

M-SPARC

User guide

Qimen Xu, Abhiraj Sharma, Phanish Suryanarayana

Material Physics & Mechanics Group
Georgia Institute of Technology

Introduction

Matlab-Simulation Package for Ab-initio Real-space Calculations (M-SPARC) is a real-space code for performing electronic structure calculations based on Kohn-Sham Density Functional Theory (DFT). Its primary purpose is the rapid development and testing of new algorithms and methods within DFT. The current features of M-SPARC include

- Boundary conditions for crystals, surfaces, wires, and molecules.
- Calculation of ground state energy, atomic forces, and stress tensor.
- Unconstrained collinear magnetization via spin polarized calculations.
- Structural relaxation and molecular dynamics (MD).
- LDA and GGA exchange correlation functionals.
- ONCV and TM pseudopotentials in psp8 (ABINIT) format.

Additional details regarding the formulation and implementation of M-SPARC can be found in the accompanying paper. Please direct any questions and report any bugs to Prof. Phanish Suryanarayana.

Input files

The required input files to run a simulation with M-SPARC are

- “.inpt” file – User options and parameters.
- “.ion” file – Atomic information.

It is required that the “.inpt” and “.ion” files are located in the same directory and share the same name. A detailed description of the input options is provided in this document. Examples of input files can be found in the directory M-SPARC/tests. In addition, M-SPARC requires pseudopotential files of psp8 format which can be generated by D. R. Hamann’s open-source pseudopotential code **ONCVSP**. Pseudopotential files are specified in the “.ion” file.

Execution

M-SPARC can be executed in MATLAB by calling the `msparc` function (which is located under `src/` directory). It is required that the “.inpt” and “.ion” files are located in the same directory and share the same name. For example, to run a simulation with input files as “filename.inpt” and “filename.ion” in the `src/` directory, use the following command:

```
S = msparc('filename');
```

In many cases, we would not want to put the input files inside the `src/` directory. In such cases, we need to provide the path to the input file name, without any extension. As an example, one can run a test located in M-SPARC/tests/MeshConvergence. First go to `src/` directory. Run a DC silicon system with $\text{mesh} = 0.4 \text{ bohr}$ by:

```
S = msparc('../tests/MeshConvergence/Si8-ONCV-0.4');
```

Execution

The result is printed to output file “Si8-ONCV-0.4.out”, located in the same directory as the input files. If the file “Si8-ONCV-0.4.out” is already present, the result will be printed to “Si8-ONCV-0.4.out_1” instead. The max number of “.out” files allowed with the same name is 100. Once this number is reached, the result will instead overwrite the “Si8-ONCV-0.4.out” file. One can compare the result with the reference out file named “Si8-ONCV-0.4.refout”.

In the `examples/` directory, we also provide a sample script file `run_examples.m`, which launches four example tests one by one. To run these examples, simply change directory to `examples/` directory, and run:

```
run_examples
```

Execution

One can also run M-SPARC using the MATLAB parallel pool over k-points/spin by providing a second argument, `parallel_switch`, when running M-SPARC:

```
S = msparc('filename',parallel_switch);
```

If `parallel_switch = 1`, M-SPARC will start using the parallel pool, and if `parallel_switch = 0`, M-SPARC will not use the parallel pool, which is the default.

Output

Upon successful execution of the `"S = msparc('filename');"` command, an output structure is returned and stored in S. The structure S contains detailed information that can be useful for post-processing and debugging. Information such as the input parameters, densities, wavefunctions, eigenvalues, and all electronic ground-state properties calculated are stored in the output structure.

Apart from the output structure returned, depending on the calculations performed, some output files will be created in the same location as the input files too.

Single point calculations

- “.out” file – Contains general information about the test, including input parameters, SCF convergence progress, ground state properties and timing information.
- “.static” file – Contains the atomic positions and atomic forces if the user chooses to print these information..

Output

Structural relaxation calculations

- “.out” file – See above.
- “.geopt” file – Contains the atomic positions and atomic forces for each relaxation step. This file is created only when the unit cell is fixed. For cell relaxation a ‘.cellopt’ file is created instead.
- “.cellopt” file – Contains the cell information (lattice vectors, cell lengths, volume) and stresses for each relaxation step. Only created for cell relaxation.
- “.restart” file – Contains information necessary to perform a restarted structural relaxation calculation.

Molecular dynamics (MD) calculations

- “.out” file – See above.

Output

- “.aimd” file – Contains the atomic positions, atomic velocities, atomic forces, electronic temperature, ionic temperature and total energy for each MD step.
- “.restart” file – Contains information necessary to perform a restarted MD calculation.

Input file options

System

CELL | LATVEC | FD_GRID | MESH_SPACING | ECUT | BC | FD_ORDER |
EXCHANGE_CORRELATION | SPIN_TYP | KPOINT_GRID | KPOINT_SHIFT |
ELEC_TEMP_TYPE | ELEC_TEMP | SMEARING | NSTATES
ATOM_TYPE | PSEUDO_POT | N_TYPE_ATOM | COORD | COORD_FRAC | RELAX |
SPIN

SCF

CHEB_DEGREE | RHO_TRIGGER | MAXIT_SCF | TOL_SCF | SCF_FORCE_ACC |
SCF_ENERGY_ACC | TOL_LANCZOS | MIXING_VARIABLE | MIXING_HISTORY |
MIXING_PARAMETER | PULAY_FREQUENCY | PULAY_RESTART_FREQ |
MIXING_PRECOND | TOL_PRECOND | PRECOND_KERKER_KTF |
PRECOND_KERKER_THRESH | PRECOND_RESTA_Q0 | PRECOND_RESTA_RS |
PRECOND_FITPOW

Input file options

Electrostatics

TOL_POISSON | TOL_PSEUDOCHARGE | REFERENCE_CUTOFF

Stress calculation

CALC_STRESS | CALC_PRES

MD

MD_FLAG | MD_METHOD | MD_NSTEP | MD_TIMESTEP | ION_TEMP |
ION_ELEC_EQT | RESTART_FLAG

Input file options

Structural relaxation

RELAX_FLAG | RELAX_METHOD | RELAX_NITER | TOL_RELAX |
TOL_RELAX_CELL | RELAX_MAXDIAL | NLCG_SIGMA | L_HISTORY |
L_FINIT_STP | L_MAXMOV | L_AUTOSCALE | L_LINEOPT | L_ICURV |
FIRE_DT | FIRE_MASS | FIRE_MAXMOV | RESTART_FLAG

Print options

PRINT_ATOMS | PRINT_FORCES | PRINT_MDOUT | PRINT_RELAXOUT |
PRINT_RESTART | PRINT_RESTART_FQ | PRINT_VELS | OUTPUT_FILE

System: .inpt file

CELL

Type

Double

Unit

Bohr

Default

None

Example

CELL: 10.20 11.21 7.58

Description

A set of three whitespace delimited values specifying the cell lengths in the lattice vector ([LATVEC](#)) directions, respectively.

Remark

The values should not be separated by more than one white space character.

LATVEC

Type

Double array

Unit

No unit

Default

```
1.0 0.0 0.0  
0.0 1.0 0.0  
0.0 0.0 1.0
```

Example

```
LATVEC:  
0.5 0.5 0.0  
0.0 0.5 0.5  
0.5 0.0 0.5
```

Description

A set of three vectors in row major order specifying the lattice vectors of the simulation domain ([CELL](#)).

FD_GRID

Type

Integer

Unit

No unit

Default

None

Example

FD_GRID: 26 26 30

Description

A set of three whitespace delimited values specifying the number of finite-difference intervals in the lattice vector ([LATVEC](#)) directions, respectively.

Remark

The convergence of results with respect to spatial discretization needs to be verified. `ECUT`, `MESH_SPACING`, `FD_GRID` cannot be specified simultaneously.

MESH_SPACING

Type

Double

Unit

Bohr

Default

None

Example

MESH_SPACING: 0.4

Description

Mesh spacing of the finite-difference grid.

Remark

The exact mesh-size will be determined by the size of the domain.
[MESH_SPACING](#), [FD_GRID](#), [ECUT](#) cannot be specified simultaneously.

ECUT

Type

Double

Unit

Ha

Default

None

Example

ECUT: 30

Description

Equivalent plane-wave energy cutoff, based on which `MESH_SPACING` will be automatically calculated.

Remark

This is not exact, but rather an estimate. `ECUT`, `MESH_SPACING`, `FD_GRID` cannot be specified simultaneously.

Type

Character

Unit

No unit

Default

None

Example

BC: P D D

Description

A set of three whitespace delimited characters specifying the boundary conditions in the lattice vector directions, respectively. P represents periodic boundary conditions and D represents Dirichlet boundary conditions.

FD_ORDER

Type

Integer

Unit

No unit

Default

12

Example

FD_ORDER: 12

Description

Order of the finite-difference approximation.

Remark

Restricted to even integers since central finite-differences are employed. The default value of 12 has been found to be an efficient choice for most systems.

EXCHANGE_CORRELATION

Type

String

Unit

No unit

Default

No Default

Example

EXCHANGE_CORRELATION: LDA_PW

Description

Choice of exchange-correlation functional. Options are LDA_PW (Perdew-Wang LDA), LDA_PZ (Purdew-Zunger LDA), and GGA_PBE (PBE GGA).

Remark

For spin-polarized calculation (`SPIN_TYP` = 1), LDA_PZ is not available.

SPIN_TYP

Type

Integer

Unit

No unit

Default

0

Example

SPIN_TYP: 1

Description

SPIN_TYP: 0 performs spin unpolarized calculation.

SPIN_TYP: 1 performs unconstrained collinear spin-polarized calculation.

Remark

SPIN_TYP can only take values 0 and 1.

KPOINT_GRID

Type

Integer array

Unit

No unit

Default

1 1 1

Example

KPOINT_GRID: 2 3 4

Description

Number of k-points in each direction of the Monkhorst-Pack grid for Brillouin zone integration.

Remark

Time-reversal symmetry is assumed to hold.

KPOINT_SHIFT

Type

Double array

Unit

No unit

Default

0.0 0.0 0.0

Example

KPOINT_SHIFT: 0.5 0.5 0.5

Description

Shift of k-points in each direction of the k-point lattice.

Remark

The shift is in reduced coordinates. The default zero shift corresponds to the Monkhorst-Pack grid.

ELEC_TEMP_TYPE

Type

String

Unit

No unit

Default

gaussian

Example

ELEC_TEMP_TYPE: fd

Description

Function used for the smearing (electronic temperature). Options are: `fermi-dirac` (or `fd`), `gaussian`.

Remark

Use `ELEC_TEMP` or `SMEARING` to set smearing value.

ELEC_TEMP

Type

Double

Unit

Kelvin

Default

1160.452

Example

ELEC_TEMP: 315.773

Description

Electronic temperature.

Remark

This is equivalent to setting **SMEARING** ($0.001 \text{ Ha} = 315.773 \text{ Kelvin}$).

SMEARING

Type

Double

Unit

Ha

Default

0.003675 for gaussian

0.007350 for fermi-dirac

Example

SMEARING: 0.001

Description

Value of smearing.

Remark

Equivalent to setting [ELEC_TEMP](#) ($0.001 \text{ Ha} = 315.773 \text{ Kelvin}$).

NSTATES

Type

Integer

Unit

No unit

Default

$N_e/2 \times 1.2 + 5$

Example

NSTATES: 24

Description

The number of Kohn-Sham states/orbitals.

Remark

This number should not be smaller than half of the total number of valence electrons (N_e) in the system. Note that the number of additional states required increases with increasing values of [ELEC_TEMP](#)/[SMEARING](#).

System: .ion file

ATOM_TYPE

Type

String

Unit

No unit

Default

None

Example

ATOM_TYPE: Fe

Description

Atomic type symbol.

Remark

The atomic type symbol can be attached with a number, e.g., Fe1 and Fe2. This feature is useful if one needs to provide two different pseudopotential files ([PSEUDO_POT](#)) for the same element.

PSEUDO_POT

Type

String

Unit

No unit

Default

None

Example

PSEUDO_POT: ../psp/Fe.psp8

Description

Path to the pseudopotential file.

Remark

The default directory for the pseudopotential files is the same as the input files. For example, if a pseudopotential Fe.psp8 is put in the same directory as the input files, one can simply specify PSEUDO_POT: Fe.psp8.

N_TYPE_ATOM

Type

Integer

Unit

No unit

Default

None

Example

N_TYPE_ATOM: 2

Description

The number of atoms of a [ATOM_TYPE](#) specified immediately before this variable.

Remark

For a system with different types of atoms, one has to specify the number of atoms for every type.

COORD

Type

Double

Unit

Bohr

Default

None

Example

COORD:

0.0 0.0 0.0

2.5 2.5 2.5

Description

The Cartesian coordinates of atoms of a [ATOM_TYPE](#) specified before this variable. If the coordinates are outside the fundamental domain (see [CELL](#) and [LATVEC](#)) in the periodic directions (see [BC](#)), it will be automatically mapped back to the domain.

Remark

For a system with different types of atoms, one has to specify the coordinates for every `ATOM_TYPE`. One can also specify the coordinates of the atoms using `COORD_FRAC`.

COORD_FRAC

Type

Double

Unit

None

Default

None

Example

COORD_FRAC:

0.5 0.5 0.0

0.0 0.5 0.5

Description

The fractional coordinates of atoms of a [ATOM_TYPE](#) specified before this variable. $\text{COORD_FRAC}(i,j) \times \text{CELL}(j)$, ($j = 1, 2, 3$) gives the coordinate of the i^{th} atom along the j^{th} [LATVEC](#) direction. If the coordinates are outside the fundamental domain (see [CELL](#) and [LATVEC](#)) in the periodic directions (see [BC](#)), it will be automatically mapped back to the domain.

Remark

For a system with different types of atoms, one has to specify the coordinates for every `ATOM_TYPE`. One can also specify the coordinates of the atoms using `COORD`.

RELAX

Type

Integer

Unit

No unit

Default

1 1 1

Example

RELAX:

1 0 1

0 1 0

Description

Atomic coordinate with the corresponding RELAX value 0 is held fixed during relaxation/MD.

SPIN

Type

Double

Unit

No unit

Default

0.0

Example

SPIN:

1.0

-1.0

Description

Specifies the net initial spin on each atom for a spin-polarized calculation.

SCF

CHEB_DEGREE

Type

Integer

Unit

No unit

Default

Automatically set.

Example

CHEB_DEGREE: 25

Description

Degree of polynomial used for Chebyshev filtering.

Remark

For larger mesh-sizes, smaller values of CHEB_DEGREE are generally more efficient, and vice-versa.

RHO_TRIGGER

Type

Integer

Unit

No unit

Default

4

Example

RHO_TRIGGER: 5

Description

The number of times Chebyshev filtering is repeated before updating the electron density in the very first SCF iteration.

Remark

Values smaller than the default value of 4 can result in a significant increase in the number of SCF iterations. Larger values can sometimes reduce the number of SCF iterations.

MAXIT_SCF

Type

Integer

Unit

No unit

Default

100

Example

MAXIT_SCF: 50

Description

Maximum number of SCF iterations.

Remark

Larger values than the default of 100 may be required for highly inhomogeneous systems, particularly when small values of [SMEARING](#)/[ELEC_TEMP](#) are chosen.

TOL_SCF

Type

Double

Unit

No unit

Default

Automatically set for 10^{-3}
Ha/Bohr accuracy in force

Example

TOL_SCF: 1e-5

Description

The tolerance on the normalized residual of the effective potential or the electron density for convergence of the SCF iteration.

Remark

Only one of `TOL_SCF`, `SCF_ENERGY_ACC`, or `SCF_FORCE_ACC` can be specified.

SCF_FORCE_ACC

Type

Double

Unit

Ha/Bohr

Default

None

Example

SCF_FORCE_ACC: 1e-4

Description

The tolerance on the atomic forces for convergence of the SCF iteration.

Remark

Only one of `SCF_FORCE_ACC`, `TOL_SCF` or `SCF_ENERGY_ACC` can be specified.

SCF_ENERGY_ACC

Type

Double

Unit

Ha/atom

Default

None

Example

SCF_ENERGY_ACC: 1e-5

Description

The tolerance on the free energy for the convergence of the SCF iteration.

Remark

Only one of `SCF_ENERGY_ACC`, `SCF_FORCE_ACC`, or `TOL_SCF` can be specified.

TOL_LANCZOS

Type

Double

Unit

No unit

Default

1e-2

Example

TOL_LANCZOS: 1e-3

Description

The tolerance within the Lanczos algorithm for calculating the extremal eigenvalues of the Hamiltonian, required as part of the CheFSI method.

Remark

Typically, the Lanczos tolerance does not need to be very strict.

MIXING_VARIABLE

Type

String

Unit

No unit

Default

potential

Example

MIXING_VARIABLE: density

Description

This specifies whether potential or density mixing is performed in the SCF iteration. Available options are: `potential` and `density`.

MIXING_HISTORY

Type

Integer

Unit

No unit

Default

7

Example

MIXING_HISTORY: 40

Description

The mixing history used in Pulay mixing.

Remark

Too small values of **MIXING_HISTORY** can result in poor SCF convergence.

MIXING_PARAMETER

Type

Double

Unit

No unit

Default

0.3

Example

MIXING_PARAMETER: 0.1

Description

The value of the relaxation parameter used in Pulay/simple mixing.

Remark

Values larger than the default value of 0.3 can be used for insulating systems, whereas smaller values are generally required for metallic systems, particularly at small values of [SMEARING](#) or [ELEC_TEMP](#).

PULAY_FREQUENCY

Type

Integer

Unit

No unit

Default

1

Example

PULAY_FREQUENCY: 4

Description

The frequency of Pulay mixing in Periodic Pulay.

Remark

The default value of 1 corresponds to Pulay mixing.

PULAY_RESTART_FREQ

Type

Integer

Unit

No unit

Default

0

Example

PULAY_RESTART_FREQ: 4

Description

The frequency for restarting the 'Periodic Pulay' mixing. If set to 0, the restarted Pulay method is turned off.

MIXING_PRECOND

Type

String

Unit

No unit

Default

none

Example

MIXING_PRECOND: kerker

Description

This specifies the preconditioner used in the SCF iteration. Available options are: none, kerker, resta and truncated_kerker.

TOL_PRECOND

Type

Double

Unit

No unit

Default

$h^2 \times 0.001$

Example

TOL_PRECOND: 1e-4

Description

The tolerance on the relative residual for the linear systems arising during the real-space preconditioning of the SCF.

Remark

The linear systems do not need to be solved very accurately. h is the mesh spacing.

PRECOND_KERKER_KTF

Type

Double

Unit

Bohr⁻¹

Default

1.0

Example

PRECOND_KERKER_KTF: 0.8

Description

The Thomas-Fermi screening length appearing in the kerker and truncated_kerker preconditioners ([MIXING_PRECOND](#)).

PRECOND_KERKER_THRESH

Type

Double

Unit

No unit

Default

0.25

Example

PRECOND_KERKER_THRESH: 0.1

Description

The threshold for the `truncated_kerker` preconditioner ([MIXING_PRECOND](#)).

Remark

This threshold will be scaled by the [MIXING_PARAMETER](#). If the threshold is set to 0, the `kerker` preconditioner is recovered.

PRECOND_RESTA_Q0

Type

Double

Unit

Bohr⁻¹

Default

1.36

Example

PRECOND_RESTA_Q0: 1.10

Description

The Fermi-momentum-related quantity appearing in resta preconditioner ([MIXING_PRECOND](#)).

PRECOND_RESTA_RS

Type

Double

Unit

Bohr

Default

2.76

Example

PRECOND_RESTA_RS: 4.28

Description

The screening length appearing in the resta preconditioner ([MIXING_PRECOND](#)).

PRECOND_FITPOW

Type

Integer

Unit

No unit

Default

2

Example

PRECOND_FITPOW: 3

Description

Half of the highest degree of rational polynomials used for the real-space preconditioning of the SCF iteration.

Remark

Currently this number cannot be larger than 5. Used only for the `resta` and `truncated_kerker` preconditioners.

Electrostatics

TOL_POISSON

Type

Integer

Unit

No unit

Default

`TOL_SCF` × 0.01

Example

TOL_POISSON: 1e-6

Description

The tolerance on the norm of the relative residual for the Poisson equation.

Remark

The tolerance for poisson solver should not be worse than `TOL_SCF`, otherwise it might seriously affect the convergence of the SCF iteration.

TOL_PSEUDOCHARGE

Type

Double

Unit

No unit

Default

`TOL_SCF` × 0.01

Example

TOL_PSEUDOCHARGE: 1e-6

Description

The normalized error in the net enclosed charge for the pseudocharge density of each atom.

REFERENCE_CUTOFF

Type

Double

Unit

Bohr

Default

0.5

Example

REFERENCE_CUTOFF: 1.0

Description

The cutoff radius of the reference potential used for evaluating the electrostatic correction arising from overlapping pseudocharge densities.

Remark

This number should be smaller than half the smallest interatomic distance.

Stress calculation

CALC_STRESS

Type

Integer

Unit

No unit

Default

0

Example

CALC_STRESS: 1

Description

Flag for calculation of the Hellmann-Feynman stress tensor (in cartesian coordinates).

CALC_PRES

Type

Integer

Unit

No unit

Default

0

Example

CALC_PRES: 1

Description

Flag for calculation of the pressure.

Remark

Pressure is directly calculated, without calculation of the stress tensor.

MD

MD_FLAG

Type

Integer

Unit

No unit

Default

0

Example

MD_FLAG: 1

Description

MD simulations are performed if the flag is set to 1.

Remark

[MD_FLAG](#) and [RELAX_FLAG](#) both cannot be set to 1.

MD_METHOD

Type

String

Unit

No unit

Default

NVE

Example

MD_METHOD: NVE

Description

Type of MD to be performed.

Remark

Only NVE (microcanonical ensemble) is supported.

MD_NSTEP

Type

Integer

Unit

No unit

Default

0

Example

MD_NSTEP: 100

Description

Specifies the number of MD steps.

Remark

If $\text{MD_NSTEP} = N$, the MD runs from 0 to $(N - 1) \times \text{MD_Timestep}$ fs.

MD_TIMESTEP

Type

Double

Unit

Femtosecond

Default

1

Example

MD_TIMESTEP: 0.1

Description

MD time step.

Remark

Total MD time is given by: $\text{MD_TIMESTEP} \times \text{MD_NSTEP}$.

ION_TEMP

Type

Double

Unit

Kelvin

Default

No Default

Example

ION_TEMP: 315

Description

Starting ionic temperature in MD, used to generate initial velocity distribution.

Remark

Must be specified if [MD_FLAG](#) is set to 1.

ION_ELEC_EQT

Type

Integer

Unit

No unit

Default

1

Example

ION_ELEC_EQT: 0

Description

Flag that determines whether the `ELEC_TEMP` will be set equal to `ION_TEMP` during MD.

Remark

If the flag is set to 0, the values of `ELEC_TEMP` and `ION_TEMP` need to be identical.

RESTART_FLAG

Type

Integer

Unit

No unit

Default

0

Example

RESTART_FLAG: 0

Description

Flag for restarting molecular dynamics and structural relaxation.

Remark

Restarts from the previous configuration which is stored in a .restart file.

Structural relaxation

RELAX_FLAG

Type

Integer

Unit

No unit

Default

0

Example

RELAX_FLAG: 1

Description

Flag for performing structural relaxation. 0 means no structural relaxation. 1 represents relaxation of atom positions. 2 represents optimization of volume with the fractional coordinates of the atoms fixed.

Remark

This flag should not be specified if [MD_FLAG](#) is set to 1.

RELAX_METHOD

Type

String

Unit

No unit

Default

LBFGS

Example

RELAX_METHOD: NLCG

Description

Specifies the algorithm for structural relaxation. The choices are 'LBFGS' (limited-memory BFGS), 'NLCG' (Non-linear conjugate gradient), and 'FIRE' (Fast inertial relaxation engine).

Remark

LBFGS is typically the best choice.

RELAX_NITER

Type

Integer

Unit

No unit

Default

100

Example

RELAX_NITER: 25

Description

Specifies the maximum number of iterations for the structural relaxation ([RELAX_FLAG](#)).

Remark

If [RESTART_FLAG](#) is set to 1, then relaxation will restart from the last atomic configuration and run for maximum of [RELAX_NITER](#) iterations.

TOL_RELAX

Type

Double

Unit

Ha/Bohr

Default

5e-4

Example

TOL_RELAX: 1e-3

Description

Specifies the tolerance for termination of the structural relaxation. The tolerance is defined on the maximum force component (in absolute sense) over all atoms.

TOL_RELAX_CELL

Type

Double

Unit

GPa

Default

1e-2

Example

TOL_RELAX: 1e-3

Description

Specifies the tolerance for termination of the cell relaxation. The tolerance is defined on the maximum principle stress component.

RELAX_MAXDIAL

Type

Double

Unit

No unit

Default

1.2

Example

RELAX_MAXDIAL: 1.4

Description

The maximum scaling of the volume allowed with respect to the initial volume defined by [CELL](#) and [LATVEC](#). This will determine the upper-bound and lower-bound in the bisection method (Brent's method) for the volume optimization.

NLCG_SIGMA

Type

Double

Unit

No unit

Default

0.5

Example

NLCG_SIGMA: 1

Description

Parameter in the secant method used to control the step length in NLCG ([RELAX_METHOD](#)).

Remark

Default value works well in most cases.

L_HISTORY

Type

Integer

Unit

No unit

Default

20

Example

L_HISTORY: 15

Description

Size of history in LBFGS ([RELAX_METHOD](#)).

Remark

Default value works well in most cases.

L_FINISH_STP

Type

Double

Unit

Bohr

Default

5e-3

Example

L_FINISH_STP: 0.01

Description

Step length for line optimizer in LBFGS ([RELAX_METHOD](#)).

Remark

Default value works well in most cases.

L_MAXMOV

Type

Double

Unit

Bohr

Default

0.2

Example

L_MAXMOV: 1.0

Description

The maximum allowed step size in LBFGS ([RELAX_METHOD](#)).

Remark

Default value works well in most cases.

L_AUTOSCALE

Type

Integer

Unit

No unit

Default

1

Example

L_AUTOSCALE: 0

Description

Flag for automatically determining the inverse curvature that is used to determine the direction for next iteration in LBFGS ([RELAX_METHOD](#)).

Remark

Default works well in most cases.

L_LINEOPT

Type

Integer

Unit

No unit

Default

1

Example

L_LINEOPT: 0

Description

Flag for atomic force based line minimization in LBFGS ([RELAX_METHOD](#)).

Remark

Required only if [L_AUTOSCALE](#) is 0.

L_ICURV

Type

Double

Unit

No unit

Default

1.0

Example

L_ICURV: 0.1

Description

Initial inverse curvature, used to construct the inverse Hessian matrix in LBFGS ([RELAX_METHOD](#)).

Remark

Needed only if [L_AUTOSCALE](#) is 0. Default value works well in most cases.

FIRE_DT

Type

Double

Unit

Femto second

Default

1

Example

FIRE_DT: 0.1

Description

Time step used in FIRE ([RELAX_METHOD](#)).

Remark

Default value works well in most cases.

FIRE_MASS

Type

Double

Unit

Atomic mass unit

Default

1.0

Example

FIRE_MASS: 2.5

Description

Pseudomass used in FIRE ([RELAX_METHOD](#)).

Remark

Default value works well in most cases.

FIRE_MAXMOV

Type

Double

Unit

Bohr

Default

0.2

Example

FIRE_MAXMOV: 1.0

Description

Maximum movement for any atom in FIRE ([RELAX_METHOD](#)).

Remark

Default value works well in most cases.

Print options

PRINT_ATOMS

Type

0 or 1

Unit

No unit

Default

0

Example

PRINT_ATOMS: 1

Description

Flag for writing the atomic positions. For ground-state calculations, atom positions are printed to a '.static' output file. For structural relaxation calculations, atom positions are printed to a '.geopt' file. For MD calculations, atom positions are printed to a '.aimd' file.

PRINT_FORCES

Type

0 or 1

Unit

No unit

Default

0

Example

PRINT_FORCES: 1

Description

Flag for writing the atomic forces. For ground-state calculations, forces are printed to a '.static' output file. For structural relaxation calculations, forces are printed to a '.geopt' file. For MD calculations, forces are printed to a '.aimd' file.

PRINT_MDOUT

Type

0 or 1

Unit

No unit

Default

1

Example

PRINT_MDOUT: 0

Description

Flag for printing the the MD output into the .aimd file.

PRINT_RELAXOUT

Type

0 or 1

Unit

No unit

Default

1

Example

PRINT_RELAXOUT: 0

Description

Flag for printing the structural relaxation data in a .geopt file.

Remark

Required only if [RELAX_FLAG](#) is set to 1.

PRINT_RESTART

Type

0 or 1

Unit

No unit

Default

1

Example

PRINT_RESTART: 0

Description

Flag for writing the .restart file, used to restart MD and structural relaxation simulations.

Remark

Relevant only if either `MD_FLAG` is 1 or `RELAX_FLAG` is 1.

PRINT_RESTART_FQ

Type

Integer

Unit

No unit

Default

1

Example

PRINT_RESTART_FQ: 10

Description

Frequency at which .restart file is written in MD and structural optimization simulations.

Remark

Relevant only if either `MD_FLAG` is 1 or `RELAX_FLAG` is 1.

PRINT_VELS

Type

0 or 1

Unit

No unit

Default

1

Example

PRINT_VELS: 0

Description

Flag for printing the ion velocities in an MD simulation into the .aimd file.

Remark

Relevant only if [MD_FLAG](#) is set to 1.

OUTPUT_FILE

Type

String

Unit

No unit

Default

Same as the input file name

Example

OUTPUT_FILE: myfname

Description

The name of the output files. The output files are attached with a suffix ('.out', '.static', '.geopt' and '.aimd').

Remark

If an output file with the same name already exist, the results will be written to a file with a number attached, e.g., 'myfname.out_1'. The maximum number of output files with the same name allowed is 100. After that the output files will be overwritten in succession.

Acknowledgments

The work was supported by the grant DE-SC0019410 funded by the U.S. Department of Energy, Office of Science. Initial development efforts were supported by the grants 1333500 and 1553212 funded by the U.S. National Science Foundation.