

# blib Code Reference v1.6

David Hobach

## Contents

blib	4
Disclaimer	4
Coding Conventions	5
Library Usage	6
Dependencies	6
Imports	6
Global Variables	6
Global Aliases	7
Functions	8
args	16
Dependencies	17
Imports	17
Global Variables	17
Functions	17
arr	20
Dependencies	20
Imports	20
Functions	20
cdoc	21
Dependencies	21
Imports	21
Functions	21
daemon	25
Dependencies	26
Imports	26
Global Variables	26
Functions	26
date	28
Dependencies	28
Imports	28
Functions	28
delay	29
Dependencies	30

	Imports . . . . .	30
	Global Variables . . . . .	30
	Functions . . . . .	30
dmcrypt . . . . .		30
	Dependencies . . . . .	31
	Imports . . . . .	31
	Functions . . . . .	31
fd . . . . .		32
	Dependencies . . . . .	32
	Imports . . . . .	33
	Functions . . . . .	33
flog . . . . .		33
	Dependencies . . . . .	34
	Imports . . . . .	34
	Global Variables . . . . .	34
	Functions . . . . .	34
fs . . . . .		37
	Dependencies . . . . .	37
	Imports . . . . .	38
	Functions . . . . .	38
hash . . . . .		40
	Dependencies . . . . .	40
	Imports . . . . .	41
	b_hash_file [file] [algorithm] . . . . .	41
	b_hash_str [string] [algorithm] . . . . .	41
http . . . . .		41
	Dependencies . . . . .	41
	Imports . . . . .	41
	Global Variables . . . . .	41
	Functions . . . . .	42
i18n . . . . .		42
	Dependencies . . . . .	43
	Imports . . . . .	43
	Global Variables . . . . .	43
	Functions . . . . .	43
ini . . . . .		43
	Dependencies . . . . .	44
	Imports . . . . .	44
	Functions . . . . .	44
keys . . . . .		45
	Dependencies . . . . .	46
	Imports . . . . .	46
	Functions . . . . .	46
meta . . . . .		48
	Dependencies . . . . .	48
	Imports . . . . .	48

Functions . . . . .	48
multithreading/ipcm . . . . .	48
Dependencies . . . . .	49
Imports . . . . .	49
Functions . . . . .	49
multithreading/ipcv . . . . .	50
Dependencies . . . . .	51
Imports . . . . .	51
Functions . . . . .	51
multithreading/mtx . . . . .	52
Dependencies . . . . .	53
Imports . . . . .	53
Functions . . . . .	53
multithreading/multiw . . . . .	55
Dependencies . . . . .	56
Imports . . . . .	56
Functions . . . . .	56
net . . . . .	57
Dependencies . . . . .	57
Imports . . . . .	57
Global Variables . . . . .	57
Functions . . . . .	57
notify . . . . .	58
Dependencies . . . . .	58
Imports . . . . .	58
Functions . . . . .	58
os/osid . . . . .	59
Dependencies . . . . .	59
Imports . . . . .	59
Functions . . . . .	59
os/qubes4/dom0 . . . . .	60
Dependencies . . . . .	60
Imports . . . . .	61
Global Variables . . . . .	61
Functions . . . . .	62
proc . . . . .	73
Dependencies . . . . .	73
Imports . . . . .	73
Functions . . . . .	73
sqlite3 . . . . .	74
Dependencies . . . . .	75
Imports . . . . .	75
Functions . . . . .	75
str . . . . .	76
Dependencies . . . . .	76
Imports . . . . .	76

Functions . . . . .	76
tcolors . . . . .	77
Dependencies . . . . .	77
Imports . . . . .	77
Global Variables . . . . .	77
traps . . . . .	77
Dependencies . . . . .	77
Imports . . . . .	77
Functions . . . . .	77
types . . . . .	78
Dependencies . . . . .	78
Imports . . . . .	78
Global Variables . . . . .	79
Functions . . . . .	79
ui . . . . .	82
Dependencies . . . . .	82
Imports . . . . .	82
Functions . . . . .	82
wm . . . . .	83
Dependencies . . . . .	83
Imports . . . . .	83
Functions . . . . .	83
tests/test_common.bash . . . . .	83
Dependencies . . . . .	83
Imports . . . . .	84
Global Variables . . . . .	84
Functions . . . . .	84
tests/user_test_data.bash . . . . .	86
Dependencies . . . . .	86
Imports . . . . .	86
Global Variables . . . . .	86
Reference List . . . . .	88

## **blib**

blib - a bash library

The basic functions which are imported by default.

Copyright (C) 2024 David Hobach LGPLv3

version: Execute **blib version** or use **b\_version**.

## **Disclaimer**

This program is free software: you can redistribute it and/or modify it under the terms of the Lesser GNU General Public License as published by

the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the Lesser GNU General Public License for more details.

You should have received a copy of the Lesser GNU General Public License along with this program. If not, see <https://www.gnu.org/licenses/>.

**The above statements apply to all modules of blib if not mentioned otherwise.**

### Coding Conventions

1. embrace the KISS principle
2. some general guidelines: <http://www.kfirlavi.com/blog/2012/11/14/defensive-bash-programming/>
3. use `b_[module]_[camel case function name]` to denote functions meant to be used by users of the library, `B_[module]_[upper case var name]` for global variables
4. use `BLIB_[module]_[upper case var name]` for global variables (to be avoided whenever possible) not meant to be used by library users (“private” variables); library users can use setters or getters
5. use the `BLIB_STORE` with the above naming conventions for “private” variables whenever possible
6. use `blib_[module]_[camel case function name]` to denote private functions not meant to be used by library users; the function name should not contain any underscores
7. the blib module itself is the only exception which can use `b_`, `B_`, `blib_`, `BLIB_` without module name
8. prefixes such as `t_`, `T_` and `UTD_` are exclusively related to test code
9. set exit codes (`!= 0 -> issue`) wherever it makes sense
10. keep the global namespace clean whenever possible
11. declare `-g` must be used in order to allow sourcing from a function (`b_import`)
12. modules must check their dependencies via `b_deps`
13. modules should provide a header similar to that of the blib source file in order to make the documentation generation work
14. modules may be placed in subfolders of arbitrary depth
15. use 0 to indicate true and 1 to indicate false for variables; for exit codes use a non-zero exit code to indicate the number of errors
16. functions should be tagged with the following tags, if applicable:
  - @StateChanging* - the function changes the internal state of the script in a way that will not propagate to supersHELLs (e.g. global variables) and

should thus not be called from subshells (unless the user wants the state to only change in that shell)  
*@B\_E* - the function uses *B\_E* for error handling and may thus behave differently depending on the implemented error handler

## Library Usage

with the default bash options:

```
source blib
b_checkVersion 1 0 || { >&2 echo "This script depends on blib (https://github.com/3hhh/blib)"
b_import [module]
```

## Dependencies

bats  
cat  
dirname  
find  
mktemp  
mv  
readlink  
rm  
sort  
su  
whoami

## Imports

no imports

## Global Variables

**B\_LIB\_DIR** *blib/B\_LIB\_DIR*  
Path of the blib installation directory.

**B\_TEST\_MODE** *blib/B\_TEST\_MODE*  
blib will set this variable to 0, if blib is running in test mode.  
This variable may be used to bypass code during testing, if bats cannot test that code due to its limitations (e.g. for EXIT traps which bats uses for itself).

**B\_CALLER\_NAME** *blib/B\_CALLER\_NAME*  
Name of the executable or script as String which called blib and any child libraries.

**B\_ERR** *blib/B\_ERR*

Global variable used for error handling throughout blib, cf. B\_E.

It is recommended to always set an at least partially static error message on confirmed errors as variables may be empty (which would indicate “no error” for B\_E).

**B\_RC** *blib/B\_RC*

Can be used to set the return code for B\_E in the case of an error. It defaults to 1.

This should be set to an integer value between 1 and 255. Any other value may cause undefined behaviour.

**B\_CONF\_DIR** *blib/B\_CONF\_DIR*

Path to the blib configuration directory. Modules may create subfolders named by their module name there. May not exist.

**B\_SCRIPT** *blib/B\_SCRIPT*

Global variable which can be used to obtain the two global variables B\_SCRIPT\_DIR and B\_SCRIPT\_NAME as follows:

```
eval "$B_SCRIPT"
```

**B\_SCRIPT\_NAME** *blib/B\_SCRIPT\_NAME*

Path of the sourced or executed bash script executing the eval (symlinks are resolved) of B\_SCRIPT.

**B\_SCRIPT\_DIR** *blib/B\_SCRIPT\_DIR*

Name of the sourced or executed bash script executing the eval (symlinks are resolved) of B\_SCRIPT.

**B\_LINE** *blib/B\_LINE*

Default output variable of b\_readLine.

**Global Aliases**

Alias expansion is automatically enabled by blib as it is required for its core functionality. So if you have strange aliases defined in your shell environment, this may cause undefined blib behaviour.

**B\_E** *blib/B\_E*

The blib error handler: All blib modules use it whenever execution errors require special handling that the currently executing code cannot achieve.

Syntax:

```
B_ERR="This is an error message." ; B_E ;
```

If you need to set the return/exit code, you can do it with B\_RC:

```
B_ERR="This is another error message." ; B_RC=6 ; B_E ;
```

Calling B\_E means:

Check B\_ERR for an error message and if there is one, handle it. It can be placed at the end of a line or on its own line. B\_E will then process the error message in the way defined by the error handler (cf. b\_defaultErrorHandler) and stop any further execution of code in the current context (function, script, ...) returning a non-zero exit code (1) unless the described error was fixed. In the latter unlikely case it'll let execution proceed.

More examples:

```
#handle a potentially failing command:  
cmd || { B_ERR="cmd failed." ; B_E ; }
```

```
#capture stdout of a potentially failing command:  
local out=  
out="$(cmd)" || { B_ERR="cmd failed." ; B_E ; }
```

```
#handle multiple potentially failing commands in a try/catch like manner:  
(  
  set -e  
  cmd1  
  cmd2  
  cmd3  
) #NOTE: || doesn't work here!  
if [ $? -ne 0 ] ; then  
  B_ERR="Some commands failed."  
  B_E  
fi
```

The error handler can be re-defined at runtime with b\_setErrorHandler.

## Functions

**b\_printStackTrace** [skip level] *blib/b\_printStackTrace*

[skip level]: skip that many levels of the stack trace (optional, default: 1 - skip this function call)

print the current stack trace in a human readable way

**returns:** stack trace with the first levels skipped as defined

**b\_nop** *blib/b\_nop*

Do nothing.

**returns:** nothing; sets a zero exit code



**b\_\_version** [**part**] *blib/b\_\_version*

Get the version of this blib instance.

[part]: Optional parameter defining the part of the version to retrieve (0: all as String (default), 1: major as Integer, 2: minor as Integer).

**returns:** blib version as string; always sets a zero exit code

**b\_\_checkVersion** [**minimum allowed major**] [**minimum allowed minor**] [**maximum allowed major**] [**maximum allowed minor**]  
*blib/b\_\_checkVersion*

Check whether the currently running blib instance meets the given blib version requirements.

To e.g. make sure you're on blib version 1.1 or higher, use

```
source blib
```

```
b__checkVersion 1 2 || { >&2 echo "This script depends on blib (https://github.com/3hhh/blib)"
```

[minimum allowed major]: The lowest acceptable major version number (default: 0).

[minimum allowed minor]: The lowest acceptable minor version number (default: 0).

[maximum allowed major]: The highest acceptable major version number (default: infinite).

[maximum allowed minor]: The highest acceptable minor version number (default: infinite).

**returns:** Sets a zero exit code, if and only if the currently running blib instance meets the version requirements.

**b\_\_defaultErrorHandler** [**error out**] [**send err**] [**send stack trace**]  
*blib/b\_\_defaultErrorHandler*

The blib default error handler.

As any error handler it must

1. handle the error message (if not the error itself) lying in B\_ERR
2. not take any non-numeric arguments
3. not error out itself
4. implement the below *[error out]* as its first parameter (to make b\_setBE work)
5. ideally use b\_\_error to send error messages to the user
6. return one of the following exit codes:
  - a) 0: **if and only if** the error was fixed entirely and the caller may ignore the error (i.e. probably never)
  - b) 1: The error wasn't fixed. Functions should return to their caller indicating an error (non-zero status code). Direct shell calls will exit. B\_ERR is **not** reset to blank, i.e. the next call to B\_E in the same context will cause another error. The caller may use this to either *throw* the error further or handle and clear the error.
  - c) 2: Force a stop of execution in the current shell / error out.

[error out]: Whether or not to call exit after the error message handling, if the error couldn't be handled (default: 0 = always error out / call exit). If set to 1, B\_E will allow e.g. functions to return to their callers.

[send err]: Whether or not to send the error message to the user (default: 0 = send).

[send stack trace]: Whether or not to send a stack trace to the user (default: identical to [send err]).

**returns:** see the description above

**b\_setBE** [error out] *blib/b\_setBE*

Set the [error out] behaviour of the currently configured error handler.

Contrary to b\_setErrorHandler this function may be called by blib modules as all error handlers are required to support [error out] as parameter.

Example for switching the error out behaviour:

```
b_setBE 1
funcThatMayCallB_E #without subshell
ret=$?
b_resetErrorHandler
```

[error out]: see b\_defaultErrorHandler (default: 0)

**returns:** nothing, always sets a zero exit code

*@StateChanging*

**b\_setErrorHandler** [handler] *blib/b\_setErrorHandler*

Set the error handler for all future executions of B\_E in the current scope.

You can do this in e.g. subshells to limit the effect.

blib modules should only use this function if absolutely necessary to temporarily modify the error behaviour whilst making sure that b\_resetErrorHandler is called in the end. Otherwise it will prevent library users from setting the general behaviour in their scripts.

Usually you do not want to write an entirely new handler, but modify the b\_defaultErrorHandler parameters with this setter or use b\_setBE for that.

[handler]: Function to handle errors. See b\_defaultErrorHandler for details.

**returns:** nothing

*@StateChanging*

**b\_resetErrorHandler** [reset B\_ERR] *blib/b\_resetErrorHandler*

Set the error handler to whatever it was before the last call to b\_setErrorHandler or b\_setBE.

[reset B\_ERR]: Whether or not to also reset B\_ERR (default: true/0).

**returns:** nothing, always sets a zero exit code

*@StateChanging*

**b\_getErrorHandler** *blib/b\_getErrorHandler*

Get the currently for B\_E configured error handler.

**returns:** the error handler function

**b\_silence** [function] [param 1] .. [param p] *blib/b\_silence*

Call the given function with its parameters in the current shell context whilst suppressing all of its output to both stdout and stderr. Anything written to B\_ERR however is passed to B\_E (which can still write to stderr).

This function is useful when you want to keep an error message set with B\_ERR, but discard everything else.

In contrast **yourfunction** &> /dev/null may also drop the error message, if you're using an error handler (see B\_E) that writes to stdout or stderr.

[function]: The function to execute.

[param p]: An arbitrary number of function parameters.

**returns:** Sets the status code of the called function, but doesn't print anything.

B\_E is called on errors.

@B\_E

**b\_readLine** [variable] [read arg 1] .. [read arg r] *blib/b\_readLine*

Read a line from stdin to the given variable. It should generally be preferred over bash's **read** function as it should be much more readable and robust.

Contrary to the definition of bash's **read** function, lines may end with newlines *or* EOF (**read** only accepts newlines).

Note that bash's **read** and this function are *relatively* slow, but use little memory. Sometimes it may make sense to use the faster **mapfile -t** instead, which however reads the entire data into memory.

[variable]: Name of the variable to read the line to (default: B\_LINE). It's content is only valid on a zero exit code. Otherwise it will be in an undefined state - in particular previous content may not be available anymore.

[read arg r]: An arbitrary number of arguments to pass to the **read** function, which is used internally (default: -r).

**returns:** Sets a zero exit code, if another line could be read. Otherwise a non-zero exit code is set.

**b\_assertLastPipes** [error message] *blib/b\_assertLastPipes*

Assert that the last pipe statements all had a zero exit code.

An alternative to **set -o pipefail**.

[error message]: Optional error message to use for B\_E in case the assertion fails.

**returns:** Nothing. Assertion failures trigger B\_E.

@B\_E

**b\_defaultMessageHandler** [message type] [message] [first part] [last part] *blib/b\_defaultMessageHandler*

Handles the given message by printing information to stdout and errors to stderr. This is the default message handler used by blib. It can be changed by `b_setMessageHandler`.

Message handler implementations must support at least the parameters of this function, but may add additional parameters. If an handler implementation does not support partial messages (i.e. the [first part] and [last part] parameters), it should be chained to a `b_cachingMessageHandler`.

[message type]: 0=informational message, 1=error message.

[message]: String representing the message.

[first part]: If set to 0, assume that the given message is the first part of an overall chain of messages (default: 0).

[last part]: If set to 0, assume that the given message is the final part of an overall chain of messages (default: 0).

**returns:** Nothing. Never causes errors.

**b\_cachingMessageHandler** [message handler] [message type] [message]  
[first part] [last part] *blib/b\_cachingMessageHandler*

A message handler implementation which caches partial messages for a receiving message handler that cannot handle them until they are completed.

Use `b_initCachingMessageHandler` && `b_setMessageHandler "b_cachingMessageHandler [your message handler]"`

to set your receiving message handler as message handler to cache messages for.

This implementation uses the `b_getDefaultMessageHandlerIntermediate` as separator between partial messages.

[message handler]: The function implementing the receiving message handler. It must handle the [message type] and the [message].

[message type]: See `b_defaultMessageHandler`.

[message]: See `b_defaultMessageHandler`.

[first part]: See `b_defaultMessageHandler`.

[last part]: See `b_defaultMessageHandler`.

**returns:** Nothing. Never causes errors.

**b\_initCachingMessageHandler** [maximum message type] *blib/b\_initCachingMessageHandler*

Initializes a new cache for a `b_cachingMessageHandler`. This function *must* be called at least once before using `b_cachingMessageHandler`.

[maximum message type]: Maximum message type for which to allocate caches (default: 1 -> allocate caches for 0..1/info..error).

**returns:** Nothing.

@B\_E

**b\_setDefaultMessageHandlerIntermediate** [intermediate] *blib/b\_setDefaultMessageHandlerIntermediate*

[intermediate]: String to use as intermediate between two message parts with `b_defaultMessageHandler`, i.e. the resulting message should be [part 1][intermediate][part 2]. Default: Space.

**returns:** Nothing.

**b\_getDefaultMessageHandlerIntermediate** *blib/b\_getDefaultMessageHandlerIntermediate*  
 Get the currently configured intermediate string for the b\_defaultMessageHandler.  
**returns:** The intermediate String.

**b\_setDefaultMessageHandlerPrefix** [message type] [prefix]  
*blib/b\_setDefaultMessageHandlerPrefix*  
 Set the prefix to use for the default message handler and the given message type.  
 [message type]: 0=informational message, 1=error message.  
 [prefix]: A string to prefix all messages of the given type.  
**returns:** Nothing.

**b\_getDefaultMessageHandlerPrefix** [message type] *blib/b\_getDefaultMessageHandlerPrefix*  
 Get the prefix used for the default message handler and the given message type.  
 [message type]: 0=informational message, 1=error message.  
**returns:** The currently configured prefix.

**b\_info** [message] [first part] [last part] [message handler param 1] ...  
 [message handler param n] *blib/b\_info*  
 Send an informational message to the user. The message is dispatched via the currently configured message handler (default: b\_defaultMessageHandler).  
 [message]: to send  
 [first part]: If set to 0, assume that the given message is the first part of an overall chain of messages (default: 0).  
 [last part]: If set to 0, assume that the given message is the final part of an overall chain of messages (default: 0).  
 [message handler param i]: Arbitrary parameters to pass to the currently configured message handler (cf. b\_setMessageHandler).  
**returns:** Nothing, always sets a zero exit code.

**b\_error** [message] [first part] [last part] [message handler param 1]  
 ... [message handler param n] *blib/b\_error*  
 Send an error message to the user *without* erroring out. The message is dispatched via the currently configured message handler (default: b\_defaultMessageHandler).  
 99.9% of all users will want to use the combination of B\_ERR and B\_E for proper error handling instead.  
 [message]: to send  
 [first part]: If set to 0, assume that the given message is the first part of an overall chain of messages (default: 0).  
 [last part]: If set to 0, assume that the given message is the final part of an overall chain of messages (default: 0).  
 [message handler param i]: Arbitrary parameters to pass to the currently configured message handler (cf. b\_setMessageHandler).  
**returns:** Nothing, always sets a zero exit code.

**b\_setMessageHandler** [handler] *blib/b\_setMessageHandler*  
Set the handler used to send messages to the user. By default, `b_defaultMessageHandler` is used.  
[handler]: Function to handle the messages. See `b_defaultMessageHandler` for the requirements.  
**returns:** Nothing.

**b\_getMessageHandler** *blib/b\_getMessageHandler*  
Get the currently configured message handler.  
**returns:** The message handler.

**b\_enforceUser** [user name] *blib/b\_enforceUser*  
enforce that the user is the given one and if not, exit the script and set a non-zero status code  
[user name]: user name to check against  
**returns:** nothing  
*@B\_E*

**b\_isFunction** [potential function name] *blib/b\_isFunction*  
check whether the given function is defined  
**returns:** zero exit code if the function is defined

**b\_getBlibModules** *blib/b\_getBlibModules*  
get all available blib module names as a newline-separated list  
**returns:** all available blib module names as newline-separated list

**b\_listContains** [list] [entry] *blib/b\_listContains*  
check whether the given list contains the given entry  
[list]: newline-separated list  
[entry]: string to be found on a single line within the list (equality check)  
**returns:** a zero exit code if the list contains the entry; a non-zero exit code otherwise

**b\_deps** [dependency 1] ... [dependency n] *blib/b\_deps*  
Assert that the given dependencies are met and error out with `B_E` otherwise. This function is meant to be used by modules or scripts to declare all of their dependencies.  
[dependency i]: Command that is absolutely required to run this script.  
**returns:** Nothing. Errors out with `B_E`, if dependencies are not met.  
*@B\_E*

**b\_import** [module] [double import] *blib/b\_import*  
Import the given module into the current context.  
[module]: relative path of the module to import (relative to the blib/lib root directory)

[double import]: if set to 1, import the given module regardless of whether it was imported before (default: 0 = don't do duplicate imports)

**returns:** nothing, errors out if the import failed and sets a non-zero status code; if the import was successful or previously done, a zero exit code is set

@StateChanging

@B\_E

**b\_generateStandalone** [function] [module dep 1] .. [module dep n] - [function dep 1] .. [function dep d] - [function param 1] .. [function param p] *blib/b\_generateStandalone*

Create a standalone variant of blib in a single file running the given function when called (sourcing that file will only make the functions available) and print that file to stdout.

The current execution state is not retained.

[function]: The function to call when the generated script is executed. All script parameters when calling [output file] are passed to this function. The function must be available in the current context.

[module dep i]: Names of the modules to include in the standalone file. They do not need to be imported. They are loaded in the specified order.

[-]: Dash used as separator between the various types of arguments. If none is provided, all parameters are assumed to be modules.

[function dep j]: An arbitrary number of functions that need to be added in order to satisfy the dependencies of the function to call (e.g. if function A is meant to be called, but uses function B internally, you'll have to pass B as one of its dependencies). Dependencies that can be found in added modules should *not* be added.

[function param p]: Static parameters to add to the function as single String. Dynamic parameters should be passed to the generated script.

**returns:** Sets a zero exit code and prints the output file to stdout on success. May error out otherwise.

@B\_E

**b\_execFuncInCurrentContext** [function] [module dep 1] .. [module dep n] - [function param 1] .. [function param p] *blib/b\_execFuncInCurrentContext*

Execute the given function in the current context.

[function]: The function to execute.

[module dep i]: Names of the modules required by the function. They do not need to be imported by the function itself.

[-]: A dash as separator character between the various parameters.

[function param p]: An arbitrary number of function parameters.

**returns:** Whatever the executed function returns.

**b\_execFuncAs** [user] [function] [module dep 1] .. [module dep n] - [function dep 1] .. [function dep d] - [function param 1] .. [function

**param p]** *blib/b\_execFuncAs*

Attempt to execute the Bash function as the given user.

Whether or not this works highly depends on the underlying OS and its (sudo & su) configuration. In particular this function may cause further execution to wait for the user to type in the password of the requested user.

If the given user is identical to the current user, `b_execFuncAs` may decide to run the function in the current context. Otherwise it may run in a different process, i.e. all initialization and state may be lost. Thus make sure to create any required state within your function.

[user]: User to execute the function as (default: root).

[function]: The function to execute.

[module dep i]: Names of the modules required by the function. They do not need to be imported by the function itself. They are loaded in the specified order.

[-]: A dash as separator character between the various parameters.

[function dep j]: An arbitrary number of functions that need to be added in order to satisfy the dependencies of the function to call (e.g. if function A is meant to be called, but uses function B internally, you'll have to pass B as one of its dependencies). Dependencies that can be found in added modules should *not* be added.

[function param p]: An arbitrary number of function parameters.

**returns:** Whatever the executed function returns. A non-zero exit code may also indicate that the user switch didn't work. In particular `B_E` is *not* called if the executed function returns an error.

*@B\_E*

**b\_isModule [module name]** *blib/b\_isModule*

Test whether the given name represents a blib module name.

**returns:** sets a zero exit code if the given name is a valid module name

## args

Stateful argument parser for bash.

Regular arguments and options are parsed via `b_args_parse`. Afterwards they can be retrieved via `b_args_get` and `b_args_getOption`. Options may have parameters, can be repeated and combined.

The module can also check the correctness of options. All remaining correctness checks (e.g. for regular or option parameters) are left to the user of this module.

Conventions:

- Options always start with - and may occur everywhere.
- Single character options may be combined, e.g. `-ajh` will be considered the same as `-a -j -h`. Long options such as `--option` cannot be combined.



*Recommendation:* Use long options for those options which require parameters and single letter options for everything else.

- Everything after a space-separated double dash (--) is not considered an option, but a regular argument.

Copyright (C) 2020 David Hobach LGPLv3  
0.9

## Dependencies

no dependencies

## Imports

types

## Global Variables

**B\_ARGS** *args/B\_ARGS*

Array of regular/non-option arguments in the order of their appearance.

Instead of using it directly, it is recommended to use `b_args_get` instead. The array may be removed in future versions.

**B\_ARGS\_OPTS** *args/B\_ARGS\_OPTS*

Map of options. `[option]_[index]` is used as key with `[index]` starting at zero. The values are the option parameters (if any). Multiple option parameters are separated by tabs.

The latter separator can be changed via `b_args_setOptionParamSeparator` before calling `b_args_parse`.

The index will only increase if options are repeated.

Instead of using it directly, it is recommended to use `b_args_getOption` instead.

The array may be removed in future versions.

## Functions

**b\_args\_setOptionParamSeparator** `[separator]` *args/b\_args\_setOptionParamSeparator*

Set the separator for multiple option parameters.

`[separator]`: String to use as separator for multiple option parameters.

**returns:** Nothing.

**b\_args\_getOptionParamSeparator** *args/b\_args\_getOptionParamSeparator*

Get the separator for multiple option parameters.

**returns:** Nothing.

**b\_args\_init** `[allow flag] [option 1] [option param count 1] ... [option n] [option param count n]` *args/b\_args\_init*

Initialize the args module. It is recommended to call this function before using

this module, if you want to achieve any non-default behaviour.

[allow flag]: If set to 0, assume that non-specified options do not have any parameters (default). If set to 1, enforce that only the given options are allowed and otherwise error out.

[option i]: An allowed option including its leading - prefix.

[option param count i]: Number of expected parameters for that option. The parameters must directly follow the option. If less parameters are found, the parser will error out.

**returns:** Nothing, always sets a zero exit code.

@StateChanging

@B\_E

**b\_args\_parse** [arguments] *args/b\_args\_parse*

Parse the given arguments.

Call **b\_args\_init** before parsing, if you desire any non-default parsing behaviour.

[arguments]: The arguments meant to be parsed, usually "\$@".

**returns:** Sets a zero exit code on success and calls **B\_E** otherwise.

@StateChanging

@B\_E

**b\_args\_assertOptions** [option 1] ... [option n] *args/b\_args\_assertOptions*

Assert that the parsed options contain only the given allowed options (or less).

[option i]: Option to check against.

**returns:** Sets a zero exit code, if the current parsed state contains only allowed options and errors out with **B\_E** otherwise. Prints a list of invalid options in the error case.

@B\_E

**b\_args\_get** [index] [fallback] *args/b\_args\_get*

Get the argument at the given index.

[index]: Index of the argument to retrieve, starting at 0.

[fallback]: Value to return, if the given index was provided as empty argument or is missing. Default: empty String

**returns:** The argument at the given index. An *empty* (existing!) argument will cause the fallback to be returned with a zero exit code. If no argument was found at that index, a nonzero exit code is set and the fallback is returned.

**b\_args\_getInt** [index] [fallback] *args/b\_args\_getInt*

Convenience wrapper for **b\_args\_get** that also checks the type of the argument to be an integer.

**returns:** See **b\_args\_get**. Also sets a nonzero exit code, if the argument is not an integer.

**b\_args\_getCount** *args/b\_args\_getCount*

Get the number of arguments.

**returns:** Number of arguments.

**b\_args\_getOption** [option] [fallback] [repeat index] [parameter index]  
*args/b\_args\_getOption*

Check whether the given option is set and retrieve its parameter, if it was.

[option]: String defining the option, e.g. `--option` or `-a`.

[fallback]: Value to return if the option did not have any parameter or was not set. Default: empty String

[repeat index]: Index of the option to retrieve, if the option was repeated multiple times (default: 0 = first option).

[parameter index]: Index of the option parameter to retrieve, starting at 0 (default: return all option parameters, separated by `b_args_getOptionParamSeparator`).

**returns:** The option parameter, if the option was set. The fallback is returned and a zero exit code is set, if the option was set, but an *empty* (existing!) parameter was provided. A nonzero exit code indicates that the option was not set (the fallback is still returned).

**b\_args\_getOptionInt** [option] [fallback] [repeat index] [parameter index]  
*args/b\_args\_getOptionInt*

Convenience wrapper for `b_args_getOption` that also checks the type of the option to be an integer.

**returns:** See `b_args_getOption`. Also sets a nonzero exit code, if the option is not an integer.

**b\_args\_getOptionCount** *args/b\_args\_getOptionCount*

Get the number of options that were set.

**returns:** Number of options (incl. repeated options).

**b\_args\_getAll** [exclude regex 1] ... [exclude regex n] *args/b\_args\_getAll*

Retrieve all arguments (excl. options).

[exclude regex i]: Arguments matching any of the given regular expressions are excluded from the return value.

**returns:** All arguments as a single escaped string that can be used to pass them to functions or other scripts (without quotes).

**b\_args\_getAllOptions** [exclude regex 1] ... [exclude regex n]  
*args/b\_args\_getAllOptions*

Retrieve all options.

[exclude regex i]: Options matching any of the given regular expressions are excluded from the return value.

**returns:** All options as a single escaped string that can be used to pass them to functions or other scripts (without quotes).

## **arr**

Collection of array related functions.

Copyright (C) 2018 David Hobach LGPLv3  
0.2

### **Dependencies**

no dependencies

### **Imports**

no imports

### **Functions**

**b\_arr\_join** [delimiter] [array] *arr/b\_arr\_join*

Join the given array; elements are separated with the given delimiter. The array is not checked to exist.

[delimiter]: String to use as delimiter.

[array]: Expanded array to join, e.g. "\${arr[@]}".

**returns:** Joined version of the array. The exit code is always zero.

**b\_arr\_toList** [array] *arr/b\_arr\_toList*

Create a newline-separated list from the given array.

[array]: Expanded array to join, e.g. "\${arr[@]}".

**returns:** List version of the array. The exit code is always zero.

**b\_arr\_contains** [element] [array] *arr/b\_arr\_contains*

Check whether an array contains an element.

[element]: element to check for its existence in the array

[array]: expanded array to check, e.g. "\${arr[@]}"

**returns:** an exit code of 0, if the element was found and 1 otherwise

**b\_arr\_mapsAreEqual** [map spec 1] [map spec 2] *arr/b\_arr\_mapsAreEqual*

Check whether the two given maps/associative arrays are equal.

[map spec 1]: First map specification to check. Since maps cannot be passed directly to functions in Bash 4.2, you'll have to use "\${declare -p yourmap}" instead.

[map spec 1]: Second map specification to check.

**returns:** an exit code of 0, if the maps are equal and 1 otherwise; B\_E is only triggered on programming errors

@B\_E

## **cdoc**

Generate code documentation in many formats (e.g. html, pdf, manpage, ...) from code comments.

Lines applicable for the documentation in your code are assumed to match static (configurable) regular expressions. These lines are then fed to pandoc in order to generate a single html page (or pdf, manpage, ...) as documentation. If no conversion is required (input format = desired output format), pandoc is bypassed.

It should be possible to use this way of generating code documentation with most programming languages (incl. bash). The defaults however are set for bash and the blib way of documenting its code, i.e. you'll have to use the getters and setters of this module if you want something different. For instance the default is to check for lines starting with `#+` (a special bash comment line) and add everything afterwards to the output documentation.

Various callback functions can be used to add content to the output of `b_cdoc_generate`. See the documentation of that function for details.

If you wish to create code documentation for your bash project in blib style, please use `../util/blib-cdoc`.

Copyright (C) 2020 David Hobach LGPLv3  
0.6

## **Dependencies**

cat  
mktemp  
mv  
rm

## **Imports**

fs

## **Functions**

**b\_cdoc\_setExtractionRegex** *[regex] cdoc/b\_cdoc\_setExtractionRegex*  
Set the regular expression used to check for matching lines in code files. The first match (`${BASH_REMATCH[1]}`) is added to the documentation output.  
**returns:** nothing  
*@StateChanging*

**b\_cdoc\_getExtractionRegex** *cdoc/b\_cdoc\_getExtractionRegex*  
See the setter.  
**returns:** The property that was set.

**b\_cdoc\_setFileCallback** [callback function name] *cdoc/b\_cdoc\_setFileCallback*

Set the function to call by b\_cdoc\_generate exactly once before starting to process a source code file.

The callback function can be used to filter certain files from processing or add them as-is.

It should be declared as follows:

```
callback_function_name [file] [output format]
[file]:                The next file to process is passed here.
[output format]:      chosen output format
returns:              Nothing. Possible exit codes:
                      0 = continue normal processing (default)
                      1 = include the file as-is without any processing
                      2 = silently ignore that file / do not process it
                      other = abort all further processing with an error
```

**returns:** nothing

*@StateChanging*

**b\_cdoc\_getFileCallback** *cdoc/b\_cdoc\_getFileCallback*

See the setter.

**returns:** The property that was set.

**b\_cdoc\_setDocumentBeginCallback** [callback function name]

*cdoc/b\_cdoc\_setDocumentBeginCallback*

Set the function to call by b\_cdoc\_generate exactly once right before it starts generating the output document.

The callback function should be declared as follows:

```
callback_function_name [document output file] [document output format]
[document output file]: path to the document output file
                      (may not exist and should not be written to)
[document output format]: chosen output format
returns:              whatever should be added at the beginning of the output document;
                      a non-zero exit code will abort further processing
```

**returns:** nothing

*@StateChanging*

**b\_cdoc\_getDocumentBeginCallback** *cdoc/b\_cdoc\_getDocumentBeginCallback*

See the setter.

**returns:** The property that was set.

**b\_cdoc\_setPostProcessingCallback** [callback function name]

*cdoc/b\_cdoc\_setPostProcessingCallback*

Set the function to call by `b_cdoc_generate` each time a code file was fully processed.

The callback function should be declared as follows:

```
callback_function_name [processed input] [input file] [document output format]
[processed input]: Everything that was found to match the
                    extraction regex in the [input file] by b_cdoc_generate.
[input file]:      The original input file.
[document output format]: chosen output format
returns:          whatever should be added to the output document for the
                    given input file (usually the processed input or some filtered
                    version of it); a non-zero exit code will abort further processing

returns: nothing
@StateChanging
```

**b\_cdoc\_getPostProcessingCallback** *cdoc/b\_cdoc\_getPostProcessingCallback*  
See the setter.  
**returns:** The property that was set.

**b\_cdoc\_setDocumentEndCallback** [callback function name]  
*cdoc/b\_cdoc\_setDocumentEndCallback*  
Set the function to call by `b_cdoc_generate` exactly once right after it generated the output document.

The callback function should be declared as follows:

```
callback_function_name [document output file] [document output format]
[document output file]: path to the document output file
                        (may not exist and should not be written to)
[document output format]: chosen output format
returns:                whatever should be added to the end of the output
                        document; a non-zero exit code will abort further processing

returns: nothing
@StateChanging
```

**b\_cdoc\_getDocumentEndCallback** *cdoc/b\_cdoc\_getDocumentEndCallback*  
See the setter.  
**returns:** The property that was set.

**b\_cdoc\_setBlockCallback** [callback function name] *cdoc/b\_cdoc\_setBlockCallback*  
Set the function to call by `b_cdoc_generate` each time it hits a block of matching comments.

The callback function should be declared as follows:

callback\_function\_name [block] [input file] [document output format]  
 [block]: The full block of documentation that was identified.  
 [block counter]: Number of blocks previously seen.  
 [input file]: The original input file.  
 [document output format]: chosen output format  
 returns: whatever should be added instead of the given block;  
           a non-zero exit code will abort further processing

returns: nothing  
 @StateChanging

**b\_cdoc\_getBlockCallback** *cdoc/b\_cdoc\_getBlockCallback*  
 See the setter.  
 returns: The property that was set.

**b\_cdoc\_generate** [input files] [output file] [output format] [additional  
 pandoc options] *cdoc/b\_cdoc\_generate*  
 Generate a documentation file from the given list of input files or directories.

The concept is really simple: Each *block* of documentation will trigger the  
 b\_cdoc\_getBlockCallback exactly once and you may add additional parsing  
 logic on a block-wise level.

The following example will call the block callback twice (once with three block  
 1 lines and once with two block 2 lines):

```

#+block 1
#+block 1
#+block 1

#say hello
echo "hello world"
#+block 2
#+block 2
  
```

The other callback functions may be used for further processing.

[input files]: Newline-separated list of files or directories to generate the docu-  
 mentation from. The given order is respected; directories are recursively searched  
 for files. It is currently assumed that these files are encoded in UTF-8.

[output file]: Path to the documentation file to generate. Should not exist.

[output format]: The target format of the documentation to generate. See  
 pandoc for a list of available output formats. If none is specified, pandoc is  
 bypassed and the input format is chosen as output format. Passing “pandoc”  
 will let pandoc decide based on the extension of the output file.

[additional pandoc options]: All remaining parameters will be directly passed  
 to pandoc. If none are provided, -s is implicitly added as default.

returns: Sets a non-zero exit code and exits the script on errors. Output from



pandoc and other calls may be printed. Otherwise nothing is returned.

@B\_E

**b\_cdoc\_generateBlibStyle** [input files] [output file] [output format]  
[delete existing] *cdoc/b\_cdoc\_generateBlibStyle*

A convenience wrapper for `b_cdoc_generate` which sets various reasonable parameters depending on the output format.

[input files]: see `b_cdoc_generate`

[output file]: where to write the generated output documentation to

[output format]: currently one of raw|html|pdf|man is supported (default: raw)

[delete existing]: whether or not to delete previously created output files (default: true/0); if set to false (1), the function will error out if a previously created file was found

**returns:** full path to the created documentation file on success; otherwise the function may error out

@B\_E

**Callback Functions** `b_cdoc_cbPrintNewline`

*cdoc/b\_cdoc\_cbPrintNewline*

Prints a newline character.

**returns:** nothing

`b_cdoc_cbPrintFirstParam` [param]

*cdoc/b\_cdoc\_cbPrintFirstParam*

Prints the first parameter.

[param]: The parameter to print.

**returns:** the first parameter

## daemon

Module providing access to a single background process providing some service (daemon). Exiting the foreground control process will *not* terminate the background process. Attempting to start multiple background daemons will be prevented in a thread-safe way.

Each background process is assumed to implement a `daemon_main` function and must be identified by a unique String.

If you need to exchange data with the background service, please have a look at the `multithreading/ipcv` or `multithreading/ipcm` modules.

Known Issue:

Since the daemon cannot detach from its session via `setsid` in bash, the daemon will remain in the process group of its parent. So killing the parent with e.g. Ctrl-C will cause the parent group including the daemon to terminate. As a

workaround, users may either ignore SIGINT requests or make sure the parent exits as soon as possible (recommended).

Copyright (C) 2019 David Hobach LGPLv3  
0.5

## Dependencies

kill  
mkdir  
mktemp  
rm  
umask

## Imports

fd  
multithreading/mtx  
proc

## Global Variables

**B\_DAEMON\_ID** *daemon/B\_DAEMON\_ID*

Contains the ID of the daemon, if and only if the current process is the daemon process.

## Functions

**b\_daemon\_init** [quiet flag] [main name] [stdout file] [stderr file] [umask setting] *daemon/b\_daemon\_init*

Init the module paramters. It is necessary to call this method *before* using any other of this module unless you want to use the default paramters.

[quiet flag]: If set to 0 (default), don't print anything to stdout during the execution of start|stop|restart|status. Otherwise use b\_info to print informational messages.

[main name]: Name of the main loop function to execute in the background process. Returning from that function will exit the background process. Default:

**daemon\_main**

[stdout file]: Where the background process should write its stdout stream to (default: /dev/null). Lines are appended.

[stderr file]: Where the background process should write its stderr stream to (default: /dev/null). Lines are appended.

[umask settings]: The umask settings to apply to the daemon (default: 0).

**returns:** Nothing.

*@StateChanging*

**b\_daemon\_start** [id] [arg 1] ... [arg n] *daemon/b\_daemon\_start*

Start the background process.

If you need to start it as a different user, simply run this function as a different user with e.g. (b\_execFuncAs)[#b\_execFuncAs]. Please keep in mind that control processes must have the permission to send signals to the daemon PID though.

[id]: Unique identifying String of the daemon to distinguish it from others.

[arg i]: An arbitrary number of arguments which can be passed to the main loop.

**returns:** Sets a zero exit code on success. Otherwise sets a non-zero exit code. In particular B\_E is called, if the daemon is already running.

@B\_E

**b\_daemon\_stop** [id] [termination signal] [kill timeout] *daemon/b\_daemon\_stop*

Stop the background process.

[id]: Unique identifying String of the daemon to distinguish it from others.

[termination signal]: A number or string specifying the signal to send to the daemon (default: 15 / SIGTERM). See `kill -l` for an overview.

[kill timeout]: Time in seconds after which the background process will be killed, if it remains unresponsive to the termination signal (default: 0 = wait indefinitely).

**returns:** Sets a zero exit code, if the daemon terminated by itself. An exit code of 2 indicates that the daemon had to be killed. An exit code of 3 means that it wasn't running. B\_E is called on unexpected errors.

@B\_E

**b\_daemon\_restart** [id] [termination signal] [kill timeout] [arg 1] ... [arg n] *daemon/b\_daemon\_restart*

Restart the background process.

[id]: Unique identifying String of the daemon to distinguish it from others.

[termination signal]: See `b_daemon_stop`.

[kill timeout]: See `b_daemon_stop`.

[arg i]: An arbitrary number of arguments which can be passed to the main loop.

**returns:** See `b_daemon_start`.

@B\_E

**b\_daemon\_statusPid** [id] *daemon/b\_daemon\_statusPid*

Check the status of the background process.

Doesn't print informational messages to stdout.

[id]: Unique identifying String of the daemon to distinguish it from others.

**returns:** The PID and sets a zero exit code, if the daemon is running and a non-zero exit code otherwise. B\_E is only called on exceptional errors.

@B\_E

**b\_daemon\_status** [id] *daemon/b\_daemon\_status*

Check the status of the background process and print informational messages to stdout (if configured).

[id]: Unique identifying String of the daemon to distinguish it from others.

**returns:** Sets a zero exit code, if the daemon is running and a non-zero exit code otherwise. B\_E is only called on exceptional errors.

@B\_E

**b\_daemon\_getPid** [id] *daemon/b\_daemon\_getPid*

Get the process ID of the background process.

[id]: Unique identifying String of the daemon to distinguish it from others.

**returns:** The process ID and sets a zero exit code, if it could be obtained. Please note that the process may be dead anyway (use b\_daemon\_statusPid for that). Otherwise a non-zero exit code is set. B\_E is only called on exceptional errors.

@B\_E

**b\_daemon\_sendSignal** [id] [signal] *daemon/b\_daemon\_sendSignal*

Send a signal to the daemon.

For termination signals, please use b\_daemon\_stop instead.

[id]: Unique identifying String of the daemon to distinguish it from others.

[signal]: A number or string specifying the signal to send to the daemon. See `kill -l` for an overview.

**returns:** Sets a zero exit code, if the daemon was running and a non-zero exit code otherwise. B\_E is only called on exceptional errors.

@B\_E

## date

Collection of date and time related functions.

Copyright (C) 2018 David Hobach LGPLv3

0.3

## Dependencies

date

## Imports

no imports

## Functions

**b\_date\_add** date [time] [unit] [format] [utc flag] *date/b\_date\_add*

Add the given number of seconds to the given date.

[date]: date to add seconds to; the format must be understood by the Unix date utility

[time]: amount of time to add  
 [unit]: unit of the time to add, may be one of d (days), h (hours) m (minutes), s (seconds, default)  
 [format]: output format of the date, in Unix date notation (default: use the localized output)  
 [utc flag]: if set to 0, use UTC as time zone if not specified for the input *and* use it for the output (default: 1 = local time zone)  
**returns:** The input date with the given number of seconds added, in the requested format; returns a non-zero exit code on errors.  
*@B\_E*

**b\_date\_addDays** *date* [days] [format] [utc flag] *date/b\_date\_addDays*  
 Convenience wrapper to b\_date\_add with days.  
 [date]: See b\_date\_add.  
 [days]: Number of days to add.  
 [format]: See b\_date\_add.  
 [utc flag]: See b\_date\_add.  
**returns:** See b\_date\_add.  
*@B\_E*

**b\_date\_diff** [date 1] [date 2] [unit] *date/b\_date\_diff*  
 Get the amount of time between the two dates, i.e. [date 2] - [date 1].  
 [date 2], [date 1]: the two dates to subtract; the time part is assumed to be identical if not specified within the dates  
 [unit]: unit of the result, may be one of d (days), h (hours) m (minutes), s (seconds, default)  
**returns:** The amount of time between the given two dates [date 2] - [date 1], rounded down. Returns a non-zero exit code on errors.  
*@B\_E*

**b\_date\_getFileModAge** [file] [unit] *date/b\_date\_getFileModAge*  
 Get the time that passed since the last modification of the file.  
 [file]: Full path to the file to check.  
 [unit]: unit of the time to retrieve, may be one of d (days), h (hours) m (minutes), s (seconds, default)  
**returns:** The amount of time in the given unit since the last modification. May be rounded down. Sets a non-zero exit code on errors.  
*@B\_E*

## delay

Simplistic module to delay commands to a future time.  
 Requires polling.

All timestamps in this module must be integers and a larger timestamp must denote a time *after* a smaller timestamp.

Copyright (C) 2019 David Hobach LGPLv3  
0.3

## Dependencies

no dependencies

## Imports

no imports

## Global Variables

**B\_DELAY\_EXECUTED** *delay/B\_DELAY\_EXECUTED*

The number of commands executed during the last invocation of `b_delay_execute`.

## Functions

**b\_delay\_to** [**timestamp**] [**command**] *delay/b\_delay\_to*

Delay the given command to be executed at the given time.

[**timestamp**]: An integer timestamp (e.g. `$SECONDS`, Unix timestamp in s/ms/ns, ...).

[**command**]: The command to execute at the given time.

**returns**: Nothing.

*@StateChanging*

**b\_delay\_execute** [**timestamp**] *delay/b\_delay\_execute*

Execute all commands which are due at the given time.

[**timestamp**]: Integer timestamp representing the current point in time.

**returns**: Nothing. The exit code is equal to the number of commands with a non-zero exit code. `B_DELAY_EXECUTED` is updated with the number of commands executed.

*@StateChanging*

**b\_delay\_getCommandAt** [**timestamp**] *delay/b\_delay\_getCommandAt*

Get the set of commands to be executed at the given point in time.

[**timestamp**]: Integer timestamp denoting the time for which to retrieve the commands.

**returns**: The commands to execute at that time.

## dmcrypt

Abstraction layer for cryptsetup / dm-crypt.

Features:

- automatic management of dm-crypt devices
- password support for non-tty environments

Copyright (C) 2020 David Hobach LGPLv3  
0.6

## Dependencies

dirname  
head  
mkdir  
readlink

## Imports

hash  
ui

## Functions

**b\_dmccrypt\_init** [ui mode] *dmccrypt/b\_dmccrypt\_init*

Initialize this module. This function *must* be called at least once before using any of the other functions.

[ui mode]: How to request a password from the user: auto|gui|tty (default: auto).

**returns:** Nothing.

*@StateChanging*

*@B\_E*

**b\_dmccrypt\_getMapperName** [path] *dmccrypt/b\_dmccrypt\_getMapperName*

Get the name of the dm-crypt mapper for a given path.

[path]: Full path to an encrypted file.

**returns:** A mapper name. This doesn't necessarily mean that the encrypted container is open. Use b\_dmccrypt\_isOpen for that.

*@B\_E*

**b\_dmccrypt\_createLuks** [path] [size] [fs type] [entropy source]  
[password prompt] [dm-crypt option 1] ... [dm-crypt option n]  
*dmccrypt/b\_dmccrypt\_createLuks*

Create an encrypted luks container file at the given location.

This function may request a password from the user and usually requires root access rights.

[path]: Full path to the encrypted file to create.

[size]: Filesystem size in bytes to create. Supported suffixes: b 512, kB 1000, K 1024, MB 10001000, M 10241024, GB 100010001000, G 102410241024

[fs type]: Filesystem to create inside the encrypted container. If none is specified (default), no file system is created.

[entropy source]: Source of entropy to use for the file setup (default: /dev/urandom).  
 [password prompt]: Prompt string to ask the user for his password (optional).  
 [dm-crypt option i]: These options are directly passed to **cryptsetup**.  
**returns:** Sets a zero exit code on success and errors out with B\_E otherwise.  
*@B\_E*

**b\_dmcrypt\_open** [path] [mount point] [output var] [password prompt]  
 [dm-crypt option 1] ... [dm-crypt option n] *dmcrypt/b\_dmcrypt\_open*  
 Open/Decrypt the given container and optionally mount it.  
 [path]: Full path to the encrypted file.  
 [mount point]: Where to mount the decrypted data (optional). If no mount point is specified, it will not be mounted.  
 [output var]: The name of the variable to write the created device to (optional).  
 [password prompt]: Prompt string to ask the user for his password (optional).  
 [dm-crypt option i]: These options are directly passed to **cryptsetup**.  
**returns:** Sets a zero exit code on success.  
*@B\_E*

**b\_dmcrypt\_close** [path] [dm-crypt option 1] ... [dm-crypt option n]  
*dmcrypt/b\_dmcrypt\_close*  
 Close the given encrypted container.  
 [path]: Full path to the encrypted file.  
 [dm-crypt option i]: These options are directly passed to **cryptsetup**.  
**returns:** A zero exit code on success. The exit code may also be zero for non-existing or already closed containers.  
*@B\_E*

**b\_dmcrypt\_isOpen** [path] *dmcrypt/b\_dmcrypt\_isOpen*  
 Check whether the given encrypted container is open (not necessarily mounted).  
 [path]: Full path to the encrypted file.  
**returns:** Sets a zero exit code, if and only if the container is open. B\_E is only called for exceptional errors.  
*@B\_E*

## fd

Collection of file descriptor related functions.

Copyright (C) 2021 David Hobach LGPLv3  
 0.3

## Dependencies

no dependencies



## Imports

no imports

## Functions

**b\_fd\_getOpen** [pid] *fd/b\_fd\_getOpen*

Retrieve all open file descriptors for the given PID.

[pid]: process ID (default: \$\$)

**returns:** Newline-separated list of open file descriptor numbers; a non-zero exit code indicates that the process could not be found.

**b\_fd\_closeNonStandard** *fd/b\_fd\_closeNonStandard*

Close all non-standard file descriptors (i.e. those > 2) held by the current process.

**returns:** Nothing. B\_E is called on unexpected errors.

@B\_E

**b\_fd\_closeAll** *fd/b\_fd\_closeAll*

Close all file descriptors held by the current process.

**returns:** Nothing. B\_E is called on unexpected errors.

@B\_E

## flog

Flexible log writer for bash.

Features:

- arbitrary output support (files, network streams, stdout, stderr, ...) in a user-defined format
- optional log file reduction
- optional thread safety
- support for partial messages

In order to log to the system log, please use the logger command instead. This library is mostly meant for application logs handled in a more custom manner.

Exact format of log entries:

[header] [message]

[header]: Can be arbitrarily defined in the  
respective callback function. If nothing  
is defined, the below default header  
is used:

[default header] = '[default date] '

[default date]: current date in the format as used  
by date +"%F %T %Z" (the format can be changed)

Copyright (C) 2020 David Hobach LGPLv3

0.6

## Dependencies

cat  
date  
mkdir  
mktemp  
readlink  
rm  
tail

## Imports

fs  
hash  
multithreading/mtx

## Global Variables

**B\_FLOG\_SEV** *flog/B\_FLOG\_SEV*

Global map for human readable severities which may be used by users of this script.

It was inspired by the severities of RFC5424.

Currently supported values: emergency|alert|critical|crit|error|err|warning|warn|notice|informational|info|debug

## Functions

**b\_flog\_printSeverity** [**severity**] *flog/b\_flog\_printSeverity*

[severity]: see b\_flog\_init

Print the given severity in a way for logging. This function is meant to be used as building block for header functions.

**returns:** a printed version of the given severity for logging

**b\_flog\_close** *flog/b\_flog\_close*

close the currently open log; is automatically called, but users may want to call it themselves to force the respective file descriptor to be closed before the program is ended

**returns:** nothing

*@StateChanging*

**b\_flog\_init** [**log file name**] [**header callback function**] [**log reduction lines**] [**thread safe**] [**intermediate**] *flog/b\_flog\_init*

Initialize this log writer. This function **must** be called before any others.

[log file name]: name of the log file to write to; special files such as /dev/stdout, /dev/stderr (default), /dev/tcp, /dev/udp are supported if your bash version supports them; the file doesn't need to exist

[header callback function]: optional name of the function to be called whenever a new log entry is generated; the function must be defined as follows:

[header callback function] [severity]  
 [severity]: see [b\_flog\_log](#b\_flog\_log)  
 returns: the full header meant to be used for the current moment in time  
         with the given severity (without knowing the message details)  
         and sets a non-zero exit code on errors; errors may cause the  
         message to be logged without header

[log reduction lines]: if set to a positive integer, reduce the log file approximately to that number of lines during logging (default: 3000) - see [b\_flog\_setLogReductionLinesApprox] for details; this option has no effect on non-file outputs (stdout, network output, ...)

[thread safe]: Whether calls to [b\_flog\_log] should be thread safe (0) or not (default: 1 = not thread safe).

[intermediate]: String to use as intermediate separator when chaining partial log messages (default: [b\_getDefaultMessageHandlerIntermediate]).

**returns:** sets a non-zero exit code on errors and may exit the script

*@StateChanging*

*@B\_E*

**b\_flog\_log** [message] [severity] [first part] [last part] *flog/b\_flog\_log*

Log the given message with the given optional severity.

If the [thread safe] variant was chosen, may wait for other log sources to write their message first.

[message]: message to log

[severity]: users may pass arbitrary numbers or even Strings here, but it is recommended to stick to the priorities defined in \$BLIB\_FLOG\_SEV (default: \${B\_FLOG\_SEV["info"]})

[first part]: If set to 0, assume that the given message is the first part of an overall chain of messages (default: 0).

[last part]: If set to 0, assume that the given message is the final part of an overall chain of messages (default: 0). Please note that other threads may be blocked from writing to the output, if the last message of a chain was not yet received.

**returns:** Sets a non-zero exit code on errors. B\_E is only called, if logging failed entirely.

*@B\_E*

**b\_flog\_messageHandler** [message type] [message] [first part] [last part] *flog/b\_flog\_messageHandler*

A message handler implementation that handles messages by logging them via [b\_flog\_log].

Issues with the logging system itself (e.g. log file not writable) are written to stderr.

If you don't want to log all messages and/or handle some of them differently, you can simply write a wrapper for this function.

[message type]: See [b\_defaultMessageHandler].

[message]: See `b_defaultMessageHandler`.  
[first part]: See `b_defaultMessageHandler`.  
[last part]: See `b_defaultMessageHandler`.  
**returns:** Nothing. Never causes errors.

**b\_flog\_getDateFormat** *flog/b\_flog\_getDateFormat*  
Get the date format used for the header by this log writer (see “man date” for explanations).  
**returns:** see above

**b\_flog\_setDateFormat** [format string] *flog/b\_flog\_setDateFormat*  
Set the date format used for the header by this log writer (see “man date” for explanations).  
**returns:** nothing  
*@StateChanging*

**b\_flog\_getLogReductionLinesLowerBound** *flog/b\_flog\_getLogReductionLinesLowerBound*  
Get the number of lines that the log file will at least have after a log file reduction.  
**returns:** see above

**b\_flog\_getLogReductionLinesUpperBound** *flog/b\_flog\_getLogReductionLinesUpperBound*  
Get the maximum number of lines that the log file will have before it is reduced.  
**returns:** see above

**b\_flog\_setLogReductionLinesLowerBound** [bound] *flog/b\_flog\_setLogReductionLinesLowerBound*  
Set the number of lines that the log file will at least have after a log file reduction.  
[bound]: number of lines to use for that bound  
**returns:** nothing  
*@StateChanging*

**b\_flog\_setLogReductionLinesUpperBound** *flog/b\_flog\_setLogReductionLinesUpperBound*  
Set the maximum number of lines that the log file will have before it is reduced.  
[bound]: number of lines to use for that bound  
**returns:** nothing  
*@StateChanging*

**b\_flog\_setLogReductionLinesApprox** [line count] *flog/b\_flog\_setLogReductionLinesApprox*  
Set the number of average number of lines that the log file should have; counts  $\leq 0$  indicate no limit.  
[line count]: reduce the log after reaching  $1.2 \times [\text{line count}]$  lines to  $0.8 \times [\text{line count}]$  lines  
**returns:** nothing  
*@StateChanging*

**b\_flog\_getHeaderFunction** *flog/b\_flog\_getHeaderFunction*

Get the name of the header callback function that is used.

**returns:** see above

**b\_flog\_setHeaderFunction** [header function] *flog/b\_flog\_setHeaderFunction*

Set the name of the header callback function to be used.

[header function]: name of the header function to use

**returns:** nothing

*@StateChanging*

**Header Functions** *b\_flog\_defaultHeader* [severity]

*flog/b\_flog\_defaultHeader*

Default header callback function used with *b\_flog\_init*.

[severity]: the default header ignores the severity

**returns:** the default header meant to be used for the current moment in time

*b\_flog\_headerDateSeverity* [severity]

*flog/b\_flog\_headerDateSeverity*

An alternative to the default header callback function which appends the severity to the default header.

[severity]: see *b\_flog\_init*

**returns:** the default header with the severity appended

*b\_flog\_headerDateScriptSeverity* [severity]

*flog/b\_flog\_headerDateScriptSeverity*

An alternative to the default header callback function which appends the calling script and the severity to the default header.

[severity]: see *b\_flog\_init*

**returns:** the default header with the calling script and severity appended

## **fs**

Collection of file and file system related functions.

Copyright (C) 2022 David Hobach LGPLv3

0.4

## **Dependencies**

cat

findmnt

head

lsblk

mktemp

mount

rm

stat  
sync  
wc

## Imports

no imports

## Functions

**b\_fs\_isEmptyDir** [dir] *fs/b\_fs\_isEmptyDir*

Check whether the given directory is empty or non-existing. It is not checked whether the passed parameter is a file preventing a directory from being created.  
[dir]: full path to the directory to check

**returns:** a zero exit code if the directory does not exist or is empty

**b\_fs\_getLineCount** [file] *fs/b\_fs\_getLineCount*

Get the number of lines of the given file.

[file]: full path to a file

**returns:** the number of lines; a non-zero exit code is set on errors

@B\_E

**b\_fs\_waitForFile** [file] [maximum time] *fs/b\_fs\_waitForFile*

Sleep until the given file appears. The check interval is 1s.

[file]: full path to the file or directory to wait for

[maximum time]: maximum time in s to wait for the file to appear (default: forever)

**returns:** Sets a zero exit code if the file appeared and a non-zero exit code on a timeout.

**b\_fs\_getMountpoints** [device] *fs/b\_fs\_getMountpoints*

Get all mountpoints for the given device.

[device]: Full path to the device (incl. /dev/) for which to obtain the mountpoints.

**returns:** A newline-separated list of mountpoints where the given device is mounted to. Sets a non-zero exit code if no such mountpoints were found.

**b\_fs\_mountIfNecessary** [device] [mount point] [enforce] [mount options] *fs/b\_fs\_mountIfNecessary*

Mount the given device if it isn't already mounted.

[device]: Full path to the device (incl. /dev/) to mount.

[mount point]: Full path where to mount the device. If no mount point is specified, a /tmp/ mount point is chosen. Non-existing directories are created. Is ignored if another mount point already exists.

[enforce]: If set to 0, enforce the given mount point to be used in addition to potentially existing ones (default: 1). Mount options are ignored.

[mount options]: Options to pass to `mount`, if it needs to be executed (default:

none).

**returns:** The chosen mount point or a newline-separated list of existing mount points on success; sets a non-zero exit code on failure.

@B\_E

**b\_fs\_createLoopDeviceIfNecessary** [file] *fs/b\_fs\_createLoopDeviceIfNecessary*

Create a loop device for the given file if no old one exists. Usually requires root access rights.

[file]: File for which to create a loop device.

**returns:** Created loop device or previously used one (incl. /dev/). Sets a non-zero exit code, if no device could be created.

@B\_E

**b\_fs\_removeUnusedLoopDevice** [device|file] *fs/b\_fs\_removeUnusedLoopDevice*

Remove a loop device, if and only if it is unused by the operating system. Otherwise mark it for removal once it becomes unused. Usually requires root access rights.

[device|file]: Full path (incl. /dev/) to the loop device or to the backing file.

**returns:** Sets a zero exit code, if the loop device was not used and could thus be successfully removed *or* does not exist. A nonzero exit code indicates that the device is still being used. B\_E is called on other errors.

@B\_E

**b\_fs\_parseSize** [string] [check flag] *fs/b\_fs\_parseSize*

Parse human-readable file system sizes that include units.

[string]: A string denoting a file system size of the format [number][unit]. Unit may be one of KB 1000, K 1024, MB 10001000, M 10241024, GB 100010001000, G 102410241024, and so on for T, P. If no unit is provided, the number is assumed to denote bytes. The number must be an integer.

[check flag]: Check whether the result makes sense (default: 0/true). This check will make integer overflows less likely.

**returns:** The respective number of bytes meant with the given string. B\_E is called on parsing errors.

@B\_E

**b\_fs\_removeWithOverwrite** [file] [randomness source] *fs/b\_fs\_removeWithOverwrite*

Overwrite the given file with random data, then remove it. This is meant to prevent a potential reconstruction of the file after its removal.

*Warning:* The reconstruction may still work on some types of file systems or physical storage systems (e.g. on flash disks/SSDs).

[file]: Full path to the file to remove. Directories are currently not supported.

[randomness source]: Device to use as source of random data (default: /dev/urandom).

**returns:** Nothing. B\_E is called on errors.

@B\_E

**b\_fs\_isRotatingDrive** [block device] *fs/b\_fs\_isRotatingDrive*  
 Check whether the given block device is a rotating disk (non-SSD) or not.  
 [block device]: Device name or path to check.  
**returns:** Nothing. Sets a zero exit code, if the device is a rotating one. Non-existing devices trigger B\_E.  
*@B\_E*

**b\_fs\_getBlockDevice** [file] *fs/b\_fs\_getBlockDevice*  
 Get the block device on which the given file or directory is stored.  
 [file]: Full path to the file.  
**returns:** Full device path where the given file or directory is stored. May return pseudo file systems (e.g. tmpfs).  
*@B\_E*

**b\_fs\_removeRelativelySafely** [file] [randomness source] *fs/b\_fs\_removeRelativelySafely*  
 A best-effort implementation that attempts to remove files from the file system in a non-reconstructible way.  
 Contrary to b\_fs\_removeWithOverwrite it'll attempt to achieve similar results on SSDs.  
**May require root privileges.**  
*Warning:* The reconstruction may still work depending on your hardware.  
 [file]: Full path to the file to remove. Directories are currently not supported.  
 [randomness source]: Device to use as source of random data (default: /dev/urandom).  
**returns:** Nothing. B\_E is called on errors.  
*@B\_E*

**b\_fs\_enumerate** [path list] [nonexisting] *fs/b\_fs\_enumerate*  
 Enumerate all files found in the given list of paths. Recurse into directories as necessary.  
 [path list]: Newline-separated list of files and directories.  
 [nonexisting]: 0 = Error out with B\_E on non-existing files (default). 1 = Silently drop non-existing files. 2 = Include non-existing files in the output.  
**returns:** List of files found in all of the given paths.  
*@B\_E*

## hash

Hash functions.

Copyright (C) 2020 David Hobach LGPLv3  
 0.5

## Dependencies

no dependencies



## Imports

no imports

### **b\_hash\_file** [file] [algorithm]

*hash/b\_hash\_file*

Compute the hash of the given file.

[file]: Full path to the file.

[algorithm]: Algorithm to use. Currently supported: md5|sha1|sha224|sha256|sha384|sha512|crc|blake2 (default: md5).

**returns:** The hash of the given file.

@B\_E

### **b\_hash\_str** [string] [algorithm]

*hash/b\_hash\_str*

Compute the hash of the given string.

[string]: String which to compute the hash for.

[algorithm]: Algorithm to use. Currently supported: md5|sha1|sha224|sha256|sha384|sha512|crc|blake2 (default: md5).

**returns:** The hash of the given string.

@B\_E

## http

Collection of http related functions.

Copyright (C) 2018 David Hobach LGPLv3

0.2

## Dependencies

curl

## Imports

types

## Global Variables

**B\_HTTP\_CHECKURLS** *http/B\_HTTP\_CHECKURLS*

Each call to `b_http_getOnlineStatus` causes one of the URLs in this array to be visited.

It is recommended to pick a relatively large number of URLs with SSL support to remain relatively anonymous, if `b_http_getOnlineStatus` is called multiple times.

Defaults to the European/US Alexa Top 10 (which hopefully blends in to the masses).

## Functions

**b\_http\_rawUrlEncode** [string] *http/b\_http\_rawUrlEncode*

Encode the given string according to RFC 3986.

[string]: to encode

**returns:** Returns a string in which all non-alphanumeric characters except `-.~` have been replaced with a percent (%) sign followed by two hex digits. This is the encoding described in RFC 3986 for protecting literal characters from being interpreted as special URL delimiters, and for protecting URLs from being mangled by transmission media with character conversions (like some email systems). A non-zero exit code is set on errors.

@B\_E

**b\_http\_rawUrlDecode** [string] *http/b\_http\_rawUrlDecode*

Decode the given string encoded with `b_str_rawUrlEncode` or an equivalent function.

[string]: to decode

**returns:** The literal string with all hex characters replaced; a non-zero exit code is set on errors.

**b\_http\_getOnlineStatus** [timeout] *http/b\_http\_getOnlineStatus*

Find out whether we are online or not by attempting an http connection.

One of `B_HTTP_CHECKURLS` is possibly visited during the process.

Use `b_net_getDNSStatus` for DNS-only checks.

[timeout]: Timeout in seconds for hanging checks (default: 5).

**returns:** 0, if we're online, 1 if only DNS works, 2 if neither DNS nor http(s) worked, 3 if the check timed out; `B_E` will be called if the status cannot be determined.

@B\_E

**b\_http\_testProxy** [proxy string] [intransparent only] [timeout]

*http/b\_http\_testProxy*

Test whether the given proxy is working as advertised.

[proxy string]: Connection string to test, e.g. `https://1.1.1.1:234`.

[intransparent only]: If set to 0 (default), only accept intransparent proxies (i.e. those not revealing your IP).

[timeout]: Time in seconds after which to consider the proxy non-responsive (default: 5).

**returns:** Nothing, but sets a zero exit code, if and only if the proxy appears to work.

## i18n

Collection of data and functions related to internationalization.

Copyright (C) 2022 David Hobach LGPLv3  
0.2

## Dependencies

shuf  
timedatectl

## Imports

no imports

## Global Variables

**B\_I18N\_COUNTRY2TIMEZONE** *i18n/B\_I18N\_COUNTRY2TIMEZONE*  
ISO 3166-2 country code -> newline-separated list of time zones in that country

## Functions

**b\_i18n\_getSystemTimezone** *i18n/b\_i18n\_getSystemTimezone*  
Get the system time zone.  
**returns:** The system time zone.  
*@B\_E*

**b\_i18n\_setRandomSystemTimezone** [**country code**] [**max retries**]  
*i18n/b\_i18n\_setRandomSystemTimezone*  
Attempt to set the system time zone to a random one. Useful to e.g. fool web trackers.  
May require root privileges.  
[country code]: ISO 3166-2 country code. If specified, limit the choice to a time zone of that country (default: empty/all countries).  
[max retries]: How often to retry before giving up - some Linux systems may not support certain time zones (default: 1).  
**returns:** The timezone that was set. Errors trigger B\_E.

## ini

Stateful ini reader for bash.

Currently only a single file per instance of this library/thread is kept in memory, but you can read multiple files one after another or in multiple threads.

Implementation Specifics:

- names/keys & values are case sensitive
- comment lines may start with ; or #
- whitespace lines are ignored

- duplicate names may result in undefined behaviour (usually the second will override the first)
- all characters following the = are considered part of the value (incl. whitespace); whitespace before and after the value may be trimmed by the getters though (check their description)
- values are not interpreted (e.g. quotes, escape characters, ...)
- whitespace around keys and around section qualifiers is ignored

Copyright (C) 2018 David Hobach LGPLv3  
0.5

## Dependencies

no dependencies

## Imports

no imports

## Functions

**b\_ini\_read** [**ini file**] *ini/b\_ini\_read*

read the given ini file and keep it in thread-local memory so that subsequent calls to the b\_ini\_get functions will return the values from the ini file; subsequent calls to this function will update the internal state to represent the file last read in this thread

[ini file]: path to the ini file to read

**returns:** an error message on errors and sets a non-zero exit code on errors

*@StateChanging*

*@B\_E*

**b\_ini\_get** [**name**] [**section**] *ini/b\_ini\_get*

get the value for the ini entry with the given name as String in raw format

[name]: name/key of the ini entry to retrieve

[section]: section where to look for the entry with the given name (default: without section)

**returns:** value of the ini entry matching exactly the given section and name incl. any whitespace; a non-zero exit code is set if such an entry wasn't found

**b\_ini\_getString** [**name**] [**section**] *ini/b\_ini\_getString*

get the value for the ini entry with the given name as String and remove all whitespace around the returned String

[name]: name/key of the ini entry to retrieve

[section]: section where to look for the entry with the given name (default: without section)

**returns:** value of the ini entry matching exactly the given section and name

excl. any whitespace around; a non-zero exit code is set if such an entry wasn't found

**b\_\_ini\_getInt** [name] [section] *ini/b\_\_ini\_getInt*

get the value for the ini entry with the given name as integer

[name]: see b\_\_ini\_get

[section]: see b\_\_ini\_get

**returns:** see b\_\_ini\_get; additionally it is checked whether the return value is an integer (if not, a non-zero exit code of 2 is set and the return value is undefined)

**b\_\_ini\_getBool** [name] [section] *ini/b\_\_ini\_getBool*

get the value for the ini entry with the given name as boolean

[name]: see b\_\_ini\_get

[section]: see b\_\_ini\_get

**returns:** see b\_\_ini\_get; 0 is returned via echo for true, 1 for false; the exit code indicates a potential error during parsing (2) or a missing entry (1) and *not* true/false

**b\_\_ini\_assertNames** [section 1] [name 1] ... [name n] – [section 2]  
[name 1] ... [name m] *ini/b\_\_ini\_assertNames*

Assert that the given sections contains *at most* the given names and no additional ones.

This is a useful function to detect user mistakes and should be called right after b\_\_ini\_read.

Multiple sections can be separated with “–”.

[section]: see b\_\_ini\_get

[name]: see b\_\_ini\_get

**returns:** Sets a zero exit code if and only if the last read ini file doesn't contain any additional names. Otherwise B\_E is triggered. B\_ERR will list the invalid names.

@B\_E

## keys

Simple *system-wide* cryptographic key store protected by a master password.

A key store is only opened when necessary. It'll remain open from then on until an application calls b\_keys\_close.

The default key store can be found at `/etc/blib/keys`. Applications may deploy their own exclusive key store, if necessary (not recommended).

Usually requires root access rights.

Features:

- thread safe: no write operation can happen to a closed key store (b\_keys\_close

and write operations are single threaded only)  
- retrieved keys are read-only unless managed via this interface

Copyright (C) 2022 David Hobach LGPLv3  
0.7

## Dependencies

cat  
cp  
find  
findmnt  
mkdir  
readlink  
rm

## Imports

dmccrypt  
multithreading/mtx

## Functions

**b\_keys\_getDefaultStore** *keys/b\_keys\_getDefaultStore*

Get the system-wide default key store directory.

**returns:** The default store directory. Always sets a zero exit code.

**b\_keys\_init** [app id] [auto create] [ui mode] [password prompt] [wait time] [store dir] *keys/b\_keys\_init*

Initialize this module. This function *must* be called at least once before any other function except `b_keys_create` can be used.

Will open the key store, if it's closed.

[app id]: Unique application ID (recommended: `$B_SCRIPT_NAME`).

[auto create]: Automatically create a new key store, if none exists (default: 0 = do it). Users may create their own key store using `cryptsetup` otherwise.

[ui mode]: How to request the master password from the user: `auto|gui|tty` (default: `auto`).

[password prompt]: Prompt string to ask the user for his password (optional).

[wait time]: Maximum time in ms to wait for another process writing to a key (default: 300) (-1 = indefinitely).

[store dir]: Full path to a directory where to manage the keys (default: `b_keys_getDefaultStore`). Only applications requiring an exclusive key store should use a non-default value here.

**returns:** Sets a zero exit code on success and errors out with `B_E` otherwise.

*@StateChanging*

*@B\_E*

**b\_keys\_add** [key id] [key path] *keys/b\_keys\_add*

Add the given key to the key store.

[key id]: Unique identifier for the key to add.

[key path]: Full path to the key to add. It is *not* removed. Use functions such as `b_fs_removeRelativelySafely` to do that.

**returns:** Sets a zero exit code on success and errors out with `B_E` otherwise.

@B\_E

**b\_keys\_get** [key id] *keys/b\_keys\_get*

Retrieve the given key from the store. If you need the content as String, please use `b_keys_getContent`.

[key id]: Unique identifier for the key to retrieve.

**returns:** Path to the key. It may not exist, if the key store was closed in the meantime or the provided ID does not exist.

@B\_E

**b\_keys\_getAll** [global] *keys/b\_keys\_getAll*

Retrieve all keys from the store.

[global]: If set to 0, also retrieve keys for other application IDs (default: 1).

**returns:** All key paths for reading as a newline-separated list. If the key store is closed or modified during the runtime, the list may be empty or incomplete.

@B\_E

**b\_keys\_getContent** [key id] *keys/b\_keys\_getContent*

Retrieve the given key content from the store. For binary keys please use `b_keys_get`.

[key id]: Unique identifier for the key to retrieve.

**returns:** The key content as String. If it doesn't exist or other errors occurred, `B_E` is called.

@B\_E

**b\_keys\_delete** [key id] [backup] *keys/b\_keys\_delete*

Delete the given key from the key store.

[key id]: Unique identifier for the key to delete.

[backup]: Whether (0) or not (1) to create a backup (default: 0).

**returns:** Sets a zero exit code on success and errors out with `B_E` otherwise.

@B\_E

**b\_keys\_close** [store dir] *keys/b\_keys\_close*

Close the key store, if necessary. Works without initialisation (which might open the key store), if necessary.

**WARNING:** 99% of all applications should *never* call this function as it may block all subsequent read operations by any other applications using this system-wide key store. The only applications that might call this function are key store management applications and only upon explicit user request. The key store is

otherwise automatically closed upon system shutdown by the running OS.  
[store dir]: The main directory of the store to close (default: the key store directory used in `b_keys_init` or - if not initialised - `b_keys_getDefaultStore`).  
**returns:** Sets a zero exit code on success (closed key store) and errors out with `B_E` otherwise.  
*@B\_E*

## meta

Functions providing information about blib modules or other bash scripts.

Copyright (C) 2020 David Hobach LGPLv3  
0.2

## Dependencies

no dependencies

## Imports

str

## Functions

**b\_meta\_getClearImports** [path] *meta/b\_meta\_getClearImports*  
Get the list of modules that the given script imports via `b_import`.  
*Important:* All `b_import` calls are assumed to be declared on a dedicated line and to start at the first character of that line (“clear” import). This is considered a feature to evade this method (for doc purposes mostly).  
[path]: Full path to the script to retrieve the module imports for.  
**returns:** Newline-separated list of imports of the given script.  
*@B\_E*

**b\_meta\_getClearDeps** [path] *meta/b\_meta\_getClearDeps*  
Get the list of dependencies that the given script declares via `b_deps`.  
*Important:* All `b_deps` calls are assumed to be declared on a dedicated line and to start at the first character of that line (“clear” dependency). This is considered a feature to evade this method (for doc purposes mostly).  
[path]: Full path to the script to retrieve the dependencies for.  
**returns:** Newline-separated list of dependencies of the given script.  
*@B\_E*

## multithreading/ipcm

An inter-process map implementation.

The map is available to all running processes during a single boot session.



Both reading and writing to the map can be done from any number of processes.

Overall Features	
# readers	multiple
# writers	multiple
read consistency	always
write consistency	always
blocking	on writes

Copyright (C) 2019 David Hobach LGPLv3  
0.2

## Dependencies

no dependencies

## Imports

multithreading/ipcv  
multithreading/mtx

## Functions

**b\_ipcm\_setNamespace** [namespace] *multithreading/ipcm/b\_ipcm\_setNamespace*  
Set the common process namespace to use. All processes inside the same namespace share a common state.

It is recommended to call this function a single time before any other functions of this module. Otherwise the default namespace, which may include unrelated processes, is used.

[namespace]: Name of the namespace to set.

**returns:** Errors out, if the name is unacceptable.

*@StateChanging*

*@B\_E*

**b\_ipcm\_getNamespace** *multithreading/ipcm/b\_ipcm\_getNamespace*  
Retrieve the currently used namespace.

**returns:** The currently used namespace.

**b\_ipcm\_change** [key] [change function] [maximum time] *multithreading/ipcm/b\_ipcm\_change*

Change the given key/value combination inside the map in a thread-safe way. May wait for changes done by other processes.

[key]: A global unique identifier for the given value.

[change function]: Name of the function to execute the change of the value. It will be called with the current key as first parameter and the current value as

second. It is expected to print the new value to set for this key. A non-zero exit code will cause `b_ipcm_change` to abort the change.

[maximum time]: maximum time in ms to wait for other processes to complete their operation (default: -1 = indefinitely)

**returns:** A zero exit code and prints the new value, if the change succeeded. An exit code of `B_RC+1` indicates that the change function returned a non-zero exit code. `B_E` is called otherwise.

@B\_E

**b\_ipcm\_get** [key] [fallback] *multithreading/ipcm/b\_ipcm\_get*

Retrieve the data found at the given key.

[key]: A global unique identifier for the data to retrieve.

[fallback]: Data to return if nothing was found for the given key (default: empty).

**returns:** Sets a zero exit code and returns the data found on success. If no data was found, the fallback data is returned and a zero exit code is set. `B_E` is called on errors.

**b\_ipcm\_unsetNamespace** [namespace] [maximum time] *multithreading/ipcm/b\_ipcm\_unsetNamespace*

Unsets the given namespace and all keys stored within it.

It is recommended to call this function when all processes finished their work.

[namespace]: The namespace to unset (default: the current namespace).

[maximum time]: maximum time in ms to wait for other processes to complete their operation (default: 0 = indefinitely)

**returns:** Sets a zero exit code only upon successful removal. Otherwise `B_E` is triggered.

@B\_E

## multithreading/ipcv

Provides means for inter-process communication (ipc) via global bash variables (v).

This implementation uses shared memory, i.e. it should be reasonably fast.

Only a single process or thread is assumed to be writing (i.e. use `b_ipcv_save`) a variable at a time and multiple processes may read it (using e.g. `b_ipcv_load`). If you need to write a single variable from multiple processes, please consider using the `multithreading/mtx` module or similar locking means in combination with this module (or just `multithreading/ipcm`).

---

### Overall Features

---

# readers	multiple
# writers	single
read consistency	always
write consistency	only for one writer

Overall Features	
blocking	never

Copyright (C) 2018 David Hobach LGPLv3  
0.3

## Dependencies

findmnt  
mkdir  
mktemp  
mv  
rm

## Imports

no imports

## Functions

**b\_ipcv\_save** [namespace] [var name 1] .. [var name n] *multithreading/ipcv/b\_ipcv\_save*

Save the current values of the given variables so that they are made available for other processes under the given namespace.

Please note that each variable is saved atomically, but individually. I.e. if you need multiple values to be updated at the same time, please use a single variable (e.g. a map).

[namespace]: Name for a common group under which the given variables should be saved. The combination of [namespace] and [variable name] must be a unique identifier across all processes running on the system.

[var name i]: The name of the global variable to make accessible for other processes. An arbitrary number of variable names can be specified.

**returns:** Nothing, but a non-zero exit code indicates failed variable save attempts. A failed save attempt also triggers B\_E.

@B\_E

**b\_ipcv\_load** [namespace] [var name 1] .. [var name n] *multithreading/ipcv/b\_ipcv\_load*

Load the given variables from the given namespace into the current process context.

[namespace]: Name of the group under which the variable was saved with b\_ipcv\_save. Must exist.

[var name i]: Name of the variable to load. Multiple names can be specified.

**returns:** A non-zero exit code indicates the number of variables that could not

be loaded unless some unexpected error occurred and B\_E is triggered. Please note that a failed load attempt/unavailable variable does generally not trigger B\_E.

@B\_E

**b\_ipcv\_loadNamespace** [namespace] [check existence] *multithreading/ipcv/b\_ipcv\_loadNamespace*

Load all variables that can be loaded for the given namespace into the current process context.

[namespace]: Name of the group for which to load all available variables.

[check existence]: Whether or not to make sure that the namespace to load exists (default: 0/check). Otherwise non-existing namespaces will not cause an error.

**returns:** Sets a zero exit code on success. Failing to load any single available variable will always trigger B\_E.

@B\_E

**b\_ipcv\_unset** [namespace] [var name 1] .. [var name n] *multithreading/ipcv/b\_ipcv\_unset*

Unset/Remove the given variables from the global namespace.

Please note that the variables will remain set in your current process context, if they were set before. Use the standard bash **unset** for that.

[namespace]: Group where the given variables belong to.

[var name i]: Name of the variable to remove. Multiple may be specified.

**returns:** The number of variables which could not be unset. B\_E is not triggered for these.

@B\_E

**b\_ipcv\_unsetNamespace** [namespace] *multithreading/ipcv/b\_ipcv\_unsetNamespace*

Remove the given global namespace and all variables it contains.

Please note that the variables will remain set in your current process context, if they were set before. Use the standard bash **unset** for that.

[namespace]: To remove.

**returns:** Sets a zero exit code only upon successful removal. Otherwise B\_E is triggered.

@B\_E

## multithreading/mtx

Collection of mutex related functions.

Mutex: Only a single process may have it at any point in time.

Semaphore: A specific maximum number of processes may have it at any point in time.

See the keys module source code for an example on how to use this mutex implementation efficiently.

Copyright (C) 2024 David Hobach LGPLv3  
0.4

## Dependencies

cat  
mkdir  
mktemp  
rm  
rmdir  
sleep  
touch

## Imports

proc

## Functions

**b\_mtx\_setSleepTime** [ms] *multithreading/mtx/b\_mtx\_setSleepTime*  
Sets the time to sleep for this module whenever active polling is done (default: 500).  
[ms]: time in milliseconds between active polling requests for e.g. mutexes done by this module; must be an integer  
**returns:** Nothing, always sets a zero exit code.

**b\_mtx\_getSleepTime** *multithreading/mtx/b\_mtx\_getSleepTime*  
Gets the time to sleep for this module whenever active polling is done.  
**returns:** The currently set time to sleep in ms.

**b\_mtx\_create** [base dir] *multithreading/mtx/b\_mtx\_create*  
Allocate a new mutex without claiming it (use b\_mtx\_try for that).  
[base dir]: Path to an *existing* directory where to store the mutex (default: not specified). By default this module will pick a temporary location. If you need a mutex that persists across reboots, please set a directory that persists across reboots here. The path should point to a local, non-network file system destination. The module must be able to create remove files or directories there at will.  
**returns:** A string identifying the mutex (mutex ID). Sets a non-zero exit code on errors.  
*@B\_E*

**b\_mtx\_release** [mutex] [block ID] *multithreading/mtx/b\_mtx\_release*  
Release the given mutex so that it can be used by other block IDs/threads.  
[mutex]: A mutex obtained via b\_mtx\_create.  
[block ID]: The block ID for which to release the mutex (default: \$\$).

**returns:** Sets a non-zero exit code if the mutex could not be removed as another process is blocking it and a zero exit code on successful removal.

**b\_mtx\_forceRelease** [mutex] *multithreading/mtx/b\_mtx\_forceRelease*  
Release the given mutex so that it can be used by other blockIDs/threads.  
Warning: This function can remove mutexes from other threads and should generally *only* be used for the removal of mutexes which are known to be stale by the calling application.  
[mutex]: A mutex obtained via b\_mtx\_create.  
**returns:** Nothing and sets a zero exit code.

**b\_mtx\_pass** [mutex] [block ID] *multithreading/mtx/b\_mtx\_pass*  
Pass a blocked mutex to another block ID (i.e. change the block ID of the given mutex).  
You should only do this if you currently own the mutex and the new process is ready to take over.  
[mutex]: A mutex obtained via b\_mtx\_create.  
[block ID]: The block ID to set for the given mutex.  
**returns:** Sets a zero exit code on success and a non-zero exit code otherwise.  
*@B\_E*

**b\_mtx\_try** [mutex] [block ID] [claim stale] [claim own] *multithreading/mtx/b\_mtx\_try*  
Attempt to obtain the given mutex. Return immediately even if it cannot be obtained.  
[mutex]: A mutex obtained via b\_mtx\_create. You may also use a static and otherwise unused directory path as mutex and share it across all relevant processes.  
[block ID]: The ID to use by which to block (default: running (sub)shell process id \$\$). This should be the process ID of the process attempting to obtain the mutex or you should know what you're doing. If you're in a subshell that should deploy a mutex against other subshells, store their \$BASHPID and call the function with that.  
[claim stale]: If set to 0, claim the mutex even if it is still blocked by some other process, but that process isn't running anymore. If set to 1 (default), the function returns without obtaining the mutex. In general this should only be used in situations where a mutex has a high probability of being stale (e.g. application start).  
[claim own]: If set to 0 (default), claim the mutex if it appears to be blocked by the provided block ID. If set to 1, consider it blocked even then.  
**returns:** The function incl. parameters to execute to remove the mutex if it was obtained and an error message stating the reason otherwise. The provided function *should* be called as part of an exit trap of the calling script or via eval. Sets an exit code of 0, if the mutex was obtained. An exit code of 1 is set, if the mutex was blocked and another non-zero exit code if some other error occurred

(the mutex might be blocked even then).

Example code:

```
local mutex=""
local mutexRet=""
mutex="$(b_mtx_create)" || { B_ERR="Failed to create a mutex." ; B_E ; }
mutexRet="$(b_mtx_try "$mutex")" \
|| { B_ERR="Failed to obtain the mutex $mutex. Reason: $mutexRet" ; B_E ; }
#assuming the mutex is only meant to be removed after full
#execution of the script:
trap "$mutexRet" EXIT
#direct removal:
#b_mtx_release "$mutex"
```

**b\_mtx\_waitFor** [mutex] [block ID] [claim stale] [maximum time]

*multithreading/mtx/b\_mtx\_waitFor*

Wait for the given mutex to become available. This will block script execution.

[mutex]: see b\_mtx\_try

[block ID]: see b\_mtx\_try

[claim stale]: see b\_mtx\_try

[maximum time]: maximum time in ms to wait for the mutex to become available  
(default: -1 = indefinitely)

**returns:** see b\_mtx\_try

## multithreading/multiw

Allow multiple processes to write to a *virtual* file at the same time without causing write inconsistencies (written data from each process mangled with each other).

This is achieved by keeping one file per process and relies on the assumption that both replacing and reading a symlink on your Linux distribution is atomic.

In order for this to work, all write operations must go through this module.

Currently reading only returns the data written by the process which wrote last. If you need some sort of appending, it makes more sense to deploy a mutex using e.g. the multithreading/mtx module.

---

Overall Features	
# readers	multiple
# writers	multiple
read consistency	partial, last writer wins
write consistency	always
blocking	never

---

Copyright (C) 2019 David Hobach LGPLv3  
0.2

## Dependencies

ln  
mv  
rm  
shuf  
stat

## Imports

no imports

## Functions

**b\_multiw\_setMaxHangTime** [seconds] *multithreading/multiw/b\_multiw\_setMaxHangTime*

Set the maximum time that a process is expected to hang between two instructions. This is relevant for various internal guarantees.

[seconds]: Time in seconds that a process hangs at most.

**returns:** Nothing.

*@StateChanging*

**b\_multiw\_getMaxHangTime** *multithreading/multiw/b\_multiw\_getMaxHangTime*

Get the maximum time that a process is expected to hang between two instructions. This is relevant for various internal guarantees.

**returns:** Time in seconds.

**b\_multiw\_write** [file path] *multithreading/multiw/b\_multiw\_write*

Write all data lying in stdin to the given *virtual* file in a thread-safe way.

[file path]: Full path to the virtual file to write to. Must not be a regular file (but may not exist).

**returns:** A zero exit code, if the write operation was successful and a non-zero exit code otherwise.

*@B\_E*

**b\_multiw\_remove** [file path] *multithreading/multiw/b\_multiw\_remove*

Remove the given virtual file *and all of its revisions*.

This function should only be called when all processes finished reading and writing. It is recommended to use it over the standard Linux **rm** as the latter will leave remnants behind.

**returns:** A zero exit code on success.

*@B\_E*



## **net**

Collection of network related functions.

Copyright (C) 2020 David Hobach LGPLv3  
0.1

### **Dependencies**

dig

### **Imports**

no imports

### **Global Variables**

**B\_NET\_CHECKHOSTS** *net/B\_NET\_CHECKHOSTS*

Each call to `b_net_getDNSStatus` causes one of the host records in this array to be requested.

It is recommended to pick a relatively large number of URLs with SSL support to remain relatively anonymous, if `b_net_getDNSStatus` is called multiple times. Defaults to the European/US Alexa Top 10 (which hopefully blends in to the masses).

**B\_NET\_DNSSERVERS** *net/B\_NET\_DNSSERVERS*

Each call to `b_net_getDNSStatus` with a `random` [server] causes one of the IPs in this array to be used as DNS server.

Defaults to common large-scale free DNS providers (that probably save your requests).

Sources:

- <https://www.techradar.com/news/best-dns-server>
- <https://dnsmap.io/articles/most-popular-dns-servers>

### **Functions**

**b\_net\_getDNSStatus** [timeout] [server] *net/b\_net\_getDNSStatus*

Find out whether DNS appears to work or not by testing it.

One of `B_NET_CHECKHOSTS` is possibly requested during the process.

Use `b_http_getOnlineStatus` for http checks.

[timeout]: Timeout in seconds for hanging checks (default: 5).

[server]: DNS server to use (default: the OS default). Passing `random` will pick a random DNS server.

**returns:** 0 if DNS works as expected, 1 if DNS works but returns NXDOMAIN and 2 on timeout; `B_E` will be called if the status cannot be determined.

@B\_E

## notify

Collection of notification related functions.

Copyright (C) 2021 David Hobach LGPLv3  
0.6

### Dependencies

getent  
id  
notify-send  
su

### Imports

fs

### Functions

**b\_notify\_waitForUserDbus** [user] [maximum time] *notify/b\_notify\_waitForUserDbus*

Wait for *some* dbus user session to come up at `/run/user/[uid]/bus`. As dbus is required for notifications to work, waiting may be required for early notifications.

[maximum time]: Maximum time in s to wait for the file to appear (default: forever).

[user]: Name of the user whose instance to wait for (default: first user with a readable home directory).

**returns:** Sets a zero exit code and returns the identified dbus instance, if a dbus instance came up and a non-zero exit code on timeout. `B_E` is used for exceptional errors.

@B\_E

**b\_notify\_send** [arg 1] ... [arg n] *notify/b\_notify\_send*

Send out a notification to the user via `notify-send`.

If run as root, may send the notification to *all* active non-root users.

Calling `notify-send` directly can be problematic depending on the user, dbus session, environment variables, ... This function aims to circumvent these potential issues.

[arg i]: All arguments are directly passed to `notify-send`.

**returns:** Nothing. Errors during notification sending will trigger `B_E`.

@B\_E

**b\_notify\_sendNoError** [arg 1] ... [arg n] *notify/b\_notify\_sendNoError*

Convenience variant of `b_notify_send` that does not exit and only prints errors with `b_defaultErrorHandler`. This function should e.g. be used in custom error

handlers to avoid recursion.

**returns:** Sets a non-zero exit code on errors.

## **os/osid**

Functions for operating system identification.

Copyright (C) 2018 David Hobach LGPLv3  
0.2

### **Dependencies**

no dependencies

### **Imports**

no imports

### **Functions**

**b\_osid\_init** [**force**] *os/osid/b\_osid\_init*

[**force**]: if set to 0, force an init even if it would otherwise not be necessary (default: 1 - only initialize if it didn't happen before)

Initialize the osid module. It should normally *not* be necessary to call this function directly, but it will be called by the osid module internally as needed.

**returns:** May error out and set a non-zero exit code on failures.

**b\_osid\_isDebian** *os/osid/b\_osid\_isDebian*

Check whether the OS running this function is a Debian Linux.

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

**b\_osid\_isDebianLike** *os/osid/b\_osid\_isDebianLike*

Check whether the OS running this function is a Debian Linux or one of its derivatives (e.g. ubuntu).

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

**b\_osid\_isOpenSuse** *os/osid/b\_osid\_isOpenSuse*

Check whether the OS running this function is a OpenSUSE.

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

**b\_osid\_isFedora** *os/osid/b\_osid\_isFedora*

Check whether the OS running this function is a Fedora Linux.

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

**b\_\_osid\_\_isCentOS** *os/osid/b\_\_osid\_\_isCentOS*

Check whether the OS running this function is a CentOS.

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

**b\_\_osid\_\_isRedHat** *os/osid/b\_\_osid\_\_isRedHat*

Check whether the OS running this function is a RedHat Linux.

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

**b\_\_osid\_\_isUbuntu** *os/osid/b\_\_osid\_\_isUbuntu*

Check whether the OS running this function is an Ubuntu Linux.

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

**b\_\_osid\_\_isFedoraLike** *os/osid/b\_\_osid\_\_isFedoraLike*

Check whether the OS running this function is a Fedora Linux or one of its derivatives (e.g. CentOS, Red Hat, Qubes OS).

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

**b\_\_osid\_\_isQubesDom0** *os/osid/b\_\_osid\_\_isQubesDom0*

Check whether the OS running this function is a Qubes OS in dom0.

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

**b\_\_osid\_\_isQubesVM** *os/osid/b\_\_osid\_\_isQubesVM*

Check whether the OS running this function is a Qubes OS in a VM.

**returns:** Sets a zero exit code if the check returns true. Does not print any output.

## **os/qubes4/dom0**

Collection of functions supporting scripting in Qubes OS 4.x dom0.

**Important:** Whenever you parse output from VMs to dom0, you **must** be extra careful and assume it totally untrusted as parsing bugs are a plausible attack vector for compromised VMs. Passing data to potentially compromised VMs of course also exposes that data's confidentiality.

Copyright (C) 2022 David Hobach LGPLv3

0.7

## **Dependencies**

basename

cat

dd  
dirname  
kill  
mktemp  
ps  
python3  
qubesdb-rm  
qubesdb-write  
qubes-prefs  
qvm-block  
qvm-check  
qvm-firewall  
qvm-ls  
qvm-pool  
qvm-run  
qvm-shutdown  
qvm-volume  
readlink  
setsid  
sleep  
sort  
tar  
tee  
timeout  
xxd

## Imports

fs  
proc  
types  
ui

## Global Variables

**B\_DOM0\_VM\_STDERR** *os/qubes4/dom0/B\_DOM0\_VM\_STDERR*

Where to append the VM stderr output for b\_dom0\_qvmRun and its related functions.

Defaults to /dev/null for security reasons (VM output is always untrusted).

**B\_DOM0\_QVM\_RUN\_PARAMS** *os/qubes4/dom0/B\_DOM0\_QVM\_RUN\_PARAMS*

Alternative method to pass parameters to b\_dom0\_qvmRun and its related functions.

Useful for e.g. --no-gui to speed up performance when you never use a VM's GUI.

Default: Empty array.

## Functions

**b\_dom0\_setVMDeps** [list] [keep defaults] *os/qubes4/dom0/b\_dom0\_setVMDeps*

Set the dependencies for all VMs used with this module to the given list of binaries.

These dependencies are checked before *any* execution of commands in *any* VM; in particular whenever `b_dom0_qvmRun`, `b_dom0_execIn`, `b_dom0_execStrIn` or `b_dom0_execFuncIn` are called.

[list]: Newline-separated list of binaries or commands that VMs must be able to execute.

[keep defaults]: If set to 0 (default), merge the default list of dependencies with the supplied one. Otherwise only keep the supplied list of dependencies.

**returns:** Nothing.

*@StateChanging*

**b\_dom0\_getVMDeps** *os/qubes4/dom0/b\_dom0\_getVMDeps*

Getter for `b_dom0_setVMDeps`.

**returns:** The current list of dependencies for VMs.

**b\_dom0\_qvmRun** [parameter 1] ... [parameter n] [vm] [command]

*os/qubes4/dom0/b\_dom0\_qvmRun*

A wrapper for `qvm-run` which sets reasonable defaults for shell scripting and applies various fixes.

Most calls to `qvm-run` should be made via this function rather than interacting with `qvm-run` directly as the Qubes OS `qvm-run` was designed with interactive shell usage in mind whereas this wrapper is intended for bash developers.

Particular features:

- a certain set of reasonable default parameters is used: `-p -q -n -u root`
- `-n` was set as auto-starting VMs during Bash scripting can heavily influence the user experience (imagine the VM being shut down manually by the user whilst a bash script is running → constant restarts)
- `stdin` is redirected to `/dev/null` by default to avoid potential security implications (accidental reads from `dom0` `stdin` passed to a VM); this can be overridden using `-stdin`
- `stdout` has the VM output and the exit code is the one of the VM
- `stderr` VM output is appended to `B_DOM0_VM_STDERR` (default: `/dev/null` for security reasons)
- distinguished exit conditions (executed command failed vs. `qvm-run` failed)
- workarounds for known Qubes bugs wrt `qvm-run` may be implemented here (e.g. qubes issues #3083, #4476, #4633 in the past)
- VM dependencies set with `b_dom0_setVMDeps` are checked

Please note that calling this function will make your script wait for the execution of the commands in the client VM.

Wherever possible, this function should be combined with `b_silence` as the VM output shouldn't be trusted. Otherwise please keep in mind that **both** `stdout` and `stderr` may have untrusted output which may even contain binary data. In order to validate against binary data you can e.g. use `b_types_parseString` or `b_types_str`.

[parameters]: Any parameters supported by `qvm-run`. If you pass `-a`, the default `-n` will be overridden. If you pass `-u`, the default root user is overridden. If you pass `-v`, `-q` will be overridden. If you pass `--stdin`, even `stdin` is passed to `qvm-run`. `-p` can be overridden by using `/dev/null` redirection. Only the short parameter versions and only one switch per argument are supported. Parameters may also be globally specified via `B_DOM0_QVM_RUN_PARAMS`, but the global parameters are ignored, if any local parameters are specified.

[vm]: The VM where to run the given [command].

[command]: The command to run.

**returns:** Sets the exit code of `qvm-run` and prints its output. May error out using `B_E` if `qvm-run` itself fails.

@B\_E

**b\_dom0\_getDispVMs** *os/qubes4/dom0/b\_dom0\_getDispVMs*

Get a list of all currently existing disposable VMs.

**returns:** The currently existing disposable VMs as newline-separated list.

@B\_E

**b\_dom0\_startDispVM** [template] *os/qubes4/dom0/b\_dom0\_startDispVM*

Start a dispVM from the given template in the background and return its name. The disposable VM will remain started until it is shut down. If you only wish to execute a single command, please use `b_dom0_qvmRun` with the `--dispVM` parameter.

It may take a while for this function to obtain the name of the dispVM.

[template]: The template to use for the dispVM. If no template is specified, use the default Qubes template.

**returns:** Name of the dispVM that was started and sets a zero exit code on success. This function may error out.

@B\_E

**b\_dom0\_execIn** [vm] [file] [user] *os/qubes4/dom0/b\_dom0\_execIn*

Execute the file as bash code in the given VM and wait for it to finish.

See `b_dom0_qvmRun` for various notes and words of caution.

[vm]: Name of the VM where to execute the given string. The VM is assumed to be started.

[file]: Bash file to execute in the given VM.

[user]: user as which to execute the bash file (default: root)

**returns:** Whatever the executed Bash code prints in the VM to `stderr` or `stdout`; the status code is set to the one of the executed Bash code on success (0).

Non-zero exit codes and error messages may come from both this function as well as the code executed in the given VM.

@B\_E

**b\_dom0\_execStrIn** [vm] [string] [user] *os/qubes4/dom0/b\_dom0\_execStrIn*

Execute the String as bash code in the given VM and wait for it to finish.

Convenience wrapper for b\_dom0\_execIn.

See b\_dom0\_qvmRun for various notes and words of caution.

[vm]: see b\_dom0\_execIn

[string]: Bash String to execute in the given VM.

[user]: see b\_dom0\_execIn

**returns:** see b\_dom0\_execIn; B\_E is *not* called if the executed command returns an error

@B\_E

**b\_dom0\_execFuncIn** [vm] [user] [function] [module dep 1] .. [module dep n] - [function dep 1] .. [function dep d] - [function param 1] .. [function param p] *os/qubes4/dom0/b\_dom0\_execFuncIn*

Execute the Bash function in the given VM and wait for it to finish.

Convenience wrapper for b\_dom0\_execIn.

See b\_dom0\_qvmRun for various notes and words of caution.

[vm]: see b\_dom0\_execIn

[user]: see b\_dom0\_execIn

[function]: Name of the function as it is declared in the current scope.

[module dep i]: Names of the modules required by the function. They do not need to be imported by the function itself.

[-]: A dash as separator character between the various parameters.

[function dep j]: An arbitrary number of functions that need to be added in order to satisfy the dependencies of the function to call (e.g. if function A is meant to be called, but uses function B internally, you'll have to pass B as one of its dependencies). Dependencies that can be found in added modules must *not* be added.

[function param p]: An arbitrary number of function parameters.

**returns:** see b\_dom0\_execIn; B\_E is *not* called if the executed command returns an error

@B\_E

**b\_dom0\_waitForFileIn** [vm] [file] [maximum time] *os/qubes4/dom0/b\_dom0\_waitForFileIn*

Convenience wrapper for b\_fs\_waitForFile.

[vm]: VM where to execute.

[file]: See [b\_fs\_waitForFile].

[maximum time]: See [b\_fs\_waitForFile].



**returns:** See [b\_fs\_waitForFile].

@B\_E

**b\_dom0\_isMountedIn** [vm] [device] *os/qubes4/dom0/b\_dom0\_isMountedIn*

Check whether the device is mounted in the given VM.

[vm]: VM where to execute.

[device]: Full path to the device (incl. /dev/) to check.

**returns:** Sets a zero exit code if the device is mounted in the VM; a non-zero exit code means that it's either not mounted or some other error occurred.

@B\_E

**b\_dom0\_mountIfNecessary** [vm] [device] [mount point] [enforce]

[mount options] *os/qubes4/dom0/b\_dom0\_mountIfNecessary*

Mount the given device in the target VM if it isn't already mounted there.

Actually a wrapper for b\_fs\_mountIfNecessary.

[vm]: VM where to execute.

[device]: Full path to the device (incl. /dev/) to mount.

[mount point]: Full path where to mount the device. If no mount point is specified, a /tmp/ mount point is chosen. Non-existing directories are created. Is ignored if another mount point already exists.

[enforce]: If set to 0, enforce the given mount point to be used in addition to potentially existing ones (default: 1).

[mount options]: Options to pass to **mount**, if it needs to be executed (default: none).

**returns:** The chosen mount point or a newline-separated list of existing mount points on success; sets a non-zero exit code on failure. As these strings are returned from the VM, extra care must be taken when parsing them.

@B\_E

**b\_dom0\_createLoopDeviceIfNecessary** [vm] [file] *os/qubes4/dom0/b\_dom0\_createLoopDeviceIfNecessary*

Create a loop device for the file in the given VM if no old one exists. Actually a wrapper for b\_fs\_createLoopDeviceIfNecessary.

This usually requires root privileges.

[vm]: VM where to execute.

[file]: File for which to create a loop device.

**returns:** Created loop device or previously used one (incl. /dev/). Sets a non-zero exit code, if no device could be created.

@B\_E

**b\_dom0\_removeUnusedLoopDevice** [vm] [device|file] [type] [map]

*os/qubes4/dom0/b\_dom0\_removeUnusedLoopDevice*

Remove a loop device from the given VM, if it is *neither* used by Qubes OS *nor* by the given VM.

*Important:* Calling this function may cause the device to be removed as soon as it becomes unused by the VM (and the VM *only!*). So if you called this function,

you should *not* use the device any further from dom0 with e.g. `qvm-block` afterwards - even if it wasn't removed.

[vm]: VM where to remove the loop device.

[device|file]: Full path (incl. `/dev/`) to the loop device or to the backing file inside the VM.

[type]: Whether the given path represents a loop device (0) or the backing file (1). If not specified, a device will be assumed, if and only if the path starts with `/dev/`.

[map]: Optional output from a previous call to `b_dom0_parseQvmBlock`. If none is specified, this function will internally call `b_dom0_parseQvmBlock`.

**returns:** Sets a zero exit code, if the loop device was not used and could thus be successfully removed *or* does not exist. A nonzero exit code indicates that the device is still being used. `B_E` is called on other errors.

@B\_E

**b\_dom0\_copy** [dom0 file] [target VM] [target VM dir] [overwrite]  
[parent dir] *os/qubes4/dom0/b\_dom0\_copy*

Grab a file or directory in dom0 and push it to the given file path in the target VM.

[dom0 file]: location of the dom0 file or directory to read from, assumed to exist

[target VM]: VM to write to, assumed to exist. Must be started.

[target VM dir]: full path to the parent directory in the target VM to copy the file or directory to; non-existing parent directories are created; the name is taken from the name of the file/directory in dom0

[overwrite]: Whether or not to overwrite an existing [destination file] (default: 0 = overwrite).

[parent dir]: Set this to 0, if the [target VM dir] is the target *parent* directory (default) and to 1 if it includes the target file or folder *name* as last element.

**returns:** Sets an exit code of 0, if everything went fine, and a non-zero exit code otherwise.

@B\_E

**b\_dom0\_crossCopy** [source VM] [source file] [target VM] [target VM dir] [overwrite] [parent dir] *os/qubes4/dom0/b\_dom0\_crossCopy*

Cross copy a file or directory from one VM to another, initiated by dom0. No user prompt is displayed.

[source VM]: Where to copy the source file from. Must be started.

[source file]: The file or directory to copy.

[target VM]: Where to copy the file to. Must be started.

[target VM dir]: full path to the parent directory in the target VM to copy the file or directory to; non-existing parent directories are created; the name is taken from the name of the file/directory in dom0

[overwrite]: Whether or not to overwrite an existing [destination file] (default: 0 = overwrite).

[parent dir]: Set this to 0, if the [target VM dir] is the target *parent* directory

(default) and to 1 if it includes the target file or folder *name* as last element.  
**returns:** Sets an exit code of 0, if everything went fine, and a non-zero exit code otherwise.  
*@B\_E*

**b\_dom0\_ensureRunning** [vm 1] ... [vm n] *os/qubes4/dom0/b\_dom0\_ensureRunning*  
 Start or unpause the given VMs if needed.  
 [vm i]: The VM to start.  
**returns:** Nothing. B\_E will be called for VMs that could not be started (maybe they don't exist?).  
*@B\_E*

**b\_dom0\_isRunning** [vm 1] ... [vm n] *os/qubes4/dom0/b\_dom0\_isRunning*  
 Check whether the given VMs are running *and* fully operational / not hanging / not paused / not booting.  
 In contrast `qvm-check --running [vm]` returns true for VMs which are currently booting and `qvm-ls` doesn't check whether the OS of a VM is hanging.  
 [vm i]: The VM to check.  
**returns:** Nothing. B\_E will be called for VMs that are not running (or don't exist?).  
*@B\_E*

**b\_dom0\_isHalted** [vm 1] ... [vm n] *os/qubes4/dom0/b\_dom0\_isHalted*  
 Check whether the given VMs are halted.  
 This is not necessarily the inverse of `b_dom0_isRunning` as VMs may e.g. be paused.  
 [vm i]: The VM to check.  
**returns:** Nothing. B\_E will be called for VMs that are not halted (or don't exist?).  
*@B\_E*

**b\_dom0\_ensureHalted** [vm 1] ... [vm n] *os/qubes4/dom0/b\_dom0\_ensureHalted*  
 Shut down the given VMs if needed.  
 [vm i]: The VM to halt.  
**returns:** Nothing. B\_E will be called for VMs that could not be halted (maybe they don't exist?).  
*@B\_E*

**b\_dom0\_exists** [vm] *os/qubes4/dom0/b\_dom0\_exists*  
 Check whether the given VM exists.  
 [vm]: The VM to check.  
**returns:** Sets a zero exit code, if the VM exists a non-zero exit code otherwise.

**b\_dom0\_openCrypt** [vm] [device] [mapper name] [rw flag]  
 [mount point] [key file] [additional options] [password prompt]

*os/qubes4/dom0/b\_dom0\_openCrypt*

In the given VM, open the given crypto device with dm-crypt and mount it to the mount point.

[vm]: The VM where to open the crypto device.

[device]: Full path to the device (incl. /dev/) to open.

[mapper name]: The name to assign to the decrypted version of the crypto block device. The created decrypted device will be found at */dev/mapper/[mapper name]*.

[rw flag]: 0=open read-write, 1=open read-only (default: 0)

[mount point]: Where to mount the decrypted data to. Non-existing directories will be created. If no mount point is specified, it will not be mounted (default).

[key file]: Full vm path to the key to use for decryption. If none is specified, password-based decryption is assumed and stdin will be read to obtain the password.

[additional options]: Single string with additional cryptsetup parameters to pass on (default: none). They are passed *as-is*, i.e. you'll have to take care of proper escaping etc. yourself.

[password prompt]: Optional string to use when the user is required to provide a decryption password.

[password]: Optional password to use for decryption. Key files have precedence over this option. Make sure to securely handle passwords in memory!

**returns:** nothing (except for user interaction prompts if no key file is provided), but sets a non-zero exit code on errors

*@B\_E*

**b\_dom0\_closeCrypt** [vm] [mapper name] [mount point] *os/qubes4/dom0/b\_dom0\_closeCrypt*

Close a crypto device opened with *b\_dom0\_openCrypt*.

[vm]: The VM where to close the crypto device.

[mapper name]: The name used when it was opened.

[mount point]: If the decrypted data is mounted inside the [vm], please specify the mount point here so that it can be unmounted before closing the device. Otherwise the function will attempt to close the device without unmounting (likely to fail).

**returns:** nothing, but sets a non-zero exit code on errors

*@B\_E*

**b\_dom0\_parseQvmBlock** [variable name] [input] *os/qubes4/dom0/b\_dom0\_parseQvmBlock*

Parse data from *qvm-block ls* to an associative array.

The indices of the associative array will be of the format *[counter]\_[field]* (counters run from 0 (inclusive) to max (exclusive)).

The special index “max” is equal to the number of lines. It can be used for iterations over the map.

Currently supported [field] values: backend|device id|id|description|used by|read-only|frontend-dev

[variable name]: Name of the associative array to use as output.

[input]: Optional output from a previous **qvm-block ls** call; if none is specified, this function will execute the call and use its output.

**returns:** A string specifying an associative array in bash syntax. You can eval that string to obtain all relevant data or use the more convenient **b\_dom0\_getQvmBlockInfo**. On errors **B\_E** is called.

@B\_E

**b\_dom0\_getQvmBlockInfo** [map] [retrieve field] [filter field 1] [filter value 1] .. [filter field n] .. [filter value n] *os/qubes4/dom0/b\_dom0\_getQvmBlockInfo*  
Convenience function to retrieve information from the output of **b\_dom0\_parseQvmBlock**. Searches for the given filter values in the given fields and retrieves the first field value matching all filters.

More simple, but less flexible than **b\_dom0\_parseQvmBlock**.

[map]: Optional output from a previous call to **b\_dom0\_parseQvmBlock**. If none is specified, this function will internally call **b\_dom0\_parseQvmBlock**.

[retrieve field]: Name of the field to retrieve.

[filter field i]: Name of any field supported by **b\_dom0\_parseQvmBlock**.

[filter value i]: The value to search for in [filter field i] (equality check).

**returns:** The value of the requested field and sets a zero exit code on success. Sets a non-zero exit code if no matching value could be found or the found value was empty. On errors **B\_E** is called.

@B\_E

**b\_dom0\_attachDevice** [dom0 device] [target VM] [rw flag] [force] *os/qubes4/dom0/b\_dom0\_attachDevice*

Attach the given device from dom0 (!) as block device to the target VM.

[dom0 device]: Full path to the device node (incl. /dev/) *in dom0*.

[target VM]: VM to attach the device to. Must be started.

[rw flag]: If set to 0, attaches the dom0 device in r/w (read-write) mode. If set to 1 (default), attaches the file in r/o (read only) mode.

[force]: If set to 0, attempt to force Qubes OS to recognize the device (default: 1). This is required for e.g. VM images. Please call **b\_dom0\_detachDevice** with the clean flag for the detach operation, if set to 0.

**returns:** The full path to the device created in the target VM and sets a zero exit code on success. Otherwise a non-zero exit code is set.

@B\_E

**b\_dom0\_attachFile** [dom0 file] [target VM] [rw flag] [force] *os/qubes4/dom0/b\_dom0\_attachFile*

Attach the given file from dom0 (!) as block device to the target VM.

The function may attempt to acquire root privileges (and thus display a password prompt).

[dom0 file]: Full path to the file *in dom0* to attach.

[target VM]: VM to attach the file to. Must be started.

[rw flag]: If set to 0, attaches the dom0 file in r/w (read-write) mode. If set to 1

(default), attaches the file in r/o (read only) mode.

[force]: If set to 0, attempt to force Qubes OS to recognize the device (default: 1). This is required for e.g. VM images. Please call `b_dom0_detachDevice` with the `clean` flag for the detach operation, if set to 0.

**returns:** The full path to the device created in the target VM and sets a zero exit code on success. Otherwise a non-zero exit code is set.

@B\_E

**b\_dom0\_attachVMDisk** [source VM] [target VM] [rw flag] [pool driver] [disk path] *os/qubes4/dom0/b\_dom0\_attachVMDisk*

Attach the entire private disk image (`private.img`) of the source VM to the target VM.

**Warning:** This is contradictory to all Qubes principles and should only be done if you know exactly what you're doing. Qubes OS even has some countermeasures to prevent accidental use of this feature which are bypassed here.

[source VM]: Name of the VM whose private disk to attach to the target VM. *All data* of that VM will be shared with the target VM. Will be shut down as part of this function and must remain shut down as long as the disk is attached.

[target VM]: VM where to attach the disk as block device to. Must be started.

[rw flag]: If set to 0, attaches the disk file in r/w (read-write) mode. If set to 1 (default), attaches the file in r/o (read only) mode.

[pool driver]: Driver of the pool that the disk was created in: One of `file`, `file-reflink` or `lvm_thin` (default: driver of the given [source VM]).

[disk path]: Full path to the disk. Default: Path to the private volume of the [source VM] in the pool of the respective [pool driver]. May override the [source VM] parameter.

**returns:** The full path to the device created in the target VM and sets a zero exit code on success. Otherwise a non-zero exit code is set. Please call `b_dom0_detachDevice` with the `clean` flag for the detach operation.

@B\_E

**b\_dom0\_getPoolDriver** [vm] [volume] *os/qubes4/dom0/b\_dom0\_getPoolDriver*

Get the name of the pool driver used by the given VM.

[vm]: VM for which to retrieve the pool driver (default: system default pool).

[volume]: VM volume type for which to retrieve the pool driver (default: `private`).

**returns:** Name of the pool driver. `B_E` is called on errors.

@B\_E

**b\_dom0\_getDefaultPoolDriver** [volume] *os/qubes4/dom0/b\_dom0\_getDefaultPoolDriver*

Retrieve the driver name of the system's default pool.

[volume]: Volume type for which to retrieve the pool driver (default: `private`).

**returns:** Driver name of the system's default pool.

@B\_E

**b\_dom0\_crossAttachDevice** [source VM] [source device] [target VM]  
**[rw flag]** *os/qubes4/dom0/b\_dom0\_crossAttachDevice*  
 Attach the given block device from the source VM to the target VM.  
 This is merely a convenience wrapper for **qvm-block attach**.  
**[source VM]**: VM where the source file can be found.  
**[source device]**: Device to attach to the [target VM].  
**[target VM]**: VM to attach the device to. Must be started.  
**[rw flag]**: If set to 0, attaches the [source device] in r/w (read-write) mode. If set to 1 (default), attaches the file in r/o (read only) mode.  
**returns**: The full path to the device created in the target VM and sets a zero exit code on success. Otherwise a non-zero exit code is set.  
*@B\_E*

**b\_dom0\_crossAttachFile** [source VM] [source file] [target VM] [rw flag]  
**[rw flag]** *os/qubes4/dom0/b\_dom0\_crossAttachFile*  
 Attach the given file from the source VM as block device to the target VM.  
**[source VM]**: VM where the source file can be found.  
**[source file]**: File to attach as block device.  
**[target VM]**: VM to attach the file to. Must be started.  
**[rw flag]**: If set to 0, attaches the [source file] in r/w (read-write) mode. If set to 1 (default), attaches the file in r/o (read only) mode.  
**returns**: The full path to the device created in the target VM and sets a zero exit code on success. Otherwise a non-zero exit code is set.  
*@B\_E*

**b\_dom0\_detachDevice** [vm] [device] [clean flag] *os/qubes4/dom0/b\_dom0\_detachDevice*  
 Attempts to detach the given device from the VM. This may fail if the VM is using the device and thus it is usually a better idea to just shut the VM down.  
**[vm]**: VM from which to detach the device.  
**[device]**: Full path to the device in the VM. E.g. the return values of **b\_dom0\_crossAttachFile**, **b\_dom0\_attachFile** or **b\_dom0\_attachVMDisk**.  
**[clean flag]**: Also wipe the device from the Qubes DB, if it's there (default: 1).  
**returns**: nothing, but sets a zero exit code on success  
*@B\_E*

**b\_dom0\_enterEventLoop** [callback function] [heartbeat interval]  
*os/qubes4/dom0/b\_dom0\_enterEventLoop*  
 Enter a blocking loop to react to Qubes OS events. **b\_dom0\_disconnectEventLoop** can be used to disconnect from the event loop asynchronously, e.g. from exit traps.  
 If you want to obtain an overview of Qubes OS events, please use the **qwatch** utility manually.  
**[callback function]**: Name of the function to call for *every* Qubes OS event. Since the number of events may be high, the function should do appropriate filtering at high performance.

The callback function should be declared as follows:

`callback_function_name [subject] [event name] [event info] [timestamp]`  
[subject]: The subject name Qubes OS provides. Usually the VM for which the event was reported. 'None' appears to mean 'dom0'.  
[event name]: Name of the event for which the callback function was called.  
[event info]: May contain additional information about the event (e.g. arguments).  
[timestamp]: When the event was received in ms since EPOCH.  
returns: Nothing. A non-zero exit code will abort further processing.  
[heartbeat interval]: Interval in ms at which to send heartbeat events (default: no heartbeat events).  
**returns:** Nothing, but uses the exit code of the last callback function execution as its own. Sets an exit code of 0, if the event loop was terminated by `b_dom0_disconnectEventLoop`. `B_E` is only called on exceptional errors.  
*@StateChanging*  
*@B\_E*

**b\_dom0\_disconnectEventLoop** *os/qubes4/dom0/b\_dom0\_disconnectEventLoop*  
Send a termination request to a dom0 event loop started with `b_dom0_enterEventLoop`. This is useful to exit the event loop from outside of it.  
**returns:** A non-zero exit code indicates that either no active event loop existed or the signal sending failed. Never errors out to be suitable for e.g. exit traps.  
*@StateChanging*

**b\_dom0\_testMultiple** `[vm] [operator] [list]` *os/qubes4/dom0/b\_dom0\_testMultiple*  
Run multiple **test** checks inside the given VM with a single `qvm-run` call.  
[vm]: Where to run the checks.  
[operator]: The test operator to use for the list of parameters, e.g. `-f`.  
[list]: Newline-separated list of parameters to check, e.g. a list of files for the `-f` operator.  
**returns:** The subset of the list that matched the operator and sets a zero exit code on success.  
*@B\_E*

**b\_dom0\_applyFirewall** `[vm] [rules]` *os/qubes4/dom0/b\_dom0\_applyFirewall*  
Apply the given rules to the VM firewall.  
**Important:** Since the rules are applied iteratively, there may be short timeframes during which the VM may have no network access.  
[vm]: VM for which to apply the firewall rules.  
[rules]: Newline-separated list of firewall rules in *raw* format (cf. `man qvm-firewall`). The rules are added in the order as specified. (This corresponds to the `qvm-firewall --raw [vm]` output.) Previously applied rules are left untouched.  
Empty lines and lines starting with `#` (comments) are ignored.



**returns:** Nothing. If a rule cannot be added for whatever reason, a drop-all rule will be inserted in the beginning for security reasons.

@B\_E

**b\_dom0\_clearFirewall** [vm] *os/qubes4/dom0/b\_dom0\_clearFirewall*

Clears the given VM firewall entirely (no rules left). This will make the VM firewall drop all connections.

Existing connections may continue to work as long as the VM and the connection remain up (this is a known Qubes OS quirk).

[vm]: VM for which to clear all rules.

**returns:** Nothing. Errors will result in a drop-all state.

@B\_E

## proc

Collection of process and thread related functions.

Copyright (C) 2020 David Hobach LGPLv3

0.2

## Dependencies

kill

killall

tail

timeout

## Imports

no imports

## Functions

**b\_proc\_pidExists** [pid] *proc/b\_proc\_pidExists*

Check whether the given process ID exists on the system.

[pid]: process ID to check for existence (process exists)

**returns:** A zero exit code, if it exists and a non-zero exit code if it doesn't; this function attempts to check the existence of the given process across *all* users, but it cannot guarantee correctness if the user running this script has very low privileges.

**b\_proc\_childExists** [pid] *proc/b\_proc\_childExists*

Check whether the given process ID exists *and* is a *direct* child of the calling bash process.

[pid]: process ID to check

**returns:** A zero exit code, if the caller is a parent of the given pid.

**b\_\_proc\_waitForPid** [pid] [maximum time] *proc/b\_\_proc\_waitForPid*

Wait for the given process to exit. If it doesn't exist, exit immediately.

[pid]: Process ID of the process to wait for.

[maximum time]: Maximum time in seconds to wait for the process to exit (default: 0 = indefinitely).

**returns:** Nothing, always sets a zero exit code. Use `b__proc_pidExists` if you need to know whether the process finished.

**b\_\_proc\_resolveSignal** [signal] *proc/b\_\_proc\_resolveSignal*

Resolve process (kill) signal names to their numeric identifiers.

[signal]: Signal name (string) or numeric identifier.

**returns:** The numeric identifier corresponding to the given signal.

@B\_E

**b\_\_proc\_killAndWait** [pid] [signal] [timeout] *proc/b\_\_proc\_killAndWait*

Send a kill/exit signal to a process and wait for it to terminate.

[pid]: Process ID of the process to wait to terminate.

[signal]: Signal name (string) or numeric identifier to send (default: SIGTERM).

[timeout]: Time in seconds after which to send a SIGKILL if the process doesn't terminate (default: 0 = wait forever).

**returns:** A zero exit code, if the process terminated without timeout or could not be found.

@B\_E

**b\_\_proc\_killByRegexAndWait** [regex] [signal] [timeout] *proc/b\_\_proc\_killByRegexAndWait*

Kill/Terminate all matching processes.

[regex]: Regular expression matched against running process names. Matching processes will be terminated.

[signal]: Signal name (string) or numeric identifier to send (default: SIGTERM).

[timeout]: Time in seconds after which to send a SIGKILL if the processes don't terminate (default: 0 = wait forever).

**returns:** A zero exit code, if the process terminated without timeout or could not be found.

@B\_E

## sqlite3

Stateful sqlite driver for bash.

This module provides all features of the sqlite interactive mode to non-interactive bash scripts. See `man sqlite3` for the available commands.

Keeping a single database connection open usually exhibits better performance than calling `sqlite3` in batch mode over and over again.

Side Note: If you want to read or write csv files, this module can also do the job for you with standard SQL syntax. See `man sqlite3` on how to read and write

csv files with sqlite.

Copyright (C) 2020 David Hobach LGPLv3  
0.5

## Dependencies

mkfifo  
mktemp  
rm  
sqlite3

## Imports

no imports

## Functions

**b\_sqlite3\_open** [db file] [timeout] *sqlite3/b\_sqlite3\_open*

Open a new sqlite connection to a database. This **must** be called exactly once before any calls to `b_sqlite3_exec`.

[db file]: The database file to connect to (default: a new in-memory database). If it doesn't exist, it may be created (the behaviour is identical to `sqlite3`).

[timeout]: Maximum time in seconds to wait for a command to execute on the database via `b_sqlite3_exec`. Default: -1 = indefinitely

**returns:** Nothing.

*@StateChanging*

*@B\_E*

**b\_sqlite3\_getOpen** *sqlite3/b\_sqlite3\_getOpen*

Retrieve the currently open database.

**returns:** Prints the currently open database and an empty string for an unnamed database. Sets a zero exit code, if and only if a database is currently open.

**b\_sqlite3\_exec** [command] [timeout] [filter input] *sqlite3/b\_sqlite3\_exec*

Executes the given command on an open sqlite database (cf. `b_sqlite3_open`).

[command]: The command to execute. All commands supported by `sqlite3` in interactive mode incl. the SQL commands are supported. The only exception is the `.output` command. Please use the bash output redirection instead of `.output`. **Warning:** Incomplete (e.g. missing `;`) or incorrect commands may cause this function to make your bash script hang forever, if no [timeout] is specified.

[timeout]: Maximum time in seconds to wait for the command to execute on the database (default: the timeout initialized via `b_sqlite3_open`).

[filter input]: Whether or not to filter command input lines from the returned output (default: 0 = true).

**returns:** The output provided by the database in response to the executed

command incl. potential errors. The function attempts to set a non-zero exit code, if the output contains error messages. B\_E is only called on timeouts or other database connectivity issues.

@B\_E

**b\_sqlite3\_close** *sqlite3/b\_sqlite3\_close*

Closes a currently open database connection.

It is highly recommended to execute this function once you don't need the database connection anymore (usually at the end of a script).

**returns:** Nothing. A non-zero exit code indicates a failed close operation.

@StateChanging

## str

Collection of string related functions.

Copyright (C) 2021 David Hobach LGPLv3

0.2

## Dependencies

no dependencies

## Imports

no imports

## Functions

**b\_str\_stripQuotes** [string] *str/b\_str\_stripQuotes*

Remove any single or double quotes around the given string.

[string]: string which might be enclosed in single or double quotes ( ' or “ )

**returns:** [string] without the enclosed single or double quotes, if there were any; if none were found the original string is returned; the exit code is always zero

**b\_str\_trim** [string] *str/b\_str\_trim*

Remove any whitespace from around a string.

[string]: string to trim

**returns:** [string] beginning and ending without whitespace; the exit code is always zero

**b\_str\_prefixLines** [string] [prefix] *str/b\_str\_prefixLines*

Prefix all lines of the given string with a given prefix.

[string]: Each line of this string will be prefixed.

[prefix]: The string to put in front of each line.

**returns:** All lines of the input string, each of them prefixed with the given prefix.

## tcolors

Defines some tput related constants. In order to change terminal colors you can then use something such as

```
echo "$(tput setaf ${B_TCOLORS[red]})This is red, \  
$(tput setaf ${B_TCOLORS[blue]})this blue, $(tput sgr0)this normal."
```

tput can do a lot more than colors, see: man tput & man terminfo.

Copyright (C) 2018 David Hobach LGPLv3

0.1

### Dependencies

tput

### Imports

no imports

### Global Variables

**B\_TCOLORS** *tcolors/B\_TCOLORS*

Global map for human readable colors to tput style color identifiers.

Currently supported values: black|red|green|yellow|blue|magenta|cyan|white

## traps

Collection of trap related functions.

Copyright (C) 2018 David Hobach LGPLv3

0.2

### Dependencies

no dependencies

### Imports

no imports

### Functions

**b\_traps\_getCodeFor [signal]** *traps/b\_traps\_getCodeFor*

Retrieve the current trap code / commands for the given signal.

**returns:** The current code and sets a zero exit code on success.

@B\_E

**b\_traps\_add** [code] [signal] [tag] [append flag] *traps/b\_traps\_add*

Add the given commands to the given trap signal.

[code]: Whatever should be added to the trap.

[signal]: Name of the signal to add the commands to.

[tag]: An optional *unique* marker for these commands so that they can be removed with `b_traps_remove` later on.

[append flag]: Whether to append the new commands to the end (0: default) or insert them in the beginning (1).

**returns:** Whatever the internal call to *trap* to set the new trap returns.

@B\_E

**b\_traps\_prepend** [code] [signal] [tag] *traps/b\_traps\_prepend*

Prepend the given commands to the ones currently existing for the given trap signal.

Convenience wrapper to `b_traps_add` with [append flag] set to 1.

[code]: see `b_traps_add`

[signal]: see `b_traps_add`

[tag]: see `b_traps_add`

**returns:** see `b_traps_add`

@B\_E

**b\_traps\_remove** [signal] [tag] *traps/b\_traps\_remove*

Remove the commands tagged with the given tag from the signal trap.

[signal]: Name of the signal to remove the commands from.

[tag]: The *unique* marker to identify the commands to be removed.

**returns:** Nothing, but sets a zero exit code on success. May error out if the tag isn't found or the internal trap call failed.

@B\_E

## types

Functions for data type checks and conversions.

Copyright (C) 2022 David Hobach LGPLv3

0.6

## Dependencies

python3

## Imports

no imports

## Global Variables

### **B\_TYPES\_ENCODING** *types/B\_TYPES\_ENCODING*

String encoding parameter for `b_types_str` and `b_types_parseString`. Default: `ascii`

`ascii` makes sense in 99% of all cases as scripts should use ASCII only anyway (when no user-interaction is involved) in order to remain portable. Keep in mind that bash also needs to support the target encoding in order to support further processing. Currently available encodings: <https://docs.python.org/3.7/library/codecs.html#standard-encodings>

### **B\_TYPES\_MAX\_BYTES** *types/B\_TYPES\_MAX\_BYTES*

Parameter for `b_types_str` and `b_types_parseString` to specify the maximum number of bytes to read per line (default: -1/infinite). Ignore additional bytes. Useful to avoid memory DoS for untrusted input.

### **B\_TYPES\_CHECK\_NON\_BINARY** *types/B\_TYPES\_CHECK\_NON\_BINARY*

Whether or not `b_types_int` should also ensure that the command output is non-binary (default: 0/true).

## Functions

### **b\_types\_parseString** [encoding] [max bytes] *types/b\_types\_parseString*

Checks whether whatever is lying in stdin is a string (and not binary) and if so, prints it to stdout.

#### Important:

- bash has major issues whenever binary data is involved. For example equality checks may return undefined results. So whenever you are unsure as to whether a variable is a string or not, better pass it through this function.
- The input is taken from *stdin* rather than as parameter as binary parameters may also cause issues (special bytes etc.).
- Even builtins such as `echo` do not necessarily play well with binary data. So it is recommended to pipe binary data through this function before further processing.

Examples:

```
#check a file
```

```
b_types_parseString < "/path/to/potential/binary" > /dev/null && echo "It is a string file."
```

```
#read parts of a file as string
```

```
str="$(dd if="/path/to/another/file" bs=1 skip=8 | b_types_parseString)"  
[ $? -eq 0 ] && echo "Found the following string: $str"
```

[encoding]: The encoding of the string lying in stdin. Default: `B_TYPES_ENCODING/ascii`

[max bytes]: Maximum number of bytes to read per line. Additional bytes are

ignored. Default: B\_TYPES\_MAX\_BYTES/-1/infinite

**returns:** The data as String, if the input data was found to be a String. If no String was found to be lying in stdin, the output is an undefined string and a non-zero exit code is set. B\_E is only called on exceptional errors.

@B\_E

**b\_types\_str** [cmd] [cmd arg 1] ... [cmd arg n] *types/b\_types\_str*

Execute the given command and ensure that its output / stdout is a string.

Use B\_TYPES\_ENCODING to specify the encoding (default: ascii) and B\_TYPES\_MAX\_BYTES (default: -1/infinite) to specify the maximum number of bytes to read.

[cmd]: Command to execute. Stdout is checked to be a string, stderr is passed through.

[cmd arg i]: Arguments to pass to [cmd].

**returns:** Stdout of [cmd], if it is a string and an undefined string otherwise. The exit code is that of the executed command. B\_E is called if the output is *not* a string.

@B\_E

**b\_types\_parseInteger** *types/b\_types\_parseInteger*

Checks whether whatever is lying in stdin is an Integer and if so, prints it to stdout.

B\_TYPES\_CHECK\_NON\_BINARY can be used to enable/disable additional non-binary checking (default: 0/enabled).

**returns:** The data as Integer, if the input data was found to be an Integer. If no Integer was found to be lying in stdin, the output is an undefined string and a non-zero exit code is set. B\_E is only called on exceptional errors.

@B\_E

**b\_types\_isInteger** [string] *types/b\_types\_isInteger*

Check whether the given String is an integer (positive or negative) or not.

B\_TYPES\_CHECK\_NON\_BINARY can be used to enable/disable additional non-binary checking (default: 0/enabled).

[string]: The string to check.

**returns:** Nothing, but sets a zero exit code if and only if the given string represents an integer.

**b\_types\_assertInteger** [string] [error msg] *types/b\_types\_assertInteger*

Check whether the given String is an integer (positive or negative) and if not, error out.

B\_TYPES\_CHECK\_NON\_BINARY can be used to enable/disable additional non-binary checking (default: 0/enabled).

[string]: The string to check.

[error msg]: Error message to use, if the check fails (optional).



**returns:** Nothing. If it's no integer, B\_E is called.

@B\_E

**b\_types\_int** [cmd] [cmd arg 1] ... [cmd arg n] *types/b\_types\_int*

Execute the given command and ensure that its output / stdout is an integer (positive or negative).

B\_TYPES\_CHECK\_NON\_BINARY can be used to enable/disable additional non-binary checking (default: 0/enabled).

[cmd]: Command to execute. Stdout is checked to be an integer, stderr is passed through.

[cmd arg i]: Arguments to pass to [cmd].

**returns:** Stdout of [cmd], if it is an integer and an undefined string otherwise. The exit code is that of the executed command. B\_E is called if the output is *not* an integer.

@B\_E

**b\_types\_looksLikeArray** [string] *types/b\_types\_looksLikeArray*

Check whether the given String “looks like” a bash array or not.

It may still contain malicious code or whatnot. So you **must not** rely on this function when processing untrusted input.

[string]: The string to check. Use “\$(declare -p var)” on variables to obtain it.

**returns:** Nothing, but sets a zero exit code if the given string looks like it could be eval’ed to a bash array. References (declare -n) will result in a non-zero exit code.

**b\_types\_assertLooksLikeArray** [string] [error msg] *types/b\_types\_assertLooksLikeArray*

Check whether the given String “looks like” a bash array and if not, error out.

It may still contain malicious code or whatnot. So you **must not** rely on this function when processing untrusted input.

[string]: The string to check. Use “\$(declare -p var)” on variables to obtain it.

[error msg]: Error message to use, if the check fails (optional).

**returns:** Nothing. If doesn’t look like a bash array, B\_E is called.

@B\_E

**b\_types\_looksLikeMap** [string] *types/b\_types\_looksLikeMap*

Check whether the given String “looks like” a bash map / associative array or not.

It may still contain malicious code or whatnot. So you **must not** rely on this function when processing untrusted input.

[string]: The string to check. Use “\$(declare -p var)” on variables to obtain it.

**returns:** Nothing, but sets a zero exit code if the given string looks like it could

be `eval`'ed to a bash associative array. References (`declare -n`) will result in a non-zero exit code.

**b\_\_types\_\_assertLooksLikeMap** [string] [error msg] *types/b\_\_types\_\_assertLooksLikeMap*  
Check whether the given String “looks like” a bash map / associative array and if not, error out.

It may still contain malicious code or whatnot. So you **must not** rely on this function when processing untrusted input.

[string]: The string to check. Use "`$(declare -p var)`" on variables to obtain it.

[error msg]: Error message to use, if the check fails (optional).

**returns:** Nothing. If doesn't look like a bash array, `B_E` is called.

@*B\_E*

## ui

Collection of user interface and user interaction related functions.

Copyright (C) 2020 David Hobach LGPLv3

0.2

## Dependencies

no dependencies

## Imports

no imports

## Functions

**b\_ui\_passwordPrompt** [output var] [ui mode] [prompt string]  
*ui/b\_ui\_passwordPrompt*

Prompt the user for a password. Should run inside the parent process (i.e. not inside a subshell).

Once you do not need the password anymore, it is recommended to wipe it from memory as such:

```
#overwrite the password in memory with zeroes, then free it  
pass="${pass//?/0}" ; pass=""
```

[output var]: The name of the variable to write the password to.

[ui mode]: How to request the password from the user: `auto|gui|tty` (default: `auto`).

[prompt string]: The string to present to the user asking for the password (default: “Password:”).

**returns:** Nothing. Sets a non-zero exit code on errors.

@*B\_E*

## **wm**

Collection of functions related to window managers.

Copyright (C) 2020 David Hobach LGPLv3  
0.1

### **Dependencies**

wmctrl

### **Imports**

no imports

### **Functions**

**b\_wm\_getActiveWindowProperties** [variable name] *wm/b\_wm\_getActiveWindowProperties*

Retrieve information about the currently active windows.

[variable name]: Name of the associative array to use as output.

**returns:** A string specifying an associative array in bash syntax. You can eval that string to obtain all relevant data. On errors B\_E is called.

The information is returned as an associative array containing the following data:

[window ID]\_\_[id] = hexadecimal window ID

[window ID]\_\_[desktop] = desktop number

[window ID]\_\_[pid] = PID of the window

[window ID]\_\_[x] = x-offset

[window ID]\_\_[y] = y-offset

[window ID]\_\_[width] = window width

[window ID]\_\_[height] = window height

[window ID]\_\_[class] = window class name

[window ID]\_\_[client] = client machine name

[window ID]\_\_[title] = window title

Missing data may result in an empty String for the respective property.

@B\_E

### **tests/test\_\_common.bash**

Some code and vars meant to be shared across bats tests.

Copyright (C) 2018 David Hobach LGPLv3  
0.5

### **Dependencies**

no dependencies

## Imports

no imports

## Global Variables

**TEST\_STATE** *tests/test\_common.bash/TEST\_STATE*

A map which can be used to create a persistent state across multiple tests.

By default, bats creates a new shell environment for each test it runs, resetting all changes to global variables.

The state can be managed with the load/save/clearBlibTestState functions below.

## Functions

**loadBlib** *tests/test\_common.bash/loadBlib*

Loads blib for testing.

**returns:** Nothing

**skipIfNoUserData** *tests/test\_common.bash/skipIfNoUserData*

Skip the test if no user data was found.

**returns:** Nothing.

**skipIfCommandMissing** [command] *tests/test\_common.bash/skipIfCommandMissing*

Skip the test if the given command is not installed.

**returns:** Nothing.

**skipIfNotQubesDom0** *tests/test\_common.bash/skipIfNotQubesDom0*

Skip the test if we're not running inside Qubes OS dom0.

**returns:** Nothing.

**skipIfNotRoot** *tests/test\_common.bash/skipIfNotRoot*

Skip the test if root is not available.

**returns:** Nothing.

**skipIfCI** [ci] *tests/test\_common.bash/skipIfCI*

Skip the test, if it's run inside the given CI pipeline.

[ci]: Disallowed CI pipeline. Leave it empty to match any CI pipeline.

**returns:** Nothing.

**loadBlibTestState** *tests/test\_common.bash/loadBlibTestState*

Load the TEST\_STATE with the data that was saved last via saveBlibState. If you want to use TEST\_STATE, call this function during test setup.

**returns:** Nothing.

**saveBlibTestState** *tests/test\_common.bash/saveBlibTestState*

Save the current TEST\_STATE to make it available for further tests.

**returns:** Nothing.

**clearBlibTestState** *tests/test\_common.bash/clearBlibTestState*

Clears the current test state and removes its persistent files.

**returns:** Nothing.

**testGetterSetter** [setter function] [value to set] [reset] *tests/test\_common.bash/testGetterSetter*

Executes the given setter function *in the current environment* and makes sure the respective getter function (assumed to have the same name with just a *get* instead of *set*) returns that value.

[setter function]: name of the setter function to call

[value to set]: value to set with the setter function

[reset]: if set to 0 (default), reset the value back to its original value after testing the setter function

**returns:** nothing, but errors out on test failures

**startTimer** *tests/test\_common.bash/startTimer*

Start a new time measurement window.

**returns:** nothing

**endTimer** *tests/test\_common.bash/endTimer*

Get the difference in time in seconds since the last time startTimer was called.

**returns:** time difference in seconds

**funcTimeout** [timeout] [function] args *tests/test\_common.bash/funcTimeout*

Run the given function with a timeout inside a subshell.

[timeout]: Timeout in seconds after which to terminate the function.

[function]: The function to execute.

[args]: Function arguments.

**returns:** An exit code of 124, if the function timed out. Otherwise returns whatever the function returned.

**runSL** [commands] *tests/test\_common.bash/runSL*

A version of the bats **run** command which makes sure that the bash runtime state does not change after running the given commands (SL = stateless).

This *should* be the default method of executing tests for blib.

If the given commands are expected to change the state, use runSC instead. In particular the default bats **run** should almost never be used.

Also prints an identifier for easier debugging. The identifier starts at 1 on the first run call per test and increases with each further run call.

**WARNING:** As the bats **run** it runs inside a subshell. So don't expect changes to persist.

[commands]: The commands to run.

**returns:** whatever bats run returns

**runSC** [commands] *tests/test\_common.bash/runSC*

A version of the bats **run** command which ignore changes to the bash runtime state (SC = state changing).

If the given commands are expected to be stateless, use runSL instead. In particular the default bats **run** should almost never be used.

Also prints an identifier for easier debugging. The identifier starts at 1 on the first run call per test and increases with each further run call.

**WARNING:** As the bats **run** it runs inside a subshell. So don't expect changes to persist.

[commands]: The commands to run.

**returns:** whatever bats run returns

**assertReadOnly** [path] *tests/test\_common.bash/assertReadOnly*

Assert that the given file or directory is read-only by attempting to write to it.

[path]: Full path to a file or directory. If it is not r/o, it may be changed.

**returns:** A zero exit code, if the path is r/o.

@B\_E

## tests/user\_test\_data.bash

Example of a user\_test\_data file.

That file is meant for static bash variables that must be set *by the user* (as they may e.g. be OS specific) in order for some tests to work.

If that file doesn't exist or could not be loaded, these tests may be skipped by blib.

Copyright (C) 2018 David Hobach LGPLv3

0.5

## Dependencies

no dependencies

## Imports

no imports

## Global Variables

**UTD\_ONLINE** *tests/user\_test\_data.bash/UTD\_ONLINE*

Whether or not the test machine is connected to the Internet.

**UTD\_OS** *tests/user\_test\_data.bash/UTD\_OS*

Specify your operating system here, currently supported values:  
debian|fedora|red hat|centos|ubuntu|opensuse|qubes dom0|other  
Qubes VMs should be specified with their OS.

**UTD\_QUBES** *tests/user\_test\_data.bash/UTD\_QUBES*

Specify whether you are running Qubes OS and in what environment here,  
possible values:  
no|vm|dom0

**UTD\_CI** *tests/user\_test\_data.bash/UTD\_CI*

Specify whether you are running from a CI pipeline and from what pipeline,  
possible values:  
no|github  
May enable or disable pipeline-specific quirks.

**UTD\_QUBES\_TESTVM** *tests/user\_test\_data.bash/UTD\_QUBES\_TESTVM*

If you're using Qubes OS, please specify a *disposable* virtual machine with a static name to be used for testing here. This test VM may crash, be destroyed or whatever - so please don't use a production VM!  
Apart from that, the tests will be conducted with disposable VMs with dynamic names using your default template.

Example command to create such a test VM:

```
qvm-create --class DispVM --prop netvm='' --template nonet-dvm -l red d-testing
```

Can safely be ignored if you don't run Qubes OS-related tests.

**UTD\_QUBES\_TESTVM\_PERSISTENT** *tests/user\_test\_data.bash/UTD\_QUBES\_TESTVM\_PERS*

If you're using Qubes OS, please specify a *persistent/non-disposable* virtual machine with a static name to be used for testing here. This test VM may crash, be destroyed or whatever - so please don't use a production VM!

Example command to create such a test VM:

```
qvm-create -l red --prop netvm='' testing-pers
```

Can safely be ignored if you don't run Qubes OS-related tests.

**UTD\_QUBES\_DISPVM\_TEMPLATE** *tests/user\_test\_data.bash/UTD\_QUBES\_DISPVM\_TEMPLA*

Qubes OS disposable VM template to use for testing. The test code will create disposable VMs from that template. It will *not* modify the template itself.  
If no template is specified, the Qubes OS default template is used.

**UTD\_PW\_FREE\_USER** *tests/user\_test\_data.bash/UTD\_PW\_FREE\_USER*

A user that allows password-less logons with sudo or su for testing.

If you run bats as root, neither sudo nor su should ask for a password.  
Tests requiring admin privileges (e.g. mounting devices) may require this to be root or skip otherwise.

## Reference List

assertReadOnly  
B\_ARGS  
b\_args\_assertOptions  
b\_args\_get  
b\_args\_getAll  
b\_args\_getAllOptions  
b\_args\_getCount  
b\_args\_getInt  
b\_args\_getOption  
b\_args\_getOptionCount  
b\_args\_getOptionInt  
b\_args\_getOptionParamSeparator  
b\_args\_init  
B\_ARGS\_OPTS  
b\_args\_parse  
b\_args\_setOptionParamSeparator  
b\_arr\_contains  
b\_arr\_join  
b\_arr\_mapsAreEqual  
b\_arr\_toList  
b\_assertLastPipes  
b\_cachingMessageHandler  
B\_CALLER\_NAME  
b\_cdoc\_cbPrintFirstParam  
b\_cdoc\_cbPrintNewline  
b\_cdoc\_generate  
b\_cdoc\_generateBlibStyle



b\_cdoc\_getBlockCallback  
b\_cdoc\_getDocumentBeginCallback  
b\_cdoc\_getDocumentEndCallback  
b\_cdoc\_getExtractionRegex  
b\_cdoc\_getFileCallback  
b\_cdoc\_getPostProcessingCallback  
b\_cdoc\_setBlockCallback  
b\_cdoc\_setDocumentBeginCallback  
b\_cdoc\_setDocumentEndCallback  
b\_cdoc\_setExtractionRegex  
b\_cdoc\_setFileCallback  
b\_cdoc\_setPostProcessingCallback  
b\_checkVersion  
B\_CONF\_DIR  
b\_daemon\_getPid  
B\_DAEMON\_ID  
b\_daemon\_init  
b\_daemon\_restart  
b\_daemon\_sendSignal  
b\_daemon\_start  
b\_daemon\_status  
b\_daemon\_statusPid  
b\_daemon\_stop  
b\_date\_add  
b\_date\_addDays  
b\_date\_diff  
b\_date\_getFileModAge  
b\_defaultErrorHandler  
b\_defaultMessageHandler  
b\_delay\_execute  
B\_DELAY\_EXECUTED

b\_delay\_getCommandAt  
b\_delay\_to  
b\_deps  
b\_dmccrypt\_close  
b\_dmccrypt\_createLuks  
b\_dmccrypt\_getMapperName  
b\_dmccrypt\_init  
b\_dmccrypt\_isOpen  
b\_dmccrypt\_open  
b\_dom0\_applyFirewall  
b\_dom0\_attachDevice  
b\_dom0\_attachFile  
b\_dom0\_attachVMDisk  
b\_dom0\_clearFirewall  
b\_dom0\_closeCrypt  
b\_dom0\_copy  
b\_dom0\_createLoopDeviceIfNecessary  
b\_dom0\_crossAttachDevice  
b\_dom0\_crossAttachFile  
b\_dom0\_crossCopy  
b\_dom0\_detachDevice  
b\_dom0\_disconnectEventLoop  
b\_dom0\_ensureHalted  
b\_dom0\_ensureRunning  
b\_dom0\_enterEventLoop  
b\_dom0\_execFuncIn  
b\_dom0\_execIn  
b\_dom0\_execStrIn  
b\_dom0\_exists  
b\_dom0\_getDefaultPoolDriver  
b\_dom0\_getDispVMs

b\_dom0\_getPoolDriver  
b\_dom0\_getQvmBlockInfo  
b\_dom0\_getVMDeps  
b\_dom0\_isHalted  
b\_dom0\_isMountedIn  
b\_dom0\_isRunning  
b\_dom0\_mountIfNecessary  
b\_dom0\_openCrypt  
b\_dom0\_parseQvmBlock  
b\_dom0\_qvmRun  
B\_DOM0\_QVM\_RUN\_PARAMS  
b\_dom0\_removeUnusedLoopDevice  
b\_dom0\_setVMDeps  
b\_dom0\_startDispVM  
b\_dom0\_testMultiple  
B\_DOM0\_VM\_STDERR  
b\_dom0\_waitForFileIn  
B\_E  
b\_enforceUser  
B\_ERR  
b\_error  
b\_execFuncAs  
b\_execFuncInCurrentContext  
b\_fd\_closeAll  
b\_fd\_closeNonStandard  
b\_fd\_getOpen  
b\_flog\_close  
b\_flog\_defaultHeader  
b\_flog\_getDateFormat  
b\_flog\_getHeaderFunction  
b\_flog\_getLogReductionLinesLowerBound

b\_flog\_getLogReductionLinesUpperBound  
b\_flog\_headerDateScriptSeverity  
b\_flog\_headerDateSeverity  
b\_flog\_init  
b\_flog\_log  
b\_flog\_messageHandler  
b\_flog\_printSeverity  
b\_flog\_setDateFormat  
b\_flog\_setHeaderFunction  
b\_flog\_setLogReductionLinesApprox  
b\_flog\_setLogReductionLinesLowerBound  
b\_flog\_setLogReductionLinesUpperBound  
B\_FLOG\_SEV  
b\_fs\_createLoopDeviceIfNecessary  
b\_fs\_enumerate  
b\_fs\_getBlockDevice  
b\_fs\_getLineCount  
b\_fs\_getMountpoints  
b\_fs\_isEmptyDir  
b\_fs\_isRotatingDrive  
b\_fs\_mountIfNecessary  
b\_fs\_parseSize  
b\_fs\_removeRelativelySafely  
b\_fs\_removeUnusedLoopDevice  
b\_fs\_removeWithOverwrite  
b\_fs\_waitForFile  
b\_generateStandalone  
b\_getBlibModules  
b\_getDefaultMessageHandlerIntermediate  
b\_getDefaultMessageHandlerPrefix  
b\_getErrorHandler

b\_getMessageHandler  
b\_hash\_file  
b\_hash\_str  
B\_HTTP\_CHECKURLS  
b\_http\_getOnlineStatus  
b\_http\_rawUrlDecode  
b\_http\_rawUrlEncode  
b\_http\_testProxy  
B\_I18N\_COUNTRY2TIMEZONE  
b\_i18n\_getSystemTimezone  
b\_i18n\_setRandomSystemTimezone  
b\_import  
b\_info  
b\_ini\_assertNames  
b\_ini\_get  
b\_ini\_getBool  
b\_ini\_getInt  
b\_ini\_getString  
b\_ini\_read  
b\_initCachingMessageHandler  
b\_ipcm\_change  
b\_ipcm\_get  
b\_ipcm\_getNamespace  
b\_ipcm\_setNamespace  
b\_ipcm\_unsetNamespace  
b\_ipcv\_load  
b\_ipcv\_loadNamespace  
b\_ipcv\_save  
b\_ipcv\_unset  
b\_ipcv\_unsetNamespace  
b\_isFunction

b\_isModule  
b\_keys\_add  
b\_keys\_close  
b\_keys\_delete  
b\_keys\_get  
b\_keys\_getAll  
b\_keys\_getContent  
b\_keys\_getDefaultStore  
b\_keys\_init  
B\_LIB\_DIR  
B\_LINE  
b\_listContains  
b\_meta\_getClearDeps  
b\_meta\_getClearImports  
b\_mtx\_create  
b\_mtx\_forceRelease  
b\_mtx\_getSleepTime  
b\_mtx\_pass  
b\_mtx\_release  
b\_mtx\_setSleepTime  
b\_mtx\_try  
b\_mtx\_waitFor  
b\_multiw\_getMaxHangTime  
b\_multiw\_remove  
b\_multiw\_setMaxHangTime  
b\_multiw\_write  
B\_NET\_CHECKHOSTS  
B\_NET\_DNSSERVERS  
b\_net\_getDNSStatus  
b\_nop  
b\_notify\_send

b\_notify\_sendNoError  
b\_notify\_waitForUserDbus  
b\_osid\_init  
b\_osid\_isCentOS  
b\_osid\_isDebian  
b\_osid\_isDebianLike  
b\_osid\_isFedora  
b\_osid\_isFedoraLike  
b\_osid\_isOpenSuse  
b\_osid\_isQubesDom0  
b\_osid\_isQubesVM  
b\_osid\_isRedHat  
b\_osid\_isUbuntu  
b\_printStackTrace  
b\_proc\_childExists  
b\_proc\_killAndWait  
b\_proc\_killByRegexAndWait  
b\_proc\_pidExists  
b\_proc\_resolveSignal  
b\_proc\_waitForPid  
B\_RC  
b\_readLine  
b\_resetErrorHandler  
B\_SCRIPT  
B\_SCRIPT\_DIR  
B\_SCRIPT\_NAME  
b\_setBE  
b\_setDefaultMessageHandlerIntermediate  
b\_setDefaultMessageHandlerPrefix  
b\_setErrorHandler  
b\_setMessageHandler

b\_silence  
b\_sqlite3\_close  
b\_sqlite3\_exec  
b\_sqlite3\_getOpen  
b\_sqlite3\_open  
b\_str\_prefixLines  
b\_str\_stripQuotes  
b\_str\_trim  
B\_TCOLORS  
B\_TEST\_MODE  
b\_traps\_add  
b\_traps\_getCodeFor  
b\_traps\_prepend  
b\_traps\_remove  
b\_types\_assertInteger  
b\_types\_assertLooksLikeArray  
b\_types\_assertLooksLikeMap  
B\_TYPES\_CHECK\_NON\_BINARY  
B\_TYPES\_ENCODING  
b\_types\_int  
b\_types\_isInteger  
b\_types\_looksLikeArray  
b\_types\_looksLikeMap  
B\_TYPES\_MAX\_BYTES  
b\_types\_parseInteger  
b\_types\_parseString  
b\_types\_str  
b\_ui\_passwordPrompt  
b\_version  
b\_wm\_getActiveWindowProperties  
clearBlibTestState



endTimer  
funcTimeout  
loadBlib  
loadBlibTestState  
runSC  
runSL  
saveBlibTestState  
skipIfCI  
skipIfCommandMissing  
skipIfNotQubesDom0  
skipIfNotRoot  
skipIfNoUserData  
startTimer  
testGetterSetter  
TEST\_STATE  
UTD\_CI  
UTD\_ONLINE  
UTD\_OS  
UTD\_PW\_FREE\_USER  
UTD\_QUBES  
UTD\_QUBES\_DISPVM\_TEMPLATE  
UTD\_QUBES\_TESTVM  
UTD\_QUBES\_TESTVM\_PERSISTENT