
TECHNICAL SERVICE MANAGEMENT

FTSE Distribution Interface

Implementation Guide – Java (Unix)

API v2.0.0

FTSE

Contents

Introduction	3
Runtime & Development Environment	4
Client Development.....	5
Downloading the API	6
Location of Installed Software.....	7
FDIConfiguration.xml	7
Failover.xml	8
Connecting to the FTSE Test Platform.....	9
Connection	9
Entitlement & Subscription	10
Replay.....	13
Documentation	14
Connections via HTTPS	15
Troubleshooting.....	16
Unable to run the Java compiler.	16
No connection	16
User Unknown.....	16
Tips & Hints	17
Service Resilience	17
Service Failover	18
Optimisation	18
TickCounts.....	19
Replay Handling	19

INTRODUCTION

This document forms an implementation guide for developers utilising the **FTSE Distribution Interface (FDI)**.

Developer tips and hints have been provided on core areas of the service and of specific data handling considerations.

It also provides details of how to compile and utilise the Java (Unix) sample applications which are components included in the FDI API.

This document should be read in conjunction with the following FTSE technical documentation

- FTSE Distribution Interface Overview
- FTSE Distribution Interface Conformance Testing

A Java (Windows) version of the API is also available for which the following documentation exists:

- FTSE Distribution Interface Implementation Guide – Java (Windows)


A Microsoft .NET version of the API is also available for which the following documentation exists:

- FTSE Distribution Interface Implementation Guide – . NET

RUNTIME & DEVELOPMENT ENVIRONMENT

Before progressing open a command line session and check the Java runtime environment and compiler on the computer ***[java -version]***.

The software API is designed to run Java at a minimum of v5.0, i.e. 1.5.0_xxx as reported.


A screenshot of a terminal window with a blue title bar. The title bar text is 'caplin@ukubs-q01-gds01:~'. The terminal content shows the command 'java -version' being executed, followed by the output: 'java version "1.5.0_05"', 'Java(TM) 2 Runtime Environment, Standard Edition (build 1.5.0_05-b05)', and 'Java HotSpot(TM) Server VM (build 1.5.0_05-b05, mixed mode)'. The prompt returns to 'caplin@ukubs-q01-gds01 ~]' with a green cursor.

```
caplin@ukubs-q01-gds01:~  
[caplin@ukubs-q01-gds01 ~]$ java -version  
java version "1.5.0_05"  
Java(TM) 2 Runtime Environment, Standard Edition (build 1.5.0_05-b05)  
Java HotSpot(TM) Server VM (build 1.5.0_05-b05, mixed mode)  
[caplin@ukubs-q01-gds01 ~]$
```

CLIENT DEVELOPMENT

If you want to develop applications then the Java compiler will need to be present.

This can be checked for by running the following from the command prompt [**javac -version**] as per example below.



```
caplin@ukubs-q01-gds01:/usr/java/jdk1.5.0_05/bin
[caplin@ukubs-q01-gds01 bin]$ javac -version
javac 1.5.0_05
javac: no source files
Usage: javac <options> <source files>
where possible options include:
  -g               Generate all debugging info
  -g:none          Generate no debugging info
  -g:{lines,vars,source}  Generate only some debugging info
  -nowarn          Generate no warnings
  -verbose         Output messages about what the compiler is doing
  -deprecation     Output source locations where deprecated APIs are used
  -classpath <path> Specify where to find user class files
  -cp <path>       Specify where to find user class files
  -sourcepath <path> Specify where to find input source files
  -bootclasspath <path> Override location of bootstrap class files
  -extdirs <dirs>   Override location of installed extensions
  -endorseddirs <dirs> Override location of endorsed standards path
  -d <directory>   Specify where to place generated class files
  -encoding <encoding> Specify character encoding used by source files
  -source <release> Provide source compatibility with specified release
  -target <release> Generate class files for specific VM version
  -version         Version information
  -help           Print a synopsis of standard options
  -X             Print a synopsis of nonstandard options
  -J<flag>        Pass <flag> directly to the runtime system

[caplin@ukubs-q01-gds01 bin]$
```

If required the JSDK can be downloaded from the following URL:


<http://www.oracle.com/technetwork/java/javase/downloads/index-jdk5-jsp-142662.html>

DOWNLOADING THE API

Please contact info@ftse.com for the latest edition of the API.

The API is distributed as a zip file.

In this example the FDI has been unpacked to directory **API2.0**



```
caplin@ukubs-q01-gds02:~/API2.0
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ ls -l
total 948
drwxr-xr-x 3 caplin 19527 4096 Jan 7 12:02 bin
-rwxrwxrwx 1 caplin 19527 91 Aug 14 09:22 buildSimple.bat
-rwxrwxrwx 1 caplin 19527 102 Aug 14 09:22 buildTerminal.bat
drwxr-xr-x 2 caplin 19527 4096 Jan 7 12:11 conf
drwxr-xr-x 3 caplin 19527 4096 Jan 7 12:02 doc
-rw-r--r-- 1 caplin 19527 763733 Aug 14 14:48 ftseDistribution.jar
-rw-r--r-- 1 caplin 19527 149474 Aug 14 14:48 licence.rtf
drwxr-xr-x 2 caplin 19527 4096 Jan 7 12:12 logs
-rw-r--r-- 1 caplin 19527 936 Aug 14 09:22 readme.txt
-rw-r--r-- 1 caplin 19527 9421 Aug 14 14:48 RELEASNOTE.txt
-rwxrwxrwx 1 caplin 19527 78 Aug 14 09:22 runSimple.bat
-rwxrwxrwx 1 caplin 19527 90 Jan 7 12:07 runTerminal.bat
drwxr-xr-x 3 caplin 19527 4096 Jan 7 12:03 src
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $
```

NOTE: It would be advisable to remove any previously installed API before commencing installing the latest version.

The key files in the FDI directory are:

<i>buildSimple.bat</i>	Batch file to build the Simple java application*
<i>buildTerminal.bat</i>	Batch file to build the Terminal java application*
<i>ftseDistribution.jar</i>	The FDI jar
<i>runSimple.bat</i>	Batch file to run the Simple application**
<i>runTerminal.bat</i>	Batch file to run the Terminal application**

*


NOTE: These files will need to have the path separator changed from DOS "\\" to Unix "/".

**

NOTE: These files will need to have the semi-colon ";" replaced with a colon ":" and execute permissions added

LOCATION OF INSTALLED SOFTWARE

The unpacked directory structure is as follows (excluding documentation):


A terminal window titled 'caplin@ukubs-q01-gds02:~/API2.0' showing the output of the command 'find . -type d | grep -v doc'. The output lists the following directories: ., ./logs, ./conf, ./src, ./src/com, ./src/com/ftse, ./src/com/ftse/distribution, ./src/com/ftse/distribution/examples, ./src/com/ftse/distribution/examples/simple, ./src/com/ftse/distribution/examples/terminal, ./bin, ./bin/com, ./bin/com/ftse, ./bin/com/ftse/distribution, ./bin/com/ftse/distribution/examples, ./bin/com/ftse/distribution/examples/simple, and ./bin/com/ftse/distribution/examples/terminal. The prompt 'DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 \$' is visible at the bottom.

```
caplin@ukubs-q01-gds02:~/API2.0 $ find . -type d | grep -v doc
.
./logs
./conf
./src
./src/com
./src/com/ftse
./src/com/ftse/distribution
./src/com/ftse/distribution/examples
./src/com/ftse/distribution/examples/simple
./src/com/ftse/distribution/examples/terminal
./bin
./bin/com
./bin/com/ftse
./bin/com/ftse/distribution
./bin/com/ftse/distribution/examples
./bin/com/ftse/distribution/examples/simple
./bin/com/ftse/distribution/examples/terminal
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $
```

The **conf** folder contains two xml configuration files.

FDICONFIGURATION.XML

This configuration file helps to define the behaviour of the logging and by default it looks like this:

A screenshot of a Windows Internet Explorer browser window displaying the file 'P:\Service_Management\Technical Services Management\FDI\FDI Releases\JAVA\Fdi-java-kit-2.0.0-29\conf\FDIConfiguration.xml'. The XML content is as follows:

```
<FDIConfiguration>
  <LogSettings>
    <FDILogging logfilepath="logs/fdi.log" loglevel="FINE" logtype="FILE" maxfiles="5" maxfilesize="5" />
    <StreamlinkLogging logfilepath="logs/streamlink.log" logtype="FILE" maxfiles="5" maxfilesize="5" />
  </LogSettings>
  <ReplaySettings timeout="60" />
  <NoopSettings interval="60" />
</FDIConfiguration>
```

The browser interface includes a menu bar (File, Edit, View, Favorites, Tools, Help), a search bar, and a status bar at the bottom showing 'Done' and 'Local intranet'.

By sticking to the default path and filenames logs are generated in the **logs** directory relative location to where the API resides.

fdi.log and **streamlink.log** size and version limits are controlled by altering some of the parameters, for example:


```
1 <FDIConfiguration>
2   <LogSettings>
3     <FDILogging logfilepath="logs/fdi.log" logtype="FILE" maxfiles="10" maxfilesize="25"/>
4     <StreamlinkLogging logfilepath="logs/streamlink.log" logtype="FILE" maxfiles="10" maxfilesize="25"/>
5   </LogSettings>
6
7   <NoopSettings interval="60" timeout="60" />
8   <ReplaySettings timeout="60" />
9 </FDIConfiguration>
```

The above would limit each of the log files to a maximum size of 25Mb before a new log file is created up to a maximum of 10 log files, at which point the initial log will be overwritten.

FAILOVER.XML

This configuration file is optional, but is needed if the "FTSE API failover" functionality is required.

This file resides in the same location as the **FDIConfiguration.xml** file.



In the above example, the address could be an IP address or a FQD name.


NOTE: For external client access to FTSE Production/DR platforms only https on port 443 is used.

CONNECTING TO THE FTSE TEST PLATFORM

CONNECTION

To connect to the Test Platform using the standard API tool execute the sample Terminal application via the runTerminal batch file.

NOTE: In the original file the semi colon ";" was replaced with a colon ":"

A screenshot of a terminal window. The title bar reads 'caplin@ukubs-q01-gds02:~/API2.0'. The terminal content shows the command 'DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 \$./runTerminal.bat' being executed. Below this, a message says 'Enter a command, followed by [Enter]. Use 'HELP' command for help'. A green cursor is visible on the line following the message.

```
caplin@ukubs-q01-gds02:~/API2.0
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ ./runTerminal.bat
Enter a command, followed by [Enter]. Use 'HELP' command for help

```

From the command line two methods exist to connect to the service.

The first and standard method is via a simple login request, syntax as follows:

login <hostname> <port number> <login name> <password>


The second method is invoked via the built in API failover, syntax as follows:

loginfailover <username> <password> <configURL>

In the following example the standard login method is used.

NOTE: For an external connection the following command should be input before login:

setprotocol https

A terminal window titled 'caplin@ukubs-q01-gds02:~/API2.0'. The prompt is 'DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 \$'. The user has entered './runTerminal.bat'. The terminal displays the following output: 'Enter a command, followed by [Enter]. Use 'HELP' command for help', 'login ukubs-q01-gds02 8080 gdsrt1 gdsrt1', 'SimpleConnectionListener: Connection Information: Connecting', 'SimpleConnectionListener: Connection Information: Connected', 'SimpleConnectionListener: Connection Information: Retrieving Credentials', 'SimpleConnectionListener: Connection Information: Credentials Retrieved', and 'SimpleConnectionListener: Connection OK: LoggedIn'. A green cursor is visible on the line following the 'LoggedIn' message.

```
caplin@ukubs-q01-gds02:~/API2.0
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ ./runTerminal.bat
Enter a command, followed by [Enter]. Use 'HELP' command for help


login ukubs-q01-gds02 8080 gdsrt1 gdsrt1
SimpleConnectionListener: Connection Information: Connecting
SimpleConnectionListener: Connection Information: Connected
SimpleConnectionListener: Connection Information: Retrieving Credentials
SimpleConnectionListener: Connection Information: Credentials Retrieved
SimpleConnectionListener: Connection OK: LoggedIn
█
```

NOTE: FTSE support will provide individual clients with suitable login parameters on request.

Successful connectivity is achieved when the "***LoggedIn***" message is observed.

ENTITLEMENT & SUBSCRIPTION

To confirm entitlement run the ***listproductgroups*** command from within the Terminal example.

A terminal window titled 'caplin@ukubs-q01-gds02:~/API2.0'. The prompt is 'DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 \$'. The user has entered './runTerminal.bat'. The terminal displays the same login sequence as the previous image, followed by 'LISTPRODUCTGROUPS' and 'SimpleSubscriptionListener: Permissioned product groups: Product Group Names=[PDG101, PDG26, PDG5]'. A green cursor is visible on the line following the product group names.

```
caplin@ukubs-q01-gds02:~/API2.0
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ ./runTerminal.bat
Enter a command, followed by [Enter]. Use 'HELP' command for help


login ukubs-q01-gds02 8080 gdsrt1 gdsrt1
SimpleConnectionListener: Connection Information: Connecting
SimpleConnectionListener: Connection Information: Connected
SimpleConnectionListener: Connection Information: Retrieving Credentials
SimpleConnectionListener: Connection Information: Credentials Retrieved
SimpleConnectionListener: Connection OK: LoggedIn
LISTPRODUCTGROUPS
SimpleSubscriptionListener: Permissioned product groups: Product Group Names=[PDG101, PDG26, PDG5]
█
```

FTSE provide permission at the Product Data Group (PDG) level, therefore by definition if permission is granted to the PDG all indices contained therein are granted.

Subscriptions can be achieved at an individual index level or at the PDG level. At a PDG level all updates for all indices contained therein will be provided, at the individual index subscription only updates for that index will be provided.

For an individual index the syntax is: ***SUBSCRIBE <PDG> INDEX***

e.g. ***SUBSCRIBE PDG101 UKX*** (as in the example below)




```
caplin@ukubs-q01-gds01:~/API
[caplin@ukubs-q01-gds01 API]$ ./runTerminal.bat
Enter a command, followed by [Enter]. Use 'HELP' command for help

login ukubs-q01-gds01 8080 gdsrt1 gdsrt1
SimpleConnectionListener: Connection Information: Connecting
SimpleConnectionListener: Connection Information: Connected
SimpleConnectionListener: Connection OK: LoggedIn
SUBSCRIBE PDG101 UKX
Index update for PDG101/UKX:Tick=2881, Replay=false, Fields=[IndexCode=UKX,
TickCount=2881, TimeStamp=080448, PrevCloseDate=20110629, Currency=GBP, Date
=20110630, Status=N, Change=18.83, TotalReturnValue=3631.17, PrevClose=5569.
27, TRICChange=12.23, LastValue=5588.10]
Index update for PDG101/UKX:Tick=2882, Replay=false, Fields=[TimeStamp=08045
0, TickCount=2882, LastValue=5585.87, TRICChange=10.78, Change=16.60, TotalRe
turnValue=3629.72]
```

NOTE : Example screenshot from prior API version

Subscribing to a PDG is simpler, the syntax is : ***SUBSCRIBE PDG***

e.g. ***SUBSCRIBE PDG26***



```
caplin@ukubs-q01-gds01:~/API
[caplin@ukubs-q01-gds01 API]$ ./runTerminal.bat
Enter a command, followed by [Enter]. Use 'HELP' command for help

login ukubs-q01-gds01 8080 gdsrt1 gdsrt1
SimpleConnectionListener: Connection Information: Connecting
SimpleConnectionListener: Connection Information: Connected
SimpleConnectionListener: Connection OK: LoggedIn
SUBSCRIBE PDG26
Index update for PDG26/FSTHM:Tick=313, Replay=false, Fields=[SourceInterval=
60, IndexCode=FSTHM, TickCount=313, TimeStamp=080700, PrevCloseDate=20110629
, Currency=THB, Date=20110630, Status=N, Change=0.28, PrevClose=1258.35, Las
tValue=1258.63]
Index update for PDG26/FSTSH:Tick=1249, Replay=false, Fields=[SourceInterval
=15, IndexCode=FSTSH, TickCount=1249, TimeStamp=080700, PrevCloseDate=201106
29, Currency=THB, Date=20110630, Status=N, Change=1.24, PrevClose=963.76, La
stValue=965.00]
Index update for PDG26/FSTHMS:Tick=313, Replay=false, Fields=[SourceInterval
=60, IndexCode=FSTHMS, TickCount=313, TimeStamp=080700, PrevCloseDate=201106
29, Currency=THB, Date=20110630, Status=N, Change=-2.26, PrevClose=1280.76,
LastValue=1278.50]
Index update for PDG26/FSTHL:Tick=1249, Replay=false, Fields=[SourceInterval
=15, IndexCode=FSTHL, TickCount=1249, TimeStamp=080700, PrevCloseDate=201106
29, Currency=THB, Date=20110630, Status=N, Change=0.66, PrevClose=1162.70, L
astValue=1163.36]
Index update for PDG26/FSTHS:Tick=313, Replay=false, Fields=[SourceInterval=
60, IndexCode=FSTHS, TickCount=313, TimeStamp=080700, PrevCloseDate=20110629
, Currency=THB, Date=20110630, Status=N, Change=3.21, PrevClose=1367.16, Las
tValue=1370.37]
Index update for PDG26/FSTHA:Tick=313, Replay=false, Fields=[SourceInterval=
60, IndexCode=FSTHA, TickCount=313, TimeStamp=080700, PrevCloseDate=20110629
, Currency=THB, Date=20110630, Status=N, Change=3.08, PrevClose=1186.39, Las
tValue=1189.47]
Index update for PDG26/FSTHF:Tick=313, Replay=false, Fields=[SourceInterval=
60, IndexCode=FSTHF, TickCount=313, TimeStamp=080700, PrevCloseDate=20110629
, Currency=THB, Date=20110630, Status=N, Change=4.55, PrevClose=1263.57, Las
tValue=1268.12]
```


NOTE : Example screenshot from prior API version

Log out from the session by typing ***logout*** at the prompt.

REPLAY

It is possible to request a replay of data for Pulse indices only. The replay request itself must be made at the index level and is qualified by the TickCount.

NOTE: Replays are only available in the current trade day and are not supported across day boundaries.



```
caplin@ukubs-q01-gds01:~/API
[caplin@ukubs-q01-gds01 API]$ ./runTerminal.bat
Enter a command, followed by [Enter]. Use 'HELP' command for help


login ukubs-q01-gds01 8080 gdsrt1 gdsrt1
SimpleConnectionListener: Connection Information: Connecting
SimpleConnectionListener: Connection Information: Connected
SimpleConnectionListener: Connection OK: LoggedIn
REPLAY PDG26 FSTHF 200 202
Index update for PDG26/FSTHF:Tick=200, Replay=true, Fields=[SourceInterval=60, IndexCode=F
STHF, TickCount=200, TimeStamp=061400, PrevCloseDate=20110629, Currency=THB, Date=20110630
, Status=N, Change=1.39, PrevClose=1263.57, LastValue=1264.96]
Index update for PDG26/FSTHF:Tick=201, Replay=true, Fields=[SourceInterval=60, IndexCode=F
STHF, TickCount=201, TimeStamp=061500, PrevCloseDate=20110629, Currency=THB, Date=20110630
, Status=N, Change=3.15, PrevClose=1263.57, LastValue=1266.72]
Index update for PDG26/FSTHF:Tick=202, Replay=true, Fields=[SourceInterval=60, IndexCode=F
STHF, TickCount=202, TimeStamp=061600, PrevCloseDate=20110629, Currency=THB, Date=20110630
, Status=N, Change=-3.60, PrevClose=1263.57, LastValue=1259.97]
```

NOTE : Example screenshot from prior API version

DOCUMENTATION

The documentation can be accessed via a Browser from the `/doc/javadoc` directory.

The starting point for navigation is ***index.html***



```
caplin@ukubs-q01-gds02:~/API2.0
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ ls -l doc/javadoc/
total 8
drwxr-xr-x 7 caplin 19527 4096 Jan  7 12:02 examples
drwxr-xr-x 8 caplin 19527 4096 Jan  7 12:03 FDI
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ ls -l doc/javadoc/FDI/
total 396
-rw-r--r-- 1 caplin 19527  6944 Aug 14 14:46 allclasses-frame.html
-rw-r--r-- 1 caplin 19527  6124 Aug 14 14:46 allclasses-noframe.html
drwxr-xr-x 4 caplin 19527  4096 Jan  7 12:02 com
-rw-r--r-- 1 caplin 19527  5677 Aug 14 14:46 constant-values.html
-rw-r--r-- 1 caplin 19527  4673 Aug 14 14:46 deprecated-list.html
drwxr-xr-x 2 caplin 19527  4096 Jan  7 12:03 doc-files
-rw-r--r-- 1 caplin 19527  9101 Aug 14 14:46 help-doc.html
-rw-r--r-- 1 caplin 19527 121718 Aug 14 14:46 index-all.html
-rw-r--r-- 1 caplin 19527  2757 Aug 14 14:46 index.html
-rw-r--r-- 1 caplin 19527 149474 Aug 14 14:48 licence.rtf
drwxr-xr-x 3 caplin 19527  4096 Jan  7 12:03 META-INF
drwxr-xr-x 5 caplin 19527  4096 Jan  7 12:03 org
-rw-r--r-- 1 caplin 19527  1051 Aug 14 14:46 overview-frame.html
-rw-r--r-- 1 caplin 19527  6398 Aug 14 14:46 overview-summary.html
-rw-r--r-- 1 caplin 19527 17332 Aug 14 14:46 overview-tree.html
-rw-r--r-- 1 caplin 19527    51 Aug 14 14:46 package-list
drwxr-xr-x 2 caplin 19527  4096 Jan  7 12:03 resources
-rw-r--r-- 1 caplin 19527  6074 Aug 14 14:46 serialized-form.html
drwxr-xr-x 3 caplin 19527  4096 Jan  7 12:03 src-html
-rw-r--r-- 1 caplin 19527 11139 Aug 14 14:46 stylesheet.css
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $
```

CONNECTIONS VIA HTTPS

The Production environment ONLY support HTTPS connections and clients are encouraged to configure their systems for HTTPS as soon as possible.

In order to run an encrypted secure socket connection the FTSE service needs to be set up as a known and certified application.

If required contact info@ftse.com for a copy of the certification file which will need to be added to the local certificates file on the computer where the API is installed.

TROUBLESHOOTING

UNABLE TO RUN THE JAVA COMPILER.

Check the install details for your selected development environment, in particular check that the PATH settings are correct for *javac*.


No CONNECTION

In the first instance it is advised to check the connectivity between your client and the FTSE server.

testgds.ftse.com is the name the Test system is known to the internet.


telnet is the advised connectivity check method which must be qualified by the GDS port. Externally this will typically be **443**.

Successful telnet example (internal connection hence port is not 443):



```
caplin@ukubs-q01-gds02:~/API2.0
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ telnet ukubs-q01-gds02 8080
Trying 172.20.133.11...
Connected to ukubs-q01-gds02.uk.ftse.com (172.20.133.11).
Escape character is '^]'.
█
```

Unsuccessful telnet example :



```
caplin@ukubs-q01-gds02:~/API2.0
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ telnet ukubs-q01-gds02 1080
Trying 172.20.133.11...
telnet: connect to address 172.20.133.11: Connection refused
telnet: Unable to connect to remote host: Connection refused
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ █
```


USER UNKNOWN

Confirm that the username and password are accurate; these will have been provided by FTSE previously.

TIPS & HINTS

SERVICE RESILIENCE

The recommended standard distribution architecture is outlined below. This offers unbroken service in the event of any single FTSE Distribution Server or single client API node losing connectivity.



It should be noted that there are no differences between either the service availability or content as delivered through either the Primary or Secondary Distribution Servers and both can be considered Production class nodes.

They are fed independently with the same content from the Live side of our Calculation Server.


SERVICE FAILOVER

Instead of connecting just to a single named service the API supports automatic failover to a second service which is recommended.

The connection alternatives are defined in an XML file which itself can be referenced in the configuration parameters of the login method. When used in this way the host and port parameters are defined by the XML file and override any passed explicitly to the login method.

Should a disconnection occur, for any reason, the API itself will handle the login and re-subscription* automatically when utilising this functionality.

* if an automatic reconnection is achieved subscriptions will be maintained however clients are advised to check for re-subscription success in the event that an immediate reconnection has not been possible which could jeopardise subscription objects on the platform.



```
caplin@ukubs-q01-gds02:~/API2.0
DEVELOPMENT (pdc) caplin@ukubs-q01-gds02:~/API2.0 $ ./runTerminal.bat
Enter a command, followed by [Enter]. Use 'HELP' command for help

LOGINFAILOVER gdsrt1 gdsrt1 file:/home/caplin/API2.0/conf/failover.xml
SimpleConnectionListener: Connection Information: Connecting
SimpleConnectionListener: Connection Information: Connected
SimpleConnectionListener: Connection Information: Retrieving Credentials
SimpleConnectionListener: Connection Information: Credentials Retrieved
SimpleConnectionListener: Connection OK: LoggedIn
```

OPTIMISATION

The IndexUpdate method only returns changed fields, i.e. fields which have not changed are optimised out of the distributed message.

For example at start-up the IndexEvent Method returns data for the following

SUBSCRIBE PDG101 UKX

Index update for PDG1/UKX:Tick=1730, Replay=false, Fields=[SourceInterval=15, IndexCode=UKX, TickCount=1730, TimeStamp=151215, PrevCloseDate=20090313, Currency=GBP, Date=20090316, Status=N, Change=79.13, PrevClose=3753.68, LastValue=3832.81]

Whereas subsequent messages for the same PDG/index/session would feature a stripped down message:

Index update for PDG1/UKX:Tick=1731, Replay=false, Fields=[TimeStamp=151230, TickCount=1731, LastValue=3833.01, Change=79.33]

This field optimisation will exist across trade date boundaries as well intraday sequential messages. Clients need to anticipate optimisation in their market logic.

TICKCOUNTS

The TickCount increments on all iterations of an index sent to the FDI under normal operational conditions.

NOTE: There is a known (though rare) scenario where the TickCount for an index can increment by more than one or regress between consecutive messages.

For Pulse Indices the updates will be sent at regular intervals. If the LastValue itself has not changed between messages then the TickCount will still increase by one and the TimeStamp field will update (please see Optimisation).

For Streaming Indices a new TickCount is generated for every calculation event.

It is possible however to get a Streaming Index message without a LastValue field due to Optimisation where the actual price change granularity is less than two decimal places which is the dissemination limit.

REPLAY HANDLING

Whilst the FDI maintains sessions and failover behaviour it is expected that the client application will monitor TickCount numbers and invoke Replay requests where required for Pulse Indices.

The onus is on the client application to request any missed ticks through Replay.

If the replay request cannot be fulfilled due to lack of requested data then the application will receive a SubscriptionError.NOT_FOUND message.

Please note that Replay requests are only actioned for the current trade date and there is no facility to Replay prior trade day data at this time.