

宿主机操作

1. 安装 docker

安装参考连接：[docker install](#)

若本地尚未安装docker，先进入docker_server目录：

```
cd ICRA-RM-Sim2Real/docker_server
```

执行：

```
./docker_install.sh
```

若脚本无法执行，则检查脚本是否有运行权限

验证：

```
docker --version
```

```
base) hpf@hpf:~$ docker --version
docker version 20.10.12, build e91ed57
base) hpf@hpf:~$
```

2. 安装 nvidia driver

推荐使用Software & Updates中Additional Drivers安装

创建镜像和容器前需要检查宿主机的显卡驱动是否正常

打开终端，输入nvidia-smi

```

Try: sudo apt install <deb name>

(base) user@syl:~$ nvidia-smi
Thu Jan 20 10:34:06 2022

+-----+
| NVIDIA-SMI 470.86                Driver Version: 470.86                CUDA Version: 11.4                |
+-----+-----+-----+-----+-----+-----+
| GPU   Name           Persistence-M| Bus-Id        Disp.A | Volatile Uncorr. ECC |
| Fan  Temp  Perf    Pwr:Usage/Cap|      Memory-Usage | GPU-Util  Compute M. |
|=====+=====+=====+=====+=====+=====+
|  0  NVIDIA GeForce ...   Off    | 00000000:01:00.0  On  |          2%      Default |
| 30%   29C   P8     27W / 350W    | 788MiB / 24234MiB |              MIG M.    |
|                               |                      |                      N/A  |
+-----+-----+-----+-----+-----+-----+

Processes:
+-----+-----+-----+-----+-----+-----+
| GPU   GI    CI          PID    Type   Process name                      GPU Memory |
|   ID   ID   ID                  |                 |          Usage |
+-----+-----+-----+-----+-----+-----+
|  0   N/A  N/A         1103      G   /usr/lib/xorg/Xorg                  523MiB |
|  0   N/A  N/A         1817      G   /usr/bin/gnome-shell                 85MiB |
|  0   N/A  N/A          3162      G   ...nlogin/bin/sunloginclient        10MiB |
|  0   N/A  N/A        147003      G   ...token=4084161354625565244        13MiB |
|  0   N/A  N/A        173926      G   ...AAAAAAAA= --shared-files          44MiB |
|  0   N/A  N/A        175019      G   ...AAAAAAAA= --shared-files         106MiB |
+-----+-----+-----+-----+-----+-----+

```

目前支持的驱动版本为470和510

3. 安装 nvidia-docker2

安装参考连接：[nvidia-docker2](#)

摘取的主要步骤，可做参考

```
sudo systemctl --now enable docker
```

```

distribution=$(. /etc/os-release;echo $ID$VERSION_ID) \
  && curl -s -L https://nvidia.github.io/nvidia-docker/gpgkey | sudo apt-
key add - \
  && curl -s -L https://nvidia.github.io/nvidia-
docker/$distribution/nvidia-docker.list | sudo tee
/etc/apt/sources.list.d/nvidia-docker.list

```

```

sudo apt-get update
sudo apt-get install -y nvidia-docker2
sudo systemctl restart docker

```

验证：

```
sudo docker run --rm --gpus all nvidia/cuda:11.0-base nvidia-smi
```

```

11.0-base: Pulling from nvidia/cuda
54ee1f796a1e: Pull complete
7bfea53ad12: Pull complete
46d371e02073: Pull complete
b66c17bbf772: Pull complete
8642f1a6dfb3: Pull complete
e5ce55b8b4b9: Pull complete
155bc0332b0a: Pull complete
Digest: sha256:774ca3d612de15213102c2dbbba55df44dc5cf9870ca2be6c6e9c627fa63d67a
Status: Downloaded newer image for nvidia/cuda:11.0-base
Thu Jan 20 02:40:21 2022

```

NVIDIA-SMI 470.86		Driver Version: 470.86		CUDA Version: 11.4	
GPU	Name	Persistence-M	Bus-Id	Disp.A	Volatile Uncorr. ECC
Fan	Temp	Perf	Pwr:Usage/Cap	Memory-Usage	GPU-Util Compute M. MIG M.
0	NVIDIA GeForce ...	Off	00000000:01:00.0	On	N/A
30%	28C	P8	27W / 350W	897MiB / 24234MiB	0% Default N/A

```

Processes:
GPU  GI  CI  PID  Type  Process name  GPU Memory
  ID  ID  ID             Usage

```

4. 注册 dockerhub

注册dockerhub账号：[dockerhub](#)

登录dockerhub账号

```
sudo docker login
```

```

hpf@hpf-ThinkStation-P520:~$ sudo docker login
Authenticating with existing credentials...
Stored credentials invalid or expired
Login with your Docker ID to push and pull images from Docker Hub. If you don't
have a Docker ID, head over to https://hub.docker.com to create one.
Username (hpf9017): hpf9017
Password:
WARNING! Your password will be stored unencrypted in /root/.docker/config.json.
Configure a credential helper to remove this warning. See
https://docs.docker.com/engine/reference/commandline/login/#credentials-store

Login Succeeded

```

5. 下载 docker image

下载镜像(tag以最后发布为准)

```
sudo docker pull rmus2022/server:v0.0.2
```

```
hpf@hpf-ThinkStation-P520:~$ sudo docker pull rmus2022/server:v0.0.1
v0.0.1: Pulling from rmus2022/server
35807b77a593: Pulling fs layer
c63faf7ebb91: Pulling fs layer
d0af4aff2aac: Pulling fs layer
4860ac2ea9aa: Pulling fs layer
964f8d4cad4: Pulling fs layer
f68bad238d01: Pulling fs layer
75dd747f11f9: Pulling fs layer
66bca8babce2: Pulling fs layer
97cfad4752a5: Pulling fs layer
97ed0d5f10a8: Pulling fs layer
d35c98dc1ca2: Pulling fs layer
d47c4d48afef: Pulling fs layer
68f4730d0214: Pulling fs layer
9bd3efcf1156: Pulling fs layer
00f94e76c029: Pulling fs layer
b315e699e5e3: Pulling fs layer
f68bad238d01: Downloading 208.6MB/1.303GB
```

因为镜像文件较大，需等待较长时间

```
7f4183e6255f: Pull complete
fe03d076a06f: Pull complete
3a91a2d10a8c: Pull complete
b83461a2e6dd: Pull complete
483ebabda3d8: Pull complete
65dcfd31299f: Pull complete
9564ffd5b934: Pull complete
41940571ed61: Pull complete
bb83b4ee7497: Pull complete
d7109b48513f: Pull complete
60a1c03c590b: Pull complete
533dcaa506ce: Pull complete
3210a529c5fd: Pull complete
cf017de893d0: Pull complete
c3338802871c: Pull complete
f05d4dbf4046: Pull complete
aba47372644d: Pull complete
bb7a618a61bc: Pull complete
c1c4d57e3d59: Pull complete
83397bc8dc2c: Pull complete
Digest: sha256:ed7e8f6b29744ddb1f78086b037d391da1436b3901409b21b20a0d0f2739d903
Status: Downloaded newer image for rmus2022/server:v0.0.1
docker.io/rmus2022/server:v0.0.1
```

6. 创建 docker container

```
cd ICRA-RM-Sim2Real/docker_server
```

需要确认create_container_server中的tag为正确版本

```
sudo docker rm -f sim2real_server

sudo docker run -id --gpus all --name sim2real_server --network host \
  --privileged -v /dev:/dev -e DISPLAY=$DISPLAY -e QT_X11_NO_MITSHM=1 \
  -v /dev/bus/usb:/dev/bus/usb \
  -v /dev/video0:/dev/video0 \
  -v /dev/video1:/dev/video1 \
  -v /dev/video2:/dev/video2 \
  -v /dev/video3:/dev/video3 \
  -v /dev/video4:/dev/video4 \
  -v /dev/video5:/dev/video5 \
  -v /tmp/.X11-unix:/tmp/.X11-unix \
  -v $HOME/Desktop/shared:/shared \
  rmus2022/server:v0.0.2

sudo xhost +
```

```
./create_container_server.sh
```

```
hpf@hpf-ThinkStation-P520:~/ICRA-RM-Sim2Real/docker_server$ ./create_container_s
erver.sh
[sudo] password for hpf:
Error: No such container: sim2real_server
b638f34c5514db9ac6255a880e7967bc603e703b919e3ef4dafcf47037ed1c45
access control disabled, clients can connect from any host
```

当本地没有sim2real_server容器时会报错，不影响

每次运行该脚本，会删除没有docker commit的修改

docker操作

1. 运行docker

重启后需要执行一次

```
sudo docker start sim2real_server
```

```
cd ICRA-RM-Sim2Real/docker_server
```

密码：123

```
./exec_server.sh
```

进入docker环境

2. 运行habitat sim例程

```
cd ~/habitat-sim/
```

```
./build/viewer ./data/scene_datasets/habitat-test-scenes/van-gogh-room.glb
```

可以通过 w, a, s, d控制机器人移动，通过方向键控制机器人视角。



2. 运行比赛环境

新建terminal

```
cd ICRA-RM-Sim2Real/docker_server
```

```
./exec_server.sh
```

```
roscore
```


新建terminal

```
cd ICRA-RM-Sim2Real/docker_server
```

```
./exec_server.sh
```

```
cd ~/ros_x_habitat_ws/src/ros_x_habitat/
```

```
python3 src/scripts/roam_with_joy.py --hab-env-config-path  
./configs/roam_configs/pointnav_rgbd_roam_mp3d_test_scenes.yaml
```



3. 键盘控制运动和抓取

新建terminal

```
cd ICRA-RM-Sim2Real/docker_server
```

```
./exec_server.sh
```

```
roslaunch teleop_twist_keyboard teleop_twist_keyboard.py
```

需要鼠标点击，激活键盘控制程序的terminal

```
(habitat) sim2real@hpf-ThinkStation-P520:/$ rosrund teleop_twist_keyboard teleop_twist_keyboard.py

Reading from the keyboard and Publishing to Twist!
-----
Moving around:
   u   i   o
   j   k   l
   m   ,   .

For Holonomic mode (strafing), hold down the shift key:
-----
   U   I   O
   J   K   L
   M   <   >

t : up (+z)
b : down (-z)

anything else : stop

q/z : increase/decrease max speeds by 10%
w/x : increase/decrease only linear speed by 10%
e/c : increase/decrease only angular speed by 10%

CTRL-C to quit

currently:      speed 0.5      turn 1.0
```

按键q, z, 增大和降低机器人速度

按键i, j, , , l, 控制机器人前进后退和旋转

按键l, J, <, L, 控制机器人横向移动

通过k, 停止机器人运动

按键1, 移动机械臂到抓取位置

按键2, 移动机械臂到放置位置

按键3, 抓取矿石

按键4, 放置矿石