

General Reference-1.Data Types & Altibase Properties

Altibase 7.3

Altibase® Administration

Altibase Administration General Reference

Release 7.3

Copyright © 2001~2023 Altibase Corp. All Rights Reserved.

This manual contains proprietary information of Altibase® Corporation; it is provided under a license agreement containing restrictions on use and disclosure and is also protected by copyright patent and other intellectual property law. Reverse engineering of the software is prohibited.

All trademarks, registered or otherwise, are the property of their respective owners.

Altibase Corp

10F, Daerung PostTower II,

306, Digital-ro, Guro-gu, Seoul 08378, Korea

Telephone : +82-2-2082-1000

Fax : +82-2-2082-1099

Customer Service Portal : <http://support.altibase.com/en/>

Homepage : <http://www.altibase.com>

Table Of Contents

- [Preface](#)
 - [About This Manual](#)
- [1. Data Types](#)
 - [Overview](#)
 - [Character Data Types](#)
 - [Numeric Data Types](#)
 - [Date Data Type](#)
 - [Binary Types](#)
 - [LOB Data Type](#)
 - [Spatial Types](#)
- [2. Altibase Properties](#)
 - [Configuration](#)
 - [Properties Overview](#)
 - [Database Initialization Properties](#)
 - [Performance Properties](#)
 - [Session Properties](#)
 - [Time-out Properties](#)
 - [Transaction Properties](#)
 - [Backup and Recovery Properties](#)
 - [Replication Properties](#)
 - [Network and Security Properties](#)
 - [Message Logging Properties](#)
 - [Database Link Properties](#)
 - [Auditing Properties](#)
 - [C/C++ External Procedure Agent Properties](#)
 - [Account Security Properties](#)
 - [Other Properties](#)

Preface

About This Manual

This manual explains the concepts, components, and basic use of Altibase

Audience

This manual has been prepared for the following Altibase users:

- Database managers
- Performance managers
- Database users
- Application developers
- Technical support engineers

It is recommended for those reading this manual possess the following background knowledge:

- Basic knowledge in the use of computers, operating systems, and operating system utilities
- Experience in using relational databases and understanding of database concepts
- Computer programming experience
- Experience in database server management, operating system management, or network administration

Organization

This manual has been organized as follows:

- Chapter 1. Data Types
This chapter explains the data types that are supported in Altibase
- Chapter 2. Altibase Properties
This chapter explains the Altibase properties

Documentation Conventions


This section describes the conventions used in this manual. Understanding these conventions will make it easier to find information in this manual and other manuals in the series.









There are two sets of conventions:

- Syntax diagrams
- Sample code conventions

Syntax diagrams

This manual describes command syntax using diagrams composed of the following elements:

Elements	Meaning
	Indicates the start of a command. If a syntactic element starts with an arrow, it is not a complete command.

Elements	Meaning
	Indicates that the command continues to the next line. If a syntactic element ends with this symbol, it is not a complete command.
	Indicates that the command continues from the previous line. If a syntactic element starts with this symbol, it is not a complete command.
	Indicates the end of a statement.
	Indicates a mandatory element.
	Indicates an optional element.
	Indicates a mandatory element comprised of options. One, and only one, option must be specified.
	Indicates an optional element comprised of options.
	Indicates an optional element in which multiple elements may be specified. A comma must precede all but the first element.

Sample Code Conventions

The code examples explain SQL, stored procedures, iSQL, and other command line syntax.

The following describes the conventions used in the code examples:

Rules	Meaning	Example
[]	Indicates an optional item	VARCHAR [(size)] [[FIXED] VARIABLE]
{ }	Indicates a mandatory field for which one or more items must be selected.	{ ENABLE DISABLE COMPILE }
	A delimiter between optional or mandatory arguments.	{ ENABLE DISABLE COMPILE } [ENABLE DISABLE COMPILE]

Rules	Meaning	Example
...	Indicates that the previous argument is repeated, or that sample code has been omitted.	<pre>SQL> SELECT ename FROM employee; ENAME ----- SWNO HJNO HSCHOI . . . 20 rows selected.</pre>
Other Symbols	Symbols other than those shown above are part of the actual code.	EXEC :p1 := 1; acc NUMBER(11,2)
Italics	Statement elements in italics indicate variables and special values specified by the user.	<pre>SELECT * FROM <i>table_name</i>; CONNECT <i>userID/password</i>;</pre>
Lower case words	Indicate program elements set by the user, such as table names, column names, file names, etc.	SELECT ename FROM employee;
Upper case words	Keywords and all elements provided by the system appear in upper case.	DESC SYSTEM.SYS_INDICES;

Related Documents

For more detailed information, please refer to the following documents:

- Installation Guide
- Getting Started Guide
- Administrator's Manual
- Replication Manual

Altibase Welcomes Your Comments and Feedback

Please let us know what you like or dislike about our manuals. To help us with better future versions of our manuals, please tell us if there are any corrections or classifications that you would find useful.

Include the following information:

- The name and version of the manual that you are using
- Any comments about the manual
- Your name, address, and phone number

If you need immediate assistance regarding any errors, omissions, and other technical issues, please contact [Altibase's Support Portal](#).

Thank you. We always welcome your feedback and suggestions.

1. Data Types

In order to use SQL to store, change, and query the data in a database, it is first necessary to possess a thorough understanding of the available data types. This chapter presents a detailed explanation of the data types supported in Altibase.

Overview

Data Type Overview

The following data types are supported in Altibase:

Character Data Types

M : Defined column length L : The length of the input string		
Type	Length	Size
CHAR(M)	1 ~ 32000	M + 2
VARCHAR(M)	1 ~ 32000	length + 2 where length = L if the input value is stored in a variable area length = M if the input value is stored in a fixed area
NCHAR(M)	1 ~ 16000(UTF16) 1 ~ 10666(UTF8)	M*2 + 2(UTF16) M*3 + 2(UTF8)
NVARCHAR(M)	1 ~ 16000(UTF16) 1 ~ 10666(UTF8)	length*2 + 2(UTF16) length*3 + 2(UTF8) where: length = L if the input value is stored in a variable area length = M if the input value is stored in a fixed area

NCHAR and NVARCHAR are Unicode character types. The available maximum length of a UTF16-encoded string is different from that of a UTF8-encoded string.

Numerical Data Types

	Type	Precision	Scale	Size (bytes)	Remarks
Non-native	NUMERIC	38	0	3+ ((precision)+2)/2	*Fixed-Point Numbers * The NUMERIC data type is the same as the DECIMAL datatype.
	NUMERIC(p)	1 ~ 38	0		
	NUMERIC(p,s)	1 ~ 38	-84 ~ 128		
	DECIMAL	38	0		
	DECIMAL(p)	1 ~ 38	0		
	DECIMAL(p,s)	1 ~ 38	-84 ~ 128		
	NUMBER(p)	1 ~ 38	0		
	NUMBER(p,s)	1 ~ 38	-84 ~ 128		
	NUMBER	38	X	3+ ((precision)+2)/2	* Floating-Point Numbers
	FLOAT	38	X		
	FLOAT(p)	1 ~ 38	X		
Native	Type	Compatible C Type		Size(bytes)	Remarks
	DOUBLE	double		8	*Floating-Point Numbers
	REAL	float		4	
	BIGINT	long or long long		8	*Integer Type
	INTEGER	int		4	
	SMALLINT	short		2	

Example 1

Fixed-Point Numbers Size Calculation:

$$(3 + ((p) + 2) / 2)$$

- NUMERIC
NUMERIC(38, 0): Size = $3 + 40/2 = 23$ bytes
- NUMERIC(p) / NUMERIC(p, 0)
NUMERIC(10): Size = $3 + 12/2 = 9$ bytes
- NUMERIC(p, s)
NUMERIC(10, 9): Size = $3 + 12/2 = 9$ bytes
- DECIMAL: the same as NUMERIC

- `DECIMAL(p)`: the same as `NUMERIC(p)`
- `DECIMAL(p,s)`: the same as `NUMERIC(p,s)`
- `NUMBER(p)`: the same as `NUMERIC(p)`
- `NUMBER(p,s)`: the same as `NUMERIC(p,s)`

Example 2

Floating-Point Numbers Size Calculation: $(3 + ((p) + 2) / 2)$

- `FLOAT`
`FLOAT(38)`: Size = $3 + 40/2 = 23$ bytes
- `FLOAT(p)`
`FLOAT(20)`: Size = $3 + 22/2 = 14$ bytes
- - `NUMBER`: the same as `FLOAT`

Date Data Type

Type	Size (byte)
DATE	8

Binary Data Types

M : Defined column length L : The length of the input value		
Type	Length	Size
BLOB/CLOB		1 ~ 4294967295
BYTE	1 ~ 32000	M + 2
NIBBLE	1 ~ 254	M/2 + 1
BIT	1 ~ 64000	M/8 + 4
VARBIT	1 ~ 64000	length/8 + 4 where length = L if the input value is stored in a variable area length = M if the input value is stored in a fixed area

Geometry Data Type

Type	Length	Size (byte)
GEOMETRY	8~104857600	length + 40

The actual record size is the size of each data type as indicated above, plus the size of header information. The size of the header information varies depending on the OS.

NULL

When a row is inserted into a table, the value of a column is set to NULL if the value for that column is not known or has not been determined yet. In other words, NULL indicates that no value exists. Therefore, NULL is not the same as 0 (zero) or blank space, and is handled differently when performing comparison operations or saving data.

If any operation other than the NVL() function or the IS NULL or IS NOT NULL conditions is performed on a NULL value, the final result of the formula containing the operation will be NULL. In other words, comparisons and operations are meaningless when performed on NULL values.

NULL can appear in columns of any data type, as long as they are not restricted by NOT NULL or PRIMARY KEY constraints.

Data Type Conversion

The data type conversions that are possible are shown in matrix form in the following table.

When a comparison operation is to be performed on two values having the same data type, the comparison operation is performed on the values directly without any prior conversion. In contrast, when a comparison operation is to be performed on two values having different data types, the comparison is performed after one of the values is converted into the same type as the other value. Note however that when comparisons are performed, character data types are always converted into the data type of the other comparison operand, not the other way around

The following table shows convertible matrices of implicit data types (O: shows that attributes are retained even when data types are converted). For more detailed information on how to convert an existing table's data type to MODIFY, please refer to *modify_column_clause* statement in the *SQL Reference*.

After Before	char	var char	nchar	nvarchar	clob	big int	decimal	double	float	integer	number	numeric	real	small int	date	blob	byte	varbyte	nibble	bit	varbit	geometry
char	O	O	O	O		O	O	O	O	O	O	O	O	O	O							
varchar	O	O	O	O	O	O	O	O	O	O	O	O	O	O	O							
nchar	O	O	O	O		O	O	O	O	O	O	O	O	O	O							
nvarchar	O	O	O	O	O	O	O	O	O	O	O	O	O	O	O							
clob					O																	
bigint	O	O	O	O		O	O	O	O	O	O	O	O	O								
decimal	O	O	O	O		O	O	O	O	O	O	O	O	O								
double	O	O	O	O		O	O	O	O	O	O	O	O	O								
float	O	O	O	O		O	O	O	O	O	O	O	O	O								
integer	O	O	O	O		O	O	O	O	O	O	O	O	O								
number	O	O	O	O		O	O	O	O	O	O	O	O	O								
numeric	O	O	O	O		O	O	O	O	O	O	O	O	O								
real	O	O	O	O		O	O	O	O	O	O	O	O	O								
smallint	O	O	O	O		O	O	O	O	O	O	O	O	O								
date	O	O	O	O											O							
blob																O						
byte																O	O	O				
varbyte																O	O	O				
nibble																			O			
bit																				O	O	
varbit		O																		O	O	
geometry																						O

Implicit Data Type Conversion

If '1000' of bit type is entered into table t10 table, the conversion succeeds to integer '1000', but it is not an implicit data type conversion because the attribute of data type is changed.

```

isQL> create table t10 (i1 integer);
Create success.
isQL> insert into t10 values (bit'1000');
1 row inserted.
isQL> select * from t10;
I1
-----
1000
1 row selected.

```

Therefore, implicit data type conversion follows the rules below:

- When comparing numeric or character data types or arithmetic operations, the character data types are converted to numeric data types.
- When comparing the date data type with the character data type, the character data type is converted to the date data type and the comparison operation is performed.
- Operation that cannot convert data types are invalidated.
- The argument used in the function is converted to the data type of the argument defined in the function.
- If a character data type or numeric data type that uses decimal precisions to a floating-point data type that uses binary precision is converted
- When executing an INSERT or UPDATE, the data type is converted to the data type of the INSERT and UPDATE columns.

Example

<Query> When comparing numeric data types, character data type '10' is converted to numeric data.

```

isQL> create table emp (empno integer, name varchar(10), hire_date date);
insert into emp values (10,'altibase', '10-nov-2015');

isQL> select name from emp where empno = '10';
NAME
-----
altibase
1 row selected.

```

<Query> When arithmetic between numeric data type and character data type, character data type '10' is converted to numeric data type.

```

isQL> select empno + '10' from emp;
EMPNO+'10'
-----
20
1 row selected.

```

<Query> When comparing a date data type with a character data type, the character data type '10-nov-2015' is converted to a date data type.

```
isQL> select hire_date from emp where hire_date = '10-nov-2015';
HIRE_DATE
-----
10-NOV-2015
1 row selected.
```

<Query> When arithmetic between numeric data type and character type is performed, binary data type cannot be converted to numeric data type and operation is invalidated.

```
isQL> select empno + cast(12345 as nibble(6)) from emp;
[ERR-2100C : Conversion not applicable.
0001 : select EMPNO + CAST(12345 as NIBBLE(6)) from EMP
          ^                               ^
]

```

<Query> When the function SUM receives the character data type '10' as an argument, it is converted.

```
isQL> select sum('10') from dual;
SUM('10')
-----
10
1 row selected.
```

<Query> When the character data type '12.123456789' is converted to a floating-point numeric data type, the number of significant digits becomes float (11), which causes a loss of value.

```
isQL> select float'12.123456789' from dual;
FLOAT'12.123456789'
-----
12.1234568
1 row selected.
```

<Query> The value of numeric data to be inserted is converted according to the data type of the column to be inserted and the value is INSERT.

```
isQL> create table t1 ( i1 char(10), i2 integer, i3 double);
Create success.
isQL> insert into t1 values (integer'1020', char'1928', float'123.1234');
1 row inserted.
isQL> select * from t1;
I1          I2          I3
-----
1020        1928        123.1234
1 row selected.
```

Explicit Data Type Conversion

Data type conversion can be explicitly performed using SQL conversion functions or by type-casting, as shown below. The SQL functions that are used to explicitly convert a value from one data type to another are explained in the *SQL Reference*.

Syntax

```
datatype 'string or constant literal '
```

Description

Explicitly converts a numeric value from one data type to another. In the following example, the number 157.27 is converted to the characters "157.27".

```
CHAR '157.27'
```

Using the Character Strings

Single quotation mark should be used when displaying character strings in a SQL query. Since the single quotation mark becomes an escape letter when displaying a single quotation mark ('), the double quotation mark should be used in front.

Example

```
SELECT * FROM EMPLOYEE WHERE NAME = 'KIM';
INSERT INTO EMPLOYEE VALUES ('GILDONG'); //Insert the value GILDONG
SELECT * FROM REMOTE_TABLE(link1, 'SELECT * FROM EMPLOYEE WHERE NAME='''KIM''';
//'' are not the double quotation mark, it is two single quotation marks
```

FIXED/VARIABLE Option

FIXED or VARIABLE specifies where the data in a column will be stored.

When an entire record is stored in a contiguous space, this is called a 'FIXED' area. When one of the columns is stored in a separated space, rather than being stored in the fixed area contiguous with the rest of the record, this column is said to be stored in a 'VARIABLE' area.

When a column is stored in a variable area, the header information for the column, such as the length of the data and the pointer to the actual data, is stored in the fixed area, whereas the data for that column are stored in the variable area.

When a table is created in a disk tablespace, whether the user specifies FIXED or VARIABLE is ignored, and all columns in the table are treated as FIXED. However, when a table is created in a memory table space, the user-specified value is used.

However, the exception to this is that all LOB data type columns are always treated as VARIABLE, and the data can thus be stored in a fixed or variable area depending on the value specified using the IN ROW clause.

The following data types can be specified as VARIABLE: CHAR, VARCHAR, NCHAR, NVARCHAR, BYTE, VARBATE, NIBBLE, BIT, VARBIT, BLOB, and CLOB

IN ROW Clause

This clause pertains only to column data that are to be stored in a variable area. If the FIXED and IN ROW clause are both specified when a table is created, the IN ROW clause is ignored. When data are entered into a VARIABLE column, if the length of the data is less than or equal to the value specified using the IN ROW clause, the data will be stored in the fixed area, whereas if the data length is greater than the value specified using the IN ROW clause, the data will be stored in the variable area.

Here, "data length" does not mean the length of the input data, but the length of the data to be stored in memory or on disk, which will be somewhat larger. For example, when a column is defined as "VARCHAR(400) in row 200", data will be inserted into the fixed area if the length of the data that is input is smaller than or equal to 198, because 2 additional bytes are required when storing the data.

The default size of lob data stored in the fixed area can be specified using the MEMORY_LOB_COLUMN_IN_ROW_SIZE property for memory tables and the DISK_LOB_COLUMN_IN_ROW_SIZE for disk tables. Additionally, the default size for columns containing other types of data with the VARIABLE option can be specified using the MEMORY_VARIABLE_COLUMN_IN_ROW_SIZE property.

Setting these properties eliminates the need to use the IN ROW clause repeatedly for each column when creating a table. For more detailed information about these properties, please refer to chapter 2.

Character Data Types


Character data types are used to store character (alphanumeric) data, meaning words or free-form text, in either the database character set or the national character set.

In Altibase, character data types comprise the following types:

- CHAR
- VARCHAR
- NCHAR
- NVARCHAR

CHAR

Syntax Diagram



Syntax

```
CHAR [(size)] [ FIXED | VARIABLE [IN ROW size] ]
```

Description


This is a character data type that has a fixed length equal to the specified size. If an input value is shorter than the specified size, the remaining area is filled with blank spaces.

The default size of CHAR column is 1 byte, and its maximum length is 32000 bytes.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW clauses" section above.

VARCHAR

Syntax Diagram



Syntax

```
VAR [ (size) ] [ FIXED | VARIABLE [ IN ROW size ] ]
```

Description

This is a character data type for storing alphanumeric data that vary in length within a specified size.


The default size of VARCHAR column is 1 byte, and its maximum length is 32000 bytes.

VARCHAR is a variable length data type; that is, when the length of input data is shorter than the specified column size, only the data that were actually inserted are stored. In contrast, for the CHAR data type, if the length of input data is shorter than the column length, the remaining space in the column is padded with blank spaces. For example, if a column is defined as CHAR(10) and the word "magic" is to be stored, it will be stored as "magic_", where "_" represents a blank space.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" section above.

NCHAR

Syntax Diagram



Syntax

```
NCHAR [(size)] [ FIXED | VARIABLE [IN ROW size] ]
```

Description

This is a character data type having a specified fixed length. If an input value is shorter than the specified size, the remainder is filled with blank spaces.


If the national character set is UTF16, the size of one character in an NCHAR column is fixed at 2 bytes, that is, it does not vary in length. In contrast, if the national character set is UTF8, the size of one character in an NCHAR column is not fixed; rather, it varies from 1 to 3 bytes.

The maximum size is 16000 bytes if the national character set is UTF16.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" section above.

NVARCHAR

Syntax Diagram



Syntax

```
NVARCHAR [(size)] [ FIXED | VARIABLE [IN ROW size] ]
```

Description

This is a character data type for storing Unicode alphanumeric data that vary in length within a specified size.

If the national character set is UTF16, the size of one character in an NVARCHAR column is fixed at 2 bytes, that is, it does not vary in length. In contrast, if the national character set is UTF8, the size of one character in an NVARCHAR column is not fixed; rather, it varies from 1 to 3 bytes.

In other aspects, the NVARCHAR type is the same as the VARCHAR type, so for more detailed information please refer to the description of the VARCHAR type.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" section above.


Numeric Data Types

Numeric data types are used to store zero as well as positive and negative numbers having fixed values. Altibase supports the following numeric types:

- BIGINT
- DECIMAL
- DOUBLE
- FLOAT
- INTEGER
- NUMBER
- NUMERIC
- REAL
- SMALLINT

BIGINT

Syntax Diagram



Syntax

BIGINT

Description


This is an 8-byte integer data type.

It is equivalent to the “long” (on 64-bit systems) and “long long” (on 32-bit systems) types in the C language.

Range: $-2^{63} + 1(-9223372036854775807)$ ~ $2^{63} - 1(9223372036854775807)$

DECIMAL

Syntax Diagram




Syntax

```
DECIMAL [(precision[, scale])]
```

Description

This data type is the same as the NUMERIC type.


DOUBLE**Syntax Diagram****Syntax**

```
DOUBLE
```

Description

This is an 8-byte floating-point numeric data type.

It is the same as the “double” type in the C language.

FLOAT**Syntax Diagram****Syntax**


```
FLOAT [(precision)]
```

Description

This is a floating-point numeric data type that can store a value ranging from -1E+120 to 1E+120.

Precision is the number of significant digits, that is, the number of digits used to express the mantissa of the floating-point number.

Precision can range from 1 to 38. If it is not expressly specified, the default precision is 38.

INTEGER**Syntax Diagram**

Syntax

```
INTEGER
```

Description


This is an integer data type that is 4 bytes in size.

It is the same as the "int" data type in the C language.

It can have an integer value ranging from -2,147,483,647 to 2,147,483,647.

NUMBER

Syntax Diagram



Syntax


```
NUMBER [(precision, scale)]
```

Description

This is an alias of the NUMERIC data type. However, when precision and scale are not defined, they are the same as for the FLOAT data type. The FLOAT data type is rounded to the 39th digit.

NUMERIC

Syntax Diagram



Syntax

```
NUMERIC [(precision, scale)]
```

Description

NUMERIC is a fixed decimal data type that can contain a total number of significant digits up to the value specified using precision and a number of digits to the right of the decimal place up to the value specified using scale. In contrast to the FLOAT data type, which is a floating-point numerical data type used for representing real numbers, when both precision and scale are omitted from a NUMERIC data type declaration, precision defaults to 38 and scale to 0, i.e.


- Precision can be specified within the range from 1 to 38.
- Scale can be specified within the range from -84 to 128.
- If precision is omitted, the default is 38.
- If scale is omitted, the default is 0.

The following shows the respective values that would result when the input value 1234567.89 is converted to the NUMERIC types defined as shown.

- NUMERIC=> 1234568
- NUMERIC(9)=> 1234568
- NUMERIC(9, 2)=> 1234567.89
- NUMERIC(9, 1)=> 1234567.9
- NUMERIC(6)=> Precision exceeded
- NUMERIC(7, -2)=> 1234500
- NUMERIC(7, 2)=> Precision exceeded

REAL

Syntax Diagram



Syntax

REAL


Description

The data type is used to store 4-byte floating-point numeric values.

It is the same as the “float” type in the C language.

SMALLINT

Syntax Diagram



Syntax

SMALLINT

Description

This data type is used to store 2-byte integer values.

It is the same as the "short" type in the C language.

It can be used to store integers ranging from $-2^{15} + 1$ (-32,767)에서 $2^{15} - 1$ (32,767) inclusive

Number Format Model

When data are converted using typecasting functions such as TO_CHAR or TO_NUMBER, numeric data can be specified in the following formats. A number format model consists of one or more elements that represent a number. In this section, each of these elements will be explained with reference to examples showing the related number formats.

, (Comma)**Descriptions**

Outputs a comma at the specified position.

Commas can be used multiple times.

Restriction

A comma cannot be placed at the end of a number, to the right of a decimal point, or at the very beginning of a number.

Example

```

iSQL> SELECT TO_CHAR (1234, '99,99') FROM dual;
TO_CHAR (1234, '99,99')
-----
12,34
1 row selected.

iSQL> SELECT TO_NUMBER ( '12,34', '99,99') FROM dual;
TO_NUMBER ( '12,34', '99,99')
-----
1234
1 row selected.
```

. (Decimal Point)**Description**

Adds a decimal point at the specified position

Restriction

Only one decimal point can be used within a number

Example

```

iSQL> SELECT TO_CHAR (1.234, '99.999') FROM dual;
TO_CHAR (1.234, '99.999')
-----
1.234
1 row selected.

iSQL> SELECT TO_NUMBER ( '1.234', '99.999') FROM dual;
TO_NUMBER ( '1.234', '99.999')
-----
1.234
1 row selected.

```

\$**Description**

Prepends the \$ sign to a number

Example

```

iSQL> SELECT TO_CHAR (123, '$9999') FROM dual;
TO_CHAR (123, '$9999')
-----
$123
1 row selected.

iSQL> SELECT TO_NUMBER ( '$0123', '09$99') FROM dual;
TO_NUMBER ( '$0123', '09$99')
-----
123
1 row selected.

```

0(Numeral 0)**Description**

If the number of significant digits to be output exceeds the number of digits in the number that is input, 0's (zeroes) are prepended to the number before it is returned. In all other aspects, this element is the same as the "9" element, which is described below.

Example

```

iSQL> SELECT TO_CHAR (123, '0999') FROM dual;
TO_CHAR (123, '0999')
-----
0123

```

9(Numeral 9)

Description

Uses the numeral 9 to indicate the number of digits to output. If the number of 9's is greater than the number of digits in the number that is input, the space to the left of the number is padded with blank spaces before the number is output. If the number of 9's to the left of the decimal point is less than the number of digits to the left of the decimal point in the input number, the pound sign ("£") is repeatedly output. The number of pound signs that are output is the number of characters in the user-defined format plus one (a sign character). A decimal point placed in between 9's separates the integer and fractional parts of a number

When there are digits to the right of the decimal point in the first argument, i.e. when the input number has a fractional part, but the user-defined format either has no fractional part or has a fractional part with a smaller number of decimal places than the input number, the input number is rounded off to the number of decimal places in the user-defined format

Example

```

iSQL> SELECT TO_CHAR (123, '99999') FROM dual;
TO_CHAR (123, '99999')
-----
      123

iSQL> SELECT TO_CHAR (123.55, '999') FROM dual;
TO_CHAR (123.55, '999')
-----
      124
1 row selected.

iSQL> SELECT TO_CHAR (123.4567, '999999') FROM dual;
TO_CHAR (123.4567, '999999')
-----
      123
1 row selected.

iSQL> SELECT TO_CHAR (1234.578, '9999.99') FROM dual;
TO_CHAR (1234.578, '9999.99')
-----
    1234.58
1 row selected.

iSQL> SELECT TO_CHAR (1234.578, '999.99999') FROM dual;
TO_CHAR (1234.578, '999.99999')
-----
#####
1 row selected.

iSQL> SELECT TO_NUMBER ( '123', '99999') FROM dual;
TO_NUMBER ( '123', '99999')
-----
      123
1 row selected.

iSQL> SELECT TO_NUMBER ( '1234.58', '9999.99') FROM dual;
TO_NUMBER ( '1234.58', '9999.99')
-----

```

```
1234.58
1 row selected.
```

FM

Description

Removes spaces or zeroes from the left part of the output string.

Example

```
iSQL> select to_char(00123.100,'99999.999') from dual;
TO_CHAR(00123.100,'99999.999')
-----
      123.100
1 row selected.
iSQL> select to_char(00123.100,'FM99999.999') from dual;
TO_CHAR(00123.100,'FM99999.999')
-----
      123.100
1 row selected.
```

B

Description

0's (zeroes) in the integer part of the fixed-point number are replaced with blank spaces.

Example

```
iSQL> SELECT TO_CHAR (0.4, 'B9') FROM T1;
TO_CHAR (0.4, 'B9')
-----

1 row selected.
```

C

Description

Returns the ISO currency symbol(the value set for the NLS_ISO_CURRENCY property) in the specified position.

Example

```
iSQL> SELECT TO_CHAR (4000, 'C9999') FROM dual;
TO_CHAR (4000, 'C9999')
-----
      KRW4000
1 row selected.
```


D**Description**

Returns the decimal character(the value set for the NLS_NUMERIC_CHARACTER property) in the specified position. The default value is a period(.).

Restriction

Only one decimal character can be included when specifying a number format model.

Example

```

iSQL> SELECT TO_CHAR (24.06, '99D99') FROM dual;
TO_CHAR (24.06, '99D99')
-----
24.06
1 row selected.
iSQL> SELECT TO_CHAR (206, '999D99') FROM dual;
TO_CHAR (206, '999D99')
-----
206.00
1 row selected.

```

EEEE**Description**

Displays the input number in exponential notation

Restriction

EEEE should always be at the right end. It is possible to be at the left rather than S, PR, or MI. It cannot be used with commas. In addition, it cannot be used in the TO_NUMBER function.

Example

```

iSQL> SELECT TO_CHAR (1234, '9.9EEEE') FROM dual;
TO_CHAR (1234, '9.9EEEE')
-----
1.2E+03
1 row selected.

```

G**Description**

Returns the group separator(the value set for the NLS_NUMERIC_CHARACTER property) in the specified position. Multiple group separators can be specified for a number format model.

Restriction

In a number format model, a group separator cannot appear to the right of a decimal character or a period.

Example

```

iSQL> SELECT TO_CHAR (2534.3, '999G999D99') FROM dual;
TO_CHAR (2534.3, '999G999D99')
-----
      2,534.30
1 row selected.

```

L**Description**

Returns the local currency symbol(the value set for the NLS_CURRENCY property) in the specified position.

Example

```

iSQL> SELECT TO_CHAR (4000, 'L9999') FROM dual;
TO_CHAR (4000, 'L9999')
-----
    ?4000
1 row selected.

```

MI**Description**

When MI is used at the rightmost place in the number format, if the input value is negative, the minus (-) sign is output at the end of the number, rather than at the beginning. If the input value is positive, a blank space is output instead of the minus sign.

Restrictions

MI must always be at the rightmost place in the number format. It cannot be used together with S or PR.

Example

```

iSQL> SELECT TO_CHAR (-123, '999MI') FROM dual;
TO_CHAR (-123, '999MI')
-----
    123-
1 row selected.

iSQL> SELECT TO_NUMBER ( '123-', '999MI') FROM dual;
TO_NUMBER ( '123-', '999MI')
-----
    -123
1 row selected.

```

PR**Description**

When PR is used at the rightmost place in the number format, if the input value is negative, the value is output in the form of "", rather than using the minus ("-") sign.

Restriction

PR must always be at the rightmost place in the number format. It cannot be used together with S or MI.

Example

```

iSQL> SELECT TO_CHAR (-123, '999PR') FROM dual;
TO_CHAR (-123, '999PR')
-----
<123>
1 row selected.

iSQL> SELECT TO_NUMBER ( '<123>', '999PR') FROM dual;
TO_NUMBER ( '<123>', '999PR')
-----
-123
1 row selected.
```

RN**Description**

Converts an input number to Roman numerals. The valid input range is from 1 to 3,999. If the lower-case letters "rn" are used in the number format, lower-case Roman numerals are output.

Restriction

RN cannot be used with any other number format elements or with the TO_NUMBER function.

Example

```

iSQL> SELECT TO_CHAR (14, 'RN') FROM dual;
TO_CHAR (14, 'RN')
-----
XIV
1 row selected.
```

S**Description**

When S is placed at the beginning or end of the number format, a plus ("+") or minus ("-") sign is output at the same position, corresponding to the sign of the input number.

Restriction

S can be placed at the beginning or end of the number format. It cannot be used with MI or PR.

Example

```

iSQL> SELECT TO_CHAR (123, 'S999.99') FROM dual;
TO_CHAR (123, 'S999.99')
-----
+123.00
1 row selected.

iSQL> SELECT TO_CHAR (-123, '999.99S') FROM dual;
TO_CHAR (-123, '999.99S')
-----
123.00-
1 row selected.

iSQL> SELECT TO_NUMBER ( '+123', 'S999.99') FROM dual;
TO_NUMBER ( '+123', 'S999.99')
-----
123
1 row selected.

iSQL> SELECT TO_NUMBER ( '123.00-', '999.99S') FROM dual;
TO_NUMBER ( '123.00-', '999.99S')
-----
-123
1 row selected.

```

V**Description**

The input number is multiplied by 10 to the power of the number of 9's after V. The number of 9's before V represents the number of significant digits to return from the input number.

Restriction

V cannot be used with a decimal point, and cannot be used with the TO_NUMBER function.

Example

```

iSQL> SELECT TO_CHAR (12, '99V99') FROM dual;
TO_CHAR (12, '99V99')
-----
1200
1 row selected.

iSQL> SELECT TO_CHAR (1200, '99V99') FROM dual;
TO_CHAR (1200, '99V99')
-----
#####
1 row selected.

iSQL> SELECT TO_CHAR (-123.456, '999V999EEEEMI') from dual;
TO_CHAR (-123.456, '999V999EEEEMI')
-----
1235E+02-
1 row selected.

```

XXXX**Description**

Converts the input number to a hexadecimal number. If the input number is not an integer, it is rounded off before being converted to a hexadecimal number. Specifying “xxxx” in lower-case returns the letters in the hexadecimal number in lower-case.

Restriction

XXXX cannot be used with other number format elements. The number to be converted must be greater than 0 (zero).

Example

```


iSQL> SELECT TO_CHAR (123, 'XXXX') FROM dual;
TO_CHAR (123, 'XXXX')
-----
7B
1 row selected.

iSQL> SELECT TO_NUMBER ('ABC', 'XXXX') FROM dual;
TO_NUMBER ('ABC', 'XXXX')
-----
2748
1 row selected.

```

Date Data Type

The DATE type is used to store date and time information

DATE**Syntax Diagram****Syntax**

```
DATE
```

Description

This data type is used to store date values in 8 bytes.

The range of dates that can be stored depends on the system. Typically, the dates that can be stored range from 0001/01/01 - 9999/12/31.

The date value can be displayed in various formats using a date format string.

The Datetime Format Model

The date data type is managed as numerical data and it is internally managed by the database. However, it can be displayed with character strings with the conversion function TO_CHAR or TO_DATE. The user should specify a character string of the date data type in accordance with a report format when using conversion functions.

The date data types are comprised of the following basic elements.

- AM, PM
- SCC, CC
- D, DD, DDD, DAY, DY
- HH, HH12, HH24
- MM, MON, MONTH
- MI
- Q
- SS, SSSSS, SSSSSS, SSSSSSSS, FF[1..6]
- WW, WW2, W, IW
- Y,YYY
- SYYYY, YYYY, YYY, YY, Y, RR, RRRR
- IYYY, IYY, IY, I

Along with these basic elements, the datetime format model also consists of the following punctuation marks and special characters:

- Hyphen (-)
- Slash (/)
- Comma (,)
- Period (.)
- Colon (:)
- Single Quotation (')

The meaning and use of each of these basic elements will be explained below with reference to examples.

AM, PM

Description

Returns either "AM" or "PM" depending on whether the input time is before or after noon. (AM or PM)

Example

```

iSQL> SELECT TO_CHAR ( TO_DATE( '13', 'HH' ), 'AM' ) FROM dual;
TO_CHAR ( TO_DATE( '13', 'HH' ), 'AM' )
-----
PM
1 row selected.

iSQL> SELECT TO_DATE('1980-12-28 PM', 'YYYY-MM-DD AM') FROM dual;
TO_DATE('1980-12-28 PM', 'YYYY-MM-DD AM'
-----
1980/12/28 12:00:00
1 row selected.

```

SCC**Description**

Represents a century

- If the last 2 digits of an input 4-digit year are within the range from 01 to 99, the sum of 1 plus the first 2 digits of the 4-digit year is returned.
- If the last 2 digits of an input 4-digit year are 00, the first 2 digits of the 4-digit year are returned unchanged.

BC is preceded by a year with a minus sign (-).

- A year of 0000 is one year B.C.E and -0001 is a two year B.C.E.
- 0000 to -0099 are in -1 century and are represented by -01.

SCC cannot be used as an argument for the TO_DATE function.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'SCC' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'SCC' )
-----
20
1 row selected.

iSQL> SELECT TO_CHAR ( DATE'01-JAN-0001' - 1, 'SCC' ) FROM dual;
TO_CHAR ( DATE'01-JAN-0001' - 1, 'SCC' )
-----
-01
1 row selected.

```

CC**Description**

Represents a century

- If the last 2 digits of an input 4-digit year are within the range from 01 to 99, the sum of 1 plus the first 2 digits of the 4-digit year is returned.
- If the last 2 digits of an input 4-digit year are 00, the first 2 digits of the 4-digit year are returned unchanged.

CC cannot be used as an argument for the TO_DATE function.

Example

```
iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'CC' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'CC' )
-----
20
1 row selected.
```

D

Description

Returns the day of the week, represented by a number from 1 to 7. Sunday is represented by the number 1.

D cannot be used as an argument for the TO_DATE function.

Example

```
iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'D' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'D' )
-----
1
1 row selected.
```

DAY

Description

Returns the day of the week in upper-case letters in English (SUNDAY, MONDAY,...).

DAY cannot be used with the TO_DATE function.

Example

```
iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'DAY' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'DAY' )
-----
SUNDAY
1 row selected.
```

DD

Description

Returns the day of the month, represented by a number from 1 to 31.

Example

```
iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'DD' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'DD' )
-----
28
1 row selected.

iSQL> SELECT TO_DATE( '1980-12-28', 'YYYY-MM-DD') FROM dual;
TO_DATE( '1980-12-28', 'YYYY-MM-DD')
-----
1980/12/28 00:00:00
1 row selected.
```

DDD**Description**

Returns the day of the year, represented by a number from 1 to 366.

DDD cannot be used with the TO_DATE function.

Example

```
iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'DDD' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'DDD' )
-----
363
1 row selected.
```

DY**Description**

Returns the day of the week in abbreviated form (SUN, MON, TUE, ...).

DY cannot be used with the TO_DATE function.

Example

```
iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'DY' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'DY' )
-----
SUN
1 row selected.
```

FF [1..6]**Description**

A number from 1 to 6 after FF is used to represent the number of microseconds (0~999999). The FF returns the same result as FF6.

FF cannot be used with the TO_DATE function.

Example

```

iSQL> SELECT TO_CHAR ( SYSDATE, 'FF5' ) FROM dual;
TO_CHAR ( SYSDATE, 'FF5' )
-----
34528
1 row selected.

```

HH, HH24**Description**

Returns the hour of the day in 24-hour format (i.e. returns a number from 0 to 23)

Example

```

iSQL> SELECT TO_CHAR ( TO_DATE( '2008-12-28 17:30:29', 'YYYY-MM-DD HH:MI:SS' ),
'HH' ) FROM dual;
TO_CHAR ( TO_DATE( '2008-12-28 17:30:29'
-----
17
1 row selected.

iSQL> SELECT TO_CHAR ( TO_DATE( '2008-12-28 17:30:29', 'YYYY-MM-DD HH24:MI:SS' ),
'YYYY-MM-DD HH24:MI:SS' ) FROM dual;
TO_CHAR ( TO_DATE( '2008-12-28 17:30:29',
-----
2008-12-28 17:30:29
1 row selected.

```

HH12**Description**

Returns the hour of the day in 12-hour format (i.e. returns a number from 1 to 12).

Example

```

iSQL> SELECT TO_CHAR ( TO_DATE( '2008-12-28 17:30:29', 'YYYY-MM-DD HH:MI:SS' ),
'HH12' ) FROM dual;
TO_CHAR ( TO_DATE( '2008-12-28 17:30:29',
-----
05
1 row selected.

iSQL> SELECT TO_CHAR( TO_DATE ( '08-12-28 05:30:29', 'RR-MM-DD HH12:MI:SS' ),
'RR-MM-DD HH12:MI:SS') FROM dual;
TO_CHAR( TO_DATE ( '08-12-28 05:30:29', 'R
-----
08-12-28 05:30:29
1 row selected.

```

MI**Description**

Returns a number ranging from 0 to 59, indicating the minutes portion of the input date.

Example

```
iSQL> SELECT TO_CHAR ( TO_DATE( '1980-12-28 17:30:29', 'YYYY-MM-DD HH:MI:SS' ),
'HH' ) FROM dual;
TO_CHAR ( TO_DATE( '1980-12-28 17:30:29'
-----
17
1 row selected.

iSQL> SELECT TO_DATE ( '05-12-28 14:30:29', 'RR-MM-DD HH:MI:SS' ) FROM dual;
TO_DATE ( '05-12-28 14:30:29', 'RR-MM-DD
-----
2005/12/28 14:30:29
1 row selected.
```

MM**Description**

Returns a number ranging from 01 to 12, indicating the month of the input date.

Example

```
iSQL> SELECT TO_CHAR ( TO_DATE( '1980-12-28 17:30:29', 'YYYY-MM-DD HH:MI:SS' ),
'HH' ) FROM dual;
TO_CHAR ( TO_DATE( '1980-12-28 17:30:29'
-----
17
1 row selected.

iSQL> SELECT TO_DATE ( '05-12-28 14:30:29', 'RR-MM-DD HH:MI:SS' ) FROM dual;
TO_DATE ( '05-12-28 14:30:29', 'RR-MM-DD
-----
2005/12/28 14:30:29
1 row selected.
```

MON**Description**

Returns the name of the month in upper case in abbreviated form. (JAN, FEB, MAR, ...)

Example

```
SQL> SELECT TO_CHAR (TO_DATE ( '1995-12-05', 'YYYY-MM-DD'), 'MON') FROM dual;
TO_
---
DEC
```

MONTH

Description

Returns the name of the month in upper case. (JANUARY, FEBRUARY, ...)

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'Month' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'Month' )
-----
December
1 row selected.

iSQL> SELECT TO_DATE ( '05-APRIL-28 14:30:29', 'RR-MONTH-DD HH:MI:SS' ) FROM
dual;
TO_DATE ( '05-APRIL-28 14:30:29', 'RR-MO
-----
2005/04/28 14:30:29
1 row selected.

```

Q

Description

Returns a number ranging from 1 to 4, indicating the quarter of the year of the input date.

This element cannot be used with the TO_DATE function.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'Q' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'Q' )
-----
4
1 row selected.

```

RM

Description

Returns the month of the input date in Roman numerals (I, II, III, IV...).

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'RM' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'RM' )
-----
XII
1 row selected.

iSQL> SELECT TO_DATE ('28-V-1980', 'DD-RM-YYYY') FROM dual;
TO_DATE ('28-V-1980', 'DD-RM-YYYY')
-----
1980/05/28 00:00:00
1 row selected.

```

RR**Description**

Returns the year of the input date as a 2-digit integer. When the year portion of the input date has 2 digits, if it is less than 50, 2000 is added to it (i.e. the 21st Century is assumed), whereas if it is greater than or equal to 50, 1900 is added to it before it is displayed. Therefore, the range of years that can be displayed is between 1950 – 2049.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-80', 'RR' ) FROM dual;
TO_CHAR ( '28-DEC-80', 'RR' )
-----
80
1 row selected.

iSQL> SELECT TO_DATE ( '28-DEC-80', 'DD-MON-RR' ) FROM dual;
TO_DATE ( '28-DEC-80', 'DD-MON-RR' )
-----
1980/12/28 00:00:00
1 row selected.

```

RRRR**Description**

Year (0 - 9999)

Returns the year of the input date as a 4-digit integer. When the year portion of the input date has 2 digits, if it is less than 50, 2000 is added to it (i.e. the 21st Century is assumed), whereas if it is greater than or equal to 50 and less than 100, 1900 is added to it before it is displayed. When the year portion of the input date has 4 digits, it is output without change.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'RRRR' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'RRRR' )
-----
1980
1 row selected.

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'DD-MON-RRRR' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'DD-MON-RRRR' )
-----
28-DEC-1980
1 row selected.

```

SS**Description**

Returns a number ranging from 0 to 59, indicating the seconds' portion of the input date.

Example

```

iSQL> SELECT TO_CHAR ( TO_DATE( '1980-12-28 17:30:29', 'YYYY-MM-DD HH:MI:SS' ),
'HH' ) FROM dual;
TO_CHAR ( TO_DATE( '1980-12-28 17:30:29'
-----
17
1 row selected.

iSQL> SELECT TO_DATE ( '05-12-28 14:30:29', 'RR-MM-DD HH:MI:SS' ) FROM dual;
TO_DATE ( '05-12-28 14:30:29', 'RR-MM-DD
-----
2005/12/28 14:30:29
1 row selected.

```

SSSSS

Description

Returns a number ranging from 0 to 86399, indicating the number of seconds that have passed since midnight.

Example

```

iSQL> SELECT TO_CHAR ( TO_DATE( '1980-12-28 17:30:29', 'YYYY-MM-DD HH24:MI:SS' ),
'SSSSS' ) FROM dual;
TO_CHAR ( TO_DATE( '1980-12-28 17:30:29'
-----
62940
1 row selected.

iSQL> SELECT TO_DATE('1980-12-28 12345', 'YYYY-MM-DD SSSSS') FROM dual;
TO_DATE('1980-12-28 12345', 'YYYY-MM-DD
-----
1980/12/28 03:25:45
1 row selected.

```

SSSSS

Description

Returns the fractional part of a second. (0 ~ 999999)

Example

```

iSQL> SELECT TO_CHAR (SYSDATE, 'SSSSSS') FROM dual;
TO_CHAR (SYSDATE, 'SSSSSS')
-----
490927
1 row selected.

iSQL> SELECT TO_CHAR ( TO_DATE('1980-12-28 123456', 'YYYY-MM-DD SSSSSS'),
'SSSSSS' ) FROM dual;
TO_CHAR ( TO_DATE('1980-12-28 123456', '
-----
123456
1 row selected.

```

SSSSSSSS**Description**

Returns the integer and fractional parts of the number of seconds in the input date, expressed as an 8-digit integer ranging from 0 to 59999999. The first two digits indicate the number of seconds, and the remaining 6 digits represent the fractional part of the second.

Example

```

iSQL> SELECT TO_CHAR (SYSDATE, 'SSSSSSSS') FROM dual;
TO_CHAR (SYSDATE, 'SSSSSSSS')
-----
48987403
1 row selected.

iSQL> SELECT TO_DATE ( '12.345678', 'SS.SSSSSS') FROM dual;
TO_DATE ( '12.345678', 'SS.SSSSSS')
-----
2005/12/01 00:00:12
1 row selected.

iSQL> SELECT TO_CHAR( TO_DATE( '12.345678', 'SS.SSSSSS'), 'SSSSSS') FROM dual;
TO_CHAR( TO_DATE( '12.345678', 'SS.SSSSS
-----
345678
1 row selected.

```

WW**Description**

Returns a number ranging from 1 to 54, indicating the week of the year. The period from January 1 to the first Saturday is considered the first week of the year.

This element cannot be used with the TO_DATE function.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'WW' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'WW' )
-----
53
1 row selected.

```

WW2**Description**

This date type indicates the week of the year regardless of day of the week. The first week begins with the 1st of January distinguished by a 7-days unit (1st to 53th week).

This element cannot be used within the TO_DATE function.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'WW2' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'WW2' )
-----
52
1 row selected.

```

W**Description**

Returns a number ranging from 1 to 6, indicating the week of the month. The period from the first day of the month to the first Saturday is considered the first week of the year.

This element cannot be used with the TO_DATE function.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'W' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'W' )
-----
5
1 row selected.

```

IW**Description**

This displays which week of the year it is (1~52 or 1~53) depending on ISO 8601. The start of the week is Monday, and the first week includes the first Thursday (January, 4th) of the year.

This element cannot be used with the TO_DATE function.

- 12.31. 2012 (Mon) ~ 01.06. 2013 (Sun): 1st week in 2013
- 12.29. 2014 (Mon) ~ 01.04. 2015 (Sun): 1st week in 2015
- 12.28. 2015 (Mon) ~ 01.03. 2016 (Sun): 53th week in 2015
- 12.26. 2016 (Mon) ~ 01.01. 2017 (Sun): 52th week in 2016

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'IW' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'IW' )
-----
52
1 row selected.

```

Y,YYY**Description**

Returns the year of the input date. A comma can be inserted at any place within a number representing the year, including the very beginning or end.

This element cannot be used with the TO_DATE function.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'Y,YYY' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'Y,YYY' )
-----
1,980
1 row selected.

```

SYYYY**Description**

Returns the four digits of the year. BC is marked with a minus sign '-'. (-9999 ~ 9999)

If the year is 0000, one year B.C.E, -0001 represents two years B.C.E.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'SYYYY' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'SYYYY' )
-----
1980
1 row selected.

iSQL> SELECT TO_CHAR ( DATE'01-JAN-0000' - 1, 'SYYYY-MM-DD' ) FROM dual;
TO_CHAR ( DATE'01-JAN-0000' - 1, 'SYYYY-MM
-----
-0001-12-31
1 row selected.

```

YYYY**Description**

Handles a positive four-digit number ranging from 0 - 9999 as the year.

Example

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'YYYY' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'YYYY' )
-----
1980
1 row selected.

iSQL> SELECT TO_DATE ( '28-DEC-1980', 'DD-MON-YYYY' ) FROM dual;
TO_DATE ( '28-DEC-1980', 'DD-MON-YYYY' )
-----
1980/12/28 00:00:00
1 row selected.

```

YY

Description

Returns the last two digits of the year. The 21st Century is assumed, so 2000 is added to it to obtain the actual year, which can range from 2000 to 2099.

Example 1

```

iSQL> SELECT TO_CHAR ( '28-DEC-1980', 'YY' ) FROM dual;
TO_CHAR ( '28-DEC-1980', 'YY' )
-----
80
1 row selected.

iSQL> SELECT TO_DATE ( '28-DEC-80', 'DD-MON-YY' ) FROM dual;
TO_DATE ( '28-DEC-80', 'DD-MON-YY' )
-----
2080/12/28 00:00:00
1 row selected.

```

Example 2

```

iSQL> CREATE TABLE timetbl(i1 INTEGER, t1 DATE, etc VARCHAR(10));
Create success.

iSQL> INSERT INTO timetbl VALUES (1, SYSDATE, 'Start');
1 row inserted.

iSQL> INSERT INTO timetbl VALUES (2, TO_DATE('2003-02-20 12:15:50', 'YYYY-MM-DD
HH:MI:SS'), 'The end');
1 row inserted.

iSQL> SELECT TO_CHAR(T1, 'YYYY YY MM MON Mon mon DD HH MI SS SSSSSS D DDD')
Date_format FROM timetbl WHERE i1 = 2;
DATE_FORMAT
-----
2003 03 02 FEB Feb feb 20 12 15 50 000000 5 051
1 row selected.

```

RR, RRRR, YY, YYYY Comparison

Obtains the actual year, which can range from 2000 to 2099.

- [YYYY]: The number is treated as a year, without change.

'23-FEB-5' = February 23, 0005

'23-FEB-05' = February 23, 0005

'23-FEB-2005' = February 23, 2005

'23-FEB-95' = February 23, 0095

- [YY]: 2000 is added to YY to obtain the year.

'23-FEB-5' = February 23, 2005

'23-FEB-05' = February 23, 2005

'23-FEB-2005' = Error

'23-FEB-95' = February 23, 2095

'23-FEB-05' = February 23, 2005

'23-FEB-2005' = Error

'23-FEB-95' = February 23, 2095

- [RRRR]: A number greater than 100 is taken as the year without change. If the input number has one or two digits, if it is < 50, 2000 is added to it, and if it is >= 50 and < 100, 1900 is added to it before it is output.

'23-FEB-5' = February 23, 2005

'23-FEB-05' = February 23, 2005

'23-FEB-2005' = February 23, 2005

'23-FEB-95' = February 23, 1995

'23-FEB-100' = February 23, 0100

'23-FEB-0005' = February 23, 0005

- [RR]: If the input number is < 50, 2000 is added to it, whereas if the input number is >= 50 and < 100, 1900 is added to it before it is output.

'23-FEB-5' = February 23, 2005

'23-FEB-05' = February 23, 2005

'23-FEB-2005' = Error

'23-FEB-95' = February 23, 1995

YYY**Description**

The last 3 digits of the year. As the 21st Century is assumed, 2000 is added to it to obtain the actual year, which can range from 2000 to 2099.

Y**Description**

The final digit of the year. As the 21st Century is assumed, 2000 is added to it to obtain the actual year, which can range from 2000 to 2099.

IYYY, IYY, IY, I**Description**

Represents a year according to the ISO 8601 standard. The start of the week is Monday, and the first week includes the first Thursday of the year.

IYYYY returns the ISO standard year.

IYY returns the last three digits of the ISO standard year.

IY returns the last two digits of the ISO standard year.

I returns the last 1 digit of the ISO standard year.

This cannot be used with the TO_DATE function.

- 2012.12.31 (MONDAY) ~ 2013.01.06 (SUNDAY) : 2013
- 2014.12.29 (MONDAY) ~ 2015.01.04 (SUNDAY) : 2015
- 2015.12.28 (MONDAY) ~ 2016.01.03 (SUNDAY) : 2015
- 2016.12.26 (MONDAY) ~ 2017.01.01 (SUNDAY) : 2016

Example

```
isql> SELECT TO_CHAR ( '1-JAN-2017', 'IYYY IYY IY I' ) FROM dual;
TO_CHAR('1-JAN-2017','IYYY IYY IY I')
-----
2016 016 16 6
1 row selected
```


Binary Types

Large and unstructured data such as text, images, video, and spatial data can be stored as binary data. Altibase supports the following binary types:

- BYTE
- VARBYTE
- NIBBLE
- BIT
- VARBIT

BYTE

Syntax Diagram



Syntax

```
BYTE [(size)] [[FIXED |] VARIABLE ( IN ROW size ) ]
```

Description

The BYTE is a binary data type containing a specified length. The right space of inserted data is filled with '0' if a character string with a shorter length, which is shorter than the specified the length, is inserted.

The default size of a BYTE column is 1 byte. The maximum length of a BYTE column is 32000 bytes. The data can be expressed in hexadecimal format using a combination of alphabet and numeric characters, such as '0FAE13.' The allowable alphanumeric characters are 0 (zero) to 9 and A to F.

The specified size should be adjusted when executing data retrieval or entering the BYTE column. Two characters can be inserted in a byte; for example, if BYTE(3) is defined, values ranging from '000000' to 'FFFFFF' can be inserted.

In the case of inserting the lower case letters from 'a' from 'f', they are stored as being converted.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" sections above.


Example

```

iSQL> CREATE TABLE T1 (I1 BYTE(1), I2 BYTE(5));
Create success.
iSQL> INSERT INTO T1 VALUES (BYTE'11', BYTE'0011');
1 row inserted.
iSQL> SELECT TO_CHAR(I1), TO_CHAR(I2) FROM T1;
TO_CHAR(I1)  TO_CHAR(I2)
-----
11  0011000000
1 row selected.
  
```

VARBYTE

Syntax Diagram



Syntax

```
VARBYTE [(size)] [[FIXED |] VARIABLE ( IN ROW size ) ]
```

Description

This is a binary data type containing a variable length. The default size of a VARBYTE column is one byte, and its maximum size is 32000 bytes.

The data can be expressed through a hexadecimal format with combination of alphabets and numbers such as '0FAE13'. The allocable alphabet and numeric characters range from 0 to 9 and A to F. The specified size should be adjusted when executing data retrieval or entering the BYTE column.

Two characters can be inserted in a byte; for example, if BYTE(3) is defined, values ranging from '000000' to 'FFFFFF' can be inserted. In the case of inserting the lower case letters from 'a' from 'f', they are stored as being converted.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" sections above.

Example


```

iSQL> CREATE TABLE T1 (I1 VARBYTE(1), I2 VARBYTE(5) );
Create success.
iSQL> INSERT INTO T1 VALUES (VARBYTE'11', VARBYTE'0011');
1 row inserted.
iSQL> SELECT TO_CHAR(I1), TO_CHAR(I2) FROM T1;
TO_CHAR(I1)  TO_CHAR(I2)
-----
11  0011
1 row selected.

```

NIBBLE

Syntax Diagram



Syntax

```
NIBBLE [(size)] [[FIXED |] VARIABLE ( IN ROW size ) ]
```

Description

NIBBLE column is that of a single character, and the maximum size is 254nibbles.

The data can be expressed in hexadecimal format using a combination of alphabet and numeric characters. The allowable alphanumeric characters are 0 (zero) to 9 and A to F. Unlike the BYTE type, only one character can be entered into one nibble.


For example, for NIBBLE (6), '000000' to 'FFFFFF' can be inserted.

When the lower case letters 'a' through 'f' are input, they are converted into upper-case letters.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" sections above.

BIT

Syntax Diagram



Syntax

```
BIT [(size)] [[FIXED |] VARIABLE ( IN ROW size ) ]
```

Description

This is a binary data type that has a fixed length and consists only of 0's and 1's.

The default size of a BIT column is one bit. Its maximum size is 64000 bits.

If an attempt is made to input a string that is longer than the specified length, an 'Invalid data type length' error will be raised. If a string shorter than the specified length is input, the space to the right of the input data is populated with 0's. If a value other than 0 or 1 is input, an 'Invalid literal' error is raised.


For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" sections above.

Example

```
isql> CREATE TABLE T1 ( I1 BIT(1), I2 BIT(5) );
Create success.
isql> INSERT INTO T1 VALUES ( BIT'1', BIT'011' );
1 row inserted.
isql> SELECT TO_CHAR(I1), TO_CHAR(I2) FROM T1;
TO_CHAR(I1)  TO_CHAR(I2)
-----
1  01100
1 row selected.
isql> INSERT INTO T1 VALUES ( BIT'1111', BIT'011' );
[ERR-2100D : Invalid data type length]
isql> INSERT INTO T1 VALUES ( BIT'1', BIT'1234' );
[ERR-21011 : Invalid literal]
```

VARBIT

Syntax Diagram



Syntax

```
VARBIT [(size)] [[FIXED |] VARIABLE ( IN ROW size ) ]
```

Description

This is a binary data type that has a variable length and consists only of 0's and 1's.

The default size of a BIT column is one bit. Its maximum size is 64000 bits. If an attempt is made to input a string that is longer than the specified length, an "Invalid data type length" error will be raised.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" sections above.

Example

```
iSQL> CREATE TABLE T1 ( I1 VARBIT(1), I2 VARBIT(5) );
Create success.
iSQL> INSERT INTO T1 VALUES ( VARBIT'1', VARBIT'011' );
1 row inserted.
iSQL> SELECT TO_CHAR(I1), TO_CHAR(I2) FROM T1;
TO_CHAR(I1)  TO_CHAR(I2)
-----
1  011
1 row selected.
iSQL> INSERT INTO T1 VALUES ( VARBIT'1111', VARBIT'011' );
[ERR-2100D : Invalid data type length]
iSQL> INSERT INTO T1 VALUES ( VARBIT'1', VARBIT'1234' );
[ERR-21011 : Invalid literal]
```

LOB Data Type

Overview

The LOB (which stands for Large Object) data type is for holding large amounts of data. Up to 4GB-1byte can be stored in one column of LOB data. Unlike other data types, the length of a LOB column does not need to be specified when a table is created. Additionally, more than one LOB type column can be defined in a table.

The LOB data type is divided into the Binary Large Object (BLOB) type, which is for holding binary data such as image and video files, and the Character Large Object (CLOB) type, which is for holding string data.

The Features of LOB

The LOB data type provided with Altibase has the following features:

- Data Storage Functions
- Partial Read
- Disk LOB Partitioning

Features of LOB

The LOB data type provided with Altibase has the following features:

- Data Storage Functions
- Partial Read
- Disk LOB Partitioning

Partial Read

It is possible to read only a desired portion of LOB data. A specific amount of data, offset a specific distance from the beginning of the file, can be read using the SQLGetLob function in Altibase ODBC.

Disk LOB Partitioning

Disk LOB data can be stored in a disk tablespace other than the one in which the table is stored. This tablespace can be configured in a method similar to partitioning.

Storing LOB Columns


In most cases, LOB data are stored in a variable area, away from the rest of the record. However, if a small amount of data is stored in the LOB column, the column can be stored in an area that is contiguous with the rest of the record (i.e. in the fixed area) using the 'in row' option. Note that this is possible for memory tables only; regardless of their size, LOB data in disk tables are always stored in a separate, variable area.

Because the amount of LOB column data that is stored in the variable area is typically very large, storing it in the same tablespace as the rest of the record has a negative impact on the efficiency of usage of space.

In a disk table, LOB column data can be stored in a tablespace other than the one containing the table to which the LOB column belongs. However, in a memory table, LOB column data cannot be stored separately, and thus are stored in the same tablespace as the table.

BLOB

Syntax Diagram



Syntax

```
BLOB [ VARIABLE ( IN ROW size ) ]
```


Description

BLOB is a binary data type that can vary in length up to 4GB-1byte and is intended for use in storing large amounts of binary data.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" sections above.

CLOB

Syntax Diagram



Syntax

```
CLOB [ VARIABLE ( IN ROW size ) ]
```

Description

CLOB is a character data type that can vary in length up to 4GB-1byte and is intended for use in storing large amounts of character data.

For more detailed information about the FIXED and VARIABLE clauses, please refer to the "FIXED/VARIABLE OPTIONS" and "IN ROW Clauses" sections above.

Restriction

- LOB type columns can't be used with cursors.
- LOB type columns can't be used in volatile tables or disk temporary tablespaces.
- LOB columns associated with tables in discarded tablespaces cannot be accessed.
- LOB type columns cannot be used for partitioning conditions, because in order to partition a column it must be possible to perform comparisons on the data in the column.
- Indexes cannot be created for LOB columns.
- It is possible to define a NOT NULL constraint for a LOB type column. However, when an insert attempt is made, a constraint violation error may be raised while the Altibase server is internally processing the data. Therefore, it is recommended that the NOT NULL constraint not be used with LOB type columns.

Spatial Types

The only geometry data type that is defined and supported for use with SQL in Altibase is the GEOMETRY data type. The Geometry data type consists of the following seven subtypes:

- Point
- LineString
- Polygon
- GeomCollection
- MultiPolygon
- MultiLineString
- MultiPoint

For more detailed information about the geometry datatype, please refer to the *Spatial SQL Reference*.

2. Altibase Properties

Altibase server can be run in various modes. The `altibase.properties` file is used to set Altibase server environment settings. The `altibase.properties` file contains all elements related to the operation and adjustment of the Altibase server.

This chapter describes the Altibase properties that need to be set and managed to configure and operate Altibase as a database suitable for the user's purposes.

Configuration

There are three ways to set Altibase server environment settings.

The first method involves making changes to the Altibase properties file, which is located at `$ALTIBASE_HOME/conf/altibase.properties`. Because this method of configuration is static, meaning that changes can only be made while Altibase is not running, the Altibase instance must be restarted in order for the changes to the properties file to take effect.

The second method is dynamic, meaning that configuration changes can be made even while Altibase server is running. Although this method confers the advantage of being able to make and apply changes without shutting down the server, it is not possible for all properties. For properties that can be dynamically changed, the `ALTER SYSTEM` or `ALTER SESSION` statements can be used to apply the configuration changes to the entire Altibase server or to individual sessions, respectively.

The third method of configuring the Altibase environment is through the use of operating system environment variables. Like the method involving the `altibase.properties` file, this configuration method is also static. Properties that are read-only or that can only have a single value can be set in this way. After specifying the environment variable as `ALTIBASE_property_name`, it will be necessary to reboot the database server in order to implement the changes.

Here is an example.

```
$ export ALTIBASE_DEFAULT_DATE_FORMAT=YYYY/MM/DD
```

The precedence of the property-setting methods is as follows:

1. Environment variable settings
2. `altibase.properties` file settings
3. Default system values

As can be seen in the following example, when properties are set, because environment variables take highest precedence, the value of `DEFAULT_DATE_FORMAT` in the `altibase.properties` file is ignored, and the value of the environment variable is used.

```
$ export ALTIBASE_DEFAULT_DATE_FORMAT=YYYY-MM-DD
DEFAULT_DATE_FORMAT=YYYY-MM-DD (altibase.properties)
```

Similarly, in the following example, `NLS_USE` in the `altibase.properties` file is ignored, and `UTF-8`, which is specified by the `NLS_USE` environment variable, is used, because environment variables have the highest priority.

```
$ export ALTIBASE_NLS_USE=UTF8
NLS_USE=KO16KSC5601 (altibase.properties)
```

Properties Overview

The property file for configuring the Altibase server is called "altibase.properties" and is located in the conf subdirectory of ALTIBASE_HOME. The properties therein are broadly grouped as follows:

- Database initialization properties
- Performance properties
- Session properties
- Transaction properties
- Backup and recovery properties
- Replication properties
- Network and security properties
- Message logging properties
- Database link properties
- Auditing properties
- C/C++ external procedure agent properties
- User account security properties
- Other properties

The following table lists all Altibase properties. For reference, each group in the table has the following meaning:

- D: Database initialization properties
- P: Performance properties
- S: Session properties
- T: Transaction properties
- B: Backup and recovery properties
- R: Replication properties
- NM: Network Management and security properties
- M: Message logging properties
- L: Database link properties
- U: Auditing properties
- A: C/C++ external procedure agent properties
- AS: Account Security properties
- E: Other properties

The values in the "Alter Level" column have the following meaning:

- SESSION: the property can be changed using an ALTER SESSION statement.
- SYSTEM: the property can be changed using an ALTER SYSTEM statement.

- BOTH: the property can be changed using either an ALTER SESSION or an ALTER SYSTEM statement
- NONE: Cannot be changed

Group	Class	Property Name	Alter Level
-------	-------	---------------	-------------

D		BUFFER_AREA_CHUNK_SIZE	
		BUFFER_AREA_SIZE	SYSTEM
		BUFFER_CHECKPOINT_LIST_CNT	
		BUFFER_FLUSHER_CNT	
		BUFFER_FLUSH_LIST_CNT	
		BUFFER_HASH_BUCKET_DENSITY	
		BUFFER_HASH_CHAIN_LATCH_DENSITY	
		BUFFER_LRU_LIST_CNT	
		BUFFER_PREPARE_LIST_CNT	
		COMPRESSION_RESOURCE_GC_SECOND	
		DB_NAME	
		DDL_SUPPLEMENTAL_LOG_ENABLE	SYSTEM
		DEFAULT_DISK_DB_DIR	
		DEFAULT_MEM_DB_FILE_SIZE	
		DEFAULT_SEGMENT_MANAGEMENT_TYPE	
		DEFAULT_SEGMENT_STORAGE_INITTEXTENTS	
		DEFAULT_SEGMENT_STORAGE_MAXEXTENTS	
		DEFAULT_SEGMENT_STORAGE_MINEXTENTS	
		DEFAULT_SEGMENT_STORAGE_NEXTTEXTENTS	
		DIRECT_PATH_BUFFER_PAGE_COUNT	SYSTEM
		DISK_INDEX_UNBALANCED_SPLIT_RATE	SYSTEM
		DISK_LOB_COLUMN_IN_ROW_SIZE	
		DISK_MAX_DB_SIZE	
		DOUBLE_WRITE_DIRECTORY	
		DOUBLE_WRITE_DIRECTORY_COUNT	
		DRDB_FD_MAX_COUNT_PER_DATAFILE	SYSTEM
		EXPAND_CHUNK_PAGE_COUNT	
		LOB_OBJECT_BUFFER_SIZE	
		LOCK_MGR_CACHE_NODE	
		LOCK_NODE_CACHE_COUNT	
		LOGANCHOR_DIR	

	LOG_DIR	
	LOG_FILE_SIZE	
	MAX_CLIENT	
	MEM_DB_DIR	
	MEM_MAX_DB_SIZE	
	MEMORY_INDEX_BUILD_RUN_SIZE	SYSTEM
	MEMORY_INDEX_BUILD_VALUE_LENGTH_THRESHOLD	SYSTEM
	MEMORY_INDEX_UNBALANCED_SPLIT_RATE	SYSTEM
	MEMORY_LOB_COLUMN_IN_ROW_SIZE	
	MEMORY_VARIABLE_COLUMN_IN_ROW_SIZE	
	MEM_SIZE_CLASS_COUNT	
	MIN_COMPRESSION_RESOURCE_COUNT	
	MIN_LOG_RECORD_SIZE_FOR_COMPRESS	SYSTEM
	MIN_PAGES_ON_DB_FREE_LIST	
	MIN_PAGES_ON_TABLE_FREE_LIST	SYSTEM
	MIN_TASK_COUNT_FOR_THREAD_LIVE	SYSTEM
	PCTFREE	
	PCTUSED	
	QP_MEMORY_CHUNK_SIZE	
	RECYCLEBIN_DISK_MAX_SIZE	SYSTEM
	RECYCLEBIN_ENABLE	SESSION
	RECYCLEBIN_MEM_MAX_SIZE	SYSTEM
	REDUCE_TEMP_MEMORY_ENABLE	SYSTEM
	SECURITY_ECC_POLICY_NAME	SYSTEM
	SECURITY_MODULE_LIBRARY	SYSTEM
	SECURITY_MODULE_NAME	SYSTEM
	SERVICE_THREAD_INITIAL_LIFESPAN	SYSTEM
	SMALL_TABLE_THRESHOLD	SYSTEM
	ST_OBJECT_BUFFER_SIZE	BOTH

		SYS_DATA_FILE_INIT_SIZE	
		SYS_DATA_FILE_MAX_SIZE	
		SYS_DATA_FILE_NEXT_SIZE	
		SYS_DATA_TBS_EXTENT_SIZE	
		SYS_TEMP_FILE_INIT_SIZE	
		SYS_TEMP_FILE_MAX_SIZE	
		SYS_TEMP_FILE_NEXT_SIZE	
		SYS_TEMP_TBS_EXTENT_SIZE	
		SYS_UNDO_FILE_INIT_SIZE	
		SYS_UNDO_FILE_MAX_SIZE	
		SYS_UNDO_FILE_NEXT_SIZE	
		SYS_UNDO_TBS_EXTENT_SIZE	
		TABLE_BACKUP_FILE_BUFFER_SIZE	
		TABLE_COMPACT_AT_SHUTDOWN	SYSTEM
		TEMP_HASH_BUCKET_DENSITY	
		TEMP_PAGE_CHUNK_COUNT	
		USER_DATA_FILE_INIT_SIZE	
		USER_DATA_FILE_MAX_SIZE	
		USER_DATA_FILE_NEXT_SIZE	
		USER_DATA_TBS_EXTENT_SIZE	
		USER_TEMP_FILE_INIT_SIZE	
		USER_TEMP_FILE_MAX_SIZE	
		USER_TEMP_FILE_NEXT_SIZE	
		USER_TEMP_TBS_EXTENT_SIZE	
		VOLATILE_MAX_DB_SIZE	

P		AGER_WAIT_MAXIMUM	
		AGER_WAIT_MINIMUM	
		BUFFER_VICTIM_SEARCH_INTERVAL	SYSTEM
		BUFFER_VICTIM_SEARCH_PCT	SYSTEM
		BULKIO_PAGE_COUNT_FOR_DIRECT_PATH_INSERT	SYSTEM
		CHECKPOINT_BULK_SYNC_PAGE_COUNT	SYSTEM
		CHECKPOINT_BULK_WRITE_PAGE_COUNT	SYSTEM
		CHECKPOINT_BULK_WRITE_SLEEP_SEC	SYSTEM
		CHECKPOINT_BULK_WRITE_SLEEP_USEC	SYSTEM
		CHECKPOINT_FLUSH_COUNT	SYSTEM
		CHECKPOINT_FLUSH_MAX_GAP	SYSTEM
		CHECKPOINT_FLUSH_MAX_WAIT_SEC	SYSTEM
		CM_BUFFER_MAX_PENDING_LIST	
		CM_DISPATCHER SOCK_POLL_TYPE	
		DATABASE_IO_TYPE	
		DATAFILE_WRITE_UNIT_SIZE	SYSTEM
		DB_FILE_MULTIPAGE_READ_COUNT	SYSTEM
		DEDICATED_THREAD_CHECK_INTERVAL	
		DEDICATED_THREAD_INIT_COUNT	
		DEDICATED_THREAD_MAX_COUNT	
		DEDICATED_THREAD_MODE	
		DEFAULT_FLUSHER_WAIT_SEC	SYSTEM
		DELAYED_FLUSH_LIST_PCT	SYSTEM
		DELAYED_FLUSH_PROTECTION_TIME_MSEC	SYSTEM
		DIRECT_IO_ENABLED	
		DISK_INDEX_BUILD_MERGE_PAGE_COUNT	SYSTEM
		EXECUTE_STMT_MEMORY_MAXIMUM	SYSTEM
		EXECUTOR_FAST_SIMPLE_QUERY	
		FAST_START_IO_TARGET	SYSTEM
		FAST_START_LOGFILE_TARGET	SYSTEM
		FAST_UNLOCK_LOG_ALLOC_MUTEX	

HASH_AREA_SIZE	SYSTEM
HASH_JOIN_MEM_TEMP_AUTO_BUCKET_COUNT_DISABLE	SYSTEM
HASH_JOIN_MEM_TEMP_PARTITIONING_DISABLE	SYSTEM
HIGH_FLUSH_PCT	SYSTEM
HOT_LIST_PCT	SYSTEM
HOT_TOUCH_CNT	SYSTEM
INDEX_BUILD_THREAD_COUNT	SYSTEM
INDEX_INITTRANS	
INDEX_MAXTRANS	
LFG_GROUP_COMMIT_INTERVAL_USEC	
LFG_GROUP_COMMIT_RETRY_USEC	
LFG_GROUP_COMMIT_UPDATE_TX_COUNT	
LOB_CACHE_THRESHOLD	BOTH
LOCK_ESCALATION_MEMORY_SIZE	SYSTEM
LOG_CREATE_METHOD	
LOG_IO_TYPE	
LOW_FLUSH_PCT	SYSTEM
LOW_PREPARE_PCT	SYSTEM
MATHEMATICS_TEMP_MEMORY_MAXIMUM	SYSTEM
MAX_FLUSHER_WAIT_SEC	SYSTEM
MEM_INDEX_KEY_REDISTRIBUTION	SYSTEM
MEM_INDEX_KEY_REDISTRIBUTION_STANDARD_RATE	SYSTEM
MULTIPLEXING_CHECK_INTERVAL	SYSTEM
MULTIPLEXING_MAX_THREAD_COUNT	SYSTEM
MULTIPLEXING_THREAD_COUNT	
NORMALFORM_MAXIMUM	BOTH
OPTIMIZER_AUTO_STATS	BOTH
OPTIMIZER_DELAYED_EXECUTION	SESSION
OPTIMIZER_FEATURE_ENABLE	SYSTEM
OPTIMIZER_MODE	BOTH
OPTIMIZER_PERFORMANCE_VIEW	

OPTIMIZER_UNNEST_AGGREGATION_SUBQUERY	SYSTEM
OPTIMIZER_UNNEST_COMPLEX_SUBQUERY	SYSTEM
OPTIMIZER_UNNEST_SUBQUERY	SYSTEM
OUTER_JOIN_OPERATOR_TRANSFORM_ENABLE	SYSTEM
PARALLEL_LOAD_FACTOR	
PARALLEL_QUERY_THREAD_MAX	SYSTEM
PARALLEL_QUERY_QUEUE_SIZE	SYSTEM
PREPARE_STMT_MEMORY_MAXIMUM	SYSTEM
QUERY_REWRITE_ENABLE	BOTH
REFINE_PAGE_COUNT	
RESULT_CACHE_ENABLE	BOTH
RESULT_CACHE_MEMORY_MAXIMUM	SYSTEM
SECONDARY_BUFFER_ENABLE	
SECONDARY_BUFFER_FILE_DIRECTORY	
SECONDARY_BUFFER_FLUSHER_CNT	
SECONDARY_BUFFER_SIZE	
SECONDARY_BUFFER_TYPE	
SORT_AREA_SIZE	SYSTEM
SQL_PLAN_CACHE_BUCKET_CNT	
SQL_PLAN_CACHE_HOT_REGION_LRU_RATIO	SYSTEM
SQL_PLAN_CACHE_PREPARED_EXECUTION_CONTEXT_CNT	SYSTEM
SQL_PLAN_CACHE_SIZE	SYSTEM
STATEMENT_LIST_PARTIAL_SCAN_COUNT	SYSTEM
TABLE_INITTRANS	
TABLE_LOCK_ENABLE	SYSTEM
TABLE_LOCK_MODE	
TABLE_MAXTRANS	
TABLESPACE_LOCK_ENABLE	BOTH
TEMP_MAX_PAGE_COUNT	SYSTEM
TEMP_STATS_WATCH_TIME	SYSTEM

		THREAD_CPU_AFFINITY	
		THREAD_REUSE_ENABLE	
		TIMED_STATISTICS	SYSTEM
		TIMER_RUNNING_LEVEL	
		TIMER_THREAD_RESOLUTION	SYSTEM
		TOP_RESULT_CACHE_MODE	BOTH
			SYSTEM
		TOUCH_TIME_INTERVAL	SYSTEM
		TRANSACTION_SEGMENT_COUNT	SYSTEM
		TRX_UPDATE_MAX_LOGSIZE	BOTH

S	Normal	CM_DISCONNECT_DETECT_TIME	
		CONCURRENT_EXEC_DEGREE_DEFAULT	SYSTEM
		CONCURRENT_EXEC_DEGREE_MAX	
		CONCURRENT_EXEC_WAIT_INTERVAL	SYSTEM
		DEFAULT_THREAD_STACK_SIZE	
		IPC_CHANNEL_COUNT	
		IPC_FILEPATH	
		IPCDATA_CHANNEL_COUNT	
		IPCDATA_DATABLOCK_SIZE	SYSTEM
		IPCDATA_FILEPATH	
		MAX_LISTEN	
		MAX_STATEMENTS_PER_SESSION	BOTH
		NET_CONN_IP_STACK	
		NLS_COMP	
		NLS_CURRENCY	SESSION
		NLS_ISO_CURRENCY	SESSION
		NLS_NCHAR_CONV_EXCP	SESSION
		NLS_NCHAR_LITERAL_REPLACE	SESSION
		NLS_NUMERIC_CHARACTERS	SESSION
		NLS_TERRITORY	SESSION
		PORT_NO	
		PSM_CURSOR_OPEN_LIMIT	SYSTEM
		PSM_FILE_OPEN_LIMIT	SYSTEM
		TIME_ZONE	SESSION
		UNIXDOMAIN_FILEPATH	
		USE_MEMORY_POOL	
		USER_LOCK_POOL_INIT_SIZE	SYSTEM
		USER_LOCK_REQUEST_CHECK_INTERVAL	SYSTEM
		USER_LOCK_REQUEST_LIMIT	SYSTEM
		USER_LOCK_REQUEST_TIMEOUT	SYSTEM
		XA_HEURISTIC_COMPLETE	

	Time-Out	BLOCK_ALL_TX_TIME_OUT	SYSTEM
		DDL_LOCK_TIMEOUT	SYSTEM
		DDL_TIMEOUT	BOTH
		FETCH_TIMEOUT	BOTH
		IDLE_TIMEOUT	BOTH
		LOGIN_TIMEOUT	SYSTEM
		MULTIPLEXING_POLL_TIMEOUT	SYSTEM
		QUERY_TIMEOUT	BOTH
		SHUTDOWN_IMMEDIATE_TIMEOUT	SYSTEM
		UTRANS_TIMEOUT	BOTH
		XA_INDOUBT_TX_TIMEOUT	
T		AUTO_COMMIT	SYSTEM
		ISOLATION_LEVEL	
		TRANSACTION_TABLE_SIZE	
B		ARCHIVE_DIR	
		ARCHIVE_FULL_ACTION	
		ARCHIVE_MULTIPLEX_COUNT	
		ARCHIVE_MULTIPLEX_DIR	
		ARCHIVE_THREAD_AUTOSTART	
		CHECKPOINT_ENABLED	
		CHECKPOINT_INTERVAL_IN_LOG	SYSTEM
		CHECKPOINT_INTERVAL_IN_SEC	SYSTEM
		COMMIT_WRITE_WAIT_MODE	BOTH
		INCREMENTAL_BACKUP_CHUNK_SIZE	
		INCREMENTAL_BACKUP_INFO_RETENTION_PERIOD	
		LOG_BUFFER_TYPE	
		LOG_MULTIPLEX_COUNT	
		LOG_MULTIPLEX_DIR	
		PREPARE_LOG_FILE_COUNT	
		SNAPSHOT_MEM_THRESHOLD	SYSTEM
		SNAPSHOT_DISK_UNDO_THRESHOLD	SYSTEM

R		REPLICATION_ACK_XLOG_COUNT	
		REPLICATION_ALLOW_DUPLICATE_HOSTS	SYSTEM
		REPLICATION_BEFORE_IMAGE_LOG_ENABLE	SYSTEM
		REPLICATION_COMMIT_WRITE_WAIT_MODE	SYSTEM
		REPLICATION_CONNECT_RECEIVE_TIMEOUT	SYSTEM
		REPLICATION_CONNECT_TIMEOUT	SYSTEM
		REPLICATION_DDL_ENABLE	SYSTEM
		REPLICATION_DDL_ENABLE_LEVEL	
		REPLICATION_DDL_SYNC	SYSTEM
		REPLICATION_DDL_SYNC_TIMEOUT	
		REPLICATION_EAGER_PARALLEL_FACTOR	
		REPLICATION_EAGER_RECEIVER_MAX_ERROR_COUNT	SYSTEM
		REPLICATION_FAILBACK_INCREMENTAL_SYNC	
		REPLICATION_GAP_UNIT	
		REPLICATION_GAPLESS_ALLOW_TIME	SYSTEM
		REPLICATION_GAPLESS_MAX_WAIT_TIME	SYSTEM
		REPLICATION_GROUPING_AHEAD_READ_NEXT_LOG_FILE	SYSTEM
		REPLICATION_GROUPING_TRANSACTION_MAX_COUNT	SYSTEM
		REPLICATION_HBT_DETECT_HIGHWATER_MARK	SYSTEM
		REPLICATION_HBT_DETECT_TIME	SYSTEM
		REPLICATION_IB_LATENCY	
		REPLICATION_IB_PORT_NO	
		REPLICATION_INSERT_REPLACE	SYSTEM
		REPLICATION_KEEP_ALIVE_CNT	
		REPLICATION_LOCK_TIMEOUT	SYSTEM
		REPLICATION_LOG_BUFFER_SIZE	
		REPLICATION_MAX_COUNT	
		REPLICATION_MAX_LISTEN	
		REPLICATION_MAX_LOGFILE	SYSTEM
		REPLICATION_POOL_ELEMENT_COUNT	SYSTEM
		REPLICATION_POOL_ELEMENT_SIZE	SYSTEM

	REPLICATION_PORT_NO	
	REPLICATION_RECEIVE_TIMEOUT	SYSTEM
	REPLICATION_RECEIVER_APPLIER_ASSIGN_MODE	SYSTEM
	REPLICATION_RECEIVER_APPLIER_QUEUE_SIZE	SYSTEM
	REPLICATION_PREFETCH_LOGFILE_COUNT	SYSTEM
	REPLICATION_RECOVERY_MAX_LOGFILE	
	REPLICATION_RECOVERY_MAX_TIME	
	REPLICATION_SENDER_AUTO_START	
	REPLICATION_SENDER_COMPRESS_XLOG	SYSTEM
	REPLICATION_SENDER_ENCRYPT_XLOG	
	REPLICATION_SENDER_SEND_TIMEOUT	SYSTEM
	REPLICATION_SENDER_SLEEP_TIME	
	REPLICATION_SENDER_SLEEP_TIMEOUT	SYSTEM
	REPLICATION_SENDER_START_AFTER_GIVING_UP	SYSTEM
	REPLICATION_SERVER_FAILBACK_MAX_TIME	
	REPLICATION_SQL_APPLY_ENABLE	
	REPLICATION_SYNC_APPLY_METHOD	SYSTEM
	REPLICATION_SYNC_LOCK_TIMEOUT	SYSTEM
	REPLICATION_SYNC_LOG	
	REPLICATION_SYNC_TUPLE_COUNT	SYSTEM
	REPLICATION_TIMESTAMP_RESOLUTION	SYSTEM
	REPLICATION_TRANSACTION_POOL_SIZE	SYSTEM
	REPLICATION_UPDATE_REPLACE	SYSTEM

NM		IB_CONCHKSPIN	
		IB_ENABLE	
		IB_LATENCY	
		IB_LISTEN_DISABLE	
		IB_MAX_LISTEN	
		IB_PORT_NO	SYSTEM
		SNMP_ALARM_QUERY_TIMEOUT	
		SNMP_ALARM_FETCH_TIMEOUT	
		SNMP_ALARM_UTRANS_TIMEOUT	
		SNMP_ALARM_SESSION_FAILURE_COUNT	
		SNMP_ENABLE	
		SNMP_MSGLOG_FLAG	SYSTEM
		SNMP_PORT_NO	
		SNMP_TRAP_PORT_NO	
		SNMP_RECV_TIMEOUT	
		SNMP_SEND_TIMEOUT	
		SSL_CA	
		SSL_CAPATH	
		SSL_CERT	
		SSL_CIPHER_LIST	
		SSL_CLIENT_AUTHENTICATION	
		SSL_ENABLE	
		SSL_KEY	
		SSL_MAX_LISTEN	
		SSL_PORT_NO	SYSTEM
		TCP_ENABLE	

M		ALL_MSGLOG_FLUSH	SYSTEM
		COLLECT_DUMP_INFO	SYSTEM
		DK_MSGLOG_COUNT	
		DK_MSGLOG_FILE	
		DK_MSGLOG_FLAG	SYSTEM
		DK_MSGLOG_RESERVE_SIZE	
		DK_MSGLOG_SIZE	
		DUMP_MSGLOG_COUNT	
		DUMP_MSGLOG_SIZE	
		DUMP_MSGLOG_RESERVE_SIZE	
		ERROR_MSGLOG_COUNT	
		ERROR_MSGLOG_FILE	
		ERROR_MSGLOG_SIZE	
		ERROR_MSGLOG_RESERVE_SIZE	
		LB_MSGLOG_COUNT	
		LB_MSGLOG_FILE	
		LB_MSGLOG_FLAG	
		LB_MSGLOG_SIZE	
		MM_MSGLOG_COUNT	
		MM_MSGLOG_FILE	
		MM_MSGLOG_RESERVE_SIZE	
		MM_MSGLOG_SIZE	
		MM_SESSION_LOGGING	SYSTEM
		NETWORK_ERROR_LOG	SYSTEM
		QP_MSGLOG_COUNT	
		QP_MSGLOG_FILE	
		QP_MSGLOG_FLAG	SYSTEM
		QP_MSGLOG_RESERVE_SIZE	
		QP_MSGLOG_SIZE	
		QUERY_PROF_FLAG	SYSTEM
		QUERY_PROF_LOG_DIR	SYSTEM

		RP_CONFLICT_MSGLOG_COUNT	
		RP_CONFLICT_MSGLOG_DIR	
		RP_CONFLICT_MSGLOG_ENABLE	
		RP_CONFLICT_MSGLOG_FILE	
		RP_CONFLICT_MSGLOG_FLAG	SYSTEM
		RP_CONFLICT_MSGLOG_SIZE	
		RP_MSGLOG_COUNT	
		RP_MSGLOG_FILE	
		RP_MSGLOG_FLAG	SYSTEM
		RP_MSGLOG_RESERVE_SIZE	
		RP_MSGLOG_SIZE	
		SERVER_MSGLOG_COUNT	
		SERVER_MSGLOG_DIR	
		SERVER_MSGLOG_FILE	
		SERVER_MSGLOG_FLAG	SYSTEM
		SERVER_MSGLOG_RESERVE_SIZE	
		SERVER_MSGLOG_SIZE	
		SM_MSGLOG_COUNT	
		SM_MSGLOG_FILE	
		SM_MSGLOG_FLAG	SYSTEM
		SM_MSGLOG_RESERVE_SIZE	
		SM_MSGLOG_SIZE	
		TRC_MSGLOG_RESERVE_SIZE	
		TRCLOG_DETAIL_PREDICATE	SYSTEM
		XA_MSGLOG_COUNT	
		XA_MSGLOG_FILE	
		XA_MSGLOG_FLAG	SYSTEM
		XA_MSGLOG_RESERVE_SIZE	
		XA_MSGLOG_SIZE	

L		DBLINK_ALTLINKER_CONNECT_TIMEOUT	
		DBLINK_DATA_BUFFER_ALLOC_RATIO	
		DBLINK_DATA_BUFFER_BLOCK_COUNT	
		DBLINK_DATA_BUFFER_BLOCK_SIZE	
		DBLINK_ENABLE	
		DBLINK_GLOBAL_TRANSACTION_LEVEL	
		DBLINK_RECOVERY_MAX_LOGFILE	SYSTEM
		DBLINK_REMOTE_STATEMENT_AUTOCOMMIT	BOTH
		DBLINK_REMOTE_TABLE_BUFFER_SIZE	
U		AUDIT_FILE_SIZE	SYSTEM
		AUDIT_LOG_DIR	SYSTEM
		AUDIT_OUTPUT_METHOD	SYSTEM
		AUDIT_TAG_NAME_IN_SYSLOG	SYSTEM
A		EXTPROC_AGENT_CONNECT_TIMEOUT	SYSTEM
		EXTPROC_AGENT_CALL_RETRY_COUNT	SYSTEM
		EXTPROC_AGENT_IDLE_TIMEOUT	SYSTEM
		EXTPROC_AGENT_SOCKET_FILEPATH	
AS		CASE_SENSITIVE_PASSWORD	SYSTEM
		FAILED_LOGIN_ATTEMPTS	
		PASSWORD_LOCK_TIME	
		PASSWORD_LIFE_TIME	
		PASSWORD_GRACE_TIME	
		PASSWORD_REUSE_TIME	
		PASSWORD_REUSE_MAX	
		PASSWORD_VERIFY_FUNCTION	

E		ACCESS_LIST	
		ACCESS_LIST_FILE	
		ADMIN_MODE	SYSTEM
		ARITHMETIC_OPERATION_MODE	SESSION
		CHECK_MUTEX_DURATION_TIME_ENABLE	SYSTEM
		COERCE_HOST_VAR_IN_SELECT_LIST_TO_VARCHAR	
		DEFAULT_DATE_FORMAT	
		EXEC_DDL_DISABLE	SYSTEM
		GROUP_CONCAT_PRECISION	SYSTEM
		JOB_SCHEDULER_ENABLE	SYSTEM
		JOB_THREAD_COUNT	
		JOB_THREAD_QUEUE_SIZE	
		MSG_QUEUE_PERMISSION	
		PSM_CHAR_DEFAULT_PRECISION	
		PSM_IGNORE_NO_DATA_FOUND_ERROR	SYSTEM
		PSM_NCHAR_UTF16_DEFAULT_PRECISION	
		PSM_NCHAR_UTF8_DEFAULT_PRECISION	
		PSM_NVARCHAR_UTF16_DEFAULT_PRECISION	
		PSM_NVARCHAR_UTF8_DEFAULT_PRECISION	
		PSM_PARAM_AND_RETURN_WITHOUT_PRECISION_ENABLE	
		PSM_VARCHAR_DEFAULT_PRECISION	
		QUERY_STACK_SIZE	BOTH
		RECURSION_LEVEL_MAXIMUM	SESSION
		REMOTE_SYSDBA_ENABLE	SYSTEM
		SELECT_HEADER_DISPLAY	BOTH
		SYS_CONNECT_BY_PATH_PRECISION	SYSTEM
		SERIAL_EXECUTE_MODE	BOTH

In this chapter, each property is explained as follows:

- Property name
- Data type
- Default value

- Attributes (e.g. read-only vs. read-write, single vs. multiple values)
- Range (maximum and minimum possible values)
- Description

Database Initialization Properties

BUFFER_AREA_CHUNK_SIZE (Unit: byte)

Data Type

Unsigned Long

Default Value

33554432 (32M)

Attributes

Read-Only, Single Value

Range

[8192, $2^{64}-1$]

Description

This indicates the unit, in bytes, by which the buffer size is incremented. When the buffer size is increased, it is increased in multiples of this number. This property can't be changed while the server is running.

BUFFER_AREA_SIZE (Unit: byte)

Data Type

Unsigned Long

Default Value

134217728 (128M)

Attributes

Read-Write, Single Value

Range

[$8 * 1024 * 10$, $2^{64}-1$]

Description

This indicates the total memory size, in bytes, used by the buffer pool of Altibase. The value specified by the user will be rounded up to the nearest multiple of BUFFER_AREA_CHUNK_SIZE. The size of the buffer pool is governed by the size of the page that can be used by a single transaction and the number of transactions executing at the same time. Therefore, when modifying the property that is related to the number of pages or the DISK_INDEX_BUILD_MERGE_PAGE_COUNT property, the BUFFER_AREA_SIZE property shouldn't be too small.

BUFFER_CHECKPOINT_LIST_CNT

Data Type

Unsigned Integer

Default Value

4

Attributes

Read-Only, Single Value

Range

[1, 64]

Description

This indicates the number of checkpoint lists. The greater the number of checkpoint lists, the less lock contention there is among transactions.

BUFFER_FLUSH_LIST_CNT

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[1, 64]

Description

This indicates the number of flush lists. The more flush lists there are, the less lock contention there is among transactions.

BUFFER_FLUSHER_CNT

Data Type

Unsigned Integer

Default Value

2

Attributes

Read-Only, Single Value

Range

[1, 16]

Description

This indicates the number of buffer flushers. This parameter can't be changed while the server is running.

BUFFER_HASH_BUCKET_DENSITY**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[1, 100]

Description

This indicates the percentage of BCBs (Buffer Control Blocks) that can be contained in one bucket. For example, when the number of BCBs is 100, if this value is set to 1, lock contention is minimized because the number of buckets is the same as the number of buffer frames in the buffer pool. If this value is set to 2, the number of buckets is half the number of frames, whereas if this value is set to 100, there is only one bucket. As this value is increased, less memory is used; however, operational costs increase because a single bucket will manage more buffer frames.

BUFFER_HASH_CHAIN_LATCH_DENSITY**Data type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[1, 100]

Description

This sets the percentage of buckets that correspond to each latch in a hash table. For example, when the number of buckets is 1000, if this value is 1, one latch corresponds to ten buckets. If this value is 2, twenty buckets share a single latch. If this value is 100, only one latch exists for the entire hash table

This property is used to control concurrency when inserting a BCB (Buffer Control Block) into a hash table or deleting it therefrom. The more latches there are, the less hash chain latch contention will occur.

BUFFER_LRU_LIST_CNT

Data Type

Unsigned Integer

Default Value

7

Attributes

Read-Only, Single Value

Range

[1, 64]

Description

This indicates the number of LRU lists. LRU list lock contention among transactions decreases as this value is increased.

BUFFER_PREPARE_LIST_CNT

Data Type

Unsigned Integer

Default Value

7

Attributes

Read-Only, Single Value

Range

[1, 64]

Description

This indicates the number of prepare lists. The greater this value is, the less prepare list lock contention there is among transactions.

BULKIO_PAGE_COUNT_FOR_DIRECT_PATH_INSERT (Unit: count)

Data Type

Unsigned Integer

Default Value

128

Attributes

Read-Write, Single Value

Range

[128, 12800]

Description

This property indicates how many pages can be simultaneously written to disk when entering data using direct-path INSERT.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

COMPRESSION_RESOURCE_GC_SECOND (Unit: second)**Data Type**

Unsigned Integer

Default Value

3600

Attributes

Read-Only, Single Value

Range[1, $(2^{64}-1)/1000000$]**Description**

This property specifies the amount of time, in seconds, that unused resources are retained in the log compression resource pool before they are discarded.

DB_NAME**Data Type**

String

Default Value

mydb

Attributes

Read-Only, Single Value

Range

None

Description

This indicates the database name. When a database is created, you must set the database name to the same value as the value in this property. A new database needs to be created in order to modify the database name.

DDL_SUPPLEMENTAL_LOG_ENABLE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property determines whether to add a log file when a DDL statement is executed. This property can be changed using the ALTER SYSTEM statement while Altibase is running.

0: Disabled (Do not add a log file)

1: Enabled (add a log file)

DEFAULT_DISK_DB_DIR**Data Type**

String

Default Value

\$ALTIBASE_HOME/dbs

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the directory in which to save the disk database files. This property must be set, even if the DRDBMS feature is not used. The default value is \$ALTIBASE_HOME/dbs.

DEFAULT_MEM_DB_FILE_SIZE (Unit: byte)**Data Type**

Unsigned Long

Default Value

1073741824 bytes (1G)

Attributes

Read-Only, Single Value

Range

[4194304 (4M), $2^{64}-1$]

Description

This property indicates the default checkpoint image file size, in bytes, for memory tablespaces.

DEFAULT_SEGMENT_MANAGEMENT_TYPE**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

None

Description

This indicates how segments are managed when creating disk tablespaces.

0: MANUAL –segments are created on the basis of a so-called "free list" method of managing available space in the user tablespace.

1: AUTO –segments are created on the basis of a bitmap index to manage available space in the user tablespace.

DEFAULT_SEGMENT_STORAGE_INITEXTENTS (Unit: count)**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

$[1, 2^{32}-1]$

Description

This sets the default number of extents that are initially allocated to a segment.

DEFAULT_SEGMENT_STORAGE_MAXEXTENTS (Unit: count)**Data Type**

Unsigned Integer

Default Value

$2^{32}-1$

Attributes

Read-Only, Single Value

Range

$[1, 2^{32}-1]$

Description

This sets the minimum number of extents that can be allocated to a segment.

DEFAULT_SEGMENT_STORAGE_MINEXTENTS (Unit: count)**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

$[1, 2^{32}-1]$

Description

This sets the minimum number of extents that can be allocated to a segment.

DEFAULT_SEGMENT_STORAGE_NEXTTEXTENTS (Unit: count)**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

$[1, 2^{32}-1]$

Description

This sets the number of extents that can be added to an existing segment.

DIRECT_PATH_BUFFER_PAGE_COUNT (Unit: count)**Data Type**

Unsigned Integer

Default Value

1024

Attributes

Read-Write, Single Value

Range

$[1024, 2^{32}-1]$

Description

This sets the number of pages in the direct-path INSERT buffer.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

DISK_INDEX_UNBALANCED_SPLIT_RATE (Unit: percentage)**Data Type**

Unsigned Integer

Default Value

90

Attributes

Read-Write, Single Value

Range

[50, 99]

Description

In a disk B+ tree index, when the last child node of a leaf node in the lowest rank is divided, this property specifies the ratio by which to divide keys between the node to be divided and the created node. When this value is set to 90, which is the default value, the key ratio between the 2 nodes is 90:10.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

DISK_LOB_COLUMN_IN_ROW_SIZE (Unit: bytes)**Data Type**

Unsigned Long

Default Value

4000

Attributes

Read-Only, Single Value

Range

[0,4000]

Description

This property sets the default column size, in bytes, when LOB type data are stored directly in disk tables. When data are entered into a LOB data type column, if the data length is smaller or the same as the value specified here, they are saved in table segment, whereas if the data are larger than this value, they are saved in a LOB segment. This property pertains only to disk tables, and has no effect on how memory tables are managed.

For more detailed information about LOB type data, please refer to Chapter1: Data Types.

DISK_MAX_DB_SIZE (Unit: byte)**Data Type**

Unsigned Long

Default Value $2^{64}-1$ **Attributes**

Read-Only, Single Value

Range

64bits: [2097152, 2⁶⁴]

Description

The maximum size (in bytes) Altibase allows to be set for a disk database.

When a database exceeds DISK_MAX_DB_SIZE, the transaction being executed fails as well as all subsequent SQL statements (except SELECTs)..

DOUBLE_WRITE_DIRECTORY**Data Type**

String

Default Value

None

Attributes

Read-Only, Multiple Values

Range

None

Description

This specifies the directory in which double-write files are saved. Multiple values can be saved for this property, according to the value specified in DOUBLE_WRITE_DIRECTORY_COUNT.

DOUBLE_WRITE_DIRECTORY_COUNT**Data Type**

Unsigned Integer

Default Value

2

Attributes

Read-Only, Single Value

Range

[1, 16]

Description

This specifies the number of directories in which double-write files are saved. Double write files can independently be saved on different disks. Because respective double-write files are used for each flusher, better flush performance can be realized when directories on different disks are specified.

DRDB_FD_MAX_COUNT_PER_DATAFILE**Data Type**

Unsigned Integer

Default Value

8

Attributes

Read-Write, Single Value

Range

[1, 1024]

Description

This property specifies the maximum number of FD (File Descriptors) that can be opened for I/O operations on a single disk data file. If the maximum number of FDs specified in this property has been opened, requests to open additional FDs will wait until previous I/O operations are completed.

EXPAND_CHUNK_PAGE_COUNT**Data Type**

Unsigned Integer

Default Value

128

Attributes

Read-Only, Single Value

Range[64, $2^{32}-1$]**Description**

This property specifies the number of pages by which to increase the size of the memory database. An Expand Chunk is a unit that can extend a page in a memory database. The user can set it when you create the database, and if you want to change the number of pages, you need to regenerate the database.

LOB_OBJECT_BUFFER_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

32000

Attributes

Read-Only, Single Value.

Range

[32000, 104857600]

Description

This property specifies the maximum size of the LOB data internally used by the Altibase server in order to process LOB values during the execution of stored procedures/functions or triggers that have parameters, internal variables or return values type declared as LOB.

LOCK_MGR_CACHE_NODE**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 2]

Description

This property specifies the cache type of a table lock node. It cannot be modified during the server operation.

0: It does not cache.

1: It caches with a linked list.

2: It caches with an array, and fixed with 64

LOCK_NODE_CACHE_COUNT (Unit: count)**Data Type**

Unsigned Integer

Default Value

2

Attributes

Read-Only, Single Value

Range

[0, 1024]

Description

This property specifies the number(Unit: count) of table lock nodes which will be cached if the case is LOCK_MGR_CACHE_NODE=1.

LOGANCHOR_DIR**Data Type**

String

Default Value

\$ALTIBASE_HOME/logs

Attributes

Read-Only, Multiple Values

Range

None

Description

This property specifies the pathnames for the log anchor files. There must be three log anchor file pathways. They are all set to the same default path.

LOG_DIR**Data Type**

String

Default Value

\$ALTIBASE_HOME/logs

Attributes

Read-Only, Multiple Values

Range

None

Description

This property specifies the pathname for log files

LOG_FILE_SIZE (Unit: byte)

Data Type

Unsigned long

Default Value

100 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[64 * 1024, 2³²-1]

Description

This property specifies the size, in bytes, of a log file. When an active log file fills up, writing continues in a new log file. This property can be set only when creating a database; it can't be changed afterwards. The user should create a new database in order to modify the log file size.

* Restriction

- In order to perform offline replication, this property must be set the same on the local (active) server and the remote (standby) server.

MAX_CLIENT

Data Type

Unsigned Integer

Default Value

1000

Attributes

Read-Only, Single Value

Range

[0, 65535]

However, if the value of JOB_THREAD_COUNT property is set to greater than 0, the maximum value is obtained by subtracting the value of the JOB_THREAD_COUNT property from 65535.

Description

This is used to specify the maximum number of clients which can be accessed to the Altibase.

MEM_DB_DIR

Data Type

String

Default Value

\$ALTIBASE_HOME/dbs

Attributes

Read-Only, Multiple Values

Range

None

Description

This property specifies the pathname for the memory database files.

It is possible to specify a minimum of 1 to a maximum of 8 paths. If multiple paths are specified, the database files are distributed among the paths. All of the paths specified using this property must be actual existing paths. The default number of paths is two, and they are both set to \$ALTIBASE_HOME/dbs.

MEM_MAX_DB_SIZE (Unit: byte)

Data Type

Unsigned Long

Default Value

2^{31}

Attributes

Read-Only, Single Value

Range

32-bit: [2097152, $2^{32}+1$]

64-bit: [2097152, 2^{64}]

Description

This property specifies the maximum size, in bytes, to which a memory database can dynamically increase while the server is running. The default value is 2GB for both 32-bit and 64-bit mode.

If a database expands to a size exceeding MEM_MAX_DB_SIZE, the offending transaction is treated as an error, and all subsequent SQL statements other than SELECT statements are also treated as errors.

MEMORY_INDEX_BUILD_RUN_SIZE (Unit: byte)**Data Type**

Unsigned Long

Default Value

131072

Attributes

Read-Write, Single Value

Range

$[1024, 2^{64}-1]$

Description

This sets the size, in bytes, of the in-memory sorting area for building memory indexes.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

MEMORY_INDEX_BUILD_VALUE_LENGTH_THRESHOLD (Unit: byte)**Data Type**

Unsigned Long

Default Value

64

Attributes

Read-Write, Single Value

Range

$[0, 2^{64}-1]$

Description

This property sets the maximum length, in bytes, of the key value used for intermediate sorting when building memory indexes. If the length of the key value is less than this value, the key value is used for intermediate sorting. If this property is set to 0, the index build thread uses a pointer to the record rather than this key value.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

MEMORY_INDEX_UNBALANCED_SPLIT_RATE (Unit: percentage)**Data Type**

Unsigned Integer

Default Value

50

Attributes

Read-Write, Single Value

Range

[50, 99]

Description

In a memory B+ tree index, when the last child node of a leaf node in the lowest rank is divided, the MEMORY_INDEX_UNBALANCED_SPLIT_RATE property sets the ratio by which to divide keys between the node to be divided and the created node.

When this value is set to 50, which is the default value, the key ratio between the 2 nodes is 50:50.

The user can change the value of the MEMORY_INDEX_UNBALANCED_SPLIT_RATE property using the ALTER SYSTEM statement while Altibase is running.

MEMORY_LOB_COLUMN_IN_ROW_SIZE (Unit: bytes)**Data Type**

Unsigned Long

Default Value

64

Attributes

Read-Only, Single Value

Range

[0,4000]

Description

This property sets the default column size, in bytes, when LOB type data are stored directly in memory tables.

When data are entered into a LOB data type column, if the data length is smaller or the same as the value specified here, they are saved in a fixed amount of area, whereas if the data are larger than this value, they are saved in a variable area. This property pertains only to memory tables, and has no effect on how disk tables are managed.

For more detailed information about LOB type data, please refer to Chapter1: Data Types.

MEMORY_VARIABLE_COLUMN_IN_ROW_SIZE (Unit: bytes)**Data Type**

Unsigned Long

Default Value

32

Attributes

Read-Write, Single Value

Range

[0,4000]

Description

This property sets the default column size, in bytes, when the variable type data are stored directly in memory tables. When data are entered into the variable type column, if the data length is smaller or the same as the value specified here, they are saved in a fixed amount of area, whereas if the data are larger than this value, they are saved in a variable area. This property pertains only to memory tables, and has no effect on how disk tables are managed.

For more detailed information about the IN ROW clause, please refer to Chapter1: Data Types.

MEM_SIZE_CLASS_COUNT (Unit: count)**Data Type**

Unsigned Integer

Default

4

Attributes

Read-Only, Single Value

Range

[1, 4]

Description

This property determines the number of categories into which memory pages are classified based on the amount of free space in them.

MIN_COMPRESSION_RESOURCE_COUNT (Unit: counts)**Data Type**

unsigned integer

Default Value

16

Attributes

Read-Only, Single value

Range

[1, 16384]

Description

This property indicates the minimum number of buffer chunks used by the log manager for log compression. (One compression buffer chunk is about 16kB.)

MIN_LOG_RECORD_SIZE_FOR_COMPRESS (Unit: bytes)**Data Type**

Unsigned Integer

Default Value

512

Attributes

Read-Write, Single Value

Range[0, $2^{32}-1$]**Description**

This property specifies the log size, in bytes, that is used to determine whether to compress logs. When this property is set to 0, logs are never compressed. If the size of a log exceeds the size specified here, logs will be compressed.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

MIN_PAGES_ON_DB_FREE_LIST**Data Typer**

Unsigned Integer

Default Value

16

Attributes

Read-Only, Single Value

Range[1, $2^{32}-1$]**Description**

This property specifies the minimum number of free pages that must be available on each list of free pages. These pages are allocated to table free lists as required.

MIN_PAGES_ON_TABLE_FREE_LIST**Data Type**

Unsigned Integer

Default

1

Attributes

Read-Write, Single Value

Range

[1, $2^{32}-1$]

Description

This property specifies the minimum number of free pages that each table must maintain on its own list of free pages.

MIN_TASK_COUNT_FOR_THREAD_LIVE**Data Type**

Unsigned Integer

Default value

1

Attributes

Read-Write, Single Value

Range

[1, 1024]

Description

This property specifies the minimum number of clients a service thread is to be allocated in order to avoid being destroyed. If the number of clients a service thread is allocated is smaller than the value of this property, instead of being destroyed immediately, it is put in standby mode for a given time. If the number of clients allocated to the service thread on standby within the time limit set for the SERVICE_THREAD_INITIAL_LIFESPAN property is smaller than the value set for the MIN_TASK_COUNT_FOR_THREAD_LIVE property, the service thread is destroyed.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

PCTFREE (Unit: Percentage)

Data Type

Unsigned Integer

Default Value

10

Attributes

Read-Only, Single Value

Range

[0, 99]

Description

This property indicates the minimum percentage of space to keep free in each page for the insertion of data. The value specified by PCTFREE indicates the percentage of space that is kept free in order to allow existing records to be updated.

If the total size of the tablespace is 100MB and the value of PCTFREE is 10, up to 90MB of data, or data equivalent in size to 90% of the total space, can be inserted.

If the value of PCTFREE is not set using a CREATE TABLE statement when a disk table is created, the default value is used.

PCTUSED

Data Type

Unsigned Integer

Default Value

40

Attributes

Read-Only, Single Value

Range

[0, 99]

Description

The PCTUSED property is the minimum percentage of used space for reinsertion when Altibase can only update record. This property indicates the amount of space that is used to convert the state of a tablespace page from one on which only updates can be performed to one on which insert operations can also be performed.

When enough data have been entered that the amount of used page space reaches the value specified in PCTFREE, only update operations can be performed. In this state, if the amount of used space falls below the value of PCTUSED due to update and delete operations, new records can be inserted.

If the value of PCTUSED is not explicitly set using a CREATE TABLE statement when a disk table is created, the default value is used.

QP_MEMORY_CHUNK_SIZE (Unit: byte)

Data Type

Unsigned long

Default Value

65536

Attributes

Read-Only, Single Value

Range

[1024, $2^{64}-1$]

Description

This property specifies the number of additional bytes allocated by the system each time the Query Processor requires additional memory.

RECYCLEBIN_DISK_MAX_SIZE (Unit: byte)

Data Type

Unsigned Long

Default Value

$2^{64}-1$

Attributes

Read-Only, Single Value

Range

[0, $2^{64}-1$]

Description

Specifies the size of the recycle bin (in bytes) to which disk tables are moved.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

RECYCLEBIN_ENABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

When a table is dropped with the DROP statement, RECYCLEBIN_ENABLE specifies whether a table is to be moved to a recycle bin or dropped directly from the database system.

If the recycle bin contains a table, the table can be queried or recovered/dropped with the FLASHBACK or PURGE statement, even if the value of this property is altered to 0.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

0 : Disable(default) - The table is dropped from the database.

1 : Enable - The table is moved to the recycle bin.

RECYCLEBIN_MEM_MAX_SIZE (Unit: byte)**Data Type**

Unsigned Long

Default Value

4 GB

Attributes

Read-Write, Single Value

Range[0, $2^{64}-1$]**Description**

Specifies the size of the recycle bin to which memory tables are dropped. The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

REDUCE_TEMP_MEMORY_ENABLE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property can minimize the space occupied by data of variable-length columns, when the data is temporarily stored in the memory tablespace.

The disk temporary tablespace is where the Altibase server temporarily stores intermediate results by default, when processing queries on disk tables or views. To enhance performance, intermediate results can be stored in the memory tablespace, using the TEMP_TBS_MEMORY hint (please refer to Administrator's Manual and *Performance Tuning Guide*).

The default value 0 can occupy unnecessary space, due to data of variable-length columns using temporary storage space of a fixed length, as data of fixed-length columns do. To reduce such waste of space, this property can be set to 1 and only as much space as the actual data of the variable-length column is used. While memory usage is smaller, however, the speed of query processing can slow down.

0: The variable-length columns use as much temporary storage space as the length defined.

1: The variable-length columns use as much temporary storage space as the actual data.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

SECURITY_ECC_POLICY_NAME**Data Type**

String

Default Value

None

Attributes

Read-Write, Single Value

Range

None

Description

This property indicates the name of the ECC (Encrypted Comparison Code) algorithm used when you run the security module for the encrypted columns.

SECURITY_MODULE_LIBRARY

Data Type

String

Default value

None

Attributes

Read-Write, Single Value

Range

None

Description

This property indicates the library file name of the security module, and is used when you perform the security module.

SECURITY_MODULE_NAME

Data Type

String

Default Value

None

Attributes

Read-Write, Single Value

Range

None

Description

This property indicates the name of the security module, and is used when you perform the security module.

SERVICE_THREAD_INITIAL_LIFESPAN

Data Type

Unsigned Integer

Default Value

6000

Attributes

Read-Write, Single Value

Range[30, $2^{32}-1$]**Description**

This property specifies the number of times necessary for the thread manager to check the status of standby service threads, in order to destroy the threads. If the standby service threads are not allocated a client for the number of times the thread manager has set for this property, they are destroyed.

Service threads are placed on standby when they are allocated a smaller number of clients than the value set for the MIN_TASK_COUNT_FOR_THREAD_LIVE property.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

SMALL_TABLE_THRESHOLD**Data Type**

Unsigned Integer

Default Value

128

Attributes

Read-Write, Single Value

Range[0, $2^{32}-1$]**Description**

When a full scan is performed on a disk table, if the number of pages in the table is equal to or less than the number specified in this property, the pages that have been read from disk to a buffer all at one time will remain in the buffer after the full scan. If the number of pages in the table is greater than the number specified here, the pages will not remain in the buffer.

If this property is set to 0, no pages will be maintained in buffers regardless of the number of pages in the table.

If this property is set to the maximum value, which is $2^{32}-1$, pages will always remain in buffers, regardless of the number of pages in a table.

ST_OBJECT_BUFFER_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

32000 (32KByte)

Properties

Read-Write, Single Value

Range

[32000, 104857600]

Description

This sets the maximum size, in bytes, of a single geometry object.

SYS_DATA_FILE_INIT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default

100M (100 * 1024 * 1024)

Attributes

Read-Only, Single Value

Range

[8*8K, 32GB]

Description

This specifies the initial size, in bytes, of the data file (system001.dbf) when SYS_TBS_DISK_DATA (system disk tablespace) is created. Moreover, if the initial size is not specified when a data file (that is, a user-specified file other than system001.dbf) is added to SYS_TBS_DISK_DATA, the initial size of that data file also defaults to the value specified here.

SYS_DATA_FILE_MAX_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

2 * 1024 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[8 * 8K, 32GB]

Description

This property specifies the maximum size, in bytes, of the allocated data file when SYS_TBS_DISK_DATA (system disk tablespace) is created. It must be equal to or greater than the value of SYS_DATA_FILE_INIT_SIZE. The minimum possible value is 64kB.

Moreover, if no maximum value is set when data files are added to SYS_TBS_DISK_DATA (system disk tablespace), the value specified here will be taken for SYS_DATA_FILE_MAX_SIZE.

SYS_DATA_FILE_NEXT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

1 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[8 * 8K, 32GB]

Description

When the autoextend property of the system disk tablespace (SYS_TBS_DISK_DATA) is set to “autoextend on”, data files are automatically incremented in size by the number of bytes specified here in order to accommodate increased amounts of data.

If the size of a data file reaches the value specified in SYS_DATA_FILE_MAX_SIZE , and additionally the amount of valid space in other data files is less than that specified in SYS_DATA_FILE_NEXT_SIZE, an insufficient tablespace error will be raised.

SYS_DATA_TBS_EXTENT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

512 * 1024

Attributes

Read-Only, Single Value

Range

[40K, 32G]

Description

This specifies the size, in bytes, of an extent when SYS_TBS_DISK_DATA (system disk tablespace¹) is created . In order for an extent to contain at least 5 pages, the minimum value of this property is 40kB (5*8kB)².

[¹] System Disk Data Tablespace:

This is the disk tablespace that is created by default when a database is created. The disk table and disk index are the only database objects that are saved.

[²] The initial extent size cannot be changed after the database has been created. The default value is 32 pages.

SYS_TEMP_FILE_INIT_SIZE (Unit: byte)

Data Type

Unsigned long

Default Value

100M (100 * 1024 * 1024)

Attributes

Read-Only, Single Value

Range

[8 * 8kB, 32GB]

Description

This specifies the initial size, in bytes, of the temporary data file (temp001.dbf) when SYS_TBS_DISK_TEMP is created. Moreover, if the initial size is not specified when a temporary data file is added to SYS_TBS_DISK_TEMP, the value specified here is used.

SYS_TEMP_FILE_MAX_SIZE (Unit: byte)

Data Type

Unsigned long

Default Value

2 * 1024 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[8 * 8K, 32GB]

Description

This specifies the maximum size, in bytes, of the data file (temp001.dbf) that is allocated when SYS_TBS_DISK_TEMP is created.

The value of this property must be at least as great as that of SYS_TEMP_FILE_INIT_SIZE. The minimum possible value is 64kB. Moreover, if the maximum size is not specified when a temporary data file is added to SYS_TBS_DISK_TEMP, the size specified here is the default maximum size.

SYS_TEMP_FILE_NEXT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

$1 * 1024 * 1024$

Attributes

Read-Only, Single Value

Range

[8 * 8kB, 32GB]

Description

If there is not enough space in a data file in the SYS_TBS_DISK_TEMP tablespace, the size of the file is increased by the amount specified here.

SYS_TEMP_TBS_EXTENT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

$256 * 1024$

Attributes

Read-Only, Single Value

Range

[40kB, 32GB]

Description

This specifies the size, in bytes, of an extent when the SYS_TBS_DISK_TEMP (system disk temporary tablespace)³ is created.

It must be large enough to contain at least five pages (40kB = 5 * 8kB).

[³] System disk temporary tablespace:

This is automatically created by default when a database is created, and is a tablespace for temporary storage related to various kinds of database operations. It is set as the default temporary tablespace for storing objects on disk for all users. The only database objects that are stored here are disk tables and disk indexes.

SYS_UNDO_FILE_INIT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

100 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[32 * 8kB, 32GB]

Description

This specifies the default size, in bytes, of the data file (undo001.dbf) when the SYS_TBS_DISK_UNDO tablespace is created. Additionally, when a data file is added to SYS_TBS_DISK_UNDO without specifying its initial size, the size specified here is used.

SYS_UNDO_FILE_MAX_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

2 * 1024 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[32 * 8kB, 32GB]

Description

This specifies the maximum size, in bytes, of the data file (undo001.dbf) that is allocated when the SYS_TBS_DISK_UNDO is created.

The value of this property must be at least as great as that of SYS_UNDO_FILE_INIT_SIZE. The minimum possible value is 256kB. Moreover, if the maximum size is not specified when a temporary data file is added to SYS_TBS_DISK_UNDO, the value specified here is used as the default maximum size.

SYS_UNDO_FILE_NEXT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

1 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[8 * 8kB, 32GB]

Description

When there is not enough space in the SYS_TBS_DISK_UNDO tablespace data file, the size of the data file is incremented by the number of bytes specified here.

SYS_UNDO_TBS_EXTENT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

256 * 1024

Attributes

Read-Only, Single Value

Range

[40kB, 32GB]

Description

This specifies the size, in bytes, of an extent when SYS_TBS_DISK_UNDO (system disk undo ⁴ is created.

[⁴] System disk undo tablespace):

This is automatically created by default when a database is created, and is used only for saving undo information. Only one system disk undo tablespace exists in a database. The user cannot create or delete tables, indexes, or anything else in the system disk undo tablespace.

TABLE_BACKUP_FILE_BUFFER_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

1024

Attributes

Read-Only, Single Value

Range

[0, 1048576]

Description

This property specifies the table backup buffer size, in bytes, for use when using the ALTER TABLE command to add or delete columns to or from memory tables.

TABLE_COMPACT_AT_SHUTDOWN**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property indicates whether to compact tables when you shut down the database. It is recommended to specify this property as 1 to reduce memory consumption of tables when you restart the database.

TEMP_HASH_BUCKET_DENSITY**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[1, 50]

Description

This specifies as a percentage the number of page frames of a temporary table one hash bucket is to manage. As this value increases, less memory is used as the number of necessary hash buckets decreases; however, operational costs increase since the number of temporary page frames to be managed per bucket increases.

For example, when the number of temporary page frames is 100 and this value is set to 1, the number of buckets and frames are the same. If this value is set to 2, the number of buckets is 50, half the number of frames, whereas if this value is set to 100, there is only one bucket.

TEMP_PAGE_CHUNK_COUNT

Data Type

Unsigned Integer

Default Value

128

Attributes

Read-Only, Single Value

Range

$[1, 2^{32}-1]$

Description

This property indicates the number of temporary data pages that can be allocated at one time.

USER_DATA_FILE_INIT_SIZE (Unit: byte)

Data Type

Unsigned long

Default Value

$100 * 1024 * 1024$

Attributes

Read-Only, Single Value

Range

$[8 * 8\text{KB}, 32\text{GB}]$

Description

This property sets the initial size, in bytes, of a user-defined data file that is created or added to a user disk data tablespace. The default value specified here is used if no initial size is specified.

USER_DATA_FILE_MAX_SIZE (Unit: byte)

Data Type

Unsigned long

Default Value

$2 * 1024 * 1024 * 1024$

Attributes

Read-Only, Single Value

Range

[8 * 8kB, 32GB]

Description

This sets the maximum size, in bytes, of a user-defined data file that is created or added to a user disk data tablespace.

The value of this property should be at least as big as that specified in `USER_DATA_FILE_INIT_SIZE`. The minimum possible value is 64kB. If no maximum size is specified when a data file is created or added, the default value specified here is used.

USER_DATA_FILE_NEXT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

1 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[8 * 8kB, 32GB]

Description

If the data file in the user-defined data file of the user disk data tablespace lacks space, the data file size is increased as specified for this property.

USER_DATA_TBS_EXTENT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

512 * 1024

Attributes

Read-Only, Single Value

Range

[2 * 8kB, 2⁶⁴-1]

Description

This specifies the size, in bytes, of an extent when a user disk data tablespace⁵ is created.

[⁵] User disk data tablespace:

This is a tablespace for storing user objects. Only disk tables and disk indexes are stored among database objects.

USER_TEMP_FILE_INIT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

100 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[8 * 8kB, 32GB]

Description

This specifies the initial size, in bytes, of a data file when a user-defined temporary data file is created or added to a user temporary tablespace. If no initial size is specified, the default value specified here is used.

USER_TEMP_FILE_MAX_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

2 * 1024 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[8 * 8kB, 32GB]

Description

This property limits the maximum size, in bytes, of user-defined temporary data files that are created in or added to a user temporary tablespace.

This parameter must be at least as great as USER_DATA_FILE_INIT_SIZE. The minimum possible value is 64kB. If no maximum size is specified when temporary data files are created or added, the default value specified here is used.

USER_TEMP_FILE_NEXT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

$1 * 1024 * 1024$

Attributes

Read-Only, Single value

Range

$[8 * 8\text{kB}, 32\text{GB}]$

Description

If there is insufficient space in a user-defined temporary data file in a user temporary tablespace, the size of the data file is increased by the number of bytes specified here.

USER_TEMP_TBS_EXTENT_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

$256 * 1024$

Attributes

Read-Only, Single Value

Range

$[2 * 8\text{kB}, 2^{64}-1]$

Description

This specifies the size, in bytes, of an extent when a user temporary tablespace is created. It must be at least 2 pages ($16\text{kB} = 2 * 8\text{kB}$).

VOLATILE_MAX_DB_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

$2^{32}+1$

Attributes

Read-Only, Single Value

Range

32 bits: [2097152, $2^{32}+1$]

64 bits: [2097152, 2^{64}]

Description

This property specifies the maximum size, in bytes, of volatile tablespaces.

Performance Properties**AGER_WAIT_MAXIMUM (Unit: microsecond)****Data Type**

Unsigned Integer

Default Value

1000000

Attributes

Read-Only, Single Value

Range

[0, $2^{32}-1$]

Description

This property specifies the maximum waiting time, in microseconds, of the garbage collector (also known as the "Ager").

This property is intended to prevent deterioration in performance (especially in HP systems) resulting from excessive "sleep" system calls by threads related to the garbage collector while the garbage collector is asleep. This parameter allows the maximum sleep time of the garbage collector to be suitably regulated while the server is running.

AGER_WAIT_MINIMUM (Unit: microsecond)**Data Type**

Unsigned Integer

Default Value

200000

Attributes

Read-Only, Single Value

Range[0, 2³²-1]**Description**

This property specifies the minimum waiting time, in microseconds, of the garbage collector (also known as the “Ager”).

This property is intended to prevent deterioration in performance (especially in HP systems) resulting from excessive “sleep” system calls by threads related to the garbage collector while the garbage collector is asleep. This parameter allows the minimum sleep time of the garbage collector to be suitably regulated while the server is running.

BUFFER_VICTIM_SEARCH_INTERVAL (Unit: millisecond)**Data Type**

Unsigned Integer

Default Value

3000

Attributes

Read-Write, Single Value

Range

[0, 86400000]

Description

After a search for a replacement BCB (“victim”) fails, this property specifies the amount of time, in milliseconds, to wait for the flusher to flush dirty buffer frames before searching again for a victim.

If, as the result of the subsequent search, a replacement BCB still cannot be found, the value of VICTIM_SEARCH_WARP in the V\$BUFFPOOL_STAT performance view is increased.

BUFFER_VICTIM_SEARCH_PCT(Unit: Percentage)**Data Type**

Unsigned Integer

Default Value

5

Attributes

Read-Write, Single Value

Range

[0, 100]

Description

This property sets how much to explore when searching for replacement buffers in an LRU list. In other words, this property indicates the percentage of an LRU list that is searched, with the least recently accessed records searched first. A value of 100 indicates that the entire list is searched.

CHECKPOINT_BULK_SYNC_PAGE_COUNT (Unit: page count)**Data Type**

Unsigned Integer

Default Value

3200

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

When performing checkpointing between memory and disk tables, this property sets the number of pages that are synchronized at one time.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

CHECKPOINT_BULK_WRITE_PAGE_COUNT (Unit: count)**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

When checkpointing, a given number of dirty pages can be separated and saved to disk. When this happens, this property specifies the number of dirty pages that are saved to disk at one time. If this is set to 0, all of the dirty pages are saved to the disk database at one time.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

CHECKPOINT_BULK_WRITE_SLEEP_SEC (Unit: second)**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 2592000]

Description

This property specifies the amount of time to wait (in seconds) after saving dirty pages to disk if the value of CHECKPOINT_BULK_WRITE_PAGE_COUNT is not set to 0.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

CHECKPOINT_BULK_WRITE_SLEEP_USEC (Unit: microsecond)**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 60000000]

Description

This property specifies the amount of time to wait (in microseconds) after saving dirty pages to disk if the value of CHECKPOINT_BULK_WRITE_PAGE_COUNT is not set to 0.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

CHECKPOINT_FLUSH_COUNT (Unit: frame count)**Data Type**

Unsigned Integer

Default Value

64

Attributes

Read-Write, Single Value

Range

$[1, 2^{64}-1]$

Description

This property specifies the number of buffer pages (frames) that can be flushed in one flusher cycle when checkpoint flushing.

CHECKPOINT_FLUSH_MAX_GAP (Unit: log files count)**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This is one of the conditions for conducting checkpoint processing. Checkpoint flushing is performed when the number of logfiles between the most recent LSN (Log Sequence Number) and the earliest LSN reaches this value.

This property influences the recovery time when the server is restarted. Greater values mean that checkpoint processing is performed less often, and that it takes more time for the server to recover when restarted.

CHECKPOINT_FLUSH_MAX_WAIT_SEC (Unit: second)**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This is one of the conditions for conducting checkpoint processing. Checkpoint flushing is performed when the number of seconds specified by this property has passed since the most recent flush.

CM_BUFFER_MAX_PENDING_LIST**Data Type**

Unsigned Integer

Default Value

512

Attributes

Read-Only, Single Value

Range

[1, 512]

Description

In order to prevent sudden increases in memory usage, this property specifies the maximum number of communication buffer blocks that can be allocated in one session.

CM_DISPATCHER_SOCK_POLL_TYPE**Data Type**

Unsigned Integer

Default Value

3

Attribute

Read-Only, Single Value

Range

[1, 2, 3]

Description

This property enables the Altibase dispatcher to select the system call for detecting sockets. If there are more than 1,000 concurrent client connections, using the POLL() system call helps improve performance.

- 1: SELECT() system call
- 2: POLL() system call; available for use only on supported operating systems
- 3: EPOLL() system call; available for use only on supported operating systems

DATABASE_IO_TYPE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

Altibase provides two disk I/O methods related to database files:

- Direct I/O
- Buffered I/O

To use direct I/O, set this parameter to 1, or to use buffered I/O, set it to 0.

The advantage of Direct I/O is that it reduces CPU resources during the occurrence of Disk I/O. On the other hand, since buffered I/O uses the read-ahead and asynchronous write techniques, it does not necessarily incur disk access every time disk I/O is requested. This means that buffered I/O can realize better performance than direct I/O from the aspect of client applications; however, buffered I/O consumes more CPU resources than direct I/O.

DATAFILE_WRITE_UNIT_SIZE (Unit: count)

Data Type

Unsigned Long

Default Value

1024

Attributes

Read-Write, Single Value

Range

[1, 1024]

Description

This property specifies the default data unit size when a data file is created.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

DB_FILE_MULTIPAGE_READ_COUNT**Data Type**

Unsigned Integer

Default Value

8

Attributes

Read-Write, Single Value

Range

[1, 128]

Description

This property determines the number of pages to read at a time when a full scan is performed on a disk table.

At this time, if a disk table's extent size, that is, the number of pages in the extent, is a multiple of (and greater than) the value specified here, Multiple Page Read (MPR) is conducted. However, if the extent size is not a multiple of, or is smaller than, the value specified here, Single Page Read (SPR) is conducted.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

DEDICATED_THREAD_CHECK_INTERVAL (Unit: second)**Data Type**

Unsigned Integer

Default Value

3600

Attributes

Read-Only, Single Value

Range

[0, $2^{64}-1$]

Description

This property specifies the time interval at which to terminate service threads in dedicated thread mode. This property is only valid if the value of the DEDICATED_THREAD_MODE property is 1.

Idle service threads are terminated at the time interval set in this property; however, the number of service threads specified in the DEDICATED_THREAD_INIT_COUNT property is maintained.

Service threads are not terminated if this property is set to 0.

DEDICATED_THREAD_INIT_COUNT

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 65535]

Description

This property specifies the number of initial service threads to be created in dedicated thread mode. This property is only valid if the value of the DEDICATED_THREAD_MODE property is 1.

The value of the DEDICATED_THREAD_INIT_COUNT property must be smaller than the value set in the DEDICATED_THREAD_MAX_COUNT property.

DEDICATED_THREAD_MAX_COUNT

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 65535]

Description

This property specifies the maximum number of service threads to be created in dedicated thread mode. This property is only valid if the value of the DEDICATED_THREAD_MODE property is 1.

If all of the initial service threads created are allocated to clients, the number of service threads can increase up to the value of the DEDICATED_THREAD_MAX_COUNT property.

The value of the DEDICATED_THREAD_MAX_COUNT property must be smaller than the value set in the MAX_CLIENT property.

DEDICATED_THREAD_MODE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property specifies whether or not service threads are to be run in dedicated thread mode for clients.

- 1: Service threads run in dedicated mode
- 0: Service threads run in multiplexing mode

DEFAULT_FLUSHER_WAIT_SEC (Unit: second)

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[1, 2³²-1]

Description

This property sets the minimum number of seconds that the flusher waits. As long as there are no special conditions, flushing is always conducted after waiting this amount of time. The wait time is repeatedly incremented 1 second at a time if the flusher is removed from the queue or doesn't perform any flushing work.

DELAYED_FLUSH_LIST_PCT (Unit: percentage)

Data Type

Unsigned Integer

Default Value

30

Attributes

Read-Write, Single Value

Range

[0, 100]

Description

This property specifies the maximum rate of the delayed flush list. This property can be changed using the ALTER SYSTEM statement while the server is running.

DELAYED_FLUSH_PROTECTION_TIME_MSEC (Unit: millisecond)**Data Type**

Unsigned Integer

Default Value

100

Attributes

Read-Write, Single Value

Range

[0, 100000]

Description

This property indicates the reference time to determine the last used page. If the last used time is below the set value, it is judged to be the last used page. This property can be changed using the ALTER SYSTEM statement while the server is running.

DIRECT_IO_ENABLED**Data Types**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property indicates whether database I/O can be performed via direct disk access.

0: Disable

1: Enable

DISK_INDEX_BUILD_MERGE_PAGE_COUNT (Unit: page count)**Data Type**

Unsigned Integer

Default Value

128

Attributes

Read-Write, Single Value

Range

$[2, 2^{32}-1]$

Description

When a disk index is created, if the keys extracted from data cannot all be sorted in memory at the same time, this property specifies the number of pages to be used for external sorting.

This property can be changed using the ALTER SYSTEM statement during system operation.

EXECUTE_STMT_MEMORY_MAXIMUM (Unit: byte)**Data Type**

Unsigned Long

Default Value

1G

Attributes

Read-Write, Single Value

Range

$[1024*1024, 2^{64}-1]$

Description

This property limits the number of bytes of memory that can be used to execute a single query statement.

This property can be changed using the ALTER SYSTEM statement during system operation.

EXECUTOR_FAST_SIMPLE_QUERY**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 2]

Description

This property prints a simple query plan; it optimizes the execution plan of simple DML statements or statements that use nested loop joins for faster performance.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

0: Uses the SIMPLE QUERY PLAN.

1: Uses the SIMPLE QUERY PLAN on a memory table.

2: Uses the SIMPLE QUERY PLAN on a partition table.

FAST_START_IO_TARGET (Unit: page count)**Data Type**

Unsigned Long

Default Value

10000

Attributes

Read-Write, Single Value

Range

[1, $2^{64}-1$]

Description

This property indicates the number of redo pages that the server reads when performing recovery after being restarted.

When the flusher performs checkpoint flushing while the system is running, if the number of dirty pages remaining in the buffer is greater than the value saved in this property, the oldest dirty pages, equal in number to the difference there between, are written to disk.

This value is important in determining the recovery time when the server is restarted. Because the number of pages to be flushed increases as this value is decreased, the recovery time when the server is restarted can be reduced.

The value of this property can be changed using the ALTER SYSTEM statement while the server is running.

FAST_START_LOGFILE_TARGET (Unit: log file count)

Data Type

Unsigned Integer

Default Value

100

Attributes

Read-Write, Single Value

Range

[1, $2^{32}-1$]

Description

This property indicates the number of log files that the server reads when performing recovery after being restarted.

When the flusher performs checkpoint flushing while the server is running, if the difference between the LogFileNo of the LSN of the current log and the LogFileNo of the LSN of one of the dirty pages in the checkpoint list is greater than the value specified in this property, that page is flushed.

This value is important in determining the recovery time when the server is restarted. Because the number of pages to be flushed increases as this value is decreased, the recovery time when the server is restarted can be reduced.

The value of this property can be changed using the ALTER SYSTEM statement while the server is running.

FAST_UNLOCK_LOG_ALLOC_MUTEX

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property specifies whether or not the log buffer can be simultaneously accessed by multiple threads of the server. If the value of this property is set to 0, multiple server threads can sequentially access the log buffer; if the value of this property is set to 1, server threads can simultaneously access the log buffer.

0: Simultaneous access is disabled.

1: Simultaneous access is enabled.

HASH_AREA_SIZE (Unit: byte)**Data Type**

Unsigned Long

Default Value

4MB

Attributes

Read-Write, Single Value

Range

[3M, $2^{64}-1$]

Description

This property specifies the memory size, in bytes, of each temporary table that the server uses for hashing operations.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

HASH_JOIN_MEM_TEMP_AUTO_BUCKET_COUNT_DISABLE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

Sets the necessary number of buckets for memory hash temporary tables used in hash joins.

- 0 : The number of actual records inserted into a hash table.

- 1 : The number of buckets predicted by the query optimizer or set with the /*+ HASH BUCKET COUNT () */ hint.

If the value for the HASH_JOIN_MEM_TEMP_PARTITIONING_DISABLE property is 0 (partitioning method), it is efficient to divide as many sections as there are buckets.

If the value for the HASH_JOIN_MEM_TEMP_PARTITIONING_DISABLE property is 1 (bucket method), the number of buckets is predicted by the query optimizer or set by a hint.

The value of the HASH_JOIN_MEM_TEMP_PARTITIONING_DISABLE property can be altered using the ALTER SYSTEM statement while Altibase is running.

HASH_JOIN_MEM_TEMP_PARTITIONING_DISABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

Sets how to insert records into and scan memory hash temporary tables that are used in hash joins.

0 : Partitioning method

1 : Bucket method

The partitioning method scans the records by partitions; the number of partitions is automatically set according to the number of records inserted into the temporary space. The bucket method stores records into buckets in list format and scans records by buckets. The partitioning method consumes additional memory; however, it inserts and scans faster than the bucket method when handling bulk databases.

The value of the HASH_JOIN_MEM_TEMP_PARTITIONING_DISABLE property can be altered using the ALTER SYSTEM statement while Altibase is running.

HIGH_FLUSH_PCT (Unit: percentage)

Data Type

Unsigned Integer

Default Value

5

Attributes

Read-Write, Single Value

Range

[0, 100]

Description

When the flusher is not in a waiting state, if the flush list is longer than the percentage of the total buffer size specified here, replacement flushing occurs. At this time, all updated buffers in the flush list are flushed sequentially without waiting.

HOT_LIST_PCT (Unit: percentage)**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Default Value

[0, 100]

Description

This property specifies the percentage of an LRU list that is a hot area. The value of this property can be changed while the server is running.

HOT_TOUCH_CNT**Data Type**

Unsigned Integer

Default Value

2

Attributes

Read-Write, Single Value

Range[1, $2^{32}-1$]

Description

This property defines what constitutes a hot buffer in terms of the number of times the buffer is accessed. If the buffer is accessed more times than the value specified for this property, the buffer is considered hot. Hot buffers are moved to the hot list when replacement buffer searching is performed.

INDEX_BUILD_THREAD_COUNT**Data Type**

Unsigned Integer

Default Value

The number of physical core

Attributes

Read-Write, Single Value

Range

[1, 512]

Description

This property indicates the number of index-building threads that are created when an index is rebuilt at runtime.

If this property is commented out, the default number of parallel threads generated by the system is equal to the number of physical core.

INDEX_INITTRANS (Unit: count)**Data Type**

Unsigned Integer

Default Value

8

Attributes

Read-Only, Single Value

Range

[0, 50]

Description

This property indicates the initial number of TTS (Touched Transaction Slots) in an index page.

INDEX_MAXTRANS (Unit: count)**Data Type**

Unsigned Integer

Range

50

Attributes

Read-Only, Single Value

Range

[0, 50]

Description

This property indicates the maximum number of TTS (Touched Transaction Slots) in an index page.

LFG_GROUP_COMMIT_INTERVAL_USEC (Unit: microsecond)**Data Type**

Unsigned Integer

Default Value

1000

Attributes

Read-Only, Single Value

Range

[0, $2^{32}-1$]

Description

This property pertains to group commit.

A record is kept of the last time point at which disk I/O was performed for writing logs to disk to commit transactions. Logs are written to disk after the number of microseconds specified in this property has passed since that time point.

In this way, multiple transactions can be collectively committed to disk at the same time, and the required disk I/O can all be performed at once.

LFG_GROUP_COMMIT_RETRY_USEC (Unit: microsecond)**Data Type**

Unsigned Integer

Default Value

100

Attributes

Read-Only, Single Value

Range

[0, 60000000]

Description

This property pertains to group commit.

If the amount of time specified in LFG_GROUP_COMMIT_INTERVAL_USEC has not passed since the last time disk I/O was performed to record logs, a transaction to be committed waits for the number of microseconds specified in this property and then checks again whether sufficient time has passed to perform disk I/O.

LFG_GROUP_COMMIT_UPDATE_TX_COUNT**Data Type**

Unsigned Integer

Default Value

80

Attributes

Read-Only, Single Value

Range

[0, $2^{32}-1$]

Description

This property pertains to group commit.

When the number of uncommitted database UPDATE transactions (note: this can be checked by querying the UPDATE_TX_COUNT column in the V\$LFG performance view) is greater than the value specified in this property, group commit is performed. If this property is set to 0, group commit is disabled.

LOB_CACHE_THRESHOLD (Unit: byte)**Data Type**

Unsigned Integer

Default Value

8192

Attributes

Read-Write, Single Value

Range

[0, 524288]

Description

This property specifies the maximum size, in bytes, for LOB data capable of being stored on the client LOB cache. If a value larger than 0 is specified for this property, LOB data that does not exceed the specified value is temporarily stored on the client; if 0 is specified for this property, LOB data is not temporarily stored on the client.

If the threshold is appropriately adjusted with the use of this property, LOB data is stored on the client LOB cache and Bulk-select speed is improved.

This property can be changed using either the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

LOCK_ESCALATION_MEMORY_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

100M

Attributes

Read-Write, Single Value

Range

[0, 1000MB]

Description

This property is used to prevent abnormal increases in memory usage due to versioning when large-volume UPDATE batch tasks are performed on memory tables. If the size of logs created by a DML statement increases beyond the value specified in this property, so-called “in-place update”⁶ is performed without versioning in order to prevent increased memory usage.

[⁶] In-place update” means directly updating the value of a column in an original record without creating another version of the record.

When using versioning while updating records, an X lock is placed on the record, and an IX lock is placed on the table. However, when in-place update is performed, an X lock, that is, an exclusive lock, is placed on the table. Therefore, care must be taken when setting this value as it can degrade the scalability of the corresponding table if the value is set too low. This property value can be changed using the ALTER SYSTEM statement while A is running.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

LOG_IO_TYPE

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This indicates the I/O mode used to write logs.

0: buffered I/O

1: direct I/O

LOG_CREATE_METHOD

Data Type

Unsigned Integer

Default Value

- 0 (on HP-UX or AIX Environment)
- 1 (on Linux Environment)

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property selects the system call used to create the log file.

0 : write() system call

1: fallocate() system call (Only available on Linux)

LOW_FLUSH_PCT (Unit: percentage)

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Attributes

[0, 100]

Description

If the length of the flush list becomes equal to or greater than the percentage of the total buffer size specified by this value, replacement flushing occurs. At this time, all update buffers in the flush list are flushed.

LOW_PREPARE_PCT (Unit: percentage)**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 100]

Description

When the flusher awakes from a waiting state, if the length of the Prepare list is less than or equal to the percentage of the total buffer size specified by this value, replacement flushing occurs. At this time, all update buffers in the flush list are flushed.

MATHEMATICS_TEMP_MEMORY_MAXIMUM (Unit: byte)**Data Type**

Unsigned Long

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 2^{64}-1]$

Description

This property limits the amount of memory in MATHEMATICS TEMP used by analytic functions on the system. (Analytic functions: listagg, percentile_cont, percentile_disk, ...) An error occurs if the amount of used memory is equal or greater than MATHEMATICS_TEMP_MEMORY_MAXIMUM. If the property value is 0, the memory usage is not checked.

MAX_FLUSHER_WAIT_SEC (Unit: second)**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read-Write, Single Value

Range

$[1, 2^{32}-1]$

Description

This property specifies the maximum number of seconds that the flusher waits. The flusher wait time can increase depending on the frequency with which a task is conducted, but cannot exceed this value.

MEM_INDEX_KEY_REDISTRIBUTION**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

$[0, 1]$

Description

The MEM_INDEX_KEY_REDISTRIBUTION property redistributes memory index keys.

This property is highly efficient to use for inserting numerous reverse index keys, a lot of leaf node splits, or when the index range is much larger than that of the database.

0: The memory index keys are not redistributed.

1: The memory index keys are redistributed (Default value).

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

MEM_INDEX_KEY_REDISTRIBUTION_STANDARD_RATE

Data Type

Unsigned Integer

Default Value

50

Attributes

Read-Only, Single Value

Range

[10, 90]

Description

The MEM_INDEX_KEY_REDISTRIBUTION_STANDARD_RATE property sets up the minimum values for ratio of unused space in order to redistribute the memory index keys. For example, if the value of this property is 30, the memory key indexes are redistributed when there is at least minimum 30% of unused space of leaf nodes

MEM_INDEX_KEY_REDISTRIBUTION property would not be working if it is set to 0.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

MULTIPLEXING_CHECK_INTERVAL(Unit: microsecond)

Data Type

Unsigned Integer

Default Value

200000

Attributes

Read-Write, Single Value

Range

[100000, 10000000]

Description

This property indicates the interval at which sessions are checked, so that the thread manager service thread can be distributed. It is expressed in units of microseconds.

The thread manger periodically checks the status of threads, updates statistical data, and adds and deletes service threads.

MULTIPLEXING_MAX_THREAD_COUNT

Data Type

Unsigned Integer

Default Value

1024

Attributes

Read-Write, Single Value

Range

[1, 1024]

Description

This is the maximum number of multiplex threads.

If the capacity of existing threads is exceeded, new threads are automatically added. However, because performance can suffer if new threads are continually created, care must be taken to set this property appropriately.

Nevertheless, when queuing (QUEUE) is used, a number of threads exceeding the value specified by this property can be created.

MULTIPLEXING_THREAD_COUNT

Data Type

Unsigned Integer

Default Value

The number of logical cores

Attributes

Read-Only, Single Value

Range

[1, 1024]

Description

This is the minimum number of shared service threads that Altibase keeps running. The default is the number of logical cores.

This parameter cannot be changed after the server has been started.

NORMALFORM_MAXIMUM

Data Type

Unsigned Integer

Default Value

2048

Range

Read-Write, Single Value

Range

$[1, 2^{32}-1]$

Description

This property specifies the maximum number of normal form nodes when normalizing a condition clause.

When the predicates in a WHERE statement of a SELECT query are complicated by the use of logical operators (AND, OR), Altibase normalizes the predicates so that the table(s) can be searched more quickly.

There are two normalization methods: Conjunctive Normal Form (CNF) and Disjunctive Normal Form (DNF). If the use of either of these normal forms results in the number of nodes specified here being exceeded, no attempt to perform normalization using that normal form is made.

If both of the normal forms exceed the number specified here, execution proceeds Not Normal Form (NNF) without the condition clause being normalized. Using the NNF method, the condition is not normalized and the index can not be used.

On the other hand, if the value specified here is set to a larger number to avoid the NNF, the process of normalizing the complicated condition clause can use vast amounts of memory, thus the normalizing process itself becomes so expensive

Therefore, it is important to avoid the excessive use of logical operators when writing condition clauses, and to write condition clauses in normal forms.

Similarly, this rule also applies to an ON predicate joined to an ON condition.

OPTIMIZER_AUTO_STATS

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 10]

Description

This property can automatically collect statistical information when there is no available statistical information the optimizer can use.

The number of collectable pages range from 1 to 10 as described below. If it is set to 0, the statistical information cannot be automatically collected.

This property can be changed by using the ALTER SESSION and SYSTEM statements while the system is running.

Value	Pages	Collection Status for gathering statistics (ON/OFF)
0(Default value)	0	OFF
1	32	ON
2	64	ON
3	128	ON
4	256	ON
5	512	ON
6	1024	ON
7	4096 (32M)	ON
8	16384 (128M)	ON
9	65536 (512M)	ON
10	ALL	ON

OPTIMIZER_DELAYED_EXECUTION**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property performs execution of hierarchy, sorting, windowing, grouping, set, and distinction in fetch based upon execution plan graphs. The user can check the added DELAY plan under the top PROJECTION in the execution plan

This property reduces execution time and extends the first fetch time by delaying execution to be carried out in the first fetch when executing a query. The first fetch time remains the same, and the execution time can be viewed with the performance view V\$STATEMENT.

0 : disable (Deactivated, Default value)

1 : enable (Activated)

This property can be modified with the ALTER SESSION during the Altibase operation.

OPTIMIZER_FEATURE_ENABLE**Data Type**

String

Default Value

Altibase Server Version

Attributes

Read-Write, Single Value

Range

[6.1.1.0.6 | 6.1.1.0.7 | 6.3.1.0.1 | 6.5.1.0.0 | 7.1.0.0.0]

Description

This property controls properties related to the query optimizer in a uniform manner.

Only the versions specified in the range of this property can be altered with the ALTER SYSTEM statement.

```
e.g) ALTER SYSTEM SET optimizer_feature_enable = '6.1.1.0.6';
```

The following table shows how values of properties related to the query optimizer are set according to the settings of this property

OPTIMIZER_FEATURE_ENABLE	6.1.1.0.6	6.1.1.0.7	6.3.1.0.1	6.5.1.0.0	7.1.0.0.0
QUERY_REWRITE_ENABLE	0 (off)	0 (off)	0 (off)	0 (off)	0 (off)
OPTIMIZER_UNNEST_SUBQUERY	0 (off)	0 (off)	1 (on)	1 (on)	1 (on)
OPTIMIZER_UNNEST_COMPLEX_SUBQUERY	0 (off)	0 (off)	1 (on)	1 (on)	1 (on)
OPTIMIZER_UNNEST_AGGREGATION_SUBQUERY	0 (off)	0 (off)	0 (off)	1 (on)	1 (on)
RESULT_CACHE_ENABLE	0 (off)	0 (off)	0 (off)	0 (off)	0 (off)
TOP_RESULT_CACHE_MODE	0 (off)	0 (off)	0 (off)	0 (off)	0 (off)
OPTIMIZER_AUTO_STATS	0 (off)	0 (off)	0 (off)	0 (off)	0 (off)
OPTIMIZER_PERFORMANCE_VIEW	0 (off)	0 (off)	0 (off)	0 (off)	1 (on)

OPTIMIZER_MODE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

If this property is set to 0, cost-based optimization will be used to optimize query statements, whereas if it is set to 1, rule-based optimization will be used.

This property can be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

OPTIMIZER_PERFORMANCE_VIEW**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property configures whether or not to set a constraint on the memory. Internal enhancement can be expected when monitoring information of Altibase system

0: (Not apply) : There is no constraints on the memory.

1: {Apply, Default Value} : Memory constraints exist. If the value of EXECUTE_STMT_MEMORY_MAXIMUM exceeds, query execution fails.

OPTIMIZER_UNNEST_AGGREGATION_SUBQUERY**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

If a “nested subquery”⁷, which only contains an aggregate function without the GROUP BY clause, is included in the SELECT statement, this property specifies whether or not the query optimizer is to unnest the subquery.

[⁷] (Nested Subquery)

This is a subquery that is contained in the WHERE clause. A nested subquery mainly references columns from a main query in order to limit the result set. Converting a query that contains a nested subquery into an unnested join statement is called “Subquery Unnesting”

The value of this property can be modified using the ALTER SYSTEM statement while Altibase is running.

0: unnesting is disabled

1: unnesting is disabled

OPTIMIZER_UNNEST_COMPLEX_SUBQUERY**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

If a complex nested subquery is included in the SELECT statement, this property specifies whether or not the query optimizer is to unnest the subquery. Complexity denotes the existence of two or more tables within the FROM clause or the inclusion of other clauses other than the SELECT, FROM, WHERE clause.

The value of this property can be modified using the ALTER SYSTEM statement while Altibase is running.

0: unnesting is disabled.

1: unnesting is enabled.

OPTIMIZER_UNNEST_SUBQUERY

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

If a nested subquery is included in the SELECT statement, this property specifies whether or not the query optimizer is to unnest the subquery.

The value of this property can be modified using the ALTER SYSTEM statement while Altibase is running.

0: unnesting is disabled

1: unnesting is enabled

OUTER_JOIN_OPERATOR_TRANSFORM_ENABLE

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property allows the user to execute an optimized query plan by specifying that an outer join operation supported by the ANSI/ISO SQL standard is to be performed.

If this value is set to 0, an outer join operation supported by the ANSI/ISO SQL standard is performed. If the query statement has an Oracle outer join operator (+), an error occurs. The default value is 1 and uses the Oracle outer join operator (+).

0 : Disable

1 : Enable (Default value, uses the Oracle outer join operator)

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

PARALLEL_LOAD_FACTOR

Data Type

Unsigned Integer

Default Value

2N (N: the number of logical cores)

Attributes

Read-Only, Single Value

Range

[1, 512]

Description

This property controls the number of database refinement and index rebuilding threads that are created to refine the database or rebuild indexes when an Altibase server is restarted.

If this property is commented out, the default system behavior is to generate a number of parallel threads equal to the double of logical cores.

PARALLEL_QUERY_THREAD_MAX

Data Type

Unsigned Integer

Default Value

The number of logical cores

Attributes

Read-Write, Single Value

Range

[1, 1024]

Description

This property specifies the maximum number of worker threads that Altibase can create for the execution of parallel queries. On omission, the number of logical cores under the system is set as the default value for this property.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

PARALLEL_QUERY_QUEUE_SIZE

Data Type

Unsigned Integer

Default Value

1024

Attributes

Read-Write, Single Value

Range

[4, 1048576]

Description

This property specifies the size of the queue which temporarily stores data on the PARALLEL-QUEUE (PRLQ) node when the Altibase server executes parallel queries.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

PREPARE_STMT_MEMORY_MAXIMUM (Unit: byte)

Data Type

Unsigned Long

Default Value

100M

Attributes

Read-Write, Single Value

Range

[1024*1024, 2^{64} -1]

Description

This property indicates the maximum amount of memory, in bytes, that can be used to prepare a query statement.

This property may be changed using the ALTER SYSTEM statement while Altibase is running.

QUERY_REWRITE_ENABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies whether or not to apply function-based indexes on query conversion by the Altibase server.

0: disable

1: enable

REFINE_PAGE_COUNT

Data Type

Unsigned Integer

Default Value

50

Attributes

Read-Only, Single Value

Range

[0, $2^{32}-1$]

Description

One of the Altibase startup steps handles database refinement. When the Altibase server was shut down the previous time, some so-called “versioning records” created by transactions are not handled by the garbage collector, and thus unneeded records may exist in the database, and furthermore, other versioning records created by recovery processes when the server is started up may also exist. The database refining step is conducted so that these records can be reused.

Because this process can be time-consuming when many records are to be refined, it is conducted in parallel by multiple threads. This property specifies the number of pages handled by each thread.

RESULT_CACHE_ENABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This is a property that uses the result cache to save the execution plan of intermediate results.

0: Disabled (Default value) – Do not use the cache function

1: Enabled – Use the cache function

This property may be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

RESULT_CACHE_MEMORY_MAXIMUM (Unit: byte)

Data Type

Unsigned Long

Default Value

10M

Attributes

Read-Write, Single Value

Range

[4096, ULONG MAX]

Description

When using result cache and top result cache, it limits the amount of memory to store. If this size is exceeded, it is not stored in memory but released. This property is a constraint for one query and does not provide a system-wide constraint.

This property may be changed using the ALTER SYSTEM statement while Altibase is running.

SECONDARY_BUFFER_ENABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

The secondary buffer feature is the flushing of data pages of a memory buffer to the secondary buffer of an SSD(Solid-state Drive) first, instead of flushing them immediately to disk. The data pages of a secondary buffer are flushed to disk by a separate thread within the Altibase server

In order to use the secondary buffer feature normally, the SECONDARY_BUFFER_ENABLE, SECONDARY_BUFFER_FILE_DIRECTORY and SECONDARY_BUFFER_SIZE properties must be specified.

This property specifies whether or not to enable secondary buffer.

0: Enables secondary buffer.

1: Disables secondary buffer.

SECONDARY_BUFFER_FILE_DIRECTORY

Data Type

String

Default Value

""

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the path of the directory where the secondary buffer file is to exist. The file name is fixed as sbuffer.sbf and cannot be changed. When this property is unspecified, secondary buffer is disabled, even if the SECONDARY_BUFFER_ENABLE property is set to 1.

For more detailed information about the secondary buffer feature, please refer to the description of the SECONDARY_BUFFER_ENABLE property.

SECONDARY_BUFFER_FLUSHER_CNT

Data Type

Unsigned Integer

Default Value

2

Attributes

Read-Only, Single Value

Range

[1, 16]

Description

This property specifies the number of flushers that flush data pages of the secondary buffer to the hard disk.

For more detailed information about the secondary buffer feature, please refer to the description of the SECONDARY_BUFFER_ENABLE property

SECONDARY_BUFFER_SIZE (Unit: byte)

Data Type

Unsigned Long

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 32GB]

Description

This property specifies the size, in bytes, of the secondary buffer file. When the value of this property is set to 0, secondary buffer is disabled, even if the SECONDARY_BUFFER_ENABLE property is set to 1.

For further information about the secondary buffer feature, please refer to the description of the SECONDARY_BUFFER_ENABLE property.

SECONDARY_BUFFER_TYPE

Data Type

Unsigned Integer

Default Value

2

Attributes

Read-Only, Single Value

Range

[0, 2]

Description

This property specifies the data page type which is to be stored in the secondary buffer. One of the following values can be specified:

0: Pages of all types

1: Dirty pages

2: Clean pages

For more detailed information about the secondary buffer feature, please refer to the description of the `SECONDARY_BUFFER_ENABLE` property.

`SORT_AREA_SIZE` (Unit: byte)**Data Type**

Unsigned long

Default Value

1048576

Attributes

Read-Write, Single Value

Range[512, $2^{64}-1$]**Description**

This property specifies the memory size, in bytes, of each temporary table that the server uses for sorting operations.

This property can be changed using the `ALTER SYSTEM` statement while the system is running.

`SQL_PLAN_CACHE_BUCKET_CNT`**Data Type**

Unsigned Integer

Default Value

127

Attributes

Read-Only, Single Value

Range

[5, 4096]

Description

This property indicates the number of hash table buckets in a SQL plan cache.

SQL_PLAN_CACHE_HOT_REGION_LRU_RATIO (Unit: percentage)**Data Type**

Unsigned Integer

Default Value

50

Attributes

Read-Write, Single Value

Range

[10, 100]

Description

This property indicates the percentage of a hot area in an LRU list in a SQL plan cache. A HOT area in an LRU list is a separate portion of an LRU list in a SQL plan cache in which plans that are referred to frequently are saved.

This property can be changed using the ALTER SYSTEM statement while the system is running.

SQL_PLAN_CACHE_PREPARED_EXECUTION_CONTEXT_CNT**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1024]

Description

This property indicates the number of execution contexts that are initially created when plans are generated.

The initial number of execution contexts is specified before plans are created, however, this only determines the initial number. The number of execution contexts increases or decreases automatically as required during runtime.

Increasing this value can help realize better performance when only one plan is executed at a time, however, in other cases the plan size is merely increased, without realizing improved performance

SQL_PLAN_CACHE_SIZE (Unit: byte)**Data Type**

Unsigned long

Default Value

64 M

Attributes

Read-Write, Single Value

Range

$[0, 2^{64}-1]$

Description

This property indicates the maximum size, in bytes, of the SQL plan cache. If set to 0, the cache can't be used. This property can be checked by viewing the value of MAX_CACHE_SIZE of V\$SQL_PLAN_CACHE.

This property can be changed using the ALTER SYSTEM statement while the system is running.

STATEMENT_LIST_PARTIAL_SCAN_COUNT**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This property indicates the maximum number of statements to return to the application in response to a SELECT query executed on V\$STATEMENT, V\$SQLTEXT, or V\$PLANTEXT. If this property is set to 0, all rows pertaining to all statements are returned.

This property can be changed using the ALTER SYSTEM statement while the system is running.

TABLE_INITRANS**Data Type**

Unsigned Integer

Default Value

2

Attributes

Read-Only, Single Value

Range

[0, 120]

Description

This property indicates the initial number of TTS (Touched Transaction Slots) to be maintained in a table page.

TABLE_LOCK_ENABLE**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property controls the lock level.

0: This does not support the table lock, but the record lock. Efficiency is improved when using it on a simple DML.

1: This supports the table and record lock.

If the value of this property is set to 0, the following restrictions are applied:

- DDL statements cannot be executed.
- CREATE DATABASE cannot be executed.

- Parallel SYNC cannot be used when performing replication.

This property can be changed using the ALTER SYSTEM statement.

TABLE_LOCK_MODE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property controls the lock level of a table partition lock. This property is available for use only if the TABLE_LOCK_ENABLE is set to 1.

0: Table partition lock is supported. If the partition lock is used, the simultaneity is enhanced when using a query statement executing per a partition, such as ALTER TABLE...TRUNCATE PARTITION.

1: This does not support the table partition lock, it is identical with the lock on a non-partitioned table of a partitioned table. DML performance is much more improved due to the reduced lock count.

TABLE_MAXTRANS

Data Type

Unsigned Integer

Default Value

120

Attributes

Read-Only, Single Value

Range

[0, 120]

Description

This property indicates the maximum size of the TTS (Touched Transaction Slots) that is maintained for one table page.

TABSPACE_LOCK_ENABLE

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies the lock level for tablespaces.

1: Locks for table spaces are supported.

0: Locks for tablespaces are unsupported. In this case, the processing speed is enhanced for the execution of simple DML statements; however, the following restrictions apply.

- DDL statements cannot be executed.
- The CREATE DATABASE statement cannot be executed.
- Parallel Synchronization for replication is not supported.

The value of this property can be changed using the ALTER SYSTEM or the ALTER SESSION statement while Altibase is running. However, it can only be changed in the absence of activated transactions

TEMP_STATS_WATCH_TIME

Data Type

Unsigned Int

Default Value

10

Attributes

Read-Write, Single Value

Range

[0, $2^{32}-1$]

Description

This property specifies the standard time to be registered for statistical information. Among the operations using temporary tables, operations that take longer than the value specified for this property are registered for statistical information.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

THREAD_CPU_AFFINITY

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property specifies whether or not to bind CPUs to service threads. If this is turned on, a service thread will only be assigned to the same CPU core during its execution. It will reduce costs for moving thread information from one CPU core to another CPU core.

- 0: Do not use CPU affinity feature
- 1: Use CPU affinity feature

However, logging bottlenecks can occur when using CPU affinity on HP-UX IA64. Thus, the Altibase server does not enable CPU affinity, even if the value of this property is set to 1 (in the altibase.properties file) on HP-UX IA64.

THREAD_REUSE_ENABLE

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property indicates whether or not to reuse threads used on internal Altibase server.

0: New threads

1: Reusing threads (default value)

When you reuse a thread, reduce the cost of creating threads because using the threads waiting in memory.

TIMED_STATISTICS

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property determines whether to measure the wait time for wait events and the time required for SQL operations. Using this property to specify that the time is to be measured can negatively impact performance.

0: Do not measure the time

1: Measure the time

TIMER_RUNNING_LEVEL

Data Type

Unsigned Integer

Default Value

The default value for this property differs depending on the platform as follows:

1 : all platforms not listed below

2 : IBM-AIX

3 : x86-linux, Amd64-linux

Attributes

Read-Only, Single Value

Range

[1, 3]

Description

This property specifies how to measure the wait time for wait events and the time required for SQL operation.

1: The time measurement thread measures the time at regular intervals specified in the property `TIMER_THREAD_RESOLUTION`.

2: The time is measured using the library functions provided with respective platforms.

3: This method is similar to #1, but the time is measured using the system clock. Therefore, this method doesn't hinder performance as much as the other methods.

If this property is set to 3 on OS platforms other than Linux and PA-RISC-HP-64, it may become impossible to start the Altibase server due to the inability to correctly check the system time. In this case, the Altibase server will leave a warning message in the altibase_boot.log file, reset the TIMER_RUNNING_LEVEL property to its default value, and restart. On platforms for which the default value is 1, the following message is written to the boot log:

[Warning] Because a TIMER_RUNNING_LEVEL of 3 is not supported on this platform, it has been set to the default(=1) for this platform.

TIMER_THREAD_RESOLUTION (Unit: microsecond)

Data Type

Unsigned Integer

Default Value

1000

Attributes

Read-Write, Single Value

Range

[50, 10000000]

Description

If TIMER_RUNNING_LEVEL is set to 1, this property specifies the time interval.

TOP_RESULT_CACHE_MODE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 3]

Description

This property sets whether to save the execution plan of the final result using the top result cache.

0: Disabled (default value) – Do not use the top result cache function

1: MEMORY - cache the final result of queries using only memory tables

2: DISK – cache the final result of queries using only disk tables

3: ALL – cache the final result of queries regardless of the table type

The value of this property can be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

TOTAL_WA_SIZE (Unit: byte)

Data Type

Unsigned Long

Default Value

128MB

Attributes

Read-Write, Single Value

Range

[512K, $2^{64}-1$]

Description

This property specifies the maximum size of memory available for allocation for sorting or hashing operations.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running. The response to a request for alteration is immediately returned, however, the altered value is not actually applied to the server until the temporary table in use is nonexistent.

INIT_TOTAL_WA_SIZE (Unit: bytes)

Data Type

Unsigned Long

Default Value

128MB

Attributes

Read-Write, Single Value

Range

[512K, $2^{64}-1$]

Description

Specifies the amount of memory to be allocated in advance for sorting or hashing.

If it is larger than TOTAL_WA_SIZE, only TOTAL_WA_SIZE is created.

The value of this property can be changed by using the ALTER SYSTEM statemen when Altibase is running

TOUCH_TIME_INTERVAL (Unit: second)**Data Type**

Unsigned Integer

Default Value

3

Attributes

Read-Write, Single Value

Range

[0, 100]

Description

This property specifies the minimum time interval, in seconds, at which to increase the buffer access count. After the value specified in this property has passed since the last time the buffer was accessed, the access count is increased.

If this property is set to 3, which is the default value, the access count is not updated if a particular buffer is accessed again less than 3 seconds since it was previously accessed.

TRANSACTION_SEGMENT_COUNT (Unit: count)**Data Type**

Unsigned Integer

Default Value

256

Attributes

Read-Write, Single Value

Range

[1, 512]

Description

This property specifies the number of transaction segments (Undo segments and TTS segments) created when the server is started.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

TRX_UPDATE_MAX_LOGSIZE (Unit: byte)**Data Type**

Unsigned Integer

Default

10 MB

Attributes

Read-Write, Single Value

Range

$[0, 2^{64}-1]$

Description

If the size of logs created by a DML statement becomes greater than the number of bytes specified in this property, the corresponding transaction is aborted and an error is returned.

This property is used to prevent unusual increases in system load attributable to large volume batch tasks that result from the user's carelessness.

Because the log size has no limit if this property is set to 0, logs can be used without limit when records are updated. This property can be changed using the ALTER SYSTEM or ALTER SESSION statement when Altibase is running.

SERIAL_EXECUTE_MODE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single value

Range

$[0, 1]$

Description

This property optimizes the filter in the SCAN PLAN to improve the performance of the filter. At this time, it is optimized only for simple filter, and whether it is optimized can be checked in PLAN TREE.

0: Not optimized

1: Optimized

Session Properties

Session-related properties define the rules for communication between clients and the database server when Altibase is run in a client-server configuration. They are as follows:

CM_DISCONN_DETECT_TIME (Unit: second)**Data Type**

Unsigned Integer

Default Value

3

Attributes

Read-Only, Single Value

Range

[1, 2³²-1]

Description

Altibase server provides a session management thread for checking whether the connection between a client and a server has been interrupted. This property specifies the interval, in seconds, at which the session management thread operates.

Usually, when a client process is abnormally terminated, the server to which the client is connected can immediately detect this.

However, when a session has an unfinished task, and furthermore if the task is an internal Altibase server operation that is not directly related to the client session, and it is taking a long time, the server cannot check whether the client has terminated abnormally. That is to say, because the server cannot check whether the connection with the client has ended abnormally, such abnormal termination would be disregarded and Altibase would continue to process the task.

Such sessions must be detected, and the corresponding transactions must be rolled back. For this purpose, the session management thread regularly checks the status of all sessions.

CONCURRENT_EXEC_DEGREE_DEFAULT**Data Type**

Unsigned Integer

Default Value

4

Attributes

Read-Write, Single Value

Range

[2, 1024]

Description

CONCURRENT_EXEC_DEGREE_DEFAULT specifies for each session, the number of procedures in the DBMS_CONCURRENT_EXEC package that are allowed to execute in parallel concurrently. If the number of procedures to be executed in parallel is omitted, the CONCURRENT_EXEC_DEGREE_DEFAULT value is applied.

Altibase does not allow a stored package to execute more procedures than the value set for the `CONCURRENT_EXEC_DEGREE_MAX` property.

The value of this property can be changed with the `ALTER SYSTEM` statement while Altibase is running.

CONCURRENT_EXEC_DEGREE_MAX

Data Type

Unsigned Integer

Default Value

The number of logical cores

Attributes

Read-Only, Single Value

Range

[0, 1024]

Description

`CONCURRENT_EXEC_DEGREE_MAX` specifies the maximum number of procedures in the `DBMS_CONCURRENT_EXEC` package that are allowed to execute in parallel.

If this value is set to 0, the `DBMS_CONCURRENT_EXEC` package cannot be executed.

The value of this property can be changed with the `ALTER SYSTEM` statement while Altibase is running.

CONCURRENT_EXEC_WAIT_INTERVAL

Data Type

Unsigned Integer

Default Value

100

Attributes

Read-Write, Single Value

Range

[10, 1000000]

Description

`CONCURRENT_EXEC_WAIT_INTERVAL` specifies the interval to wait before checking whether a procedure in the `DBMS_CONCURRENT_EXEC` package has executed successfully.

The value of this property affects the `REQUEST` and `WAIT_REQ` functions. These functions wait for the procedure to finish execution.

The value of this property can be changed with the `ALTER SYSTEM` statement while Altibase is running.

DEFAULT_THREAD_STACK_SIZE (Unit: byte)

Data Type

Unsigned Integer

Default

10485760 (10MB)

Attributes

Read-Only, Single Value

Range

[1048576, 134217728]

Description

This property specifies the stack size, in bytes, for all system threads other than service threads.

IPC_CHANNEL_COUNT

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 65535]

Description

This property, which specifies the maximum number of IPC communication channels between a client and an Altibase server, must be set. Because shared memory and semaphore(s) are allocated in proportion to the channel count, it is important to set the maximum number of IPC connections that can be simultaneously established with the server.

IPC_FILEPATH

Data Type

String

Default Value

\$ALTIBASE_HOME/trc/cm-ipc

Attributes

Read-Only, Single Value

Range

None

Description

This is a socket file created for Altibase server to connect with the client through IPC in the UNIX environment.

If the server starts, a socket file is created under \$ALTIBASE_HOME/trc/cm-ipc directory, and be careful not to delete this file.

IPCDA_CHANNEL_COUNT**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 65535]

Description

The maximum number of communication channels using IPCDA between the client and server is specified with this property.

This property specifies the maximum number of IPCDA which can concurrently connect to the server plays an important role since shared memory and semaphores are proportionally allocated to the number of IPCDA channels. The optimized number of IPCDA channels should be half value of the number of CPU cores.

IPCDA_DATABLOCK_SIZE (Unit: KB)**Data Type**

Unsigned Integer

Default Value

20480

Attributes

Read-Only, Single Value

Range

[32, 102400]

Description

This is a property specifying the size of shared memory in a communication channel using IPCDA. If the value is 1000, and IPCDA_CHANNEL_COUNT is 24, the entire memory size (IPCDA_CHANNEL_COUNT * IPCDA_DATABLOCK_SIZE) used for the communication channel in server is 1000KB * 24 = 24000KB.

The value should be properly specified in order not to interrupt the operation of other programs using shared memory depending on the system size. For example, If IPCDA_CHANNEL_COUNT is 24 in 4GB system memory, the maximum value of IPCDA_DATABLOCK_SIZE cannot be used because the actual memory to use is 2457600KB.

IPCDA_FILEPATH**Data Type**

String

Default Value

\$ALTIBASE_HOME/trc/cm-ipcda

Attributes

Read-Only, Multiple Value

Range

None

Description

This is a socket file created for Altibase server to connect with the client through IPCDA in the UNIX environment.

If the server starts, a socket file is created under \$ALTIBASE_HOME/trc/cm-ipcda directory, and be careful not to delete this file.

MAX_LISTEN**Data Type**

Unsigned Integer

Default Value

128

Attributes

Read-Only, Single Value

Range

[0, 16384]

Description

This property specifies the maximum size of the “listen queue” when TCP/IP or UNIX domain protocol is used for communication between a client and Altibase.

MAX_STATEMENTS_PER_SESSION**Data Type**

Unsigned Integer

Default

1024

Attributes

Read-Write, Single Value

Range

[1, 65535]

Description

This property specifies the maximum number of statements that can be executed in a session.

This property value can be modified with the ALTER SESSION or ALTER SYSTEM statement while Altibase is running.

NET_CONN_IP_STACK**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1, 2]

Description

This property specifies the Internet Protocol Stack to be used when creating sockets on the server side for communication between the client and the server via TCP/IP.

0: An Internet Protocol Stack supporting only IPv4 will be used.

1: A dual stack (Internet Protocol Stack supporting both IPv4 and IPv6) will be used.

2: An Internet Protocol Stack supporting only IPv6 will be used.

NLS_COMP

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

When a database is created, it cannot be guaranteed that the sequence of characters in the character set specified by NLS_USE is the same as in a dictionary for the language of the country in question.

If this property is set to 1, character comparisons are performed based on the order in which the words in that language appear in a dictionary. If this property is set to 0, character comparisons are performed based on the binary values of the characters.

This is supported only when the database character set is set to Korean (KSC-5601 complete and MS extended complete) because the system currently supports Korean only.

NLS_CURRENCY

Data Type

String

Default Value

Determined by the value of NLS_TERRITORY

Attributes

Read-Write, Single Value

Range

Character string, maximum 10 bytes

Description

This property specifies the currency symbol. The value for this property is used to display the local currency symbol with the L number format. This property value cannot begin with +, -, <, > signs.

While Altibase is running, this property value can be modified with the ALTER SESSION statement as below:

```
ALTER SESSION SET NLS_CURRENCY = '$';
```

Note: In order to display the Arabic currency symbol properly, the client application program(or shell/editor) must support the display of Arabic characters.

NLS_ISO_CURRENCY

Data Type

String

Default Value

Determined by the value of NLS_TERRITORY.

Attributes

Read-Write, Single Value

Range

Value that exists in the V\$NLS_TERRITORY performance view.

Description

This property specifies the ISO currency symbol. The value of this property is used with the C number format to display the international currency symbol. The value of this property is limited to the value(territory) that exists in the V\$NLS_TERRITORY performance view.

While Altibase is running, this property value can be modified with the ALTER SESSION statement as below:

```
ALTER SESSION SET NLS_ISO_CURRENCY = America;
```

NLS_NCHAR_CONV_EXCP

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

When NCHAR type data are converted to another character set, data loss can occur. In such cases, this property determines whether to raise an error or to continue converting the data despite the possibility of data loss.

This property raises an error only when data conversion is performed on the server; it doesn't apply to conversion performed on clients.

This property can be changed using the ALTER SESSION statement while Altibase is running.

0: FALSE (Do not raise an error.)

1: TRUE

NLS_NCHAR_LITERAL_REPLACE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

By default, clients convert an entire query string to the database character set before sending the data to the database. This behavior can be prevented for a given string literal by setting this property to 1 and placing the "N" character in front of the string literal.

A property setting of 1 instructs the client to search for the "N" character in front of every string literal. If the "N" character is found, the client sends the string to the database without converting it to the database character set. This is useful when it is desired to use NCHAR type data that are encoded differently from the database character set.

This property can be changed using the ALTER SESSION statement while Altibase is running.

0: convert all strings to the database character set without checking for the "N" character

1: do not convert strings that are preceded by the "N" character to the database character set

Note: Setting this property to 1 can be expensive in terms of usage of client resources.

NLS_NUMERIC_CHARACTERS

Data Type

String

Default Value

Determined by the value of NLS_TERRITORY.

Attributes

Read-Write, Single Value

Range

None

Description

This property specifies the decimal character and the group separator. The group separator is used to display numbers in thousands and generally uses a comma(.). The decimal character generally uses a period(.). This property value cannot begin with +, -, <, > signs.

Of a character string specified for this property, only the first two characters are set as decimal characters; the group separator and the rest are ignored.

While Altibase is running, this property value can be modified with the ALTER SESSION statement as below:

```
ALTER SESSION SET NLS_NUMERIC_CHARACTERS='.,';
```

NLS_TERRITORY**Data Type**

String

Default Value

KOREA

Attributes

Read-Write, Single Value

Range

Value that exists in the V\$NLS_TERRITORY performance view

Description

This property specifies the name of the territory. Values of the NLS_NUMERIC_CHARACTER, NLS_CURRENCY, NLS_ISO_CURRENCY properties are automatically modified according to the territory set for this property. Territory names available for specification of this property can be checked by querying the V\$NLS_TERRITORY performance view.

While Altibase is running, this property value can be modified with the ALTER SESSION statement as below. Territory names do not distinguish upper or lower class, and apostrophes(') can be used.

```
ALTER SESSION SET NLS_TERRITORY = America;
or
ALTER SESSION SET NLS_TERRITORY = 'America';
```

PORT_NO**Data Type**

Unsigned Integer

Default Value

20300

Attributes

읽기 전용, 단일 값

Range

[1024, 65535]

Description

This property specifies the port number for communication between the client and the server via TCP/IP. The user can set this port number to any number not being used by another application within the range of port numbers (up to number 65535) excluding the so-called “well-known TCP port numbers” (from 1 to 1023). Application programs of Altibase can connect to the server via this port number.

PSM_CURSOR_OPEN_LIMIT**Data Type**

Unsigned Integer

Default Value

32

Attributes

Read-Only, Single Value

Range

[1,1024]

Description

The PMS_CURSOR_OPEN_LIMIT specifies the cursor which can be open by using DBMS_SQL in the session.

PSM_FILE_OPEN_LIMIT**Data Type**

Unsigned Integer

Default Value

16

Attributes

Read-Write, Single Value

Range

[0,128]

Description

This property specifies the maximum number of stored procedure file handles that can be opened for a session.

TIME_ZONE**Data Type**

String

Default Value

OS_TZ

Attributes

Read-Write, Single Value

Range

The value that exists in the V\$TIME_ZONE_NAMES performance view.

Description

This property sets the time zone. Region names, abbreviations or character strings such as the UTC offset value(e.g., +09:00) can be used for specification.

This property can be modified using the ALTER SESSION statement while Altibase is running.

UNIXDOMAIN_FILEPATH**Data Type**

String

Default Value

\$ALTIBASE_HOME/trc/cm-unix

Attributes

Read-Only, Single Value

Range

None

Description

This property is a socket file created for Altibase server to connect with a client through the Unix domain.

If the server is driven, the basic socket file is created under \$ALTIBASE_HOME/trc directory, and it should be ensured that the file is not deleted.

USE_MEMORY_POOL

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0,1]

Description

This property specifies whether memory pooling is used. “Memory pooling” means assigning server memory in advance.

When this function is used, because server memory is allocated in advance, memory use is increased.

0: Do not use memory pooling

1: Use memory pooling

USER_LOCK_POOL_INIT_SIZE (Unit: count)

Data Type

Unsigned Integer

Default Value

128

Attributes

Read-Only, Single Value

Range

[128, 10000]

Description

The number of times for user lock in the database can be specified through the USER_LOCK_POOL_INIT_SIZE property.

By exceeding the property values, the user lock can be used for maximum number of times; however, in that case, performance degradation might be occurred due to overutilization. Moreover, once the user lock is created the user lock cannot be eliminated even though it is released; thus, it can be said that re-using the user unlock that has been once released is rather efficient.

USER_LOCK_REQUEST_CHECK_INTERVAL (Unit: microsecond)**Data Type**

Unsigned Integer

Default Value

10000

Attributes

Read-Write, Single Value

Range

[10, 999999]

Description

The USER_LOCK_REQUEST_CHECK_INTERVAL configures a cycle for examining whether the user lock is available for use or not. If a user, who is currently using in a different session, requests the user lock, the session would be waiting until the user lock is released.

The property value can be modified by using the ALTER SYSTEM statement during the operation of Altibase.

USER_LOCK_REQUEST_LIMIT (Unit: count)**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read-Write, Single Value

Attributes

[0, 10000]

Default Value

The USER_LOCK_REQUEST_LIMIT sets number of times the user lock that one session can request. The value of this property can be modified through the ALTER SYSTEM statement during the operation of Altibase.

USER_LOCK_REQUEST_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default value

10

Attributes

Read-Write, Single Value

Range $[0, 2^{32}-1]$ **Description**

The USER_LOCK_REQUEST_TIMEOUT establishes the maximum waiting time until the user lock is obtained in a session.

The value of this property can be modified through the ALTER SYSTEM statement during the operation of Altibase.

XA_HEURISTIC_COMPLETE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range $[0, 2]$ **Description**

In a distributed transaction environment, Two-Phase Commit Protocol (XA) is used. While a transaction is underway, after a Prepare command has been received from the global transaction coordinator, if for some reason a COMMIT or ROLLBACK command does not arrive for a long time, Altibase will keep the transaction active for a long time, which will negatively affect database performance.

To prevent this, Altibase terminates the entire transaction if it has been in a PREPARE (or IN_DOUBT) state beyond a certain period of time. In such cases, this property determines whether to use COMMIT or ROLLBACK to terminate the transaction.

Altibase waits for the amount of time specified with the XA_INDOUBT_TX_TIMEOUT property before cancelling a transaction in this way. If the value of XA_HEURISTIC_COMPLETE is 0, which is the default, nothing will be done; if it is 1, the transaction will be committed, and if it is 2, the transaction will be rolled back.

Time-out Properties

BLOCK_ALL_TX_TIME_OUT (Unit: second)

Data Type

Unsigned Integer

Default Value

3

Attributes

Read-Write, Single Value

Range

[0, $2^{32}-1$]

Description

This property restricts transactions' access to the hash table when the buffer manager resizes the hash table. The minimum value of 0 specifies that error handling is to be performed without any wait time.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

DDL_LOCK_TIMEOUT (Unit: second)

Data Type

Short integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[-1, 65535]

Description

When DDL query statements are executed, this property sets how long to wait to establish a lock when the target table has already been locked by another transaction. In cases where a transaction cannot immediately gain write access to the table, If this parameter is set to -1, the transaction will wait indefinitely, whereas if this parameter is set to a positive value, the transaction will wait for that number of seconds before trying again.

The default value of this parameter is 0, which tells Altibase to return an error code if it cannot obtain a lock immediately at the time of executing a DDL statement.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

DDL_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

If the execution time of a DDL statement exceeds the number of seconds specified here, execution of that statement is canceled. The default value of this property is 0, in which case Altibase waits indefinitely for DDL operations to finish.

This property can be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

Note: In Altibase versions up to 5.5.1, the execution time of DDL statements was governed by the UTRANS_TIMEOUT and QUERY_TIMEOUT properties, which still govern the execution time of DML and DCL statements.

FETCH_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

60

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This property prevents abnormal increases in database memory consumption when SELECT statements executed by client applications take an excessive amount of time. In cases where the query execution time exceeds the number of seconds specified using this property, the session will be disconnected and the transaction will be rolled back.

This property can be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

IDLE_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

If a large number of clients are connected to a server for an excessive period of time due to some abnormality, the number of available connections will significantly decrease, ultimately leading to failure to provide service.

This property functions to preemptively prevent this situation. If the number of seconds that a session is idle exceeds this value, the session will be disconnected and any associated transactions will be rolled back.

The value of this property can be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

LOGIN_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the permitted amount of time, in seconds, to wait for authorization to be completed after a connection has been made to an Altibase port. If authorization is not completed within this time, the server disconnects.

MULTIPLEXING_POLL_TIMEOUT (Unit: microsecond)**Data Type**

Unsigned Integer

Default Value

10000

Attributes

Read-Write, Single Value

Range

[1000, 1000000]

Description

This property specifies the interval at which the multiplexed thread running service detects sessions.

QUERY_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

600

Attributes

Read-Write, Single Value

Range

[0, $2^{32}-1$]

Description

This property is set to prevent abnormal increases in database memory consumption when particular kinds of queries (especially those involving sort operations or joins) are executed. If the query execution time exceeds the number of seconds specified here, the transaction is partially rolled back.

This property can be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

SHUTDOWN_IMMEDIATE_TIMEOUT**Data Type**

Unsigned Integer

Default Value

60

Attributes

Read-Write, Single Value

Range $[0, 2^{32}-1]$ **Description**

When shutting down Altibase with the IMMEDIATE option, Altibase is shut down after uncommitted transactions are rolled back. This property specifies the amount of time, in seconds, to wait for the transactions to be rolled back. If the elapsed time exceeds the specified value, Altibase is shut down forcibly and uncommitted transactions are not rolled back. If this property is set to 0, Altibase waits until all transactions are rolled back.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

UTRANS_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default value

3600

Attributes

Read-Write, Single Value

Range $[0, 2^{32}-1]$ **Description**

This property is set to prevent the number of log files from abnormally increasing when write operations (UPDATE, DELETE, INSERT) take a long time. If such a transaction takes longer than the number of seconds specified here, the session will be disconnected and the transaction in question will be rolled back.

This property can be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

XA_INDOUBT_TX_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

60

Attributes

Read-Only, Single Value

Range $[0, 2^{32}-1]$ **Description**

When using the Two-Phase Commit Protocol, this property specifies the number of seconds to wait before terminating an entire transaction that has taken a long time and is thus in IN_DOUBT state.

Transaction Properties**AUTO_COMMIT****Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range $[0, 1]$ **Description**

This property determines whether to handle each individual SQL statement as a separate transaction and commit it when SQL statements are executed in a session. A value of 1 indicates auto-commit mode, while a value of 0 indicates non-autocommit mode. When using non-autocommit mode, the client application must explicitly indicate the beginning and end of a transaction.

Even if this value is set to 1, indicating auto-commit, when the server is started, this property can be changed for individual sessions. For example, if ALTER SESSION SET AUTOCOMMIT = FALSE (non-autocommit) is executed from a client, the user must explicitly specify whether to commit or rollback any transactions that occur for the remainder of the session.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

ISOLATION_LEVEL**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 3]

Description

This property specifies the transaction isolation level. When a single transaction searches the same table multiple times, the result varies depending on the isolation level.

For more information about transaction isolation levels, please refer to the *Altibase Administrator's Manual*.

Isolation Level	Characteristics
0 (Committed Read)	This is the default mode of Altibase. This isolation level guarantees that previously read data that have been modified by another transaction will reflect the changes of that other transaction. When a SELECT transaction reads data one time and then reads the data again, if another transaction simultaneously executes and commits an INSERT or DELETE statement, due to this change, it is possible for a new row to be found, or for a previously found row to have disappeared.
1 (Repeatable Read)	This isolation level guarantees that the contents of a row will be the same upon repeated reads by the same transaction. This isolation level places a lock on a row once it has been read. Therefore, when the table is subsequently read, previously read rows will not change or disappear, but it is possible for new rows to appear.
2 (No Phantom)	This isolation level guarantees identical results for repeated reads.

TRANSACTION_TABLE_SIZE (Unit: Transaction count)**Data Type**

Unsigned Integer

Default Value

1024

Attributes

Read-Only, Single Value

Range

[16,16384]

Description

The number of transactions which can be simultaneously created during the Altibase service is specifiable when creating a database, and memory for such process is allocated in advance.

This property should increase or decrease the value by 2n and the database must be created again when decreasing the value.

Backup and Recovery Properties

These properties are related to the management of change logs, which are maintained in response to database changes.

ARCHIVE_DIR**Data Type**

String

Default Value

\$ALTIBASE_HOME/arch_logs

Attributes

Read-Only, Multiple Values

Range

None

Description

This property specifies the directory or directories in which to store archive log files when performing an archive log backup. If this value is not expressly specified by the user, the default location is \$ALTIBASE_HOME/arch_logs.

The number of directories specified in this property must be the same as the number specified in the LOG_DIR property.

The user can explicitly specify the value(s), but the specified directories must be created first. If not, an error message will be output, and Altibase will not start.

ARCHIVE_FULL_ACTION

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property controls the action of the archivelog thread, which conducts archive log backup, when there is not enough disk space in the archive log destination (specified using ARCHIVE_DIR).

If this parameter is set to 0, the archivelog thread will output an error message and stop the archive log file backup. Even if enough disk space can subsequently be secured, archive log backup will not resume until the user explicitly issues a command to do so. If checkpointing takes place in such cases, unnecessary log files will be deleted, even if no archive log file backup has been conducted. Therefore care must be taken when using this mode.

If this parameter is set to 1, the archivelog thread waits until enough disk space can be secured to perform the archive log file backup. Because the archive log files have not been backed up, care must be taken to prevent the log files from being deleted if checkpointing takes place during this waiting period.

ARCHIVE_MULTIPLEX_COUNT

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 10]

Description

This property specifies how many copies of the archive log file⁹ are to be kept by the Altibase server. After this property has been specified, copies of newly archived log files are kept.

[⁹] Multiplexing archive log files

This feature copies the archive log files to a separate disk to prepare for the event of damage to the original archive log files.

The ARCHIVE_MULTIPLEX_COUNT and ARCHIVE_MULTIPLEX_DIR properties can be specified while the server is shutdown.

ARCHIVE_MULTIPLEX_DIR

Data Type

String

Default Value

""

Attributes

Read-Only, Multiple Value

Range

None

Description

This property specifies the path for copies of the archive log file. The number of values specified in the ARCHIVE_MULTIPLEX_DIR properties must be equal to the value specified in the ARCHIVE_MULTIPLEX_COUNT property. It is recommended to set each path to a separate disk.

ARCHIVE_THREAD_AUTOSTART

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property specifies whether to activate the archivelog thread, which periodically performs archive log file backups. If this property is 1, the archivelog thread is activated.

After the archivelog thread has been suspended due to insufficient disk space in the backup directory, this property is used to restart the thread automatically after sufficient disk space is secured.

CHECKPOINT_ENABLED

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property specifies whether checkpointing is enabled ("ON") or disabled ("OFF").

0: OFF

1: ON

When this value is 0 ("OFF"), the checkpoint thread cannot be started, and additionally it cannot operate the checkpoint interval specified by CHECKPOINT_INTERVAL_IN_SEC and CHECKPOINT_INTERVAL_IN_LOG. However, the user can perform checkpointing manually.

CHECKPOINT_INTERVAL_IN_LOG

Data Type

Unsigned Integer

Default Value

100

Attributes

Read-Write, Single Value

Range

[1, $2^{32}-1$]

Description

This property defines the checkpoint interval based on the log file creation count. In other words, after the log files have been replaced the number of times specified using this property, checkpointing will be automatically executed. When checkpointing is requested based on this property, it may be impossible to execute, either because checkpointing is already underway, or for some other reason.

In such cases, checkpointing is not initiated immediately again after the checkpointing that is already underway has finished; instead, the current checkpointing request is canceled. Therefore, the next checkpointing request will occur when the number of log files reaches the value set in this property.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

CHECKPOINT_INTERVAL_IN_SEC (Unit: second)

Data Type

Unsigned Integer

Default Value

6000

Attributes

Read-Write, Single Value

Range

[3, 2592000]

Description

This property specifies the checkpoint interval in seconds.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

COMMIT_WRITE_WAIT_MODE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies whether to wait until logs have been written to log files when committing transactions. In Altibase, the default is not to wait, in the interests of better performance.

This property can be set for the entire system or for individual user sessions, and thus this property can be changed using either the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

0: Do Not Wait

1: Wait

INCREMENTAL_BACKUP_CHUNK_SIZE

Data Type

Unsigned Integer

Default Value

4

Attributes

Read-Only, Multiple Value

Range

$[0, 2^{32}-1]$

Description

This property is specified to track the changes made to pages of data(unit: pages). For example, if the value of this property is set to 4, change tracking information is recorded for every 4 pages and all of the 4 pages are backed up if one of the 4 pages is changed.

To alter the value of this property, the changeTracking file must be recreated in the following steps:

1. Shut down the server and then alter the value in the properties file.
2. Start up the server.
3. Disable change tracking and then reactivate it.

INCREMENTAL_BACKUP_INFO_RETENTION_PERIOD

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the period of time(unit: days) during which backup information stored in the backupInfo file is retained

Backup information deleted with the ALTER DATABASE DELETE OBSOLETE BACKUP FILES statement ranges from the oldest expired level 0 backup to the level 1 backup immediately prior to the oldest unexpired level 0 backup.

Note: Backup files backed up at level 0 are a prerequisite for incremental backups. Regardless of the existence of backup information which has expired the maintenance period specified for this property and the corresponding backup files, if only a level 0 backup has been performed, expired backup information and backup files are not deleted, even if the "ALTER DATABASE DELETE OBSOLETE ..." statement is executed.

LOG_BUFFER_TYPE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property determines the log buffer type. If it is set to 0, the OS kernel log buffer is used. If it is set to 1, the process memory log buffer is used.

This property cannot be changed while the system is running.

LOG_MULTIPLEX_COUNT

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 10]

Description

This property specifies how many copies of the log file¹⁰ are to be kept by the Altibase server. Whenever original log files are created or dropped, the copies of log files are also simultaneously created or dropped.

[¹⁰] Multiplexing Log Files

This feature copies the log files to which all changes of the database have been written, to a separate disk to prepare for the event of damage to the original log files.

The LOG_MULTIPLEX_COUNT and LOG_MULTIPLEX_DIR properties can be specified while the server is shutdown.

LOG_MULTIPLEX_DIR

Data Type

String

Default Value

""

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the path for copies of the log file. The number of values specified in the LOG_MULTIPLEX_DIR properties must be equal to the value of the LOG_MULTIPLEX_COUNT property. It is recommended to set each path to a separate disk.

PREPARE_LOG_FILE_COUNT

Data Type

Unsigned Integer

Default Value

5

Attributes

Read-Only, Single Value

Range

[0, 2³²-1]

Description

If there is not enough space in the log file when logs are written, a new log file is created, which can increase the transaction response time. To prevent such delays in transaction execution caused by the creation of log files, Altibase creates extra log files ("prepare log files") in advance. This parameter specifies the number of such log files.

SNAPSHOT_MEM_THRESHOLD (Unit: percentage)

Data Type

Unsigned Integer

Default Value

80

Attributes

Read-Write, Single Value

Range

[0, 100]

Description

This is a property which sets up available thresholds for use in memory database after the snapshot settings (BEGIN SNAPSHOT).

The percentage of the MEM_MAX_DB_SIZE property which is currently being used by memory is verified, and if it exceeds the specified threshold, the snapshot is automatically stopped.

SNAPSHOT_DISK_UNDO_THRESHOLD (Unit: percentage)**Data Type**

Unsigned Integer

Default Value

80

Attributes

Read-Write, Single Value

Range

[0, 100]

Description

This property specifies thresholds usable in disk after the snapshot settings (BEGIN SNAPSHOT).

It verifies what percentage of the SYS_UNDO_FILE_MAX_SIZE property has been used by the disk undo tablespace up to now, and if it exceeds specified threshold, the snapshot is automatically stopped.

Replication Properties

The following parameters pertain to database replication. For more information about database replication, please refer to the *Getting Started Guide* and to the *Replication User's Manual*.

REPLICATION_ACK_XLOG_COUNT**Data Type**

Unsigned Integer

Default Value

100

Attributes

Read-Write, Single Value

Range $[0, 2^{32}-1]$ **Description**

This property indicates the frequency with which the Receiver thread sends ACK to the Sender thread.

The Receiver thread receives XLogs and replays them one by one. When the number of replayed XLogs exceeds the value specified here, the Receiver thread sends ACK to the Sender thread.

If this value is set too low, the Receiver thread sends ACK too often, leading to reduced performance.

If it is set too high, the amount of time that the Sender thread waits for ACK can increase excessively, and may be treated as a network fault. In addition, if the Sender thread does not receive ACK for an extended time, the replication restart SN is not updated, and thus the Sender thread will start over from the most recent log record if checkpointing occurs, resulting in the deletion of unreplicated logs.

REPLICATION_ALLOW_DUPLICATE_HOSTS**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range $[0, 1]$ **Description**

This property specifies whether or not to allow replication objects to set duplicate values for the IP address and port number of the remote server.

0: Disallowed

1: Allowed

REPLICATION_BEFORE_IMAGE_LOG_ENABLE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

If the "before image" of the replication Receiver differs from the "before image" of the XLog received from the Sender, it is possible for data conflict to occur.

With this property, the "before image" of the replication receiver can be stored in the trace log to enable the user to check which data conflicted.

0: Disables trace logging

1: Enables trace logging

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_COMMIT_WRITE_WAIT_MODE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property determines whether the replication Receiver checks whether XLOGs have been applied to disk after the replication Receiver has completed executing all of the transactions that are necessary in order to apply the contents of XLOGs to disk. If this property is set to 0, the replication Receiver doesn't wait to ensure that the contents of XLOGs have been applied to disk. If the value of this property is set to 1, the replication Receiver ensures that the contents of XLOGs have been applied to disk.

REPLICATION_CONNECT_RECEIVE_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

60

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the amount of time, in seconds, to wait after attempting to connect to the target host at the start of replication.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_CONNECT_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

When attempting to connect to a target host to perform replication, if there is no response within the number of seconds specified in this property, no further connection attempts are made.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_DDL_ENABLE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies whether to allow DDL statements to be executed on replication target tables. If this property is set to 1, DDL statements can be executed on replication target tables.

Before executing DDL statements, if the replication property of a transaction in the current session is set to a value other than NONE, the Sender thread can be made aware of the execution of DDL statements.

For a list of DDL statements permitted during replication and other restrictions, please refer to the *Replication Manual*.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_DDL_ENABLE_LEVEL**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property determines the range of DDL statements that can be used for the replication target table. To use this property, the value of the REPLICATION_DDL_ENABLE has to be set to 1. The following DDL statement is allowed according to the REPLICATION_DDL_ENABLE_LEVEL value.

- REPLICATION_DDL_ENABLE_LEVEL = 0

```
ALTER TABLE table_name ADD COLUMN ( column_name DATA_TYPE );
```

```
ALTER TABLE table_name DROP COLUMN column_name;
```

```
ALTER TABLE table_name ALTER COLUMN column_name SET DEFAULT
```

```
ALTER TABLE table_name ALTER COLUMN column_name DROP DEFAULT
```

```
ALTER TABLE table_name TRUNCATE PARTITION
```

```
TRUNCATE TABLE table_name;
```

```
CREATE INDEX index_name ON table_name ( column_name );
```

```
DROP INDEX index_name; -- for Normal Index
```

- REPLICATION_DDL_ENABLE_LEVEL = 1

```
ALTER TABLE table_name ADD COLUMN ( column_name DATA_TYPE NOT NULL );
```

```
ALTER TABLE table_name ADD COLUMN ( column_name DATA_TYPE UNIQUE );
```

```
ALTER TABLE table_name ALTER COLUMN ( column_name NOT NULL );
```

```
ALTER TABLE table_name ALTER COLUMN ( column_name NULL );
```

```
ALTER TABLE table_name MODIFY COLUMN ( column_name DATA_TYPE );
```

```
ALTER TABLE table_name MODIFY COLUMN ( column_name NULL );
```

```
ALTER TABLE table_name MODIFY COLUMN ( column_name NOT NULL );
```

ALTER TABLE table_name DROP COLUMN column_name; (NOT NULL, NULL, Unique, function-base index can also be deleted.)

```
ALTER TABLE table_name ADD CONSTRAINT constraint_name UNIQUE ( column_name );
```

```
ALTER TABLE table_name ADD CONSTRAINT constraint_name UNIQUE ( column_name )
LOCAL;
```

```
ALTER TABLE table_name DROP CONSTRAINT constraint_name; ( Unique, Local Unique )
```

```
CREATE UNIQUE INDEX index_name ON table_name ( column_name );
```

```
CREATE INDEX index_name ON table_name ( expression );
```

```
DROP INDEX index_name; ( unique, function-base indexes can be deleted. )
```

REPLICATION_DDL_SYNC

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property indicates whether DDL is replicated during replication.

0 : Do not allow DDL replication during replication. When executing DDL, it is executed only in the replication local server.

1 : Allow DDL replication during replication. When executing DDL, DDL is replicated to the replication remote server.

This property can be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

REPLICATION_DDL_SYNC_TIMEOUT (Unit: second)

Data Type

Unsigned Integer

Default Value

7200

Attributes

Read-Write, Single Value

Range

[0, $2^{32}-1$]

Description

If the execution time of DDL copy exceeds the number of seconds set in this property, the execution of that statement is canceled for both the replication local and remote servers.

Timeout value is measured based on the replication local server that performs DDL replication.

This property can be changed using the ALTER SYSTEM or ALTER SESSION statement while Altibase is running.

REPLICATION_EAGER_PARALLEL_FACTOR

Data Type

Unsigned Integer

Default Value

The smaller value among 'number of logical cores/2' and '512'

Attributes

Read-Only, Single Value

Range

[1, 512]

Description

When replication is executed on EAGER mode, multiple Sender threads are operated in parallel. This property specifies the number of Sender threads to be operated in parallel; an increase in the number of Sender threads leads to an improvement in replication performance.

When increasing the number of Sender threads with this property, however, the user must note that the order in which the Sender threads send transactions are not guaranteed. For further information about this matter, please refer to the *Replication Manual*.

If this property is not set, the default value is the smaller value among the number of logical cores/2 and 512.

REPLICATION_EAGER_RECEIVER_MAX_ERROR_COUNT**Data Type**

Unsigned Integer

Default Value

5

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

When replication is performed in eager mode, this property can set the number of times the replication Receiver is to attempt data replication.

If this value is set to 5 and an Xlog replication error occurs, the replication Receiver attempts replication up to 5 times, and forcefully terminates the Altibase server if the last attempt fails.

When this value is set to 0, if an Xlog replication error occurs, the replication Receiver attempts replication until it succeeds and does not forcefully terminate the server.

Replication in eager mode is mainly used in environments where data concurrency between the replication Receiver and the Sender are important. Therefore, data replication is stopped and the server is terminated to prevent data conflicts.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_FAILBACK_INCREMENTAL_SYNC**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

$[0, 1]$

Description

This property sets the execution of incremental sync on or off. If one of the servers during replication in EAGER mode fails and data inconsistency occurs, Incremental Sync performs data synchronization on the inconsistent data upon restart of the failure server.

- 0: Deactivates Incremental Sync

- 1: Activates Incremental Sync

The value of this property for both Altibase servers participating in replication must be identical. For more detailed information about incremental synchronization and EAGER replication failure recovery, refer to *Replication Manual*.

REPLICATION_GAP_UNIT (Unit: byte)

Data Type

Unsigned Long

Default Value

1048576 (1MB)

Attributes

Read-Write, Single Value

Range

$[1, 2^{64}-1]$

Description

This property sets the unit that represents the value of REP_GAP for querying the size of the replication gap.

The value of REP_GAP is the result of dividing the value of REP_GAP_SIZE by this property, and rounding up the rest.

By default, REP_GAP_SIZE of V\$REPGAP is retrieved in bytes, and REP_GAP is retrieved in megabytes (MB).

REPLICATION_GAPLESS_ALLOW_TIME (Unit: microsecond)

Data Type

Unsigned Integer

Default Value

2000

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

If the GAPLESS option is enabled, the replication sender allows a replication gap for as long as the value (unit: microseconds) set for the REPLICATION_GAPLESS_ALLOW_TIME property. The replication sender delays transaction commits if it anticipates the replication gap to still exist after the amount of time set for this property.

For example, if the `REPLICATION_GAPLESS_ALLOW_TIME` property is set to 5 and the sender sends 1,000 XLogs per second, a replication gap of 5,000 XLogs is allowed. If the current replication gap consists of 10,000 XLogs, this means that transaction commits must be delayed for five microseconds, since 5,000 XLogs have exceeded the limit.

If the `REPLICATION_GAPLESS_ALLOW_TIME` property is set to 0, this means that no replication gaps are allowed; transactions will be committed only after replication gaps are dissolved.

The value of this property can be altered using the `ALTER SYSTEM` statement while Altibase is running.

REPLICATION_GAPLESS_MAX_WAIT_TIME (Unit: microsecond)

Data Type

Unsigned Integer

Default Value

10,000,000

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

When the `GAPLESS` option is enabled, the `REPLICATION_GAPLESS_MAX_WAIT_TIME` property sets the maximum amount of time (unit: microseconds) that the replication sender can delay transaction commits to dissolve replication gaps.

If the `REPLICATION_GAPLESS_MAX_WAIT_TIME` property is set to 0, transactions will be committed only after replication gaps are dissolved.

The value of this property can be altered using the `ALTER SYSTEM` statement while Altibase is running.

REPLICATION_GROUPING_TRANSACTION_MAX_COUNT (Unit: count)

Data Type

Unsigned Integer

Default Value

5

Attributes

Read-Only, Single Value

Range

[1, 1000]

Description

The REPLICATION_GROUPING_TRANSACTION_MAX_COUNT property sets the maximum number of transactions that are allowed to be accumulated into a single transaction group.

The value of this property can be altered using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_GROUPING_AHEAD_READ_NEXT_LOG_FILE (Unit: count)**Data Type**

Unsigned Integer

Default Value

2

Attributes

Read-Only, Single Value

Range[1, $2^{32}-1$]**Description**

The REPLICATION_GROUPING_AHEAD_READ_NEXT_LOG_FILE property sets the value to be incremented to the current file being read by the sender; the Ahead Analyzer will start analyzing an XLog that increments (starting from the value of the current file) by as much as this value.

The value of this property can be altered using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_HBT_DETECT_HIGHWATER_MARK**Data Type**

Unsigned Integer

Default Value

5

Attribute

Read-Write, Single Value

Range[0, $2^{32}-1$]

Description

This property specifies the number of failed connection attempts to make before determining that a failure has occurred in a replication environment. Thus, the maximum time that can pass before it is determined that a host has failed can be calculated by multiplying
`REPLICATION_HBT_DETECT_TIME * REPLICATION_HBT_DETECT_HIGHWATER_MARK`.

In other words, if the HeartBeat thread (see below) fails to connect for 30 seconds (i.e. 5 attempts * 6 seconds, the default values for each of the above properties), it will be handled as a failure.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_HBT_DETECT_TIME (Unit: second)**Data Type**

Unsigned Integer

Default Value

6

Attributes

Read-Write, Single Value

Range

[0, 2592000]

Description

This property specifies the interval, in seconds, at which to check the HeartBeat thread¹². The HeartBeat thread checks the host for a fault every 6 seconds (the default value). This property can be changed using the ALTER SYSTEM statement while Altibase is running.

[¹²] HeartBeat thread

In an Altibase replication environment, in order to allow physical faults to be detected as quickly as possible while data are being exchanged between a Sender thread and a Receiver thread, a HeartBeat Thread is used to allow each host to regularly check the condition of the other host.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_IB_LATENCY**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property is the RDMA_LATENCY option value of rsocket.

If this value is 1, it uses latency even if it consumes CPU resources.

REPLICATION_IB_PORT_NO**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 65535]

Description

When connecting with replication, this property displays the connection port number of the local server when connecting using the InfiniBand.

To use the InfiniBand, the value of the IB_ENABLE property must be 1. If this value is 0, replication cannot be connected with the InfiniBand.

REPLICATION_INSERT_REPLACE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies whether to keep inserted contents if an insert conflict occurs during replication. If this value has been set to 0, the insert will not be committed, and the data conflict will be handled as an error, whereas if this value has been set to 1, the data conflict will be ignored and the insert will be committed.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_KEEP_ALIVE_CNT**Data Type**

Unsigned Integer

Default Value

600

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

A KEEP_ALIVE signal is sent when a Sender thread has not sent a packet and has slept for $\text{REPLICATION_SENDER_SLEEP_TIME} * \text{REPLICATION_KEEP_ALIVE_CNT}$.

REPLICATION_LOCK_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

5

Attributes

Read-Write, Single Value

Description

$[0, 3600]$

Description

When a replication deadlock occurs, the Receiver thread will wait indefinitely to establish a lock, which may result in a service interruption. To prevent this, when the Receiver thread requests a lock to perform this kind of operation, it will only wait for the number of seconds specified using this property.

If a lock cannot be acquired within the given time, the corresponding operation will be rolled back.

REPLICATION_LOG_BUFFER_SIZE (단위 : MB)**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read Only, Single Value

Range[0, 2¹²-1]**Description**

This property is set in order to improve replication performance using a dedicated replication log buffer. The dedicated replication log buffer filters and stores only replication logs. The Sender thread can read logs from the log buffer or from disk. However, when reading logs from disk, the processing speed of the Sender thread may be greatly reduced. Furthermore, the additional burden of reading unnecessary logs is imposed. The dedicated replication log buffer mitigates this burden.

When multiple replication Sender threads are working, replication and overall service performance can suffer. This is because there is only one replication log buffer, so if it is accessed by more than one Sender thread, synchronization overhead is more likely to occur. When the REPLICATION_SYNC_LOG value is set to 1, this property must be set to 0. Otherwise, the Altibase server will fail to start. If the value of this property is set too small, it may lead to worse performance than when it is not used at all (i.e. when it is set to 0).

REPLICATION_MAX_COUNT (Unit: count)**Data Type**

Unsigned Integer

Default Value

32

Attributes

Read-Only, Single Value

Range

[0, 10240]

Description

This property specifies the maximum number of replication objects which can be created in Altibase.

The default value is 32, which means that one server can connect to a maximum number of 32 remote servers by replication.

REPLICATION_MAX_LISTEN

Data Type

Unsigned Integer

Default Value

32

Attributes

Read-Only, Single Value

Range

[0, 512]

Description

This property specifies the maximum size of the “listen queue” when TCP/IP is used for communication between a Sender thread and an Altibase server that maintains a Receiver thread.

REPLICATION_MAX_LOGFILE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 65535]

Description

This property specifies the maximum number of log files preceding the Restart Redo Point that are to be prevented from being deleted, for use in replication. If, after replication starts, changes to a local server are not also made on a remote server for some reason, such as reduced network speed between the local and remote servers, replication will prevent log files from being deleted, even after checkpointing has taken place. Under such circumstances, the number of log files on the local server will continue to increase, which can ultimately lead to a disk full error.

Therefore, when checkpointing occurs, if the number of accumulated log files preceding the Restart Redo Point exceeds the number specified using this property, replication is temporarily suspended, and the time and XSN at which replication was suspended are stored in the GIVE_UP_TIME and GIVE_UP_XSN columns in the SYS_REPLICATIONS_ meta table. Additionally, all of the log files preceding the Restart Redo Point are deleted. The replication restart SN is set to the highest SN in the current log file, and this value is stored in the XSN column in the SYS_REPLICATIONS_ meta table. Replication will be performed starting from this new restart SN. If it is desired to change this default behavior, change the value of the REPLICATION_SENDER_START_AFTER_GIVING_UP property. Additionally, in order to reinitialize all

of the information pertaining to a particular replication object in the SYS_REPLICATIONS_ meta table, execute "ALTER REPLICATION replication_name RESET".

If the REPLICATION_MAX_LOGFILE property is set to 0, or if replication is running in EAGER mode, this function is disabled. Please note that because log files are erased when checkpointing is carried out, the values of the CHECKPOINT_INTERVAL_IN_SEC and CHECKPOINT_IN_LOG properties should be considered when setting the value of this property.

REPLICATION_POOL_ELEMENT_COUNT (Unit: count)

Data Type

Unsigned Integer

Default Value

10

Attributes

Read-Write, Single Value

Range

[1, 1024]

Description

This is the amount of memory (number of elements) used when a Sender thread analyzes a log and copies column values. Memory elements are pre-allocated from the memory pool, and their size is specified by REPLICATION_POOL_ELEMENT_SIZE.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_POOL_ELEMENT_SIZE (Unit : Byte)

Data Type

Unsigned Integer

Default value

256

Attributes

Read-Write, Single Value

Range

[128, 65536]

Description

This is the size of a memory element, in bytes, that is used when the sender thread analyzes a log and copies column values.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_PORT_NO

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 65535]

Description

This property specifies the replication port number on the local server, to be used when a replication connection is established. Set this property to 0 to disable replication.

REPLICATION_PREFETCH_LOGFILE_COUNT

Data Type

Unsigned Integer

Default Value

3

Attributes

Read-Write, Single Value

Range

[0, 1024]

Description

This property specifies the number of prefetch log files, that is, the number of log files in each log file group that are read in advance. Pre-reading and caching log files allows the Sender thread to read logs from log files more quickly.

REPLICATION_RECEIVE_TIMEOUT (Unit: second)

Data Type

Unsigned Integer

Default Value

7200

Attributes

Read-Write, Single Value

Range

[0, 2³²-1]

Description

This property, which is used by both the Sender thread and the Receiver thread, specifies the maximum amount of time, in seconds, to wait for a message from the Receiver or Sender thread, respectively.

In the case where the Sender thread has waited for a response from the Receiver thread for the maximum amount of time specified here, the Sender thread will enter into sleep mode for the amount of time specified using the REPLICATION_SENDER_SLEEP_TIMEOUT property before again attempting to connect to the Receiver thread. In this case, the existing socket is closed and a new socket is created for the new connection attempt.

This property also specifies the maximum time that the Receiver thread waits for a message from a Sender thread. If the specified amount of time has passed, the Receiver thread is automatically terminated, and a new Receiver thread will be created when the Sender thread sends a message.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_RECEIVER_APPLIER_ASSIGN_MODE**Data Type**

Unsigned Integer

Default Value

0

Attributes

REPLICATION_RECEIVER_APPLIER_ASSIGN_MODE

Range

[0, 1]

Description

The REPLICATION_RECEIVER_APPLIER_ASSIGN_MODE property sets the mode in which the replication sender is to assign XLogs to the applier.

0: XLog Count Mode

1: Transaction Count Mode

If the REPLICATION_RECEIVER_APPLIER_ASSIGN_MODE property is set to 0, XLogs are assigned to the applier with the least amount of XLogs.

If the REPLICATION_RECEIVER_APPLIER_ASSIGN_MODE property is set to 1, XLogs are assigned to the applier with the least number of transactions.

The value of this property can be altered using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_RECEIVER_APPLIER_QUEUE_SIZE**Data Type**

Unsigned Integer

Default Value

20

Attributes

Read-Write, Single Value

Range

$[2, 2^{32}-1]$

Description

The REPLICATION_RECEIVER_APPLIER_QUEUE_SIZE sets the maximum number of XLogs that the sender is allowed to be passed to the queue for applier threads.

Although a large value for the REPLICATION_RECEIVER_APPLIER_QUEUE_SIZE property means that a large number of XLogs will be passed to the applier, memory usage increases because XLogs are queued. The user is recommended to set the REPLICATION_RECEIVER_APPLIER_QUEUE_SIZE property to twice as much as the number of appliers.

The value of this property can be altered using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_RECOVERY_MAX_LOGFILE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum number of log files that are not deleted, based on a Restart Redo Point, for data recovery using replication.

In order to recover data at the time of replication, the local server does not delete logs that have not been flushed to disk on remote servers. Even if checkpointing takes place at this time, because the log files cannot be deleted, the number of log files on the local server will continue to increase and this can ultimately lead to a disk full error.

Thus, if the maximum log file count in the recovery options is exceeded when checkpointing occurs, replication-based recovery is aborted and the log files are deleted. Then, replication starts over.

If this property is set to 0 or replication runs in eager mode, this function is not used. Because log files are deleted when checkpointing occurs, the values of CHECKPOINT_INTERVAL_IN_SEC and CHECKPOINT_IN_LOG should be considered together.

REPLICATION_RECOVERY_MAX_TIME (Unit: second)

Data Type

Unsigned Integer

Default Value

$2^{32}-1$

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

If the number of seconds specified using this property is exceeded while the replication module is performing recovery, recovery is stopped and service is provided in the state in which recovery has been performed up to that point.

If this property is set to 0, replication-based recovery is not performed.

Before replication-based data recovery is completed, Altibase will not be able to proceed to the service stage, and service may be delayed.

REPLICATION_SENDER_AUTO_START

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

$[0, 1]$

Description

If a replication object which has not been stopped at the termination of the previous Altibase server exists, this replication object is automatically started by default when the server restarts.

If this value is set to 0, a replication object can be prevented from automatically starting.

REPLICATION_SENDER_COMPRESS_XLOG**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies whether or not a packet is to be compressed, when data is transmitted via network for replication purposes.

0: Compression is disabled for transmissive data

1: Compression is enabled for transmissive data

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_SENDER_ENCRYPT_XLOG**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

The REPLICATION_SENDER_ENCRYPT_XLOG property sets whether or not to encrypt XLogs that the sender thread sends during replication.

0: Does not encrypt XLogs.

1: Encrypts XLogs.

REPLICATION_SENDER_SEND_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

7200

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum amount of time that the sending thread will wait when sending a packet to a remote server.

It is recommended that this value be the same as the value of the REPLICATION_RECEIVER_TIMEOUT (default 7200 seconds) property. If the value is set to 0, the sender thread uses a blocking socket.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_SENDER_SLEEP_TIME (Unit: microsecond)**Data Type**

Unsigned Integer

Default Value

10000

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This property indicates the sleep time, in microseconds, when there are no more logs to be read by the Sender thread. Because certain platforms ignore short Sleep time values, a suitable value must be specified. The value specified here is used in conjunction with REPLICATION_KEEP_ALIVE_CNT to determine when to send KEEP_ALIVE.

REPLICATION_SENDER_SLEEP_TIMEOUT (Unit: second)**Data Type**

Unsigned Integer

Default Value

60

Attributes

Read-Write, Single Value

Range

[0, 2592000]

Description

This property specifies the number of microseconds that a replication Sender thread that is in an error state must sleep before trying again.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_SENDER_START_AFTER_GIVING_UP**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property determines how replication proceeds after replication has been suspended due to the number of accumulated log files preceding the Restart Redo Point exceeding the value of the REPLICATION_MAX_LOGFILE property.

If this value is set to 0, the replication restart SN (which is stored in the XSN column in the SYS_REPLICATIONS_ meta table) is reinitialized (set to -1), and replication is suspended. Additionally, the value of the IS_STARTED column in the SYS_REPLICATIONS_ meta table is set to 0.

If this value is set to 1, the replication restart SN is set to the last generated sequence number in the current log file, and replication is performed starting from this new restart SN.

REPLICATION_SERVER_FAILBACK_MAX_TIME**Data Type**

Unsigned Integer

Default Value

$2^{32}-1$

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

In EAGER mode replication, when a server that was terminated abnormally is restarted, it resumes providing service only after it has synchronized its data with the data on another (i.e. the remote) server. At this time, if the process of applying the logs from the other server on the server that experienced the fault takes longer than the number of seconds specified using this property, the server that experienced the fault gives up waiting for synchronization to complete.

REPLICATION_SQL_APPLY_ENABLE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

$[0, 1]$

Description

This property configures how to synchronize inconsistent data between the local and remote servers during the replication.

- 0: Replication works using XLog. At this time, if the meta information is different, a Handshaking error occurs.
- 1: If replication is performed under the following conditions, XLog is converted into a SQL statement and reflected in the replicated table.
 - Column information
If the data types are different.
If sizes, precisions, and scales are different.
 - Constraints
If the check constraints are different.

If Not Null constraints are different.

If any of the other meta information contains a LOB column.

- Indexes

If a unique index or function-based index consists of columns to be replicated and not to be replicated

If the configuration information for the unique index is different

If the configuration information for the function-based index is different

REPLICATION_SYNC_APPLY_METHOD

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property configures how to synchronize inconsistent data between the local and remote servers during the replication.

- 0: Normal Insert
- 1: Direct-Path Insert

Please refer to *Administrator's Manual* for in-depth description on Direct-Path Insert.

The value of this property can be modified through ALTER SYSTEM statement during the Altibase operation.

REPLICATION_SYNC_LOCK_TIMEOUT (Unit: second)

Data Type

Unsigned Integer

Default Value

30

Attributes

Read-Write, Single Value

Range

[0, 2³²-1]

Description

When replication synchronization is performed, the Replication Sender Thread determines the current position in the log at which replication will start after synchronization. In order to prevent another transaction from changing the data in the table on which synchronization is to be performed right at the time of this determination, the Replication Sender Thread obtains an S Lock on the table on which synchronization is to be performed for a short time before synchronization. This property specifies the amount of time, in seconds, to wait to establish a lock when a table to be synchronized has been locked by another transaction. If a lock is requested but cannot be obtained immediately, the replication process will wait for the amount of time specified here. If a lock cannot be obtained within the amount of time specified here, the synchronization attempt will be handled as an error. If this value is specified as 0, a lock is not established on the replication target table; however, data conflict can occur.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_SYNC_LOG**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

When performing replication, because the Sender thread sends logs that are in memory regardless of whether they have been committed to disk, data inconsistency or other problems may occur in the event of system or media failure.

To prevent this problem, setting this value to 1 ensures that the Sender thread only sends logs that have already been committed to disk.

REPLICATION_SYNC_TUPLE_COUNT**Data Type**

Unsigned long

Default Value

50000

Attributes

Read-Write, Single Value

Range

$[0, 2^{64}-1]$

Description

This property specifies the maximum number of records that each Sender thread can read and handle during parallel synchronization.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_TIMESTAMP_RESOLUTION**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value $\frac{7}{8}$

Range

$[0, 1]$

Description

In an Active-Active replication environment, if this property is set to 1 and a TIMESTAMP column exists in a given replication target table, then the TIMESTAMP-based resolution scheme is used to resolve any data conflicts that occur in that table.

However, even if a TIMESTAMP column exists in a replication target table, if this value has been set to 0, some other conflict resolution scheme is used.

For more detailed information about TIMESTAMP-based resolution and data conflicts, please refer to the *Altibase Replication Manual*.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_TRANSACTION_POOL_SIZE**Data Type**

Unsigned Integer

Default Value

2

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

Replication receivers use transactions when copying data and create respective transaction pools - wherein transactions can be created in advance for use - for performance improvement. This property specifies the number of transactions that are to be created in advance in transaction pools.

If the number of transactions existing in pools falls short, the replication receiver will create new transactions and use them. The transactions thus created are returned to pools after use; if the number of transactions existing at that time is larger than the value specified in this property, the transactions are immediately freed, instead of being returned.

If set to an excessively large value, it can constrain the number of normal transactions; therefore, an appropriate number of transactions must be specified. This property permits the maximum value of $2^{32}-1$; however, the actual maximum value is identical to the value specified in the property of TRANSACTION_TABLE_SIZE. If the user specifies this value to be larger than the value of TRANSACTION_TABLE_SIZE, the value of this property will be internally set as the value of the TRANSACTION_TABLE_SIZE.

This property value can be changed while Altibase is running; however, transaction pools are initialized at the creation of replication receiver threads and replication must be restarted for the modified property values to be applied.

This property value can be changed using the ALTER SYSTEM statement while Altibase is running.

REPLICATION_UPDATE_REPLACE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 1]$

Description

This property specifies whether to keep updated contents if an update conflict occurs during replication. If this value has been set to 0, the update will not be committed, and the data conflict will be handled as an error, whereas if this value has been set to 1, the data conflict will be ignored and the update will be committed.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

Network and Security Properties

IB_CONCHKSPIN

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 2147483]

Description

This property sets the value of the RDMA_CONCHKSPIN option of rsocket. This is the value to set which period to check the connection of InfiniBand. If this value is 0, the default value of rsocket is used.

This property is only available when using the Altibase rdma-core. (<https://github.com/ALTIBASE/rdma-core>)

IB_ENABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read Only, Single Value

Range

[0, 1]

Description

This property is an option to use InfiniBand in Altibase. This feature is only available on Linux.

0 : IB is not used (default value).

1: IB is used.

IB_LATENCY

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property sets the value of the RDMA_LATENCY option of rsocket.

If the value of this property is 1, tuning code is used to reduce latency even though it consumes more CPU resources.

This property is only available when using the Altibase rdma-core. (<https://github.com/ALTIBASE/rdma-core>)

IB_LISTENER_DISABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property can set whether to start the InfiniBand listener when starting Altibase.

0: InfiniBand listener is started (default).

1: InfiniBand listener is not started.

IB_MAX_LISTEN

Data Type

Unsigned Integer

Default Value

128

Attributes

Read-Only, Single Value

Range

[0, 1024]

Description

This property specifies the maximum number of clients that can connect to InfiniBand and use Altibase at the same time.

IB_PORT_NO**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[1024, 65535]

Description

This property specifies the port number used for communication using the InfiniBand.

SNMP_ALARM_QUERY_TIMEOUT**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

Sets whether or not to send a trap when a query timeout occurs in a session. The default value is 1 and sends a trap. For more detailed information, please refer to `altiPropertyAlarmQueryTimeout` in the SNMP Agent Guide.

SNMP_ALARM_FETCH_TIMEOUT**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

Sets whether or not to send a trap when a fetch timeout occurs. The default value is 1 and sends a trap. For more detailed information, please refer to `altiPropertyAlarmFetchTimeout` in the SNMP Agent Guide.

SNMP_ALARM_UTRANS_TIMEOUT**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

Sets whether or not to send a trap when a utrans timeout occurs.

0: Does not raise a trap.

1: Raises a trap.

For more detailed information, please refer to `altiPropertyAlarmUtransTimeout` in the SNMP Agent Guide.

SNMP_ALARM_SESSION_FAILURE_COUNT

Data Type

Unsigned Integer

Default Value

3

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

Sets the number of times an error is allowed to continuously occur before a trap is sent. The default value is 3. If the value is 0, a trap is not sent. For more detailed information, please refer to altiPropertyAlarmSessionFailureCount in the SNMP Agent Guide.

SNMP_ENABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read Only, Single Value

Range

$[0, 1]$

Description

To use SNMP, this property must be set to 1(Enable). The default value is 0(Disable).

0 : Use SNMP

1: Do not use SNMP

SNMP_MSGLOG_FLAG

Data Type

Unsigned Integer

Default Value

3

Attributes

Read-Write, Single Value

Range

[3, 12]

Description

Sets the log output level. Four levels ('1', '2', '4', '8') are available and the sum of these can comprise a level. The default value is 3(1+2) and logs are output for Level1 and Level3.

SNMP_PORT_NO**Data Type**

Unsigned Integer

Default Value

20400

Attributes

Read-Only, Single Value

Range

[1024, 65535]

Description

This is the UDP port for communication between Altibase and altisnmpd (Altibase SNMP subagent).

SNMP_TRAP_PORT_NO**Data Type**

Unsigned Integer

Default Value

20400

Attributes

Read-Only, Single Value

Range

[1024, 65535]

Description

This is the UDP port for sending traps between Altibase and altisnmpd (Altibase SNMP subagent).

SNMP_RECV_TIMEOUT (Unit: millisecond)**Data Type**

Unsigned Integer

Default Value

1000

Attributes

Read-Only, Single Value

Range

[1, 2³²-1]

Description

This is the communication timeout value.

When Altibase and altisnmpd(Altibase SNMP subagent) communicate, the application waits for as many milliseconds as specified for this property.

SNMP_SEND_TIMEOUT (Unit: millisecond)**Data Type**

Unsigned Integer

Default Value

100

Attributes

Read-Only, Single Value

Range

[1, 2³²-1]

Description

This is the communication timeout value.

When Altibase and altisnmpd (Altibase SNMP subagent) communicate, the application waits for as many milliseconds as specified for this property.

SSL_CA**Data Type**

String

Default Value

None

Attributes

Read-Only, Single Value

Range

None

Description

Specifies the file path to store CA certificates to certify the ownership of received certificates. CA certificates can exist in a user-specific file path or a X.509 structured directory. An example of this value could be \$ALTIBASE_HOME/cert/ ca-cert.pem.

SSL_CAPATH**Data Type**

String

Default Value

None

Attributes

Read-Only, Single Value

Range

None

Description

Specifies CAPATH in a CA directory format. An example of this value could be \$ALTIBASE_HOME/etc/ssl/certs.

SSL_CERT**Data Type**

String

Default Value

None

Attributes

Read-Only, Single Value

Range

None

Description

Sets the Altibase certificate path. An example of this value could be \$ALTIBASE_HOME/cert.pem.

SSL_CIPHER_LIST**Data Type**

String

Default Value

None

Attributes

Read-Only, Single Value

Range

255

Description

A list of cipher algorithms available for the server and client to use and negotiate with. Depending on your security policy, you can specify one or more cipher names and separate them by colons. You can check the list at OpenSSL (<http://www.openssl.org/>) or execute the following command in the shell environment.

```
$ openssl ciphers
```

SSL_CIPHER_SUITES**Data Type**

String

Default Value

None

Attributes

Read-Only, Single Value

Range

None

Description

This property allows users to set one or more specific cipher algorithm candidates for TLS v1.3, separated by a colon (:). If not configured, OpenSSL allows the use of all available TLS 1.3 cipher algorithm candidates.

SSL_CLIENT_AUTHENTICATION

Data Type

Unsigned Integer

Default Value

0

Attributes

Read Only, Single Value

Range

[0, 1]

Description

Sets whether or not to request a certificate from the client when the server and client communicate over SSL. If the value is 0 (default), the client requests a certificate from the server. If the value is 1, the server requests a certificate from the client during the SSL handshake.

0: Authenticates the server only (default)

1: Authenticates the server and client concurrently

SSL_ENABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

Switches the SSL/TLS feature on or off within Altibase. The default value is 0 (Disable).

0: Disables SSL/TLS

1: Enables SSL/TLS

SSL_KEY

Data Type

String

Default Value

None

Attribute

Read-Only, Single Value

Range

None

Description

Sets the server private (secret) key path.

An example of this value could be \$ALTIBASE_HOME/cert/server- key.pem.

SSL_LOAD_CONFIG**Data Type**

String

Default Value

0

Attributes

Read-Only, Single Value

Range

[0,1]

Description

This property configures loading the OpenSSL configuration file (openssl.cnf). The default value is 0 (Disable). To use the OpenSSL FIPS module, this property should be set to 1.

0: Do not load the file

1: Load the file

SSL_MAX_LISTEN**Data Type**

Unsigned Integer

Default Value

128

Attributes

Read-Only, Single Value

Range

[0, 16384]

Description

Sets the listen queue maximum size for concurrent SSL/TLS connections. Note that more listeners require more memory.

SSL_PORT_NO**Data Type**

Unsigned Integer

Default Value

20443

Attributes

Read-Only, Single Value

Range

[1024, 65535]

Description

Specifies the listening port number for SSL connections.

TCP_ENABLE**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

Altibase server can configure whether or not to communicate with TCP/IP as a communication protocol.

0: Using TCP/IP

1: Not using TCP/IP

Message Logging Properties

ALL_MSGLOG_FLUSH

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

If this property is set to 1, all database messages are written immediately to disk, whereas if it is set to 0, Altibase writes the messages all at once at regularly scheduled intervals. In order to prevent reduced performance attributable to excessive logging, it is recommended that this value be set to 0 for normal operations, and that it be set to 1 when troubleshooting.

COLLECT_DUMP_INFO

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies whether or not information about message files and log files are to be collected when the server terminates abnormally.

0: Information about message files and log files are not collected.

1: Information about message files and log files are collected.

DK_MSGLOG_COUNT

Data Type

Unsigned Integer

Default Value

10

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum number of message files that in the connection process when linking a database.

DK_MSGLOG_FILE

Data Type

String

Default Value

altibase_lik.log

Attributes

Read-Only, Single Value

Range

None

Description

This is property specifies a database link file that records message that occur during the connection process.

DK_MSGLOG_FLAG

Data Type

Unsigned Integer

Default Value

6

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

Flag value indicating whether warning messages or trace messages generated by the connection process module of the database link are logged to LK_MSGLOG_FILE.

If it is 0, it is not written. If it is greater than 0, it is written.

DK_MSGLOG_SIZE**Data Type**

Unsigned Integer

Default Value

$10 * 1024 * 1024$

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum size of the message file of the connect process in the database link.

DUMP_MSGLOG_COUNT**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum number of message files to which debugging information for server errors are written.

DUMP_MSGLOG_FILE**Data Type**

String

Default Value

altibase_dump.log

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the name of the message file to which debugging information for server errors is written.

DUMP_MSGLOG_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[0, 2³²-1]

Description

This property specifies the name of the message file to which debugging information for server errors is written.

DUMP_MSGLOG_RESERVE_SIZE (Unit : byte)**Data type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-only, Single value

Range

[0, 2³²-1]

Description

This property specifies the amount of space to secure in advance on the disk to store the message file in which debugging information is recorded.

ERROR_MSGLOG_COUNT**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read-Only, Single Value

Range

[0, 2³²-1]

Description

This property specifies the maximum number of message files for server errors.

ERROR_MSGLOG_FILE**Data Type**

String

Default Value

altibase_error.log

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the name of the file to which errors raised on the server are written. Also, the process call stack is recorded in this file when Altibase shuts down abnormally.

ERROR_MSGLOG_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum size, in bytes, of the file to which server error messages are stored.

ERROR_MSGLOG_RESERVE_SIZE (Unit : byte)**Data type**

Unsigned Integer

Default value

10 * 1024 * 1024

Attributes

Read-Only, Single value

Range

$[0, 2^{32}-1]$

Description

This property specifies the amount of space to be reserved in advance for the file where the server error message is stored.

LB_MSGLOG_COUNT**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read-Only, Single Value

Range

[0, 2³²-1]

Description

This property specifies the maximum number of message files about service thread.

LB_MSGLOG_FILE**Data Type**

String

Default Value

altibase_lb.log

Attributes

Read-Only, Single Value

Range

None

Description

This property is the file to which service thread-related message are written.

LB_MSGLOG_FLAG**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 2³²-1]

Description

This property specifies the message of service thread to be written to LB_MSGLOG_FILE as follows.

0: not record

1: Creation and release of the service thread

2: Log for the service thread moved to task

3: (1+2) Creation and release of the service thread, log for the service thread moved to task

LB_MSGLOG_SIZE

Data Type

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[0, $2^{32}-1$]

Description

This property specifies the maximum size of the file to which service thread are written.

MM_MSGLOG_COUNT

Data Type

Unsigned Integer

Default Value

10

Attributes

Read-Only, Single Value

Range

[0, $2^{32}-1$]

Description

This sets the maximum number of message files for the Main module.

MM_MSGLOG_FILE

Data Type

String

Default Value

altibase_mm.log

Attributes

Read Only, Single Value

Range

None

Description

This property specifies the file in which to write messages that arise during Main module processing.

MM_MSGLOG_RESERVE_SIZE (Unit : byte)**Data type**

Unsigned Integer

Default value

10 * 1024 * 1024

Attributes

Read-Only, Single value

Range

[0, $2^{32}-1$]

Description

This property specifies the amount of space to reserve on the disk in advance to store the message file for the main module.

MM_MSGLOG_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

[0, $2^{32}-1$]

Description

This property sets the maximum size of the Main module message files.

MM_SESSION_LOGGING

Data Type

Unsigned Integer

Default

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This is a flag value that indicates whether to write session information regarding all database logon and logoff events to MM_MSGLOG_FILE. Session information includes session ID, user name, IP address, client program PID and other details about the client program.

If this property is set to 0, no messages are written, whereas if it is set to 1, the messages are written.

NETWORK_ERROR_LOG

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies whether to write network-related error messages in the server message file.

In an unstable network environment, in which error messages are frequently output, setting this value to 0 prevents network-related error messages from being output.

QP_MSGLOG_COUNT

Data Type

Unsigned Integer

Default Value

10

Attributes

Read-Only, Single Value

Range $[0, 2^{32}-1]$ **Description**

This property sets the maximum number of message log files for the Query Processor.

QP_MSGLOG_FILE**Data Type**

String

Default Value

altibase_qp.log

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the name of the file in which to write messages when processing queries.

QP_MSGLOG_FLAG**Data Type**

Unsigned Integer

Default Value

2

Attributes

Read-Write, Single Value

Range $[0, 2^{32}-1]$ **Description**

This is a flag value that indicates whether to write trace messages generated by the Query Processor in QP_MSGLOG_FILE.

If this property is set to 0, the messages are not written, whereas if it is set to a value greater than 0, the messages are written.

QP_MSGLOG_RESERVE_SIZE (Unit : byte)**Data type**

Unsigned Integer

Default value

10 * 1024 * 1024

Attributes

Read-Only, Single value

Range

$[0, 2^{32}-1]$

Description

This property specifies the amount of space to be reserved on disk to store the message file of the query processor.

QP_MSGLOG_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum size, in bytes, of the Query Processor message log files.

QUERY_PROF_FLAG**Data Type**

Integer

Default Value

0

Attributes

Read-Write, Single Value

Range[0, 2⁶-1]**Description**

This property enables information about the work being conducted by a server and the overall state of the server to be written to a file for later analysis. The user can specify that information is written as desired by suitably combining the following values:

- 0 : Write nothing
- 1: Every time a SQL statement is executed, write the executed SQL statement, execution time, execution information, and information about index and disk access. The value for the TIMED_STATISTICS property must be set to 1 to print the proper execution time.
- 2: Every time a SQL statement is executed, write the BIND parameter(s).
- 4: Every time a SQL statement is executed, write the execution plan.
- 8: Write session information (i.e. the data in V\$SESSTAT) every 3 seconds.
- 16: Write system information (i.e. the data in V\$SYSSTAT) every 3 seconds.
- 32: Write information about memory (i.e. the data in V\$SYSSTAT) every 3 seconds.

For example, if this property is set to 1+4+32=37, then whenever a SQL statement is executed, the execution information and execution plan for the SQL statement is written, and additionally, information about memory is written every 3 seconds.

This file can be converted to a form suitable for analysis using the altiprofile utility. For more information, please refer to the portion of the *Altibase Utilities Manual* pertaining to the altiprofile utility.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

QUERY_PROF_LOG_DIR**Data Type**

String

Default Value

\$ALTIBASE_HOME/trc

Attributes

Read-Write, Single Value

Range

[1, 1024]

Description

This property specifies the directory path in which files to which status information of the Altibase server and operations executed on it are written are to be saved.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

RP_CONFLICT_MSGLOG_COUNT

Data Type

Unsigned Integer

Default

10

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum number of files to which the trace log is written in the event of a replication conflict.

RP_CONFLICT_MSGLOG_DIR

Data Type

String

Default

\$ALTIBASE_HOME/trc

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the directory for the file to which the trace log is written in the event of a replication conflict.

RP_CONFLICT_MSGLOG_ENABLE

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property specifies whether or not the trace log of a replication conflict is to be written.

RP_CONFLICT_MSGLOG_FILE**Data Type**

String

Default Value

altibase_rp_conflict.log

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the file to which the trace log of a replication conflict is written.

RP_CONFLICT_MSGLOG_FLAG**Data Type**

Unsigned Integer

Default Value

6

Attributes

Read-Write, Single Value

Range

[0, $2^{32}-1$]

Description

This property specifies the logging level of the trace log of a replication conflict.

The following values are available for specification:

2: Writes conflict messages

4: Writes SQL statements that cause conflict

6: Write both conflict messages and SQL statements that cause conflict

RP_CONFLICT_MSGLOG_RESERVE_SIZE (Unit : byte)**Data type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Only, Single value

Range

$[0, 2^{32}-1]$

Description

This property specifies the amount of space to be reserved on disk for storing the trace log file for a replication collision.

RP_CONFLICT_MSGLOG_SIZE (Unit: bytes)**Data Type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum size, in bytes, of replication conflict trace logs.

RP_MSGLOG_COUNT**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum number of replication message log files.

RP_MSGLOG_FILE**Data Type**

String

Default Value

altibase_rp.log

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the name of the file in which to write messages output from the Replication Manager.

RP_MSGLOG_FLAG**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This is a flag value that indicates whether to write trace messages generated by the Replication Manager module in RP_MSGLOG_FILE.

If this property is set to 0, no messages are written, whereas if it is set to a value greater than 0, the messages are written.

RP_MSGLOG_RESERVER_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the amount of space to be reserved on the disk for storage of the replication message file.

RP_MSGLOG_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum size, in bytes, of the replication message log file.

SERVER_MSGLOG_COUNT**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read Only, Single Value

Range

[0, 2³²-1]

Description

This property specifies the maximum number of server message log files.

SERVER_MSGLOG_DIR**Data Type**

String

Default Value

\$ALTIBASE_HOME/trc

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the path in which altibase.lock, which is an internally used server maintenance file, and SERVER_MSGLOG_FILE, which is the server module message file in which information about the server startup, shutdown etc. is written, are located.

This directory can also serve as the default directory for individual server modules' message files, such as SM_MSGLOG_FILE, QP_MSGLOG_FILE, RP_MSGLOG_FILE and the like.

SERVER_MSGLOG_FILE**Data Type**

String

Default Value

altibase_boot.log

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the file name for messages left by the server module.

Messages pertaining to Altibase startup, warnings, and abnormal termination are written to the server message log file.

SERVER_MSGLOG_FLAG

Data Type

Unsigned Integer

Default Value

7

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This is a flag value that indicates whether to write trace messages generated by the server module in SERVER_MSGLOG_FILE.

If this property is set to 0, no messages are written, whereas if it is set to a value greater than 0, the messages are written.

SERVER_MSGLOG_RESERVE_SIZE (Unit : byte)

Data type

Unsigned Integer

Default Value

$10 * 1024 * 1024$

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the amount of space to be reserved on the disk for storage of the server message file.

SERVER_MSGLOG_SIZE (Unit: byte)

Data Type

Unsigned Integer

Default Value

$10 * 1024 * 1024$

Attributes

Read-Only, Single Value

Range

[0, 2³²-1]

Description

This property specifies the maximum size, in bytes, of server message log files.

SM_MSGLOG_COUNT**Data Type**

Unsigned Integer

Default Value

10

Attributes

Read-Only, Single Value

Range

[0, 2³²-1]

Description

This property specifies the maximum number of Storage Manager message log files.

SM_MSGLOG_FILE**Data Type**

String

Default Value

altibase_sm.log

Attributes

Read Only, Single Value

Range

None

Description

This property specifies the prefix of the name of the message file(s) in which the Storage Manager writes messages.

SM_MSGLOG_FLAG**Data Type**

Unsigned Integer

Default Value

2147483647

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This is a flag value that indicates whether to write trace messages generated by the Storage Manager module in the file(s) specified in SM_MSGLOG_FILE.

If this property is set to 0, no messages are written, whereas if it is set to a value greater than 0, the messages are written.

SM_MSGLOG_RESERVE_SIZE (Unit : byte)**Data Type**

Unsigned Integer

Default Value

$10 * 1024 * 1024$

Attributes

Read-Only, Single value

Range

$[0, 2^{32}-1]$

Description

This property specifies the amount of space to be reserved on the disk to store the message file of the storage manager.

SM_MSGLOG_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

$10 * 1024 * 1024$

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum size, in bytes, of the Storage Manager message log files.

TRC_MSGLOG_RESERVE_SIZE (Unit : byte)**Data Type**

Unsigned Integer

Default Value

$10 * 1024 * 1024$

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the size in advance to secure the space of the trace log file on the disk where warning messages, etc., generated when starting the server can be recorded.

TRCLOG_DETAIL_PREDICATE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

$[0, 1]$

Description

When Explain Plan mode is being used in iSQL, this property specifies whether to display the status of a predicate portion of a WHERE clause. To use this trace log, set this parameter to 1.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

XA_MSGLOG_COUNT

Data Type

Unsigned Integer

Default Value

10

Attributes

Read Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the maximum number of XA message files used by the server.

XA_MSGLOG_FILE

Data Type

String

Default Value

altibase_xa.log

Attributes

Read-Only, Single Value

Range

None

Description

This property specifies the prefix of the name of the file(s) in which XA message logs from the server are written.

XA_MSGLOG_FLAG

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 3]

Description

This property determines which of the server XA messages to write to disk. The possible values are as follows:

0: Write only critical XA-related messages

1: Write messages pertaining to XA calls

2: Write messages when XIDs are allocated, freed, etc.

3: Write all message logs related to XA

XA_MSGLOG_RESERVE_SIZE (Unit : byte)**Data Type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read-Only, Single Value

Range[0, 2³²-1]**Description**

This property specifies the amount to space to be reserved in advance for storage of the XA message file for the server.

XA_MSGLOG_SIZE**Data Type**

Unsigned Integer

Default Value

10 * 1024 * 1024

Attributes

Read Only, Single Value

Range[0, 2³²-1]

Description

This property specifies the maximum size of XA message files used by the server.

Database Link Properties**DBLINK_ALTIlinker_CONNECT_TIMEOUT (Unit: second)****Data Type**

Unsigned Integer

Default Value

100

Attributes

Read-Only, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the connection timeout, in seconds, when the Altibase server attempts to establish a connection to AltiLinker.

DBLINK_DATA_BUFFER_ALLOC_RATIO**Data Type**

Unsigned Integer

Default Value

50

Attributes

Read-Only, Single Value

Range

$[0, 1]$

Description

This is the space in which the local server retrieves and stores the result sets of a query executed on a remote server through a database link. This is called the database link-exclusive data buffer. This property specifies the ratio of the record buffer to be allocated per query for the remaining space in the database link-exclusive data buffer.

DBLINK_DATA_BUFFER_BLOCK_COUNT**Data Type**

Unsigned Integer

Default Value

128

Attributes

Read-Only, Single Value

Range

$[0, 2^{12}-1]$

Description

This is the space in which the local server retrieves and stores the result sets of a query executed on a remote server through a database link. This is called the database link-exclusive data buffer. This property specifies the initial number of allocations for record buffer blocks that compose the data buffer. The size of the data buffer is `DBLINK_DATA_BUFFER_BLOCK_COUNT * DBLINK_DATA_BUFFER_BLOCK_SIZE`.

DBLINK_DATA_BUFFER_BLOCK_SIZE (Unit: byte)**Data Type**

Unsigned Integer

Default Value

2 MBytes

Attributes

Read-Only, Single Value

Range

$[0, 29]$

Description

This is the space in which the local server retrieves and stores the result sets of a query executed on a remote server through a database link. This is called the database link-exclusive data buffer. This property specifies the size, in bytes, of the record buffer block which composes the data buffer.

DBLINK_ENABLE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies the AUTOCOMMIT mode of the remote database. This property is only applied when the DBLINK_GLOBAL_TRANSACTION_LEVEL is set to 0.

0: Autocommit-Off

1: Autocommit-On

DBLINK_GLOBAL_TRANSACTION_LEVEL**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0, 2]

Description

This property specifies the execution level of the global transaction. When this property is set to 0, the DBLINK_REMOTE_STATEMENT_AUTOCOMMIT property must be set to correspond to the AUTOCOMMIT mode of the remote database.

- 0: Remote Statement Execution Level.

This level perceives each transaction on servers(local and remote servers) participating in one global transaction as separate transactions, so the transactions must be respectively committed at the local and remote servers in order to commit the global transaction. Even if a global transaction is in this level, a COMMIT performed on the local server does not affect the remote server.

- 1: Simple Transaction Commit Level.

This level perceives all transactions on servers(local and remote servers) participating in one global transaction as one transaction. Therefore, if a global transaction is committed on a local server, all transactions participating in the global transaction are committed..

- 2:Two-Phase Commit (2PC) Level.

At this level, the 2PC protocol is supported to ensure transaction consistency of database systems that participating in one global transaction. If a global transaction begins, this property cannot be changed until the end of the transaction.

DBLINK_RECOVERY_MAX_LOGFILE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[1, $2^{32}-1$]

Description

This property specifies the maximum number of log files that Altibase HDB maintains or distributed transaction recovery when a heterogeneous database system fails during a transaction.

If this property value is 0, consistency is guaranteed because the log for distributed transaction recovery is not deleted.

However, if the property value is set to a value greater than 1, consistency cannot be guaranteed because the log is deleted by a checkpoint even if the distributed transaction is not completed when the number of log files is exceeded.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

DBLINK_REMOTE_STATEMENT_AUTOCOMMIT

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies the AUTOCOMMIT mode of the remote database. This property is only applied when the DBLINK_GLOBAL_TRANSACTION_LEVEL is set to 0.

0: Autocommit-Off

1: Autocommit-On

DBLINK_REMOTE_TABLE_BUFFER_SIZE (Unit: MB)**Data Type**

Unsigned Integer

Default Value

50

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This is a memory buffer which can temporarily store query results if a query is executed through REMOTE_TABLE keyword in the remote server.

The stored query results are deleted after being delivered to a query processor. However, the property value should be adjusted since it cannot be specified if one of records of the result set is larger than the specified size.

Auditing Properties**AUDIT_FILE_SIZE (Unit: byte)****Data Type**

Unsigned Int

Default Value

100M

Attributes

Read-Write, Single Value

Range

$[0, 2^{32}-1]$

Description

This property specifies the size of the binary audit log file in bytes. This property is used when AUDIT_OUTPUT_METHOD is 0.

The value of this property can be changed using the ALTER SYSTEM statement, as shown below, while Altibase is running.

```
ALTER SYSTEM SET AUDIT_FILE_SIZE=10000;
```

However, if the server is in the process of auditing, the changed size applies to files that are created thereafter. For the immediate application of the changed value of this property, restart auditing with the ALTER SYSTEM STOP AUDIT and ALTER SYSTEM START AUDIT statement.

AUDIT_LOG_DIR**Data Type**

String

Default Value

\$ALTIBASE_HOME/trc

Attributes

Read-Write, Multiple Value

Range

None

Description

This property specifies the directory in which the binary audit log file is created. This property is used when AUDIT_OUTPUT_METHOD is 0.

The value of this property can be changed using the ALTER SYSTEM statement, as shown below, while Altibase is running.

```
ALTER SYSTEM SET AUDIT_LOG_DIR='/tmp';
```

However, if the server is in the process of auditing, the changed size applies to files that are created thereafter. For the immediate application of the changed value of this property, restart auditing with the ALTER SYSTEM STOP AUDIT and ALTER SYSTEM START AUDIT statement.

AUDIT_OUTPUT_METHOD**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 9]

Description

This property sets the file format for the audit log file. Altibase can store audit information in binary or syslog (syslog is only supported on Linux).

If this property is set to the default value, audit logs are saved in the directory specified for AUDIT_LOG_DIR in binary format. If this property is set to a value between 1~9, logs are stacked in syslog.conf (or rsyslog.conf) using syslog. The syslog message order uses LOG_INFO priority from the syslog.conf file.

0: Stores binary files in the directory specified for AUDIT_LOG_DIR.

1: Stores user facility in /var/log/messages. The file name can be edited at system configuration.

2: Stores to local0 facility, according to user definition.

3: Stores to local1 facility, according to user definition.

4: Stores to local2 facility, according to user definition.

5: Stores to local3 facility, according to user definition.

6: Stores to local4 facility, according to user definition.

7: Stores to local5 facility, according to user definition.

8: Stores to local6 facility, according to user definition.

9: stores to local7 facility, according to user definition.

AUDIT_TAG_NAME_IN_SYSLOG**Data Type**

String

Default Value

AUDIT

Attributes

Read-Only, Single Value

Range

None

Description

This property uses the "AUDIT" tag as a delimiter for saving audit logs using syslog.

C/C++ External Procedure Agent Properties

EXTPROC_AGENT_CONNECT_TIMEOUT

Data Type

Unsigned Integer

Default Value

60 Seconds

Attributes

Read-Only, Single Value

Range

[5, $2^{32}-1$]

Description

This property specifies the maximum length of time in seconds during which Altibase attempts to connect to the external procedure agent when the user calls an external procedure. If the connection does not succeed within the time specified in this property, the call is terminated with the error message displaying that the external procedure call failed. Once a connection is made, external procedure calls are not affected by the value of this property.

EXTPROC_AGENT_CALL_RETRY_COUNT

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[1, 10]

Description

When the user calls an external procedure, EXTPROC_AGENT_CALL_RETRY_COUNT specifies the number of times Altibase tries to reconnect to the external procedure agent.

Altibase first needs to check whether the external procedure agent exists. The external procedure agent may have been timed out and terminated due to the value specified for the EXTPROC_AGENT_CONNECT_TIMEOUT property. In this case, EXTPROC_AGENT_CALL_RETRY_COUNT specifies the number of times Altibase tries to reconnect to the external procedure agent.

The value of this property can be altered with the ALTER SYSTEM statement while Altibase is running.

EXTPROC_AGENT_IDLE_TIMEOUT

Data Type

Unsigned Integer

Default Value

300 Seconds

Attributes

Read-Only, Multiple Value

Range

[5, $2^{32}-1$]

Description

This property specifies the maximum length of time, in seconds, in which the external procedure agent process is to stand by in an idle state. If an external procedure call is made when the external procedure agent process is standing by in an idle state, response time is optimized, as the procedure is executed without connecting to the agent process. However, standby of the agent process in the absence of an external procedure call is a waste of resources; the extension of standby time is recommended only when external procedure calls are highly frequent.

EXTPROC_AGENT_SOCKET_FILEPATH

Data Type

String

Default Value

\$ALTIBASE_HOME/trc

Attributes

Read-Only, Single Value

Range

None

Description

This is a socket file's path created for Altibase server to connect with the external procedure agent. If the external procedure uses, the session creates a socket file with socket_sessionID when creating an external procedure agent. The socket file is automatically deleted when the session is closed normally. And, be careful not to delete this file.

Account Security Properties

CASE_SENSITIVE_PASSWORD

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This specifies whether or not the database is to distinguish between uppercase and lowercase letters in user passwords. The default value for this property is 0 (case-insensitive), which means that the database treats user passwords as uppercase letters.

- 0: Does not distinguish between uppercase and lowercase letters (case-insensitive).
- 1: Distinguishes between uppercase and lowercase letters (case sensitive); however, only if passwords are enclosed in quotation marks (") in the CREATE USER statement. Passwords which are not enclosed in quotation marks are treated as uppercase letters.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

FAILED_LOGIN_ATTEMPTS

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1000]

Description

If an attempt to log in fails more than number of times set in this property, the account cannot be logged in.

PASSWORD_LOCK_TIME

Data Type

Unsigned Int

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 3650]

Description

This specifies the date(unit: days) required to elapse for a locked account to become unlocked.

PASSWORD_LIFE_TIME

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 3650]

Description

This specifies the period of validity(unit: days) for the account password.

PASSWORD_GRACE_TIME

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 3650]

Description

This property specifies the grace period (unit: days) after the expiry date of the account password.

PASSWORD_REUSE_TIME**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 3650]

Description

This specifies the period of time(unit: days) needed to elapse for the reuse of identical passwords. Thus, identical passwords can be reused after the period of time specified for this option elapses.

PASSWORD_REUSE_MAX**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1000]

Description

This specifies the number of times passwords can be altered for the reuse of identical passwords. Thus, identical passwords can be reused after they have been altered for the number of times specified by this option.

PASSWORD_VERIFY_FUNCTION

Data Type

String

Default Value

""

Attributes

Read-Only, Single Value

Range

Maximum length : 40 bytes

Description

This specifies a user-defined CALLBACK function for verifying passwords.

Other Properties

ACCESS_LIST

Format

ACCESS_LIST = operation, address, mask

Range

- operation ::= [PERMIT | DENY]
Indicates whether to allow or deny access by an IP packet that matches a validation rule.
- address
Indicates the IP address of the packet to validate. It can be in IPv4 or IPv6 address notation.
- mask
If the specified address is in IPv4 address notation, mask specifies that only part of the IP address of a packet, the subnet mask, is to be validated.

If the specified address is in IPv6 address notation, mask gives the length of prefix bits to be compared. An IPv6 address is matched if the specified mask bits of the specified address are equal to the specified mask bits of the originating address of an incoming IP packet.
- limit

limit is an optional item. Specifies the maximum number of sessions allowed to access the Altibase server from the accessible IP address range specified in ACCESS_LIST.

If a value is entered in the limit item, limit condition checks are performed on all access requests. Therefore, access is not allowed if the number of access requests from allowed IPs exceeds the limit. If there is no value in the limit item, the limit condition is not checked.

If ACCESS_LIST is added with the ALTER SYSTEM RELOAD ACCESS LIST statement while the Altibase server is running, existing connected sessions are not affected, and the ACCESS_LIST condition is applied only to new connection requests after the change. So when retrieving V\$ACCESS_LIST, the CONNECTED value may be greater than the LIMIT value.

Validation Rule

```
IF
  BITXOR(BITAND(IP_패킷,mask), BITAND(address,mask)) = 0
THEN  valid
ELSE  invalid
```

Description

This property can grant or deny an IP packet attempting to access to Altibase in accordance with an address. By inspecting the IP packet address based upon the specified inspection rules, it can be decided whether or not to allow access. If the IP packet address is corresponding as described in the operation, the access is permitted, but if not, the IP packet is neglected and the next list will be inspected.

If multiple IP packet addresses are specified, the inspection is executed in the order delineated. If there is no address to be matched, the access is allowed.

If the property value of ACCESS_LIST_FILE is described, an external file list defined in the ACCESS_LIST property can be used. The external file can use maximum 1024 lists, but 'ACCESS_LIST=' should be omitted and only the contents should be written out.

Example

Block packets with the IP address 192.168.1.55 and allow all other packets.

```
ACCESS_LIST = deny, 192.168.1.55, 255.255.255.255
```

Allow access to packets from the addresses 192.168.3.* and 219.211.253.*, and block all other packets.

```
ACCESS_LIST = permit, 192.168.3.0, 255.255.255.0
ACCESS_LIST = permit, 219.211.253.0, 255.255.255.0
ACCESS_LIST = deny ,0.0.0.0, 0.0.0.0
```

Block all Ipv4 and IPv6 address except for localhost.

```
ACCESS_LIST = deny, 0.0.0.0, 0.0.0.0
ACCESS_LIST = deny, ::1, 1
ACCESS_LIST = deny, fe80::, 1
```

Describe the IP address which will be inspected in the external file. Block all IP address except for IPv6 address starting with 192.168.3.* and fe80.

```
permit, 192.168.3.0, 255.255.255.0
permit, fe80::, 16
deny, 0.0.0.0, 0.0.0.0
deny, ::1, 1
deny, fe80::, 1
```

Limit the number of sessions accessible from the 192.168.3.17 address to 5.

```
ACCESS_LIST = permit, 192.168.3.17, 255.255.255.255, 5
```

ACCESS_LIST_FILE**Data Type**

String

Default Value

None

Attributes

Read-Only, Single Value

Range

None

Description

This property configures the file path when ACCESS_LIST references an external file path. If the file name and path is not precisely configured, the server will not drive. The absolute path should be specified for an external file path. Refer to the description section of the ACCESS_LIST property for the ACCESS_LIST format.

The list described in ACCESS_LIST property is used if this property is not used.

ADMIN_MODE**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

ADMIN_MODE limits the database connection to administrators only.

0: OFF

1: ON

When this property is set to 1, administrator mode is activated, and only the SYS and SYSTEM_ users can connect to the server using the SYSDBA option, and other users will be unable to establish a connection.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

ARITHMETIC_OPERATION_MODE

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property sets the Altibase server to arithmetic operation mode.

0: The server runs in arithmetic operation mode with precision as its priority. The server mainly uses FLOAT or NUMERIC data types to reduce errors from arithmetic operations. The processing speed can be slower than arithmetic operation mode with performance as its priority.

1: The server runs in arithmetic operation mode with performance as its priority. The server mainly uses DOUBLE data types for arithmetic operations to enhance performance; the occurrence of errors is relatively higher.

CHECK_MUTEX_DURATION_TIME_ENABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies whether to check MUTEX_DURATION_TIME.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

0: check disable

1: check enable

COERCE_HOST_VAR_IN_SELECT_LIST_TO_VARCHAR

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 32000]

Description

This property enables host variables to be used in the select target list without CAST operators.

If this property is 1 or greater, the server treats host variables without CAST operators as VARCHAR data types, and the specified value in this property is used as the size (precision) of the VARCHAR data type.

If this property is set to 0, using host variables without CAST operators will cause an error.

DEFAULT_DATE_FORMAT

Data Type

String

Default Value

DD-MON-RRRR

Attributes

Read-Only, Single Value

Range

None

Description

This property sets the default format of DATE type data table columns. If not specified otherwise when SQL statements are executed, DATE type data are input or output according to this setting. This type must specify the formats in which both dates and times are saved. It is also possible to use blanks within double quotation marks, such as "DD MON RRRR".

```
DEFAULT_DATE_FORMAT = YYYY/MM/DD
iSQL> select sysdate from dual;
SYSDATE
-----
2008/06/16
1 row selected.
```

EXEC_DDL_DISABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

Generally, after a database is initially created, DML statements are executed much more frequently than DDL statements. Because DDL statements change existing database schema, they must be executed with caution.

The administrator can thus use this property to prevent the execution of DDL statements. When this property is set to 1, DDL statements cannot be executed while Altibase is running, whereas if it is set to 0, DDL statements can be executed.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

GROUP_CONCAT_PRECISION

Data Type

Unsigned Integer

Default Value

4000

Attributes

Read-Write, Single Value

Range

[0, 32000]

Description

This property specifies the size of the VARCHAR type that the GROUP_CONCAT function returns.

This property can be modified using the ALTER SYSTEM statement while Altibase is running.

JOB_SCHEDULER_ENABLE

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This controls the operation of the job scheduler. The job scheduler does not operate if the value of the JOB_THREAD_COUNT property is set to 0, even if the value of this property is set to 1.

0: The job scheduler terminates the job.

1: The job scheduler starts the job the run.

The value of this property can be changed using the ALTER SYSTEM statement while Altibase is running.

JOB_THREAD_COUNT

Data Type

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 128]

Description

This property specifies the number of threads to be created at server startup for a JOB to run. If the value of this property is 0, threads are not created for the job scheduler.

JOB_THREAD_QUEUE_SIZE

Data Type

Unsigned Integer

Default Value

64

Attributes

Read-Only, Single Value

Range

[64, 1024]

Description

This property specifies the number of queues to be created at server startup for a JOB to run. If the value of this property is large, a larger number of jobs can run in a given amount of time.

MSG_QUEUE_PERMISSION**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Only, Single Value

Range

[0, 1]

Description

This property sets the permission type of a message queue. The value of this property can be modified by the ALTER SYSTEM statement during ALTIBASE HDB operation

0: (rw-rw-rw 0666) - All users are allowed to read and write, but cannot perform an execution.

1: (rw-r-r 0644) - Only the system owner can read and write, but other users are only allowed to read.

PSM_CASE_SENSITIVE_MODE**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property sets whether to use case sensitivity when referring to column names of RECORD and ROWTYPE types or LABEL names in PSM. If set to 0, the behavior is case insensitive, and if set to 1, the behavior is case sensitive.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

PSM_CHAR_DEFAULT_PRECISION**Data Type**

Unsigned Integer

Default Value

32000

Attributes

Read-Only, Single Value

Range

[1, 65534]

Description

In case that the size of CHAR type is unspecified in the stored procedures or functions, Altibase determines the specified values in the PSM_CHAR_DEFAULT_PRECISION property as the size of CHAR.

PSM_IGNORE_NO_DATA_FOUND_ERROR**Data Type**

Unsigned Integer

Default Value

0

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

The NO_DATA_FOUND exception is one of the system defined exceptions provided by Altibase's PSM. This exception is raised when the "SELECT ~INTO" statement contained in PSM(stored procedures, functions, triggers) returns no result sets. With the PSM_IGNORE_NO_DATA_FOUND_ERROR property, the user can guard against this exception.

- 0: When no result set is returned, the NO_DATA_FOUND exception is raised.

- 1: When no result set is returned, the NO_DATA_FOUND exception is not raised.

This property can be changed using the ALTER SYSTEM statement while Altibase is running.

PSM_NCHAR_UTF16_DEFAULT_PRECISION

Data Type

Unsigned Integer

Default Value

16000

Attributes

Read-Only, Single Value

Range

[1, 32766]

Description

Altibase determines the values specified in the PSM_NCHAR_UTF16_DEFAULT_PRECISION property as the size of NCHAR in the case Altibase character set is UTF16, and the size of NCHAR type is unspecified in parameters or return values when creating stored procedures and functions.

PSM_NCHAR_UTF8_DEFAULT_PRECISION

Data Type

Unsigned Integer

Default Value

10666

Attributes

Read-Only, Single Value

Range

[1, 21843]

Description

In the case the Altibase character set is UTF8, and the NCHAR type size is unspecified in parameters or return values when creating the stored procedures or functions, Altibase determines the specified values in the PSM_CHAR_DEFAULT_PRECISION property as the size of NCHAR.

PSM_NVARCHAR_UTF16_DEFAULT_PRECISION

Data Type

Unsigned Integer

Default

16000

Attributes

Read-Only, Single Value

Range

[1, 32766]

Description

Altibase determines the specified values in the PSM_NCHAR_UTF16_DEFAULT_PRECISION property as the size of NVARCHAR in the case that Altibase character set is UTF16, and the size of NVARCHAR type is not specified in parameters or return values when creating the stored procedures and stored functions.

PSM_NVARCHAR_UTF8_DEFAULT_PRECISION**Data Type**

Unsigned Integer

Default Value

10666

Attributes

Read-Only, Single Value

Range

[1, 21843]

Description

In the case the Altibase character set is UTF8 and the NCHAR type size is unspecified in parameters or return values when creating the stored procedures or functions, Altibase determines the specified values in the PSM_NVARCHAR_UTF8_DEFAULT_PRECISION property as the size of NVARCHAR.

PSM_PARAM_AND_RETURN_WITHOUT_PRECISION_ENABLE**Data Type**

Unsigned Integer

Default Value

1

Attributes

Read-Only, Single Value

Range

[0,1]

Description

The size of usable data varies depending on the value of this property if the scale of parameter is unspecified when creating the stored procedures or if the data size of parameters and return values is not specified in case of creating stored functions.

If the type of parameter or return values is CHAR, NCHAR, NVARCHAR or VARCHAR, and the property value is 1, the size of data type is determined by the values specified in the following properties; however, if the value is set to 0, the size of data type would be 1.

- PSM_CHAR_DEFAULT_PRECISION
- PSM_NCHAR_UTF8_DEFAULT_PRECISION
- PSM_NCHAR_UTF16_DEFAULT_PRECISION
- PSM_NVARCHAR_UTF8_DEFAULT_PRECISION
- PSM_NVARCHAR_UTF16_DEFAULT_PRECISION
- PSM_PARAM_AND_RETURN_WITHOUT_PRECISION_ENABLE
- PSM_VARCHAR_DEFAULT_PRECISION

PSM_VARCHAR_DEFAULT_PRECISION**Data Type**

Unsigned Integer

Default Value

32000

Attributes

Read-Only, Single Value

Range

[1, 65534]

Description

In case that the size of VARCHAR type is unspecified in the stored procedures or functions, Altibase determines the specified values in the PSM_VARCHAR_DEFAULT_PRECISION property as the size of VARCHAR.

QUERY_STACK_SIZE (Unit: count)**Data Type**

Unsigned Integer

Default Value

1024

Range

Read-Write, Single Value

Range

[8, 65536]

Description

This property specifies the size of the stack internally used in the system to process query operations such as comparisons and other operations.

When complicated calculations or stored procedures are used, a stack overflow error may occur. In such cases, the property must be changed to a bigger value.

This parameter must be set according to the application environment. If it is set to a value higher than necessary, memory space will be wasted, so this parameter must be set carefully.

This property can be set in the altibase.properties file, and can be changed using the ALTER SYSTEM or ALTER SESSION statements.

This property can be changed using the ALTER SESSION statement as follows: ALTER SESSION SET STACK SIZE = n;

RECURSION_LEVEL_MAXIMUM**Data Type**

Unsigned Integer

Default Value

1000

Attributes

Read-Write, Single Value

Range[5, $2^{32}-1$]**Description**

This property repeatedly executes recursive queries for specified number of times(level).

The value of this property can be modified through ALTER SESSION statement during the Altibase operation.

REMOTE_SYSDBA_ENABLE

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

This property specifies whether the SYS user can access the database with SYSDBA privileges from a remote location. Its value can be changed using the ALTER SYSTEM statement.

0: Deny remote database access with SYSDBA privileges.

1: Allow remote database access with SYSDBA privileges (default).

SELECT_HEADER_DISPLAY

Data Type

Unsigned Integer

Default Value

1

Attributes

Read-Write, Single Value

Range

[0, 1]

Description

When the results of a SELECT query are output over iSQL, this system property determines whether only the column names are output, or whether the table names are output along with the column names.

This property can be set in the altibase.properties file, and can be changed using the ALTER SYSTEM or ALTER SESSION statements.

If this parameter is set to 0, the table names are displayed along with the column names when the results of SQL statements are output using iSQL

SYS_CONNECT_BY_PATH_PRECISION

Data Type

Unsigned Integer

Default Value

4000

Attributes

Read-Write, Single Value

Range

[0, 32000]

Description

This property specifies the size of the VARCHAR type that the SYS_CONNECT_BY_PATH function returns.

This property can be modified using the ALTER SYSTEM statement while Altibase is running.

This is a property that sets the regular expression mode. Each value indicates the following.

0

Altibase regular expression mode.

POSIX Basic Regular Expression (BRE) and Extended Regular Expression (ERE) are partially supported.

1

PCRE2 compatibility mode.

Supports the regular expression syntax of the Perl Compatible Regular Expressions (PCRE2) library.

This mode can be used when the Altibase server character set is US7ASCII or UTF-8, and there is a difference in syntax from Altibase regular expression mode. For more information, please refer to [SQL Reference-Appendix A. Regular Expressions](#).