

MOOSLIB Reference Manual

Generated by Doxygen 1.4.6

Fri Sep 28 20:14:20 2007

Contents

1	MOOSLIB Hierarchical Index	1
1.1	MOOSLIB Class Hierarchy	1
2	MOOSLIB Class Index	3
2.1	MOOSLIB Class List	3
3	MOOSLIB Class Documentation	5
3.1	CMOOSApp Class Reference	5
3.2	CMOOSCommClient Class Reference	13
3.3	CMOOSCommObject Class Reference	22
3.4	CMOOSCommPkt Class Reference	23
3.5	CMOOSCommServer Class Reference	25
3.6	CMOOSException Class Reference	31
3.7	CMOOSInstrument Class Reference	32
3.8	CMOOSMsg Class Reference	35

Chapter 1

MOOSLIB Hierarchical Index

1.1 MOOSLIB Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

CMOOSApp	5
CMOOSInstrument	32
CMOOSCommObject	22
CMOOSCommClient	13
CMOOSCommServer	25
CMOOSCommPkt	23
CMOOSException	31
CMOOSMsg	35

Chapter 2

MOOSLIB Class Index

2.1 MOOSLIB Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

CMOOSApp	5
CMOOSCommClient	13
CMOOSCommObject	22
CMOOSCommPkt	23
CMOOSCommServer	25
CMOOSException	31
CMOOSInstrument	32
CMOOSMsg	35


Chapter 3

MOOSLIB Class Documentation

3.1 CMOOSApp Class Reference

```
#include <MOOSApp.h>
```

Inheritance diagram for CMOOSApp::



Public Member Functions

- bool **Run** (char *sName, char *sMissionFile)
- virtual bool **OnConnectToServer** ()
- virtual bool **OnDisconnectFromServer** ()
- void **OnDisconnectToServerPrivate** ()
- void **OnConnectToServerPrivate** ()

Protected Member Functions

- virtual bool **Iterate** ()
- virtual bool **OnNewMail** (MOOSMSG_LIST &NewMail)
- virtual bool **OnCommandMsg** (CMOOSMsg Msg)
- virtual std::string **MakeStatusString** ()
- void **SetCommsFreq** (unsigned int nFreq)
- void **SetAppFreq** (double dfFreq)
- double **GetAppStartTime** ()
- void **SetServer** (const char *sServerHost="LOCALHOST", long lPort=9000)
- bool **UseMOOSComms** (bool bUse)
- bool **MOOSDebugWrite** (const std::string &sTxt)
- void **EnableCommandMessageFiltering** (bool bEnable)
- bool **LookForAndHandleAppCommand** (MOOSMSG_LIST &NewMail)

- std::string **GetAppName** ()
- std::string **GetMissionFileName** ()
- bool **AddMOOSVariable** (std::string sName, std::string sSubscribeName, std::string sPublishName, double dfCommsTime)
- CMOOSVariable * **GetMOOSVar** (std::string sName)
- bool **RegisterMOOSVariables** ()
- bool **UpdateMOOSVariables** (MOOSMSG_LIST &NewMail)
- bool **SetMOOSVar** (const std::string &sName, const std::string &sVal, double dfTime)
- bool **SetMOOSVar** (const std::string &sVarName, double dfVal, double dfTime)
- bool **PublishFreshMOOSVariables** ()
- bool **IsSimulateMode** ()
- virtual bool **OnStartup** ()
- bool **ConfigureComms** ()
- double **GetTimeSinceIterate** ()
- double **GetLastIterateTime** ()
- int **GetIterateCount** ()
- std::string **GetCommandKey** ()
- bool **IsDebug** ()

Protected Attributes

- CMOOSCommClient **m_Comms**
- CProcessConfigReader **m_MissionReader**
- MOOSVARMAP **m_MOOSVars**
- bool **m_bSimMode**
- long **m_lServerPort**
- std::string **m_sServerHost**
- std::string **m_sServerPort**
- bool **m_bServerSet**
- bool **m_bUseMOOSComms**
- std::string **m_sAppName**
- int **m_nCommsFreq**
- double **m_dfFreq**
- std::string **m_sMissionFile**
- bool **m_bCommandMessageFiltering**
- double **m_dfAppStartTime**
- double **m_dfLastRunTime**
- bool **m_bDebug**

3.1.1 Detailed Description

This is a class from which all MOOS component applications can be derived. `main()` will typically end with a call to `MOOSAppDerivedClass::Run()`. It provides automatic connection to the MOOSDB, provides slots for Mail Processing and application work, callbacks for connection/disconnection to MOOSDB, Configuration file reading and dynamic (runtime) variables. Definitely worth getting to know.

3.1.2 Member Function Documentation

3.1.2.1 `bool CMOOSApp::AddMOOSVariable (std::string sName, std::string sSubscribeName, std::string sPublishName, double dfCommsTime) [protected]`

Add a dynamic (run time) variable

Parameters:

sName name of the variable

sSubscribeName if you call **RegisterMOOSVariables()**(p.9) the variable will be updated with mail called <sSubscribeName> if and when you call **UpdateMOOSVariables()**(p.10)

sPublishName if you call **PublishFreshMOOSVariables()**(p.9) (and you've written to the dynamic variable since the last call) the variable will be published under this name.

CommsTime - if sSubscribeName is not empty this is the minimum time between updates which you are interested in knowing about, so if CommsTime=0.1 then the maximum update rate you will see on the variable from the DB is 10HZ.

3.1.2.2 `bool CMOOSApp::ConfigureComms () [protected]`

start up the comms

3.1.2.3 `void CMOOSApp::EnableCommandMessageFiltering (bool bEnable) [protected]`

enable/disable the behind the scenes search for command messages

3.1.2.4 `string CMOOSApp::GetAppName () [protected]`

return the application name

3.1.2.5 `double CMOOSApp::GetAppStartTime () [protected]`

return the boot time of the App

3.1.2.6 `std::string CMOOSApp::GetCommandKey () [protected]`

returns the string which constitutes a command string for this application. if CommandFiltering is enabled (see **EnableCommandMessageFiltering()**(p.7)) the application will filter incoming mail and Call **OnCommandMsg()**(p.8) (which can be overriden) if a message with this command string as a name is received. Command strings look like APPNAME_CMD

3.1.2.7 `int CMOOSApp::GetIterateCount () [protected]`

return number of times iterate has been called

3.1.2.8 double CMOOSApp::GetLastIterateTime () [protected]

Return time at which the Run loop last ran (called Iterate)

3.1.2.9 std::string CMOOSApp::GetMissionFileName () [protected]

return the application mission file name

3.1.2.10 CMOOSVariable* CMOOSApp::GetMOOSVar (std::string *sName*) [protected]

return a pointer to a named variable

3.1.2.11 double CMOOSApp::GetTimeSinceIterate () [protected]

Time since last iterate was called

3.1.2.12 bool CMOOSApp::IsSimulateMode () [protected]

Returns true if Simulate = true is found in the mission/configuration file (a global flag) - the mission file is not re-read on each call

3.1.2.13 bool CMOOSApp::Iterate () [protected, virtual]

called when the application should iterate. Overload this function in a derived class and within it write all the application specific code. It will be called at approximately nFreq = 1/AppTick Hz

3.1.2.14 bool CMOOSApp::LookForAndHandleAppCommand (MOOSMSG_LIST & *NewMail*) [protected]

dispatching function for OnCommandMsg

3.1.2.15 std::string CMOOSApp::MakeStatusString () [protected, virtual]

make a status string - overload this in a derived class if you want to modify or what the status string looks like

3.1.2.16 bool CMOOSApp::MOOSDebugWrite (const std::string & *sTxt*) [protected]

Call this to write a debug string to the DB under the name "MOOS_DEBUG"

3.1.2.17 bool CMOOSApp::OnCommandMsg (CMOOSMsg *Msg*) [protected, virtual]

optionally (see EnableCommandMessageFiltering()) called when a command message (<MOOSNAME>_CMD) is recieved by the application.

Parameters:

a copy of CmdMsg the message purporting to be a "command" - i.e. has the name <MOOSNAME>_CMD

3.1.2.18 bool CMOOSApp::OnConnectToServer () [virtual]

Called when the class has successfully connected to the server. Overload this function and place use it to register for notification when variables of interest change

3.1.2.19 bool CMOOSApp::OnDisconnectFromServer () [virtual]

Called when the class has disconnects from the server. Put code you want to run when this happens in a virtual version of this method

3.1.2.20 void CMOOSApp::OnDisconnectToServerPrivate ()

these two functions are used to handle private MOOSApp work that need to occur on behalf of derived classes at the same time as the overloaded OnConnectToServer and OnDisconnectFromServer methods are called. They are public to allow their invocation from a call back. They are not interesting to the casual user

3.1.2.21 bool CMOOSApp::OnNewMail (MOOSMSG_LIST & *NewMail*) [protected, virtual]

called when new mail has arrived. Overload this method in a derived class to process new mail. It will be called at approximately 1/CommsTick Hz. In this function you'll most likely iterate over the collection of mail message received or call a m_Comms::PeekMail() to look for a specific named message.

Parameters:

NewMail a list of new mail messages

3.1.2.22 bool CMOOSApp::OnStartup () [protected, virtual]

called just before the main app loop is entered. Specific initialisation code can be written in an overloaded version of this function

Reimplemented in **CMOOSInstrument** (p. 33).

3.1.2.23 bool CMOOSApp::PublishFreshMOOSVariables () [protected]

Send any variables (under their sPublishName see AddMOOSVariable) which been written too since the last call of **PublishFreshMOOSVariables()**(p. 9)

3.1.2.24 bool CMOOSApp::RegisterMOOSVariables () [protected]

Register with the DB to be mailed about any changes to any dynamic variables which were created with non-empty sSubscribeName fields

3.1.2.25 `bool CMOOSApp::Run (char * sName, char * sMissionFile)`

called to start the application

Parameters:

sName The name of this application (must be unique amongst MOOS components)
the name of the mission file

3.1.2.26 `void CMOOSApp::SetAppFreq (double dfFreq)` [protected]

Set the time between calls of Iterate (which is where you'll probably do Application work)- can be set using the AppTick flag in the config file

3.1.2.27 `void CMOOSApp::SetCommsFreq (unsigned int nFreq)` [protected]

Set the time between calls into the DB - can be set using the CommsTick flag in the config file

3.1.2.28 `bool CMOOSApp::SetMOOSVar (const std::string & sVarName, double dfVal, double dfTime)` [protected]

Set value in a dynamic variable if the variable is of type string (type is set on first write)

3.1.2.29 `bool CMOOSApp::SetMOOSVar (const std::string & sName, const std::string & sVal, double dfTime)` [protected]

Set value in a dynamic variable if teh variable is of type double (type is set on first write)

3.1.2.30 `void CMOOSApp::SetServer (const char * sServerHost = "LOCALHOST", long lPort = 9000)` [protected]

Called to set the MOOS server info used rarely usually this info will be picked up by the MOOSApp automatically when it Run is called specifying the configuration file (which contains the DB's coordinates)

Parameters:

sServerHost name of the machine hosting the MOOSDB application
lPort port nuymber that MOOSDB listens on

3.1.2.31 `bool CMOOSApp::UpdateMOOSVariables (MOOSMSG_LIST & NewMail)` [protected]

Pass mail (usually collected in OnNewMail) to the set of dynamic variables. If they are interested (mail name matches their subscribe name) they will update themselves automatically

3.1.2.32 `bool CMOOSApp::UseMOOSComms (bool bUse)` [protected]

By default MOOSDB comms are on - but you may want to use the structuire of MOOSApp as a standalone application - if so call this function with a false parameter

3.1.3 Member Data Documentation

3.1.3.1 `bool CMOOSApp::m_bCommandMessageFiltering` [protected]

flag specifying whether command message filtering is enabled

3.1.3.2 `bool CMOOSApp::m_bServerSet` [protected]

true if the server has been set

3.1.3.3 `bool CMOOSApp::m_bSimMode` [protected]

flag saying whether MOOS is running with a simulator can be set by registering for `SIMULATION_MODE` variable

3.1.3.4 `bool CMOOSApp::m_bUseMOOSComms` [protected]

true if we want to use MOOS comms

3.1.3.5 `CMOOSCommClient CMOOSApp::m_Comms` [protected]

The MOOSComms node. All communications happens by way of this object. You'll often do things like `m_Comms.Notify("VARIABLE_X", "STRING_DATA", dfTime)` to send data

3.1.3.6 `double CMOOSApp::m_dfAppStartTime` [protected]

The start time of the application

3.1.3.7 `double CMOOSApp::m_dfFreq` [protected]

frequency at which this application will iterate

3.1.3.8 `double CMOOSApp::m_dfLastRunTime` [protected]

Time at which the Run loop last ran (called Iterate)

3.1.3.9 `long CMOOSApp::m_lServerPort` [protected]

Port on which server application listens for new connection

3.1.3.10 `CProcessConfigReader CMOOSApp::m_MissionReader` [protected]

a very useful object that lets us retrieve configuration information from the mission file using calls like `GetConfigurationParam()`

3.1.3.11 MOOSVARMAP CMOOSApp::m_MOOSVars [protected]

a map of dynamic/run time moos variables that may be set by comms - avoid messy long if else if statements

3.1.3.12 int CMOOSApp::m_nCommsFreq [protected]

frequency at which server will be contacted

3.1.3.13 std::string CMOOSApp::m_sAppName [protected]

name of this application

3.1.3.14 std::string CMOOSApp::m_sMissionFile [protected]

std::string name of mission file

3.1.3.15 std::string CMOOSApp::m_sServerHost [protected]

name of machine on which MOOS Server resides

3.1.3.16 std::string CMOOSApp::m_sServerPort [protected]

std::string version of m_lServerPort


The documentation for this class was generated from the following files:

- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSApp.h
- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSApp.cpp

3.2 CMOOSCommClient Class Reference

```
#include <MOOSCommClient.h>
```

Inheritance diagram for CMOOSCommClient::



Public Member Functions

- **CMOOSCommClient** ()
default constructor
- virtual **~CMOOSCommClient** ()
default destructor
- bool **Notify** (const std::string &sVar, const std::string &sVal, double dfTime=-1)
- bool **Notify** (const std::string &sVar, double dfVal, double dfTime=-1)
- bool **Register** (const std::string &sVar, double dfInterval)
- bool **UnRegister** (const std::string &sVar)
- bool **IsConnected** ()
- bool **Fetch** (MOOSMSG_LIST &MsgList)
- bool **Post** (CMOOSMsg &Msg)
- bool **ClientLoop** ()
- virtual bool **DoClientWork** ()
- bool **Run** (const char *sServer, long lPort, const char *sMyName, unsigned int n-FundamentalFreq=5)
- void **SetOnConnectCallback** (bool(*pfn)(void *pParamCaller), void *pCallerParam)
- void **SetOnDisconnectCallback** (bool(*pfn)(void *pParamCaller), void *pCallerParam)
- bool **ServerRequest** (const std::string &sWhat, MOOSMSG_LIST &MsgList, double df-TimeOut=2.0, bool bContinuouslyClearBox=true)
- bool **Peek** (MOOSMSG_LIST &List, int nIDRequired, bool bClearBox=true)
- std::string **GetDescription** ()
- bool **FakeSource** (bool bFake)
- bool **Close** (bool bNice=true)
- std::set< std::string > **GetPublished** ()
- std::set< std::string > **GetRegistered** ()

Static Public Member Functions

- static bool **PeekMail** (MOOSMSG_LIST &Mail, const std::string &sKey, CMOOSMsg &Msg, bool bErase=false, bool bFindYoungest=false)
- static std::string **GetLocalIPAddress** ()

Protected Types

- typedef pthread_t **THREAD_ID**

Protected Member Functions

- bool **ClearResources** ()
- void **DoBanner** ()
- bool **OnCloseConnection** ()
- bool **HandShake** ()
- bool **ConnectToServer** ()
- bool **StartThreads** ()
- bool **UpdateMOOSSkew** (double dfTxTime, double dfRxTime)

Protected Attributes

- int **m_nNextMsgID**
- bool **m_bConnected**
- bool **m_bFakeSource**
- unsigned int **m_nOutPendingLimit**
- unsigned int **m_nInPendingLimit**
- std::string **m_sMyName**
- CMOOSLock **m_OutLock**
- CMOOSLock **m_InLock**
- XPCTcpSocket * **m_pSocket**
- std::string **m_sDBHost**
- long **m_IPort**
- bool **m_bQuit**
- bool **m_bMailPresent**
- **THREAD_ID** **m_nClientThreadID**
- MOOSMSG_LIST **m_OutBox**
- MOOSMSG_LIST **m_InBox**
- void * **m_pConnectCallbackParam**
- bool(* **m_pfnConnectCallback**)(void *pConnectParam)
- void * **m_pDisconnectCallbackParam**
- bool(* **m_pfnDisconnectCallback**)(void *pParam)
- unsigned int **m_nFundamentalFreq**
- std::set< std::string > **m_Registered**
- std::set< std::string > **m_Published**

3.2.1 Detailed Description

This class is the most important component of MOOS as seen from the eyes of a component developer

3.2.2 Member Typedef Documentation

3.2.2.1 typedef pthread_t CMOOSCommClient::THREAD_ID [protected]

ID of IO thread

3.2.3 Member Function Documentation

3.2.3.1 bool CMOOSCommClient::ClientLoop ()

internal method which runs in a separate thread and manages the input and output of messages from the server. DO NOT CALL THIS METHOD.

3.2.3.2 bool CMOOSCommClient::Close (bool *bNice* = true)

make the client shut down

3.2.3.3 bool CMOOSCommClient::ConnectToServer () [protected]

Connect to the server process using info supplied to Init

See also:

Init

3.2.3.4 void CMOOSCommClient::DoBanner () [protected]

send library info to stdout

3.2.3.5 bool CMOOSCommClient::DoClientWork () [virtual]

called by the above to do the client mail box shuffling

3.2.3.6 bool CMOOSCommClient::FakeSource (bool *bFake*)

call with "true" if you want this client to fake its own outgoing name. This is rarely used but very useful when it is

3.2.3.7 bool CMOOSCommClient::Fetch (MOOSMSG_LIST & *MsgList*)

Called by a user of CMOOSCommClient(p. 13) to retrieve mail

Parameters:

MsgList a list of messages into which the newly received message will be placed

Returns:

true if there is new mail

3.2.3.8 string CMOOSCommClient::GetDescription ()

describe this client in a string

3.2.3.9 string CMOOSCommClient::GetLocalIPAddress () [static]

return a string of the host machine's IP address

3.2.3.10 `std::set<std::string> CMOOSCommClient::GetPublished ()` [inline]

return the list of messages names published

3.2.3.11 `std::set<std::string> CMOOSCommClient::GetRegistered ()` [inline]

return the list of messages registered

3.2.3.12 `bool CMOOSCommClient::HandShake ()` [protected]

performs a handshake with the server when a new connection is made. Within this function this class tells teh server its name

3.2.3.13 `bool CMOOSCommClient::IsConnected ()`

returns true if this obecjt is connected to the server

3.2.3.14 `bool CMOOSCommClient::Notify (const std::string & sVar, double dfVal, double dfTime = -1)`

notify the MOOS community that something has changed (double)

3.2.3.15 `bool CMOOSCommClient::Notify (const std::string & sVar, const std::string & sVal, double dfTime = -1)`

notify the MOOS community that something has changed (string)

3.2.3.16 `bool CMOOSCommClient::OnCloseConnection ()` [protected]

called when connection to server is closed

3.2.3.17 `bool CMOOSCommClient::Peek (MOOSMSG_LIST & List, int nIDRequired, bool bClearBox = true)`

Have a peek at mail box and remove a particular message, by default all other messages are removed. Note this is quite different from PeekMail

3.2.3.18 `static bool CMOOSCommClient::PeekMail (MOOSMSG_LIST & Mail, const std::string & sKey, CMOOSMsg & Msg, bool bErase = false, bool bFindYoungest = false)` [static]

a static helper function hat lets a user browse a mail list the message is removed if bremove is true

3.2.3.19 `bool CMOOSCommClient::Post (CMOOSMsg & Msg)`

place a single message in the out box and return immediately. Completion of this method does not infer transmission. However transmission will occur at the next available oppurtunity. Inpractice

the apparent speed of message transmission will be very fast indeed. This model however prevents wayward user software bring down the MOOSComms by way of denial of service. (ie hogging the network)

Parameters:

Msg reference to **CMOOSMsg**(p.35) which user wishes to send

3.2.3.20 **bool CMOOSCommClient::Register (const std::string & *sVar*, double *dfInterval*)**

Register for notification in changes of named variable

Parameters:

sVar name of variable of interest

dfInterval minimum time between notifications

3.2.3.21 **bool CMOOSCommClient::Run (const char * *sServer*, long *lPort*, const char * *sMyName*, unsigned int *nFundamentalFreq* = 5)**

Run the MOOSCommClient Object. This call is non blocking and begins managing process IO with the MOOSComms protocol

Parameters:

sServer Name of machine on which server resides eg LOCALHOST or guru.mit.edu

lPort number of port on which server is listening for new connections eg 9000

sMyName std::string name by which this MOOS process will be known - eg "Motion-Controller" or "DepthSensor"

nFundamentalFrequency the basic tick frequency of the comms loop. Default value of 5 implies mail will be retrieved and sent from the server at 5Hz

3.2.3.22 **bool CMOOSCommClient::ServerRequest (const std::string & *sWhat*, MOOSMSG_LIST & *MsgList*, double *dfTimeOut* = 2.0, bool *bContinuouslyClearBox* = true)**

Directly and asynchronously make a request to the server (use this very rarely if ever. Its not meant for public consumption)

Parameters:

sWhat string specifying what request to make - ALL, DB_CLEAR, PROCESS_SUMMARY or VAR_SUMMARY

MsgList List of messages returned by server

dfTimeOut TimeOut

bContinuouslyClearBox true if all other message returned with query are to be discarded.

3.2.3.23 void CMOOSCommClient::SetOnConnectCallBack (bool*)(void *pParamCaller) *pfn*, void * *pCallerParam*)

set the user supplied OnConnect call back. This callback , when set, will be invoked when a connection to the server is made. It is a good plan to register for notification of variables in this callback

Parameters:

pfn pointer to static function of type bool Fn(void * pParam)

pCallerParam parameter passed to callback function when invoked

3.2.3.24 void CMOOSCommClient::SetOnDisconnectCallBack (bool*)(void *pParamCaller) *pfn*, void * *pCallerParam*)

set the user supplied OnConnect call back. This callback , when set, will be invoked when a connection to the server is lost.

Parameters:

pfn pointer to static function of type bool Fn(void * pParam)

pCallerParam parameter passed to callback function when invoked

3.2.3.25 bool CMOOSCommClient::StartThreads () [protected]

called internally to start IO management thread

See also:

ClientLoop(p. 15)

3.2.3.26 bool CMOOSCommClient::UnRegister (const std::string & *sVar*)

UnRegister for notification in changes of named variable

Parameters:

sVar name of variable of interest

3.2.4 Member Data Documentation

3.2.4.1 bool CMOOSCommClient::m_bConnected [protected]

true if we are connected to the server

3.2.4.2 bool CMOOSCommClient::m_bFakeSource [protected]

true if we want to be able to fake sources of messages (used by playback)

3.2.4.3 bool CMOOSCommClient::m_bMailPresent [protected]

true if mail present (saves using a semaphore to open an empty box)

3.2.4.4 `bool CMOOSCommClient::m_bQuit` [protected]

IO thread will continue so long as this flag is false

3.2.4.5 `MOOSMSG_LIST CMOOSCommClient::m_InBox` [protected]

List of message that have been received and are ready for reading by user

See also:

`Fetch`(p. 15)

3.2.4.6 `CMOOSLock CMOOSCommClient::m_InLock` [protected]

Mutex around incoming mail box

See also:

`CMOOSLock`

3.2.4.7 `long CMOOSCommClient::m_lPort` [protected]

port number on which server process is listening for new connections

See also:

`Init`

3.2.4.8 `unsigned int CMOOSCommClient::m_nFundamentalFreq` [protected]

fundamental frequency with which comms with server occurs

See also:

`Run`(p. 17)

3.2.4.9 `unsigned int CMOOSCommClient::m_nInPendingLimit` [protected]

The number of unread incoming messages that can be tolerated

3.2.4.10 `unsigned int CMOOSCommClient::m_nOutPendingLimit` [protected]

The number of pending unsent messages that can be tolerated

3.2.4.11 `MOOSMSG_LIST CMOOSCommClient::m_OutBox` [protected]

List of messages that a pending to be sent

See also:

`Post`(p. 16)

3.2.4.12 CMOOSLock CMOOSCommClient::m_OutLock [protected]

Mutex around Outgoing mail box

See also:

CMOOSLock

3.2.4.13 void* CMOOSCommClient::m_pConnectCallBackParam [protected]

parameter that user wants passed to him/her with connect callback

3.2.4.14 void* CMOOSCommClient::m_pDisconnectCallBackParam [protected]

parameter that user wants passed to him/her with disconnect callback

3.2.4.15 bool(* CMOOSCommClient::m_pfnConnectCallBack)(void *pConnectParam) [protected]

the user supplied OnConnect callback

3.2.4.16 bool(* CMOOSCommClient::m_pfnDisconnectCallBack)(void *pParam) [protected]

the user supplied OnDisConnect callback

3.2.4.17 XPCTcpSocket* CMOOSCommClient::m_pSocket [protected]

pointer to socket connected to server

3.2.4.18 std::set<std::string> CMOOSCommClient::m_Published [protected]

the set of messages names/keys that have been sent

3.2.4.19 std::set<std::string> CMOOSCommClient::m_Registered [protected]

a set of strings of the resources (messages names/keys) that have been registered for

3.2.4.20 std::string CMOOSCommClient::m_sDBHost [protected]

name of teh host on which the server process lives

See also:

Init

3.2.4.21 std::string CMOOSCommClient::m_sMyName [protected]

name of MOOS process

See also:

Init


The documentation for this class was generated from the following files:

- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSCommClient.h
- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSCommClient.cpp

3.3 CMOOSCommObject Class Reference

```
#include <MOOSCommObject.h>
```

Inheritance diagram for CMOOSCommObject::



Static Public Member Functions

- static bool **SocketsInit** ()
called to initialise system socket services. Only does something useful in Win32 land

Protected Member Functions

- bool **SendPkt** (XPCTcpSocket *pSocket, **CMOOSCommPkt** &PktTx)
- bool **ReadPkt** (XPCTcpSocket *pSocket, **CMOOSCommPkt** &PktRx, int nSecondsTimeOut=-1)
- bool **SendMsg** (XPCTcpSocket *pSocket, **CMOOSMsg** &Msg)
- bool **ReadMsg** (XPCTcpSocket *pSocket, **CMOOSMsg** &Msg, int nSecondsTimeOut=-1)

3.3.1 Detailed Description

A base class for the **CMOOSCommServer**(p. 25) and **CMOOSCommClient**(p. 13) objects. This class provides basic Receive and Transmit capabilities of CMOOSMsg's and CMOOSCommPkts. Where messages are passed as parameters then there are transparently packed into packets.

The documentation for this class was generated from the following files:

- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSCommObject.h
- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSCommObject.cpp

3.4 CMOOSCommPkt Class Reference

```
#include <MOOSCommPkt.h>
```

Public Member Functions

- **Serialize** (MOOSMSG_LIST &List, bool bToStream=true, bool bNoNULL=false, double *pdfPktTime=NULL)
- **GetStreamLength** ()
- **Fill** (unsigned char *InData, int nData)
- **GetBytesRequired** ()

Public Attributes

- unsigned char * **m_pStream**
- unsigned char * **m_pNextData**
- int **m_nStreamSpace**
- unsigned char **DefaultStream** [MOOS_PKT_DEFAULT_SPACE]

Protected Member Functions

- **InflateTo** (int nNewStreamSize)
- **CopyToStream** (unsigned char *pData, int nBytes)

Protected Attributes

- int **m_nByteCount**
- int **m_nMsgLen**
- bool **m_bAllocated**

3.4.1 Detailed Description

This class is part of MOOS's internal transport mechanism. It any number of CMOOSMsg's can be packed into a **CMOOSCommPkt**(p. 23) and sent in one lump between a **CMOOSCommServer**(p. 25) and **CMOOSCommClient**(p. 13) object. It is never used by a user of MOOSLib

3.4.2 Member Function Documentation

- ##### 3.4.2.1 **bool CMOOSCommPkt::Serialize** (MOOSMSG_LIST & *List*, bool *bToStream* = true, bool *bNoNULL* = false, double * *pdfPktTime* = NULL)

This function stuffs messages in/from a packet

3.4.3 Member Data Documentation

3.4.3.1 `bool CMOOSCommPkt::m_bAllocated` [protected]

true is the packet has been inflated to increase capacity and `m_pStream` no longer points to `DefaultStream` but to heap space allocated with `new`


The documentation for this class was generated from the following files:

- `/home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSCommPkt.h`
- `/home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSCommPkt.cpp`

3.5 CMOOSCommServer Class Reference

```
#include <MOOSCommServer.h>
```

Inheritance diagram for CMOOSCommServer::



Public Types

- typedef std::list< XPCTcpSocket * > **SOCKETLIST**
- typedef std::map< int, std::string > **SOCKETFD_2_CLIENT_NAME_MAP**
- typedef std::list< std::string > **STRING_LIST**

Public Member Functions

- bool **GetClientNames** (STRING_LIST &sList)
- void **SetOnRxCallBack** (bool(*pfn)(const std::string &sClient, MOOSMSG_LIST &MsgListRx, MOOSMSG_LIST &MsgListTx, void *pParam), void *pParam)
- void **SetOnDisconnectCallBack** (bool(*pfn)(std::string &sClient, void *pParam), void *pParam)
- bool **ListenLoop** ()
- bool **ServerLoop** ()
- bool **TimerLoop** ()
- bool **Run** (long lPort, const std::string &sCommunityName)
- **CMOOSCommServer** ()
default constructor
- virtual ~**CMOOSCommServer** ()
default destructor

Protected Types

- typedef pthread_t **THREAD_ID**

Protected Member Functions

- int **GetMaxSocketFD** ()
- virtual void **DoBanner** ()
- std::string **GetClientName** (XPCTcpSocket *pSocket)
- void **PoisonClient** (XPCTcpSocket *pSocket, char *sReason)
- bool **HandShake** (XPCTcpSocket *pNewSocket)
- bool **IsUniqueName** (std::string &sClientName)
- virtual bool **OnClientDisconnect** ()

called when a client disconnects or an error occurs

- virtual bool **OnAbsentClient** (XPCTcpSocket *pClient)
called when a client goes quiet...
- virtual bool **OnNewClient** (XPCTcpSocket *pNewClient, char *sName)
- virtual bool **ProcessClient** ()
- bool **StartThreads** ()
called from init to start the listen and server threads up

Protected Attributes

- CMOOSLock **m__SocketListLock**
- int **m__nTotalActions**
internal count of the number of calls processed
- **THREAD_ID m__nListenThreadID**
ID of Listen Thread.
- **THREAD_ID m__nServerThreadID**
ID of Server Thread.
- **THREAD_ID m__nTimerThreadID**
ID of timer Thread.
- bool(* **m__pfnRxCallback**)(const std::string &sClient, MOOSMSG_LIST &MsgListRx, MOOSMSG_LIST &MsgListTx, void *pCaller)
- void * **m__pRxCallbackParam**
- bool(* **m__pfnDisconnectCallback**)(std::string &sClient, void *pParam)
- void * **m__pDisconnectCallbackParam**
- XPCTcpSocket * **m__pListenSocket**
- XPCTcpSocket * **m__pFocusSocket**
- SOCKETLIST **m__ClientSocketList**
- SOCKETFD_2_CLIENT_NAME_MAP **m__Socket2ClientMap**
- long **m__lListenPort**
port listen socket is bound to
- bool **m__bQuit**
threads continue while this flag is false
- int **m__nMaxSocketFD**
largest FD of all connected sockets
- std::string **m__sCommunityName**
name of community being served

3.5.1 Detailed Description

This class is the MOOS Comms Server. It lies at the heart of the communications architecture and typically is of no interest to the component developer. It maintains a list of all the connected clients and their names. It simultaneously listens on all sockets for calling clients and then calls a user supplied call back to handle the request. This class is only used by the CMOOSDB application

3.5.2 Member Typedef Documentation

3.5.2.1 `typedef pthread_t CMOOSCommServer::THREAD_ID` [protected]

Win32 handle to Server thread

See also:

`ServerLoop`(p. 28)

3.5.3 Member Function Documentation

3.5.3.1 `void CMOOSCommServer::DoBanner ()` [protected, virtual]

prints class information banner to stdout

3.5.3.2 `string CMOOSCommServer::GetClientName (XPCTcpSocket * pSocket)` [protected]

Get the name of the client on the remote end of pSocket

3.5.3.3 `int CMOOSCommServer::GetMaxSocketFD ()` [protected]

figures out what the largest socket FD of all connected sockets. (needed by select)

3.5.3.4 `bool CMOOSCommServer::HandShake (XPCTcpSocket * pNewSocket)` [protected]

Perform handshaking with client just after a connection has been accepted

3.5.3.5 `bool CMOOSCommServer::IsUniqueName (std::string & sClientName)` [protected]

returns true if a server has no connection to the named client

Parameters:

sClientName reference to client name std::string

3.5.3.6 `bool CMOOSCommServer::ListenLoop ()`

This function is the listen loop called from one of the two server threads. It is responsible for accepting a coonection and creating a new client socket.

3.5.3.7 `bool CMOOSCommServer::OnNewClient (XPCTcpSocket * pNewClient, char * sName)` [protected, virtual]

Called when a new client connects. Performs handshaking and adds new socket to m_ClientSocketList

Parameters:

pNewClient pointer to teh new socket created in ListenLoop;

See also:

ListenLoop(p. 27)

3.5.3.8 `void CMOOSCommServer::PoisonClient (XPCTcpSocket * pSocket, char * sReason)` [protected]

Send a Poisoned mesasge to the client on the end of pSocket. This may cause teh client comms thrad to die

3.5.3.9 `bool CMOOSCommServer::ProcessClient ()` [protected, virtual]

called from Server loop this function handles all the processing for the current client call. It inturn invokes the user supplied callback function

3.5.3.10 `bool CMOOSCommServer::Run (long lPort, const std::string & sCommunityName)`

Initialise the server. This is a non blocking call and launches the MOOS Comms server threads.

Parameters:

lPort port number to listen on

3.5.3.11 `bool CMOOSCommServer::ServerLoop ()`

This function is the server loop called from one of the two server threads. It listens to all presently connected sockets and when a call is received invokes thse user supplied callback

3.5.3.12 `void CMOOSCommServer::SetOnDisconnectCallBack (bool(*) (std::string & sClient, void * pParam) pfn, void * pParam)`

Set the disconnect message call back handler. The supplied call back must be of the form static bool MyCallBack(std::string & sClient,, void * pParam).

Parameters:

sClient contains the incoming messages.

TxLst passed to the handler as a recepticle for all the message that should be sent back to the client in response to teh incoming messages.

pParam user supplied parameter to be passed to callback function

3.5.3.13 `void CMOOSCommServer::SetOnRxCallBack (bool*)(const std::string &sClient, MOOSMSG_LIST &MsgListRx, MOOSMSG_LIST &MsgListTx, void *pParam) pfn, void * pParam)`

Set the receive message call back handler. The callback will be called whenever a client sends one or more messages to the server. The supplied call back must be of the form `static bool MyCallBack(MOOSMSG_LIST & RxLst, MOOSMSG_LIST & TxLst, void * pParam)`.

Parameters:

sClient Name of client at the end of the socket sending this Pkt

RxLst contains the incoming messages.

TxLst passed to the handler as a receptacle for all the message that should be sent back to the client in response to the incoming messages.

pParam user supplied parameter to be passed to callback function

3.5.3.14 `bool CMOOSCommServer::TimerLoop ()`

This function is the timer loop called from one of the three server threads. It makes sure all clients speak occasionally

3.5.4 Member Data Documentation

3.5.4.1 `SOCKETLIST CMOOSCommServer::m_ClientSocketList` [protected]

list of all currently connected sockets

3.5.4.2 `void* CMOOSCommServer::m_pDisconnectCallBackParam` [protected]

place holder for the address of the object passed back to the user during a Disconnect callback

See also:

`SetOnDisconnectCallBack`(p. 28)

3.5.4.3 `bool(* CMOOSCommServer::m_pfnDisconnectCallBack)(std::string &sClient, void *pParam)` [protected]

user supplied OnDisconnect callback

See also:

`SetOnDisconnectCallBack`(p. 28)

3.5.4.4 `bool(* CMOOSCommServer::m_pfnRxCallBack)(const std::string &sClient, MOOSMSG_LIST &MsgListRx, MOOSMSG_LIST &MsgListTx, void *pCaller)` [protected]

user supplied OnRx callback

See also:

`SetOnRxCallBack`(p. 29)

3.5.4.5 XPCTcpSocket* CMOOSCommServer::m_pFocusSocket [protected]

pointer to the socket which server is currently processing call from

3.5.4.6 XPCTcpSocket* CMOOSCommServer::m_pListenSocket [protected]

Listen socket (bound to port address supplied in constructor)

3.5.4.7 void* CMOOSCommServer::m_pRxCallBackParam [protected]

place holder for teh address of the object passed back to the user during an Rx callback

See also:

SetOnRxCallBack(p. 29)

3.5.4.8 SOCKETFD_2_CLIENT_NAME_MAP CMOOSCommServer::m_Socket2ClientMap [protected]

map of socket file descriptors to the std::string name of the client process at teh other end

3.5.4.9 CMOOSLock CMOOSCommServer::m_SocketListLock [protected]

a simple mutex to guard access to m_ClientSocketList

See also:

m_ClientSocketList(p. 29)

The documentation for this class was generated from the following files:

- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSCommServer.h
- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSCommServer.cpp

3.6 CMOOSEException Class Reference

```
#include <CMOSEException.h>
```

Public Member Functions

- **CMOSEException** (const char *sStr)
- **CMOSEException** (const std::string &s)
- char * **c_str** ()

Public Attributes

- char **m_sReason** [100]
storage for the exception reason

3.6.1 Detailed Description

A trivial Exception class

3.6.2 Constructor & Destructor Documentation

3.6.2.1 CMOOSEException::CMOSEException (const char * sStr)

construct an exception with a string argument giving the reason for teh exception


The documentation for this class was generated from the following files:

- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOSEException.h
- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOSEException.cpp

3.7 CMOOSInstrument Class Reference

```
#include <MOOSInstrument.h>
```

Inheritance diagram for CMOOSInstrument::



Static Public Member Functions

- static std::string **Message2NMEA** (std::string sMsg)
- static bool **DoNMEACheckSum** (std::string sNMEA)

Public Attributes

- CMOOSLinuxSerialPort **m_Port**

Protected Member Functions

- virtual bool **OnStartUp** ()
- virtual bool **InitialiseSensor** ()
- bool **InitialiseSensorN** (int nAttempts, std::string sSensorName)
- virtual bool **SetupPort** ()
- bool **PublishRaw** ()
- double **GetMagneticOffset** ()
- void **SetInstrumentErrorMessage** (std::string sError)
- void **SetPrompt** (std::string sPrompt)

Protected Attributes

- bool **m_bPublishRaw**
- std::string **m_sResourceName**
- double **m_dfMagneticOffset**
- std::string **m_sPrompt**
- std::string **m_sInstrumentErrorMessage**

3.7.1 Detailed Description

Class that derives from **CMOOSApp**(p. 5) and adds functionality of cross platform serial ports

3.7.2 Member Function Documentation

3.7.2.1 static bool CMOOSInstrument::DoNMEACheckSum (std::string *sNMEA*) [static]

performs NMEA string checksum

3.7.2.2 double CMOOSInstrument::GetMagneticOffset () [protected]

some legacy stuff that should be removed...

3.7.2.3 bool CMOOSInstrument::InitialiseSensor () [protected, virtual]

called from OnStartUp - overload to execute custom start up code for sensor

3.7.2.4 bool CMOOSInstrument::InitialiseSensorN (int *nAttempts*, std::string *sSensorName*) [protected]

called from OnStartUp class InitialiseSensor N times

3.7.2.5 static std::string CMOOSInstrument::Message2NMEA (std::string *sMsg*) [static]

turns a string into NMEA string

3.7.2.6 bool CMOOSInstrument::OnStartUp () [protected, virtual]

CMOOSApp(p. 5) override

Reimplemented from CMOOSApp (p. 9).

3.7.2.7 bool CMOOSInstrument::PublishRaw () [inline, protected]

returns true if instrument is publishing raw data

3.7.2.8 bool CMOOSInstrument::SetupPort () [protected, virtual]

Set up the serial port by reading parameters from mission file

3.7.3 Member Data Documentation

3.7.3.1 bool CMOOSInstrument::m_bPublishRaw [protected]

set to true if this instrument should publish the raw incoming data to the DB

3.7.3.2 double CMOOSInstrument::m_dfMagneticOffset [protected]

some legacy stuff that should be removed...

3.7.3.3 CMOOSLinuxSerialPort CMOOSInstrument::m_Port

A sensor port

3.7.3.4 std::string CMOOSInstrument::m_sResourceName [protected]

a place holder for a the name of this sensor resource - rarely used

The documentation for this class was generated from the following files:

- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSInstrument.h
- /home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSInstrument.cpp

3.8 CMOOSMsg Class Reference

```
#include <MOOSMsg.h>
```

Public Member Functions

- **CMOOSMsg** ()
- **CMOOSMsg** (char cMsgType, const std::string &sKey, double dfVal, double dfTime=-1)
- **CMOOSMsg** (char cMsgType, const std::string &sKey, const std::string &sVal, double dfTime=-1)
- bool **IsDataType** (char cDataType)
- bool **IsDouble** ()
- bool **IsString** ()
- bool **IsSkewed** (double dfTimeNow, double *pdfSkew=NULL)
- bool **IsYoungerThan** (double dfAge)
- bool **IsType** (char cType)
- double **GetTime** ()
- double **GetDouble** ()
- std::string **GetString** ()
- std::string **GetKey** ()
- std::string **GetName** ()
- std::string **GetSource** ()
- std::string **GetCommunity** ()
- std::string **GetAsString** (int nFieldWidth=12)
- void **Trace** ()
- void **SetDouble** (double dfD)
- int **Serialize** (unsigned char *pBuffer, int nLen, bool bToStream=true)
- bool **operator<** (const **CMOOSMsg** &Msg) const

Public Attributes

- char **m_cMsgType**
- char **m_cDataType**
- std::string **m_sKey**
- int **m_nID**
- double **m_dfTime**
- double **m_dfVal**
- double **m_dfVal2**
- std::string **m_sVal**
- std::string **m_sSrc**
- std::string **m_sOriginatingCommunity**

3.8.1 Detailed Description

MOOS Comms Messaging class. This is a class encapsulating the data which the MOOS Comms API shuttles between the MOOSDB and other clients

3.8.2 Constructor & Destructor Documentation

3.8.2.1 CMOOSMsg::CMOOSMsg ()

standard construction destruction

3.8.2.2 CMOOSMsg::CMOOSMsg (char *cMsgType*, const std::string & *sKey*, double *dfVal*, double *dfTime* = -1)

specialised construction

3.8.2.3 CMOOSMsg::CMOOSMsg (char *cMsgType*, const std::string & *sKey*, const std::string & *sVal*, double *dfTime* = -1)

specialised construction

3.8.3 Member Function Documentation

3.8.3.1 string CMOOSMsg::GetAsString (int *nFieldWidth* = 12)

format the message as string regardless of type

3.8.3.2 std::string CMOOSMsg::GetCommunity () [inline]

return the name of the MOOS community in which the originator lives

3.8.3.3 double CMOOSMsg::GetDouble () [inline]

return double val of message

3.8.3.4 std::string CMOOSMsg::GetKey () [inline]

return the name of the message

3.8.3.5 std::string CMOOSMsg::GetSource () [inline]

return the name of the process (as registered with the DB) which posted this notification

3.8.3.6 std::string CMOOSMsg::GetString () [inline]

return string value of message

3.8.3.7 double CMOOSMsg::GetTime () [inline]

return time stamp of message

3.8.3.8 bool CMOOSMsg::IsDataType (char *cDataType*)

check data type (MOOS_STRING or MOOS_DOUBLE)

3.8.3.9 bool CMOOSMsg::IsDouble () [inline]

check data type is double

3.8.3.10 bool CMOOSMsg::IsSkewed (double *dfTimeNow*, double * *pdfSkew* = NULL)

return true if message is substantially (SKEW_TOLERANCE) older than dfTimeNow if pdfSkew is not NULL, the time skew is returned in *pdfSkew

3.8.3.11 bool CMOOSMsg::IsString () [inline]

check data type is string

3.8.3.12 bool CMOOSMsg::IsType (char *cType*)

check message type MOOS_NOTIFY, REGISTER etc

3.8.3.13 bool CMOOSMsg::IsYoungerThan (double *dfAge*)

return true if message is younger than dfAge

3.8.3.14 void CMOOSMsg::SetDouble (double *dfD*) [inline]

set the Double value

3.8.3.15 void CMOOSMsg::Trace ()

print a summary of the message

3.8.4 Member Data Documentation**3.8.4.1 char CMOOSMsg::m_cDataType**

what kind of data is this? String,Double,Array?

3.8.4.2 char CMOOSMsg::m_cMsgType

what type of message is this? Notification,Command,Register etc

3.8.4.3 double CMOOSMsg::m_dfTime

double precision time stamp (UNIX time)

3.8.4.4 `int CMOOSMsg::m_nID`

ID of message

3.8.4.5 `std::string CMOOSMsg::m_sKey`

what is the variable name?

The documentation for this class was generated from the following files:

- `/home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSMsg.h`
- `/home/pnewman/code/MOOS/trunk/Core/MOOSLIB/MOOSMsg.cpp`

Index

- AddMOOSVariable
 - CMOOSApp, 7
- ClientLoop
 - CMOOSCommClient, 15
- Close
 - CMOOSCommClient, 15
- CMOOSApp, 5
 - AddMOOSVariable, 7
 - ConfigureComms, 7
 - EnableCommandMessageFiltering, 7
 - GetAppName, 7
 - GetAppStartTime, 7
 - GetCommandKey, 7
 - GetIterateCount, 7
 - GetLastIterateTime, 7
 - GetMissionFileName, 8
 - GetMOOSVar, 8
 - GetTimeSinceIterate, 8
 - IsSimulateMode, 8
 - Iterate, 8
 - LookForAndHandleAppCommand, 8
 - m_bCommandMessageFiltering, 11
 - m_bServerSet, 11
 - m_bSimMode, 11
 - m_bUseMOOSComms, 11
 - m_Comms, 11
 - m_dfAppStartTime, 11
 - m_dfFreq, 11
 - m_dfLastRunTime, 11
 - m_lServerPort, 11
 - m_MissionReader, 11
 - m_MOOSVars, 11
 - m_nCommsFreq, 12
 - m_sAppName, 12
 - m_sMissionFile, 12
 - m_sServerHost, 12
 - m_sServerPort, 12
 - MakeStatusString, 8
 - MOOSDebugWrite, 8
 - OnCommandMsg, 8
 - OnConnectToServer, 9
 - OnDisconnectFromServer, 9
 - OnDisconnectToServerPrivate, 9
 - OnNewMail, 9
 - OnStartup, 9
 - PublishFreshMOOSVariables, 9
 - RegisterMOOSVariables, 9
 - Run, 9
 - SetAppFreq, 10
 - SetCommsFreq, 10
 - SetMOOSVar, 10
 - SetServer, 10
 - UpdateMOOSVariables, 10
 - UseMOOSComms, 10
- CMOOSCommClient, 13
- CMOOSCommClient
 - ClientLoop, 15
 - Close, 15
 - ConnectToServer, 15
 - DoBanner, 15
 - DoClientWork, 15
 - FakeSource, 15
 - Fetch, 15
 - GetDescription, 15
 - GetLocalIPAddress, 15
 - GetPublished, 15
 - GetRegistered, 16
 - HandShake, 16
 - IsConnected, 16
 - m_bConnected, 18
 - m_bFakeSource, 18
 - m_bMailPresent, 18
 - m_bQuit, 18
 - m_InBox, 19
 - m_InLock, 19
 - m_lPort, 19
 - m_nFundamentalFreq, 19
 - m_nInPendingLimit, 19
 - m_nOutPendingLimit, 19
 - m_OutBox, 19
 - m_OutLock, 19
 - m_pConnectCallBackParam, 20
 - m_pDisconnectCallBackParam, 20
 - m_pfnConnectCallBack, 20
 - m_pfnDisconnectCallBack, 20
 - m_pSocket, 20
 - m_Published, 20
 - m_Registered, 20
 - m_sDBHost, 20

- m_sMyName, 20
- Notify, 16
- OnCloseConnection, 16
- Peek, 16
- PeekMail, 16
- Post, 16
- Register, 17
- Run, 17
- ServerRequest, 17
- SetOnConnectCallBack, 17
- SetOnDisconnectCallBack, 18
- StartThreads, 18
- THREAD_ID, 14
- UnRegister, 18
- CMOOSCommObject, 22
- CMOOSCommPkt, 23
- CMOOSCommPkt
 - m_bAllocated, 24
 - Serialize, 23
- CMOOSCommServer, 25
- CMOOSCommServer
 - DoBanner, 27
 - GetClientName, 27
 - GetMaxSocketFD, 27
 - HandShake, 27
 - IsUniqueName, 27
 - ListenLoop, 27
 - m_ClientSocketList, 29
 - m_pDisconnectCallBackParam, 29
 - m_pfnDisconnectCallBack, 29
 - m_pfnRxCallBack, 29
 - m_pFocusSocket, 29
 - m_pListenSocket, 30
 - m_pRxCallBackParam, 30
 - m_Socket2ClientMap, 30
 - m_SocketListLock, 30
 - OnNewClient, 27
 - PoisonClient, 28
 - ProcessClient, 28
 - Run, 28
 - ServerLoop, 28
 - SetOnDisconnectCallBack, 28
 - SetOnRxCallBack, 28
 - THREAD_ID, 27
 - TimerLoop, 29
- CMOOSException, 31
 - CMOOSException, 31
- CMOOSInstrument, 32
 - DoNMEACheckSum, 33
 - GetMagneticOffset, 33
 - InitialiseSensor, 33
 - InitialiseSensorN, 33
 - m_bPublishRaw, 33
 - m_dfMagneticOffset, 33
 - m_Port, 33
 - m_sResourceName, 34
 - Message2NMEA, 33
 - OnStartUp, 33
 - PublishRaw, 33
 - SetupPort, 33
- CMOOSMsg, 35
 - CMOOSMsg, 36
 - GetAsString, 36
 - GetCommunity, 36
 - GetDouble, 36
 - GetKey, 36
 - GetSource, 36
 - GetString, 36
 - GetTime, 36
 - IsDataType, 36
 - IsDouble, 37
 - IsSkewed, 37
 - IsString, 37
 - IsType, 37
 - IsYoungerThan, 37
 - m_cDataType, 37
 - m_cMsgType, 37
 - m_dfTime, 37
 - m_nID, 37
 - m_sKey, 38
 - SetDouble, 37
 - Trace, 37
- ConfigureComms
 - CMOOSApp, 7
- ConnectToServer
 - CMOOSCommClient, 15
- DoBanner
 - CMOOSCommClient, 15
 - CMOOSCommServer, 27
- DoClientWork
 - CMOOSCommClient, 15
- DoNMEACheckSum
 - CMOOSInstrument, 33
- EnableCommandMessageFiltering
 - CMOOSApp, 7
- FakeSource
 - CMOOSCommClient, 15
- Fetch
 - CMOOSCommClient, 15
- GetAppName
 - CMOOSApp, 7
- GetAppStartTime
 - CMOOSApp, 7
- GetAsString

-
- CMOOSMsg, 36
 - GetClientName
 - CMOOSCommServer, 27
 - GetCommandKey
 - CMOOSApp, 7
 - GetCommunity
 - CMOOSMsg, 36
 - GetDescription
 - CMOOSCommClient, 15
 - GetDouble
 - CMOOSMsg, 36
 - GetIterateCount
 - CMOOSApp, 7
 - GetKey
 - CMOOSMsg, 36
 - GetLastIterateTime
 - CMOOSApp, 7
 - GetLocalIPAddress
 - CMOOSCommClient, 15
 - GetMagneticOffset
 - CMOOSInstrument, 33
 - GetMaxSocketFD
 - CMOOSCommServer, 27
 - GetMissionFileName
 - CMOOSApp, 8
 - GetMOOSVar
 - CMOOSApp, 8
 - GetPublished
 - CMOOSCommClient, 15
 - GetRegistered
 - CMOOSCommClient, 16
 - GetSource
 - CMOOSMsg, 36
 - GetString
 - CMOOSMsg, 36
 - GetTime
 - CMOOSMsg, 36
 - GetTimeSinceIterate
 - CMOOSApp, 8
 - HandShake
 - CMOOSCommClient, 16
 - CMOOSCommServer, 27
 - InitialiseSensor
 - CMOOSInstrument, 33
 - InitialiseSensorN
 - CMOOSInstrument, 33
 - IsConnected
 - CMOOSCommClient, 16
 - IsDataType
 - CMOOSMsg, 36
 - IsDouble
 - CMOOSMsg, 37
 - IsSimulateMode
 - CMOOSApp, 8
 - IsSkewed
 - CMOOSMsg, 37
 - IsString
 - CMOOSMsg, 37
 - IsType
 - CMOOSMsg, 37
 - IsUniqueName
 - CMOOSCommServer, 27
 - IsYoungerThan
 - CMOOSMsg, 37
 - Iterate
 - CMOOSApp, 8
 - ListenLoop
 - CMOOSCommServer, 27
 - LookForAndHandleAppCommand
 - CMOOSApp, 8
 - m_bAllocated
 - CMOOSCommPkt, 24
 - m_bCommandMessageFiltering
 - CMOOSApp, 11
 - m_bConnected
 - CMOOSCommClient, 18
 - m_bFakeSource
 - CMOOSCommClient, 18
 - m_bMailPresent
 - CMOOSCommClient, 18
 - m_bPublishRaw
 - CMOOSInstrument, 33
 - m_bQuit
 - CMOOSCommClient, 18
 - m_bServerSet
 - CMOOSApp, 11
 - m_bSimMode
 - CMOOSApp, 11
 - m_bUseMOOSComms
 - CMOOSApp, 11
 - m_cDataType
 - CMOOSMsg, 37
 - m_ClientSocketList
 - CMOOSCommServer, 29
 - m_cMsgType
 - CMOOSMsg, 37
 - m_Comms
 - CMOOSApp, 11
 - m_dfAppStartTime
 - CMOOSApp, 11
 - m_dfFreq
 - CMOOSApp, 11
 - m_dfLastRunTime
 - CMOOSApp, 11
-

- m_dfMagneticOffset
 - CMOOSInstrument, 33
- m_dfTime
 - CMOOSMsg, 37
- m_InBox
 - CMOOSCommClient, 19
- m_InLock
 - CMOOSCommClient, 19
- m_lPort
 - CMOOSCommClient, 19
- m_lServerPort
 - CMOOSApp, 11
- m_MissionReader
 - CMOOSApp, 11
- m_MOOSVars
 - CMOOSApp, 11
- m_nCommsFreq
 - CMOOSApp, 12
- m_nFundamentalFreq
 - CMOOSCommClient, 19
- m_nID
 - CMOOSMsg, 37
- m_nInPendingLimit
 - CMOOSCommClient, 19
- m_nOutPendingLimit
 - CMOOSCommClient, 19
- m_OutBox
 - CMOOSCommClient, 19
- m_OutLock
 - CMOOSCommClient, 19
- m_pConnectCallBackParam
 - CMOOSCommClient, 20
- m_pDisconnectCallBackParam
 - CMOOSCommClient, 20
 - CMOOSCommServer, 29
- m_pfnConnectCallBack
 - CMOOSCommClient, 20
- m_pfnDisconnectCallBack
 - CMOOSCommClient, 20
 - CMOOSCommServer, 29
- m_pfnRxCallBack
 - CMOOSCommServer, 29
- m_pFocusSocket
 - CMOOSCommServer, 29
- m_pListenSocket
 - CMOOSCommServer, 30
- m_Port
 - CMOOSInstrument, 33
- m_pRxCallBackParam
 - CMOOSCommServer, 30
- m_pSocket
 - CMOOSCommClient, 20
- m_Published
 - CMOOSCommClient, 20
- m_Registered
 - CMOOSCommClient, 20
- m_sAppName
 - CMOOSApp, 12
- m_sDBHost
 - CMOOSCommClient, 20
- m_sKey
 - CMOOSMsg, 38
- m_sMissionFile
 - CMOOSApp, 12
- m_sMyName
 - CMOOSCommClient, 20
- m_Socket2ClientMap
 - CMOOSCommServer, 30
- m_SocketListLock
 - CMOOSCommServer, 30
- m_sResourceName
 - CMOOSInstrument, 34
- m_sServerHost
 - CMOOSApp, 12
- m_sServerPort
 - CMOOSApp, 12
- MakeStatusString
 - CMOOSApp, 8
- Message2NMEA
 - CMOOSInstrument, 33
- MOOSDebugWrite
 - CMOOSApp, 8
- Notify
 - CMOOSCommClient, 16
- OnCloseConnection
 - CMOOSCommClient, 16
- OnCommandMsg
 - CMOOSApp, 8
- OnConnectToServer
 - CMOOSApp, 9
- OnDisconnectFromServer
 - CMOOSApp, 9
- OnDisconnectToServerPrivate
 - CMOOSApp, 9
- OnNewClient
 - CMOOSCommServer, 27
- OnNewMail
 - CMOOSApp, 9
- OnStartUp
 - CMOOSApp, 9
 - CMOOSInstrument, 33
- Peek
 - CMOOSCommClient, 16
- PeekMail
 - CMOOSCommClient, 16

- PoisonClient
 - CMOOSCommServer, 28
- Post
 - CMOOSCommClient, 16
- ProcessClient
 - CMOOSCommServer, 28
- PublishFreshMOOSVariables
 - CMOOSApp, 9
- PublishRaw
 - CMOOSInstrument, 33
- Register
 - CMOOSCommClient, 17
- RegisterMOOSVariables
 - CMOOSApp, 9
- Run
 - CMOOSApp, 9
 - CMOOSCommClient, 17
 - CMOOSCommServer, 28
- Serialize
 - CMOOSCommPkt, 23
- ServerLoop
 - CMOOSCommServer, 28
- ServerRequest
 - CMOOSCommClient, 17
- SetAppFreq
 - CMOOSApp, 10
- SetCommsFreq
 - CMOOSApp, 10
- SetDouble
 - CMOOSMsg, 37
- SetMOOSVar
 - CMOOSApp, 10
- SetOnConnectCallBack
 - CMOOSCommClient, 17
- SetOnDisconnectCallBack
 - CMOOSCommClient, 18
 - CMOOSCommServer, 28
- SetOnRxCallBack
 - CMOOSCommServer, 28
- SetServer
 - CMOOSApp, 10
- SetupPort
 - CMOOSInstrument, 33
- StartThreads
 - CMOOSCommClient, 18
- THREAD_ID
 - CMOOSCommClient, 14
 - CMOOSCommServer, 27
- TimerLoop
 - CMOOSCommServer, 29
- Trace
 - CMOOSMsg, 37
- UnRegister
 - CMOOSCommClient, 18
- UpdateMOOSVariables
 - CMOOSApp, 10
- UseMOOSComms
 - CMOOSApp, 10