

pFUnit

Generated by Doxygen 1.8.5

Mon Dec 16 2013 12:49:57



# Contents

<b>1</b>	<b>pFUnit 2 - Documentation - Version 0.0 (2013-1213-1 MLR)</b>	<b>1</b>
1.1	Overview . . . . .	1
1.2	Contents . . . . .	1
1.3	See Also . . . . .	2
1.4	Copyright . . . . .	2
<b>2</b>	<b>Installation</b>	<b>3</b>
2.1	Installing pFUnit . . . . .	3
2.2	Prerequisites . . . . .	3
2.3	Obtaining pFUnit . . . . .	4
2.4	Manifest - What's in the directory? . . . . .	4
2.5	Configuration . . . . .	4
2.6	Building pFUnit . . . . .	5
2.6.1	Building pFUnit for testing serial codes (Non-MPI) . . . . .	5
2.6.2	Building pFUnit for testing parallel codes (MPI) . . . . .	5
2.6.3	Cleaning . . . . .	5
2.6.4	Documentation . . . . .	6
2.7	Installation . . . . .	6
2.7.1	Installation - Serial . . . . .	6
2.7.2	Installation - MPI . . . . .	6
2.7.3	Installation - DEFAULT DIRECTORY . . . . .	6
<b>3</b>	<b>Usage</b>	<b>7</b>
3.1	Usage . . . . .	7
3.1.1	Usage - Configuration . . . . .	7
3.1.2	Usage - Hello World . . . . .	7
3.1.3	Usage - Preprocessor . . . . .	8
<b>4</b>	<b>Development</b>	<b>9</b>
<b>5</b>	<b>Feedback &amp; Support</b>	<b>11</b>
5.1	Feedback . . . . .	11
5.2	Support . . . . .	11

<b>6</b>	<b>FAQ and Tips</b>	<b>13</b>
6.1	FAQ	13
6.1.1	Zero Tests Run	13
6.1.2	Some Tests Are Not Running	13
6.2	Tips	14
6.2.1	Environment Modules	14
6.2.2	Compile Time Errors	14
6.2.3	Intermediate files used by pFUnit	14
<b>7</b>	<b>Platform Specific Notes</b>	<b>15</b>
7.1	Mac OSX	15
7.2	Windows/CYGWIN	15
<b>8</b>	<b>Acknowledgments</b>	<b>17</b>
<b>9</b>	<b>Known Installations &amp; Versions</b>	<b>19</b>
<b>10</b>	<b>TODO</b>	<b>21</b>
<b>11</b>	<b>The Preprocessor - pFUnitParser</b>	<b>23</b>
11.1	Using The Preprocessor	23
11.1.1	Configuration - testSuites.inc	23
11.1.2	Invocation	24
11.1.3	Preprocessor Input File (.pf)	24
11.1.4	Directives	24
11.1.4.1	@Parameters	24
11.1.4.2	@TestCase	24
11.1.4.3	@Test	25
11.1.4.4	@MPITest	25
<b>12</b>	<b>Revision Notes</b>	<b>27</b>
<b>13</b>	<b>Data Type Index</b>	<b>29</b>
13.1	Class Hierarchy	29
<b>14</b>	<b>Data Type Index</b>	<b>33</b>
14.1	Data Types List	33
<b>15</b>	<b>Data Type Documentation</b>	<b>37</b>
15.1	pFUnitParser.Action Class Reference	37
15.2	add_mod Module Reference	37
15.3	addcomplex_mod Module Reference	38
15.4	CodeUtilities.ArrayDescription Class Reference	38
15.5	assert_mod Module Reference	38

15.5.1 Detailed Description . . . . .	39
15.6 assertbasic_mod Module Reference . . . . .	39
15.6.1 Detailed Description . . . . .	39
15.7 assertinteger_mod Module Reference . . . . .	40
15.7.1 Detailed Description . . . . .	40
15.8 GenerateRealArrayNewSignature.AssertRealArrayArgument Class Reference . . . . .	40
15.9 pFUnitParser.AtAfter Class Reference . . . . .	41
15.10pFUnitParser.AtAssert Class Reference . . . . .	41
15.11pFUnitParser.AtBefore Class Reference . . . . .	42
15.12pFUnitParser.AtBegin Class Reference . . . . .	42
15.13pFUnitParser.AtMpiTest Class Reference . . . . .	43
15.14pFUnitParser.AtParameters Class Reference . . . . .	43
15.15pFUnitParser.AtSuite Class Reference . . . . .	44
15.16pFUnitParser.AtTest Class Reference . . . . .	44
15.17pFUnitParser.AtTestCase Class Reference . . . . .	45
15.18basetestrunner_mod Module Reference . . . . .	45
15.18.1 Detailed Description . . . . .	45
15.19beforeafter_mod Module Reference . . . . .	46
15.20brokensetupcase_mod Module Reference . . . . .	46
15.21brokentestcase_mod Module Reference . . . . .	46
15.22GenerateRealArrayNewSignature.constraintASSERTEQUAL Class Reference . . . . .	46
15.22.1 Constructor & Destructor Documentation . . . . .	47
15.22.1.1 __init__ . . . . .	47
15.22.2 Member Data Documentation . . . . .	47
15.22.2.1 name1 . . . . .	47
15.22.2.2 tolerance . . . . .	47
15.23mods.pre.pre2.dataString Class Reference . . . . .	47
15.24debuglistener_mod Module Reference . . . . .	48
15.24.1 Detailed Description . . . . .	48
15.25CodeUtilities.declaration Class Reference . . . . .	49
15.26dynamictestcase_mod Module Reference . . . . .	49
15.26.1 Detailed Description . . . . .	49
15.27exception_mod Module Reference . . . . .	49
15.28fixture_mod Module Reference . . . . .	50
15.29fixturetestcase_mod Module Reference . . . . .	50
15.30CodeUtilities.fortranSubroutineSignature Class Reference . . . . .	50
15.31halo_mod Module Reference . . . . .	51
15.32mods.pre.pre_If.IfDirective Class Reference . . . . .	51
15.33CodeUtilities.implementation Class Reference . . . . .	52
15.34CodeUtilities.interfaceBlock Class Reference . . . . .	52

15.35mods.pre.pre_if.interval Class Reference . . . . .	52
15.36GenerateRealArrayNewSignature.IsWithinTolerance Class Reference . . . . .	52
15.37test_restrictsphericalcoordinates_mod::latloncase Type Reference . . . . .	53
15.38linearinterpolator_mod Module Reference . . . . .	53
15.39makeinfinity_mod Module Reference . . . . .	53
15.39.1 Detailed Description . . . . .	54
15.40makenan_mod Module Reference . . . . .	54
15.40.1 Detailed Description . . . . .	54
15.41mockcall_mod Module Reference . . . . .	55
15.41.1 Detailed Description . . . . .	55
15.42mocklistener_mod Module Reference . . . . .	55
15.43testParser.MockParser Class Reference . . . . .	55
15.44mockrepository_mod Module Reference . . . . .	56
15.44.1 Detailed Description . . . . .	56
15.45mocksut_mod Module Reference . . . . .	56
15.46testParser.MockWriter Class Reference . . . . .	56
15.47CodeUtilities.module Class Reference . . . . .	57
15.48mpicontext_mod Module Reference . . . . .	57
15.48.1 Detailed Description . . . . .	57
15.49mpistubs_mod Module Reference . . . . .	58
15.49.1 Detailed Description . . . . .	58
15.50mpitestcase_mod Module Reference . . . . .	58
15.50.1 Detailed Description . . . . .	59
15.51mpitestmethod_mod Module Reference . . . . .	59
15.51.1 Detailed Description . . . . .	59
15.52parallelcontext_mod Module Reference . . . . .	59
15.52.1 Detailed Description . . . . .	60
15.53parallelexception_mod Module Reference . . . . .	60
15.53.1 Detailed Description . . . . .	60
15.54parameterizedtestcase_mod Module Reference . . . . .	60
15.54.1 Detailed Description . . . . .	61
15.55params_mod Module Reference . . . . .	61
15.55.1 Detailed Description . . . . .	61
15.56pFUnitParser.Parser Class Reference . . . . .	62
15.57test_parameters_mod::pecase Type Reference . . . . .	62
15.58pfunit Module Reference . . . . .	63
15.58.1 Detailed Description . . . . .	63
15.59pfunit_mod Module Reference . . . . .	63
15.59.1 Detailed Description . . . . .	63
15.60privateexception_mod Module Reference . . . . .	64

15.60.1 Detailed Description . . . . .	64
15.61 mods.pre.pre2.procDirective Class Reference . . . . .	65
15.61.1 Member Function Documentation . . . . .	65
15.61.1.1 addTokenRE . . . . .	65
15.62 remoteproxytestcase_mod Module Reference . . . . .	65
15.62.1 Detailed Description . . . . .	65
15.63 mods.pre.pre_Repeat.RepeatDirective Class Reference . . . . .	66
15.64 resultprinter_mod Module Reference . . . . .	66
15.64.1 Detailed Description . . . . .	67
15.65 robustrunner_mod Module Reference . . . . .	67
15.65.1 Detailed Description . . . . .	67
15.66 robusttestsuite_mod Module Reference . . . . .	68
15.67 CodeUtilities.routineUnit Class Reference . . . . .	68
15.68 serialcontext_mod Module Reference . . . . .	68
15.68.1 Detailed Description . . . . .	69
15.69 simpletestcase_mod Module Reference . . . . .	69
15.70 sourcelocation_mod Module Reference . . . . .	69
15.70.1 Detailed Description . . . . .	70
15.71 sphericalcoordinates_mod Module Reference . . . . .	70
15.72 testlistener_mod::startTest Interface Reference . . . . .	70
15.73 stringconversionutilities_mod Module Reference . . . . .	70
15.73.1 Detailed Description . . . . .	71
15.74 subsetrunner_mod Module Reference . . . . .	71
15.74.1 Detailed Description . . . . .	71
15.75 surrogatetestcase_mod Module Reference . . . . .	72
15.75.1 Detailed Description . . . . .	72
15.76 sut_mod Module Reference . . . . .	72
15.77 test_assert_mod Module Reference . . . . .	72
15.78 test_assertbasic_mod Module Reference . . . . .	72
15.79 test_assertcomplex_mod Module Reference . . . . .	73
15.80 test_assertinteger_mod Module Reference . . . . .	73
15.81 test_assertreal_mod Module Reference . . . . .	74
15.82 test_exception_mod Module Reference . . . . .	74
15.83 test_fixturetestcase_mod Module Reference . . . . .	75
15.84 test_linearinterpolator_mod::test_linearinterpolator Type Reference . . . . .	75
15.85 test_linearinterpolator_mod Module Reference . . . . .	75
15.86 test_mockcall_mod Module Reference . . . . .	76
15.87 test_mockrepository_mod Module Reference . . . . .	76
15.88 test_mod Module Reference . . . . .	76
15.88.1 Detailed Description . . . . .	76

15.89	<a href="#">test_mpicontext_mod Module Reference</a>	77
15.90	<a href="#">test_mpiexception_mod Module Reference</a>	77
15.91	<a href="#">test_mptestcase_mod Module Reference</a>	77
15.92	<a href="#">test_parameters_mod::test_parameters Interface Reference</a>	78
15.93	<a href="#">test_parameters_mod Module Reference</a>	78
15.94	<a href="#">test_restrictsphericalcoordinates_mod::test_restrictsphericalcoordinates Interface Reference</a>	79
15.95	<a href="#">test_restrictsphericalcoordinates_mod Module Reference</a>	79
15.96	<a href="#">test_robustrunner_mod Module Reference</a>	80
15.97	<a href="#">test_simpletestcase_mod Module Reference</a>	80
15.98	<a href="#">test_stringconversionutilities_mod Module Reference</a>	80
15.99	<a href="#">test_testmethod_mod Module Reference</a>	80
15.100	<a href="#">test_testresult_mod Module Reference</a>	81
15.101	<a href="#">test_testsuite_mod Module Reference</a>	81
15.102	<a href="#">test_unixprocess_mod Module Reference</a>	81
15.103	<a href="#">testcase_mod Module Reference</a>	81
15.103.1	<a href="#">Detailed Description</a>	82
15.104	<a href="#">testfailure_mod Module Reference</a>	82
15.104.1	<a href="#">Detailed Description</a>	82
15.105	<a href="#">nodes.pre.pre_If.TestIfDirective Class Reference</a>	82
15.106	<a href="#">nodes.pre.interleavedp.TestInterleaved Class Reference</a>	83
15.107	<a href="#">testlistener_mod Module Reference</a>	83
15.107.1	<a href="#">Detailed Description</a>	84
15.108	<a href="#">testmethod_mod Module Reference</a>	84
15.108.1	<a href="#">Detailed Description</a>	84
15.109	<a href="#">nodes.pre.parseArgs.TestParseArgs Class Reference</a>	84
15.110	<a href="#">testParser.TestParseLine Class Reference</a>	85
15.110.1	<a href="#">Member Function Documentation</a>	85
15.110.1.1	<a href="#">testAtMpiTest</a>	85
15.110.1.2	<a href="#">testAtTest</a>	86
15.110.1.3	<a href="#">testMatchAtAfter</a>	86
15.110.1.4	<a href="#">testMatchAtAssertEqual</a>	86
15.110.1.5	<a href="#">testMatchAtAssertOther</a>	86
15.110.1.6	<a href="#">testMatchAtBefore</a>	86
15.110.1.7	<a href="#">testMatchAtSuite</a>	86
15.110.1.8	<a href="#">testMatchAtTestCase</a>	86
15.111	<a href="#">nodes.pre.pre_Repeat.TestRepeatDirective Class Reference</a>	86
15.112	<a href="#">testresult_mod Module Reference</a>	87
15.112.1	<a href="#">Detailed Description</a>	87
15.113	<a href="#">testrunner_mod Module Reference</a>	87
15.113.1	<a href="#">Detailed Description</a>	88



15.114. <a href="#">testsuite_mod</a> Module Reference . . . . .	88
15.114.1. Detailed Description . . . . .	88
15.115. <a href="#">throwfundamentaltypes_mod</a> Module Reference . . . . .	89
15.115.1. Detailed Description . . . . .	89
15.116. <a href="#">nixpipeinterfaces_mod</a> Module Reference . . . . .	89
15.116.1. Detailed Description . . . . .	89
15.117. <a href="#">nixprocess_mod</a> Module Reference . . . . .	90
15.117.1. Detailed Description . . . . .	90
15.118. <a href="#">GenerateRealArrayNewSignature.VECTOR_NORM</a> Class Reference . . . . .	90

**Index****92**



# Chapter 1

## pFUnit 2 - Documentation - Version 0.0 (2013-1213-1 MLR)

### 1.1 Overview

pFUnit is a unit testing framework enabling JUnit-like testing of serial and MPI-parallel software written in Fortran. It makes use of modern Fortran programming techniques, including object oriented programming, offering a convenient, lightweight mechanism for Fortran developers to create and run software tests that specify the desired behavior for a given piece of code. The framework was originally created by developers from NASA and NGC TASC. The project is hosted at [sourceforge/projects/pfunit](https://sourceforge.net/projects/pfunit).

If you are using pFUnit, please leave a note/topic at [Applications of pFUnit](#), or send a note to [Tom Clune](#), Ph.D., Chief, Software Systems Support Office Code 610.3, NASA Goddard Space Flight Center.

Please refer revisions and comments about the documentation to [Mike Rilee](#), Ph.D., Rilee Systems Technologies.

### 1.2 Contents

- [Installation](#)
- [Usage](#)
- [Development](#)
- [Feedback & Support](#)
- [FAQ and Tips](#)
- [Platform Specific Notes](#)
- [Acknowledgments](#)
- [Known Installations & Versions](#)
- [TODO](#)
- [The Preprocessor - pFUnitParser](#)
- [Revision Notes](#)

## 1.3 See Also

- [sourceforge/projects/pfunit](#)
- [NASA Modeling Guru](#)
- [JUnit.org](#)

## 1.4 Copyright

Copyright 2005 United States Government as represented by the Administrator of the National Aeronautics and Space Administration. All Rights Reserved.

## Chapter 2

# Installation

### 2.1 Installing pFUnit

Comentatry for the page.

- [Prerequisites](#)
- [Obtaining pFUnit](#)
- [Manifest - What's in the directory?](#)
- [Configuration](#)
- [Building pFUnit](#)
  - [Building pFUnit for testing serial codes \(Non-MPI\)](#)
  - [Building pFUnit for testing parallel codes \(MPI\)](#)
  - [Cleaning](#)
  - [Documentation](#)
- [Installation](#)

### 2.2 Prerequisites

The development work for pFUnit has mostly been carried out on a mixture of systems, including high-end computers, Apple Mac OSX, and linux-based systems. A preliminary Windows/CYGWIN port has been contributed by a user. Full use of the system depends on the following being available.

- Fortran 2003+ (Tested with Intel 13.1+, NAG 5.3, GCC 4.8.1., IBM's XLF)
- The Message Passing Interface (MPI)
- GNU Make
- Python

[Doxygen](#) is used to generate documentation.

The system is routinely tested with GNU, Intel, and NAG fortran compilers and OpenMPI, as well as nightly regression testing.

## 2.3 Obtaining pFUnit

The best way to obtain pFUnit is to clone the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

<http://sourceforge.net/projects/pfunit/> or <http://sourceforge.net/projects/pfunit/files/la>

Extracting this tarfile via a command like

```
$ tar xzf ./pFUnit.tar.gz
```

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

<https://sourceforge.net/p/pfunit/code/ci/master/tree/>

or contact the pFUnit team.

## 2.4 Manifest - What's in the directory?

In the top level of the pFUnit distribution you will see the following files.

**COPYRIGHT** - Contains information pertaining to the use and distribution of pFUnit.

**Examples** - Contains examples of how to use pFUnit once it is installed.

**GNUmakefile** - The top level makefile for building and installing pFUnit.

**bin** - Executables used to construct and perform unit tests.

**include** - Files to be included into makefiles or source, including use code.

**source** - Source code and scripts of the pFUnit library and framework.

**tests** - Source code for unit testing pFUnit itself.

**tools** - Tools used to help develop, build, and install pFUnit.

## 2.5 Configuration

Little needs to be done to configure pFUnit for the build, however there are several environment variables on which the package depends.

**F90\_VENDOR** - is set to include the correct makefile in /include, i.e. GNU, Intel, NAG, or PGI. Case insensitive file systems may cause some confusion from time-to-time.

**F90** - is set to the Fortran compiler being used: e.g. ifort for Intel, gfortran for GNU.

**COMPILER** - is set according to **F90\_VENDOR** and is automatically set in the top level makefile.

For MPI-based unit testing, your setup may require the following as well.

**MPIF90**

```
$ export MPIF90=mpif90
```

As a convenience for working with multiple MPI configurations, you may also set the following.

**MPIRUN**

```
$ export MPIRUN=/some.path/mpirun
```

## 2.6 Building pFUnit

### 2.6.1 Building pFUnit for testing serial codes (Non-MPI)

1. Change to the directory into which pFUnit has been placed.
2. Set the environment variables (in bash):

```
$ export F90=gfortran-mp-4.8
$ export F90_VENDOR=GNU
```

3. To build pFUnit for unit testing of serial codes, execute make. The unit tests for pFUnit itself will run automatically.

```
$ make tests
```

3.1 Occasionally on the first run through, one will get a spurious (runtime) error, for example in the unix process component.

Re-execute "make tests" to check again.

4. At this point the pFUnit object library is in the source directory, along with a large number of Fortran module files.

### 2.6.2 Building pFUnit for testing parallel codes (MPI)

To build pFUnit for unit testing MPI-based codes, be sure that the environment is properly set up for the MPI implementation you are using. Depending on your local environment, you may need execute the build within a batch or other job queuing system, e.g. an interactive batch job under PBS. The steps for building pFUnit start out the same as for the serial case above, but add MPI=YES to the environment to switch on MPI support. The MPI-based unit tests for pFUnit itself will run automatically. Again, occasionally a spurious (runtime) error may appear on the first execution.

1. Execute make as follows.

```
$ make tests MPI=YES
```

2. At this point an MPI-enabled pFUnit object library is in the source directory, along with a large number of Fortran module files.

Also, one may get some harmless "no symbols" warnings when the pFUnit library is constructed.

### 2.6.3 Cleaning

To clean the pFUnit build directory for the space or to rebuild there are two options.

1. Make clean to remove object files and other intermediate products.

```
$ make clean
```

2. Make distclean to remove libraries and other more final products.

```
$ make distclean
```

3. Some directories support a `make src_clean` to remove intermediate products in subdirectories.

## 2.6.4 Documentation

A start at documentation for pFUnit is in the documentation directory. `Doxygen` is our primary documentation tool. To make the documentation, which will be generated in the documentation directory, please invoke the following.

```
$ make documentation
```

## 2.7 Installation

### 2.7.1 Installation - Serial

To install pFUnit for regular use, set `INSTALL_DIR` to the location in which to place pFUnit. This can be done on the make command line. For example, after compiling pFUnit for serial use (MPI absent or `MPI=NO`), please try.

```
$ # In the top of the pFUnit build directory.
$ make install INSTALL_DIR=/opt/pfunit/pfunit-serial
```

Note: you may need special privileges to install in some locations, e.g. via `sudo`.

To test the installation set `PFUNIT` to `INSTALL_DIR`, then change the working directory to Examples in pFUnit distribution and execute "buildIt," which will run a number of examples. These include some expected failures.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-serial
$ pushd Examples
$ ./buildIt
```

### 2.7.2 Installation - MPI

For installing an MPI-enabled pFUnit library, change to the top of the distribution and execute make with `MPI=YES`. You may need to "make distclean" first. After compilation and pFUnit passes its self-tests, then installation proceeds as for the serial case above.

```
$ make install INSTALL_DIR=/opt/pfunit/pfunit-parallel
```

To test, set `PFUNIT` and go into Examples/MPI\_Halo directory.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-parallel
$ # The variable MPIF90 must be set to the appropriate build script.
$ export MPIF90=mpif90
$ cd Examples/MPI_Halo/Semi-Automatic
$ make
```

This will compile and run a set of parallel examples that includes intentional failures.

### 2.7.3 Installation - DEFAULT DIRECTORY

If `INSTALL_DIR` is not set, "make install" will attempt to install pFUnit into the top build directory. This will create directories such as `lib` and `mod` in the top level of the build directory and will overwrite the `include/base.mk` with `include/base-install.mk`. If this is not desired, then "make develop" will put back the original `base.mk`, which is the file to be used for development and building pFUnit. In general, we recommend installing to a directory that is not also the build directory.



## Chapter 3

# Usage

- [Usage - Configuration](#)
- [Usage - Hello World](#)
- [Usage - Preprocessor](#)

### 3.1 Usage

#### 3.1.1 Usage - Configuration

For regular use, after installation, the same compiler/MPI development configuration that was used to build pFUnit should be used. Once the environment variables and paths associated with the environment are set, to configure pFUnit, please set the following.

PFUNIT - set to the directory into which pFUnit was installed.

F90\_VENDOR - set to Intel, GNU, NAG, or PGI accordingly.

#### 3.1.2 Usage - Hello World

For an example of a simple usage of pFUnit, see Examples/Simple/Semi-Automatic/tests.

The simplest way to write a test is to write a preprocessor input file (extension ".pf"), which is a Fortran free format file with preprocessor directives added. An example from "helloWorld.pf" follows.

```
! from helloWorld.pf
@test
subroutine testHelloWorld()
  use pfunit_mod
  implicit none
  @assertEqual("Hello World!", "Hello World!")
end subroutine testHelloWorld
```

One then instructs the preprocessor to construct a suite to execute these tests via the "testSuites.inc" file as follows.

```
! from testSuites.inc
ADD_TEST_SUITE(helloWorld_suite)
```

At this point, one can invoke the preprocessor to generate a Fortran file that when compiled and linked with pFUnit will execute the tests. For more information please see [The Preprocessor - pFUnitParser](#) or try out the examples in Example/Simple.

### 3.1.3 Usage - Preprocessor

Please see [The Preprocessor - pFUnitParser](#).

## Chapter 4

# Development

Generally pFUnit development is performed in the build directory structure. Care should be taken to make clean or distclean in between configuration changes. As stated in [Installation](#), it is best to set INSTALL\_DIR and "make install" pFUnit to another directory that can be placed in a user's paths.



## Chapter 5

# Feedback & Support

- [Feedback](#)
- [Support](#)

### 5.1 Feedback

Feedback is welcome, please use the facilities at [sourceforge/projects/pfunit](https://sourceforge.net/projects/pfunit/) to share your views.

Open a [ticket](#) for bugs, features, and patch recommendations.

If you use pFUnit, please let us know by leaving a note in our [Applications of pFUnit](#) forum, or email [Tom Clune](#), Ph.D., NASA Goddard Space Flight Center. Letting us know about your application helps us seek support for pFUnit's continued development and improvement.

### 5.2 Support

Please open a [ticket](#) for bugs, features, and patch recommendations. For longer term needs or considerations, please visit our [discussion forums](#) or contact [Tom Clune](#), Ph.D., NASA Goddard Space Flight Center.

You may also find some help at [FAQ and Tips](#).

pFUnit supports the software development of several weather and climate simulations efforts. We constantly seek to improve and correct pFUnit for our users' benefit, granting priority to the needs of our major users. Please share with us information about your application on our [Applications of pFUnit](#) forum.



## Chapter 6

# FAQ and Tips

- [FAQ](#)
  - [Zero Tests Run](#)
  - [Some Tests Are Not Running](#)
- [Tips](#)
  - [Environment Modules](#)
  - [Compile Time Errors](#)
  - [Intermediate files used by pFUnit](#)

## 6.1 FAQ

### 6.1.1 Zero Tests Run

*Symptom:* The system under test compiles and runs fine, but reports zero tests run.

*Solutions:*

- There is no `testSuites.inc` file. Please add a `testSuites.inc` that lists the suites to add via `ADD_TEST_SUITE ( the_suite_to_add )`, one to a line.
- There is no `-DUSE_MPI` passed to the compiler during the build. Please add to the compiler invocation. Please see [Some Tests Are Not Running](#).

### 6.1.2 Some Tests Are Not Running

*Symptom:* The system under test compiles and runs fine, but reports that some tests don't run.

*Solutions:*

- There is no `-DUSE_MPI` passed to the compiler during the build. Please add as in the following example.

```
% $PFUNIT/bin/pFUnitParser.py test_pio.pf test_pio.F90
% mpif90 -DUSE_MPI $PFUNIT/include/driver.F90 \
%      -I$PFUNIT/mod -L$PFUNIT/lib -lpfunit test_pio.F90

% mpirun -np 8 ./a.out

.
Time:          0.004 seconds

OK
```

## 6.2 Tips

### 6.2.1 Environment Modules

Though not strictly required, the Environment Modules package can be a convenient way to package, maintain, and switch between environments. This can be particularly important for pFUnit, which must be built using the same tool suite being used for development, e.g. compilers, linkers, etc. [To do: A sample pFUnit modulefile is provided in the OTHER directory.]

### 6.2.2 Compile Time Errors

Compile time errors like "'include [...]include/.mk" not found' likely signify that you are not executing make in the top level directory during a build. Alternatively, during regular usage after installation, PFUNIT has not been set.

During building, if you wish to compile in a subdirectory within the pFUnit hierarchy, please try setting the COMPILER environment variable on the make command line. For example:

```
$ make all COMPILER=Intel
```

### 6.2.3 Intermediate files used by pFUnit

If you wish to see the intermediate files, use the target .PRECIOUS in the makefile to keep them from being deleted. For example:

```
# In GNUmakefile
.PRECIOUS: %_cpp.F90
```



## Chapter 7

# Platform Specific Notes

### 7.1 Mac OSX

The MacPorts package management system is a convenient way to install and maintain many packages, including gcc which includes gfortran.

### 7.2 Windows/CYGWIN

User contributed code for Windows/CYGWIN has been added, but is currently not tested and supported by the pFUnit team. At this writing, 2013-1031, serial Examples and MPI are not known to be supported. Please contact us if you wish to either contribute or otherwise discuss this port.



## Chapter 8

# Acknowledgments

Thanks to the following for their review and comments: B. Van Aartsen, T. Clune.

Windows/CYGWIN contributions from E. Lezar.

Other acknowledgments: S.P. Santos (NCAR), M. Hambley (UK Met).

The design of pFUnit is strongly influenced by [JUnit](#).

Initial pFUnit 2 documentation by Michael Rilee (Rilee Systems Technologies).



## **Chapter 9**

# **Known Installations & Versions**

TBD



## Chapter 10

### TODO

- Make other directory.
- Make Environment Modules example in other directory.
- Other build systems, e.g. CMake.





# Chapter 11

## The Preprocessor - pFUnitParser

Overview of Preprocessor (pFUnitParser.py)

- Using The Preprocessor
  - Configuration - testSuites.inc
  - Invocation
  - Preprocessor Input File (.pf)
  - Directives
    - \* @Parameters
    - \* @TestCase
    - \* @Test
    - \* @MPITest

////////////////////////////////////

### 11.1 Using The Preprocessor

How to write tests using the ".pf" files. We expect this to be the main way people write pFUnit-based tests. Please see the Examples directory for a wide range of examples. The .pf files themselves are generally to be found in an example's semi-automatic/tests subdirectory.

#### 11.1.1 Configuration - testSuites.inc

The include file "testSuites.inc" tells the preprocessor to generate code for TestSuites listed therein. The suite names are based on the TestCases provided in the preprocessor input file or the name of the preprocessor input file (.pf) itself. For example, if no module is defined in a .pf file, i.e. the preprocessor will define the module, one can set up a "testSuites.inc" as follows.

```
! To load "exampleTestsNoModule.pf".
ADD_TEST_SUITE(exampleTestsNoModule_suite)
```

For a .pf file that contains a module associated with a test suite the syntax is as follows.

```
! To load "exampleTests.pf" implementing the module exampleTests_mod.
ADD_TEST_SUITE(exampleTests_mod_suite)
```

### 11.1.2 Invocation

To run the preprocessor on a preprocessor input file "exampleTests.pf", invoke:

```
$ ${PFUNIT}/bin/pFUnitParser.py exampleTests.pf exampleTests.F90
```

A convenient GNUmakefile rule is as follows.

```
%.F90: %.pf
${PFUNIT}/bin/pFUnitParser.py $< $@
```

### 11.1.3 Preprocessor Input File (.pf)

The preprocessor input file is a Fortran free format file that contains subroutines, including those implementing the suite of tests, or a module with the tests, TestCases, and support for parameters. The preprocessor reads and parses this file producing a fortran file implementing the tests, automating some boilerplate code. Embedded "@" directives inform the preprocessor about information needed to generate the test suite. If the .pf file does not implement a module providing a test suite, the preprocessor will use the name of .pf file referred to by "test-Suites.inc". Currently only one test suite per .pf file is allowed, a limitation of the current implementation of the parser.

Many example .pf files may be found in the examples' semi-automatic/tests subdirectories in the Examples directory.

### 11.1.4 Directives

Preprocessor "@" directives instruct the preprocessor how to interpret parts of the code relevant to the generation of the test suite. The most important directives follow.

#### 11.1.4.1 @Parameters

The directive indicates the declaration of the parameterized type used to generate the iteration over the multiple parameter values. It also identifies the names of the parameters to be iterated over. The preprocessor extracts type information from the declaration of the parameter type collection that immediately follows the directive. This directive will set up the iteration. To define the parameter values per iteration the `getParameters` method of the abstract `ParameterizedTest` must be implemented. For example:

```
@Parameters = [p1,p2]
type, extends (AbstractTestParameter) :: exampleCase
  integer :: i
  real :: x
end type exampleCase
```

#### 11.1.4.2 @TestCase

This directive identifies to the preprocessor the `TestCase` declaration. The type declared at this point extends `TestCase` (or its extension), which includes setting methods such as the following: `setUp`, `tearDown`, `runMethod`, `userMethod`. For the extension `MPITestCase`, as with `ParameterizedTestCase`, you have the option (requirement if parameters are used) to set `getParameters` and `getParameterString`. For example:

```
@TestCase
type, extends (MPITestCase) :: Test_Parameters
  integer :: p1, p2
  procedure (runMethod), pointer :: userMethod => null()
contains
  procedure, nopass :: getParameters
  procedure :: getParameterString => getParameterString_
  procedure :: runMethod
end type Test_Parameters
```

## 11.1.4.3 @Test

This directive is used to indicate a test routine to the preprocessor, which then includes it in the test suite. There may be multiple tests in the .pf file, each annotated by the directive. For example, from Examples/Fixture:

```
@Test
  subroutine testBracketInterior(this)
    class (Test_LinearInterpolator), intent(inout) :: this
    @assertEqual([3,4], this%interpolator%getBracket(at=4.))
  end subroutine testBracketInterior

@Test
  subroutine testInterpolateAtNode(this)
    class (Test_LinearInterpolator), intent(inout) :: this
    @assertEqual(2., this%interpolator%interpolate(at=3.))
  end subroutine testInterpolateAtNode
```

## 11.1.4.4 @MPITest

This directive indicates an MPI parallel test to the preprocessor, which then includes it in an MPI enabled test suite. The directive takes a single argument, the requested number of MPI processes to run. The syntax, exemplified by one of the tests from Examples/MPI\_Halo:

```
@mpiTest( npes=[1,2,3])
subroutine testHaloInterior(this)
  use Halo_mod
  use pfunit_mod
  implicit none
  class (MpiTestMethod) :: this

  integer, parameter :: N = 2
  real :: a(N,0:N+1)
  integer :: p

  p = this%getProcessRank()
  a(:,1:N) = p
  a(:,0) = -1
  a(:,N+1) = -1

  call haloFill(a, this%getMpiCommunicator())

  @assertEqual(real(p), a(1,1))
  @assertEqual(real(p), a(2,1))
  @assertEqual(real(p), a(1,2))
  @assertEqual(real(p), a(2,2))

end subroutine testHaloInterior
```



## Chapter 12

### Revision Notes

- 2013-1212. Initial draft of Doxygen version. MLR
- 2013-1107. Minor edits. MLR
- 2013-1031. Added user contributed code for Windows/CYGWIN & IBM's XLF. MLR
- 2013-0830-1359. Minor corrections and added MPIF90 to 6.2. MLR
- 2013-0806-1345. Corrected git reference. Was using old URL. MLR
- 2013-0805. Initial draft. MLR



## Chapter 13

# Data Type Index

### 13.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

AbstractTestParameter	
test_parameters_mod::pecase . . . . .	62
test_restrictsphericalcoordinates_mod::latloncase . . . . .	53
pFUnitParser.Action . . . . .	37
pFUnitParser.AtAfter . . . . .	41
pFUnitParser.AtAssert . . . . .	41
pFUnitParser.AtBefore . . . . .	42
pFUnitParser.AtBegin . . . . .	42
pFUnitParser.AtMpiTest . . . . .	43
pFUnitParser.AtParameters . . . . .	43
pFUnitParser.AtSuite . . . . .	44
pFUnitParser.AtTest . . . . .	44
pFUnitParser.AtTestCase . . . . .	45
add_mod . . . . .	37
addcomplex_mod . . . . .	38
CodeUtilities.ArrayDescription . . . . .	38
assert_mod . . . . .	38
assertbasic_mod . . . . .	39
assertinteger_mod . . . . .	40
GenerateRealArrayNewSignature.AssertRealArrayArgument . . . . .	40
basetestrunner_mod . . . . .	45
beforeafter_mod . . . . .	46
brokensetupcase_mod . . . . .	46
brokentestcase_mod . . . . .	46
mods.pre.pre2.dataString . . . . .	47
debuglistener_mod . . . . .	48
CodeUtilities.declaration . . . . .	49
dynamictestcase_mod . . . . .	49
exception_mod . . . . .	49
fixture_mod . . . . .	50
fixturetestcase_mod . . . . .	50
CodeUtilities.fortranSubroutineSignature . . . . .	50
halo_mod . . . . .	51
CodeUtilities.implementation . . . . .	52
CodeUtilities.interfaceBlock . . . . .	52
mods.pre.pre_if.interval . . . . .	52
linearinterpolator_mod . . . . .	53
makeinfinity_mod . . . . .	53

makenan_mod . . . . .	54
mockcall_mod . . . . .	55
mocklistener_mod . . . . .	55
testParser.MockParser . . . . .	55
mockrepository_mod . . . . .	56
mocksut_mod . . . . .	56
testParser.MockWriter . . . . .	56
CodeUtilities.module . . . . .	57
mpicontext_mod . . . . .	57
mpistubs_mod . . . . .	58
MPITestCase	
test_parameters_mod::test_parameters . . . . .	78
mpitestcase_mod . . . . .	58
mpitestmethod_mod . . . . .	59
parallelcontext_mod . . . . .	59
parallelexception_mod . . . . .	60
ParameterizedTestCase	
test_restrictsphericalcoordinates_mod::test_restrictsphericalcoordinates . . . . .	79
parameterizedtestcase_mod . . . . .	60
params_mod . . . . .	61
pFUnitParser.Parser . . . . .	62
pfunit . . . . .	63
pfunit_mod . . . . .	63
privateexception_mod . . . . .	64
mods.pre.pre2.procDirective . . . . .	65
mods.pre.pre_If.IfDirective . . . . .	51
mods.pre.pre_Repeat.RepeatDirective . . . . .	66
remoteproxytestcase_mod . . . . .	65
resultprinter_mod . . . . .	66
robustrunner_mod . . . . .	67
robusttestsuite_mod . . . . .	68
CodeUtilities.routineUnit . . . . .	68
GenerateRealArrayNewSignature.constraintASERTEQUAL . . . . .	46
GenerateRealArrayNewSignature.IsWithinTolerance . . . . .	52
GenerateRealArrayNewSignature.VECTOR_NORM . . . . .	90
serialcontext_mod . . . . .	68
simpletestcase_mod . . . . .	69
sourcelocation_mod . . . . .	69
sphericalcoordinates_mod . . . . .	70
testlistener_mod::startTest . . . . .	70
stringconversionutilities_mod . . . . .	70
subsetrunner_mod . . . . .	71
surrogatetestcase_mod . . . . .	72
sut_mod . . . . .	72
test_assert_mod . . . . .	72
test_assertbasic_mod . . . . .	72
test_assertcomplex_mod . . . . .	73
test_assertinteger_mod . . . . .	73
test_assertreal_mod . . . . .	74
test_exception_mod . . . . .	74
test_fixturetestcase_mod . . . . .	75
test_linearinterpolator_mod . . . . .	75
test_mockcall_mod . . . . .	76
test_mockrepository_mod . . . . .	76
test_mod . . . . .	76
test_mpicontext_mod . . . . .	77
test_mpiexception_mod . . . . .	77
test_mpitestcase_mod . . . . .	77



test_parameters_mod . . . . .	78
test_restrictsphericalcoordinates_mod . . . . .	79
test_robustrunner_mod . . . . .	80
test_simpletestcase_mod . . . . .	80
test_stringconversionutilities_mod . . . . .	80
test_testmethod_mod . . . . .	80
test_testresult_mod . . . . .	81
test_testsuite_mod . . . . .	81
test_unixprocess_mod . . . . .	81
TestCase	
mods.pre.interleavedp.TestInterleaved . . . . .	83
mods.pre.parseArgs.TestParseArgs . . . . .	84
mods.pre.pre_If.TestIfDirective . . . . .	82
mods.pre.pre_Repeat.TestRepeatDirective . . . . .	86
testParser.TestParseLine . . . . .	85
testcase_mod . . . . .	81
testfailure_mod . . . . .	82
testlistener_mod . . . . .	83
testmethod_mod . . . . .	84
testresult_mod . . . . .	87
testrunner_mod . . . . .	87
testsuite_mod . . . . .	88
throwfundamentaltypes_mod . . . . .	89
unixpipeinterfaces_mod . . . . .	89
unixprocess_mod . . . . .	90
TestCase	
test_linearinterpolator_mod::test_linearinterpolator . . . . .	75



## Chapter 14

# Data Type Index

### 14.1 Data Types List

Here are the data types with brief descriptions:

<a href="#">pFUnitParser.Action</a>	37
<a href="#">add_mod</a>	37
<a href="#">addcomplex_mod</a>	38
<a href="#">CodeUtilities.ArrayDescription</a>	38
<a href="#">assert_mod</a>	
<BriefDescription>	38
<a href="#">assertbasic_mod</a>	
<BriefDescription>	39
<a href="#">assertinteger_mod</a>	
<BriefDescription>	40
<a href="#">GenerateRealArrayNewSignature.AssertRealArrayArgument</a>	40
<a href="#">pFUnitParser.AtAfter</a>	41
<a href="#">pFUnitParser.AtAssert</a>	41
<a href="#">pFUnitParser.AtBefore</a>	42
<a href="#">pFUnitParser.AtBegin</a>	42
<a href="#">pFUnitParser.AtMpiTest</a>	43
<a href="#">pFUnitParser.AtParameters</a>	43
<a href="#">pFUnitParser.AtSuite</a>	44
<a href="#">pFUnitParser.AtTest</a>	44
<a href="#">pFUnitParser.AtTestCase</a>	45
<a href="#">basetestrunner_mod</a>	
<BriefDescription>	45
<a href="#">beforeafter_mod</a>	46
<a href="#">brokensetupcase_mod</a>	46
<a href="#">broken testcase_mod</a>	46
<a href="#">GenerateRealArrayNewSignature.constraintASERTEQUAL</a>	46
<a href="#">mods.pre.pre2.dataString</a>	47
<a href="#">debuglistener_mod</a>	
<BriefDescription>	48
<a href="#">CodeUtilities.declaration</a>	49
<a href="#">dynamic testcase_mod</a>	
<BriefDescription>	49
<a href="#">exception_mod</a>	49
<a href="#">fixture_mod</a>	50
<a href="#">fixturetestcase_mod</a>	50
<a href="#">CodeUtilities.fortranSubroutineSignature</a>	50
<a href="#">halo_mod</a>	51
<a href="#">mods.pre.pre_.lfDirective</a>	51

<a href="#">CodeUtilities.implementation</a>	52
<a href="#">CodeUtilities.interfaceBlock</a>	52
<a href="#">mods.pre.pre_if.interval</a>	52
<a href="#">GenerateRealArrayNewSignature.IsWithinTolerance</a>	52
<a href="#">test_restrictsphericalcoordinates_mod::latloncase</a>	53
<a href="#">linearinterpolator_mod</a>	53
<a href="#">makeinfinity_mod</a>	
<BriefDescription>	53
<a href="#">makenan_mod</a>	
<BriefDescription>	54
<a href="#">mockcall_mod</a>	
<BriefDescription>	55
<a href="#">mocklistener_mod</a>	55
<a href="#">testParser.MockParser</a>	55
<a href="#">mockrepository_mod</a>	
<BriefDescription>	56
<a href="#">mocksut_mod</a>	56
<a href="#">testParser.MockWriter</a>	56
<a href="#">CodeUtilities.module</a>	57
<a href="#">mpicontext_mod</a>	
<BriefDescription>	57
<a href="#">mpistubs_mod</a>	
<BriefDescription>	58
<a href="#">mpitestcase_mod</a>	
<BriefDescription>	58
<a href="#">mpitestmethod_mod</a>	
<BriefDescription>	59
<a href="#">parallelcontext_mod</a>	
<BriefDescription>	59
<a href="#">parallelexception_mod</a>	
<BriefDescription>	60
<a href="#">parameterizedtestcase_mod</a>	
<BriefDescription>	60
<a href="#">params_mod</a>	
<BriefDescription>	61
<a href="#">pFUnitParser.Parser</a>	62
<a href="#">test_parameters_mod::pecase</a>	62
<a href="#">pfunit</a>	
<BriefDescription>	63
<a href="#">pfunit_mod</a>	
<BriefDescription>	63
<a href="#">privateexception_mod</a>	
<BriefDescription>	64
<a href="#">mods.pre.pre2.procDirective</a>	65
<a href="#">remoteproxytestcase_mod</a>	
<BriefDescription>	65
<a href="#">mods.pre.pre_Repeat.RepeatDirective</a>	66
<a href="#">resultprinter_mod</a>	
<BriefDescription>	66
<a href="#">robustrunner_mod</a>	
<BriefDescription>	67
<a href="#">robusttestsuite_mod</a>	68
<a href="#">CodeUtilities.routineUnit</a>	68
<a href="#">serialcontext_mod</a>	
<BriefDescription>	68
<a href="#">simpletestcase_mod</a>	69
<a href="#">sourcelocation_mod</a>	
<BriefDescription>	69

sphericalcoordinates_mod	70
testlistener_mod::startTest	70
stringconversionutilities_mod	
<BriefDescription>	70
subsetrunner_mod	
<BriefDescription>	71
surrogatetestcase_mod	
<BriefDescription>	72
sut_mod	72
test_assert_mod	72
test_assertbasic_mod	72
test_assertcomplex_mod	73
test_assertinteger_mod	73
test_assertreal_mod	74
test_exception_mod	74
test_fixturetestcase_mod	75
test_linearinterpolator_mod::test_linearinterpolator	75
test_linearinterpolator_mod	75
test_mockcall_mod	76
test_mockrepository_mod	76
test_mod	
<BriefDescription>	76
test_mpicontext_mod	77
test_mpiexception_mod	77
test_mpitestcase_mod	77
test_parameters_mod::test_parameters	78
test_parameters_mod	78
test_restrictsphericalcoordinates_mod::test_restrictsphericalcoordinates	79
test_restrictsphericalcoordinates_mod	79
test_robustrunner_mod	80
test_simpletestcase_mod	80
test_stringconversionutilities_mod	80
test_testmethod_mod	80
test_testresult_mod	81
test_testsuite_mod	81
test_unixprocess_mod	81
testcase_mod	
<BriefDescription>	81
testfailure_mod	
<BriefDescription>	82
mods.pre.pre_if.TestIfDirective	82
mods.pre.interleavedp.TestInterleaved	83
testlistener_mod	
<BriefDescription>	83
testmethod_mod	
<BriefDescription>	84
mods.pre.parseArgs.TestParseArgs	84
testParser.TestParseLine	85
mods.pre.pre_Repeat.TestRepeatDirective	86
testresult_mod	
<BriefDescription> Note: A possible extension point for user-specialized TestResults	87
testrunner_mod	
<BriefDescription>	87
testsuite_mod	
<BriefDescription>	88
throwfundamentaltypes_mod	
<BriefDescription>	89


<a href="#">unixpipeinterfaces_mod</a>	
<BriefDescription> . . . . .	89
<a href="#">unixprocess_mod</a>	
<BriefDescription> . . . . .	90
<a href="#">GenerateRealArrayNewSignature.VECTOR_NORM</a> . . . . .	90

## Chapter 15

# Data Type Documentation

### 15.1 pUnitParser.Action Class Reference

Inheritance diagram for pUnitParser.Action:



#### Public Member Functions

- def **apply**

The documentation for this class was generated from the following file:

- `pUnitParser.py`

### 15.2 add\_mod Module Reference

## Public Member Functions

- real function **add** (x, y)
- real function **add** (x, y)
- real function **add** (x, y)

The documentation for this module was generated from the following files:

- Robust/Semi-Automatic/src/add.F90
- Simple/Semi-Automatic/src/add.F90
- Simple\_Windows/Semi-Automatic/src/add.F90

## 15.3 addcomplex\_mod Module Reference

### Public Member Functions

- complex function, dimension(size(z0)) **add** (z0, z1)
- complex function, dimension(size(z0)) **add** (z0, z1)

The documentation for this module was generated from the following files:

- Semi-Automatic/src/addComplex.F90
- Windows/Semi-Automatic/src/addComplex.F90

## 15.4 CodeUtilities.ArrayDescription Class Reference

### Public Member Functions

- def **\_\_init\_\_**
- def **NAME**
- def **DECLARE**
- def **DECLARESCALAR**
- def **KIND**
- def **RANK**
- def **FTYPE**
- def **EXPANDSHAPE**
- def **FailureMessageFork**

### Public Attributes

- **fType**
- **kind**
- **rank**

The documentation for this class was generated from the following file:

- CodeUtilities.py

## 15.5 assert\_mod Module Reference

<BriefDescription>



### 15.5.1 Detailed Description

<BriefDescription>

**Author**

Tom Clune, NASA/GSFC SIVO

**Date**

07 Nov 2013

**Note**

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- Assert.F90

## 15.6 assertbasic\_mod Module Reference

<BriefDescription>

### Public Member Functions

- subroutine **assertexceptionraisedmessage** (message)
- subroutine, public **assertsameshape** (shapeA, shapeB, message, location)
- logical function, public **conformable** (shapeA, shapeB)
- logical function, public **nonconformable** (shapeA, shapeB)
- subroutine, public **assertany** (conditions, message, location)
- subroutine, public **assertall** (conditions, message, location)
- subroutine, public **assertnone** (conditions, message, location)
- subroutine, public **assertnotall** (conditions, message, location)
- subroutine **assertisnan\_double** (x, message, location)
- subroutine **assertisfinite\_single** (x, message, location)
- subroutine **assertisfinite\_double** (x, message, location)

### 15.6.1 Detailed Description

<BriefDescription>

**Author**

Tom Clune, NASA/GSFC SIVO

**Date**

07 Nov 2013

**Note**

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- AssertBasic.F90

## 15.7 assertinteger\_mod Module Reference

<BriefDescription>

### Public Member Functions

- subroutine **assertequalinteger1d1d\_** (expected, found, message, location)
- subroutine **assertequalinteger0d1d\_** (expected, found, message, location)
- subroutine **assertequalinteger2d2d\_** (expected, found, message, location)
- subroutine **assertequalinteger0d2d\_** (expected, found, message, location)
- subroutine **assertlessthan\_** (a, b, message, location)

### 15.7.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- AssertInteger.F90

## 15.8 GenerateRealArrayNewSignature.AssertRealArrayArgument Class Reference

### Public Member Functions

- def **\_\_init\_\_**
- def **updateDescriptions**
- def **getExpectedDescription**
- def **getFoundDescription**
- def **getTolerance**

### Public Attributes

- **expectedFType**
- **expectedPrecision**
- **expectedRank**
- **foundFType**
- **foundPrecision**
- **foundRank**
- **tolerance**
- **expectedDescription**


- **foundDescription**

The documentation for this class was generated from the following file:

- GenerateRealArrayNewSignature.py

## 15.9 pFUnitParser.AtAfter Class Reference

Inheritance diagram for pFUnitParser.AtAfter:



### Public Member Functions

- def **\_\_init\_\_**
- def **match**
- def **action**

### Public Attributes


- **parser**

The documentation for this class was generated from the following file:

- pFUnitParser.py

## 15.10 pFUnitParser.AtAssert Class Reference

Inheritance diagram for pFUnitParser.AtAssert:



### Public Member Functions

- def **\_\_init\_\_**
- def **match**
- def **appendSourceLocation**
- def **action**

### Public Attributes


- **parser**

The documentation for this class was generated from the following file:

- pFUnitParser.py

## 15.11 pFUnitParser.AtBefore Class Reference

Inheritance diagram for pFUnitParser.AtBefore:



### Public Member Functions

- def **\_\_init\_\_**
- def **match**
- def **action**

### Public Attributes


- **parser**

The documentation for this class was generated from the following file:

- pFUnitParser.py

## 15.12 pFUnitParser.AtBegin Class Reference

Inheritance diagram for pFUnitParser.AtBegin:



### Public Member Functions

- def **\_\_init\_\_**
- def **match**
- def **action**

### Public Attributes


- **parser**

The documentation for this class was generated from the following file:

- pUnitParser.py

## 15.13 pUnitParser.AtMpiTest Class Reference

Inheritance diagram for pUnitParser.AtMpiTest:



### Public Member Functions

- def **\_\_init\_\_**
- def **match**
- def **action**

### Public Attributes


- **parser**

The documentation for this class was generated from the following file:

- pUnitParser.py

## 15.14 pUnitParser.AtParameters Class Reference

Inheritance diagram for pUnitParser.AtParameters:



### Public Member Functions

- def **\_\_init\_\_**
- def **match**
- def **action**

### Public Attributes


- **parser**

The documentation for this class was generated from the following file:

- pFUnitParser.py

## 15.15 pFUnitParser.AtSuite Class Reference

Inheritance diagram for pFUnitParser.AtSuite:



### Public Member Functions

- def **\_\_init\_\_**
- def **match**
- def **action**

### Public Attributes


- **parser**

The documentation for this class was generated from the following file:

- pFUnitParser.py

## 15.16 pFUnitParser.AtTest Class Reference

Inheritance diagram for pFUnitParser.AtTest:



### Public Member Functions

- def **\_\_init\_\_**
- def **match**
- def **action**

### Public Attributes


- **parser**

The documentation for this class was generated from the following file:

- pFUnitParser.py

## 15.17 pFUnitParser.AtTestCase Class Reference

Inheritance diagram for pFUnitParser.AtTestCase:



### Public Member Functions

- def **\_\_init\_\_**
- def **match**
- def **action**

### Public Attributes

- **parser**

The documentation for this class was generated from the following file:

- pFUnitParser.py

## 15.18 basetestrunner\_mod Module Reference

<BriefDescription>

### 15.18.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- BaseTestRunner.F90

## 15.19 beforeafter\_mod Module Reference

### Public Member Functions

- subroutine **first** (this)
- subroutine **last** (this)
- subroutine **succeeds** (this)
- subroutine **fails** (this)

### Public Attributes

- integer **countstart** = 0
- integer **countcomplete** = 0

The documentation for this module was generated from the following file:

- beforeAfter.pf

## 15.20 brokensetupcase\_mod Module Reference

### Public Member Functions

- type(brokensetupcase) function,  
pointer, public **newbrokensetupcase** ()

The documentation for this module was generated from the following file:

- BrokenSetUpCase.F90

## 15.21 brokentestcase\_mod Module Reference

### Public Member Functions


- subroutine **teardown** (this)

The documentation for this module was generated from the following file:

- BrokenTestCase.F90

## 15.22 GenerateRealArrayNewSignature.constraintASERTEQUAL Class Reference

Inheritance diagram for GenerateRealArrayNewSignature.constraintASERTEQUAL:





## Public Member Functions

- def `__init__`

*This next line actually generates the text of the code.*

## Public Attributes

- `expectedDescr`
- `foundDescr`
- `name`
- `name1`

*Add in the extra module procedures...*

- `tolerance`

*If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...*

### 15.22.1 Constructor & Destructor Documentation

15.22.1.1 `def GenerateRealArrayNewSignature.constraintASERTEQUAL.__init__( self, expectedDescr, foundDescr, tolerance )`

This next line actually generates the text of the code.

### 15.22.2 Member Data Documentation

15.22.2.1 `GenerateRealArrayNewSignature.constraintASERTEQUAL.name1`

Add in the extra module procedures...

If needed... Kluge. Need to make makeSubroutineNames and load the extra interface entries there.

15.22.2.2 `GenerateRealArrayNewSignature.constraintASERTEQUAL.tolerance`

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

E.g. to implement `assertEqual(Logical(...))`

The documentation for this class was generated from the following file:

- `GenerateRealArrayNewSignature.py`

## 15.23 mods.pre.pre2.dataString Class Reference

### Public Member Functions

- def `__init__`
- def `insert`
- def `getLength`
- def `getPosition`
- def `setPosition`
- def `getItem`
- def `getDataAtPosition`

- def **getData**
- def **getSlice**
- def **getSliceForward**
- def **removeSlice**
- def **getCurrentData**
- def **insertAtCurrent**
- def **append**
- def **advanceAndGetNextData**
- def **validPosition**
- def **findToEnd**
- def **match**
- def **matchToEnd**
- def **searchToEnd**
- def **searchToPosition**
- def **finditerToEnd**
- def **finditerToPosition**

### Public Attributes

- **data**
- **position**

The documentation for this class was generated from the following file:

- pre2.py

## 15.24 debuglistener\_mod Module Reference

<BriefDescription>

### Public Member Functions

- subroutine **starttest** (this, testName)

### 15.24.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- DebugListener.F90

## 15.25 CodeUtilities.declaration Class Reference

### Public Member Functions

- def **\_\_init\_\_**
- def **generate**

### Public Attributes

- **simpleDeclaration**
- **fullDeclaration**
- **name**

The documentation for this class was generated from the following file:

- CodeUtilities.py

## 15.26 dynamictestcase\_mod Module Reference

<BriefDescription>

### Public Member Functions

- type(dynamictestcase) function,  
pointer, public **newdynamictestcase** (testMethod, name)

### 15.26.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- DynamicTestCase.F90

## 15.27 exception\_mod Module Reference

### Public Member Functions

- subroutine, public **initializeglobalexceptionlist** ()

- type(exception) function, public **catchany** (preserve)
- type(exception) function, dimension(:), allocatable, public **getexceptions** ()
- logical function, public **noexceptions** ()
- logical function, public **anyerrors** ()
- subroutine, public **gatherexceptions** (context)
- subroutine, public **clearall** ()

The documentation for this module was generated from the following file:

- Exception.F90

## 15.28 fixture\_mod Module Reference

### Public Member Functions

- subroutine **mysetup** ()
- subroutine **myteardown** ()
- subroutine **testread** ()
- subroutine **testeof** ()
- subroutine **mysetup** ()
- subroutine **myteardown** ()
- subroutine **testread** ()
- subroutine **testeof** ()

The documentation for this module was generated from the following files:

- Semi-Automatic/tests/fixtureTests.pf
- Windows/Semi-Automatic/tests/fixtureTests.pf

## 15.29 fixturetestcase\_mod Module Reference

### Public Member Functions

- type(fixturetestcase) function, public **newfixturetestcase** ()
- subroutine, public **simpletestmethod** (this)
- subroutine, public **methoda** (this)
- subroutine, public **methodb** (this)

The documentation for this module was generated from the following file:

- FixtureTestCase.F90

## 15.30 CodeUtilities.fortranSubroutineSignature Class Reference

### Public Member Functions

- def **\_\_init\_\_**
- def **setReturnFType**

- def **addArg**
- def **generateInterfaceEntry**
- def **generateImplementationSignature**
- def **generateImplementationClose**

#### Public Attributes

- **name**
- **ArgumentToFType**
- **ReturnFType**
- **SubroutineType**

The documentation for this class was generated from the following file:

- CodeUtilities.py

## 15.31 halo\_mod Module Reference

#### Public Member Functions


- subroutine **halofill** (array, communicator)

The documentation for this module was generated from the following file:

- Halo.F90

## 15.32 mods.pre.pre\_If.IfDirective Class Reference

Inheritance diagram for mods.pre.pre\_If.IfDirective:



#### Public Member Functions

- def **evaluate**

#### Public Attributes

- **startPosition**
- **newPosition**

The documentation for this class was generated from the following file:

- pre\_If.py

### 15.33 CodeUtilities.implementation Class Reference

#### Public Member Functions

- def **\_\_init\_\_**
- def **generate**

#### Public Attributes

- **name**
- **source**

The documentation for this class was generated from the following file:

- CodeUtilities.py

### 15.34 CodeUtilities.interfaceBlock Class Reference

The documentation for this class was generated from the following file:

- CodeUtilities.py

### 15.35 mods.pre.pre\_if.interval Class Reference

#### Public Member Functions

- def **\_\_init\_\_**
- def **getInterval**
- def **setInterval**
- def **getStart**
- def **getEnd**

#### Public Attributes


- **start**
- **end**
- **interval**

The documentation for this class was generated from the following file:

- pre\_if.py

### 15.36 GenerateRealArrayNewSignature.IsWithinTolerance Class Reference

Inheritance diagram for GenerateRealArrayNewSignature.IsWithinTolerance:



### Public Member Functions

- def `__init__`

### Public Attributes


- **rank**
- **precision**
- **name**
- **fType**
- **declaration**
- **declarations**

The documentation for this class was generated from the following file:

- GenerateRealArrayNewSignature.py

## 15.37 test\_restrictsphericalcoordinates\_mod::latloncase Type Reference

Inheritance diagram for test\_restrictsphericalcoordinates\_mod::latloncase:



### Public Attributes

- real **lat**
- real **lon**
- real **restrictedlat**
- real **restrictedlon**

The documentation for this type was generated from the following file:

- Test\_RestrictedSphericalCoordinates.pf

## 15.38 linearinterpolator\_mod Module Reference

The documentation for this module was generated from the following file:

- LinearInterpolator.F90

## 15.39 makeinfinity\_mod Module Reference

<BriefDescription>

## Public Member Functions

- `real(r32)` function, public **makeinf\_32** ()
- `real(r64)` function, public **makeinf\_64** ()

### 15.39.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- `MakeInfinity.F90`

## 15.40 makenan\_mod Module Reference

<BriefDescription>

## Public Member Functions

- `real(r32)` function, public **makenan\_32** ()
- `real(r64)` function, public **makenan\_64** ()

### 15.40.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- `MakeNaN.F90`



## 15.41 mockcall\_mod Module Reference

<BriefDescription>

### Public Member Functions

- type(mockcall) function, public **newmockcall** (name)

### 15.41.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- MockCall.F90

## 15.42 mocklistener\_mod Module Reference

### Public Member Functions

- subroutine **starttest** (this, testName)

The documentation for this module was generated from the following file:

- MockListener.F90

## 15.43 testParser.MockParser Class Reference

### Public Member Functions

- def **\_\_init\_\_**
- def **nextLine**

### Public Attributes

- **line**
- **outputFile**
- **outLines**
- **tests**

- **mpitests**

The documentation for this class was generated from the following file:

- testParser.py

## 15.44 mockrepository\_mod Module Reference

<BriefDescription>

### Public Member Functions

- type(mockrepository) function, pointer, public **newmockrepository** ()
- subroutine **expectcall** (this, obj, method)

### 15.44.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- MockRepository.F90

## 15.45 mocksut\_mod Module Reference

### Public Member Functions

- type(mocksut) function, allocatable, public **newmocksut** (repository)
- subroutine **method1** (this)

The documentation for this module was generated from the following file:

- Test\_MockRepository.F90

## 15.46 testParser.MockWriter Class Reference

### Public Member Functions

- def **\_\_init\_\_**
- def **write**

### Public Attributes

- **parser**

The documentation for this class was generated from the following file:

- testParser.py

## 15.47 CodeUtilities.module Class Reference

### Public Member Functions

- def **\_\_init\_\_**
- def **generate**
- def **addDeclaration**
- def **addImplementation**
- def **addRoutineUnit**
- def **addInterfaceBlock**
- def **getName**
- def **setFileName**
- def **getFileName**

### Public Attributes

- **name**
- **declarations**
- **implementations**
- **generation**
- **fileName**

The documentation for this class was generated from the following file:

- CodeUtilities.py

## 15.48 mpicontext\_mod Module Reference

<BriefDescription>

### Public Member Functions

- subroutine **barrier** (this)
- integer function **getmpicommunicator** (this)

### 15.48.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

**Date**

07 Nov 2013

**Note**

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- `MpiContext.F90`

## 15.49 `mpistubs_mod` Module Reference

<BriefDescription>

### Public Member Functions

- subroutine, public **`mpi_comm_rank`** (`comm`, `rank`, `ier`)
- subroutine, public **`mpi_comm_size`** (`comm`, `size`, `ier`)
- subroutine, public **`mpi_comm_dup`** (`comm`, `newComm`, `ier`)
- subroutine, public **`mpi_comm_group`** (`comm`, `group`, `ier`)
- subroutine, public **`mpi_group_range_incl`** (`group`, `n`, `ranges`, `newGroups`, `ier`)
- subroutine, public **`mpi_comm_create`** (`comm`, `group`, `newComm`, `ier`)

### Public Attributes

- integer, parameter, public **`mpi_comm_world`** = -1
- integer, parameter, public **`mpi_comm_null`** = -1
- integer, parameter, public **`mpi_comm_success`** = 0

### 15.49.1 Detailed Description

<BriefDescription>

**Author**

Tom Clune, NASA/GSFC SIVO

**Date**

07 Nov 2013

**Note**

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- `MpiStubs.F90`

## 15.50 `mpitestcase_mod` Module Reference

<BriefDescription>

## Public Member Functions

- recursive subroutine **runbare** (this)
- subroutine **setup** (this)

### 15.50.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- MpiTestCase.F90

## 15.51 mpitestmethod\_mod Module Reference

<BriefDescription>

### 15.51.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- MpiTestMethod.F90

## 15.52 parallelcontext\_mod Module Reference

<BriefDescription>

### 15.52.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- ParallelContext.F90

## 15.53 `parallelexception_mod` Module Reference

<BriefDescription>

### Public Member Functions

- subroutine, public **gather** (context)

### 15.53.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- ParallelException.F90

## 15.54 `parameterizedtestcase_mod` Module Reference

<BriefDescription>

## Public Attributes

- integer, parameter, public **max\_len\_label** = 32

### 15.54.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- ParameterizedTestCase.F90

## 15.55 params\_mod Module Reference

<BriefDescription>

## Public Attributes

- integer, parameter **r32** = selected\_real\_kind(p=6)
- integer, parameter **r64** = selected\_real\_kind(p=14)
- integer, parameter **c32** = selected\_real\_kind(p=6)
- integer, parameter **c64** = selected\_real\_kind(p=14)
- integer, parameter **neqp** = 0
- integer, parameter **eqp** = 1
- integer, parameter **gtp** = 2
- integer, parameter **gep** = 3
- integer, parameter **ltp** = 4
- integer, parameter **lep** = 5
- integer, parameter **releqp** = 6

### 15.55.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

## Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- Params.F90

## 15.56 pFUnitParser.Parser Class Reference

### Public Member Functions

- def **\_\_init\_\_**
- def **run**
- def **nextLine**
- def **makeSuite**
- def **final**

### Public Attributes


- **inputFile**
- **outputFile**
- **moduleName**
- **suiteName**
- **testCase**
- **setUp**
- **tearDown**
- **defaultName**
- **fileName**
- **lineNumber**
- **parameters**
- **parameterType**
- **tests**
- **mpitests**
- **actions**

The documentation for this class was generated from the following file:

- pFUnitParser.py

## 15.57 test\_parameters\_mod::pecase Type Reference

Inheritance diagram for test\_parameters\_mod::pecase:





## Public Attributes

- integer **p1**
- integer **p2**

The documentation for this type was generated from the following file:

- parameterizedTests.pf

## 15.58 pfunit Module Reference

<BriefDescription>

### 15.58.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- pFUnitPackage.F90

## 15.59 pfunit\_mod Module Reference

<BriefDescription>

## Public Member Functions

- subroutine, public **initialize** (useMpi)
- subroutine, public **finalize** ()

### 15.59.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

**Date**

07 Nov 2013

**Note**

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- pFUnit.F90

## 15.60 privateexception\_mod Module Reference

<BriefDescription>

### Public Member Functions

- type(exceptionlist) function,  
public **newexceptionlist** ()
- logical function **noexceptions** (this)

### Public Attributes

- integer, parameter, public **maxlen\_message** = 80\*15
- integer, parameter, public **maxlen\_file\_name** = 80
- character(len=\*), parameter, public **null\_message** = "

### 15.60.1 Detailed Description

<BriefDescription>

**Author**

Tom Clune, NASA/GSFC SIVO

**Date**

07 Nov 2013

**Note**


<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- Exception.F90

## 15.61 mods.pre.pre2.procDirective Class Reference

Inheritance diagram for mods.pre.pre2.procDirective:



### Public Member Functions

- def `__init__`
- def `getLength`
- def `match`
- def `evaluate`
- def `getNewPosition`
- def `addTokenRE`
- def `searchTokenToEnd`
- def `searchTokenToPosition`
- def `finditerTokenToPosition`
- def `makeTokenErrorMessage`

### Public Attributes

- `name`
- `newPosition`
- `tokens`
- `TokenREs`

#### 15.61.1 Member Function Documentation

15.61.1.1 `def mods.pre.pre2.procDirective.addTokenRE ( self, args, key, defaultToken, prefix = r''' (?i) [ \t]*''', postfix = '' )`

Add a token/create an RE with a prefix that by default ignores preceding whitespace.  
Stores the RE in a dictionary for this directive.

The documentation for this class was generated from the following file:

- `pre2.py`

## 15.62 remoteproxytestcase\_mod Module Reference

<BriefDescription>

### 15.62.1 Detailed Description

<BriefDescription>

**Author**

Tom Clune, NASA/GSFC SIVO

**Date**

07 Nov 2013

**Note**


<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- RemoteProxyTestCase.F90

## 15.63 mods.pre.pre\_Repeat.RepeatDirective Class Reference

Inheritance diagram for mods.pre.pre\_Repeat.RepeatDirective:

**Public Member Functions**

- def **evaluate**

**Public Attributes**

- **startPosition**
- **newPosition**

The documentation for this class was generated from the following file:

- pre\_Repeat.py

## 15.64 resultprinter\_mod Module Reference

<BriefDescription>

**Public Member Functions**

- type(resultprinter) function,  
public **newresultprinter** (unit)
- subroutine **adderror** (this, testName, exceptions)
- subroutine **starttest** (this, testName)
- subroutine **printhead** (this, runTime)

### 15.64.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- ResultPrinter.F90

## 15.65 robustrunner\_mod Module Reference

<BriefDescription>

### Public Member Functions

- type(robustrunner) function **newrobustrunner\_unit** (remoteRunCommand, unit)
- subroutine **runwithresult** (this, aTest, context, result)
- subroutine **launchremoterunner** (this, numSkip)
- subroutine **starttest** (this, testName)
- subroutine **adderror** (this, testName, exceptions)
- type(testresult) function **createtestresult** (this)

### 15.65.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- RobustRunner.F90

## 15.66 robusttestsuite\_mod Module Reference

### Public Member Functions


- type(testsuite) function, public **suite** ()
- subroutine **testrunsucceeds** ()
- subroutine **testrunstops** ()

The documentation for this module was generated from the following file:

- robustTestSuite.F90

## 15.67 CodeUtilities.routineUnit Class Reference

Inheritance diagram for CodeUtilities.routineUnit:



### Public Member Functions

- def **\_\_init\_\_**
- def **setName**
- def **getName**
- def **setDeclaration**
- def **addDeclaration**
- def **setImplementation**
- def **getDeclaration**
- def **getDeclarations**
- def **getImplementation**
- def **clearDeclarations**

### Public Attributes

- **name**
- **declaration**
- **declarations**
- **implementation**

The documentation for this class was generated from the following file:

- CodeUtilities.py

## 15.68 serialcontext\_mod Module Reference

<BriefDescription>

## Public Member Functions

- type(serialcontext) function,  
public **newserialcontext** ()

## Public Attributes

- type(serialcontext), parameter,  
public **the\_serial\_context** = SerialContext(1)

### 15.68.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- SerialContext.F90

## 15.69 simpletestcase\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- type(simpletestcase) function,  
public **newsimpletestcase** (name, userMethod)
- subroutine, public **method1** (this)
- subroutine, public **method2** (this)
- subroutine, public **methodwith2exceptions** (this)
- subroutine **delete\_** (this)

The documentation for this module was generated from the following file:

- SimpleTestCase.F90

## 15.70 sourcelocation\_mod Module Reference

<BriefDescription>

## Public Attributes

- character(len=maxlen\_file\_name),  
parameter, public **unknown\_file\_name** = '<unknown file>'
- integer, parameter, public **unknown\_line\_number** = -1
- type(sourcelocation),  
parameter, public **unknown\_source\_location** = SourceLocation()

### 15.70.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- SourceLocation.F90

### 15.71 sphericalcoordinates\_mod Module Reference

The documentation for this module was generated from the following file:

- SphericalCoordinates.F90

### 15.72 testlistener\_mod::startTest Interface Reference

The documentation for this interface was generated from the following file:

- TestListener.F90

### 15.73 stringconversionutilities\_mod Module Reference

<BriefDescription>

## Public Member Functions

- character(len=len\_trim(a)+1+len\_trim(b))  
function, public **appendwithspace** (a, b)
- character(len=:) function,  
allocatable, public **nullterminate** (string)
- character(len=:) function,  
allocatable, public **unlessscalar** (vShape, string)



## Public Attributes

- integer, parameter, public **maxlen\_string** = 80

### 15.73.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- StringConversionUtilities.F90

## 15.74 subsetrunner\_mod Module Reference

<BriefDescription>

## Public Member Functions

- subroutine **addfailure** (this, testName, exceptions)
- subroutine **starttest** (this, testName)

### 15.74.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- SubsetRunner.F90

## 15.75 `surrogatetestcase_mod` Module Reference

<BriefDescription>

### 15.75.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- `SurrogateTestCase.F90`

## 15.76 `sut_mod` Module Reference

The documentation for this module was generated from the following file:

- `Test_MockRepository.F90`

## 15.77 `test_assert_mod` Module Reference

### Public Member Functions

- `type(testsuite) function, public suite ()`
- `subroutine testassertequalstringdiffer1st ()`

The documentation for this module was generated from the following file:

- `Test_Assert.F90`

## 15.78 `test_assertbasic_mod` Module Reference

### Public Member Functions

- `type(testsuite) function, public suite ()`
- `subroutine testassertruef ()`
- `subroutine testassertisfinite ()`

The documentation for this module was generated from the following file:

- `Test_AssertBasic.F90`

## 15.79 test\_assertcomplex\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testequality\_c\_complexscalar** ()
- subroutine **testequality\_c\_0d1d** ()
- subroutine **testequality\_c\_1d\_nonconformable1** ()
- subroutine **testequality\_c\_2d\_singleelementdifferent** ()
- subroutine **testequality\_c\_multid\_singleelementdifferent** ()
- subroutine **testequality\_c\_multid\_singleelementdifferent1**
- subroutine **testequality\_c\_multid\_singleelementdifferent2**
- subroutine **testequality\_c\_multid\_singleelementdifferent3**
- subroutine **testequality\_c\_multid\_singleelementdifferent4**
- subroutine **testequality\_c\_multid\_singleelementdifferent5**
- subroutine **testequality\_c\_multidmultiprec\_singleeltdiff** ()
- subroutine **testequality\_c\_multidmultiprec\_singleeltdiff1** ()
- subroutine **testequality\_c\_multidmultiprec\_singleeltdiff2** ()
- subroutine **testequality\_c\_multidmultiprec\_singleeltdiff3** ()
- subroutine **testequality\_c\_multidmultiprec\_singleeltdiff4** ()
- subroutine **testequality\_c\_multidmultiprec\_singleeltdiff5** ()
- subroutine **testequality\_c\_multidmultiprec\_singleeltdiff6** ()
- subroutine **testequality\_c\_multidmultiprec\_singleeltdiff7** ()
- subroutine **testequality\_c\_multidmultiprec\_singleeltdiff8** ()
- subroutine **testequality\_scalarwithtolerance** ()
- subroutine **testequality\_c\_multidwithtolerance** ()
- subroutine **testequality\_c\_multidwithtolerance1** ()
- subroutine **testequality\_c\_multidwithtolerance64** ()
- subroutine **testequality\_c\_multidwithtolerance64\_1** ()
- subroutine **testequality\_c\_multidwithtolerance64\_2** ()
- subroutine **testequality\_c\_multidsourcelocation** ()
- subroutine **testequality\_4dpcomplex\_differencereport** ()
- subroutine **assertcatch** (string, location)

The documentation for this module was generated from the following file:

- Test\_AssertComplex.F90

## 15.80 test\_assertinteger\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testassertequal\_equal** ()

The documentation for this module was generated from the following file:

- Test\_AssertInteger.F90

## 15.81 test\_assertreal\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testequality\_0d1d** ()
- subroutine **testequality\_1d\_nonconformable1** ()
- subroutine **testequality\_2d\_singleelementdifferent** ()
- subroutine **testequality\_multid\_singleelementdifferent** ()
- subroutine **testequality\_multid\_singleelementdifferent1**
- subroutine **testequality\_multid\_singleelementdifferent2**
- subroutine **testequality\_multid\_singleelementdifferent3**
- subroutine **testequality\_multid\_singleelementdifferent4**
- subroutine **testequality\_multid\_singleelementdifferent5**
- subroutine **testequality\_multidmultiprec\_singleeltdiff** ()
- subroutine **testequality\_multidmultiprec\_singleeltdiff1** ()
- subroutine **testequality\_multidmultiprec\_singleeltdiff2** ()
- subroutine **testequality\_multidmultiprec\_singleeltdiff3** ()
- subroutine **testequality\_multidmultiprec\_singleeltdiff4** ()
- subroutine **testequality\_multidmultiprec\_singleeltdiff5** ()
- subroutine **testequality\_multidmultiprec\_singleeltdiff6** ()
- subroutine **testequality\_multidmultiprec\_singleeltdiff7** ()
- subroutine **testequality\_multidmultiprec\_singleeltdiff8** ()
- subroutine **testequality\_scalarwithtolerance** ()
- subroutine **testequality\_scalarwithtolerancenormsg** ()
- subroutine **testequality\_vectorwithtolerancenormsg** ()
- subroutine **testequality\_multidwithtolerance** ()
- subroutine **testequality\_multidwithtolerance1** ()
- subroutine **testequality\_multidwithtolerance64** ()
- subroutine **testequality\_multidwithtolerance64\_1** ()
- subroutine **testequality\_multidwithtolerance64\_2** ()
- subroutine **testequality\_multidsourcelocation** ()
- subroutine **testequality\_scalarandlocation** ()
- subroutine **testequality\_scalarinfinity\_equal** ()
- subroutine **testequality\_scalarinfinity\_unequal\_a** ()
- subroutine **testequality\_scalarinfinity\_unequal\_b** ()
- subroutine **testequality\_scalarinfinity\_unequal\_c** ()
- subroutine **assertcatch** (string, location)

The documentation for this module was generated from the following file:

- Test\_AssertReal.F90

## 15.82 test\_exception\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testgetnumexceptions** ()
- subroutine **testcatchsucceed** ()
- subroutine **testgetlinenumber** ()
- subroutine **testgetfilename** ()

The documentation for this module was generated from the following file:

- Test\_Exception.F90

## 15.83 test\_fixturetestcase\_mod Module Reference

### Public Member Functions


- type(testsuite) function, public **suite** ()
- subroutine **testrunwithfixture** ()
- subroutine **testbrokentestcase** ()
- subroutine **testbrokensetupcase** ()

The documentation for this module was generated from the following file:

- Test\_FixtureTestCase.F90

## 15.84 test\_linearinterpolator\_mod::test\_linearinterpolator Type Reference

Inheritance diagram for test\_linearinterpolator\_mod::test\_linearinterpolator:



### Public Member Functions

- type([test\\_linearinterpolator](#))  
function **newtest\_linearinterpolator** (name, userMethod)
- procedure **setup**
- procedure **teardown**
- procedure **runmethod**

### Public Attributes

- type(linearinterpolator) **interpolator**
- procedure(runmethod), pointer **usermethod** => null()

The documentation for this type was generated from the following file:

- Test\_LinearInterpolator.pf

## 15.85 test\_linearinterpolator\_mod Module Reference

### Data Types

- type [test\\_linearinterpolator](#)

## Public Member Functions

- type([test\\_linearinterpolator](#))  
function **newtest\_linearinterpolator** (name, userMethod)
- subroutine **setup** (this)
- subroutine **teardown** (this)
- subroutine **runmethod** (this)
- subroutine **testbracketatnode** (this)
- subroutine **testbracketinterior** (this)
- subroutine **testinterpolateatnode** (this)
- subroutine **testinterpolateconstant** (this)

The documentation for this module was generated from the following file:

- Test\_LinearInterpolator.pf

## 15.86 test\_mockcall\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testexpectoneintegerargument**
- subroutine **testfailexpectoneintegerargument**

The documentation for this module was generated from the following file:

- Test\_MockCall.F90

## 15.87 test\_mockrepository\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testnoaction** ()

The documentation for this module was generated from the following file:

- Test\_MockRepository.F90

## 15.88 test\_mod Module Reference

<BriefDescription>

### 15.88.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

## Date

07 Nov 2013

## Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- Test.F90

## 15.89 test\_mpicontext\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testnumprocesses1** (context)

The documentation for this module was generated from the following file:

- Test\_MpiContext.F90

## 15.90 test\_mpiexception\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **test\_anyexceptions\_none** (this)
- subroutine **test\_getnumexceptions** (this)
- subroutine **test\_gather** (this)

The documentation for this module was generated from the following file:

- Test\_MpiException.F90

## 15.91 test\_mpitestcase\_mod Module Reference

### Public Member Functions


- type(testsuite) function, public **suite** ()
- type(test\_mpitestcase) function, public **newtest\_mpitestcase** (name, userMethod, numProcesses)
- subroutine **testrunon2processors** (this)
- subroutine **brokenprocess1** (this)
- subroutine **brokenonprocess2** (this)
- subroutine **testfailon1** (this)
- subroutine **testfailon2** (this)
- subroutine **testtoofewprocs** (this)
- recursive subroutine **runmethod** (this)

The documentation for this module was generated from the following file:

- Test\_MpiTestCase.F90

## 15.92 test\_parameters\_mod::test\_parameters Interface Reference

Inheritance diagram for test\_parameters\_mod::test\_parameters:



### Public Member Functions

- procedure, nopass **getparameters**
- procedure **getparameterstring** => getParameterString\_
- procedure **runmethod**
- type([test\\_parameters](#)) function **newtest** (name, method, npe, p1, p2)

### Public Attributes

- integer **p1**
- integer **p2**
- procedure(runmethod), pointer **usermethod** => null()

The documentation for this interface was generated from the following file:

- parameterizedTests.pf

## 15.93 test\_parameters\_mod Module Reference

### Data Types

- type [pecase](#)
- interface [test\\_parameters](#)

### Public Member Functions

- type([test\\_parameters](#)) function **newtest** (name, method, npe, p1, p2)
- type([pecase](#)) function, dimension(:), allocatable **getparameters** ()
- character(:) function, allocatable **getparameterstring\_** (this)
- subroutine **runmethod** (this)
- subroutine, public **testparambroken** (this)


The documentation for this module was generated from the following file:

- parameterizedTests.pf



## 15.94 test\_restrictsphericalcoordinates\_mod::test\_restrictsphericalcoordinates Interface Reference

Inheritance diagram for test\_restrictsphericalcoordinates\_mod::test\_restrictsphericalcoordinates:



### Public Member Functions

- procedure, nopass **getparameters**
- procedure **getparameterstring**
- procedure **runmethod**
- type([test\\_restrictsphericalcoordinates](#))  
function **newtest** (name, method, lat, lon, restrictedLat, restrictedLon)

### Public Attributes

- real **lat**
- real **lon**
- real **restrictedlat**
- real **restrictedlon**
- type(sphericalcoordinates) **unrestricted**
- type(sphericalcoordinates) **restricted**
- procedure(runmethod), pointer **usermethod** => null()

The documentation for this interface was generated from the following file:

- Test\_RestrictedSphericalCoordinates.pf

## 15.95 test\_restrictsphericalcoordinates\_mod Module Reference

### Data Types

- type [latloncase](#)
- interface [test\\_restrictsphericalcoordinates](#)

### Public Member Functions

- type([test\\_restrictsphericalcoordinates](#))  
function **newtest** (name, method, lat, lon, restrictedLat, restrictedLon)
- type([latloncase](#)) function,  
dimension(:), allocatable **getparameters** ()
- subroutine **testrestrict** (this)
- character(:) function, allocatable **getparameterstring** (this)
- subroutine **runmethod** (this)

The documentation for this module was generated from the following file:

- Test\_RestrictedSphericalCoordinates.pf

## 15.96 test\_robustringrunner\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testrunvariety** ()

The documentation for this module was generated from the following file:

- Test\_RobustRunner.F90

## 15.97 test\_simpletestcase\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- type(testsuite) function **internalsuite** ()
- subroutine **testworks** ()
- subroutine **testfails** ()
- subroutine **testrunsuite** ()

The documentation for this module was generated from the following file:

- Test\_SimpleTestCase.F90

## 15.98 test\_stringconversionutilities\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testtostringinteger1d** ()

The documentation for this module was generated from the following file:

- Test\_StringConversionUtilities.F90

## 15.99 test\_testmethod\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testmethodwasrun** ()
- subroutine **testwasrun** ()

The documentation for this module was generated from the following file:

- Test\_TestMethod.F90

## 15.100 test\_testresult\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testgetnumrun** ()
- subroutine **testgetnumfailed** ()
- subroutine **testaddlistenerend** ()
- subroutine **testaddlistenerstart** ()
- subroutine **testaddlistenerfailure** ()

The documentation for this module was generated from the following file:

- Test\_TestResult.F90

## 15.101 test\_testsuite\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testcounttestcases** ()
- subroutine **testcounttestcasesnesteda** ()
- subroutine **testcounttestcasesnestedb** ()
- subroutine **testcounttestcasesnestedc** ()
- subroutine **testgettestcases** ()
- subroutine **mytestmethod** ()

The documentation for this module was generated from the following file:

- Test\_TestSuite.F90

## 15.102 test\_unixprocess\_mod Module Reference

### Public Member Functions

- type(testsuite) function, public **suite** ()
- subroutine **testisactive** ()

The documentation for this module was generated from the following file:

- Test\_UnixProcess.F90

## 15.103 testcase\_mod Module Reference

<BriefDescription>

### Public Member Functions

- recursive subroutine **runbare** (this)
- recursive subroutine **runbare\_surrogate** (this)

### 15.103.1 Detailed Description

<BriefDescription>

**Author**

Tom Clune, NASA/GSFC SIVO

**Date**

07 Nov 2013

**Note**

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- TestCase.F90

### 15.104 testfailure\_mod Module Reference

<BriefDescription>

#### 15.104.1 Detailed Description

<BriefDescription>

**Author**

Tom Clune, NASA/GSFC SIVO

**Date**

07 Nov 2013

**Note**


<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- TestFailure.F90

### 15.105 mods.pre.pre\_if.TestIfDirective Class Reference

Inheritance diagram for mods.pre.pre\_if.TestIfDirective:



### Public Member Functions


- def **testTokenNotFound1**
- def **testNoTest**
- def **testIfTestFalse**
- def **testIfTestTrue1**
- def **testIfTestTrue2**
- def **testIfClearTokens**
- def **testIfClearTokensUntilEnd1**

The documentation for this class was generated from the following file:

- pre\_if.py

## 15.106 mods.pre.interleavedp.TestInterleaved Class Reference

Inheritance diagram for mods.pre.interleavedp.TestInterleaved:



### Public Member Functions

- def **test\_InOrder**
- def **test\_NumberMismatch**
- def **test\_OrderMismatch1**
- def **test\_OrderMismatch2**
- def **test\_OrderMismatch3**
- def **test\_ElseMid1**
- def **test\_ElseMid2**
- def **test\_ElseMid3**
- def **test\_ElseMid4**
- def **test\_ElseMid5**
- def **test\_ElseMid6**
- def **test\_ElseMid7**
- def **test\_ElseMid8**
- def **test\_ElseMid9**
- def **test\_ElseMid10**

The documentation for this class was generated from the following file:

- interleavedp.py

## 15.107 testlistener\_mod Module Reference

<BriefDescription>

## Data Types

- interface [startTest](#)

### 15.107.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- TestListener.F90

## 15.108 testmethod\_mod Module Reference

<BriefDescription>

### 15.108.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note


<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- TestMethod.F90

## 15.109 mods.pre.parseArgs.TestParseArgs Class Reference

Inheritance diagram for mods.pre.parseArgs.TestParseArgs:



## Public Member Functions


- def **test\_ParseArgs\_OneArgWithBrackets1**
- def **test\_ParseArgs\_OneArgWithBrackets2**
- def **test\_ParseArgs\_OneArgWithBrackets3**
- def **test\_ParseArgs\_OneArgWithBrackets4**
- def **test\_ParseArgs\_OneArgWithBrackets5**
- def **test\_ParseArgs\_OneArgWithBrackets6**
- def **test\_ParseArgs\_OneArgWithBrackets7**
- def **test\_ParseArgs\_oneArg**
- def **test\_ParseArgs\_twoArgs1**
- def **test\_ParseArgs\_twoArgs2**
- def **test\_ParseArgs\_oneArgArray1**
- def **test\_ParseArgs\_TwoArgArray**
- def **test\_ParseArgs\_ThreeArgs**

The documentation for this class was generated from the following file:

- parseArgs.py

## 15.110 testParser.TestParseLine Class Reference

Inheritance diagram for testParser.TestParseLine:



## Public Member Functions

- def **testCppSetLineAndFile**
- def **testGetSubroutineName**
- def **testGetTypeNames**
- def [testAtTest](#)
- def [testAtMpiTest](#)
- def [testMatchAtTestCase](#)
- def [testMatchAtAssertEqual](#)
- def [testMatchAtAssertOther](#)
- def [testMatchAtBefore](#)
- def [testMatchAtAfter](#)
- def [testMatchAtSuite](#)

## 15.110.1 Member Function Documentation

## 15.110.1.1 def testParser.TestParseLine.testAtMpiTest ( self )

Check that a line starting with '@mpitest' is detected as an annotation and that optional parameters are collected.

**15.110.1.2** `def testParser.TestParseLine.testAtTest ( self )`

Check that a line starting with '@test' is detected as an annotation.

**15.110.1.3** `def testParser.TestParseLine.testMatchAtAfter ( self )`

Check that a line starting with '@after\*' ...

**15.110.1.4** `def testParser.TestParseLine.testMatchAtAssertEqual ( self )`

Check that a line starting with '@assertEqual' is detected as an annotation.

**15.110.1.5** `def testParser.TestParseLine.testMatchAtAssertOther ( self )`

Check that a line starting with '@assert\*' is detected as an annotation.

**15.110.1.6** `def testParser.TestParseLine.testMatchAtBefore ( self )`

Check that a line starting with '@before\*' ...

**15.110.1.7** `def testParser.TestParseLine.testMatchAtSuite ( self )`

Check that a line starting with '@suite changes the suite name ...

**15.110.1.8** `def testParser.TestParseLine.testMatchAtTestCase ( self )`


Check that a line starting with '@testcase' is detected as an annotation.

The documentation for this class was generated from the following file:

- testParser.py

**15.111** `mods.pre.pre_Repeat.TestRepeatDirective` Class Reference

Inheritance diagram for `mods.pre.pre_Repeat.TestRepeatDirective`:





### Public Member Functions

- def **test\_copyBlock1**
- def **test\_copyBlock2**
- def **test\_copyBlock2Vars**
- def **test\_copyBlock2VarsMulti**
- def **test\_copyBlock2VarsMultiWithStrings**
- def **test\_copyNaiveRecursion**
- def **test\_copyNaiveRecursion1**
- def **test\_copyFunction1**

The documentation for this class was generated from the following file:

- pre\_Repeat.py

## 15.112 testresult\_mod Module Reference

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

### Public Member Functions

- type(testresult) function, pointer, public **newtestresult** ()
- subroutine **adderror** (this, aTest, exceptions)
- integer function **failurecount** (this)
- subroutine **addlistener** (this, listener)

### 15.112.1 Detailed Description

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- TestResult.F90

## 15.113 testrunner\_mod Module Reference

<BriefDescription>

## Public Member Functions

- type(testrunner) function **newtestrunner\_unit** (unit)
- subroutine **run** (this, aTest, context)
- subroutine **starttest** (this, testName)

### 15.113.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- TestRunner.F90

## 15.114 testsuite\_mod Module Reference

<BriefDescription>

## Public Member Functions

- recursive subroutine **addtest** (this, aTest)

### 15.114.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- TestSuite.F90

## 15.115 throwfundamentaltypes\_mod Module Reference

<BriefDescription>

### Public Member Functions

- subroutine, public **thrownonconformable** (shapeExpected, shapeFound, location)
- character(len=maxlen\_shape)  
function, public **locationformat** (iLocation)

### 15.115.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- ThrowFundamentalTypes.F90

## 15.116 unixpipeinterfaces\_mod Module Reference

<BriefDescription>

### Public Attributes

- integer(c\_int), parameter, public **close\_failed** = -1

### 15.116.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note

<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- UnixPipeInterfaces.F90

## 15.117 unixprocess\_mod Module Reference

<BriefDescription>

### Public Member Functions

- character(len=:) function,  
allocatable **makecommand** (baseCommand, runInBackground)
- logical function **isactive** (this)
- character(len=:) function,  
allocatable **getdelim** (this, delimiter)
- integer function **getpid** (this)

### 15.117.1 Detailed Description

<BriefDescription>

#### Author

Tom Clune, NASA/GSFC SIVO

#### Date

07 Nov 2013

#### Note


<A note here.> <Or starting here...>

The documentation for this module was generated from the following file:

- UnixProcess.F90

## 15.118 GenerateRealArrayNewSignature.VECTOR\_NORM Class Reference

Inheritance diagram for GenerateRealArrayNewSignature.VECTOR\_NORM:



### Public Member Functions

- def **\_\_init\_\_**

### Public Attributes

- **rank**
- **fType**
- **precision**
- **name**
- **declaration**
- **declarations**

The documentation for this class was generated from the following file:

- GenerateRealArrayNewSignature.py

# Index

- `__init__`
  - `GenerateRealArrayNewSignature::constraintASS-  
ERTEQUAL`, [47](#)
- `add_mod`, [37](#)
- `addTokenRE`
  - `mods::pre::pre2::procDirective`, [65](#)
- `addcomplex_mod`, [38](#)
- `assert_mod`, [38](#)
- `assertbasic_mod`, [39](#)
- `assertinteger_mod`, [40](#)
- 
- `basetestrunner_mod`, [45](#)
- `beforeafter_mod`, [46](#)
- `brokensetupcase_mod`, [46](#)
- `broken testcase_mod`, [46](#)
- 
- `CodeUtilities.ArrayDescription`, [38](#)
- `CodeUtilities.declaration`, [49](#)
- `CodeUtilities.fortranSubroutineSignature`, [50](#)
- `CodeUtilities.implementation`, [52](#)
- `CodeUtilities.interfaceBlock`, [52](#)
- `CodeUtilities.module`, [57](#)
- `CodeUtilities.routineUnit`, [68](#)
- 
- `debuglistener_mod`, [48](#)
- `dynamic testcase_mod`, [49](#)
- 
- `exception_mod`, [49](#)
- 
- `fixture_mod`, [50](#)
- `fixturedtestcase_mod`, [50](#)
- 
- `GenerateRealArrayNewSignature.AssertRealArray-  
Argument`, [40](#)
- `GenerateRealArrayNewSignature.constraintASSERTE-  
QUAL`, [46](#)
- `GenerateRealArrayNewSignature.IsWithinTolerance`, [52](#)
- `GenerateRealArrayNewSignature.VECTOR_NORM`, [90](#)
- `GenerateRealArrayNewSignature::constraintASSERTE-  
QUAL`
  - `name1`, [47](#)
  - `tolerance`, [47](#)
- 
- `halo_mod`, [51](#)
- 
- `linearinterpolator_mod`, [53](#)
- 
- `makeinfinity_mod`, [53](#)
- `makenan_mod`, [54](#)
- `mockcall_mod`, [55](#)
- 
- `mocklistener_mod`, [55](#)
- `mockrepository_mod`, [56](#)
- `mocksut_mod`, [56](#)
- `mods.pre.interleavedp.TestInterleaved`, [83](#)
- `mods.pre.parseArgs.TestParseArgs`, [84](#)
- `mods.pre.pre2.dataString`, [47](#)
- `mods.pre.pre2.procDirective`, [65](#)
- `mods.pre.pre_if.IfDirective`, [51](#)
- `mods.pre.pre_if.interval`, [52](#)
- `mods.pre.pre_if.TestIfDirective`, [82](#)
- `mods.pre.pre_Repeat.RepeatDirective`, [66](#)
- `mods.pre.pre_Repeat.TestRepeatDirective`, [86](#)
- `mods::pre::pre2::procDirective`
  - `addTokenRE`, [65](#)
- `mpicontext_mod`, [57](#)
- `mpistubs_mod`, [58](#)
- `mpitestcase_mod`, [58](#)
- `mpitestmethod_mod`, [59](#)
- 
- `name1`
  - `GenerateRealArrayNewSignature::constraintASS-  
ERTEQUAL`, [47](#)
- 
- `pFUnitParser.Action`, [37](#)
- `pFUnitParser.AtAfter`, [41](#)
- `pFUnitParser.AtAssert`, [41](#)
- `pFUnitParser.AtBefore`, [42](#)
- `pFUnitParser.AtBegin`, [42](#)
- `pFUnitParser.AtMpiTest`, [43](#)
- `pFUnitParser.AtParameters`, [43](#)
- `pFUnitParser.AtSuite`, [44](#)
- `pFUnitParser.AtTest`, [44](#)
- `pFUnitParser.AtTestCase`, [45](#)
- `pFUnitParser.Parser`, [62](#)
- `parallelcontext_mod`, [59](#)
- `parallelexception_mod`, [60](#)
- `parameterizedtestcase_mod`, [60](#)
- `params_mod`, [61](#)
- `pfunit`, [63](#)
- `pfunit_mod`, [63](#)
- `privateexception_mod`, [64](#)
- 
- `remoteproxytestcase_mod`, [65](#)
- `resultprinter_mod`, [66](#)
- `robustrunner_mod`, [67](#)
- `robusttestsuite_mod`, [68](#)
- 
- `serialcontext_mod`, [68](#)
- `simpletestcase_mod`, [69](#)
- `source location_mod`, [69](#)

- sphericalcoordinates\_mod, 70
- stringconversionutilities\_mod, 70
- subsetrunner\_mod, 71
- surrogatetestcase\_mod, 72
- sut\_mod, 72
- test\_assert\_mod, 72
- test\_assertbasic\_mod, 72
- test\_assertcomplex\_mod, 73
- test\_assertinteger\_mod, 73
- test\_assertreal\_mod, 74
- test\_exception\_mod, 74
- test\_fixturetestcase\_mod, 75
- test\_linearinterpolator\_mod, 75
- test\_linearinterpolator\_mod::test\_linearinterpolator, 75
- test\_mockcall\_mod, 76
- test\_mockrepository\_mod, 76
- test\_mod, 76
- test\_mpicontext\_mod, 77
- test\_mpiexception\_mod, 77
- test\_mpitestcase\_mod, 77
- test\_parameters\_mod, 78
- test\_parameters\_mod::pecase, 62
- test\_parameters\_mod::test\_parameters, 78
- test\_restrictsphericalcoordinates\_mod, 79
- test\_restrictsphericalcoordinates\_mod::latloncase, 53
- test\_restrictsphericalcoordinates\_mod::test\_restrictsphericalcoordinates, 79
- test\_robustrunner\_mod, 80
- test\_simpletestcase\_mod, 80
- test\_stringconversionutilities\_mod, 80
- test\_testmethod\_mod, 80
- test\_testresult\_mod, 81
- test\_testsuite\_mod, 81
- test\_unixprocess\_mod, 81
- testAtMpiTest
  - testParser::TestParseLine, 85
- testAtTest
  - testParser::TestParseLine, 85
- testMatchAtAfter
  - testParser::TestParseLine, 86
- testMatchAtAssertEqual
  - testParser::TestParseLine, 86
- testMatchAtAssertOther
  - testParser::TestParseLine, 86
- testMatchAtBefore
  - testParser::TestParseLine, 86
- testMatchAtSuite
  - testParser::TestParseLine, 86
- testMatchAtTestCase
  - testParser::TestParseLine, 86
- testParser.MockParser, 55
- testParser.MockWriter, 56
- testParser.TestParseLine, 85
- testParser::TestParseLine
  - testAtMpiTest, 85
  - testAtTest, 85
  - testMatchAtAfter, 86
  - testMatchAtAssertEqual, 86
  - testMatchAtAssertOther, 86
  - testMatchAtBefore, 86
  - testMatchAtSuite, 86
  - testMatchAtTestCase, 86
- testcase\_mod, 81
- testfailure\_mod, 82
- testlistener\_mod, 83
- testlistener\_mod::startTest, 70
- testmethod\_mod, 84
- testresult\_mod, 87
- testrunner\_mod, 87
- testsuite\_mod, 88
- throwfundamentaltypes\_mod, 89
- tolerance
  - GenerateRealArrayNewSignature::constraintASS-ERTEQUAL, 47
- unixpipeinterfaces\_mod, 89
- unixprocess\_mod, 90