

Introduction

Duik

Attributes

Objects

Methods

IK

goal

addController

addControllers

wiggle

exposure

addBones

Duik.uiStrings

Attributes

Duik.settings

Attributes

Methods

save

load

restoreDefaults

Duik.utils

Methods

prepareProperty

getPropertyDimensions

getLength

getAverageSpeed

addPseudoEffect

Introduction

libDuik is a complete library of objects, attributes and methods from Duik – Duduf IK & Animation Tools for After Effects. It allows to easily include Duik functions into other scripts.

Including libDuik in your scripts

There are three ways to use libDuik in your scripts:

- **#include libDuik.jsxinc**

Adding this line at the beginning of the script automatically loads libDuik at first run of the script. *libDuik.jsxinc* must be in the same folder as your script.

This is the recommended way of including libDuik.

- **Copying all content of libDuik.jsxinc in the beginning of your script**

Copying the whole library inside your script allows you to deploy only one file.

- **Renaming libDuik.jsxinc to libDuik.jsx and move it to Scripts/Startup/**

libDuik will be loaded during After Effects startup, and will then be available to all scripts. This is a good way to use Duik functions in several scripts without having to include libDuik in all scripts.

Using libDuik

Once libDuik has been loaded, all its classes, attributes and methods are available in the javascript object *Duik*, for all scripts run by After Effects.

libDuik is loaded only once; this allows a faster run of your scripts.

Modifying libDuik

If you're modifying libDuik and need to test it without having to reboot After Effects, you can set *Duik.forceReload* to *true* instead of *false* **inside libDuik itself**. You'll find this attribute just after the declaration of the *Duik* object in the beginning of libDuik.

Duik

Duik Attributes

string *Duik.version*

float *Duik.versionNumber*

boolean *Duik.forceReload*

Name	Type	Description
<i>version</i>	string, read-only	Version string of libDuik
<i>versionNumber</i>	float, read-only	Version number of libDuik
<i>forceReload</i>	boolean, read-only during run time	<p>When true, forces libDuik to be reloaded each time it is included in a script.</p> <p>When false, libDuik loads only on first run and then stays available until After Effects is shut down.</p> <p>This attribute should not be changed, unless you're editing libDuik.jsxinc itself and you need to do some testing and reload it without shutting down After Effects.</p> <p>To speed up launching of your scripts even at first launch, instead of including <i>libDuik.jsxinc</i>, you can copy it in the <i>Startup</i> subfolder of the <i>Scripts</i> folder of After Effects, and rename it to <i>libDuik.jsx</i>. This way, libDuik will be available to all scripts without <i>#include</i> macro.</p> <p>This attribute must be set by directly by editing libDuik.jsxinc to work.</p>

Duik Objects

Duik.uiString

Duik.settings

Duik.utils

Name	Description
<i>uiStrings</i>	Contains all string names used by effects created by Duik. You can set these strings to translate libDuik at runtime. Default values are English names.
<i>settings</i>	Access to settings used by Duik.
<i>utils</i>	Some useful tools

Duik Methods

//TODO tri par ordre alphabétique

Low-level methods are listed below (greyed) but they are not documented.

If you do not understand what low-level methods do by reading them in *libDuik.jsxinc*, you shouldn't need them.

Duik.IK(controller, layer1, layer2, layer3, goal, clockWise, threeD, frontFacing)

Duik.goal(layer, controller)

Duik.addController(layer)

Duik.addControllers(layers)

Duik.oneLayerIK(controller,layer)

Duik.twoLayerIK(threeD,controller,root,end,clockWise,frontFacing)

Duik.wiggle(layer,property,separateDimensions)

Duik.threeDWiggle(layer,property,)

Duik.twoDWiggle(layer,property)

Duik.oneDWiggle(layer,property)

Duik.exposure(layer,property,adaptative,limit,minExp,maxExp)

Duik.adaptativeExposure(layer,property,precision,minExp,maxExp)

Duik.fixedExposure(layer,property)

Duik.addBones(layers)

Duik.addZeros(layers)

Name	Description	Return
<i>IK(controller, layer1, layer2, layer3, goal, clockWise, threeD, frontFacing)</i>	Adds IK on the layers	true if successful, false if anything went wrong
<i>goal(layer, controller)</i>	Adds a goal effect to the layer, which may be controlled by a controller	true if successful, false if anything went wrong
<i>addController(layer)</i>	Creates a null object (controller) at layer position and named by layer.name	AVLayer; controller
<i>addControllers(layers)</i>	For each layer, Creates a null object (controller) at layer position and named by layer.name	Array of AVLayer; controllers
<i>wiggle(layer, property, separateDimensions)</i>	Adds a wiggle effect to given property	true if successful, false if anything went wrong
<i>exposure(layer, property, adaptative, precision, minExp, maxExp)</i>	Adds exposure controles to given property	true if successful, false if anything went wrong
<i>addBones(layers)</i>	Adds bones to the layers	Array of AVLayer; bones
<i>addZeros(layers)</i>	Adds zeros to the layers	Array of AVLayer; zeros

Duik.IK(controller, layer1, layer2, layer3, goal, clockWise, threeD, frontFacing)

high-level method.

Adds IK on the layers

parameters:

- controller | AVLayer
- layer1 | AVLayer
- layer2 | AVLayer or undefined
- layer3 | AVLayer or undefined
- goal | AVLayer or undefined
- clockWise | boolean, used only with two-layer and three-layer IK, default: false
- threeD | boolean, works only with two-layer IK, default: false
- frontFacing | boolean, default: false

returns

true if successful, false if anything went wrong

Duik.goal(layer, controller)

high-level method.

Adds a goal effect to the layer, which may be controlled by a controller

parameters:

- layer | AVLayer
- controller | AVLayer or undefined

returns

true if successful, false if anything went wrong

Duik.addController(layer)

high-level method.

Creates a null object (controller) at layer position and named by layer.name

parameters

- layer | AVLayer

returns

AVLayer controller

Duik.addControllers(layers)

This is a convenience method, which runs Duik.addController(layer) on each layer of the given array of layers.

parameters

layers | Array of AVLayer

returns

Array of AVLayer controllers

Duik.wiggle(layer, property, separateDimensions)

high-level method.

Adds a wiggle effect to given property.

parameters

layer | AVLayer of the property

property | Property

separateDimensions | boolean, false to apply the same wiggle to all dimensions,

default: false

returns

true if successful, false if anything went wrong

Duik.exposure(layer, property, adaptative, limit, minExp, maxExp)

high-level method.

Adds exposure controls to given property.

parameters

layer | AVLayer of the property

property | Property

adaptative | boolean, default: true

limit | float, default: 100

minExp | integer, default : 1, minimum exposure

maxExp | integer, default : 4, maximum exposure

returns

true if successful, false if anything went wrong

Duik.addBones(layers)

high-level method.

Adds bones to the layers, only on selected pins if any, or else on all puppet pins found on those layers.

parameters

layers | Array of AVLayers

returns

Array of AVLayers, the bones created

Duik.addZeros(layers)

high-level method.

Adds a null object for each layer, at the same place and orientation, and then parents the layer to it, parenting the null object (the zero) to the former parent of the layer.

parameters

layers | Array of AVLayers

returns

Array of AVLayers, the zeros created

Duik.uiStrings

Contains all string names used by effects created by Duik.
You can set these strings to translate libDuik at runtime.
Default values are English names.

Duik.uiStrings Attributes

Duik.uiStrings.ik
Duik.uiStrings.wiggle
Duik.uiStrings.exposure

Name	Type	Description
<i>ik</i>	string	"IK"
<i>wiggle</i>	string	"Wiggle"
<i>exposure</i>	string	"Exposure"

Duik.settings

Access to settings used by Duik.

Duik.settings Attributes

These attributes define some settings and preferences needed by Duik.

If you set them, they can be saved to be reloaded even if After Effects is shutdown, using *Duik.settings.save()*. If this method is not called, the settings will be set back to previous values if After Effects is shut down.

Saved settings must be loaded at runtime calling *Duik.settings.load()*.

Default values can be restored using *Duik.settings.restoreDefaults()*.

Duik.settings.controllerSize

Duik.settings.controllerSizeAuto

Duik.settings.controllerSizeHint

Duik.settings.boneType = eval(app.settings.getSetting("duik","boneType"));

Duik.settings.boneSize = eval(app.settings.getSetting("duik","boneSize"));

Duik.settings.boneSizeAuto = eval(app.settings.getSetting("duik","boneSizeAuto"));

Duik.settings.boneSizeHint = eval(app.settings.getSetting("duik","boneSizeAutoValue"));

Duik.settings.boneColor = app.settings.getSetting("duik","boneColor");

Name	Type	Description	Default
<i>controllerSize</i>	integer	Size of controllers in pixels	100
<i>controllerSizeAuto</i>	boolean	If true, controller sizes will be automatically adapted to comp size, according to <i>Duik.settings.controllerSizeHint</i>	true
<i>controllerSizeHint</i>	integer	Enumerated value, one of: Duik.sizes.SMALL Duik.sizes.MEDIUM Duik.sizes.BIG	Duik.sizes.MEDIUM
<i>boneType</i>	integer	Enumerated value, one of: Duik.layerTypes.NULL Duik.layerTypes.SOLID	Duik.layerTypes.SOLID
<i>boneSize</i>	integer	Size of bones in pixels	20
<i>boneSizeAuto</i>	boolean	If true, bone sizes will be automatically adapted to comp size, according to <i>Duik.settings.boneSizeHint</i>	true
<i>boneSizeHint</i>	integer	Enumerated value, one of: Duik.sizes.SMALL Duik.sizes.MEDIUM Duik.sizes.BIG	Duik.sizes.MEDIUM
<i>boneColor</i>	string	Hex value of the color of the bones, excluding leading « # »	« FF0000 »

Duik.settings Methods

Duik.settings.save()

Duik.settings.load()

Duik.settings.restoreDefaults()

Name	Description	Return
<i>save()</i>	Saves Duik settings into After Effects preferences	void
<i>load()</i>	Loads Duik settings from After Effects preferences	void
<i>restoreDefaults()</i>	Restore default values to Duik settings	void

Duik.settings.save()

Saves Duik settings attributes into After Effects preferences (using `app.settings.saveSetting()`)

Those settings can be loaded when the script runs using *Duik.settings.load()*. This allows to easily restore the settings set by the user even if After Effects is shut down.

parameters:

none

returns

void

Duik.settings.load()

Loads Duik settings attributes from After Effects preferences (using `app.settings.getSetting()`)

This allows to easily restore the settings set by the user even if After Effects is shut down.

If this method is not called at runtime, default values will be loaded at first run.

parameters:

none

returns

void

Duik.settings.restoreDefaults()

Restore default values to Duik settings. These values will not be saved until `Duik.settings.save()` is called.

parameters:

none

returns

void

Duik.utils

Some useful methods.

Duik.utils Methods

Duik.utils.prepareProperty(property,isFX,index,depth,parentName)

Duik.utils.getPropertyDimensions(property)

Duik.utils.getLength(value1,value2)

Duik.utils.getAverageSpeed(layer,property)

Duik.utils.addPseudoEffect(layer,pseudoEffectName)

Name	Description	Return
<i>prepareProperty(property, isFX, index, depth, parentName)</i>	Prepares property to be rigged	true if property can set expression, false otherwise
<i>getPropertyDimensions(property)</i>	Gets the dimensions of the property (1, 2 or 3), taking care of 2D layer positions (reported as 3D by AFX, but to be considered as 2D)	integer, number of dimensions
<i>getLength(value1, value2)</i>	Gets the length between the values, whichever dimensions they are	float, length between the values
<i>getAverageSpeed(layer, property)</i>	Gets the average speed of the animated property, between its first and last keyframe only	float, average speed of the property
<i>addPseudoEffect(layer, pseudoEffectName)</i>	Adds a Duik predefined pseudo effect to the layer	Property, the effect added

Duik.utils.prepareProperty(property,isFX,index,depth,parentName)

Prepare the given property to be rigged.

isFX, index, depth, parentName will be filled by the method with the values corresponding to this property.

parameters:

property | Property
isFX | boolean
index | integer
depth | integer
parentName | string

returns

true if property can set expression, false otherwise

Duik.utils.getPropertyDimensions(property)

Gets the dimensions of the property (1, 2 or 3), taking care of 2D layer positions (reported as

3D by AFX, but to be considered as 2D)

parameters:

property | Property

returns

integer, number of dimensions

Duik.utils.getLength(value1, value2)

Gets the length between the values, whichever dimensions they are

parameters:

value1 | float or Array of float, first coordinates

value2 | float or Array of float, second coordinates

returns

float, length between the values

Duik.utils.getAverageSpeed(layer, property)

Gets the average speed of the animated property, between its first and last keyframe only.

parameters:

layer | AVLayer of the property

property | Property

returns

float, average speed of the property

Duik.utils.addPseudoEffect(layer, pseudoEffectFileName)

Adds a Duik predefined pseudo effect to the layer. The AFX preset file of the pseudo effect must be located in the same folder as libDuik.jsxinc and called « Duik_ » + pseudoEffectName + « .ffx ».

In the preset, the effect must be called pseudoEffectName.

parameters:

layer | AVLayer

pseudoEffectFileName | string, name of the file of the pseudo effect

returns

Property, the effect added