

Packet Tracer - Use Diagnostic Commands

Objectives

Part 1: Gather End User Device Settings

Part 2: Gather Information about Network Devices

Part 3: Diagnose Connectivity Issues

Background / Scenario

In this Packet Tracer (PT) activity, you will use various commands to gather device information and troubleshoot device configuration and connectivity issues. Device information includes IP address, default gateway, and DNS server settings. These settings are critical to enable a device to communicate on networks and connect to the internet.

Instructions


Part 1: Gather End User Device Settings

In this part, you will document the IP address settings for end devices.

Step 1: Document the IP address settings for HQ-Laptop-1.

- The activity opens in the **HQ** cluster. The **Wiring Closet** is the tall, black chassis in the bottom left corner of the first floor. Locate all the devices on the first floor: PCs **1-1**, **1-2**, **1-3**, and **1-4**; printer **FL-1P**; and **HQ-Laptop-1**.
- Click **HQ-Laptop-1** > **Desktop** tab > **Command Prompt**.
- Enter the **ipconfig** command.

Which IPv4 address is displayed for the **Wireless0 Connection**?



```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

Wireless0 Connection: (default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: FE80::20A:F3FF:FEE4:EEAA
    IPv6 Address . . . . .: ::
    Autoconfiguration IPv4 Address...: 169.254.238.171
    Subnet Mask . . . . .: 255.255.0.0
    Default Gateway . . . . .: ::
                                   0.0.0.0

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: ::
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 0.0.0.0
    Subnet Mask . . . . .: 0.0.0.0
    Default Gateway . . . . .: ::
                                   0.0.0.0
```

Ini mungkin ditampilkan sebagai alamat 169.254.0.0/16 karena koneksi nirkabel mungkin belum dibuat. Alamat akan berada dalam jaringan 192.168.50.0/24.

If the IPv4 address is in the 169.254.0.0/16 range, what method is being used to assign IPv4 addresses? Why is the laptop assigned an IPv4 address in the 169.254.0.0/16 range?

It indicates that the device was unable to obtain addressing from a DHCP server. Therefore, the device assigned itself an address 169.254.0.0/16 pool used for automatic private IP addressing (APIPA).

If the IPv4 address is in the 169.254.0.0/16, wait a few seconds and repeat the **ipconfig** command.

```
C:\>ipconfig

Wireless0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: FE80::20A:F3FF:FEE4:EEAA
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 192.168.50.4
    Subnet Mask . . . . .: 255.255.255.0
    Default Gateway . . . . .: ::
                                   192.168.50.1

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: ::
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 0.0.0.0
    Subnet Mask . . . . .: 0.0.0.0
    Default Gateway . . . . .: ::
                                   0.0.0.0
```

When the IPv4 address is no longer from 169.254.0.0/16 range, what is the IP addressing information displayed? Record your answers in the table below.

Wireless0	IP Addressing Information
Link-local IPv6 Address	FE80::20A:F3FF:FEE4:EEAA
IPv6 Address	::
IPv4 Address	192.168.50.4 (it may vary, but will be within the 192.168.50.0/24 range)
Subnet Mask	255.255.255.0
Default Gateway	192.168.50.1
DNS Servers	N/A

Wireless0, No additional information

Do you see a DNS server address? Explain.

Perintah ipconfig tidak melaporkan alamat server DNS.

- d. Enter the **ipconfig /all** command.

```
C:\>ipconfig /all

Wireless0 Connection:(default port)

Connection-specific DNS Suffix...:
Physical Address.....: 000A.F3E4.EEAA
Link-local IPv6 Address.....: FE80::20A:F3FF:FEE4:EEAA
IPv6 Address.....: ::
IPv4 Address.....: 192.168.50.4
Subnet Mask.....: 255.255.255.0
Default Gateway.....: ::
                        192.168.50.1
DHCP Servers.....: 192.168.50.1
DHCPv6 IAID.....: 720630881
DHCPv6 Client DUID.....: 00-01-00-01-43-B9-1D-8A-00-0A-F3-E4-EE-AA
DNS Servers.....: ::
                        10.2.0.125

Bluetooth Connection:

Connection-specific DNS Suffix...:
Physical Address.....: 00E0.A3A2.D8AA
Link-local IPv6 Address.....: ::
IPv6 Address.....: ::
IPv4 Address.....: 0.0.0.0
Subnet Mask.....: 0.0.0.0
Default Gateway.....: ::
                        0.0.0.0
DHCP Servers.....: 0.0.0.0
DHCPv6 IAID.....: 720630881
DHCPv6 Client DUID.....: 00-01-00-01-43-B9-1D-8A-00-0A-F3-E4-EE-AA
DNS Servers.....: ::
                        10.2.0.125
```

Do you see the DNS server address? What is it?

10.2.0.125

Step 2: Document the IP address settings for Net-Admin.

- Click **Wiring Closet > Net-Admin > Desktop tab > Command Prompt**.
- Enter the **ipconfig /all** command.

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig /all

FastEthernet0 Connection:(default port)

Connection-specific DNS Suffix...:
Physical Address.....: 0001.C910.22D6
Link-local IPv6 Address.....: FE80::201:C9FF:FE10:22D6
IPv6 Address.....: ::
IPv4 Address.....: 192.168.99.9
Subnet Mask.....: 255.255.255.0
Default Gateway.....: ::
                        192.168.99.1
DHCP Servers.....: 0.0.0.0
DHCPv6 IAID.....:
DHCPv6 Client DUID.....: 00-01-00-01-67-A3-E9-BD-00-01-C9-10-22-D6
DNS Servers.....: ::
                        10.2.0.125

Bluetooth Connection:

Connection-specific DNS Suffix...:
Physical Address.....: 0001.649E.81BB
Link-local IPv6 Address.....: ::
IPv6 Address.....: ::
IPv4 Address.....: 0.0.0.0
Subnet Mask.....: 0.0.0.0
Default Gateway.....: ::
                        0.0.0.0
DHCP Servers.....: 0.0.0.0
DHCPv6 IAID.....:
DHCPv6 Client DUID.....: 00-01-00-01-67-A3-E9-BD-00-01-C9-10-22-D6
DNS Servers.....: ::
                        10.2.0.125
```

What is the IP addressing information displayed under the FastEthernet0 interface? Record your answers in the table below.

FastEthernet0	IP Addressing Information
Physical Address	0001.C910.22D6
Link-local IPv6 Address	FE80::201:C9FF:FE10:22D6
IPv6 Address	::
IPv4 Address	192.168.99.9
Subnet Mask	255.255.255.0
Default Gateway	192.168.99.1
DNS Servers	10.2.0.125

Part 2: Gather Information about Network Devices

In this part, you will document information about the link to ISP. You will then document the IP addressing information for all the end devices in HQ and discover that devices belong to different virtual local area networks (VLANs).

Step 1: Gather network connection information about the link between HQ and ISP.

The **HQ-Edge** router is the router between the HQ network and the ISP. We need to identify the upstream device information located in the ISP.

- In the **Wiring Closet** left rack, click **HQ-Edge > CLI** tab.
- Press **Enter** to get the **HQ-Edge>** prompt, and then enter the **enable** command.
- Enter the **show ip route | begin Gateway** command.

```
HQ-Edge> enable
HQ-Edge#show ip route | begin Gateway
Gateway of last resort is 0.0.0.0 to network 0.0.0.0

 10.0.0.0/8 is variably subnetted, 6 subnets, 4 masks
O   10.0.0.0/29 [110/2] via 10.0.0.49, 00:23:13, GigabitEthernet0/0/0
O   10.0.0.32/29 [110/2] via 10.0.0.49, 00:23:13, GigabitEthernet0/0/0
C   10.0.0.48/29 is directly connected, GigabitEthernet0/0/0
L   10.0.0.50/32 is directly connected, GigabitEthernet0/0/0
O   10.0.3.0/24 [110/3] via 10.0.0.49, 00:23:13, GigabitEthernet0/0/0
O   10.2.0.0/16 [110/2] via 10.0.0.49, 00:23:13, GigabitEthernet0/0/0
 192.168.10.0/24 is variably subnetted, 2 subnets, 2 masks
C   192.168.10.0/24 is directly connected, GigabitEthernet0/0/1.10
L   192.168.10.1/32 is directly connected, GigabitEthernet0/0/1.10
 192.168.20.0/24 is variably subnetted, 2 subnets, 2 masks
C   192.168.20.0/24 is directly connected, GigabitEthernet0/0/1.20
L   192.168.20.1/32 is directly connected, GigabitEthernet0/0/1.20
 192.168.30.0/24 is variably subnetted, 2 subnets, 2 masks
C   192.168.30.0/24 is directly connected, GigabitEthernet0/0/1.30
L   192.168.30.1/32 is directly connected, GigabitEthernet0/0/1.30
 192.168.50.0/24 is variably subnetted, 2 subnets, 2 masks
C   192.168.50.0/24 is directly connected, GigabitEthernet0/0/1.50
L   192.168.50.1/32 is directly connected, GigabitEthernet0/0/1.50
 192.168.75.0/24 is variably subnetted, 2 subnets, 2 masks
C   192.168.75.0/24 is directly connected, GigabitEthernet0/0/1.75
L   192.168.75.1/32 is directly connected, GigabitEthernet0/0/1.75
 192.168.99.0/24 is variably subnetted, 2 subnets, 2 masks
C   192.168.99.0/24 is directly connected, GigabitEthernet0/0/1.99
L   192.168.99.1/32 is directly connected, GigabitEthernet0/0/1.99
S*  0.0.0.0/0 is directly connected, GigabitEthernet0/0/0
```

What is the address for the gateway of last resort (or default gateway)?

0.0.0.0

Why is the next hop address not displayed?

Ini tidak dikonfigurasi secara eksplisit.

- d. Enter the **show running-config | begin ip route** command.

```
HQ-Edge#show running-config | begin ip route
ip route 0.0.0.0 0.0.0.0 GigabitEthernet0/0/0
!
ip flow-export version 9
!
!
ip access-list standard NAT-PERMIT
permit 192.168.10.0 0.0.0.255
permit 192.168.20.0 0.0.0.255
permit 192.168.99.0 0.0.0.15
permit 192.168.75.0 0.0.0.7
ip access-list standard ADMIN-ONLY
permit 192.168.99.0 0.0.0.255
deny any
access-list 101 permit ip 192.168.10.0 0.0.0.255 10.0.3.0 0.0.0.255
access-list 101 permit ip 192.168.20.0 0.0.0.255 10.0.3.0 0.0.0.255
access-list 101 permit ip 192.168.75.0 0.0.0.255 10.0.3.0 0.0.0.255
access-list 101 permit ip 192.168.99.0 0.0.0.255 10.0.3.0 0.0.0.255
access-list 101 permit icmp any 10.0.3.0 0.0.0.255
ip access-list extended NAT-NOVPN
permit ip 192.168.0.0 0.0.255.255 10.2.0.0 0.0.255.255
permit ip 192.168.0.0 0.0.255.255 10.1.0.0 0.0.255.255
permit ip 192.168.0.0 0.0.255.255 192.168.0.0 0.0.0.255
permit ip 192.168.0.0 0.0.255.255 172.0.0.0 0.0.255.255
```

How is the default route configured? Does it use the next hop address?

Type your answers here.

Ini dikonfigurasi dengan antarmuka keluar, bukan alamat hop berikutnya.

- e. Enter the **show cdp neighbors detail** command.

```
HQ-Edge#show cdp neighbors detail

Device ID: ISP
Entry address(es):
  IP address : 10.0.0.49
Platform: cisco PT1000, Capabilities: Router
Interface: GigabitEthernet0/0/0, Port ID (outgoing port): GigabitEthernet1/0
Holdtime: 146

Version :
Cisco Internetwork Operating System Software
IOS (tm) PT1000 Software (PT1000-I-M), Version 12.2(28), RELEASE SOFTWARE (fc5)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2005 by cisco Systems, Inc.
Compiled Wed 27-Apr-04 19:01 by miwang

advertisement version: 2
Duplex: full
```

What is the IPv4 address of the next hop (ISP) address?

10.0.0.49

Which port on the ISP router is connected to **HQ-Edge**?

GigabitEthernet 1/0

What IOS version is used on the ISP router?

IOS (tm) PT1000 Software (PT1000-I-M), Version 12.2(28), RELEASE SOFTWARE (fc5)

- f. Enter the **ping 10.0.0.49** command.

```
HQ-Edge#ping 10.0.0.49

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 10.0.0.49, timeout is 2 seconds:
!!!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 0/7/34 ms
```

- g. Enter the **show arp** command.

```
HQ-Edge#show arp
Protocol Address Age (min) Hardware Addr Type Interface
Internet 10.0.0.49 28 0060.2FE1.903B ARPA GigabitEthernet0/0/0
Internet 10.0.0.50 - 0000.0C99.CB04 ARPA GigabitEthernet0/0/0
```

What is the MAC address of the interface on the **ISP** router that is connected to **HQ-Edge**?

0060.2FE1.903B

- h. Close **HQ-Edge** and exit the **Wiring Closet**.

Step 2: Gather network connection information about the devices in HQ.

- a. From **1-1**, **1-2**, **1-3**, **1-4**, **FL-1P**, and **HQ-Laptop-1**, use the **ipconfig** command to find their IPv4 addresses and Default Gateways.

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

FastEthernet0 Connection: (default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: FE80::201:C7FF:FE54:EB5
    IPv6 Address . . . . .: ::
    IPv4 Address. . . . .: 192.168.10.3
    Subnet Mask . . . . .: 255.255.255.0
    Default Gateway . . . . .: ::
                                192.168.10.1

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: ::
    IPv6 Address . . . . .: ::
    IPv4 Address. . . . .: 0.0.0.0
    Subnet Mask . . . . .: 0.0.0.0
    Default Gateway . . . . .: ::
                                0.0.0.0
```

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

FastEthernet0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address.....: FE80::202:4AFF:FE8A:D20E
    IPv6 Address.....: ::
    IPv4 Address.....: 192.168.10.2
    Subnet Mask.....: 255.255.255.0
    Default Gateway.....: ::
                           192.168.10.1

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address.....: ::
    IPv6 Address.....: ::
    IPv4 Address.....: 0.0.0.0
    Subnet Mask.....: 0.0.0.0
    Default Gateway.....: ::
                           0.0.0.0
```

PC 1-2

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

FastEthernet0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address.....: FE80::201:C9FF:FEE9:887E
    IPv6 Address.....: ::
    IPv4 Address.....: 192.168.20.3
    Subnet Mask.....: 255.255.255.0
    Default Gateway.....: ::
                           192.168.20.1

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address.....: ::
    IPv6 Address.....: ::
    IPv4 Address.....: 0.0.0.0
    Subnet Mask.....: 0.0.0.0
    Default Gateway.....: ::
                           0.0.0.0
```

PC 1-3

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

FastEthernet0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: FE80::201:97FF:FEBA:7BB0
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 192.168.20.2
    Subnet Mask . . . . .: 255.255.255.0
    Default Gateway . . . . .: ::
                                   192.168.20.1

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: ::
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 0.0.0.0
    Subnet Mask . . . . .: 0.0.0.0
    Default Gateway . . . . .: ::
                                   0.0.0.0
```

PC 1-4

IP Configuration	
<input checked="" type="radio"/> DHCP	
<input type="radio"/> Static	
IPv4 Address	192.168.50.2
Subnet Mask	255.255.255.0

FL-1P

```
C:\>ipconfig

Wireless0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: FE80::20A:F3FF:FEE4:EEAA
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 192.168.50.4
    Subnet Mask . . . . .: 255.255.255.0
    Default Gateway . . . . .: ::
                                   192.168.50.1

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: ::
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 0.0.0.0
    Subnet Mask . . . . .: 0.0.0.0
    Default Gateway . . . . .: ::
                                   0.0.0.0
```

HQ-Laptop-1

Device	IPv4 Address	Default Gateway
--------	--------------	-----------------

1-1	192.168.10.3	192.168.10.1
1-2	192.168.10.2	192.168.10.1
1-3	192.168.20.3	192.168.20.1
1-4	192.168.20.2	192.168.20.1
FL-1P	192.168.50.2	192.168.50.1
HQ-Laptop-1	192.168.50.4	192.168.50.1

- b. From PC 1-1, open **Command Prompt**, and then enter the **arp -a** command.

```
C:\>arp -a
No ARP Entries Found
```

What information is displayed?

No ARP Entries Found.

- c. Use the **ping** command to ping 1-2, 1-3, 1-4, FL-1P, and HQ-Laptop-1.

```
C:\>ping 192.168.10.2

Pinging 192.168.10.2 with 32 bytes of data:

Reply from 192.168.10.2: bytes=32 time=5ms TTL=128
Reply from 192.168.10.2: bytes=32 time<1ms TTL=128
Reply from 192.168.10.2: bytes=32 time<1ms TTL=128
Reply from 192.168.10.2: bytes=32 time=16ms TTL=128

Ping statistics for 192.168.10.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 16ms, Average = 5ms
```

Ping ke PC 1-2

```
C:\>ping 192.168.20.3

Pinging 192.168.20.3 with 32 bytes of data:

Request timed out.
Reply from 192.168.20.3: bytes=32 time<1ms TTL=127
Reply from 192.168.20.3: bytes=32 time<1ms TTL=127
Reply from 192.168.20.3: bytes=32 time<1ms TTL=127

Ping statistics for 192.168.20.3:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms
```

Ping ke PC 1-3

```
C:\>ping 192.168.20.2

Pinging 192.168.20.2 with 32 bytes of data:

Request timed out.
Reply from 192.168.20.2: bytes=32 time=26ms TTL=127
Reply from 192.168.20.2: bytes=32 time<1ms TTL=127
Reply from 192.168.20.2: bytes=32 time=11ms TTL=127

Ping statistics for 192.168.20.2:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 26ms, Average = 12ms
```

Ping ke PC 1-4

```
C:\>ping 192.168.50.2

Pinging 192.168.50.2 with 32 bytes of data:

Request timed out.
Reply from 192.168.50.2: bytes=32 time=25ms TTL=127
Reply from 192.168.50.2: bytes=32 time=34ms TTL=127
Reply from 192.168.50.2: bytes=32 time=20ms TTL=127

Ping statistics for 192.168.50.2:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 20ms, Maximum = 34ms, Average = 26ms
```

Ping ke FL-1P

```
C:\>ping 192.168.50.4

Pinging 192.168.50.4 with 32 bytes of data:

Request timed out.
Reply from 192.168.50.4: bytes=32 time=131ms TTL=127
Reply from 192.168.50.4: bytes=32 time=30ms TTL=127
Reply from 192.168.50.4: bytes=32 time=17ms TTL=127

Ping statistics for 192.168.50.4:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 17ms, Maximum = 131ms, Average = 59ms
```

Ping ke HQ-Laptop-1

- d. Enter the **arp -a** command.

```
C:\>arp -a

Internet Address      Physical Address      Type
192.168.10.1          000a.41ea.6b47       dynamic
192.168.10.2          0002.4a8a.d20e       dynamic
```

What information is displayed?

Internet Address	Physical Address	Type
192.168.10.1	000a.41ea.6b47	dynamic
192.168.10.3	0002.4a8a.d20e	dynamic

ARP provides a table that maps known MAC addresses to their associated IP addresses.

Why do the entries in the ARP table not contain information about devices in the 192.168.20.0 and 192.168.50.0 networks while the ping is successful?

192.168.10.0/24, 192.168.20.0/24, dan 192.168.50.0/24 berada di VLAN yang berbeda. Ping dari jaringan 192.168.10.0 ke jaringan VLAN lainnya harus melalui gateway default terlebih dahulu. Oleh karena itu, tabel ARP hanya berisi informasi tentang perangkat dalam jaringan yang sama atau VLAN yang sama.

- e. To find the route a packet takes to reach the DNS server, enter the `tracert 10.2.0.125` command.

```
C:\>tracert 10.2.0.125

Tracing route to 10.2.0.125 over a maximum of 30 hops:

  1  0 ms    0 ms    0 ms    192.168.10.1
  2  0 ms    0 ms    0 ms    10.0.0.49
  3  *        0 ms    15 ms   10.2.0.125

Trace complete.
```

What information is displayed?

Tracing route to 10.2.0.125 over a maximum of 30 hops:

1	0 ms	0 ms	0 ms	192.168.10.1
2	0 ms	0 ms	0 ms	10.0.0.49
3	*	0 ms	15 ms	10.2.0.125

How many routers, or hops, are between PC 1-1 and the DNS server?


2

Part 3: Diagnose Connectivity Issues

In this part, you will use a variety of diagnostic commands and techniques. You will use the **nslookup** command to query a DNS server and troubleshoot a DNS database. You will then diagnose why a ping fails but web access is successful. Finally, you will use the **netstat** command to discover which ports are listening on the target device.

Step 1: Test a URL to investigate a connectivity issue.


- On PC 1-1, close the **Command Prompt**, and then click **Web Browser**.
- Enter the URL **test.ptsecurity.com**.



Does the web page display? If not, what is the message?

No, it does not. The message is "Host Name Unresolved".

- Enter the IP address **192.168.75.2**.



Does the web page display?

Yes

Why does the web page display by using the IP address but not the domain name?

The PC cannot resolve the domain name to the IP address.

Step 2: Use the nslookup command to verify DNS service.

- a. Close **Web Browser**, and then click **Command Prompt**.
- b. Enter the **ping test.ptsecurity.com** command.

```
C:\>ping test.ptsecurity.com
Ping request could not find host test.ptsecurity.com. Please check the name and try again.
```

What message is displayed?

Ping request could not find host test.ptsecurity.com. Please check the name and try again.

What does the message indicate?

The DNS entry is not in the database of the DNS server.

- c. Enter the **nslookup test.ptsecurity.com** command.

```
C:\>nslookup test.ptsecurity.com

Server: [10.2.0.125]
Address: 10.2.0.125
*** UnKnown can't find test.ptsecurity.com: Non-existent domain.
```

What message is displayed?

```
Server: [10.2.0.125]
Address: 10.2.0.125
*** UnKnown can't find test.ptsecurity.com: Non-existent domain.
```

Which server is the default DNS server?

10.2.0.125

- d. The **nslookup** command supports the use of alternate DNS server. Enter the **nslookup /?** command to learn options available for the command.

```
C:\>nslookup /?
Usage:

nslookup          # interactive mode using default server
nslookup host     # just look up 'host' using default server
nslookup host a.b.c.d # just look up 'host' using DNS server with ip address 'a.b.c.d'
```

- e. Enter the **nslookup test.ptsecurity.com 192.168.99.3** command and press **Enter**.

Note: Packet Tracer may take several seconds to converge.

```
C:\>nslookup test.ptsecurity.com 192.168.99.3

Server: [192.168.99.3]
Address: 192.168.99.3
DNS request timed out.
        timeout was 15000 milli seconds.

Server: [192.168.99.3]
Address: 192.168.99.3

Non-authoritative answer:
Name:   test.ptsecurity.com
Address: 192.168.75.2
```

What message is displayed?

```
C:\> nslookup test.ptsecurity.com 192.168.99.3
Server: [192.168.99.3]
Address: 192.168.99.3
```

Non-authoritative answer:

Name: test.ptsecurity.com
Address: 192.168.75.2

In Step 2c, why is the domain name unable to be resolved?

When a domain name is entered in the URL box, the PC is trying to resolve it through the default DNS server. In this case, the default DNS server does not contain the information in its database.

Step 3: Use output from the ping command to diagnose connectivity issues.

- a. Enter the **ping mail.cybercloud.com** command.

```
C:\>ping mail.cybercloud.com

Pinging 172.19.0.4 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 172.19.0.4:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```

What message is displayed?

```
C:\> ping mail.cybercloud.com
Pinging 172.19.0.4 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 172.19.0.4:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```

What information is indicated by the message?

The DNS name resolution is successful. However, the ping failed. Possible reasons are that the host is inactive or the ICMP echo/echo-reply is disabled on the host.

- b. Enter the **ping www.ptsecurity.com** command.

```
C:\>ping www.ptsecurity.com

Pinging 10.0.0.3 with 32 bytes of data:

Request timed out.
Request timed out.
Reply from 10.0.0.3: Destination host unreachable.
Reply from 10.0.0.3: Destination host unreachable.

Ping statistics for 10.0.0.3:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```

What message is displayed?

```
Pinging 10.0.0.3 with 32 bytes of data:
Request timed out.
Request timed out.
Reply from 10.0.0.3: Destination host unreachable.
Reply from 10.0.0.3: Destination host unreachable.

Ping statistics for 10.0.0.3:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```

What information is indicated by the message?

There is a firewall in the path that blocks the ping to the destination.

- c. Close the **Command Prompt**, open **Web Browser**, and then navigate to **www.ptsecurity.com**.



Does the web page display?

Yes

What conclusion can be drawn?

The web host is running; however, the ping to the web server is blocked.

Step 4: Use the netstat command to find active and listening ports.

- Close **Web Browser**, and reopen **Command Prompt**.
- In **HQ**, click the **Wiring Closet**
- From the right rack, click the **FTP** server > **Desktop** tab > **Command Prompt**.
- Arrange the PC 1-1 and FTP server **Command Prompt** windows side by side.
- From the PC 1-1 window, enter the **netstat** command.

```
C:\>netstat

Active Connections

Proto Local Address          Foreign Address         State
```

What message is displayed? Does it show any data?

```
C:\>netstat
```

```
Active Connections
```

```
Proto Local Address          Foreign Address         State
C:\>
```

No data is shown.

- f. From the **FTP** server, enter the **netstat** command.

```
Cisco Packet Tracer SERVER Command Line 1.0
C:\>netstat

Active Connections

Proto Local Address          Foreign Address         State
TCP    0.0.0.0:25              0.0.0.0:0               CLOSED
TCP    0.0.0.0:110            0.0.0.0:0               CLOSED
TCP    0.0.0.0:8443           0.0.0.0:0               CLOSED
```

What message is displayed? Does it show any data?

```
C:\>netstat
```

Active Connections

Proto	Local Address	Foreign Address	State
TCP	0.0.0.0:25	0.0.0.0:0	CLOSED
TCP	0.0.0.0:110	0.0.0.0:0	CLOSED
TCP	0.0.0.0:8443	0.0.0.0:0	CLOSED

```
C:\>
```

It shows no active connection to other devices and no listening ports.

- g. On **FTP** server, enter the **ipconfig** command to determine its IP address.

```
C:\>ipconfig

FastEthernet0 Connection: (default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address . . . . .: FE80::290:21FF:FE64:E9B9
IPv6 Address . . . . .: ::
IPv4 Address. . . . .: 192.168.75.2
Subnet Mask . . . . .: 255.255.255.0
Default Gateway . . . . .: ::
                             192.168.75.1
```

- h. From **PC 1-1**, start an FTP session with the FTP server.

```
C:\>ftp 192.168.75.2
Trying to connect...192.168.75.2
Connected to 192.168.75.2
220- Welcome to PT Ftp server
Username:
```

- i. On the **FTP** server, enter the **netstat** command.

```
C:\>netstat

Active Connections

Proto Local Address Foreign Address State
TCP 0.0.0.0:25 0.0.0.0:0 CLOSED
TCP 0.0.0.0:110 0.0.0.0:0 CLOSED
TCP 0.0.0.0:8443 0.0.0.0:0 CLOSED
TCP 192.168.75.2:21 192.168.10.3:1027 ESTABLISHED
```

What message is displayed? Is there any new information?

Yes, a new entry shows TCP 192.168.75.2:21 192.168.10.3:1025 ESTABLISHED.

Which port is the listening port and what is the status of the connection?

The listening port is TCP 21 and the TCP connection is established.

- j. From **PC 1-1**, enter **bob** as the username.

```
C:\>ftp 192.168.75.2
Trying to connect...192.168.75.2
Connected to 192.168.75.2
220- Welcome to PT Ftp server
Username:bob
331- Username ok, need password
Password:
```

- k. From the **FTP** server, enter the **netstat** command.


```
C:\>netstat

Active Connections

    Proto Local Address           Foreign Address         State
    TCP    0.0.0.0:25              0.0.0.0:0               CLOSED
    TCP    0.0.0.0:110             0.0.0.0:0               CLOSED
    TCP    0.0.0.0:8443            0.0.0.0:0               CLOSED
    TCP    192.168.75.2:21         192.168.10.3:1028       ESTABLISHED
```

Does the displayed information change?

No.

- l. From **PC 1-1**, enter **cisco123** as the password.
- m. From **PC 1-1**, enter the **dir** command.
- n. From the **FTP** server, enter the **netstat** command.

```
C:\>netstat

Active Connections

    Proto Local Address           Foreign Address         State
    TCP    0.0.0.0:25              0.0.0.0:0               CLOSED
    TCP    0.0.0.0:110             0.0.0.0:0               CLOSED
    TCP    0.0.0.0:8443            0.0.0.0:0               CLOSED
    TCP    192.168.75.2:21         192.168.10.3:1028       ESTABLISHED
    TCP    192.168.75.2:1030       192.168.10.3:1030       CLOSED
```

Does the displayed information change?

Yes. A new entry shows TCP 192.168.75.2:1030 192.168.10.3:1030 CLOSED.

What is indicated by this new entry?

A new TCP connection is opened to transfer the file names in the FTP directory and the connection is closed after the operation completes.

- o. From **PC 1-1**, enter the **put Sample2.txt** command and press **Enter**. This will upload the Sample2.txt file to the **FTP** server.

```
ftp>put Sample2.txt

Writing file Sample2.txt to 192.168.75.2:
File transfer in progress...

[Transfer complete - 43 bytes]

43 bytes copied in 0.062 secs (693 bytes/sec)
```

- p. From the **FTP** server, enter the **netstat** command.

```
C:\>netstat

Active Connections

    Proto Local Address           Foreign Address         State
    TCP    0.0.0.0:25              0.0.0.0:0               CLOSED
    TCP    0.0.0.0:110             0.0.0.0:0               CLOSED
    TCP    0.0.0.0:8443            0.0.0.0:0               CLOSED
    TCP    192.168.75.2:21         192.168.10.3:1028       ESTABLISHED
    TCP    192.168.75.2:1034       192.168.10.3:1032       CLOSING
```

Does the displayed information change?

Yes. A new entry shows:

TCP 192.168.75.2:1034 192.168.10.3:1032 CLOSING.

- q. Wait for a few seconds and then enter the **netstat** command again.

```
C:\>netstat

Active Connections

Proto Local Address          Foreign Address         State
TCP   0.0.0.0:25              0.0.0.0:0               CLOSED
TCP   0.0.0.0:110             0.0.0.0:0               CLOSED
TCP   0.0.0.0:8443            0.0.0.0:0               CLOSED
TCP   192.168.75.2:21         192.168.10.3:1028       ESTABLISHED
```

Does the displayed information change?

Yes. The “CLOSING” line is gone.

- r. From **PC 1-1**, enter the **quit** command.

```
ftp>quit

221- Service closing control connection.
```

- s. From the **FTP** server, enter the **netstat** command.

```
C:\>netstat

Active Connections

Proto Local Address          Foreign Address         State
TCP   0.0.0.0:25              0.0.0.0:0               CLOSED
TCP   0.0.0.0:110             0.0.0.0:0               CLOSED
TCP   0.0.0.0:8443            0.0.0.0:0               CLOSED
TCP   192.168.75.2:21         192.168.10.3:1033       CLOSED
```

Does the displayed information change?

Yes. Now the TCP connection between 192.168.75.2:21 and 192.168.10.2:1033 is CLOSED.

- t. From **PC 1-1**, close **Command Prompt**, and then open **Web Browser**.
u. Navigate to **192.168.75.2**.



- v. From the **FTP** server, enter the **netstat** command.

```
C:\>netstat

Active Connections

Proto Local Address          Foreign Address         State
TCP   0.0.0.0:25              0.0.0.0:0               CLOSED
TCP   0.0.0.0:110             0.0.0.0:0               CLOSED
TCP   0.0.0.0:8443            0.0.0.0:0               CLOSED
TCP   192.168.75.2:80         192.168.10.3:1034      CLOSED
```

Does the displayed information change?

Yes. A new entry shows TCP 192.168.75.2:80 192.168.10.2:1034 CLOSED.

What does this new entry indicate?

A web page request is made by the host 192.168.10.2. The web page is transmitted (displayed on the web browser of PC 1-1) and the TCP connection is closed.