

Nama : Sasmita Rachmawati

Absen : 15

## Packet Tracer - Use Diagnostic Commands

### Objectives

#### Part 1: Gather End User Device Settings

#### Part 2: Gather Information about Network Devices

#### Part 3: Diagnose Connectivity Issues

### Background / Scenario

In this Packet Tracer (PT) activity, you will use various commands to gather device information and troubleshoot device configuration and connectivity issues. Device information includes IP address, default gateway, and DNS server settings. These settings are critical to enable a device to communicate on networks and connect to the internet.

### Instructions

#### Part 1: Gather End User Device Settings


In this part, you will document the IP address settings for end devices.

##### Step 1: Document the IP address settings for HQ-Laptop-1.

- The activity opens in the **HQ** cluster. The **Wiring Closet** is the tall, black chassis in the bottom left corner of the first floor. Locate all the devices on the first floor: PCs **1-1**, **1-2**, **1-3**, and **1-4**; printer **FL-1P**; and **HQ-Laptop-1**.
- Click **HQ-Laptop-1** > **Desktop** tab > **Command Prompt**.
- Enter the **ipconfig** command.

### Questions:

Which IPv4 address is displayed for the **Wireless0 Connection**? 192.168.50.4



```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

Wireless0 Connection:(default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: FE80::20A:F3FF:FEE4:EEAA
IPv6 Address.....: ::
IPv4 Address.....: 192.168.50.4
Subnet Mask.....: 255.255.255.0
Default Gateway.....: ::
                        192.168.50.1
```

If the IPv4 address is in the 169.254.0.0/16 range, what method is being used to assign IPv4 addresses? Why is the laptop assigned an IPv4 address in the 169.254.0.0/16 range?

- This indicates that the device cannot obtain an address from the DHCP server. However in my packet tracer experiment the IPv4 is at 192.168.50.0 which is used for automatic private IP addressing (APIPA).

If the IPv4 address is in the 169.254.0.0/16, wait a few seconds and repeat the **ipconfig** command.

Questions:

When the IPv4 address is no longer from 169.254.0.0/16 range, what is the IP addressing information displayed? Record your answers in the table below.

```

Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

Wireless0 Connection:(default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address.....: FE80::20A:F3FF:FEE4:EEAA
IPv6 Address.....: ::
IPv4 Address.....: 192.168.50.4
Subnet Mask.....: 255.255.255.0
Default Gateway.....: ::
                        192.168.50.1
  
```

Do you see a DNS server address? Explain.

- The **ipconfig** command does not report the DNS server address.

d. Enter the **ipconfig /all** command.

Question:

Do you see the DNS server address? What is it? 10.2.0.125

```

C:\>ipconfig /all

Wireless0 Connection:(default port)

Connection-specific DNS Suffix...:
Physical Address.....: 000A.F3E4.EEAA
Link-local IPv6 Address.....: FE80::20A:F3FF:FEE4:EEAA
IPv6 Address.....: ::
IPv4 Address.....: 192.168.50.4
Subnet Mask.....: 255.255.255.0
Default Gateway.....: ::
                        192.168.50.1

DHCP Servers.....: 192.168.50.1
DHCPv6 IAID.....: 1781104527
DHCPv6 Client DUID.....: 00-01-00-01-43-B9-1D-8A-00-0A-F3-E4-EE-AA
DNS Servers.....: ::
                        10.2.0.125
  
```

## Step 2: Document the IP address settings for Net-Admin.

- Click **Wiring Closet > Net-Admin > Desktop tab > Command Prompt**.
- Enter the **ipconfig /all** command.

Question:

What is the IP addressing information displayed under the FastEthernet0 interface? Record your answers in the table below.

```

Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig /all

FastEthernet0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Physical Address.....: 0001.C910.22D6
    Link-local IPv6 Address.....: FE80::201:C9FF:FE10:22D6
    IPv6 Address.....: ::
    IPv4 Address.....: 192.168.99.9
    Subnet Mask.....: 255.255.255.0
    Default Gateway.....: ::
                                192.168.99.1
    DHCP Servers.....: 0.0.0.0
    DHCPv6 IAID.....:
    DHCPv6 Client DUID.....: 00-01-00-01-67-A3-E9-BD-00-01-C9-10-22-D6
    DNS Servers.....: ::
                                10.2.0.125

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Physical Address.....: 0001.649E.81BB
    Link-local IPv6 Address.....: ::
    IPv6 Address.....: ::
    IPv4 Address.....: 0.0.0.0
    Subnet Mask.....: 0.0.0.0
    Default Gateway.....: ::
                                0.0.0.0
    DHCP Servers.....: 0.0.0.0
    DHCPv6 IAID.....:
    DHCPv6 Client DUID.....: 00-01-00-01-67-A3-E9-BD-00-01-C9-10-22-D6
    DNS Servers.....: ::
                                10.2.0.125

C:\>
  
```

FastEthernet0	IP Addressing Information
Physical Address	<b>0001.C910.22D6</b>
Link-local IPv6 Address	<b>FE80::201::C9FF::FE10:22D^</b>
IPv6 Address	<b>::</b>
IPv4 Address	<b>192.168.99.9</b>
Subnet Mask	<b>255.255.255.0</b>
Default Gateway	<b>192.168.99.1</b>
DNS Servers	<b>10.2.0.125</b>

## Part 2: Gather Information about Network Devices

In this part, you will document information about the link to ISP. You will then document the IP addressing information for all the end devices in HQ and discover that devices belong to different virtual local area networks (VLANs).

### Step 1: Gather network connection information about the link between HQ and ISP.

The **HQ-Edge** router is the router between the HQ network and the ISP. We need to identify the upstream device information located in the ISP.

- In the **Wiring Closet** left rack, click **HQ-Edge > CLI** tab.
- Press **Enter** to get the **HQ-Edge>** prompt, and then enter the **enable** command.
- Enter the **show ip route | begin Gateway** command.

```
HQ-Edge>enable
HQ-Edge#show ip route | begin Gateway
Gateway of last resort is 0.0.0.0 to network 0.0.0.0

    10.0.0.0/8 is variably subnetted, 6 subnets, 4 masks
O       10.0.0.0/29 [110/2] via 10.0.0.49, 00:08:20, GigabitEthernet0/0/0
O       10.0.0.32/29 [110/2] via 10.0.0.49, 00:08:20, GigabitEthernet0/0/0
C       10.0.0.48/29 is directly connected, GigabitEthernet0/0/0
L       10.0.0.50/32 is directly connected, GigabitEthernet0/0/0
O       10.0.3.0/24 [110/3] via 10.0.0.49, 00:08:20, GigabitEthernet0/0/0
O       10.2.0.0/16 [110/2] via 10.0.0.49, 00:08:20, GigabitEthernet0/0/0
    192.168.10.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.10.0/24 is directly connected, GigabitEthernet0/0/1.10
L       192.168.10.1/32 is directly connected, GigabitEthernet0/0/1.10
    192.168.20.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.20.0/24 is directly connected, GigabitEthernet0/0/1.20
L       192.168.20.1/32 is directly connected, GigabitEthernet0/0/1.20
    192.168.30.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.30.0/24 is directly connected, GigabitEthernet0/0/1.30
L       192.168.30.1/32 is directly connected, GigabitEthernet0/0/1.30
    192.168.50.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.50.0/24 is directly connected, GigabitEthernet0/0/1.50
L       192.168.50.1/32 is directly connected, GigabitEthernet0/0/1.50
    192.168.75.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.75.0/24 is directly connected, GigabitEthernet0/0/1.75
L       192.168.75.1/32 is directly connected, GigabitEthernet0/0/1.75
    192.168.99.0/24 is variably subnetted, 2 subnets, 2 masks
C       192.168.99.0/24 is directly connected, GigabitEthernet0/0/1.99
L       192.168.99.1/32 is directly connected, GigabitEthernet0/0/1.99
S*    0.0.0.0/0 is directly connected, GigabitEthernet0/0/0

HQ-Edge#
```

Questions:

What is the address for the gateway of last resort (or default gateway)? **0.0.0.0**

Why is the next hop address not displayed? **It is not explicitly configured**

- Enter the **show running-config | begin ip route** command.

```

HQ-Edge#show running-config | begin ip route
ip route 0.0.0.0 0.0.0.0 GigabitEthernet0/0/0
!!
ip flow-export version 9
!
!
ip access-list standard NAT-PERMIT
 permit 192.168.10.0 0.0.0.255
 permit 192.168.20.0 0.0.0.255
 permit 192.168.99.0 0.0.0.15
 permit 192.168.75.0 0.0.0.7
ip access-list standard ADMIN-ONLY
 permit 192.168.99.0 0.0.0.255
 deny any
access-list 101 permit ip 192.168.10.0 0.0.0.255 10.0.3.0 0.0.0.255
access-list 101 permit ip 192.168.20.0 0.0.0.255 10.0.3.0 0.0.0.255
access-list 101 permit ip 192.168.75.0 0.0.0.255 10.0.3.0 0.0.0.255
access-list 101 permit ip 192.168.99.0 0.0.0.255 10.0.3.0 0.0.0.255
access-list 101 permit icmp any 10.0.3.0 0.0.0.255
ip access-list extended NAT-NOVPN
 permit ip 192.168.0.0 0.0.255.255 10.2.0.0 0.0.255.255
 permit ip 192.168.0.0 0.0.255.255 10.1.0.0 0.0.255.255
 permit ip 192.168.0.0 0.0.255.255 192.168.0.0 0.0.0.255
 permit ip 192.168.0.0 0.0.255.255 172.0.0.0 0.0.255.255
!
!
!
!
!
!
line con 0
!
line aux 0
!
line vty 0 4
 login
!
!
!
end

```

Question:

How is the default route configured? Does it use the next hop address? **It is configured with the exit interface instead of next hop address.**

e. Enter the **show cdp neighbors detail** command.

```

HQ-Edge#show cdp neighbors detail

Device ID: ISP
Entry address(es):
  IP address : 10.0.0.49
Platform: cisco PT1000, Capabilities: Router
Interface: GigabitEthernet0/0/0, Port ID (outgoing port): GigabitEthernet1/0
Holdtime: 160

Version :
Cisco Internetwork Operating System Software
IOS (tm) PT1000 Software (PT1000-I-M), Version 12.2(28), RELEASE SOFTWARE (fc5)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2005 by cisco Systems, Inc.
Compiled Wed 27-Apr-04 19:01 by miwang

advertisement version: 2
Duplex: full

HQ-Edge#

```

Questions:

What is the IPv4 address of the next hop (ISP) address? **10.0.0.49**

Which port on the ISP router is connected to **HQ-Edge**? **GigabitEthernet1/0**

What IOS version is used on the ISP router? **IOS™ PT1000 Software (PT1000-I-M), Version 12.2(28)**

f. Enter the **ping 10.0.0.49** command.

```
HQ-Edge#ping 10.0.0.49
```

```
Type escape sequence to abort.
```

```
Sending 5, 100-byte ICMP Echos to 10.0.0.49, timeout is 2 seconds:
```

```
!!!!
```

```
Success rate is 100 percent (5/5), round-trip min/avg/max = 0/0/0 ms
```

```
HQ-Edge#
```

g. Enter the **show arp** command.

```
HQ-Edge#show arp
```

Protocol	Address	Age (min)	Hardware Addr	Type	Interface
Internet	10.0.0.49	12	0060.2FEE1.903B	ARPA	GigabitEthernet0/0/0
Internet	10.0.0.50	-	0000.0C99.CB04	ARPA	GigabitEthernet0/0/0

```
HO-Edge#
```

Question:

What is the MAC address of the interface on the **ISP** router that is connected to **HQ-Edge**?  
**0060.2FEE1.903b**

h. Close **HQ-Edge** and exit the **Wiring Closet**.

**Step 2: Gather network connection information about the devices in HQ.**

- a. From **1-1**, **1-2**, **1-3**, **1-4**, **FL-1P**, and **HQ-Laptop-1**, use the **ipconfig** command to find their IPv4 addresses and Default Gateways.

- 1-1

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

FastEthernet0 Connection: (default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address . . . . . : FE80::201:C7FF:FE54:EB5
IPv6 Address . . . . . : ::
IPv4 Address . . . . . : 192.168.10.5
Subnet Mask . . . . . : 255.255.255.0
Default Gateway . . . . . : ::
                          192.168.10.1
```

- 1-2

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

FastEthernet0 Connection: (default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address . . . . . : FE80::202:4AFF:FE8A:D20E
IPv6 Address . . . . . : ::
IPv4 Address . . . . . : 192.168.10.3
Subnet Mask . . . . . : 255.255.255.0
Default Gateway . . . . . : ::
                          192.168.10.1
```

- 1-3

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

FastEthernet0 Connection: (default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address . . . . . : FE80::201:C9FF:FE9:887E
IPv6 Address . . . . . : ::
IPv4 Address . . . . . : 192.168.20.3
Subnet Mask . . . . . : 255.255.255.0
Default Gateway . . . . . : ::
                          192.168.20.1
```

- 1-4

```
Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

FastEthernet0 Connection: (default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address . . . . . : FE80::201:97FF:FEBA:7BB0
IPv6 Address . . . . . : ::
IPv4 Address . . . . . : 192.168.20.2
Subnet Mask . . . . . : 255.255.255.0
Default Gateway . . . . . : ::
                          192.168.20.1
```

- FL-1P

Global Settings

Display Name: FL-1P

Gateway/DNS IPv4

☒ DHCP

☐ Static

Default Gateway: 192.168.50.1

DNS Server: 10.2.0.125

IP Configuration


☒ DHCP

☐ Static

IPv4 Address: 192.168.50.2

Subnet Mask: 255.255.255.0

- HQ-Laptop-1



```

Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

Wireless0 Connection:(default port)

Connection-specific DNS Suffix...:
Link-local IPv6 Address...: FE80::20A:F3FF:FEE4:EEAA
IPv6 Address...: ::
IPv4 Address...: 192.168.50.4
Subnet Mask...: 255.255.255.0
Default Gateway...: ::
                  192.168.50.1
  
```

Device	IPv4 Address	Default Gateway
1-1	192.168.10.5	192.168.10.1
1-2	192.168.10.3	192.168.10.1
1-3	192.168.20.3	192.168.20.1
1-4	192.168.20.2	192.168.20.1
FL-1P	192.168.50.2	192.168.50.1
HQ-Laptop-1	192.168.50.4	192.168.50.1

- b. From PC **1-1**, open **Command Prompt**, and then enter the **arp -a** command.

Question:

What information is displayed?

- **No arp entries found**

- c. Use the **ping** command to ping **1-2**, **1-3**, **1-4**, **FL-1P**, and **HQ-Laptop-1**.

- d. Enter the **arp -a** command.

Questions:

What information is displayed? **No arp entries found**

Why do the entries in the ARP table not contain information about devices in the 192.168.20.0 and 192.168.50.0 networks while the ping is successful?

- **Because 192.168.20.0/24, and 192.168.50.0/24 are on different VLANs**

- e. To find the route a packet takes to each the DNS server, enter the **tracert 10.2.0.125** command.

Question:

What information is displayed?

```
C:\>tracert 10.2.0.125

Tracing route to 10.2.0.125 over a maximum of 30 hops:

  1  0 ms    0 ms    0 ms    192.168.10.1
  2  0 ms    0 ms    0 ms    10.0.0.49
  3  *        0 ms    0 ms    10.2.0.125

Trace complete.
```

How many routers, or hops, are between PC 1-1 and the DNS server? **2**

### Part 3: Diagnose Connectivity Issues


In this part, you will use a variety of diagnostic commands and techniques. You will use the **nslookup** command to query a DNS server and troubleshoot a DNS database. You will then diagnose why a ping fails but web access is successful. Finally, you will use the **netstat** command to discover which ports are listening on the target device.

#### Step 1: Test a URL to investigate a connectivity issue.

- On PC **1-1**, close the **Command Prompt**, and then click **Web Browser**.
- Enter the URL **test.ptsecurity.com**.

Question:


Does the web page display? If not, what is the message?



- Enter the IP address **192.168.75.2**.

Questions:

Does the web page display?



Why does the web page display by using the IP address but not the domain name?

- The PC cannot resolve the domain name to the IP address.

#### Step 2: Use the nslookup command to verify DNS service.

- Close **Web Browser**, and then click **Command Prompt**.
- Enter the **ping test.ptsecurity.com** command.



Questions:

What message is displayed?

```
C:\>ping test.ptsecurity.com
Ping request could not find host test.ptsecurity.com. Please check the name and try again.
```

What does the message indicate?

- **The DNS entry is not in the database of the DNS server.**
- c. Enter the **nslookup test.ptsecurity.com** command.

Question:

What message is displayed?

```
C:\>nslookup test.ptsecurity.com

Server: [10.2.0.125]
Address: 10.2.0.125
*** UnKnown can't find test.ptsecurity.com: Non-existent domain.

C:\>|
```

Which server is the default DNS server? **10.2.0.125**

- d. The **nslookup** command supports the use of alternate DNS server. Enter the **nslookup /?** command to learn options available for the command.
- e. Enter the **nslookup test.ptsecurity.com 192.168.99.3** command and press **Enter**.

**Note:** Packet Tracer may take several seconds to converge.

Questions:

What message is displayed?

```
C:\>nslookup test.ptsecurity.com 192.168.99.3

Server: [192.168.99.3]
Address: 192.168.99.3
DNS request timed out.
        timeout was 15000 milli seconds.

Server: [192.168.99.3]
Address: 192.168.99.3

Non-authoritative answer:
Name:   test.ptsecurity.com
Address: 192.168.75.2
```

In Step 2c, why is the domain name unable to be resolved?

- **When a domain name is entered in the URL box, the PC is trying to resolve it through the default DNS server. In this case, the default DNS server does not contain the information in its database.**

**Step 3: Use output from the ping command to diagnose connectivity issues.**

- a. Enter the **ping mail.cybercloud.com** command.

Questions:

What message is displayed?

```
C:\>ping mail.cybercloud.com

Pinging 172.19.0.4 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 172.19.0.4:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```

What information is indicated by the message?

- **The DNS name resolution is successful. However, the ping failed. Possible reasons are that the host is inactive or the ICMP echo/echo-reply is disabled on the host.**

b. Enter the **ping www.ptsecurity.com** command.

Questions:

What message is displayed?

```
C:\>ping www.ptsecurity.com

Pinging 10.0.0.3 with 32 bytes of data:

Request timed out.
Request timed out.
Reply from 10.0.0.3: Destination host unreachable.
Reply from 10.0.0.3: Destination host unreachable.

Ping statistics for 10.0.0.3:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>
```

What information is indicated by the message?

- **There is a firewall in the path that blocks the ping to the destination.**

c. Close the **Command Prompt**, open **Web Browser**, and then navigate to **www.ptsecurity.com**.

Questions:

Does the web page display?



What conclusion can be drawn?

- **The web host is running; however, the ping to the web server is blocked.**

**Step 4: Use the netstat command to find active and listening ports.**

- Close **Web Browser**, and reopen **Command Prompt**.
- In **HQ**, click the **Wiring Closet**
- From the right rack, click the **FTP server** > **Desktop** tab > **Command Prompt**.
- Arrange the **PC 1-1** and **FTP server Command Prompt** windows side by side.
- From the **PC 1-1** window, enter the **netstat** command.

Questions:

What message is displayed? Does it show any data? **No data show**

```
C:\>netstat


Active Connections

    Proto Local Address           Foreign Address         State
C:\>
```

- From the **FTP server**, enter the **netstat** command.

Question:

What message is displayed? Does it show any data? **Yes**



The screenshot shows the FTP server's desktop environment with the 'Desktop' tab selected. A 'Command Prompt' window is open, displaying the output of the 'netstat' command. The output shows three active connections, all in a 'CLOSED' state.

```
Cisco Packet Tracer SERVER Command Line 1.0
C:\>netstat

Active Connections

    Proto Local Address           Foreign Address         State
TCP    0.0.0.0:25              0.0.0.0:0               CLOSED
TCP    0.0.0.0:110             0.0.0.0:0               CLOSED
TCP    0.0.0.0:8443            0.0.0.0:0               CLOSED
C:\>
```

- On **FTP server**, enter the **ipconfig** command to determine its IP address.

```
C:\>ipconfig

FastEthernet0 Connection:(default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: FE80::290:21FF:FE64:E9B9
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 192.168.75.2
    Subnet Mask . . . . .: 255.255.255.0
    Default Gateway . . . . .: ::
                                   192.168.75.1
C:\>
```

- From **PC 1-1**, start an **FTP** session with the **FTP server**.

```
C:\>ftp 192.168.75.2
Trying to connect...192.168.75.2
Connected to 192.168.75.2
220- Welcome to PT Ftp server
Username:
```

i. On the **FTP** server, enter the **netstat** command.

*Questions:*

What message is displayed? Is there any new information?

```
C:\>netstat

Active Connections

Proto Local Address           Foreign Address         State
TCP   0.0.0.0:25              0.0.0.0:0              CLOSED
TCP   0.0.0.0:110             0.0.0.0:0              CLOSED
TCP   0.0.0.0:8443            0.0.0.0:0              CLOSED
TCP   192.168.75.2:21         192.168.10.5:1027      ESTABLISHED
C:\>
```

- Yes, a new entry shows **TCP 192.168.75.2:21 192.168.10.5:1025 ESTABLISHED**.

Which port is the listening port and what is the status of the connection?

- The listening port is **TCP 21** and the **TCP** connection is established.

j. From **PC 1-1**, enter **bob** as the username.

k. From the **FTP** server, enter the **netstat** command.

*Question:*

Does the displayed information change? **No**

l. From **PC 1-1**, enter **cisco123** as the password.

m. From **PC 1-1**, enter the **dir** command.

```
C:\>ftp 192.168.75.2
Trying to connect...192.168.75.2
Connected to 192.168.75.2
220- Welcome to PT Ftp server
Username:bob
331- Username ok, need password
Password:
230- Logged in
(passive mode On)
ftp>dir

Listing /ftp directory from 192.168.75.2:
ftp>
```

n. From the **FTP** server, enter the **netstat** command.

*Questions:*

Does the displayed information change? **No**

```
C:\>netstat

Active Connections

Proto Local Address           Foreign Address         State
TCP   0.0.0.0:25              0.0.0.0:0              CLOSED
TCP   0.0.0.0:110             0.0.0.0:0              CLOSED
TCP   0.0.0.0:8443            0.0.0.0:0              CLOSED
TCP   192.168.75.2:21         192.168.10.5:1027      ESTABLISHED
C:\>
```

What is indicated by this new entry? **No new entries**

o. From **PC 1-1**, enter the **put Sample2.txt** command and press **Enter**. This will upload the **Sample2.txt** file to the **FTP** server.

```
ftp>put Sample2.txt

Writing file Sample2.txt to 192.168.75.2:
File transfer in progress...

[Transfer complete - 43 bytes]

43 bytes copied in 0.075 secs (573 bytes/sec)
ftp>
```

p. From the **FTP** server, enter the **netstat** command.

*Questions:*

Does the displayed information change? **No**

q. Wait for a few seconds and then enter the **netstat** command again.

*Question:*

Does the displayed information change? **No**

```
C:\>netstat

Active Connections

Proto Local Address           Foreign Address         State
TCP   0.0.0.0:25               0.0.0.0:0               CLOSED
TCP   0.0.0.0:110              0.0.0.0:0               CLOSED
TCP   0.0.0.0:8443             0.0.0.0:0               CLOSED
TCP   192.168.75.2:21          192.168.10.5:1027      ESTABLISHED
C:\>
```

r. From **PC 1-1**, enter the **quit** command.

```
ftp>quit

221- Service closing control connection.
C:\>
```

s. From the **FTP** server, enter the **netstat** command.

*Question:*

Does the displayed information change?

- **Yes. Now the TCP connection between 192.168.75.2:21 and 192.168.10.5:1027 is CLOSED.**

```
C:\>netstat

Active Connections

Proto Local Address           Foreign Address         State
TCP   0.0.0.0:25               0.0.0.0:0               CLOSED
TCP   0.0.0.0:110              0.0.0.0:0               CLOSED
TCP   0.0.0.0:8443             0.0.0.0:0               CLOSED
C:\>
```

t. From **PC 1-1**, close **Command Prompt**, and then open **Web Browser**.

u. Navigate to **192.168.75.2**.



v. From the **FTP** server, enter the **netstat** command.

*Questions:*

Does the displayed information change? **No**

```
C:\>netstat

Active Connections

Proto Local Address           Foreign Address         State
TCP   0.0.0.0:25              0.0.0.0:0               CLOSED
TCP   0.0.0.0:110             0.0.0.0:0               CLOSED
TCP   0.0.0.0:8443            0.0.0.0:0               CLOSED
C:\>
```

What does this new entry indicate? **No new entries**