



Manage storage

SnapCenter Plug-in for VMware vSphere 4.8

NetApp

February 17, 2023

This PDF was generated from https://docs.netapp.com/us-en/sc-plugin-vmware-vsphere/scpivs44_add_storage_01.html on February 17, 2023. Always check docs.netapp.com for the latest.

Table of Contents

- Manage storage 1
 - Add storage 1
 - Manage storage systems 3
 - Modify the configured storage timeout 5

Manage storage

Add storage

Before you can backup or restore VMs, you must add storage clusters or storage VMs. Adding storage enables the SnapCenter Plug-in for VMware vSphere to recognize and manage backup and restore operations in vCenter.

- Which GUI to use

Use the VMware vSphere client to add storage.

- Large LUNs

SnapCenter Plug-in for VMware vSphere 4.5 and later supports datastores on large LUN sizes up to 128 TB on ASA aggregates. For large LUNs, SnapCenter only supports thick provisioned LUNs to avoid latency.

- VMware virtual volumes (vVols)

You must first add the vVols storage system to ONTAP tools for VMware vSphere and then add the vVols storage system to SnapCenter Plug-in for VMware vSphere.

For more information, see [ONTAP tools for VMware vSphere](#)

Before you begin

The ESXi server, the SnapCenter VMware plug-in, and each vCenter must be synchronized to the same time. If you try to add storage but the time settings for your vCenters are not synchronized, the operation might fail with a Java certificate error.

About this task

The SnapCenter VMware plug-in performs backup and restore operations on directly connected storage VMs and on storage VMs in a storage cluster.



If you are using the SnapCenter VMware plug-in to support application-based backups on VMDKs, then you must use the SnapCenter GUI to enter storage authentication details and register storage systems.

- For vCenters in linked mode, you must separately add storage systems to each vCenter.
- Names for storage VMs must resolve to management LIFs.

If you added etc host entries for storage VM names in SnapCenter, you must verify that they are also resolvable from the virtual appliance.

If you add a storage VM with a name that cannot resolve to the management LIF, then scheduled backup jobs fail because the plug-in is unable to discover any datastores or volumes on that storage VM. If this occurs, either add the storage VM to SnapCenter and specify the management LIF or add a cluster that contains the storage VM and specify the cluster management LIF.

- Storage authentication details are not shared between multiple instances of the SnapCenter VMware plug-in or between Windows SnapCenter Server and the SnapCenter plug-in on vCenter.

Steps

1. In the left Navigator pane of the vSphere client, click **Storage Systems**.
2. On the Storage Systems page, click **+ Add**.
3. In the **Add Storage System** wizard, enter the basic storage VM or cluster information as listed in the following table:

For this field...	Do this...
Storage system	Enter the FQDN or IP address of a storage cluster or storage VM. The SnapCenter VMware plug-in does not support multiple storage systems with the same name on different clusters. Each storage system that is supported by SnapCenter must have a unique data LIF IP address.
Platform	Select the platform.
Authentication Method	Select either Credentials or Certificate. Two types of certificates are supported: - CA signed certificate - Self signed certificate
Username	This field is visible when you select Credentials as your authentication method. Enter the ONTAP username that is used to log on to the storage VM.
Password	This field is visible when you select Credentials as your authentication method. Enter the storage VM logon password.
Certificate	This field is visible when you select Certificate as your authentication method. Browse to select the certificate file.
Private Key	This field is visible when you select Certificate as your authentication method. Browse to select the private Key file.
Protocol	Select storage protocol.
Port	Select port 443 (the default) or port 80 to communicate with vCenter. Port 443 is used for communication between the storage VM host for SnapCenter Plug-in for VMware vSphere and vCenter when performing VM and datastore backup and restore operations. You must select the default port 443 if you plan to protect vVol VMs.
Timeout	Enter the number of seconds vCenter should wait before timing out the operation. The default is 60 seconds.

For this field...	Do this...
Preferred IP	If the storage VM has more than one management IP address, check this box and enter the IP address that you want SnapCenter to use. Note: Do not use square brackets ([]) when entering the IP address.
Event Management System(EMS) & AutoSupport Setting	If you want to send EMS messages to the storage system syslog or if you want to have AutoSupport messages sent to the storage system for applied protection, completed restore operations, or failed operations, select the appropriate checkbox. Select the Send AutoSupport Notification for failed operations to storage system checkbox and the Log SnapCenter Server events to syslog checkbox to enable AutoSupport notifications.
Log SnapCenter Server events to syslog	Check the box to log events for the SnapCenter VMware plug-in.
Send AutoSupport Notification for failed operation to storage system	Check the box if you want AutoSupport notification for failed data protection jobs. You must also enable AutoSupport on the storage VM and configure the AutoSupport email settings.

4. Click **Add**.

If you added a storage cluster, all storage VMs in that cluster are automatically added. Automatically added storage VMs (sometimes called “implicit” storage VMs) are displayed on the cluster summary page with a hyphen (-) instead of a username. Usernames are displayed only for explicit storage entities.

Manage storage systems

Before you can back up or restore VMs or datastores using the VMware vSphere client, you must add the storage.

Modify storage VMs


You can use the VMware vSphere client to modify the configurations of clusters and storage VMs that are registered in SnapCenter Plug-in for VMware vSphere and used for VM data protection operations.

If you modify a storage VM that was automatically added as part of a cluster (sometimes called an implicit storage VM), then that storage VM changes to an explicit storage VM and can be separately deleted without changing the rest of the storage VMs in that cluster. On the Storage Systems page, the username is displayed as N/A when the authentication method is through the certificate; usernames are displayed only for explicit storage VMs in the cluster list and have the ExplicitSVM flag set to true. All storage VMs are always listed under the associated cluster.



If you added storage VMs for application-based data protection operations using the SnapCenter GUI, you must use the same GUI to modify those storage VMs.

Steps

1. In the left Navigator pane of the SCV plug-in, click **Storage Systems**.
2. On the **Storage Systems** page, select the storage VM to be modified and then click  **Edit**.
3. On the **Edit Storage System** window, enter the new values, and then click **Update** to apply the changes.

Edit Storage System ✕

Storage System	sti104-vsimg-ucs555u-cm.cti.gdl.englab.netaj	
Platform	FAS	
Authentication Method	<input checked="" type="radio"/> Credentials <input type="radio"/> Certificate	
Username	admin	
Password	Storage system password	
Protocol	HTTPS	
Port	443	
Timeout	60	Seconds
<input type="checkbox"/> Preferred IP	Preferred IP	
Event Management System(EMS) & AutoSupport Setting		
<input type="checkbox"/> Log Snapcenter server events to syslog		
<input type="checkbox"/> Send AutoSupport Notification for failed operation to storage system		

CANCEL UPDATE

Remove storage VMs

You can use the VMware vSphere client to remove storage VMs from the inventory in vCenter.



If you added storage VMs for application-based data protection operations using the SnapCenter GUI, you must use the same GUI to modify those storage VMs.

Before you begin

You must unmount all datastores in the storage VM before you can remove the storage VM.

About this task

If a resource group has backups that reside on a storage VM that you remove, then subsequent backups for that resource group fail.

Steps

1. In the left Navigator pane of the SCV plug-in, click **Storage Systems**.
2. On the **Storage Systems** page, select the storage VM to be removed and then click **Delete**.
3. In the **Remove Storage System** confirmation box, check the box for **Delete storage system(s)** and then click **Yes** to confirm.

Note: Only ESXi 7.0U1 and later releases are supported.

[Restart the VMware vSphere client service.](#)

Modify the configured storage timeout

Even though backups have run successfully in the past, they might start failing when the time that the SnapCenter Plug-in for VMware vSphere must wait for the storage system exceeds the configured timeout period. If this condition occurs, you can increase the configured timeout.

You might encounter the error `Unable to discover resources on SCV: Unable to get storage details for datastore <xxx>...`

Steps

1. In the VMware vSphere client, click **Storage Systems**.
2. On the Storage Systems page, select the storage system to be modified and click **Edit**.
3. In the Timeout field, increase the number of seconds.



180 seconds is recommended for large environments.

Copyright information

Copyright © 2023 NetApp, Inc. All Rights Reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

LIMITED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (b)(3) of the Rights in Technical Data -Noncommercial Items at DFARS 252.227-7013 (FEB 2014) and FAR 52.227-19 (DEC 2007).

Data contained herein pertains to a commercial product and/or commercial service (as defined in FAR 2.101) and is proprietary to NetApp, Inc. All NetApp technical data and computer software provided under this Agreement is commercial in nature and developed solely at private expense. The U.S. Government has a non-exclusive, non-transferrable, nonsublicensable, worldwide, limited irrevocable license to use the Data only in connection with and in support of the U.S. Government contract under which the Data was delivered. Except as provided herein, the Data may not be used, disclosed, reproduced, modified, performed, or displayed without the prior written approval of NetApp, Inc. United States Government license rights for the Department of Defense are limited to those rights identified in DFARS clause 252.227-7015(b) (FEB 2014).

Trademark information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.