



Proteus VR template

Latest Version: 3.2

Latest release August 8, 2017

Features


- A heavily-modified version of Epic's VR Template plus:
 - 3 fully animated controllers meshes: Hands, Oculus Touch controllers and HTC Vive controllers
 - Can be controlled with Oculus Touch or HTC Vive controllers, and support for Oculus remote
 - Full input mapping
 - Control over controllers opacity, scale, HTC Vive controllers skins, Avatar color
 - Function to spawn poles at the 4 corners of the Oculus Guardian or SteamVR chaperone limits
 - Optimizations for Oculus Rift and HTC Vive HMDs
 - "Ghost Mode" with gamepad
 - Avatar head
 - Rumble functions adapted to work with Touch & Vive
 - UI interactions, VR keyboard
 - Fade out vision when head goes through objects with VRCollision enabled
 - Skeletal socket use when grabbing objects
 - Vive Tracker tracking
 - Oculus Avatars compatible
 - "VR Essential Kit" compatible
 - Network and single player mode
 - Works single player, or multiplayer via LAN, Steam or Oculus Network
 - Direct IP Connect
 - Oculus Direct Connect
 - VOIP

What's new in version 3.2?


- Many bugs fixed, extensively tested, single & multiplayer + Vive trackers
- 2 versions: Unreal 4.16.3 and 4.17.0

What are the main difference between the templates in 4.16.3 and 4.17.0?

1) Get HMD Device Name returns a different name (Oculus only):




4.16




4.17


2) The command vr.MirrorMode has been replaced by Set Spectator Screen Mode:




4.16




4.17



3) Vive Trackers are not of “invalid” type but now of “other” type



4.16



4.17

Known bugs

Oculus only, and only in UE 4.17.0: When starting game, the center of playground is wrongly and automatically set to HMD 2D position. This will affect player position inside his playground, as well as teleport position. This bug has been reported, is not encountered with Vive nor version 4.16.3. Topic at <https://answers.unrealengine.com/questions/677881/oculus-center-of-play-area-wrongly-assigned-to-hmd.html>

Extra Sphere collision is shown when using debug shapes including the debug line for the widget interaction component. This is an issue currently related to the 4.16.1 version. By disabling Instanced Stereo the bug goes away. This has been logged as UE-44947 at <https://issues.unrealengine.com/issue/UE-44947> .

VR Essential Kit won't work with clients in multiplayer mode. I'll have to review/rethink @jamis 's excellent work to enable interactions with clients.

Physics objects: It's normal to experience client-side lag on physics objects (i.e. Interactive Objects). Many tricks exist to fix that problem; search for “multiplayer physics objects”. This would be an entire different topic and is not specifically related to VR.



Let's begin with some quick Q&A

So, what this is about?

This template consists of HTC Vive and Oculus Rift compatible pawn and settings, ready to drop in your single or multiplayer app. So what you can do is choose the features you want, and build yourself/modify a pawn based on the functionalities you need.

Source material

- Epic VR template
- Epic Twitch on Steam blueprints
- All other meshes, animations and blueprints are from Proteus

Which HMD works with the template?

The template is optimized for the HTC Vive and Oculus Rift with Vive or Touch controllers w/wo gamepad

Which Unreal Engine 4 version works with the template?

The template has been developed and tested with Unreal Engine 4.16.3 and 4.17.0


Which Steam / Oculus version is compatible with it?

UE4.16 is natively compatible with Steam SDK 1.39 and Oculus SDK 1.12

- UE4.17 is natively compatible with Steam SDK 1.39 Open "Proteus.uproject"
- Inside the editor, right-click on the folder "Proteus_Multi" and select Migrate
- Migrate everything inside the folder to your project, inside the folder your project/Content/

How can I install it?

- Files can be found at <https://1drv.ms/f/s!Av77lIxt2OY0XGGW8UDwykohjuT>
- GitHub version at <https://github.com/ProteusVR/ProteusTemplate> (you need to be logged to Github to open the link)
- Main infos found in the forum at <https://forums.unrealengine.com/showthread.php?133957-Single-Multiplayer-Touch-amp-Vive-Proteus-blueprint-only-Template>
- **To install as a template**, just unzip into the appropriate templates directory like C:\Program Files\Unreal Engine[Version]\Templates for launcher version or [ForkLocation]\UE4\Templates for source version. Launch a new project, and you'll find it in the blueprint section.
- **To open as a project file**, open the project with the launcher or directly from the .uproject file.




How can I install it in my project?

In the template

- Open “Proteus.uproject”
- Inside the editor, right-click on the folder “Proteus_Multi” and select Migrate
- Migrate everything inside the folder to your project, inside the folder your project/Content/

In your project

- If needed, adjust Project settings (see “[What are the best Project Settings for VR?](#)”)
- Ensure that ProjectSettings/Maps & Mode/Game Instance Class/GameInfoInstance is selected
- Select your starting map as Editor Starting Map and Game Default Map
- Select MainMenuGM as GameMode
- Don’t forget to put a navmesh bound volume to allow teleportation!
- Pawn will spawn at playerstart (placed on the floor) and will teleport on navmesh
- Set a VR Collision preset in Project Settings/Engine/Collision/Preset
- In the control panel found in MainMenuPC, select your options



What is the default input mapping for the Oculus Rift Touch Controllers?

- **Both controllers**
 - Thumbstick directions / Controller orientation: Playground rotation before teleportation
 - Index Trigger: Grab / Release
- **Right Controller**
 - A Button: Teleport
 - B Button: UI Interaction
- **Left Controller**
 - Thumbstick button: VR keyboard
 - X Button: Teleport
 - Y Button: Guardian poles on/off

What is the default input mapping for the Vive controllers?

- **Both controllers**
 - Trackpad directions / Controller orientation: Playground rotation before teleportation
 - Trackpad release: Teleport
 - Trigger: Grab / Release
- **Right Controller**
 - Menu Button: UI Interaction
- **Left Controller**
 - Left or Right Grab Button: VR keyboard
 - Menu Button: Chaperone poles on/off

What is the input mapping for the Xbox One gamepad?

- Primary (left) thumbstick: Move in “ghost” mode
- Secondary (right) thumbstick: Rotate in “ghost” mode

What is the input mapping for the Oculus Rift remote?


- By default it is not mapped to anything

➤ **You'll find the input mappings in the AvatarMaster pawn.**




What are the best Project Settings for VR?

➤ Different settings may fit better your project. This is only suggestions.

- In settings/General Settings/Framerate



- In settings/Rendering



- Avoid using auto exposure, motion blur, lens flares and screen space reflections
- Pawn will spawn at playerstart (placed on the floor) and will teleport on navmesh

The Control Panel





Setting	
Controller Mesh	Hands / Oculus Touch / Vive controller
Controller Opacity	0 up to whatever
Controller Scale	For the hands, the scale is 1:1 with Epic VR template. Reduce scale to approx. 0.75 to come close to real-life for the hands.
Vive Controller Skin (if Vive controller is selected in Controller Mesh)	Default / Apperture / Carbon / Tron Aqua / Tron Clu
Teleport Rotation from Controller	If unselected, rotation is from thumbstick (Touch) or Trackpad (Vive)
Teleport Angle Tolerance	Safety feature to teleport only on surfaces under a certain inclination. Between 0 and 90 degrees. Put 90 degrees to disable it.
Enable Screen Messages	Yes / No
Teleport Rotation from Controller	If unselected, rotation is from thumbstick (Touch) or Trackpad (Vive)
Output Resolution	The resolution on your monitor. Oculus Rift Only.
GPU VRAM	GPU Video Memory, can be useful to tweak to stream large textures, by default 4000 (MB). You should put it around 1GB under your GPU VRAM
HMD Mirror Mode	See below
HMD Screen Percentage	Set the screen percentage. Use a higher number for better quality, and a lower one for better performance
Is Single Player Only.	Check if you don't use multiplayer functionalities. See the Single Player section.
Avatar Color	Avatar color in Single Player mode.
Is Showing Laser Pointer – Single Player	If Single Player Only is selected , will display the widget debug on / off.
Is Showing Laser Pointer in MainMenu	Will display the widget debug in the MainMenu Map
Is Showing Laser Pointer in Game	Will display the widget debug in the other maps
Is Using Oculus Subsystem	Check to use the Oculus subsystem (direct mode or via sessions). Mandatory for Oculus Avatars.
Is Using Oculus Avatars	Use Oculus Avatars. If not selected, the default AvatarMaster will be used. ProteusAvatar plugin must be enabled.
Alternative Oculus ID	Enter a 16-digits Oculus ID number to use a friend's / random Avatar, rather than you own. Is Using Oculus Avatars must be enabled.


HMD Mirror Modes


Mode	Oculus Rift	SteamVR	PS VR	Notes
Disabled	✓	✓		For the best performance on HMDs, this mode disables Spectator Screen output.
SingleEyeLetterboxed	✓	✓	✓	This mode is primarily intended for debugging purposes, showing only one letterboxed eye on the screen.
Undistorted	✓	✓	✓	This is a debug mode, showing the entire rendered area for both eyes.
Distorted	✓			This mode is only supported by Oculus. Specifically, this is an Oculus specific debug mode, showing chromatic aberrations, etc.
SingleEye	✓	✓	✓	Much like the Undistorted mode, this a debug mode for only one eye. Because this mode stretches the scene, it may be useful for identifying small artifacts in the scene.
SingleEyeCroppedToFit	✓	✓	✓	This mode crops the eye to fill the entire screen.

MULTIPLAYER MODE

IMPORTANT

- Ensure that ProjectSettings/Maps & Mode/Game Instance Class/GameInfoInstance is selected
- Start at MainMenu map
- Select MainMenuGM as GameMode in the Main Menu map, and override game mode with MultiGM in all other maps.






How does it work?


You can use any combination of Oculus Rifts and HTC Vive via LAN or Steam networks, and only Oculus Rifts via Oculus Network. Everyone must be in VR.

Each HMD must be connected to a different computer

IMPORTANT: You cannot connect to Steam, LAN or Oculus networks in the editor or VR Preview. To connect, you must first package your game, then start from the compiled .exe



The first time you'll launch the game you will be directed to the Options Menu. You will then be able to select Avatar Icon (for future use) and Avatar color





USING STEAM NETWORK

- Plugins/Virtual Reality/Steam VR must be selected
- Plugins/Online Platform/Online Subsystem Steam must be selected
- GameInfoInstance/Oculus Network must be deselected
- Each player must be connected to Steam with a different account
- The file /Config/DefaultGame.ini must contain the following lines:

```
[/Script/Engine.GameSession]
bRequiresPushToTalk=false
```

- The file /Config/DefaultEngine.ini must contain the following lines:

```
[/Script/Engine.AudioSettings]
VoIPSoundClass=/Game/Proteus_Multi/VOIPSoundClass.VOIPSoundClass
DefaultSoundClassName=/Game/Proteus_Multi/VOIPSoundClass.VOIPSoundClass
```

```
[OnlineSubsystem]
DefaultPlatformService=Steam
;DefaultPlatformService=Oculus
;bHasVoiceEnabled=true
PollingIntervalInMs=20
VoiceNotificationDelta=0.2
```


```
[OnlineSubsystemSteam]
bEnabled=true
SteamDevAppId=480
GameServerQueryPort=27015
bRelaunchInSteam=false
GameVersion=1.0.0.0
bVACEnabled=1
bAllowP2PPacketRelay=true
P2PConnectionTimeout=90
Achievement_0_Id=
```

```
[/Script/OnlineSubsystemSteam.SteamNetDriver]
NetConnectionClassName=OnlineSubsystemSteam.SteamNetConnection
```

```
[OnlineSubsystemOculus]
;Enable this if using Oculus Network
;Then enter you app ID
bEnabled=false
OculusAppId=1200222206710107
```

```
[/Script/OnlineSubsystemOculus.OculusNetDriver]
NetConnectionClassName=OnlineSubsystemOculus.OculusNetConnection
```

```
[/Script/Engine.GameEngine]
!NetDriverDefinitions=ClearArray
; Uncomment the next line if you are using the Null Subsystem
;+NetDriverDefinitions=(DefName="GameNetDriver",DriverClassName="/Script/OnlineSubsystemUtils.IpNetDriver",DriverClassNameFallback="/Script/OnlineSubsystemUtils.IpNetDriver")
; Uncomment the next line if you are using the Steam Subsystem
+NetDriverDefinitions=(DefName="GameNetDriver",DriverClassName="OnlineSubsystemSteam.SteamNetDriver",DriverClassNameFallback="OnlineSubsystemUtils.IpNetDriver")
; Uncomment the next line if you are using the Oculus Subsystem
;+NetDriverDefinitions=(DefName="GameNetDriver",DriverClassName="OnlineSubsystemOculus.OculusNetDriver",DriverClassNameFallback="OnlineSubsystemUtils.IpNetDriver")
```



```
[/Script/Engine.Player]  
ConfiguredInternetSpeed=500000  
ConfiguredLanSpeed=500000
```

```
[/Script/Engine.GameNetworkManager]  
TotalNetBandwidth=500000  
MaxDynamicBandwidth=80000  
MinDynamicBandwidth=20000
```

```
[/Script/OnlineSubsystemUtils.IpNetDriver]  
MaxClientRate=800000  
MaxInternetClientRate=800000
```

```
[Voice]  
bEnabled=true
```


- By default, you'll be playing the App ID #480, which is Space Wars. Your friends will see you're playing Space Wars. When developing your own app, replace with your correct Steam App ID.

HOSTING A GAME

Select Host World via LAN, Steam or Oculus Network



Select Steam/Oculus, Map, Maximum number of players, Time (not linked to anything yet), and Accept.




JOINING A GAME

Select Find a match via Steam or LAN, select Steam and Refresh.



Steam friends hosting a session should appear. Select the session and Accept.




CONNECT VIA LAN / DIRECT IP CONNECT

- Plugins/OnlineSubsystem/Online Subsystem NULL must be selected

You can use the same settings as Steam Network, with one exception: be sure that everyone is logged out of Steam. You can still use Steam VR. Select LAN when hosting a game.

To join a match, select Find a Match via Steam or Lan/Select LAN for LAN, or Direct Connection via IP Address for direct connection.



Using Oculus Network

- Plugins/Virtual Reality/Oculus Rift and Oculus Library must be selected
- Plugins/Online Platform/Online Subsystem Oculus must be selected
- GameInfoInstance/Oculus Network must be selected
- Each player must be connected to Oculus Home with a different account
- The file /Config/DefaultEngine.ini must contain the following changes:

```
[OnlineSubsystem]
;DefaultPlatformService=Steam
DefaultPlatformService=Oculus
;bHasVoiceEnabled=true
PollingIntervalInMs=20
VoiceNotificationDelta=0.2
```

```
[OnlineSubsystemSteam]
bEnabled=false
SteamDevAppId=480
GameServerQueryPort=27015
bRelaunchInSteam=false
GameVersion=1.0.0.0
bVACEnabled=1
bAllowP2PPacketRelay=true
P2PConnectionTimeout=90
Achievement_0_Id=
```

```
[/Script/OnlineSubsystemSteam.SteamNetDriver]
;NetConnectionClassName=OnlineSubsystemSteam.SteamNetConnection
```

```
[OnlineSubsystemOculus]
;Enable this if using Oculus Network
;Then enter you app ID
bEnabled=true
OculusAppId=1111111111111111
```

```
[/Script/OnlineSubsystemOculus.OculusNetDriver]
NetConnectionClassName=OnlineSubsystemOculus.OculusNetConnection
```


```
[/Script/Engine.GameEngine]
!NetDriverDefinitions=ClearArray
; Uncomment the next line if you are using the Null Subsystem
;+NetDriverDefinitions=(DefName="GameNetDriver",DriverClassName="/Script/OnlineSubsystemUtils.IpNetDriver",DriverClassNameFallback="/Script/OnlineSubsystemUtils.IpNetDriver")
; Uncomment the next line if you are using the Steam Subsystem
;+NetDriverDefinitions=(DefName="GameNetDriver",DriverClassName="OnlineSubsystemSteam.SteamNetDriver",DriverClassNameFallback="OnlineSubsystemUtils.IpNetDriver")
; Uncomment the next line if you are using the Oculus Subsystem
+NetDriverDefinitions=(DefName="GameNetDriver",DriverClassName="OnlineSubsystemOculus.OculusNetDriver",DriverClassNameFallback="OnlineSubsystemUtils.IpNetDriver")
```

The 16-digits App ID is your Oculus App ID found in your App Oculus dashboard URL (i.e.


<https://dashboard.oculus.com/application/1111111111111111/build>). For more information on publishing your game on Oculus platform see <https://developer3.oculus.com/documentation/publish/latest/>.

IMPORTANT:


- Plugins/Virtual Reality/Steam VR must be deselected
- Plugins/Online Platform/Online Subsystem Steam must be deselected
- In AvatarMaster/Set Boundaries for Chaperone & Guardian, delete the following code:




- Delete all functions related to Vive Trackers (in pink)



- Delete Tracker OnRep_TrackerSpace RepNotify function





OCULUS DIRECT CONNECT


In MainMenuPC, Using Oculus Subsystem must be selected

HOSTING A GAME:

Same as hosting a game on Steam Network


JOINING A GAME:

Select Direct Connection via Oculus Network



Type the 16-digits Oculus ID of your Oculus friend who is hosting a session, and Connect.

- You'll also find there your Oculus ID and your Oculus Name
- VOIP doesn't work yet via the Oculus Network



OCULUS AVATARS

- **Use the Proteus Template, Oculus Avatar Version (latest is 3.1)**
- **All previous considerations related to using Oculus Network still apply**
- **In MainMenuPC, Using Oculus Subsystem AND Using Oculus Avatar must be selected**

Put the following in DefaultInput.ini:

```
+ActionMappings=(ActionName="AvatarLeftTrigger",Key=MotionController_Left_Trigger,bShift=False,bCtrl=False,bAlt=False,bCmd=False)
+ActionMappings=(ActionName="AvatarRightTrigger",Key=MotionController_Right_Trigger,bShift=False,bCtrl=False,bAlt=False,bCmd=False)
+ActionMappings=(ActionName="AvatarLeftGrip1",Key=MotionController_Left_Grip1,bShift=False,bCtrl=False,bAlt=False,bCmd=False)
+ActionMappings=(ActionName="AvatarRightGrip1",Key=MotionController_Right_Grip1,bShift=False,bCtrl=False,bAlt=False,bCmd=False)
+AxisMappings=(AxisName="MoveForward",Key=W,Scale=1.000000)
+AxisMappings=(AxisName="MoveForward",Key=S,Scale=-1.000000)
+AxisMappings=(AxisName="MoveForward",Key=Up,Scale=1.000000)
+AxisMappings=(AxisName="MoveForward",Key=Down,Scale=-1.000000)
+AxisMappings=(AxisName="MoveForward",Key=Gamepad_LeftY,Scale=1.000000)
+AxisMappings=(AxisName="MoveRight",Key=A,Scale=-1.000000)
+AxisMappings=(AxisName="MoveRight",Key=D,Scale=1.000000)
+AxisMappings=(AxisName="MoveRight",Key=Gamepad_LeftX,Scale=1.000000)
+AxisMappings=(AxisName="TurnRate",Key=Gamepad_RightX,Scale=1.000000)
+AxisMappings=(AxisName="TurnRate",Key=Left,Scale=-1.000000)
+AxisMappings=(AxisName="TurnRate",Key=Right,Scale=1.000000)
+AxisMappings=(AxisName="Turn",Key=MouseX,Scale=1.000000)
+AxisMappings=(AxisName="LookUpRate",Key=Gamepad_RightY,Scale=1.000000)
+AxisMappings=(AxisName="LookUp",Key=MouseY,Scale=-1.000000)
+AxisMappings=(AxisName="MoveForward",Key=MotionController_Left_Thumbstick_Y,Scale=-1.000000)
+AxisMappings=(AxisName="MoveRight",Key=MotionController_Left_Thumbstick_X,Scale=1.000000)
+AxisMappings=(AxisName="AvatarLeftTrigger",Key=OculusTouch_Left_Trigger,Scale=1.000000)
+AxisMappings=(AxisName="AvatarRightTrigger",Key=OculusTouch_Right_Trigger,Scale=1.000000)
+AxisMappings=(AxisName="AvatarLeftIndexPointing",Key=OculusTouch_Left_IndexPointing,Scale=1.000000)
+AxisMappings=(AxisName="AvatarRightIndexPointing",Key=OculusTouch_Right_IndexPointing,Scale=1.000000)
+AxisMappings=(AxisName="AvatarLeftThumbUp",Key=OculusTouch_Left_ThumbUp,Scale=1.000000)
+AxisMappings=(AxisName="AvatarRightThumbUp",Key=OculusTouch_Right_ThumbUp,Scale=1.000000)
+AxisMappings=(AxisName="AvatarLeftTriggerAxis",Key=MotionController_Left_Trigger,Scale=1.000000)
+AxisMappings=(AxisName="AvatarRightTriggerAxis",Key=MotionController_Right_Trigger,Scale=1.000000)
```



```
+AxisMappings=(AxisName="AvatarLeftGrip1Axis",Key=MotionController_Left_Grip1,Scale=1.000000)
```

```
+AxisMappings=(AxisName="AvatarRightGrip1Axis",Key=MotionController_Right_Grip1,Scale=1.000000)
```

```
+ActionMappings=(ActionName="AvatarLeftFaceButton1",Key=MotionController_Left_FaceButton1,bShift=False,bCtrl=False,bAlt=False,bCmd=False)
```

```
+ActionMappings=(ActionName="AvatarRightFaceButton1",Key=MotionController_Right_FaceButton1,bShift=False,bCtrl=False,bAlt=False,bCmd=False)
```

```
+ActionMappings=(ActionName="AvatarLeftFaceButton2",Key=MotionController_Left_FaceButton2,bShift=False,bCtrl=False,bAlt=False,bCmd=False)
```

```
+ActionMappings=(ActionName="AvatarRightFaceButton2",Key=MotionController_Right_FaceButton2,bShift=False,bCtrl=False,bAlt=False,bCmd=False)
```

SINGLE PLAYER

- **In MainMenuPC, Is Single Players should be selected**
- Use MainMenuGM as game mode and GameInfoInstance on all maps

MULTIPLAYER - EXPERIMENTAL

Connect the same way as Steam


Steam can still be running, do not interfere with process

LAN doesn't work with Avatars

Multiplayer mode is experimental.

What works for now: VOIP, spawning local and remote Avatar

What still doesn't work: remote Avatars are still controlled by each locally-controlled player.



How the Avatars Works

The appearance of every person's avatar is stored in his or her Oculus user profile as an Avatar Specification. The Avatar Specification identifies the meshes and textures that make up a person's avatar. Before we retrieve this specification data, we have to initialize both the Platform SDK and the Avatar SDK using our app ID. Avatar Specifications are indexed by Oculus user ID. An app has easy access to the Oculus user ID of the currently logged in user. Proteus Template uses a third-person avatar which depicts hands, body, and base cone.

When logging in, the Oculus ID and Entitlement are fired in the MainMenuPC, the Oculus ID and name are sent to GameInfoInstance. When the menu widgets spawn, they retrieve this information. The host then starts and register in a map. Other clients go through the SteamLan widget. This widget relies on OculusLogin c++ class to find an Oculus session. Note that only friends that have installed the game (or registered beta users) will appear.


When spawning in a level, each player spawns 4 avatars: 1 for himself (AvatarMaster, based on ProteusLocal), and 3 AvatarRemote, based on ProteusRemote: 1 remote for the locally-controlled listen-server, 1 remote for the pawns, and it also make previously spawned clients to fire a copy of the non-locally controlled remote Avatar. In the AvatarMaster pawn, the VOIP is also enabled.

How Avatar is rendered (from Oculus):

- Retrieve the avatar specification for the Oculus user
- Set the Avatar capabilities
- Iterate through the avatar specification to load the static avatar assets (mesh and textures) into the avatar.
- Apply the vertex transforms to determine the position of the avatar component.
- Apply the material states to determine the appearance of the avatar component.
- For each render part of an avatar component:
 - Get the OpenGL mesh data and tell the renderer to use the Avatar shader program you compiled earlier.
 - Calculate the inputs on the vertex uniforms.
 - Set the view position, the world matrix, the view matrix, and the array of mesh poses.
 - Transform everything in the joint hierarchy.
 - Set the material state.
 - Draw the mesh, depth first so that it self-occludes.
 - Render to the color buffer.
- When there are no more components to render, the avatar render is complete.

Controlling the Remote Avatar – Still in development

Each player spawns a copy of Remote Avatar for each other players, and this copy is attached and possessed by these players. For this version, all Remote are driven by the inputs and transforms originating from the locally-controlled authority or client. The avatar packet recording system saves avatar movement data as packets: each time a packet is recorded, our code places the packet into a memory stream we are using as a stand-in for a real network layer. The remainder of our code receives the packet from the memory stream and plays it back on our loopback avatar object.



I'm working now on sending this data stream not to the memory buffer and back, but through the network to other players. Other avenue would be to use another copy of ProteusLocal, duplicate local inputs and transforms and send these back to the Avatar copies spawned by other clients.

Opening the Avatar Project

➤ **You must have Visual Studio 2015 or 2017 properly installed**

Right-click on Proteus.uproject/Generate Visual Studio Project files

Click on Proteus.uproject; required files should then be created.

If it doesn't work, open the Proteus.sln file with Visual Studio, rebuild the project, then you can open the project.

Packaging Avatars Project

Check the following options:


Packaging/Include Prerequisites

Packaging/Share Material Shader Code

Packaging/Share Material Native Libraries

Packaging/Include List of Maps to include in a packaged build (select your maps)

Additional Asset Directories to Cook/select the Content/Avatars directory



Using the Multiplayer Map (MultiMap01)

The first to login becomes the host. All other players are clients. All Avatars are the same.

What are the possible settings?

TAKE THE TIME TO REVIEW EACH SETTING BEFORE LAUNCHING / PACKAGING THE GAME

DefaultEngine.ini and DefaultGame.ini specific lines are mandatory (see above)

Project Settings should accommodate most, but there may be cases where you select otherwise

There are 3 type of settings:

- The PlayerSettings are chosen in the Options and Host Menu during gameplay (see above)
- The VRSettings are chosen within the MainMenuPC
- Some other settings are set in specific blueprints


Multiplayer settings:

Setting	You can change it in the following blueprint:
Max Number of Players available to host	/HostMenu/MaximumPlayers
Default Server Name	/HostMenu/DefaultServerName
List of Game Maps	/HostMenu/MapNames
Game Map Icons	/HostMenu/MapImages
Avatar Icon Images	/OptionsMenu/AvatarIcons
Avatar Images	/OptionsMenu/AvatarImages
Default Player Name	/OptionsMenu/MyPlayerName


How can I grab objects?

To enable object to be picked up, you have to:

- Make a blueprint of the mesh
- Be sure that the mesh inside the blueprint is set at PhysicsActor



- Implement BI Interactable Actor



- Copy the functions found in any objects in “Interactive Objects” folder

Collision with physics object

By default, when the trigger button is pressed (i.e. hand closed), the sphere on the motioncontroller has its collision channel set to physics objects so it will interact with objects, **and only if not actively grabbing anything**. Otherwise, it is disabled.

Using Sockets

There are many ways you can use sockets. In this template you'll find one example. You can try to pick up the baton, the gun, the book and the sword. Simply said, to use them, put a socket on the controller mesh you use. For an example, the CVR_Hand_Skeleton has 8 sockets, one for each object and hand side. Name the socket the same as the display name of the class blueprint holding the object. You can then attach it to a bone, place and orient the socket to fit in the controller mesh you use.

Put “r” or “l” before a socket name to specify a different right or left hand position. If you don’t put any socket, the right and left hand will pick up the object by the closest collision mesh surface. An example is found with the cube and the hat.



- **NOTE: The sockets have been roughly calibrated for the Oculus Touch Closed Hands Pose, you’ll want to adjust the sockets if using the Vive.**

Interacting with objects

You can do that many ways. To try many different type of interactions, @jamis's VR Essential Kit Map has been included with the template. The reason that it is included is that minor changes were made to @jamis' blueprints to be compatible with the AvatarMaster pawn. You'll find more infos at

<https://forums.unrealengine.com/showthread.php?131379-WIP-VR-Essential-Kit&highlight=vr+essential+kit>




- Note that the VR Essential Kit is a project made by @jamis. All questions concerning this project should be directed to him.
- As of now (version 3.0), the VR Essential Kit won't respond to clients in multiplayer game.

Fingers / Controllers Poses

The hand model (.fbx and ASCII Maya) can be found on OneDrive at the same place as the template:

<https://1drv.ms/f/s!Av77IIxt2OY0XGGW8UDwykohjuT>



You can then use your favorite 3D software to create fingers poses.

- You'll also find there the Oculus Touch, Vive Tracker and HTC Vive Controllers files



Using Vive Tracker

- You can use a mix of Oculus Rifts and HTC Vive in the game, but the Vive Trackers can only be tracked with an HTC Vive.
- If Vive Trackers are detected by SteamVR, they will appear in the level
- You can add or remove Trackers during gameplay.
- The Vive Trackers are tracked via functions found in the Avatar_Master
- By default, the Trackers detected by one Vive will have their position broadcasted in relation to the orientation and position of the Playground Center of this Vive.
- It's entirely possible to physically and virtually interact with the same trackers if you have more than one HMD sets in the same real-world room. It doesn't matter if Rifts or Vive are used, as long as:
 - The Trackers are tracked by HTC Vive(s)
 - The playground centers of all players are centered around the same origin

Teleporting


Pawn are able to teleport on surfaces when these 2 conditions are met:

- Has a NavMeshBoundsVolume;
- Is below the teleportation angle limit (see VR settings) – put 90 to this setting to disable it

IMPORTANT: Enable Project Settings / Engine / Navigation System / Allow Client Side Navigation for multiplayer teleportation; if not selected, clients won't be able to detect the Navigation Mesh.


Single Player Only


- Use the same settings as the Multiplayer mode
- Select "Is Single Player Only" in VRSettings
- Select Avatar color in VRSettings and other pawn-related settings
- Use MainMenuGM as game mode on all maps



Important dev notes

Before packaging your game, select List of maps to include in a packaged build in Project settings/packaging





Rants

I want to access the camera in the Vive! What can I do?

For now, it works well with the Unreal4AR plugin found at <http://www.unreal4ar.com/> (personal license for 99\$), but the camera is in low-quality VGA.

I don't have 45/90 fps! Your template is crap!

The template and the functions inside the pawns are not computer-intensive. It has been rigorously tested and within MultiMap, it stays at 90 fps.


99.99% of the time, the problem can be resolved by checking materials, lights and shadows. You have also to carefully assess and tweak the scalability and post-process settings.

Other settings

- Try to avoid any other materials than opaque and masked
- Avoid fancy collision boxes
- Eliminate / reduce to minimum dynamic lights and shadows
- Avoid meshes with high poly count
- Reduce the number of animated objects

I'm still having problems

If you have an NVIDIA card, try the latest iteration of VR Works for Unreal Engine, including features such as Multi-Res shading, VR SLI, Single Pass Stereo and Lens Matched Shading: <https://developer.nvidia.com/nvidia-vrworks-and-ue4>




Supplemental resources

- UE4 Forum/VR development: <https://forums.unrealengine.com/forumdisplay.php?27-VR-Development>
- UE4 Virtual Reality development: <https://docs.unrealengine.com/latest/INT/Platforms/VR/>
- UE4 Networking and Multiplayer: <https://docs.unrealengine.com/latest/INT/Gameplay/Networking/>
- Tom Looman getting started in VR: <http://www.tomlooman.com/getting-started-with-vr/>
- Cedrik Neukirchen UE4 Multiplayer Network Compendium: <http://cedric-neukirchen.net/2017/02/14/multiplayer-network-compendium/>
- Mitch McCaffrey Unreal Engine VR Cookbook: <http://ue4vrcookbook.com/>
- Oculus UE4 GitHub: <https://github.com/oculus-vr/unrealengine>
- Oculus UE4 Developer Guide: <https://developer3.oculus.com/documentation/game-engines/latest/concepts/book-unreal/>
- Vive Tracker for developers: <https://www.vive.com/ca/vive-tracker-for-developer/>
- SteamVR Developer Hardware: <https://steamcommunity.com/app/358720/discussions/>

Questions?

Don't hesitate to contact me mathieu.beaulieu@proteus-vr.com .



What are the license terms?

Assets created by Epic can be freely reused in any Unreal Engine 4 project.

Assets created by Proteus are under the MIT license terms.

MIT licence terms (MIT)

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Proteus