

JacORB 2.0 Programming Guide

The JacORB Team

February 10, 2004

Contributors:

Gerald Brose
Nicolas Noffke
André Spiegel
Sebastian M"uller
Steve Osselton
Nick Cross
Jason Courage

Contents

1	Introduction	7
1.1	A Brief CORBA introduction	7
1.2	Project History	8
1.3	Support	8
1.4	Contributing — Donations	9
1.5	Contributing — Development	9
1.6	Limitations, Feedback	9
1.6.1	Feedback, Bug reports	10
2	Installing JacORB	11
2.1	Downloading JacORB	11
2.2	Installation	11
2.2.1	Requirements	11
3	Configuration	13
3.1	Properties	13
3.1.1	Properties file	13
3.1.2	Command-line properties	14
3.1.3	Arguments to ORB.init()	14
3.2	Common Configuration Options	15
3.2.1	Initial references	15
3.2.2	Logging	15
3.3	Configuration Properties	17
4	Getting Started	27
4.1	JacORB development: an overview	27
4.2	IDL specifications	27
4.3	Generating Java classes	28
4.4	Implementing the interface	29
4.5	Writing the Server	31
4.6	Writing a client	32
4.6.1	The Tie Approach	34

5	The JacORB Name Service	37
5.1	Running the Name Server	37
5.2	Accessing the Name Service	38
5.3	Constructing Hierarchies of Name Spaces	39
5.4	NameManager — A simple GUI front-end to the Naming Service	40
6	The server side: POA, Threads	41
6.1	POA	41
6.2	Threads	42
7	Implementation Repository	43
7.1	Overview	43
7.2	Using the JacORB Implementation Repository	44
7.3	Server migration	46
7.4	A Note About Security	47
8	Dynamic Management of Any Values	49
8.1	Overview	49
8.2	Interfaces	49
8.3	Usage Constraints	50
8.4	Creating a DynAny Object	50
8.5	Accessing the Value of a DynAny Object	52
8.6	Traversing the Value of a DynAny Object	52
8.7	Constructed Types	54
8.7.1	DynFixed	54
8.7.2	DynEnum	54
8.7.3	DynStruct	54
8.7.4	DynUnion	54
8.7.5	DynSequence	55
8.7.6	DynArray	55
8.8	Converting between Any and DynAny Objects	55
8.9	Further Examples	56
9	Objects By Value	57
9.1	Example	57
9.2	Factories	59
10	Interface Repository	61
10.1	Type Information in the IR	61
10.2	Repository Design	62
10.3	Using the IR	63
11	The JacORB Appligator	67
11.1	Appligator Functionality	67

11.2 Using The Appligator	67
11.2.1 Starting Appligator	67
11.2.2 Client Configuration	68
11.2.3 Appligator Configuration Appligator	68
11.3 Applet Support	69
11.3.1 Summary	69
11.3.2 Applet Properties	70
11.3.3 Appligator and Netscape/IE, appletviewer	70
11.3.4 Examples	70
11.4 Firewall Support	71
11.4.1 Summary	71
11.4.2 NAT Firewalls	72
11.4.3 Security Considerations	72
11.4.4 Use of SSH	72
12 IIOP over SSL	75
12.1 Re-Building JacORB's security libraries	75
12.2 IAIK specific setup	76
12.2.1 Setting up an IAIK key store	76
12.2.2 Step-By-Step certificate creation	78
12.3 Configuring SSL properties	78
12.3.1 Client side configuration	79
12.3.2 Server side configuration	80
13 BiDirectional GIOP	81
13.1 Setting up Bidirectional GIOP	81
13.1.1 Setting the ORBInitializer property	81
13.1.2 Creating the BiDir Policy	81
13.2 Verifying that BiDirectional GIOP is used	82
13.3 TAO interoperability	82
14 Portable Interceptors	85
15 Asynchronous Method Invocation	87
16 Quality of Service	89
16.1 Sync Scope	90
16.2 Timing Policies	90
17 Connection Management and Connection Timeouts	95
17.1 Timeouts	95
17.2 Connection Management	95
17.2.1 Basics and Design	96
17.2.2 Configuration	97

17.2.3	Limitations	97
18	Extensible Transport Framework	99
18.1	Implementing a new Transport	99
18.2	Configuring Transport Usage	100
19	Security Attribute Service	103
19.1	Overview	103
19.2	GSSUP Example	104
19.2.1	GSSUP IDL Example	104
19.2.2	GSSUP Client Example	104
19.2.3	GSSUP Target Example	105
19.3	Kerberos Example	107
19.3.1	Kerberos IDL Example	107
19.3.2	Kerberos Client Example	107
19.3.3	Kerberos Target Example	109
20	The JacORB Notification Service	113
20.1	Installation	113
20.2	Running the Notification Service	113
20.2.1	Running as a NT Service or a UNIX Daemon	114
20.3	Accessing the Notification Service	116
20.4	Configuration	117
21	JacORB utilities	121
21.1	idl	121
21.2	ns	123
21.3	nmg	123
21.4	lsns	124
21.5	dior	124
21.6	pingo	125
21.7	ir	125
21.8	qir	125
21.9	ks	125
21.10	fixior	126

1 Introduction

This document gives an introduction to programming distributed applications with JacORB, a free Java object request broker. JacORB comes with full source code, a couple of CORBA Object Service implementations, and a number of example programs. The JacORB version described in this document is JacORB 2.0.

1.1 A Brief CORBA introduction

The idea behind CORBA is to model distributed resources as objects that provide a well-defined interface, and to invoke services through remote invocations (RPCs). Since the transfer syntax for sending messages to objects is strictly defined, it is possible to exchange requests and replies between processes running program written in arbitrary programming languages and hosted on arbitrary hardware and operating systems. Target addresses are represented as *Interoperable Object References* (IORs), which contain transport addresses as well as identifiers needed to dispatch incoming messages to implementations.

Interfaces to remote objects are described declaratively in an programming language-independent *Interface Definition Language* (IDL), which can be used to automatically generate language-specific stub code.

It is important to stress that:

- CORBA objects are abstract entities seen by clients and represented by artifacts in potentially arbitrary, even non-OO languages. These artifacts are called *servants* in CORBA terminology.
- CORBA objects achieve location transparency, i.e., clients need not be (and generally are not) aware of the actual target hosts where servants reside. However, complete distribution transparency is not achieved in the sense that clients would not notice a difference between a local function call and a remote CORBA invocation. This is due to factors such as increased latency, network error conditions, and CORBA-specific initialization code in applications, and data type mappings.

Please see [[BVD01](#), [Sie00](#), [Vin97](#)] for more information and additional details, and [[HV99](#)] for advanced issues.

1.2 Project History

JacORB originated in 1995 (was it 1996?) in the CS department at Freie Universität Berlin (FUB). It evolved from a small Java RPC library and a stub compiler that would process Java interfaces. This predecessor was written — most for fun and out of curiosity — by Boris Bokowski and Gerald Brose because at that time no Java RMI was available. The two of us then realized how close the Java interface syntax was to CORBA IDL, so we wrote an IDL grammar for our parser generator and moved to GIOP and IIOP as the transport protocol. It was shortly before Christmas 1996 when the first interoperable GIOP request was sent from a JacORB client to an IONA Orbix server. For a long time, JacORB was the only free (in the GNU sense) Java/CORBA implementation available, and it soon enjoyed widespread interest, at first mostly in academic projects, but commercial use followed soon after.

For a while, Gerald developed JacORB as a one-man-project until a few student projects and master theses started adding to it, most notably Reimo Tiedemann's POA implementation, and Nicolas Noffke's Implementation Repository and Portable Interceptor implementations. Other early contributors were Sebastian Müller, who wrote the Appligator, and Herbert Kiefer, who added a policy domain service (which is no longer part of the JacORB distribution).

A more recent addition is Alphonse Bendt's implementation of the CORBA Notification Services as part of his master's theses. Substantial additions to the JacORB core were made by André Spiegel, who contributed OBV and AMI implementations. Other substantial contributions to JacORB have been added over time by the team at PrismTech UK (Steve Osselton, Nick Cross, Simon McQueen, Jason Courage). Still other active contributors are Francisco Reverbel of the JBoss team (RMI/IIOP), and David Robison, who contributed CSIv2.

JacORB continues to be used for research at FUB, especially in the field of distributed object security. Even though a number of people from the core team have left FUB (Gerald, Nico, and Reimo are now with Xtradyne Technologies, André Spiegel is now a free-lance developer and consultant), the JacORB project is still rooted at Freie Universität Berlin, which hosts the JacORB web and CVS server.

Due to the limited number of developers, the philosophy around the development has never been to achieve feature-completeness beyond the core 90%, but standards compliance and quality. (e.g., JacORB 2.0 does not come with a PolicyManager). Brand-new and less widely-used features had to wait until the specification had reached a minimum maturity — or until someone offered project funding.

1.3 Support

The JacORB core team and the user community together provide best effort support over our mailing lists.

To enquire about commercial support, please send email to info@jacorb.com if you want

members of the JacORB core team. Commercial support is also available from PrismTech and OCI.

1.4 Contributing — Donations

In essence, the early development years were entirely funded by public research. JacORB did receive some sponsoring over the years, but not as much as would have been desirable. A few development tasks that would otherwise not have been possible could be paid for, but more would have been possible — and still is.

If you feel that returning some of the value created by the use of Open Source software in your company is a wise investment in the future of that the software (maintenance, quality improvements, further development) in the future, then you should contact us about donations.

Buying hardware and sending it to us is one option. It is also possible to directly donate money to the JacORB project at Freie Universität Berlin. If approval for outright donations is difficult to obtain at your company, we can send you an invoice for, e.g., CORBA consulting.

1.5 Contributing — Development

If you want to contribute to the development of the software directly, you should do the following:

- download JacORB and run the software to gain some first-hand expertise first
- read this document and other sources of CORBA documentation, such as [\[BVD01\]](#), and the OMG's set of specifications (CORBA spec., IDL/Java language mapping)
- start reading the code
- subscribe to the `jacorb-developer` mailing list to share your expertise
- contact us to get subscribed to the core team's mailing list and gain CVS access
- read the coding guide line
- contribute code and test cases

1.6 Limitations, Feedback

A few limitations and known bugs (list is incomplete):

- the IDL compiler does not support
 - the `context` construct
- the API documentation and this document are incomplete.

1.6.1 Feedback, Bug reports

For bug reporting, please use our Bugzilla bug tracking system available at <http://www.jacorb.org/bugzilla>. Please send problems as well as criticism and experience reports to our developer mailing list available from <http://www.jacorb.org/contact.html>.

2 Installing JacORB

In this chapter we explain how to obtain and install JacORB, and give an overview of the package contents.

2.1 Downloading JacORB

JacORB can be downloaded as a g-zipped tar-archive or as a zip-archive from the JacORB home page at <http://www.jacorb.org>.

To install JacORB, first unzip and untar (or simply unzip) the archive somewhere. This will result in a new directory `JacORB2.0`. After this follow the instructions in `JacORB2.0/doc/INSTALL`.

2.2 Installation

2.2.1 Requirements

JacORB requires JDK 1.2 or above properly installed on your machine. To build JacORB (and compile the examples) you need to have the XML-based make tool “Ant” installed on your machine. Ant can be downloaded from <http://jakarta.apache.org/ant>. All make files (`build.xml`) are written for this tool. To rebuild JacORB completely, just type `ant` in the installation directory. Optionally, you might want to do a `ant clean` first.

For SSL, you need an implementation of the SSL protocol. We currently support:

1. IAIK’s ¹ implementation consisting of the crypto provider IAIK-JCE 2.5 (or higher) and the SSL library iSaSiLk 3.0 (or higher). Using this implementation allows you to access the clients authenticated certificates.
2. Sun’s JSSE Reference implementation included in the JDK 1.4 and separately available from the Developer Connection.

¹<http://jcewww.iaik.tu-graz.ac.at/>

3 Configuration

This chapter explains the general mechanism how JacORB is configured, and lists all configuration properties.

3.1 Properties

JacORB has a number of configuration options which can be set as Java properties. There are three options for setting properties: properties files, command line properties, and properties passed as arguments to `ORB.init()` in the code of your applications.

3.1.1 Properties file

JacORB looks for and loads a standard properties file called either `.jacorb.properties` or `jacorb.properties`. Properties files with these names will be searched in the following places:

1. in the `lib` directory of the JDK installation. (The JDK's home directory denoted by the system property `"java.home"`).
2. in the user home directory. (This is denoted by the system property `"user.home"`. On Windows, this is `c:\documents\username`, on Unixes it's `~user`. If in doubt where your home directory is, write a small Java program that prints out this property.
3. in the classpath.

Properties files are searched in the order presented above. If a properties file is found, it is loaded, and any property values loaded will override values of the same property that were loaded earlier.

In addition to standard JacORB properties files, a *custom properties file* can be loaded by passing the name of that properties files the `custom.props` property to JacORB.

The value of this property is the absolute path to a properties file, which contains the properties you want to load. As an example, imagine that you usually use plain TCP/IP connections, but in some cases want to use SSL (see section 12). The different ways of achieving this are

- Use just one properties file, but you will have to edit that file if you want to switch between SSL and plaintext connections.
- Use commandline properties exclusively (cf. below), which may lead to very long commands
- Use a command property file for all applications and different custom properties files for each application.

For example, you could start a JacORB program like this:

```
$ jaco -Dcustom.props=c:/tmp/ns.props org.jacorb.naming.NameServer  
c:/NS_Ref
```

In addition to loading any standard properties files found in the places listed above, JacORB will now also load configuration properties from the file `c:/tmp/ns.props`, but this last file will be loaded after the default properties files and its values will thus take precedence over earlier settings.

3.1.2 Command-line properties

In the same way as the `custom.props` property in the example above, arbitrary other Java properties can be passed to JacORB programs using the `-D<prop name>=<prop value>` command line syntax for the `java` interpreter, but can be used in the same way with the `jaco` script. Note that in any case the properties must precede the class name on the command line.

The ORB configuration mechanism will give configuration properties passed in this way precedence over property values found in configuration files.

3.1.3 Arguments to ORB.init()

For more application-specific properties, you can pass a `java.util.Properties` object to `ORB.init()` during application initialization. Properties set this way will override properties set by a properties file. The following code snippet demonstrates how to pass in a `Properties` object (`args` is the `String` array containing command line arguments):

```
java.util.Properties props = new java.util.Properties();  
props.setProperty("jacorb.implname", "StandardNS");  
// use put() under Java 1.1  
  
org.omg.CORBA.ORB orb = org.omg.CORBA.ORB.init(args, props);
```

3.2 Common Configuration Options

We are now ready to have a look at the most basic JacORB configuration properties. As a starting point, you should look at the file `/etc/jacorb.properties.template`, which you can adapt to your own needs.

3.2.1 Initial references

Initial references are object references that are available to CORBA application through the bootstrap `orb.resolve_initial_service()` API call. This call takes a string argument as the name of an initial reference and returns a CORBA object reference, e.g., to the initial name service.

```
#####
#                                     #
#   Initial references configuration   #
#                                     #
#####

#
# URLs where IORs are stored (used in orb.resolve_initial_service())
# DO EDIT these! (Only those that you are planning to use,
# of course ;-).
#
# The ORBInitRef references are created on ORB startup time. In the
# cases of the services themselves, this may lead to exceptions being
# displayed (because the services aren't up yet). These exceptions
# are handled properly and cause no harm!

#ORBInitRef.NameService=corbaloc::160.45.110.41:38693/StandardNS/NameServer-POA/
#ORBInitRef.NameService=file:/c:/NS_Ref
ORBInitRef.NameService=http://www.x.y.z/~user/NS_Ref
#ORBInitRef.TradingService=http://www.x.y.z/~user/TraderRef
```

The string value for `ORBInitRef.NameService` is a URL for a resource used to set up the JacORB name server. This URL will be used by the ORB to locate the file used to store the name server's object reference (see also chapter 5).

3.2.2 Logging

Beginning with version 2.0, JacORB uses external log kit implementations for writing logs. The default log kit used by JacORB is the Apache LogKit implementation. To plug in different loggers, you need to write code for a custom `LoggerFactory` class yourself and supply the class name as the value of the `jacorb.log.loggerFactory` property. Any new factory needs to implement the interface `org.jacorb.util.LoggerFactory`.

Log levels and different log components

The JacORB logging mechanism can be fine-tuned to set different log levels for different components of JacORB. It is still possible to rely only on one single, default log level. This log level is specified like this (note that the properties have changed from previous JacORB versions!):

```
#####
#                                     #
#  Default Logging configuration  #
#                                     #
#####

# Name of the factory class that plugs in a given log kit
# The default value is JacORB's own factory for the Apache
# LogKit. Only edit (or uncomment) if you want a different
# log kit.
jacorb.log.loggerFactory=org.jacorb.util.LogKitLoggerFactory

# log levels:
#
# 0 = fatal errors only = "almost off" (FATAL ERRORS)
# 1 = non-fatal errors and exceptions (ERROR)
# 2 = important messages (WARN)
# 3 = informational messages and exceptions (INFO)
# 4 = debug-level output (DEBUG) (may confuse the unaware user :-)
jacorb.log.default.verbosity=3
```

For other components, the individual log levels are set using log properties specific to that component, e.g.,

```
jacorb.naming.log.verbosity=0
```

will turn logging off for the naming service, but all other parts of the ORB will still use the default log level. The general pattern for the log level property is `jacorb.<component>.log.verbosity`. Other components are, e.g., `poa`, or `ssl`.

Logging output to a file

The properties specific to file logging are the following:

```
# where does output go? Terminal is default
jacorb.logfile=c:/tmp/jacorb.log

# Append to an existing log file or overwrite? (Applies to
# file logging only)
jacorb.logfile.append=on
```



```
# If jacorb.logfile.append is on, set rolling log size in kilobytes.
# A value of 0 implies no rolling log
jacorb.logfile.maxLogSize=0
```

Unless the `jacorb.logfile` property is set to a file name, output will be sent to the terminal. The `jacorb.logfile.append` value tells the logger whether to overwrite existing log files or to append to the. The `jacorb.logfile.maxLogSize` property, finally, determines how large a log file may become before the logger automatically creates a new file. This value is in kilobytes. If it is set to 0, log files may become arbitrarily large, no log file rotation is used.

The `jacorb.poa.monitoring` property determines whether the POA should bring up a monitoring GUI for servers that let you examine the dynamic behavior of your POA, e.g. how long the request queue gets and whether your thread pool is big enough. Also, this tool lets you change the state of a POA, e.g. from *active* to *holding*. Please see chapter 6 on the POA for more details.

3.3 Configuration Properties

A comprehensive listing and description of the properties which are used to configure JacORB are given in the following tables.

Table 3.1: ORB Configuration

Property	Description	Type	Default
ORBInitRef.<service>	Properties of this form configure initial service objects which can be resolved via the ORB <code>resolve_initial_references</code> . A variety of URL formats are supported.	URL	unset
org.omg.PortableInterceptor.ORBInitializerClass.<name>	A portable interceptor initializer class instantiated at ORB creation.	class	unset
jacorb.orb.objectKeyMap.<name>	Maps an object key to an arbitrary string thereby enabling better readability for corbaloc URLs.	string	
jacorb.giop_minor_version	The GIOP minor version number to use for newly created IORs	integer	2
jacorb.retries	Number of retries if connection cannot directly be established	integer	5
jacorb.retry_interval	Time in milliseconds to wait between retries	millisec.	500

Table 3.1: ORB Configuration

Property	Description	Type	Default
<code>jacorb.maxManagedBufSize</code>	This is NOT the maximum buffer size that can be used, but just the largest size of buffers that will be kept and managed. This value will be added to an internal constant of 5, so the real value in bytes is $2^{**} (5 + \text{maxManagedBufSize} - 1)$. You only need to increase this value if you are dealing with LOTS of LARGE data structures. You may decrease it to make the buffer manager release large buffers immediately rather than keeping them for later reuse	integer	18
<code>jacorb.bufferManagerFlushMax</code>	Whether to use an additional unlimited size buffer cache for CDROutputStreams. If -1 then off, if zero then this is feature is enabled, if greater than zero then it is enabled and flushed every x seconds	integer	-1
<code>jacorb.connection.client.pending_reply_timeout</code>	Wait the specified number of msec for a reply to a request. If exceeded, a <code>org.omg.CORBA.TIMEOUT</code> exception will be thrown. Not set by default	millisec.	0
<code>jacorb.connection.client.idle_timeout</code>	Client-side timeout. This is set to non-zero in order to stop blocking after specified number of milliseconds	millisec.	unset
<code>jacorb.connection.client.timeout_ignores_pending_messages</code>	Controls if client-side idle timeouts take care of pending messages or not.	boolean	
<code>jacorb.connection.client.retry_on_failure</code>	Controls if network failures on existing connections should yield a <code>COMM_FAILURE</code> or should trigger a remarshaling of all pending messages.	boolean	
<code>jacorb.connection.server.timeout</code>	Maximum time in milliseconds that a server keeps a connection open if nothing happens	millisec.	unset
<code>jacorb.connection.max_server_transports</code>	This property sets the maximum number of TCP/IP connections that will be listened on by the server-side ORB	integer	unlimited
<code>jacorb.connection.wait_for_idle_interval</code>	This property sets the interval to wait until the next try is made to find an idle connection to close	millisec	500
<code>jacorb.connection.selection_strategy_class</code>	This property sets the <code>SelectionStrategy</code>	class	
<code>jacorb.connection.statistics_provider_class</code>	This property sets the <code>StatisticsProvider</code>	class	

Table 3.1: ORB Configuration

Property	Description	Type	Default
<code>jacorb.connection.delay_close</code>	This property controls the behaviour after sending a GIOP CloseConnection message. If set to “on”, the TCP/IP connection won’t be closed directly. Instead, it is waited for the client to do so first	boolean	off
<code>jacorb.transport.factories</code>	This property controls which transport plug-ins are available to the ORB. The value is a list of classes that implement the <code>ETF Factories</code> interface.	comma-separated list of classes	
<code>jacorb.transport.server.listeners</code>	Controls which transports should be offered by JacORB on the server side. The value is a list of numeric profile tags for each transport that should be available on the server side.	comma-separated list of integers	
<code>jacorb.transport.client.selector</code>	Name of a class that selects the transport profile to use for communication on the client side. The value is the fully qualified name of a class that implements <code>org.jacorb.orb.ProfileSelector</code> .	class	
<code>jacorb.reference_caching</code>	Whether or not JacORB caches objects references	boolean	unset
<code>jacorb.hashtable_class</code>	The following property specifies the class which is used for reference caching. <code>WeakHashtable</code> uses <code>WeakReferences</code> , so entries get garbage collected if only the <code>Hashtable</code> has a reference to them. This is useful if you have many references to short-living non-persistent CORBA objects. It is only available for java 1.2 and above. On the other hand the standard <code>Hashtable</code> keeps the references until they are explicitly deleted by calling <code>_release()</code> . This is useful for persistent and long-living CORBA objects	class	<code>Hashtable</code>
<code>jacorb.use_bom</code>	Use GIOP 1.2 byte order markers, since CORBA 2.4-5	boolean	off
<code>jacorb.giop.add_1_0_profiles</code>	Add additional IIOP 1.0 profiles even if using IIOP 1.2	boolean	off
<code>jacorb.dns.enable</code>	Use DNS names in IORs, rather than numeric IP addresses	boolean	off
<code>jacorb.compactTypecodes</code>	Whether to send compact typecodes. Options are 0 (off), 1 (Partial compaction), 2 (full compaction of all optional parameters)	integer	2
<code>jacorb.cacheTypecodes</code>	Whether to cache read typecodes	boolean	off
<code>jacorb.cachePoaNames</code>	Whether to cache scoped poa names	boolean	off

Table 3.1: ORB Configuration

Property	Description	Type	Default
<code>jacorb.interop.indirection_encoding_disable</code>	Turn off indirection encoding for repeated type-codes. This fixes interoperability with certain broken ORB's eg. Orbix 2000	boolean	off
<code>jacorb.interop.comet</code>	Enable additional buffer length checking and adjustment for interoperability with Comet CORBA/COM bridge which can incorrectly encode buffer lengths	boolean	off
<code>jacorb.interop.lax_boolean_encoding</code>	Treat any non zero CDR encoded boolean value as true (strictly should be 1 not non zero)	boolean	off
<code>org.omg.PortableInterceptor.ORBInitializerClass.bidir_init</code>	This portable interceptor must be configured to support bi-directional GIOP	class	unset
<code>jacorb.ior_proxy_host</code>	The <code>jacorb.ior_proxy_host</code> and <code>jacorb.ior_proxy_port</code> properties inform the ORB what IP/port IORs should contain, if the ServerSockets IP/port can't be used (e.g. for traffic through a firewall). WARNING: this is just dumb replacing, so you have to take care of your configuration!	node	unset
<code>jacorb.ior_proxy_port</code>	See <code>jacorb.ior_proxy_host</code> above	port	unset
<code>OAIAddr</code>	The Object Adapter Internet Address: IP address on multi-homed host (this gets encoded in object references). NOTE: Addresses like 127.0.0.X will only be accessible from the same machine!	node	unset
<code>OAPort</code>	See <code>OAIAddr</code> above	port	unset
<code>org.omg.PortableInterceptor.ORBInitializerClass.standard_init</code>	Standard portable interceptor. DO NOT REMOVE.	class	
<code>jacorb.net.socket_factory</code>	Sets or defines the socket factory that must implement the operations defined in the <code>org.jacorb.orb.factory.SocketFactory</code> interface.	class	
<code>jacorb.net.server_socket_factory</code>	Sets or defines the socket factory that must implement the operations defined in the <code>org.jacorb.orb.factory.ServerSocketFactory</code> interface.	class	
<code>jacorb.net.socket_factory.port.min</code>	Sets the minimum port number that can be used for an additional supported socket factory. This property is used in conjunction with the <code>jacorb.net.socket_factory.port.max</code> property. These properties enable the factory to traverse firewalls through a fixed port range	integer	unset (disabled)

Table 3.1: ORB Configuration

Property	Description	Type	Default
<code>jacorb.net.socket_factory.port.max</code>	Sets the maximum port number that can be used for the additional supported socket factory. Refer to <code>jacorb.net.socket_factory.port.min</code> above	integer	disabled

Table 3.2: Logging Configuration

Property	Description	Type	Default
<code>jacorb.orb.print_version</code>	If enabled, the ORB's version number is printed whenever the ORB is initialized.	boolean	on
<code>jacorb.log.loggerLogFactory</code>	Name of the logger factory class, can be used to plug in different log implementations	class	<code>org.jacorb.util.LogKitLoggerFactory</code>
<code>jacorb.log.default.verbosity</code>	Log levels: 0 = fatal errors, 1 = error, 2 = warning, 3 = info, 4 = debug	integer	0
<code>jacorb.logfile</code>	Output destination for diagnostic log file. If not set, diagnostics are sent to standard error.	filename	unset
<code>jacorb.logfile.append</code>	Whether to append to existing log file or overwrite (if file logging)	boolean	off
<code>jacorb.logfile.maxLogSize</code>	If appending to a file sets the size in kilobytes at which the file is rolled over	integer	0
<code>jacorb.debug.dump_outgoing_messages</code>	Hex dump outgoing messages	boolean	off
<code>jacorb.debug.dump_incoming_messages</code>	Hex dump incoming messages	boolean	off

Table 3.3: Appligator Configuration

Property	Description	Type
<code>jacorb.ProxyServer.URL</code>	This is the URL for the default Appligator and is used when applets or firewall traversal is supported via the JacORB Appligator.	URL
<code>jacorb.ProxyServer.URL-<network>-<netmask></code>	Additional appligators can be configured for remote subnets using this subnet form of URL configuration. The subnet for a scoped appligator is calculated by the logical ANDing of the network and netmask values.	URL
<code>jacorb.ProxyServer.Name</code>	The name the appligator uses when adding itself to the Name Service (if available) on start up. Default is Appligator.	string
<code>jacorb.ProxyServer.ID</code>	Defines the object identity for the appligator IOR. If not set, then this defaults to 'Appligator': it is recommended that this is set to some other value for additional security.	string

Table 3.3: Appligator Configuration

Property	Description	Type
<code>jacorb.ProxyServer.Netmask</code>	Optionally used to configure the network for the local client. When used, the calls to objects within the local subnet will not be redirected. Not set by default.	IP address
<code>jacorb.ProxyServer.Network</code>	See <code>jacorb.ProxyServer.Netmask</code> above. Not set by default.	IP address

Table 3.4: POA Configuration

Property	Description	Type
<code>jacorb.poa.monitoring</code>	Displays a GUI monitoring tool for servers. Default is off.	boolean
<code>jacorb.poa.thread_pool_max</code>	Maximum thread pool configuration for request processing	integer
<code>jacorb.poa.thread_pool_min</code>	Minimum thread pool configuration for request processing	integer
<code>jacorb.poa.thread_priority</code>	If set, request processing threads in the POA will run at this priority. If not set or invalid, <code>MAX_PRIORITY</code> will be used. Not set by default.	integer
<code>jacorb.poa.queue_wait</code>	Specifies whether the POA should block when the request queue is full (On), or throw <code>TRANSIENT</code> exceptions (Off). Default is Off.	boolean
<code>jacorb.poa.queue_max</code>	The maximum length of the request queue. If this length has been reached, and further requests arrive, <code>jacorb.poa.queue_wait</code> specifies what to do. Default is 100.	integer
<code>jacorb.poa.queue_min</code>	If <code>jacorb.poa.queue_wait</code> is On, and the request queue gets full, then the POA blocks until the queue contains no more than <code>queue_min</code> requests. Default is 10.	integer

Table 3.5: Implementation Repository Configuration

Property	Description	Type
<code>jacorb.use_imr</code>	Switch on to contact the Implementation Repository (IR) on every server start-up. Default is off.	boolean
<code>jacorb.use_imr_endpoint</code>	Switch off to prevent writing the IMR address into server IORs. This property is ignored if <code>jacorb.use_imr = off</code> . Default is off.	boolean
<code>jacorb.imr.allow_auto_register</code>	If set to on servers that don't already have an entry on their first call to the IR, will get automatically registered. Otherwise, an <code>UnknownServer</code> exception is thrown. Default is off.	boolean

Table 3.5: Implementation Repository Configuration

Property	Description	Type
<code>jacorb.imr.check_object_liveness</code>	If set on the IR will try to ping every object reference that it is going to return. If the reference is not alive, then <code>TRANSPORT</code> is thrown. Default is off.	boolean
<code>ORBInitRef.ImplementationRepository</code>	The initial reference for the IR.	URL
<code>jacorb.imr.table_file</code>	File in which the IR stores data.	file
<code>jacorb.imr.backup_file</code>	Backup data file for the IR.	file
<code>jacorb.imr.ior_file</code>	File to which the IR writes its IOR. This is usually referred to by the initial reference for the IR (configured above).	file
<code>jacorb.imr.timeout</code>	Time in milliseconds that the implementation will wait for a started server to register. After this timeout is exceeded the IR assumes the server has failed to start. Default is 12000 (2 minutes).	millisec.
<code>jacorb.imr.no_of_poas</code>	Initial number of POAs that can be registered with the IR. This is an optimization used to size internal data structures. This value can be exceeded. Default is 100.	integer
<code>jacorb.imr.no_of_servers</code>	Initial number of servers that can be registered with the IR. This is an optimization used to size internal data structures. This value can be exceeded. Default is 5.	integer
<code>jacorb.imr.port_number</code>	Starts the IMR on a fixed port (equivalent to the <code>-p</code> option).	integer
<code>jacorb.imr.connection_timeout</code>	Time in milliseconds that the IR waits until a connection from an application client is terminated. Default is 2000.	millisec.
<code>jacorb.implname</code>	The implementation name for persistent servers. Persistent servers should set this to a unique name. This is the service name that is registered in the IR.	name
<code>jacorb.java_exec</code>	Command used by the IR to start servers.	command

Table 3.6: Security Configuration

Property	Description	Type
<code>OASSSLPort</code>	The port number used by SSL, will be dynamically assigned by default.	port
<code>org.omg.PortableInterceptor.ORBInitializerClass.ForwardInit</code>	Portable interceptor required to support SSL. Not set by default.	class
<code>jacorb.security.access_decision</code>	The qualified classname of access decision object.	class
<code>jacorb.security.principal_authenticator</code>	A list of qualified classnames of principle authenticator objects, separated by commas (no whitespaces.). The first entry (that can be successfully created) will be available through the <code>principal_authenticator</code> property.	class

Table 3.6: Security Configuration

Property	Description	Type
<code>jacorb.ssl.socket_factory</code>	The qualified classname of the SSL socket factory class.	class
<code>jacorb.ssl.server_socket_factory</code>	The qualified classname of the SSL server socket factory class.	class
<code>jacorb.security.change_ssl_roles</code>	Exchange SSL client server roles to enforce client authentication. Beware: this causes problems with peers that not prepared to handle this role change. Default is off.	boolean
<code>jacorb.security.support_ssl</code>	Whether SSL security is supported. Default is off.	boolean
<code>jacorb.security.ssl.client.supported_options</code>	SSL client supported options - IIOP/SSL parameters (numbers are hex values, without the leading 0x): NoProtection = 1, EstablishTrustInClient = 40, EstablishTrustInTarget = 20, mutual authentication = 60. Default is 0. Please see the programming guide for more explanation.	integer
<code>jacorb.security.ssl.client.required_options</code>	SSL client required options (See IIOP/SSL parameters above). Default is 0.	integer
<code>jacorb.security.ssl.server.supported_options</code>	SSL server supported options (See IIOP/SSL parameters above). Default is 0.	integer
<code>jacorb.security.ssl.server.required_options</code>	SSL server required options (See IIOP/SSL parameters above). Default is 0.	integer
<code>jacorb.security.ssl.corbaloc_ssliop.supported_options</code>	Used in conjunction with <code>jacorb.security.ssl.corbaloc_ssliop.required_options</code> . If these properties are set, then two values will be placed in the IOR, "corbaloc:ssliop and "ssliop. If not set, only EstablishTrustInTarget is used for both supported and required options.	integer
<code>jacorb.security.ssl.corbaloc_ssliop.required_options</code>	Default is 0.	integer
<code>jacorb.security.keystore</code>	The name and location of the keystore. This may be absolute or relative to the home directory. NOTE (for Sun JSSE users): The <code>javax.net.ssl.trustStore [Password]</code> properties doesn't seem to take effect, so you may want to add trusted certificates to normal keystores. In this case, please set the property <code>jacorb.security.jsse.trustees.from_ks</code> to on, so trusted certificates are taken from the keystore instead of a dedicated truststore.	file
<code>jacorb.security.keystore_password</code>	The keystore password.	string

Table 3.6: Security Configuration

Property	Description	Type
<code>jacorb.security.trustees</code>	Files with public key certificates of trusted Certificate Authorities (CA). WARNING: If no CA certificates are present, the IAIK chain verifier will accept ALL otherwise valid chains.	file
<code>jacorb.security.default_user</code>	The name of the default key alias to look up in the keystore.	name
<code>jacorb.security.default_password</code>	The name of the default key alias to look up in the keystore.	string
<code>jacorb.security.iaik_debug</code>	Sets IAIKS SSL classes to print debug output to standard output. Default is off.	boolean
<code>jacorb.security.jsse.trustees_from_ks</code>	Sun JSSE specific settings: Use the keystore to take trusted certificates from. Default is off.	boolean
<code>jacorb.security.ssl.server.cipher_suites</code>	A comma-separated list of cipher suite names which must NOT contain whitespaces. See the JSSE documents on how to obtain the correct cipher suite strings.	string
<code>jacorb.security.ssl.client.cipher_suites</code>	See <code>jacorb.security.ssl.server.cipher_suites</code> above.	string

4 Getting Started

Before we explain an example in detail, we look at the general process of developing CORBA applications with JacORB. We'll follow this roadmap when working through the example. The example can be found in `demo/grid` which also contains a build file so that the development steps do not have to be carried out manually every time. Still, you should know what is going on.

As this document gives only a short introduction to JacORB programming and does not cover all the details of CORBA IDL, we recommend that you also look at the other examples in the `demo/` directory. These are organized so as to show how the different aspects of CORBA IDL can be used with JacORB.

4.1 JacORB development: an overview

The steps we will generally have to take are:

1. write an IDL specification.
2. compile this specification with the IDL compiler to generate Java classes (Java interfaces, helper and holder classes, as well as stubs and skeletons).
3. write an implementation for the Java interface generated in step 2
4. write a "Main" class that instantiates the server implementation and registers it with the ORB
5. write a client class that retrieves a reference to the server object and makes remote invocations, i.e. CORBA calls.

4.2 IDL specifications

Our example uses a simple server the definition of which should be clear if you know IDL. Its interface is given in `server.idl`. All the source code for this example can be found in `JacORB2_0/demo/grid`.

```
// server.idl
// IDL definition of a 2-D grid:
module demo
{
    module grid
    {
        interface MyServer
        {
            typedef fixed <5,2> fixedT;

            readonly attribute short height; // height of the grid
            readonly attribute short width;  // width of the grid

            // set the element [n,m] of the grid, to value:
            void set(in short n, in short m, in fixedT value);

            // return element [n,m] of the grid:
            fixedT get(in short n, in short m);

            exception MyException
            {
                string why;
            };

            short opWithException() raises( MyException );
        };
    };
};
```

4.3 Generating Java classes

Feeding this file into the IDL compiler

```
$ idl -d ./generated server.idl
```

produces a number of Java classes that represent the IDL definitions. This is done according to a set of rules known as the IDL-to-Java language mapping as standardized by the OMG. If you are interested in the details of the language mapping, i.e. which IDL language construct is mapped to which Java language construct, please consult the specifications available from <http://www.omg.org>. The language mapping used by the JacORB IDL compiler is the one defined in CORBA 2.3 and is explained in detail in [BVD01]. For practical usage, please consult the examples in the demo directory.

The most important Java classes generated by the IDL compiler are the interfaces `MyServer` and `MyServerOperations`, and the stub and skeleton files `_MyServerStub`,

MyServerPOA and MyServerPOATie. We will use these classes in the client and server as well as in the implementation of the grid's functionality and explain each in turn.

Note that the IDL compiler will produce a directory structure for the generated code that corresponds to the module structure in the IDL file, so it would have produced a subdirectory `demo/grid` in the current directory had we not directed it to put this directory structure to `./generated` by using the compiler's `-d` switch. Where to put the source files for generated classes is a matter of taste. Some people prefer to have everything in one place (as using the `-d` option in this way achieves), others like to have one subdirectory for the generated source code and another for the output of the Java compiler, i.e. for the `.class` files.

4.4 Implementing the interface

Let's try to actually provide an implementation of the functionality promised by the interface. The class which implements that interface is called `gridImpl`. Apart from providing a Java implementation for the operations listed in the IDL interface, it has to inherit from a generated class that both defines the Java type that represents the IDL type `MyServer` and contains the code needed to receive remote invocations and return results to remote callers. This class is `MyServerPOA`.

You might have noticed that this approach is impractical in situations where your implementation class needs to inherit from other classes. As Java only has single inheritance for implementations, you would have to use an alternative approach — the “tie”-approach — here. The tie approach will be explained later.

Here is the Java code for the grid implementation. It uses the Java library class `java.math.BigDecimal` for values of the IDL fixed-point type `fixedT`:

```
package demo.grid;

/**
 * A very simple implementation of a 2-D grid
 */

import demo.grid.MyServerPackage.MyException;

public class gridImpl
    extends MyServerPOA
{
    protected short height = 31;
    protected short width = 14;
    protected java.math.BigDecimal[][] mygrid;

    public gridImpl()
```

```
{
    mygrid = new java.math.BigDecimal[height][width];
    for( short h = 0; h < height; h++ )
    {
        for( short w = 0; w < width; w++ )
        {
            mygrid[h][w] = new java.math.BigDecimal("0.21");
        }
    }
}

public java.math.BigDecimal get(short n, short m)
{
    if( ( n <= height ) && ( m <= width ) )
        return mygrid[n][m];
    else
        return new java.math.BigDecimal("0.01");
}

public short height()
{
    return height;
}

public void set(short n, short m, java.math.BigDecimal value)
{
    if( ( n <= height ) && ( m <= width ) )
        mygrid[n][m] = value;
}

public short width()
{
    return width;
}

public short opWithException()
    throws demo.grid.MyServerPackage.MyException
{
    throw new demo.grid.MyServerPackage.MyException("This is only a test exc
}
}
```

4.5 Writing the Server

To actually instantiate a `gridImpl` object which can be accessed remotely as a CORBA object of type `MyServer`, you have to instantiate it in a main method of some other class and register it with a component of the CORBA architecture known as the *Object Adapter*. Here is the class `Server` which does all that is necessary to activate a CORBA object of type `MyServer` from a Java `gridImpl` object:

```
package demo.grid;

import java.io.*;
import org.omg.CosNaming.*;

public class Server
{
    public static void main( String[] args )
    {
        org.omg.CORBA.ORB orb = org.omg.CORBA.ORB.init(args, null);
        try
        {
            org.omg.PortableServer.POA poa =
                org.omg.PortableServer.POAHelper.narrow(
                    orb.resolve_initial_references("RootPOA"));

            poa.the_POAManager().activate();

            org.omg.CORBA.Object o = poa.servant_to_reference(new gridImpl());

            if( args.length == 1 )
            {
                // write the object reference to args[0]

                PrintWriter ps = new PrintWriter(
                    new FileOutputStream(
                        new File( args[0] )));
                ps.println( orb.object_to_string( o ) );
                ps.close();
            }
            else
            {
                // register with the naming service

                NamingContextExt nc =
                    NamingContextExtHelper.narrow(
                        orb.resolve_initial_references("NameService"));
                nc.bind( nc.to_name("grid.example"), o);
            }
        }
    }
}
```

```

        }
    }
    catch ( Exception e )
    {
        e.printStackTrace();
    }
    orb.run();
}
}

```

After initializing the ORB we need to obtain a reference to the object adapter — the POA — by asking the ORB for it. The ORB knows about a few initial references that can be retrieved using simple names like “RootPOA”. The returned object is an untyped reference of type `CORBA.Object` and thus needs to be narrowed to the correct type using a static method `narrow()` in the helper class for the type in question. We now have to activate the POA because any POA is created in “holding” state in which it does not process incoming requests. After calling `activate()` on the POA’s `POAManager` object, the POA is in an active state and can now be asked to create a CORBA object reference from a Java object also known as a `Servant`.

In order to make the newly created CORBA object accessible, we have to make its object reference available. This is done using a publicly accessible directory service, the naming server. A reference to the naming service is obtained by calling `orb.resolve_initial_references("NameService")` on the ORB and narrowing the reference using the `narrow()` method found in class `org.omg.CosNaming.NamingContextExtHelper`. Having done this, you should call the `bind()` operation on the name server. The name for the object which has to be supplied as an argument to `bind()` is not simply a string. Rather, you need to provide a sequence of `CosNaming.NameComponents` that represent the name. In the example, we chose to use an extended Name Server interface that provides us with a more convenient conversion operation from strings to Names.

4.6 Writing a client

Finally, let’s have a look at the client class which invokes the server operations:

```

package demo.grid;

import org.omg.CosNaming.*;

public class Client
{
    public static void main(String args[])
    {
        try
        {

```



```
MyServer grid;
org.omg.CORBA.ORB orb = org.omg.CORBA.ORB.init(args,null);

if(args.length==1 )
{
    // args[0] is an IOR-string
    grid = MyServerHelper.narrow(orb.string_to_object(args[0]));
}
else
{
    NamingContextExt nc =
        NamingContextExtHelper.narrow(
            orb.resolve_initial_references("NameService"));

    grid = MyServerHelper.narrow(
        nc.resolve(nc.to_name("grid.example")));
}

short x = grid.height();
System.out.println("Height = " + x);

short y = grid.width();
System.out.println("Width = " + y);

x -= 1;
y -= 1;

System.out.println("Old value at (" + x + "," + y + "): " +
    grid.get( x,y));

System.out.println("Setting (" + x + "," + y + ") to 470.11");

grid.set( x, y, new java.math.BigDecimal("470.11"));

System.out.println("New value at (" + x + "," + y + "): " +
    grid.get( x,y));

try
{
    grid.opWithException();
}
catch (jacorb.demo.grid.MyServerPackage.MyException ex)
{
    System.out.println("MyException, reason: " + ex.why);
}
```

```

    }
    catch (Exception e)
    {
        e.printStackTrace();
    }
}
}

```

After initializing the ORB, the client obtains a reference to the “grid” service by locating the reference using the name service. Again, resolving the name is done by getting a reference to the naming service by calling `orb.resolve_initial_references("NameService")` and querying the name server for the “grid” object by calling `resolve()`. The argument to the resolve operation is, again, a string that is converted to a `Name`. The result is an object reference of type `org.omg.CORBA.Object` which has to be narrowed to the type we are expecting, i.e. `MyServer`.

After compiling everything we’re now ready to actually run the server and the client on different (virtual) machines. Make sure the name server is running before starting either the server or the client. If it isn’t, type something like:

```
$ ns /home/me/public_html/NS_Ref
```

where `/home/me/public_html/NS_Ref` is the name of a locally writable file which can be read by using the URL given in both the remote client and server code. (This is to avoid using a well-known address for the name server, so both client and server look up the location of the name server via the URL and later communicate with it directly.)

You can now launch the server:

```
$ jaco demo.grid.Server
```

The client can be invoked on any machine you like:

```
$ jaco demo.grid.Client
```

Running the client after starting the server produces the following output on your terminal:

```

Height = 31
Width = 14
Old value at (30,13): 0.21
Setting (30,13) to 470.11
New value at (30,13): 470.11
MyException, reason: This is only a test exception, no harm done :-)
done.

```

4.6.1 The Tie Approach

If your implementation class cannot inherit from the generated servant class `MyServerPOA` because, e.g., you need to inherit from another base class, you can use the tie approach. Put simply, it replaces

inheritance by delegation. Instead of inheriting from the generated base class, your implementation needs to implement the generated *operations interface* `MyServerOperations`:

```
package demo.grid;

import demo.grid.MyServerPackage.MyException;

public class gridOperationsImpl
    implements MyServerOperations
{
    ...
}
```

Your server is then written as follows:

```
package demo.grid;

import java.io.*;
import org.omg.CosNaming.*;

public class TieServer
{
    public static void main( String[] args )
    {
        org.omg.CORBA.ORB orb =
            org.omg.CORBA.ORB.init(args, null);
        try
        {
            org.omg.PortableServer.POA poa =
                org.omg.PortableServer.POAHelper.narrow(
                    orb.resolve_initial_references("RootPOA"));

            // use the operations implementation and wrap it in
            // a tie object

            org.omg.CORBA.Object o =
                poa.servant_to_reference(
                    new MyServerPOATie( new gridOperationsImpl() ) );

            poa.the_POAManager().activate();

            if( args.length == 1 )
            {
                // write the object reference to args[0]
```

```
        PrintWriter ps = new PrintWriter(
            new FileOutputStream(new File( args[0] )));
        ps.println( orb.object_to_string( o ) );
        ps.close();
    }
    else
    {
        NamingContextExt nc =
            NamingContextExtHelper.narrow(
                orb.resolve_initial_references("NameService"));
        NameComponent [] name = new NameComponent[1];
        name[0] = new NameComponent("grid", "whatever");
        nc.bind( name, o );
    }
}
catch ( Exception e )
{
    e.printStackTrace();
}
orb.run();
}
```

5 The JacORB Name Service

Name servers are used to locate objects using a human-readable reference (their name) rather than a machine or network address. If objects providing a certain service are looked up using the service name, their clients are decoupled from the actual locations of the objects that provide this service. The binding from name to service can be changed without the clients needing to know.

JacORB provides an implementation of the OMG's Interoperable Naming Service (INS) which supports binding names to object references and to lookup object references using these names. It also allows clients to easily convert names to strings and vice versa. The JacORB name service comprises two components: the name server program, and a set of interfaces and classes used to access the service.

One word of caution about using JDK 1.2 with the JacORB naming service: JDK 1.2 comes with a couple of outdated and apparently buggy naming service classes that do not work properly with JacORB. To avoid having these classes loaded and used inadvertently, please make sure that you always use the `NamingContextExt` interface rather than the plain `NamingContext` interface in your code. Otherwise, you will see your application receive null pointer or other exceptions.

5.1 Running the Name Server

The JacORB name server is a process that needs to be started before the name service can be accessed by programs. Starting the name server is done by typing on the command line either simply

```
$ ns [<ior filename>][-p port] [-t <timeout>]
```

You can also start the Java interpreter explicitly by typing

```
$ jaco jacobnaming.NameServer [<filename>][-p port] [-t <timeout>]
```

In the example

```
$ ns /home/me/public_html/NS_Ref
```

we direct the name server process to write location information (its own object reference) to the file `/home/me/public_html/NS_Ref`. A client-side ORB uses this file to locate the name server process. The client-side ORB does not, however, need to be able to access the file through a local or shared file system because the file is read as a resource by using a URL pointing to it. This implies that the name server log file is accessible through a URL in the first place, i.e., that you know of a web server in your domain which can answer HTTP request to read the file.

The advantage of this approach is that clients do not need to rely on a hard-coded well known port and

that the name server is immediately available world-wide if the URL uses HTTP. If you want to restrict name server visibility to your domain (assuming that the log file is on a shared file system accessible throughout your domain) or you do not have access to a web server, you can use file URLs rather than HTTP URLs, i.e. the URL pointing to your name server log file would look like

```
file:/home/brose/public_html/NS_Ref
```

rather than

```
http://www.inf.fu-berlin.de/~brose/NS_Ref
```

Specifying file URLs is also useful if clients and servers are run on a single machine that may have no network connection at all. Please note that the overhead of using HTTP is only incurred once — when the clients first locate the name server. Subsequent requests will use standard CORBA operation invocations which means they will be IIOP requests (over TCP). In JacORB 1.4, the file name argument was made optional because the JacORB 1.4 name server also answers requests that are made using simplified corbaloc: URLs of the form `corbaloc::ip-address:port/NameService`. This means that all you need to know to construct an object reference to your name service is the IP address of the machine and the port number the server process is listening on (the one specified using `-p`).

The name server stores its internal state, i.e., the name bindings in its context, in files in the current directory unless the property `jacorb.naming.db_dir` is set to a different directory name. This saving is done when the server goes down regularly, i.e. killing the server with CTRL-C will result in loss of data. The server will restore state from its files if any files exist and are non-empty.

The second parameter is a port number on which you want the name service to listen for incoming requests. If this parameter is not set, the name server will come up on the first free port it is provided with by the operating system. The port number can also be set using specific properties in the properties file, but the `-p` switch was added merely for convenience.

The last parameter is a time-out value in msecs. If this value is set, the name server will shut down after the specified amount of time and save its state. This is useful if the name server is registered with the Implementation Repository and can thus be restarted on demand.

Configuring a Default Context

Configuring a naming context (i.e. a name server) as the ORB's default or root context is done by simply writing the URL that points to this server's bootstrap file to the properties file `.jacorb.properties`. Alternatively, you can set this file name in the property `ORBInitRef.NameService` either on the command line or within the application as described in 2.2. After the default context has thus been configured, all operations on the `NamingContextExt` object that was retrieved by a call to `orb.resolve_initial_references("NameService")` will go to that server — provided it's running or can be started using the Implementation Repository.

5.2 Accessing the Name Service

The JacORB name service is accessed using the standard CORBA defined interface:

```
// get a reference to the naming service
ORB orb = ORB.init(args, null);
org.omg.CORBA.Object o = orb.resolve_initial_references("NameService")
NamingContextExt nc = NamingContextExtHelper.narrow( o );

// look up an object
server s = serverHelper.narrow( nc.resolve(nc.to_name("server.service")) );
```

Before an object can be looked up, you need a reference to the ORB's name service. The standard way of obtaining this reference is to call `orb.resolve_initial_references("NameService")`. In calls using the standard, extended name service interface, object names are represented as arrays of `NameComponents` rather than as strings in order to allow for structured names. Therefore, you have to construct such an array and specify that the name's name is "server" and that it is of kind "service" (rather than "context"). Alternatively, you can convert a string "server.service" to a name by calling the `NamingContextExt` interface's `to_name()` operation, as shown above.

Now, we can look up the object by calling `resolve()` on the naming context, supplying the array as an argument.

5.3 Constructing Hierarchies of Name Spaces

Like directories in a file system, name spaces or contexts can contain other contexts to allow hierarchical structuring instead of a simple flat name space. The components of a structured name for an object thus form a path of names, with the innermost name space directly containing the name binding for the object. This can very easily be done using `NameManager` but can also be explicitly coded.

A new naming context within an enclosing context can be created using either `new_context()` or `bind_new_context()`. The following code snippet requests a naming context to create an inner or subcontext using a given name and return a reference to it:

```
// get a reference to the naming service
ORB orb = ORB.init();
org.omg.CORBA.Object o =
    orb.resolve_initial_references("NameService");
NamingContextExt rootContext =
    NamingContextExtHelper.narrow( o );

// look up an object
NameComponent[] name = new NameComponent[1];
name[0] = new NameComponent("sub", "context");
NamingContextExt subContext =
    NamingContextExtHelper.narrow( rootContext.bind_new_context( name ) );
```

Please note that the JacORB naming service always uses `NamingContextExt` objects internally, even if the operation signature indicates `NamingContext` objects. This is necessary because of the limitations with JDK 1.2 as explained at the beginning of this section.

5.4 NameManager — A simple GUI front-end to the Naming Service

The graphical front-end to the name service can be started by simply calling

```
$ nmgr
```

The GUI front-end will simply look up the default context and display its contents. Figure 5.1 gives a screen shot.




Figure 5.1: NameManager Screenshot

NameManager has menus that let you unbind names and create or delete naming contexts within the root context. Creating a nested name space, e.g., can be done by selecting the `RootContext` and bringing up a context by clicking the right mouse button. After selecting “new context” from that menu, you will be prompted to enter a name for the new, nested context.

6 The server side: POA, Threads

This chapter describes the facilities offered by JacORB for controlling how servers are started and executed. These include an activation daemon, the Portable Object Adapter (POA), and threading.

This chapter gives only a very superficial introduction to the POA. A thorough explanation of how the POA can be used in different settings and of the different policies and strategies it offers is beyond our scope here, but can be found in [BVD01]. Other references that explain the POA are [HV99, Vin98]. More in-depth treatment in C++ can be found in the various C++-Report Columns on the POA by Doug Schmidt and Steve Vinoski. These articles are available at <http://www.cs.wustl.edu/~schmidt/report-doc.html>. The ultimate reference, of course, is the CORBA specification.

6.1 POA

The POA provides a comprehensive set of interfaces for managing object references and servants. The code written using the POA interfaces is now portable across ORB implementations and has the same semantics in every ORB that is compliant to CORBA 2.2 or above.

The POA defines standard interfaces to do the following:

- Map an object reference to a servant that implements that object
- Allow transparent activation of objects
- Associate policy information with objects
- Make a CORBA object persistent over several server process lifetimes

In the POA specification, the use of pseudo-IDL has been deprecated in favor of an approach that uses ordinary IDL, which is mapped into programming languages using the standard language mappings, but which is locality constrained. This means that references to objects of these types may not be passed outside of a server's address space. The POA interface itself is one example of a locality-constrained interface.

The object adapter is that part of CORBA that is responsible for creating CORBA objects and object references and — with a little help from skeletons — dispatching operation requests to actual object implementations. In cooperation with the Implementation Repository it can also activate objects, i.e. start processes with programs that provide implementations for CORBA objects.

6.2 Threads

JacORB currently offers one server-side thread model. The POA responsible for a given request will obtain a request processor thread from a central thread pool. The pool has a certain size which is always between the maximum and minimum value configured by setting the properties `jacorb.poa.thread_pool_max` and `jacorb.poa.thread_pool_min`.

When a request arrives and the pool is found to contain no threads because all existing threads are active, new threads may be started until the total number of threads reaches `jacorb.poa.thread_pool_max`. Otherwise, request processing is blocked until a thread is returned to the pool. Upon returning threads that have finished processing a request to the pool, it must be decided whether the thread should actually remain in the pool or be destroyed. If the current pool size is above the minimum, a processor thread will not be put into the pool again. Thus, the pool size always oscillates between max and min.

Setting min to a value greater than one means keeping a certain number of threads ready to service incoming requests without delay. This is especially useful if you know that requests are likely to come in in a bursty fashion. Limiting the pool size to a certain maximum is done to prevent servers from occupying all available resources.

Request processor threads usually run at the highest thread priority. It is possible to influence thread priorities by setting the property `jacorb.poa.thread_priority` to a value between Java's `Thread.MIN_PRIORITY` and `Thread.MAX_PRIORITY`. If the configured priority value is invalid JacORB will assign maximum priority to request processing threads.

7 Implementation Repository

“... it is very easy to be blinded to the essential uselessness of them by the sense of achievement you get from getting it to work at all. In other words — and that is a rock-solid principle on which the whole of the Corporation’s Galaxywide success is founded — their fundamental design flaws are completely hidden by their superficial design flaws.”

D. Adams: So Long and Thanks for all the Fish

The Implementation Repository is not, as its name suggests, a database of implementations. Rather, it contains information about where requests to specific CORBA objects have to be redirected and how implementations can be transparently instantiated if, for a given request to an object, none is reachable. “Instantiating an implementation” means starting a server program that hosts the target object. In this chapter we give a brief overview and a short introduction on how to use the Implementation Repository. For more details please see [[HV99](#)].

7.1 Overview

Basically, the Implementation Repository (ImR) is an indirection for requests using persistent object references. A persistent object reference is one that was created by a POA with a PERSISTENT lifespan policy. This means that the lifetime of the object is longer than that of its creating POA. Using the Implementation Repository for objects the lifetime of which does not exceed the life time of its POA does not make sense as the main function of the Implementation Repository is to take care that such a process exists when requests are made — and to start one if necessary.

To fulfill this function, the ImR has to be involved in every request to “persistent objects”. This is achieved by rewriting persistent object references to contain *not* the address of its server process but the address of the ImR. Thus, requests will initially reach the ImR and not the actual server — which may not exist at the time of the request. If such a request arrives at the ImR, it looks up the server information in its internal tables to determine if the target object is reachable or not. In the latter case, the ImR has to have information about how an appropriate server process can be started. After starting this server, the client receives a LOCATION_FORWARD exception from the ImR. This exception, which contains a new object reference to the actual server process now, is handled by its runtime system transparently. As a result, the client will automatically reissue its request using the new reference, now addressing the target directly.

7.2 Using the JacORB Implementation Repository

The JacORB Implementation Repository consists of two separate components: a repository process which need only exist once in a domain, and process startup daemons, which must be present on every host that is to start processes. Note that none of this machinery is necessary for processes that host objects with a TRANSIENT life time, such as used by the RootPOA.

First of all, the central repository process (which we will call ImR in the following) must be started:

```
$ imr [-n] [-p <port>] [-i <ior_file>][-f <file>][-b <file>] [-a]
```

The ImR is located using the configuration property `ORBInitRef.ImplementationRepository`. This property must be set such that a http connection can be made and the ImR's IOR can be read. Next, startup daemons must be created on selected hosts. To do this, the following command must be issued on each host:

```
$ imr_ssd
```

When a startup daemon is created, it contacts the central ImR.

To register a program such that the ImR can start it, the following command is used (on any machine that can reach the ImR):

```
$ imr_mg add "AServerName" -c "jaco MyServer"
```

The `imr_mg` command is the generic way of telling the ImR to do something. It needs another command parameter, such as `add` in this case. To add a server to the ImR, an *implementation name* is needed. Here, it is `"AServerName"`. If the host where the server should be restarted is not the local one, use the `-h hostname` option. Finally, the ImR needs to know how to start the server. The string `"jaco MyServer"` tells it how. The format of this string is simply such that the server daemon can execute it (using the Java API call `exec()`), i.e. it must be intelligible to the target host's operating system. For a Windows machine, this could, e.g. be `"start jaco MyServer"` to have the server run in its own terminal window, under Unix the same can be achieved with `"xterm -e jaco MyServer"`.

The startup command is a string that is passed as the *single* argument to `java Runtime.exec()` method, without interpreting it or adding anything. Since `Runtime.exec()` has system-dependent behaviour, the startup string has to reflect that. While for most unix systems it is sufficient to avoid shell-expansions like `*` and `~`, windows-based systems do not pass the string to a commandline interpreter so a simple `jaco MyServer` will fail even if it works if directly typed in at the dos prompt. Therefore you have to "wrap" the core startup command in a call to a commandline interpreter. On NT the following startup command will do the job: `cmd /c "jaco MyServer"`. Please keep in mind that if you use the `imr_mg` command to set the startup command, you have to escape the quotes so they appear inside of the resulting string.

If you don't intend to have your server automatically started by the ImR you can also set the property `"jacorb.imr.allow_auto_register"` or use the `-a` switch of the ImR process. If this property is set, the ImR will automatically create a new entry for a server on POA activation, if the server has not been registered previously. In this case you don't have to use the ImR Manager to register your server.

For a client program to be able to issue requests, it needs an object reference. Up to this point, we haven't said anything about how persistent object references come into existence. Reference creation

happens as usual, i.e. in the server application one of the respective operations on a POA is called. For a reference to be created as “persistent”, the POA must have been created with a PERSISTENT lifespan policy. This is done as in the following code snippet:

```
/* init ORB and root POA */
orb = org.omg.CORBA.ORB.init(args, props);
org.omg.PortableServer.POA rootPOA =
    org.omg.PortableServer.POAHelper.narrow(
        orb.resolve_initial_references("RootPOA"));

/* create policies */

org.omg.CORBA.Policy [] policies = new org.omg.CORBA.Policy[2];
policies[0] = rootPOA.create_id_assignment_policy(
    IdAssignmentPolicyValue.USER_ID);
policies[1] = rootPOA.create_lifespan_policy(
    LifespanPolicyValue.PERSISTENT);

/* create POA */

POA myPOA = rootPOA.create_POA("XYZPOA",
    rootPOA.the_POAManager(), policies);

/* activate POAs */
poa.the_POAManager().activate();
```

(Note that in general the id assignment policy will be `USER_ID` for a POA with persistent object references because this id will often be a key into a database where the object state is stored). If a POA is created with this lifespan policy and the ORB property “`use_imr`” is set, the ORB will try to notify the ImR about this fact so the ImR knows it doesn’t need to start a new process for requests that target objects on this POA. To set the ORB policy, simply set the property `jacorb.use_imr=on`. The ORB uses another property, `jacorb.implname`, as a parameter for the notification, i.e. it tells the ImR that a process using this property’s value as its *implementation name* is present. If the server is registered with the ImR, this property value has to match the implementation name that is used when registering.

The application can set these properties on the command line using `java -Djacorb.implname=MyName`, or in the code like this:

```
/* create and set properties */
java.util.Properties props = new java.util.Properties();
props.setProperty("jacorb.use_imr", "on");
props.setProperty("jacorb.implname", "MyName");

/* init ORB */
orb = org.omg.CORBA.ORB.init(args, props);
```

There are a few things you have to consider especially when restoring object state at startup time or saving the state of your objects on shutdown. It is important that, at startup time, object initialization is complete when the object is activated because from this instant on operation calls may come in. The repository knows about the server when the first POA with a PERSISTENT lifespan policy registers, but does not forward object references to clients before the object is actually reachable. (Another, unreliable way to handle this problem is to increase the `jacorb.imr.object_activation_sleep` property, so the repository waits longer for the object to become ready again.)

When the server shuts down, it is equally important that object state is saved by the time the last POA in the server goes down because from this moment the Implementation Repository regards the server as down and will start a new one upon requests. Thus, a server implementor is responsible for avoiding reader/writer problems between servers trying to store and restore the object state. (One way of doing this is to use POA managers to set a POA to holding while saving state and to inactive when done.)

Please keep in mind that even if you don't have to save the state of your objects on server shutdown you *must* deactivate your POAs prior to exiting your process (or at least use `orb.shutdown(...)` which includes POA deactivation). Otherwise the ImR keeps the server as active and will return invalid IORs. In case of a server crash you can either notify the ImR manually by using the command `imr_mg setdown AServerName` or allow the ImR to detect the crashed server and restart it if necessary.

7.3 Server migration

The implementation repository offers another useful possibility: server migration. Imagine the following scenario: You have written your server with persistent POAs, but after a certain time your machine seems to be too slow to serve all those incoming requests. Migrating your server to a more powerful machine is the obvious solution. Using the implementation repository, client references do not contain addressing information for the slow machine, so server migration can be done transparently to client.

Assuming that you added your server to the repository, and it is running correctly.

```
$ imr_mg add AServerName -h a_slow_machine -c "jaco MyServer"
```

The first step is to *hold* the server, that means the repository delays all requests for that server until it is released again.

```
$ imr_mg hold AServerName
```

Now your server will not receive any requests for its registered POAs. If you can't shut your server down such that it sets itself down at the repository, i.e. your POAs are set to inactive prior to terminating the process, you can use

```
$ imr_mg setdown AServerName
```

to do that. Otherwise your POAs can't be reactivated at the repository because they are still logged as active.

If you want your server to be restarted automatically, you have to tell the repository the new host and maybe a new startup command.

```
$ imr_mg edit AServerName -h the_fastest_available_machine
```

```
-c "jaco MyServer"
```

If your server can be restarted automatically, you now don't even have to start it manually, but it is instead restarted by the next incoming request. Otherwise start it manually on the desired machine now.

The last step is to release the server, i.e. let all delayed requests continue.

```
$ imr_mg release AServerName
```

By now your server should be running on another machine, without the clients noticing.

7.4 A Note About Security

Using the imr can pose a major security threat to your system. Imagine the following standard setup: an imr is running on a machine, its IOR file is placed in a directory where it can be read by the web server, and several imr_ssds are running on other machines. An attacker can now execute processes on the machines the ssds are running on by taking the following steps:

1. Setting the `ORBInitRef.ImplementationRepository` property to the IOR file on your server.
2. Creating a new logical server with the desired command to execute as startup command on the desired host (where a ssd is running). This is the crucial point. The ssd calls `Runtime.exec()` with the supplied string, and there is no way to check if the command does what it is supposed to do, i.e. start a server.
3. Start the server with the imr_mg. The startup command of the server will be exec'd on the specified host.

Now this should not generally discourage you to use the imr but show you that there are risks, which can be reduced significantly nonetheless. There are several ways to encounter this threat and we don't consider this list to be complete:

1. Try to control the distribution of the IOR file. Hiding it should not be considered here, because *security by obscurity* is generally a bad approach. Try to make use of file system mechanisms like groups and ACLs.
2. Use a firewall which blocks incoming traffic. Keep in mind that if the attacker is inside of your protection domain, the firewall won't help. It is also not that hard to write a Trojan that can tunnel those firewalls that block incoming traffic.
3. Enforce SSL connections to the imr. This blocks all client connections that don't have a certificate signed by a CA of your choice. See chapter 12 for more information.

8 Dynamic Management of Any Values

by Jason Courage

The purpose of this chapter is to describe the DynAny specification, which is the specification for the dynamic management of Any values. This chapter only describes the main features of the DynAny specification; for the complete specification consult the appropriate chapter of the CORBA specification available from the OMG.

8.1 Overview

DynAny objects are used to dynamically construct and traverse Any values. A DynAny can represent a value of a basic type, such as boolean or long, or a constructed type, such as enum or struct.

8.2 Interfaces

The UML diagram below shows the relationship between the interfaces in the org.omg.DynamicAny module.




Figure 8.1: DynAny Relationships

The DynAny interface is the base interface that represents values of the basic types. For each constructed type there is a corresponding interface that extends the DynAny interface and defines operations specific to the constructed type. The table below lists the interfaces in the DynamicAny module and the types they represent.

Interface	Type
DynAny	basic types (boolean, long, etc.)
DynFixed	fixed
DynEnum	enum
DynStruct	struct
DynUnion	union
DynSequence	sequence
DynArray	array
DynValue*	non-boxed valuetype
DynValueBox*	boxed valuetype

* Not currently implemented by JacORB.

8.3 Usage Constraints

Objects that implement interfaces in the DynamicAny module are intended to be local to the process that constructs and uses them. As a result, references to these objects cannot be exported to other processes or externalized using `ORB::object_to_string`; an operation that attempts to do so will throw the MARSHAL system exception.

8.4 Creating a DynAny Object

The DynAnyFactory interface is used to create a DynAny object. There are two operations for creating a DynAny object; these are listed in the table below.

Operation	Description
<code>create_dyn_any</code>	Constructs a DynAny object from an Any value
<code>create_dyn_any_from_type_code</code>	Constructs a DynAny object from a TypeCode

The example below illustrates how to obtain a reference to the DynAnyFactory object and then use it to construct a DynAny object with each of the create operations. Exception handling is omitted for brevity.

The following line of code imports the classes in the DynamicAny package.

```
import org.omg.DynamicAny.*;
```

The following code segment obtains a reference to the DynAnyFactory object.

```
DynAnyFactory factory = null;
DynAny DynAny = null;
DynAny DynAny2 = null;
org.omg.CORBA.Any any = null;
org.omg.CORBA.TypeCode tc = null;
org.omg.CORBA.Object obj = null;

// obtain a reference to the DynAnyFactory
obj = orb.resolve_initial_references ("DynAnyFactory");

// narrow the reference to the correct type
factory = DynAnyFactoryHelper.narrow (obj);
```

The following code segment creates a DynAny with each of the create operations.

```
// create a DynAny object from an Any
any = orb.create_any ();
any.insert_long (1);
DynAny = factory.create_dyn_any (any);

// create a DynAny object from a TypeCode
tc = orb.get_primitive_tc (org.omg.CORBA.TCKind.tk_long);
DynAny2 = factory.create_dyn_any_from_type_code (tc);
```

If the Any value or TypeCode represents a constructed type then the DynAny can be narrowed to the appropriate subtype, as illustrated below.

The following IDL defines a struct type.

```
// example struct type
struct StructType
{
    long field1;
    string field2;
};
```

The following code segment illustrates the creation of a DynStruct object that represents a value of type StructType.

```

StructType type = null;
DynStruct dynStruct = null;

// create an Any that contains an object of type StructType
type = new StructType (999, "Hello");
any = orb.create_any ();
StructTypeHelper.insert (any, type);

// construct a DynAny from an Any and narrow it to a DynStruct
dynStruct = (DynStruct) factory.create_dyn_any (any);

```

8.5 Accessing the Value of a DynAny Object

The DynAny interface defines a set of operations for accessing the value of a basic type represented by a DynAny object. The operation to get a value of basic type <type> from a DynAny has the form `get_<type>`. The operation to insert a value of basic type <type> into a DynAny has the form `insert_<type>`. A `TypeMismatch` exception is thrown if the type of the operation used to get/insert a value into a DynAny object does not match the type of the DynAny.

The operations for accessing the value of a constructed type represented by a DynAny are defined in the interface specific to the constructed type. For example, the `DynStruct` interface defines the operation `get_members`, which returns a sequence of name/value pairs representing the members of the struct or exception represented by a DynStruct object.

8.6 Traversing the Value of a DynAny Object

DynAny objects can be viewed as an ordered collection of component DynAnys. For example, in a DynStruct object the ordered collection of component DynAnys is the members of the struct or exception it represents. For DynAny objects representing basic types or constructed types that do not have components, the collection of component DynAnys is empty.

All DynAny objects have a current position. For DynAnys representing constructed types that have components, the current position is the index of the component DynAny that would be obtained by a call to the `current_component` operation (described in the table below). The component DynAnys of a DynAny object are indexed from 0 to $n-1$, where n is the number of components. For DynAnys representing basic types, or constructed types that do not have components, the current position is fixed at the value -1.

The operations for traversing the component DynAnys of a DynAny object are common to all DynAny subtypes, hence they are defined in the DynAny base interface. The table below lists the operations available for traversing a DynAny object.

Operation	Description
-----------	-------------

Operation	Description
seek	Sets the current position to the specified index
rewind	Sets the current position to the first component (index 0)
next	Advances the current position to the next component
component_count	Returns the number of components
current_component	Returns the component at the current position

The following code segment illustrates one way of traversing the component DynAny's of a DynStruct object. As the DynStruct is traversed, the value of each component is obtained and printed. Exception handling is omitted for brevity.

```
DynAny curComp = null;

// print the value of the first component
curComp = dynStruct.current_component ();
System.out.println ("field1 = " + curComp.get_long ());

// advance to the next component
dynStruct.next ();

// print the value of the second component
curComp = dynStruct.current_component ();
System.out.println ("field2 = " + curComp.get_string ());
```

The next code segment illustrates another way to perform the same task.

```
// go back to the first component
dynStruct.rewind (); // same as calling seek (0)

// print the value of the first component
System.out.println ("field1 = " + dynStruct.get_long ());

// advance to the next component
dynStruct.seek (1);

// print the value of the second component
System.out.println ("field2 = " + dynStruct.get_string ());
```

As the second code segment illustrates, if the component `DynAny` represents a basic type, its value can be extracted (or inserted) by calling the accessor operation on the parent `DynAny` directly, rather than first obtaining the component using the `current_component` operation.

8.7 Constructed Types

This section describes the interfaces in the `DynamicAny` module that represent the constructed types supported by JacORB. Each of these interfaces extends the `DynAny` interface.

8.7.1 DynFixed

A `DynFixed` object represents a fixed value. Since IDL does not have a generic type to represent a fixed type, the operations in this interface use the IDL string type. The value represented by a `DynFixed` object can be accessed (as a string) using the `get_value` and `set_value` operations.

A `DynFixed` object has no components.

8.7.2 DynEnum

A `DynEnum` object represents a single enumerated value. The integer (ordinal) value of the enumerated value can be accessed with the `get_as_ulong` and `set_as_ulong` operations. The string (IDL identifier) value of the enumerated value can be accessed with the `get_as_string` and `set_as_string` operations.

A `DynEnum` object has no components.

8.7.3 DynStruct

A `DynStruct` object represents a struct value or an exception value. The `current_member_name` and `current_member_kind` operations return the name and `TCKind` value of the `TypeCode` of the member at the current position of the `DynStruct`. The members of the `DynStruct` can be accessed with the `get_members` and `set_members` operations.

The component `DynAnys` of a `DynStruct` object are the members of the struct or exception. A `DynStruct` representing an empty exception has no components.

8.7.4 DynUnion

A `DynUnion` object represents a union value. The value of the discriminator can be accessed using the `get_discriminator` and `set_discriminator` operations.

If the discriminator is set to a value that names a member of the union then that member becomes active. Otherwise, if the value of the discriminator does not name a member of the union then there is no active member.

If there is an active member, the member operation returns its value as a DynAny object, and the member_name and member_kind operations return its name and the TCKind value of its TypeCode. These operations throw an InvalidValue exception if the union has no active member.

A DynUnion object can have either one or two components. The first component is always the discriminator value. The second component is the value of the active member, if one exists.

8.7.5 DynSequence

A DynSequence object represents a sequence. The length of the sequence can be accessed using the get_length and set_length operations. The elements of the sequence can be accessed using the get_elements and set_elements operations.

The component DynAnys of a DynSequence object are the elements of the sequence.

8.7.6 DynArray

A DynArray object represents an array. The elements of the array can be accessed using the get_elements and set_elements operations.

The component DynAnys of a DynArray object are the elements of the array.

8.8 Converting between Any and DynAny Objects

The DynAny interface defines operations for converting between Any objects and DynAny objects. The from_any operation initialises the value of a DynAny with the value of a specified Any. A TypeMismatch exception is thrown if the type of the Any does not match the type of the DynAny. The to_any operation creates an Any from a DynAny.

As an example of how these operations might be useful, suppose one wants to dynamically modify the contents of some constructed type, such as a struct, which is represented as an Any. The following steps will accomplish this task:

1. A DynStruct object is constructed from the TypeCode of the struct using the DynAnyFactory::create_dyn_any_from_type_code operation.
2. The DynAny::from_any operation is used to initialise the value of the DynStruct with the value of the Any.
3. The contents of the DynStruct can now be traversed and modified.
4. A new Any can be created to represent the modified struct using the DynAny::to_any operation.

8.9 Further Examples

The demo/dynany directory of the JacORB repository contains example code illustrating the use of DynAny objects. Further code can be found in the `org.jacorb.test.orb.dynany` package of the JacORB-Test repository.

9 Objects By Value

Until CORBA 2.3, objects could only be passed using reference semantics: there was no way to specify that object state should be copied along with an object reference. A further restriction of the earlier CORBA versions was that all non-object types (structs, unions, sequences, etc.) were *values*, so you could not use, e.g. a reference-to-struct to construct a graph of structure values that contained shared nodes. Finally, there was no inheritance between structs.

All these shortcomings are addressed by the *objects-by-value* (OBV) chapters of the CORBA specification: the addition of stateful value types supports copy semantics for objects and inheritance for structs, boxed value types introduce reference semantics for base types, and abstract interfaces determine whether an argument is sent by-value or by-reference by the argument's runtime type. The introduction of OBV into CORBA presented a major shift in the CORBA philosophy, which had been to strictly avoid any dependence on implementation details (state, in particular). It also added a considerable amount of marshaling complexity and interoperability problems. (As a personal note: Even in CORBA 2.6, the OBV marshaling sections are still not particularly precise...)

JacORB 2.0 implements most of the OBV specification. Boxed value types and regular value types work as prescribed in the standard (including value type inheritance, recursive value types, and factories). Still missing in the current implementation is run-time support for abstract value types (although the compiler does accept the corresponding IDL syntax), and the marshaling of truncatable value types does not yet meet all the standard's requirements (and should thus be called "beta").

9.1 Example

To illustrate the use of various kinds of value types, here's an example which is also part of the demo programs in the JacORB distribution. The demo shows the use of boxed value types and a recursive stateful value type. Here's the IDL definition from `demo/value/server.idl`:

```
module demo {
  module value {

    valuetype boxedLong    long;
    valuetype boxedString  string;

    valuetype Node {
      public long id;
    };
  };
};
```


With a regular `long` parameter, a `null` reference would have resulted in a `BAD_PARAM` exception. With boxed value types, this usage is entirely legal and the result string returned from the `ValueServer` object is `''one or two null values''`.

A second new possibility of the reference semantics that can be achieved by “boxing” primitive IDL types is *sharing* of values. With primitive values, two variables can have copies of the same value, but they cannot both refer to the same value. This means that when one of the variables is changed, the other one retains its original value. With shared values that are *referenced*, both variables would always point to the same value.

The stateful value type `Node` is implemented by the programmer in a class `NodeImpl` (see the JacORB distribution for the actual code). The relationship between this implementation class and the corresponding IDL definition is not entirely trivial, and we will discuss it in detail below.

9.2 Factories

When an instance of a (regular) value type is marshaled over the wire and arrives at a server, a class that implements this value type must be found, so that a Java object can be created to hold the state information. For interface types, which are only passed by reference, something similar is accomplished by the POA, which accepts remote calls to the interface and delivers them to a local implementation class (the *servant*). For value type instances, there is no such thing as a POA, because they cannot be called remotely. Thus, the ORB needs a different mechanism to know which Java implementation class corresponds to a given IDL value type.

The CORBA standard introduces *value factories* to achieve this. Getting your value factories right can be anywhere from trivial to tricky (we will cover the details in a minute), and so the standard suggests that ORBs also provide convenience mechanisms to relieve programmers from writing value factories if possible. JacORB’s convenience mechanism is straightforward:

If the implementation class for an IDL value type A is named AImpl, resides in the same package as A, and has a no-argument constructor, then no value factory is needed for that type.

In other words, if your implementation class follows the common naming convention (“...Impl”), and it provides a no-arg constructor so that the ORB can instantiate it, then the ORB has all that it needs to (a) find the implementation class, and (b) create an instance of it (which is then initialized with the unmarshaled state from the wire).

This mechanism ought to save you from having to write a value factory 99% of the time. It works for all kinds of regular value types, including those with inheritance, and recursive types (where a type has members of its own type).

If you do need more control over the instance creation process, or the unmarshaling from the wire, you can write your own value factory class and register it with the ORB using `ORB.register_value_factory(repository_id, factory)`. The *factory* object needs to implement the interface `org.omg.CORBA.portable.ValueFactory`, which requires a single method:

```
public Serializable read_value (InputStream is);
```

When an instance of type *repository_id* arrives over the wire, the ORB calls the `read_value()` method, which must unmarshal the data from the input stream, create an instance of the appropriate implementation class from it, and return that.

The easiest way to implement this method is to create an instance of the implementation class, and pass it to the `read_value()` method of the given `InputStream`:

```
public Serializable read_value (InputStream is) {  
    A result = new AImpl();  
    return is.read_value(result);  
}
```

The `InputStream.read_value()` method registers the newly created instance in the stream's indirection table, and then reads the data from the stream and initializes the given value instance from it.

The value factory must be registered with the ORB using `register_value_factory()`. As a special convenience (defined in the CORBA standard), if the value factory class for type `A` is called `ADefaultFactory`, then the ORB will find it automatically and use it, unless a different factory has been explicitly registered.

It sometimes causes confusion that you can also define *factory methods* in a value type's IDL. These factory methods are completely unrelated to the unmarshaling mechanism discussed above; they are simply a portable means to declare what kinds of "constructors" a value type implementation should have. They are purely for local use, but since they are "factories", the corresponding methods must also be implemented in the type's `ValueFactory` implementation.

10 Interface Repository

Run-time type information in CORBA is managed by the ORB's *Interface Repository* (IR) component. It allows to request, inspect and modify IDL type information dynamically, e.g., to find out which operations an object supports. Some ORBs may also need the IR to find out whether a given object's type is a subtype of another, but most ORBs can do without the IR by encoding this kind of type information in the helper classes generated by the IDL compiler.

In essence, the IR is just another remotely accessible CORBA object that offers operations to retrieve (and in theory also modify) type information.

10.1 Type Information in the IR

The IR manages type information in a hierarchical containment structure that corresponds to the structure of scoping constructs in IDL specifications: modules contain definitions of interfaces, structures, constants etc. Interfaces in turn contain definitions of exceptions, operations, attributes and constants. Figure 10.1 illustrates this hierarchy.




Figure 10.1: Containers in the Interface Repository

The descriptions inside the IR can be identified in different ways. Every element of the repository has

a unique, qualified name which corresponds to the structure of name scopes in the IDL specification. An interface `I1` which was declared inside module `M2` which in turn was declared inside module `M1` thus has a qualified name `M1::M2::I1`. The IR also provides another, much more flexible way of naming IDL constructs using *Repository Ids*. There are a number of different formats for *RepositoryIds* but every Repository must be able to handle the following format, which is marked by the prefix "IDL:" and also carries a suffix with a version number, as in, e.g., "IDL:jacorb/demo/grid:1.0". The name component between the colons can be set freely using the IDL compiler directives `#pragma prefix` and `#pragma ID`. If no such directive is used, it corresponds to the qualified name as above.

10.2 Repository Design

When designing the Interface Repository, our goal was to exploit the Java reflection API's functionality to avoid having to implement an additional data base for IDL type descriptions. An alternative design is to use the IR as a back-end to the IDL compiler, but we did not want to introduce such a dependency and preferred to have a rather "light-weight" repository server. As it turned out, this design was possible because the similarities between the Java and CORBA object models allow us to derive the required IDL information at run time. As a consequence, we can even do without any IDL at compile time. In addition to this simplification, the main advantage of our approach lies in avoiding redundant data and possible inconsistencies between persistent IDL descriptions and their Java representations, because Java classes have to be generated and stored anyway.

Thus, the Repository has to load Java classes, interpret them using reflection and translate them into the appropriate IDL meta information. To this end, the repository realizes a reverse mapping from Java to IDL. Figure 10.2 illustrates this functionality, where f^{-1} denotes the reverse mapping, or the inverse of the language mapping.




Figure 10.2: The JacORB Interface Repository

10.3 Using the IR

For the ORB to be able to contact the IR, the IR server process must be running. To start it, simply type the `ir` command and provide the required arguments:

```
$ ir /home/brose/classes /home/brose/public_html/IR.Ref
```

The first argument is a path to a directory containing `.class` files and packages. The IR loads these classes and tries to interpret them as IDL compiler-generated classes. If it succeeds, it creates internal representations of the adequate IDL constructs. The second argument on the command line above is simply the name of the file where the IR stores its object reference for ORB bootstrapping.

To view the contents of the repository, you can use the GUI IRBrowser tool or the query command. First, let's query the IR for a particular repository ID. JacORB provides the command `qir` ("query IR") for this purpose:

```
$ qir IDL:raccoon/test/cyberchair/Paper:1.0
```

As result, the IR returns an `InterfaceDef` object, and `qir` parses this and prints out:

```
interface Paper
{
    void read(out string arg_0);
    raccoon::test::cyberchair::Review getReview(in long arg_0);
    raccoon::test::cyberchair::Review submitReview(
        in string arg_0, in long a rg_1);
    void listReviews(out string arg_0);
};
```

To start the IRBrowser, simply type

```
$ irbrowser
```

Figure 10.3 gives a screen shot of the IR browser.

The Java classes generated by the IDL compiler using the standard OMG IDL/Java language mapping do not contain enough information to rebuild all of the information contained in the original IDL file. For example, determining whether an attribute in an interface was `readonly` or not is not possible, or telling the difference between `in` and `inout` parameter passing modes. Moreover, IDL modules are not explicitly represented in Java, so telling whether a directory in the class path represents an IDL module is not easily possible. For these reasons, the JacORB IDL compiler generates a few additional classes that hold the required extra information if the compiler switch `-ir` is used when compiling IDL files:

```
$ idl -ir myIdlFile.idl
```

The additional files generated by the compiler are:

- a `_XModule.java` class file for any IDL module X
- a `YIRHelper.java` class file for any interface Y.

If no `.class` files that are compiled from these extra classes are found in the class path passed to the IR server process, the IR will not be able to derive any representations. Note that the IDL compiler does not make any non-compliant modifications to any of the standard files that are defined in the Java language mapping — there is only additional information.

One more caveat about these extra classes: The compiler generates the `_XModule.java` class only for genuine modules. Java package scopes created by applying the `-d` switch to the IDL compiler do not represent proper modules and thus do not generate this class. Thus, the contents of these directories will not be considered by the IR.

When an object's client calls the `get_interface()` operation, the ORB consults the IR and returns an `InterfaceDef` object that describes the object's interface. Using `InterfaceDef` operations on this description object, further description objects can be obtained, such as descriptions for operations or attributes of the interface under consideration.

The IR can also be called like any other CORBA object and provides `lookup()` or `lookup_name()` operations to clients so that definitions can be searched for, given a qualified name. Moreover, the complete contents of individual containers (modules or interfaces) can be listed.

Interface Repository meta objects provide further description operations. For a given `InterfaceDef` object, we can inspect the different meta objects contained in this object (e.g., `OperationDef` objects). It is also possible to obtain descriptions in form of a simple structure of type `InterfaceDescription` or `FullInterfaceDescription`. Since structures are passed by value and a `FullInterfaceDescription` fully provides all contained descriptions, no further — possibly remote — invocations are necessary for searching the structure.




Figure 10.3: IRBrowser Screenshot

11 The JacORB Appligator

by Sebastian Müller and Steve Osselton

Version 1.4 of JacORB includes a new implementation of the Appligator. This is a portable interceptor based IIOP proxy. Using this proxy you can both run Java Applets with JacORB and use JacORB across firewalls and the Internet. This new implementation no longer supports HTTP tunneling.

11.1 Appligator Functionality

The Appligator is a GIOP proxy. When the Appligator is used, instead of a client calling directly to a server it calls to the Appligator which then itself calls on to the server. This is all transparent as far as a client is concerned. The basic mechanism of operation is as follows:

1. A client that wishes to use the Appligator installs a client side interceptor.
2. When the client makes a call the interceptor checks to determine whether the call should be redirected to an Appligator. If so, then the original call target is encoded within a service context and a `ForwardRequest` exception is thrown so that the ORB redirects the call to the Appligator.
3. When the Appligator receives a forwarded request it extracts the original target from the service context and calls onto the original target. The actual proxy implementation within the Appligator is invoked via DSI and calls on to the target via DII.

11.2 Using The Appligator

The Appligator can be run as a normal CORBA server via the 'appligator' shell script or batch file. The Appligator is configured via both command line arguments and properties stored in the ORB configuration file 'jacorb.properties'.

11.2.1 Starting Appligator

The Appligator can be invoked as follows:

```
$ appligator <port> <filename> [-dynamic]
```

This starts the Appligator on the specified port and writes its IOR to the specified file.

The '-dynamic' flag is optional and determines whether the object key used for the Appligator IOR is dynamically (i.e. randomly) selected or fixed. If a fixed id is used then the configuration property 'jacorb.ProxyServer.ID' is used as the object key value. If this is not set then this defaults to 'Appligator'. Using a fixed object key has the advantage that this key is used every time the Appligator restarts so a remote client would not have to update its reference to the Appligator (typically an IOR file).

11.2.2 Client Configuration

Appligator clients need to install the appropriate client side interceptor class. This can be done by configuring the portable ORB initializer class 'ProxyClientInitializer' by setting the following ORB initialization property:

```
org.omg.PortableInterceptor.ORBInitializerClass.org.jacorb.  
proxy.ProxyClientInitializer
```

11.2.3 Appligator Configuration Appligator

configuration properties are placed in the 'jacorb.properties' file, all have the common prefix 'jacorb.ProxyServer'. Configuration properties are used either for the configuration of the Appligator server itself or for the configuration of Appligator clients.

Appligator Server Properties

If the 'jacorb.ProxyServer.Name' property is set and the name service has been configured and is available then the Appligator will register itself in the name service using this name. If the 'jacorb.ProxyServer.ID' property is set and the Appligator has not been run with the '-dynamic' flag then this property is used as the object key in the created Appligator IOR.

Appligator Client Properties

The 'jacorb.ProxyServer.URL' configuration property is used by clients to locate the default Appligator. This URL should map to an IOR file written by an Appligator. If the 'jacorb.ProxyServer.Network' and 'jacorb.ProxyServer.Netmask' properties are set these are used to determine the local network address for a client. If this is set then any calls to objects within this network will not be redirected to the Appligator. This is useful when a CORBA server may need to call to an Appligator to access remote servers but may want to communicate with local servers directly. The dotted decimal form should be used for both these properties, for example:

```
jacorb.ProxyServer.Netmask=255.255.255.0  
jacorb.ProxyServer.Network=160.45.110.0
```

Clients can be configured to use different Appligators to access objects in different subnets. To do this configuration properties of the form 'jacorb.ProxyServer.URL-;network;_;netmask;' can be used. Here the URL property should map to the Appligator IOR for the particular subnet identified by ;network; and ;netmask;. For example:

```
jacorb.ProxyServer.URL-160.45.120.0-255.255.255.0=file:/tmp/net1.ior
```

11.3 Applet Support

Regular Java programs can connect to every host on the Internet, applets can only open connections to their applethost (the host they are downloaded from). This lets Applets only use CORBA servers on their applethost, if no proxy is used. With JacORB Appligator, access for your Applets is no longer restricted. Placed on the applethost, Appligator handles all connections from and to your Applet transparently.

Due to the transparency of JacORB Appligator you can write your Applet as if it were a normal CORBA program. The only thing you have to do is to use a special initialization of the ORB by calling the ORB init operation that takes an Applet as a parameter:

```
ORB orb = ORB.init (applet, properties);
```

A normal JacORB program reads a local jacob.properties file to get the URL of its name server and other vital settings. An Applet of course has no local properties file, but a remote one: You have to place the properties file (which has the same syntax and parameters as the normal file) in the same directory as your Applet (the file name has to be: jacob.properties, without a leading dot).

Similar to the name server, Appligator writes its IOR to a file. Your Applet has to know the location of this file to retrieve the IOR of Appligator. You must set the location of the IOR file via the jacob.properties file (jacorb.ProxyServer.URL) or with an Applet parameter in the ;APPLET; HTML tag (JacorbProxyServerURL).

11.3.1 Summary

- Init the ORB with jacob.orb.init(applet,properties), where applet is this Applet and properties are java.util.Properties (which can be null).
- Put a jacob.properties file in the directory of the Applet.
- Specify the location for the Appligator IOR file in the jacob.properties (jacorb.ProxyServer.URL) or in an Applet parameter (JacorbProxyServerURL)
- Make sure the name server IOR file is accessible for the Applet (lies on the applethost)
- Start Appligator on the applethost (web server) with:

```
$ appligator <port> <filename>
```

Where filename is the location where the Appligator IOR is written and is the location specified in the JacORB properties file or Applet parameter.

11.3.2 Applet Properties

As described above there are some ways for the Applet to get its JacORB properties file. The most important property is the URL to the Appligator IOR file. Without this property the Applet will not work. If you use a name server, the URL to the name server IOR must also be specified.

Properties can be set in three ways:

1. In the ORB.init() call with the java.util.Properties parameter.
2. In the JacORB properties file located in the same directory as the Applet
3. The URL to the name server and Appligator IOR file can be set in the Applet tag in the HTML file

11.3.3 Appligator and Netscape/IE, appletviewer

Netscape Navigator/Communicator comes with its own (outdated) CORBA support. You have to delete Netscape's CORBA classes to use JacORB. To do this you have to delete the file iiop10.jar located in NS ROOT/java/classes. It's a good idea to store a backup of Netscape's file in another directory. Note that renaming this jar file in the original directory does not suffice if you don't also change the .jar extension because Netscape loads all jar files in this directory. You then need to install jacorb.jar in this directory.

If Netscape loads wrong classes or throws security exceptions (have a look at Netscape's Java Console to see this) be sure to check your CLASSPATH and look for old jar files or ".". Remove all JacORB and VisiBroker classes from your CLASSPATH. We succeeded running JacORB Applet clients on Netscape 4.72 with the Java 1.3 plugin.

Microsoft's Internet Explorer is stricter than Netscape: Even downloaded classes are not allowed to listen on a socket. We strongly advise to use Sun's Java 1.3 plugin with IE also. To trick IE into using JacORB, you need to copy JacORB classes to \$WINNT\Java\TrustLib. You can either copy the entire jacorb.jar and unpack it in this directory or just copy the directories jacorb, org, and HTTPClient.

Appligator works well with Sun's appletviewer. You only have to make the appletviewer replace the Sun's CORBA classes with JacORB's classes. A typical appletviewer call for JacORB Applets looks like this (written in one command line):

```
$ appletviewer http://www.example.com/CORBA/dii example.html
```

There is a shell script called "jacapplet" in JacORB's bin directory, which calls the appletviewer with the appropriate options (you have to edit it to match your local JDK path).

If you use the Appligator with other browsers or if you know a way to load the JacORB classes without removing and copying jars please let us know.

11.3.4 Examples

There are some example applets in the demo directory (jacorb/demo/applet). They are based on the normal examples. The examples include a HTML file which calls the Applet. To run the example start the name

server first. Start Appligator on your web server and then the normal example server corresponding to the Applet example on any computer in any order. Then you can call the example Applet with the JDK appletviewer or Netscape.

Be sure to have a `jacorb.properties` file and the `jacorb.jar` in place.

11.4 Firewall Support

Typically firewalls do two things: filter traffic by port, and filter traffic by protocol. The JacORB Appligator can be used to deal with port restrictions.

The Appligator was written to avoid the sandbox restrictions for Java applets. Unsigned applets can only have connections to the host they are loaded from, which makes them useless in most distributed CORBA scenarios. The Appligator is a GIOP proxy, which enables applets to connect to every CORBA server by redirecting the traffic from the Applet to the CORBA server to the proxy. The Appligator also works the other way round: Every connection the Applet is redirected to the Appligator.

Even without applets the Appligator can be used as a GIOP proxy on a firewall. The Appligator is a CORBA object itself and is explicitly started on a given port using a command line argument `port`. All incoming traffic to the Appligator will go to port `port`. If you configure your CORBA object behind the firewall to be aware of the Appligator all traffic from and to this objects will go through the Appligator.

To make your port filtering firewall working with CORBA and GIOP messages you must ask your system administrator to assign a port for GIOP messages on the firewall. Start the Appligator on this port.

Now all CORBA servers (which are aware of the Appligator) in your enclave can be contacted over the Appligator. If your CORBA client wants to contact a server in the Internet outside the firewall the connection will go over the Appligator. Callbacks from the Internet to your client do not work with Netscape.

Finally you have to specify the location on the Appligator. This is done the same way as JacORB determines to location of the name server: When the Appligator starts the IOR of the Appligator is written to a file which is put to the location you specified as command parameter. This file must be accessible to all clients that want to use the Appligator. You can use a shared file system to access this file or put it on a web server etc. The location of the file in which the IOR of the Appligator is stored must be set in the `jacorb.properties` file. Use the `"jacorb.ProxyServer.URL"` property for this.

11.4.1 Summary

- Use the Appligator as a GIOP proxy on a firewall if your firewall is configured to block all traffic but traffic on some special ports.
- Ask your system administrator to assign a special port for GIOP on your firewall and start the Appligator on this port on the firewall: for example: `$ appligator 7777 app.ior`
- All CORBA objects that should be reachable from outside the firewall or need to contact a CORBA object outside the firewall must use the Appligator as a proxy. Configure the client side ORB

initializer for those applications

- Set the location of the Appligator in the `jacorb.properties` file of your clients (`jacorb.ProxyServer.URL`)

11.4.2 NAT Firewalls

Most commercial firewalls support Network Address Translation (NAT). Here the address of an internal server is not made directly visible to the external Internet, but transformed into another configured address (typically that of the firewall).

The problem here is that the IOR written by an Appligator will contain its internal address. If a remote client wishes to access this Appligator via a NAT firewall then it cannot use this IOR direct as it will not contain a routeable address. To support this the Appligator IOR used by a remote client must be patched to contain the NAT address of the firewall. A new utility 'fixior' has been provided to do this. This can be run as follows:

```
$ fixior <host> <port> <ior_file>
```

11.4.3 Security Considerations

When allowing Appligator traffic through a fixed port in a firewall the Appligator can in effect allow access to any internal CORBA server. As the real service target is contained within a service context a knowledgeable user could attempt to exploit this to access an unauthorized service. To do this a hacker would have to know the object key used for the Appligator and a CORBA reference to an internal service. For this reason if fixed Appligator keys are used it is recommended that the default value is not used. A much better solution is to tunnel the Appligator communication through a secure channel such as afforded by a Secure Shell (SSH) or a Virtual Private Network (VPN).

11.4.4 Use of SSH

Rather than configure a firewall to allow direct access to an Appligator a better solution is to enable SSH and use SSH as a secure tunnel to the Appligator. To do this you first need to patch the Appligator IOR file used by the client so that this refers to a local port on the local host:

```
$ fixior 127.0.0.1 11111 app.ior
```

SSH can then be used to create a secure tunnel between this port and the remote port on the server machine used by the Appligator. If the Appligator was running on remote machine 'server' on port 22222 this could be done as follows:

```
$ ssh -T -L 11111:server:22222 server
```

If you have a scenario where the server needs to callback to a client and dual Appligators are deployed on either side of a firewall then SSH can be used to create a tunnel for each Appligator as follows:

```
$ ssh -T -L 11111:server:22222 -R 33333:client:44444 server
```


Here SSH has created a local tunnel between port 11111 on 'client' and port 22222 on 'server' and a remote tunnel between port 33333 on 'server' and port 44444 on 'client'. The 'server' Appligator would be running on port 22222 and the 'client' Appligator on port 44444. The Appligator IOR used by 'client' to access the 'server' Appligator would be patched to have endpoint 127.0.0.1:11111 and the Appligator IOR used by 'server' to access the 'client' Appligator would be patched to have endpoint 127.0.0.1:33333.

12 IIOP over SSL

Using SSL to authenticate clients and to protect the communication between client and target requires no changes in your source code. The only notable effect is that SSL/TLS type sockets are used for transport connections instead of plain TCP sockets — and that connection setup takes a bit longer.

The only prerequisites are that you rebuild JacORB with cryptography support. You also need to set up a key store file that holds your cryptographic keys, and to configure SSL by setting a few properties. All of this is described in this chapter.

12.1 Re-Building JacORB's security libraries

In the standard distribution, the JacORB security libraries are not enabled. To do so, you simply need to recompile JacORB with the required SSL libraries in your CLASSPATH. If these libraries are not found, JacORB will be rebuilt without SSL support.

To successfully rebuild JacORB with SSL support, the following is required:

- when using IAIKs libraries:
 - IAIK-JCE 2.591 or later, the security provider classes downloadable from <http://jcewww.iaik.tu-graz.ac.at>,
 - iSaSiLk 3.0 or later, the SSL implementation from the same source.
- when using Suns libraries:
 - JDK 1.4 or jsse1.0.2 available from the Developer Connection (for jsse1.0.2, please see the `README.jsse_1_0_2` in `src/org/jacorb/security/ssl/sun_jsse` on how to compile).
 - For key management, you also need additional packages like OpenSSL. These are not necessary for JacORB to work.

Install the desired packages and read the documentation carefully. After successful installation, build JacORB anew by typing `ant` in your JacORB installation directory.

12.2 IAIK specific setup

This section covers topics that are specific to IAIKs libraries.


12.2.1 Setting up an IAIK key store

SSL relies on public key certificates in the standard X.509 format. These certificates are presented in the authentication phase of the SSL handshake and used to compute and exchange session keys. This section explains how to create and store these certificates.


The Java 2 security API provides interfaces that access a persistent data structure called *KeyStore*. A key store is simply a file that contains public key certificates and the corresponding private keys. It also contains other certificates that can be used to verify public key certificates. All cryptographic data is protected using passwords and accessed using names called *aliases*.

JacORB provides a GUI tool to create and manipulate key store files, the *KeyStoreManager*. It can generate key pairs, sign public keys, import or export certificates, and define trusted certificate authorities. To start the *KeyStoreManager*, simply type `ks` on the command line. The GUI lets you select and open existing key store files, or create new ones.


Starting with an empty key store, you first need to create a new key store and then a key pair and certificate. Select *New* from the *File* menu to create a key store, and then *New* from the *Keys* menu. You will then be asked to provide a new alias name for your new key entry. You also need to choose a password. You can leave the algorithm and key length fields in the combobox menu unchanged.



You now have a public key certificate that you can present for authentication, claiming identity with the alias name that has been embedded in the certificate. Since anybody could present such a certificate, receivers require that the certificate be digitally signed by someone they trust, a *Certificate Authority* (CA). By signing the certificate, a CA supports the identity claim of the certificate subject. Whose signature is accepted as trustworthy is just a matter of configuration, but normally proper CAs are expected to only sign certificates that they have carefully scrutinized — or even created themselves.



For convenience you can act as a CA yourself, using the KeyStoreManager GUI to import certificates and then sign and export them again. The originating key store can then re-import the certificate that now bears the digital signature of someone acting as a CA. The key store has a standard key chain format that must be used to store public key certificates. The first entry in the key chain is your own public key certificate as generated by the key store. It is automatically signed with its own private key. Second in the chain is the public key certificate that is signed by the CA. The last entry in a key chain must hold the CA's public key certificate, signed using its private key. Trust in the CA key is "axiomatic".



You can check the validity of a key chain by selecting an alias and then choosing **Verify Chain** from the **Keys** menu. Unless the key chain has the proper format *and* the CA's public key certificate is also declared as trusted using the **Trustees--add** menu, the verification will fail. Only if the verification succeeds will you be able to use a public key certificate in the SSL connection setup. More documentation on key stores can be found in the Java tool documentation for the `keytool` command. If

you care for “real” security, be advised that setting up and managing (or finding) a properly administered CA is essential for the overall security of your system.

Finally, note that key stores are normally used only for client authentication in JacORB. Servers may, but need not, have their own keys and passwords because server authentication is optional and not mandatory like client authentication. Technically, this is achieved by exchanging the client and server roles at SSL setup. This is entirely transparent to applications, of course, but might prevent interoperation with other ORBs over SSL if their SSL setup is not prepared to handle this role change.

12.2.2 Step–By–Step certificate creation

In order to generate a simple public key infrastructure you can perform the following steps:

1. Create new keystores (File/new) and keypairs (Keys/new) for the CA and for the user.
2. Open the user keystore (File/open), select the key entry and export the self-signed certificate (Certificates/Export).
3. Open the CA keystore and add the user certificate as a Trustee (Trustees/add. . .).
4. Select the trusted user certificate and create a signed public key certificate (Certificates/Create). Leave the role name field empty, enter the CAs private key password and save the new certificate by clicking OK.
5. Export the CAs self-signed certificate to a file (as explained above). Delete the trusted certificate from the CA keystore (Trustees/Delete).
6. Open the user keystore again. Select the key entry, the import the CA-signed user cert (Certificates/Import), and the self-signed CA cert.
7. Add the self-signed CA cert as a trustee. This is only needed for verifying the chain, therefore the keystore can be deployed without it. Please note that a failed verification might result in a `SignatureException`.

12.3 Configuring SSL properties

When the ORB is initialized by the application, a couple of properties are read from files and the command line. To turn on SSL support, you have to set the following property to “on”:

```
jacorb.security.support_ssl=on
```

This will just load the SSL classes on startup. The configuration of the various aspects of SSL is done via additional properties.

As explained in the previous section, cryptographic data (key pairs and certificates) is stored in a keystore file. To configure the file name of the keystore file, you need to define the following property:

```
jacorb.security.keystore=AKeystoreFileName
```

The keystore file name can either be an absolute path or relative to the home directory. Keystores are searched in this order, and the first one found is taken. If this property is not set, the user will be prompted to enter a keystore location on ORB startup.

To avoid typing in lots of aliases and passwords (one for the key store, and one for each entry that is used), you can define default aliases and passwords like this:

```
# the name of the default key alias to look up in the keystore
jacorb.security.default_user=brose
jacorb.security.default_password=jacorb
```

These SSL settings can be further refined using security options as in the following property definitions:

```
jacorb.security.ssl.client.supported_options=0
jacorb.security.ssl.client.required_options=0

jacorb.security.ssl.server.supported_options=0
jacorb.security.ssl.server.required_options=0
```

The value of these security options is a bit mask coded as a hexadecimal integer. The meanings of the individual bits is defined in the CORBA Security Service Specification and reproduced here from the `Security.idl` file:

```
typedef unsigned short    AssociationOptions;

const AssociationOptions NoProtection = 1;
const AssociationOptions Integrity = 2;
const AssociationOptions Confidentiality = 4;
const AssociationOptions DetectReplay = 8;
const AssociationOptions DetectMisordering = 16;
const AssociationOptions EstablishTrustInTarget = 32;
const AssociationOptions EstablishTrustInClient = 64;
const AssociationOptions NoDelegation = 128;
const AssociationOptions SimpleDelegation = 256;
const AssociationOptions CompositeDelegation = 512;
```

12.3.1 Client side configuration

```
jacorb.security.ssl.client.supported_options=20 //EstablishTrustInTarget
```

This value indicates that the client can use SSL. Actually, this is default SSL behaviour and must always be supported by the client.

```
jacorb.security.ssl.client.supported_options=40 //EstablishTrustInClient
```

This makes the client load it's own key/certificate from it's keystore, because it must be prepared to authenticate to the server.

```
jacorb.security.ssl.client.required_options=20 //EstablishTrustInTarget
```

This enforces SSL to be used.

```
jacorb.security.ssl.client.required_options=40 //EstablishTrustInClient
```

This enforces SSL to be used. Actually, this is no meaningful value, since in SSL, the client can't force it's own authentication to the server.

12.3.2 Server side configuration

```
jacorb.security.ssl.server.supported_options=1 //NoProtection
```

This tells the clients that the server also supports unprotected connections. If NoProtection is set, no required options should be set as well, because they override this value.

```
jacorb.security.ssl.server.supported_options=20 //EstablishTrustInTarget
```

This value indicates that the server supports SSL. Actually, this is default SSL behaviour and must always be supported by the server. This also makes the server load it's key/certificate from the keystore.

```
jacorb.security.ssl.server.supported_options=40 //EstablishTrustInClient
```

This value is ignored, because authenticating the client is either required, or not done at all (the client can't force its own authentication).

```
jacorb.security.ssl.server.required_options=20 //EstablishTrustInTarget
```

This enforces SSL to be used.

```
jacorb.security.ssl.server.required_options=40 //EstablishTrustInClient
```

This enforces SSL to be used, and will request the client to authenticate. It also will load trusted certificates for the authentication process.

13 BiDirectional GIOP

BiDirectional GIOP has its main use in configurations involving callbacks with applets or firewalls where it sometimes isn't possible to open a direct connection to the desired target. As a small example, imagine that you want to monitor the activities of a server via an applet. This would normally be done via a callback object that the applet registers at the server, so the applet doesn't have to poll the server for events. To accomplish this without BiDirectional GIOP, the server would have to open a new connection to the client which will not work because applets usually aren't allowed to act as servers, i.e. open `ServerSockets`. At this point BiDirectional GIOP can help because it allows to reuse the connection the applet opened to the server for GIOP requests from the server to the applet (which isn't allowed in "standard" GIOP).

13.1 Setting up Bidirectional GIOP

Setting up BiDirectional GIOP consists of two steps:

1. Setting an `ORBInitializer` property and creating the BiDir policy
2. Adding this policy to the servant's POA.

13.1.1 Setting the ORBInitializer property

The first thing that is necessary for BiDirectional GIOP to be available is the presence of the following property, which can be added by the usual ways (see chapter 3):

```
org.omg.PortableInterceptor.ORBInitializerClass.bidir_init=  
org.jacorb.orb.giop.BiDirConnectionInitializer
```

If this property is present on ORB startup, the corresponding policy factory and interceptors will be loaded.

13.1.2 Creating the BiDir Policy

Creating the necessary BiDir Policy is done via a policy factory hidden in the ORB.

```
import org.omg.BiDirPolicy.*;
import org.omg.CORBA.*;

[...]

Any any = orb.create_any();
BidirectionalPolicyValueHelper.insert( any, BOTH.value );

Policy p = orb.create_policy( BIDIRECTIONAL_POLICY_TYPE.value,
                              any );
```

The value of the new policy is passed to the factory inside of an any. The ORB is told to create a policy of the specified type with the specified value. The newly created policy is then used to create a user POA. Please note that if *any* POA of has this policy set, *all* connections will be enabled for BiDirectional GIOP, that is even those targeted at object of POAs that don't have this policy set. For the full source code, please have a look at the bidir demo in the demo directory.

13.2 Verifying that BiDirectional GIOP is used

From inside of your application, it is impossible to tell whether requests arrived over a unidirectional or BiDirectional connection. Therefore, to check if connections are used in both directions, you can either use a network monitoring tool or take a look at JacORBs output to tell you if your server created a new connection to the client, or if the existing one is being reused.

If the debug level is set to 2 or larger, the following output on the server side will tell you that a connection is being reused:

```
[ ConnectionManager: found conn to target <my IP>:<my port> ]
```

If, on the other hand, the connection is not being reused, the client will show the following output:

```
[ Opened new server-side TCP/IP transport to <my host>:<my port> ]
```

13.3 TAO interoperability

There is one problem that may prevent TAO and JacORB to interoperate using BiDirectional GIOP: If JacORB uses IP addresses as host names (JacORBs default) and TAO uses DNS names as host names (TAOs default), connections from JacORB clients to TAO servers will not be reused. If, on the other hand, both use the same “format” for host addresses, interoperability will be successful. There are two ways to solve this problem:

1. Use `--ORBdotteddecimaladdresses 1` as an command line argument to the TAO server.

2. Recompile JacORB with DNS support (See the INSTALL file for more information).

14 Portable Interceptors

Since revision 1.1 JacORB provides support for Portable Interceptors. These interceptors are compliant to the standard CORBA specification. Therefore we don't provide any documentation on how to program interceptors but supply a few (hopefully helpful) hints and tips on JacORB specific solutions.

The first step to have an interceptor integrated into the ORB is to register an *ORBInitializer*. This is done by setting a property the following way:

```
org.omg.PortableInterceptor.ORBInitializerClass.<any_suffix>=  
    <orb initializer classname>
```

For compatibility reasons with the spec, the properties format may also be like this:

```
org.omg.PortableInterceptor.ORBInitializerClass.<orb initializer classname>
```

The suffix is just to distinguish between different initializers and doesn't have to have any meaningful value. The value of the property however has to be the fully qualified classname of the initializer. If the verbosity is set to ≥ 2 JacORB will display a `ClassNotFoundException` in case the initializers class is not in the class path.

An example line might look like:

```
org.omg.PortableInterceptor.ORBInitializerClass.my_init=  
    test.MyInterceptorInitializer
```

Unfortunately the interfaces of the specification don't provide any access to the ORB. If you need access to the ORB from out of the initializer you can cast the `ORBInitInfo` object to `jacorb. orb.portableInterceptor.ORBInitInfoImpl` and call `getORB()` to get a reference to the ORB that instantiated the initializer.

When working with service contexts please make sure that you don't use `0x4A414301` as an id because a service context with that id is used internally. Otherwise you will end up with either your data not transferred or unexpected internal exceptions.

15 Asynchronous Method Invocation

JacORB allows you to invoke objects asynchronously, as defined in the *Messaging* chapter of the CORBA specification (chapter 22 in CORBA 3.0). Only the callback model is implemented at this time; there is no support for polling yet.

Asynchronous Method Invocation (AMI) means that when you invoke a method on an object, control returns to the caller immediately; it does not block until the reply has been received from the remote object. The results of the invocation are delivered later, as soon as they are received by the client ORB. Asynchronous Invocation is entirely a client-side feature. The server is never aware whether it is invoked synchronously or asynchronously.

In the callback model, replies are delivered to a special *ReplyHandler* object that is registered at the client side when the asynchronous invocation is started. Here is a brief example for this (see the *Messaging* specification for further details). Suppose you have a Server object, defined in a file `server.idl`.

```
interface Server
{
    long operation (in long p1, inout long p2);
};
```

The first step is to compile this IDL definition with the “ami_callback” compiler switch:

```
idl -ami_callback server.idl
```

This lets the compiler generate an additional ReplyHandler class, named `AMI.ServerHandler`. For each operation of the Server interface, this class has an operation with the same name that receives the return value and out parameters of the original operation. There is an additional method named `operation_excep` that is called if the invocation raises an exception. If it were defined in IDL, the ReplyHandler class for the above Server would look like this:

```
interface AMI_ServerHandler : Messaging::ReplyHandler
{
    void operation (in long ami_return_val, in long p2);
    void operation_excep (in Messaging::ExceptionHolder excep_holder);
};
```

To implement this interface, extend the corresponding POA class (or use the tie approach), as with any CORBA object:

```
public class AMI_ServerHandlerImpl extends AMI_ServerHandlerPOA
{
    public void operation (int ami_return_val, int p2)
    {
        System.out.println ("operation reply received");
    }

    public void operation_excep
        (org.omg.Messaging.ExceptionHolder excep_holder)
    {
        System.out.println ("received an exception");
    }
}
```

For each method *m* of the original Server interface, the IDL compiler generates a special method *sendc_m* into the stub class if the “ami_callback” switch is on. The parameters of this method are (1) a reference to a ReplyHandler object, and (2) all *in* or *inout* parameters of the original operation, with their mode changed to *in* (*out* parameters are omitted from this operation). The *sendc* operation does not have a return value.

To actually make an asynchronous invocation, an instance of the ReplyHandler needs to be created, registered with the ORB, and passed to the *sendc* method. The code for this might look as follows:

```
ORB    orb = ...
Server s    = ...

// create handler and obtain a CORBA reference to it
AMI_ServerHandler h = new AMI_ServerHandlerImpl()._this (orb);

// invoke sendc
((_ServerStub)s).sendc_operation (h, 4, 5);
```

Note that the *sendc* operation is only defined in the stub, and therefore the cast is necessary to invoke it. There is not yet any consensus in the OMG whether the *sendc* operation should also be declared in any of the Java interfaces that make up the Server type. Thus, the fact that you need to make a cast to the stub class may change in a future version of JacORB.

If you want to try asynchronous invocations with code such as above, make sure that your client process does something else or at least waits after the invocation has been made, otherwise it will likely exit before the reply can be delivered to the handler.

The *Messaging* specification also defines a number of CORBA policies that allow you to control the timing of asynchronous invocations. Since these policies are applicable to both synchronous and asynchronous invocations, we describe them in a separate section (see chapter 16).

16 Quality of Service

JacORB implements a subset of the QoS policies defined in chapter 22.2 of the CORBA 3.0 specification. In the following, we describe each of the policies we have currently implemented, along with notes on particular JacORB issues concerning each policy. Policies not listed in the following are not yet implemented.

As of yet, all the policies in this chapter are *client-side override policies*. That means that you must specify them for individual objects, always using the same mechanism:

Step 1. Get an Any from the ORB and put the value for the policy into it.

Step 2. Get a Policy object from the ORB which encapsulates the desired value (the Any value from the previous step).

Step 3. Apply the policy to a particular object using `_set_policy_override()`.

Here is the code for this, using the *SyncScopePolicy* (described in the following section) as an example:

```
SomeCorbaType    server = ...
org.omg.CORBA.ORB orb    = ...
org.omg.CORBA.Any a      = orb.create_any();
a.insert_short (SYNC_WITH_SERVER.value); // policy value
try
{
    Policy p =
        orb.create_policy(SYNC_SCOPE_POLICY_TYPE.value, a);
    server._set_policy_override (new Policy[]{ p },
                                SetOverrideType.ADD_OVERRIDE);
}
catch (PolicyError e)
{
    throw new RuntimeException ("policy error: " + e);
}
```

Because this is somewhat cumbersome to write, JacORB allows you to simplify it by creating the Policy object directly via its constructor:

```
SomeCorbaType server = ...

Policy p = new org.jacorb.orb.policies.SyncScopePolicy
            (SYNC_WITH_TARGET.value);
server._set_policy_override (new Policy[] { p },
                           SetOverrideType.ADD_OVERRIDE);
```

See the package `org.jacorb.orb.policies` to find out which constructors are defined for the individual policy types.

16.1 Sync Scope

The *SyncScopePolicy* specifies at which point a oneway invocation returns to the caller. (The policy is ignored for non-oneway invocations.) There are four possible values:

SYNC_NONE The invocation returns immediately.

SYNC_WITH_TRANSPORT The invocation returns after the request has been passed to the transport layer.

SYNC_WITH_SERVER The server sends an acknowledgement back to the client when it has received the request, but *before* actually invoking the target. The client-side call blocks until this acknowledgement has been received.

SYNC_WITH_TARGET An ordinary reply is sent back by the server, *after* the target invocation has completed. The client-side call blocks until this reply has been received.

The default mechanism in JacORB is *SYNC_WITH_TRANSPORT*, since the call to the socket layer is a synchronous one. In order to implement *SYNC_NONE*, an additional thread is created on the fly which in turn calls the socket layer, while the client-side invocation returns after this thread has been created. Given this additional overhead, it is unlikely that *SYNC_NONE* yields a significant performance gain for the client, not even on a multiprocessor machine.

16.2 Timing Policies

For each CORBA request four different points in time can be specified:

Request Start Time the time after which the request may be delivered to its target

Request End Time the time after which the request may no longer be delivered to its target

Reply Start Time the time after which the reply may be delivered to the client

Reply End Time the time after which the reply may no longer be delivered to the client

Each of these points in time can be specified on a per-object level as a client-side override policy: *RequestStartTimePolicy*, *RequestEndTimePolicy*, *ReplyStartTimePolicy*, and *ReplyEndTimePolicy* (see below for concrete code examples).

Each of these policies specifies an absolute time, which means that they will usually have to be set again for each individual request. As a convenience, there are two additional policies that allow you to specify a *relative* time for *Request End Time* and *Reply End Time*; they are called *RelativeRequestTimeoutPolicy* and *RelativeRoundtripTimeoutPolicy*, respectively. These timeouts are simply more convenient ways for expressing these two times; before each individual invocation, the ORB computes absolute times from them (measured from the start of the invocation at the client side) and handles them just as if an absolute *Request End Time* or *Reply End Time* had been specified. We will therefore only discuss the four absolute timing policies below.

All of these policies apply to synchronous and asynchronous invocations alike.




Figure 16.1: Timing Policies in JacORB

Figure 16.1 shows how JacORB interprets the timing policies in the course of a single request.

- As soon as the ORB receives control (prior to marshaling), it converts any *RelativeRequestTimeoutPolicy* or *RelativeRoundtripTimeoutPolicy* to an absolute value, by adding the relative value to the current system time.
- The ORB then checks whether *Request End Time* or *Reply End Time* have already elapsed. If so, no invocation is made, and an `org.omg.CORBA.TIMEOUT` is thrown to the client.
- After the ORB has sent the request, it waits for a reply until *Reply End Time* has elapsed. If it receives no reply before that, the request is discarded and an `org.omg.CORBA.TIMEOUT` thrown to the client. (JacORB does not currently cancel the outstanding request, it simply discards the reply, should one arrive after the timeout has elapsed.)

- On the server side (before demarshaling), the ORB checks whether *Request End Time* or *Reply End Time* have already elapsed. If so, the request is not delivered to the target, and an `org.omg.CORBA.TIMEOUT` is thrown back to the client.
- If the request proceeds, the ORB waits until the *Reply Start Time* has been reached, if one was specified, and has not already elapsed. After that, the request is delivered to the target.
- After the target has returned control to the ORB, it checks whether *Reply End Time* has already elapsed. If it has, the ORB sends an `org.omg.CORBA.TIMEOUT` back to the client, rather than the actual reply.
- If the reply arrives at the client before *Reply End Time* has elapsed, the ORB waits until *Reply Start Time* has been reached, if one was specified, and has not already elapsed. After that, the reply is delivered back to the client.

The bottom line of this is that for a simple, per-invocation timeout, you should specify a *RelativeRoundtripTimeoutPolicy*. Note that since this relative time is converted into an absolute time, and also checked on the server side, the clocks on both the server and the client need to be synchronized at least to the same order of magnitude as the desired timeout.

Programming

In CORBA, points of time are specified to an accuracy of 100 ns, using values of struct `TimeBase::UtcT`. To allow easy manipulation of such values from Java, JacORB provides a number of static methods in `org.jacorb.util.Time`. For example, to convert the current Java time into a `UtcT` value, write

```
UtcT currentTime = org.jacorb.util.corbaTime();
```

To create a `UtcT` value that specifies a time n ms in the future, you can write

```
UtcT time = org.jacorb.util.corbaFuture (10000 * n);
```

(The argument to `corbaFuture()` is in CORBA time units of 100 ns; we multiply n by 10000 here to convert it from Java time units (milliseconds).)

The following shows how to set a timing policy for an object using the standard mechanism (see the beginning of this chapter for an explanation). In this example, we set a *Reply End Time* that lies one second in the future:

The difference between this and the example before, where a *Reply End Time* was used, is that the latter specifies a *relative time* to CORBA. The policy will therefore be valid for all subsequent invocations, because the absolute deadline will be recomputed before each invocation. In the first example, the deadline will no longer make sense for any subsequent invocations, since only an absolute time was specified to the ORB.

17 Connection Management and Connection Timeouts

JacORB offers a certain level of control over connections and timeouts. You can

- set connection idle timeouts.
- set request timing.
- set the maximum number of accepted TCP/IP connections on the server.

17.1 Timeouts

Connection idle timeouts can be set individually for the client and the server. They control how long an idle connection, i.e. a connection that has no pending replies, will stay open. The corresponding properties are `jacorb.connection.client.idle_timeout` and `jacorb.connection.server.timeout` and take their values as milliseconds. If not set, connections will stay open indefinitely (or until the OS decides to close them).

Request timing controls how long an individual request may take to complete. The programmer can specify this using QoS policies, discussed in chapter [16](#).

17.2 Connection Management

When a client wants to invoke a remote object, it needs to send the request over a connection to the server. If the connection isn't present, it has to be created. In JacORB, this will only happen once for every combination of host name and port. Once the connection is established, all requests and replies between client and server will use the same connection. This saves resources while adding a thin layer of necessary synchronization, and is the recommended approach of the OMG. Occasionally people have requested to allow for multiple connections to the same server, but nobody has yet presented a good argument that more connections would speed up things considerably.

On the server side, the property `jacorb.connection.max_server_transports` allows to set the maximum number of TCP/IP connections that will be listened on for requests. When using a network

sniffer or tools like netstat, more inbound TCP/IP connections than the configured number may be displayed. This is for the following reason: Whenever the connection limit is reached, JacORB tries to close existing idle connections (see the subsection below). This is done on the thread that accepts the new connections, so JacORB will not actively accept more connections. However, the `ServerSocket` is initialized with a backlog of 20. This means that 20 more connections will be quasi-accepted by the OS. Only the 21st will be rejected right away.

17.2.1 Basics and Design

Whenever there is the need to close an existing connection because of the connection limit, the question arises on which of the connection to close. To allow for maximum flexibility, JacORB provides the interface `SelectionStrategy` that allows for a custom way to select a connection to close. Because selecting a connection usually requires some sort of statistical data about it, the interface `StatisticsProvider` allows to implement a class that collects statistical data.

```
package org.jacorb.orb.giop;

public interface SelectionStrategy
{
    public ServerGIOPConnection
        selectForClose( java.util.List connections );
}

public interface StatisticsProvider
{
    public void messageChunkSent( int size );
    public void flushed();
    public void messageReceived( int size );
}
```

The interface `SelectionStrategy` has only the single method of `selectForClose()`. This is called by the class `GIOPConnectionManager` when a connection needs to be closed. The argument is a `List` containing objects of type `ServerGIOPConnection`. The call itself is synchronized in the `GIOPConnectionManager`, so no additional synchronization has to be done by the implementor of `SelectionStrategy`. When examining the connections, the strategy can get hold of the `StatisticsProvider` via the method `getStatisticsProvider()` of the class `GIOPConnection`. The strategy implementor should take care only to return idle connections. While the connection state is checked anyway while closing (it may have changed in the meantime), it seems to be more efficient to avoid cycling through the connections. When no suitable connection is available, the strategy may return `null`. The `GIOPConnectionManager` will then wait for a configurable time, and try again. This goes on until a connection can be closed.

The interface `StatisticsProvider` is used to collect statistical data about a connection and provide it to the `SelectionStrategy`. Because the nature of this data may vary, there is no standard access to the data via the interface. Therefore, `StatisticsProvider` and

SelectionStrategy usually need to be implemented together. Whenever a new connection is created¹, a new StatisticsProvider object is instantiated and stored with the Transport². The StatisticsProvider interface is oriented along the mode of use of the Transport. For efficiency reasons, messages are not sent as one big byte array. Instead, they are sent piecewise over the wire. When such a chunk is sent, the method `messageChunkSent(int size)` will be called. After the message has been completely sent, method `flush()` is called. This whole process is synchronized, so all consecutive `messageChunkSents` until a `flush()` form a single message. Therefore, no synchronization on this level is necessary. However, access to gathered statistical data by the SelectionStrategy is concurrent, so care has to be taken. Receiving messages is done only on the whole, so there exists only one method, `messageReceived(int size)`, to notify the StatisticsProvider of such an event.

JacORB comes with two pre-implemented strategies: least frequently used and least recently used. LFU and LRU are implemented by the classes `org.jacorb.orb.giop.L[F|R]USelectionStrategyImpl` and `org.jacorb.orb.giop.L[F|R]UStatisticsProviderImpl`.

17.2.2 Configuration

To configure connection management, the following properties are provided:

`jacorb.connection.max_server_transports` This property sets the maximum number of TCP/IP connections that will be listened on by the server-side ORB.

`jacorb.connection.wait_for_idle_interval` This property sets the interval to wait until the next try is made to find an idle connection to close. Value is in microseconds.

`jacorb.connection.selection_strategy_class` This property sets the SelectionStrategy.

`jacorb.connection.statistics_provider_class` This property sets the StatisticsProvider.

`jacorb.connection.delay_close` If turned on, JacORB will delay closing of TCP/IP connections to avoid certain situations, where message loss can occur. See also section [17.2.3](#).

17.2.3 Limitations

No sunshine without rain. When trying to close a connection, it is first checked that the connection is idle, i.e. has no pending messages. If this is the case, a GIOP CloseConnection message is sent, and the TCP/IP connection is closed. Under high load, this can lead to the following situation:

1. Server sends the CloseConnection message.

¹Currently, connection management is only implemented for the server side. Therefore, only accepted ServerGIOPConnections will get a StatisticsProvider

²This is actually only done when a StatisticsProvider is configured

2. Server closes the TCP/IP connection.
3. The client sends a new request into the connection, because it hasn't yet read and acted on the `CloseConnection` message.
4. The server-side OS will send a TCP RST, which cancels out the `CloseConnection` message.
5. The client finds the connection closed and must consider the request lost.

To get by this situation, JacORB takes the following approach. Instead of closing the connection right after sending the `CloseConnection` message, we delay closing and wait for the client to close the connection. This behaviour is turned off by default, but can be enabled by setting the property `jacorb.connection.delay_close` to "yes". When non-JacORB clients are used care has to be taken that these ORBs do actively close the connection upon receiving a `CloseConnection` message.

18 Extensible Transport Framework

The *Extensible Transport Framework (ETF)*, which JacORB implements, allows you to plug in other transport layers besides the standard IIOP (TCP/IP) protocol¹.

To use an alternative transport, you need to (a) implement it as a set of Java classes following the ETF specification, and (b) tell JacORB to use the new transport instead of (or alongside with) the standard IIOP transport. We cover both steps below.

18.1 Implementing a new Transport

The interfaces that an ETF-compliant transport must implement are described in the ETF specification, and there is thus no need to repeat that information here. JacORB's default IIOP transport, which is realized in the package `org.jacorb.orb.iiop`, can also serve as a starting point for implementing your own transports.

For each transport, the following interfaces must be implemented (defined in `ETF.idl`, the package is `org.omg.ETF`):

Profile encapsulates addressing information for this transport

Listener server-side communication endpoint, waits for incoming connections and passes them up to the ORB

Connection an actual communication channel for this transport

Factories contains factory methods for the above interfaces

The `Handle` interface from the ETF package is implemented in the ORB (by the class `org.jacorb.orb.BasicAdapter`), not by individual transports. There is currently no support in JacORB for the optional zero-copy mechanism; the interface `ConnectionZeroCopy` therefore needn't be implemented.

On the server side, the `Listener` must pass incoming connections up to the ORB using the “Handle” mechanism; the `accept()` method needn't be implemented. Once a `Connection` has been passed up to the ORB, it will never be “returned” to the `Listener` again. The method `completed_data()` in

¹At the time of this writing (July 2003), ETF is still a draft standard (OMG TC document mars/2003-02-01).

the `Listener` interface therefore needn't be implemented, and neither should the `Listener` ever call `Handle.signal_data_available()` or `Handle.closed_by_peer()` (these methods throw a `NO_IMPLEMENT` exception in JacORB).

At the time of this writing (July 2003), there is still uncertainty in ETF about how server-specific Profiles (as returned by `Listener.endpoint()`, for example) should be turned into object-specific ones for inclusion into IORs. We have currently added three new operations to the `Profile` interface to resolve this issue, see JacORB's version of `ETF.idl` for details.

18.2 Configuring Transport Usage

You tell JacORB which transports it should use by listing the names of their `Factories` classes in the property `jacorb.transport.factories`. In the standard configuration, this property contains only `org.jacorb.orb.iiop.IIOPFactories`, the `Factories` class for the standard IIOP transport. The property's value is a comma-separated list of fully qualified Java class names; each of these classes must be found somewhere on the `CLASSPATH` that JacORB is started with. For example:

```
jacorb.transport.factories = my.transport.Factories, org.jacorb.orb.iiop.IIOPFactories
```

By default, a JacORB server creates listeners for each transport listed in the above property, and publishes profiles for each of these transports in any IOR it creates. The order of profiles within an IOR is the same as that of the transports in the property.

If you don't want your servers to listen on each of these transports (e.g. because you want some of your transports only to be used for client-side connections), you can specify the set of actual listeners in the property `jacorb.transport.server.listeners`. The value of this property is a comma-separated list of numeric profile tags, one for each transport that you want listeners for, and which you want published in IOR profiles. The numeric value of a transport's profile tag is the value returned by the implementation of `Factories.profile_tag()` for that transport. Standard IIOP has profile tag 0 (`TAG_INTERNET_IOP`). Naturally, you can only specify profile tag numbers here for which you have a corresponding entry in `jacorb.transport.factories`.

So, to restrict your server-side transports to standard IIOP, you would write:

```
jacorb.transport.server.listeners = 0
```

On the client side, the ORB must decide which of potentially many transports it should use to contact a given server. The default strategy is that for each IOR, the client selects *the first profile for which there is a transport implementation available at the client side* (specified in `jacorb.transport.factories`). Profiles for which the client has no transport implementation are skipped.

Note that this is a purely static decision, based on availability of an implementation. JacORB does not attempt to actually establish a transport connection in order to find out which transport can be used. Also, should the selected transport fail, JacORB does not "fall back" to the next transport in the list. (This is because JacORB opens connections lazily, only when the first actual data is being sent.)

You can customize this strategy by providing your own implementation of `org.jacorb.orb.ProfileSelector`, and specifying it in the property `jacorb.transport.client.selector`. The interface `ProfileSelector` requires a single method,

```
public Profile selectProfile (List profiles,
                             ClientConnectionManager ccm);
```

For each IOR, this method receives a list of all profiles from the IOR for which the client has a transport implementation, in the order in which they appear in the IOR. The method should select one profile from this list and return it; this profile will then be used for communication with the server.

To help with the decision, JacORB's `ClientConnectionManager` is passed as an additional parameter. The method implementation can use it to check whether connections with a given transport, or to a given server, have already been made; it can also try and pre-establish a connection using a given transport and store it in the `ClientConnectionManager` for later use. (See the JacORB source code to find out how to deal with the `ClientConnectionManager`.)

The default `ProfileSelector` does not use the `ClientConnectionManager`, it simply returns the first profile from the list, unconditionally. To let JacORB use your own implementation of the `ProfileSelector` interface, specify the fully qualified classname in the property:

```
jacorb.transport.client.selector=my.pkg.MyProfileSelector
```


19 Security Attribute Service

The Security Attribute Service (SAS) is part of the Common Secure Interoperability Specification, Version 2 (CSIv2) CORBA specification. It is defined in the Secure Interoperability chapter (chapter 24) of the CORBA 3.0.2 Specification.

19.1 Overview

The SAS specification defines the interchange between a Client Security Service (CSS) and a Target Security Service (TSS) for the exchange of security authentication and authorization elements. This information is exchanged in the Service Context of the GIOP request and reply messages. The SAS may be used in conjunction with SSL to provide privacy of the messages being sent and received.

The SAS service is implemented as a series of standard CORBA interceptors, one for the CSS and one for the TSS. The service also uses a user specified SAS context class to support different authentication mechanisms, such as GSSUP and Kerberos.

The SAS service is activated based on entries in the JacORB properties file and CORBA Properties assigned to the POA.

The following is a part of the JacORB properties file that is used by the SAS.

```
#####
#
#   SAS configuration
#
#####

jacorb.SAS.log.verbosity=INFO
jacorb.SAS.CSS.log.verbosity=INFO
jacorb.SAS.TSS.log.verbosity=INFO

# This option defines the specific SAS context generator/validator
# Currently supported contexts include:
#   GssUpContext      - Uses GSSUP security
#   KerberosContext   - uses Kerberos security
# At least one context must be selected for SAS support
jacorb.security.sas.contextClass=org.jacorb.security.sas.GssUpContext
#jacorb.security.sas.contextClass=org.jacorb.security.sas.KerberosContext

# This initializer installs the SAS interceptors
# Comment out this line if you do not want SAS support
org.omg.PortableInterceptor.ORBInitializerClass.SAS=org.jacorb.security.sas.SASInitializer
```

```
# This option is used for GSSUP security and sets up the GSS Provider
# Comment out this line if you are not using GSS UP authentication
org.omg.PortableInterceptor.ORBInitializerClass.GSSUPProvider=org.jacorb.security.sas.GSSUPProviderInitializer
```

19.2 GSSUP Example

The GSSUP (GSS Username/Password) example demonstrates the simplest usage of the SAS service. In this example, username and password pairs are sent via the SAS service. The client registers its username and password with the GSSUP Context which is later used by the CSS interceptor to generate the user's authentication information. The TSS retrieves the username and password without validating them. It is assumed by the TSS that the username and password are correct and/or will be further validated by a later interceptor or application code.

The following describes a SAS example using GSSUP.

19.2.1 GSSUP IDL Example

```
module demo{
  module sas{
    interface SASDemo{
      void printSAS();
    };
  };
};
```

The IDL contains a single interface. This interface is used to print out the user principal sent and received by the SAS service.

19.2.2 GSSUP Client Example

The following is a sample GSSUP client.

```
package demo.sas;

import java.io.BufferedReader;
import java.io.File;
import java.io.FileReader;

import org.jacorb.security.sas.GssUpContext;
import org.omg.CORBA.ORB;

public class GssUpClient {
  public static void main(String args[]) {
    if (args.length != 3) {
      System.out.println("Usage: java demo.sas.GssUpClient <ior_file> <username> <password>");
      System.exit(1);
    }
  }

  try {
```



```
// set security credentials
GssUpContext.setUsernamePassword(args[1], args[2]);

// initialize the ORB.
ORB orb = ORB.init(args, null);

// get the server
File f = new File(args[0]);
if (!f.exists()) {
    System.out.println("File " + args[0] + " does not exist.");
    System.exit(-1);
}
if (f.isDirectory()) {
    System.out.println("File " + args[0] + " is a directory.");
    System.exit(-1);
}
BufferedReader br = new BufferedReader(new FileReader(f));
org.omg.CORBA.Object obj = orb.string_to_object(br.readLine());
br.close();
SASDemo demo = SASDemoHelper.narrow(obj);

//call single operation
demo.printSAS();
demo.printSAS();
demo.printSAS();

System.out.println("Call to server succeeded");
} catch (Exception ex) {
    ex.printStackTrace();
}
}
}
```

The key to the client is the call to:

```
GssUpContext.setUsernamePassword(args[1], args[2]);
```

This call registers the client's username and password with the GSSUP context. This information will then later be used by the CSS interceptor as the user's authentication information.

19.2.3 GSSUP Target Example

The following is a sample GSSUP target.

```
package demo.sas;

import java.io.FileWriter;
import java.io.PrintWriter;

import org.jacorb.sasPolicy.SASPolicyValues;
import org.jacorb.sasPolicy.SAS_POLICY_TYPE;
import org.jacorb.sasPolicy.SASPolicyValuesHelper;
import org.omg.PortableServer.IdAssignmentPolicyValue;
import org.omg.PortableServer.LifespanPolicyValue;
import org.omg.PortableServer.POA;
import org.omg.CORBA.ORB;
import org.omg.CORBA.Any;
import org.omg.CSIOP.EstablishTrustInClient;
```

```

public class GssUpServer extends SASDemoPOA {

    private ORB orb;

    public GssUpServer(ORB orb) {
        this.orb = orb;
    }

    public void printSAS() {
        try {
            org.omg.PortableInterceptor.Current current = (org.omg.PortableInterceptor.Current)orb.resolve_initial_referen
            org.omg.CORBA.Any anyName = current.get_slot(org.jacorb.security.sas.SASInitializer.sasPrincipalNamePIC);
            if( anyName.type().kind().value() == org.omg.CORBA.TCKind._tk_null ) {
                System.out.println("Null Name");
            } else {
                String name = anyName.extract_string();
                System.out.println("printSAS for user " + name);
            }
        } catch (Exception e) {
            System.out.println("printSAS Error: " + e);
        }
    }

    public static void main(String[] args) {
        if (args.length != 1) {
            System.out.println("Usage: java demo.sas.GssUpServer <ior_file>");
            System.exit(-1);
        }

        try {
            // initialize the ORB and POA.
            ORB orb = ORB.init(args, null);
            POA rootPOA = (POA) orb.resolve_initial_references("RootPOA");
            org.omg.CORBA.Policy [] policies = new org.omg.CORBA.Policy[3];
            policies[0] = rootPOA.create_id_assignment_policy(IdAssignmentPolicyValue.USER_ID);
            policies[1] = rootPOA.create_lifespan_policy(LifespanPolicyValue.PERSISTENT);
            Any sasAny = orb.create_any();
            SASPolicyValuesHelper.insert( sasAny, new SASPolicyValues(EstablishTrustInClient.value, EstablishTrustInClient
            policies[2] = orb.create_policy(SAS_POLICY_TYPE.value, sasAny);
            POA securePOA = rootPOA.create_POA("SecurePOA", rootPOA.the_POAManager(), policies);
            rootPOA.the_POAManager().activate();

            // create object and write out IOR
            GssUpServer server = new GssUpServer(orb);
            securePOA.activate_object_with_id("SecureObject".getBytes(), server);
            org.omg.CORBA.Object demo = securePOA.servant_to_reference(server);
            PrintWriter pw = new PrintWriter(new FileWriter(args[0]));
            pw.println(orb.object_to_string(demo));
            pw.flush();
            pw.close();

            // run the ORB
            orb.run();
        } catch (Exception e) {
            e.printStackTrace();
        }
    }
}

```

19.3 Kerberos Example

The Kerberos example demonstrates how to integrate the use of a kerberos service to provide authentication credentials to the SAS service. In this example, the Java(TM) Authentication and Authorization Service (JAAS) is used to perform the Kerberos login and to return the principal and Kerberos ticket. The actual username and password may either be entered by the user or derived from the current user's Kerberos login session. For Windows 2000 Active Directory networks, this means that the user's credentials can be automatically obtained from the Windows login.

The following describes a SAS example using Kerberos.

19.3.1 Kerberos IDL Example

```
module demo{
  module sas{
    interface SASDemo{
      void printSAS();
    };
  };
};
```

The IDL contains a single interface. This interface is used to print out the user principal sent and received by the SAS service.

19.3.2 Kerberos Client Example

The following is a sample Kerberos client.

```
package demo.sas;

import java.io.BufferedReader;
import java.io.File;
import java.io.FileReader;
import java.security.Principal;
import java.security.PrivilegedAction;

import javax.security.auth.Subject;
import javax.security.auth.login.LoginContext;
import javax.security.auth.login.LoginException;

import org.omg.CORBA.ORB;

public class KerberosClient {
  private static Principal myPrincipal = null;
  private static Subject mySubject = null;
  private static ORB orb = null;

  public KerberosClient(String args[]) {

    try {
      // initialize the ORB.
      orb = ORB.init(args, null);
```

```

// get the server
File f = new File(args[0]);
if (!f.exists()) {
    System.out.println("File " + args[0] + " does not exist.");
    System.exit(-1);
}
if (f.isDirectory()) {
    System.out.println("File " + args[0] + " is a directory.");
    System.exit(-1);
}
BufferedReader br = new BufferedReader(new FileReader(f));
org.omg.CORBA.Object obj = orb.string_to_object(br.readLine());
br.close();
SASDemo demo = SASDemoHelper.narrow(obj);

//call single operation
demo.printSAS();
demo.printSAS();
demo.printSAS();

System.out.println("Call to server succeeded");
} catch (Exception ex) {
    ex.printStackTrace();
}
}

public static void main(String args[]) {
    if (args.length != 3) {
        System.out.println("Usage: java demo.sas.KerberosClient <ior_file> <username> <password>");
        System.exit(1);
    }

    // login - with Kerberos
    LoginContext loginContext = null;
    try {
        JaasTxtCallbackHandler txtHandler = new JaasTxtCallbackHandler();
        txtHandler.setMyUsername(args[1]);
        txtHandler.setMyPassword(args[2].toCharArray());
        loginContext = new LoginContext("KerberosClient", txtHandler);
        loginContext.login();
    } catch (LoginException le) {
        System.out.println("Login error: " + le);
        System.exit(1);
    }
    mySubject = loginContext.getSubject();
    myPrincipal = (Principal) mySubject.getPrincipals().iterator().next();
    System.out.println("Found principal " + myPrincipal.getName());

    // run in privileged mode
    final String[] finalArgs = args;
    try {
        Subject.doAs(mySubject, new PrivilegedAction() {
            public Object run() {
                try {
                    KerberosClient client = new KerberosClient(finalArgs);
                    orb.run();
                } catch (Exception e) {
                    System.out.println("Error running program: "+e);
                }
                System.out.println("Exiting privileged operation");
                return null;
            }
        });
    } catch (Exception e) {
        System.out.println("Error running privileged: "+e);
    }
}

```

```
}
}
}
```

The CSS uses JAAS to logon and return the user's Kerberos credentials. The CSS must then run the rest of the application as a PrivilegedAction using the logged on credentials. This allows the CSS interceptor to retrieve the Kerberos ticket from the logon session.

The following is the JAAS logon configuration for the CSS:

```
KerberosClient
{
    com.sun.security.auth.module.Krb5LoginModule required storeKey=true useTicketCache=true debug=true;
};
```

19.3.3 Kerberos Target Example

The following is a sample Kerberos target.

```
package demo.sas;

import java.io.FileWriter;
import java.io.PrintWriter;
import java.security.Principal;
import java.security.PrivilegedAction;

import javax.security.auth.Subject;
import javax.security.auth.login.LoginContext;
import javax.security.auth.login.LoginException;

import org.jacorb.sasPolicy.SASPolicyValues;
import org.jacorb.sasPolicy.SAS_POLICY_TYPE;
import org.jacorb.sasPolicy.SASPolicyValuesHelper;
import org.omg.PortableServer.IdAssignmentPolicyValue;
import org.omg.PortableServer.LifespanPolicyValue;
import org.omg.PortableServer.POA;
import org.omg.CORBA.ORB;
import org.omg.CORBA.Any;
import org.omg.CSIOP.EstablishTrustInClient;

public class KerberosServer extends SASDemoPOA {
    private static Principal myPrincipal = null;
    private static Subject mySubject = null;
    private ORB orb;

    public KerberosServer(ORB orb) {
        this.ORB = orb;
    }

    public void printSAS() {
        try {
            org.omg.PortableInterceptor.Current current = (org.omg.PortableInterceptor.Current) orb.resolve_initial_referer
            org.omg.CORBA.Any anyName = current.get_slot(org.jacorb.security.sas.SASInitializer.sasPrincipalNamePIC);
            String name = anyName.extract_string();
            System.out.println("printSAS for user " + name);
        } catch (Exception e) {
            System.out.println("printSAS Error: " + e);
        }
    }
}
```

```

}

public KerberosServer(String[] args) {
    try {
        // initialize the ORB and POA.
        orb = ORB.init(args, null);
        POA rootPOA = (POA) orb.resolve_initial_references("RootPOA");
        org.omg.CORBA.Policy [] policies = new org.omg.CORBA.Policy[3];
        policies[0] = rootPOA.create_id_assignment_policy(IdAssignmentPolicyValue.USER_ID);
        policies[1] = rootPOA.create_lifespan_policy(LifespanPolicyValue.PERSISTENT);
        Any sasAny = orb.create_any();
        SASPolicyValuesHelper.insert( sasAny, new SASPolicyValues(EstablishTrustInClient.value, EstablishTrustInClient.value));
        policies[2] = orb.create_policy(SAS_POLICY_TYPE.value, sasAny);
        POA securePOA = rootPOA.create_POA("SecurePOA", rootPOA.the_POAManager(), policies);
        rootPOA.the_POAManager().activate();

        // create object and write out IOR
        securePOA.activate_object_with_id("SecureObject".getBytes(), this);
        org.omg.CORBA.Object demo = securePOA.servant_to_reference(this);
        PrintWriter pw = new PrintWriter(new FileWriter(args[0]));
        pw.println(orb.object_to_string(demo));
        pw.flush();
        pw.close();
    } catch (Exception e) {
        e.printStackTrace();
    }
}

public static void main(String[] args) {
    if (args.length != 2) {
        System.out.println("Usage: java demo.sas.KerberosServer <ior_file> <password>");
        System.exit(-1);
    }

    // login - with Kerberos
    LoginContext loginContext = null;
    try {
        JaasTxtCallbackHandler cbHandler = new JaasTxtCallbackHandler();
        cbHandler.setMyPassword(args[1].toCharArray());
        loginContext = new LoginContext("KerberosService", cbHandler);
        loginContext.login();
    } catch (LoginException le) {
        System.out.println("Login error: " + le);
        System.exit(1);
    }
    mySubject = loginContext.getSubject();
    myPrincipal = (Principal) mySubject.getPrincipals().iterator().next();
    System.out.println("Found principal " + myPrincipal.getName());

    // run in privileged mode
    final String[] finalArgs = args;
    try {
        Subject.doAs(mySubject, new PrivilegedAction() {
            public Object run() {
                try {
                    // create application
                    KerberosServer app = new KerberosServer(finalArgs);
                    app.ORB.run();
                } catch (Exception e) {
                    System.out.println("Error running program: "+e);
                }
                return null;
            }
        });
    } catch (Exception e) {

```

```
System.out.println("Error running privileged: "+e);  
}  
}  
}
```

The TSS uses JAAS to logon and return the user's Kerberos credentials. The logon principal to use is defined in the JAAS login configuration file. The TSS must then run the rest of the application as a PrivilegedAction using the logged on credentials. This allows the TSS interceptor to retrieve the Kerberos ticket from the logon session.

The following is the JAAS logon configuration for the TSS:

```
KerberosService  
{  
    com.sun.security.auth.module.Krb5LoginModule required storeKey=true principal="testService@OPENROADSCONSU  
};
```


20 The JacORB Notification Service

The JacORB Notification Service is a partial implementation of the Notification Service specified by the OMG.

20.1 Installation

If you're using JDK 1.3 and want to use the JacORB Notification Service you'll need to download the additional library `gnu.regex` from <http://www.cacas.org/java/gnu/regex> and put it in your classpath. This is necessary because the JacORB Notification Service depends on regular expressions. This functionality is available in the JDK since version 1.4.

20.2 Running the Notification Service

Before the JacORB Notification Service can be accessed a server process must be started. Starting the notification server is done by running

```
$ ntfy [-printIOR] [-printCorbaloc] [-writeIOR filename]  
[-registerName nameID.nameKind] [-port oaPort] [-channels channels]  
[-help]
```

<code>-printIOR</code>	print the IOR to STDOUT
<code>-printCorbaloc</code>	print the Corbaloc to STDOUT
<code>-writeIOR <i>filename</i></code>	write the IOR to a file
<code>-registerName <i>nameID.nameKind</i></code>	make a Name Service entry for the EventChannelFactory. The Notification Service resolves the Name Service via a call to <code>resolve_initial_references("NameService")</code> . Ensure that the Name Service is available.
<code>-port <i>oaPort</i></code>	start the Notification Service on the specified port.
<code>-channels <i>channels</i></code>	create a number EventChannels.

20.2.1 Running as a NT Service or a UNIX Daemon

With a little help from [the Java Service Wrapper](#) it is easy to run the JacORB notification service as a Windows Service or as a UNIX daemon.

Note for JDK 1.3 Users

As noted if you are running JDK 1.3 you need to provide an additional library. If you use the Wrapper you also need to add a classpath entry to the Wrapper configuration file.

Edit `bin/NotifyService-Wrapper.conf` and add a classpath entry:

```
# Java Classpath (include wrapper.jar)  Add class path elements as
# needed starting from 1
wrapper.java.classpath.1=../lib/wrapper-3.0.3.jar
...
wrapper.java.classpath.6=../lib/avalon-framework-4.1.5.jar
wrapper.java.classpath.7=../lib/gnu.regex.jar
```

Installing and Running as a NT Service

The necessary wrapper configuration files are preconfigured in the `JacORB/bin` directory.

The notification service can be installed as a service by double clicking on the `NotifyService-Install-NT.bat` batch file which is located in the `JacORB/bin` directory. Alternatively you can open a Command Window and then run the install script from the command prompt.

```
C:\JacORB\bin>NotifyService-Install-NT.bat
wrapper | JacORB Notification Service installed.
```

Once the service has been installed, it can be started by opening up the Service Control Panel, selecting the service, and then pressing the start button.

The service can also be started and stopped from within a Command Window by using the `net start JacORB-Notify` and `net stop JacORB-Notify` commands, or by passing commands to the `Wrapper.exe` executable.

The wrapper is set up to start the JacORB Notification Service whenever the machine is rebooted.

The service can be uninstalled by running the `NotifyService-Uninstall-NT.bat` batch file.

See the Windows specific [wrapper documentation](#) for more details.

Installing and Running as a UNIX Daemon

JacORB is shipped with a `sh` script which can be used to start and stop the JacORB Notification Service controlled by the Java Service Wrapper.

First you need to download the appropriate binary for your system from <http://wrapper.tanukisoftware.org>. The Java Service Wrapper is supported on Windows, Linux, Solaris, AIX, HP-UX, Macintosh OS X, DEC OSF1, FreeBSD, and SGI Irix systems (Note: You don't need to download anything if you are running Windows. All necessary stuff is shipped with the JacORB distribution).

You'll need two files from the downloaded distribution. One is the system-specific wrapper executable. Place it somewhere in your searchpath. The second is the native library `libwrapper.so` in the `wrapper-dir/lib` directory. This library is required by the wrapper executable. Place the library in the `JacORB/lib` directory. Alternatively you can create a link to the library.

Ensure that the shell-script `JacORB/bin/ntfy-wrapper` has the executable bit set. Note that the `sh` script will attempt to create a `pid` file in the directory specified by the property `PIDDIR` in the script. If the user used to launch the Wrapper does not have permission to write to this directory then this will result in an error. An alternative that will work in most cases is to write the `pid` file to another directory. To make this change, edit the `sh` script and change the following line:

```
PIDDIR=" . "
```

to something more appropriate:

```
PIDDIR="/var/run"
```

Running in the console The JacORB notification service can now be run by simply executing `bin/ntfy-wrapper console`.

When running using the console command, output from the notification service will be visible in the console.

The notification service can be terminated by hitting CTRL-C in the command window. This will cause the Wrapper to shut down the service cleanly.

If you omit the command the script prints the available commands. The script accepts the commands `start`, `stop`, `restart` and `dump`. The `start`, `stop`, and `restart` commands are common to most daemon scripts and are used to control the wrapper and the notification service as a daemon process. The `console` command will launch the wrapper in the current shell, making it possible to kill the application with CTRL-C. The final command, `dump`, will send a `kill -3` signal to the wrapper causing the its JVM to do a full thread dump.

Running as a Daemon Process The application can be run as a detached daemon process by executing the script using the `start` command.

When running using the start command, output from the JVM will only be visible by viewing the logfile `NotifyService-Wrapper.log` using `tail -f NotifyService-Wrapper.log`. The location of the logfile can be configured in the wrapper configuration file `bin/NotifyService-Wrapper.conf`

Because the application is running as a detached process, it can not be terminated using CTRL-C and will continue to run even if the console is closed.

To stop the application rerun the script using the *stop* command.

Installing The Application To Start on Reboot This is system specific. See the UNIX specific [wrapper documentation](#) for instructions for some platforms.

20.3 Accessing the Notification Service

Configuring a default notification service as the ORB's default is done by adding the URL that points to the service to the properties files `.jacorb.properties`. A valid URL can be obtained in various ways:

1. By specifying the option `-printIOR` as you start the notification service a stringified IOR is printed out to the console. From there you can copy it to a useful location.
2. Usually the stringified IOR makes most sense inside a file. Use the option `-writeIOR <filename>` to write the IOR to the specified file.
3. A more compact URL can be obtained by using the option `-printCorbaloc`. In conjunction with the option `-port` you can use the simplified corbaloc: URL of the form `corbaloc::ip-address:port/NotificationService`. This means all you need to know to construct an object reference to your notification service is the IP address of the machine and the port number the server process is listening on (the one specified using `-port`).

Add the property `ORBInitRef.NotificationService` to your properties file. The value can be a corbaloc: URL or alternatively the file name where you saved the IOR.

The JacORB notification service is accessed using the standard CORBA defined interface:

```
// get a reference to the notification service
ORB orb = ORB.init(args, null);
org.omg.CORBA.Object obj;
obj = orb.resolve_initial_references("NotificationService");
EventChannelFactory ecf = EventChannelHelper.narrow( o );
IntHolder ih = new IntHolder();
Property[] p1 = new Property[0];
Property[] p2 = new Property[0];
EventChannel ec = ecf.create_channel(p1, p2, ih);
...
```

20.4 Configuration

Following is a brief description of the properties that control Notification Service behaviour.

The Notification Service uses up to three Thread Pools with a configurable size. The first Thread Pool is used to process the filtering of the Messages. The second Thread Pool is used to deliver the Messages to the Consumers. The third Thread Pool is used to pull Messages from PullSuppliers.

Table 20.1: Notification Service Properties

Property	Description	Type	Default
<code>filter.thread_pool_size</code> ¹	This is the Size of the Thread Pool used to process the filters. Increasing this value on a Multiprocessor machine or if Filters are on a different machine than the Channel could increase the Filtering Performance as multiple events can be processed concurrently.	<code>int</code> ≥ 0	2
<code>proxysupplier.thread_pool_size</code>	This is the Size of the Thread Pool used to deliver the Messages to the Consumers. By using the property <code>proxysupplier.threadpolicy</code> ² it is also possible to use one Thread per ProxySupplier.	<code>int</code> ≥ 0	4
<code>proxyconsumer.thread_pool_size</code>	Specifies the Size of the Thread Pool used to pull Messages from PullSuppliers	<code>int</code> ≥ 0	2
<code>proxysupplier.threadpolicy</code>	Specify which thread policy the ProxySuppliers should use to deliver the Messages to its Consumers. Valid values are: ThreadPool a fixed number of threads is used. See property <code>proxysupplier.thread_pool_size</code> . ThreadPerProxy Each ProxySupplier uses its own thread.	string	Thread-Pool
<code>supplier.poll_intervall</code>	Specifies how often Messages should be pulled from a PullSupplier. The value specifies the intervall between two pull-Operations.	milli-seconds	1000

¹ All notification service properties share the common prefix *jacorb.notification* which is omitted here to save some space

² also abbreviated.

Table 20.1: Notification Service Properties

Property	Description	Type	Default
<code>supplier.max_number</code>	Specify the maximum number of Suppliers that may be connected to a Channel at a time. If a Supplier tries to connect, while this limit is exceeded, <code>AdminLimitExceeded</code> is raised. Note that this property can also be set programatically via the <code>set_admin</code> operation.	<code>int > 0</code>	maximum int value
<code>consumer.max_number</code>	Specify the maximum number of Consumers that may be connected to a Channel at a time. If a Consumer tries to connect, while this limit is exceeded, <code>AdminLimitExceeded</code> is raised. Note that this property can also be set programatically via the <code>set_admin</code> operation.	<code>int > 0</code>	maximum int value
<code>max_events_per_consumer</code>	Specifies how many Events a ProxySupplier at most should queue for a consumer. If this number is exceeded Events are discarded according to the DiscardPolicy configured for the ProxySupplier.	<code>int > 0</code>	100
<code>max_batch_size</code>	Specifies the maximal number of Messages a SequencePushSupplier should queue before a delivery to its connected SequencedPushConsumer is forced.	<code>int >= 0</code>	1
<code>order_policy</code>	Specify how events that are queued should be ordered. Valid values are: <ul style="list-style-type: none"> • AnyOrder • PriorityOrder • DeadlineOrder • FifoOrder 	string	Priority-Order
<code>discard_policy</code>	Specifies which Events are discarded if more than the maximal number of events are queued for a consumer. Valid values are: <ul style="list-style-type: none"> • AnyOrder • PriorityOrder • DeadlineOrder • FifoOrder • LifoOrder 	string	Priority-Order

Table 20.1: Notification Service Properties

Property	Description	Type	Default
consumer.backout_interval	After a delivery to a Consumer has failed the Channel will pause delivery to that Consumer for a while before retrying. This property specifies how long a consumer should stay disabled.	milli-seconds	1000
consumer.error_threshold	Each failed delivery to a consumer increments an errorcounter. If this errorcounter exceeds the specified value the consumer is disconnected from the channel.	int ≥ 0	3
default_filter_factory	Specify which FilterFactory (CosNotifyFilter::FilterFactory) the attribute EventChannel::default_filter_factory should be set to. Default value is <i>builtin</i> . This special value implies that a FilterFactory will be created during start of the EventChannel. Its possible to set this property to a URL that points to another CosNotifyFilter::FilterFactory object. In this case no FilterFactory is started by the EventChannel. The URL is resolved by a call to ORB::string_to_object.	URL	builtin
proxy.destroy_causes_disconnect	Specify if a destroyed Proxy should call the disconnect operation of its consumer/supplier.	boolean	on

21 JacORB utilities

In this chapter we briefly explain the executables that come with JacORB. These include the IDL-compiler, a utility to decode IORs and print their components, the JacORB name server, a utility to test a remote object's liveness, etc.

21.1 idl

The IDL compiler parses IDL files and maps type definitions to Java classes as specified by the OMG IDL/Java language mapping. For example, IDL interfaces are translated into Java interfaces, and typedefs, structs, const declarations etc. are mapped onto corresponding Java classes. Additionally, stubs and skeletons for all interface types in the IDL specification are generated.

Compiler Options

-h help	print help on compiler options
-v version	print compiler version information
-d dir	root of directory tree for output (default: current directory)
-syntax	syntax check only, no code generation
-Dx	define preprocessor symbol x with value 1
-Dx=y	define preprocessor symbol x with value y
-Idir	set include path for idl files
-Usymbol	undefine preprocessor symbol
-W [1..4]	debug output level (default is 1)
-all	generate code for all IDL files, even included ones (default is off) If you want to make sure that for a given IDL no code will be generated even if this option is set, use the (proprietary) preprocessor directive <code>#pragma inhibit_code_generation</code> .
-forceOverwrite	generate Java code even if the IDL files have not changed since the last compiler run (default is off)
-ami_callback	generate AMI reply handlers and sendc methods (default is off). See chapter 15
-ami_polling	generate AMI poller and sendp methods (default is off). See chapter 15
-backend classname	use classname as compiler (code generator) backend. The default code generator class is <code>org.jacorb.idl.javamapping.JavaMappingGeneratingVisitor</code> (c.f. API documentation). Custom generators must implement the interface

	<code>org.jacorb.idl.IDLTreeVisitor</code>
<code>-i x</code>	(deprecated) generated Java classes will contain an "import x;" statement (default is off)
<code>-i2jpackage x:a.b.c</code>	replace IDL package name x by a.b.c in generated Java code (e.g. CORBA:org.omg.CORBA)
<code>-i2jpackagefile filename</code>	replace IDL package names using list from {filename}.
	Format as above.
<code>-ir</code>	generate extra information required by the JacORB Interface Repository (One extra file for each IDL module, and another additional file per IDL interface.) (default is off)
<code>-nofinal</code>	generated Java code will contain no final class definitions, which is the default to allow for compiler optimizations.
<code>-unchecked_narrow</code>	use unchecked_narrow in generated code for IOR parameters in operations (default is off). Generated helper classes contain marshalling code which, by default, will try to narrow any object references to statically known interface type. This may involve remote invocations to test a remote object's type, thus incurring runtime overhead to achieve static type safety. The -unchecked_narrow option generates code that will not be statically type safe, but avoids remote tests of an object's type. If the type is not as expected, clients will experience CORBA.BAD_OPERATION exceptions at invocation time.
<code>-noskel</code>	disables generation of POA skeletons (e.g., for client-side use)
<code>-nostub</code>	disables generation of client stubs (for server-side use)
<code>-sloppy_forward</code>	allow forward declarations without later definitions (useful only for separate compilation).
<code>-sloppy_names</code>	less strict checking of module name scoping (default: off) CORBA IDL has a number of name resolution rules that are stricter than necessary for Java (e.g., a struct member's name identifier must not equal the type name). The -sloppy_names option relaxes checking of these rules. Note that IDL accepted with this option will be rejected by other, conformant IDL compilers!
<code>-permissive_rmic</code>	tolerate dubious and buggy IDL generated by JDK's rmic stub generator (e.g., incorrectly empty inheritance clauses), includes -sloppy_names.

The `-i2jpackage` switch can be used to flexibly redirect generated Java classes into packages. Using this option, any IDL scope x can be replaced by one (or more) Java packages y. Specifying `-i2jpackage X:a.b.c` will thus cause code generated for IDL definitions within a scope x to end up in a Java package a.b.c, e.g. an IDL identifier `X::Y::ident` will be mapped to `a.b.c.y.ident` in Java. It is also possible to specify a file containing these mappings using the `-i2jpackagefile` switch.

(The IDL parser was generated with Scott Hudson's CUP parser generator. The LALR grammar for the CORBA IDL is in the file `org/jacorb/idl/parser.cup`.)

21.2 ns

JacORB provides a service for mapping names to network references. The name server itself is written in Java like the rest of the package and is a straightforward implementation of the CORBA “Naming Service” from Common Object Services Spec., Vol.1 [OMG97]. The IDL interfaces are mapped to Java according to our Java mapping.

Usage

```
$ ns <filename> [<timeout>]
```

or

```
$ jaco jacob.Naming.NameServer <filename> [<timeout>]
```

Example

```
$ ns ~/public_html/NS_Ref
```

The name server does *not* use a well known port for its service. Since clients cannot (and need not) know in advance where the name service will be provided, we use a bootstrap file in which the name server records an object reference to itself (its *Interoperable Object Reference* or IOR). The name of this bootstrap file has to be given as an argument to the `ns` command. This bootstrap file has to be available to clients network-wide, so we demand that it be reachable via a URL — that is, there must be an appropriately configured HTTP server in your network domain which allows read access to the bootstrap file over a HTTP connection. (This implies that the file must have its read permissions set appropriately. If the binding to the name service fails, please check that this is the case.) After locating the name service through this mechanism, clients will connect to the name server directly, so the only HTTP overhead is in the first lookup of the server.

The name bindings in the server’s database are stored in and retrieved from a file that is found in the current directory unless the property `jacob.naming.db_dir` is set to a different directory name. When the server starts up, it tries to read this file’s contents. If the file is empty or corrupt, it will be ignored (but overridden on exit). The name server can only save its state when it goes down after a specified timeout. If the server is interrupted (with `CTRL-C`), state information is lost and the file will not contain any usable data.

If no timeout is specified, the name server will simply stay up until it is killed. Timeouts are specified in milliseconds.

21.3 nmg

The JacORB NameManager, a GUI for the name service, can be started using the `nmg` command. The NameManager then tries to connect to an existing name service.

Usage

```
$ nmg
```

21.4 lsns

This utility lists the contents of the default naming context. Only currently active servers that have registered are listed. The `-r` option recursively lists the contents of naming contexts contained in the root context. If the graph of naming contexts contains cycles, trying to list the entire contents recursively will not return...

Usage

```
$ lsns [-r]
```

Example

```
$ lsns
/grid.service
```

when only the server for the grid example is running and registered with the name server.

21.5 dior

JacORB comes with a simple utility to decode an interoperable object reference (IOR) in string form into a more readable representation.

Usage

```
$ dior <IOR-string> | -f <filename>
```

Example

In the following example we use it to print out the contents of the IOR that the JacORB name server writes to its file:

```
$ dior -f ~/public_html/NS_Ref
```

```
-----IOR components-----
TypeId      :          IDL:omg.org/CosNaming/NamingContextExt:1.0
```

```
Profile Id      : TAG_INTERNET_IOP
IIOP Version    : 1.0
Host           : 160.45.110.41
Port           : 49435
Object key      : 0x52 6F 6F 74 50 4F 41 3A 3A 30 D7 D1 91 E1 70 95 04
```

21.6 pingo

“Ping” an object using its stringified IOR. Pingo will call `_non_existent()` on the object’s reference to determine whether the object is alive or not.

Usage

```
$ pingo <IOR-string> | -f <filename>
```

21.7 ir

This command starts the JacORB Interface Repository, which is explained in chapter 10.

Usage

```
$ ir <repository class path> <IOR filename>
```

21.8 qir

This command queries the JacORB Interface Repository and prints out re-generated IDL for the repository item denoted by the argument repository ID.

Usage

```
$ qir <repository Id>
```

21.9 ks

This command starts the JacORB KeyStoreManager, which is explained in chapter 12

Usage

```
$ ks
```

21.10 fixior

This command patches host and port information into an IOR file.

Usage

```
$ fixior <host> <port> <ior_file>
```

Bibliography

- [BVD01] Gerald Brose, Andreas Vogel, and Keith Duddy. *Java Programming with CORBA*. John Wiley & Sons, 3rd edition, 2001.
- [HV99] Michi Henning and Steve Vinoski. *Advanced CORBA Programming with C++*. Addison–Wesley, 1999.
- [OMG97] OMG. *CORBAservices: Common Object Services Specification*, November 1997.
- [Sie00] Jon Siegel. *CORBA 3 Fundamentals and Programming*. Wiley, 2nd edition, 2000.
- [Vin97] Steve Vinoski. Corba: Integrating diverse applications within distributed heterogeneous environments. *IEEE Communications Magazine*, 14(2), February 1997.
- [Vin98] Steve Vinoski. New features for corba 3.0. *CACM*, 41(10):44–52, October 1998.