

XSM  
eXperimental String Machine  
Version 1.0

Dr. K. Muralikrishnan  
`kmurali@nitc.ac.in`  
NIT Calicut

September 25, 2012

# Contents

<b>1</b>	<b>Introduction</b>	<b>3</b>
1.1	Brief Machine Description . . . . .	3
1.2	Components of the Machine . . . . .	3
<b>2</b>	<b>Registers</b>	<b>4</b>
2.1	Introduction . . . . .	4
2.2	Register Set . . . . .	4
<b>3</b>	<b>Memory</b>	<b>4</b>
3.1	Introduction . . . . .	4
3.2	Address Translation . . . . .	5
<b>4</b>	<b>Disk Storage</b>	<b>5</b>
<b>5</b>	<b>Instructions</b>	<b>6</b>
5.1	Introduction . . . . .	6
5.2	Classification . . . . .	6
5.2.1	Unprivileged Instructions . . . . .	6
5.2.2	Privileged Instructions . . . . .	9
5.3	Processor Modes . . . . .	10
<b>6</b>	<b>Interrupts</b>	<b>10</b>
6.1	Introduction . . . . .	10
6.2	The INT instruction . . . . .	11
6.3	Types of Interrupts . . . . .	11

# 1 Introduction

## 1.1 Brief Machine Description

The machine simulator is known as Experimental String Machine (XSM). It is an interrupt driven uniprocessor machine. The machine handles data as strings. A string is a sequence of characters terminated by '\0'. The length of a string is atmost 16 characters including '\0'. Each of these strings is stored in a **word** (Refer Section 3). The machine interprets a single character also as a string.

## 1.2 Components of the Machine




Figure 1: Components of the Machine

- Disk : It is a non-volatile storage that stores user programs (executables) and data files. The Operating System code is also stored in the disk.
- Memory : It is a volatile storage that stores the programs to be run on the machine as well as the operating system that manages the various programs.
- Processor : It is the main computational unit that is used to execute the instructions.

- Timer : It is a device that interrupts the processor after a pre-defined specific time interval.
- Load/Store : It is a macro that performs the functionalities of DMA (Direct Memory Access) controller. (Refer Section 5)

## 2 Registers

### 2.1 Introduction

The XSM architecture maintains 24 registers (each one **word**).

### 2.2 Register Set

There are 16 General Purpose Registers (GPR), R0 - R15, of which R0 - R7 are Program Registers and R8 - R15 are Kernel Registers. There are 4 temporary registers T0 - T3 which are reserved for code translation. These registers cannot be used by the system programmer. In addition to these 20 registers there are 4 Special Purpose Registers (SPR) namely BP (Base Pointer), SP (Stack Pointer), PID (Process Identifier) and IP (Instruction Pointer).

Name	Register
Program Register	R0-R7
Kernel Register	R8-R15
Temporary Registers	T0-T3
Base Pointer	BP
Instruction Pointer	IP
Stack Pointer	SP
Process Identifier	PID

## 3 Memory

### 3.1 Introduction

- The basic unit of memory in XSM is a 16 character string.
- The machine memory can be thought of as a linear sequence of strings.
- A collection of 512 contiguous strings is known as a page.
- The total size of the memory is 64 pages or 32768 ( $512 \times 64$ ) strings.

- Each string in the memory is identified by the *string address* in the range 0 to 32767 ( $512 \times 64 - 1$ ). Similarly, each page in the memory is identified by the *page number* in the range 0 to 63.

### 3.2 Address Translation

There are two kinds of memory addresses,

- Logical address : When a process runs, CPU generates address for the data accessed by this process. This address is called the Logical address.
- Physical address : It is the actual location of the data in the main memory.

Address translation is the process of obtaining the physical address from the logical address. It is done by the machine in the following way.

1. The logical address generated by the CPU is divided by the page size (512) to get the **logical page number**. The remainder is the **offset** of the data within that page.
2. A **page table** is used for address translation. It contains physical page numbers corresponding to each logical page number. The logical page number is used to index the page table to get the corresponding physical page number.
3. The **offset** is then used to refer to the word in the physical page containing the data.

## 4 Disk Storage

**Block** : It is the basic unit of storage in the disk.

The disk can be thought of as consisting of a linear sequence of 512 blocks. The size of each block is equal to that of a page in the memory (512 strings).

Any particular block in the disk is addressed by the corresponding number in the sequence 0 to 511 known as the **block number**.

## 5 Instructions

### 5.1 Introduction

Every instruction in XSM is 2 strings long. The instructions provided by the XSM architecture can be classified into privileged and unprivileged instructions.

### 5.2 Classification

#### 5.2.1 Unprivileged Instructions

##### 1. MOV

- Immediate Addressing:  
*Syntax* : MOV Ri, NUM/STRING  
Copies the NUM/STRING to the register Ri.
- Register Addressing:  
*Syntax* : MOV Ri, Rj  
Copies the contents of the register Rj to Ri.
- Register Indirect Addressing:  
*Syntax* : MOV Ri, [Rj]  
Copy contents of memory location pointed by Rj to register Ri.  
*Syntax* : MOV [Ri], Rj  
Copy contents of Rj to the location whose address is in Ri.
- Direct Addressing:  
*Syntax* : MOV [LOC], Rj  
Copy contents of Rj to the memory address LOC.  
*Syntax* : MOV Rj, [LOC]  
Copy contents of the memory location LOC to the register Rj.

##### 2. Arithmetic Instructions

- ADD, SUB, MUL, DIV and MOD.  
*General Syntax* : OP Ri, Rj  
The result of Ri op Rj is stored in Ri. Ri and Rj should represent integers. Otherwise no operation is performed on the registers.
- INR  
*Syntax* : INR Ri  
Increments the value of register Ri by 1. Ri should represent an integer. Otherwise no operation is performed on Ri.

- DCR

*Syntax* : DCR Ri

Decrements the value of register Ri by 1. Ri should represent an integer. Otherwise no operation is performed on Ri.

### 3. Logical Instructions

- LT

*Syntax* : LT Ri, Rj

Stores 1 in Ri if the value stored in Ri is less than that in Rj. Ri is set to 0 otherwise. Strings can also be compared using LT

- GT

*Syntax* : GT Ri, Rj

Stores 1 in Ri if the value stored in Ri is greater than that in Rj. Ri set to 0 otherwise. Strings can also be compared using GT

- EQ

*Syntax* : EQ Ri, Rj

Stores 1 in Ri if the value stored in Ri is equal to that in Rj. Set to 0 otherwise. Strings can also be compared using EQ

- NE

*Syntax* : NE Ri, Rj

Stores 1 in Ri if the value stored in Ri is not equal to that in Rj. Set to 0 otherwise. Strings can also be compared using NE

- GE

*Syntax* : GE Ri, Rj

Stores 1 in Ri if the value stored in Ri is greater than or equal to that in Rj. Set to 0 otherwise. Strings can also be compared using GE

- LE

*Syntax* : LE Ri, Rj

Stores 1 in Ri if the value stored in Ri is less than or equal to that in Rj. Set to 0 otherwise. Strings can also be compared using LE

### 4. Labels

*Syntax* : LABEL *labelname*

Creates a label with a *labelname* which is a string. Labels are used in branching instruction to specify memory location of target instructions.

## 5. Branching Instructions

Branching is achieved by changing the value of the IP to the address of a specified `labelname`.

- JZ  
Syntax : JZ Ri, labelname  
Jumps to `labelname` if the contents of Ri is zero.
- JNZ  
Syntax : JNZ Ri, labelname  
Jumps to `labelname` if the contents of Ri is not zero.
- JMP  
Syntax : JMP labelname  
Unconditional jump to address specified by `labelname`

## 6. Stack Instructions

- PUSH  
Syntax : PUSH Ri  
Increment SP by 1 and copy contents of Ri to the location pointed to by SP.
- POP  
Syntax : POP Ri  
Copy contents of the location pointed to by SP into Ri and decrement SP by 1.  
For both these instructions Ri may be any register except IP.

## 7. Subroutine Instructions

The `CALL` instruction copies the address of the next instruction to be fetched ( $IP + 2$ ) on to location  $SP + 1$ , increments SP by one and transfers control to the `labelname` specified. The `RET` instruction restores the IP value stored at location pointed by SP, decrements SP by one and continues execution fetching the next instruction pointed to by IP. The subroutine instructions provide a neat mechanism for procedure evocations.

- CALL  
Syntax : CALL labelname  
Increment SP by 1, transfers  $IP+1$  to location pointed to by SP and jumps to LABEL



- RET  
Syntax : RET  
Sets IP to the value pointed to by SP and decrements SP.

#### 8. Input/Output Instructions

- IN  
Syntax : IN Ri  
Transfers the contents of the standard input to Ri.
- OUT  
Syntax : OUT Ri  
Transfers the contents of Ri to the standard output.

- #### 9. START
- Syntax : START  
IP will be initialised to this instruction automatically when a program is taken for execution.

- #### 10. END
- Syntax : END  
This instruction marks the end of a program.

- #### 11. INT
- Syntax : INT n  
Generates an interrupt to the kernel with n (1 to 6) as a parameter.  
(Read Section 6)

### 5.2.2 Privileged Instructions

There are four privileged instructions. They are:

1. IRET  
Syntax : IRET

Set IP to the value pointed to by SP and decrements SP by one. IRET does the same action as RET, but it tells the processor that the interrupt handler has finished. With the execution of the IRET instruction, interrupts are enabled. (Read Section 6)

2. LOAD  
Syntax : LOAD *pagenum blocknum*

This instruction loads the block specified by the *blocknum*, from the disk, to the page specified by the *pagenum* in the memory. *blocknum* and *pagenum* should be numbers or registers containing numbers. Otherwise no action is performed.

### 3. STORE

Syntax : STORE *blocknum pagenum*

This instruction stores the page specified by the *pagenum*, from the memory, to the block specified by the *blocknum* in the disk. *blocknum* and *pagenum* should be numbers or registers containing numbers. Otherwise no action is performed.

### 4. HALT

Syntax : HALT

This instruction causes the simulator to halt immediately.

## 5.3 Processor Modes

The XSM architecture is interrupt driven and uses a single processor. There are two privilege modes of execution, the user mode and the kernel mode. The privilege mode of execution is determined by the value of IP, i.e. the area in memory where the currently executing code executes.

- User mode : Only unprivileged instructions can be executed in this mode. The value of IP cannot be changed in unprivileged mode.
- Kernel mode : Both privileged and unprivileged instructions can be executed in this mode.

Page Number	Privilege Space
0	ROM Code
1 - 7	Kernel Space
8 - 55	User Space
56 - 63	Kernel Space (INT 0 - 7)

## 6 Interrupts

### 6.1 Introduction

Interrupts are mechanisms by which the user code interrupts the execution of the processor and passes control to the kernel to accomplish low level functionalities like disk access, arithmetic exception handling etc.

## 6.2 The INT instruction

The instruction used to generate an interrupt is **INT**.

Syntax : **INT n**

The **INT** instruction passes control to the Interrupt Service Routine (ISR) for this interrupt located at the physical address computed using the value **n**.

Address computation is done as follows. The physical address of the ISR corresponding to interrupt number **n** is given by:

**Physical Address = (56 + n) x Page Size**

Note that the interrupts are disabled once this instruction is executed as interrupts cannot be executed in kernel mode.

## 6.3 Types of Interrupts

There are 8 interrupts (numbered from 0 to 7) supported by the XSM architecture. The interrupts 0 and 7 are hardware interrupts and the remaining interrupts (1 to 6) are software interrupts.

### Hardware Interrupts

These interrupts cannot be called from user/kernel mode.

- **Interrupt 0**

It transfers control of execution, i.e. changes the value of IP to *page number* 56 (address = 28672). This is the timer interrupt which interrupts the processor forcing a context switch. It contains the code for the scheduler of the operating system, which schedules the CPU time among the various active processes.

- **Interrupt 7** : It transfers control of execution to *page number* 63 (address = 32256). It is generated when the following exceptions occur:

1. Illegal memory access : occurs when any address generated by the process **does not** lie in the range **[0, 2047]**.
2. Arithmetic exception : occurs when divisor is 0.
3. Illegal instruction : occurs when an attempt is made to execute an instruction not belonging to the instruction set and also when the operands to the instruction is not legal. Eg: **MOV 4 R0, MOV IP 4** when executed in user mode. These instructions are considered illegal.

4. Stack overflow and stack underflow : Stack overflow occurs when the value in the **SP** register exceeds **2047** and stack underflow occurs when the value falls below **1536**.

### **Software Interrupts**

These interrupts are unprivileged and can be called from user mode.

- INT 1  
It transfers control of execution to *page number* 57 (address = 29184)
- INT 2  
It transfers control of execution to *page number* 58 (address = 29696)
- INT 3  
It transfers control of execution to *page number* 59 (address = 30208)
- INT 4  
It transfers control of execution to *page number* 60 (address = 30720)
- INT 5  
It transfers control of execution to *page number* 61 (address = 31232)
- INT 6  
It transfers control of execution to *page number* 62 (address = 31744).