

User Manual

CP2K

A program package to perform
Molecular Dynamics Simulations

The CP2K developers group

CP2K program release 1.0

March 17, 2003

ETH Zurich, Swiss Center for Scientific Computing, Switzerland
University of Zurich, Physical Chemistry Institute, Switzerland

Disclaimer

Please note that this manual is not complete. Basically it refers to the CP2K program release 1.0, but the CP2K program package is continuously improved and extended. Therefore the ultimate reference is always the CP2K source code.

Please cite this manual as:

The CP2K developers group, *CP2K User Manual (Release 1.0)*, Zurich (2003).

This version of the manual was compiled by Matthias Krack (krack@cscs.ch).

Copyright

CP2K: A program package to perform molecular dynamics simulations

Copyright © 2003 [The CP2K developers group](#)

This program is free software; you can redistribute it and/or modify it under the terms of the [GNU General Public License](#) as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version. This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details. You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 675 Mass Ave, Cambridge, MA 02139, USA.

Contents

1	Introduction	5
2	Installation	6
3	Running CP2K	7
3.1	Input files	7
3.1.1	Fist	7
3.1.2	Quickstep	7
4	Input description	8
4.1	General rules	8
4.2	Section &CP2K	8
4.2.1	Required keywords	8
4.2.2	Optional keywords	9
4.3	Section &IO	9
4.4	Section &CELL	9
4.4.1	Required keywords	9
4.4.2	Optional keywords	10
4.5	Section &COORD	10
4.6	Section &KIND	10
4.6.1	Required keywords	10
4.6.2	Optional keywords	11
4.7	Section &DFT	11
4.8	Section &QS	12
4.9	Section &SCF	13
4.10	Section &PRINT	15
5	Input examples	19
5.1	Argon atom	19
5.2	Water molecule	20
6	Methods	21
6.1	GPW method	21
	References	23
	Index	24

1 Introduction

The CP2K project was started in 2000 at the Max-Planck institute for solid state research in Stuttgart. Now it is continued at the ETH Zurich (CSCS) and at the University of Zurich.

The current members of the CP2K developers group are

- Thomas Chassaing (University of Zurich)
- Harald Forbert (University of Bochum)
- Jürg Hutter (University of Zurich)
- Matthias Krack (ETH Zurich/CSCS)
- William Kuo (LLNL)
- Fawzi Mohamed (ETH Zurich/CSCS)
- Christopher J. Mundy (LLNL)
- Ari P. Seitsonen (University of Zurich)
- Gloria Tabacchi (Università degli studi dell'Insubria, Como)
- Joost VandeVondele (University of Zurich)

2 Installation

You can download the current version of the CP2K code from

http://developer.berlios.de/project/?group_id=129

using CVS or FTP which also allow to update your current CP2K version. Alternatively, you can directly download the full [CP2K tarball](#) which you have to uncompress with

```
$ gunzip cp2k.tar.gz
```

Then extract the archive file with

```
$ tar -xvf cp2k.tar
```

In order to generate an executable change to the directory with the makefile

```
$ cd cp2k/makefiles
```

and run GNU make which is on LINUX systems simply make

```
$ make
```

The default make will create a serial optimized (sopt) executable which is equivalent to
`make sopt`

Other choices are

```
$ make sdbg (serial executable for debugging)
```

```
$ make pdbg (parallel executable for debugging)
```

```
$ make popt (optimized parallel executable)
```

You can remove all the stuff generated by make with

```
$ make distclean
```

If you want to remove only one version completely use e.g.

```
$ make sopt/realclean
```

or

```
$ make sopt/clean
```

to get rid of the object files only. After a successful compilation you may find the corresponding executable in the directory

```
cp2k/exe/⟨architecture name⟩
```

There are some test inputs in the directory

```
cp2k/tests
```

and the next section describes how to run the example inputs.

3 Running CP2K

The CP2K program is started with the command

```
$ cp2k.sopt <input file> ><output file>
```

The start command for the parallel CP2K version depends on the parallel execution environment of the underlying architecture, e.g. with LINUX/MPICH you may start 4 processes with

```
$ mpirun -np 4 cp2k.popt <input file> ><output file>
```

whereas on IBMs (AIX) you have to type something like

```
$ poe cp2k.popt <input file> -procs 4 ><output file>
```

3.1 Input files

The methods implemented in CP2K may require different additional input files.

3.1.1 Fist

3.1.2 Quickstep

- Potential file (default name: POTENTIAL)
- Basis set file (default name: BASIS_SET)

The Gaussian basis set format and all the atomic potential formats are explained in the corresponding default database files.

4 Input description

4.1 General rules

- **Warning:** Do not expect the input to be logic. The programmers logic may be different from yours.
- **Warning:** This input description may not refer to the actual version of the program you are using. Therefore the ultimate and authoritative input guide is the source code.
- The input is free format and is not case sensitive except where especially stated.
- Empty lines and white spaces at the beginning of a line are ignored.
- All characters in a line following the comment character are ignored. The default comment character is #.
- The CP2K input file is divided into input sections which are started and terminated with the section keywords listed below.
- Each section keyword starts with the section character. The default section character is &.
- The order of the keywords inside an input section is arbitrary except where especially stated.
- For some keywords there are one or even more alias names which are given below as a comma-separated list.
- Lists enclosed in { } imply that you have to choose **exactly one** of the items.
- Lists enclosed in [] imply that you can choose **any number** of items (optional keywords).
- There are several possibilities to define a floating point number $\langle \text{real} \rangle$, e.g. 0.05, 5.0E-2, 5.e-2, 1/20, or 50/1000. Also the specification of an integer number $\langle \text{integer} \rangle$ is allowed where a floating point number $\langle \text{real} \rangle$ is requested, but not vice versa.
- Strings $\langle \text{string} \rangle$ with special characters like blanks have to be delimited by " ".

4.2 Section &CP2K

The global CP2K section.

4.2.1 Required keywords

PROGRAM {FIST, QUICKSTEP}

Defines the methods which is used for the calculation.

4.2.2 Optional keywords

FFTLIB {FFTESSL, FFTSG, FFTSGI, FFTW}

Defines the library which is used for the Fast Fourier Transformations (FFT). The availability of the libraries depends on the architecture and/or installation, but at least the FFTSG library is available which is included in the CP2K distribution.

default: FFTSG

IOLEVEL {<integer>}

Global print level. See also input section &PRINT.

default: 0

PP_LIBRARY_PATH {<path name>}

Path to the directory with the pseudo potential database files.

Default: <the current working directory>

PROJECT {<string>}

Name of the actual project.

default: project

4.3 Section &IO

In this section the names of input and/or output files can be modified.

BASIS_SET_FILE {<file name>}

Name of the Gaussian basis set database file.

default: BASIS_SET

POTENTIAL_FILE {<file name>}

Name of the potential database file.

default: POTENTIAL

RESTART_FILE {<file name>}

Name of the restart file.

default: RESTART

4.4 Section &CELL

This section is always needed to define the simulation cell.

4.4.1 Required keywords

ABC {<real> <real> <real>}

Lengths of the vectors **a**, **b**, and **c** which define the orthorhombic simulation cell. The unit of length is defined by the keyword UNIT.

4.4.2 Optional keywords

UNIT {ANGSTROM, BOHR, SCALED_ANGSTROM, SCALED_BOHR}

Defines the unit of length for the simulation cell and it also applies to the definition of the atomic coordinates in the input section &COORD. Moreover, all lengths and distances in the output are printed using this unit.

default: BOHR

4.5 Section &COORD

Each non-empty input line in this section defines an atom of the considered system. The first entry in each line has to correspond to an atomic kind name defined by a &KIND section which can be a $\langle \text{string} \rangle$ or an $\langle \text{integer} \rangle$ number. The kind name has to follow a set of three $\langle \text{real} \rangle$ numbers defining the x , y , and z coordinates of the atom.

4.6 Section &KIND

This section has to be defined for each atomic kind in a QUICKSTEP run. The name of the kind has to be defined right after the &KIND section keyword on the same input line. The kind name is referenced by the &COORD section. Alternatively, the atomic number of the kind can be defined as an integer number, e.g.

```
&KIND 6
```

for carbon which is equivalent to

```
&KIND C
```

In general, any $\langle \text{string} \rangle$ can be defined for an atomic kind

```
&KIND  $\langle \text{string} \rangle$ 
```

which allows to define different atomic kinds for the same element e.g. carbon with different orbital basis sets

```
&KIND C-DZVP
```

```
&KIND C-TZVP
```

One or more &KIND sections are required for a QUICKSTEP run.

4.6.1 Required keywords

ORBITAL_BASIS_SET, BASIS_SET, BAS { $\langle \text{string} \rangle$ }

Name of the Gaussian orbital basis set which has to be read from the Gaussian basis set database file (see [section &IO](#)).

POTENTIAL, POT { $\langle \text{string} \rangle$ }

Name of the atomic potential which has to be read from the potential database file (see [section &IO](#)).

4.6.2 Optional keywords

ELEMENT_SYMBOL, ELEMENT {<string>}

Defines the element to which the atomic kind belongs.

ATOMIC_MASS, MASS {<real>}

Defines an atomic mass different from the default atomic mass, e.g. for the definition of isotopes.

PAO_MIN_BAS {list of <integer>}

Definition of the projected atomic orbital (PAO) basis. Indices of the PAOs with respect to the full basis set.

4.7 Section &DFT

In this section the configuration of a density functional calculation (DFT) can be modified.

CHARGE {<integer>}

The total charge of the system.

default: 0

CORRELATION-FUNCTIONAL, C-FUNCTIONAL {LYP, P86, NONE}

Name of the requested correlation functional.

default: PADE

EXCHANGE-CORRELATION-FUNCTIONAL, XC-FUNCTIONAL, FUNCTIONAL
{BLYP, BP86, LDA, PADE, PBE, NONE}

Name of the requested exchange-correlation functional for a density functional calculation.

default: PADE

EXCHANGE-FUNCTIONAL, X-FUNCTIONAL {B88, SLATER, NONE}

Name of the requested exchange functional.

default: NONE

DENSITY-CUTOFF {<real>}

Cutoff for the calculation of the density.

default: 1.0E-10

GRADIENT-CUTOFF {<real>}

Cutoff for the calculation of the gradients.

default: 1.0E-8

GRID {CUTOFF, MESH, PLANE_WAVES}

Definition of the integration grid.

CUTOFF {<real>}

Definition of the plane waves cutoff.

MESH {⟨integer⟩ ⟨integer⟩ ⟨integer⟩}

Explicit definition of the grid size.

PLANE_WAVES, PW

default

KINETIC-ENERGY-FUNCTIONAL, KE-FUNCTIONAL {NONE}

Name of the requested kinetic energy functional.

default: NONE

LSD

A spin-polarized (unrestricted Kohn-Sham) calculation is requested.

MULTIPLICITY, MULTIP {⟨integer⟩}

The multiplicity, i. e. the number of unpaired electrons in the system plus one.

default: 1 for an even and 2 for an odd number of electrons

4.8 Section &QS

Program parameters QUICKSTEP

CUTOFF {⟨real⟩}

Plane waves cutoff of the largest grid in Rydberg.

default: 320

EPS_DEFAULT {⟨real⟩}

Defines a default threshold value. All threshold values of QUICKSTEP are set to this value.

EPS_CORE_CHARGE {⟨real⟩}

Threshold value for the interaction range of the atomic core charge distributions.

default: 1.0E-12

EPS_GVG_RSPACE, EPS_GVG {⟨real⟩}

Threshold value for the integration of the Hartree potential on the real space grid.

default: 1.0E-6

EPS_PGF_ORB {⟨real⟩}

Threshold value for interaction range of the primitive Gaussian-type orbital functions.

default: 1.0E-6

EPS_PPL {⟨real⟩}

Threshold value for the interaction range of the local part of the GTH pseudo potential.

default: 1.0E-12

EPS_PPNL {⟨real⟩}

Threshold value for the interaction range of the non-local part of the GTH pseudo potential.

default: 1.0E-12

EPS_RHO {<real>}

Threshold values for EPS_RHO_GSPACE and EPS_RHO_RSPACE.

default: 1.0E-8

EPS_RHO_GSPACE {<real>}

Threshold value for the calculation of the electronic charge density in Fourier space.

default: 1.0E-8

EPS_RHO_RSPACE {<real>}

Threshold value for the calculation of the electronic charge density in real space.

default: 1.0E-8

PROGRESSION_FACTOR, PROFAC {<real>}

Progression factor for the generation of the multi-grid levels.

default: 2.0

RELATIVE_CUTOFF, REL_CUTOFF {<real>}

Relative plane waves cutoff for each multi-grid level. Values less than 20.0 give inaccurate results and values greater than 30.0 are used for reference calculations (save).

default: 25.0

METHOD {GPW}

Method used by QUICKSTEP. GAPW is not available yet.

default: GPW

MULTI_GRID {list of <integer>}

The plane waves cutoffs for each multi grid level in Rydberg. The number of grid levels is defined by the keyword NGRID_LEVEL.

NGRID_LEVEL, NGRID {<integer>}

Number of the multi-grid levels.

default: 4

PAO

Use the projected atomic orbital (PAO) method.

default: no PAO

4.9 Section &SCF

This section defines the parameters for the configuration of the self consistent field (SCF) procedure which is used for the wavefunction optimization.

ARPACK_ON

The ARPACK eigensolver is used in a parallel run which requires a proper installation of the ARPACK library.

default: no ARPACK usage

CHOLESKY_ON, CHOLESKY_OFF

Decides whether the Cholesky decomposition is used in the eigensolver or not.

default: CHOLESKY_ON

DENSITY_GUESS, SCF_GUESS, GUESS {ATOMIC, CORE}

Defines the type of guess which is employed to generate the first density matrix.

default: ATOMIC

DENSITY_MIXING, MIXING {<real>}

Factor for the mixing of the old and new density matrix during the wavefunction optimization.

default: 0.4 (i.e. 40% of the new and 60% of the old density are used)

EPS_DIIS {<real>}

The DIIS procedure is switched on, if the maximum DIIS error vector element is below this threshold value.

default: 0.1

EPS_EIGVAL {<real>}

Threshold value for eigenvector quenching when $S^{-1/2}$ is used as the orthogonalization matrix in the eigensolver.

default: 1.0E-5

EPS_JACOBI {<real>}

Pseudo diagonalization (Jacobi rotations) [1] is used, if the maximum difference between the corresponding density matrix elements of two consecutive SCF iteration steps is smaller than the specified threshold value.

default: 0.0

EPS_SCF {<real>}

SCF convergence criterion, i. e. the maximum difference between the corresponding density matrix elements of two consecutive SCF iteration steps.

default: 1.0E-5

JACOBI_THRESHOLD {<real>}

Threshold value for a Kohn-Sham matrix element in the MO basis to perform a Jacobi rotations, if pseudo diagonalization is used.

default: 1.0E-7

LEVEL_SHIFT {<real>}

Shift value for the unoccupied (virtual) molecular orbitals (MOs) in atomic units.

default: 0.0

MAX_DIIS {<integer>}

Maximum size of the SCF DIIS buffer.

default: 0

MAX_SCF {<integer>}

Maximum number of SCF iteration steps.

default: 30

NREBUILD {<integer>}

Number of SCF steps between two full calculations of the electronic charge density.

default: 1

OT

An orbital transformation approach instead of a diagonalization is used for the wave-function optimization during the SCF iteration procedure.

SMEAR {<real>}

Window size in atomic units with respect to the eigenvalue of the highest occupied molecular orbital (HOMO) for the smearing of the occupation numbers.

default: 0.0

WORK_SYEVX {<real>}

Defines the amount of additional work space for the PDSYEVX routine from the SCALAPACK library. A value between 0.0 and 1.0 is accepted. (only for parallel runs using SCALAPACK and an eigensolver with diagonalization.)

default: 0.0

4.10 Section &PRINT

This section allows for detailed output control when running QUICKSTEP. There are 5 predefined print levels: 0, 1, 2, 3, and 4 which correspond to the keywords NO, LOW, MEDIUM, HIGH, and DEBUG or FULL. The print level has to be defined right after the &PRINT section keyword on the same input line, e.g.

```
&PRINT LOW
```

which is equivalent to

```
&PRINT 1
```

The following keywords may be used based on the selected print level to request an additional output or to suppress an output selectively by using the prefix NO_ for the keyword, e.g. at print level LOW the atomic coordinates are listed in the output which may be inconvenient for large systems, thus simply request NO_COORDINATES in the &PRINT section. The default print level is LOW.

ANGLES

Print the angles between all atom triples in the simulation cell.

Warning: That is much output for large systems.

ATOMIC_COORDINATES, COORDINATES, COORD

Print all atomic coordinates together with the some atomic kind information.

BASIC_DATA_TYPES

Print informations about the basic data types like REAL, INTEGER, or LOGICAL.

BASIS_SETS, BASIS_SET, BASIS

Print the Gaussian basis set information, i. e. all Gaussian function exponents and the corresponding contraction coefficients as read from the Gaussian basis set database file. Furthermore, the normalized contraction coefficients are printed.

BLACS_INFO

Print the process grid information of BLACS (Basic linear algebra subprograms)

CARTESIAN_MATRICES

Print all operator matrices in the Cartesian instead of the spherical representation.

CELL_PARAMETERS, CELL

Print the simulation cell data like the cell vectors, cell volume etc.

CORE_HAMILTONIAN_MATRIX, H_MATRIX

Print the core Hamiltonian matrix.

CORE_CHARGE_RADII, CORE_RADII

Print the radius of the core charge distribution for each atomic kind.

DENSITY_MATRIX, P_MATRIX

Print the density matrix.

DERIVATIVES

Print the first derivatives of the operator matrices.

DFT_CONTROL_PARAMETERS

Print the DFT control parameters as defined in the &DFT section.

DIIS_INFORMATION

Print information about the SCF DIIS procedure.

DISTRIBUTION

Print the distribution and the sparsity of the overlap matrix (only parallel version).

EACH_SCF_STEP

Print the requested energies, densities, or matrices for each SCF iteration step.

E_DENSITY_CUBE

Print the electronic charge density as a cube file.

FORCES

Print the atomic force contributions for all atoms.

HOMO

Print the highest occupied molecular orbital (HOMO) as a cube file.

INTERATOMIC_DISTANCES , DISTANCES

Print a matrix with the interatomic distances.

Warning: That is much output for large systems.

KIND_RADII

Print the maximum interaction radius of each atomic kind.

KINETIC_ENERGY_MATRIX , T_MATRIX

Print the kinetic energy integral matrix.

KOHN_SHAM_MATRIX

Print the Kohn-Sham matrix.

LUMO

Print the lowest unoccupied molecular orbital (LUMO) as a cube file.

MEMORY

Print informations about the memory usage of the CP2K program.

MO_EIGENVALUES

Print the eigenvalues of the molecular orbitals (MOs).

MO_EIGENVECTORS , MOS

Print the eigenvectors, eigenvalues, and the occupation numbers of the molecular orbitals (MOs).

MO_OCCUPATION_NUMBERS

Print the occupation numbers and the eigenvalues of the molecular orbitals (MOs).

NEIGHBOR_LISTS

Print all neighbor lists.

Warning: That is much output for large systems.

ORTHO_MATRIX

Print the orthogonalisation matrix used to transform the Kohn-Sham matrix.

OVERLAP_MATRIX

Print the overlap matrix.

PGF_RADII

Print the interaction radii of all primitive Gaussian-type functions.

PHYSICAL_CONSTANTS , PHYSCON

Print the values of all physical constants used in the program.

POTENTIALS

Print a detailed atomic potential information for each atomic kind.

PPL_RADII

Print the interaction radii of the local part of the Goedecker-Teter-Hutter (GTH) pseudo potential [2, 3].

PPNL_RADII

Print the interaction radii of the non-local projector functions of the Goedecker-Teter-Hutter (GTH) pseudo potential [2, 3].

PROGRAM_BANNER

Print a program banner.

PROGRAM_RUN_INFORMATION

Print informations about the current program run.

PW_GRID_INFORMATION

Print detailed informations about the used plane waves grid.

RADII

Print all interaction radii for each atomic kinds.

SCF

Print the SCF iteration.

SCF_ENERGIES

Print all contributions to the total SCF energy.

SET_RADII

Print the interaction radii of all Gaussian orbital sets.

SPHERICAL_HARMONICS

Print the transformation matrices between Cartesian and spherical function.

TIMING_INFORMATION

Print timing information depending on the IOLEVEL defined in the &CP2K section.

TITLE

Print the title.

TOTAL_DENSITIES

Print

TOTAL_NUMBERS

Print the total number of atoms, shell sets, basis functions, projectors etc.

V_HARTREE_CUBE

Print the Hartree potential as a cube file.

W_MATRIX

Print the energy weighted density matrix used for the force calculation.

5 Input examples

5.1 Argon atom

```
&CP2K
  PROGRAM      Quickstep
  IOLEVEL      10
  FFTLIB       FFTSG
  RUN_TYPE     WFN_OPT
&END

&DFT
  FUNCTIONAL    PADE
&END

&QS
  CUTOFF       300
  REL_CUTOFF    30
&END

&SCF
  GUESS        ATOMIC
  EPS_DIIS     0.1
  MAX_DIIS     4
  EPS_SCF      1.0E-6
  MAX_SCF      30
  MIXING       0.4
&END

&PRINT medium
  NO_BLACS_INFO
&END

&KIND Ar
  BASIS_SET     DZVP-GTH-PADE
  POTENTIAL     GTH
&END

&CELL
  UNIT          ANGSTROM
  ABC           12.0  12.0  12.0
&END

&COORD
  18            0.000000  0.000000  0.000000
&END
```

5.2 Water molecule

```
&CP2K
  PROGRAM      Quickstep
  IOLEVEL      10
  FFTLIB       FFTSG
  RUN_TYPE     GEO_OPT
&END

&DFT
  FUNCTIONAL    Pade
&END

&QS
  CUTOFF        200
&END

&SCF
  GUESS         ATOMIC
  MIXING        0.4
  EPS_SCF       1.0E-5
&END

&PRINT medium
&END

&KIND H
  BASIS_SET     DZV-GTH-PADE
  POTENTIAL     GTH
&END

&KIND O
  BASIS_SET     DZVP-GTH-PADE
  POTENTIAL     GTH
&END

&CELL
  UNIT          ANGSTROM
  ABC           10.0  10.0  10.0
&END

&COORD
  H   0.000000   -0.757136    0.520545
  O   0.000000    0.000000   -0.065587
  H   0.000000    0.757136    0.520545
&END
```

6 Methods

6.1 GPW method

The electronic energy functional for a molecular or crystalline system in the framework of the Gaussian plane waves (GPW) method [4] using the Kohn-Sham formulation of density functional theory (DFT) [5, 6] is defined as

$$\begin{aligned}
 E^{\text{el}}[n] &= E^{\text{T}}[n] + E^{\text{V}}[n] + E^{\text{H}}[n] + E^{\text{XC}}[n] \\
 &= \sum_{\mu\nu} P_{\mu\nu} \langle \phi_{\mu}(\mathbf{r}) | -\frac{1}{2} \nabla^2 | \phi_{\nu}(\mathbf{r}) \rangle + \\
 &\quad \sum_{\mu\nu} P_{\mu\nu} \langle \phi_{\mu}(\mathbf{r}) | V_{\text{loc}}^{\text{PP}}(r) | \phi_{\nu}(\mathbf{r}) \rangle + \\
 &\quad \sum_{\mu\nu} P_{\mu\nu} \langle \phi_{\mu}(\mathbf{r}) | V_{\text{nl}}^{\text{PP}}(\mathbf{r}, \mathbf{r}') | \phi_{\nu}(\mathbf{r}') \rangle + \\
 &\quad 4\pi\Omega \sum_{|\mathbf{G}| < G_{\text{C}}} \frac{\tilde{n}^*(\mathbf{G}) \tilde{n}(\mathbf{G})}{\mathbf{G}^2} + \\
 &\quad \int \tilde{n}(\mathbf{r}) \varepsilon_{\text{XC}}[\tilde{n}] d\mathbf{r}
 \end{aligned} \tag{1}$$

where $E^{\text{T}}[n]$ is the kinetic energy, $E^{\text{V}}[n]$ is the electronic interaction with the ionic cores, $E^{\text{H}}[n]$ is the electronic Hartree (Coulomb) energy and $E^{\text{XC}}[n]$ is the exchange-correlation energy.

The electronic density

$$n(\mathbf{r}) = \sum_{\mu\nu} P_{\mu\nu} \phi_{\mu}(\mathbf{r}) \phi_{\nu}(\mathbf{r}) \tag{2}$$

is expanded in a set of contracted Gaussian functions

$$\phi_{\mu}(\mathbf{r}) = \sum_i d_{i\mu} g_i(\mathbf{r}) \tag{3}$$

$P_{\mu\nu}$ is a density matrix element, $g_i(\mathbf{r})$ is a primitive Gaussian function and $d_{i\mu}$ is the corresponding contraction coefficient.

An auxiliary basis set of plane waves is used as an intermediate basis set to describe the electronic charge density

$$\tilde{n}(\mathbf{r}) = \frac{1}{\Omega} \sum_{|\mathbf{G}| < G_{\text{C}}} n(\mathbf{G}) e^{i\mathbf{G}\mathbf{r}} \tag{4}$$

which is used for the calculation of the density dependent contributions $E^{\text{H}}[n]$ and $E^{\text{XC}}[n]$. Ω is the volume of the periodic simulation cell. The plane wave expansion is truncated by the specification of a cut-off value for the kinetic energy

$$E_{\text{C}} = \frac{1}{2} G_{\text{C}}^2 \tag{5}$$

of the plane waves. Since the $G = 0$ term of the Hartree energy is treated with the Ewald method, the nuclear charges are represented by a Gaussian charge distribution and not by point charges.

The GPW method works like pure plane waves methods with atomic pseudo potentials (PP), since an expansion of Gaussian functions with large exponents is numerically not efficient or even not feasible.

The current implementation of the GPW method uses only the pseudo potentials of Gödecker, Teter, and Hutter (GTH) [2] which are available for the whole periodic table [3]. The separable dual-space GTH pseudo potentials consist of a local part

$$V_{\text{local}}^{\text{PP}}(r) = -\frac{Z_{\text{ion}}}{r} \text{erf}(\alpha^{\text{PP}} r) + \sum_{i=1}^4 C_i^{\text{PP}} \left(\sqrt{2} \alpha^{\text{PP}} r \right)^{2i-2} \exp \left[-(\alpha^{\text{PP}} r)^2 \right] \quad (6)$$

$$\text{with } \alpha^{\text{PP}} = \frac{1}{\sqrt{2} r_{\text{local}}^{\text{PP}}}$$

and a non-local part

$$V_{\text{nl}}^{\text{PP}}(\mathbf{r}, \mathbf{r}') = \sum_{lm} \sum_{ij} \langle \mathbf{r} | p_i^{lm} \rangle h_{ij}^l \langle p_j^{lm} | \mathbf{r}' \rangle \quad (7)$$

with the Gaussian-type projectors

$$\langle \mathbf{r} | p_i^{lm} \rangle = N_i^l Y^{lm}(\hat{r}) r^{l+2i-2} \exp \left[-\frac{1}{2} \left(\frac{r}{r_l} \right)^2 \right]$$

as shown in Eq. 1 resulting in a fully analytical formulation which requires only the definition of a small parameter set for each element. Moreover, the GTH pseudo potentials are transferable and norm-conserving. Nevertheless, plane waves methods employ this pseudo potential type only for reference calculations or if no other reliable pseudo potentials are available, since this type requires relative high cut-off values, i. e. more plane waves. However, in the framework of the GPW method there are no such limitations, since all contributions are integrals over Gaussian functions which can be calculated analytically.

References

- [1] J. J. P. Stewart, P. Császár, and P. Pulay, *J. Comput. Chem.* **3**, 227 (1982).
- [2] S. Gödecker, M. Teter, and J. Hutter, *Phys. Rev. B* **54**, 1703 (1996).
- [3] C. Hartwigsen, S. Gödecker, and J. Hutter, *Phys. Rev. B* **58**, 3641 (1998).
- [4] G. Lippert, J. Hutter, and M. Parrinello, *Mol. Phys.* **92**, 477 (1997).
- [5] P. Hohenberg and W. Kohn, *Phys. Rev. B* **136**, 864 (1964).
- [6] W. Kohn and L. J. Sham, *Phys. Rev. A* **140**, 1133 (1965).

Index

ARPACK, [13](#)

files

 basis set, [7](#)

 potential, [7](#)

General Public License, [2](#)

GNU, [2](#)

GPL, [2](#)

input

 examples, [19](#)

 general rules, [8](#)

 special characters, [8](#)

input sections, optional

 &DFT, [11](#)

 &IO, [9](#)

 &PRINT, [15](#)

 &QS, [12](#)

 &SCF, [13](#)

input sections, required

 &CELL, [9](#)

 &COORD, [10](#)

 &CP2K, [8](#)

 &KIND, [10](#)

keyword arguments

 ANGSTROM, [10](#)

 ATOMIC, [14](#)

 BLYP, [11](#)

 BOHR, [10](#)

 BP86, [11](#)

 CORE, [14](#)

 FFTESSL, [9](#)

 FFTSGI, [9](#)

 FFTSG, [9](#)

 FFTW, [9](#)

 FIST, [8](#)

 GAPW, [13](#)

 GPW, [13](#)

 LDA, [11](#)

 PADE, [11](#)

 PBE, [11](#)

 QUICKSTEP, [8](#)

 SCALED_ANGSTROM, [10](#)

 SCALED_BOHR, [10](#)

keywords, optional

 V_HARTREE_CUBE, [18](#)

 ANGLES, [15](#)

 ARPACK_ON, [13](#)

 ATOMIC_COORDINATES, [15](#)

 ATOMIC_MASS, [11](#)

 BASIS_SETS, [16](#)

 BASIS_SET_FILE, [9](#)

 BASIS, [16](#)

 BLACS_INFO, [16](#)

 CARTESIAN_MATRICES, [16](#)

 CELL_PARAMETERS, [16](#)

 CELL, [16](#)

 CHARGE, [11](#)

 CHOLSKY_OFF, [14](#)

 CHOLSKY_ON, [14](#)

 COORDINATES, [15](#)

 COORD, [15](#)

 CORE_CHARGE_RADII, [16](#)

 CORE_RADII, [16](#)

 CUTOFF, [12](#)

 DENSITY_GUESS, [14](#)

 DENSITY_MATRIX, [16](#)

 DENSITY_MIXING, [14](#)

 DERIVATIVES, [16](#)

 DFT_CONTROL_PARAMETERS, [16](#)

 DIIS_INFORMATION, [16](#)

 DISTANCES, [17](#)

 DISTRIBUTION, [16](#)

 EACH_SCF_STEP, [16](#)

 ELEMENT_SYMBOL, [11](#)

 EPS_CORE_CHARGE, [12](#)

 EPS_DEFAULT, [12](#)

 EPS_DIIS, [14](#)

 EPS_EIGVAL, [14](#)

 EPS_GVG_RSPACE, [12](#)

 EPS_GVG, [12](#)

 EPS_JACOBI, [14](#)

 EPS_PGF_ORB, [12](#)

- EPS_PPL, 12
- EPS_PPNL, 12
- EPS_RHO_GSPACE, 13
- EPS_RHO_RSPACE, 13
- EPS_RHO, 13
- EPS_SCF, 14
- EXCHANGE-CORRELATION-
 - FUNCTIONAL, 11
- E_DENSITY_CUBE, 16
- FFTLIB, 9
- FORCES, 16
- FUNCTIONAL, 11
- GUESS, 14
- HOMO, 16
- H_MATRIX], 16
- INTERATOMIC_DISTANCES, 17
- IOLEVEL, 9
- JACOBI_THRESHOLD, 14
- KINETIC_ENERGY_MATRIX, 17
- KOHN_SHAM_MATRIX, 17
- LEVEL_SHIFT, 14
- LSD, 12
- LUMO, 17
- MAX_DIIS, 14
- MAX_SCF, 15
- MEMORY, 17
- METHOD, 13
- MIXING, 14
- MOS, 17
- MO_EIGENVALUES, 17
- MO_EIGENVECTORS, 17
- MO_OCCUPATION_NUMBERS, 17
- MULTIPLICITY, 12
- MULTIP, 12
- MULTI_GRID, 13
- NEIGHBOR_LISTS, 17
- NGRID_LEVEL, 13
- NGRID, 13
- NREBUILD, 15
- ORTHO_MATRIX, 17
- OT, 15
- OVERLAP_MATRIX, 17
- PAO_MIN_BAS, 11
- PAO, 13
- POTENTIALS, 17
- POTENTIAL_FILE, 9
- PPL_RADII, 17
- PPNL_RADII, 18
- PP_LIBRARY_PATH, 9
- PROFAC, 13
- PROGRAM_BANNER, 18
- PROGRAM_RUN_INFO, 18
- PROGRESSION_FACTOR, 13
- PROJECT, 9
- PW_GRID_INFORMATION, 18
- P_MATRIX, 16
- RADII, 18
- RELATIVE_CUTOFF, 13
- REL_CUTOFF, 13
- RESTART_FILE, 9
- SCF_ENERGIES, 18
- SCF_GUESS, 14
- SCF, 18
- SET_RADII, 18
- SMEAR, 15
- SPHERICAL_HARMONICS, 18
- TIMING_INFORMATION, 18
- TITLE, 18
- TOTAL_DENSITIES, 18
- TOTAL_NUMBERS, 18
- T_MATRIX, 17
- UNIT, 10
- WORK_SYEVX, 15
- W_MATRIX, 18
- XC-FUNCTIONAL, 11
- KIND_RADII, 17
- keywords, required
 - ABC, 9
 - BASIS_SET, 10
 - BAS, 10
 - ORBITAL_BASIS_SET, 10
 - POTENTIAL, 10
 - PROGRAM, 8
- PDSYEVX, 15
- SCALAPACK, 15