

NAME

systemd-boot, sd-boot – A simple UEFI boot manager

DESCRIPTION

systemd-boot (short: **sd-boot**) is a simple UEFI boot manager. It provides a graphical menu to select the entry to boot and an editor for the kernel command line. **systemd-boot** supports systems with UEFI firmware only.

systemd-boot loads boot entry information from the EFI system partition (ESP), usually mounted at /efi/, /boot/, or /boot/efi/ during OS runtime, as well as from the Extended Boot Loader partition if it exists (usually mounted to /boot/). Configuration file fragments, kernels, initrds and other EFI images to boot generally need to reside on the ESP or the Extended Boot Loader partition. Linux kernels must be built with **CONFIG_EFI_STUB** to be able to be directly executed as an EFI image. During boot systemd-boot automatically assembles a list of boot entries from the following sources:

- Boot entries defined with [Boot Loader Specification](#)^[1] description files located in /loader/entries/ on the ESP and the Extended Boot Loader Partition. These usually describe Linux kernel images with associated initrd images, but alternatively may also describe arbitrary other EFI executables.
- Unified kernel images following the [Boot Loader Specification](#)^[1], as executable EFI binaries in /EFI/Linux/ on the ESP and the Extended Boot Loader Partition.
- The Microsoft Windows EFI boot manager, if installed
- The Apple MacOS X boot manager, if installed
- The EFI Shell binary, if installed
- A reboot into the UEFI firmware setup option, if supported by the firmware

kernel-install(8) may be used to copy kernel images onto the ESP or the Extended Boot Loader Partition and to generate description files compliant with the Boot Loader Specification. **bootctl**(1) may be used from a running system to locate the ESP and the Extended Boot Loader Partition, list available entries, and install **systemd-boot** itself.

systemd-boot will provide information about the time spent in UEFI firmware using the [Boot Loader Interface](#)^[2]. This information can be displayed using **systemd-analyze**(1).

KEY BINDINGS

The following keys may be used in the boot menu:

↑ (Up), ↓ (Down), j, k, PageUp, PageDown, Home, End
Navigate up/down in the entry list

↵ (Enter)
Boot selected entry

d
Make selected entry the default

e
Edit the kernel command line for selected entry

+, t
Increase the timeout before default entry is booted

-, T
Decrease the timeout

v
Show systemd-boot, UEFI, and firmware versions

P
Print status

Q

Quit

h, ?

Show a help screen

Ctrl+l

Reprint the screen

The following keys may be used during bootup or in the boot menu to directly boot a specific entry:

l

Linux

w

Windows

a

OS X

s

EFI shell

1, 2, 3, 4, 5, 6, 7, 8, 9

Boot entry number 1 ... 9

In the editor, most keys simply insert themselves, but the following keys may be used to perform additional actions:

← (Left), → (Right), Home, End

Navigate left/right

Esc

Abort the edit and quit the editor

Ctrl+k

Clear the command line

Ctrl+w, Alt+Backspace

Delete word backwards

Alt+d

Delete word forwards

↵ (Enter)

Boot entry with the edited command line

Note that unless configured otherwise in the UEFI firmware, systemd-boot will use the US keyboard layout, so key labels might not match for keys like +/-.

FILES

The files **systemd-boot** processes generally reside on the UEFI ESP which is usually mounted to /efi/, /boot/ or /boot/efi/ during OS runtime. It also processes files on the Extended Boot Loader partition which is typically mounted to /boot/, if it exists. **systemd-boot** reads runtime configuration such as the boot timeout and default entry from /loader/loader.conf on the ESP (in combination with data read from EFI variables). See **loader.conf(5)**. Boot entry description files following the **Boot Loader Specification**^[1] are read from /loader/entries/ on the ESP and the Extended Boot Loader partition. Unified kernel boot entries following the **Boot Loader Specification**^[1] are read from /EFI/Linux/ on the ESP and the Extended Boot Loader partition.

EFI VARIABLES

The following EFI variables are defined, set and read by **systemd-boot**, under the vendor UUID "4a67b082-0a4c-41cf-b6c7-440b29bb8c4", for communication between the OS and the boot loader:

LoaderBootCountPath

If boot counting is enabled, contains the path to the file in whose name the boot counters are encoded. Set by the boot loader. **systemd-bleed-boot.service(8)** uses this information to mark a boot as

successful as determined by the successful activation of the `boot-complete.target` target unit.

LoaderConfigTimeout, LoaderConfigTimeoutOneShot

The menu timeout in seconds. Read by the boot loader. *LoaderConfigTimeout* is maintained persistently, while *LoaderConfigTimeoutOneShot* is a one-time override which is read once (in which case it takes precedence over *LoaderConfigTimeout*) and then removed. *LoaderConfigTimeout* may be manipulated with the t/T keys, see above.)

LoaderDevicePartUUID

Contains the partition UUID of the EFI System Partition the boot loader was run from. Set by the boot loader. **systemd-gpt-auto-generator**(8) uses this information to automatically find the disk booted from, in order to discover various other partitions on the same disk automatically.

LoaderEntries

A list of the identifiers of all discovered boot loader entries. Set by the boot loader.

LoaderEntryDefault, LoaderEntryOneShot

The identifier of the default boot loader entry. Set primarily by the OS and read by the boot loader. *LoaderEntryOneShot* sets the default entry for the next boot only, while *LoaderEntryDefault* sets it persistently for all future boots. **bootctl**(1)'s **set-default** and **set-oneshot** commands make use of these variables. The boot loader modifies *LoaderEntryDefault* on request, when the d key is used, see above.)

LoaderEntrySelected

The identifier of the boot loader entry currently being booted. Set by the boot loader.

LoaderFeatures

A set of flags indicating the features the boot loader supports. Set by the boot loader. Use **bootctl**(1) to view this data.

LoaderFirmwareInfo, LoaderFirmwareType

Brief firmware information. Set by the boot loader. Use **bootctl**(1) to view this data.

LoaderImageIdentifier

The path of executable of the boot loader used for the current boot, relative to the EFI System Partition's root directory. Set by the boot loader. Use **bootctl**(1) to view this data.

LoaderInfo

Brief information about the boot loader. Set by the boot loader. Use **bootctl**(1) to view this data.

LoaderTimeExecUsec, LoaderTimeInitUsec, LoaderTimeMenuUsec

Information about the time spent in various parts of the boot loader. Set by the boot loader. Use **systemd-analyze**(1) to view this data. These variables are defined by the [Boot Loader Interface](#)^[2].

BOOT COUNTING

systemd-boot implements a simple boot counting mechanism on top of the [Boot Loader Specification](#)^[1], for automatic and unattended fallback to older kernel versions/boot loader entries when a specific entry continuously fails. Any boot loader entry file and unified kernel image file that contains a "+" followed by one or two numbers (if two they need to be separated by a "-"), before the .conf or .efi suffix is subject to boot counting: the first of the two numbers ('tries left') is decreased by one on every boot attempt, the second of the two numbers ('tries done') is increased by one (if 'tries done' is absent it is considered equivalent to 0). Depending on the current value of these two counters the boot entry is considered to be in one of three states:

1. If the 'tries left' counter of an entry is greater than zero the entry is considered to be in 'indeterminate' state. This means the entry has not completed booting successfully yet, but also hasn't been determined not to work.
2. If the 'tries left' counter of an entry is zero it is considered to be in 'bad' state. This means no further attempts to boot this item will be made (that is, unless all other boot entries are also in 'bad' state), as all attempts to boot this entry have not completed successfully.

3. If the 'tries left' and 'tries done' counters of an entry are absent it is considered to be in 'good' state. This means further boot counting for the entry is turned off, as it successfully booted at least once. The **systemd-bless-boot.service**(8) service moves the currently booted entry from 'indeterminate' into 'good' state when a boot attempt completed successfully.

Generally, when new entries are added to the boot loader, they first start out in 'indeterminate' state, i.e. with a 'tries left' counter greater than zero. The boot entry remains in this state until either it managed to complete a full boot successfully at least once (in which case it will be in 'good' state) — or the 'tries left' counter reaches zero (in which case it will be in 'bad' state).

Example: let's say a boot loader entry file `foo.conf` is set up for 3 boot tries. The installer will hence create it under the name `foo+3.conf`. On first boot, the boot loader will rename it to `foo+2-1.conf`. If that boot does not complete successfully, the boot loader will rename it to `foo+1-2.conf` on the following boot. If that fails too, it will finally be renamed `foo+0-3.conf` by the boot loader on next boot, after which it will be considered 'bad'. If the boot succeeds however the entry file will be renamed to `foo.conf` by the OS, so that it is considered 'good' from then on.

The boot menu takes the 'tries left' counter into account when sorting the menu entries: entries in 'bad' state are ordered at the end of the list, and entries in 'good' or 'indeterminate' at the beginning. The user can freely choose to boot any entry of the menu, including those already marked 'bad'. If the menu entry to boot is automatically determined, this means that 'good' or 'indeterminate' entries are generally preferred (as the top item of the menu is the one booted by default), and 'bad' entries will only be considered if there are no 'good' or 'indeterminate' entries left.

The **kernel-install**(8) kernel install framework optionally sets the initial 'tries left' counter to the value specified in `/etc/kernel/tries` when a boot loader entry is first created.

SEE ALSO

bootctl(1), **loader.conf**(5), **systemd-bless-boot.service**(8), **kernel-install**(8), **Boot Loader Specification**^[1], **Boot Loader Interface**^[2]

NOTES

1. Boot Loader Specification
https://systemd.io/BOOT_LOADER_SPECIFICATION
2. Boot Loader Interface
https://systemd.io/BOOT_LOADER_INTERFACE