

CPU frequency scaling

From ArchWiki

CPU frequency scaling enables the operating system to scale the CPU frequency up or down in order to save power. CPU frequencies can be scaled automatically depending on the system load, in response to ACPI events, or manually by userspace programs.

CPU frequency scaling is implemented in the Linux kernel, the infrastructure is called *cpufreq*. Since kernel 3.4 the necessary modules are loaded automatically and the recommended ondemand governor is enabled by default. However, userspace tools like cpupower, acpid, Laptop Mode Tools, or GUI tools provided for your desktop environment, may still be used for advanced configuration.

Related articles

- Power saving
- Laptop Mode Tools
- pm-utils
- PHC

Contents

- 1 Userspace tools
 - 1.1 thermald
 - 1.2 i7z
 - 1.3 cpupower
- 2 CPU frequency driver
 - 2.1 Setting maximum and minimum frequencies
- 3 Scaling governors
 - 3.1 Tuning the ondemand governor
 - 3.1.1 Switching threshold
 - 3.1.2 Sampling rate
 - 3.1.3 Make changes permanent
- 4 Interaction with ACPI events
- 5 Privilege granting under GNOME
- 6 Troubleshooting
 - 6.1 BIOS frequency limitation
- 7 See also

Userspace tools

thermald

thermald (<https://www.archlinux.org/packages/?name=thermald>) is a Linux daemon used to prevent the overheating of platforms. This daemon monitors temperature and applies compensation using available cooling methods.

By default, it monitors CPU temperature using available CPU digital temperature sensors and maintains CPU temperature under control, before HW takes aggressive correction action. If there is a skin temperature sensor in thermal sysfs, then it tries to keep skin temperature under 45C.

i7z

i7z (<https://www.archlinux.org/packages/?name=i7z>) is an i7 (and now i3, i5) CPU reporting tool for Linux. It can be launched from a Terminal with the command `i7z` or as GUI with `i7z-gui`.

cpupower

cpupower (<https://www.archlinux.org/packages/?name=cpupower>) is a set of userspace utilities designed to assist with CPU frequency scaling. The package is not required to use scaling, but is highly recommended because it provides useful command-line utilities and a systemd service to change the governor at boot.

The configuration file for *cpupower* is located in `/etc/default/cpupower`. This configuration file is read by a bash script in `/usr/lib/systemd/scripts/cpupower` which is activated by *systemd* with `cpupower.service`. You may want to enable `cpupower.service` to start at boot.

CPU frequency driver

- Note:
- The native CPU module is loaded automatically.
 - The `pstate` power scaling driver is used automatically for modern Intel CPUs instead of the other drivers below. This driver takes

priority over other drivers and is built-in as opposed to being a module. This driver is currently automatically used for Sandy Bridge and newer CPUs. If you encounter a problem while using this driver, add `intel_pstate=disable` to your kernel line. You can use the same user space utilities with this driver, but cannot control it.

- Even P State behavior mentioned above can be influenced with `/sys/devices/system/cpu/intel_pstate` , e.g. Intel Turbo Boost can be deactivated with `# echo 1 > /sys/devices/system/cpu/intel_pstate/no_turbo` for keeping CPU-Temperatures low.
- Additional control for modern Intel CPUs is available with the Linux Thermal Daemon (<https://01.org/linux-thermal-daemon>) (available as `thermald` (<https://www.archlinux.org/packages/?name=thermald>)), which proactively controls thermal using P-states, T-states, and the Intel power clamp driver. `thermald` can also be used for older Intel CPUs. If the latest drivers are not available, then the daemon will revert to x86 model specific registers and the Linux ‘cpufreq subsystem’ to control system cooling.

cpupower requires modules to know the limits of the native CPU:

Module	Description
intel_pstate	This driver implements a scaling driver with an internal governor for Intel Core (Sandy Bridge and newer) processors.
acpi-cpufreq	CPUFreq driver which utilizes the ACPI Processor Performance States. This driver also supports the Intel Enhanced SpeedStep (previously supported by the deprecated speedstep-centrino module).
speedstep-lib	CPUFreq driver for Intel SpeedStep-enabled processors (mostly Atoms and older Pentiums (< 3))
powernow-k8	CPUFreq driver for K8/K10 Athlon 64/Opteron/Phenom processors. Since Linux 3.7 'acpi-cpufreq' will automatically be used for more modern CPUs from this family.
pcc-cpufreq	This driver supports Processor Clocking Control interface by Hewlett-Packard and Microsoft Corporation which is useful on some ProLiant servers.
p4-clockmod	CPUFreq driver for Intel Pentium 4/Xeon/Celeron processors which lowers the CPU temperature by skipping clocks. (You probably want to use a SpeedStep driver instead.)

To see a full list of available modules, run:

```
$ ls /usr/lib/modules/$(uname -r)/kernel/drivers/cpufreq/
```

Load the appropriate module (see Kernel modules for details). Once the appropriate cpufreq driver is loaded, detailed information about the CPU(s) can be displayed by running

```
$ cpupower frequency-info
```

Setting maximum and minimum frequencies

In rare cases, it may be necessary to manually set maximum and minimum frequencies.

To set the maximum clock frequency (*clock_freq* is a clock frequency with units: GHz, MHz):

```
# cpupower frequency-set -u clock_freq
```

To set the minimum clock frequency:

```
# cpupower frequency-set -d clock_freq
```

To set the CPU to run at a specified frequency:

```
# cpupower frequency-set -f clock_freq
```

- Note:
- To adjust for only a single CPU core, append `-c core_number` .
 - The governor, maximum and minimum frequencies can be set in `/etc/default/cpupower` .

Scaling governors

Governors (see table below) are power schemes for the CPU. Only one may be active at a time. For details, see the kernel documentation (<https://www.kernel.org/doc/Documentation/cpu-freq/governors.txt>) in the kernel source.

Governor	Description
performance	Run the CPU at the maximum frequency.
powersave	Run the CPU at the minimum frequency.
userspace	Run the CPU at user specified frequencies.
ondemand	Scales the frequency dynamically according to current load. Jumps to the highest frequency and then possibly back off as the idle time increases.
conservative	Scales the frequency dynamically according to current load. Scales the frequency more gradually than ondemand.
schedutil	Scheduler-driven CPU frequency selection [1] (http://lwn.net/Articles/682391/), [2] (https://lkml.org/lkml/2016/3/17/420).

Depending on the scaling driver, one of these governors will be loaded by default:

- `ondemand` for AMD and older Intel CPU.
- `powersave` for Intel CPUs using the `intel_pstate` driver (Sandy Bridge and newer).

Note: The `intel_pstate` driver supports only the performance and powersave governors, but they both provide dynamic scaling. The performance governor should give better power saving functionality than the old ondemand governor (http://www.phoronix.com/scan.php?page=news_item&px=MTM3NDQ).

Warning: Use CPU monitoring tools (for temperatures, voltage, etc.) when changing the default governor.

To activate a particular governor, run:

```
# cpupower frequency-set -g governor
```

Note:

- To adjust for only a single CPU core, append `-c core_number` to the command above.
- Activating a governor requires that specific kernel module (named `cpufreq_governor`) is loaded. As of kernel 3.4, these modules are loaded automatically.

Alternatively, you can activate a governor on every available CPU manually:

```
# echo governor | tee /sys/devices/system/cpu/cpu*/cpufreq/scaling_governor >/dev/null
```

Tip: To monitor cpu speed in real time, run:

```
$ watch grep \"cpu MHz\" /proc/cpuinfo
```

Tuning the ondemand governor

See the kernel documentation (<https://www.kernel.org/doc/Documentation/cpu-freq/governors.txt>) for details.

Switching threshold

To set the threshold for stepping up to another frequency:

```
# echo -n percent > /sys/devices/system/cpu/cpufreq/<governor>/up_threshold
```

To set the threshold for stepping down to another frequency:

```
# echo -n percent > /sys/devices/system/cpu/cpufreq/<governor>/down_threshold
```

Sampling rate

The sampling rate determines how frequently the governor checks to tune the CPU. `sampling_down_factor` is a tunable that multiplies the sampling rate when the CPU is at its highest clock frequency thereby delaying load evaluation and improving performance. Allowed values for `sampling_down_factor` are 1 to 100000. This tunable has no effect on behavior at lower CPU frequencies/loads.

To read the value (default = 1), run:

```
$ cat /sys/devices/system/cpu/cpufreq/ondemand/sampling_down_factor
```

To set the value, run:

```
# echo -n value > /sys/devices/system/cpu/cpufreq/ondemand/sampling_down_factor
```

Make changes permanent

To have the desired scaling enabled at boot, kernel module options and systemd#Temporary files are regular methods. However, in some cases there might be race conditions, as noted in systemd#Temporary files. udev is doing better.

For example, to set the scaling governor of the CPU core 0 to performance while the scaling driver is acpi_cpufreq , create the following udev rule:

```
/etc/udev/rules.d/50-scaling-governor.rules

SUBSYSTEM=="module", ACTION=="add", KERNEL=="acpi_cpufreq", RUN+= " /bin/sh -c ' echo performance > /sys/devices/system/cpu/cpufreq/policy0/scaling_governor ' "
```

To have the rule already applied in the *initramfs*, follow the example at udev#Debug output.

Interaction with ACPI events

Users may configure scaling governors to switch automatically based on different ACPI events such as connecting the AC adapter or closing a laptop lid. A quick example is given below, however it may be worth reading full article on acpid.

Events are defined in /etc/acpi/handler.sh . If the acpid (https://www.archlinux.org/packages/?name=acpid) package is installed, the file should already exist and be executable. For example, to change the scaling governor from performance to conservative when the AC adapter is disconnected and change it back if reconnected:

```
/etc/acpi/handler.sh

[...]

ac_adapter)
case "$2" in
AC*)
case "$4" in
00000000)
echo "conservative" >/sys/devices/system/cpu/cpu0/cpufreq/scaling_governor
echo -n $minspeed >$setspeed
#/etc/laptop-mode/laptop-mode start
;;
00000001)
echo "performance" >/sys/devices/system/cpu/cpu0/cpufreq/scaling_governor
echo -n $maxspeed >$setspeed
#/etc/laptop-mode/laptop-mode stop
;;
esac
;;
*) logger "ACPI action undefined: $2" ;;
esac
;;

[...]
```

Privilege granting under GNOME

Note: systemd introduced logind which handles consolekit and policykit actions. The following code below does not work. With logind, simply edit in the file /usr/share/polkit-1/actions/org.gnome.cpufreqselector.policy the <defaults> elements according to your needs and the polkit manual [3] (http://www.freedesktop.org/software/polkit/docs/latest/polkit.8.html).

GNOME has a nice applet to change the governor on the fly. To use it without the need to enter the root password, simply create following file:

```
/var/lib/polkit-1/localauthority/50-local.d/org.gnome.cpufreqselector.pkla

[org.gnome.cpufreqselector]
Identity=unix-user:user
Action=org.gnome.cpufreqselector
ResultAny=no
ResultInactive=no
ResultActive=yes
```

Where the word *user* is replaced with the username of interest.

The desktop-privileges (https://aur.archlinux.org/packages/desktop-privileges/)^{AUR} package in the AUR contains a similar .pkla file for authorizing all users of

the `power` group to change the governor.

Troubleshooting

- Some applications, like `ntop`, do not respond well to automatic frequency scaling. In the case of `ntop` it can result in segmentation faults and lots of lost information as even the `on-demand` governor cannot change the frequency quickly enough when a lot of packets suddenly arrive at the monitored network interface that cannot be handled by the current processor speed.
- Some CPU's may suffer from poor performance with the default settings of the `on-demand` governor (e.g. flash videos not playing smoothly or stuttering window animations). Instead of completely disabling frequency scaling to resolve these issues, the aggressiveness of frequency scaling can be increased by lowering the `up_threshold` `sysctl` variable for each CPU. See how to change the on-demand governor's threshold.
- Sometimes the on-demand governor may not throttle to the maximum frequency but one step below. This can be solved by setting `max_freq` value slightly higher than the real maximum. For example, if frequency range of the CPU is from 2.00 GHz to 3.00 GHz, setting `max_freq` to 3.01 GHz can be a good idea.
- Some combinations of ALSA drivers and sound chips may cause audio skipping as the governor changes between frequencies, switching back to a non-changing governor seems to stop the audio skipping.

BIOS frequency limitation

Some CPU/BIOS configurations may have difficulties to scale to the maximum frequency or scale to higher frequencies at all. This is most likely caused by BIOS events telling the OS to limit the frequency resulting in `/sys/devices/system/cpu/cpu0/cpufreq/bios_limit` set to a lower value.

Either you just made a specific Setting in the BIOS Setup Utility, (Frequency, Thermal Management, etc.) you can blame a buggy/outdated BIOS or the BIOS might have a serious reason for throttling the CPU on it's own.

Reasons like that can be (assuming your machine's a notebook) that the battery is removed (or near death) so you're on AC-power only. In this case a weak AC-source might not supply enough electricity to fulfill extreme peak demands by the overall system and as there is no battery to assist this could lead to data loss, data corruption or in worst case even hardware damage!

Not all BIOS'es limit the CPU-Frequency in this case, but for example most IBM/Lenovo Thinkpads do. Refer to thinkwiki for more thinkpad related info on this topic (http://www.thinkwiki.org/wiki/Problem_with_CPU_frequency_scaling).

If you checked there's not just an odd BIOS setting and you know what you're doing you can make the Kernel ignore these BIOS-limitations.

Warning: Make sure you read and understood the section above. CPU frequency limitation is a safety feature of your BIOS and you should not need to work around it.

A special parameter has to be passed to the processor module.

For trying this temporarily change the value in `/sys/module/processor/parameters/ignore_ppc` from `0` to `1`.

For setting it permanently Kernel modules#Setting module options describes alternatives. For example, you can add `processor.ignore_ppc=1` to your kernel boot line, or create

```
/etc/modprobe.d/ignore_ppc.conf
# If the frequency of your machine gets wrongly limited by BIOS, this should help
options processor ignore_ppc=1
```

See also

- Linux CPUFreq - kernel documentation (<https://www.kernel.org/doc/Documentation/cpu-freq/index.txt>)
- Comprehensive explanation of `pstate` (http://www.reddit.com/r/linux/comments/1hdogn/acpi_cpufreq_or_intel_pstates/)

Retrieved from "https://wiki.archlinux.org/index.php?title=CPU_frequency_scaling&oldid=474595"

Categories: Power management | CPU

- This page was last modified on 19 April 2017, at 13:55.
- Content is available under GNU Free Documentation License 1.3 or later unless otherwise noted.