

AutoCAD® Map 3D 2008

ObjectARX Developer's Guide

The Autodesk logo is displayed in white text on a black rectangular background. The word "Autodesk" is written in a bold, sans-serif font, oriented vertically from bottom to top.

April 2007

Copyright© 2007 Autodesk, Inc.

All Rights Reserved

This publication, or parts thereof, may not be reproduced in any form, by any method, for any purpose.

AUTODESK, INC., MAKES NO WARRANTY, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE REGARDING THESE MATERIALS, AND MAKES SUCH MATERIALS AVAILABLE SOLELY ON AN "AS-IS" BASIS.

IN NO EVENT SHALL AUTODESK, INC., BE LIABLE TO ANYONE FOR SPECIAL, COLLATERAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH OR ARISING OUT OF ACQUISITION OR USE OF THESE MATERIALS. THE SOLE AND EXCLUSIVE LIABILITY TO AUTODESK, INC., REGARDLESS OF THE FORM OF ACTION, SHALL NOT EXCEED THE PURCHASE PRICE, IF ANY, OF THE MATERIALS DESCRIBED HEREIN.

Autodesk, Inc., reserves the right to revise and improve its products as it sees fit. This publication describes the state of the product at the time of publication, and may not reflect the product at all times in the future.

Autodesk Trademarks

The following are registered trademarks or trademarks of Autodesk, Inc., in the USA and other countries: 3DEC (design/logo), 3December, 3December.com, 3ds Max, ActiveShapes, Actrix, ADI, Alias, Alias (swirl design/logo), AliasStudio, AliasWavefront (design/logo), ATC, AUGI, AutoCAD, AutoCAD Learning Assistance, AutoCAD LT, AutoCAD Simulator, AutoCAD SQL Extension, AutoCAD SQL Interface, Autodesk, Autodesk Envision, Autodesk Insight, Autodesk Intent, Autodesk Inventor, Autodesk Map, Autodesk MapGuide, Autodesk Streamline, AutoLISP, AutoSnap, AutoSketch, AutoTrack, Backdraft, Built with ObjectARX (logo), Burn, Buzzsaw, CAiCE, Can You Imagine, Character Studio, Cinestream, Civil 3D, Cleaner, Cleaner Central, ClearScale, Colour Warper, Combustion, Communication Specification, Constructware, Content Explorer, Create>what's>Next> (design/logo), Dancing Baby (image), DesignCenter, Design Doctor, Designer's Toolkit, DesignKids, DesignProf, DesignServer, DesignStudio, DesignStudio (design/logo), Design Your World, Design Your World (design/logo), DWF, DWG, DWG (logo), DWG TrueConvert, DWG TrueView, DXF, EditDV, Education by Design, Extending the Design Team, FBX, Filmbox, FMDesktop, GDX Driver, Gmax, Heads-up Design, Heidi, HOOPS, HumanIK, i-drop, iMOUT, Incinerator, IntroDV, Kaydara, Kaydara (design/logo), LocationLogic, Lustre, Maya, Mechanical Desktop, MotionBuilder, ObjectARX, ObjectDBX, Open Reality, PolarSnap, PortfolioWall, Powered with Autodesk Technology, Productstream, ProjectPoint, Reactor, RealDWG, Real-time Roto, Render Queue, Revit, Showcase, SketchBook, StudioTools, Topobase, Toxik, Visual, Visual Bridge, Visual Construction, Visual Drainage, Visual Hydro, Visual Landscape, Visual Roads, Visual Survey, Visual Syllabus, Visual Toolbox, Visual Tugboat, Visual LISP, Voice Reality, Volo, and Wiretap.

The following are registered trademarks or trademarks of Autodesk Canada Co. in the USA and/or Canada and other countries: Backburner, Discreet, Fire, Flame, Flint, Frost, Inferno, Multi-Master Editing, River, Smoke, Sparks, Stone, Wire.

Third Party Trademarks

All other brand names, product names or trademarks belong to their respective holders.

Third Party Software Program Credits

ACIS Copyright © 1989-2001 Spatial Corp.

Copyright © 1999-2000 The Apache Software Foundation. All rights reserved. This product includes software developed by the Apache Software Foundation (<http://www.apache.org>) subject to its license terms and conditions (<http://xml.apache.org/dist/LICENSE.txt>).

Typefaces from the Bitstream® typeface library Copyright © 1992.

HLM © Copyright D-Cubed Ltd. 1996-2006. HLM is a trademark of D-Cubed Ltd.

AutoCAD® 2008 and AutoCAD LT® 2008 are produced under a license of data derived from DIC Color Guide® from Dainippon Ink and Chemicals, Inc. Copyright © Dainippon Ink and Chemicals, Inc. All rights reserved. DIC and DIC Color Guide are registered trademarks of Dainippon Ink and Chemicals, Inc.

Portions of this software are based on the work of the Independent JPEG Group.

Active Delivery™ 2.0 © 1999-2004 Inner Media, Inc. All rights reserved.

ISYS and the ISYS logo are registered trademarks or trademarks of ISYS® Search Software Inc.

Copyright © 1988-1997 Sam Leffler. Copyright © 1991-1997 Silicon Graphics, Inc.

Copyright © Lingea s.r.o. 2006.

The New Features Workshop contains Macromedia Flash™ Player software by Macromedia, Inc. Copyright © 1995-2005 Macromedia, Inc. All rights reserved. Macromedia® and Flash® are registered trademarks or trademarks of Adobe Systems Incorporated in the United States or other countries.

Copyright © 1996-2006 Macrovision Corporation. All rights reserved.

Copyright © 1996-2006 Microsoft Corporation. All rights reserved.

Copyright © 2002 Joseph M. O'Leary.

PANTONE® Colors displayed in the software application or in the user documentation may not match -PANTONE-identified standards. Consult current PANTONE Color Publications for accurate color.

PANTONE® and other Pantone, Inc. trademarks are the property of Pantone, Inc. © Pantone, Inc., 2004.

Pantone, Inc. is the copyright owner of color data and/or software which are licensed to Autodesk, Inc., to distribute for use only in combination with certain Autodesk software products. PANTONE Color Data and/or Software shall not be copied onto another disk or into memory unless as part of the execution of this Autodesk software product.

Typefaces from Payne Loving Trust © 1992, 1996. All rights reserved.

RAL DESIGN © RAL, Sankt Augustin, 2004.

RAL CLASSIC © RAL, Sankt Augustin, 2004.

Representation of the RAL Colors is done with the approval of RAL Deutsches Institut für Gütesicherung und Kennzeichnung e.V. (RAL German Institute for Quality Assurance and Certification, re. Assoc.), D-53757 Sankt Augustin.

This product includes code licensed from RSA Security, Inc. Some portions licensed from IBM are available at <http://oss.software.ibm.com/icu4j/>. The Sentry Spelling-Checker Engine Copyright © 1994-2003 Wintertree Software, Inc. Portions of this product include one or more Boost libraries. Use of the Boost libraries is subject to its license agreement http://www.boost.org/LICENSE_1_0.txt.

Stingray® is Copyright © 1995-2005, Quovadx, Inc. All Rights Reserved. Protected by copyright and licenses restricting use, copying, distribution and decompilation. The Rogue Wave name and logo and the Stingray name and logo are either registered trademarks or trademarks of Quovadx, Inc. in the United States and/or other countries.

Xerces and Xalan are Copyright © 1999-2005, The Apache Software Foundation. Licensed under the Apache License, Version 2.0; you may not use this file except in compliance with the license. You may obtain a copy of the license at the following web address: <http://www.apache.org/licenses/LICENSE-2.0>.

Copyright © 1998-2006 The OpenSSL Project. All rights reserved.

This product includes software written by Tim Hudson (tjh@cryptsoft.com). This product includes cryptographic software written by Eric Young (eay@cryptsoft.com). Copyright © 1995-1998 Eric Young (eay@cryptsoft.com). All rights reserved.

ACE™ is copyrighted by Douglas C. Schmidt and his research group at Washington University, University of California, Irvine, and Vanderbilt University, Copyright ©1993-2006, all rights reserved.

The Director General of the Geographic Survey Institute has issued the approval for the coordinates exchange numbered TKY2JGD for Japan Geodetic Datum 2000, also known as technical information No H1-N0.2 of the Geographic Survey Institute, to be installed and used within this software product (Approval No.: 646 issued by GSI, April 8, 2002).

MrSID image compression format is Copyright © 2005, LizardTech, a division of Celartem, Inc. All rights reserved. MrSID technology is protected by U.S. Patent No 5,710,835 and patents pending.

Portions of this computer program are Copyright © 2000 Earth Resource Mapping, Inc.

The OSTN97 coordinate transformation is © Crown copyright 1997. All rights reserved.

The OSTN02 coordinate transformation is © Crown copyright 2002. All rights reserved.

The OSGM02 coordinate transformation is © Crown copyright 2002, © Ordnance Survey Ireland, 2002.

FME Objects Engine Copyright © 2005 SAFE Software. All rights reserved.

Libcurl is Copyright ©1996 - 2007, Daniel Stenberg, <daniel@haxx.se>. All rights reserved.

The Redland RDF Application Framework is Copyright © 2000-2005 Institute for Learning and Research Technology, University of Bristol. Licensed under the Apache License, Version 2.0; you may not use this file except in compliance with the license. You may obtain a copy of the license at the following web address: <http://www.apache.org/licenses/LICENSE-2.0>.

GDAL is Copyright © 2000, Frank Warmerdam.

Portions of sample data provided by NAVTEQ. Copyright © NAVTEQ 2001-2006, All rights reserved.

GOVERNMENT USE

Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in FAR 12.212 (Commercial Computer Software-Restricted Rights) and DFAR 227.7202 (Rights in Technical Data and Computer Software), as applicable.

Published By: Autodesk, Inc.
111 McInnis Parkway
San Rafael, CA 94903, USA

Contents

| | | |
|-----------|--------------------------------------|----|
| Chapter 1 | Before You Begin | 1 |
| | Sources of Information | 2 |
| | Compatability of SDKs | 2 |
| | Typographic Conventions | 2 |
| Chapter 2 | Drawing Sets | 5 |
| | Drawing Sets Detail | 6 |
| Chapter 3 | Drawing Set Sample | 9 |
| | Drawing Set Sample | 10 |
| Chapter 4 | Queries | 17 |
| | Queries Detail | 18 |
| Chapter 5 | Query Sample | 23 |
| | Query Sample Code | 24 |
| Chapter 6 | Property Alteration | 27 |
| | Property Alteration | 28 |

| | | |
|------------|--|-----|
| Chapter 7 | Property Alteration Sample | 31 |
| | Property Alteration Sample | 32 |
| Chapter 8 | Designing Queryable Custom Objects | 43 |
| | Designing Queryable Custom Objects Details | 44 |
| Chapter 9 | Custom Object Protocol Extensions | 47 |
| Chapter 10 | Data Sources | 49 |
| Chapter 11 | Object Data | 51 |
| Chapter 12 | Object Data Samples | 53 |
| | Creating an Object Data Table | 54 |
| | Attaching Object Data | 55 |
| | Traversing Object Data | 57 |
| | Adding or Changing Object Data | 58 |
| Chapter 13 | Coordinate Systems | 63 |
| | Coordinate Systems Details | 64 |
| Chapter 14 | Converting Coordinates | 67 |
| | Converting Coordinates | 68 |
| Chapter 15 | Feature Classification | 71 |
| | Feature Classification Detail | 72 |
| Chapter 16 | Object Filters | 81 |
| | Object Filters Detail | 82 |
| Chapter 17 | Import-Export | 85 |
| | Import-Export Detail | 86 |
| Chapter 18 | Oracle Spatial Data | 97 |
| | Oracle Spatial Data Detail | 98 |
| Chapter 19 | Oracle Spatial Samples | 105 |
| | Connecting to an Oracle Spatial Database | 106 |

| | | |
|-------------------|---|------------|
| | Subclassing Custom Reactors | 109 |
| | Exporting to an Oracle Spatial Database | 110 |
| | Importing from an Oracle Spatial Database | 114 |
| | Getting Corresponding IDs | 116 |
| | Filtering Objects | 120 |
| Chapter 20 | Oracle Spatial Sample Projects | 125 |
| | Importing From an Oracle Spatial Database | 126 |
| | Storing Block Definitions in an Oracle Spatial Database | 128 |
| | Storing Block Attribute Positions in an Oracle Spatial Database | 129 |
| Chapter 21 | Topology | 131 |
| | Topology Detail | 132 |
| Chapter 22 | Centroids | 151 |
| | Creating Centroids | 152 |
| Chapter 23 | Drawing Cleanup | 155 |
| | Drawing Cleanup Details | 156 |
| Chapter 24 | Annotation | 161 |
| | Annotation Details | 162 |
| Chapter 25 | Display Manager | 171 |
| Chapter 26 | User Management | 173 |
| | User Management Detail | 174 |
| Chapter 27 | Map Plotting and Publishing | 177 |
| | Map Plotting and Publishing Detail | 178 |
| Chapter 28 | Managed Wrapper Classes | 179 |
| | Managed Wrapper Classes Detail | 180 |
| Chapter 29 | Notes, Tips, and Warnings | 183 |
| | Colors | 184 |
| | Index | 187 |

Before You Begin

AutoCAD Map 3D ObjectARX Developer's Guide describes how to use ObjectARX classes to automate and extend AutoCAD Map 3D.

AutoCAD Map 3D ObjectARX extends AutoCAD ObjectARX into the AutoCAD Map 3D domain.

The ObjectARX and ObjectARX .NET APIs each cover most of AutoCAD Map 3D functionality. But they don't cover Resource Service, Feature Service, or Mapping Service. These areas are covered by the Geospatial Platform API, which is exposed as .NET only.

In this chapter

- [Sources of Information](#)
- [Compatibility of SDKs](#)
- [Typographic Conventions](#)

Sources of Information

To develop applications using AutoCAD Map 3D ObjectARX, you should be familiar with AutoCAD ObjectARX and also the AutoCAD Map 3D and AutoCAD applications.

For information about...

Refer to...

AutoCAD ObjectARX

AutoCAD ObjectARX Help, *arxdoc.chm*, which is located in the *docs* folder of AutoCAD Map 3D SDK installations.

AutoCAD Map 3D and AutoCAD

AutoCAD Map 3D Help, which is located in the *Help* folder of AutoCAD Map 3D installations.

AutoCAD Map 3D Help is especially useful for understanding how AutoCAD Map 3D models its domain. For understanding drawing sets and queries, for example. Since detailed explanations of these paradigms are available in AutoCAD Map 3D Help, AutoCAD Map 3D SDK Help explains them only briefly or not at all. Before you attempt to automate or extend an AutoCAD Map 3D feature, be sure to review the subject in AutoCAD Map 3D Help.

Compatibility of SDKs

The AutoCAD Map 3D SDK must be installed in an existing AutoCAD SDK installation, and the AutoCAD Map 3D SDK and AutoCAD SDK versions must be compatible with each other and with the version of AutoCAD Map 3D that you are extending. For example, the AutoCAD Map 3D 2008 SDK must be installed into an existing AutoCAD 2008 SDK installation, and you need both to build ObjectARX applications for AutoCAD Map 3D 2008.

Typographic Conventions

Text element

Description

bold sans serif

Text you enter at the AutoCAD Map 3D command prompt.

| Text element | Description |
|---|---------------------------------|
| <i>italic</i> | Names of files and directories. |
| monospace font | Sample code. |
| <hr/> NOTE Note All file names and directory paths in AutoCAD Map 3D are case sensitive. | |

Drawing Sets

2

The collection of drawings used in a particular project is the project's drawing set.

In this chapter

- [Drawing Sets Detail](#)

Drawing Sets Detail

When you save a project, AutoCAD Map 3D automatically saves references to all the project's drawing set files in the project's DWG file.

You attach drawings to and detach drawings from a drawing set.

Attached Drawings

A drawing set is a tree of attached drawings. Any of the attached drawings can have other drawings attached to them. The drawings that are not directly attached to the root of the drawing set (at level 0 of the tree) are called nested drawings.

You can use `AcMapDrawingSet` functions to edit and manipulate only drawings that are directly attached to the drawing set at the root level (level 0) of the drawing set. To access and edit drawings at deeper levels, use the functions of the `AcMapAttachedDrawing` class.

A single drawing can be directly attached to the drawing set only once. However, a single drawing can have multiple entries in the drawing set at nested levels 1 and deeper.

You can designate an attached drawing as active or inactive. When a query is executed in the project, only the active drawings are considered. When you work with object data in a project, open drawings instead of attaching them.

Drawing Set Reactors

You can attach a reactor to a drawing set. A drawing set reactor notifies an application about drawing set-related events, such as attachment, detachment, activation, or deactivation. Whenever the drawing set is modified, an appropriate function of the reactor object is called before termination of the zero level Map transaction.

Saving Attached Drawings

If, after modifying an attached drawing, you want to save the changes in the source drawing, you must specify the set of drawing objects to be saved in a save set.

Saving an attached drawing with its drawing objects is typically a three-part procedure:

- 1 Lock the drawing for writing using `AcMapAttachedDrawing::LockForWrite`.

- 2 Clone the drawing objects that you wish to save using one of the `AcMapAttachedDrawing` class's functions.
- 3 Save the changes back to the drawing's source file using `AcMapAttachedDrawing::Save`.

For More Information

For more information about drawing sets, see the UI documentation, Autodesk Map Help.

Drawing Set Sample

3

In this chapter

- [Drawing Set Sample](#)

Drawing Set Sample

The following sample demonstrates drawing set operations.

```

void editDSet()
{
    AcMapSession    *mapApi;
    AcMapProject     *pProj;
    AcMapDrawingSet  *pDSet;
    char             res[32];
    do {
        mapApi = AcMapGetSession();
        if (mapApi == NULL)
        {
            acutPrintf ("\nCan't connect MAP") ;
            break ;
        }
        if (mapApi->GetProject(pProj) == Adesk::kFalse)
        {
            break ;
        }
        if (pProj->GetDrawingSet(pDSet) == Adesk::kFalse)
        {
            acutPrintf ("\nCan't get drawing set") ;
            break ;
        }
    }
    do {
        // Setup
        printDSet(pDSet) ;
        *res = EOS ;
        acedInitGet(
            0,
            "eXit aTtach Detach Activate deaCtivate Settings
            gettaBle aLiases View Preview Report Query Zoom") ;
        if (acedGetKword(
            "\naTtach/Detach/Activate/deaCtivate/
            Settings/gettaBle/aLiases/View/Preview/Report/
            Query/Zoom/&lt;eXit&gt;: ",
            res
            ) == RTNORM)
        {
            if (*res == EOS || !(strcmp(res, "eXit")))
            {
                break ;
            }
            // Attach a drawing
            else if (!strcmp(res, "aTtach"))

```

```

{
if (acedGetString (
1,
"Enter alias path: ",
res
) == RTNORM)
{
AcMapAttachedDrawing *pDwg = NULL ;
if (pDSet->AttachDrawing(pDwg, res) == AcMap::kOk)
{
delete pDwg ;
}
}
// Detach a drawing
else if (!strcmp(res, "Detach"))
{
acedGetString(1, "Enter drawing path ", res) ;
AcMapAttachedDrawing *pDwg = NULL ;
pDSet->DetachDrawing(res) ;
}
// Activate a drawing
else if (!strcmp(res, "Activate"))
{
acedGetString(1, "Enter drawing path ", res) ;
AcMapAttachedDrawing *pDwg = NULL ;
if (pDSet->GetDrawing(
pDwg,
res,
Adesk::kFalse
) == AcMap::kOk)
{
pDwg->Activate() ;
delete pDwg ;
}
}
// Deactivate a drawing
else if (!strcmp(res, "deactivate"))
{
acedGetString(1, "Enter drawing path ", res) ;
AcMapAttachedDrawing *pDwg = NULL ;
if (pDSet->GetDrawing(
pDwg,

```

```

res,
Adesk::kFalse
) == AcMap::kOk)
{
pDwg->Deactivate() ;
delete pDwg ;
}
}
// Get a drawing's symbol table
else if (!strcmp(res, "gettable"))
{
acedGetString(1, "Enter drawing path ", res) ;
AcMapAttachedDrawing *pDwg = NULL ;
if (pDSet->GetDrawing(
pDwg,
res,
Adesk::kFalse
) == AcMap::kOk)
{
getTable(pDwg) ;
delete pDwg ;
}
}
// Edit a drawing's settings
else if (!strcmp(res, "Settings"))
{
acedGetString(1, "Enter drawing path ", res) ;
AcMapAttachedDrawing *pDwg = NULL ;
if (pDSet->GetDrawing(
pDwg,
res,
Adesk::kFalse
) == AcMap::kOk)
{
editSettings(pDwg) ;
delete pDwg ;
}
}
// Preview all of a drawing
else if (!strcmp(res, "View"))
{
acedGetString(1, "Enter drawing path ", res) ;
AcMapAttachedDrawing *pDwg = NULL ;

```

```

if (pDSet->GetDrawing(
pDwg,
res,
Adesk::kFalse
) == AcMap::kOk)
{
pDwg->Preview() ;
delete pDwg ;
}
}
// Preview queried objects in a drawing
else if (!strcmp(res, "Preview"))
{
acedGetString(1, "Enter drawing path ", res) ;
AcMapAttachedDrawing *pDwg = NULL ;
if (pDSet->GetDrawing(
pDwg,
res,
Adesk::kFalse
) == AcMap::kOk)
{
AcDbObjectIdArray tIds ;
pDwg->ApplyQuery(tIds) ;
pDwg->Preview(tIds) ;
delete pDwg ;
}
}
// Create a report of the queried objects in a drawing
else if (!strcmp(res, "Report"))
{
acedGetString(1, "Enter drawing path ", res) ;
AcMapAttachedDrawing *pDwg = NULL ;
if (pDSet->GetDrawing(
pDwg,
res,
Adesk::kFalse
) == AcMap::kOk)
{
AcDbObjectIdArray tIds ;
pDwg->ApplyQuery(tIds) ;
pDwg->Report(tIds) ;
delete pDwg ;
}
}

```

```

    }
    // Copy the drawing objects matching the
    // current query to the project drawing
    else if (!strcmp(res, "Query"))
    {
        acedGetString(1, "Enter drawing path ", res) ;
        AcMapAttachedDrawing *pDwg = NULL ;
        if (pDSet->GetDrawing(
            pDwg,
            res,
            Adesk::kFalse
        ) == AcMap::kOk)
        {
            AcDbObjectIdArray tIds ;
            pDwg->ApplyQuery(tIds) ;
            pDwg->QueryIn(tIds) ;
            delete pDwg ;
        }
    }
    // Zoom the drawings to the maximum
    else if (!strcmp(res, "Zoom"))
    {
        pDSet->ZoomExtents() ;
    }
    else
    {
        break ;
    }
    printErrStack() ;
} while(1) ;
} while (0) ;
}

```


Queries

4

A query is the mechanism by which the application retrieves a subset of objects from a source drawing, or from an external database associated with a source drawing, for use in the project drawing.

In this chapter

- [Queries Detail](#)

Queries Detail

After a query has been defined, it can be saved externally and subsequently loaded into an application, where it can be executed or modified.

The building blocks for creating a query definition are query conditions and query branches.


Query Conditions

The criteria that the query uses to select objects are expressed in query conditions. There are four types of query conditions.

| | Description |
|---------------------|---|
| Location Conditions | Based on the location of objects relative to a boundary. There are several boundary types. See Location Boundaries below. |
| Property Conditions | Based on a particular AutoCAD property. |
| Data Conditions | Based on object data?information about drawing objects that is stored with drawing objects themselves. |
| SQL Conditions | Based on data about drawing objects that is stored in external database tables and is specified by the WHERE clause of a SQL query. |

Location Boundaries

There are several types of location boundaries. They are all represented by descendants of the `AcMapLocationBoundary` class, as illustrated in the following diagram.




For more information about query condition types, refer to AutoCAD Map 3D Help. On the Contents tab, click Using AutoCAD Map 3D > Queries > Defining Queries.


Query Branches

Query branches are trees composed of query conditions, possibly subordinate query branches, and join operators, which connect the components.

The following diagram illustrates the structure of a simple query branch, in which a, b, and c are query conditions and AND and OR are join operators. It expresses the query, a AND b or c.



Both query branches and query conditions inherit from the same base class, as shown in the following diagram.



To build a query

- 1 Create one or more query conditions (also called query units or operands).
- 2 Create one or more query branches.
- 3 Append or insert query conditions onto the branch(es).
- 4 Create the query definition by passing the query branch to the **AcMapQuery::Define** function.
- 5 Create the query as an object in the project using the **AcMapProject::CreateQuery** function. This makes the query available to the application.
- 6 Save the query definition in an external file or query library.

To execute a query

- 1 You may want to set the mode, enable or disable property alteration, or create a report template for the query.
- 2 Call **AcMapQuery::Run** to execute the query.

For More Information

For more information about queries, see the UI documentation, AutoCAD Map 3D Help, and the Map Samples folder of ObjectARX installations.

Query Sample

The following sample demonstrates query operations.

5

In this chapter

- [Query Sample Code](#)

Query Sample Code


```

AcMapProject *pProj = NULL;
// Create a new branch object
AcMapQueryBranch *pRootBranch = NULL;
pRootBranch = new AcMapQueryBranch(AcMap::kOperatorOr);
// Create a new property condition
const char *pcValuePC = "Layer1";
AcMapPropertyCondition *pPropertyCondition = NULL;
pPropertyCondition = new AcMapPropertyCondition(
AcMap::kOperatorOr,
AcMap::kLayer,
AcMap::kCondEq,
pcValuePC
);
AcMapSession *pMapSession = NULL;
AcMapQuery *pNewQuery = NULL;
// Get the session object
pMapSession = AcMapGetSession();
if (pMapSession)
{
    // Get the currently active project
    if (pMapSession->GetProject(pProj) == AcMap::kOk)
    {
        // Create a new query object
        if ( pProj->CreateQuery(
pNewQuery,
Adesk::kFalse) == AcMap::kOk )
        {
            // Create a new property condition
            const char *pcValuePC = "Layer1";
            AcMapPropertyCondition *pPropertyCondition = NULL;
            pPropertyCondition = new AcMapPropertyCondition(
AcMap::kOperatorOr,
AcMap::kLayer,
AcMap::kCondEq,
pcValuePC
            );
            // Create a new branch object
            AcMapQueryBranch *pBranch = NULL;
            pBranch = new AcMapQueryBranch();
            // Append the condition to the branch
            pBranch->AppendOperand(pPropertyCondition);
            // Define the branch in the query
            if (pNewQuery->Define(pBranch) == AcMap::kOk)

```

```
    {  
        // Run the query.  
        pNewQuery->Run();  
    }  
    // Clean up  
    delete pPropertyCondition;  
    delete pBranch;  
    delete pNewQuery;  
} // if (pProj->CreateQuery  
} // if (pMapSession->GetProject  
} // if (pMapSession)
```

Property Alteration

6

Property alteration does not affect corresponding objects in the source drawing or drawings (unless you deliberately save the queried objects back). The process is controlled by a set of one or more property alterations, each of which describes how a particular property of queried objects should be displayed. All the property alterations for a particular query are contained in the query's property alteration definition.

In this chapter

- [Property Alteration](#)

Property Alteration

You associate a property alteration definition with the query that it affects using the `AcMapQuery::GetPropertyAlteration` function. You create a property alteration and add it to the definition, with the `AcMapPropertyAlterationDefinition::AddAlteration` function.

The classes used to create and manipulate property alteration for a query are

`AcMapPropertyAlterationDefinition` `AcMapPropertyAlteration`
`AcMapTextAlteration` `AcMapHatchAlteration`

The last two classes, which are subclassed from `AcMapPropertyAlteration`, are specialized property alterations for adding text labels and hatch patterns to queried objects.

You can alter properties conditionally, depending on existing values of the property to be altered or of some other property. To do so, you will also need to use the following classes:

`AcMapRangeLibrary` `AcMapRangeTable` `AcMapRangeLine`

Property Types

A property alteration's type identifies the property that it alters. The properties that can be altered are enumerated in `AcMap::EAlterationType`. When you create a property alteration, you set its type by assigning it one of these enumerators. Note that two of these enumerators, `AcMap::kAlterationTextEntity` and `AcMap::kAlterationHatch`, create the specialized property alteration objects `AcMapTextAlteration` and `AcMapHatchAlteration`, which are subclassed from `AcMapPropertyAlteration`. The remaining enumerators simply identify the different kinds of `AcMapPropertyAlteration` objects, the simple property alterations.

`AcMapTextAlteration` objects in a property alteration definition create text objects when the query executes, which serve as text labels for queried objects. `AcMapHatchAlteration` objects create hatch objects, which apply hatch patterns to closed or closeable queried objects.

The value that the property acquires when the query is run is indicated by the property alteration's value expression, which you set with the `AcMapPropertyAlteration::SetExpression` function. For example, if the property alteration's type is `AcMap::kAlterationColor`, you might set its expression to "Red". If the property alteration's type is `AcMap::kAlterationTextEntity`, the property alteration's value expression is the text for the label. If the type is `AcMap::kAlterationHatch`, the value expression is a pattern name.

To define a property alteration for a query

- 1 Get the property alteration definition of the query using the `AcMapQuery::GetPropertyAlteration` function.
- 2 Create a property alteration and add it to the property alteration definition using the `AcMapPropertyAlterationDefinition::AddPropertyAlteration` function.
- 3 Set the property alteration's expression using the `AcMapPropertyAlteration::SetExpression` function.
- 4 Repeat steps 2 and 3 for every property alteration that you want to be executed by the query.

Applying Property Alteration

When the query is executed, property alteration is applied only if it is defined and enabled. Use the following `AcMapQuery` functions to determine whether property alteration has been defined for a query, whether it has been enabled, and to enable or disable it as needed.

`AcMapQuery::IsPropertyAlterationDefined`

`AcMapQuery::IsPropertyAlterationEnabled`

`AcMapQuery::EnablePropertyAlteration`

Property alteration is defined if the query's property alteration definition contains at least one property alteration.

Conditional Property Alteration

You can alter properties conditionally, depending on existing values of the property to be altered or of some other property. For example, you can alter the colors of queried parcels depending on their assessed value.

A range table is a collection of range lines. A range line consists of a comparative operator (such as "greater than"), a comparison value (such as 1,000,000), and a return value (such as "Green"), to express a conditional alteration such as, "If the value is greater than 1,000,000, return green." To use a range table, pass a range table expression to the property alteration's `SetExpression` function. A range table expression has the following format.

where `Range` is an invariant keyword.

All the range tables available to a project are contained in the project's range library, an instance of the `AcMapRangeLibrary` class. A project contains a single range library.

For More Information

For more information about property alteration and range tables, see the UI documentation, AutoCAD Map 3D Help, and the Map Samples folder of ObjectARX installations.

The property alteration feature of AutoCAD Map 3D lets you modify the appearance of objects queried into the project drawing.

Property Alteration Sample

This example shows how to create range lines and alterations.

7

In this chapter

- [Property Alteration Sample](#)

Property Alteration Sample

It also shows how to use them together with a query. It assumes there is a current project, a project drawing, and at least one active attached drawing with some drawing objects in it.


```

////////////////////////////////////
// MAIN LOOP
//
// Clears the current query and calls
// DefineRangeLines(), TextAlt(), and
// HatchAlt().
//
////////////////////////////////////
void doPropAlts()
{
    AcMapSession *mapSession = NULL;
    mapSession = AcMapGetSession();
    if (mapSession)
    {
        AcMapProject *pProj;
        if (mapSession->GetProject(pProj) == Adesk::kTrue)
        {
            // Get the current Query
            AcMapQuery *pCurrentQuery = NULL;
            if (pProj->CreateQuery(
                pCurrentQuery,
                Adesk::kTrue
            ) == AcMap::kOk)
            {
                // Before we start, clear the current query
                pCurrentQuery->Clear(Adesk::kTrue);
                // clean up
                delete pCurrentQuery;
            }
        }
        // make the calls
        DefineRangeLines()
        TextAlt()
        HatchAlt()
    }
    //////////////////////////////////
    // DefineRangeLines()
    //
    // Creates two range tables and
    // adds them to the range library
    //
    //////////////////////////////////

```

```
void DefineRangeLines()  
{  
    AcMapSession *mapSession = NULL;  
    try  
    {
```

```

mapSession = AcMapGetSession();
if (mapSession)
{
    AcMapProject *pProj;
    if (mapSession->GetProject(pProj) == Adesk::kTrue)
    {
        // Get the range library
        AcMapRangeLibrary *pRangeLib = NULL;
        if (pProj->GetRangeLibrary(pRangeLib) == Adesk::kTrue)
        {
            // Add a range table to the library
            AcMapRangeTable *pTable = NULL;
            const char *pcName = "MyTypeRangeTable";
            const char *pcDsc = "Table for types";
            if (pRangeLib->AddRangeTable(
                pTable,
                pcName,
                pcDsc
            ) == AcMap::kOk)
            {
                // Add range lines that will add text next to
                // entites that match the input criteria.
                pTable->AddRangeLine(
                    AcMap::kRangeEq,
                    "circle",
                    "CIRCLE");
                pTable->AddRangeLine(
                    AcMap::kRangeEq,
                    "polygon",
                    "POLYGON");
                pTable->AddRangeLine(
                    AcMap::kRangeEq,
                    "polyline",
                    "PLINE");
                pTable->AddRangeLine(
                    AcMap::kRangeEq,
                    "line",
                    "LINE");
                pTable->AddRangeLine(
                    AcMap::kRangeEq,
                    "lwpolyline",
                    "LWPOLYLINE");
                pTable->AddRangeLine(

```

```

AcMap::kRangeEq,
"text",
"TEXT");
pTable-&gt;AddRangeLine(
AcMap::kRangeOtherwise,
NULL,
"Unknown Type");
}
// clean up
if (NULL != pTable)
{
delete pTable;
pTable = NULL;
}
pcName = "MyHatchRangeTable";
pcDsc = "Table for hatch ranges";
if (pRangeLib-&gt;AddRangeTable(
pTable,
pcName,
pcDsc
) == AcMap::kOk)
{
// Add range lines that will add hatch patterns
// to entites that match the input criteria.
pTable-&gt;AddRangeLine(
AcMap::kRangeEq,
"circle",
"ANSI31");
pTable-&gt;AddRangeLine(
AcMap::kRangeEq,
"polygon",
"CROSS");
pTable-&gt;AddRangeLine(
AcMap::kRangeEq,
"polyline",
"ANSI33");
pTable-&gt;AddRangeLine(
AcMap::kRangeEq,
"lwpolyline",
"DASH");
pTable-&gt;AddRangeLine(
AcMap::kRangeOtherwise,
NULL,

```

```

        "SOLID");
    }
    // clean up
    if (NULL != pTable)
    {
        delete pTable;
        pTable = NULL;
    }
}
}
catch(...)
{
    // do some error handling
}
}
////////////////////////////////////////
// TextAlt()
//
// Creates a Text Alteration and sets the
// expression to the table, MyTypeRangeTable.
// Defines and runs a query with property
// alteration.
//
////////////////////////////////////////
void TextAlt()
{
    AcMapSession *mapSession = NULL;
    try
    {

```

```

mapSession = AcMapGetSession();
if (mapSession)
{
    AcMapProject *pProj;
    if (mapSession->GetProject(pProj) == Adesk::kTrue)
    {
        // Get the current Query
        AcMapQuery *pCurrentQuery = NULL;
        if (pProj->CreateQuery(
            pCurrentQuery,
            Adesk::kTrue
        ) == AcMap::kOk)
        {
            // Get the Property alteration object from the query
            AcMapPropertyAlterationDefinition *pPADef = NULL;
            if (pCurrentQuery->GetPropertyAlteration(
                pPADef
            ) == AcMap::kOk)
            {
                AcMapPropertyAlteration *pPropAltObj = NULL;
                // Add a Text Alteration
                if (pPADef->AddAlteration(
                    pPropAltObj,
                    AcMap::kAlterationTextEntity
                ) == AcMap::kOk)
                {
                    // First we need to cast it
                    AcMapTextAlteration *pTextAlt = NULL;
                    pTextAlt = (AcMapTextAlteration*)pPropAltObj;
                    // set some attributes
                    pTextAlt->SetColor("Magenta");
                    pTextAlt->SetJustification("MIDDLE");
                    pTextAlt->SetRotation("45.0");
                    pTextAlt->SetHeight("0.5");
                    pTextAlt->SetExpression(
                        "(Range .TYPE MyTypeRangeTable)"
                    );
                }
                // clean up
                if (pPropAltObj)
                {
                    delete pPropAltObj;
                    pPropAltObj = NULL;
                }
            }
        }
    }
}

```

```

    }
    }
    // enable property alterations for the query
    pCurrentQuery->EnablePropertyAlteration(Adesk::kTrue);
    // Create a query branch Entity Type = ALL
    AcMapQueryBranch qBranch;
    AcMapPropertyCondition propCond;
    propCond.SetPropertyType(AcMap::kEntityType);
    propCond.SetConditionOperator(AcMap::kCondEq);
    propCond.SetValue("") ;
    qBranch.AppendOperand(&propCond);
    // define the query branch
    pCurrentQuery->Define(&qBranch);
    // set the query mode to draw
    pCurrentQuery->SetMode(AcMap::kQueryDraw);
    // run the query
    pCurrentQuery->Run();
    // clean up
    delete pCurrentQuery;
    }
    }
}
catch(...)
{
    // do some error handling
}
}
////////////////////////////////////////
// HatchAlt()
//
// Creates a Hatch Alteration and sets the
// expression to the table, MyHatchRangeTable.
// Defines and runs a query with property
// alteration.
//
////////////////////////////////////////
void HatchAlt()
{
    AcMapSession *mapSession = NULL;
    try
    {

```

```

mapSession = AcMapGetSession();
if (mapSession)
{
    AcMapProject *pProj;
    if (mapSession->GetProject(pProj) == Adesk::kTrue)
    {
        // Get the current Query
        AcMapQuery *pCurrentQuery = NULL;
        if (pProj->CreateQuery(
            pCurrentQuery,
            Adesk::kTrue
        ) == AcMap::kOk)
        {
            // Get the Property alteration object from the query
            AcMapPropertyAlterationDefinition *pPADef = NULL;
            if (pCurrentQuery->GetPropertyAlteration(
                pPADef
            ) == AcMap::kOk)
            {
                AcMapPropertyAlteration *pPropAltObj = NULL;
                // Now add a Hatch Alteration
                if (pPADef->AddAlteration(
                    pPropAltObj,
                    AcMap::kAlterationHatch
                ) == AcMap::kOk)
                {
                    // First we need to cast it
                    AcMapHatchAlteration *pHatchAlt = NULL;
                    pHatchAlt = (AcMapHatchAlteration*)pPropAltObj;
                    // set some attributes
                    pHatchAlt->SetScale("2.0");
                    pHatchAlt->SetColor("Yellow");
                    pHatchAlt->SetRotation("45.0");
                    pHatchAlt->SetExpression(
                        "(Range .TYPE MyHatchRangeTable)"
                    );
                }
                // clean up
                if (pPropAltObj)
                {
                    delete pPropAltObj;
                    pPropAltObj = NULL;
                }
            }
        }
    }
}

```



```

    }
    // enable property alterations for the query
    pCurrentQuery->EnablePropertyAlteration(Adesk::kTrue);
    // Create a query branch Entity Type = ALL
    AcMapQueryBranch qBranch;
    AcMapPropertyCondition propCond;
    propCond.SetPropertyType(AcMap::kEntType);
    propCond.SetConditionOperator(AcMap::kCondEq);
    propCond.SetValue("") ;
    qBranch.AppendOperand(&propCond);
    // define the query branch
    pCurrentQuery->Define(&qBranch);
    // set the query mode to draw
    pCurrentQuery->SetMode(AcMap::kQueryDraw);
    // run the query
    pCurrentQuery->Run();
    // clean up
    delete pCurrentQuery;
}
}
}
catch(...)
{
    // do some error handling
}
}
// END

```


Designing Queryable Custom Objects

8

If you are using AutoCAD ObjectARX to create AcDb custom objects, you must make sure that they will be retrievable using AutoCAD Map 3D queries.

In this chapter

- [Designing Queryable Custom Objects Details](#)

Designing Queryable Custom Objects Details

Observe the following guidelines:

- Subclass each custom object class from the appropriate ARX parent class, as detailed below.
- Ensure that each custom object instance in a drawing is added to the Model Space section of the drawing's Block table.

To support SQL or Data queries, the parent class doesn't matter.

To support location queries, a custom class must derive from `AcDbEntity` and overload the methods `getGeomExtents`, `intersectWith`, `getStretchPoints`, and `transformBy`.

To support property queries, custom class requirements depend on the properties to be queried:

| Queryable Property | Class to Derive From | Methods to Overload |
|--------------------|---------------------------------|--|
| Area | <code>AcDbCurve</code> | <code>getArea</code> |
| Block Name | <code>AcDbBlockReference</code> | None |
| Elevation | Not supported. | |
| Object Type | <code>AcDbEntity</code> | None |
| Length | <code>AcDbCurve</code> | <code>getEndParam</code> <code>getDistAtParam</code> |
| Text Style | <code>AcDbText</code> | None |
| Text Value | <code>AcDbText</code> | None |
| Thickness | Not supported. | |
| Color | <code>AcDbEntity</code> | None |
| Group | <code>AcDbEntity</code> | None |

| Queryable Property | Class to Derive From | Methods to Overload |
|--------------------|----------------------|---------------------|
| Layer | AcDbEntity | None |
| Linetype | AcDbEntity | None |

Note Object Type name specified via special MACRO, such as
ACRX_DXF_DEFINE_MEMBERS.

Custom Object Protocol Extensions

Enables custom objects to participate in AutoCAD Map 3D operations such as Query and Save Back.

For more information, see

- *Custom Object Protocol Extensions* in AutoCAD Map 3D ObjectARX Reference Help.
- Custom Object PE sample code, which is located in the Map Samples\QueryPESample folder of AutoCAD Map 3D ObjectARX installations.

Data Sources

The AutoCAD Map 3D data-sources feature links information from an external database to objects in a drawing.

[Data Sources](#) (page 49)

Other Information Sources

[Data Sources Samples](#) (page 50) [Data Sources Class](#) (page 50)

Data Sources

The *AcMapDataSources* class provides the following data-sources functions:

- Constructor/destructor -
AcMapDataSources()/~AcMapDataSources()
- Attach data source - *AttachDataSource()*
- Detach data source - *DetachDataSource()*
- Detach all data sources - *DetachAllDataSources()*
- Connect data source - *ConnectDataSource()*
- Disconnect data source - *DisconnectDataSource()*
- Disconnect all data sources - *DisconnectAllDataSources()*
- Count attached data sources -
GetAttachedDataSourcesCount()

- Count connected data sources - *GetConnectedDataSourcesCount()*
- Retrieve connected data sources - *GetConnectedDataSources()*
- Retrieve disconnected data sources - *GetDisconnectedDataSources()*
- Retrieve attached data sources - *GetAttachedDataSources()*

For data-sources source-code samples, see [Data Sources Samples](#) (page 50).

[Back to top](#)

Other Information Sources

- For more information about data sources in AutoCAD Map 3D, choose Help > Autodesk Map Help > Contents tab (or press F1), and then navigate to Using AutoCAD Map 3D (by feature) > External Databases > Attaching and Configuring Data Sources.
- For a data-sources tutorial in AutoCAD Map 3D, choose Help > Tutorials > Contents tab, and then choose "Working with External Databases".

[Back to top](#)

Data Sources Samples

To view code samples of data-sources functions, open the Samples folder in your AutoCAD Map 3D ObjectARX installation and navigate to Map Samples\DataSource.

[Back to top](#)

Data Sources Class

To view the data-sources class, click the following links:

AcMapDataSources Class

[Back to top](#)

Object Data

Object data is non-graphical information about an object in a drawing.

When you want to add such data to a drawing or drawing object, you create an object data table to store the data.

A single object data table contains records of a similar structure, which is defined by the object data table's table definition. The individual records in an object data table may be associated with different drawing objects. The association between the data and the object is at the level of the individual record, not at the table level.

The classes used to create and manipulate object data tables are

AcMapODColumnDefinition AcMapODContainer

AcMapODRecordIterator AcMapODTable

AcMapODTableDefinition AcMapODTableRecord AcMapValue

For More Information

For more information about object data, see the UI documentation, Autodesk Map Help, and the Map Samples folder of ObjectARX installations.

Object Data Samples

12

In this chapter

- [Creating an Object Data Table](#)
- [Attaching Object Data](#)
- [Traversing Object Data](#)
- [Adding or Changing Object Data](#)

Creating an Object Data Table

The following sample creates an object data table called Zones with two columns, Residential and Commercial.

To create an object data table

- 1 Include the necessary header files:

```
#include "StdAfx.h"
#include "StdArx.h"
#include <MapODColumn.h>;
#include <MapArxApi.h>;
#include <MapODDefinition.h>;
#include <MapProj.h>;
```

- 2 Create variables for the session, project, object data container, table, and columns. For example, create variables for a table with two columns.

```
AcMapSession *mapApi;
AcMapProject *pProj;
AcMapODContainer *pODCont;
AcMapODTableDefinition *pTabDef = NULL;
AcMapODColumnDefinition *pColDef1 = NULL;
AcMapODColumnDefinition *pColDef2 = NULL;
```

- 3 Create an AutoCAD Map 3D session and get the top level objects.

```
mapApi = AcMapGetSession();
mapApi->GetProject(pProj);
pProj->GetODContainer(pODCont);
```

- 4 Allocate memory for table and column objects by calling the table and column constructors with the new operator.

```
pTabDef = new AcMapODTableDefinition();
pColDef1 = new AcMapODColumnDefinition();
pColDef2 = new AcMapODColumnDefinition();
```

- 5 For each of the columns, set the column name and description and the type of data the column stores. Set the default value for the data.

```
pColDef1->SetName("Residential");
pColDef1->SetDescription("Residential R1-R3");
pColDef1->SetType(AcMap::kCharacter);
pColDef1->SetDefaultValue("R1");
pColDef2 = new AcMapODColumnDefinition();
pColDef2->SetName("Commercial");
```

```
pColDef2->SetDescription("Commercial C1-C3");
pColDef2->SetType(AcMap::kCharacter);
pColDef2->SetDefaultValue("C1");
```

6 Add the column definitions to the table definition.

```
pTabDef->AddColumn(*pColDef1);
pTabDef->AddColumn(*pColDef2);
```

7 Create the object data table. For example, create a table called Zones to store XData using the following code:

```
pODCont->CreateODTable("Zones", *pTabDef, "Zoning of King
City",
Adesk::kTrue);
```

8 Release the memory you allocated for the table and columns in step 4 using the delete operator.

```
if (pColDef2) delete pColDef2;
if (pColDef1) delete pColDef1;
if (pTabDef) delete pTabDef;
```

Attaching Object Data

The following sample attaches object data to selected objects in a drawing.

It creates a record for each of the objects and adds the data from an existing table to the records. Open rather than attach the drawing that contains the objects.

To attach object data

1 Include the necessary header files:

```
#include "StdAfx.h"
#include "StdArx.h"
#include <MapArxApi.h>
#include <MapProj.h>
#include <MapODRecord.h>
#include <MapODTable.h>
```

2 Declare variables.

```
ads_name ss, ename;
long sslen, sscur;
AcDbObjectId eId;
```

```

AcMapSession *mapApi = NULL;
AcMapProject *pProj = NULL;
AcMapODContainer *pODCont = NULL;
AcMapODTable *pODTable = NULL;

```

3 Create an AutoCAD Map 3D session and get the top level objects.

```

mapApi = AcMapGetSession();
mapApi->GetProject(pProj);
pProj->GetODContainer(pODCont);

```

4 Get the table containing the data to attach.

```

pODCont->GetODTable(pODTable, "Zones");

```

5 Use ADS functions to prompt user to select the objects to which to attach the data, and process the selections.

```

acutPrintf("\nAttach data to which object(s)?");
if (acedSSGet(NULL, NULL, NULL, NULL, ss) != RTNORM) {
    acutPrintf("\nNo objects selected.\n");
    acedSSFree(ss);
    return;
}

```

6 Use an ADS function to determine the number of objects selected in step 5.

```

acedSSLength(ss, &sslen);

```

7 Loop through the objects selected in step 5, getting the entity name of the next object, and converting it to an object ID, which you pass to AcMapODTable::AddRecord. Within the for loop, you create the AcMapODTableRecord using the new operator, thereby allocating memory for each record added. Remember to delete each pointer to AcMapODTableRecord within the loop, as shown here.

```

for (sscur = 0; sscur < sslen; sscur++)
{
    acedSSName(ss, sscur, ename);
    acdbGetObjectID(eId, ename);
    AcMapODTableRecord *pTabRec = NULL;
    pTabRec = new AcMapODTableRecord();
    pODTable->AddRecord(*pTabRec, eId);
    acutPrintf("\nOD Record added to object.");
    if (pTabRec) delete pTabRec;
}

```


- 8 Delete the memory allocated by calling `AcMapODContainer::GetODTable` in step 4, and free the memory allocated for the selection set in step 5.

```
delete pODTable;  
acedSSFree(ss);
```

Traversing Object Data

The following sample iterates all of an object's records using `AcMapODContainer::GetObjectODRecordIterator`.

You can also iterate only those records that are contained in a specified table using `AcMapODTable::GetObjectODRecordIterator`.

To traverse records

- 1 Include the necessary header files:

```
#include "StdAfx.h"  
#include "StdArx.h"  
#include <MapArxApi.h>  
#include <MapProj.h>  
#include <MapODIterator.h>
```

- 2 Declare variables.

```
int retCode = FALSE;  
ads_name ename;  
ads_point spt;  
AcDbObjectId eId;  
int recQuantity = 0;  
AcMapSession *mapApi = NULL;  
AcMapProject *pProj = NULL;  
AcMapODContainer *pODCont = NULL;  
AcMapODRecordIterator *pIter = NULL;
```

- 3 Create an AutoCAD Map 3D session and get the top level objects.

```
mapApi = AcMapGetSession();  
mapApi->GetProject(pProj);  
pProj->GetODContainer(pODCont);
```

- 4 Use ADS functions to prompt user to select an object, and convert the entity name of the selected object to an object ID for initializing the iterator in the next step.

```
retCode = acedEntSel(NULL, ename, spt);
if (retCode != RTNORM) {
    acutPrintf("\nNo object selected.\n");
    return;}
acdbGetObjectId(eId, ename);
```

5 Get a record iterator and initialize it for reading.

```
pODCont->GetObjectODRecordIterator (pIter);
pIter->Init (eId, AcMap::kOpenForRead, Adesk::kFalse);
```

6 Use the record iterator to count records attached to the object. Print the results.

```
recQuantity = pIter->CountRecords();
acutPrintf("\nObject has %d records attached.", recQuantity);
```

7 Delete the iterator when you're finished with it.

```
if (pIter) delete pIter;
```

Adding or Changing Object Data

The structure for containing data in an object data table is a table record (AcMapODTableRecord object).

The actual data in the record is contained in instances of the AcMapValue class, one value for each field (column) in the record. You read the value of a record using one form of AcMapODTableRecord::Value, and you add new data or modify the existing value, using the other form, which is the non-const override of the function.

The following sample shows how to add new data or modify the current data in the object records of selected objects. Before performing this procedure, create a table named Zones. Next, attach data. Data attached to selected objects consists of two columns: a zoning code column called Code and an Approved By column.

To add or change object data

1 Include the necessary header files:

```
#include "StdAfx.h"
#include "StdArx.h"
#include <MapODColumn.h>;
```

```

#include <MapArxApi.h>;
#include <MapODDefinition.h>;
#include <MapProj.h>;
#include <MapODRecord.h>;
#include <MapODIterator.h>;

```

2 Define a constant for input of the record values and declare variables.

```

#define USR_STRG_LENGTH 133
int retCode = FALSE;
ads_name ename;
ads_point spt;
char zoneCode [USR_STRG_LENGTH] = "";
char approveCode [USR_STRG_LENGTH] = "";
AcMapSession *mapApi = NULL;
AcMapProject *pProj = NULL;
AcMapODContainer *pODCont = NULL;
AcMapODRecordIterator *pIter = NULL;
AcDbObjectId eId;
AcMapODTableRecord record;

```

3 Create an AutoCAD Map 3D session and get the top level objects.

```

mapApi = AcMapGetSession();
mapApi->GetProject(pProj);
pProj->GetODContainer(pODCont);

```

4 Use ADS functions to prompt user to select an object, and convert the entity name of the selected object to an object ID for initializing the iterator in the next step.

```

retCode = acedEntSel(NULL, ename, spt);
if (retCode != RTNORM) {
    acutPrintf("\nNo object selected.\n");
    return;}
acdbGetObjectId(eId, ename);

```

5 Get a record iterator and initialize it for writing. Using the iterator in a for loop, traverse the records of the object selected in step 4, getting the table associated with each record.

```

pODCont->GetObjectODRecordIterator (pIter);
pIter->Init (eId, AcMap::kOpenForWrite, Adesk::kFalse);
for (; pIter->IsDone() == Adesk::kFalse; pIter->Next())
{
    pIter->GetRecord (record);
    pODCont->GetODTable (pTable, record.ODTableName());
}

```

```
acutPrintf("\n*** OD Table %s.", record.ODTableName());
```

- 6** Loop through the columns of each record, and print the name of the column, which in this example is either Code or Approved By.

```
for (int i = 0; i < record.Count(); i++)
{
    AcMapODTableDefinition tableDef = pTable->Definition();

    AcMapODColumnDefinition Column;
    tableDef.GetColumn(Column, i);
    acutPrintf("\n%-15s", Column.Name());
}
```

- 7** Print the value at the column of the record and get a pointer, colname, to the column.

```
AcMapValue &val = record.Value(i);
acutPrintf(" %s", ((const char *)val));
colname = Column.Name();
```

- 8** Create an AcMapValue variable and assign the value entered by the user to it. Then, assign the AcMapValue variable to the value of the record using the AcMapODTableRecord::Value function. Update the record using the record iterator.

```
if(!strcmp(colname, "Code")){
    acedGetString(TRUE, "\nNew zoning code:", zoneCode);
    AcMapValue v = zoneCode;
    record.Value(i) = v;
    pIter->UpdateRecord(record);
}
```

- 9** Using the same paradigm as step 9, get and update the record's Approved by column.

```
if(!strcmp(colname, "Approved")){
    acedGetString(TRUE, "\nApproved by:", approveCode);
    AcMapValue v = approveCode;
    record.Value(i) = v;
    pIter->UpdateRecord(record);
}
```

- 10** End the for loop started in step 7 and delete the pointer to the table created with AcMapODContainer::GetODTable. End the for loop started in step 6 and delete the iterator created in step 5.

```
//end for
if (pTable) delete pTable;
```

```
} //end for  
if (pIter) delete pIter;
```


Coordinate Systems

13

The AutoCAD Map 3D coordinate-systems functions measure geodetic distance and transform entities to a specified coordinate system.

In this chapter

- [Coordinate Systems Details](#)

Coordinate Systems Details

[Coordinate-Systems Functions](#) (page 64)

Other Information Sources

[Coordinate Systems Samples](#) (page 64) [Coordinate Systems Globals](#)

Coordinate-Systems Functions

The following coordinate-systems functions are available:

- Measure the geodetic distance between two points - *ade_projwsgeodistance()*
- Transform an entity from the source to the destination coordinate system - *ade_projentityforward()*
- Transform an entity from the destination to the source coordinate system - *ade_projentitybackward()*

For coordinate-systems source-code samples, see [Coordinate Systems Samples](#) (page 64).

[Back to top](#)

Other Information Sources

- For more information about coordinate systems in AutoCAD Map 3D, choose Help > Autodesk Map Help > Contents tab (or press F1), and then navigate to Using AutoCAD Map 3D (by feature) > Coordinate Systems.
- For a coordinate-systems tutorial in AutoCAD Map 3D, choose Help > Tutorials > Contents tab, and then choose "Working with Coordinate Systems".

[Back to top](#)

Coordinate Systems Samples

To view code samples of coordinate-systems functions, open the Samples folder in your AutoCAD Map 3D ObjectARX installation and navigate to Map Samples\CoordinateSystem.

[Back to top](#)

Coordinate Systems Globals

To view the coordinate-systems globals, click the following links:

[ade_projwsgeodistance\(\)](#) Global Function
[ade_projentityforward\(\)](#) Global Function
[ade_projentitybackward\(\)](#) Global Function

[Back to top](#)

Converting Coordinates

14

Converting coordinates from one geo-referenced coordinate system to another.

In this chapter

- [Converting Coordinates](#)

Converting Coordinates

Any Cartesian coordinate pair you select in a geo-referenced coordinate system corresponds to a point on the surface of the earth. This fact defines a relation between the coordinate pairs in one coordinate system and the coordinate pairs in any other, so long as the point in question actually exists in both systems. In other words, so long as the coordinate systems have a region of intersection, and the point in question is in it.

To convert the coordinates of a point from one geo-referenced coordinate system to another

- 1 Define a "source" coordinate system with *ade_projsetsrc*.
- 2 Define a "destination" coordinate system with *ade_projsetdest*.
- 3 Pass a coordinate pair to *ade_projptforward*.

The function assumes that the coordinate pair you pass to it is a point in the source system, and it returns the corresponding coordinate pair in the destination system. If there is no corresponding coordinate pair, it returns nil.

To convert in the other direction, use *ade_projptbackward*.

You can specify coordinate triplets, but if you do, the Z value is ignored.

The following sample converts a known position from Latitude Longitude (LL) to Universal Transverse Mercator (UTM) using *ade_projptforward()*. If the conversion is successful, information about the conversion is displayed and the UTM coordinate is converted back to Lat Long using *ade_projptbackward()*. If you don't know the specific coordinate system code, click Select Coordinate System. In the Select Global Coordinate System dialog box, which is located under the Map ->Tools->Assign Global Coordinate System menu option. Select a category, and then select from a list of available coordinate systems. Click Properties to view the Code value of the selected coordinate system.

```

char* pszSourceCoordSys = "LL84";
int resultCode = ade_projsetsrc(pszSourceCoordSys);
char* pszDestCoordSys = "UTM27-15";
resultCode = ade_projsetdest(pszDestCoordSys);
ads_point coordPairToConvert;
coordPairToConvert[0] = -90.4794;
coordPairToConvert[1] = 38.7503;
ads_point convertedCoordPair;
resultCode = ade_projtforward(
coordPairToConvert,
convertedCoordPair);
if (RTNORM == resultCode){
    acutPrintf(
        "\nThe %s coordinate value of: %.4lf\,%.4lf was successfully
        converted"
        " to %s yielding the value of: %.4lf\,%.4lf"
        , pszSourceCoordSys, coordPairToConvert[0], coordPairToCon
        vert[1]
        , pszDestCoordSys, convertedCoordPair[0], convertedCoord
        Pair[1]);
    coordPairToConvert[0] = convertedCoordPair[0];
    coordPairToConvert[1] = convertedCoordPair[1];
    ads_point convertedBackCoordPair;
    resultCode = ade_projtbackward(
    coordPairToConvert,
    convertedBackCoordPair);
    acutPrintf(
        "\n\n\nUsing ade_projtbackward(), the %s coordinate value
        of: %.4lf\,%.4lf was"
        " successfully converted back to %s yielding the value of:
        %.4lf\,%.4lf"
        , pszDestCoordSys, coordPairToConvert[0], coordPairToConvert[1]
        , pszSourceCoordSys, convertedBackCoordPair[0], convertedBack
        CoordPair[1]);
}
else {
    acutPrintf(
        "\nNo coordinate conversion took place.");
}
}

```


Feature Classification

15

Use AutoCAD Map 3D's feature-classification feature to create standard objects in drawings.

In this chapter

- [Feature Classification Detail](#)

Feature Classification Detail

Each standard object, called a *feature*, has a set of user-defined properties and data, called a *feature class*. All feature class definitions are stored in a *feature-definition file*, or *schema*. After setting up feature class definitions, you can use them to create objects with a standard set of properties and data. You can change property values, or the properties themselves, programmatically. An organization that creates road maps, for example, might have standard Primary Road and Secondary Road polyline objects in which the Primary Road features are created with thick lineweight on the Primary Roads layer, and Secondary Road features appear with thin lineweight on the Secondary Roads layer. Each road feature has associated object data, such as speed limit, number of lanes, and surface type. See also Other Information Sources.

[Creating and Managing Schemas](#) (page 72)

[Creating and Managing Feature Class Definitions](#) (page 74)

[Classifying Entities](#) (page 74)

Managing Attributes of Feature Class Definitions

[Managing Properties](#) (page 77)

[Using Reactors with Feature Class Definition Events](#) (page 78)

[Handling Errors](#) (page 79)

Other Information Sources

[Feature Classification Samples](#) (page 80)

[Feature Classification Classes and Namespaces](#) (page 80)

Creating and Managing Schemas

Before you can [Creating and Managing Feature Class Definitions](#) (page 74), you must create a schema and attach it to the current drawing by using *AcMapClassificationManager* functions. However, before you create a new feature-definition file with *CreateFeatureDefinitionFile()*, use *CanCurrentUserAlterSchema()* to check whether the current user has sufficient privileges to create or change a schema. (Even though you don't check this first, *CreateFeatureDefinitionFile()* will catch an insufficient-privileges error.)

Alternatively, rather than creating a new schema, use the currently attached schema, indicated by *GetFeatureDefinitionFileAttached()*, or attach an existing schema with *AttachFeatureDefinitionFile()*. You can detach a schema explicitly with *DetachCurrentFeatureDefinitionFile()*.

After creating or modifying a feature class definition in a schema, save the file with `SaveCurrentFeatureDefinitionFile()` or save a copy with `SaveCurrentFeatureDefinitionFileAs()`. You also can refresh the current schema with `ReloadCurrentFeatureDefinitionFile()`, but doing so is risky because it might reload outdated data, depending on the user's actions.

For feature-classification source-code samples, see [Feature Classification Samples](#) (page 80).

```
// Creates a new feature-definition file.
AcMapObjClass::EErrCode errCode;
const char* pszSchemaFileName = "mySchema.xml";
// Check whether current user can create or change schema.
if (CanCurrentUserAlterSchema())
{
    // Create the schema file.
    errCode = CreateFeatureDefinitionFile(pszSchemaFileName);
    // Handle errors.
    switch (errCode)
    {
        case AcMapObjClass::eNoUserPrivilegeToAlterSchema:
            // Insufficient-privileges error.
            break;
        case AcMapObjClass::eFileAlreadyExists:
            // Schema file already exists (and will be attached).
            break;
        case AcMapObjClass::eFileNameInvalid:
            // Invalid file name.
            break;
        case AcMapObjClass::eFailed:
            // Failed for some other reason.
            break;
        default:
            break;
    }
    // Attach the schema file.
    errCode = AttachFeatureDefinitionFile(pszSchemaFileName);
    if (errCode == AcMapObjClass::eOk)
    {
        ...
    }
}
```

[Back to top](#)

Creating and Managing Feature Class Definitions

After you attach a feature-definition file to the current drawing, you can define feature classes by using *AcMapClassificationManager* functions.

It's prudent to run a few safety checks before you create a feature class definition. For example, you could do the following:

- Use *GetFeatureClassDefinitionCount()* to indicate whether any existing feature classes are defined in the current schema and use *GetFeatureClassNames()* to list their names.
- Use *IsFeatureClassDefinitionPresent()* to determine whether a specific class definition exists.

Create a feature class definition by using *CreateFeatureClassDefinition()* (*two forms*). Alternatively, you can use *DuplicateFeatureClassDefinition()* to copy an existing feature class definition and then change its attributes by using *GetFeatureClassDefinition()*.

After creating or modifying a feature class definition in a schema, save your changes with *SaveCurrentFeatureDefinitionFile()* or *SaveCurrentFeatureDefinitionFileAs()*.

To rename or delete a feature class definition, use *RenameFeatureClassDefinition()* or *DeleteFeatureClassDefinition()*.

For feature-classification source-code samples, see [Feature Classification Samples](#) (page 80).

[Back to top](#)

Classifying Entities

After you create feature class definitions, you can use them to classify the entities in the current drawing by using *AcMapClassificationManager* functions.

Use any of the following methods to check entities:

- To avoid redoing or overwriting previous classifications, check which entities already are classified and with which feature class definitions. *GetClassifiedEntities()* (*two forms*) lists all classified entities in the current drawing, and *GetUnclassifiedEntities()* lists the unclassified ones.
- Use *GetUndefinedEntities()* to list entities that are classified but whose feature class definitions are not in the attached feature-definition file.
- Use *IsClassified()* to determine whether a specific entity is classified.

Use any of the following methods to manage classified entities:

- To classify one or more entities, use `Classify()` (*two forms*).
- To inspect an entity's properties, use `GetProperties()` (*two forms*).
- To determine how an entity should be classified (or reclassified), use `GetClassifiedProperties()` (*two forms*).
- To fix out-of-range or missing values of classified properties, use `Audit()` (*two forms*).
- If an entity was classified multiple times by using different feature-definition files, use `GetAllTags()` to retrieve all the entity's feature class names and corresponding feature-definition files.
- To unclassify one or more entities, use `Unclassify()` (*two forms*) or `ClearAllTags()` (*two forms*).

For feature-classification source-code samples, see [Feature Classification Samples](#) (page 80).

[Back to top](#)

Managing Attributes of Feature Class Definitions

Use `AcMapObjClassDefinition` functions to manage the attributes of a feature class definition stored in the feature-definition file attached to the current drawing. You can retrieve and (in some cases) set the following attributes:

- Name - `GetName()/SetName()`
- Description - `GetDescription()/SetDescription()`
- Icon - `GetIconName()/SetIconName()`
- Visibility - `IsVisibleInWorkspace()/SetVisibleInWorkspace()`
- Feature definition file - `GetFeatureDefinitionFile()`
- Supported entity types - `GetSupportedEntityTypes()` (*two forms*)

```

// Print the name of this feature class definition and the
// pathname of the feature-definition file that it belongs to.
const char* pszFeatureClassName = GetName();
const char* pszFeatureDefinitionFile = GetFeatureDefinition
File();
acutPrintf("\nThe feature class definition name is %s", pszFea
tureClassName);
acutPrintf("\nThe feature-definition file pathname is %s",
pszFeatureDefinitionFile);

```

Use the following functions to determine where a specific feature class exists in the feature-class hierarchy: *GetDirectBaseClassName()*, *IsBaseClassOf()*, *IsBaseClassOnly()*, *IsDerivedClassOf()*, and *IsDirectBaseClassOf()*.

```

// Determine whether this feature class definition is a base class
// of the feature class "Parcels".
AcMapObjClass::EErrCode errCode;
bool bBaseClassOf; // Output.
errCode = IsBaseClassOf(&bBaseClassOf, "Parcels");
if (errCode == AcMapObjClass::eOk)
{
    if (bBaseClassOf == true)
    {
        ...
    }
}

```

Use *GetProperty()* or *GetProperties()* to retrieve a specific property, or all properties, of a feature class definition. *GetProperties()* retrieves only properties that are classified, which you can determine with *IsPropertyClassified()*. You can add or delete a property with *AddProperty()* or *DeleteProperty()*. To change a property's attributes, see [Managing Properties](#) (page 77).

```

// Retrieve the Linetype property.
AcMapObjClass::EErrCode errCode;
AcMapObjClassProperty* pProperty = NULL;
AcMapStringArray aStrParentToSubCategoryNames;
aStrParentToSubCategoryNames.Append("General");
const char* pszPropertyName="Linetype";
errCode = GetProperty(pProperty, aStrParentToSubCategoryNames,
pszPropertyName);
if (errCode == AcMapObjClass::eOk)
{
// Process the property.
}

```

For digitizing data, use `SetCreateMethod()` (*twoforms*), `GetCreateMethod()`, and `GetCreateMethodName()` to set or retrieve the AutoCAD entity type that a feature class definition uses when a digitize process runs.

For feature-classification source-code samples, see [Feature Classification Samples](#) (page 80).

[Back to top](#)

Managing Properties

Use *AcMapObjClassProperty* functions to manage a property for a feature class definition. You can retrieve and (in some cases) set the following attributes of a property:

- Name - *GetName()*
- Direct category - *GetCategory()*
- Type - *GetType()*
- Default value - *GetDefaultValue()/SetDefaultValue*
- Range - *GetRange()/SetRange()/IsInRange()*
- Visibility - *IsVisible()/SetVisible()*
- Read-only - *IsReadOnly()/SetReadOnly()*
- String representation - *FromString()/ToString()*

For feature-classification source-code samples, see [Feature Classification Samples](#) (page 80).

```

// Set the range of the Length property.
AcMapObjClass::EErrCode errCode;
AcMapObjClassProperty* pProperty = NULL;
AcMapStringArray aStrParentToSubCategoryNames;
aStrParentToSubCategoryNames.Append("Geometry");
const char* pszPropertyName = "Length";
errCode = GetProperty(pProperty, aStrParentToSubCategoryNames,
pszPropertyName);
if (errCode == AcMapObjClass::eOk)
{
    errCode = pProperty->SetRange("0.0,1.0,2.0,3.0");
    if (errCode == AcMapObjClass::eOk)
    {
        ...
    }
}

```

Back to top

Using Reactors with Feature Class Definition Events

The *AcMapObjClassReactor* class provides callback functions that notify an application immediately of feature class definition events. You use this mechanism to monitor or control feature class definition operations by registering reactor instances. Functions are invoked automatically depending on the operation's type, as described in the following table:

| Function | Invoked when a |
|---|---|
| <i>FeatureClassDefinitionCreated()</i> | Feature class definition is created |
| <i>FeatureClassDefinitionDeleted()</i> | Feature class definition is deleted |
| <i>FeatureClassDefinitionModified()</i> | Feature class definition is modified |
| <i>FeatureClassDefinitionRenamed()</i> | Feature class definition is renamed |
| <i>FeatureDefinitionFileAttached()</i> | Feature-definition file is attached to or detached from the current drawing |
| <i>FeatureDefinitionFileModified()</i> | Feature-definition file is modified and saved |

Use *AcMapObjClassSystem* to register and unregister classification reactors with *AddObjClassReactor()* and *RemoveObjClassReactor()*. To use a reactor, perform the following steps, as shown in the sample code that follows:

- 1 Derive a custom class from *AcMapObjClassReactor*.
- 2 Implement events by overriding the virtual functions that you need.
- 3 Create an instance of the custom reactor.
- 4 Register the instance so that it becomes active.
- 5 Write some classification reactor code.
- 6 Remove the reactor from the list and delete it.

For feature-classification source-code samples, see [Feature Classification Samples](#).

```
// Derive a custom class from AcMapObjClassReactor.
class AcMapObjClassMyReactor : public AcMapObjClassReactor
{
    // Override virtual functions for the desired events.
};
// Create an instance of the custom reactor.
AcMapObjClassMyReactor* pMyReactor = new AcMapObjClassMyReactor;
// Register the custom reactor.
AcMapObjClassSystem().AddObjClassReactor(pMyReactor);
// Insert classification reactor code here.
// Remove the reactor and delete it.
AcMapObjClassSystem().RemoveObjClassReactor(pMyReactor);
delete pMyReactor;
```

[Back to top](#)

Handling Errors

Many functions in the various feature-classification classes return an *AcMapObjClass::EErrCode* error code. When a particular function returns an error code, read that function's documentation for function-specific error conditions rather than relying on only the generic error descriptions in the *AcMapObjClass::EErrCode* documentation.

Other Information Sources

- For more information about feature classification in AutoCAD Map 3D, choose [Help > AutoCAD Map 3D Help > Contents tab](#) (or press F1),

and then navigate to Using AutoCAD Map 3D (by feature) > Feature Classification.

- For a feature-classification tutorial in AutoCAD Map 3D, choose Help > Tutorials > Contents tab, and then choose "Using Feature Classification".

[Back to top](#)

Feature Classification Samples

To view code samples of classification functions, open the Samples folder in your AutoCAD Map 3D ObjectARX installation and navigate to Map Samples\Classification.

[Back to top](#)

Feature Classification Classes and Namespaces

To view the feature-classification classes and namespaces, click the following links:

[AcMapClassificationManager Class](#)

[AcMapObjClass Namespace](#)

[AcMapObjClassDefinition Class](#)

[AcMapObjClassProperty Class](#)

[AcMapObjClassReactor Class](#)

[AcMapObjClassSystem Class](#)

[Back to top](#)

Object Filters

16

The AutoCAD Map 3D object-filters feature filters objects (entities) in the current drawing based on the specified filtering criteria.

In this chapter

- [Object Filters Detail](#)

Object Filters Detail

Object Filters

The *AcDbObjectFilter* class is the base class for creating object filters, and provides the following functions:

- Constructor/destructor - *AcDbObjectFilter()*/*~AcDbObjectFilter()*
- Filter objects - *FilterObjects()*
- Activate object filter - *IsActive()/SetActive()*

For object-filters source-code samples, see Object Filters Samples.

Basic Filters

The *AcDbBasicFilter* class (derived from The *AcDbObjectFilter*) filters objects in the current drawing based on layer, feature-class, and block criteria, and provides the following functions:

- Constructor/destructor - *AcDbBasicFilter()* (*two forms*)/*~AcDbBasicFilter()*
- Filter objects - *FilterObjects()*
- Layer filters:
 - Retrieve layers - *Layers()*
 - Set layers - *SetLayers()* (*two forms*)
 - Add layers - *AddLayers()*
 - Clears layers - *ResetLayers()*
 - Layer status - *LayerStatusMask()/SetLayerStatusMask()*. See also *ELayerStatus* enum.
- Feature-class filters:
 - Retrieve feature classes - *FeatureClasses()*
 - Set feature classes - *SetFeatureClasses()* (*two forms*)
 - Add feature classes - *AddFeatureClasses()*

- Clears feature classes - *ResetFeatureClasses()*

- Block filters:

- Retrieve blocks - *Blocks()*

- Set blocks - *SetBlocks()* (*two forms*)

- Add blocks - *AddBlocks()*

- Clears blocks - *ResetBlocks()*

For object-filters source-code samples, see Object Filters Samples.

[Back to top](#)

Using Multiple Filters

The *AcDbObjectFilterGroup* class (derived from The *AcDbObjectFilter*) filters objects in the current drawing based the based on the criteria of one or more listed filters, and provides the following functions:

- Constructor/destructor - *AcDbObjectFilterGroup()/~AcDbObjectFilterGroup()*

- Add filter - *AddObjectFilter()*

- Insert filter - *InsertObjectFilter()*

- Remove filter - *RemoveObjectFilter()/RemoveAllObjectFilter()*

- Count filters - *ObjectFilterCount()*

- Empty test - *IsEmpty()*

- Retrieve filter - *GetObjectFilter()*

- Filter objects - *FilterObjects()*

For object-filters source-code samples, see Object Filters Samples.

Other Information Sources

- For more information about object filters in AutoCAD Map 3D, choose Help > Autodesk Map Help > Index tab, and then type the keywords *filters* and *queries* to display the related topics.

Object Filters Samples

To view code samples of object-filters functions, open the Samples folder in your AutoCAD Map 3D ObjectARX installation and navigate to Map Samples\ObjectFilter.

Object Filters Classes

To view the object-filters classes, click the following links:

[AcDbObjectFilter Class](#) *[AcDbBasicFilter Class](#)* *[AcDbObjectFilterGroup Class](#)*

Import-Export

Use AutoCAD Map 3D's import-export feature to exchange data in industry-standard GIS and mapping formats.

17

In this chapter

- [Import-Export Detail](#)

Import-Export Detail

By importing a map, you can combine data from other mapping or GIS programs by importing the data into AutoCAD Map 3D. You can import the map objects themselves, and the data and display options associated with them. In addition, you can specify an import area to determine which area of the map will be imported, assign incoming objects to existing feature classes, and automatically perform a coordinate conversion on the objects as they are imported.

By exporting a map, you can export data to an external file format. You can export the map objects themselves, and the data associated with them, and specify that AutoCAD Map 3D performs a coordinate conversion on the objects automatically as they are exported.

Use profiles to save your import and export settings in a profile to automate the process of importing and exporting files. You can save and load import profile files (*.ipf*) or export profile files (*.epf*).

The following file formats are supported for both import and export, unless otherwise indicated:

- ArcView ShapeFile (also called ESRI ShapeFile or ESRI Shape)
- ArcInfo Coverages and E00
- GML (Geography Markup Language) version 2
- GML (Geography Markup Language) version 2, Ordnance Survey of Great Britain MasterMap (import only)
- MapInfo MIF/MID
- MapInfo TAB
- MicroStation DGN versions 7 and 8
- SDTS (Spatial Data Transfer Standard) (import only)
- VML (Vector Markup Language) (export only)
- VPF (Vector Product Format) (import only)

See also Other Information Sources.

Importing MapsSetting Import OptionsExporting MapsSetting Export OptionsUsing Reactors with Export and Import EventsUsing IteratorsHandling

Importing Maps

To import an file to an AutoCAD Map 3D drawing, perform the following steps, as shown in the sample code that follows:

- 1 Retrieve the Autodesk Map importer object, an *AcMapIEImporter* singleton instance, by calling the global function *AcMapImporter()*.
- 2 Initialize the importer with *Init()*. (You must call *Init()* before you call any other *AcMapIEImporter* functions.)
Init() requires an *AcMapIEFormat* name that specifies the format of the incoming file.
- 3 Optionally, add reactors to the importer.
- 4 Set the import options.
-or-
Use *LoadIPF()* to load previously saved import settings from a profile (.ipf) file. (You can save the current import options in a profile file with *SaveIPF()*.)
- 5 Call *Import()* to perform the import.
Import results are stored in an *AcMapIE::CImportResults* struct.

For import-export source-code samples, see Import-Export Samples.

```

AcMapIE::ErrCode errCode;
// Retrieve the AutoCAD Map 3D importer object.
AcMapIEImporter* pImporter = AcMapImporter();
// Initialize the importer.
char* pszFormat = "MIF"; // Name of an AcMapIEFormat.
char* pszImpFileName = "C:\\temp\\my_import_file.mif";
errCode = pImporter->Init(pszFormat, pszImpFileName);
if (errCode != AcMapIE::kErr_OK)
{
// Handle the error.
}
// Get an iterator over the layers in the imported file.
AcMapIEInputLayerIterator* pInputLayers;
errCode = pImporter->InputLayerIterator(pInputLayers);
if (errCode != AcMapIE::kErr_OK)
{
// Handle the error.
}
// Iterate over each layer.
for (pInputLayers->Rewind(); !pInputLayers->Done(); pInputLayers->Step())
{
AcMapIEInputLayer* pLayer = NULL;
if(pInputLayers->Get(pLayer) == false)
{
// Handle the error.
}
// Import attribute data from the import file to the
// new object-data table in the Autocad Map drawing.
// Insert code to set the table type and table name
// with AcMapIEInputLayer::SetDataMapping()
// and set the feature class name
// with AcMapIEInputLayer::SetFeatureClassName().
// Set column mappings.
AcMapIEColumnIterator* pColumns = pLayer->ColumnIterator();
if(pColumns)
{
for (pColumns->Rewind(); !pColumns->Done(); pColumns->Step())
{
// Insert code to set column data mappings
// with AcMapIEColumn::SetColumnDataMapping()
// and set column feature-class mappings
// with AcMapIEColumn::SetColumnClassMapping().

```



```

    }
    delete pColumns;
    }
    delete pLayer;
    }
    delete pInputLayers;
    // Perform the import and get the results.
    AcMapIE::CImportResults results;
    bool bUseProgressDialog = false;
    errCode = pImporter->Import(results, bUseProgressDialog);
    if(errCode != AcMapIE::kErr_OK)
    {
        // Handle the error.
    }
    // Process or log the import results, if desired.

```

Back to top

Setting Import Options

When importing a drawing into AutoCAD Map 3D, you can set import options for each incoming layer. *AcMapIEImporter::InputLayerIterator()* retrieves an iterator over all imported layers; each layer is an *AcMapIEInputLayer* instance, named *Name()*. Use the following *AcMapIEInputLayer* functions to set and retrieve layer-level import options:

- Data-mapping table type and name - *DataMapping()/SetDataMapping()*. See also *AcMapIE::ImportDataMapping* enum.
- Feature class - *FeatureClassName()/SetFeatureClassName()*
- Import-layer switch - *ImportFromInputLayerOn()/SetImportFromInputLayerOn()*
- Layer name - *LayerName()/SetLayerName()*. See also *AcMapIE::LayerNameType* enum.
- Point-import mode - *PointToBlockMapping()/SetPointToBlockMapping()*. See also *AcMapIE::PointMappingType* enum.
- Target coordinate system - *TargetCoordSys()/SetTargetCoordSys()*. See also *OriginalCoordSys()*.
- Import-attributes switch - *UseForBlockAttributes()/SetUseForBlockAttributes()*
- Unique keys for imported objects - *UseUniqueKeyField()/SetUseUniqueKeyField()*

On each layer, you can set individual mappings from each incoming column to a target column in AutoCAD Map 3D. *AcMapIEInputLayer::ColumnIterator()* retrieves an iterator over a layer's columns; each column is an *AcMapIEColumn* instance, named *ColumnName()*. You can define two types of column mappings, provided that you already have set the column's data table and feature class with *AcMapIEInputLayer::SetDataMapping()* and *AcMapIEInputLayer::SetFeatureClassName()*:

- Data mapping - *ColumnDataMapping()/SetColumnDataMapping()*.
- Feature-class mapping - *ColumnClassMapping()/SetColumnClassMapping()*. Feature-class mappings are not set by default for any column.

You also can use the following *AcMapIEImporter* functions to set and retrieve high-level import options:

- Audit classified properties - *AuditClassifiedAfterImport()/SetAuditClassifiedAfterImport()*
- Driver options - *DriverOptions()/SetDriverOptions()/InvokeDriverOptionsDialog()*
- Import polygons as closed polylines - *ImportPolygonsAsClosedPolylines()/SetImportPolygonsAsClosedPolylines()*
- Location-window filter - *LocationWindowAndOptions()/SetLocationWindowAndOptions()*. See also *AcMapIE::LocationOption* enum.
- Reactors - *AddReactor()/RemoveReactor()*; see Using Reactors with Export and Import Events

For import-export source-code samples, see Import-Export Samples.

[Back to top](#)

Exporting Maps

To export an AutoCAD Map 3D drawing, perform the following steps, as shown in the sample code that follows:

- 1 Retrieve the Autodesk Map exporter object, an *AcMapIEExporter* singleton instance, by calling the global function *AcMapExporter()*.
- 2 Initialize the exporter with *Init()*. (You must call *Init()* before you call any other *AcMapIEExporter* functions.)

Init() requires an *AcMapIEFormat* name that specifies the target file format. You can use *FormatName()* to retrieve the format name at any time after initialization.

3 Optionally, add reactors to the exporter.

4 Set the export options.

-or-

Use *LoadEPF()* to load previously saved export settings from a profile (.epf) file. (You can save the current export options in a profile file with *SaveEPF()*.)

5 Call *Export()* to perform the export.

Export results are stored in an *AcMapIE::CExportResults* struct.

For import-export source-code samples, see Import-Export Samples.

```
AcMapIE::ErrCode errCode;
// Retrieve the AutoCAD Map 3D exporter object.
AcMapIEExporter* pExporter = AcMapExporter();
// Initialize the exporter.
char* pszFormat = "MIF"; // Name of an AcMapIEFormat.
char* pszExpFileName = "C:\\temp\\my_export_file.mif";
errCode = pExporter->Init(pszFormat, pszExpFileName);
if (errCode != AcMapIE::kErr_OK)
{
    // Handle the error.
}
// Insert code to set filter, data mapping,
// and other <a href="#export_options">export options</a>.
// Perform the export and get the results.
AcMapIE::CExportResults results;
bool bUseProgressDialog = false;
errCode = pExporter->Export(results, bUseProgressDialog);
if (errCode != AcMapIE::kErr_OK)
{
    // Handle the error.
}
// Process or log the export results, if desired.
```

[Back to top](#)

Setting Export Options

Use export options to control which objects in the current drawing are exported by applying a layer filter, feature-class filter, and selection set. (*CountObjects()* counts the number and type of entities to export.) You also can set storage options, driver options, data mappings, and other options. Use the following *AcMapIEXporter* functions to set and retrieve export options:

- Discretization angle - *DiscretizationAngle()/SetDiscretizationAngle()*
- Driver options - *DriverOptions()/SetDriverOptions()/InvokeDriverOptionsDialog()*
- Export closed polylines as polygons -
ClosedPolylinesAsPolygons()/SetClosedPolylinesAsPolygons()
- Feature classes to export - *FeatureClassFilter()/SetFeatureClassFilter()*
- Layers to export - *LayerFilter()/SetLayerFilter()*
- Mapping layers to DGN levels - *LayerLevelMapping()/SetLayerLevelMapping()*
- Polygon topology -
ExportFromPolygonTopology()/SetExportFromPolygonTopology()
- Selection set - *SelectionSet()/SetSelectionSet()* and *ExportAll()/SetExportAll()*
- Source-column and output-column data mappings -
ExportDataMappings()/SetExportDataMappings()
- Storage options - *StorageOpts()/SetStorageOpts()*. See also *AcMapIE::StorageType* enum and *AcMapIE::GeometryType* enum.
- Target coordinate system - *TargetCoordSys()/SetTargetCoordSys()*
- Unique keys for exported objects -
UseUniqueKeyField()/SetUseUniqueKeyField()
- Reactors - *AddReactor()/RemoveReactor()*; see Using Reactors with Export and Import Events

For import-export source-code samples, see Import-Export Samples.

[Back to top](#)

Using Reactors with Export and Import Events

The *AcMapIEXportReactor* and *AcMapIEImportReactor* classes provide callback functions that notify an application immediately of export and import

events. You can use these mechanisms to monitor or control export and import operations by adding reactor instances. Functions are invoked automatically depending on the stage of the operation, as described in the following tables:

| Export reactor function | Invoked |
|-------------------------------|----------------------------------|
| <i>RecordError()</i> | If an error occurs during export |
| <i>RecordExported()</i> | After an entity is exported |
| <i>RecordReadyForExport()</i> | Before an entity is exported |
| Import reactor function | Invoked |
| <i>RecordError()</i> | If an error occurs during import |
| <i>RecordImported()</i> | After an entity is imported |
| <i>RecordReadyForImport()</i> | Before an entity is imported |

You can add or remove export reactors with *AcMapIExportReactor::AddReactor()* or *AcMapIExportReactor::RemoveReactor()*, and add or remove import reactors with *AcMapIImportReactor::AddReactor()* or *AcMapIImportReactor::RemoveReactor()*. To use a reactor, perform the following steps, as shown in the sample code that follows:

- 1 Derive a custom class from *AcMapIExportReactor* or *AcMapIImportReactor*.
- 2 Implement events by overriding the virtual functions that you need.
- 3 Create an instance of the custom reactor.
- 4 Add the instance so that it becomes active.
- 5 Write some export or import reactor code.
- 6 Remove the reactor and delete it.

For import-export source-code samples, see [Import-Export Samples](#).

```
// Derive a custom class from AcMapIExportReactor.
class AcMapIEMyExportReactor : public AcMapIExportReactor
{
// Override virtual functions for the desired export events.
} ;
// Create an instance of the custom reactor.
AcMapIEMyExportReactor* pMyReactor = new AcMapIEMyExportReactor;
// Add the custom reactor.
AcMapIExporter().AddReactor(pMyReactor);
// Insert export reactor code here.
// Remove the reactor and delete it.
AcMapIExporter().RemoveReactor(pMyReactor);
delete pMyReactor;
```

[Back to top](#)

Using Iterators

The following table lists the iterator classes, which provide iterators over collections of objects that import-export functions return or take. The *AcMapIExpressionTargetIterator* and *AcMapINameValueIterator* classes allow you to modify the iterator's underlying collection by adding, updating, and deleting elements, whereas the other classes iterate over fixed collections. The global functions *AcMapExportFormatIterator()* and *AcMapImportFormatIterator()* return the export-format and import-format iterators, respectively.

| Class | Iterates over a collection of |
|---------------------------------------|-----------------------------------|
| <i>AcMapIColumnIterator</i> | <i>AcMapIColumn</i> instances |
| <i>AcMapIExpressionTargetIterator</i> | Expression-target pairs |
| <i>AcMapIFormatIterator</i> | <i>AcMapIFormat</i> instances |
| <i>AcMapIInputLayerIterator</i> | <i>AcMapIInputLayer</i> instances |
| <i>AcMapINameValueIterator</i> | Name-value pairs |

For import-export source-code samples, see [Import-Export Samples](#).

[Back to top](#)

Handling Errors

Many functions in the various import-export classes return an *AcMapIE::ErrCode* error code. When a particular function returns an error code, read that function's documentation for function-specific error conditions rather than relying on only the generic error descriptions in the *AcMapIE::ErrCode* documentation.

[Back to top](#)

Other Information Sources

- For more information about importing and exporting maps in AutoCAD Map 3D, choose Help > AutoCAD Map 3D Help > Contents tab (or press F1), and then navigate to Using AutoCAD Map 3D (by feature) > Importing and Exporting Maps.
- For an import-export tutorial in AutoCAD Map 3D, choose Help > Tutorials > Contents tab, and then choose "Importing and Exporting Data".

[Back to top](#)

Import-Export Samples

To view code samples of import-export functions, open the Samples folder in your AutoCAD Map 3D ObjectARX installation and navigate to Map Samples\ImportExport.

[Back to top](#)

Import-Export Classes, Namespaces, and Globals

To view the import-export classes, namespaces, and globals, click the following links:

*AcMapIEColumn ClassAcMapIEColumnIterator ClassAcMapIEExporter
ClassAcMapIEExportReactor ClassAcMapIEExpressionTargetIterator
ClassAcMapIEFormat ClassAcMapIEFormatIterator ClassAcMapIEImporter
ClassAcMapIEImportReactor ClassAcMapIEInputLayer
ClassAcMapIEInputLayerIterator ClassAcMapIENamespaceValueIterator ClassAcMapIE
NamespaceAcMapExporter Global FunctionAcMapExportFormatIterator Global
FunctionAcMapImporter Global FunctionAcMapImportFormatIterator Global Function*

[Back to top](#)

Oracle Spatial Data

18

This topic describes the latest implementation of the Oracle Spatial API.

In this chapter

- [Oracle Spatial Data Detail](#)

Oracle Spatial Data Detail

Class names in this API begin with "AcMapOSE". Use it for all new development that involves Oracle Spatial access, or consider using the FDO Enabler API, a still later implementation, which provides access to Oracle Spatial databases and other database formats as well.

Although the earlier implementation of the Oracle Spatial API remains in place, and existing code that is based on it is still valid, it is deprecated. Class names in the earlier Oracle Spatial API begin with "AcMapOracle". The AcMapOracle classes are described in the AutoCAD Map 3D ObjectARX Reference, but they are not discussed in the Developer's Guide.

Managing the connection [Managing reactors](#) (page 99) [Exporting data](#) (page 99)

[Querying and importing data](#) (page 100)

[Oracle and AutoCAD IDs](#) (page 100)

[Getting corresponding IDs](#) (page 101)

[Getting other information](#) (page 101)

[Filtering objects](#) (page 101)

[Error processing](#) (page 102)

[Other information sources](#) (page 102)

[Code samples](#) (page 102)

[Classes](#) (page 102)

Managing the connection

Before you can do anything else, you must get the AcMapOSEConnection object.

So long as AutoCAD Map 3D is running, there is always an AcMapOSEConnection object, even if no connection is currently in effect. The object is instantiated automatically when an AutoCAD Map 3D session opens, and is destroyed automatically when the session closes.

Because the AcMapOSEConnection object is unique within a session, there can never be more than one connection in effect at a time. To connect, disconnect, or change the current connection, you modify this unique object. You can modify it (or assess its state) either through the the UI or the API. It's the same object either way.

AcMapOSEConnection class

AcMapOSEGetConnection global function

[Connecting to an Oracle Spatial Database](#) (page 106)

Managing reactors

In addition to functions for modifying or assessing its state, the *AcMapOSEConnection* object has functions for managing reactors. For example, to monitor and react to connection events, subclass a custom reactor from *AcMapOSEConnectionReactor*, and then add an instance of it to your application using *AcMapOSEConnection::AddConnectionReactor()*. Similarly, you can create and add reactors for import and export events.

AcMapOSEConnection class

AcMapOSEConnectionReactor class

AcMapOSEExportReactor class

AcMapOSEImportReactor class

[Connecting to an Oracle Spatial Database](#) (page 106)

Exporting data

To add new records to the Oracle database, or to update records that were imported and then edited by adding, changing, or deleting data, use an *AcMapOSEExport* object. To set export options and specify which features will be exported, use *AcMapOSEExport::Init()*.

Note that an *AcMapOSEExport* object has two functions for exporting. *ExportObjects()* exports objects listed in an *AcDbObjectIdArray*. *ExportObjectsAll()* exports all objects in the drawing database. Both functions export only features specified in the *vFeaturesNames* argument of *AcMapOSEExport::Init()*, and both functions are subject to export options specified by the *nOptions* argument of *AcMapOSEExport::Init()*. Option values are defined in the *AcMapOSEExport::EExportOptions* enumeration.

To monitor and react to export events, use a custom subclass of *AcMapOSEExportReactor*.

Note that, for the sake of performance, the export operation does not process a set of objects one by one. Rather, it collects the objects with their associated data in a cache and then bulk-processes them. The complement of *AcMapOSEExportReactor* functions reflects this two-step process.

AcMapOSEExport class

AcMapOSEExport::EExportOptions enumeration

AcMapOSEExportReactor class

[Exporting to an Oracle Spatial Database](#) (page 110)

Querying and importing data

To import objects from an Oracle database to a project drawing, first use an `AcMapOSEQuery` object to specify conditions for the objects to import, and then use an `AcMapOSEImport` object for the import itself.

You can initialize the `AcMapOSEQuery` object with

- The current import query, as defined in the Import dialog box in the user interface.
To see this dialog, use the `MAPOSERREAD` command.
- An import query loaded from the Oracle database after saving one there previously.
- An explicit set of conditions.

After initializing the `AcMapOSEQuery` object, you can convert its query to SQL format for viewing purposes.

To monitor and react to import events, use a custom subclass of `AcMapOSEImportReactor`.

AcMapOSEQuery class


AcMapOSEImport class

AcMapOSEImportReactor class

[Importing from an Oracle Spatial Database](#) (page 114)


Oracle and AutoCAD IDs

In Oracle databases, entities have Oracle IDs (`OValue`). In AutoCAD databases, they have AutoCAD IDs (`AcDbObjectId`). When drawing objects are imported from an Oracle database to a project drawing (`AcMapProject` object), AutoCAD Map 3D assigns them AutoCAD IDs, but keeps track their corresponding Oracle IDs. Note however, that this information is discarded without saving when the drawing closes, which means that the entire process of updating a set of Oracle records — importing, editing, exporting — must run from start to finish on a continuously open drawing.

For information about getting corresponding IDs, click  .

Getting corresponding IDs

If you have imported a set of records from an Oracle database, and you need to know explicitly which record is associated with a given drawing object (entity), or which entity with a given record, you can use an `AcMapOSEObject` object to find out. After initializing such an object with an entity's AutoCAD ID, you can get its Oracle ID, and vice-versa, provided that the drawing has remained open since the entity was imported. If the drawing has not remained open, imported entities lose their imported status, in which case, instead of the `AcMapOSEObject` object giving you an Oracle ID in exchange for an entity's AutoCAD ID, it gives you 0 (an invalid key value), as it does for any entity that is not an imported one.

For information about Oracle and AutoCAD IDs, click  .

Getting other information

You can use `AcMapOSEObject` functions to get other information about a queried object besides its AutoCAD or Oracle ID. For example, its `EditSet` status, in or out.

AcMapOSEObject class

[Getting Corresponding IDs](#) (page 116)

Filtering objects

To filter new objects from a set of drawing objects, use `AcMapOSEProject::FilterNewObjects()`. In addition, you can constrain the result by feature or edit-set status (in or out).

Likewise, to filter queried objects, use `AcMapOSEProject::FilterQueriedObjects()`. In addition, you can constrain the result by feature or edit-set status (in or out). Queried objects are delivered in three subsets by edit status: erased, modified, and unchanged.

AcMapOSEProject class

[Filtering Objects](#) (page 120)

Error processing

When an AutoCAD Map 3D operation fails, the error message and error code are pushed to the error stack (AcMapErrorStack). In the event of an error, check the stack to discover what went wrong and take appropriate action.

Other information sources

For more information about AutoCAD Map 3D and Oracle Spatial data, refer to

- *User Interface Help for the Polygon and Advanced Oracle Extension to AutoCAD Map 3D*— In the Autodesk Map application, click the question mark icon in the Polygon And Advanced Oracle Extension toolbar.

Code samples

To view code samples, click links below.

[Connecting to an Oracle Spatial Database](#) (page 106)

[Exporting to an Oracle Spatial Database](#) (page 110)

[Importing from an Oracle Spatial Database](#) (page 114)

[Subclassing Custom Reactors](#) (page 109)

[Getting Corresponding IDs](#) (page 116)

[Filtering Objects](#) (page 120)

The following topics describe sample ObjectARX projects. The project folders are under Map Samples\Oracle Spatial in your AutoCAD Map 3D ObjectARX installation.

[Storing Block Attribute Positions in an Oracle Spatial Database](#) (page 129)

[Storing Block Definitions in an Oracle Spatial Database](#) (page 128)

[Importing From an Oracle Spatial Database](#) (page 126)

Note The sample projects that are located in Map Samples\Oracle are for the earlier Oracle Spatial implementation, which is still supported, but is now deprecated.

Classes

To view Oracle Spatial data classes, click links below.

[*AcMapOSEConnection*](#)

AcMapOSEConnectionReactor

AcMapOSEExport

AcMapOSEExportReactor

AcMapOSEImport

AcMapOSEImportReactor

AcMapOSEObject

AcMapOSEProject

AcMapOSEQuery

Oracle Spatial Samples

19

The Oracle Spatial samples.

Connecting to an Oracle Spatial Database
Subclassing Custom Reactors
Exporting to an Oracle Spatial Database
Importing from an Oracle Spatial Database
Getting Corresponding IDs
Filtering Objects

In this chapter

- [Connecting to an Oracle Spatial Database](#)
- [Subclassing Custom Reactors](#)
- [Exporting to an Oracle Spatial Database](#)
- [Importing from an Oracle Spatial Database](#)
- [Getting Corresponding IDs](#)
- [Filtering Objects](#)

Connecting to an Oracle Spatial Database

The following code sample illustrates connecting to an Oracle database and adding custom reactors.

Custom reactor declarations are in `MyMapOracleReactors.h`, one of the files included at the beginning of the sample. The "Subclassing Custom Reactors" sample shows what such a file would contain.

[Managing the connection](#) (page 98) [Subclassing Custom Reactors \(Sample\)](#) [Code samples](#) (page 102)

```

#include "StdAfx.h"
#include "StdArx.h"
#include "AdMapOracleConnection.h"
#include "MyMapOracleReactors.h"    // Custom reactors
BOOL ConnectToOracle()
{
    // Get connection pointer
    AcMapOSEConnection *pConnection = AcMapOSEGetConnection();
    // Initialize reactors
    MyConnectionReactor *pConnectReactor = new MyConnectionReactor();
    MyExportReactor *pExportReactor = new MyExportReactor();
    MyImportReactor *pImportReactor = new MyImportReactor();
    // Add reactors to connection object
    pConnection->AddConnectionReactor(pConnectReactor);
    pConnection->AddExportReactor(pExportReactor);
    pConnection->AddImportReactor(pImportReactor);
    // Make the connection
    BOOL bConnect = FALSE;
    if(!pConnection->IsConnected())
    {
        bConnect = pConnection->Connect("Scott", "TestDB", "Scott",
            "Tiger", false);
    }
    else
    {
        acutPrintf("Already connected to Oracle!");
        return FALSE;
    }
    // Check for valid connection using various diagnostic functions
    // Check if schema is valid()
    if(pConnection->IsSchemaValid())
    {
        acutPrintf("\nSchema is valid for this connection\n");
    }
    else
    {
        acutPrintf("\nSchema is not valid\n");
    }
    // Get the latest state of the Oracle database if it has been
    // changed since the connection was made

```

```

if(pConnection->RefreshSchema())
{
    acutPrintf("\nSchema refreshed\n");
}
else
{
    acutPrintf("\nError refreshing schema\n");
}
// Get a list of the feature names in the current schema
std::vector<std::string> vFeatureNames;
if(pConnection->Features(vFeatureNames))
{
    acutPrintf("\nGot feature names\n");
}
else
{
    acutPrintf("\nError getting feature names\n");
}
// Get the service name
char *pService = 0;
pService = new char[80];
strcpy(pService, pConnection->Service());
acutPrintf("\nService is %s\n",pService);
delete [] pService;
// Get the schema name
char *pSchema = 0;
pSchema = new char[80];
strcpy(pSchema,pConnection->Schema());
acutPrintf("\nSchema is %s\n",pSchema);
delete [] pSchema;
// Get the user name
char *pUserName = 0;
pUserName = new char[80];
strcpy(pUserName,pConnection->UserName());
acutPrintf("\nUserName is %s\n",pUserName);
delete [] pUserName;
// Break the connection
if(pConnection->Disconnect())
    acutPrintf("\nDisconnected from Oracle\n");
else
    acutPrintf("\nError disconnecting from Oracle\n");
// Remove reactors from connection interface
pConnection->RemoveConnectionReactor(pConnectReactor);

```

```
pConnection->RemoveExportReactor (pExportReactor) ;  
pConnection->RemoveImportReactor (pImportReactor) ;  
delete pConnectReactor  
delete pExportReactor  
delete pImportReactor  
}
```

Subclassing Custom Reactors

The following sample code illustrates subclassing custom reactors from AcMapOSE[xx]Reactor classes.

Classes and functions are declared, but function definitions, which would be highly implementation specific, are not shown. This is an example of what MyMapOracleReactors.h, one of the include files in the "Connecting to an Oracle Database" sample, would contain.

[Managing reactors](#) (page 99)

[Connecting to an Oracle Spatial Database](#) (page 106)

[Code samples](#) (page 102)

```

#include "AdMapOracleReactor.h"
class MyConnectionReactor : public AcMapOSEConnectionReactor
{
public:
    MyConnectionReactor();
    virtual ~MyConnectionReactor();
    virtual void Connected();
    virtual void Disconnected();
    virtual void BeforeConnect();
    virtual void BeforeDisconnect();
};
class MyExportReactor : public AcMapOSEExportReactor
{
public:
    MyExportReactor();
    virtual ~MyExportReactor();
    virtual void BeforeObjectCached(AcDbEntity *);
    virtual void ObjectCached(AcDbEntity *,OValue);
    virtual void ObjectRejected(AcDbEntity *);
    virtual void BeforeObjectsExported(std::vector<OValue> &);
    virtual void ObjectsExported(std::vector<OValue> &);
};
class MyImportReactor : public AcMapOSEImportReactor
{
public:
    MyImportReactor();
    virtual ~MyImportReactor();
    virtual void BeforeRecordImport(const ODynaset &);
    virtual void RecordImported(const ODynaset &,AcDbEntity *);
    virtual void RecordRejected(const ODynaset &);
};

```

Exporting to an Oracle Spatial Database

The following code sample illustrates exporting spatial data from a project drawing to an Oracle database.

NOTE The sample assumes an open project drawing containing some objects. It also assumes that the connection object is actually connected to a database. Click "Connecting to an Oracle Database" for sample code.

Connecting to an Oracle Spatial Database (Sample)[Exporting data](#) (page 99)[Code samples](#) (page 102)

```

#include "StdAfx.h"
#include "StdArx.h"
#include "AdMapOracleConnection.h"
#include "AdMapOracleExport.h"
BOOL ExportToOracle()
{
    // Get connection pointer
    AcMapOSEConnection *pConnection = AcMapOracleGetConnection();
    // Declare export interface
    AcMapOSEExport *pExport = new AcMapOSEExport(pConnection);
    // Note: Before calling export functions, initialize the
    // export interface to specify export options and which
    // features to export
    // Export Option 1 - Export only new objects and erase
    // exported objects from the drawing
    // Empty feature vector means export all features in the
    // drawing database when you call export functions
    std::vector<std::string> vFeatureNames;
    // Initialize
    if(pExport->Init(vFeatureNames, kRemoveExported))
    {
        acutPrintf("\nInit() successful\n");
        // Export
        AcDbDatabase *pDwg;
        // Get a valid drawing database reference for *pDwg
        // ... (add code here)
        if(pExport->ExportObjectsAll(pDwg))
        {
            acutPrintf("\nExport successful\n");
        }
        else
        {
            acutPrintf("\nExport failed\n");
        }
    }
    else
    {
        acutPrintf("\nExport->Init() failed\n");
    }
    // Export Option 2 - Export selected features, update
    // modified objects in Oracle, and delete erased objects
    // from Oracle
    vFeatureNames.push_back("Feature1");

```



```

vFeatureNames.push_back("Feature2");
// Initialize
if(pExport->Init(vFeatureNames,
AcMapOSEExport::kUpdateModified |
AcMapOSEExport::kUpdateErased |
AcMapOSEExport::kRemoveExported))
{
    acutPrintf("\nInit() successful\n");
    // Export
    if(pExport->ExportObjectsAll(pDwg))
    {
        acutPrintf("\nExport successful\n");
    }
    else
    {
        acutPrintf("\nExport failed\n");
    }
}
else
{
    acutPrintf("\nExport->Init() failed\n");
}
// Export Option 3 - Export a specific set of objects
// Initialize - see initializing code samples above
// Export
AcDbObjectIdArray idArray;
// Populate idArray with a set of objects to export by
// manually selecting or iterating through the drawing
// database
// ... (add code to populate idArray)
if(pExport->ExportObjects(idArray);
{
    acutPrintf("\nExport successful\n");
}
else
{
    acutPrintf("\nExport failed\n");
}
delete pExport;
}

```

Importing from an Oracle Spatial Database

The following sample illustrates importing spatial data from an Oracle database to a project drawing.

The sample is in two parts. First, it defines a query to specify a condition for the objects to import, and then it imports them.

NOTE The sample assumes that there is an open project drawing, and that an import query has been defined already through the Import dialog box in the UI (use the MAPOSERead command). It also assumes that the connection object is actually connected to a database. Click "Connecting to an Oracle Database" for sample code.

[Connecting to an Oracle Spatial Database](#) (page 106)

[Querying and importing data](#) (page 100)

[Code samples](#) (page 102)

```

#include "StdAfx.h"
#include "StdArx.h"
#include "AdMapOracleConnection.h"
#include "AdMapOracleQuery.h"
#include "AdMapOracleImport.h"
BOOL ImportFromOracle()
{
    // Define Query
    // Get connection pointer
    AcMapOSEConnection *pConnection = AcMapOSEGetConnection();
    // Declare query interface
    AcMapOSEQuery *pQuery = new AcMapOSEQuery(pConnection);
    // Initialize query interface with the current import query
    // (defined through the user interface) of an open project
    // drawing; in this case, the current project drawing
    pQuery->InitWithCurrent(
        acdbHostApplicationServices()->workingDatabase());
    // Or initialize with a NULL database, which has the same
    // effect as the previous call
    pQuery->InitWithCurrent();
    // Or initialize with specific condition(s)
    // Empty vector of features means query all features in the
    // Oracle database
    std::vector<std::string> vFeatureNames;
    pQuery->AddWhereConditionInFeatures(
        vFeatureNames,
        "AdMapEntityType IS NOT NULL");
    // You can clear the query with pQuery->Clear(),
    // but not right now; we still need it
    // Check the query with ConvertToSql()
    char *psql = pQuery->ConvertToSql();
    // Save the query to the Oracle database
    pQuery->Save("MyQuery");
    // Load the saved query into another query object
    AcMapOSEQuery *pNewQuery = new AcMapOSEQuery(pConnection);
    pNewQuery->Load("MyQuery");
    // Compare old and new queries
    char *pNewSql = pNewQuery->ConvertToSql();
    if(strcmp(pSql,pNewSql) == 0)
        acutPrintf("Query Load/Save works!\n");
    else
        acutPrintf("Query Load/Save failed!\n");
    // Import Data

```

```

AcMapOSEImport *pImport = new AcMapOSEImport(pConnection);
// Use query defined above to import data
if (pImport->Import(pQuery))
    acutPrintf("\n Import successful\n");
else
    acutPrintf("\n Import failed\n");
delete pQuery;
delete pImport;
}

```

Getting Corresponding IDs

The following sample demonstrates getting an entity's Oracle ID if its AutoCAD ID is known, and vice versa.

It also demonstrates that round trips with corresponding IDs are reliable — that if you use an AutoCAD ID to get an Oracle ID, and then use the Oracle ID to get an AutoCAD ID, the two AutoCAD IDs are the same.

NOTE The sample assumes an open project drawing containing imported entities. It also assumes that the connection object is actually connected to a database. Click "Connecting to an Oracle Database" for sample code.

[Connecting to an Oracle Spatial Database](#) (page 106) [Oracle and AutoCAD IDs](#) (page 100) [Getting corresponding IDs](#) (page 101) [Code samples](#) (page 102)

```

#include "StdAfx.h"
#include "StdArx.h"
#include "AdMapOracleConnection.h"
#include "AdMapOracleIdentification.h"
BOOL Identification()
{
    // Get connection pointer
    AcMapOSEConnection *pConnection = AcMapOSEGetConnection();
    // Declare identification object
    AcMapOSEObject *pId = new AcMapOSEObject(pConnection);
    AcDbObjectId AcadId;
    AcDbEntity *pEntity;
    ads_name en;
    ads_point pt;
    OValue OracleID;
    char pBuf[100];
    // Get a drawing object (entity) from the user
    if(acedEntSel("\nSelect an entity: ", en , pt) == RTNORM)
    {
        // Get the entity's AutoCAD ID
        acdbGetObjectID(AcadId, en);
        // Get the entity's handle and print it to the AutoCAD Map
        3D text window
        if (Acad::eOk == acdbOpenAcDbEntity( pEntity, AcadId,
        AcDb::kForRead ))
        {
            AcadId.handle().getIntoAsciiBuffer(pBuf);
            acutPrintf("\nAcad handle sel:%s",pBuf);
            pEntity->close();
        }
        // Initialize identification object with AutoCAD ID
        bInit = pId->Init(AcadId);
        // Get the entity's corresponding Oracle ID
        OracleID = pId->GetOracleID();
        // Again initialize identification object, now with Oracle
        ID
        bInit = pId->Init(OracleID);
        // Get the entity's corresponding AutoCAD ID
        AcadId = pId->GetAcadID();
        // Get the entity's handle and print it to the AutoCAD Map
        3D text window,
        // and note that it is the same entity as before
    }
}

```

```

if (Acad::eOk == AcDbOpenAcDbEntity( pEntity, AcadId,
AcDb::kForRead ))
{
    AcadId.handle().getIntoAsciiBuffer(pBuf);
    acutPrintf("\nAcad handle sel:%s",pBuf);
    pEntity->close();
}
// You can get other information about this entity besides
its IDs
// FeatureName()
char *pName;
strcpy(pName,pId->FeatureName());
acutPrintf("\nFeatureName = %s\n",pName);
// IsInEditSet()
if(pId->IsInEditSet())
{
    acutPrintf("\nObject is locked\n");
}
else
{
    acutPrintf("\nObject is not locked\n");
}
// IsModified()
if(pId->IsModified())
{
    acutPrintf("\nObject has been modified\n");
}
else
{
    acutPrintf("\nObject has not been modified\n");
}
// IsErased()
if(pId->IsErased())
{
    acutPrintf("\nObject has been erased\n");
}
else
{
    acutPrintf("\nObject has not been erased\n");
}
// AddToEditSet()
if(pId->AddToEditSet())
{

```

```

        acutPrintf("\nObject added to EditSet\n");
    }
    else
    {
        acutPrintf("\nObject not added to EditSet\n");
    }
    // RemoveFromEditSet()
    if(pId->removeFromEditSet())
    {
        acutPrintf("\nObject removed from EditSet\n");
    }
    else
    {
        acutPrintf("\nObjects not removed from EditSet\n");
    }
    // Version()
    unsigned long ulVersion;
    ulVeresion = pId->Version();
    // IsUpToDate()
    if(pId->IsUpToDate())
    {
        acutPrintf("\nObject is up to date\n");
    }
    else
    {
        acutPrintf("\nObject has been modified since importing
        it\n");
    }
    // WhoHasIt()
    unsigned long ulUserId;
    std::string strNtuser, strDbUser, strMapUser, strComputer,
        strLoginTime;
    if(pId->WhoHasIt(
        ulUserId,
        strNtUser,
        strDbUser,
        strMapUser,
        strComputer,
        strLoginTime))
    {

```

```

        acutPrintf("\nUserId   = %ul\n",ulUserId);
        acutPrintf("\nNtUser   = %s\n",strNtUser.data());
        acutPrintf("\nDbuser   = %s\n",strDbUser.data());
        acutPrintf("\nMapUser   = %s\n",strMapUser.data());
        acutPrintf("\nComputer = %s\n",strcomputerr.data());
        acutPrintf("\nLoginTime = %s\n",strComputer.data());
    }
    else
    {
        acutPrintf("\nObject is not locked\n");
    }
} // if(acedEntSel("\nSelect an entity: ", en , pt) == RTNORM)
acadSSFree(en);
delete pId;
}

```

Filtering Objects

The following code sample illustrates filtering queried and new drawing objects, and adding and removing objects from the EditSet.

[Filtering objects](#) (page 101)

[Code samples](#) (page 102)


```

#include "StdAfx.h"
#include "StdArx.h"
#include "AdMapOracleConnection.h"
#include "AdMapOracleProject.h"
BOOL FilterProjectObjects()
{
    // Get connection pointer
    AcMapOSEConnection *pConnection = AcMapOSEGetConnection();
    // Declare project interface
    AcMapOSEProject *pProject = new AcMapOSEProject(pConnection);
    // Initialize project interface with a drawing database
    if(pProject->Init(
        acdbHostApplicationServices()->workingDatabase()))
    {
        acutPrintf("\nProject interface initialized\n");
    }
    else
    {
        acutPrintf("\nError initializing project interface\n");
    }
    // Filter queried objects
    // Empty vector of features means filter all features in
    // the drawing database
    std::vector<std::string> vFeatureNames;
    // Similarly empty input array of objectIds means filter
    // all objects in the drawing database
    AcDbObjectIdArray arrInput, arrErased;
    AcDbObjectIdArray arrModified, arrUnchanged, arrFilteredOut;
    if(pProject->FilterQueriedObjects(
        vFeatureNames,
        arrInput,
        arrErased,
        arrModified,
        arrUnchanged,
        arrFilteredOut,
        AcMapOSEProject::kInEditSet | AcMapOSEProject::kNotInEditSet))
    {
        acutPrintf("\n Input array   = %d\n",arrInput.length());
        acutPrintf("\n Erased array   = %d\n",arrErased.length());
        acutPrintf("\n Modified array = %d\n",arrModified.length());
        acutPrintf("\n Unchanged array = %d\n",arrUn
            changed.length());
    }
}

```

```

        acutPrintf("\n Filter array  = %d\n",arr
        rFilteredOut.length());
    } else {
        acutPrintf("\nFilterQueriedObjects() returned false\n");
    }
    // Filter new objects
    // Filter these features
    vFeatureNames.push_back("Feature1");
    vFeatureNames.push_back("Feature2");
    // Empty input array of objectIds means filter all objects
    // in the drawing database
    AcDbObjectIdArray arrInput, arrNew, arrFilteredOut;
    if(pProject->FilterNewObjects(
    vFeatureNames,
    arrInput,
    arrNew,
    arrFilteredOut,
    AcMapOSEProject::kInEditSet | AcMapOSEProject::kNotInEditSet))
    {
        acutPrintf("\n Input array = %d\n",arrInput.length());
        acutPrintf("\n New array  = %d\n",arrErased.length());
        acutPrintf("\n Filter array = %d\n",arrFilteredOut.length());
    } else {
        acutPrintf("\nFilterNewObjects() returned false\n");
    }
    // Add objects to EditSet
    // Populate arrAcadIds with drawing objects by manually
    // selecting or iterating through drawing database;
    // arrFilteredOut reports objects that could not be
    // added to the EditSet
    AcDbObjectIdArray arrAcadIds, arrFilteredOut;
    // ... (add code to populate arrAcadIds)
    if(pProject->AddToEditSet(arrAcadIds, arrFilteredOut))
    {
        acutPrintf("\nObjects added to EditSet\n");
    }
    else
    {
        acutPrintf("\nError adding objects to EditSet\n");
    }
    // Remove objects from EditSet
    // Populate arrAcadIds with drawing objects by manually
    // selecting or iterating through drawing database;

```

```

// arrFilteredOut reports objects that could not be
// removed from the EditSet
AcDbObjectIdArray arrAcadIds, arrFilteredOut;
// ... (add code to populate arrAcadIds)
if(pProject->RemoveFromEditSet(arrAcadIds, arrFilteredOut))
{
    acutPrintf("\nObjects removed from EditSet\n");
}
else
{
    acutPrintf("\nError removing objects from EditSet\n");
}
delete pProject;
}

```


Oracle Spatial Sample Projects

The Oracle Spatial sample projects.

Importing From an Oracle Spatial Database Storing Block

Definitions in an Oracle Spatial Database Storing Block

Attribute Positions in an Oracle Spatial Database

The project folders are in the Map Samples\Oracle Spatial folder in AutoCAD Map 3D ObjectARX installations.

Note The sample projects that are in Map Samples\Oracle are for the earlier Oracle Spatial implementation, which is still supported, but is now deprecated.

In this chapter

- [Importing From an Oracle Spatial Database](#)
- [Storing Block Definitions in an Oracle Spatial Database](#)
- [Storing Block Attribute Positions in an Oracle Spatial Database](#)

Importing From an Oracle Spatial Database

Oracle Spatial Data (Overview) [Code samples](#) (page 102)

The "Importing From an Oracle Spatial Database" sample is an ObjectARX project located in the Map Samples\AcMapFlatOrclQuery folder in AutoCAD Map 3D ObjectARX installations.

Commands Implemented

The project creates an rx module which exposes the following commands.

- ORAAPICONNECT — for connecting to the Oracle database.
- ORAAPIIMPORT — for reviewing, composing, or running queries
- ORAAPIDISCONNECT — for disconnecting.

Import dialog box

The ORAAPIIMPORT command opens the Import dialog box, which includes the following elements, among others.

- Condition Samples — A list of conditions read from SqlWhereClauses.txt on the local machine. Click a condition to view or change it.
- Connect — Click to connect to the Oracle database if not connected already.
- Features — When connected, a list of features in the current schema. Click a feature and then click Get Aliases to display a list of aliases and corresponding names for the feature's tables. See "Table Aliases" below.

Table aliases

To compose a condition for a given feature, you have to specify which table to use if the feature has more than one, and you have to refer to this table by its alias. If there is only one table, its alias is "Table0" and specifying it is optional. The following condition uses a table alias.

```
Select *  
From RIVERS Table0  
Where Table.DEPTH > 5;
```

To get table aliases when there is more than one table for a feature, click Get Aliases in the Import dialog.

Column types

To write a condition, you may need the type of a given column. To get column types, click Describe Table in the Import dialog box to get information about any table in the current schema.

To create a query

- 1 Select one or more features in the Features list box.
- 2 Type a WHERE clause in the edit control below the Condition Samples list.
The WHERE clause is applied to each of the selected features as it is typed, without checking to see if it is valid. If the condition is not valid — for example, if it references a table that does not belong to the feature — the query fails when it executes.
- 3 Click View Sql Statement to see the corresponding SQL statement.
If more than one feature is selected, there will be a corresponding number of SQL statements.
- 4 Click Save to save the query for future use.
- 5 Click Import to run the query and import objects.

To view a saved query

- Click Load.
This action loads a query from the table ADMPIMPORTSETTINGS in the current schema and displays its SQL statement in a separate dialog box. You can't execute the query, but you can view it, and you can copy parts of it to use in other queries.

To run a query

- Click Import.

Note

Keep in mind that the purpose of this application is to instruct. It lacks extensive error handling. Use it with caution.

Storing Block Definitions in an Oracle Spatial Database

Oracle Spatial Data (Overview) [Code samples](#) (page 102)

The "Storing Blocks" sample is an ObjectARX project located in the Map Samples\AcMapFlatOrclBlock folder in AutoCAD Map 3D ObjectARX installations.

Classes highlighted

It highlights the following Oracle Spatial classes.

AcMapOSEExportReactor

The following classes are included also, but their use is less extensive.

AcMapOSEConnection

Commands implemented

The project creates an rx module which exposes the following commands.

- SAVEBLOCKTOORACLE installs custom export and connection reactors. These reactors enable storing block definitions in an Oracle database.
- LOADBLOCKSFROMORACLE reads block definitions from an Oracle database and places them in the table record of the active project drawing. This command should be executed to set block definitions in place before importing block references.
- STOPSAVEBLOCKTOORACLE removes the custom reactors that were added by SAVEBLOCKTOORACLE.

Note

Keep in mind that the purpose of this application is to instruct. Use it with caution. It lacks extensive error handling, and it may bog down when the data set is large.

Storing Block Attribute Positions in an Oracle Spatial Database

Oracle Spatial Data (Overview) [Code samples](#) (page 102)

The "Storing Block Attribute Positions" sample is an ObjectARX project located in Map Samples\AcMapFlatOrclAttrPos in AutoCAD Map 3D ObjectARX installations.

Classes Highlighted

It highlights the following Oracle Spatial classes.

AcMapOSEConnection AcMapOSEImportReactor AcMapOSEExportReactor
AcMapOSEObject

The following classes are included also, but their use is less extensive.

AcMapOSEImport AcMapOSEExport AcMapOSEQuery
AcMapOSEConnectionReactor

Commands implemented

The project creates an rx module which lets the user change attribute positions in a project drawing and preserve these changes in an Oracle database. It exposes the following commands.

- APEXPORT exports the active project drawing to an Oracle database, including information about attribute positions.
- APIMPORT imports Oracle Spatial data to the active project drawing, restoring attributes to their original positions.

Note

The sample assumes that features are already defined completely using our MAPOSEADMIN command.

Keep in mind that the purpose of this application is to instruct. Use it with caution. It lacks extensive error handling, and it may bog down when the data set is large.

Topology

21

An AutoCAD Map 3D topology is a set of objects and the object data that defines the relationships between the objects.

In this chapter

- [Topology Detail](#)

Topology Detail

A *node topology* defines the interrelation of nodes (point objects). Node topologies often are used in conjunction with other topologies in analysis. Examples of node topologies include street lights, city-maintained trees, or drill holes for core samples. A *network topology* considers the interconnection of links (lines) forming a linear network. Links can connect nodes. Examples of network topologies include a street network and a water-distribution application that traces the flow of water from a pumping station to residences. A *polygon topology* defines polygons that represent enclosed areas such as land parcels and census tracts. A single link defines the common boundary between adjacent areas. A polygon topology can be used for tax assessment and land planning in which parcels of land are represented by polygons. Polygon topologies can represent political boundaries, such as voting districts, city, state, or provincial boundaries, special districts, and school districts.

With topologies, you can perform spatial analyses such as:

- Trace through network topologies (shortest-path traces, best-route analysis, and flood traces)
- Find the area within a certain distance of map features (by creating buffers)
- Dissolve and overlay polygon topologies
- Determine conditions of adjacency (what is next to what), containment (what is enclosed by what), and proximity (how close something is to something else)

Topology information is stored as object data on each element that makes up the topology. This data can be saved as part of the current map, or saved back to a source drawing. Because topology is definable for a map, identifiers used to store the topology are unique to the map. Topology in each drawing must be separate and unique. Autodesk Map does not support topology data that spans several drawing files (such as tiled maps) unless they are combined in a project.

You must create centroids for mpolygons and closed polylines before building a topology with them.

See [Creating Centroids](#).

You must clean drawing objects before building a topology with them.

See [Drawing Cleanup](#).

Creating and Managing Topologies

AcMapTopologyAcMapTopologyManager

- Close a topology - *Close()*
- Create an instance of topology - *AcMapTopology()*
- Create a fully specified topology - *Create()* (*two forms*). See also *ETopologyType* enum and *ECreateOptions* enum.
Prior to creating a new topology with *Create()*, call the following functions to override the default centroid-, edge-, and node-creation settings:
 - *SetCentroidCreationSettings()*. See also *AcMapPointCreationSettings* class.
 - *SetEdgeCreationSettings()*. See also *AcMapEntityCreationSettings* class.
 - *SetNodeCreationSettings()*. See also *AcMapPointCreationSettings* class.
- Delete a topology - *Delete()*
- Existence test - *TopologyExists()* (*two forms*). See also *ETopologyScope* enum.
- Open a topology in the current drawing - *Open()*. See also *EOpenMode* enum.
- Open a topology in the current and source drawings - *Open()*. See also *EOpenMode* enum and *EAuditResults* enum.
- Update a topology - *Refresh()/NeedsRefresh()*

For topology source-code samples, see Topology Samples.

```

// Create a topology object, verify it, close it, and destroy
it.
AcMap::EErrCode errCode;
ETopologyType eType = ePoint;
const char* pszTopologyName = "MyNodeTopology";
// For safety, usually add the existence test
// if (AcMapTopologyManager::TopologyExists(pszTopology
Name)){...}
// before creating a new topology.
AcMapTopology* pTopology = new AcMapTopology(pszTopologyName);
// See <a href="#samples">Topology Samples</a> for sample code
// that shows how to populate these arrays.
AcDbObjectIdArray edgeObjIds;
AcDbObjectIdArray nodeObjIds;
AcDbObjectIdArray centroidObjIds;
...
errCode = pTopology->Create(edgeObjIds, nodeObjIds,
centroidObjIds, int(eType));
if (AcMap::kOk == errCode)
{
    // Verify the result by closing and reopening the newly created
    topology.
    pTopology->Close();
    pTopology->Open(AcMapTopology::eForRead);
    // Another test: Confirm that the topology has the correct
    nodes.
    AcMapNodePtrArray apNodes;
    if (AcMap::kOk == pTopology->GetNodes(apNodes))
    {
        // Verify the nodes....
        apNodes.Empty();
    }
    else
    {
        // Cannot get nodes - handle the error.
    }
}
else
{
    // Cannot create topology - handle the error.
}
// Clean up.
pTopology->Close();

```

```
delete pTopology;
pTopology = NULL;
```

Managing Topology Properties

AcMapTopologyAcMapTopologyManagerAcMapTopologySource

- Completeness - *IsComplete()*
- Description - *GetDescription()/SetDescription()*
- Error-marker styles - *GetMarkerStyles()*. See also *AcMapMarkerStyles* class.
- Highlighting - *ShowGeometry()*
- Loaded or unloaded - *IsLoaded()*
- Name - *GetName()/Rename()*
- Scope - *GetTopologyScope()*. See also *ETopologyScope* enum.
- Source - *GetTopologySource()/GetSource()*
- Status - *GetStatus()*. See also *EStatus* enum.
- Type -
GetType()/IsFixedType()/IsLinearType()/IsLogicalType()/IsPointType()/IsPolygonType().
See also *ETopologyType* enum.

Note *GetTopologySource()* takes topology source information as *AcMapTopologySource* instances in the array `typedef AcArray< AcMapTopologySource > AcMapTopologySourceArray`.

For topology source-code samples, see Topology Samples.

```

// Rename a topology.
AcMap::EErrCode errCode;
const char* pszTopologyName = "MyTopology";
const char* pszNewTopologyName = "MyRenamedTopology";
errCode = AcMapTopologyManager::Rename(pszTopologyName, pszNew
TopologyName);
if (AcMap::kOk == errCode)
{
    // Process the renamed topology.
    // Perhaps inspect and change its description.
    ...
}
else if (AcMap::kErrTopInvalidName == errCode)
{
    // Handle the bad topology name. A bad name typically is
    // NULL, empty, too long, or has nonalphabetic characters.
}
else if (AcMap::kErrTopNotExist == errCode)
{
    // The given topology doesn't exist.
}
else
{
    // Handle a different type of error.
}

```

Adding, Editing, and Deleting Topology Elements

AcMapTopologyAcMapTopoFullEdgeAcMapTopoNodeAcMapTopoPolygon

- Add a curve (linear object) - *AddCurveObject()*
- Add a point - *AddPointObject()*
- Add polygon edges - *AddPolygons()*
- Delete a node - *DeleteNode()* (*two forms*)
- Delete a polygon - *DeletePolygon()* (*two forms*)
- Delete an edge - *DeleteEdge()*
- Merge many neighboring polygons - *MergePolygons()* (*two forms*)
- Merge two neighboring polygons - *MergePolygons()* (*two forms*)

- Move a node - `MoveNode()` (*two forms*)
- Split a polygon - `SplitPolygon()` (*two forms*)

For topology source-code samples, see [Topology Samples](#).

```
// Move a node in a topology.
AcMap::EErrCode errCode;
const char* pszTopologyName = "MyNodeTopology";
AcMapTopology* pTopology = new AcMapTopology(pszTopologyName);
// Open the topology for write.
if (AcMap::kOk == pTopology->Open(AcMapTopology::eForWrite))
{
    // Get the node of interest (with object ID = 4, in this case)
    // and move it to a new location.
    AcMapTopoNode* pNode = NULL;
    pTopology->GetNode(pNode, 4);
    AcGePoint3d newLocation(39.0, 15.0, 0.0000);
    if (AcMap::kOk != pTopology->MoveNode(*pNode, newLocation))
    {
        // Handle the error.
    }
    delete pNode;
    pTopology->Close();
}
else
{
    // Cannot open topology - handle the error.
}
```

Querying Topologies

AcMapTopologyAcMapTopoFullEdgeAcMapTopoNodeAcMapTopoPolygon

- Specific edge - *FindEdge()*
- Edge nearest a point - *FindEdge()*
- Edge, node, or polygon nearest a point - *FindTopologyObject()*. See also *AcMapTopoElement* class.
- Node nearest a point - *FindNode()*
- Polygon containing a point - *FindPolygon()*

- Polygons neighboring a curve - *FindNeighborPolygons()*. See also Arrays of Topology Elements.

For topology source-code samples, see [Topology Samples](#) (page 149).

```
// Find a polygon in a topology.
AcMap::EErrCode errCode;
const char* pszTopologyName = "MyPolygonTopology";
AcMapTopology* pTopology= new AcMapTopology(pszTopologyName);
// Open the topology from the source drawing for read.
if (AcMap::kOk == pTopology->Open(AcMapTopology::eForRead, true,
    false, NULL))
{
    // Find the polygon containing a specific point.
    AcMapTopoPolygon* pPolygon;
    AcGePoint3d point(30.0, 12.0, 0.0000);
    errCode = pTopology->FindPolygon(pPolygon, point);
    if (AcMap::kOk == errCode)
    {
        // Is this a polygon of interest (with object ID = 184, in
        this case)?
        if (pPolygon->GetID() == 184)
        {
            // Process the polygon.
        }
    }
    else
    {
        // FindPolygon() failed - handle the error.
    }
    // Clean up.
    delete pPolygon;
    pPolygon = NULL;
    pTopology->Close();
}
else
{
    // Failed to open topology - handle the error.
}
```

Retrieving Topology Elements

AcMapTopologyAcMapTopoFullEdgeAcMapTopoHalfEdgeAcMapTopoNodeAcMapTopoPolygon

- All AutoCAD entities - *GetEntityIds()*
- All full edges - *GetFullEdges()*. See also Arrays of Topology Elements.
- All nodes - *GetNodes()*. See also Arrays of Topology Elements.
- All polygons - *GetPolygons()*. See also Arrays of Topology Elements.
- Specific AutoCAD entity - *GetEntityId()*
- Specific full edge - *GetFullEdge()*
- Specific half edge - *GetBackwardEdge()/GetForwardEdge()*
- Specific node - *GetNode()*
- Specific polygon - *GetPolygon()*

For topology source-code samples, see Topology Samples.

```

// Get the nodes of a topology.
AcMap::EErrCode errCode;
const char* pszTopologyName = "MyNodeTopology";
AcMapTopology* pTopology = new AcMapTopology(pszTopologyName);
AcMapNodePtrArray apNodes;
// Open the topology for read.
if (AcMap::kOk != pTopology->Open(AcMapTopology::eForRead, true,
    false, NULL))
{
    // Failed to open topology - handle the error.
}
if (Acad::eOk == pTopology->GetNodes(apNodes))
{
    // Process each node.
    for (int i = 0; i < apNodes.length(); i++)
    {
        // Get the node location.
        AcGePoint3d point;
        errCode = apNodes[i]->GetLocation(point);
        if(Acad::eOk == errCode)
        {
            // Process the node.
        }
    }
}
else
{
    // GetNodes() failed - handle the error.
}
// Clean up.
apNodes.Empty();
pTopology->Close();

```

Back to top

Managing Topology Elements

AcMapTopology

- Full edges - *AcMapTopoFullEdge* instances (derived from *AcMapTopoElement*)
- Associated AutoCAD entity - *GetEntity()*
- Associated polygon - *GetPolygon()*. See also *AcMapTopoPolygon* class.

- Associated ring - *GetRing()*. See also *AcMapTopoRing* class.
 - Associated topology - *GetTopology()*. See also *AcMapTopology* class.
 - Coincident or nearby point - *IsOnThisObject()*
 - Edge direction - *GetDirection()/SetDirection()*. See also *EDirection* enum.
 - Edge length - *GetLength()*
 - Edge resistance - *GetResistance()/SetResistance()*
 - Next edge - *GetNextEdge()*
 - Next node - *GetNextNode()*
 - Traversing half edge - *GetHalfEdge()*
 - Unique identifier - *GetID()*
-
- Half edges - *AcMapTopoHalfEdge* instances
-
- Associated polygon - *GetPolygon()*. See also *AcMapTopoPolygon* class.
 - Associated ring - *GetRing()*. See also *AcMapTopoRing* class.
 - Associated topology - *GetTopology()*. See also *AcMapTopology* class.
 - Containing full edge - *GetFullEdge()*
 - Edge resistance - *GetResistance()/SetResistance()*
 - Next edge - *GetNextEdge()*
 - Next/previous node - *GetNextNode()/GetPreviousNode()*
-
- Nodes - *AcMapTopoNode* instances (derived from *AcMapTopoElement*)
-
- Associated AutoCAD entity - *GetEntity()*
 - Associated topology - *GetTopology()*. See also *AcMapTopology* class.
 - Coincident or nearby point - *IsOnThisObject()*
 - Edges - *GetEdges()*. See also *AcMapTopoHalfEdge* class and Arrays of Topology Elements.
 - Next edge - *GetNextEdge()* (*two forms*). See also *AcMapTopoFullEdge* and *AcMapTopoHalfEdge* classes.

- Node location - *GetLocation()/SetLocation()*
- Node mobility - *IsMoveable()/SetIsMoveable()*
- Node resistance - *GetResistance()/SetResistance()*
- Unique identifier - *GetID()*

- Polygons - *AcMapTopoPolygon* instances (derived from *AcMapTopoElement*)

- Associated AutoCAD entity - *GetEntity()*
- Associated topology - *GetTopology()*. See also *AcMapTopology* class.
- Coincident or nearby point - *IsOnThisObject()*
- Hierarchical parent/children polygons - *GetHierParent()/GetHierChildren()*
- Multi-polygon parent - *GetParent()*
- Polygon area - *GetArea()*
- Polygon boundary - *GetBoundary()*. See also Arrays of Topology Elements.
- Polygon centroid - *GetCentroid()*
- Polygon perimeter - *GetPerimeter()*
- Traversal to neighboring polygon - *Traverse()*
- Unique identifier - *GetID()*

- Rings - *AcMapTopoRing* instances

- Constituent edges - *GetEdges()*. See also *AcMapTopoHalfEdge* class and Arrays of Topology Elements.
- First edge - *GetStartEdge()*. See also *AcMapTopoHalfEdge* class.
- Outer polygon boundary - *IsExterior()*. See also *AcMapTopoPolygon::GetBoundary()*.
- Ring area - *GetArea()*
- Ring length - *GetLength()*

For topology source-code samples, see Topology Samples.

```

// Get a specific polygon from a topology and print
// statistics for its rings.
AcMap::EErrCode errCode;
char* pszTopologyName = "MyTopology";
AcMapTopology* pMapTopology = NULL;
// Open the topology for read.
if (AcMapTopologyManager::TopologyExists(pszTopologyName))
{
    pMapTopology = new AcMapTopology(pszTopologyName);
    if (AcMap::kOk != pMapTopology->Open(AcMapTopology::eForRead))
    {
        // Cannot open topology - handle the error.
    }
}
// Get a polygon of interest (with object ID = 10, in this case)
// and retrieve its rings with GetBoundary().
AcMapTopoPolygon* pPolygon = NULL;
if (AcMap::kOk == pTopology->GetPolygon(pPolygon, 10))
{
    // Get the polygon's rings.
    AcMapRingPtrArray apRings;
    errCode = pPolygon->GetBoundary(apRings);
    if (AcMap::kOk == errCode)
    {
        // Get statistics for each ring.
        int nRings = apRings.length(); // Number of rings.
        for (int nRingIndex = 0; nRingIndex < nRings; nRingIndex++)
        {
            AcMapTopoRing* pRing = apRings[nRingIndex];
            // Is ring exterior or interior?.
            char* pszExtOrInt = pRing->IsExterior() ? "exterior" :
                "interior";
            // Print the rings' area and length.
            acutPrintf("\n#%d is %10s, Area: %-0.4lf Length: %-0.4lf",
                (nRingIndex + 1), pszExtOrInt, pRing->GetArea(), pRing-
                >GetLength());
        }
        apRings.Empty(); // Free the array of rings.
    }
    else
    {
        // Cannot get the polygon's boundary - handle the error.
    }
}

```

```

    }
    else
    {
        // Cannot get the specified polygon - handle the error.
    }
    // Clean up.
    delete pPolygon;
    pPolygon = NULL;
    pMapTopology->Close();

```

[Back to top](#)

Analyzing Topologies

- **Shortest-path trace** - A shortest-path trace uses a network topology to calculate the shortest path between two points or determine the optimal route based on values of direction and resistance. In a street network, for example, you can find the shortest path between a fire station and a school. Use *TraceLeastCostPath()* to calculate a shortest-path trace and an *AcMapTraceParameters* instance to set trace parameters.
- **Best-route trace** - A best-route trace uses a network topology to calculate the best route from a starting point to an end point, with one or more intermediate points. AutoCAD Map 3D determines the optimal route based on values of direction and resistance. In a street network, for example, you can find the best route to travel when visiting several customer sites from a hotel. Use *TraceBestPath()* to calculate a best-route trace and an *AcMapTraceParameters* instance to set trace parameters.
- **Flood trace** - A network flood trace traces out from a point in all directions, given the point where the network starts and the maximum distance that the network can traverse. A flood trace determines how many links and nodes can be traveled before the accumulated resistance exceeds the specified maximum resistance. You can find all restaurants within a 10-minute walk of a hotel, for example, or check the integrity of a network topology (if some links are not flooded, the topology is incomplete). Use *TraceFlood()* to calculate a flood trace and an *AcMapFloodParameters* instance to set trace parameters.
- **Buffering a topology** - Buffer analysis, or buffering, identifies objects within a specified offset of elements in node, network, and polygon topologies. A buffer is a zone that is drawn around a topology. You can specify a buffer on either side of a river to show the extent of a flood plain, for example. Use *Buffer()* to create a new topology with a buffer setting.

- Dissolving a composite topology - If a topology contains many smaller polygons, you can create a new topology by combining polygons that share the same data value in a specified field, called the dissolve field, which can be an object-data field or a column in a linked external database. Use *Dissolve()* to dissolve a topology.
- Overlaying topologies - Overlay analysis lets you overlay topologies that are loaded into the current drawing. The three types of overlay analysis are nodes with polygons, networks with polygons, and polygons with polygons. When you overlay two topologies, you choose the method in which the two selected topologies interact. In some cases, the result varies according to which topology is the source and which is the overlay. You have the following overlay options:
 - *Clip()* - A clip operation uses the overlay polygon topology as a boundary. The parts of the source polygons outside the overlay polygons are clipped and discarded. You can use this option to show polygons within a boundary polygon, such as a city or state boundary.
 - *Erase()* - An erase operation uses the overlay polygon topology like a mask and erases everything in the source polygon topology that is covered by the overlay topology.
 - *Identity()* - An identity operation works like *Union()* on the source topology and like *Intersect()* on the overlay topology. Use *Identity()* to combine nodes, links, or polygons with polygons and keep all the input geometry. *Identity()* creates one topology with one link where the link is crossed by the overlay topology.
 - *Intersect()* - An intersect operation combines topologies and keeps only the common geometry. *Intersect()* acts like the Boolean AND operation. The results are the same whichever topology is chosen as the first or second. Object data is combined for the two operations.
 - *Paste()* - A paste operation pastes the overlay polygon topology on top of the source polygons. The source polygons not covered by the overlay remain. *Paste()* can be used with only polygons.
 - *Union()* - A union operation combines polygons with polygons and keeps all geometry. *Union()* acts like the Boolean OR operation and can be used with only polygons. You can combine parcels with soils information for property assessment, for example. Use *Union()* to maintain both sets of geometry together and pull them apart as needed.

- The overlay functions all take source and overlay data as *AcMapTopoOverlayData* instances in the array `typedef AcArray< AcMapTopoOverlayData > AcMapOverlayDataArray`.

Note Before creating new topologies by buffering or overlaying existing topologies, you can call *SetCentroidCreationSettings()*, *SetEdgeCreationSettings()*, and *SetNodeCreationSettings()* to override the default topology-creation values.

For topology source-code samples, see Topology Samples.

```

// Two topologies are needed: source and overlay.
const char* pszSourceTopologyName = "MyNodeTopology";
AcMapTopology* pSourceTopology = new AcMapTopology(pszSourceTo
pologyName);
const char* pszOverlayTopologyName = "MyPolygonTopology";
AcMapTopology* pOverlayTopology = new AcMapTopology(pszOverlayTo
pologyName);
AcMap::EErrCode errCode;
// Open both source and overlay topologies for read.
if(AcMap::kOk == pSourceTopology->Open(AcMapTopology::eForRead))
{
    if(AcMap::kOk == pOverlayTopology->Open(AcMapTopology::eFor
Read))
    {
        // Create the intersection of the source and overlay topo
gies.
        errCode = pSourceTopology->Intersect(pOverlayTopology,
"OutputTopo", "Intersect", NULL, NULL, NULL);
        if(AcMap::kOk == errCode)
        {
            // Process the topology intersection.
        }
    }
    else
    {
        // Cannot create topology intersection - handle the error.
    }
    pOverlayTopology->Close();
}
else
{
    // Cannot open overlay topology - handle the error.
}
pSourceTopology->Close();
}
else
{
    // Cannot open source topology - handle the error.
}
}

```

Using Iterators

AcMapTopoIteratorAcMapTopology

- Count the number of topologies - *Count()*

- Last-element flag - *IsDone()*
- Move to first/next element - *First()/Next()*
- Current topology - *GetTopology()*
- Current topology's name - *GetName()*
- Current topology's description - *GetDescription()*
- Current topology's type - *GetType()*

For topology source-code samples, see Topology Samples.

```
AcMap::EErrCode errCode;
// Initialize the iterator.
AcMapTopoIterator* pIterator = new AcMapTopoIterator;
AcMapTopology* pTopology = NULL;
// Iterate through the topology objects.
pIterator->First();
while (!pIterator->IsDone())
{
    pIterator->GetTopology(pTopology);
    // Process the topology...
    errCode = pIterator->Next();
}
delete pIterator;
delete pTopology;
// To iterate with a for-loop:
// for (pIterator.First(); !pIterator.IsDone(); pIterator.Next())
{...}
```

Arrays of Topology Elements

AcMapTopoElementPtrArray

| Array class | Holds pointers to |
|------------------------------|------------------------------------|
| <i>AcMapFullEdgePtrArray</i> | <i>AcMapTopoFullEdge</i> instances |
| <i>AcMapHalfEdgePtrArray</i> | <i>AcMapTopoHalfEdge</i> instances |
| <i>AcMapNodePtrArray</i> | <i>AcMapTopoNode</i> instances |

| Array class | Holds pointers to |
|-----------------------------|-----------------------------------|
| <i>AcMapObjectPtrArray</i> | <i>AcMapTopoElement</i> instances |
| <i>AcMapPolygonPtrArray</i> | <i>AcMapTopoPolygon</i> instances |
| <i>AcMapRingPtrArray</i> | <i>AcMapTopoRing</i> instances |

For topology source-code samples, see Topology Samples.

Handling Errors

Many functions in the various topology classes return an `AcMap::EErrCode` error code. When a particular function returns an error code, read that function's documentation for function-specific error conditions rather than relying on only the generic error descriptions in the `AcMap::EErrCode` documentation.

Other Information Sources

- For more information about topology in AutoCAD Map 3D, choose Help > AutoCAD Map 3D Help > Contents tab (or press F1), and then navigate to Using AutoCAD Map 3D (by feature) > Topology (Spatial Analysis).
- For a topology tutorial in AutoCAD Map 3D, choose Help > Tutorials > Contents tab, and then choose "Using Topology and Spatial Analysis".
- For information about object data in AutoCAD Map 3D, choose Help > AutoCAD Map 3D Help > Contents tab (or press F1), and then navigate to Using AutoCAD Map 3D (by feature) > Object Data.

Topology Samples

To view code samples of topology functions, open the Samples folder in your AutoCAD Map 3D ObjectARX installation and navigate to Map Samples\Topology.

Topology Classes, Namespaces, and Globals

To view the topology classes, namespaces, and globals, click the following links:

AcMapTopology Class
AcMapTopoElement Class
AcMapTopoFullEdge Class
AcMapTopoHalfEdge Class
AcMapTopoNode Class
AcMapTopoPolygon Class
AcMapTopoRing Class
AcMapTopoIterator
AcMapTopologySource Class
AcMapTopoOverlayData Class
AcMapEntityCreationSettings Class
AcMapPointCreationSettings Class
AcMapFloodParameters Class
AcMapTraceParameters Class
AcMapNetAnalysisParameters Class
AcMapMarkerStyles Class
AcMapTopoElementPtrArray Template Class
AcMapObjectPtrArray Class
AcMapFullEdgePtrArray Class
AcMapHalfEdgePtrArray Class
AcMapNodePtrArray Class
AcMapPolygonPtrArray Class
AcMapRingPtrArray Class
AcMapTopologyManager Namespace
AcMapObjectDataField Global Struct
AcMapObjectDataTable Global Struct
ETopologyMarkType Global Enum
ETopologyType Global Enum

Centroids

22

Creating centroids moves attached data from the perimeters of mpolygons and closed polylines to their centroids so that the data is not lost when topologies are created.

In this chapter

- [Creating Centroids](#)

Creating Centroids

You must create centroids for mpolygons and closed polylines before building a topology with them.

A closed polyline is a polygon produced by the POLYGON command.

[Creating Centroids](#) (page 152)

Other Information Sources

[Creating Centroids Samples](#) (page 152)[Creating Centroids Namespace](#) (page 152)

Creating Centroids

Use the CreateCentroids() (*twoforms*) functions in the *AcMapUtilities* namespace to create centroids.

For centroid-creation source-code samples, see [Creating Centroids Samples](#) (page 152).

[Back to top](#)

Other Information Sources

- For more information about creating centroids in AutoCAD Map 3D, choose Help > Autodesk Map Help > Contents tab (or press F1), and then navigate to Using AutoCAD Map 3D (by feature) > Topology (Spatial Analysis) > Editing Topologies > Creating Centroids for Polygons.

[Back to top](#)

Creating Centroids Samples

To view code samples of centroid-creation functions, open the Samples folder in your AutoCAD Map 3D ObjectARX installation and navigate to Map Samples\CreateCentroid.

[Back to top](#)

Creating Centroids Namespace

To view the centroid-creation namespace, click the following link:

AcMapUtilities Namespace

[Back to top](#)

Drawing Cleanup

23

You must clean drawing objects before building a topology with them.

In this chapter

- [Drawing Cleanup Details](#)

Drawing Cleanup Details

Let's look at this in two phases, preparing the cleanup model, which ends with a call to *tpm_cleaninit*, and executing the cleanup, which begins with a call to *tpm_cleanstart*.

To prepare the cleanup model

- 1 Allocate memory for the cleanup model. Use *tpm_cleanalloc*.

```
ade_id cleanupModelId = tpm_cleanalloc();
```

- 2 Allocate memory for *cleanup variables*, which specify properties for the cleanup process. The variables are initialized to their default values. Use *tpm_varalloc*.

```
ade_id cleanupVarId = tpm_varalloc();
```

If you will be specifying an explicit list of cleanup actions (you create and manage this list with calls to *tpm_cleanactionlistins* and related functions), also allocate memory for *cleanup action variables*, which specify properties for individual actions. Again use *tpm_varalloc*.

```
ade_id cleanupActionVarId = tpm_varalloc();
```

- 3 Get a selection set of objects to be cleaned (the *include* set).

```
ads_name ssObjsForCleanup;  
acutPrintf("\nSelect the objects to perform cleanup on.");  
acedSSGet(NULL, NULL, NULL, NULL, ssObjsForCleanup);
```

Or create one.

```
struct resbuf* pFilteredEntitySelectionRb = acutBuildList(  
RTDXFO, "LWPOLYLINE",  
8, "UtilityNetwork-Electric",  
0);  
ads_name ssObjsForCleanup;  
acedSSGet("X", NULL, NULL, pFilteredEntitySelectionRb,  
ssObjsForCleanup);  
acutRelRb(pFilteredEntitySelectionRb);
```

You can also get a selection set of objects to be anchored (the *anchor* set). Anchored objects are not repositioned by the cleanup process, but remain fixed while others are repositioned around them.

```
ads_name ssObjsToAnchor;  
acutPrintf("\nSelect the objects to serve as an anchor.");
```

```
acedSSGet(NULL, NULL, NULL, NULL, ssObjsToAnchor);
```

The `acedSSGet` function prompts the user to select objects and returns a selection set. This function can also be used with a resbuf to filter selected objects. Make sure to release selection sets when finished with them, using `acedSSFree()`

- 4 Set cleanup variables using `tpm_varset` with the `clean_var_id` that you allocated in step 2. A few of these variables specify cleanup actions, but most of them specify how cleanup actions will be performed.

```
// Set the cleanup variable "LINK_ERROR" for break crossing.
char* pszConfigVarName = "LINK_ERROR";
struct resbuf* pLinkErrorVarValRb = acutBuildList(
RTSHORT, 2,
0);
int resultCode = tpm_varset(
cleanupVarId,
pszConfigVarName,
pLinkErrorVarValRb);
acutRelRb(pLinkErrorVarValRb);
// Set the cleanup variable "INCLUDEOBS_AUTOSELECT".
// Must be included with a filtered selection set.
pszConfigVarName = "INCLUDEOBS_AUTOSELECT";
struct resbuf* pIncludeObjsVarValRb = acutBuildList(
RTSHORT, 0,
0);
resultCode = tpm_varset(
cleanupVarId,
pszConfigVarName,
pIncludeObjsVarValRb);
acutRelRb(pIncludeObjsVarValRb);
// Set the cleanup variable "INCLUDEOBS_LAYERS".
// Must be included with a filtered selection set.
pszConfigVarName = "INCLUDEOBS_LAYERS";
struct resbuf* pIncludeObjsLyrVarValRb = acutBuildList(
RTSTR, "UtilityNetwork-Electric",
0);
resultCode = tpm_varset(
cleanupVarId,
pszConfigVarName,
pIncludeObjsLyrVarValRb);
acutRelRb(pIncludeObjsLyrVarValRb);
```

Before setting cleanup variables, you can load a cleanup profile if you saved one previously, and in that way set many variables at once. Use *tpm_cleanprofileload*.

```
resultCode = tpm_cleanprofileload(
cleanupVarId,
"C:\\profile.dpf");
```

If you specify an explicit list of cleanup actions, note that those will be the only actions performed. Cleanup actions specified by the variables `NODE_ERROR`, `LINK_ERROR`, and `GENERALIZE` will be ignored, as well as any setting specific to them only, such as `CORRIDOR`'s, which defines the tolerance for `GENERALIZE`.

Using an action list is the best way to specify cleanup actions, because you can specify the order in which they execute, and you can include the same action more than once. Using variables to specify cleanup actions is an older technique, which is still supported for the sake of older scripts, but it is deprecated from AutoCAD Map 3D 6 onward.

Note When you insert the Simplify Objects action (clean group type 128), it is always listed first, and you cannot insert it more than once.

With an explicit list of cleanup actions, note that certain individual actions can have individual tolerance settings (and in some cases, other settings also). See *Cleanup Action Variables*. When you are about to insert an action into the action list, you can use *tpm_varset* with the `action_var_id` that you allocated in step 2 to set variables for this action before calling *tpm_cleanactionlistins*. You can continually reset and reuse the same set of cleanup action variables with each action that you insert.

```
// Set CLEAN_TOL cleanup variable for simplify objects, (weeding).
pszConfigVarName = "CLEAN_TOL";
struct resbuf* pCleanTolVarValRb = acutBuildList(
RTREAL, 2.0,
0);
resultCode = tpm_varset(
cleanupActionVarId,
pszConfigVarName,
pCleanTolVarValRb);
acutRelRb(pCleanTolVarValRb);
```

Insert a cleanup action for simplify objects by specifying the cleanup variables id (real) returned by *tpm_cleanalloc()*, the index at which the item will be inserted into the list, the clean group type code, (see *tpm_cleangrouptype* for a list of types) and the cleanup action variable id (real) returned by *tpm_varalloc()*.

```

resultCode = tpm_cleanactionlistins(
cleanupVarId,
0,
128,
cleanupActionVarId);

```

Insert an additional cleanup action for break crossing objects. The index position of -1 is for the last position.

```

resultCode = tpm_cleanactionlistins(
cleanupVarId,
-1,
2,
cleanupActionVarId);

```

At any point while you are setting cleanup variables, or after you have finished, you can save the current cleanup profile using *tpm_cleanprofilesave*.

```

resultCode = tpm_cleanprofilesave(
cleanupVarId,
"C:\\profile.dpf");

```

Note that saved profiles are XML files. You can view or edit them in a text editor as you can with saved queries (which are AutoLISP scripts). See *Editing Query Files*.

- 5 Call *tpm_cleaninit* to add cleanup variables and the selection set of objects to clean to the cleanup model.

```

resultCode = tpm_cleaninit(
cleanupModelId,
cleanupVarId,
ssObjsForCleanup);

```

If you have collected a selection set of objects to be anchored, first call *tpm_cleaninitanchorset* before calling *tpm_cleaninit*.

```

resultCode = tpm_cleaninitanchorset(
cleanupModelId,
cleanupVarId,
ssObjsForAnchor);

```

The cleanup model is now complete.

To execute the cleanup

- 1 Begin the cleanup process with *tpm_cleanstart*.

```
resultCode = tpm_cleanstart(cleanupModelId);
```

- 2** Execute cleanup actions (process cleanup groups) until cleanup is complete. With each cleanup group, with each error, mark and fix it.

```
resultCode = tpm_cleangroupNext(cleanupModelId);
if (resultCode == RTNORM){
    while (! (tpm_cleancomplete(cleanupModelId))){
        long lCleanErrors = 0;
        tpm_cleangroupqty(cleanupModelId, &lCleanErrors);
        for (int i = 0; i < lCleanErrors; i++){
            resultCode = tpm_cleanerrorcur(cleanupModelId, i);
            resultCode = tpm_cleanerrormark(cleanupModelId);
            resultCode = tpm_cleanerrorfix(cleanupModelId);
        }
        resultCode = tpm_cleangroupNext(cleanupModelId);
    }
}
else {
    acutPrintf("\nNothing to clean.");
}
```

- 3** Update the drawing with *tpm_cleanend*.

```
resultCode = tpm_cleanend(cleanupModelId);
```

Optional, To clear the cleanup model without updating the drawing, use *tpm_cleancancel*.

```
resultCode = tpm_cleancancel(cleanupModelId);
```

- 4** Free the cleanup model.

```
resultCode = tpm_cleanfree(cleanupModelId);
```

- 5** Free the selection set.

```
resultCode = acedSSFree(ssObjsForCleanup);
```


Annotation

24

These textual values might be attributes (such as object data), display properties (such as a lineweight), or geometric values (such as the line direction). In addition, you can add graphics, such as arrows, static text, or other geometry, to your annotation by using standard AutoCAD drawing commands. Annotation functions are available in the *AcMapAnnotationManager* namespace. See also Other Information Sources.

In this chapter

- [Annotation Details](#)

Annotation Details

Use AutoCAD Map 3D's annotation feature to indicate textual values on a drawing object.

[Creating Annotation Templates](#) (page 162)

[Setting Annotation Template Properties](#) (page 163)

[Setting Annotation Text and Expressions](#) (page 163)

[Inserting Annotation References](#) (page 165)

[Updating Annotations](#) (page 165)

[Deleting Annotations](#) (page 166)

[Managing Annotations](#) (page 167)

[Other Information Sources](#) (page 168)

[Annotation Samples](#) (page 169)[Annotation Namespace](#) (page 169)

Creating Annotation Templates

Before you can add annotation to a drawing, you first must call *CreateAnnotationTemplate()* to define an annotation template that specifies what information will be included and how it will be displayed. Call *AnnotationTemplateExists()* to check whether a specific template already exists; if it does exist, *CreateAnnotationTemplate()* won't overwrite it, but rather will return a null object ID.

For annotation source-code samples, see [Annotation Samples](#) (page 169).

```
char* pszTemplateName = "MyAnnotationTemplate";
AcDbObjectId idCreatedAnnTem;
if (!AnnotationTemplateExists(pszTemplateName))
{
    // Create a template with the name stored in pszTemplateName.
    idCreatedAnnTem = CreateAnnotationTemplate(pszTemplateName);
    // Test whether the template's object ID is valid.
    if (idCreatedAnnTem != AcDbObjectId::kNull)
    {
    }
}
```

[Back to top](#)

Setting Annotation Template Properties

After creating an annotation template, you can retrieve or set its following static properties:

- Color - *GetTemplateColor()/SetTemplateColor()*
- Layer - *GetTemplateLayer()/SetTemplateLayer()*
- Linetype - *GetTemplateLinetype()/SetTemplateLinetype()*
- Lineweight - *GetTemplateLineWeight()/SetTemplateLineWeight()*
- Rotation - *GetTemplateRotation()/SetTemplateRotation()*
- Scale factor - *GetTemplateScaleFactor()/SetTemplateScaleFactor()*

For annotation source-code samples, see [Annotation Samples](#) (page 169).

```
Acad::ErrorStatus acErrStatus;  
char* pszTemplateName = "MyAnnotationTemplate";  
AcCmColor acClrInColor;  
char* pszInLayerName = "aLayer";  
// Set a few template properties.  
acErrStatus = SetTemplateScaleFactor(pszTemplateName, 2.0);  
acErrStatus = SetTemplateRotation(pszTemplateName, PI); // PI  
radians = 180 degrees  
acClrInColor.setColorIndex(1); // Red.  
acErrStatus = SetTemplateColor(pszTemplateName, acClrInColor);  
acErrStatus = SetTemplateLayer(pszTemplateName, pszInLayerName);  
// Get the scale factor.  
double dOutScaleFactor;  
acErrStatus = GetTemplateScaleFactor(dOutScaleFactor, pszTemplate  
Name);
```

[Back to top](#)

Setting Annotation Text and Expressions

To set the text that appears on an annotation, call *CreateAnnotationText()* to create a text object and set its properties (tag, height, color, justification, and so on), and then call *SetExpressionString()* to set the value that appears. The expression can be any valid combination of functions and variables that can appear in the AutoCAD Map 3D Expression Evaluator. *One form* of *SetExpressionString()* takes a `char*` expression, and the *other form* takes an `AcMapExpression` expression. To retrieve an expression, call

GetExpressionString(). *GetExpressionString()* and *SetExpressionString()* take an *eAnnotationExpressionFields* argument that indicates which expression to retrieve or store. Use *IsAnnotationText()* to determine whether a particular attribute definition is an annotation text entity.

For annotation source-code samples, see [Annotation Samples](#) (page 169).

```
#include dbmain.h // Needed for acdbOpenObject().
Acad::ErrorStatus acErrStatus;
// idCreatedAnnTem was created earlier with CreateAnnotationTem
plate().
AcDbObjectId idTagText;
acErrStatus = CreateAnnotationText(idTagText, idCreatedAnnTem);
// Open the newly created text object for write.
AcDbAttributeDefinition* pTagText = NULL;
acErrStatus = acdbOpenObject((AcDbObject *)&pTagText, idTagText,
    AcDb::kForWrite);
// Check if this is an annotation text object.
if (IsAnnotationText(pTagText))
{
    // Set a few properties for the text object.
    pTagText->setTag("Area"); // Always set the tag attribute.
    pTagText->setPosition(AcGePoint3d(0.0,0.0,0.0));
    pTagText->setHeight(0.5);
    pTagText->setVerticalMode(AcDb::TextVertMode::kTextVertMid);
    pTagText->setHorizontalMode(AcDb::TextHorzMode::kTextCenter);
    // Set the value of the expression to display
    // the area of the associated entity.
    char* pszExpressionString = ".AREA";
    // Store the expression with the annotation text object.
    acErrStatus = SetExpressionString(kpszExpressionString, pTag
    Text, kAttDefAnnotationString);
}
// Print the value of the expression that we just set.
char* pszOutExpression = NULL;
acErrStatus = GetExpressionString(pchOutExpression, pTagText,
    kAttDefAnnotationString);
if (acErrStatus == Acad::eOk)
{
    acutPrintf("Tag = %s. Expression string = %s\n", pTagText-
    >tag(), pchOutExpression);
    acutDelString(pchOutExpression);
}
```

Back to top

Inserting Annotation References

Call `InsertAnnotationReference()` to attach an annotation reference to a particular entity. Optionally, you can override the default property values of the base annotation template when you insert a new annotation reference: *One form* of `InsertAnnotationReference()` uses the property values of an existing annotation reference to set the values of the new reference, and the *other form* lets you specify an `AnnotationOverrides` struct of explicit override values. To attach an annotation reference to more than one entity, call `InsertAnnotationReferences()` (which also supports property overrides).

For annotation source-code samples, see [Annotation Samples](#) (page 169).

```
AcDbObjectId idNewBlkRefId; // Output object ID of the newly
                             created annotation reference.
char* pszTemplateName = "MyAnnotationTemplate"; // Name of exist
                             ing template.
AcDbObjectId idAssocEnt; // Object ID of entity to attach annota
                             tion to.
Acad::ErrorStatus acErrStatus;
// Draw a circle to associate the annotation with.
AcGePoint3d ptCenter(0,0,0);
AcGeVector3d vcNorm(0,0,1);
double dInRadius = 5.5;
idAssocEnt = DrawCircle(ptCenter, vcNorm, dInRadius);
// Attach the annotation reference to the circle.
// The annotation will appear in the current drawing
// if its annotation text expression(s) can be evaluated.
// The MyAnnotationTemplate text expression is set to .AREA.
acErrStatus = InsertAnnotationReference(idNewBlkRefId, pszTem
plateName, idAssocEnt);
// Test to see if the insertion succeeded.
if(acErrStatus != Acad::eOk)
{
    // Handle the error...
}
```

[Back to top](#)

Updating Annotations

If an entity associated with an annotation reference changes, call `RefreshAnnotationReferences()` to refresh the annotation. If an annotation template changes, call `UpdateAnnotationReferences()` to update the annotation

references based on that template. Both functions let you control how the annotation reference's property values are updated.

For annotation source-code samples, see [Annotation Samples](#) (page 169).

```
char* pszTemplateName = "MyAnnotationTemplate"; // Name of exist
ing template.
bool bFullAnnotation;
bool bRetainLocal;
Acad::ErrorStatus acErrStatus;
bFullAnnotation = false; // Re-evaluate only the text string -
don't change other properties.
acErrStatus = RefreshAnnotationReferences(pszTemplateName,
bFullAnnotation);
bRetainLocal = true; // Don't discard the local property values.
acErrStatus = UpdateAnnotationReferences(pszTemplateName,
bRetainLocal);
// Test to see if the update succeeded.
if(acErrStatus != Acad::eOk)
{
    // Handle the error...
}
```

[Back to top](#)

Deleting Annotations

To delete an annotation template, call *DeleteAnnotationTemplate()*. You can delete only templates with no annotation references, which you can check with *IsAnnotationTemplateReferenced()*. *AnnotationTemplateReferencedObjIds()* lists all of a template's references, which you must delete before you can delete the template. Delete an annotation reference in the same way that you would delete any AutoCAD object.

For annotation source-code samples, see [Annotation Samples](#) (page 169).

```

#include dbmain.h // Needed for acdbOpenObject().
char* pszTemplateName = "MyAnnotationTemplate"; // Template to
delete.
Acad::ErrorStatus acErrStatus;
if(AnnotationTemplateExists(pszTemplateName))
{
    // If the template has any annotation references, delete them.
    if(IsAnnotationTemplateReferenced(pszTemplateName))
    {
        AcDbObjectIdArray arrOutIdObjs;
        AcDbObject* pObj = NULL;
        if((AnnotationTemplateReferencedObjIds(arrOutIdObjs, pszTem
        plateName)) == Acad::eOk)
        {
            // Open, erase, and close each returned object reference.
            while(arrOutIdObjs.length( ))
            {
                acErrStatus = acdbOpenObject(pObj, arrOutIdObjs.first( ),
                AcDb::kForWrite);
                if((acErrStatus == Acad::eOk) && (pObj))
                {
                    pObj->erase( );
                    pObj->close( );
                    pObj = NULL;
                    // Remove the ID of the erased object.
                    arrOutIdObjs.removeFirst( );
                }
            }
            else
            {
                // Handle the error...
            }
            if((DeleteAnnotationTemplate(pszTemplateName)) != Acad::eOk)
            {
                // Handle the error...
            }
        }
    }
}

```

[Back to top](#)

Managing Annotations

You can use several general functions to manage annotation templates and references. *GetTemplateName()* lists the annotation templates defined in the current drawing. Autodesk Map stores an annotation template as a block

(AcDbBlockTableRecord) and an annotation reference as a block reference (AcDbBlockReference).

IsAnnotationTemplate() determines whether an AcDbBlockTableRecord is an annotation template and *AnnotationTemplateBlockDefinitionId()* gets a template's AcDbBlockTableRecord.

IsAnnotationBlockReference() determines whether a AcDbBlockReference is an annotation reference; *AnnotationBlockReferenceAssociatedObjectId()* returns the ID of the object associated with a specific annotation reference; and *TemplateNameBTRPrefix()* returns the special prefix string ("ACMAP_ANN_TEMPLATE_") that Autodesk Map silently prepends to each annotation template name.

For annotation source-code samples, see [Annotation Samples](#) (page 169).

```
// Get all the annotation template names.
Acad::ErrorStatus acErrStatus;
AcArray<char*> acarrTemNameArray;
acErrStatus = GetTemplateNameArray(acarrTemNameArray);
if((acErrStatus == Acad::eOk) && !(acarrTemNameArray.isEmpty(
))))
{
    // Process the templates...
}
```

[Back to top](#)

Other Information Sources

- For more information about annotation in AutoCAD Map 3D, choose Help > Autodesk Map Help > Contents tab (or press F1), and then navigate to Using AutoCAD Map 3D (by feature) > Annotation.
- For an annotation tutorial in AutoCAD Map 3D, choose Help > Tutorials > Contents tab, and then choose "Adding Annotations to Objects".
- For more information about expressions in AutoCAD Map 3D, choose Help > Autodesk Map Help > Contents tab (or press F1), and then navigate to Expression Evaluator.

[Back to top](#)

Annotation Samples

To view code samples of annotation functions, open the Samples folder in your AutoCAD Map 3D ObjectARX installation and navigate to Map Samples\Annotation.

[Back to top](#) (page 161)

Annotation Namespace

To view the annotation namespace, click the following link:

AcMapAnnotationManager Namespace

Display Manager

Manages the display of selected objects in a drawing for theming or highlighting.

For more information, see

- *Display Manager* in ObjectARX Reference Help.
- Display Manager sample code, which is located in the Map Samples\DisplayManagement folder of AutoCAD Map 3D ObjectARX installations.
- Display Manager in the UI documentation, AutoCAD Map 3D Help.

User Management

26

The AutoCAD Map 3D user-management feature provides user- and session-management tools for system administrators.

In this chapter

- [User Management Detail](#)

User Management Detail

User Management

Other Information Sources

User Management Samples User Management Classes and Globals

User Management

The *AcMapSession* class provides the following user and session functions. The *AcMapGetSession()* global function retrieves the AutoCAD Map 3D session pointer, an instance of *AcMapSession*.

- Retrieve aliases - *GetAliases()*
- Retrieve error stack - *GetErrorStack()*
- Retrieve project iterator - *GetProjectIterator()*
- Log in a user - *LogIn()*
- List registered users - *GetUserList()*
- Retrieve the current user - *GetCurrentUser()*
- Retrieve/set a user's rights - *GetUserRights()*/SetUserRights()**
- Lock/unlock Autodesk Map - *Lock()/Unlock()*
- Retrieve AutoCAD Map 3D ObjectARX API version - *ArxApiVersion()*
- Retrieve/set workspace rectangle - *GetWSpaceRectangle()/SetWSpaceRectangle()*
- Execute AutoCAD Map 3D command - *InvokeCommand()*
- Execute AutoCAD Map 3D API function - *InvokeFunction()*
- Retrieve AutoCAD Map 3D project - *GetProject()* (*two forms*)
- Retrieve AutoCAD document - *GetDocument()*
- Add/remove session reactor - *AddSessionReactor()/RemoveSessionReactor()*
- Add/remove options reactor - *AddOptionsReactor()/RemoveOptionsReactor()*
- Retrieve/set option values - *GetOptionValue()* (*three forms: 1 2 3*)/*SetOptionValue()* (*three forms: 1 2 3*)
- Option node test - *IsOptionNodeEnabled()*

- Set the Options dialog box active page - *SetActiveOptionPage()*
- Retrieve the users' root folder - *getAllUsersRootFolder()*
- Retrieve AutoCAD Map 3D application services - *GetApplicationServices()*
- Create a new user - *CreateUser()**
- Delete an existing user - *DeleteUser()**
- Change a user's password - *ChangePassword()**
- Retrieve AutoCAD Map 3D project - *GetProjectForDb()*

For user-management source-code samples, see User Management Samples.

Other Information Sources

- For more information about user management in AutoCAD Map 3D, choose Help > Autodesk Map Help > Contents tab (or press F1), and then navigate to Using AutoCAD Map 3D (by feature) > Setting Up AutoCAD Map 3D Drawings > Setting Options > Setting Up Users.

User Management Samples

To view code samples of user-management functions, open the Samples folder in your AutoCAD Map 3D ObjectARX installation and navigate to Map Samples\UserManager.

User Management Classes and Globals

To view the user-management classes and globals, click the following links:

AcMapSession Class *AcMapGetSession()* *Global Function*

Map Plotting and Publishing

27

This topic describes plotting and publishing maps using Map Book classes.

In this chapter

- [Map Plotting and Publishing Detail](#)

Map Plotting and Publishing Detail

Although the global-function API for map plotting remains in place, and existing code that is based on it is still valid, new development for plotting maps should use Map Book classes.

For more information, see

- *Map Book* in AutoCAD Map 3D ObjectARX Reference Help.
- Map Book sample code, which is located in the Map Samples\Plotting folder of Autodesk Map ObjectARX installations.
- Map Book in the UI documentation, AutoCAD Map 3D Help.

Managed Wrapper Classes

28

ObjectARX presented as managed C++.

In this chapter

- [Managed Wrapper Classes
Detail](#)

Managed Wrapper Classes Detail

The following discussion assumes that you are familiar with managed C++ and managed wrapper classes in AutoCAD ObjectARX. Refer to the managed wrapper sections in AutoCAD ObjectARX Help.

Get and Set Functions and Properties

If you are using C# or VB.NET to address the managed wrapper classes API, note that `get_xx` and `set_xx` functions are addressed as properties, and the property name is the `xx` part of the corresponding function names. If there are matching `get_xx` and `set_xx` functions, the property is read-write. If there is only a `get_xx` function, the property is read-only. In a few cases, where there is only a `set_xx` function, the property is write-only.

Option Strings Option Properties

Getting and setting project or session options is not the same with managed wrapper classes as it is with ObjectARX.

To get or set a session or project option using ObjectARX, use a `GetOptionValue` or `SetOptionValue` function. Specify the target option by passing the option name. For example, to set the log file name for a session (AcMapSession object, which corresponds to the MapApplication object, or the application, in managed wrapper context), you pass the option name and a file name:

```
pSession->SetOptionValue("LogFileName", "filename.ext");
```

To get or set the same option in managed wrapper context, first use the `MapApplication::Options` property to get the `SystemOptions` object, and then use an option-specific `SystemOptions` property:

```
oSysOptions.LogFileName = "filename.ext";  
strLogFile = oSysOptions.LogFileName;
```

Getting Application and Project Objects

Autodesk Map objects are related in a containment hierarchy, with the Application object at the root. To access AutoCAD Map 3D objects, first get the Application object, and then use the `Application::ActiveProject` property to get the current project (a `ProjectModel` object).

```
NAMESPACE_MAP3D::MapApplication* mapApi = Autodesk::HostMapApplicationServices::Application;  
NAMESPACE_MAP3D_PROJECT::ProjectModel* pProj = mapApi->ActiveProject;
```

With a project in hand, use ProjectModel properties to get objects that it contains. For example, its drawing set (DrawingSet object).

```
NAMESPACE_MAP3D_PROJECT::DrawingSet* pDSet = pProj->DrawingSet;
```

Sample Code

To get managed-wrapper samples, open MapSamples\DotNet in an AutoCAD Map 3D ObjectARX installation.

Notes, Tips, and Warnings

29

In this chapter

- [Colors](#)

Colors

Colors can be specified or returned as AutoCAD color indexes or true colors.

AutoCAD Color Indexes (ACIs)

The valid ACI formats are

Color Indexes, integer strings from 0 through 256. For example, "123". Note that indexes 0 and 256 do not specify colors literally, as 1 through 255 do, but logically. See "Logical Colors" below. And note that indexes 8 and 9 (a dark gray and a light gray), together with the named colors (see "Color Names" below), are collectively called the *standard colors*.

Color Names, which correspond to indexes 1 through 7. The color names are red, yellow, green, cyan, blue, magenta, and white. For example, "yellow" (always double-quoted). Note that index 7, the color named white, displays as white or black depending on background color.

| Index | Name |
|-------|---------|
| 1 | Red |
| 2 | Yellow |
| 3 | Green |
| 4 | Cyan |
| 5 | Blue |
| 6 | Magenta |
| 7 | White |

Logical Colors, which correspond to indexes 0 and 256. The logical colors are ByBlock (0) and ByLayer (256), and they reflect the current block and layer colors respectively. For example, "ByBlock" (always double-quoted). Note that ByBlock and ByLayer can return true colors or ACIs.

For more information about ACIs,

- 1 In AutoCAD Map 3D, click Format > Color.
- 2 In the Select Color dialog box, click Help.

True Colors

By *true colors* we mean 24-bit color: three RGB components, 8 bits each, with no alpha component (that is, no transparency value).

The valid true-color formats are

RGB Triplets, where each component is an integer from 0 through 255. For example, "255,0,0". RGB triplets are wrapped in double quotes except when they are used in query conditions, in which case they must always be wrapped in escaped double quotes ('\""). See "Color Patterns" below.

Color Book Colors, such as "Pantone, 123 CVC", a composite of two comma-separated names representing a Color Book and a color within it. Color book strings are wrapped in double quotes except when they are used in query conditions, in which case they must always be wrapped in escaped double quotes ('\""). See "Color Patterns" below. And no matter where they are used, color book strings must always be wrapped in escaped double quotes if they contain certain special characters. If you are unsure if a color book string contains special characters, there is no harm wrapping it in escaped double quotes just to be sure.

Expressions, such as ".COLOR" or ".TRUECOLOR" (always double-quoted). ".COLOR" always returns an ACI color. If the selected object's color is a true color it returns the nearest ACI equivalent. ".TRUECOLOR" returns a true color if the selected object's color is a true color, or an ACI if its color is an ACI. Note that ".TRUECOLOR", and other expressions that can return true colors, return in valid format only if the type argument of (ade_expreval) is "string".

Color Patterns, comma-separated lists of colors in any of the valid formats, including ACI colors, always double-quoted. Color patterns are used to express multiple color conditions in compact format. Consider the color pattern "red, green". The pseudocode expression, color = "red,green", is logically equivalent to (color = "red") OR (color = "green"). Similarly, color && "red,green" is logically equivalent to (color && "red") AND (color && "green"). Because color patterns are comma-separated lists, Color Book colors and RGB colors in query conditions are always bounded by escaped double quotes ('\"') because they are themselves comma-separated. For example, the following color pattern includes six colors: three ACIs, one RGB, and one Color Book color.

"12,34,56,\"12,34,56\", \"Pantone, 123 CVC\""

NOTE Note You can use wildcard characters when you specify a match string for Color Book colors (but not for RGB colors). For this reason, any wildcard character in a Color Book string that is meant to be taken literally must be escaped using a backquote, ``. For example, the "." character in the following string, normally a wildcard matching any non-alphanumeric character, is meant as a literal: "My`.Colors, Hot".

Colors in Query Conditions

You can specify ACI colors in query conditions as color names or color indexes. But if you retrieve such conditions, ACI colors are always reported as color indexes, because that is how they are stored, even if they were originally specified as color names.

However, this is not the case with color patterns, which can include color indexes, color names, or both. If you retrieve a query condition where color is specified as a color pattern, the color pattern is reported as it was originally specified.

Index

A

annotation 162
 about 162
annotation, 162

C

centroids 152
 about 152
centroids, 152
converting from one coordinate system to
 another 67
coordinate systems 63, 67
 about 63
 converting from one coordinate
 system to another 67
coordinate systems, 63, 67
custom objects 43, 47
 queryable 43, 47
custom objects, 43, 47

D

data sources 49
 about 49
data sources, 49
display manager 171
 about 171
display manager, 171
drawing cleanup for topology 155
drawing sets 5, 10
 about 5
 sample code 10
drawing sets, 5, 10
drawings 5, 10, 155
 about 5
 drawing cleanup for topology 155
 sample code 10
drawings, 5, 10

E

exporting 85
 about 85
exporting, 85

F

feature classification 71
 about 71
feature classification, 71
filtering objects 81

I

importing 85
 about 85
importing, 85

L

labels 162

M

managing users 173
 about 173
managing users, 173
map plotting 177
 about 177
map plotting, 177

O

object data tables 51, 54–55, 57–58
 about 51
 sample code 54–55, 57–58
object data tables, 51, 54–55, 57–58

- object filters 81
 - about 81
- object filters, 81
- objects 43, 47, 81
 - filtering 81
 - queryable custom objects 43, 47
- objects, 43, 47, 81
- Oracle Spatial data 97, 106, 109–110, 114, 116, 120, 126, 128–129
 - about 97
 - sample code 106, 109–110, 114, 116, 120, 126, 128–129
- Oracle Spatial data, 97, 106, 109–110, 114, 116, 120, 126, 128–129

P

- plotting maps 177
 - about 177
- plotting maps, 177
- points 67
 - converting from one coordinate system to another 67
- points, 67
- property alteration 30–31
 - about 30
 - sample code 31
- property alteration, 30–31
- protocol extensions for querying custom objects 47

Q

- queries 17, 23, 43, 47
 - about 17

- custom objects and 43, 47
 - queryable custom objects 43, 47
 - sample code 23
- queries, 17, 23, 43, 47

R

- reactors 97
 - about 97
- reactors, 97

S

- subclassing queryable custom objects 43

T

- topology 131, 152, 155
 - about 131
 - centroids 152
 - drawing cleanup for 155
- topology, 131, 155

U

- user management 173
 - about 173
- user management, 173
- users 173
 - managing 173
- users, 173