



NUXIS Manual Central Management v2.0.0

September 17, 2013

Rua Irmãs Missionárias do Espírito Santo, 27
4715-340 Braga
Portugal

Tel: +351 253 680 300
Fax: +351 253 680 319



excelência'12

Change Log

- 2013-08-09 – Carlos Rodrigues <cmar@eurotux.com>
Update Sub-Section *Storage* with information about *Storage iSCSI*
- 2013-05-30 – Carlos Rodrigues <cmar@eurotux.com>
Update Section *Users, groups and permission administration*
- 2013-02-11 – Carlos Rodrigues <cmar@eurotux.com>
Update some images, add Section *Changelog* and change name UnitBox
- 2012-10-03 – Carlos Rodrigues <cmar@eurotux.com>
Section *Servers, Snapshots* added
- 2012-10-01 – Carlos Rodrigues <cmar@eurotux.com>
Section *Virtual cluster, Edit cluster* update *Node High availability*
- 2012-07-23 – Carlos Rodrigues <cmar@eurotux.com>
Section *Virtual cluster*, sub-section *Nodes* updated and rebrand some images for NUXIS
- 2012-07-20 – Carlos Rodrigues <cmar@eurotux.com>
Sub-section *Storage* updated
- 2012-07-13 – Carlos Rodrigues <cmar@eurotux.com>
Sub-section *Edit virtual machine* updated
- 2012-05-17 – Manuel Dias <mfd@eurotux.com>
Name change from ETVM to NUXIS. Sub-section *Edit virtual machine* updated
- 2012-04-20 – Carlos Rodrigues <cmar@eurotux.com>
Version change
- 2011-12-19 – Manuel Dias <mfd@eurotux.com>
English version of the manual
- 2011-11-30 – Manuel Dias <mfd@eurotux.com>
Sub-section *Drivers virtio* of Section *Virtual machine*
- 2013-02-11 – Carlos Rodrigues <cmar@eurotux.com>
Update some images and add Section *Changelog*
- 2012-11-08 – Carlos Rodrigues <cmar@eurotux.com>
Chapter *Installation*
- 2012-10-03 – Carlos Rodrigues <cmar@eurotux.com>
Section *Servers, Snapshots* added
- 2012-10-01 – Carlos Rodrigues <cmar@eurotux.com>
Section *Virtual cluster, Edit cluster* update *Node High availability*
- 2012-07-23 – Carlos Rodrigues <cmar@eurotux.com>

Section *Virtual cluster*, sub-section *Nodes* updated and rebrand some images for NUXIS

2012-07-20 – Carlos Rodrigues <cmar@eurotux.com>
Sub-section *Storage* updated

2012-07-13 – Carlos Rodrigues <cmar@eurotux.com>
Sub-section *Edit virtual machine* updated

2012-05-17 – Manuel Dias <mfd@eurotux.com>
Name change from ETVM to NUXIS. Sub-section *Edit virtual machine* updated

2012-04-20 – Carlos Rodrigues <cmar@eurotux.com>
Version change

2011-12-19 – Manuel Dias <mfd@eurotux.com>
English version of the manual

2011-11-30 – Manuel Dias <mfd@eurotux.com>
Sub-section *Drivers virtio* of Section *Virtual machine*

2011-11-21 – Manuel Dias <mfd@eurotux.com>
Sub-section *Virtual cluster management* of Section *System administration*

2011-10-13 – Manuel Dias <mfd@eurotux.com>
Sub-section *User, groups and permission administration* of Section *System administration*

2011-07-13 – Carlos Rodrigues <cmar@eurotux.com>
Sub-section *ETFW* of Section *ETVA Management Agents*

2011-07-01 – Carlos Rodrigues <cmar@eurotux.com>
Sub-section *Primavera* of Section *ETVA Management Agents*

2010-08-06 – Ricardo Gomes <rjg@eurotux.com>
Initial version.

Contents

1. NUXIS	9
2. Installation	11
2.1. Enterprise version	11
3. Central Management	18
3.1. First access	19
3.2. Default cluster	20
3.2.1. Nodes	20
3.2.2. Networks	20
3.2.2.1. Network administration	21
3.2.2.2. MAC address pool management	22
3.2.2.3. Virtual machines' network interfaces management	22
3.3. Virtual cluster	23
3.4. Virtualization server	24
3.4.1. Node information	27
3.4.2. Servers	27
3.4.2.1. Add virtual machine	28
3.4.2.2. Edit virtual machine	34
3.4.2.3. Remove virtual machine	37
3.4.2.4. Connect to a virtual machine over VNC	37
3.4.2.5. Start/stop virtual machine	38
3.4.2.6. Migrate virtual machine	39
3.4.2.7. Snapshots	39
3.4.3. Storage	39
3.4.3.1. Physical Volumes administration	40
3.4.3.2. Volume groups administration	42
3.4.3.3. Logical volumes administration	45
3.4.4. Node Load	47
3.4.5. Shutdown node	48
3.5. Virtual machine	50
3.5.1. Server information	50
3.5.2. Statistics	50
3.5.3. Services	52
3.5.4. Virtio drivers	53

3.6. Tools	56
3.6.1. Import OVF	56
3.6.2. Export OVF	61
3.6.3. ISO manager	61
3.6.4. Nodes' agent monitor	62
3.6.5. System events log	63
3.7. System administration	63
3.7.1. One time set wizard	63
3.7.2. Virtual cluster management	64
3.7.2.1. Virtual cluster setup wizard	65
3.7.2.2. Moving a node between datacenters	66
3.7.2.3. Authorize node	67
3.7.3. System Preferences	68
3.7.4. Users, groups and permission administration	69
3.7.5. Shutdown Central Management	74
4. Appendix	75
4.1. Changelog	75
4.1.1. Release 1.0	75
4.1.2. Release 1.0.1	76
4.1.3. Release 1.1	77
4.1.4. Release 1.2.0	78
4.1.5. Release 1.2.1	79
4.1.6. Release 1.2.2	80

List of Figures

1.1. NUXIS architecture	9
1.2. NUXIS model	10
2.1. Enterprise version menu installation	11
2.2. Enterprise version installation - Startup	12
2.3. Enterprise version installation - Configuration	13
2.4. Enterprise version installation - Packages	14
2.5. Enterprise version installation - complete installation	14
2.6. Configuration after installation - Boot	15
2.7. Configuration after installation - Login and network configuration	15
2.8. Configuration after installation - Authentication	16
2.9. Configuration after installation - First time configuration	16
2.10. Configuration after installation - Virtualization server	17
3.1. Layout principal	18
3.2. Authentication window	19
3.3. Central Management nodes view	20
3.4. System networks view and virtual machines' interfaces	21
3.5. Add network window	22
3.6. MAC pool creation window	22
3.7. Virtual machine interfaces (management window)	23
3.8. Edit cluster	24
3.9. Edit node	25
3.10. Agent connectivity configuration	26
3.11. Node maintenance	26
3.12. Node's information	27
3.13. Node's virtual machines	28
3.14. Add server wizard - Welcome	28
3.15. Add server wizard - Virtual machine name	29
3.16. Add server wizard - Memory	30
3.17. Add server wizard - Processors	30
3.18. Add server wizard - Storage	31
3.19. Add server wizard - Host network	32
3.20. Add server wizard - Startup	33
3.21. Add server wizard - Finished!	33

3.22. Edit server - General	34
3.23. Edit server - Network interfaces	35
3.24. Edit server - Disks	35
3.25. Edit server - Devices	36
3.26. Edit server - Other options	36
3.27. Edit server - High availability	37
3.28. Remove server window	37
3.29. Virtual machine boot parameters	38
3.30. Virtual machine migration	39
3.31. Snapshots	39
3.32. Information about node's storage	40
3.33. Context menu of a physical volume	41
3.34. Scan <i>physical devices</i>	41
3.35. <i>Storage iSCSI</i> list	42
3.36. Set up new <i>Storage iSCSI</i>	42
3.37. Context menu of a volume group	43
3.38. Create volume group window	43
3.39. Volume group extension	44
3.40. Scan <i>volume groups</i>	44
3.41. Logical volume context menu	45
3.42. Create a new logical volume window	46
3.43. Resize of a volume group	46
3.44. Scan <i>logical volumes</i>	47
3.45. Node load	47
3.46. Node usage statistics - CPU load	48
3.47. Shutting down a node	49
3.48. Information about the virtual machine	50
3.49. Virtual machine cpu load	51
3.50. Virtual machine network interfaces	51
3.51. Virtual machine memory usage	52
3.52. Virtual machine disk input/output	52
3.53. Driver's - iso selection	54
3.54. Set logical volume (drivers virtio)	54
3.55. Set the startup disk	55
3.56. Windows - driver update	55
3.57. Change the disk driver to virtio	56
3.58. OVF import wizard - Welcome	57
3.59. OVF import wizard - Source OVF file	57
3.60. OVF import wizard - OVF details	58
3.61. OVF import wizard - License	58
3.62. OVF import wizard - Name and location	59
3.63. OVF import wizard - Storage	60
3.64. OVF import wizard - Network interfaces	60

3.65.OVF import wizard - Finished!	61
3.66.OVF export window	61
3.67.Iso management panel	62
3.68.System events log window	63
3.69.One time setup wizard	64
3.70.Cluster management panels	65
3.71.Virtual cluster setup wizard	66
3.72.Move nodes between clusters (NUXIS version)	67
3.73.Node authorization	67
3.74.Authorize node - performing operation	68
3.75.System preferences window - General panel	68
3.76.System preferences window - Connectivity tab	69
3.77.Users' and permissions' administration - Manage Users	69
3.78.Users' and permissions' administration - Add user (Step 1)	70
3.79.Users' and permissions' administration - Add user (User details)	70
3.80.Users' and permissions' administration - Add user (User permissions)	71
3.81.Users' and permissions' administration - Add user (Final)	71
3.82.Users' and permissions' administration - Manage Groups	72
3.83.Permission option in node's context	72
3.84.Permission option in server's context	73
3.85.Changing servers' access permissions	73

1. NUXIS

Description

NUXIS is a centralized tool that allows the management of available resources on a network. It consists of a Linux distribution pre-installed and configured, which allows you to manage servers' resources.

The NUXIS is divided into two functional blocks:

- *Central Management (CM)*
- *Virtualization Agent (VA)*




Figure 1.1.: NUXIS architecture

The CM (Central Management) is the block responsible for managing the entire infrastructure. The *Virtualization Agents* are responsible for processing the requests between the virtualization server (*node*) and CM.

Within a virtualization server there may be virtual machines with *Management Agents*. These type agent enables the managing of existing services/applications on the virtual machine (see Figure 1.1).

In the NUXIS , there are several virtualization servers (nodes) that communicate with the CM. The initial network configuration is performed, using VLANs through the *One time setup wizard* as shown in Figure 3.69.




Figure 1.2.: NUXIS model

This user's manual describes the configuration management tool (CM - *Central Management*).

2. Installation

2.1. Enterprise version

To make installation we need to use CD-ROM with NUXIS ISO installation and boot the server from it.

For enterprise version, we need one server to install manager interface (*Central Management*) and do installation on each virtualization server.




Figure 2.1.: Enterprise version menu installation

In both cases, we need boot by CD-ROM and choose *Install NUXIS-ENTERPRISE* option to do the installation step-by-step.




Figure 2.2.: Enterprise version installation - Startup




Figure 2.3.: Enterprise version installation - Configuration




Figure 2.4.: Enterprise version installation - Packages

On packages interface we should choose *Nuxis Central Management* package for management interface installation, *Nuxis Kernel Virtual Machine* for virtualization server with KVM support and *Nuxis Xen Virtual Machine* for server with XEN support.




Figure 2.5.: Enterprise version installation - complete installation

At the end of installation, we start up the server and proceed to network configuration.




Figure 2.6.: Configuration after installation - Boot




Figure 2.7.: Configuration after installation - Login and network configuration

For network configuration, we should access to server console with login *root* and password and set the IP address.



Figure 2.8.: Configuration after installation - Authentication

Next we access to web interface with IP address and authentication with user *admin* and default password (*admin*).




Figure 2.9.: Configuration after installation - First time configuration

On first time configuration, we should change the admin password, generate MAC pool, change connectivity preferences and configure network (see 3.69).




Figure 2.10.: Configuration after installation - Virtualization server

After configure management interface and after install the virtualizations servers, it should be possible to see the servers registered on interface and authorize them (with right click menu) to allow the management.

3. Central Management

The main frame of Central Management consists in four areas:

Top panel - This panel provides the necessary menus for main system configuration, such as user administration, ISOs management and the interface that shows the system events.

Left panel (Nodes) - This panel lists the real machines/virtualization servers - **nodes** - and any existing virtual machines - **servers**. The first level of the tree show the system datacenters. After that level we can find the available physical servers, and on the bottom nodes the virtual machines. All features that can be done on each node of the tree, are described on Section 3.4(Node) and in Section 3.5(Server). When some node is clicked, its information is loaded and appears on the main panel.

Main panel (at right) - In this area is displayed the information about the selected node.

Information panel (at bottom) - This areas shows the volatile information about any operations made on the interface. Here we can found the success of the operations.




Figure 3.1.: Layout principal

3.1. First access

After the installation, the CM can be accessed on the web browser by entering the address `http://<IP ADDRESS>`¹




Figure 3.2.: Authentication window

The Figure 3.2 shows the first displayed frame, that asks the user his username and password. In this window we can also select the pretended language².

Note

The default credentials are:

Username: admin

Password: admin

For safety reasons the default password should be changed. This can be done after the first access, on the *first time wizard*.

During the first access, the user is prompted with some questions, that allows him to setup the system (see Section 3.7).

After the installation and configuration of the CM, and having an already installed agent, it should appear automatically on the left panel.

On the left panel, see Figure 3.1, will appear the virtualization *node* registered on CM. We can right click the *node* and select the option *Authorize*. In this case the cm sends a message to the virtualization agent, requesting information about the *node*. After the end of the authorization process, the *node* can be managed as stated on Section 3.4.

¹The ip address is specified during the installation process .

²Currently two languages are available: Portuguese and English

3.2. Default cluster

In this panel we can see an overview of the CM. The virtualization servers can be seen as well as any existing networks (see Figure 3.3).

3.2.1. Nodes

In *Nodes* we can see some information about the virtualization servers such as the supported hypervisor, the state of the virtualization server, among other info.




Figure 3.3.: Central Management nodes view

3.2.2. Networks

This panel allow us to do the following operations:

- System's network administration
- MAC address pool management
- Manage the virtual machines' network interfaces




Figure 3.4.: System networks view and virtual machines' interfaces

Also, it's possible to filter the network interfaces by a given network, as stated on Figure 3.4. The Figure 3.4 lists the network interfaces for the network *Internet*.

3.2.2.1. Network administration

To add a network, click on the *Add network* button.

The network info is constituted by its name and ID³

To remove a network, choose the desired network and press the button *Remove network*.

Note

The add/remove operations are only available on version NUXIS .

³If the network/vlan is *tagged*, the field *network ID* refers to its *VLAN ID* (see Figure 3.5)




Figure 3.5.: Add network window

After successfully add or remove a network, all Central Management nodes are notified.

3.2.2.2. MAC address pool management

On *MAC Pool Management* (see Figure 3.4), its possible to create new addresses. Also, we can see the associated network for each MAC address, and the available addresses.




Figure 3.6.: MAC pool creation window

3.2.2.3. Virtual machines' network interfaces management

If we select a network interface and access to the context menu, it's possible to remove the network interface associated to this record - *Remove network interface* or change the network interfaces for the associated virtual machine - *Manage network interfaces*.




Figure 3.7.: Virtual machine interfaces (management window)

On the management window it's possible to select the network card's driver⁴.

3.3. Virtual cluster

On left side panel it's possible to select a *cluster*(virtual cluster) and do the following operations:

- *Nodes* - View information about nodes (see Section 3.2.1)
- *Storage* - Storage management on *Cluster* context (see Section 3.4.3)
- *Networks* - Network management (see Section 3.2.2)

In addition. it's possible to access the context menu (right click) to perform the following operations:

- Edit cluster
- Remove cluster

In *Edit cluster* it's possible to change the name of *cluster* and allow use to activate nodes high availability.

⁴This option is available on HVM or KVM machines. The available drivers are: e1000, rtl8139 e virtio




Figure 3.8.: Edit cluster

When we enable *Node High availability*⁵, we may choose one of this options:

- *Host failures tolerates* - number of hosts in failure that we can guarantee high availability with restrictions of resources allocation;
- *Percentage of resources reserved to failover* - percentage of resources reserved to guarantee the high availability of critical services;
- *Spare node* - it's define one *spare node* that will be used to guarantee the high availability of one of the others nodes. This *spare node* should have necessary resources to ensure the availability of critical virtual servers of fail node.

The *Node High availability* provides, in failure case, the migration of the virtual servers by priority order (see figure 3.27), to keep the services of this virtual servers operational.

The operation *Remove cluster* removes information related to *cluster* (nodes, networks and storage) from the *Central Management* database.

3.4. Virtualization server

On panel *Nodes* it's possible to select a *node*(virtualization server), and do the following operations:

- See the *node* information (see Section 3.4.1)
- Manage its virtual machines (see Section 3.4.2)
- Manage *node* storage (see Section 3.4.3)

In addition to these options, it's possible to access the context menu (right click). This menu allow us to perform the following operations:

⁵The option *Node High availability* will be enable only if *fencing* configuration is defined for all node (see 3.4)

- Load node
- Edit node
- Remove node
- Connectivity options ⁶
- Change keymap
- Check node state

In *Load node*, it's send one request to *Central Management* for node state update.

For operation *Edit node* it's available edition of server virtualization proprieties like name and *fencing* device configuration.




Figure 3.9.: Edit node

In *Enable fencing configuration* we can activate *fencing* device for node management and configure the parameters accord on following types: *bladecenter*, *virsh*, *ilo*, *ipmilan* e *rsa*.

The operation *Remove node* removes one node from the *Central Management* and delete the information related to it on database.

In *Connectivity options*, it's possible to configure the interface *Management* that is connected with the virtualization agent.

⁶Only available on version *NUXIS*




Figure 3.10.: Agent connectivity configuration

In *Change keymap*, depending on the selected item, the virtualization server or virtual machine, it's possible to define the standard VNC keymap, or the specific virtual machine keymap.

In *Node status*, it's possible to access to subset of options:

- Check status - it send an request to the virtualization server to check the agent connectivity
- Maintenance / Recover - Put the node in maintenance/recover mode
- Shutdown - it shuts node down (see Section 3.4.5).

In operation *Maintenance* we able to put node in maintenance mode in order to run maintenance tasks.




Figure 3.11.: Node maintenance

When node is moved to maintenance mode, the virtual servers will be migrated by priority order (see figure 3.27).

The operation *Recover* runs some tasks like node agent status check, connectivity and storage info consistency, before recover node from maintenance mode.

3.4.1. Node information

In *Node information* we can see the information about the virtualization server. We can see the "real" machine supported hypervisors and, among other information, the virtualization agent's state.





Figure 3.12.: Node's information

3.4.2. Servers

In *Servers* we can see the information of every virtual machines existing on the selected virtualization server. In addition, allows to perform the following operations:

- Add a virtual machine
- Edit a virtual machine
- Remove virtual machine
- Access virtual machine in a VNC console
- Start/Stop virtual machine
- Migrate virtual machine
- Snapshots



Name	Description	Memory (MB)	CPUs	IP	Type	State
Centos6	Linux	4096	4	000.000.000.000	kvm	running
ETFW	Linux	512	1	000.000.000.000	hvm	stop
linuxserver	Linux	5120	4	000.000.000.000	hvm	stop
npfcentos5	Linux	4096	4	000.000.000.000	hvm	stop
pxecient	Linux	512	1	000.000.000.000	kvm	running
srvLinux	Linux	1024	2	000.000.000.000	kvm	stop
Ulteo	Linux	4096	4	000.000.000.000	kvm	running
win2k3	Windows	2048	2	000.000.000.000	kvm	running
windows	Windows	4098	3	000.000.000.000	kvm	stop
winVio	Windows	2048	2	000.000.000.000	kvm	stop


Figure 3.13.: Node's virtual machines

3.4.2.1. Add virtual machine

To add a new virtual machine, press the button *Add server wizard*.

Note

The panel options will be enable, if the virtualization agent is running on the *node* (physical machine) and if it is able to establish a connection with the CM.



Add server wizard

Create new virtual server

Step 1 of 8: Welcome

Steps

1. Welcome
2. Virtual server name
3. Memory
4. Processor
5. Storage
6. Host network
7. Startup
8. Finished!

Welcome to the virtual server creation wizard.
Follow the steps to configure a full capable server

< Previous Next > Cancel

Figure 3.14.: Add server wizard - Welcome

The server wizard has the following steps:

Virtual machine name: In this step we can define the virtual machine name and the type of the operating system. The operating system option varies depending on the type of virtualization node.

- with XEN e hardware virtualization support:
 - Linux PV
 - Linux HVM
 - Windows
- with XEN without hardware virtualization support:
 - Linux PV
- with KVM
 - Linux
 - Windows




Figure 3.15.: Add server wizard - Virtual machine name

Memory: Total assigned memory.




Figure 3.16.: Add server wizard - Memory

Processor: In this stage is necessary choose the number of processor that the virtual machine will have access.




Figure 3.17.: Add server wizard - Processors

Storage: Defines the boot disk for the virtual machine. One of three options can be chosen:

- use an existing logical volume/file - *Existing logical volume*

- create a new logical volume - *New logical volume*
- at last, a file can be created on the option *New file*




Figure 3.18.: Add server wizard - Storage

Note

If the *node* does not support *physical volumes* the option *Existing logical volume* will be disabled.

Host network: Network interfaces for the server. If there are no available MAC addresses, it's possible to create new ones by pressing the *MAC pool management*. Is also possible to create networks in this step using the button *Add network*.




Figure 3.19.: Add server wizard - Host network

Startup: Specifies startup parameters of the virtual machine. The options at this stage vary with the type system, defined in step *Virtual machine name*:

- *Linux PV*
 - Network installation. Url of the kernel.
- Others
 - Network Boot (PXE)
 - CD-ROM (ISO)

The figure 3.20 refers to a virtual machine options for *Linux* in *KVM*.




Figure 3.20.: Add server wizard - Startup

Finished! Final step of the wizard. After confirmation of the creation of the server, the data collected in previous steps are processed and sent to the virtualization server. Later in the panel *servers* the virtual machine can be initiated through the option *Start server*.




Figure 3.21.: Add server wizard - Finished!

3.4.2.2. Edit virtual machine

To edit a server, you choose the machine you want and click on *Edit server*.

Note

If the virtual machine is running, depending on the virtual machine type and the virtualization system, some options will be disabled, it is required to stop the machine in order to make the changes.

The following options are available on virtual machine configuration:

General: This allows change the name, memory, number of CPUs and number of sockets, cores and threads, operating system and boot parameters. The boot parameters vary depending on the virtual machine type and the virtualization system. (see Section 3.4.2.1).




Figure 3.22.: Edit server - General

Network interfaces: Add/remove interfaces. Here we can change the type of driver to use⁷.

⁷You can only specify the driver to use if the virtual machine is HVM and KVM




Figure 3.23.: Edit server - Network interfaces

Disks: Add/remove machine disks. To add/remove a disk, select the desired disc and drag-n-drop between the tables.

Note

The boot disk is the disk of the machine that is in first position of the table.




Figure 3.24.: Edit server - Disks

Devices: Attach/detach USB/PCI devices into the virtual server. A device can only be associated with one virtual server.

Note

If the virtual server have any associated devices, it cannot be migrated/move into another node of the cluster.




Figure 3.25.: Edit server - Devices

Other options: Lets you set VNC options like keymap and configure ACPI, APIC and PAE flags.




Figure 3.26.: Edit server - Other options

High availability: Provides a way to configure server priority to start and to migrate and define if high availability is active on this server.

Nota

For *VM High availability* we set heartbeat timeout that server should be restart if not responding. This option will be available only if the guest tools are installed on virtual machine.




Figure 3.27.: Edit server - High availability

3.4.2.3. Remove virtual machine

To remove a server, choose the machine to remove and click on the button *Remove server*. The *Keep disks* option keeps the hard disks connected to the machine, otherwise it will also be removed.




Figure 3.28.: Remove server window

3.4.2.4. Connect to a virtual machine over VNC

Selecting a server and then clicking on button *Open console* is possible to establish a VNC connection with the machine, since the machine is running.

Note 1

If the keyboard is mangled you can change the *VNC keymap* through the option *Set keymap* available in parent node context menu. Also, the *keymap* can be defined in each server, through the option *Edit server*.

Note 2

When open VNC console with HTTPS we may get the following error:

Network Error: sun.security.validator.ValidatorException: PKIX path building fa

In this case, it maybe required to add server certificate to Java *keystore*⁸. For do that, we can run this command:

```
keytool -import -keystore $JAVA_HOME/lib/security/jssecacerts -file server-cert
```

Note: for keystore without password we can use "changeit"

After that, we need restart the browser.

3.4.2.5. Start/stop virtual machine

It's possible to choose between one of the following boot parameters to start the virtual machine:

VM Filesystem: Boot from the disk associated with the server.

PXE: Boot from PXE⁹.

Location URL: Boot from url defined in *Location*¹⁰.

CD-ROM: Boot from a CD-ROM image⁹.




Figure 3.29.: Virtual machine boot parameters

It's possible to choose the option *Start server With console* to allow start the server and open console.

⁸For more information access to the following links: <http://docs.oracle.com/javase/7/docs/technotes/tools/solaris/keytool.html> and <http://docs.oracle.com/javase/7/docs/technotes/guides/deployment/deployment-guide/jcp.html>

⁹Only available if the type of virtual machine is not *Linux PV*

¹⁰Only available if the type of virtual machine is *Linux PV*

3.4.2.6. Migrate virtual machine

Selecting a server and then clicking on *Migrate server* you can migrate a machine from a *node* to another, since they share the same storage.




Figure 3.30.: Virtual machine migration

Note

This option is only available on *NUXIS*.

3.4.2.7. Snapshots

In *Snapshots* we can create one *snapshot* of virtual machine state, that consists on disks snapshots and, if virtual machines is running, the state of virtual machine on that moment. It's also possible revert, remove or download of backup of one virtual machine snapshot.




Figure 3.31.: Snapshots

3.4.3. Storage

The information about the existing volumes on the *node* can be found on the tab *Storage*. This panel is divided into three sections:

Devices - Information about the *physical volumes*¹¹ and its state. Allows to do the *physical volumes* administration of the *node*.

¹¹A *physical volume* it's a physical device, such as a disk

Volume Groups - List of *volumes groups*¹² existing in the node and its associated *physical volumes*. Allow *volume groups* management.

Logical Volumes - Displays information about the *logical volumes*¹³ *node*. *Logical volumes* administration area.

Note

There is a special *volume group*, `__DISK__`, used in the handling of files. When creating a *logical volume*, this tag is used to indicate that the disk to be used is not a *logical volume* but a file.




Figure 3.32.: Information about node's storage

3.4.3.1. Physical Volumes administration

The *physical volumes* administration consists of the following operations:

- Initialize *physical volume*
- Uninitialize *physical volume*
- Register/Unregister *physical volume*
- Set up Storage iSCSI

¹²A *volume group* is the aggregation of several *physical volumes* in a single virtual volume

¹³A *logical volume* it's a slice of a *volume group*. It's used as a system's partition




Figure 3.33.: Context menu of a physical volume

To initialize a *physical volume*, access to the sub-context menu of the device and select *Initialize physical volume*. To remove a *physical volume* the operation is similar, simply select the option *Uninitialize physical volume* in the context menu.

Note

The *physical volume* can only be removed if it does not belong to any *volume group*.






Figure 3.34.: Scan physical devices

On "Scan *physical devices*" it is possible to run a task on virtualization agent to look-up new disks and to register them on *Central Management*. It is also possible to unregister the physical device on *Central Management* to get it out of system management.

For *storage iSCSI* configuration go to "Scan *physical devices*" web interface and select "Storage iSCSI" menu.

Figure 3.35.: *Storage iSCSI* list

When we choose this option, we have access to the interface of the figure 3.35 and we can review all *Storages* connections previously configured and set up another one.

Figure 3.36.: Set up new *Storage iSCSI*

For set up a new *storage iSCSI* connection, we need to provide a name and *IP* address and click on *discovery* for fill "*Target IQN*" field. Review all fields filled and click on "*Save*" for to create configuration on node agents.

We have also more options for the *Storage iSCSI* management like reload configuration on all node agents on option "*Reload Storage iSCSI*" and remove configuration on option "*Remove Storage iSCSI*".

3.4.3.2. Volume groups administration

In the administration of *volume groups* is allowed to:

- Add *volume groups*

- Extend a *volume group*
- Re-size a *volume group*
- Remove a *volume group*
- Register/Unregister *volume group*




Figure 3.37.: Context menu of a volume group

To create a *volume group*, access to the context menu on any *volume group* and select *Add volume group*. The *volume group* name should be introduced and selected one or more *physical volumes* available.

A *physical volume* is available when volume is not allocated to any *volume group* and it's initialized.




Figure 3.38.: Create volume group window

To extend a *volume group* drag and drop a *physical volume* into a *volume group*.

In the removal/reduction of a *volume group*, select the *volume group/physical volume* to remove and choose the corresponding option in the context menu.

Note

It's only allowed to remove a *volume group* if there is no associated *logical volumes*.




Figure 3.39.: Volume group extension

On Figure 3.39 we extend a *volume group* with a new *physival volume*.




Figure 3.40.: Scan volume groups

On "Scan *volume groups*", it is possible to get *volume groups* from virtualization agent and register them on *Central Management*. It is also possible to unregister the *volume group* on *Central Management* to get it out of system management.

3.4.3.3. Logical volumes administration

The operations available on the *logical volumes* are:

- Create a *logical volume*
- Resize a *logical volume*
- Remove a *logical volume*
- Register/Unregister *logical volume*
- Clone *logical volume*
- Convert *logical volume*




Figure 3.41.: Logical volume context menu

To create a new *logical volume*, we access the context menu (over any *logical volume*, and select the option *Add logical volume*.

The pretended name should be introduced in the creation window form, such as the *volume group* size. Note that the size should not exceed the *volume group* available size. It's also possible define the format of disk (raw, cow2,qcow,cow and vmdk - raw by default) and percentage of *snapshot* usage.




Figure 3.42.: Create a new logical volume window

To resize a *logical volume*, select and access into the context menu. Then we can find the option *Resize logical volume*, that allows us to increase/reduce the *logical volume* size.

Note

By reducing the size of a *logical volume* could make existing data unusable. It is your responsibility to check that it is affordable/secure resizing the *logical volume* without affecting the data.




Figure 3.43.: Resize of a volume group

To remove a *logical volume*, access the context menu and select the option *Remove logical volume*. The *logical volume* will be removed if it's not assigned to any virtual machine. To verify if it is in use you may pass the mouse over the *logical volume* and observe the information contained in the *tooltip*.

We have the operation to clone one *logical volume*, if *volume group* have free space to do the copy. And we can convert the disks format to one of the formats (raw, qcow2, qcow, cow and vmdk).




Figure 3.44.: Scan logical volumes

On "Scan logical volumes" it synchronizes *logical volumes* that are on virtualization agent and they are not registered on *Central Management*. It is may be possible that exist *logical volumes* that are registered on *Central Management* but really don't exist for some reason. In this cases, it is possible remove the register from the system and get the *logical volumes* synchronized with "Scan logical volumes".

3.4.4. Node Load

In the *Node Load* panel, we can find information about the node's load. In Figure 3.45, we can see the load information of the node in a hour range.




Figure 3.45.: Node load

In this panel we can also view the data by intervals:

- Last hour
- Last 2 hours
- Last 24 hours
- Last week

To view other time intervals use the option *Generate graph image*. The image is generated as shown in figure 3.46.




Figure 3.46.: Node usage statistics - CPU load

3.4.5. Shutdown node

Through the Central Management interface we can power off a physical node. To do so do the following steps:

- On the left panel, select the desired node. Then access to it's context menu;
- Press the option *Shutdown*.

Note

During the procedure, all node's virtual servers will also turned off.




Figure 3.47.: Shutting down a node

3.5. Virtual machine

In the nodes pane we can select the virtual machine on which we intend to perform operations such as:

- Manage the virtual machine
- View usage statistics
- Manage *Management Agent* services

3.5.1. Server information

In *Information Server* we can see the state of the virtual machine and, among other information, the state of the *Management Agent*. In addition to displaying information, this panel lets you perform the following operations:

- Add a virtual machine (see Section 3.4.2.1)
- Edit a virtual machine (see Section 3.4.2.2)
- Remove virtual machine (see Section 3.4.2.3)
- Open a virtual machine in a VNC console (see Section 3.4.2.4)
- Start/stop virtual machine (see Section 3.4.2.5)
- Migrate a virtual machine (see Section 3.4.2.6)
- Snapshots (see Section 3.4.2.7)




Figure 3.48.: Information about the virtual machine

3.5.2. Statistics

In *statistics* tab it's possible to see, graphically, information about:

- Cpu Usage (Figure 3.49)
- Networks (Figure 3.50)
- Memory Usage (Figure 3.51)
- Disk (Figure 3.52)




Figure 3.49.: Virtual machine cpu load




Figure 3.50.: Virtual machine network interfaces




Figure 3.51.: Virtual machine memory usage




Figure 3.52.: Virtual machine disk input/output

In each of these panels we can view the data by pre-set intervals. For more information see Section 3.4.4.

3.5.3. Services

In *Services* tab panel, we can configure the available services on the corresponding management agent.

3.5.4. Virtio drivers

The virtio drivers facilitate communication between the operating system that runs the virtual machine, and the various hardware components. These components are the network devices and storage units - disks. As the use of the virtio drivers increases the overall system, its installation is recommended.

If the virtual machine's operating system is a complete Linux distribution whose kernel is a version less than 2.6.25, the virtio is supported without the need to follow any procedure to install the drivers. To take advantage of, simply select the driver tab virtio *Network Interfaces* and *Disks* on *server edit* window.

The requirements for the use of the virtio drivers can be found at:

<http://wiki.libvirt.org/page/Virtio>

Installation on windows virtual machines

Download the iso with the drivers, available at:

<http://alt.fedoraproject.org/pub/alt/virtio-win/stable/>.

Upload iso with the drivers - more information in Section 3.6.3. *Tools, ISO Manager, upload applet*, select the file and upload. The file should appear in the list of ISOs.

Then select the server where you want to install the drivers, and choose the *Edit server*. Choose the ISO image with the drivers as shown in Figure 3.53. Go to the tab *Disk* and assign a new volume, choosing the virtio driver - Figure 3.54.




Figure 3.53.: Driver's - iso selection




Figure 3.54.: Set logical volume (drivers virtio)

Set the startup disk server as shown in Figure 3.55.




Figure 3.55.: Set the startup disk

With Windows running, go to device manager. Note that the added logical volume appears as shown in Figure 3.56.

Then select the *Update Driver Software, Browse my computer for driver software*, indicate where is the drivers (in the virtual CD drive), completing the installation procedure.




Figure 3.56.: Windows - driver update

Stop the virtual machine and edit the settings by changing the main driver of the logical volume where you installed the operating system - Figure 3.57.




Figure 3.57.: Change the disk driver to virtio

3.6. Tools

In menu *Tools* we can access the following options:

- Import OVF
- Export OVF
- ISO Manager
- Node agent monitor
- System events' log

3.6.1. Import OVF

This tool allows you to import virtual machines in OVF format (*Open Virtualization Format*).




Figure 3.58.: OVF import wizard - Welcome

The OVF import wizard is constituted by the following stages:

Source OVF file: In this stage we define the OVF file URL (see Figure 3.59).

Note

The CM must have HTTP access to the specified URL.




Figure 3.59.: OVF import wizard - Source OVF file

OVF details: OVF file details. Provides information about the product, version, total size of the files referenced by the OVF, if available.




Figure 3.60.: OVF import wizard - OVF details

License: If specified in the OVF file, this step will come with the EULA. Otherwise, this step is omitted.




Figure 3.61.: OVF import wizard - License

Name and location: This step defines the virtual machine name, the destination node and the type of operating system. The operating system options vary depending on the specification of the node:

- with XEN and hardware hardware support:

- Linux PV
- Linux HVM
- Windows
- with XEN and without the hardware support:
 - Linux PV
- with KVM
 - Linux
 - Windows




Figure 3.62.: OVF import wizard - Name and location

Before proceeding to the next step, the wizard checks if the disks' drivers and network interfaces mentioned in the OVF are supported by the chosen virtualization server.

The supported drivers by XEN machines, with or without hardware virtualization, are: IDE, SCSI and xen and in machines with KVM drivers are: ide, virtio and scsi.

The supported network card drivers for HVM and KVM machines are: e1000, virtio and rtl8139. On a XEN machine without hardware virtualization support, no drivers can be used.

If the selected virtualization server does not support the drivers mentioned, the OVF import can not be performed.

Storage: This step is carried out mapping of disks in the node. You can specify the name of the *logical volume* and define the its *volume group*. It is required that all disks are mapped to proceed to the next step.




Figure 3.63.: OVF import wizard - Storage

Network interfaces: In this stage we map the network interfaces. You can specify new network interfaces. It is necessary that all the network interfaces are mapped to proceed to the next step.




Figure 3.64.: OVF import wizard - Network interfaces

Finished!: Final step of the wizard. After confirmation of the import of virtual machine, the collected data in previous steps are processed and sent to the virtualization server. Later in the panel *server* the virtual machine can be initiated through the option *Start server*.




Figure 3.65.: OVF import wizard - Finished!

3.6.2. Export OVF

This tool allows you to export virtual machines in OVF format (*Open Virtualization Format*). The generated file will be in the OVA format (*Open Virtualization Archive*).

Note

The virtual machine to export needs to be stopped to perform the export.




Figure 3.66.: OVF export window

3.6.3. ISO manager

this tool allows you to manage the images that will be available for use in virtual machines. The files will be used later for mounting virtual machine's *CD-ROM* unit.




Figure 3.67.: Iso management panel

The supported operations are:

- Upload of multiple files
- Download of files
- Rename files
- Delete files

Note


Changes to existing images that are set at boot from CD-ROM of any virtual machine, will not be reflected automatically. The user must check if the mounted image on the CD-ROM unit is still valid.

3.6.4. Nodes' agent monitor

This tool is for real-time communication testing of the multiple nodes of the CM. Verification is done periodically. To stop checking close the pop up that appears when activating the tool.

3.6.5. System events log

In *System events log* menu it's possible to see the changes made by user interaction.



System events log			
Filter by log level			
Id	Level	Message	Created At
47294	Info	{blade01} Node blade01 updated	2011-12-21 10:19:38
47280	Info	{blade01} Node blade01 updated	2011-12-21 10:18:37
47266	Info	{blade01} Node blade01 updated	2011-12-21 10:17:36
47251	Info	{blade01} Node blade01 updated	2011-12-21 10:16:34
47238	Info	{blade01} Node blade01 updated	2011-12-21 10:15:33
47224	Info	{blade01} Node blade01 updated	2011-12-21 10:14:32
47211	Info	{blade01} Node blade01 updated	2011-12-21 10:13:30
47196	Info	{blade01} Node blade01 updated	2011-12-21 10:12:28
47182	Info	{blade01} Node blade01 updated	2011-12-21 10:11:27
47168	Info	{blade01} Node blade01 updated	2011-12-21 10:10:26

Page 1 of 4095 | Displaying 1 - 10 of 4094 | Show 10 records at a time

Figure 3.68.: System events log window

The event log messages can be filtered by three message types:

- **Debug** - Displays all messages. Aggregate levels *Info* and *Error*
- **Info** - Messages with information on events that have been successful
- **Error** - Messages with information on events that haven't been successful

3.7. System administration

In the *System administration* menu it's possible we can access to:

- One-time setup wizard
- Cluster setup wizard
- Change preferences
- Users' and permissions' administration

3.7.1. One time set wizard

The initialization setup wizard gathers the set of operations to be carried out on first access to the CM. Lets you make a quick system configuration.

The setup wizard, as shown in Figure 3.69, consists in the following steps:

- Default password change

- MAC pool generation
- System preferences
- Network setup




Figure 3.69.: One time setup wizard

Note

On version *NUXIS*, the network configuration step is omitted.

3.7.2. Virtual cluster management

When we select one of the tree nodes that appears in the left panel, is shown in the right panel its context panels - Figure 3.70. In them you can manage the networks and shared storage volumes, always in the context of the selected virtual datacenter (cluster).




Figure 3.70.: Cluster management panels

3.7.2.1. Virtual cluster setup wizard

The cluster setup wizard enables the definition of a new cluster of nodes. Each cluster has its own networks, and shared storage volumes ¹⁴.

To open the wizard select *System Administration* followed by the option *Cluster setup wizard*. Then you will see the setup window, which requires the following configuration steps (Figure 3.71):

1. Set the name of the data center, which can be changed later
2. Define the networks that nodes are going to have access. For more information see Section 3.2.2

¹⁴Option only available in version *NUXIS*




Figure 3.71.: Virtual cluster setup wizard

3.7.2.2. Moving a node between datacenters

You can move nodes between existing data centers. For this purpose it is necessary that the node has not been authorized, i.e., by selecting the option *Authorize* in the node's context menu - see Figure 3.72).

To move, drag and drop the node to the desired target (datacenter).




Figure 3.72.: Move nodes between clusters (NUXIS version)

3.7.2.3. Authorize node

When a new node is added, it appears in the left pane with the text color in blue. In this case, in order to manage through the *Central management*, you must authorize it.

To proceed with the authorization, select the desired node and access into its context menu (right click on the mouse button). Then select *Authorize*. The Figure 3.73 and 3.73 illustrate the process.




Figure 3.73.: Node authorization




Figure 3.74.: Authorize node - performing operation

In the authorization process, the *Central Management* checks if the node has the same vision of shared storage volumes as the other cluster nodes. If an error occur, check the system's event log - see Section 3.6.5.

3.7.3. System Preferences

By accessing the system references you can set some parameters. In the general panel you can specify the default VNC keymap to access virtual machines as well as define the duration of the event logs of the system.




Figure 3.75.: System preferences window - General panel

In the connectivity tab you're allowed to change the CM IP address and for the LAN network (only available in *NUXIS* version). In the *UnitBox* version you are only allowed to change the CM IP.




Figure 3.76.: System preferences window - Connectivity tab

3.7.4. Users, groups and permission administration

The administration menu is available to the super users the system, and can be found on the top bar (then *System Administration*), in *Users' and permissions' administration*.

When we select this option, a window with two following tabs is open:

- *User management*;
- *Group management*.

The image 3.77 illustrates the window that appears. In this window, users can be created to access the management interface, and assigned access permissions on virtual machine level, or on cluster cluster level.




Figure 3.77.: Users' and permissions' administration - Manage Users

For create new user, there is setup wizard where it can be configured the following user data: name, email, password, group and permissions.




Figure 3.78.: Users' and permissions' administration - Add user (Step 1)




Figure 3.79.: Users' and permissions' administration - Add user (User details)




Figure 3.80.: Users' and permissions' administration - Add user (User permissions)




Figure 3.81.: Users' and permissions' administration - Add user (Final)

To facilitate the assignment of permissions you can set groups. For example, one group can have several associated permissions, and can be assigned to multiple users. This makes adding/removing a set of permissions to users easier.




Figure 3.82.: Users' and permissions' administration - Manage Groups

In addition, you have another way to assign permissions and/or groups, right clicking the mouse on the desired node/server, as stated on Figures 3.83, 3.84 and 3.85.




Figure 3.83.: Permission option in node's context




Figure 3.84.: Permission option in server's context




Figure 3.85.: Changing servers' access permissions

Note

In *Manage groups* it's not possible to remove the group with ID=1 (system reserved).

3.7.5. Shutdown Central Management

To turn off Central Management we must access the *System Administration* menu, and choose the *Shutdown Central Management* option. Then answer yes to the confirmation question.

Note

Shutting down Central Management will also terminate any existing virtual machines.

4. Appendix

4.1. Changelog

4.1.1. Release 1.0

- feature - Multiple datacenter support (see #209)
- bug fix - OVF network import
- bug fix - several fixes on browser interface (ExtJS)
- bug fix - devices consistency check
- bug fix - "resize" and "remove" logical volume messages
- bug fix - consistency check when cloning a logical volume
- bug fix - user permissions in server context
- feature - better debug messages (on nodes)
- bug fix - Servers' state check: unassigned VMs filtered
- feature - crons reviewed for failure notification
- bug fix - refresh button of the tree that lists all Nodes/Servers
- bug fix - VMs icons after a state change
- bug fix - logrotate configuration
- feature - NRPE Plugin for Nagios integration (see #272)
- improvement - Symfony ORM updated to version 1.6
- bug fix - refresh of the "not mounted" logical volumes
- bug fix - total number of fork in the VA
- improvement - interface translations
- feature - diagnostic mechanism (see #189)
- feature - validator for the location field available during the installation of paravirtualized VMs (see #193)
- bug fix - virtagent memory leak (see #179)

- feature - servers with autostart

4.1.2. Release 1.0.1

- bug fix - PAE and APIC defined by default (see #400)
- bug fix - update mounted logical volume (see #392)
- bug fix - LVM compatibility commands (see #311)
- bug fix - read-only devices (see #311)
- bug fix - mounted flag and swap devices (see #311)
- bug fix - ccis/c* devices (see #311)
- bug fix - parser for pvinfo devices (/dev/mapper/...) (see #311)
- bug fix - consistency check on devices (see #320)
- bug fix - default gateway setting when a new network is added (see #372)
- bug fix - SOAP commands to unauthorized nodes (see #333)
- bug fix - Boot from logical volume option (new server wizard) (see #373)
- bug fix - choose from available mac-addresses on server network interfaces configuration (see #371)
- bug fix - network boot scripts (see #332)
- bug fix - mouse bus for paravirtualized servers (see #341)
- bug fix - VLAN Name-Type configuration VLAN_NAME_TYPE_PLUS_VID_NO_PAD (see #328)
- bug fix - cluster node election reviewed. (errors in logical volumes creation on cluster context) (see #323)
- bug fix - concurrent logical volume creation (see #301)
- bug fix - IE9 compatibility errors (JS) (see #307)
- bug fix - field validation on server wizard (KVM) (see #309)
- bug fix - netmask calculation for network interfaces (see #315)
- bug fix - user permissions in cluster level (see #397)
- bug fix - Virtagent IP address (see #409)
- bug fix - logical volume clone in two steps (1 - lv create; 2 - lv clone) (see #391 and #393)
- bug fix - disallowance of 'dev' named networks (see #379)
- bug fix - server info panel changed to include the disk type and network interface model

(see #405)

- bug fix - improved error messages (see #382)
- bug fix - bus=xen when device=cdrom and hypervisor for xen (see #381)
- bug fix - Anaconda's selinux doesn't work. SeLinux? disabled in postscript. (see #410)

4.1.3. Release 1.1

- bug fix - problem with VMs without state identified as notrunning when really are running (see #386)
- bug fix - problem in changing the agent's hostname (see #434)
- bug fix - problem generating CA certificate's cn (see #432)
- bug fix - fix spec to correct certificates (see #436 and #472)
- bug fix - increase dom0_mem to 1500MB (see #411)
- bug fix - fix xend-config to allow migration of vms (see #437)
- bug fix - problem adding physical volumes to volume group (see #440)
- bug fix - xen driver support to nics in Xen+HVM (see #446)
- bug fix - automatic start of vms that are marked as 'running' (see #460)
- bug fix - conflict in disk type of shared harddisks between vms (see #462)
- bug fix - error removing harddisk from vm (see #463)
- bug fix - error opening Mac Pool in vm creation wizard (see #465)
- bug fix - nos paths do physical disks (see #471)
- bug fix - physical disk initialization (see #473)
- bug fix - context menus in storage (pvs,vgs,lvs) (see #474)
- bug fix - move vm while node is down (see #412)
- enhancement - update kvm to 0.15.0 (see #316)
- enhancement - update xen to 4.1.2 (see #420)
- enhancement - update virtio-win to 0.1-22 (see #424)
- enhancement - add feature for specify CPU sockets, cores and threads (see #425)
- enhancement - Add windows xen drivers (see #427)
- enhancement - upgrade libvirt to 0.9.4
- enhancement - Allow the creation of vms without harddisk (see #292)
- enhancement - pass-through of USB and PCI devices (see #300)

- enhancement - Allow the creation of vms without nics (see #308 and #345)
- enhancement - Windows and Linux guest agent (see #353)
- enhancement - VM Priority Restart (see #355)
- enhancement - Rebrand Nuxis (see #422)
- enhancement - VM High-available (see #431)
- enhancement - Node High availability (see #430)
- enhancement - harddisk search (see #258)
- enhancement - Node shutdown (see #205)
- enhancement - Allow vm edit while it is running (see #461)
- enhancement - Change the type of vm (see #399)
- enhancement - Define APIC, ACPI and PAE of the VM (see #374)
- enhancement - Menu start/stop vm in treeview (see #347)
- enhancement - Order logical volumes (see #343)
- enhancement - Improve storage management (see #325, #329, #331 and #335)
- enhancement - Search new physical disks (see #247)
- enhancement - Allow resizing vm disks while running (see #228)
- enhancement - Support the installation of RedHat? 6, Ubuntu e Debian in XEN-PV (see #288 and #321)

4.1.4. Release 1.2.0

- bug fix - Flags pae, acpi, apic (see #520)
- bug fix - edit live server change os to windows (see #510)
- bug fix - boot by cdrom on VMs with HVM (see #518)
- bug fix - Problem installing Centos 6 guest VM on Xen+HVM (see #446)
- bug fix - USB pass-through problems (see #413)
- bug fix - Migrate in mode live (see #531)
- enhancement - Update virtio drivers to 0.1-30 (see #503)
- enhancement - rename default datacenter (see #368)
- enhancement - start server with console (see #287)
- enhancement - create/convert disks with format (raw, qcow2, qcow, cow, vmdk) (see #479)

- enhancement - datacenter permissions on datacenter level (see #398)
- enhancement - ovf import: allow mac-address configuration (see #370)
- enhancement - Snapshots and backups using snapshots (see #127)
- enhancement - Node High-available without Spare Node (see #514)
- enhancement - VM Admission Gate (see #513)

4.1.5. Release 1.2.1

- bug fix - edit server (see #557)
- bug fix - boot from disk on XEN PV (see #560)
- bug fix - user permissions (see #546 see #547)
- bug fix - edit datacenter (see #558)
- bug fix - save connectivity preferences (see #564, see #581 and #584)
- bug fix - edit server live mode (see #570 and #569)
- bug fix - edit server and change cdrom on XEN+HVM (see #574)
- bug fix - issues with USB passthrough (see #568)
- bug fix - issues server HA (see #563)
- bug fix - ETVA::NetworkTools::fix_hostname_resolution (see #516)
- bug fix - start VM (see #554)
- bug fix - disks interface of edit server (see #501)
- bug fix - remove datacenter (see #572)
- bug fix - remove server and disk (see #571)
- bug fix - problem with create datacenter (see #565)
- bug fix - problems when don't have snapshots support (see #550)
- bug fix - issues with update and install scripts (see #542 and #527)
- bug fix - requires qemu-img > 0.14 (see #548)
- bug fix - edit server to change VM type (see #543)
- bug fix - missing icons on server menu (see #578)
- bug fix - on call for scan of Fiber-channel disks (see #593)
- bug fix - problem with LV names (see #595)
- bug fix - VNC console with HTTPS/SSL connection (see #597)
- bug fix - xend configuration to accept live migrate connections (see #599)

- bug fix - remove/resize lv when agent restarts (see #604)
- bug fix - agent lock after restarts (see #607)
- bug fix - on detect LV format function caused by names conflict (see #608)
- bug fix - mount etva_iso call after CM URL changed (see #611)
- bug fix - problems with VNC console authentication (see #612)
- bug fix - agent doesn't restart properly (see #614)

4.1.6. Release 1.2.2

- bug fix - Fetch install logs script with diagnostics (see #639)
- bug fix - Add new checks to lcdagent (see #645)
- bug fix - scan new physical volumes (see #629)
- bug fix - virtagent-libs requires perl(Sys::Virt) (see #648)
- bug fix - datacenter permissions (see #644)
- bug fix - call diagnostic (see #640 and #641)
- bug fix - VNC errors after some time (see #634)
- bug fix - VNC Authentication Required errors for different Timezone (see #626)
- bug fix - rename VM for KVM (see #625)
- bug fix - send stats after VM migrate (see #576)
- bug fix - VM maintenance that migrate all servers (see #628)
- bug fix - Agent doesn't restart properly (see #614)
- bug fix - lvclone makes agent to restart (see #655)
- bug fix - problems with system-config-network-cmd (see #656 and #657)
- bug fix - conflict with USB vendorid on USB pass-through (see #664)
- bug fix - kvm 1.2.0 updated with patches for smart cards by USB pass-through support (see #660)
- bug fix - VM drag/drop for move/migrate operations (see #631)
- bug fix - logs _ERR_LIST_SNAPSHOTS_ (see #666)
- bug fix - manuals and documentation (see #667)
- bug fix - VM with qcow2 disks on XEN (see #669)
- bug fix - error on hvmloder for KVM when try to start VM (see #674)
- bug fix - parsing output of new versions of multipath and scsi_id commands (see #658)

- bug fix - segfault after live migrate on XEN (see #606)
- bug fix - problems with VM live migrate for version 0.10.2 of libvirt on KVM (see #675)
- bug fix - log service-run (see #636)
- bug fix - NTP synchronization (see #601)