

NAME

ovn-nbctl – Open Virtual Network northbound db management utility

SYNOPSIS

ovn-nbctl [*options*] *command* [*arg...*]

DESCRIPTION

This utility can be used to manage the OVN northbound database.

GENERAL COMMANDS

show [*lswitch*]

Prints a brief overview of the database contents. If *lswitch* is provided, only records related to that logical switch are shown.

LOGICAL SWITCH COMMANDS

lswitch-add [*lswitch*]

Creates a new logical switch named *lswitch*. If *lswitch* is not provided, the switch will not have a name so other commands must refer to this switch by its UUID. Initially the switch will have no ports.

lswitch-del *lswitch*

Deletes *lswitch*.

lswitch-list

Lists all existing switches on standard output, one per line.

ACL COMMANDS

[--log] acl-add *lswitch direction priority match action*

Adds the specified ACL to *lswitch*. *direction* must be either **from-lport** or **to-lport**. *priority* must be between **1** and **65534**, inclusive. If **--log** is specified, packet logging is enabled for the ACL. A full description of the fields are in **ovn-nb(5)**.

acl-del *lswitch [direction [priority match]]*

Deletes ACLs from *lswitch*. If only *lswitch* is supplied, all the ACLs from the logical switch are deleted. If *direction* is also specified, then all the flows in that direction will be deleted from the logical switch. If all the fields are given, then a single flow that matches all the fields will be deleted.

acl-list *lswitch*

Lists the ACLs on *lswitch*.

LOGICAL PORT COMMANDS

lport-add *lswitch lport*

Creates on *lswitch* a new logical port named *lport*.

lport-add *lswitch lport parent tag*

Creates on *lswitch* a logical port named *lport* that is a child of *parent* that is identified with VLAN ID *tag*. This is useful in cases such as virtualized container environments where Open vSwitch does not have a direct connection to the container's port and it must be shared with the virtual machine's port.

lport-del *lport*

Deletes *lport*.

lport-list *lswitch*

Lists all the logical ports within *lswitch* on standard output, one per line.

lport-get-parent *lport*

If set, get the parent port of *lport*. If not set, print nothing.

lport-get-tag *lport*

If set, get the tag for *lport* traffic. If not set, print nothing.

lport-set-addresses *lport* [*address*]...

Sets the addresses associated with *lport* to *address*. Each *address* should be either an Ethernet address or an Ethernet address followed by an IP address (separated by a space and quoted to form a single command-line argument). The special form **unknown** is also valid. Multiple Ethernet addresses or Ethernet+IP pairs may be set. If no *address* argument is given, *lport* will have no addresses associated with it.

lport-get-addresses *lport*

Lists all the addresses associated with *lport* on standard output, one per line.

lport-set-port-security *lport* [*addrs*]...

Sets the port security addresses associated with *lport* to *addrs*. Multiple sets of addresses may be set by using multiple *addrs* arguments. If no *addrs* argument is given, *lport* will not have port security enabled.

Port security limits the addresses from which a logical port may send packets and to which it may receive packets. See the **ovn-nb**(5) documentation for the **port_security** column in the **Logical_Port** table for details.

lport-get-port-security *lport*

Lists all the port security addresses associated with *lport* on standard output, one per line.

lport-get-up *lport*

Prints the state of *lport*, either **up** or **down**.

lport-set-enabled *lport* *state*

Set the administrative state of *lport*, either **enabled** or **disabled**. When a port is disabled, no traffic is allowed into or out of the port.

lport-get-enabled *lport*

Prints the administrative state of *lport*, either **enabled** or **disabled**.

lport-set-type *lport* *type*

Set the type for the logical port. No special types have been implemented yet.

lport-get-type *lport*

Get the type for the logical port.

lport-set-options *lport* [*key=value*]...

Set type-specific key-value options for the logical port.

lport-get-options *lport*

Get the type-specific options for the logical port.

OPTIONS

--db *database*

The OVSDB database remote to contact. If the **OVN_NB_DB** environment variable is set, its value is used as the default. Otherwise, the default is **unix:/usr/local/var/run/openvswitch/db.sock**, but this default is unlikely to be useful outside of single-machine OVN test environments.

-h | **--help**

-o | **--options**

-V | **--version**

LOGGING OPTIONS

-vspec, **--verbose=spec**

-v, **--verbose**

--log-file[=*file*]

--syslog-target=*host:port*

PKI CONFIGURATION (REQUIRED TO USE SSL)

- p, --private-key=*file*** file with private key
- c, --certificate=*file*** file with certificate for private key
- C, --ca-cert=*file*** file with peer CA certificate