



ColossusXT Masternode Setup Guide

SECURITY WARNING

Please use common sense and security best practices when working with other people to help configure and troubleshoot your masternode! Scammers often pose as team members or "tech support". All official ColossusXT team members have custom colored names in the ColossusXT Discord.

Never share your keys, passwords, or wallet files with anyone.

Never install third-party software or allow people to remotely control or view your system.

Remember, where there is money there are thieves!

This is a living document. The most current version can be found [here](#).

Welcome to the ColossusXT project, and congrats on your decision to become part of the backbone of the ColossusXT currency!

This guide will help you set up your ColossusXT masternode (MN).

As you may know, the ColossusXT MN system involves two running wallets:

- 1) The MN server wallet. In this guide, we will refer to this as the "server wallet". This wallet is the MN's brain, which processes ColossusXT

transactions, verifies new blocks as they are created, and distributes blocks to ColossusXT users. This wallet is a server only, and holds no ColossusXT coins.

- 2) The local control wallet. We will refer to this as the "local wallet". The local wallet holds the 10,000,000 ColossusXT MN collateral transaction, receives MN rewards, and is used to start and stop the MN server wallet.

The most common setup for these two wallets is the local wallet installed on the MN holder's own local Windows or OSX machine, and the MN server wallet installed on a remote Linux VPS (Virtual Private Server) using a service such as VULTR or DigitalOcean. This guide will be geared toward such a setup.

While this is the most common and convenient setup, a VPS is not required. All that is needed are two systems, capable of running a current version of the ColossusXT wallet. The local and server wallets can be Windows, OSX, or Linux, and can run on any hardware that can host these operating systems, including desktops, laptops, a Raspberry Pi, embedded Linux systems, hacked refrigerators, etc. The system requirements are very low: generally speaking, if a system can run the host operating system, it can run the corresponding ColossusXT wallet.

Before you can begin setting up your MN, the local wallet and server wallet must both be installed and synchronized. There is ample documentation on this topic, so it won't be repeated here.

The ColossusXT setup guide for Windows and OSX can be located [here](#).

The ColossusXT setup guide for Linux / VPS systems can be located [here](#).

Once your local wallet and server wallet are installed and synchronized, you are ready to begin.

Linux / VPS Password Security

Use a long, strong, and unique password. Your password should be at least 20 characters. Your password should not be in any dictionary. It should contain uppercase and lowercase letters, numbers, special characters, etc. Don't use obvious substitutions like 0 for O or 5 for S. Don't use a password that you use anywhere else, or even a password *similar* to one you use elsewhere.

To change your password, use the `passwd` command after logging in.

Linux / VPS Additional Security Options

Because ColossusXT MNs are always online, with their IP easily discoverable from the ColossusXT wallet, some users wish to take additional security precautions to protect their system.

First, let's understand the security risks: Because your MN server wallet contains no coins at any point, the risks are surprisingly minimal. There are no coins to steal! If someone gained complete control of your MN server wallet, there are really only two things they could do to impact you: Take your masternode offline, or change your MN privkey, then restart your MN from another local wallet and begin to collect your MN rewards. In either case, you would notice this quickly and could take simple steps to fix the situation. Your local wallet and 10M COLX are NEVER in jeopardy.

Here are two optional security steps you can consider to increase your server's system security:

Disable root Login: Some users opt to disable SSH login for the default `root` account, and create a new user account for SSH access. [Here](#) is a good guide on setting this up.

If your wallet is already installed under the `root` account, be sure to stop the server using the `./colx-cli stop` command while logged in as `root` before you disable the account. You'll also need to move your ColossusXT wallet and application files from the `/root/` folder into your new user directory.

For example, if you installed your ColossusXT wallet as `root`, and then created a new user named `newuser`, you can move your ColossusXT folders using these commands:

```
sudo mv /root/.ColossusXT /home/newuser/.ColossusXT
sudo mv /root/colx-1.0.3 /home/newuser/colx-1.0.3
```

Note the `sudo` command above. If you disable `root` login, you will need to become familiar with this command, which allows you to run commands as `root`. For example, when logged in as `newuser`, you won't be able to reboot the system without using the `sudo` command `sudo reboot`.

Install a Firewall: A good option to protect your system from attacks including Denial of Service (DoS) is to install a firewall. The most common one for Linux is

Uncomplicated Firewall, or `ufw`. In fact, depending on which Linux distribution you choose to use, this may already be installed.

To check if `ufw` is installed, type `ufw status` at the command prompt. If it says "command not found", it's not installed yet.

If `ufw` isn't installed, use the command `apt-get install ufw` to install it. And remember, if you disabled `root` SSH login and are logged in as a different user, you'll need to include the `sudo` command (`sudo apt-get install ufw`).

Once `ufw` is installed, configure it with the following commands:

```
ufw allow 51572/tcp    (to open the port used by your server wallet)
ufw allow 51573/tcp    (to open the RPC port used by your server wallet)
ufw allow ssh          (to allow ssh and prevent locking yourself out!)
ufw enable             (to enable the firewall)
```

If you're having network connectivity issues and want to check if the firewall is the problem, you can use the command `ufw disable` to see if that fixes your problem.

For more information, a good `ufw` starter guide can be found [here](#).

Now that we're comfortable with the security of our server, we can begin setting up the masternode.

Create The 10M MN Collateral Transaction

To run a ColossusXT MN, the local wallet needs to contain an address with exactly 10M COLX sent in a single transaction. When purchasing COLX for your MN, keep in mind that you'll likely need to pay some transaction fees to get the coins off an exchange, into your wallet, and sent in a single 10M transaction, so remember to pad your 10M COLX investment with some extra COLX to cover these transaction costs if needed.

First, we need to create a receive address for the 10M transaction. In your local wallet, click on the Receive tab. Enter a new label for this address, such as "Masternode Transaction", then click "Request Payment".

ColossusCoinXT Core - Wallet [testnet]

File Settings Tools Help

Overview Send Receive Transactions Masternodes

Use this form to request payments. All fields are **optional**.

Label: Masternode Transaction

Amount: [] tCOLX

Message: []

☐ Reuse an existing receiving address (not recommended)

Request payment []

NOTE: This guide was created using a wallet on the ColossusXT Testnet. In the screenshots, instead of "COLX", you will see references to "tCOLX", which is our fake Testnet currency.

Once the payment address is created, send **EXACTLY** 10M COLX to this address. Remember, whether you are sending to yourself from within the ColossusXT wallet, or sending from an exchange, the amount received needs to be exactly 10,000,000 COLX. Be sure to account for transaction fees, exchange fees, and withdrawal fees when creating this transaction.

For example, a local transaction sent to yourself will automatically add the transaction fee. Make sure you have enough additional COLX to cover this fee.

Confirm send coins

Are you sure you want to send?

10 000 000.00000000 tCOLX using **any available funds (not recommended)** to Masternode Transaction (yDtFkYVFyTrwf66F1qRejNsPUtVwFX1T4F)

1.91000000 tCOLX are added as transaction fee (0.191 kB)

Total Amount = **10 000 001.91000000 tCOLX**
= 10 000 001 910.000000 mtCOLX
= 10 000 001 910 000.00 µtCOLX

(1 of 1 entries displayed)

Yes Cancel

A transaction from an exchange will add its own fees also. For example, on Crypto-Bridge, you would actually need to withdraw 10,000,141.1375 to cover their Gateway fee and blockchain withdrawal fee and receive 10,000,000 COLX.

Withdraw ColossusCoinXT (COLX)

AMOUNT TO WITHDRAW

AVAILABLE: 0.0000 COLX

BRIDGE.COLX

WITHDRAW TO ADDRESS

▼

Gateway fee: 1 COLX

Blockchain withdrawal fee: 140.1375 COLX

You will receive: 10,000,000 COLX

WITHDRAW

CANCEL

Once you receive your 10M COLX, open the wallet debug console, type `masternode outputs`, and press [Enter]. This will give you your MN txhash, and your outputidx.

```
13:42:01  ↖  masternode outputs
13:42:01  ↗  [
              {
                "txhash" : "98620a11d477fed62baedella6f90db6c2a4149db1888c48a4192f8d69ef8276",
                "outputidx" : 0
              }
            ]
```

Save both of these pieces of information to a text file; you will need them later.

Create A MN Privkey

In the local wallet debug console, type `masternode genkey` and press [Enter]. This will generate a new privkey (private key) for your masternode.

```
13:50:57  masternode genkey
13:50:57  9229ThpizSfrfjryx21oCZiY85NrHCdNKQ33sad5oQBTXAe64J5
```

Save this along with your txhash and outputidx from the previous step.

Edit The Local Wallet masternode.conf

In on your local wallet system, open your masternode.conf file.

In Windows, you can press [Windows]+R, type `%appdata%\ColossusCoinXT`, and open the file from there. If prompted for a program to use to edit the file, select Notepad.

In OSX, you can press [Command]+[Shift]+G, enter `~/Library/Application Support/ColossusCoinXT/` (Note: case sensitive!), click Go, and open the file from there. If prompted for a program to use to edit the file, select TextEdit.

On a new line below the include examples that begin with the # symbol, add a line of text in the following format:

```
name ip:port privkey txhash txoutputidx
```

name: Create a name for your new masternode, such as "COLXMN" or "MN01".

ip: The external ip address of your server wallet system.


port: Use 51572, the default ColossusXT communicate port.

privkey: Use the privkey generated in the last step.

txhash: Use the txhash generated from the `masternode outputs` command.

txoutputidx: Use the txoutputidx generated from the `masternode outputs` command (it will be a 1 or a 0).

This will result in a very long string that looks like this:



```
masternode.conf - Notepad
File Edit Format View Help
# Masternode config file
# Format: alias IP:port masternodeprivkey collateral_output_txid collateral_output_index
# Example: mn1 127.0.0.2:51474 93HaYBVUCYjEMeeH1Y4sBGLALQZE1Yc1K64xiqgX37tGBDQL8Xg 2bcd3c84c84f87eaa86e4e56834c92927a07f9e18718810b92e0d0324456a67c 0
COLXMN 123.234.123.234:51572 9229ThpizSfrfjryx21pCZiY85NrHCdNKQ33sad5oQBTXAe64J5 98620a11d477fed62baede11a6f90db6c2a4149db1888c48a4192f8d69ef8276 0
```

Save and close the local masternode.conf file, then close and restart your local ColossusXT wallet application.

Edit The Server wallet ColossusCoinXT.conf

Because most server wallets are running on a Linux-based VPS, we will use a Linux text-based text editor to edit the server wallet ColossusCoinXT.conf

Log in to your VPS. Open the server wallet ColossusCoinXT file in the pico editor by typing `pico ~/.ColossusCoinXT/ColossusCoinXT.conf` (NOTE: This command is CASE SENSITIVE).

Add the following lines of text to the server wallet ColossusCoinXT file. NOTE: If you are using PuTTY to connect to your VPS, you can right-click to paste, and avoid having to type out the long MN private key.

```
rpcuser=s9gs49ghs9ghs
rpcpassword=349hdhfgdhfhg39
daemon=1
masternode=1
bind=<your IP>:51573
externalip=<your IP>
masternodeaddr=<your IP>
masternodeprivkey=<your privkey>
addnode=seed.colossusxt.org
addnode=seed.colossuscoinxt.org
addnode=seed.colxt.net
```

For `rpcuser` and `rpcpassword`, enter your own random characters.

Replace `<your ip>` with the IP address of your server wallet. Do not include the `<>` brackets.

Replace `<your privkey>` with the privkey created in the previous steps. Do not include the `<>` brackets.



```
GNU nano 2.2.6 Modified
rpcuser=s9gs49ghs9ghs
rpcpassword=349hdhfgdhfhg39
daemon=1
masternode=1
bind=123.234.123.234:51573
externalip=123.234.123.234
masternodeaddr=123.234.123.234
masternodeprivkey=9229ThpizSfrfjryx21oCZiY85NrHCdNKQ33sad5oQBTXAe64J5
addnode=seed.colossusxt.org
addnode=seed.colossuscoinxt.org
addnode=seed.colxt.net

^G Get Help  ^O WriteOut  ^R Read File  ^Y Prev Page  ^K Cut Text   ^C Cur Pos
^X Exit      ^J Justify   ^W Where Is  ^V Next Page  ^U UnCut Text ^T To Spell
```

Once everything is entered and correctly changed to your own MN details, press [CTRL]+X to exit. Press Y to save, and [ENTER] to retain the original filename.

Restart The Server Wallet

Navigate to the location of the server wallet executables. If you installed your server wallet using the [ColossusXT Linux / VPS Wallet 1.0.3 Setup Guide](#), use the command `cd ~/colx-1.0.3/bin` to change to that directory. If you installed to a different location, use that path instead. Verify that you are in the correct folder by typing `ls` to list the files in that directory. You should see your ColossusXT executables listed:

 PuTTY (inactive)

```
root@mnhost:~# cd colx-1.0.3/bin/
root@mnhost:~/colx-1.0.3/bin# ls
colx-cli  colx-qt  colx-tx  colxd  test_colx  test_colx-qt
root@mnhost:~/colx-1.0.3/bin#
```


Now type `./colx-cli stop` to stop the server wallet. Once that completes, type `./colxd` to start it up again.

```
root@mnhost:~/colx-1.0.3/bin# ./colx-cli stop
COLX server stopping
root@mnhost:~/colx-1.0.3/bin# ./colxd
ColossusCoinXT server starting
root@mnhost:~/colx-1.0.3/bin#
```


Start The Masternode From The Local Wallet

Everything is now in place to start your MN from your local wallet.

Open the local wallet, click the Masternodes tab. Select your MN so that it is highlighted in green. Click Start Alias, then click OK when prompted for confirmation:



Once the MN starts, you will see this success message on your local wallet:



If you receive an error about "unavailable txid", open the local wallet debug console and use the command `masternode start-alias "your MN name"` to start your MN manually.


Once your MN is started, you can use the command `./colx-cli masternode status` on your masternode server wallet to confirm the status of your masternode:

```
root@mnhost:~/colx-1.0.3/bin# ./colx-cli masternode status
{
  "txhash" : "98620a11d477fed62baede11a6f90db6c2a4149db1888c48a4192f8d69ef8276",
  "outputidx" : 0,
  "netaddr" :
  "addr" : "yDtfKYVFyTrwf66FlqRejNsPUtVwfx1T4F",
  "status" : 4,
  "message" : "Masternode successfully started"
}
root@mnhost:~/colx-1.0.3/bin#
```

You're done! Your masternode is now up and running, and you should begin to receive masternode rewards within the next 5-7 hours.

Viewing Masternode Rewards

Once you begin to receive MN Rewards, they will be visible as "Masternode Reward" transactions on the Transactions tab of your local wallet:



ColossusCoinXT Core - Wallet [testnet]				
File Settings Tools Help				
Overview		Send	Receive	Transactions
All		All	Enter address or label to search	Min amount
Date	Type	Address	Amount (tCOLX)	
4/25/2018 17:14	Masternode Reward	Masternode Transaction	[2 025.00000000]	
4/25/2018 17:14	Masternode Reward	Masternode Transaction	[2 025.00000000]	
4/25/2018 17:04	Masternode Reward	Masternode Transaction	2 025.00000000	
4/25/2018 17:04	Masternode Reward	Masternode Transaction	2 025.00000000	
4/25/2018 16:51	Masternode Reward	Masternode Transaction	2 025.00000000	
4/25/2018 16:51	Masternode Reward	Masternode Transaction	2 025.00000000	
4/25/2018 16:45	Masternode Reward	Masternode Transaction	2 025.00000000	

Spending Masternode Rewards

New MN holders often worry about accidentally spending COLX from their 10M COLX collateral transaction and inadvertently taking their MN offline. However, this is not possible: Once your txhash is added to your local wallet masternode.conf file, the 10M collateral transaction become unavailable for spending, and cannot be used until the masternode is removed. This will prevent you from accidentally breaking your masternode. You will see a gray lock icon next to this transaction in your payment inputs window:

Coin Selection
?
×

Quantity: 0
Amount: 0.00000000 tCOLX
Fee: 0.00000000 tCOLX
After Fee: 0.00000000 tCOLX

Bytes: 0
Priority: none
Dust: no
Change: 0.00000000 tCOLX

(un)select all
toggle lock state
☐ Tree mode
☒ List mode
(1 locked)

	Amount	Received with label	Received with address	DS Rounds	Date	Confirmations	Priority
<input type="checkbox"/>	5 000 000.00...	Address 1	y6T2RNub9faZ1VY3ymq7...	n/a	4/25/201...	237	highest
<input type="checkbox"/>	4 999 997.74...	(change)	yG3GETtYS6bEpbHVNwS...	n/a	4/25/201...	237	highest
<input type="checkbox"/>	45 000 111.3...	(change)	y1Wn6WYFeT97r42jGFCFe...	n/a	4/24/201...	1367	highest
<input type="checkbox"/>	35 000 109.4...	(change)	yAstWkd7U93SYjXkEIRxsL...	n/a	4/25/201...	218	highest
<input checked="" type="checkbox"/>	10 000 000.0...	Masternode Transaction	yDtfKYVFyTrwf66F1qRejN...	n/a	4/25/201...	218	highest
<input type="checkbox"/>	2025.00000...	Masternode Transaction	yDtfKYVFyTrwf66F1qRejN...	n/a	4/25/201...	37	medium
<input type="checkbox"/>	2025.00000...	Masternode Transaction	yDtfKYVFyTrwf66F1qRejN...	n/a	4/25/201...	16	medium
<input type="checkbox"/>	2025.00000...	Masternode Transaction	yDtfKYVFyTrwf66F1qRejN...	n/a	4/25/201...	28	medium
<input type="checkbox"/>	2025.00000...	Masternode Transaction	yDtfKYVFyTrwf66F1qRejN...	n/a	4/25/201...	17	medium
<input type="checkbox"/>	2025.00000...	Masternode Transaction	yDtfKYVFyTrwf66F1qRejN...	n/a	4/25/201...	29	medium

OK

Additional Resources

If you have any additional questions or run into issues, or would like to suggest changes or additions to this guide, please join us in the #masternode-support channel on our Discord:

<https://discord.gg/6YATaYD>