


CONNECTOR

User Manual

1. Configuring the MT5 terminal

1.1. In the terminal window, in the menu bar, select **Tools** → **Options** (or press **Ctrl+O**).




1.2. In the **Options** window select the **Expert Advisors** tab and make sure the following options are selected:

- **Allow DLL imports;**
- **Allow WebRequest for listed URL.**

For the latter option add the following URLs:

- 1.2.1. Connector Solutions server URL <https://ls.connector.solutions> - required;
- 1.2.2. Binance API endpoint URLs – required if you are going to use the CONNECTOR to synchronize with Binance:
 - 1.2.2.1. Spot – at least one of the URLs: <https://api.binance.com>, <https://api1.binance.com>, <https://api2.binance.com>, <https://api3.binance.com>, <https://api4.binance.com>;
 - 1.2.2.2. USDⓈ-M Futures: <https://fapi.binance.com>;
 - 1.2.2.3. Spot Test Network: <https://testnet.binance.vision>;
 - 1.2.2.4. USDⓈ-M Futures Test Network: <https://testnet.binancefuture.com>;
- 1.2.3. KuCoin API endpoint URLs – required if you are going to use the CONNECTOR to synchronize with KuCoin:
 - 1.2.3.1. Spot: <https://api.kucoin.com>;
 - 1.2.3.2. Futures: <https://api-futures.kucoin.com>;
 - 1.2.3.3. Spot sandbox: <https://openapi-sandbox.kucoin.com>;
 - 1.2.3.4. Futures sandbox: <https://api-sandbox-futures.kucoin.com>;
- 1.2.4. Kraken API endpoint URLs – required if you are going to use the CONNECTOR to synchronize with Kraken:
 - 1.2.4.1. Spot: <https://api.kraken.com>;
 - 1.2.4.2. Futures: <https://api.futures.kraken.com>;
 - 1.2.4.3. Futures sandbox: <https://demo-futures.kraken.com>;
- 1.2.5. Bybit API endpoint URL – required if you are going to use the CONNECTOR to synchronize with Bybit:
 - 1.2.5.1. Live: <https://api.bybit.com> or <https://api.bytick.com>;
 - 1.2.5.2. Sandbox: <https://api-testnet.bybit.com>;

1.2.6. OKX API endpoint URL – required if you are going to use the CONNECTOR to syn-
chronize with OKX: <https://www.okx.com>.




1.3. Click the **OK** button to save the changes.

2. Configuring the IB terminal (TWS)

The following steps are only necessary if you are going to use the CONNECTOR to synchronize with IB.

2.1. In the terminal window, in the menu bar, select **File → Global Configuration**.




2.2. In the settings window that opens, on the left in the navigation bar, select **API → Settings**.

2.2.1. Make sure the **Read-Only API** option is not selected and the following options are selected on the right in the settings panel:


- **Enable Active-X and Socket Clients;**
- **Create API message log file**

2.2.2. Set the settings values:

- **Socket port** – the port through which the CONNECTOR will connect to the TWS;
- **Trusted IPs** – IP-addresses to which the CONNECTOR will connect. It is not required if the connection will be at 127.0.0.1.



2.3. In the navigation bar, select **API → Precautions**. Make sure the option **Bypass Order Precautions for API Orders** is selected.




2.4. Click the **OK** button to save the changes.


3. Configuring a Binance account

The following steps are only necessary if you are going to use the CONNECTOR to synchronize with Binance.

- 3.1. [Register](#) an account at the [Binance website](#) or log in to your account if it was previously registered.
- 3.2. Go to your [profile](#) and make sure the two-factor authentication (2FA) is [enabled](#).
- 3.3. Make sure you have completed the [Identity Verification](#) and your Verification Level is Verified Plus.
- 3.4. If you are going to use the USD[Ⓢ]-M Futures derivative and have not used it previously, go to the [Binance Futures web-terminal](#) and make sure that this instrument is activated.
- 3.5. Create an API Key.
 - 3.5.1. Go to the [API management page](#) and click the **Create API** button:



- 3.5.2. Select the **System generated** API Key type and click the **Next** button:



- 3.5.3. Enter an arbitrary API Key label and click the **Next** button:

3.5.4. Pass a security check including CAPTCHA and 2FA.


3.5.5. Click **Edit restrictions**

3.5.6. Make sure that the API functions you need are enabled: **Futures** and/or **Spot trading**. Select the **Unrestricted** IP access option to allow using the key from any IP address. Keep the **API Key** and the **Secret Key** in a safe place. Click the **Save** button.


3.6. If you use Futures, the MT5 account type (netting, hedge) must match the Binance Position Mode (one-way, hedge), otherwise the CONNECTOR will not be launched.

To change the Binance Position Mode in the [Binance Futures web-terminal](#):

3.6.1. Click the settings icon in the upper right corner, and then click **Preference** in the menu that opens:




3.6.2. Select the **Position Mode** tab in the **Preference** window, and then select the required position mode:



4. Configuring a KuCoin account

The following steps are only necessary if you are going to use the CONNECTOR to synchronize with KuCoin.

- 4.1. [Register](#) an account at the [KuCoin website](#) or log in to your account if it was previously registered.
- 4.2. Go to the [Account Security](#) page and make sure that [Google Verification](#) and [Trading Password](#) are configured.
- 4.3. Create an API Key.
 - 4.3.1. Go to the [API Management page](#) and click the **Create API** button:



- 4.3.2. Enter an arbitrary **API Name** and an **API Passphrase**. Keep the API Passphrase in a safe place. Select the **General** and the **Trade** API Restrictions options. Select the **No IP Restriction** option to allow using the key from any IP address. Click **Next**.

Create API

KuCoin offers robust API services. You can create API according to your needs and therefore access or trade in the market of KuCoin. [Check API document](#).

API Name

API Name

API Passphrase

For security, API Passphrase is needed for the interface call, please keep it safe. If you lose API Passphrase, you need to create a new API Key.

API Restrictions

☒ **General** Users can only carry out read-only operations such as checking the account information, account statement and order information, etc. Users cannot place orders, withdraw, etc.

☒ **Trade** Users can place orders, cancel orders, etc.

☐ **Transfer** *Not recommended* Users can withdraw, acquire deposit address, cancel withdrawals, etc.

IP Restriction Current IP: 255.255.255.255

☒ **No** Less can access to the API Secret *Not recommended*

☐ **Yes** Only trusted IP address can access to the API Secret *Recommended*

Next

4.3.3. Enter your **Trading Password** and click **Confirm**:

Security Verification

Trading Password

.....

Confirm

4.3.4. Keep the API **Key** and **Secret** in a safe place along with your API **Passphrase**.

×

API Created!

API Name

API Name

Key

648a0051ba02b40001f9f920

Secret

API Secret cannot be retrieved and will ONLY be displayed for ONE time.
Please note it down and keep it safe.

0bbe24c7-4576-443f-b0bf-b5ee898e84a2

API Restrictions

General, Trade

IP Restriction


No

Confirm

5. Configuring a Kraken account

The following steps are only necessary if you are going to use the CONNECTOR to synchronize with Kraken.


- 5.1. [Register](#) an account at the [Kraken website](#) or log in to your account if it was previously registered.
- 5.2. Create a spot trading API Key (required if you are going to use the CONNECTOR to synchronize with Kraken spot).
 - 5.2.1. Go to the [trading API settings page](#) and click the **Create API key** button in the **Spot trading API** section.



- 5.2.2. Enter an arbitrary **Name**. Select the **Query** funds permission. Select the options **Query open orders & trades**, **Query closed orders & trades**, **Create & modify orders** of the orders and trades permissions. Make sure the **IP address restriction** is disabled to allow using the key from any IP address. Click **Generate key**.

A screenshot of the 'Add API key' dialog box. The dialog has a title bar 'Add API key' with a close button. The main content is titled 'API key settings'. It includes a 'Name' field with the value 'test API key' and a red circle with the number 1. Below this is a section 'Select at least one permission' with three columns: 'Funds permissions', 'Orders and trades', and 'Data'. Under 'Funds permissions', the 'Query' option is selected with a red circle with the number 2. Under 'Orders and trades', the options 'Query open orders & trades', 'Query closed orders & trades', and 'Create & modify orders' are selected with a red circle with the number 3. Under 'Data', the 'Query ledger entries' and 'Export data' options are unselected. Below this is a 'WebSocket interface' section with a toggle switch set to 'Off'. Below that is an 'IP address restriction' section with a toggle switch set to 'Off' and a red circle with the number 4. At the bottom is a 'Key expiration' section with a toggle switch set to 'Off'. Below that is a 'Query start date' section with a toggle switch set to 'Off'. Below that is a 'Query end date' section with a toggle switch set to 'Off'. At the bottom is a 'Custom nonce window' section with a toggle switch set to 'Off'. A large blue button labeled 'Generate key' with a red circle with the number 5 is at the bottom right.


5.2.3. Keep the **API key** and the **Private key** in a safe place.




5.2.4. To enable 2FA for the spot trading API key, click the context menu button of the key and click the **Add 2FA** button of the context menu.




Enable the **Two-factor authentication** in the **2FA settings** window.




Select **Password** as 2FA method.



Enter and re-type the password. Keep the **2FA password** in a safe place. Click **Confirm password**.




Choose when to use the 2FA and click **Change 2FA settings**.




5.3. Create a futures trading API Key (required if you are going to use the CONNECTOR to synchronize with Kraken futures).


5.3.1. Go to the [trading API settings page](#) and click the **Create API key** button in the **Futures trading API** section.



5.3.2. Make sure the **Full access** option is selected for the **General API** and click **Generate key**.



5.3.3. Keep the **Public key** and the **Private key** in a safe place.



6. Configuring a Bybit account


The following steps are only necessary if you are going to use the CONNECTOR to synchronize with Bybit.

6.1. [Register](#) an account at the [Bybit website](#) or log in to your account if it was previously registered.


6.2. Go to the [Account & Security](#) page and make sure that [Google 2FA Authentication](#) is configured.

6.3. Create an API Key.

6.3.1. Go to the [API Management](#) page and click the **Create New key** button.



6.3.2. Select the **System-generated** API key type:



6.3.3. Select **API Transaction** from the **API Key Usage** options. Enter an arbitrary **Name** for the API key. Select **Read-Write** from the **API Key Permissions** options, and make sure the **No IP Restriction** option is selected if you want to use the key from any IP address.

6.3.4. Select the following **Standart Account** options: **Orders** and **Positions** for **Contract**, **USDC Derivatives Trading** for **USDC Contracts** (if required) and **Trade** for **SPOT**.

Trade	Type	Read-Write
<input checked="" type="checkbox"/> Standard Account	Contract	<input checked="" type="checkbox"/> Orders Query order info; submit, modify or cancel orders (Derivatives)
		<input checked="" type="checkbox"/> Positions Query positions info; modify margin balance, leverage and more (Derivatives)
		<input type="checkbox"/> Copy Trading Query copy trading orders and submit orders to open/close (only available to users who've successfully enabled copy trading)
	USDC Contracts ⓘ	<input checked="" type="checkbox"/> USDC Derivatives Trading Query order and asset info; submit, modify or cancel orders (USDC Contracts)
	SPOT	<input checked="" type="checkbox"/> Trade Query order info; submit or cancel orders (Spot)

6.3.5. Click **Submit**. Enter **Google verification code** and click **Confirm**.

API Settings Authentication

Google verification code

2

Having problems with verification?

Confirm

Cancel

6.3.6. Keep the **API Key** and the **API Secret** in a safe place.

Key successfully added

To ensure the security of your account, your API secret key will be revealed only once at the time of creation and will be hidden thereafter. Please keep the secret key confidential and do not disclose it to anyone.

Name

API key name

API Key

MaKIgeH5vPxmMBS8P5

Copy

API Secret

YAetNSZrjISbZD3rJ3CN1JPVSWv1KRLtoqXY

Copy

Permission

Contracts - Orders Positions , USDC Contracts - Trade , SPOT


7. Configuring an OKX account

The following steps are only necessary if you are going to use the CONNECTOR to synchronize with OKX.


7.1. [Register](#) an account at the [OKX website](#) or log in to your account if it was previously registered.

7.2. Create an API Key.

7.2.1. Go to the [API keys](#) page and click the **Create V5 API key** button.



7.2.2. Select **API trading** purpose option. Enter an arbitrary **API name**, enter and remember **Passphrase**. Make sure the **IP address allowlist** is empty if you want to use the key from any IP address. Select **Read** and **Trade** permissions. Click **Confirm**.



7.2.3. Click **Send code** in both **Email verification** and **Phone verification** fields of the **Two-factor authentication** window. When you receive the verification codes, enter them in the appropriate fields and click **Confirm**.

Two-factor authentication

Email verification

Enter code

Send code

Phone verification

Enter code

Send code

Cancel

Confirm

7.2.4. Keep the **API Key** and the **Secret key** in a safe place.

API key created

API key

a2a4bd7c-9829-46bf-bef8-8cc379f4245b

Purpose

API trading

API name

API name

IP address allowlist (optional)

Permissions

Read Trade

Secret key

D3F7E33EC4C20C00F691C2BD78B57D14




For your security, don't share your API keys with anyone

Copy API info

Confirm


8. Launching the CONNECTOR

8.1. If you are going to use the CONNECTOR to synchronize with IB, launch the IB terminal (TWS), enter your username and password.



8.2. Launch the **Connector Solutions / CSMultiConnector** Expert Advisor.

8.2.1. Make sure the **Allow DLL imports** option is selected on the **Dependencies** tab.



8.2.2. On the **Inputs Parameters** tab set the parameter values:

8.2.2.1. **Common** – general CONNECTOR settings:

8.2.2.1.1. **Stop when a critical error occurs** – the flag to terminate the CONNECTOR when a critical error occurs.

Default value: false

8.2.2.2. **Logging** – logging options:

8.2.2.2.1. **Show alert if an error occurs** – the flag for displaying errors in the **Alert** window. If set to false, errors will be logged without displaying the **Alert** window.
Default value: true

8.2.2.2.2. **Duplicate log messages to the Expert Log** – the flag for displaying log records on the **Experts** tab of the **Toolbox** panel. If set to false, the log entries will be written to a text log file only.
Default value: true


8.2.2.2.3. **Print information messages to the Expert Log** – the flag for displaying informational log records on the **Experts** tab of the **Toolbox** panel. If the value is set to false, informational log records will be written to a text log file only, and warning and error log records will be displayed on the **Experts** tab in accordance with the value of the **Duplicate log messages to the Expert Log** parameter.
Default value: true

8.2.2.2.4. **Max. log file size (Mbytes)** – the maximum size of the log file in megabytes. If the log size exceeds the value of this parameter, a new file will be created.
Default value: 20


8.2.2.3. **License** – licensing parameters:

8.2.2.3.1. **License key** – your license key. If the value is not set or **default**, the trial version of the CONNECTOR will be launched, unless the trial period has expired. If you have previously registered a license key, insert it in this field.
Default value: default


8.2.3. Click the **OK** button.



8.2.4. If a new CONNECTOR version is available, you will see a window prompting you to install the update. You can choose not to install the update and continue to use the current version.




If installing the update is mandatory, then if you refuse to install the update or an error occurs when installing the update, the CONNECTOR will be closed.




Upon receiving consent to install the update, the CONNECTOR will be closed and the installation dialog box will open. After the installation process is complete, you can start the CONNECTOR again.

Note. If such a message occurs during the installation of the update:



- then you should check whether an instance of the **Connector Solutions/CSMultiConnector** Expert Advisor is running in the MT5 terminal, and if it is running, then stop it and click OK in the installer window. If this message appears again, then restart the MT5 terminal and click OK again in the installer window.


8.2.5. If the current version of the CONNECTOR is up to date, a window prompting you to choose a connector will open.



The list of connectors will contain only those connectors that are activated for your licensed or trial version. If only one connector is activated, this window will be skipped.


8.2.6. After selecting the connector, the license key will be checked.

8.2.6.1. If you are running the trial version (**License** → **License key** input parameter value is empty string or **default**) and it is not expired, you will see a window with a message indicating the time remaining before the trial period expires and an offer to purchase a license:




You may click **No** and continue using the trial version.

8.2.6.2. If the trial period has expired, a window will appear with the corresponding message:




In this case, if you click **No**, the CONNECTOR will terminate its operation.

8.2.6.3. If you agree to purchase a license, a window will appear asking you to enter your email address:




Enter your email and click **OK**. After a successful license key registration, a window with your new license key will open:




Keep the key in a safe place and use it at the next CONNECTOR launches as the **License** → **License key** input parameter. The CONNECTOR will continue to operate after the window is closed.

8.2.6.4. If the value of the **License** → **License key** input parameter is a valid license key, the full version of the CONNECTOR will be launched. If there are less than 7 days left before the license expires, a message with a proposal to renew the validity of the license key will appear. You may click **No** and proceed.




8.2.6.5. If the license has expired, a warning with a proposal to renew the validity of the license key will appear:



In this case, if you click **No**, the CONNECTOR will terminate its operation.

8.2.6.6. Click **Yes** to renew the license. In case of successful renewal of the license key validity period, a message will be displayed indicating the period for which the key validity period was renewed:



The CONNECTOR will continue its operation as soon as the window is closed.

8.2.7. If the license check succeeded, a settings window for a selected connector will open:

8.2.7.1. IB settings window:

 A dialog box titled "IB settings" with a close button (X) in the top right corner. It contains several input fields and a checkbox:

- TWS IP: 127 . 0 . 0 . 1
- Port: 7497
- Client ID: 1
- Account: test
- Exchange: SMART
- Security's type: CFD (dropdown menu)
- Max. order resubmit tries: 3
- Order timeout (s): 30
- Reconnection interval (s): 300
- Positions sync period (s): 180
- ☐ Reset cache

 At the bottom, there are four buttons: Save, Load, OK (highlighted with a blue border), and Cancel.

8.2.7.1.1. **TWS IP** – the IP address at which TWS is available for connection.

Default value: 127.0.0.1

8.2.7.1.2. **Port** – the socket port assigned in the TWS settings.

Default value: 7497

8.2.7.1.3. **Client ID** – the client ID must be unique if more than one client is connected to TWS.

Default value: 1

8.2.7.1.4. **Account** – the IB account trades will be allocated to.

Default value: empty string

8.2.7.1.5. **Exchange** - the target exchange of the contract.

Default value: SMART

8.2.7.1.6. **Security's type** – the type of securities of the contract. Currently, only CFD and CASH contracts are supported.

Default value: CFD

8.2.7.1.7. **Max. order resubmit tries** – the maximum number of attempts to place an order in IB in case of an error on the IB server side.

Default value: 3

8.2.7.1.8. **Order timeout (s)** – the maximum waiting time for the full execution of the order in seconds.

Default value: 30

8.2.7.1.9. **Reconnection interval (s)** – the time interval in seconds between repeated connection attempts in case of connection loss.

Default value: 300


8.2.7.1.10. **Position sync period (s)** – the periodicity of positions synchronization in seconds. Set to 0 to disable periodic positions synchronization.

Default value: 180

8.2.7.1.11. **Reset cache** – the flag for resetting the saved mappings between the symbols of the original trades and IB contracts. This may be necessary in case of a change in the symbol name by the broker or a change in the IB contract.

Default value: not selected

8.2.7.2. **Binance settings window:**



Binance settings

Endpoint: Futures

☒ Sync positions at startup

☐ Log headers

API URL: https://testnet.binancefuture.com

API key: cui8jqzer0i5au5xyo1rdvl93yu7ubil1x1bl0zrecozb8qt4m

Secret key: 1yomcj3u63df9zj8gkllr7unflura8q250ss416rb3gx4jsiv9l

Positions sync period (s): 0

Save Load OK Cancel

8.2.7.2.1. **Endpoint** – the Binance API endpoint type: Spot or Futures.

Default value: Spot

8.2.7.2.2. **Sync positions at startup** – the flag to synchronize positions between MT5 and Binance at startup.

Default value: not selected

8.2.7.2.3. **Log headers** – the flag to enable logging HTTP headers during the data exchange between MT5 and Binance.

Default value: not selected

8.2.7.2.4. **API URL** – the Binance API endpoint URL.

Default value: empty string

8.2.7.2.5. **API key** – previously registered Binance API key.

Default value: empty string


8.2.7.2.6. **Secret key** – a secret key associated with the API key.

Default value: empty string

8.2.7.2.7. **Position sync period (s)** – the periodicity of positions synchronization in seconds. Set to 0 to disable periodic positions synchronization.

Default value: 180

8.2.7.3. **KuCoin settings window:**



KuCoin settings

Endpoint: Futures

API URL: https://api-sandbox-futures.kucoin.com

API key: y7sfbs8magj03p3ql7wf7343

Secret key: f55b5c44-7658-4d37-bdd1-eb0871068c7a

Passphrase: btp35yncxt08h95fsyddley69a26jits

Quote currency: USDT

MT profit currency: USD

Positions sync period (s): 0

Sync positions at startup: ☒

Log headers: ☒

Save Load OK Cancel

8.2.7.3.1. **Endpoint** – the KuCoin API endpoint type: Spot or Futures.

Default value: Spot

8.2.7.3.2. **Sync positions at startup** – the flag to synchronize positions between MT5 and KuCoin at startup.

Default value: not selected

8.2.7.3.3. **Log headers** – the flag to enable logging HTTP headers during the data exchange between MT5 and KuCoin.

Default value: not selected

8.2.7.3.4. **API URL** – the KuCoin API endpoint URL.

Default value: empty string

8.2.7.3.5. **API key** – previously registered KuCoin API key.

Default value: empty string

8.2.7.3.6. **Secret key** – a secret key associated with the API key.

Default value: empty string

8.2.7.3.7. **Passphrase** – a passphrase associated with the API key.

Default value: empty string

8.2.7.3.8. **Quote currency** – KuCoin symbol quote currency.

Default value: empty string


8.2.7.3.9. **MT profit currency** – MT5 symbol profit currency.

Default value: empty string

8.2.7.3.10. **Position sync period (s)** – the periodicity of positions synchronization in seconds. Set to 0 to disable periodic positions synchronization.

Default value: 180

8.2.7.4. **Kraken settings window:**



Kraken settings

Endpoint: Futures

☒ Sync positions at startup

☒ Log headers

API URL: https://futures.kraken.com

API key: lgoJ2zHgEYUeiqfWS2HyHz6aGcbJ18DDMdFUT5/Wzm

Private key: KiUkUzQ/2/5aOuDZ2RL0aoWQiyiMqoRn2tIWuf8bqQY

One-time password:

Quote currency: USD

MT profit currency: USD

Positions sync period (s): 180

Save Load OK Cancel

8.2.7.4.1. **Endpoint** – the Kraken API endpoint type: Spot or Futures.

Default value: Spot

8.2.7.4.2. **Sync positions at startup** – the flag to synchronize positions between MT5 and Kraken at startup.

Default value: not selected

8.2.7.4.3. **Log headers** – the flag to enable logging HTTP headers during the data exchange between MT5 and Kraken.

Default value: not selected

8.2.7.4.4. **API URL** – the Kraken API endpoint URL.

Default value: empty string

8.2.7.4.5. **API key** – previously registered Kraken API key.

Default value: empty string

8.2.7.4.6. **Private key** – a private key associated with the API key.

Default value: empty string

8.2.7.4.7. **One-time password** – a one-time password for 2FA (mandatory if 2FA is enabled for the API key).

Default value: empty string

8.2.7.4.8. **Quote currency** – Kraken symbol quote currency.

Default value: empty string


8.2.7.4.9. **MT profit currency** – MT5 symbol profit currency.

Default value: empty string

8.2.7.4.10. **Position sync period (s)** – the periodicity of positions synchronization in seconds. Set to 0 to disable periodic positions synchronization.

Default value: 180

8.2.7.5. Bybit settings window:



8.2.7.5.1. **Endpoint** – the Bybit API endpoint type: Spot or Futures.

Default value: Spot

8.2.7.5.2. **Sync positions at startup** – the flag to synchronize positions between MT5 and Bybit at startup.

Default value: not selected

8.2.7.5.3. **Log headers** – the flag to enable logging HTTP headers during the data exchange between MT5 and Bybit.

Default value: not selected

8.2.7.5.4. **API URL** – the Bybit API endpoint URL.

Default value: empty string

8.2.7.5.5. **API key** – previously registered Bybit API key.

Default value: empty string

8.2.7.5.6. **Secret key** – a secret key associated with the API key.

Default value: empty string

8.2.7.5.7. **Quote currency** – Bybit symbol quote currency.

Default value: empty string


8.2.7.5.8. **MT profit currency** – MT5 symbol profit currency.

Default value: empty string

8.2.7.5.9. **Position sync period (s)** – the periodicity of positions synchronization in seconds. Set to 0 to disable periodic positions synchronization.

Default value: 180

8.2.7.6. **OKX settings window:**



8.2.7.6.1. **Endpoint** – the OKX API endpoint type: Spot or Futures.

Default value: Spot

8.2.7.6.2. **Sync positions at startup** – the flag to synchronize positions between MT5 and OKX at startup.

Default value: not selected

8.2.7.6.3. **Log headers** – the flag to enable logging HTTP headers during the data exchange between MT5 and OKX.

Default value: not selected

8.2.7.6.4. **API URL** – the OKX API endpoint URL.

Default value: <https://www.okx.com>

8.2.7.6.5. **Demo trading** – the flag to enable OKX demo trading.

Default value: not selected

8.2.7.6.6. **API key** – previously registered OKX API key.

Default value: empty string

8.2.7.6.7. **Secret key** – a secret key associated with the API key.

Default value: empty string

8.2.7.6.8. **Passphrase** – a passphrase associated with the API key.

Default value: empty string

8.2.7.6.9. **Quote currency** – OKX symbol quote currency.

Default value: empty string

8.2.7.6.10. **MT profit currency** – MT5 symbol profit currency.

Default value: empty string


8.2.7.6.11. **Trade mode** – the OKX account trade mode: **Cash** for spot, **Isolated margin** or **Cross-margin** for futures.

Default value: **Cash** for spot and **Isolated margin** for futures


8.2.7.6.12. **Position sync period (s)** – the periodicity of positions synchronization in seconds. Set to 0 to disable periodic positions synchronization.

Default value: 180

8.2.8. Click **OK** in a settings window. Wait while the selected connector is initialized. If the initialization was successful, the green **Pause** button will appear and the **Running** message will appear under the lines with version and license information.



8.2.9. To pause the CONNECTOR click the **Pause** button. If the red **Resume** button is visible and the **Paused** message is shown under the lines with version and license information, positions will not be synchronized until the **Resume** button is clicked.



9. CONNECTOR for IB features

- 9.1. Positions will be synchronized between MT5 and IB at the CONNECTOR startup by submitting orders to IB, bringing Binance positions in line with MT5 positions.
For example, your MT5 positions are: 0 EURUSD, 1000 JPYUSD, and your IB positions are: 2000 EURUSD, 0 JPYUSD. During the synchronization, two market orders will be executed from your IB account: sell 2000 EURUSD and buy 1000 JPYUSD.
- 9.2. An attempt to synchronize positions between MT5 and IB will be performed in the same way after clicking the **Resume** button, if the CONNECTOR was paused by clicking the **Pause** button or due to an error during the last synchronization of positions.
- 9.3. If the **Position sync period (s)** setting value is greater than 0, positions will be synchronized periodically. The frequency of synchronizations is defined by the setting value. Periodic synchronization will not be performed if the CONNECTOR is paused.
- 9.4. Only netting accounts are supported, since IB accounts allow only one position on a selected instrument in any direction.
- 9.5. It is possible to work with only one type of the IB contract securities (**Security's type** setting) at a time. If you need to switch to another type of securities, you must stop the CONNECTOR, close all positions in MT5 and IB, and then start the CONNECTOR again. Otherwise, during synchronization, all positions opened in the MT5 terminal will be duplicated in IB with the selected type of the IB contract securities, and IB positions that do not have a match in the MT5 terminal will be closed.

10. CONNECTOR for Binance features

- 10.1. If the **Sync positions at startup** option is selected, positions will be synchronized between MT5 and Binance at the CONNECTOR startup by submitting orders to Binance, bringing Binance positions in line with MT5 positions.
For example, the **Endpoint** setting value is **Futures**, your MT5 positions are: 0 BTCUSD, 0.1 ETHUSD, and your Binance futures positions are: 0.01 BTCUSDT, 0 ETHUSDT. During the synchronization, two market orders will be executed from your Binance account: sell 0.01 BTCUSDT and buy 0.1 ETHUSDT.
- 10.2. An attempt to synchronize positions between MT5 and Binance will be performed in the same way after clicking the **Resume** button, if the CONNECTOR was paused by clicking the **Pause** button or due to an error during the last synchronization of positions.
- 10.3. If the **Position sync period (s)** setting value is greater than 0, positions will be synchronized periodically. The frequency of synchronizations is defined by the setting value. Periodic synchronization will not be performed if the CONNECTOR is paused.
- 10.4. If the **Endpoint** setting value is **Spot**, make sure that your trading account has only USDT and the currencies that you are going to trade.

11. CONNECTOR for KuCoin, Kraken, Bybit and OKX features

- 11.1. If the **Sync positions at startup** option is selected, positions will be synchronized between MT5 and a target platform at the CONNECTOR startup by submitting orders to a target platform, bringing positions at a target platform in line with MT5 positions.
For example, the **Endpoint** setting value is **Spot**, the **Quote currency** setting value is **USDT**, the **MT profit currency** setting value is **USD**, your MT5 positions are: 0 BTC, 0.1 ETH, and your trading account balance at a target platform is: 0.01 BTC, 0 ETH, 100000 USDT. During the synchronization, two market orders will be executed from your trading account at a target platform: sell 0.01 BTC and buy 0.1 ETH.

- 11.2. An attempt to synchronize positions between MT5 and a target platform will be performed in the same way after clicking the **Resume** button, if the CONNECTOR was paused by clicking the **Pause** button or due to an error during the last synchronization of positions.
- 11.3. If the **Position sync period (s)** setting value is greater than 0, positions will be synchronized periodically. The frequency of synchronizations is defined by the setting value. Periodic synchronization will not be performed if the CONNECTOR is paused.
- 11.4. If the **Endpoint** setting value is **Spot**, make sure that your trading account has only the currencies that you are going to trade and the currency specified in the **Quote currency** setting.

12. How to install the CONNECTOR on Linux

12.1. Install [Wine](#) and MetaTrader 5 if not already installed.

12.1.1. Create a shell script file and make it executable using the command line:

```
nano wineAndMt5Install.sh
chmod +x wineAndMt5Install.sh
```

12.1.2. Paste a script for your system to the file and save it. Change MT5_INSTALLER_URL (and the file name on the last line of the script accordingly) if you need to install MetaTrader 5 terminal from a different source. You may also change MT5_WINE_PREFIX and WINE_VERSION if necessary.

12.1.2.1. Ubuntu:

```
#!/bin/bash

# MetaTrader 5 download URL
MT5_INSTALLER_URL="https://download.mql5.com/cdn/web/metaquotes.soft-
ware.corp/mt5/mt5setup.exe"
# Wine prefix where MetaTrader 5 will be installed
MT5_WINE_PREFIX=~/.mt5
# Wine version to install: stable or devel
WINE_VERSION="stable"

# Prepare: switch to 32 bit and add Wine key
sudo dpkg --add-architecture i386
wget -nc https://dl.winehq.org/wine-builds/winehq.key
sudo mkdir /etc/apt/keyrings
sudo mv winehq.key /etc/apt/keyrings/winehq-archive.key

# Get Ubuntu version and trim to major only
OS_VER=$(lsb_release -r |cut -f2 |cut -d "." -f1)
# Choose repository based on Ubuntu version
if (( $OS_VER >= 22 )); then
    wget -nc https://dl.winehq.org/wine-builds/ubuntu/dists/jammy/winehq-jammy.sources
    sudo mv winehq-jammy.sources /etc/apt/sources.list.d/
elif (( $OS_VER < 22 )) && (( $OS_VER >= 21 )); then
    wget -nc https://dl.winehq.org/wine-builds/ubuntu/dists/impish/winehq-impish.sources
    sudo mv winehq-impish.sources /etc/apt/sources.list.d/
elif (( $OS_VER < 21 )) && (( $OS_VER >= 20 )); then
    wget -nc https://dl.winehq.org/wine-builds/ubuntu/dists/focal/winehq-focal.sources
    sudo mv winehq-focal.sources /etc/apt/sources.list.d/
elif (( $OS_VER < 20 )); then
    wget -nc https://dl.winehq.org/wine-builds/ubuntu/dists/bionic/winehq-bionic.sources
    sudo mv winehq-bionic.sources /etc/apt/sources.list.d/
fi

# Update package and install Wine
sudo apt update
sudo apt upgrade
sudo apt install --install-recommends winehq-$WINE_VERSION

# Download MetaTrader 5
wget $MT5_INSTALLER_URL

# Set environment to Windows 10
WINEPREFIX=$MT5_WINE_PREFIX winecfg -v=win10
# Start MetaTrader 5 installer
WINEPREFIX=$MT5_WINE_PREFIX wine mt5setup.exe
```


12.1.2.2. Debian:

```
#!/bin/bash

# MetaTrader 5 download URL
MT5_INSTALLER_URL="https://download.mql5.com/cdn/web/metaquotes.soft-
ware.corp/mt5/mt5setup.exe"
# Wine prefix where MetaTrader 5 will be installed
MT5_WINE_PREFIX=~/.mt5
# Wine version to install: stable or devel
WINE_VERSION="stable"

# Prepare: switch to 32 bit and add Wine key
sudo dpkg --add-architecture i386
wget -nc https://dl.winehq.org/wine-builds/winehq.key
sudo mkdir /etc/apt/keyrings
sudo mv winehq.key /etc/apt/keyrings/winehq-archive.key

# Get Debian version and trim to major only
OS_VER=$(lsb_release -r |cut -f2 |cut -d "." -f1)
# Choose repository based on Debian version
if (( $OS_VER >= 12 )); then
    wget -nc https://dl.winehq.org/wine-builds/debian/dists/bookworm/winehq-
bookworm.sources
    sudo mv winehq-bookworm.sources /etc/apt/sources.list.d/
elif (( $OS_VER < 12 )) && (( $OS_VER >= 11 )); then
    wget -nc https://dl.winehq.org/wine-builds/debian/dists/bullseye/winehq-
bullseye.sources
    sudo mv winehq-bullseye.sources /etc/apt/sources.list.d/
elif (( $OS_VER <= 10 )); then
    wget -nc https://dl.winehq.org/wine-builds/debian/dists/buster/winehq-buster.sources
    sudo mv winehq-buster.sources /etc/apt/sources.list.d/
fi

# Update package and install Wine
sudo apt update
sudo apt upgrade
sudo apt install --install-recommends winehq-$WINE_VERSION

# Download MetaTrader 5
wget $MT5_INSTALLER_URL

# Set environment to Windows 10
WINEPREFIX=$MT5_WINE_PREFIX winecfg -v=win10
# Start MetaTrader 5 installer
WINEPREFIX=$MT5_WINE_PREFIX wine mt5setup.exe
```

12.1.3. Run the script.

12.2. Check if [Winetricks](#) is installed:

```
dpkg -s winetricks
```

If not, follow the [installation procedure](#).

12.3. Check if .NET Framework 4.8 is installed. Run command (replace [wine prefix path] with the path to the Wine prefix where you want to install the CONNECTOR):

```
WINEPREFIX=[wine prefix path] winetricks list-installed
```

If the output does not contain dotnet48 line, run .NET Framework 4.8 [automatic installation through winetricks](#) (replace [wine prefix path] with the path to the Wine prefix where you want to install the CONNECTOR):

```
WINEPREFIX=[wine prefix path] winetricks dotnet48
```

12.4. Download and start the CONNECTOR installer (replace `[wine prefix path]` with the path to the Wine prefix where you want to install the CONNECTOR):

```
wget "https://connector.solutions/Themes/Orchard.ConnectorSolutions/content/download/CSMultiConnector_Setup.exe"
```

```
WINEPREFIX=[wine prefix path] wine CSMultiConnector_Setup.exe
```


13. How to install the CONNECTOR on Mac OS

13.1. Download and install [XQuartz](#) if not installed.


13.2. [Download](#) and [install](#) PlayOnMac if not installed and run it.

13.3. Install Wine version 7.10 or later if not installed.

13.3.1. Click **Tools** → **Manage Wine versions** in the PlayOnMac menu bar.





13.3.2. Select **Wine versions (amd64)** in the **PlayOnMac wine versions manager** window. Select 7.10 or later Wine version and click > to start installation wizard.




13.3.3. Click **Next** in the wizard window.



13.3.4. Wait for the installation to complete.




13.4. Click **Configure** in the PlayOnMac window.



13.5. Select existing 64 bits virtual drive (Wine prefix) or create a new one.


13.5.1. Click **New** in the **PlayOnMac configuration** window to create a new virtual drive.




13.5.2. Click **Next** in the **Virtual drive creator** wizard window.




13.5.3. Select **64 bits windows installation** option and click **Next**.



13.5.4. Select Wine version 7.10 or later and click **Next**.




13.5.5. Enter the name of the virtual drive, click **Next** and wait for the installation to complete.




13.6. Install .NET Framework 4.8 to your Wine virtual drive if not installed.


13.6.1. Change Wine reported version to Windows XP. Select Wine virtual drive, select **Wine** tab on right pane and click **Configure Wine**.




13.6.2. Select **Applications** tab in the **Wine configuration** window. Select **Windows XP** version and click **Apply**.




13.6.3. [Download](#) .NET Framework 4.0 installer. Select **Miscellaneous** tab in the **PlayOnMac configuration** window and click **Run a .exe file in this virtual drive**.




13.6.4. Select downloaded file and click **Open**. Follow the instructions in the .NET Framework 4.0 installer wizard and wait for the installation to complete.




13.6.5. Select **Libraries** tab in the **Wine configuration** window, add a new override for library **mscoree**.




13.6.6. Select the new override in the **Existing overrides** field and click **Edit**. In the **Edit override** window select **Native (Windows)** option and click **OK**.




13.6.7. Click **Apply**.



13.6.8. Select **Applications** tab in the **Wine configuration** window. Select **Windows 7** or later Windows version and click **OK**.



13.6.9. [Download](#) and run the .NET Framework 4.8 installer. Refer to sections **11.6.3** and **11.6.4** of this manual to learn how to run .exe files on a Wine virtual drive. Follow the instructions in the .NET Framework 4.8 installer wizard and wait for the installation to complete. Allow restarting Windows or restart it manually by clicking **Reboot Windows** on the **Wine** tab in the **PlayOnMac configuration** window.



13.7. Install **MetaTrader 5** to your Wine virtual drive if not installed. Refer to sections **11.6.3** and **11.6.4** of this manual to learn how to run .exe files on a Wine virtual drive. Follow the instructions in the MetaTrader 5 installer wizard and wait for the installation to complete.

13.8. [Download](#) and run the CONNECTOR installer. Refer to sections **11.6.3** and **11.6.4** of this manual to learn how to run .exe files on a Wine virtual drive. Follow the instructions in the CONNECTOR installer wizard and wait for the installation to complete.

Index

CONNECTOR User Manual.....	1
1. Configuring the MT5 terminal	1
2. Configuring the IB terminal (TWS).....	3
3. Configuring a Binance account.....	5
4. Configuring a KuCoin account	8
5. Configuring a Kraken account	10
6. Configuring a Bybit account	14
7. Configuring an OKX account	16
8. Launching the CONNECTOR	18
8.2.7.1. IB settings window	23
8.2.7.2. Binance settings window.....	24
8.2.7.3. KuCoin settings window	25
8.2.7.4. Kraken settings window	26
8.2.7.5. Bybit settings window	27
8.2.7.6. OKX settings window	28
9. CONNECTOR for IB features	30
10. CONNECTOR for Binance features.....	30
11. CONNECTOR for KuCoin, Kraken, Bybit and OKX features.....	30
12. How to install the CONNECTOR on Linux	32
13. How to install the CONNECTOR on Mac OS	35