

Spatial Population Model User Manual

(SPM v0.1-2009-03-02-00:23:24 UTC (rev. 3018))

Alistair Dunn, Scott Rasmussen

February 2009

Citation:
Dunn, A.; Rasmussen, S. (2009) Spatial Population Model User Manual (SPM
v0.1-2009-03-02-00:23:24 UTC (rev. 3018)). National Institute of Water & Atmospheric Research
Ltd. *Unpublished report*. 125 p.

Contents

1	Introduction	1
1.1	Version	1
1.2	Citing SPM	1
1.3	Software license	1
1.4	System requirements	1
1.5	Necessary files	2
1.6	Useful add-ons	2
1.7	Getting help	2
1.8	Technical details	2
2	Model overview	3
2.1	Introduction	3
2.2	Model specification	4
2.2.1	The population section	4
2.2.2	The estimation section	6
2.2.3	The observation section	6
2.2.4	The output section	6
3	Running SPM	7
3.1	The input configuration file	7
3.2	Redirecting standard output	8
3.3	Command line arguments	8
3.4	Constructing an SPM input configuration file	9
3.4.1	Commands	9
3.4.2	Subcommands	10
3.4.3	The command-block format	10
3.4.4	Commenting out lines	11
3.4.5	Determining parameter names	11
3.5	SPM exit status values	12
4	The population section	13
4.1	Spatial structure	13
4.2	Population structure	13
4.3	Layers	15
4.4	Time sequence	17
4.4.1	Model initialisation	17
4.4.2	Model years	17
4.5	Processes	18
4.6	Population processes	18
4.6.1	Recruitment	18
4.6.2	Ageing	19
4.6.3	Mortality	19

4.6.4	Category transitions	20
4.6.5	Movement processes	21
4.7	Derived quantities	23
4.8	Size-at-age	23
4.9	Mean weight	24
4.10	Selectivities	24
4.10.1	Selectivity descriptions	25
5	The estimation section	27
5.1	Role of the estimation section	27
5.2	Specifying the free parameters	27
5.3	Point estimation	27
5.4	Posterior profiles	28
5.5	Bayesian estimation	29
6	The observation section	33
6.1	Types of observations	33
6.1.1	Event mortality proportions-at-age	33
6.1.2	Proportions-at-age	33
6.1.3	Proportions-by-age	33
6.1.4	Abundance	33
6.2	The objective function	33
6.2.1	Likelihoods	33
6.2.2	The objective function	33
7	The output section	35
8	General commands and subcommands	37
9	Population command and subcommand syntax	39
9.1	Model structure	39
9.2	Processes	41
9.2.1	Constant recruitment process	41
9.2.2	Beverton-Holt recruitment process	42
9.2.3	Ageing process	43
9.2.4	Constant mortality rate process	43
9.2.5	Annual mortality rate process	44
9.2.6	Event mortality process	44
9.2.7	Biomass event mortality process	45
9.2.8	Category transition process	46
9.2.9	Category transition rate process	46
9.2.10	Migration movement	47
9.2.11	Adjacent cell movement	47
9.2.12	Preference movement	48
9.3	Preference functions	48

9.3.1	Constant	48
9.3.2	Normal	49
9.3.3	Double-normal	49
9.3.4	Logistic	50
9.3.5	Inverse-logistic	50
9.3.6	Exponential-decay	50
9.3.7	Threshold	51
9.3.8	Threshold-biomass	51
9.4	Layers	52
9.4.1	Numeric	53
9.4.2	Categorical	53
9.4.3	Distance	53
9.4.4	Abundance	53
9.4.5	Biomass	53
9.4.6	Abundance-density	54
9.4.7	Biomass-density	54
9.4.8	MetaLayer	55
9.5	Derived quantities	55
9.5.1	Abundance	55
9.5.2	Biomass	56
9.6	Size-at-age	56
9.6.1	von Bertalanffy	56
9.6.2	Schnute	57
9.7	Size-weight	58
9.7.1	None	59
9.7.2	Basic	59
9.8	Selectivities	59
9.8.1	Constant	60
9.8.2	Knife-edge	60
9.8.3	All-values	60
9.8.4	All-values-bounded	60
9.8.5	Increasing	60
9.8.6	Logistic	61
9.8.7	Logistic producing	61
9.8.8	Double-normal	62
9.8.9	Double-exponential	62
10	Estimation command and subcommand syntax	63
10.1	Estimation methods	63
10.2	Maximum posterior density (MPD)	63
10.2.1	Numerical differences minimiser	63
10.2.2	Differential evolution minimiser	64
10.3	Monte Carlo Markov Chain (MCMC)	64

10.3.1	Metropolis-Hastings	65
10.4	Profiles	66
10.5	Defining the free parameters and priors	67
10.5.1	Uniform prior	67
10.5.2	Uniform-log prior	68
10.5.3	Normal prior	68
10.5.4	Normal-by-stdev prior	68
10.5.5	Lognormal prior	68
10.5.6	Beta prior	69
10.6	Defining ageing error	69
10.6.1	No ageing error	69
10.6.2	Normal ageing error	70
10.6.3	Off-by-one ageing error	70
10.7	Defining catchability constants	70
10.8	Defining penalties	70
11	Observation command and subcommand syntax	71
11.1	Observation types	71
11.1.1	Event mortality-at-age	71
11.1.2	Proportions at age	73
11.1.3	Proportions-by-age	75
11.1.4	Abundance	77
11.1.5	Biomass	78
12	Output command and subcommand syntax	81
12.1	Free parameters	81
13	Examples	83
13.1	An example of a simple 1×1 non-spatial model	83
13.2	An example of a simple 10×10 spatial model	83
13.3	An example of a more complex 10×10 spatial model	84
14	Post processing output using R	87
15	Troubleshooting	89
15.1	Typical errors	89
15.2	Other errors	89
15.3	Reporting errors	89
15.4	Guidelines for reporting a bug in SPM	90
16	Acknowledgements	91
17	Quick reference	93
17.1	General commands and subcommands	93
17.2	Population command and subcommand syntax	93

17.3 Estimation command and subcommand syntax	99
17.4 Observation command and subcommand syntax	101
17.5 Output command and subcommand syntax	104
18 References	105
19 Spatial Population Model software license	107
20 Index	111

List of figures

4.1	An illustration of the <i>square</i> spatial structure	14
4.2	An illustration of the <i>hexagon</i> spatial structure	14

List of tables

1. Introduction

The Spatial Population Model (SPM) is a generalised spatially explicit age-structured population dynamics and movement model. SPM can model population dynamics and movement parameters for an age-structured population using a range of observations, including tagging, relative abundance, and age frequency data. SPM implements an age-structured population within an arbitrary shaped spatial structure, which can have user defined categories (e.g., immature, mature, male, female, etc.), and age range. Movement can be modelled as either adjacent cell movements or global movements based on covariates.

This manual describes how to use SPM, including how to run SPM, how to set up an input configuration file. Further, we describe the population dynamics and estimation methods, and describe how to specify and interpret output. If you are new to SPM, then a good place to start is by reading this manual and attempting to replicate the examples (Section 13).

1.1. Version

This document (last modified 2009-02-27) details the usage of SPM v0.1-2009-03-02-00:23:24 UTC (rev. 3018) . The SPM version number is suffixed with a date/time (yyyy-mm-dd-hh:mm:ss) and revision number, giving the revision control system UTC date and revision number for the most recent modification of the source files. User manual updates will usually be issued for each minor version or date release of SPM, and can be obtained, on request, from the authors.

1.2. Citing SPM

A suitable reference for SPM and this document is:

Dunn, A.; Rasmussen, S. (2009) Spatial Population Model User Manual (SPM v0.1-2009-03-02-00:23:24 UTC (rev. 3018)). National Institute of Water & Atmospheric Research Ltd. *Unpublished report*. 125 p.

1.3. Software license

This program and the accompanying materials are made available under the terms of the Common Public License v1.0 which accompanies this distribution (Section 19).

Copyright ©2008-2009, National Institute of Water & Atmospheric Research Ltd. and the New Zealand Ministry of Fisheries. All rights reserved.

1.4. System requirements

SPM is available for most IBM compatible machines running Linux and from the command prompt under most Microsoft Windows operating systems.

Several of SPMs tasks are highly computer intensive and a fast, powerful processor is recommended. We recommend a minimum of 10 megabytes of free RAM (although, depending on the scope of the problem, you may need much more). Some of SPMs tasks can be multi-threaded, and hence multi-core machines may perform some tasks considerably quicker than single core processors. The program itself requires only a few megabytes of hard-disk space but output files can consume large amounts of disk space. Depending on number and type of user output requests, the output

could range from a few hundred kilobytes to several hundred megabytes. However, we note that, depending on the model implemented, some of SPMs tasks can take a considerable amount of time.

1.5. Necessary files

In Linux, only the executable file `spm` is required to run SPM (but, depending on your system, you may need the either the 32- or 64-bit version). For Microsoft Windows, you need the executable file `spm.exe`. There is no 64-bit version for Microsoft Windows.

1.6. Useful add-ons

No software other than the appropriate operating system or emulation package is required to run SPM. However, as SPM offers little in the way of post-processing of the output, most users will wish to have a package available that allows tabulation and graphing of model outputs. We recommend the use of software packages such as Microsoft Excel, S-Plus, or R (R Development Core Team 2007). See Section 14 for details of the `spm` R package for extracting SPM output.

1.7. Getting help

SPM is distributed as unsupported software. The authors do not, as a rule, provide help for users of SPM. However, we may be able to offer limited assistance, and we would appreciate being notified of any problems or errors in SPM. See Section 15.3 for how to report errors to the authors. Further information about SPM can be obtained by contacting the authors.

1.8. Technical details

SPM is compiled on Linux using `gcc`, the C/C++ compiler developed by the GNU Project. The 32-bit Linux version has been compiled using `gcc` version 4.1.2 20070115 (prerelease) (SuSE Linux), the 64-bit Linux version uses `gcc` version 4.1.0 (SuSE Linux). Note that SPM is not supported for Linux kernel versions prior to 2.6. The Microsoft Windows version is compiled using Mingw32 `gcc` 3.4.5, and should run on most 32-bit WindowsXP and Windows Vista systems. There are no plans to port SPM to Microsoft Windows 64-bit platforms.

SPM uses two minimisers, — the first is closely based on the main algorithm of Dennis Jr and Schnabel (1996), and which uses finite difference gradients, and the second is an implementation of the differential evolution solver (Storn and Price, 1995). The random number generator used by SPM uses an implementation of the Mersenne twister random number generator (Matsumoto and Nishimura, 1998), from the BOOST C++ library (Version 1.38.0).

Note that the output from SPM may differ slightly on the different platforms due to different precision arithmetic or other platform dependent implementation issues. The source code for SPM is available on request.

2. Model overview

2.1. Introduction

The Spatial Population Model (SPM) is a generalised spatially explicit age-structured population dynamics and movement model. It allows the implementation of population models suitable for the simulation and estimation of parameters in models with a large number of areas. It implements a statistical catch-at-age population dynamics and movement model, using a discrete time-step state-space model that represents a cohort-based population age structure in a spatially explicit manner.

The basic structure of the model is defined in terms of the *state*. The state is the current status of the population at a point in time. The state consists of two parts, the *partition* and *derived quantities*. The state will typically change one or more times in every *time step* of every year, depending on the *processes* defined for each model.

The partition is the matrix of the numbers of individuals within each spatial cell, age, and category at a particular instance in time. A derived quantity is a cumulative summary of the state at some point in time. Unlike the partition (which is updated as each new process is applied), each derived quantity records a single value for each year of the model run. Hence, derived quantities build up a vector of values over the model run years. For example, the numbers of individuals in a category labelled mature at some point in the annual cycle may be a derived quantity. Hence, the state is the combination of the partition and the derived quantities at some instance in time. Changes to the partition occur by the application of *processes*. Additions to the vectors of derived quantities occur when the model is requested to add a value to each derived quantity vector.

The application of processes within each year is controlled by the *annual cycle*. This defines what processes happen in each model year, and in what sequence. Further, each year is split up into one or more time steps (with at least one process occurring in each time step). You can think of each time step as representing a particular part of the calendar year, or you can just treat them as an abstract sequence of events.

The division of the year into an arbitrary number of time steps allows the user to specify the exact order in which processes occur and when observations are evaluated. The user specifies the time steps, their order, and the processes within each time step. If more than one process occurs in the same time step, then they occur in the order that they are specified. Observations are always evaluated at the end of a time step. Hence, time steps can be used to break processes into groups, and assist in defining the timing of the observations within the annual cycle.

An SPM model can be parametrised by both population processes (for example, ageing, recruitment, and mortality) and movement processes. Movement is by either adjacent cell movements, between cell migrations, or by global movements parametrised as a function of known attributes at each spatial location (termed preference functions — see later). SPM is designed to be flexible and to allow for the estimation of both population and movement parameters from local or aggregated spatially explicit observations.

The population structure of SPM follows the usual population modelling conventions and is similar to those implemented in other population models, for example CASAL (Bull et al., 2008). The model records the numbers of individuals by age and category (i.e., male, female), as well as the locations of these cohorts within a spatial grid. In general, cohorts are added via a recruitment event, are aged annually, and are removed from the population via various forms of mortality. The population is assumed to be closed (i.e., no immigration or emigration from the modelled area)

The spatial component of SPM is designed to allow parametrise movement cohorts and groups of individuals between spatial locations, and hence allow movement parameters to be estimated by

incorporating spatially explicit observations.

A model is implemented in SPM using an input configuration file, which is a complete description of the model structure (i.e., spatial and population processes), observations, estimation methods, and outputs (reports) requested. SPM runs from a command prompt window in Microsoft Windows or from a text terminal in Linux. A model can be either *run*, free parameters can be *estimated* or *profiled*, *MCMC* distributions calculated, and these estimates can be *projected* into the future or used as an operating model to *simulate* observations.

This section gives a quick overview of the model, and how to use it. Detailed descriptions of the components of SPM, the model structures, mathematical equations used, and command and subcommand arguments are given in the following sections.

2.2. Model specification

A model in SPM is specified by the input configuration file in four components. These are the population section (model structure, population and spatial dynamics, etc.), the estimation section (methods of estimation and the parameters to be estimated), the observation section (observational data and associated likelihoods), and the output section (printouts and reports from the model). These sections completely describe a model implemented in SPM. See Sections 9, 10, 11, and 12 for details and specification of SPMs command and subcommand syntax.

2.2.1. The population section

The population section (Section 4) defines the model of the movement and population dynamics. It describes the model structure (both the spatial and population structure), defines the population and movement processes (for example, recruitment, migration, and mortality), layers (the known attributes of each spatial cell), selectivities, and key population parameters.

It consists of several components, including;

- The spatial and population structure
- Model initialisation (i.e., the state of the model at the start of the first year)
- The annual cycle (time steps and processes that are applied in each time step)
- The specifications and parameters of the processes;
 - Population processes (i.e., processes that add, remove, or shift numbers between ages and categories)
 - Spatial processes (i.e., processes that move or shift cohorts between spatial locations but not their ages or categories)
- Layers and their definitions,
- Selectivities
- Parameter values and their definitions
- Derived quantities required as parameters for some processes (i.e., spawning stock biomass to resolve the spawner-recruit relationship in a recruitment process)

The spatial structure of SPM is represented by an $n_{rows} \times n_{cols}$ grid, with rows $i = 1 \dots n_{rows}$ and columns $j = 1 \dots n_{cols}$. Each cell of this matrix records the population structure at that point in space, where the population structure is represented by an $n_{categories} \times n_{ages}$ rectangular matrix (with categories $k = 1 \dots n_{categories}$ and ages $l = 1 \dots n_{ages} = age_{min} \dots age_{max}$). Hence we can describe any

spatial and population element of the model as $\text{element}(i, j, k, l)$. We define, within the spatial grid ($n_{\text{rows}} \times n_{\text{cols}}$), locations where the population can and cannot potentially be present using a *layer*.

The layout of the spatial grid can be either *square* or a north-south orientated *hexagon*. We note that the spatial grid can be of an arbitrary size, but must be rectangular.

Within each (i, j) element of the spatial grid element (termed spatial *cell*), the population structure in SPM is represented by a matrix containing an arbitrary number of user defined categories (rows), and an arbitrary age range (columns). Hence, each spatial cell has a population state described as $n_{\text{categories}} \times n_{\text{ages}}$ rectangular matrix with categories $k = 1 \dots n_{\text{categories}}$ and ages $l = \text{age}_{\text{min}} \dots \text{age}_{\text{max}}$.

Model initialisation can occur in several phases, each which iterates through a number of years carrying out the population and/or spatial processes defined for that phase. Analytical initialisation is not implemented in SPM, hence equilibrium and initial population states must be evaluated iteratively. At the end of the initialisation, SPM runs through the model years carrying out processes in the order defined in the annual cycle, and can evaluate expected values of observations in order to calculate likelihoods, project forward to determine future states, or simulate observations from the current state.

SPM has two types of processes, *population* and *movement* processes. Population processes are those processes which modify, move or otherwise change the numbers of individuals *within* a spatial cell, i.e., they do not affect the spatial location of a cohort. Movement processes, on the other hand, move, shift or otherwise modify cohorts *between* spatial cells, but do not affect the age or category of the numbers in each cohort.

The population processes include recruitment, ageing, mortality events (e.g., natural and exploitation) and category transition processes (i.e., processes that move individuals between categories, while preserving their age structure). See Section 4 for a complete list of available processes.

Each of these processes is carried out in the user-defined prescribed order when initialising the model, and then for a user-defined order in each year in the annual cycle.

SPM implements three different types of movement processes;

1. A migration movement rate of cohorts between any two locations, and is roughly analogous to movements between areas as implemented in other population models, such as CASAL (Bull et al., 2008).
2. An adjacent cell movements, parametrised by some function of an underlying layer—equivalent to, for example, movement processes implemented in Fish Heaven (Ball and Constable, 2000, Ball and Williamson, 2003).
3. Movement parametrised as a probability density function. Here, the key underlying idea is that the spatial distribution of cohorts at any point in time and at any location can be represented as a density function based on attributes of that location, local abundance, and/or distance from their previous location (Bentley et al., 2004a,b).

The annual cycle is implemented as a set of processes that occur, in a user-defined order, within each year. User-defined time steps are used to break the annual cycle into separate components, and allow observations to be associated with different sets of processes. Any number of processes can occur within each time step, in any order and can occur multiple times within each time step. Note that time steps are not implemented during the initialisation phases, and that the annual cycle in the initialisation phases can be different from that run during the model years.

Some processes require, as arguments, a population value derived from the population state. These are termed *derived quantities*. For example, a recruitment process may require the amount of

spawning stock biomass to resolve the stock-recruit relationship. In this example, the spawning stock biomass could be defined as the abundance or biomass of a part of the population at some point in the annual cycle, for selected ages and categories. Derived quantities are described further in the population section (Section 4).

Layers are used by SPM to evaluate locations where the population may be present (via the *base layer*, to provide sets of known attributes of each spatial location (for preference based movements), and to group or categorise cells for use by processes and observations. Layers consist of an $n \times m$ matrix and can be either *logical*, *numeric*, or *categorical*. See Section 4 for further details.

A selectivity is a function with a different value for each age class (i.e., for each column of the partition). Selectivities are used throughout SPM to interpret observations (Section 5 or to modify the effects of processes on each age class 4. SPM implements a number of different parametric forms, including logistic, knife edge, and double normal selectivities. See Section 4.10 for more details.

2.2.2. The estimation section

The estimation section specifies the free parameters, estimation methods, penalties and priors. Estimation is based on an objective function (e.g., negative log posterior). Depending on the run mode, the estimation section is used to specify the methods for finding a point estimate (i.e., the set of parameter values that minimizes the objective function), doing profiles, or MCMC methods and options, etc.

Further, the estimation section specifies the *free parameters*, i.e., those parameters that are to be estimated (i.e., free) within each model run. The estimation section specifies the choice of estimation method, which parameters are to be estimated, priors, starting values, and minimiser control values.

Penalties and priors act as constraints on the estimation. They can either encourage or discourage (depending on the specific implementation) parameter estimates that are ‘near’ some value, and hence influence the estimation process. For example, the catch-limit penalties can be used to discourage parameter estimates that lead to models where the recorded catch was unable to be fully taken.

2.2.3. The observation section

Observations are data which allow us to make inferences about unknown parameters. Examples include relative or absolute abundance indices, proportions-at-age frequencies, etc. Estimation in SPM involves finding values for each of the free parameters so that each observation is ‘close’ (in some mathematical sense) to a corresponding expected value.

Types of observations, their values, and the associated error structures are defined in the observation section.

2.2.4. The output section

The output section specifies to model outputs. It defines the quantities and model components to be output to external files or to the screen. While SPM will provide informational messages to the screen, the SPM will only produce model estimates, population states, and other data as requested by the output section.

3. Running SPM

SPM gets its information from input data files, the key one of which is the input configuration file. The input configuration file is compulsory and defines the model structure, processes, observations, free and fixed parameters, and the outputs requested. The following sections describe how to construct the SPM configuration file. By convention, the name of the input configuration file ends with the suffix `.spm`, however, any file name is acceptable.

Other input files can, in some circumstances, be supplied to define the starting point for an estimation, define the parameters for a projection, or to simulate observations.

Simple command line arguments are used to determine the actions or *tasks* of SPM, i.e., to run a model with a set of parameter values, estimate parameter values (either point estimates or MCMC), project quantities into the future, simulate observations, etc. Hence, the *command line arguments* define the *task*. For example, `-r` is *run*, `-e` is *estimation*, and `-s` is the *simulation* task. The *command line arguments* are described in Section 3.3.

3.1. The input configuration file

The input configuration file comprises of five parts (preamble, population, estimation, observations, and output). All of these, except the preamble, are compulsory. SPM will error out if one of the compulsory sections is missing.

preamble the preamble occurs at the start of the input configuration file, before the three sections defined below. SPM ignores any text within this section, and hence the preamble can be used to record comments or descriptions of the input configuration file.

population the population section is defined in the input configuration file by the text `[population]`. This must be the only text on that line. All commands and subcommands that follow the `[population]` header, until the `[estimation]` header is reached, are considered to be commands and subcommands that define the population structure of the model. The population section is described in Section 4.

estimation the estimation section is defined in the input configuration file by the text `[estimation]`. This must be the only text on that line. All commands and subcommands that follow the `[estimation]` header, until the `[observation]` header is reached, are considered to be commands and subcommands that define the estimation structure of the model. The estimation section is described in Section 5.

observation the observation section is defined in the input configuration file by the text `[observation]`. This must be the only text on that line. All commands and subcommands that follow the `[observation]` header, until the `[output]` header is reached, are considered to be commands and subcommands that define the observation structure of the model. The observation section is described in Section 6.

output the output section is defined in the input configuration file by the text `[output]`. This must be the only text on that line. All commands and subcommands that follow the `[output]` header, until the end of the file is reached, are considered to be commands and subcommands that define the outputs of the model. The output section is described in Section 7.

The command and subcommand definitions in the input configuration file can be extensive, and can result in an input configuration file that is long and difficult to navigate. To aid readability and flexibility, we can use the input configuration file command `@include 'file'`. The command causes an external file, `file`, to be read and processed, exactly as if its contents had been inserted

in the main input configuration file at that point. The file name must be a complete file name with extension, but can have either a relative or absolute path as part of its name. Note that included files can also contain `@include` commands — be careful that you do not set up a recursive state. See Section 8 for more detail.

3.2. Redirecting standard output

SPM uses the standard out to display run-time information. Standard error is not used by SPM, but may be used by the operating system to report an error with SPM. We suggest redirecting both the standard out and standard error into files. With the bash shell (on Linux systems), you can do this using the command structure,

```
(spm [arguments] > out) >& err &
```

It may also be useful to redirect the standard input, especially if you're using SPM inside a batch job software, i.e.

```
(spm [arguments] > out < /dev/null) >& err &
```

On Microsoft Windows systems, you can redirect to standard output using,

```
spm [arguments] > out
```

And, on some recent Microsoft Windows systems (e.g., Professional versions of WindowsNT, Windows2000, and WindowsXP), you can redirect to both standard output and standard error, using the syntax,

```
spm [arguments] > out 2> err
```

Note that SPM outputs a few lines of header information to the output. The header consists of the program name and version, the arguments passed to SPM from the command line, the date and time that the program was called (derived from the system time), the user name, and the machine name (including the operating system and the process identification number). These can be used to track outputs as well as identifying the version of SPM used to run the model.

3.3. Command line arguments

The call to SPM is of the following form.:

```
spm [task] [config_file] [options]
```

where *task* is one of;

- h** Display help (this page).
- l** Display the reference for the software license (CPLv1.0).
- v** Display the SPM version number.
- r config_file** Run the model once using the parameter values in the input configuration file denoted by *config_file*, or optionally, with the values in the file denoted with the command line argument *-i file*.

- e *config_file*** Do a point *estimate* of the free parameters using the parameter values in the input configuration file denoted by *config_file* as the starting point for the estimation, or optionally, with the start values in the file denoted with the command line argument **-i *file***.
- p *config_file*** Do a likelihood *profile* using the parameter values in the input configuration file denoted by *config_file* as the starting point, or optionally, with the start values in the file denoted with the command line argument **-i *file***.
- m *config_file*** Do an *MCMC* estimate of the free parameters using the parameter values in the input configuration file denoted by *config_file* as the starting point for the estimation, or optionally, with the start values in the file denoted with the command line argument **-i *file***.
- f *config_file*** Project the model *forward* in time using the parameter values in the input configuration file denoted by *config_file* as the starting point for the estimation, or optionally, with the start values in the file denoted with the command line argument **-i *file***.
- s *config_file*** *Simulate* observations of the free parameters using the parameter values in the input configuration file denoted by *config_file* as the starting point for the estimation, or optionally, with the start values in the file denoted with the command line argument **-i *file***.

In addition, the following are optional arguments [*options*],

- i *file*** *Input* one or more sets of free parameter values from *file*. See Section 12.1 for details about the format of *file*.
- t *number*** Number of *threads* to run (i.e., number of processors available for use).
- q** Run *quietly*, i.e., suppress verbose printing of SPM.
- g *seed*** Seed the random number *generator* with *seed*, a positive (long) integer value. Note, if **-g** is not specified, then SPM looks to the [estimation] section for a random number seed @random_seed, and if not defined, then automatically generates a random number seed based on the computer clock time.

3.4. Constructing an SPM input configuration file

The model definition, parameters, observations, and output are specified in an input configuration file. The population section is described in Section 4 and the population commands in Section 9. Similarly, the estimation section is described in Section 5 and its commands in Section 10, and in Section 7 and Section 12 for the output and output commands.

In general, the input configuration file uses a command-block format to describe commands, subcommands, and their arguments and values. The input configuration file consists of any number of command-blocks in any order, but these must be within the [population], [estimation], and [output] sections for the population, estimation, and output commands respectively.

3.4.1. Commands

SPM has a range of commands that define the model structure, processes, observations, and how tasks are carried out. There are three types of commands,

1. Commands that have an argument and do not have subcommands (for example, @IncludeFile *file*)

2. Commands that have a label and subcommands (for example @ConstantRecruitment MyRecruitment)
3. Commands that do not have either a label or argument, but have subcommands (for example @Structure)

Commands that have a label must have a unique label, i.e., the label cannot be used on more than one command. The labels must start with a letter or underscores, can contain letters, underscores, or numbers, but must not contain white-space or full-point ('.').

3.4.2. Subcommands

Subcommands in SPM are for defining options and parameter values for commands. They always take an argument which is one of a specific *type*. The types acceptable for each subcommand are defined in Section 8, and are summarised below.

Unlike commands (@command), subcommands and their arguments can be order specific. In other words, the order in which they appear is important, and can affect the way in which they are interpreted. SPM may report an error if they are not supplied in the order that is expected, however, in some circumstances a different order may result in a valid, but unintended set of actions, leading to possible errors in your expected results.

The arguments for a subcommand are either,

switch true/false

integer an integer number

integer vector a vector of integer numbers

constant a real number (i.e., double)

constant vector a vector of real numbers (i.e., vector of doubles)

estimable a real number that can be estimated (i.e., estimable double)

estimable vector a vector of real numbers that can be estimated (i.e., vector of estimable doubles)

string a categorical (string) value

string vector a vector of categorical values

Switches are parameters which are either true or false. Enter *true* as true or t, and *false* as false or f.

Integers must be entered as integers (i.e., if Year is an integer then use 2008, not 2008.0)

Arguments of type integer vector, constant vector, estimable vector, or categorical vector contain one or more entries on a row, separated by white space (tabs or spaces).

Estimable parameters are those parameters that SPM can estimate, if requested. If a particular parameter is not being estimated in a particular model run, then it acts as a constant. Within SPM only estimable parameters can be estimated. And, you have to tell SPM those that are to be estimated in any particular model. Estimable parameters that are being estimated within a particular model run are called the *free parameters*.

3.4.3. The command-block format

Each command-block either consists of a single command (starting with the symbol `)` and, for most commands, a label or an argument. Each command is then followed by its subcommands and their

arguments, e.g.,

```
@command, or
@command argument, or
@command label
```

and then

```
subcommand argument
subcommand argument
etc.,
```

Blank lines are ignored, as is extra white space (i.e., tabs and spaces) between arguments. But don't put extra white space before a @ character (which must also be the first character on the line), and make sure the file ends with a carriage return. Commands and subcommands consist of letters and/or underscores, must not contain a space or full-point ('.').

There is no need to mark the end of a command block. This is automatically recognized by either the end of the file, section, or the start of the next command block (which is marked by the @ on the first character of a line). Note, however, that the @IncludeFile is the only exception to this rule. See Section 8) for details of the use of @IncludeFile.

In general, commands, sub-commands, and arguments in the parameter files are case insensitive. But note, however, that if you are on a Linux system then external calls to files are case sensitive (i.e., when using @IncludeFile *file*, the argument *file* will be case sensitive).

3.4.4. Commenting out lines

Text that follows a # on a line are considered to be comments and are ignored. If you want to remove a group of commands or subcommands using #, then comment out all lines in the block, not just the first line.

Alternatively, you can comment out an entire block or section by placing curly brackets around the text that you want to comment out. Put in a { as the first character on the line to start the comment block, then end it with }. All lines (including line breaks) between { and } inclusive are ignored. (These should ideally be the first character on a line. But if not, then the entire line will be treated as part of the comment block.)

3.4.5. Determining parameter names

When SPM processes a input configuration file, it translates each command and each subcommand into a parameter with a unique name. For commands, this parameter name is simply the command name. For subcommands, the parameter name format is either,

```
Command[label].Subcommand if the command has a label, or
Command.Subcommand if the command has no label, or
Command[label].Subcommand[i] if the command has a label, and the subcommand arguments
are a vector, and we are accessing the ith element of that vector.
```

The unique parameter name is used to reference the parameter when estimating, applying a penalty, or applying a profile. For example, the parameter name of subcommand R0 of the command

@ConstantRecruitmentProcess with the label MyRecruitment is,
ConstantRecruitmentProcess[MyRecruitment].R0

3.5. SPM exit status values

When SPM completes its task successfully or errors out gracefully, it returns a single exit status value (0) to the operating system. The operating system will return -1 if SPM terminates unexpectedly. Hence, to determine if SPM completed its task successfully, check the standard output for error and information messages.

4. The population section

The population section defines the model of the movement and population dynamics. It describes the model structure (both the spatial and population structure), defines the population and movement processes (for example, recruitment, migration, and mortality), defines the layers (the known attributes of each spatial cell), selectivities, and model parameters.

The population, at any point in time, is described by the *state*, which comprises of the *partition* and any *derived quantities*. The partition is comprised of the spatial structure, and within each spatial location, the population structure.

The spatial structure of SPM is represented by an $n \times m$ grid, with rows $i = 1 \dots n$ and columns $j = 1 \dots m$. Each cell of this matrix records the population structure at that point in space and is represented by an $k \times l$ rectangular matrix (with categories $k = 1 \dots k$ and ages $l = age_{min} \dots age_{max}$). Hence we can describe any spatial and population element of the model as $element(i, j, k, l)$.

4.1. Spatial structure

SPM implements two spatial structures, one derived from a grid of *square* cells —the default (Figure 4.1) and the other derived from a grid of north-south orientated *hexagons* (Figure 4.2).

The dimensions of the spatial grid are user defined but must be at least a 1×1 grid (i.e., a single spatial cell). Associated with the spatial structure is the one compulsory layer (see Section 4.3), the *base layer*. This defines the locations where the population can and cannot potentially be present (e.g., in a marine model, the locations associated with the sea and not land) as values within the base layer that are greater than zero. There must be at least one cell in the spatial grid where the population can be present. In addition, the base layer also defines the relative *area* of each spatial cell, as used for density calculations within SPM.

Models can be implemented as a grid based on either squares or hexagons, but not both. This choice effects the location of neighbours (for adjacent movements) and the distance between cells (for preference based movements). Distance between cells is determined as the euclidean distance between cell centres, modified by an arbitrary scalar.

Hence, the definition of the spatial structure includes;

- The type of spatial grid and its dimensions, n_{rows} and m_{cols}
- The label of a numeric layer to be used as the base layer (defining the locations where the population can be present as well as the area of each cell)
- the length (distance) of a side of the grid (either a square or hexagon) to be used as the scalar for distance calculations

4.2. Population structure

The population structure in SPM is represented by a matrix containing an arbitrary number of user defined categories (rows), and an arbitrary age range (columns). Hence, each spatial cell has a population state described as $n_{categories} \times n_{ages}$ rectangular matrix with categories $k = 1 \dots n_{categories}$ and ages $l = age_{min} \dots age_{max}$.

The names and number of categories are user defined, but there just be at least one category in any model. The ages are defined as a sequence from age_{min} to age_{max} , and the last age may optionally be a plus group.




Figure 4.1: An illustration of the *square* spatial structure




Figure 4.2: An illustration of the *hexagon* spatial structure

Hence, the definition of the population structure includes;

- The number and labels of the categories, $k_{categories}$
- The minimum and maximum ages that define the ages of the model, l_{ages}
- If the last age is a plus group

4.3. Layers

Layers form a key underlying concept in SPM. They comprise of a grid of known values, with a value for every spatial cell in the model. Layers are used by processes, observations, and outputs commands to supply spatially explicit covariates and any categorical groupings required.

Every model must define at least one layer, the base later L_B . A layer is defined as a $n_{rows} \times n_{cols}$ grid of values (with one exception —the distance layer, see below), where the value for each cell represents a known quantity. For example layers may represent classifications, physical attributes, or some other assumed quantity. Typically they are provided by the user as a matrix of values, although abundance and distance layers can be calculated by SPM as and when required.

Within SPM, layers are used in three contexts:

1. The base layer: The base layer L_B is a special layer (there must be exactly one base layer defined within the model) that defines the locations where the population can and cannot potentially be present (e.g., locations associated with the sea and not land in a marine model). Here, we define that a cell may potentially have part of the population present if every element $L_B(i, j) \geq 0$. Further, positive values of the base layer L_B represent the *area* represented by that spatial cell.
2. Covariate layers: A model may have many covariate layers, and these are used as covariates of some population or movement process (e.g., the sea floor depth may be a covariate of some movement process). The values in layers used as covariates must be continuous (i.e., numeric) variables. Covariate layers must have values ≥ 0 .
3. Classification layer. A model may have many classification layers, and these are used as a classification or grouping variable for aggregating data over individual spatial cells (i, j) , e.g., statistical areas or management areas. Such layers are typically used to aggregate the population within cells into groups so-as to allow comparison with observations. The values in layers used as classification layers must be categorical.

Typically, layers are supplied by the user and are assumed known and constant. SPM defines the following types of layer;

1. Numeric layer: A model may have many numeric layers, and these can be used as covariates of a population or movement process (e.g., depth may be a covariate of some movement process), and/or locations of event mortality. Numeric layers can contain only continuous (numeric) variables. Values for a numeric layer must be supplied for each cell by the user.
2. Categorical layer: A model may have many categorical layers, and these are used as a classification or grouping variable for aggregating data over individual cells, e.g., management areas. Such layers are typically used to aggregate the population within cells into groups for comparing with observations. The values in layers used as categorical layers can contain any characters (except white space), and are interpreted as categorical values. Values for a categorical layer must be supplied for each cell by the user.
3. Distance layer: A distance layer is one that defines the distance between any two cells. By default, SPM calculates the values of the distance layer as the Euclidean distance (where the

grid type is square). Here, the distance between cell a and cell b can be defined as,

$$d(a, b) = \lambda \sqrt{(x_a - x_b)^2 + (y_a - y_b)^2} \quad (4.1)$$

where x and y represent the x - and y -coordinates of a and b respectively, and λ is an arbitrary scaler representing the length of one side of the square. Unlike other types of layers, distance layers are not a $n_{rows} \times n_{cols}$ grid of values, but rather a matrix of dimension $(n_{rows} \times n_{cols}) \times (n_{rows} \times n_{cols})$ where the distance between each cell and every other cell is evaluated. Note that under this definition, the distance between any cell and itself is 0.

4. Abundance layer: The abundance layer is the sum of the number of individuals within cell a in categories k and with selectivity S_l at age l .

$$N(a) = \sum_k \sum_l S_l \text{ element}(i, j, k, l) \quad (4.2)$$

SPM calculates the values of the layer when running the model at the point in time where the value is required.

5. Biomass layer: The biomass layer is the sum of the biomass of individuals within cell a in categories k , with selectivity S_l at age l , and mean weight w_{kl}

$$N(a) = \sum_k \sum_l w_{k,l} S_l \text{ element}(i, j, k, l) \quad (4.3)$$

SPM calculates the values of the layer when running the model at the point in time where the value is required.

6. Abundance-density layer: The abundance density layer is the density of the number of individuals within cell a with area A_a in categories k , with selectivity S_l at age l ,

$$N(a) = \frac{1}{A_a} \sum_k \sum_l S_l \text{ element}(i, j, k, l) \quad (4.4)$$

SPM calculates the values of the layer when running the model at the point in time where the value is required.

7. Biomass-density layer: The biomass-density layer is the density of the biomass of individuals within cell a with area A_a in categories k , with selectivity S_l at age l , and mean weight w_{kl} ,

$$N(a) = \frac{1}{A_a} \sum_k \sum_l w_{k,l} S_l \text{ element}(i, j, k, l) \quad (4.5)$$

SPM calculates the values of the layer when running the model at the point in time where the value is required.

8. Meta-layer: In addition to the above types of layer, SPM defines a special type of layer known as a *meta-layer*. The meta-layer allows individual layers (of the same type) to be indexed by year, and applied as a single layer within the model. For example, assume that we had a model where we wished to use Sea Surface Temperature (SST) as a layer, perhaps to control some movement process. The SST values for each year of the model would be defined as individual numeric layers, each with a unique label. We could then define a meta-layer that indexed the individual annual SST layers by year, and use the meta-layer as the control layer in the movement process.

However, there are exceptions to this rule —layers of type biomass, quantity, and distance are calculated automatically by SPM as required. For example, for the distance layer in a square grid, the distance between cell a and cell b is defined as proportional to $\sqrt{(x_a - x_b)^2 + (y_a - y_b)^2}$, where x and y represent the x- and y-coordinates of a and b respectively.

For the abundance layer, the abundance or biomass of a cell is simply a count of the number (or biomass) of individuals in the cell a within categories K , with selectivity S , e.g., $N(a) = \sum_k \sum_i \text{element}(i, j, k, l)$.

Note that SPM does not ‘edit’ or otherwise change layers, including adding or otherwise combining layers that are supplied in the input parameter files — except for a single case for numeric layers. In that instance, the numeric layer supplied can optionally be standardized prior to use, i.e., $L'(a) = L(a) / \max(L)$ so that $L'(a) < 1$.

4.4. Time sequence

The time sequence of the model is defined in three parts;

- Initialisation
- Run years
- Projection years

4.4.1. Model initialisation

SPM initialises the initial equilibrium state as an iterative process, because a general solution that initialises complex structured movement models can be difficult to implement using analytic techniques. However, initialising via iteration for a long-lived species with complex movements can also be slow to run. In SPM, we allow for user-defined multi-phased initialisation using iteration to allow the user to optimize models for speed. Each phase of the initialisation can involve any number of population and/or movement processes.

The initialisation part can consist of one or more phases, with each phase occurring for at least one year. Within each phase, the processes defined for that phase are carried out, and use as the starting point for the following phase, or if it is the last phase, then the years that the model is run over. The first phase is always initialised with each element (i.e., each age and category within each spatial cell) seeded with a zero. Note that this means that recruitment processes where the numbers of recruits is based on a stock recruitment or density dependant relationship will likely fail.

Hence, you need to define;

- The initialisation phases
- The number of years in each phase and the processes to apply in each

4.4.2. Model years

Following initialisation, the model then runs over a number of user-defined years. For this part of the model, the annual cycle can be broken into separate time steps, and observations can be associated with the state of the model at the end of any time step, i.e., likelihoods for particular observations are evaluated, if required, at the end of each time step.

Processes are carried out in the order specified within each time step, and can be the same or different to processes in other initialisation phases of the model. The run years define the years over which

the model is to run and the annual cycle within each year. The model runs from the start of year `initial` and runs to the end of year `current`. The projection part then extends the run time up to the end of year `final`.

- The time steps and the processes applied in each
- The initial year (i.e., the model start year)
- The current year (i.e., the model end year)
- The final year (i.e., the model projection end year)

4.5. Processes

Processes produce changes in the model partition, by adding, removing or moving individuals between spatial cells (movement processes), and ages or categories (population processes). These include processes such as recruitment, mortality, ageing, and movements.

An SPM model can be parametrised by both population processes (for example, ageing, recruitment, and mortality), and movement processes. Population processes are those processes which modify, move or otherwise change the numbers of individuals within a spatial cell, i.e., they do not affect the spatial location of a cohort. Movement processes, on the other hand, move, shift or otherwise modify cohorts between spatial cells, but do not affect the age or category of the numbers in each cohort.

4.6. Population processes

Population processes are those processes that change the population state of individuals, but retain their location.

4.6.1. Recruitment

Recruitment processes are defined as process that introduces new individuals into the model. SPM implements two types of recruitment process, constant recruitment and Beverton-Holt recruitment (Beverton and Holt, 1957).

In both of the recruitment process, a number of individuals are added to the partition at the age and categories specified. If more than one category is defined, then the proportions of individuals added across categories are user-defined. For example, if recruiting to categories labelled male and female, then you might set the proportions as 0.5 and 0.5 respectively to denote that half of the recruits recruit to the male category and the remaining half to the female category.

For each cell where $\text{cell}(i, j)$ is a member of some layer L_R , the number of fish added in year y is

$$\text{element}(i, j, k, l) \leftarrow \text{element}(i, j, k, l) + p_k(R_y/n) \quad (4.6)$$

where age is the age defined as the recruitment age, p_k is the proportion recruitment to category k defined to have recruitment, and n is the number of spatial locations where recruitment occurs.

In the constant recruitment process, R_y , the number of recruits in year y is simply the product of the average recruitment R_0 and the annual year class strength multiplier, YCS , i.e.,

$$R_y = R_0 \times YCS_{y-\text{offset}} \quad (4.7)$$

where *offset* is the number of years offset to link the year class with the year of spawning.

In the Beverton-Holt recruitment process, R_y , the number of recruits in year y is the product of the average recruitment R_0 , the annual year class strength multiplier, YCS , and the stock-recruit relationship i.e.,

$$R_y = R_0 \times YCS_{y-offset} \times SR(SSB_{y-offset}) \quad (4.8)$$

where *offset* is the number of years offset to link the year class with the year of spawning, and SR is the Beverton-Holt stock-recruit relationship, parametrised by the steepness, h ,

$$SR(SSB) = \frac{SSB}{B_0} / \left(1 - \frac{5h-1}{4h} \left(1 - \frac{SSB}{B_0} \right) \right) \quad (4.9)$$

Note that the Beverton-Holt recruitment process requires a value for SSB to resolve the stock-recruitment relationship. Here, a derived quantity (see Section 4.7) must be defined that provides the SSB for the recruitment process.

4.6.2. Ageing

The ageing process simply moves all individuals in the named categories to the next age class. The ageing process is defined as,

$$\text{element}(i, j, k, l) \leftarrow \text{element}(i, j, k, l-1) \quad (4.10)$$

except that in the case of the plus group (if defined),

$$\text{element}(i, j, k, age_{max}) \leftarrow \text{element}(i, j, k, age_{max}) + \text{element}(i, j, k, age_{max}-1). \quad (4.11)$$

4.6.3. Mortality

Four types of mortality processes are permissible in SPM, constant, annual-rate, event, or biomass-event. These processes remove individuals from the partition, either as a rate (for constant or annual-rate), or as a total number (abundance) or biomass of individuals (for event or biomass-event). SPM does not implement the Baranov catch equation or any other process where both natural and event mortality are concurrently applied. To approximate concurrent natural and event mortality, the population processes must be defined to remove some natural mortality (e.g., as a constant or annual-rate), then some event mortality in sequence. It is up to the user to specify how this happens.

Mortalities as rates can depend on a layer. Here only one method of dependence is implemented, the multiplicative method. The multiplicative natural mortality method defines that the value of instantaneous mortality applied to the population state within each cell is the product of the layer value, a selectivity-at-age, and the mortality rate.

For example, let the mortality rate applied to the population at cell a in category k and age l be denoted $M(a, k, l)$, and given a value from a layer L_a at a , a constant mortality rate M , and a selectivity-at-age S_l at age l for some user-defined categories k then,

$$M(a, k, l) = ML_a S_l \quad (4.12)$$

And the resulting number of individuals remaining in cell a in category k at age l from applying the constant mortality process is,

$$n'(a, k, l) = n(a, k, l) \exp(-M(a, k, l)) \quad (4.13)$$

Mortality for the annual rate is similar, except that the rate applied in each year is defined as a separate value.

The event mortality types act in a similar manner, except that it removes a specified abundance (number of individuals) or biomass from the partition, rather than applying a mortality rate. However, the maximum abundance or biomass to remove is constrained by a maximum exploitation rate.

The event mortality types must be defined using a layer. Here, the abundance or biomass to remove from a the population for each cell a is the value of the layer at a (denoted F_a) —except where there are too few individuals for the event mortality to be taken (as defined by the maximum exploitation rate). In this scenario, SPM removes as many individuals or as much biomass as it can while not exceeding the maximum exploitation rate.

For example, the event mortality applied to user-defined categories k , with the numbers removed at age l determined by a selectivity-at-age S_l is applied as follows:

First, calculate the vulnerable abundance for each category k in $1 \dots K$ for ages $l = 1 \dots L$ that are subject to event mortality,

$$V(k, l) = S(l)N(k, l) \quad (4.14)$$

And hence define the total vulnerable abundance V_{Total} as,

$$V_{Total} = \sum_K \sum_L V(k, l) \quad (4.15)$$

Hence the exploitation rate to apply is

$$U = \begin{cases} C/V_{total}, & \text{if } C/V_{total} \leq U_{max} \\ U_{max}, & \text{otherwise} \end{cases} \quad (4.16)$$

And the number removed R from each age l in category k is,

$$R(k, l) = UV(k, l) \quad (4.17)$$

Similarly, the biomass-event mortality type is applied as ... **to be added**.

4.6.4. Category transitions

Category transition processes move individuals between categories. SPM implements two types, the total number and a rate.

The transition type moves a number n between a source and sink category. The transition process with selectivity S for source category a and sink category b is,

$$\begin{aligned} \text{element}(i, j, a, l) &\leftarrow \text{element}(i, j, a, l) - \frac{nS_l}{\sum_l S_l} \times \text{element}(i, j, a, l) \\ \text{element}(i, j, b, l) &\leftarrow \text{element}(i, j, b, l) + \frac{nS_l}{\sum_l S_l} \times \text{element}(i, j, a, l) \end{aligned} \quad (4.18)$$

The transition rate type moves a proportion p between a source and sink category. The transition rate process with selectivity S for source category a and sink category b is,

$$\begin{aligned} \text{element}(i, j, a, l) &\leftarrow \text{element}(i, j, a, l) - pS_l \times \text{element}(i, j, a, l) \\ \text{element}(i, j, b, l) &\leftarrow \text{element}(i, j, b, l) + pS_l \times \text{element}(i, j, a, l) \end{aligned} \quad (4.19)$$

4.6.5. Movement processes

Movement processes are those processes that move individuals between cells but retain the their population state, and are defined such that,

$$\text{element}(i, j, k, l) \leftarrow \text{element}(i, j, k, l) + p \times \text{element}(i', j', k, l) \quad (4.20)$$

i.e., each element in $\text{cell}(i, j)$ is updated as the sum of itself and some proportion p of a neighbouring element in $\text{cell}(i', j')$. To conserve abundance we also update $\text{element}(i', j', k, l)$ as,

$$\text{element}(i', j', k, l) \leftarrow \text{element}(i', j', k, l) - p \times \text{element}(i', j', k, l) \quad (4.21)$$

SPM assumes that each movement process occurs simultaneously over all cells (synchronous updating), i.e., all cell updates from each individual movement process are first evaluated for all cells, and then applied to all cells affected.

SPM implements three types of movement;

1. A migration movement rate of cohorts between any two locations, and is roughly analogous to movements between areas as implemented in other population models, such as CASAL (Bull et al., 2008).
2. An adjacent cell movements, parametrised by some function of an underlying layer—equivalent to, for example, movement processes implemented in Fish Heaven (Ball and Constable, 2000, Ball and Williamson, 2003).
3. Movement parametrised as a probability density function. Here, the key underlying idea is that the spatial distribution of cohorts at any point in time and at any location can be represented as a density function based on attributes of that location, local abundance, and/or distance from their previous location (Bentley et al., 2004a,b).

The migration process moves individuals from one location to another. A migration can involve one or more categories and movement at age is defined as some proportion multiplies by a selectivity. Migrations are limited in scope to move individuals from one cell to another, and are available to allow compatibility with limited space models such as CASAL Bull et al. (2008).

The adjacent cell movement simply moves a proportion of individuals to neighbouring cells. It can be applied to a limited range of spatial locations by associating it with a layer.

Preference movements allows movement from any $\text{cell}(a) \rightarrow \text{cell}(b)$, for $\forall a, b \in L_B$ and is implemented as a function of the product of up to n independent *preference functions*. We define the probability of moving from any cell a to any cell b , for all $a, b \in L_B$, as a function of the relative preference for that cell. Here, we use the term *preference function* (Bentley et al., 2004a,b) to describe the movement probability distributions. We assume that the population and spatial extent are defined, and that there is a preference function that is a function of some (typically estimable) parameters and a spatially explicit set of known attributes. The preference function movement process allows the number of parameters describing movement to be reduced, and results in a movement process that is some function of some underlying property of each location. For example, if we assume that movement between areas was a function of the Euclidean distance between areas, we could model movement between any two areas as a linear decay or exponential decay function (Bentley et al., 2004a). Alternately, if distribution and density were correlated with bathymetric depth for a marine organism, we might model the movement and distribution as a function of depth.

The total preference function

Movement in SPM can be defined as a probability distribution based on an underlying preference function. Here, we define the preference for a cell x as the preference function $f_x(\theta_x, P(x))$, where θ_x are the parameters for f_x . So, given a set of n attributes for cell x , we can define a preference function for each, and hence we define the aggregated or total preference function for any cell x as the weighted product of individual preference functions,

$$P_x = f_1(\theta_1, P_1(x))^{\alpha_1} + f_2(\theta_2, P_2(x))^{\alpha_2} + f_3(\theta_3, P_3(x))^{\alpha_3} + \dots + f_n(\theta_n, P_n(x))^{\alpha_n} \quad (4.22)$$

where α_i is an arbitrary weighting factor for attribute i .

Then we define the probability of moving from cell a to any cell b (where b is defined as the set of all possible cells, including a),

$$p(a \rightarrow b) = \frac{P_a}{\sum_{i \in \forall b} P_i} \quad (4.23)$$

Note that there are three forms of preference function,

1. Those that are a function of some underlying attribute of a cell, as defined by some arbitrary layer L
2. Those that are a function of the abundance (perhaps with a selectivity and for a subset of all categories) of each cell
3. Those that are a function of the distance between the sink and the source cells.

Preference functions of the first type are determined only by the parameters of the preference function and some underlying, fixed, attribute. Preference functions of the others are dynamic, i.e. they depend on the relative locations of the cells or on the density of a cell at a particular point in time.

Preference functions

Preference functions in SPM include Constant, Normal, DoubleNormal, Logistic, InverseLogistic, ExponentialDecay, and Threshold. These are defined as,

1. The Constant preference function has dependent variable x and has no parameters, and is defined as,

$$f(x) = x, \text{ where } 0 \leq x \leq 1 \quad (4.24)$$

2. The Normal preference function has dependent variable x and parameters $\theta = (\mu, \sigma)$, and is defined as,

$$f(x|\mu, \sigma) = 2^{-[(x-\mu)/\sigma]^2} \quad (4.25)$$

3. The DoubleNormal preference function has dependent variable x and parameters $\theta = (\mu, \sigma_L, \sigma_R)$, and is defined as,

$$f(x|\mu, \sigma_L, \sigma_R) = \begin{cases} 2^{-[(x-\mu)/\sigma_L]^2}, & \text{if } x \leq \mu \\ 2^{-[(x-\mu)/\sigma_R]^2}, & \text{if } x \geq \mu \end{cases} \quad (4.26)$$

4. The `Logistic` preference function has dependent variable x and parameters $\theta = (a_{50}, a_{t095})$, and is defined as,

$$f(x|a_{50}, a_{t095}) = 1/[1 + 19^{(a_{50}-x)/a_{t095}}] \quad (4.27)$$

5. The `InverseLogistic` preference function has dependent variable x and parameters $\theta = (a_{50}, a_{t095})$, and is defined as,

$$f(x|a_{50}, a_{t095}) = 1 - 1/[1 + 19^{(a_{50}-x)/a_{t095}}] \quad (4.28)$$

6. The `ExponentialDecay` preference function has dependent variable x and parameters $\theta = (\lambda)$, and is defined as,

$$f(x|\lambda) = \exp(-\lambda x), \text{ where } x \geq 0 \text{ and } 0 \text{ otherwise} \quad (4.29)$$

7. The `Threshold` preference function has dependent variable x and parameters $\theta = (N, \lambda)$, and is defined as,

$$f(x|N, \lambda) = \begin{cases} 1, & \text{if } 0 \leq x \leq N \\ 1/\left(\frac{x}{N}\right)^\lambda, & \text{if } x \geq N \\ 0, & \text{otherwise} \end{cases} \quad (4.30)$$

4.7. Derived quantities

Derived quantities are values, calculated by `SPM` as required, that have a single value for each year of the model. Derived quantities can be calculated as either an abundances or as a biomass. Derived quantities are simply the count or sum of cells within some categories, after applying a selectivity, within cells defined by a layer.

4.8. Size-at-age

This is used to determine length frequencies and hence biomass (using a size-weight relationship) of individuals at age/category. There are two alternative growth curves in `SPM`,

von Bertalanffy where size at age is defined as,

$$\bar{s}(\text{age}) = L_\infty (1 - \exp(-k(\text{age} - t_0))) \quad (4.31)$$

Schnute where size at age is defined as,

$$\bar{s}(\text{age}) = \begin{cases} \left[y_1^b + (y_2^b - y_1^b) \frac{1 - \exp(-a(\text{age} - \tau_1))}{1 - \exp(-a(\tau_2 - \tau_1))} \right]^{1/b}, & \text{if } a \neq 0 \text{ and } b \neq 0 \\ y_1 \exp \left[\ln(y_2/y_1) \frac{1 - \exp(-a(\text{age} - \tau_1))}{1 - \exp(-a(\tau_2 - \tau_1))} \right], & \text{if } a \neq 0 \text{ and } b = 0 \\ \left[y_1^b + (y_2^b - y_1^b) \frac{\text{age} - \tau_1}{\tau_2 - \tau_1} \right]^{1/b}, & \text{if } a = 0 \text{ and } b \neq 0 \\ y_1 \exp \left[\ln(y_2/y_1) \frac{\text{age} - \tau_1}{\tau_2 - \tau_1} \right], & \text{if } a = 0 \text{ and } b = 0 \end{cases} \quad (4.32)$$

The von Bertalanffy curve is parameterised by L_∞ , k , and t_0 ; the Schnute curve (Schnute, 1981) by y_1 and y_2 , which are the mean sizes at reference ages τ_1 and τ_2 , and a and b (when $b = 1$, this reduces to the von Bertalanffy with $k = a$).

The model can incorporate changes in size-at-age during the year (i.e., growth between fish birthdays) by specifying the growth proportions for each time step of the annual cycle.

4.9. Mean weight

The size-weight parameters a and b is calculated as either,

- None: A relationship where the weight of each individual is exactly 1
- Basic: The more usual size-weight relationship, where

$$\text{mean weight} = a(\text{mean size-at-age})^b \quad (4.33)$$

Be careful about the scale of a , —this is easily specified incorrectly. If you provide your catch in tonnes, and your growth curve in centimetres, then a should be on the right scale to convert a length in centimetres to a weight in tonnes. Note that there is an optional command `@Print.VerifySizeWeightRelationship` that can be used to help check that the units specified are plausible.

If you specify a distribution for the size-at-age relationship, then the mean weight at age is calculated over that distribution, using the following formula, which is exact for lognormal distributions, and a good approximation for a normal distribution (if the c.v. is not large),

$$\text{mean weight} = a \times (\text{mean size at age})^b \times \left(1 + \text{cv}^2\right)^{\frac{b(b-1)}{2}} \quad (4.34)$$

where cv is the c.v. of sizes-at-age.

4.10. Selectivities

A selectivity is a function with a different value for each age class (i.e., for each column of the partition). Selectivities are used frequently throughout the SPM population section: for selectivity curves. Selectivities have a number of different parametric forms (types) in SPM and you can use any of these for any selectivity parameter.

A selectivity is always defined to apply just to one category of the population (i.e., row of the partition). To apply the same selectivity to more than one category, the you need to specify the categories that it applied to.

Note that selectivities are indexed by age, with indices from `min_age` to `max_age`. For example, you might have an age-based selectivity that was logistic with 50% mark at age 5 and 95% mark at age 7. This would be defined by the `Type=Logistic` with parameters $a_{50} = 5$ and $a_{0.95} = (7 - 5) = 2$. Then the value of the selectivity at age $x = 3$ is therefore 0.95.

Note that the function values for some choices of parameters for some selectivities can result in a computer numeric overflow error (i.e., the number calculated from parameter values is either too large or too small to be represented in computer memory). SPM implements range checks on some parameters to test for a possible numeric overflow error before attempting to calculate function values. For example, the logistic selectivity is implemented such that if $(a_{50} - x)/a_{0.95} > 5$ then the value of the selectivity at $x = 0$, i.e., for $a_{50} = 5$, $a_{0.95} = 0.1$, then the value of the selectivity

at $x = 1$, without range checking would be 7.1×10^{-52} . With range checking, that value is 0 (as $(a50x)/at095 = 40 > 5$).

The available selectivities are;

- Constant
- Knife-edge
- All values
- All values bounded
- Increasing
- Logistic
- Logistic-producing
- Double-normal
- Double-exponential

4.10.1. Selectivity descriptions

The available selectivities are described below.

Constant

$$f(x) = C \quad (4.35)$$

The constant selectivity has the estimable parameter C.

KnifeEdge

$$f(x) = \begin{cases} 0, & \text{if } x < E \\ 1, & \text{if } x \geq E \end{cases} \quad (4.36)$$

The knife-edge ogive has the non-estimable parameter E.

AllValues

$$f(x) = V_x \quad (4.37)$$

The all-values selectivity has estimable parameters $V_{low}, V_{low+1} \dots V_{high}$. Here, you need to provide the selectivity value for each age class.

AllValuesBounded

$$f(x) = \begin{cases} 0, & \text{if } x < L \\ V_x, & \text{if } L \leq x \leq H \\ V_H, & \text{if } x > H \end{cases} \quad (4.38)$$

The all-values-bounded selectivity has non-estimable parameters L and H. The estimable parameters are $V_L, V_{L+1} \dots V_H$. Here, you need to provide an selectivity value for each age class from $L \dots H$.

Increasing

$$f(x) = \begin{cases} 0, & \text{if } x < L \\ f(x-1) + \pi_x(C - f(x-1)), & \text{if } L \leq x \leq H \\ f(C), & \text{if } x \geq H \end{cases} \quad (4.39)$$

The increasing ogive has non-estimable parameters L and H . The estimable parameters are $\pi_L, \pi_{L+1} \dots \pi_H$ (but if these are estimated, they should always be constrained to be between 0 and 1). Note that the increasing ogive is similar to the all-values-bounded ogive, but is constrained to be non-decreasing.

Logistic

$$f(x) = 1 / [1 + 19^{(a_{50}-x)/a_{to95}}] \quad (4.40)$$

The logistic selectivity has estimable parameters a_{50} and a_{to95} . The logistic selectivity takes values 0.5 at $x = a_{50}$ and 0.95 at $x = a_{50} + a_{to95}$.

LogisticProducing

$$f(x) = \begin{cases} 0, & \text{if } x < L \\ \lambda(L), & \text{if } x = L \\ (\lambda(x) - \lambda(x-1)) / (1 - \lambda(x-1)), & \text{if } L < x < H \\ 1, & \text{if } x \geq H \end{cases} \quad (4.41)$$

The logistic-producing selectivity has the non-estimable parameters L and H , and has estimable parameters a_{50} and a_{to95} . For category transitions, $f(x)$ represents the proportion moving, not the proportion that have moved. This selectivity was designed for use in an age-based model to model maturity. In such a model, a logistic-producing maturation selectivity will (in the absence of other influences) make the proportions mature follow a logistic curve with parameters a_{50}, a_{to95} .

DoubleNormal

$$f(x) = \begin{cases} 2^{-[(x-\mu)/\sigma_L]^2}, & \text{if } x \leq \mu \\ 2^{-[(x-\mu)/\sigma_R]^2}, & \text{if } x \geq \mu \end{cases} \quad (4.42)$$

The double-normal selectivity has estimable parameters a_1, s_L , and s_R . It has values 1 at $x = a_1$, and 0.5 at $x = a_1 - s_L$ or $x = a_1 + s_R$.

DoubleExponential

$$f(x) = \begin{cases} y_0(y_1/y_0)^{(x-x_0)/(x_1-x_0)}, & \text{if } x \leq x_0 \\ y_0(y_2/y_0)^{(x-x_0)/(x_2-x_0)}, & \text{if } x > x_0 \end{cases} \quad (4.43)$$

The double-exponential selectivity has non-estimable parameters x_1 and x_2 , and estimable parameters x_0, y_0, y_1 , and y_2 . It can be ‘U-shaped’. Bounds for x_0 must be such that $x_1 < x_0 < x_2$. The selectivity passes through the points (x_1, y_1) , (x_0, y_0) , and (x_2, y_2) . If both y_1 and y_2 are greater than y_0 the selectivity is ‘U-shaped’ with minimum at (x_0, y_0) .

5. The estimation section

5.1. Role of the estimation section

The tasks carried out by the estimation section are:

1. Get the point estimate, i.e., the maximum posterior density estimate (MPD) (see Section 6.3).
2. Calculate a posterior profile selected parameters, i.e., find, for each of a series of values of a parameter, allowing the other free parameters to vary, the minimum value of the objective function (Section 6.4).
3. Generate an MCMC sample from the posterior distribution (Section 6.5).
4. Calculate the approximate covariance matrix of the parameters as the inverse of the minimizer's approximation to the Hessian, and the corresponding correlation matrix (Section 6.3).

5.2. Specifying the free parameters

You need to tell SPM which of the estimable parameters are to be freed by using `@Estimate` commands (see Section 10). An `@Estimate` command-block looks like,

```
@estimate Process[MyRecruitment].R0
lower_bound 1000
upper_bound 100000
prior uniform
```

See Section XXX for instructions on how to generate the parameter name. You have to specify at least one free parameter. You still provide values for the free parameters as normal, these are used as the starting values for the minimiser (unless you provide alternative starting values using SPM `-i`, see Section 3.3).

All parameters are estimated within bounds. For each free parameter, you need to specify the bounds and the prior (Section XXX). Note that the bounds and prior on an selectivity refer to the selectivity free parameters, not the actual values of the selectivity.

You need to estimate all the estimable parameters of an selectivity if you estimate any, but you can fix some of them if you want by setting the lower and upper bound equal. Similarly, if you want to estimate only some elements of a vector, fix the others by setting the bounds equal.

5.3. Point estimation

Point estimation is invoked with SPM `-e`. Mathematically, it is an attempt to find a minimum of the objective function. SPM has two algorithms for solving optimisation problem. The first uses a quasi-Newton minimiser built which is a slightly modified implementation of the main algorithm of Dennis Jr. & Schnabel (Dennis Jr and Schnabel, 1996), while the second uses a genetic algorithm developed by Storn & Price (Storn and Price, 1995).

The minimiser has three kinds of (non-error) exit status:

1. Successful convergence (suggests you have found a local minimum, at least).

2. Convergence failure (you have not reached a local minimum, though you may deem yourself to be ‘close enough’ at your own risk).
3. Convergence unclear (the minimiser halted but was unable to determine if convergence occurred. You may be at a local minimum, although you should check by restarting the minimiser at the final values of the free parameters).

You can choose the maximum number of quasi-Newton iterations and objective function evaluations allotted to the minimiser. If it exceeds either limit, it exits with a convergence failure. We recommend large numbers of evaluations and iterations (at least the defaults of 300 and 1000) unless you successfully reach convergence with less. You can also specify the starting point of the minimiser using `SPM -i`.

We want to stress that this is a local optimisation algorithm trying to solve a global optimisation problem. What this means is that, even if you get a ‘successful convergence’ message, your solution may be only a local minimum, not a global one. To diagnose this problem, try doing multiple runs from different starting points and comparing the results, or (probably better) doing profiles of one or more key parameters and seeing if any of the profiled estimates is actually better than the original point estimate.

The approximate covariance matrix of the free parameters can be calculated as the inverse of the minimiser’s approximation to the Hessian, and the corresponding correlation matrix is also calculated. Be aware that

- the Hessian approximation develops over many minimiser steps, so if the minimiser has only run for a small number of iterations the covariance matrix can be a very poor approximation
- the inverse Hessian is not a good approximation to the covariance matrix of the free parameters, and may not be useful to construct, for example, confidence intervals.

Also note that if a free parameter has equal lower and upper bounds, it will have entries of ‘0’ in the covariance matrix and NaN or -1.#IND (depending on the operating system) in the correlation matrix.

5.4. Posterior profiles

If profiles are requested `SPM -p`, SPM will first calculate a point estimate. For each scalar parameter or, in the case of vectors or selectivities, the element of the parameter to be profiled, SPM will fix its value at a sequence of n evenly spaced numbers between specified bounds l and u , and calculate a point estimate at each value.

By default $n = 10$, and $(l, u) = (\text{lower bound on parameter plus } (range/(2n)), \text{upper bound on parameter less } (range/(2n)))$. Each minimisation starts at the final parameter values from the previous resulting value of the parameter being profiled. SPM will report the objective function for each parameter value and all the parameter estimates. The initial point estimate is also inserted into the profile (note that this can serve as a check that none of the other points along the profile have a better objective function value than the initial ‘minimum’).

You specify which parameters are to be profiled, and optionally n , l , and u values for each. In the case of vector or selectivity parameters, you will also need to specify the element of the vector being profiled.

You can also supply the initial point estimate using `SPM -i`, so that SPM doesn’t need to do the first minimisation. Be aware that you are supplying the point estimate, not the minimiser starting point to get to the point estimate (as in other situations where `SPM -i` is used).

If you have specified multi-phase estimation (see Section XXX), it is only used for the initial point estimate. Subsequent minimisations are done single-phase, as they should start reasonably close to the endpoint and so shouldn't need multiple phases.

If you get an implausible profile, it may be a result of not using enough iterations in the minimiser (in this case, increase @MPD.MaxIters and/or @MPD.MaxEvals and retry), or the convergence criteria may not be strong enough (try setting @MPD.GradTol to a smaller value).

5.5. Bayesian estimation

SPM can use a Monte Carlo Markov Chain to generate a sample from the posterior distribution of the free parameters `SPM -m`; and output the sampled values to a file, (optionally only every *n*th set of values).

Two major steps are best done by an external package, as SPM has no post-processing capabilities. SPM cannot produce MCMC convergence diagnostics (use a package such as BOA) or plot/summarize the posterior distributions of the output quantities (for example, using a general-purpose statistical or spreadsheet package such as S-Plus, R, or Microsoft Excel).

Bayesian methodology and MCMC are both large and complex topics, and we do not describe either properly here. See Gelman et al. (1995) and Gilks et al. (1994) for details of both Bayesian analysis and MCMC methods. In addition, see Punt & Hilborn (2001) for an introduction to quantitative fish stock assessment using Bayesian methods.

This section only briefly describes the MCMC algorithms used in SPM. See Section XXX for a better description of the sequence of SPM commands used in a full Bayesian analysis.

SPM uses a straightforward implementation of the Metropolis algorithm (Gelman et al., 1995, Gilks et al., 1994). The Metropolis algorithm attempts to draw a sample from a Bayesian posterior distribution, and calculates the posterior density π , scaled by an unknown constant. The algorithm generates a 'chain' or sequence of values. Typically the beginning of the chain is discarded and every *N*th element of the remainder is taken as the posterior sample. The chain is produced by taking an initial point x_0 and repeatedly applying the following rule, where x_i is the current point:

- Draw a candidate step s from a proposal distribution J , which should be symmetric i.e., $J(-s) = J(s)$.
- Calculate $r = \min(\pi(x_i + s)/\pi(x_i), 1)$.
- Let $x_{i+1} = x_i + s$ with probability r , or x_i with probability $1 - r$.

An initial point estimate is produced before the chain starts, which is done so as to calculate the approximate covariance matrix of the free parameters (as the inverse Hessian), and may also be used as the starting point of the chain.

The user can specify the starting point of the point estimate minimiser using `SPM -i`. Don't start it too close to the actual estimate (either by using `SPM -i`, or by changing the initial parameter values in input configuration file) as it takes a few iterations to form a reasonable approximation to the Hessian.

There are two options for the starting point of the Markov Chain:

- Start from the point estimate.
- Start from a random point near the point estimate (the point is generated from a multivariate normal distribution, centred on the point estimate, with covariance equal to the inverse Hessian

times a user-specified constant). This is done to prevent the chain from getting ‘stuck’ at the point estimate.)

- Start from a point specified by the user with `SPM -i`.

The chain moves in natural space, i.e., no transformations are applied to the free parameters. The default proposal distribution is a multivariate normal centred on the current point, with covariance matrix equal to a matrix based on the approximate covariance produced by the minimiser, times some step-size factor. The following steps define the initial covariance matrix of the proposal distribution:

- The covariance matrix is taken as the inverse of the approximate Hessian from the quasi-Newton minimiser.
- The covariance matrix is modified so as to decrease all correlations greater than `@MCMC.MaxCor` down to `@MCMC.MaxCor`, and similarly to increase all correlations less than `@MCMC.MaxCor` up to `@MCMC.MaxCor` (the `@MCMC.MaxCor` parameter defaults to 0.8). This should help to avoid getting ‘stuck’ in a lower-dimensional subspace.
- The covariance matrix is then modified either by,
 - if `@MCMC.AdjustmentMethod=Covariance`: that if the variance of the i th parameter is non-zero and less than `@MCMC.MinDiff` times the difference between the parameters’ lower and upper bound, then the variance is changed, without changing the associated correlations, to $k = \text{MinDiff}(\text{upper_bound}_i - \text{lower_bound}_i)$. This is done by setting

$$\text{Cov}(i, j)' = \sqrt{k} \text{Cov}(i, j) / \text{sd}(i)$$

for $i \neq j$, and $\text{var}(i)' = k$

- if `@MCMC.AdjustmentMethod=correlation`: that if the variance of the i th parameter is non-zero and less than `@MCMC.MinDiff` times the difference between the parameters’ lower and upper bound, then its variance is changed to $k = \text{MinDiff}(\text{upper_bound}_i - \text{lower_bound}_i)$. This differs from (i) above in that the effect of this option is that it also modifies the resulting correlations between the i th parameter and all other parameters.

This allows a free parameter to move in the MCMC even if its variance is very small according to the inverse Hessian. In both cases, the `@MCMC.MinDiff` parameter defaults to 0.0001.

- The `@MCMC.StepSize` (a scalar factor applied to the covariance matrix to improve the acceptance probability) is chosen by the user. The default is $2.4d^{-0.5}$ where d is the number of free parameters, as recommended by Gelman et al. (Gelman et al., 1995), though experience has shown that this may be too high and can lead to a low acceptance rate.

The proposal distribution can also change adaptively during the chain, using two different mechanisms. Both are offered as means of improving the convergence properties of the chain. It is important to note that any adaptive behaviour must finish before the end of the burn-in period, i.e., the proposal distribution must be finalised before the kept portion of the chain starts (`SPM` enforces this). The adaptive mechanisms are as follows:

1. You can request that the step size change adaptively at one or more sample numbers. At each adaptation, the step size is doubled if the acceptance rate since the last adaptation is more than 0.5, or halved if the acceptance rate is less than 0.2. (See Gelman et al. 1995 for justification.) The new step size is recorded in the objectives file.
2. You can request that the entire covariance matrix change adaptively at one or more sample numbers. At each adaptation, it is replaced with a matrix based on the sample covariance of an earlier

section of the chain. The theory here is that the covariance of a portion of chain could potentially be a better estimate of the covariance of the posterior distribution than the inverse Hessian.

The procedure used to choose the sample of points is as follows. First, all points on the chain so far are taken. All points in an initial user-specified period are discarded. The assumption is that the chain will have started moving during this period - if this is incorrect and the chain has still not moved by the end of this period, it is a fatal error and SPM stops. The remaining set of points must contain at least some user-specified number of transitions - if this is incorrect and the chain has not moved this often, it is again a fatal error. If this test is passed, the set of points is systematically sub-sampled down to 1000 points (it must be at least this long to start with).

The variance-covariance matrix of this sub-sample of chain is calculated. As above, correlations greater than @MCMC.MaxCor are reduced to @MCMC.MaxCor, correlations less than @MCMC.MaxCor are increased to @MCMC.MaxCor, and very small non-zero variances are increased (@MCMC.CovarianceAdjustment and @MCMC.MinDiff. The result is the new variance-covariance matrix of the proposal distribution.

The step size parameter is now on a completely different scale, and must also be reset. It is set to a user-specified value (which may or may not be the same as the initial step size). We recommend that some of the step size adaptations are set to occur after this, so that the step size can be readjusted to an appropriate value which gives good acceptance probabilities with the new matrix.

All modified versions of the covariance matrix are printed to the standard output, but only the initial covariance matrix (inverse Hessian) is saved to the objectives file. The number of covariance modifications by each iteration is recorded as a column on the objectives file.

The probability of acceptance for each jump is 0 if it would move out of the bounds, or 1 if it improves the posterior, or (new posterior/old posterior) otherwise.

You can specify how often the position of the chain is recorded using the keep parameter. For example, with keep 10, only every 10th sample is written to file.

You have the option to specify that some of the free parameters are fixed during MCMC. If the chain starts at the point estimate or at a random location, these fixed parameters are set to their values at the point estimate. If you specify the start of the chain using SPM -i, these fixed parameters are set to the values in the file.

A multivariate t distribution is available as an alternative to the multivariate normal proposal distribution. If you request multivariate t proposals, you may want to change the degrees of freedom from the default of 4. As the degrees of freedom decrease, the t distribution becomes more heavy tailed. This may lead to better convergence properties.

Given a posterior (sub)sample, SPM can calculate a list of output quantities for each sample point (see Section XXX). These quantities can be dumped into a file (using SPM -v) and read into an external software package where the posterior distributions can be plotted and/or summarised.

The posterior sample can also be used for projections (Section XXX) or simulations (Section XXX), allowing the parameter uncertainty, as expressed in the posterior distribution, can be included into the risk or other output estimates.

6. The observation section

The objective function is based on the goodness-of-fit of the model to your observations. In the current release of SPM, most observations are different kinds of time series, i.e., data which were recorded for one or more years, in the same format each year. Examples of time series data types include relative abundance indices, commercial catch length frequencies, survey numbers-at-age, etc.,

Generally, time series must relate to a specified time step and a specified area, and one or more years in which they were recorded.

6.1. Types of observations

Five types

Observations of a mortality event proportions of individuals by age class

Observations of proportions of individuals by age class

Observations of proportions of individuals between categories within each age class

Relative and absolute abundance observations

Relative and absolute biomass observations

6.1.1. Event mortality proportions-at-age

6.1.2. Proportions-at-age

6.1.3. Proportions-by-age

6.1.4. Abundance

6.2. The objective function

6.2.1. Likelihoods

6.2.2. The objective function

In Bayesian estimation, the objective function is a negative log-posterior,

$$Objective(p) = -\sum_i \log [L(\mathbf{p}|O_i)] - \log [\pi(\mathbf{p})]$$

where π is the joint prior density of the parameters p .

Under either estimation method, penalties can be added to the objective function (see Section XXX). You will usually want to use penalties to ensure that the exploitation rate constraints on your fisheries are not breached (otherwise there is nothing to prevent the model from having abundances so low that the recorded catches could not have been taken). A penalty to force the YCS to average to 1 (i.e., to have mean 1) may also be necessary.

7. The output section

8. General commands and subcommands

The input configuration file comprises of four parts (preamble, population, estimation, and output). All of these, except the preamble, are compulsory. SPM will error out if one of the compulsory sections is missing. The preamble occurs at the start of the input configuration file, before the three sections defined below. SPM ignores any text within this section, and hence the preamble can be used to record comments or descriptions of the input configuration file.

The population section is defined in the input configuration file by the text [population], the estimation section by the text [estimation], and the output section by the text [output]. These must be the only text on those lines.

Otherwise, the only command that can occur in any of the [population], [estimation], or [output] sections is the command @include. It is defined as,

@include *file_name* Include an external file

file_name The name of the external file to include

Type: string

Default: None

Value: A valid external file

Condition: The file name must be enclosed in double quotes

Example: @include "my_file.txt"

Note: @include does not denote the end of the previous command block as is the case for all other commands

9. Population command and subcommand syntax

9.1. Model structure

@model Define the spatial structure, population structure, annual cycle, and model years

cell_length The length (distance) of one side of a cell

Type: Constant

Default: 1

Value: A positive real number

nrows The number of rows n_{rows} in the spatial structure

Type: Integer

Default: None

Value: A positive integer, $n_{rows} > 0$

ncols The number of columns n_{cols} in the spatial structure

Type: Integer

Default: None

Value: A positive integer, $n_{cols} > 0$

layer The label for the base layer

Type: String

Default: None

Value: Must be a label of a `numeric` layer defined by `@layer`

categories Labels of the categories (rows) of the population component of the partition

Type: Vector of strings, of length $1 \dots n_{categories}$

Default: None

Value: Names of categories must be unique

size_at_age Define the label of the associated size-at-age relationship for each category

Type: Vector of strings, of length $1 \dots n_{categories}$

Default: None

Value: Label names must be unique

min_age Minimum age of the population

Type: Integer

Default: None

Value: A non-negative integer, $Age_{min} \geq 0$ and $Age_{min} \leq Age_{max}$

max_age Maximum age of the population

Type: Integer

Default: None

Value: A non-negative integer, $Age_{max} \geq 0$ and $Age_{min} \leq Age_{max}$

age_plus_group Define the largest age as a plus group

Type: Switch
Default: True
Value: Defines the largest age as a plus group

`initialisation_phases` Define the labels of the phases of the initialisation

Type: Vector of strings, of length of the number of initialisation phases
Default: None
Value: A valid label defined by `@initialisation_phase`

`initial_year` Define the first year of the model, immediately following initialisation

Type: Integer
Default: None
Value: Defines the first year of the model, ≥ 1 , e.g. 1990

`current_year` Define the current year of the model

Type: Integer
Default: None
Value: Defines the current year of the model, i.e., the model is run from `@model..first_year` to `@model.current_year`

`final_year` Define the final year of the model in projections

Type: Integer
Default: None
Value: Defines the final year of the model for use in projections, i.e., the model is run from `@model..first_year` to `@model.current_year`, then projected to `@model..final_year`

`time_steps` Define the `@time_step` labels (in order that they are applied) to form the annual cycle

Type: String vector
Default: None
Value: Defines the labels of the time steps that are run in each year

`@initialisation_phase` *label* Define the processes and years of the initialisation phase with label

`years` Define the number of years to run

Type: Integer
Default: None
Value: A non-negative integer

`processes` Define the processes (in order of occurrence) to run in each year of the initialisation

Type: String vector
Default: None
Value: A valid process label, from one of `@process`

`@time_step` *label* Define a time step with label

`processes` Define the process labels, in the order that they are applied, for the time step

Type: String vector

Default: None

Value: Defines the labels of the processes for that time step

9.2. Processes

The population processes available are,

- Constant recruitment process
- Beverton-Holt stock-recruit relationship recruitment process
- Ageing process
- Constant mortality rate process
- Annually varying mortality rate process
- Mortality event (as a number) process
- Mortality event (as a biomass) process
- Category transition process
- Category shift process

The movement processes available are,

- Migration movement
- Adjacent cell movement
- Preference movement

Each type of process requires a set of subcommands and arguments specific to that process.

@process *label* Define a process with label

type Define the type of process

Type: String

Default: None

Value: A valid type of process

9.2.1. @process[label].type=constant_recruitment

r0 Define the total amount of recruitment at equilibrium abundance levels

Type: Estimable

Default: None

Value: Total amount (in numbers) of recruitment applied across all categories at equilibrium abundances

categories Define the categories into which recruitment occurs

Type: String vector

Default: None

Value: Valid categories from @model.categories

proportions Define the proportion of recruitment that occurs into each category

Type: Estimable vector of length `@constant_recruitment[label].categories`

Default: None

Value: Proportion of the annual recruitment that is applied to each category

ages Define the ages within each category that receive recruitment

Type: Integer vector

Default: None

Value: The age classes that receive recruitment

layer Name of the layer used to determine where recruitment occurs

Type: String

Default: None

Value: A valid layer as defined by `@layer`. If a numeric layer, then recruitment is in proportion to the layer values. If a logical layer, then recruitment occurs in cells where the layer value is `TRUE`

9.2.2. `@process[label].type=BH_recruitment`

r0 Define the total amount of recruitment at equilibrium abundance levels

Type: Estimable

Default: None

Value: Total amount (in numbers) of recruitment applied across all categories at equilibrium abundances

categories Define the categories into which recruitment occurs

Type: String vector

Default: None

Value: Valid categories from `@model.categories`

proportions Define the proportion of recruitment that occurs into each category

Type: Estimable vector of length `@process[label].categories`

Default: None

Value: Proportion of the annual recruitment that is applied to each category

ages Define the age within each category that receive recruitment

Type: Integer vector

Default: None

Value: The age classes that receive recruitment

steepness Define the Beverton-Holt stock recruitment relationship steepness (h) parameter

Type: Estimable

Default: None

Value: Steepness value between 0.2 and 1.0

sigma_r Define the recruitment variability σ_R in the stock-recruitment relationship for

- projections
Type: Estimable
Default: None
- rho Define the autocorrelation ρ in the recruitment variability in the stock-recruitment relationship for projections
Type: Estimable
Default: None
- SSB Define the label of the @derived_parameter that defines the SSB
Type: String
Default: None
Value: Must be a valid @derived_parameter label
- YCS_values YCS values
Type: Estimable vector
Default: None
Value: Must be vector
Note: Special values can be used here, i.e., mean, all
- YCS_years Years for year class strength values
Type: Integer vector
Default: None
Value: Must be vector
Note: Special year ranges (YYYY-YYYY) can be used
- layer Name of the layer used to determine where recruitment occurs
Type: String
Default: None
Value: A valid layer as defined by @layer. If a numeric layer, then recruitment is in proportion to the layer values. If a logical layer, then recruitment occurs in cells where the layer value is TRUE

9.2.3. @process[label].type=ageing

- categories Define the categories that ageing is applied to
Type: String vector
Default: None
Value: Valid categories from @model.categories

9.2.4. @process[label].type=constant_mortality_rate

- M Define the constant mortality rate to be applied
Type: Estimable
Default: None
Value: A real number ≥ 0 and ≤ 1

`categories` Define the categories that mortality is applied to
Type: String vector
Default: None
Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category
Type: String vector
Default: None
Value: Valid selectivity labels defined by `@selectivity`

9.2.5. `@process[label].type=annual_mortality_rate`

`years` Define the years when the mortality rates are applied
Type: Constant vector
Default: None
Value: Valid model years

`M` Define the mortality rate to be applied for each year
Type: Estimable vector
Default: None
Value: A real number ≥ 0 and ≤ 1

`categories` Define the categories that mortality is applied to
Type: String vector
Default: None
Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category
Type: String vector
Default: None
Value: Valid selectivity labels defined by `@selectivity`

9.2.6. `@process[label].type=event_mortality`

`categories` Define the categories that the event mortality is applied to
Type: String vector
Default: None
Value: Valid categories from `@model.categories`

`years` Define the years where the mortality even is applied
Type: Integer vector
Default: None
Value: Valid years for the model

`layers` Define the layers that specify the event mortality (as the abundance) in each year

Type: String vector, of length years
Default: None
Value: Valid layers defined by @layer

U_max Define the maximum exploitation rate
Type: Estimable
Default: None
Value: Must be ≥ 0 and ≤ 1

selectivities Define the selectivities applied to each category
Type: String vector
Default: None
Value: Valid selectivity labels defined by @selectivity

penalty Define the event mortality penalty label
Type: String
Default: None
Value: Valid penalty label defined by @penalty

9.2.7. @process[label].type=biomass_event_mortality

categories Define the categories that the event mortality is applied to
Type: String vector
Default: None
Value: Valid categories from @model.categories

size_at_age Define the age-weight relationships for each of the categories that the event mortality is applied to
Type: String vector
Default: None
Value: Valid labels from @size_at_age

years Define the years where the mortality even is applied
Type: Integer vector
Default: None
Value: Valid years for the model

layers Define the layers that specify the event mortality (as a biomass) in each year
Type: String vector, of length years
Default: None
Value: Valid layers defined by @layer

U_max Define the maximum exploitation rate
Type: Constant
Default: None
Value: Must be ≥ 0 and ≤ 1

selectivities Define the selectivities applied to each category
Type: String vector
Default: None
Value: Valid selectivity labels defined by @selectivity

penalty Define the event mortality penalty label
Type: String
Default: None
Value: Valid penalty label defined by @penalty

9.2.8. @process[label].type=category.transition

from Define the category that is the source of the transition process
Type: String
Default: None
Value: A valid category from @model.categories

to Define the category that is the sink of the transition process
Type: String
Default: None
Value: A valid category from @model.categories

N Define the number of individuals to move
Type: Estimable
Default: None
Value: A value ≥ 0

selectivity Define the selectivity applied to the source category
Type: String
Default: None
Value: A valid selectivity label defined by @selectivity

9.2.9. @process[label].type=category.transition_rate

from Define the category that is the source of the transition process
Type: String
Default: None
Value: A valid category from @model.categories

to Define the category that is the sink of the transition process
Type: String
Default: None
Value: A valid category from @model.categories

`proportion` Define the proportion of individuals to move

Type: Estimable

Default: None

Value: A value ≥ 0 and ≤ 1

`selectivity` Define the selectivity applied to the source category

Type: String

Default: None

Value: A valid selectivity label defined by `@selectivity`

9.2.10. `@process[label].type=migration_movement`

`categories` Define the categories that the migration movement event is applied to

Type: String vector

Default: None

Value: Valid categories from `@model.categories`

`source_layer` Define the label of a layer that defines the source cells of the migration movement event

Type: String

Default: None

Value: A valid layer defined by `@layer`

`sink_layer` Define the label of a layer that defines the sink cells of the migration movement event

Type: String

Default: None

Value: A valid layer defined by `@layer`

`proportions` Define the constant multiplier for the proportions that migrate

Type: Estimable

Default: 1.0

Value: A real number between 0 and 1, inclusive

`selectivities` Define the selectivities applied to each category

Type: String vector

Default: None

Value: Valid selectivity labels defined by `@selectivity`

9.2.11. `@process[label].type=adjacent_cell_movement`

Not yet implemented. No subcommands have been defined.

9.2.12. `@process[label].type=preference_movement`

`categories` Define the categories that the preference function movement is applied to

Type: String vector

Default: None

Value: Valid categories from `@model.categories`

`preference_functions` Define the labels of the individual preference functions that make up the total preference function

Type: String vector

Default: None

Value: Valid preference function labels defined by `@preference_function`

9.3. Preference functions

The individual preference functions available are,

- Constant
- Normal
- Double-normal
- Logistic
- Inverse logistic
- Exponential-decay
- Threshold
- Threshold-biomass

Each type of preference function requires a set of subcommands and arguments specific to that function.

`@preference_function label` Define a preference function with label

`type` Define the type of preference function

Type: String

Default: None

Value: A valid type of preference function

9.3.1. `@preference_function[label].type=constant`

`layer` Defines the layer which supplies the preference function independent variable

Type: String

Default: None

Value: A valid layer defined by `@layer`

`alpha` Defines the multiplicative constant α

Type: Estimable

Default: None

9.3.2. @preference_function[label].type=normal

layer Defines the layer which supplies the preference function independent variable

Type: String

Default: None

Value: A valid layer defined by @layer

alpha Defines the multiplicative constant α

Type: Estimable

Default: None

mu Defines the μ parameter of the normal preference function

Type: Estimable

Default: None

sigma Defines the σ parameter of the normal preference function

Type: Estimable

Default: None

9.3.3. @preference_function[label].type=double_normal

layer Defines the layer which supplies the preference function independent variable

Type: String

Default: None

Value: A valid layer defined by @layer

alpha Defines the multiplicative constant α

Type: Estimable

Default: None

mu Defines the μ parameter of the double-normal preference function

Type: Estimable

Default: None

sigma_l Defines the σ_L parameter of the double-normal preference function

Type: Estimable

Default: None

sigma_r Defines the σ_R parameter of the double-normal preference function

Type: Estimable

Default: None

9.3.4. `@preference_function[label].type=logistic`

`layer` Defines the layer which supplies the preference function independent variable

Type: String

Default: None

Value: A valid layer defined by `@layer`

`alpha` Defines the multiplicative constant α

Type: Estimable

Default: None

`a50` Defines the a_{50} parameter of the logistic preference function

Type: Estimable

Default: None

`ato95` Defines the a_{to95} parameter of the logistic preference function

Type: Estimable

Default: None

9.3.5. `@preference_function[label].type=inverse_logistic`

`layer` Defines the layer which supplies the preference function independent variable

Type: String

Default: None

Value: A valid layer defined by `@layer`

`alpha` Defines the multiplicative constant α

Type: Estimable

Default: None

`a50` Defines the a_{50} parameter of the inverse-logistic preference function

Type: Estimable

Default: None

`ato95` Defines the a_{to95} parameter of the inverse-logistic preference function

Type: Estimable

Default: None

9.3.6. `@preference_function[label].type=exponential_decay`

`layer` Defines the layer which supplies the preference function independent variable

Type: String

Default: None

Value: A valid layer defined by `@layer`

alpha Defines the multiplicative constant α
Type: Estimable
Default: None

lambda Defines the λ parameter of the exponential-decay preference function
Type: Estimable
Default: None

9.3.7. @preference_function[label].type=threshold

layer Defines the layer which supplies the preference function independent variable
Type: String
Default: None
Value: A valid layer defined by @layer

categories Define the categories are used to calculate the abundance
Type: String vector
Default: None
Value: Valid categories from @model.categories

selectivities Define the selectivities applied to each category
Type: String vector
Default: None
Value: Valid selectivity labels from @selectivity

alpha Defines the multiplicative constant α
Type: Estimable
Default: None

N Defines the N parameter of the threshold preference function
Type: Estimable
Default: None

lambda Defines the λ parameter of the threshold preference function
Type: Estimable
Default: None

9.3.8. @preference_function[label].type=threshold_biomass

layer Defines the layer which supplies the preference function independent variable
Type: String
Default: None
Value: A valid layer defined by @layer

categories Define the categories are used to calculate the biomass

Type: String vector
Default: None
Value: Valid categories from @model.categories

selectivities Define the selectivities applied to each category

Type: String vector
Default: None
Value: Valid selectivity labels from @selectivity

size_at_age Define the age-weight relationships for each of the categories that the biomass is calculated from

Type: String vector
Default: None
Value: Valid labels from @size_at_age

alpha Defines the multiplicative constant α

Type: Estimable
Default: None

biomass Defines the B biomass parameter of the threshold biomass preference function

Type: Estimable
Default: None

Lambda Defines the λ parameter of the threshold biomass preference function

Type: Estimable
Default: None

9.4. Layers

The available layer types are,

- Numeric
- Categorical
- Distance
- Abundance
- Biomass
- Abundance-density
- Biomass-density
- Meta-layer

@layer *label* Define a layer function with label

type Define the type of layer

Type: String
Default: None
Value: A valid type of layer

9.4.1. @layer[label].type=numeric

data Define the values of the layer

Type: Constant vector, with total length $@model.ncols \times @model.nrows$

Default: None

Value: A vector of values of length equal to the number of elements defined for the spatial structure

rescale Rescale values of the layer

Type: Constant

Default: 1.0

Value: Rescales the values in the layer so that they have maximum value defined by the rescaling constant

9.4.2. @layer[label].type=categorical

data Define the values of the layer

Type: Constant vector, with total length $@model.ncols \times @model.nrows$

Default: None

Value: A vector of values of length equal to the number of elements defined for the spatial structure

9.4.3. @layer[label].type=distance

There are no other subcommands for @layer[label].type=distance.

9.4.4. @layer[label].type=abundance

categories Define the categories are used to calculate the abundance

Type: String vector

Default: None

Value: Valid categories from @model.categories

selectivities Define the selectivities applied to each category

Type: String vector

Default: None

Value: Valid selectivity labels from @selectivity

9.4.5. @layer[label].type=biomass

categories Define the categories are used to calculate the biomass

Type: String vector

Default: None

Value: Valid categories from @model.categories

`selectivities` Define the selectivities applied to each category

Type: String vector

Default: None

Value: Valid selectivity labels from `@selectivity`

`size_at_age` Define the age-weight relationships for each of the categories that the biomass is calculated from

Type: String vector

Default: None

Value: Valid labels from `@size_at_age`

9.4.6. `@layer[label].type=abundance_density`

`categories` Define the categories are used to calculate the abundance

Type: String vector

Default: None

Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category

Type: String vector

Default: None

Value: Valid selectivity labels from `@selectivity`

9.4.7. `@layer[label].type=biomass_density`

`categories` Define the categories are used to calculate the biomass

Type: String vector

Default: None

Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category

Type: String vector

Default: None

Value: Valid selectivity labels from `@selectivity`

`size_at_age` Define the age-weight relationships for each of the categories that the biomass is calculated from

Type: String vector

Default: None

Value: Valid labels from `@size_at_age`

9.4.8. @layer[label].type=meta_layer

years Define the years

Type: Constant vector, with values for each year of the model

Default: None

layers Define the layer labels for each of the years

Type: String vector, with values for each year specified

Default: None

Condition: Listed layers cannot be @layer[label].type=meta_layer

9.5. Derived quantities

The individual types of derived quantities available are,

- Abundance
- Biomass

@derived_quantity label Define a derived quantity with label

type Define the type of derived quantity

Type: String

Default: None

Value: A valid type of derived quantity

9.5.1. @derived_quantity[label].type=abundance

categories Define the categories are used to calculate the derived quantity

Type: String vector

Default: None

Value: Valid categories from @model.categories

selectivity Define the selectivities

Type: String vector

Default: None

Value: Valid selectivity labels from @selectivity

time_step Define the time step at the end of which, the derived quantity is calculated

Type: String

Default: None

Value: A valid time step label from @time_step

9.5.2. @derived_quantity[label].type=biomass

categories Define the categories are used to calculate the derived quantity

Type: String vector

Default: None

Value: Valid categories from @model.categories

selectivity Define the selectivities

Type: String vector

Default: None

Value: Valid selectivity labels from @selectivity

time_step Define the time step at the end of which, the derived quantity is calculated

Type: String

Default: None

Value: A valid time step label from @time_step

9.6. Size-at-age

The individual types of size-at-age relationship available are,

- von Bertalanffy
- Schnute

@size_at_age label Define a size-at-age relationship with label

type Define the type of relationship

Type: String

Default: None

Value: A valid type of size-at-age relationship

9.6.1. @size_at_age[label].type=von.Bertalanffy

Linf Define the L_{∞} parameter of the von Bertalanffy relationship

Type: Estimable

Default: None

Value: A positive real number

k Define the k parameter of the von Bertalanffy relationship

Type: Estimable

Default: None

Value: A positive real number

t0 Define the t_0 parameter of the von Bertalanffy relationship

Type: Estimable

Default: None

Value: A real number

- `distribution` Define the distribution of sizes-at-age around the mean
Type: String
Default: Normal
Value: Either normal or lognormal
- `by_length` Specifies if the linear interpolation of c.v.s is a linear function of mean size or of age
Type: Logical
Default: True
Value: If true, the c.v. is a function of length, else a function of age
- `cv` Define the c.v. of the distribution of sizes-at-age around the mean
Type: Estimable
Default: None
Value: A positive real number
- `growth_proportions` Define the proportion of the year for each time step for evaluating size
Type: Constant vector
Default: None
Value: A vector of values, ≤ 1 of length equal to the number of time steps
- `size_weight` Define the label of the associated size-weight relationship
Type: String
Default: None
Value: A valid label from @size_weight

9.6.2. @size_at_age[label].type=Schnute

- `y1` Define the y_1 parameter of the Schnute relationship
Type: Estimable
Default: None
Value: A positive real number
- `y2` Define the y_2 parameter of the Schnute relationship
Type: Estimable
Default: None
Value: A positive real number
- `tau1` Define the τ_1 parameter of the Schnute relationship
Type: Estimable
Default: None
Value: A real number
- `tau2` Define the τ_2 parameter of the Schnute relationship

Type: String
 Default: Normal
 Value: Either normal or lognormal

a Define the a parameter of the Schnute relationship

Type: String
 Default: Normal
 Value: Either normal or lognormal

b Define the b parameter of the Schnute relationship

Type: String
 Default: Normal
 Value: Either normal or lognormal

by_length Specifies if the linear interpolation of c.v.s is a linear function of mean size or of age

Type: Logical
 Default: True
 Value: If true, the c.v. is a function of length, else a function of age

cv Define the c.v. of the distribution of sizes-at-age around the mean

Type: Estimable
 Default: None
 Value: A positive real number

growth_proportions Define the proportion of the year for each time step for evaluating size

Type: Constant vector
 Default: None
 Value: A vector of values, ≤ 1 of length equal to the number of time steps

size_weight Define the label of the associated size-weight relationship

Type: String
 Default: None
 Value: A valid label from @size_weight

9.7. Size-weight

The individual types of size-weight relationship available are,

- None
- Basic

@size_weight label Define a size-weight relationship with label

Type Define the type of relationship

Type: String
 Default: None
 Value: A valid type of size-weight relationship

9.7.1. @size_weight[label].type=none

There are no other subcommands for @size_weight[label].type=none.

9.7.2. @size_weight[label].type=basic

- a Define the a parameter of the basic relationship
Type: Estimable
Default: None
Value: A positive real number
- b Define the b parameter of the basic relationship
Type: Estimable
Default: None
Value: A positive real number

9.8. Selectivities

The individual selectivity functions available are,

- Constant
- Knife-edge
- All-values
- All-values-bounded
- Increasing
- Logistic
- Logistic-producing
- Double-normal
- Double-exponential

Each type of selectivity function requires a set of subcommands and arguments specific to that function.

@selectivity label Define a selectivity function with label

type Define the type of selectivity function
Type: String
Default: None
Value: A valid type of selectivity function

9.8.1. @selectivity[label].type=constant

- c Defines the C parameter of the selectivity function
 - Type: Estimable
 - Default: None
 - Value: A positive real number

9.8.2. @selectivity[label].type=knife_edge

- e Defines the E parameter of the selectivity function
 - Type: Estimable
 - Default: None
 - Value: A positive real number

9.8.3. @selectivity[label].type=all_values

- v Defines the V parameters (one for each age class) of the selectivity function
 - Type: Estimable vector
 - Default: None
 - Value: A vector of positive real numbers, of length equal to the number of age classes

9.8.4. @selectivity[label].type=all_values_bounded

- l Defines the L parameter of the selectivity function
 - Type: Integer
 - Default: None
 - Value: A positive real number
- h Defines the H parameter of the selectivity function
 - Type: Integer
 - Default: None
 - Value: A positive real number, must be greater than L
- v Defines the V parameters (one for each age class from L to H) of the selectivity function
 - Type: Estimable vector
 - Default: None
 - Value: A vector of positive real numbers, of length equal to the number of age classes from L to H

9.8.5. @selectivity[label].type=increasing

- l Defines the L parameter of the selectivity function
 - Type: Integer
 - Default: None
 - Value: A positive real number

- h Defines the H parameter of the selectivity function
Type: Integer
Default: None
Value: A positive real number, must be greater than L
- v Defines the V parameters (one for each age class from L to H) of the selectivity function
Type: Estimable vector
Default: None
Value: A vector of positive real numbers, of length equal to the number of age classes from L to H

9.8.6. @selectivity[label].type=logistic

- a50 Defines the a_{50} parameter of the selectivity function
Type: Estimable
Default: None
Value: A positive real number
- ato95 Defines the a_{to95} parameter of the selectivity function
Type: Estimable
Default: None
Value: A positive real number

9.8.7. @selectivity[label].type=logistic.producing

- l Defines the L parameter of the selectivity function
Type: Integer
Default: None
Value: A positive real number
- h Defines the H parameter of the selectivity function
Type: Integer
Default: None
Value: A positive real number, must be greater than L
- a50 Defines the a_{50} parameter of the selectivity function
Type: Estimable
Default: None
Value: A positive real number
- ato95 Defines the a_{to95} parameter of the selectivity function
Type: Estimable
Default: None
Value: A positive real number

9.8.8. @selectivity[label].type=double_normal

`mu` Defines the μ parameter of the selectivity function

Type: Estimable

Default: None

`sigma_l` Defines the σ_L parameter of the selectivity function

Type: Estimable

Default: None

`sigma_r` Defines the σ_R parameter of the selectivity function

Type: Estimable

Default: None

9.8.9. @selectivity[label].type=double_exponential

`x1` Defines the x_1 parameter of the selectivity function

Type: Integer

Default: None

`x2` Defines the x_2 parameter of the selectivity function

Type: Integer

Default: None

`x0` Defines the x_0 parameter of the selectivity function

Type: Estimable

Default: None

`y0` Defines the y_0 parameter of the selectivity function

Type: Estimable

Default: None

`y1` Defines the y_1 parameter of the selectivity function

Type: Estimable

Default: None

`y2` Defines the y_2 parameter of the selectivity function

Type: Estimable

Default: None

10. Estimation command and subcommand syntax

10.1. Estimation methods

@estimation

random_seed Defines the random number generator seed
 value The random number generator seed value
 Type: Integer
 Default: None
 Value: An integer between 0 and 10000 inclusive

minimiser The label of the minimiser to use
 Type: String
 Default: None
 Value: A valid label from @Minimiser

MCMC The label of the MCMC to use
 Type: String
 Default: None
 Value: A valid label from @MCMC

10.2. Maximum posterior density (MPD)

Two methods of minimising when estimating are,

- Numerical differences minimiser
- Differential evolution minimiser

Each type of minimiser requires a set of subcommands and arguments specific to that minimiser. Different minimisers can be called in sequence, with the results of one output as input to the next.

@Minimiser *label* Define the an minimiser estimator with label

type Define the type of minimiser
 Type: String
 Default: numerical_differences
 Value: A valid type of minimiser, either numerical_differences or DE_solver

10.2.1. @minimiser[label].type=numerical_differences

max_iterations Define the maximum number of iterations for the Numerical Differences
 minimiser
 Type: Integer
 Default: 1000
 Value: A positive integer

max_evaluations Define the maximum number of evaluations for the Numerical Differences

`minimiser`

Type: Integer

Default: 4000

Value: A positive integer

`step_size` Define the step-size for the Numerical Differences minimiser

Type: Constant

Default: 1e-6

Value: A positive real number

`gradient_tolerance` Define the gradient tolerance for the Numerical Differences minimiser

Type: Constant

Default: 0.0002

Value: A positive real number

10.2.2. `@minimiser[label].type=DE_solver`

`max_iterations` Define the maximum number of iterations for the Differential Evolution
`minimiser`

Type: Integer

Default: 1000

Value: A positive integer

`max_evaluations` Define the maximum number of evaluations for the Differential Evolution
`minimiser`

Type: Integer

Default: 4000

Value: A positive integer

`step_size` Define the step-size for the Differential Evolution minimiser

Type: Constant

Default: 1e-6

Value: A positive real number

`gradient_tolerance` Define the gradient tolerance for the Differential Evolution minimiser

Type: Constant

Default: 0.0002

Value: A positive real number

10.3. Monte Carlo Markov Chain (MCMC)

Only one method of carrying out MCMCs is available, Monte Carlo Markov Chain using Metropolis-Hastings

`@MCMC` Define the MCMC estimation arguments

`type` Define the method of MCMC

Type: String

Default: Metropolis_Hastings

Value: A valid type of MCMC, currently only Metropolis-Hastings is available

10.3.1. @MCMC.type=Metropolis_Hastings

start Covariance multiplier for the starting point of the Markov chain

Type: Constant

Default: 0

Value: If 0, defines the starting point of the chain as the point estimate. If $\neq 0$, defines the starting point as randomly generated, with covariance matrix equal to the approximate covariance (inverse Hessian) times the value of this start parameter

length Length of the Markov chain

Type: Integer

Default: None

Value: Defines the length of the Markov chain (as a number of iterations)

keep Spacing between recorded values in the chain

Type: Integer

Default: 1

Value: Defines the spacing between recorded values in the chain. Samples from the posterior are written to file only if their sample number is evenly divisible by keep

max_correlation Maximum absolute correlation in the covariance matrix of the proposal distribution

Type: Constant

Default: 0.8

Value: Defines the maximum correlation in the covariance matrix of the proposal distribution. Correlations greater than max_correlation are decreased to max_correlation, and those less than -max_correlation are increased to -max_correlation

correlation_adjustment_method Method for adjusting small variances in the covariance proposal matrix

Type: String

Default: correlation

Value: Defines the method (either correlation or covariance) for the adjusting small variances in the covariance matrix of the proposal distribution

correlation_adjustment_diff Minimum non-zero variance times the range of the bounds in the covariance matrix of the proposal distribution

Type: Constant

Default: 0.0001

Value: Defines the minimum non-zero variance times the difference in the bounds of each parameter in the covariance matrix of the proposal distribution

`step_size` Initial step-size (as a multiplier of the approximate covariance matrix)
Type: Constant
Default: $2.4d^{-0.5}$ where d is the number of free parameters
Value: The covariance of the proposal distribution is the approximate covariance (inverse Hessian) times this step-size parameter

`proposal_distribution` The shape of the proposal distribution (either *t* or normal)
Type: String
Default: *t*
Value: Either *t* or *normal*. Defines whether the proposal distribution should be multivariate *t* rather than multivariate normal

`df` Degrees of freedom of the multivariate *t* proposal distribution
Type: Integer
Default: 4
Value: Defines the degrees of freedom of the multivariate *t* proposal distribution

10.4. Profiles

`parameter` Name of the parameter to be profiled
Type: String
Default: None
Value: Defines the name of the parameter to be profiled

`N` Number of values at which to profile the parameter
Type: Integer
Default: 10
Value: Defines the number of values at which to profile the parameter

`lower_bound` lower bound on parameter
Type: Integer
Default: None
Value: Defines the lower bound on the range of the parameter to profile

`upper_bound` Upper bound on parameter
Type: Integer
Default: None
Value: Defines the upper bound on the range of the parameter to profile

10.5. Defining the free parameters and priors

@estimate *parameter_name* Estimate a free parameter *parameter_name* The SPM
name of the parameter to estimate

Type: string

Default: None

Value: A valid SPM parameter name

same Names of the other parameters which are constrained to have the same value

Type: String Vector

Default: None

Value: Defines the names of all the other parameters which are constrained to have the same value as this parameter

phase Phase at which this parameter should be estimated, in point estimation

Type: Integer

Default: 1

Value: Defines the phase at which this parameter should be freed

lower_bounds Lower bounds on this parameter

Type: Constant vector, of length equal to the parameter length

Default: None

Value: Defines the lower bound(s) on this parameter

upper_bound Upper bound on this parameter

Type: Constant vector, of length equal to the parameter length

Default: None

Value: Defines the upper bound(s) on this parameter

MCMC_fixed Should this parameter be fixed during MCMC?

Type: Switch

Default: False

Value: Define this parameter as fixed during MCMC (i.e., considered a constant for the MCMC)

prior Defines the prior for this parameter

Type: String

Default: No default

Value: Defines the type of prior on this parameter, and includes uniform, uniform-log, normal, normal-by-stdev, lognormal, Beta

Different priors require different subcommands.

10.5.1. @estimate[label].prior=uniform

The command @estimate[label].prior=uniform has no other subcommands.

10.5.2. `@estimate[label].prior=uniform_log`

The command `@estimate[label].prior=uniform_log` has no other subcommands.

10.5.3. `@estimate[label].prior=normal`

`mu` Defines the mean μ of the normal prior

Type: Constant

Default: No default

Value: Defines the mean of the normal prior

`cv` Defines the c.v. c of the normal prior

Type: Constant

Default: No default

Value: Defines the c.v. of the normal prior

10.5.4. `@estimate[label].prior=normal_by_stdev`

`mu` Defines the mean μ of the normal by standard deviation prior

Type: Constant

Default: No default

Value: Defines the mean of the normal by standard deviation prior

`stdev` Defines the standard deviation σ of the normal by standard deviation prior

Type: Constant

Default: No default

Value: Defines the standard deviation of the normal by standard deviation prior

10.5.5. `@estimate[label].prior=lognormal`

`mu` Defines the mean μ of the lognormal prior

Type: Constant

Default: No default

Value: Defines the mean of the lognormal prior

`cv` Defines the c.v. c of the lognormal prior

Type: Constant

Default: No default

Value: Defines the c.v. of the lognormal prior

10.5.6. @estimate[label].prior=beta

- A The lower value of the range parameter A of the Beta prior
Type: Constant
Default: No default
Value: Defines the lower value of the range parameter A of the Beta prior
- B The upper value of the range parameter B of the Beta prior
Type: Constant
Default: No default
Value: Defines the upper value of the range parameter B of the Beta prior
- mu Defines the mean μ of the Beta prior
Type: Constant
Default: No default
Value: Defines the mean of the Beta prior
- stdev Defines the standard deviation σ of the Beta prior
Type: Constant
Default: No default
Value: Defines the standard deviation of the Beta prior

10.6. Defining ageing error

Three methods for including ageing error into estimation with observations are,

- None
- Normal
- Off-by-one

Each type of ageing error requires a set of subcommands and arguments specific to its type.

@ageing_error label Define ageing error with label

- type The type of ageing error
Type: String
Default: None
Value: Defines the type of ageing error to use, currently only normal is defined

10.6.1. @ageing_error[label].type=none

The @ageing_error[label].type=none has no other subcommands.

10.6.2. @ageing_error[label].type=normal

- c Parameter of the normal ageing error model
Type: Constant
Default: None
Value: Define the c.v. of misclassification

10.6.3. @ageing_error[label].type=off_by_one

- k The k parameter of the off-by-one ageing error model
Type: Integer
Default: 0
Value: p_1 and p_2 define the proportions of misclassifications down and up by 1 year respectively. k defines the minimum age of fish which can be misclassified - fish under age k have no ageing error
- p_1 The p_1 parameter of the off-by-one ageing error model
Type: Constant
Default: None
Value: p_1 and p_2 define the proportions of misclassifications down and up by 1 year respectively. k defines the minimum age of fish which can be misclassified - fish under age k have no ageing error
- p_2 The p_2 parameter of the off-by-one ageing error model
Type: Constant
Default: None
Value: p_1 and p_2 define the proportions of misclassifications down and up by 1 year respectively. k defines the minimum age of fish which can be misclassified - fish under age k have no ageing error

10.7. Defining catchability constants

@q label Define a catchability constant with label

- q Value of the q parameter
Type: Estimable
Default: None
Value: Defines the value of the q parameter, a real positive number

10.8. Defining penalties

To be written...

11. Observation command and subcommand syntax

11.1. Observation types

The observation types available are,

Observations of a mortality event proportions of individuals by age class

Observations of proportions of individuals by age class

Observations of proportions of individuals between categories within each age class

Relative and absolute abundance observations

Relative and absolute biomass observations

Each type of observation requires a set of subcommands and arguments specific to that process.

@observation *label* Define an observation

type Define the type of observation

Type: String

Default: None

Value: A valid type of observation

11.1.1. @observation[label].type=event_mortality_at_age

year Define the year that the observation applies to

Type: Integer

Default: None

Value: A positive integer between @model.initial_year and @model.current_year

process_label Define the label of the event mortality process

Type: String

Default: None

Value: A valid label of @process where @process[label].type=event_mortality

proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to

Type: Constant

Default: 1.0

Value: A real number between 0 and 1, inclusive

min_age Define the minimum age for the observation

Type: Integer

Default: None

Value: A valid age in the range @model.min_age and @model.max_age

max_age Define the maximum age for the observation

Type: Integer

Default: None

Value: A valid age in the range @model.min_age and @model.max_age

- `age_plus_group` Define is the the maximum age for the observation is a plus group
Type: Switch
Default: None
Value: Either true or false
- `layer` Name of the categorical layer used to group the spacial cells for the observation
Type: String
Default: None
Value: A valid layer as defined by `@layer`. Must be a layer of type=categorical
- `obs [label]` Define the following data as observations for the categorical layer with value
[label]
Type: Constant vector
Default: None
Value: The label is valid value from the associated observation layer. It is followed by a vector of values giving the proportions at age. This subcommand is repeated for each unique value of label
- `tolerance` Define the tolerance on the sum-to-one error check in SPM
Type: Constant
Default: 0.001
Value: The tolerance on the sum to one error check. If $abs(1 - \sum O_i) > tolerance$ then SPM will report an error
- `N [label]` Define the following data as error values (N) for the categorical layer with value
[label]
Type: Constant
Default: None
Value: A valid value from the associated observation layer. This subcommand is repeated for each unique value of label
- `distribution` Define the likelihood distribution
Type: String
Default: None
Value: A valid distribution
- `process_error` Define the process error term
Type: Constant
Default: 0
Value: A non-negative real number
- `delta` Define the delta robustifying constant for the distribution
Type: Constant
Default: 0
Value: A non-negative real number
- `simulate` Defines if this observation should be simulated when doing simulations

Type: Switch
Default: True
Value: True/False

11.1.2. **@observation[label].type=proportions_at_age**

year Define the year that the observation applies to
Type: Integer
Default: None
Value: A positive integer between @model.initial_year and @model.current_year

time_step Define the time-step that the observation applies to
Type: Integer
Default: None
Value: A valid time-step

proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to
Type: Constant
Default: 1.0
Value: A real number between 0 and 1, inclusive

categories Define the categories
Type: String vector
Default: None
Value: Valid categories from @model.categories

selectivities Define the selectivities applied to each category
Type: String vector
Default: None
Value: Valid selectivity labels defined by @selectivity

min_age Define the minimum age for the observation
Type: Integer
Default: None
Value: A valid age in the range @model.min_age and @model.max_age

max_age Define the maximum age for the observation
Type: Integer
Default: None
Value: A valid age in the range @model.min_age and @model.max_age

age_plus_group Define is the the maximum age for the observation is a plus group
Type: Switch
Default: None
Value: Either true or false

- layer** Name of the categorical layer used to group the spacial cells for the observation
Type: String
Default: None
Value: A valid layer as defined by @layer. Must be a layer of type=categorical
- obs [label]** Define the following data as observations for the categorical layer with value [label]
Type: Constant vector
Default: None
Value: The label is valid value from the associated observation layer. It is followed by a vector of values giving the proportions at age. This subcommand is repeated for each unique value of label
- tolerance** Define the tolerance on the sum-to-one error check in SPM
Type: Constant
Default: 0.001
Value: The tolerance on the sum to one error check. If $abs(1 - \sum O_i) > tolerance$ then SPM will report an error
- N [label]** Define the following data as error values (N) for the categorical layer with value [label]
Type: Constant
Default: None
Value: A valid value from the associated observation layer. This subcommand is repeated for each unique value of label
- distribution** Define the likelihood distribution
Type: String
Default: None
Value: A valid distribution
- process_error** Define the process error term
Type: Constant
Default: 0
Value: A non-negative real number
- delta** Define the delta robustifying constant for the distribution
Type: Constant
Default: 0
Value: A non-negative real number
- simulate** Defines if this observation should be simulated when doing simulations
Type: Switch
Default: True
Value: True/False

11.1.3. @observation[label].type=proportions_by_age

year Define the year that the observation applies to

Type: Integer

Default: None

Value: A positive integer between @model.initial_year and @model.current_year

time_step Define the time-step that the observation applies to

Type: Integer

Default: None

Value: A valid time-step

proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to

Type: Constant

Default: 1.0

Value: A real number between 0 and 1, inclusive

categories Define the categories

Type: String vector

Default: None

Value: Valid categories from @model.categories

categories2 Define the categories

Type: String vector

Default: None

Value: Valid categories from @model.categories

selectivities Define the selectivities applied to each category

Type: String vector

Default: None

Value: Valid selectivity labels defined by @selectivity

selectivities2 Define the selectivities applied to each category

Type: String vector

Default: None

Value: Valid selectivity labels defined by @selectivity

min_age Define the minimum age for the observation

Type: Integer

Default: None

Value: A valid age in the range @model.min_age and @model.max_age

max_age Define the maximum age for the observation

Type: Integer

Default: None

Value: A valid age in the range @model.min_age and @model.max_age

- `age_plus_group` Define is the the maximum age for the observation is a plus group
Type: Switch
Default: None
Value: Either true or false
- `layer` Name of the categorical layer used to group the spacial cells for the observation
Type: String
Default: None
Value: A valid layer as defined by `@layer`. Must be a categorical layer
- `obs [label]` Define the following data as observations for the categorical layer with value
[label]
Type: Constant vector
Default: None
Value: The label is valid value from the associated observation layer. It is followed by a vector of values giving the proportions at age. This subcommand is repeated for each unique value of label
- `N [label]` Define the following data as error values (N) for the categorical layer with value
[label]
Type: Constant
Default: None
Value: A valid value from the associated observation layer. This subcommand is repeated for each unique value of label
- `distribution` Define the likelihood distribution
Type: String
Default: None
Value: A valid distribution
- `process_error` Define the process error term
Type: Constant
Default: 0
Value: A non-negative real number
- `delta` Define the delta robustifying constant for the distribution
Type: Constant
Default: 0
Value: A non-negative real number
- `simulate` Defines if this observation should be simulated when doing simulations
Type: Switch
Default: True
Value: True/False

11.1.4. @observation[label].type=abundance

year Define the year that the observation applies to

Type: Integer

Default: None

Value: A positive integer between @model.initial_year and @model.current_year

time_step Define the time-step that the observation applies to

Type: Integer

Default: None

Value: A valid time-step

proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to

Type: Constant

Default: 1.0

Value: A real number between 0 and 1, inclusive

q Define the catchability constant for the observation

Type: Estimable

Default: 1.0

Value: A positive real number

categories Define the categories into which recruitment occurs

Type: String vector

Default: None

Value: Valid categories from @model.categories

selectivities Define the selectivities applied to each category

Type: String vector

Default: None

Value: Valid selectivity labels defined by @selectivity

layer Name of the categorical layer used to group the spacial cells for the observation

Type: String

Default: None

Value: A valid layer as defined by @layer. Must be a categorical layer

obs [label] Define the following data as observations for the categorical layer with value [label]

Type: Constant vector

Default: None

Value: The label is valid value from the associated observation layer. It is followed by a vector of values giving the proportions at age. This subcommand is repeated for each unique value of label

cv [label] Define the following data as error values (cv) for the categorical layer with value

[label]

Type: Constant

Default: None

Value: A valid value from the associated observation layer. This subcommand is repeated for each unique value of label

distribution Define the likelihood distribution

Type: String

Default: None

Value: A valid distribution

process_error Define the process error term

Type: Constant

Default: 0

Value: A non-negative real number

delta Define the delta robustifying constant for the distribution

Type: Constant

Default: 0

Value: A non-negative real number

simulate Defines if this observation should be simulated when doing simulations

Type: Switch

Default: True

Value: True/False

11.1.5. @observation[label].type=biomass

year Define the year that the observation applies to

Type: Integer

Default: None

Value: A positive integer between @model.initial_year and @model.current_year

time_step Define the time-step that the observation applies to

Type: Integer

Default: None

Value: A valid time-step

proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to

Type: Constant

Default: 1.0

Value: A real number between 0 and 1, inclusive

q Define the catchability constant for the observation

Type: Estimable

Default: 1.0

Value: A positive real number

`categories` Define the categories into which recruitment occurs

Type: String vector

Default: None

Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category

Type: String vector

Default: None

Value: Valid selectivity labels defined by `@selectivity`

`layer` Name of the categorical layer used to group the spacial cells for the observation

Type: String

Default: None

Value: A valid layer as defined by `@layer`. Must be a categorical layer

`obs [label]` Define the following data as observations for the categorical layer with value

`[label]`

Type: Constant vector

Default: None

Value: The label is valid value from the associated observation layer. It is followed by a vector of values giving the proportions at age. This subcommand is repeated for each unique value of label

`cv [label]` Define the following data as error values (*cv*) for the categorical layer with value

`[label]`

Type: Constant

Default: None

Value: A valid value from the associated observation layer. This subcommand is repeated for each unique value of label

`distribution` Define the likelihood distribution

Type: String

Default: None

Value: A valid distribution

`process_error` Define the process error term

Type: Constant

Default: 0

Value: A non-negative real number

`delta` Define the delta robustifying constant for the distribution

Type: Constant

Default: 0

Value: A non-negative real number

`simulate` Defines if this observation should be simulated when doing simulations
Type: Switch
Default: True
Value: True/False

12. Output command and subcommand syntax

12.1. Free parameters

13. Examples

13.1. An example of a simple 1×1 non-spatial model

```

categories immature mature spawning
min_age 1
max_age 30
age_plus_group True
initialisation_phases Phase1 Phase2 Phase3
initial_year 1994
Current_year 2008
final_year 2108
cell_length 155.749
time_steps one two

# Initialisation
@initialisation_phase Phase1
years 200
processes Recruitment Spawning Maturation halfM halfM Postspawning Ageing

@initialisation_phase Phase2
years 1
processes Recruitment Spawning Maturation halfM halfM InitialMoveImmature
      InitialMoveMature InitialMoveSpawning Ageing Postspawning

@initialisation_phase Phase3
years 20
processes Recruitment Spawning Maturation halfM halfM MoveImmature MoveMature
      MoveSpawning Ageing Postspawning

# Annual Cycle
@time_step one
processes Recruitment Spawning Maturation halfM fishing halfM

@time_step two
processes MoveImmature MoveMature MoveSpawning PostSpawning Ageing

# Population processes
@process Ageing

```

13.2. An example of a simple 10×10 spatial model

```

categories immature mature spawning
min_age 1
max_age 30
age_plus_group True
initialisation_phases Phase1 Phase2 Phase3
initial_year 1994
Current_year 2008
final_year 2108
cell_length 155.749
time_steps one two

# Initialisation
@initialisation_phase Phase1
years 200

```

13.3 An example of a more complex 10×10 spatial model

```
processes Recruitment Spawning Maturation halfM halfM Postspawning Ageing

@initialisation_phase Phase2
years 1
processes Recruitment Spawning Maturation halfM halfM InitialMoveImmature
      InitialMoveMature InitialMoveSpawning Ageing Postspawning

@initialisation_phase Phase3
years 20
processes Recruitment Spawning Maturation halfM halfM MoveImmature MoveMature
      MoveSpawning Ageing Postspawning

# Annual Cycle
@time_step one
processes Recruitment Spawning Maturation halfM fishing halfM

@time_step two
processes MoveImmature MoveMature MoveSpawning PostSpawning Ageing

# Population processes
@process Ageing
```

13.3. An example of a more complex 10×10 spatial model

```
categories immature mature spawning
min_age 1
max_age 30
age_plus_group True
initialisation_phases Phase1 Phase2 Phase3
initial_year 1994
Current_year 2008
final_year 2108
cell_length 155.749
time_steps one two

# Initialisation
@initialisation_phase Phase1
years 200
processes Recruitment Spawning Maturation halfM halfM Postspawning Ageing

@initialisation_phase Phase2
years 1
processes Recruitment Spawning Maturation halfM halfM InitialMoveImmature
      InitialMoveMature InitialMoveSpawning Ageing Postspawning

@initialisation_phase Phase3
years 20
processes Recruitment Spawning Maturation halfM halfM MoveImmature MoveMature
      MoveSpawning Ageing Postspawning

# Annual Cycle
@time_step one
processes Recruitment Spawning Maturation halfM fishing halfM

@time_step two
processes MoveImmature MoveMature MoveSpawning PostSpawning Ageing
```

```
# Population processes  
@process Ageing
```


14. Post processing output using R

The **R** package `spm` contains a set of **R** functions for reading SPM output, and is available as a precompiled binary for Microsoft Windows (.zip file) or as a source package (.gz file) for Linux. To check the version number and date of the `spm` **R** package (useful for checking that you have the most recent version), use the function `spm.version()`.

The `spm` **R** package includes a range of extract and write functions to aid post-processing of SPM input configuration files and output. The main extract functions are briefly described below. In addition, the package also has a number of undocumented helper functions, that could be useful for writing your own analysis functions. See the **R** help for more detail e.g., `help(spm)`

15. Troubleshooting

15.1. Typical errors

SPM is a complex system, providing many opportunities for error —either because your parameter files do not correctly specify your model, or because the model you tried to specify does not work as you expect. When in doubt, ask an experienced user. Debugging versions of SPM can also be compiled that help to track down cryptic errors.

Common errors include;

1. Misspelt arguments: Probably more likely to be picked up by SPM than misspelt commands, but still a potential problem.
2. Commented out command: Commands that are commented out are ignored by SPM. However, their subcommands will be assumed to be subcommands of the previous command. This will have unintended consequences. Either SPM will error out, or it will run, but return an incorrect or nonsensical result.
3. No penalty on exceeding exploitation rate limits: Unless you use penalties, there is nothing to stop SPM from coming up with a parameter estimate under which there is not enough in the population to allow for the observed exploitation to be taken. You probably want to use a catch limit penalty for each fishery.
4. No penalty on year class strengths not averaging to 1: If you estimate recruitment you may want to force year class strengths to average to 1. You need to use a vector average penalty to do this. If you don't, you may find that all your year class strengths are much more than 1 or much less than 1.

15.2. Other errors

When SPM generates an error and the error message makes no sense, please let the SPM authors know. Even if you manage to fix the problem yourself, we may be able to implement a more helpful error message and make life easier for the next person to encounter the problem. Guidelines for reporting an error are given below in Section 15.4.

Some parameter values of functions or selectivities can result in either very large or very small numbers. These can, on occasion, generate internal numeric overflow errors within SPM. This is the most common cause of an overflow error, and can result in parameter estimates of NaN. The work-around to this type of error is to impose bounds on parameters that exclude the possibility of an overflow error.

15.3. Reporting errors

If you wish to report a bug or problem with SPM, then please send a bug report to the authors, *after* reading the guidelines below.

Use the text SPM: as the start of the subject line in the email. Following these guidelines will assist the SPM authors identify, reproduce, and hopefully solve any reported bugs. It is helpful to be as specific as possible when describing the problem.

Note that SPM is distributed as unsupported software. We will not, as a rule, provide help for users of SPM outside of National Institute of Water & Atmospheric Research Ltd. —although we will usually

endeavour to try. And, while we would appreciate being notified of any problems or errors in SPM, please note that we may not be able to provide timely solutions.

15.4. Guidelines for reporting a bug in SPM

1. Detail the version of SPM are you using? e.g., “SPM v1.0-2008/11/21 Microsoft Windows executable”
2. What operating system or environment are you using? e.g., “IBM-PC Intel CPU running Microsoft Windows XP Release 2”.
3. Give a brief one-line description of the problem, e.g., “a segmentation fault was reported”.
4. If the problem is reproducible, please list the exact steps required to cause it, remembering to include the relevant SPM configuration file, other input files, and any out generated. Specify the *exact* command line arguments that were used, e.g., “Using the command `spm -e -q > logfile.out` reports a segmentation fault. The configuration files used are attached.”
5. If the problem is not reproducible (only happened once, or occasionally for no apparent reason), please describe the circumstances in which it occurred and the symptoms observed (but note it is much harder to reproduce and hence fix non-reproducible bugs, but if several reports are made over time that relate to the same thing, then this may help to track down the problem), e.g., “SPM crashed, but I cannot reproduce how I did it. It seemed to be related to a local network crash but I cannot be sure.”
6. If the problem causes any error messages to appear, please give the *exact* text displayed, e.g., `segmentation fault (core dumped)`.
7. Remember to attach all relevant input and output files so that the problem can be reproduced (it can helpful to compress these into a single file). Without these, it may not be possible to determine the cause of the problem.

16. Acknowledgements

We thank Nokome Bently (TROPHIA) and Ian Ball (Australian Antarctic Division) for their work that led to the ideas behind the development of this program. Thanks also to Andy McKenzie, Dave Gilbert, and Murray Smith (NIWA) for their helpful discussions with the authors.

Much of the structure of *SPM*, equations, and documentation in this manual draw heavily on similar components of the population model CASAL (Bull et al., 2008). We thank the authors of CASAL for their permission to use their work as the basis for parts of *SPM* and the use of material from the CASAL manual in *SPM*.

The development of *SPM* was funded by the New Zealand Ministry of Fisheries, the Foundation for Research, Science and Technology, and the National Institute of Water & Atmospheric Research Ltd. (NIWA).

17. Quick reference

17.1. General commands and subcommands

@include *file_name* Include an external file

17.2. Population command and subcommand syntax

@model Define the spatial structure, population structure, annual cycle, and model years

cell_length The length (distance) of one side of a cell
nrows The number of rows n_{rows} in the spatial structure
ncols The number of columns n_{cols} in the spatial structure
layer The label for the base layer
categories Labels of the categories (rows) of the population component of the partition
size_at_age Define the label of the associated size-at-age relationship for each category
min_age Minimum age of the population
max_age Maximum age of the population
age_plus_group Define the largest age as a plus group
initialisation_phases Define the labels of the phases of the initialisation
initial_year Define the first year of the model, immediately following initialisation
current_year Define the current year of the model
final_year Define the final year of the model in projections
time_steps Define the @time_step labels (in order that they are applied) to form the annual cycle

@initialisation_phase *label* Define the processes and years of the initialisation phase with label

years Define the number of years to run
processes Define the processes (in order of occurrence) to run in each year of the initialisation

@time_step *label* Define a time step with label

processes Define the process labels, in the order that they are applied, for the time step

@process *label* Define a process with label

type Define the type of process

@process[label].type=constant_recruitment

r0 Define the total amount of recruitment at equilibrium abundance levels
categories Define the categories into which recruitment occurs
proportions Define the proportion of recruitment that occurs into each category
ages Define the ages within each category that receive recruitment
layer Name of the layer used to determine where recruitment occurs

@process[label].type=BH_recruitment

r0 Define the total amount of recruitment at equilibrium abundance levels

categories Define the categories into which recruitment occurs
proportions Define the proportion of recruitment that occurs into each category
ages Define the age within each category that receive recruitment
steepness Define the Beverton-Holt stock recruitment relationship steepness (h) parameter
sigma_r Define the recruitment variability σ_R in the stock-recruitment relationship for projections
rho Define the autocorrelation ρ in the recruitment variability in the stock-recruitment relationship for projections
SSB Define the label of the @derived_parameter that defines the SSB
YCS_values YCS values
YCS_years Years for year class strength values
layer Name of the layer used to determine where recruitment occurs

@process[label].type=ageing

categories Define the categories that ageing is applied to

@process[label].type=constant_mortality_rate

M Define the constant mortality rate to be applied
categories Define the categories that mortality is applied to
selectivities Define the selectivities applied to each category

@process[label].type=annual_mortality_rate

years Define the years when the mortality rates are applied
M Define the mortality rate to be applied for each year
categories Define the categories that mortality is applied to
selectivities Define the selectivities applied to each category

@process[label].type=event_mortality

categories Define the categories that the event mortality is applied to
years Define the years where the mortality even is applied
layers Define the layers that specify the event mortality (as the abundance) in each year
U_max Define the maximum exploitation rate
selectivities Define the selectivities applied to each category
penalty Define the event mortality penalty label

@process[label].type=biomass_event_mortality

categories Define the categories that the event mortality is applied to
size_at_age Define the age-weight relationships for each of the categories that the event mortality is applied to
years Define the years where the mortality even is applied
layers Define the layers that specify the event mortality (as a biomass) in each year
U_max Define the maximum exploitation rate
selectivities Define the selectivities applied to each category
penalty Define the event mortality penalty label

@process[label].type=category_transition

from Define the category that is the source of the transition process
to Define the category that is the sink of the transition process
N Define the number of individuals to move
selectivity Define the selectivity applied to the source category

@process[label].type=category_transition_rate

from Define the category that is the source of the transition process
to Define the category that is the sink of the transition process
proportion Define the proportion of individuals to move
selectivity Define the selectivity applied to the source category

@process[label].type=migration_movement

categories Define the categories that the migration movement event is applied to
source_layer Define the label of a layer that defines the source cells of the migration movement event
sink_layer Define the label of a layer that defines the sink cells of the migration movement event
proportions Define the constant multiplier for the proportions that migrate
selectivities Define the selectivities applied to each category

@process[label].type=adjacent_cell_movement

@process[label].type=preference_movement

categories Define the categories that the preference function movement is applied to
preference_functions Define the labels of the individual preference functions that make up the total preference function

@preference_function label Define a preference function with label

type Define the type of preference function

@preference_function[label].type=constant

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α

@preference_function[label].type=normal

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
mu Defines the μ parameter of the normal preference function
sigma Defines the σ parameter of the normal preference function

@preference_function[label].type=double_normal

layer Defines the layer which supplies the preference function independent variable

alpha Defines the multiplicative constant α
mu Defines the μ parameter of the double-normal preference function
sigma_l Defines the σ_L parameter of the double-normal preference function
sigma_r Defines the σ_R parameter of the double-normal preference function

@preference_function[label].type=logistic

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
a50 Defines the a_{50} parameter of the logistic preference function
ato95 Defines the a_{to95} parameter of the logistic preference function

@preference_function[label].type=inverse_logistic

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
a50 Defines the a_{50} parameter of the inverse-logistic preference function
ato95 Defines the a_{to95} parameter of the inverse-logistic preference function

@preference_function[label].type=exponential_decay

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
lambda Defines the λ parameter of the exponential-decay preference function

@preference_function[label].type=threshold

layer Defines the layer which supplies the preference function independent variable
categories Define the categories are used to calculate the abundance
selectivities Define the selectivities applied to each category
alpha Defines the multiplicative constant α
N Defines the N parameter of the threshold preference function
lambda Defines the λ parameter of the threshold preference function

@preference_function[label].type=threshold_biomass

layer Defines the layer which supplies the preference function independent variable
categories Define the categories are used to calculate the biomass
selectivities Define the selectivities applied to each category
size_at_age Define the age-weight relationships for each of the categories that the biomass is calculated from
alpha Defines the multiplicative constant α
biomass Defines the B biomass parameter of the threshold biomass preference function
Lambda Defines the λ parameter of the threshold biomass preference function

@layer label Define a layer function with label

type Define the type of layer

@layer[label].type=numeric

data Define the values of the layer

rescale Rescale values of the layer

@layer[label].type=categorical

data Define the values of the layer

@layer[label].type=distance

@layer[label].type=abundance

categories Define the categories are used to calculate the abundance

selectivities Define the selectivities applied to each category

@layer[label].type=biomass

categories Define the categories are used to calculate the biomass

selectivities Define the selectivities applied to each category

size_at_age Define the age-weight relationships for each of the categories that the biomass is calculated from

@layer[label].type=abundance_density

categories Define the categories are used to calculate the abundance

selectivities Define the selectivities applied to each category

@layer[label].type=biomass_density

categories Define the categories are used to calculate the biomass

selectivities Define the selectivities applied to each category

size_at_age Define the age-weight relationships for each of the categories that the biomass is calculated from

@layer[label].type=meta_layer

years Define the years

layers Define the layer labels for each of the years

@derived_quantity label Define a derived quantity with label

type Define the type of derived quantity

@derived_quantity[label].type=abundance

categories Define the categories are used to calculate the derived quantity

selectivity Define the selectivities

time_step Define the time step at the end of which, the derived quantity is calculated

@derived_quantity[label].type=biomass

categories Define the categories are used to calculate the derived quantity

selectivity Define the selectivities

time_step Define the time step at the end of which, the derived quantity is calculated

@size_at_age *label* Define a size-at-age relationship with label

type Define the type of relationship

@size_at_age[label].type=von_Bertalanffy

Linf Define the L_{∞} parameter of the von Bertalanffy relationship

k Define the k parameter of the von Bertalanffy relationship

t0 Define the t_0 parameter of the von Bertalanffy relationship

distribution Define the distribution of sizes-at-age around the mean

by_length Specifies if the linear interpolation of c.v.s is a linear function of mean size or of age

cv Define the c.v. of the distribution of sizes-at-age around the mean

growth_proportions Define the proportion of the year for each time step for evaluating size

size_weight Define the label of the associated size-weight relationship

@size_at_age[label].type=Schnute

y1 Define the y_1 parameter of the Schnute relationship

y2 Define the y_2 parameter of the Schnute relationship

tau1 Define the τ_1 parameter of the Schnute relationship

tau2 Define the τ_2 parameter of the Schnute relationship

a Define the a parameter of the Schnute relationship

b Define the b parameter of the Schnute relationship

by_length Specifies if the linear interpolation of c.v.s is a linear function of mean size or of age

cv Define the c.v. of the distribution of sizes-at-age around the mean

growth_proportions Define the proportion of the year for each time step for evaluating size

size_weight Define the label of the associated size-weight relationship

@size_weight *label* Define a size-weight relationship with label

Type Define the type of relationship

@size_weight[label].type=none

@size_weight[label].type=basic

a Define the a parameter of the basic relationship

b Define the b parameter of the basic relationship

@selectivity *label* Define a selectivity function with label

type Define the type of selectivity function

@selectivity[label].type=constant

c Defines the C parameter of the selectivity function

@selectivity[label].type=knife_edge

e Defines the E parameter of the selectivity function

@selectivity[label].type=all_values

v Defines the V parameters (one for each age class) of the selectivity function

@selectivity[label].type=all_values_bounded

l Defines the L parameter of the selectivity function
 h Defines the H parameter of the selectivity function
 v Defines the V parameters (one for each age class from L to H) of the selectivity function

@selectivity[label].type=increasing

l Defines the L parameter of the selectivity function
 h Defines the H parameter of the selectivity function
 v Defines the V parameters (one for each age class from L to H) of the selectivity function

@selectivity[label].type=logistic

a50 Defines the a_{50} parameter of the selectivity function
 ato95 Defines the a_{to95} parameter of the selectivity function

@selectivity[label].type=logistic_producing

l Defines the L parameter of the selectivity function
 h Defines the H parameter of the selectivity function
 a50 Defines the a_{50} parameter of the selectivity function
 ato95 Defines the a_{to95} parameter of the selectivity function

@selectivity[label].type=double_normal

mu Defines the μ parameter of the selectivity function
 sigma_l Defines the σ_L parameter of the selectivity function
 sigma_r Defines the σ_R parameter of the selectivity function

@selectivity[label].type=double_exponential

x1 Defines the x_1 parameter of the selectivity function
 x2 Defines the x_2 parameter of the selectivity function
 x0 Defines the x_0 parameter of the selectivity function
 y0 Defines the y_0 parameter of the selectivity function
 y1 Defines the y_1 parameter of the selectivity function
 y2 Defines the y_2 parameter of the selectivity function

17.3. Estimation command and subcommand syntax

@estimation

random_seed Defines the random number generator seed
 minimiser The label of the minimiser to use
 MCMC The label of the MCMC to use

@Minimiser label Define the an minimiser estimator with label

`type` Define the type of minimiser

@minimiser[label].type=numerical_differences

`max_iterations` Define the maximum number of iterations for the Numerical Differences minimiser

`max_evaluations` Define the maximum number of evaluations for the Numerical Differences minimiser

`step_size` Define the step-size for the Numerical Differences minimiser

`gradient_tolerance` Define the gradient tolerance for the Numerical Differences minimiser

@minimiser[label].type=DE_solver

`max_iterations` Define the maximum number of iterations for the Differential Evolution minimiser

`max_evaluations` Define the maximum number of evaluations for the Differential Evolution minimiser

`step_size` Define the step-size for the Differential Evolution minimiser

`gradient_tolerance` Define the gradient tolerance for the Differential Evolution minimiser

@MCMC Define the MCMC estimation arguments

`type` Define the method of MCMC

@MCMC.type=Metropolis_Hastings

`start` Covariance multiplier for the starting point of the Markov chain

`length` Length of the Markov chain

`keep` Spacing between recorded values in the chain

`max_correlation` Maximum absolute correlation in the covariance matrix of the proposal distribution

`correlation_adjustment_method` Method for adjusting small variances in the covariance proposal matrix

`correlation_adjustment_diff` Minimum non-zero variance times the range of the bounds in the covariance matrix of the proposal distribution

`step_size` Initial step-size (as a multiplier of the approximate covariance matrix)

`proposal_distribution` The shape of the proposal distribution (either *t* or normal)

`df` Degrees of freedom of the multivariate *t* proposal distribution

`parameter` Name of the parameter to be profiled

`N` Number of values at which to profile the parameter

`lower_bound` lower bound on parameter

`upper_bound` Upper bound on parameter

@estimate parameter_name Estimate a free parameter

`same` Names of the other parameters which are constrained to have the same value

`phase` Phase at which this parameter should be estimated, in point estimation

`lower_bounds` Lower bounds on this parameter

`upper_bound` Upper bound on this parameter

`MCMC_fixed` Should this parameter be fixed during MCMC?

`prior` Defines the prior for this parameter

@estimate[label].prior=uniform

@estimate[label].prior=uniform_log

@estimate[label].prior=normal

mu Defines the mean μ of the normal prior

cv Defines the c.v. c of the normal prior

@estimate[label].prior=normal_by_stdev

mu Defines the mean μ of the normal by standard deviation prior

stdev Defines the standard deviation σ of the normal by standard deviation prior

@estimate[label].prior=lognormal

mu Defines the mean μ of the lognormal prior

cv Defines the c.v. c of the lognormal prior

@estimate[label].prior=beta

A The lower value of the range parameter A of the Beta prior

B The upper value of the range parameter B of the Beta prior

mu Defines the mean μ of the Beta prior

stdev Defines the standard deviation σ of the Beta prior

@ageing_error label Define ageing error with label

type The type of ageing error

@ageing_error[label].type=none

@ageing_error[label].type=normal

c Parameter of the normal ageing error model

@ageing_error[label].type=off_by_one

k The k parameter of the off-by-one ageing error model

p1 The p_1 parameter of the off-by-one ageing error model

p2 The p_2 parameter of the off-by-one ageing error model

@q label Define a catchability constant with label

q Value of the q parameter

17.4. Observation command and subcommand syntax

@observation label Define an observation

type Define the type of observation

@observation[label].type=event_mortality_at_age

year Define the year that the observation applies to
process_label Define the label of the event mortality process
proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to
min_age Define the minimum age for the observation
max_age Define the maximum age for the observation
age_plus_group Define is the the maximum age for the observation is a plus group
layer Name of the categorical layer used to group the spacial cells for the observation
obs [label] Define the following data as observations for the categorical layer with value [label]
tolerance Define the tolerance on the sum-to-one error check in SPM
N [label] Define the following data as error values (N) for the categorical layer with value [label]
distribution Define the likelihood distribution
process_error Define the process error term
delta Define the delta robustifying constant for the distribution
simulate Defines if this observation should be simulated when doing simulations

@observation[label].type=proportions_at_age

year Define the year that the observation applies to
time_step Define the time-step that the observation applies to
proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to
categories Define the categories
selectivities Define the selectivities applied to each category
min_age Define the minimum age for the observation
max_age Define the maximum age for the observation
age_plus_group Define is the the maximum age for the observation is a plus group
layer Name of the categorical layer used to group the spacial cells for the observation
obs [label] Define the following data as observations for the categorical layer with value [label]
tolerance Define the tolerance on the sum-to-one error check in SPM
N [label] Define the following data as error values (N) for the categorical layer with value [label]
distribution Define the likelihood distribution
process_error Define the process error term
delta Define the delta robustifying constant for the distribution
simulate Defines if this observation should be simulated when doing simulations

@observation[label].type=proportions_by_age

year Define the year that the observation applies to
time_step Define the time-step that the observation applies to
proportion_time_step Define the interpolated proportion of the time-step passes that the

observation applies to

categories Define the categories
categories2 Define the categories
selectivities Define the selectivities applied to each category
selectivities2 Define the selectivities applied to each category
min_age Define the minimum age for the observation
max_age Define the maximum age for the observation
age_plus_group Define is the the maximum age for the observation is a plus group
layer Name of the categorical layer used to group the spacial cells for the observation
obs [label] Define the following data as observations for the categorical layer with value [label]
N [label] Define the following data as error values (N) for the categorical layer with value [label]
distribution Define the likelihood distribution
process_error Define the process error term
delta Define the delta robustifying constant for the distribution
simulate Defines if this observation should be simulated when doing simulations

@observation[label].type=abundance

year Define the year that the observation applies to
time_step Define the time-step that the observation applies to
proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to
q Define the catchability constant for the observation
categories Define the categories into which recruitment occurs
selectivities Define the selectivities applied to each category
layer Name of the categorical layer used to group the spacial cells for the observation
obs [label] Define the following data as observations for the categorical layer with value [label]
cv [label] Define the following data as error values (cv) for the categorical layer with value [label]
distribution Define the likelihood distribution
process_error Define the process error term
delta Define the delta robustifying constant for the distribution
simulate Defines if this observation should be simulated when doing simulations

@observation[label].type=biomass

year Define the year that the observation applies to
time_step Define the time-step that the observation applies to
proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to
q Define the catchability constant for the observation
categories Define the categories into which recruitment occurs
selectivities Define the selectivities applied to each category
layer Name of the categorical layer used to group the spacial cells for the observation
obs [label] Define the following data as observations for the categorical layer with value [label]
cv [label] Define the following data as error values (cv) for the categorical layer with value [label]

[label]
distribution Define the likelihood distribution
process_error Define the process error term
delta Define the delta robustifying constant for the distribution
simulate Defines if this observation should be simulated when doing simulations

17.5. Output command and subcommand syntax

18. References

- I. Ball and A Constable. Fish heaven: A Monte Carlo, spatially explicit single species fishery model for the testing of parameter estimation methods. Technical Report WG-FSA-00/36, Australian Antarctic Division, October 2000.
- I. Ball and A.T. Williamson. Fish heaven user's manual. Technical report, Australian Antarctic Division, August 2003.
- N. Bentley, C.R. Davies, S.E. McNeill, and N.M. Davies. A framework for evaluating spatial closures as a fisheries management tool. New Zealand Fisheries Assessment Report, Ministry of Fisheries, 2004a.
- N. Bentley, N.M. Davies, and S.E. McNeill. A spatially explicit model of the snapper (*Pagrus auratus*) fishery in SNA1. New Zealand Fisheries Assessment Report, Ministry of Fisheries, 2004b.
- R.J.H. Beverton and S.J. Holt. *On the dynamics of exploited fish populations*. Fishery investigations. HMSO, London, 1957.
- B. Bull, R.I.C.C. Francis, A. Dunn, A. McKenzie, D.J. Gilbert, M.H. Smith, and R. Bian. CASAL C++ Algorithmic Stock Assessment Laboratory): CASAL user manual v2.20-2008/02/14. Technical report, NIWA, 2008.
- J. E. Dennis Jr and R.B. Schnabel. *Numerical methods for unconstrained optimisation and nonlinear equations*. Classics in Applied Mathematics. Prentice Hall, 1996.
- A B Gelman, J S Carlin, H S Stern, and D B Rubin. *Bayesian data analysis*. Chapman and Hall, London, 1995.
- W R Gilks, A Thomas, and D J Spiegelhalter. A language and program for complex Bayesian modelling. *The Statistician*, 43(1):169–177, 1994.
- Makoto Matsumoto and Takuji Nishimura. Mersenne twister: a 623-dimensionally equidistributed uniform pseudo-random number generator. *ACM Transactions on Modeling and Computer Simulation: Special Issue on Uniform Random Number Generation*, 8(1):3–30, January 1998.
- Andre E. Punt and Ray Hilborn. *BAYES-SA. Bayesian stock assessment methods in fisheries. User's manual. FAO Computerized information series (fisheries) 12*. Food and Agriculture Organisation of the United Nations, Rome (Italy)., 2001.
- J Schnute. A versatile growth model with statistically stable parameters. *Canadian Journal of Fisheries and Aquatic Sciences*, 38(9):1128–1140, 1981.
- Rainer Storn and Kenneth Price. Differential evolution - a simple and efficient adaptive scheme for global optimization over continuous spaces. Technical Report TR-95-012, International Computer Science Institute, Berkeley, CA, 1995. URL <http://citeseer.ist.psu.edu/182432.html>.

19. Spatial Population Model software license

Common Public License Version 1.0

THE ACCOMPANYING PROGRAM IS PROVIDED UNDER THE TERMS OF THIS COMMON PUBLIC LICENSE ("AGREEMENT"). ANY USE, REPRODUCTION OR DISTRIBUTION OF THE PROGRAM CONSTITUTES RECIPIENT'S ACCEPTANCE OF THIS AGREEMENT.

1. DEFINITIONS

"Contribution" means:

a) in the case of the initial Contributor, the initial code and documentation distributed under this Agreement, and

b) in the case of each subsequent Contributor:

i) changes to the Program, and

ii) additions to the Program;

where such changes and/or additions to the Program originate from and are distributed by that particular Contributor. A Contribution 'originates' from a Contributor if it was added to the Program by such Contributor itself or anyone acting on such Contributor's behalf. Contributions do not include additions to the Program which: (i) are separate modules of software distributed in conjunction with the Program under their own license agreement, and (ii) are not derivative works of the Program.

"Contributor" means any person or entity that distributes the Program.

"Licensed Patents " mean patent claims licensable by a Contributor which are necessarily infringed by the use or sale of its Contribution alone or when combined with the Program.

"Program" means the Contributions distributed in accordance with this Agreement.

"Recipient" means anyone who receives the Program under this Agreement, including all Contributors.

2. GRANT OF RIGHTS

a) Subject to the terms of this Agreement, each Contributor hereby grants Recipient a non-exclusive, worldwide, royalty-free copyright license to reproduce, prepare derivative works of, publicly display, publicly perform, distribute and sublicense the Contribution of such Contributor, if any, and such derivative works, in source code and object code form.

b) Subject to the terms of this Agreement, each Contributor hereby grants Recipient a non-exclusive, worldwide, royalty-free patent license under Licensed Patents to make, use, sell, offer to sell, import and otherwise transfer the Contribution of such Contributor, if any, in source code and object code form. This patent license shall apply to the combination of the Contribution and the Program if, at the time the Contribution is added by the Contributor, such addition of the Contribution causes such combination to be covered by the Licensed Patents. The patent license shall not apply to any other combinations which include the Contribution. No hardware per se is licensed hereunder.

c) Recipient understands that although each Contributor grants the licenses to its Contributions set forth herein, no assurances are provided by any Contributor that the Program does not infringe the patent or other intellectual property rights of any other entity. Each Contributor disclaims any liability to Recipient for claims brought by any other entity based on infringement of intellectual property rights or otherwise. As a condition to exercising the rights and licenses granted hereunder, each Recipient hereby assumes sole responsibility to secure any other intellectual property rights needed, if any. For example, if a third party patent license is required to allow Recipient to distribute the Program, it is Recipient's responsibility to acquire that license before distributing the Program.

d) Each Contributor represents that to its knowledge it has sufficient copyright rights in its Contribution, if any, to grant the copyright license set forth in this Agreement.

3. REQUIREMENTS

A Contributor may choose to distribute the Program in object code form under its own license agreement, provided that:

a) it complies with the terms and conditions of this Agreement; and

b) its license agreement:

i) effectively disclaims on behalf of all Contributors all warranties and conditions, express and implied, including warranties or conditions of title and non-infringement, and implied warranties or conditions of merchantability and fitness for a particular purpose;

ii) effectively excludes on behalf of all Contributors all liability for damages, including direct, indirect, special, incidental and consequential damages, such as lost profits;

iii) states that any provisions which differ from this Agreement are offered by that Contributor alone and not by any other party; and

iv) states that source code for the Program is available from such Contributor, and informs licensees how to obtain it in a reasonable manner on or through a medium customarily used for software exchange.

When the Program is made available in source code form:

a) it must be made available under this Agreement; and

b) a copy of this Agreement must be included with each copy of the Program.

Contributors may not remove or alter any copyright notices contained within the Program.

Each Contributor must identify itself as the originator of its Contribution, if any, in a manner that reasonably allows subsequent Recipients to identify the originator of the Contribution.

4. COMMERCIAL DISTRIBUTION

Commercial distributors of software may accept certain responsibilities with respect to end users, business partners and the like. While this license is intended to facilitate the commercial use of the Program, the Contributor who includes the Program in a commercial product offering should do so in a manner which does not create potential liability for other Contributors. Therefore, if a Contributor includes the Program in a commercial product offering, such Contributor ("Commercial Contributor") hereby agrees to defend and indemnify every other Contributor ("Indemnified Contributor") against any losses, damages and costs (collectively "Losses") arising from claims, lawsuits and other legal actions brought by a third party against the Indemnified Contributor to the extent caused by the acts or omissions of such Commercial Contributor in connection with its distribution of the Program in a commercial product offering. The obligations in this section do not apply to any claims or Losses relating to any actual or alleged intellectual property infringement. In order to qualify, an Indemnified Contributor must: a) promptly notify the Commercial Contributor in writing of such claim, and b) allow the Commercial Contributor to control, and cooperate with the Commercial Contributor in, the defense and any related settlement negotiations. The Indemnified Contributor may participate in any such claim at its own expense.

For example, a Contributor might include the Program in a commercial product offering, Product X. That Contributor is then a Commercial Contributor. If that Commercial Contributor then makes performance claims, or offers warranties related to Product X, those performance claims and warranties are such Commercial Contributor's responsibility alone. Under this section, the Commercial Contributor would have to defend claims against the other Contributors related to those performance claims and warranties, and if a court requires any other Contributor to pay any damages as a result, the Commercial Contributor must pay those damages.

5. NO WARRANTY

EXCEPT AS EXPRESSLY SET FORTH IN THIS AGREEMENT, THE PROGRAM IS PROVIDED ON AN "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, EITHER EXPRESS OR IMPLIED INCLUDING, WITHOUT LIMITATION, ANY WARRANTIES OR CONDITIONS OF TITLE, NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Each Recipient is solely responsible for determining the appropriateness of using and distributing the Program and assumes all risks associated with its exercise of rights under this Agreement, including but not limited to the risks and costs of program errors, compliance with applicable laws, damage to or loss of data, programs or equipment, and unavailability or interruption of operations.

6. DISCLAIMER OF LIABILITY

EXCEPT AS EXPRESSLY SET FORTH IN THIS AGREEMENT, NEITHER RECIPIENT NOR ANY CONTRIBUTORS SHALL HAVE ANY LIABILITY FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING WITHOUT LIMITATION LOST PROFITS), HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OR DISTRIBUTION OF THE PROGRAM OR THE EXERCISE OF ANY RIGHTS GRANTED HEREUNDER, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

7. GENERAL

If any provision of this Agreement is invalid or unenforceable under applicable law, it shall not affect the validity or enforceability of the remainder of the terms of this Agreement, and without further action by the parties hereto, such provision shall be reformed to the minimum extent necessary to make such provision valid and enforceable.

If Recipient institutes patent litigation against a Contributor with respect to a patent applicable to software (including a cross-claim or counterclaim in a lawsuit), then any patent licenses granted by that Contributor to such Recipient under this Agreement shall terminate as of the date such litigation is filed. In addition, if Recipient institutes patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Program itself (excluding combinations of the Program with other software or hardware) infringes such Recipient's patent(s), then such Recipient's rights granted under Section 2(b) shall terminate as of the date such litigation is filed.

All Recipient's rights under this Agreement shall terminate if it fails to comply with any of the material terms or conditions of this Agreement and does not cure such failure in a reasonable period of time after becoming aware of such noncompliance. If all Recipient's rights under this Agreement terminate, Recipient agrees to cease use and distribution of the Program as soon as reasonably practicable. However, Recipient's obligations under this Agreement and any licenses granted by Recipient relating to the Program shall continue and survive.

Everyone is permitted to copy and distribute copies of this Agreement, but in order to avoid inconsistency the Agreement is copyrighted and may only be modified in the following manner. The Agreement Steward reserves the right to publish new versions (including revisions) of this Agreement from time to time. No one other than the Agreement Steward has the right to modify this Agreement. IBM is the initial Agreement Steward. IBM may assign the responsibility to serve as the Agreement Steward to a suitable separate entity. Each new version of the Agreement will be given a distinguishing version number. The Program (including Contributions) may always be distributed subject to the version of the Agreement under which it was received. In addition, after a new version of the Agreement is published, Contributor may elect to distribute the Program (including its Contributions) under the new version. Except as expressly stated in Sections 2(a) and 2(b) above, Recipient receives no rights or licenses to the intellectual property of any Contributor under this Agreement, whether expressly, by implication, estoppel or otherwise. All rights in the Program not expressly granted under this Agreement are reserved.

This Agreement is governed by the laws of the State of New York and the intellectual property laws of the United States of America. No party to this Agreement will bring a legal action under this Agreement more than one year after the cause of action arose. Each party waives its rights to a jury trial in any resulting litigation.

20. Index

- Ageing, 5
- Annual cycle, 5
- CASAL, 3
- Category transition, 5
- Citation, 1
- Command
 - IncludeFile, 11
- Command block format, 10
- Command line arguments, 7
- Commands, 9
- Commands
 - Subcommands, 10
- Comments, 11
- Common Public License, 1
- derived quantities, 3
- Estimation section, 6
- Fixed parameters, 7
- Free parameters, 7
- Input configuration file, 4, 7
- Input configuration file syntax, 9
- Model overview, 3
- Mortality, 5
- Movement, 5, 21
- Movement processes, 5
- Output section, 6
- partition, 3
- Population processes, 5
- Population section, 4, 13
- Preference function, 21
- Recruitment, 5
- Software license, 1
- state, 3
- structure, 3
- Subcommand argument type, 10
- Tasks, 7
- Version, 1