

Spatial Population Model User Manual

SPM v1.1-2012-07-12 (rev. 4728)

Alistair Dunn, Scott Rasmussen, and Sophie Mormede

July 2012



Spatial Population Model User Manual (modified: 2012-07-11)
for use with SPM v1.1-2012-07-12 (rev. 4728)

Citation:
Dunn, A.; Rasmussen, S.; Mormede, S. (2012) Spatial Population Model User Manual, SPM
v1.1-2012-07-12 (rev. 4728) . National Institute of Water & Atmospheric Research Ltd.
Unpublished report. 163 p.

Contents

1	Introduction	1
1.1	Version	1
1.2	Citing SPM	1
1.3	Software license	1
1.4	System requirements	1
1.5	Necessary files	2
1.6	Getting help	2
1.7	Technical details	2
2	Model overview	3
2.1	Introduction	3
2.2	The population section	4
2.3	The estimation section	4
2.4	The observation section	5
2.5	The report section	5
3	Running SPM	7
3.1	Using SPM	7
3.2	The input configuration file	7
3.3	Redirecting standard output	8
3.4	Command line arguments	8
3.5	Constructing an SPM input configuration file	9
3.5.1	Commands	9
3.5.2	Subcommands	9
3.5.3	The command-block format	10
3.5.4	Commenting out lines	11
3.5.5	Determining parameter names	11
3.6	SPM exit status values	12
4	The population section	13
4.1	Introduction	13
4.2	Spatial structure	13
4.3	Population structure	14
4.4	Layers	15
4.5	Time sequences	17
4.5.1	Annual cycle	17
4.5.2	Initialisation	17
4.5.3	Model years	18
4.6	Processes	18
4.7	Population processes	19
4.7.1	Recruitment	19

4.7.2	Ageing	22
4.7.3	Mortality	22
4.7.4	Category transitions	24
4.8	Movement processes	26
4.8.1	Migration movement	26
4.8.2	Adjacent cell movement	27
4.8.3	Preference movement	27
4.9	Derived quantities	29
4.10	Derived layers and meta-layers	30
4.11	Size-age relationship	31
4.12	Size-weight relationship	31
4.13	Selectivities	32
4.13.1	Constant	33
4.13.2	Knife-edge	33
4.13.3	All-values	33
4.13.4	All-values-bounded	33
4.13.5	Increasing	33
4.13.6	Logistic	34
4.13.7	Inverse logistic	34
4.13.8	Logistic producing	34
4.13.9	Double-normal	34
4.13.10	Double-exponential	34
5	The estimation section	35
5.1	Role of the estimation section	35
5.2	The objective function	35
5.3	Specifying the parameters to be estimated	35
5.4	Point estimation	36
5.4.1	The numerical differences minimiser	36
5.4.2	The differential evolution minimiser	37
5.5	Posterior profiles	37
5.6	Bayesian estimation	38
5.7	Priors	40
5.8	Penalties	41
6	The observation section	43
6.1	Observations and likelihoods	43
6.2	Proportions-at-age observations	43
6.2.1	Likelihoods for proportions-at-age observations	46
6.3	Proportions-by-category observations	47
6.3.1	Likelihoods for proportions-by-category observations	48
6.4	Abundance or biomass observations	49

6.4.1	Likelihoods for abundance observations	50
6.5	Process error	51
6.6	Ageing error	52
6.7	Simulating observations	52
6.8	Pseudo-observations	53
7	The report section	55
7.1	Printing the model spatial map	55
7.2	Printing the partition	55
7.3	Printing the partition at the end of an initialisation	55
7.4	Printing a process summary	56
7.5	Printing derived quantities	56
7.6	Printing the estimated parameters	56
7.7	Printing the estimated parameters in a vector format	56
7.8	Printing the objective function	56
7.9	Printing the covariance matrix	56
7.10	Printing observations, fits, and residuals	56
7.11	Printing simulated observations	57
7.12	Printing the ageing error misclassification matrix	57
7.13	Printing layers and meta-layers	57
7.14	Printing a derived view via a categorical layer	57
7.15	Printing selectivities	57
7.16	Printing the random number seed	57
7.17	Printing the size-weight relationship	57
7.18	Printing the size-at-age relationship	57
7.19	Printing the weight-at-age relationship	57
7.20	Printing the results of an MCMC	58
8	Population command and subcommand syntax	59
8.1	Model structure	59
8.2	Initialisation	60
8.2.1	Iterative initialisation	61
8.3	time-steps	61
8.4	Processes	61
8.4.1	Constant recruitment process	62
8.4.2	Beverton-Holt recruitment process	62
8.4.3	Local Beverton-Holt recruitment process	64
8.4.4	Ageing process	65
8.4.5	Constant mortality rate process	66
8.4.6	Annual mortality rate process	66
8.4.7	Event mortality process	67
8.4.8	Biomass event mortality process	67

8.4.9	Category transition process	68
8.4.10	Category transition rate process	69
8.4.11	Migration movement	69
8.4.12	Adjacent cell movement	70
8.4.13	Preference movement	71
8.5	Preference functions	71
8.5.1	Constant	72
8.5.2	Normal	72
8.5.3	Double-normal	72
8.5.4	Logistic	73
8.5.5	Inverse-logistic	73
8.5.6	Exponential	74
8.5.7	Threshold	74
8.5.8	Categorical	75
8.5.9	Monotonic categorical	75
8.6	Layers	76
8.6.1	Numeric	76
8.6.2	Categorical	76
8.6.3	Distance	76
8.6.4	Abundance	77
8.6.5	Biomass	77
8.6.6	Abundance-density	77
8.6.7	Biomass-density	77
8.6.8	Meta-layer	78
8.6.9	Derived-layer	78
8.6.10	Derived-meta-layer	79
8.7	Derived quantities	80
8.7.1	Abundance	80
8.7.2	Biomass	81
8.8	Age-size relationship	81
8.8.1	von Bertalanffy	82
8.8.2	Schnute	83
8.9	Size-weight	84
8.9.1	None	84
8.9.2	Basic	84
8.10	Selectivities	84
8.10.1	Constant	85
8.10.2	Knife-edge	85
8.10.3	All-values	85
8.10.4	All-values-bounded	86
8.10.5	Increasing	86
8.10.6	Logistic	86

8.10.7	InverseLogistic	87
8.10.8	Logistic producing	87
8.10.9	Double-normal	88
8.10.10	Double-exponential	88
9	Estimation command and subcommand syntax	91
9.1	Estimation methods	91
9.2	Point estimation	91
9.2.1	Numerical differences minimiser	92
9.2.2	Differential evolution minimiser	92
9.3	Monte Carlo Markov Chain (MCMC)	93
9.3.1	Metropolis-Hastings	93
9.4	Profiles	95
9.5	Defining the parameters to be estimated and their priors	95
9.6	Priors	96
9.6.1	Uniform prior	96
9.6.2	Uniform-log prior	96
9.6.3	Normal prior	97
9.6.4	Normal-by-stdev prior	97
9.6.5	Lognormal prior	97
9.6.6	Beta prior	97
9.7	Defining catchability constants	98
9.8	Defining penalties	98
10	Observation command and subcommand syntax	99
10.1	Observation types	99
10.1.1	Proportions at age	99
10.1.2	Proportions by category	101
10.1.3	Abundance	103
10.1.4	Biomass	105
10.2	Defining ageing error	106
10.2.1	No ageing error	107
10.2.2	Normal ageing error	107
10.2.3	Off-by-one ageing error	107
11	Report command and subcommand syntax	109
11.1	Available reports	109
11.2	Report commands and subcommands	109
11.2.1	Print the spatial co-ordinates of each spatial cell (i.e., row and column labels of each spatial cell) of the spatial structure	110
11.2.2	Print the partition	110
11.2.3	Print the partition at initialisation	110
11.2.4	Print a summary of a process	111

11.2.5	Print a derived quantity	111
11.2.6	Print a summary of the estimated parameters	112
11.2.7	Printing the estimated parameter values out as a vector	112
11.2.8	Print the objective function values	112
11.2.9	Print the covariance matrix	113
11.2.10	Print a summary of the an observation, including fits, and residuals	113
11.2.11	Print an observation using simulated values	113
11.2.12	Print an ageing error misclassification matrix	114
11.2.13	Print a layer	114
11.2.14	Print a derived view via a categorical layer	115
11.2.15	Print a selectivity	115
11.2.16	Print the random number seed used	116
11.2.17	Print mean size at age	116
11.2.18	Print mean weight at size	117
11.2.19	Print mean weight at age	117
11.2.20	Printing the results of an MCMC	118
12	Other commands and subcommands	119
13	Examples	121
13.1	An example of a simple 1×1 non-spatial model	121
14	Post processing output using R	125
15	Troubleshooting	127
15.1	Introduction	127
15.2	Reporting errors	127
15.3	Guidelines for reporting a bug in SPM	127
16	Acknowledgements	129
17	Quick reference	131
17.1	Population command and subcommand syntax	131
17.2	Estimation command and subcommand syntax	139
17.3	Observation command and subcommand syntax	141
17.4	Report command and subcommand syntax	143
17.5	Other commands and subcommands	146
18	References	147
19	Spatial Population Model software license	149
20	Index	151

1. Introduction

SPM (Spatial Population Model) is a generalised spatially explicit age-structured population dynamics and movement model. SPM can model population dynamics and movement parameters for an age-structured population using a range of observations, including tagging, relative abundance, and age frequency data. SPM implements an age-structured population within an arbitrary shaped spatial structure, which can have user defined categories (e.g., immature, mature, male, female, etc.), and age range.

This manual describes how to use SPM, including how to run SPM, how to set up an input configuration file. Further, we describe the population dynamics and estimation methods, and describe how to specify and interpret output.

1.1. Version

This document (last modified 2012-07-11) describes SPM v1.1-2012-07-12 (rev. 4728) . The SPM version number is suffixed with a date/time (yyyy-mm-dd) and revision number, giving the revision control system UTC date and revision number for the most recent modification of the source files. User manual updates will usually be issued for each minor version or date release of SPM, and can be obtained, on request, from the authors.

1.2. Citing SPM

A suitable reference for SPM and this document is:

Dunn, A.; Rasmussen, S.; Mormede, S. (2012) Spatial Population Model User Manual, SPM v1.1-2012-07-12 (rev. 4728) . National Institute of Water & Atmospheric Research Ltd. *Unpublished report*. 163 p.

1.3. Software license

This program and the accompanying materials are made available under the terms of the Common Public License v1.0 which accompanies this software (see Section 19).

Copyright ©2008-2012, National Institute of Water & Atmospheric Research Ltd. and the New Zealand Ministry for Primary Industries. All rights reserved.

1.4. System requirements

SPM is available for most IBM compatible machines running 64-bit Linux and Microsoft Windows operating systems.

Several of SPMs tasks are highly computer intensive and a fast processor is recommended. We recommend a minimum of 10 megabytes of free RAM (although, depending on the scope of the problem, you may need more). The program itself requires only a few megabytes of hard-disk space but output files can consume large amounts of disk space. Depending on number and type of user output requests, the output could range from a few hundred kilobytes to several hundred megabytes. However, we note that, depending on the model implemented, some of SPMs tasks can take a considerable amount of time.

1.5. Necessary files

For both 64-bit Linux and Microsoft Windows, only the executable file `spm` or `spm.exe` is required to run SPM. No other software is required. We do not compile a version for 32-bit operating systems.

SPM offers little in the way of post-processing of the output, and a package available that allows tabulation and graphing of model outputs is recommended. We suggest software such as Microsoft Excel, S-Plus, or **R** (R Development Core Team 2007). To assist in the post processing of SPM output, we provide the `spm` **R** package for importing the SPM output into R (see Section 14).

1.6. Getting help

SPM is distributed as unsupported software, however we would appreciate being notified of any problems or errors in SPM. See Section 15.2 for how to report errors to the authors. Further information about SPM can be obtained by contacting the authors.

1.7. Technical details

SPM was compiled on Linux using `gcc`, the C/C++ compiler developed by the GNU Project. The 64-bit Linux version was compiled using `gcc` version 4.1.2 20070115 (prerelease) (SUSE Linux). Note that SPM is not supported for Linux kernel versions prior to 2.6. The Microsoft Windows version was compiled using Mingw32 `gcc` (tdm-1) 4.6.1. The Microsoft Windows installer was built using the Nullsoft Scriptable Install System.

SPM uses two minimisers — the first is closely based on the main algorithm of Dennis Jr and Schnabel (1996), and which uses finite difference gradients, and the second is an implementation of the differential evolution solver (Storn and Price, 1995), and based on code by Lester E. Godwin of PushCorp, Inc. The random number generator used by SPM uses an implementation of the Mersenne twister random number generator (Matsumoto and Nishimura, 1998). This, the command line functionality, matrix operations, and a number of other functions use the BOOST C++ library (Version 1.48.0).

Note that the output from SPM may differ slightly on the different platforms due to different precision arithmetic or other platform dependent implementation issues. The source code for SPM is available either as a part of the installation, or on request from the authors.

2. Model overview

2.1. Introduction

The Spatial Population Model (SPM) is a generalised spatially explicit age-structured population dynamics and movement model. It allows the implementation of age-structured population models suitable for the simulation and estimation of parameters in models with a large number of areas. It implements a statistical catch-at-age population dynamics and movement model, using a discrete time-step state-space model that represents a cohort-based population age structure in a spatially explicit manner.

SPM is run from the console window on Microsoft Windows or from a terminal window on Linux. SPM gets its information from input data files, the main one of which is the *input configuration file*. Commands and subcommands in the input configuration file are used to define the model structure, provide observations, define parameters, and define the outputs (reports) for SPM. Command line switches tell SPM the run mode and where to direct its output. See Section 3 for the details.

The basic structure of an SPM model is a set of spatial cells, each of which contains a population. We define the model in terms of the *state*. The state consists of two parts, the *partition*, and any *derived quantities* or *derived meta-layers*. The state will typically change one or more times in every *time-step* of every year, depending on the *processes* defined for each model.

The partition is a representation of the population at an instance in time, and is a matrix of the numbers of individuals within each spatial cell, age, and category. A derived quantity is a cumulative summary of the partition at some point in time. A derived meta-layer is a cumulative summary of the partition in each of the cells at some point in time. Unlike the partition (which is updated as each new process is applied), each derived quantity records a single value for each year of the model run, and each derived meta-layer records a layer of values for each year of the model run. Hence, derived quantities build up a vector of values over the model run years, and derived meta-layers build up a list of layers over the model run years. For example, the total number of individuals in a category labelled mature at some point in the annual cycle may be a derived quantity and the total number of individuals in a category labelled mature in each cell of the model at some point in the annual cycle may be a derived meta-layer. The state is the combination of the partition and any derived quantities or derived meta-layer at some instance in time. Changes to the state occur by the application of processes. Additions to the vectors of derived quantities occur when a model is requested to add a value to each derived quantity vector.

Running of the model consists of two main parts — first the model state is initialised for a number of iterations (years), then the model runs over a range of predefined years.

The application of processes within each year is controlled by the *annual cycle*. This defines what processes happen in each model year, and in what sequence. Initialisation can be phased, and for each phase, the user need to define the processes that occur in each year, and the order in which they are applied.

For the run years, each year is split up into one or more time-steps (with at least one process occurring in each time-step). You can think of each time-step as representing a particular part of the calendar year, or you can just treat them as an abstract sequence of events.

The division of the year into an arbitrary number of time-steps allows the user to specify the exact order in which processes occur and when observations are evaluated. The user specifies the time-steps, their order, and the processes within each time-step. If more than one process occurs in the same time-step, then they occur in the order that they are specified. Observations are always evaluated at the end of the time-step in which they occur. Hence, time-steps can be used to break processes

into groups, and assist in defining the timing of the observations within the annual cycle.

An SPM model can be parametrised by both population processes (for example, ageing, recruitment, and mortality) and movement processes. Movement is parameterised by either adjacent cell movements, between cell migrations, or by global movements as a function of known attributes at each spatial location (termed preference functions — see later). SPM is designed to be flexible and to allow for the estimation of both population and movement parameters from local or aggregated spatially explicit observations.

The population structure of SPM follows the usual population modelling conventions and is similar to those implemented in other population models, for example CASAL (Bull et al., 2012). The model records the numbers of individuals by age and category (e.g., male, female), as well as the locations of these cohorts within a spatial grid. In general, cohorts are added via a recruitment event, are aged annually, and are removed from the population via various forms of mortality. The population is assumed to be closed (i.e., no immigration or emigration from the modelled area)

A model is implemented in SPM using an input configuration file, which is a complete description of the model structure (i.e., spatial and population processes), observations, estimation methods, and reports (outputs) requested. SPM runs from a console window on Microsoft Windows or from a text terminal on Linux. A model can be either *run*, estimable parameters can be *estimated* or *profiled*, MCMC distributions calculated, and these estimates can be used by SPM as parameters of an operating model to *simulate* observations.

A model in SPM is specified by an input configuration file, and comprises of four main components. These are the population section (model structure, population and spatial dynamics, etc.), the estimation section (methods of estimation and the parameters to be estimated), the observation section (observational data and associated likelihoods), and the report section (printouts and reports from the model). The input configuration file completely describes a model implemented in SPM. See Sections 8, 9, 10, and 11 for details and specification of SPMs command and subcommand syntax within the input configuration file.

2.2. The population section

The population section (Section 4) defines the model of the movement and population dynamics. It describes the model structure (both the spatial and population structure), initialisation and run years (model period), population and movement processes (for example, recruitment, migration, and mortality), layers (the known attributes of each spatial cell), selectivities, and key population parameters.

2.3. The estimation section

The estimation section (Section 5) specifies the parameters to be estimated, estimation methods, penalties and priors. Estimation is based on an objective function (e.g., negative log posterior). Depending on the run mode, the estimation section is used to specify the methods for finding a point estimate (i.e., the set of parameter values that minimizes the objective function), doing profiles, or MCMC methods and options, etc.

Further, the estimation section specifies the parameters to be estimated within each model run and the estimation methods. The estimation section specifies the choice of estimation method, which model parameters are to be estimated, priors, starting values, and minimiser control values.

Penalties and priors act as constraints on the estimation. They can either encourage or discourage (depending on the specific implementation) parameter estimates that are ‘near’ some value, and

hence influence the estimation process. For example, a penalty can be included in the objective function to discourage parameter estimates that lead to models where the recorded catch was unable to be fully taken.

2.4. The observation section

Types of observations, their values, and the associated error structures are defined in the observation section (Section 6). Observations are data which allow us to make inferences about unknown parameters. The observation section specifies the observations, their errors, likelihoods, and when the observations occur. Examples include relative or absolute abundance indices, proportions-at-age frequencies, etc. Estimation uses the observations to find values for each of the estimated parameters so that each observation is ‘close’ (in some mathematical sense) to a corresponding expected value.

2.5. The report section

The report section (Section 7) specifies the model outputs. It defines the quantities and model summaries to be output to external files or to the standard output. While *SPM* will provide informational messages to the screen, the *SPM* will only produce model estimates, population states, and other data as requested by the report section. Note that if no reports are specified, then no output will be produced.

3. Running SPM

SPM is run from the console window (i.e., the DOS command line) on Microsoft Windows or from a terminal window on Linux. SPM gets its information from input data files, the key one of which is the input configuration file.

The input configuration file is compulsory and defines the model structure, processes, observations, parameters (both the fixed parameters and the parameters to be estimated), and the reports (outputs) requested. The following sections describe how to construct the SPM configuration file. By convention, the name of the input configuration file ends with the suffix `.spm`, however, any file name is acceptable.

Other input files can, in some circumstances, be supplied to define the starting point for an estimation or as a point estimate from which to simulate observations.

Simple command line arguments are used to determine the actions or *tasks* of SPM, i.e., to run a model with a set of parameter values, estimate parameter values (either point estimates or MCMC), project quantities into the future, simulate observations, etc.. Hence, the *command line arguments* define the *task*. For example, `-r` is the *run*, `-e` is the *estimation*, and `-m` is the *MCMC* task. The *command line arguments* are described in Section 3.4.

3.1. Using SPM

To use SPM, open a console (i.e., the command prompt) window (Microsoft Windows) or a terminal window (Linux). Navigate to a directory of your choice, where your input configuration files are located. Then type `spm` with any arguments (see Section 3.4 for the the list of possible arguments). SPM will print output to the screen and return you to the command prompt when it completes its task. Note that the SPM executable (binary) must be either in the directory where you run it or somewhere in your `PATH`. Note that an automated installer is available for SPM on Microsoft Windows. If you use the installer, then it will give you the option of modifying your `PATH` for you (as well a a number of other options to make using the program a little easier). Otherwise, see your operating system documentation for help on identifying or modifying your `PATH`.

3.2. The input configuration file

The input configuration file is made up of four broad sections; the description of the population structure and parameters (the population section), the estimation methods and variables (the estimation section), the observations and their associated likelihoods (the observation section), and the outputs and reports that SPM will return (the report section). The input configuration file is made up of a number of commands (many with subcommands) which specify various options for each of these components.

The command and subcommand definitions in the input configuration file can be extensive (especially when you have a model with a large spatial structures that has many layers and/or observations), and can result in a input configuration file that is long and difficult to navigate. To aid readability and flexibility, we can use the input configuration file command `@include file`. The command causes an external file, *file*, to be read and processed, exactly as if its contents had been inserted in the main input configuration file at that point. The file name must be a complete file name with extension, but can use either a relative or absolute path as part of its name. Note that included files can also contain `@include` commands — but be careful that you do not set up a recursive state. See Section 12 for more detail.

3.3. Redirecting standard output

SPM uses the standard output stream `standard output` to display run-time information. The standard error stream is used by SPM to output the program exit status and run-time errors. We suggest redirecting both the standard output and standard error into files. With the bash shell (on Linux systems), you can do this using the command structure,

```
(spm [arguments] > out) >& err &
```

It may also be useful to redirect the standard input, especially if you're using SPM inside a batch job software, i.e.

```
(spm [arguments] > out < /dev/null) >& err &
```

On Microsoft Windows systems, you can redirect to standard output using,

```
spm [arguments] > out
```

And, on some Microsoft Windows systems (e.g., Windows7), you can redirect to both standard output and standard error, using the syntax,

```
spm [arguments] > out 2> err
```

Note that SPM outputs a few lines of header information to the output. The header consists of the program name and version, the arguments passed to SPM from the command line, the date and time that the program was called (derived from the system time), the user name, and the machine name (including the operating system and the process identification number). These can be used to track outputs as well as identifying the version of SPM used to run the model.

3.4. Command line arguments

The call to SPM is of the following form.:

```
spm [-c config_file] [task] [options]
```

-c *config_file* Define the input configuration file for SPM. If omitted, then SPM looks for a file named `config.spm`.

and where *task* is one of;

-h Display help (this page).

-l Display the reference for the software license (CPLv1.0).

-v Display the SPM version number.

-r Run the model once using the parameter values in the input configuration file, or optionally, with the values from the file denoted with the command line argument `-i file`.

-e Do a point *estimate* using the values in the input configuration file as the starting point for the parameters to be estimated, or optionally, with the start values from the file denoted with the command line argument `-i file`.

- p** Do a likelihood *profile* using the parameter values in the input configuration file as the starting point, or optionally, with the start values from the file denoted with the command line argument `-i file`.
- m** Do an *MCMC* estimate using the values in the input configuration file as the starting point for the parameters to be estimated, or optionally, with the start values from the file denoted with the command line argument `-i file`. (*not yet implemented*).
- s number** Simulate the *number* of observation sets using values in the input configuration file as the parameter values, or optionally, with the values for the parameters denoted as estimated from the file with the command line argument `-i file`.

In addition, the following are optional arguments [*options*],

- i file** Input one or more sets of estimated parameter values from *file*. See Section 11.2.7 for details about the format of *file*.
- q** Run *quietly*, i.e., suppress verbose printing of SPM.
- g seed** Seed the random number *generator* with *seed*, a positive (long) integer value. Note, if `-g` is not specified, then SPM will generate a random number seed based on the computer clock time.

3.5. Constructing an SPM input configuration file

The model definition, parameters, observations, and reports are specified in an input configuration file. The population section is described in Section 4 and the population commands in Section 8. Similarly, the estimation section is described in Section 5 and its commands in Section 9, and in Section 7 and Section 11 for the report and report commands.

3.5.1. Commands

SPM has a range of commands that define the model structure, processes, observations, and how tasks are carried out. There are three types of commands,

1. Commands that have an argument and do not have subcommands (for example, `@include file`)
2. Commands that have a label and subcommands (for example `@process`)
3. Commands that do not have either a label or argument, but have subcommands (for example `@model`)

Commands that have a label must have a unique label, i.e., the label cannot be used on more than one command of that type. The labels must start with a letter or underscore, can contain letters, underscores, or numbers. Labels must not contain white-space, a full-point ('.'), or other characters that are not letters, numbers, or an underscore.

3.5.2. Subcommands

Subcommands in SPM are for defining options and parameter values for commands. They always take an argument which is one of a specific *type*. The types acceptable for each subcommand are defined in Section 8.10.10, and are summarised below.

Like commands (`@command`), subcommands and their arguments are not order specific — except that all subcommands of a given command must appear before the next `@command` block. SPM may report an error if they are not supplied in this way, however, in some circumstances a different order may result in a valid, but unintended set of actions, leading to possible errors in your expected results.

The arguments for a subcommand are either,

switch true/false

integer an integer number

integer vector a vector of integer numbers

integer range a range of integer numbers separated by a hyphen (-), for example 1994-1996 2000 is expanded to an integer vector of values 1994 1995 1996 2000).

constant a real number (i.e., double)

constant vector a vector of real numbers (i.e., vector of doubles)

estimable a real number that can be estimated (i.e., estimable double)

estimable vector a vector of real numbers that can be estimated (i.e., vector of estimable doubles)

string a categorical (string) value

string vector a vector of categorical values

Switches are parameters which are either true or false. Enter *true* as true or t, and *false* as false or f.

Integers must be entered as integers (i.e., if year is an integer then use 2008, not 2008.0)

Arguments of type integer vector, integer range, constant vector, estimable vector, or categorical vector contain one or more entries on a row, separated by white space (tabs or spaces).

Estimable parameters are those parameters that SPM can estimate, if requested. If a particular parameter is not being estimated in a particular model run, then it acts as a constant. Within SPM only estimable parameters can be estimated. And, you have to tell SPM those that are to be estimated in any particular model. Estimable parameters that are being estimated within a particular model run are called the *estimated parameters*.

3.5.3. The command-block format

Each command-block either consists of a single command (starting with the symbol `)` and, for most commands, a label or an argument. Each command is then followed by its subcommands and their arguments, e.g.,

`@command`, or

`@command argument`, or

`@command label`

and then

subcommand argument

subcommand argument

etc.,

Blank lines are ignored, as is extra white space (i.e., tabs and spaces) between arguments. But don't put extra white space before a @ character (which must also be the first character on the line), and make sure the file ends with a carriage return.

There is no need to mark the end of a command block. This is automatically recognized by either the end of the file, section, or the start of the next command block (which is marked by the @ on the first character of a line). Note, however, that the @include is the only exception to this rule. See Section 12) for details of the use of @include.

Note that in the input configuration file, commands, sub-commands, and arguments are not case sensitive. However, labels and variable values are case sensitive. Also note that if you are on a Linux system then external calls to files are case sensitive (i.e., when using @include *file*, the argument *file* will be case sensitive).

Characters used in labels must be alphanumeric and can include underscores (_). Other characters will result in an error.

3.5.4. Commenting out lines

Text that follows a # on a line are considered to be comments and are ignored. If you want to remove a group of commands or subcommands using #, then comment out all lines in the block, not just the first line.

Alternatively, you can comment out an entire block or section by placing curly brackets around the text that you want to comment out. Put in a { as the first character on the line to start the comment block, then end it with }. All lines (including line breaks) between { and } inclusive are ignored. (These should ideally be the first character on a line. But if not, then the entire line will be treated as part of the comment block.)

3.5.5. Determining parameter names

When SPM processes a input configuration file, it translates each command and each subcommand into a parameter with a unique name. For commands, this parameter name is simply the command name. For subcommands, the parameter name format is either,

`command[label].subcommand` if the command has a label, or

`command.subcommand` if the command has no label, or

`command[label].subcommand(i)` if the command has a label and the subcommand arguments are a vector, and we are accessing the *i*th element of that vector.

`command[label].subcommand(i-j)` if the command has a label, and the subcommand arguments are a vector, and we are accessing the elements from *i* to *j* (inclusive) of that vector. (*not yet implemented*).

The unique parameter name is used to reference the parameter when estimating, applying a penalty, or applying a profile. For example, the parameter name of subcommand `r0` of the command `@process` with the label `MyRecruitment` is,

`process[MyRecruitment].r0`

3.6. SPM exit status values

When *SPM* completes its task successfully or errors out gracefully, it returns a single exit status value (0) to the operating system. The operating system will return (−1) if *SPM* terminates unexpectedly. To determine if *SPM* has completed its task successfully, check the standard output for error and information messages.

4. The population section

4.1. Introduction

The population section specifies the model structure, movement and population dynamics, and other associated parameters. It describes the model structure (both the spatial and population structure), defines the population (for example, recruitment, migration, and mortality) and movement processes, defines the layers (the known attributes of each spatial cell), selectivities, and model parameters.

The population section consists of several components, including;

- The spatial and population structure
- Model initialisation (i.e., the state of the model at the start of the first year)
- The years over which the model runs (i.e., the start and end years of the model)
- The annual cycle (time-steps and processes that are applied in each time-step)
- The specifications and parameters of the processes;
 - Population processes (i.e., processes that add, remove individuals to or from the partition, or shift numbers between ages and categories in the partition)
 - Spatial processes (i.e., processes that move or shift cohorts between spatial locations but do not alter their ages or categories)
- Layers (used by processes, observations and reports) and their definitions
- Selectivities
- Parameter values and their definitions
- Derived layers, meta-layers and quantities required as parameters for some processes (i.e., spawning stock biomass to resolve the spawner-recruit relationship in a recruitment process)

4.2. Spatial structure

The spatial structure of SPM is represented by an $n_{rows} \times n_{cols}$ grid, with rows $i = 1 \dots n_{rows}$ and columns $j = 1 \dots n_{cols}$. Each cell of this matrix records the population structure at that point in space, where the population structure is represented by an $n_{categories} \times n_{ages}$ rectangular matrix (with categories $k = 1 \dots n_{categories}$ and ages $l = 1 \dots n_{ages} = age_{min} \dots age_{max}$). Hence we can describe any spatial and population element of the model as $element(i, j, k, l)$. We define, within the spatial grid ($n_{rows} \times n_{cols}$), locations where the population can and cannot potentially be present using a *layer*.

SPM implements a single spatial structure, a grid of *square* cells (Figure 4.1). The spatial grid can be of an arbitrary size, but must be rectangular.

The dimensions of the spatial grid are user defined but must be at least a 1×1 grid (i.e., a single spatial cell), and the largest spatial structure currently allowed by SPM is a grid of 1000×1000 cells – although we note that models of this size are untested and will probably have very long run times.

Associated with the $n_{rows} \times n_{cols}$ spatial structure is the one compulsory layer (see Section 4.4), the *base layer*. This defines the locations where the population can and cannot potentially be present (e.g., in a marine model, the locations associated with the sea and not land). These are defined as the cells where the base layer has a value greater than zero. There must be at least one cell in the spatial grid where the population can be present. In addition, the base layer also defines the relative *area* of each spatial cell that is used for density calculations within SPM.

	Col 1	Col 2	Col 3	Col 4
Row 1	(1,1)	(1,2)	(1,3)	(1,4)
Row 2	(2,1)	(2,2)	(2,3)	(2,4)
Row 3	(3,1)	(3,2)	(3,3)	(3,4)

Figure 4.1: An illustration of the spatial structure

Models are implemented as a grid of square cells making up a rectangular matrix. Distance between cells is determined as the euclidean distance between cell centres, modified by an arbitrary scalar.

Hence, the definition of the spatial structure includes;

- The type of spatial grid and its dimensions, n_{rows} and n_{cols}
- The label of a numeric layer to be used as the base layer (defining the locations where the population can be present as well as the area of each cell)
- The length (distance) of a side of the grid cell to be used as the scaler for distance calculations

4.3. Population structure

The population structure in SPM is represented by a matrix containing an arbitrary number of user defined categories (rows), and an arbitrary age range (columns). Hence, each spatial cell has a population state described as $n_{categories} \times n_{ages}$ rectangular matrix with categories $k = 1 \dots n_{categories}$ and ages $l = age_{min} \dots age_{max}$.

The names and number of categories are user defined, but there must be at least one category defined for a model. The ages are defined as a sequence from age_{min} to age_{max} , with the last age optionally a plus group. In order to calculate bio mass, the age-size relationship for each category must also be defined.

Hence, the definition of the population structure includes;

- The number and labels of the categories, $k_{categories}$
- The age_size relationship for each category
- The minimum and maximum ages that define the ages of the model, l_{ages}
- If the last age is a plus group

4.4. Layers

Layers are used by SPM to evaluate locations where the population may be present (via the *base layer*), to provide sets of known attributes of each spatial location (for preference based movements), and to group or categorise cells for use by processes and observations. Layers consist of an $n_{rows} \times n_{cols}$ matrix and can be either *numeric* or *categorical*. See Section 4 for further details.

Layers are a key underlying concept in SPM. They comprise of a grid of known values, with a value for every spatial cell in the model. Layers are used by processes, observations, and outputs commands to supply spatially explicit covariates and any categorical groupings required.

Every model must define at least one layer, the base layer L_B . A layer is defined as a $n_{rows} \times n_{cols}$ matrix of values (albeit with one exception — the distance layer — which we describe below), where the value in each cell represents a known quantity. For example layers may represent classifications, physical attributes, or some other known or assumed quantity. Typically they are provided by the user as a matrix of values, although some layer (e.g., abundance and distance layers) can be calculated by SPM during a model run.

Within SPM, layers are used in three contexts:

1. The base layer: The base layer L_B is a special layer (there must be exactly one base layer defined within the model) that defines the locations where the population can and cannot potentially be present (e.g., locations associated with the sea and not land in a marine model). Here, we define that a cell may potentially have part of the population present if every element $L_B(i, j) \geq 0$. Further, positive values of the base layer L_B represent the *area* represented by that spatial cell.
2. Covariate layers: A model may have many covariate layers, and these are used as covariates of some population or movement process (e.g., the sea floor depth may be a covariate of some movement process). The values in layers used as covariates can be numeric or categorical.
3. Classification layers: A model may have many classification layers, and these are used as a classification or grouping variable for aggregating data over individual spatial cells (i, j) , e.g., statistical areas or management areas. Such layers are typically used to aggregate the population within cells into groups so-as to allow comparison with observations. The values in layers used as classification layers must be categorical.

SPM defines the following types of layer;

1. Numeric layers: A model may have many numeric layers, and these can be used as covariates of a population or movement process (e.g., depth may be a covariate of some movement process), and/or locations of event mortality. Numeric layers can contain only continuous (numeric) variables. Values for a numeric layer must be supplied for each cell by the user.
2. Categorical layers: A model may have many categorical layers, and these can be used as a classification or grouping variable for aggregating data over individual cells, e.g., management areas; or as covariates of a population or movement process. Such layers are typically used to aggregate the population within cells into groups for comparing with observations, or to apply specific movement characteristics. The values in layers used as categorical layers can contain any characters (except white space), and are interpreted as categorical values. Values for a categorical layer must be supplied for each cell by the user.
3. Distance layers: A distance layer is one that defines the distance between any two cells. By default, SPM calculates the values of the distance layer as the Euclidean distance (where the

grid type is square). Here, the distance between cell a and cell b can be defined as,

$$d(a, b) = \lambda \sqrt{(x_a - x_b)^2 + (y_a - y_b)^2} \quad (4.1)$$

where x and y represent the x - and y -coordinates of a and b respectively, and λ is an arbitrary scalar representing the length of one side of the square. Unlike other types of layers, distance layers are not a $n_{rows} \times n_{cols}$ grid of values, but rather a matrix of dimension $(n_{rows} \times n_{cols}) \times (n_{rows} \times n_{cols})$ where the distance between each cell and every other cell is evaluated. Note that under this definition, the distance between any cell and itself is 0.

4. Abundance layers: The abundance layer is the sum of the number of individuals within cell a in categories k and with selectivity S_l at age l .

$$N(a) = \sum_k \sum_l S_l \text{element}(i, j, k, l) \quad (4.2)$$

SPM calculates the values of the layer when running the model at the point in time where the value is required.

5. Biomass layers: The biomass layer is the sum of the biomass of individuals within cell a in categories k , with selectivity S_l at age l , and mean weight w_{kl}

$$N(a) = \sum_k \sum_l w_{k,l} S_l \text{element}(i, j, k, l) \quad (4.3)$$

SPM calculates the values of the layer when running the model at the point in time where the value is required.

6. Abundance-density layers: The abundance density layer is the density of the number of individuals within cell a with area A_a in categories k , with selectivity S_l at age l ,

$$N(a) = \frac{1}{A_a} \sum_k \sum_l S_l \text{element}(i, j, k, l) \quad (4.4)$$

SPM calculates the values of the layer when running the model at the point in time where the value is required.

7. Biomass-density layers: The biomass-density layer is the density of the biomass of individuals within cell a with area A_a in categories k , with selectivity S_l at age l , and mean weight w_{kl} ,

$$N(a) = \frac{1}{A_a} \sum_k \sum_l w_{k,l} S_l \text{element}(i, j, k, l) \quad (4.5)$$

SPM calculates the values of the layer when running the model at the point in time where the value is required.

To be implemented

8. Meta-layers: In addition to the above types of layer, SPM defines a special type of layer known as a *meta-layer*. The meta-layer allows individual layers (of the same type) to be indexed by year, and applied as a single layer within the model. For example, assume that we had a model where we wished to use Sea Surface Temperature (SST) as a layer, perhaps to control some movement process. The SST values for each year of the model would be defined as individual numeric layers, each with a unique label. We could then define a meta-layer that indexed the individual annual SST layers by year, and use the meta-layer as the control layer in the movement process. Meta-layers must have exactly the same number of years as the model runs as well as layers for the initialisation phase and prediction phase (interpolation or extrapolation are not permitted). Meta layers can be used in the place of layers, and SPM will extract the layer corresponding to the year being run.

9. **Derived layers and derived meta-layers:** SPM calculates the value of a derived layer or a derived meta-layer at a user-defined point in time each year, with a user-defined formula. The calculation can include other layers and estimable parameters. Derived layers will only retain the latest values whereas derived meta-layers will retain values for all years calculated. Note that layers of type biomass, quantity, and distance are specific forms of derived layers calculated by SPM. For example, for the distance layer in a square grid, the distance between cell a and cell b is defined as proportional to $\sqrt{(x_a - x_b)^2 + (y_a - y_b)^2}$, where x and y represent the x - and y -coordinates of a and b respectively. For the abundance (or biomass) layer, the abundance (or biomass) of a cell is simply a count of the number (or biomass) of individuals in the cell a within categories K , with selectivity S , e.g., $N(a) = \sum_k \sum_i \text{element}(i, j, k, l)$.

4.5. Time sequences

The time sequence of the model is defined in three parts;

- Initialisation
- Run years

4.5.1. Annual cycle

The annual cycle is implemented as a set of processes that occur, in a user-defined order, within each year. time-steps are used to break the annual cycle into separate components, and allow observations to be associated with different sets of processes. Any number of processes can occur within each time-step, in any order and can occur multiple times within each time-step. Note that time-steps are not implemented during the initialisation phases (effectively, there is only one time-step), and that the annual cycle in the initialisation phases can be different from that which is applied during the model years.

4.5.2. Initialisation

Model initialisation can occur in several phases, each which iterates through a number of years carrying out the population and/or spatial processes defined for that phase. At the end of the initialisation step, SPM runs through the model years carrying out processes in the order defined in the annual cycle, and can evaluate expected values of observations in order to calculate likelihoods, or simulate observations from the current state.

SPM initialises the initial equilibrium state as an iterative process, because a general solution that initialises complex structured movement models can be difficult to implement using analytic techniques. However, initialising via iteration for a long-lived species with complex movements can take many iterations, and be slow to run. In SPM, we allow for user-defined multi-phased initialisation using iteration to allow the user to optimize models for speed. Each phase of the initialisation can involve any number of population and/or movement processes.

In each initialisation phase, the processes defined for that phase are carried out and used as the starting point for the following phase or, if it is the last phase, then the years that the model is run over. The first phase is always initialised with each element (i.e., each age and category within each spatial cell) set at zero. Note that this means that recruitment processes where the numbers of recruits is based on a stock recruitment or density dependant relationship will likely fail if used in the first phase of an initialisation.

The multi-phase iteration also allows the user to determine if the initialisation has converged in a particular model run. Here, add an additional initialisation phase for, say, 1 year as the last initialisation phase (with the same processes applied). Then, using the initialisation reports (`@report[label].type=initialisation_phase`), print a copy of the partition just before and just after that phase. If the initialisation has converged to an equilibrium state, then the partition at both these time intervals will be the same.

Hence, for initialisation you need to define;

- The initialisation phases
- The number of years in each phase and the processes to apply in each

4.5.3. Model years

Following initialisation, the model then runs over a number of user-defined years. For this part of the model, the annual cycle can be broken into separate time-steps, and observations can be associated with the state of the model at the end of any time-step, i.e., likelihoods for particular observations are evaluated, if required, at the end of each time-step.

Processes are carried out in the order specified within each time-step, and can be the same or different to processes in other initialisation phases of the model. The run years define the years over which the model is to run and the annual cycle within each year. The model runs from the start of year `initial` and runs to the end of year `current`.

- The time-steps and the processes applied in each
- The initial year (i.e., the model start year)
- The current year (i.e., the model end year)

4.6. Processes

Processes produce changes in the model partition, by adding, removing or moving individuals between spatial cells (movement processes), and ages or categories (population processes). These include processes such as recruitment, mortality, ageing, and various forms of movement.

SPM has two types of processes, *population* and *movement* processes. Population processes are those processes which modify, move or otherwise change the numbers of individuals *within* a spatial cell, i.e., they do not affect the spatial location of a cohort. Movement processes, on the other hand, move, shift or otherwise modify cohorts *between* spatial cells, but do not affect the age or category of the numbers in each cohort.

The population processes include recruitment, ageing, mortality events (e.g., natural and exploitation) and category transition processes (i.e., processes that move individuals between categories, while preserving their age structure). See Section 4 for a complete list of available processes.

Each of these processes is carried out in the user-defined prescribed order when initialising the model, and then for a user-defined order in each year in the annual cycle.

SPM implements three different types of movement processes;

1. A migration movement rate of cohorts between any two locations, and is roughly analogous to movements between areas as implemented in other population models, such as CASAL (Bull et al., 2012).

2. An adjacent cell movements, parametrised by some function of an underlying layer — equivalent to, for example, movement processes implemented in Fish Heaven (Ball and Constable, 2000, Ball and Williamson, 2003).
3. Movement parametrised as a probability density function. Here, the key underlying idea is that the spatial distribution of cohorts at any point in time and at any location can be represented as a density function based on attributes of that location, local abundance, and/or distance from their previous location (Bentley et al., 2004a,b).

An SPM model can be parametrised by both population processes (for example, ageing, recruitment, and mortality), and movement processes. Population processes are those processes which modify, move or otherwise change the numbers of individuals within a spatial cell, i.e., they do not affect the spatial location of a cohort. Movement processes, on the other hand, move, shift or otherwise modify cohorts between spatial cells, but do not affect the age or category of the numbers in each cohort.

4.7. Population processes

Population processes are those processes that change the population state of individuals, but retain their location. The population processes are described below.

4.7.1. Recruitment

Recruitment processes are defined as process that introduces new individuals into the model. SPM implements three types of recruitment process, constant recruitment, Beverton-Holt recruitment (Beverton and Holt, 1957), and local Beverton-Holt recruitment.

In the recruitment processes, the number of individuals are added to a single age class within the partition, with the amount defined by the type of recruitment process and its function. If more than one category is defined, then the proportion of recruiting individuals to be added to each category is specified by the `proportions` parameter. For example, if recruiting to categories labelled male and female, then you might set the proportions as 0.5 and 0.5 respectively to denote that half of the recruits recruit to the male category and the remaining half to the female category.

For the constant and Beverton-Holt recruitment processes, the number of individuals in cell $\text{cell}(i, j)$ following recruitment in year y is,

$$\text{element}(i, j, k, l) \leftarrow \text{element}(i, j, k, l) + p_k(R_y/n) \frac{L_{ij}}{\sum_i j L_{ij}} \quad (4.6)$$

where age is the age defined as the recruitment age, p_k is the proportion recruitment to category k defined to have recruitment, n is the number of spatial locations where recruitment occurs, and the recruitment to each cell is scaled to be proportional to the value of the layer in that cell. See below for how R_y is determined in each of these cases.

In the local Beverton-Holt recruitment process, individuals are recruited to an individual cell, based on the local abundance or biomass (i.e., the local SSB). For each cell where $\text{cell}(i, j)$ is a member of some layer L_R , the number of individuals in that cell following recruitment in each year y is

$$\text{element}(i, j, k, l) \leftarrow \text{element}(i, j, k, l) + p_k R_y L_{ij} \quad (4.7)$$

where age is the age defined as the recruitment age, p_k is the proportion recruitment to category k defined to have recruitment, and the recruitment to each cell is the product of the Beverton-Holt stock recruitment relationship (R_y).

Constant Recruitment: In the constant recruitment process the total number of recruits added each year is R_y , and is simply R_0 , i.e.,

$$R_y = R_0 \quad (4.8)$$

It is equivalent to a Beverton-Holt recruitment process where steepness is set equal to one ($h = 1$).

For example, to specify a constant recruitment process, where individuals are added to the category ‘immature’ at $age = 1$, and the number to add is $R_0 = 5 \times 10^5$ in areas proportional to the value of the layer recruitment, then the syntax is,

```
@process Recruitment
type constant_recruitment
categories immature
proportions 1.0
R0 500000
age 1
layer recruitment
```

Beverton-Holt recruitment: In the Beverton-Holt recruitment process the total number of recruits added each year is R_y , and is the product of the average recruitment R_0 , the annual year class strength multiplier, YCS , and the stock-recruit relationship i.e.,

$$R_y = R_0 \times YCS_{y-offset} \times SR(SSB_{y-offset}) \quad (4.9)$$

where *offset* is the number of years offset to link the year class with the year of spawning y , and SR is the Beverton-Holt stock-recruit relationship parametrised by the steepness h ,

$$SR(SSB_y) = \frac{SSB_y}{B_0} / \left(1 - \frac{5h-1}{4h} \left(1 - \frac{SSB_y}{B_0} \right) \right) \quad (4.10)$$

Note that the Beverton-Holt recruitment process requires a value for B_0 and SSB_y to resolve the stock-recruitment relationship. Here, a derived quantity (see Section 4.9) must be defined that provides the annual SSB_y for the recruitment process. B_0 is then defined as the value of the SSB at the end of one of the initialisation phases. During initialisation the YSC multipliers are assumed to be equal to one, and recruitment that happens in the initialisation phases that occur before and during the phase when B_0 is determined is assumed to have steepness $h = 1$ (i.e. in those initialisation phases, recruitment is simply equal to R_0). Recruitment in the initialisation phases after the phase where B_0 was determined follow the Beverton-Holt stock-recruit relationship defined above. Recruits are then distributed across cells in proportion to the values in a numeric layer.

For example, assume a Beverton-Holt recruitment process, where individuals are added to the category ‘immature’ at $age = 1$, the number to add is $R_0 = 5 \times 10^5$ in areas proportional to the value of the layer `MyRecruitment`, B_0 is a derived quantity of total spawning stock biomass at the end of initialisation, SSB_y is a derived quantity labelled `SSB_biomass` that represents the spawning stock biomass in each year, with B_0 the value of the derived quantity at the end of the initialisation phase labelled `phase1`. The YCS are standardised to have mean one in the period 1994 to 2004, and recruits enter into the model two years following spawning. Then the command specification is,

```
@process Recruitment
type BH_recruitment
categories immature
```

```

proportions 1.0
R0 500000
steepness 0.75
age 1
layer MyRecruitment
B0 phase1
SSB SSB_biomass
standardise_YCS_years 1994-2004
YCS_years 1994 1995 1996 1997 1998 1999 2000 2001 2002 2003 2004 2005 2006
YCS_values 1 1 1 1 1 1 1 1 1 1 1 1 1
SSB_offset 2

```

Note that if not specified, *SSB_offset* is set at the value of *age*. This corresponds to cases where recruitment happens after spawning. *SSB_offset* can be user-defined to a different value if needed, such as if recruitment happens in a time-step before spawning, and therefore the offset is *age* + 1.

Local Beverton-Holt recruitment: The local Beverton-Holt recruitment process assumes that, for recruitment, each cell acts like a local population and is independent of its neighbours. The value of the SSB_y^i in each cell i for each year y is used to determine the amount of recruitment that enters that cell. If desired, locally recruits can subsequently be subjected to movement (see Section 4.8).

If the recruitment to cell i is R_y^i , then R_y^i is the product of the average recruitment R_0^i for that cell, the annual year class strength multiplier (assumed to be the same for all cells in each year), and the stock-recruit relationship, i.e.,

$$R_y^i = R_0^i \times YCS_{y-offset} \times SR(SSB_{y-offset}^i) \quad (4.11)$$

where *offset* is the number of years offset to link the year class with the year of spawning, and *SR* is the Beverton-Holt stock-recruit relationship parametrised by the steepness h and initial biomass B_0^i

$$SR(SSB^i) = \frac{SSB^i}{B_0^i} / \left(1 - \frac{5h-1}{4h} \left(1 - \frac{SSB^i}{B_0^i} \right) \right) \quad (4.12)$$

Note that the local Beverton-Holt recruitment process requires a value for B_0^i and SSB_y^i to resolve the stock-recruitment relationship. Here, layers (that probably should be abundance or biomass layers — see Section 4.10) must be provided for B_0 and the annual SSB_y for the recruitment process. B_0 is then defined as the value of the SSB at the end of one of the initialisation phases. During initialisation the YCS multipliers are assumed to be equal to one, and recruitment that happens in the initialisation phases that occur before and during the phase when B_0 is determined is assumed to have steepness $h = 1$ (i.e. in those initialisation phases, recruitment is simply equal to R_0). Recruitment in the initialisation phases after the phase where B_0 was determined follow the Beverton-Holt stock-recruit relationship defined above. R_0^i is defined for each cell as the portion of the total recruitment R_0 distributed relative to the recruitment layer `R0_layer`.

For example, assume a local Beverton-Holt recruitment process, where individuals are added to the category ‘immature’ at *age* = 1, the number to add is $R_0 = 5 \times 10^5$ multiplied by the proportional value of the layer `recruitment_layer`, B_0 is a derived layer that specifies the biomass in each cell of total spawning stock biomass at the end of initialisation, SSB_y is a derived quantity labelled `SSB_biomass` that represents the spawning stock biomass in each year, with B_0 the value of the derived quantity at the end of the initialisation phase labelled `phase1`. The YCS are standardised to have mean one in the period 1994 to 2004, and recruits enter into the model two years following spawning. Then the command specification is,

```
@process Recruitment
type local_BH_recruitment
categories immature
proportions 1.0
R0 500000
steepness 0.75
sigma_r 0.6 [not actually used yet]
rho 0.6 [not actually used yet]
age 1
R0_layer recruitment_layer
B0_layer B0_biomass_layer
SSB_layer mature_biomass_layer
standardise_ycs_years 1994-2004
YCS_years 1994 1995 1996 1997 1998 1999 2000 2001 2002 2003 2004 2005 2006
YCS_values 1 1 1 1 1 1 1 1 1 1 1 1 1
SSB_offset 1
```

Note that if not specified, *SSB_offset* is set at the value of *age*. This corresponds to cases where recruitment happens after spawning. *SSB_offset* can be user-defined to a different value if needed, such as if recruitment happens in a time-step before spawning, and therefore the offset is *age* plus one. In the example above, *SSB_offset* is equal to *age* and therefore could be omitted.

4.7.2. Ageing

The ageing process simply moves all individuals in the named categories to the next age class. The ageing process is defined as,

$$\text{element}(i, j, k, l) \leftarrow \text{element}(i, j, k, l - 1) \quad (4.13)$$

except that in the case of the plus group (if defined),

$$\text{element}(i, j, k, \text{age}_{\max}) \leftarrow \text{element}(i, j, k, \text{age}_{\max}) + \text{element}(i, j, k, \text{age}_{\max-1}). \quad (4.14)$$

For example, to apply ageing to the categories *immature* and *mature*, then the syntax is,

```
@process Ageing
type ageing
categories immature mature
```

Note that ageing is *not* applied by SPM by default. As with other processes, SPM will not apply a process unless its defined and specified as a process within the annual cycle. Hence, it is possible to specify a model where a category is not aged. SPM will not check or otherwise warn if there is a category defined where ageing is not applied.

4.7.3. Mortality

Four types of mortality processes are permissible in SPM, constant rate, annually varying rate, event, or biomass-event. These processes remove individuals from the partition, either as a rate (for constant or annually varying mortality processes), as a total number (abundance), or as a biomass of individuals. SPM does not implement the Baranov catch equation or any other process where both natural and event mortality are applied simultaneously. To approximate concurrent natural and

event mortality, the population processes must be defined to remove some natural mortality (e.g., as a constant or annually varying), then some event mortality (e.g., fishing) in sequence. It is up to the user to specify how this happens.

Mortality can depend on a layer. Here only one method of dependence is implemented, the multiplicative method. Here, the value of instantaneous mortality applied to the population state within each cell is the product of the layer value, a selectivity, and the mortality rate. If the layer is static, mortality is effectively constant each year but can be different in each cell; if the layer is a derived layer and therefore calculated each year, mortality can change every year in every cell. Complex mortality relationships such as density dependent predation mortality with prey selectivity can be applied through user-defined derived layers (see Section 4.10 for an example).

For example, to specify an constant annual mortality rate ($M = 0.2$) for categories ‘male’ and ‘female’, then,

```
@process NaturalMortality
type constant_mortality_rate
categories male female
selectivities One One
M 0.2 0.2
```

Note that the mortality rate process requires a selectivity. To apply the same mortality rate over all age classes, use a selectivity defined as $S_i = 1.0$ for all ages i , e.g.,

```
@selectivity One
type constant
c 1
```

A constant rate could also be defined as a multiplier of a layer. For example, let the mortality rate applied to the population at cell a in category k and age l be denoted $M(a, k, l)$, and given a value from a layer L_a at a , a constant mortality rate M , and a selectivity-at-age S_l at age l for some user-defined categories k then,

$$M(a, k, l) = ML_a S_l \quad (4.15)$$

And the resulting number of individuals remaining in cell a in category k at age l from applying the constant mortality process is,

$$n'(a, k, l) = n(a, k, l) \exp(-M(a, k, l)) \quad (4.16)$$

Mortality for the annual rate is similar to the constant rate, except that rate applied each year is a separate parameter, and is applied equally to all of the specified categories. For example, if annual rates were applied to males and females between 1996 and 2000, five values of M and the years that these apply to would need to be provided, e.g.,

```
@process AnnualMortality
type annual_mortality_rate
categories male female
selectivities One One
years 1996 1997 1998 1999 2000
M 0.20 0.15 0.22 0.25 0.21
```

The event mortality process and biomass mortality processes act in a similar manner, except that they remove a specified abundance (number of individuals) or biomass respectively, rather than applying mortality as a rate. However, the maximum abundance or biomass to remove is constrained by a maximum exploitation rate.

The event mortality types must be defined using a layer. Here, the abundance or biomass to remove from a the population for each cell a is the value of the layer at a (denoted F_a) — except where there are too few individuals for the event mortality to be taken (as defined by the maximum exploitation rate). In this scenario, SPM removes as many individuals or as much biomass as it can while not exceeding the maximum exploitation rate. Event mortality processes require a penalty function to discourage parameter values that do not allow a the defined number of individuals to be removed. Here, the model penalises those parameter estimates that result in an insufficient number of individuals in defined categories (after applying selectivities). See Section 5.8 for more information on specifying penalties.

For example, the event mortality applied to user-defined categories k , with the numbers removed at age l determined by a selectivity-at-age S_l is applied as follows:

First, calculate the vulnerable abundance for each category k in $1 \dots K$ for ages $l = 1 \dots L$ that are subject to event mortality,

$$V(k, l) = S(l)N(k, l) \quad (4.17)$$

And hence define the total vulnerable abundance V_{Total} as,

$$V_{Total} = \sum_K \sum_L V(k, l) \quad (4.18)$$

Hence the exploitation rate to apply is

$$U = \begin{cases} C/V_{total}, & \text{if } C/V_{total} \leq U_{max} \\ U_{max}, & \text{otherwise} \end{cases} \quad (4.19)$$

And the number removed R from each age l in category k is,

$$R(k, l) = UV(k, l) \quad (4.20)$$

For example, to specify fishing mortality based on spatially explicit catches (and given for each year as a layer, ‘Catch2000’, ‘Catch2001’, etc..) over categories ‘immature’ and ‘mature’ with selectivity ‘FishingSel’ and assuming a maximum possible exploitation rate of 0.7, then the syntax is,

```
@process Fishing
type event_mortality
categories immature mature
years 2000 2001 2002 2003
layers Catch2000 Catch2001 Catch2002 Catch2003
U_max 0.70
selectivities FishingSel FishingSel
penalty event_mortality_penalty
```

4.7.4. Category transitions

Category transition processes move individuals between categories. SPM implements two types, the total number and a rate.

The category transition process moves a number n between some source and sink category (or categories). This process may be used, for example, to implement a 'tagging' process for mark-recapture data. We define the transition process with selectivity S for source category a and sink category b as,

$$\begin{aligned} \text{element}(i, j, a, l) &\leftarrow \text{element}(i, j, a, l) - \frac{nS_l}{\sum_l S_l} \times \text{element}(i, j, a, l) \\ \text{element}(i, j, b, l) &\leftarrow \text{element}(i, j, b, l) + \frac{nS_l}{\sum_l S_l} \times \text{element}(i, j, a, l) \end{aligned} \quad (4.21)$$

Category transition processes require a penalty function to discourage parameter values that do not allow a the defined number of individuals to be moved. Here, the model penalises those parameter estimates that result in an insufficient number of individuals in the source category (after applying the selectivity) available to be moved. See Section 5.8 for more information on specifying penalties.

If multiple categories of sources or sinks are defined, then they must be defined in 'pairs'. The proportions of selected individuals in the source categories is used to define the proportions of individuals 'moved' to the sink categories, as defined by the order that they are specified. For example, to 'tag' a population of immature and mature individuals, then you might define a category transition process tagging with selectivities tagging-Sel, as,

```
@process tagging
type category_transition
from immature mature
selectivities tagging-Sel tagging-Sel
to immature-tag mature-tag
years 2001 2002 2003
layers TagRelease2001 TagRelease2002 TagRelease2003
penalty tag_release_penalty
```

Note that this syntax can be used to combine individuals, simply by repeating a category label when specifying the sink categories.

The transition rate type moves a proportion p between a source and sink category. The transition rate process with selectivity S for source category a and sink category b is,

$$\begin{aligned} \text{element}(i, j, a, l) &\leftarrow \text{element}(i, j, a, l) - pS_l \times \text{element}(i, j, a, l) \\ \text{element}(i, j, b, l) &\leftarrow \text{element}(i, j, b, l) + pS_l \times \text{element}(i, j, a, l) \end{aligned} \quad (4.22)$$

If multiple categories of sources or sinks are defined, then they must be defined in 'pairs'. SPM treats each pair of categories as an independent transition — but note that these are applied in order that they are specified. For example, to 'mature' males and females in a model with four categories male-immature, female-immature, male-mature, and female-mature, then you might define a category transition process maturation with selectivities male-maturity and female-maturity, as,

```
@process maturation
type category_transition_rate
from male-immature female-immature
to male-mature female-mature
proportions 1.0 1.0
selectivities male-maturity female-maturity
```

Note that this syntax can be used to combine individuals, simply by repeating a category label when specifying the sink categories. Similarly, individuals within a category can be split into more than one category by repeating a category label when specifying the source categories.

4.8. Movement processes

Movement processes are those processes that move individuals between cells but retain their population state, and are defined such that,

$$\text{element}(i, j, k, l) \leftarrow \text{element}(i, j, k, l) + p \times \text{element}(i', j', k, l) \quad (4.23)$$

i.e., each element in cell (i, j) is updated as the sum of itself and some proportion p of a neighbouring element in cell (i', j') . To conserve abundance we also update $\text{element}(i', j', k, l)$ as,

$$\text{element}(i', j', k, l) \leftarrow \text{element}(i', j', k, l) - p \times \text{element}(i', j', k, l) \quad (4.24)$$

SPM assumes that each movement process occurs simultaneously over all cells (synchronous updating), i.e., all cell updates from each individual movement process are first evaluated for all cells, and then applied to all cells affected.

SPM implements three types of movement;

1. A migration movement rate of cohorts between any two locations, and is roughly analogous to movements between areas as implemented in other population models, such as CASAL (Bull et al., 2012).
2. An adjacent cell movements, parametrised by some function of an underlying layer — equivalent to, for example, movement processes implemented in Fish Heaven (Ball and Constable, 2000, Ball and Williamson, 2003).
3. Movement parametrised as a probability density function. Here, the key underlying idea is that the spatial distribution of cohorts at any point in time and at any location can be represented as a density function based on attributes of that location, local abundance, and/or distance from their previous location (Bentley et al., 2004a,b).

4.8.1. Migration movement

The migration process moves individuals from one sets of locations (the source, or emigration layer) to another set of locations (the sink, or immigration layer). A migration can involve one or more categories. The emigration at age is defined as some constant proportion multiplied by a selectivity and the source layer applied as a proportion. The immigration at age is defined as the number emigrating at age distributed proportionally into the sink layer. Migrations are similar to the migration process used in some limited space models such as CASAL (Bull et al., 2012).

For example, let the emigration applied to the population at cell a in category k and age l be denoted $E(a, k, l)$, and given a value from an source layer Le_a at a , a constant migration proportion P , and a selectivity-at-age S_l at age l for some user-defined categories k then,

$$E(a, k, l) = \frac{PLe_a S_l}{\sum_a Le_a} \quad (4.25)$$

And let the immigration applied to the population at cell a in category k and age l be denoted $I(a, k, l)$, and given a value from an sink layer Li_a at a , for some user-defined categories k then,

$$I(a, k, l) = \frac{E(a, k, l) Li_a}{\sum_a Li_a} \quad (4.26)$$

4.8.2. Adjacent cell movement

The adjacent cell movement moves a proportion of individuals in each cell to its four neighbouring cells, and hence mimics a simple diffusion process. It can be applied to a limited range of spatial locations and/or as a gradient by using a layer. An adjacent cell movement can involve one or more categories and movement at age is defined as some constant proportion multiplied by a selectivity and the diffusion layer as a proportion over the four adjoining cells. If no layer is supplied, the process moves the population equally to the adjacent cells (i.e., a constant 0.25 proportion is assumed for each of the adjacent cells).

For example, let the movement from cell a to neighbouring cell b in category k and age l be denoted $V(a, b, k, l)$, and given a value from layer L_b at b , values from layer L_n at the four neighbouring cells to a (including cell b), a constant migration proportion P , and a selectivity-at-age S_l at age l for some user-defined categories k then,

$$V(a, b, k, l) = \frac{PL_b S_l}{\sum_4 L_n} \quad (4.27)$$

The movement value of all cells into all their neighbouring cells are calculated simultaneously from the population layer at the time of movement, and the balance of all movements is returned.

4.8.3. Preference movement

Preference movements allows movement from any $cell(a) \rightarrow cell(b)$, for $\forall a, b \in L_B$ and is implemented as a function of the product of up to n independent *preference functions*. We define the probability of moving from any cell a to any cell b , for all $a, b \in L_B$, as a function of the relative preference for that cell. Here, we use the term *preference function* (Bentley et al., 2004a,b) to describe the movement probability distributions.

We assume that the population and spatial extent are defined, and that there is a preference function that is a function of some (typically estimable) parameters and a spatially explicit set of known attributes. The preference function movement process allows the number of parameters describing movement to be reduced, and results in a movement process that is some function of some underlying property of each location. For example, if we assume that movement between areas was a function of the Euclidean distance between areas, we could model movement between any two areas as a linear decay or exponential decay function (Bentley et al., 2004a). Alternately, if distribution and density were correlated with bathymetric depth for a marine organism, we might model the movement and distribution as a function of depth.

The total preference function

Movement in SPM can be defined as a probability distribution based on an underlying preference function. Here, we define the preference for a cell x as the preference function $f_x(\theta_x, P(x))$, where

θ_x are the parameters for f_x . So, given a set of n attributes for cell x , we can define a preference function for each, and hence we define the aggregated or total preference function for any cell x as the weighted product of individual preference functions,

$$P_x = f_1(\theta_1, P_1(x))^{\alpha_1} \times f_2(\theta_2, P_2(x))^{\alpha_2} \times f_3(\theta_3, P_3(x))^{\alpha_3} \times \cdots \times f_n(\theta_n, P_n(x))^{\alpha_n} \quad (4.28)$$

where α_i is an arbitrary weighting factor for attribute i . In order to avoid over-parametrisation, it is recommended that at least one α_i be fixed to the value of one.

Then we define the probability of moving from cell a to any cell b (where b is defined as the set of all possible cells, including a),

$$p(a \rightarrow b) = \frac{P_a}{\sum_{i \in \forall b} P_i} \quad (4.29)$$

Note that there are three forms of preference function,

1. Those that are a function of some underlying attribute of a cell, as defined by some arbitrary layer L
2. Those that are a function of the abundance (perhaps with a selectivity and for a subset of all categories) of each cell
3. Those that are a function of the distance between the sink and the source cells.

Preference functions of the first type are determined only by the parameters of the preference function and some underlying, fixed, attribute. Preference functions of the others are dynamic, i.e. they depend on the relative locations of the cells or on the density of a cell at a particular point in time.

Preference functions

Preference functions in SPM include constant, Normal, double-Normal, logistic, inverse-logistic, Exponential, threshold, categorical, and monotonic categorical. These are defined as,

1. The constant preference function has dependent variable x and has no parameters, and is defined as,

$$f(x) = x, \text{ where } 0 \leq x \leq 1 \quad (4.30)$$

2. The Normal preference function has dependent variable x and parameters $\theta = (\mu, \sigma)$, and is defined as,

$$f(x|\mu, \sigma) = 2^{-[(x-\mu)/\sigma]^2} \quad (4.31)$$

3. The double-Normal preference function has dependent variable x and parameters $\theta = (\mu, \sigma_L, \sigma_R)$, and is defined as,

$$f(x|\mu, \sigma_L, \sigma_R) = \begin{cases} 2^{-[(x-\mu)/\sigma_L]^2}, & \text{if } x \leq \mu \\ 2^{-[(x-\mu)/\sigma_R]^2}, & \text{if } x \geq \mu \end{cases} \quad (4.32)$$

4. The Logistic preference function has dependent variable x and parameters $\theta = (a_{50}, a_{t095})$, and is defined as,

$$f(x|a_{50}, a_{t095}) = 1/[1 + 19^{(a_{50}-x)/a_{t095}}] \quad (4.33)$$

5. The inverse-Logistic preference function has dependent variable x and parameters $\theta = (a_{50}, a_{t095})$, and is defined as,

$$f(x|a_{50}, a_{t095}) = 1 - 1/[1 + 19^{(a_{50}-x)/a_{t095}}] \quad (4.34)$$

6. The Exponential preference function has dependent variable x and parameter $\theta = (\lambda)$, and is defined as,

$$f(x|\lambda) = \exp(-\lambda x), \text{ where } x \geq 0 \text{ and } 0 \text{ otherwise} \quad (4.35)$$

7. The threshold preference function has dependent variable x and parameters $\theta = (N, \lambda)$, and is defined as,

$$f(x|N, \lambda) = \begin{cases} 1, & \text{if } 0 \leq x \leq N \\ 1/\left(\frac{x}{N}\right)^\lambda, & \text{if } x \geq N \\ 0, & \text{otherwise} \end{cases} \quad (4.36)$$

8. The categorical preference function has dependent variables x_i and parameters $\theta = (\lambda_i)$, and is defined so that for each value x_i , there is a corresponding parameter λ_i .

Note that for the categorical preference function, the preference function is potentially over-parameterised if $\alpha \neq 1$. Typically the values of x are supplied via a categorical layer, with x_i representing the unique values of the layer.

9. The monotonic categorical preference function has dependent variables x_i and parameters $\theta = (\hat{\lambda}_i)$. As for the categorical preference function, it is defined so that for each x_i , there is a corresponding parameter $\hat{\lambda}_i = \lambda_i$ for the first unique value of x_i and $\hat{\lambda}_i = \lambda_i + \lambda_{i-1}$ otherwise, and that $\forall i, \lambda_i \geq 0$.

Note that for the monotonic categorical preference function, the preference function is potentially over-parameterised if $\alpha \neq 1$. Typically the values of x are supplied via a categorical layer, with x_i representing the unique values of the layer.

4.9. Derived quantities

Some processes require, as arguments, a population value derived from the population state. These are termed *derived quantities*. Derived quantities are values, calculated by SPM as the end of a specified time-step in every year, and hence they have a single value for each year of the model. Derived quantities can be calculated as either an abundance or as a biomass. Abundance derived quantities are simply the count or sum of cells within some categories (after applying a selectivity) within cells defined by a layer. Biomass derived quantities are similar, except they are a measure of biomass. Derived quantities are also calculated during the initialisation phases, and hence the time-step during each phase must also be specified. If the initialisation time-steps are not specified, SPM will calculate the derived quantity during the initialisation phases in every year, at the end of each phases annual cycle.

Derived quantities are required by some processes, for example the Beverton-Holt recruitment process. The Beverton-Holt recruitment process requires an equilibrium biomass (B_0) and annual spawning stock biomass values (SSB_y) to resolve the stock-recruit relationship. Here, these would be defined as the abundance or biomass of a part of the population at some point in the annual cycle for selected ages and categories, and would be calculated as a derived quantity.

As an example to define a biomass derived quantity (say spawning stock biomass, SSB) for a model, evaluated at the end of the first time-step (labelled `step_one`) in the initialisation phases (and assuming two initialisation phases) and at the end of the first time-step otherwise, over areas defined by a layer as the spawning ground but counting all ‘mature’ individuals, we would use the syntax,

```
@derived_quantity SSB
type biomass
time_step step_one
initialisation_time_steps step_one step_one
categories mature
selectivity One
layer spawning_ground
```

4.10. Derived layers and meta-layers

To be implemented

Derived layers are layers, calculated by SPM at a specific user-defined time-step and year(s), that have a single value for each cell of the model. For example, B_0 is a derived layer calculated once only at the last initialisation phase of the model as the spawning stock biomass at that time; or a mortality dependent layer is calculated every year based on a formula including other layers with the latest calculation over-riding previous results. Derived meta-layers are meta-layers, calculated by SPM at a specific user-defined time-step every year that the model runs, with all results retained as yearly-indexed layers.

Both derived layers and derived meta-layers are calculated based on user-defined formula, which can use a combination of existing layers and parameters, and user-defined parameters. Parameters defined in the formula need to be provided with initial values. These parameters can be estimated using the estimation section (see Section 5) as any other parameter. The formula are given as strings and SPM resolves the string, hence applies the calculation in each cell of the layers separately. The following math functions, including parentheses, are implemented,

```
+ - * / exp log(e) sqrt ^2 pow(a,b) cos sin
```

For example, density dependent mortality based on diet selectivity can be implemented by applying a derived layer to a constant relationship mortality rate (see Section 4.7.3). If predator A of a previously-defined biomass layer L_A has two potential preys B and C with estimable selectivity parameters E_B and E_C respectively of initial values 0.9 and 0.1, and with previously-defined biomass layers L_B and L_C respectively, the mortality layer Lm_B of prey B due to predation by predator A applied as a constant relationship mortality rate can be defined as,

$$Lm_B = L_A \frac{E_B L_B}{E_B L_B + E_C L_C} \quad (4.37)$$

The total mortality of prey B can be defined as due to predation by predator A only using a constant relationship mortality rate only, or as due to a combination of the mortality due to predation by predator A and other mortalities (constant or layer-based) by defining other mortality events applicable to prey B (see Section 4.7.3 for further details). The three biomass layers L_A , L_B , and L_C need to be defined in the model as (derived) biomass layers of species A , B , and C respectively at a specific time-step. These biomass layers as well as the mortality layer are updated each year by the model at the required time-step. The selectivity parameters can be fixed or estimated by the model with the given initial values.

4.11. Size-age relationship

The age-size relationship defines the size at age (and the weight at size, see Section 4.12) of individuals at age/category within the model. There are three size-age relationships available in SPM. The first is the naive no relationship (where each individual has size 1 irrespective of age). The second and third are the von-Bertalanffy and Schnute relationships respectively. The size-at-age relationship is used to determine the size frequency, given age, and then with the size-weight relationship, a weight-at-age of individuals within an age/category.

The three age-size relationships are,

None: where the size of each individual is exactly 1 for all ages, in which case the none size-weight relationship must also be used.

von Bertalanffy: where size at age is defined as,

$$\bar{s}(\text{age}) = L_{\infty} (1 - \exp(-k(\text{age} - t_0))) \quad (4.38)$$

Schnute: where size at age is defined as,

$$\bar{s}(\text{age}) = \begin{cases} \left[y_1^b + (y_2^b - y_1^b) \frac{1 - \exp(-a(\text{age} - \tau_1))}{1 - \exp(-a(\tau_2 - \tau_1))} \right]^{1/b}, & \text{if } a \neq 0 \text{ and } b \neq 0 \\ y_1 \exp \left[\ln(y_2/y_1) \frac{1 - \exp(-a(\text{age} - \tau_1))}{1 - \exp(-a(\tau_2 - \tau_1))} \right], & \text{if } a \neq 0 \text{ and } b = 0 \\ \left[y_1^b + (y_2^b - y_1^b) \frac{\text{age} - \tau_1}{\tau_2 - \tau_1} \right]^{1/b}, & \text{if } a = 0 \text{ and } b \neq 0 \\ y_1 \exp \left[\ln(y_2/y_1) \frac{\text{age} - \tau_1}{\tau_2 - \tau_1} \right], & \text{if } a = 0 \text{ and } b = 0 \end{cases} \quad (4.39)$$

The von Bertalanffy curve is parameterised by L_{∞} , k , and t_0 ; the Schnute curve (Schnute, 1981) by y_1 and y_2 , which are the mean sizes at reference ages τ_1 and τ_2 , and a and b (when $b = 1$, this reduces to the von Bertalanffy with $k = a$).

When defining size-at-age in SPM, you must also define a size-weight relationship (see Section 4.12 below).

4.12. Size-weight relationship

There are two size-weight relationship,s available in SPM. The first is the naive no relationship, where the weight of an individual, irregardless of size is always 1. The second is the basic relationship.

The two size-weight relationships are,

- None: The size-weight relationship where

$$\text{mean weight} = 1 \quad (4.40)$$

- Basic: The size-weight relationship where

$$\text{mean weight} = a(\text{mean size-at-age})^b \quad (4.41)$$

Be careful about the scale of a — this is easily specified incorrectly. If you provide your catch in tonnes, and your growth curve in centimetres, then a should be on the right scale to convert a length in centimetres to a weight in tonnes. Note that there are reports available that can be used to help check that the units specified are plausible (see Section 7).

If you specify a distribution for the size-at-age relationship, then the mean weight at age is calculated over that distribution, using the following formula, which is exact for lognormal distributions, and a good approximation for a normal distribution (if the c.v. is not large),

$$\text{mean weight} = a \times (\text{mean size at age})^b \times (1 + c^2)^{\frac{b(b-1)}{2}} \quad (4.42)$$

where c is the c.v. of sizes-at-age.

4.13. Selectivities

A selectivity is a function with a different value for each age class (i.e., for each column of the partition). Selectivities are used throughout SPM to interpret observations (Section 5) or to modify the effects of processes on each age class (Section 4). SPM implements a number of different parametric forms, including logistic, knife edge, and double normal selectivities.

A selectivity is always defined to apply just to one category of the population (i.e., row of the partition). To apply the same selectivity to more than one category, then just repeat the selectivity for each category that it is applied to.

Note that selectivities are indexed by age, with indices from `min_age` to `max_age`. For example, you might have an age-based selectivity that was logistic with 50% selected at age 5 and 95% selected at age 7. This would be defined by the `type=logistic` with parameters $a_{50} = 5$ and $a_{095} = (7 - 5) = 2$. Then the value of the selectivity at age $x = 7$ is 0.95 and the selectivity at $x = 3$ is 0.05.

Note that the function values for some choices of parameters for some selectivities can result in a computer numeric overflow error (i.e., the number calculated from parameter values is either too large or too small to be represented in computer memory). SPM implements range checks on some parameters to test for a possible numeric overflow error before attempting to calculate function values. For example, the logistic selectivity is implemented such that if $(a_{50} - x)/a_{095} > 5$ then the value of the selectivity at $x = 0$, i.e., for $a_{50} = 5$, $a_{095} = 0.1$, then the value of the selectivity at $x = 1$, without range checking would be 7.1×10^{-52} . With range checking, that value is 0 (as $(a_{50}x)/a_{095} = 40 > 5$).

The available selectivities are;

- Constant
- Knife-edge
- All values
- All values bounded
- Increasing
- Logistic
- Inverse logistic
- Logistic producing
- Double normal

- Double exponential

The available selectivities are described below.

4.13.1. constant

$$f(x) = C \quad (4.43)$$

The constant selectivity has the estimable parameter C .

4.13.2. knife_edge

$$f(x) = \begin{cases} 0, & \text{if } x < E \\ \alpha, & \text{if } x \geq E \end{cases} \quad (4.44)$$

The knife-edge ogive has the estimable parameter E and a scaling parameter α , where the default value of $\alpha = 1$

4.13.3. all_values

$$f(x) = V_x \quad (4.45)$$

The all-values selectivity has estimable parameters $V_{low}, V_{low+1} \dots V_{high}$. Here, you need to provide the selectivity value for each age class.

4.13.4. all_values_bounded

$$f(x) = \begin{cases} 0, & \text{if } x < L \\ V_x, & \text{if } L \leq x \leq H \\ V_H, & \text{if } x > H \end{cases} \quad (4.46)$$

The all-values-bounded selectivity has non-estimable parameters L and H . The estimable parameters are $V_L, V_{L+1} \dots V_H$. Here, you need to provide an selectivity value for each age class from $L \dots H$.

4.13.5. increasing

$$f(x) = \begin{cases} 0, & \text{if } x < L \\ f(x-1) + \pi_x(\alpha - f(x-1)), & \text{if } L \leq x \leq H \\ f(\alpha), & \text{if } x \geq H \end{cases} \quad (4.47)$$

The increasing ogive has non-estimable parameters L and H . The estimable parameters are $\pi_L, \pi_{L+1} \dots \pi_H$ (but if these are estimated, they should always be constrained to be between 0 and 1). α is a scaling parameter, with default value of $\alpha = 1$. Note that the increasing ogive is similar to the all-values-bounded ogive, but is constrained to be non-decreasing.

4.13.6. logistic

$$f(x) = \alpha / [1 + 19^{(a_{50}-x)/a_{t095}}] \quad (4.48)$$

The logistic selectivity has estimable parameters a_{50} and a_{t095} . α is a scaling parameter, with default value of $\alpha = 1$. The logistic selectivity takes values 0.5α at $x = a_{50}$ and 0.95α at $x = a_{50} + a_{t095}$.

4.13.7. inverse_logistic

$$f(x) = \alpha - \alpha / [1 + 19^{(a_{50}-x)/a_{t095}}] \quad (4.49)$$

The inverse logistic selectivity has estimable parameters a_{50} and a_{t095} . α is a scaling parameter, with default value of $\alpha = 1$. The logistic selectivity takes values 0.5α at $x = a_{50}$ and 0.95α at $x = a_{50} - a_{t095}$.

4.13.8. logistic_producing

$$f(x) = \begin{cases} 0, & \text{if } x < L \\ \lambda(L), & \text{if } x = L \\ (\lambda(x) - \lambda(x-1)) / (1 - \lambda(x-1)), & \text{if } L < x < H \\ 1, & \text{if } x \geq H \end{cases} \quad (4.50)$$

The logistic-producing selectivity has the non-estimable parameters L and H , and has estimable parameters a_{50} and a_{t095} . α is a scaling parameter, with default value of $\alpha = 1$. For category transitions, $f(x)$ represents the proportion moving, not the proportion that have moved. This selectivity was designed for use in an age-based model to model maturity. In such a model, a logistic-producing maturation selectivity will (in the absence of other influences) make the proportions mature follow a logistic curve with parameters a_{50} , a_{t095} .

4.13.9. double_normal

$$f(x) = \begin{cases} \alpha 2^{-[(x-\mu)/\sigma_L]^2}, & \text{if } x \leq \mu \\ \alpha 2^{-[(x-\mu)/\sigma_R]^2}, & \text{if } x \geq \mu \end{cases} \quad (4.51)$$

The double-normal selectivity has estimable parameters a_1 , s_L , and s_R . α is a scaling parameter, with default value of $\alpha = 1$. It has values α at $x = a_1$, and 0.5α at $x = a_1 - s_L$ and $x = a_1 + s_R$.

4.13.10. double_exponential

$$f(x) = \begin{cases} \alpha y_0 (y_1/y_0)^{(x-x_0)/(x_1-x_0)}, & \text{if } x \leq x_0 \\ \alpha y_0 (y_2/y_0)^{(x-x_0)/(x_2-x_0)}, & \text{if } x > x_0 \end{cases} \quad (4.52)$$

The double-exponential selectivity has non-estimable parameters x_1 and x_2 , and estimable parameters x_0 , y_0 , y_1 , and y_2 . α is a scaling parameter, with default value of $\alpha = 1$. It can be ‘U-shaped’. Bounds for x_0 must be such that $x_1 < x_0 < x_2$. With $\alpha = 1$, the selectivity passes through the points (x_1, y_1) , (x_0, y_0) , and (x_2, y_2) . If both y_1 and y_2 are greater than y_0 the selectivity is ‘U-shaped’ with minimum at (x_0, y_0) .

5. The estimation section

5.1. Role of the estimation section

The role of the estimation section is to define the tasks carried out by SPM:

1. Define the objective function (see Section 5.2)
2. Define the parameters to be estimated (see Section 5.3)
3. Calculate a point estimate, i.e., the maximum posterior density estimate (MPD) (see Section 5.4).
4. Calculate a posterior profile selected parameters, i.e., find, for each of a series of values of a parameter, allowing the other estimated parameters to vary, the minimum value of the objective function (see Section 5.5).
5. Generate an MCMC sample from the posterior distribution (see Section 5.6).
6. Calculate the approximate covariance matrix of the parameters as the inverse of the minimizer's approximation to the Hessian, and the corresponding correlation matrix (see Section 5.4).

The estimation section defines The objective function is based on a goodness-of-fit measure of the model to observations, priors and penalties. The observation section describes the objective function, observations, priors and penalties.

5.2. The objective function

In Bayesian estimation, the objective function is a negative log-posterior,

$$Objective(p) = -\sum_i \log[L(\mathbf{p}|O_i)] - \log[\pi(\mathbf{p})] \quad (5.1)$$

where π is the joint prior density of the parameters p .

The contribution to the objective function from the likelihoods are defined in Section 6.1. In addition to likelihoods, priors (see Section 5.7) and penalties (see Section 5.8) are components of the objective function.

You will usually want to use penalties to ensure that the exploitation rate constraints on your fisheries are not breached (otherwise there is nothing to prevent the model from having abundances so low that the recorded catches could not have been taken), penalties on category transitions (to ensure there are enough individuals to move), and possibly penalties to encourage estimated values to be similar, smoothed, etc.

5.3. Specifying the parameters to be estimated

You need to tell SPM which of the estimable parameters are to be estimated by using `@estimate` commands (see Section 9). An `@estimate` command-block looks like,

```
@estimate process[MyRecruitment].r0
lower_bound 1000
```

```
upper_bound 100000  
prior uniform
```

See Section 3.5.5 for instructions on how to generate the parameter name. You have to specify at least one parameter to be estimated if doing an estimation, profile, or MCMC run. You still provide values for the parameters to be estimated, and these are used as the starting values for the minimiser. However, these may be overwritten if you provide a set of alternative starting values (i.e., using `spm -i`, see Section 3.4).

All parameters are estimated within bounds. For each parameter to be estimated, you need to specify the bounds and the prior (Section 5.7). Note that the bounds and prior for each parameter refer to the values of the parameters, not the actual values resulting from the application of the parameter to an equation. If you want to estimate only some elements of a vector, either define the elements of the vector to be estimated (see 3.5.5) or fix the others by setting the bounds equal.

The estimation of parameters can be phased. Here, some of the estimated parameters are initially held fixed, and a minimisation is carried out. Next, some or all of the remaining parameters that were initially held fixed are freed, and another minimisation is carried out. This process continues until all phases have been carried out.

5.4. Point estimation

Point estimation is invoked with `spm -e`. Mathematically, it is an attempt to find a minimum of the objective function. SPM has two algorithms for solving (minimising) the optimisation problem. The first uses a quasi-Newton minimiser built which is a slightly modified implementation of the main algorithm of Dennis Jr. & Schnabel (Dennis Jr and Schnabel, 1996), while the second uses a genetic algorithm developed by Storn & Price (Storn and Price, 1995), the differential evolution minimiser.

5.4.1. The numerical differences minimiser

The minimiser has three kinds of (non-error) exit status:

1. Successful convergence (suggests you have found a local minimum, at least).
2. Convergence failure (you have not reached a local minimum, though you may deem yourself to be ‘close enough’ at your own risk).
3. Convergence unclear (the minimiser halted but was unable to determine if convergence occurred. You may be at a local minimum, although you should check by restarting the minimiser at the final values of the estimated parameters).

You can choose the maximum number of quasi-Newton iterations and objective function evaluations allotted to the minimiser. If it exceeds either limit, it exits with a convergence failure. We recommend large numbers of evaluations and iterations (at least the defaults of 300 and 1000) unless you successfully reach convergence with less. You can also specify an alternative starting point of the minimiser using `spm -i`.

We want to stress that this is a local optimisation algorithm trying to solve a global optimisation problem. What this means is that, even if you get a ‘successful convergence’ message, your solution may be only a local minimum, not a global one. To diagnose this problem, try doing multiple runs from different starting points and comparing the results, or doing profiles of one or more key parameters and seeing if any of the profiled estimates finds a better optimum than the original point estimate.

The approximate covariance matrix of the estimated parameters can be calculated as the inverse of the minimiser's approximation to the Hessian, and the corresponding correlation matrix is also calculated. Be aware that

- the Hessian approximation develops over many minimiser steps, so if the minimiser has only run for a small number of iterations the covariance matrix can be a very poor approximation
- the inverse Hessian is not a good approximation to the covariance matrix of the estimated parameters, and may not be useful to construct, for example, confidence intervals.

Also note that if an estimated parameter has equal lower and upper bounds, it will have entries of '0' in the covariance matrix and NaN or -1.#IND (depending on the operating system) in the correlation matrix.

5.4.2. The differential evolution minimiser

The differential evolution minimiser is a simple population based, stochastic function minimizer, but is claimed to be quite powerful in solving minimisation problems. It is a method of mathematical optimization of multidimensional functions and belongs to the class of evolution strategy optimizers. Initially, the procedure randomly generates and evaluates a number of solution vectors (the population size), each with p parameters. Then, for each generation (iteration), the algorithm creates a candidate solution for each existing solution by random mutation and uniform crossover. The random mutation generates a new solution by multiplying the difference between two randomly selected solution vectors by some scale factor, then adding the result to a third vector. Then an element-wise crossover takes place with probability P_{cr} , to generate a potential candidate solution. If this is better than the initial solution vector, it replaces it, otherwise the original solution is retained. The algorithm is terminated after either a predefined number of generations (`max_generations`) or when the maximum difference between the scaled individual parameters from the candidate solutions from all populations is less than some predefined amount `tolerance`.

The differential evolution minimiser can be good at finding global minimums in surfaces that may have local minima. However, the speed of the minimiser, and the ability to find a good minima depend on the number of initial 'populations'. Some authors recommend that the number of populations be set at about $10 * p$, where p is the number of free parameters. However, depending on your problem, you may find that you may need more, or that less will suffice.

We note that there is no proof of convergence for the differential evolution solver, but several papers have found it to be an efficient method of solving multidimensional problems. Our (limited) experience suggests that it can often find a better minima and may be faster or longer (depending on the actual model specification) at finding a solution when compared with the numerical differences minimiser. Comparisons with auto-differentiation minimisers or other more sophisticated algorithms have not been made.

5.5. Posterior profiles

If profiles are requested `spm -p`, SPM will first calculate a point estimate. For each scalar parameter or, in the case of vectors or selectivities, the element of the parameter to be profiled, SPM will fix its value at a sequence of n evenly spaced numbers (`step`) between a specified lower and upper bounds l and u , and calculate a point estimate at each value.

By default `step = 10`, and $(l, u) = (\text{lower bound on parameter plus } (range/(2n)), \text{upper bound on parameter less } (range/(2n)))$. Each minimisation starts at the final parameter values from the

previous resulting value of the parameter being profiled. *SPM* will report the objective function for each parameter value. Note that an initial point estimate should be compared with the profile, not least to check that none of the other points along the profile have a better objective function value than the initial ‘minimum’.

You specify which parameters are to be profiled, and optionally the number of steps, lower bound, and upper bound for each. In the case of vector parameters, you will also need to specify the element of the vector being profiled.

You can also supply the initial starting point for the estimation using `spm -i file` — this may improve the minimiser performance for the profiles.

If you get an implausible profile, it may be a result of not using enough iterations in the minimiser or a poor choice of minimiser control variables (e.g., the minimiser tolerance). It also may be useful to try both if the minimisers in *SPM* and compare the results.

5.6. Bayesian estimation

SPM can use a Monte Carlo Markov Chain to generate a sample from the posterior distribution of the estimated parameters `spm -m` and output the sampled values to a file (optionally keeping only every *n*th set of values).

As *SPM* has no post-processing capabilities. *SPM* cannot produce MCMC convergence diagnostics (use a package such as BOA) or plot/summarize the posterior distributions of the output quantities (for example, using a general-purpose statistical or spreadsheet package such as S-Plus, **R**, or Microsoft Excel).

Bayesian methodology and MCMC are both large and complex topics, and we do not describe either properly here. See Gelman et al. (1995) and Gilks et al. (1994) for details of both Bayesian analysis and MCMC methods. In addition, see Punt & Hilborn (2001) for an introduction to quantitative fish stock assessment using Bayesian methods.

This section only briefly describes the MCMC algorithms used in *SPM*. See Section 9.3 for a better description of the sequence of *SPM* commands used in a full Bayesian analysis.

SPM uses a straightforward implementation of the Metropolis-Hastings algorithm (Gelman et al., 1995, Gilks et al., 1994). The Metropolis-Hastings algorithm attempts to draw a sample from a Bayesian posterior distribution, and calculates the posterior density π , scaled by an unknown constant. The algorithm generates a ‘chain’ or sequence of values. Typically the beginning of the chain is discarded and every *N*th element of the remainder is taken as the posterior sample. The chain is produced by taking an initial point x_0 and repeatedly applying the following rule, where x_i is the current point:

- Draw a candidate step s from a proposal distribution J , which should be symmetric i.e., $J(-s) = J(s)$.
- Calculate $r = \min(\pi(x_i + s)/\pi(x_i), 1)$.
- Let $x_{i+1} = x_i + s$ with probability r , or x_i with probability $1 - r$.

An initial point estimate is produced before the chain starts, which is done so as to calculate the approximate covariance matrix of the estimated parameters (as the inverse Hessian), and may also be used as the starting point of the chain.

The user can specify the starting point of the point estimate minimiser using `spm -i`. Don’t start it too close to the actual estimate (either by using `spm -i`, or by changing the initial parameter values

in input configuration file) as it takes a few iterations to form a reasonable approximation to the Hessian.

There are two options for the starting point of the Markov Chain:

- Start from the point estimate.
- Start from a random point near the point estimate (the point is generated from a multivariate normal distribution, centred on the point estimate, with covariance equal to the inverse Hessian times a user-specified constant). This may be useful if the chain gets ‘stuck’ at the point estimate, or if you wish to generate multiple chains from for later MCMC diagnostic tests.
- Start from a point specified by the user with `spm -i` (*not yet implemented*).

The chain moves in natural space, i.e., no transformations are applied to the estimated parameters. The default proposal distribution is a multivariate t centred on the current point, with covariance matrix equal to a matrix based on the approximate covariance produced by the minimiser, times some step-size factor. The following steps define the initial covariance matrix of the proposal distribution:

- The covariance matrix is taken as the inverse of the approximate Hessian from the quasi-Newton minimiser.
- The covariance matrix is modified so as to decrease all correlations greater than `@mcmc.max_correlation` down to `@mcmc.max_correlation`, and similarly to increase all correlations less than `-@mcmc.max_correlation` up to `-@mcmc.max_correlation` (the `@mcmc.max_correlation` parameter defaults to 0.8). This should help to avoid getting ‘stuck’ in a lower-dimensional subspace.
- The covariance matrix is then modified either by,
 - if `@mcmc.adjustment_method=covariance`: that if the variance of the i th parameter is non-zero and less than `@mcmc.min_difference` times the difference between the parameters’ lower and upper bound, then the variance is changed, without changing the associated correlations, to $k = \min_diff(upper_bound_i - lower_bound_i)$. This is done by setting

$$\text{Cov}(i, j)' = \text{sqrt}(k) \text{Cov}(i, j) / \text{sd}(i)$$

for $i \neq j$, and $\text{var}(i)' = k$

- if `@mcmc.adjustment_method=correlation`: that if the variance of the i th parameter is non-zero and less than `@mcmc.min_difference` times the difference between the parameters’ lower and upper bound, then its variance is changed to $k = \min_diff(upper_bound_i - lower_bound_i)$. This differs from (i) above in that the effect of this option is that it also modifies the resulting correlations between the i th parameter and all other parameters.

This allows each estimated parameter to move in the MCMC even if its variance is very small according to the inverse Hessian. In both cases, the `@mcmc.min_difference` parameter defaults to 0.0001.

- The `@mcmc.step_size` (a scalar factor applied to the covariance matrix to improve the acceptance probability) is chosen by the user. The default is $2.4d^{-0.5}$ where d is the number of estimated parameters, as recommended by Gelman et al. (Gelman et al., 1995). However, you may find that a smaller value may often be better.

The proposal distribution can also change adaptively during the chain, using two different mechanisms. Both are offered as means of improving the convergence properties of the chain. It is important to note that any adaptive behaviour must finish before the end of the burn-in period, i.e., the proposal distribution must be finalised before the kept portion of the chain starts. The adaptive mechanisms are as follows:

1. You can request that the step size change adaptively at one or more sample numbers. At each adaptation, the step size is doubled if the acceptance rate since the last adaptation is more than 0.5, or halved if the acceptance rate is less than 0.2. (See Gelman et al. (Gelman et al., 1995) for justification.)
2. You can request that the entire covariance matrix change adaptively at one or more sample numbers. At each adaptation, it is replaced with a matrix based on the sample covariance of an earlier section of the chain. The theory here is that the covariance of a portion of chain could potentially be a better estimate of the covariance of the posterior distribution than the inverse Hessian. *(not yet implemented)*.

The probability of acceptance for each jump is 0 if it would move out of the bounds, or 1 if it improves the posterior, or (new posterior/old posterior) otherwise. You can specify how often the position of the chain is recorded using the keep parameter. For example, with keep 10, only every 10th sample is recorded.

You have the option to specify that some of the estimated parameters are fixed during the MCMC. If the chain starts at the point estimate or at a random location, these fixed parameters are set to their values at the point estimate. If you specify the start of the chain using `spm -i`, these fixed parameters are set to the values in the file. *(not yet implemented)*.

The posterior sample can also be used for simulations (Section `sec:simulation-observations`) with the values supplied using `spm -i file`.

5.7. Priors

In a Bayesian analysis, you need to give a prior for every parameter that is being estimated. There are no default priors.

Note that when some of these priors are parameterised in terms of mean, c.v., and standard deviation, these refer to the parameters of the distribution before bounds are applied. The moments of the prior after the bounds are applied may differ.

SPM has the following priors (expressed in terms of their contribution to the objective function):

1. Uniform

$$-\log(\pi(p)) = 0 \tag{5.2}$$

2. Uniform-log (i.e., $\log(p) \sim \text{uniform}$)

$$-\log(\pi(p)) = \log(p) \tag{5.3}$$

3. Normal with mean μ and c.v. c

$$-\log(\pi(p)) = 0.5 \left(\frac{p - \mu}{c\mu} \right)^2 \quad (5.4)$$

4. Normal with mean μ and standard deviation σ

$$-\log(\pi(p)) = 0.5 \left(\frac{p - \mu}{\sigma} \right)^2 \quad (5.5)$$

5. Lognormal with mean μ and c.v. c

$$-\log(\pi(p)) = \log(p) + 0.5 \left(\frac{\log(p/\mu)}{s} + \frac{s}{2} \right)^2 \quad (5.6)$$

where s is the standard deviation of $\log(p)$ and $s = \sqrt{\log(1 + c^2)}$.

6. Beta with mean μ and standard deviation σ , and range parameters A and B

$$-\log(\pi(p)) = (1 - m) \log(p - A) + (1 - n) \log(B - p) \quad (5.7)$$

where $v = \frac{\mu - A}{B - A}$, and $\tau = \frac{(\mu - A)(B - \mu)}{\sigma^2} - 1$ and then $\mu = \tau v$ and $n = \tau(1 - v)$. Note that the beta prior is undefined when $\tau \leq 0$.

5.8. Penalties

Penalties can be used to encourage or discourage parameter values or model outputs that are unlikely to be sensible, by adding a penalty to the objective function. For example, parameter estimates that do not allow a known mortality event to remove enough individuals from the population can be discouraged with an event mortality penalty. SPM requires penalty functions for processes that move or shift a *number* of individuals between categories or from the partition.

For most penalties, you need to specify a multiplier, and the objective function is increased by this multiplier times the penalty value as described below. In some cases you will need to make the multiplier quite large to prohibit some model behaviour.

Currently, the penalties for the processes `@process[label].type=event_mortality` and `@process[label].type=category_transition` are the only penalties implemented.

For both of these processes, two types of penalty can be defined, natural scale (the default) and log scale. Both of these types add a penalty value of the squared difference between the observed value (i.e., the actual number of individuals to be removed in an event mortality process or the actual number of individuals to shift in a category transition process), and the number that were moved (if less than or equal), times the penalty multiplier.

The natural scale penalty just uses the squared difference on a natural scale, while the log scale penalty uses the squared difference of the logged values.

6. The observation section

6.1. Observations and likelihoods

Observations are typically supplied as observations at an instance in time, over some spatially aggregated area. Time series of observations can be supplied as separate observations for each year or point in time.

SPM allows the following types of observations;

- Observations of proportions by age class within categories

- Observations of proportions between categories within age classes

- Relative and absolute abundance/biomass observations

The definitions for each type of observation are described below, including how the observed values should be supplied, how SPM calculates the expected values, and the likelihoods that are available for each type of observation.

6.2. Proportions-at-age observations

Proportions-at-age observations are observations of either the relative number of individuals at age or relative biomass at age.

The observation is supplied for a given year and time-step, for some selected age classes of the population (i.e., for a range of ages multiplied by a selectivity), for categories aggregated over a set of spatial cells. Note that the observations at age can include a plus group, which must be less than or equal to the maximum age defined for the partition.

The age range must be ages defined in the partition (i.e., between `@model.min_age` and `@model.max_age` inclusive), but the upper end of the age range can optionally be a plus group — which may or may not be the same as the plus group defined for the partition.

Proportions-at-age observations can be supplied for a single category, aggregated across categories, or be proportions of multiple categories. For example, for a model with the two categories *male* and *female*, we might supply either (i) observations of the proportions of males (or alternately female) within each age class; (ii) proportions of total individuals (males + females) at each age class, or (iii) the proportions of individuals for both male and female categories simultaneously. In addition, each category must have an associated selectivity, defined by `selectivities`.

The way the categories of the observation are defined specifies which of these alternatives to use. For example, to specify that the observations are of the proportions of male within each age class (example (i) above), then the subcommand `categories` for the `@observation[label].type=proportion_by_age` command is,

```
categories male
```

SPM then expects that there will be a vector of proportions supplied, with one proportion for each age class within the defined age range. For example, if the age range was 3 to 10, then 8 proportions should be supplied (one proportion for each of the ages 3, 4, 5, 6, 7, 8, 9, and 10). The expected values will be the expected proportions of males within each of these age classes, after applying a selectivity at the year and time-step specified. Note that the supplied vector of proportions (i.e., in this example, the 8 proportions) must sum to one (with a default tolerance of 0.001).

By default, categories are aggregated. For example, to specify that the observations are of the proportions of total individuals (males + females) at each age class (example (ii) above), then the subcommand `categories` is,

To be removed from the code

Note that we are changing the notation to + here, and nothing instead of : to make it less ambiguous

```
categories male female
```

To be implemented

```
categories male + female
```

SPM then expects that there will be a vector of proportions supplied, with one proportion for each age class within the defined age range. For example, if the age range was 3 to 10, then 8 proportions should be supplied. The expected values will be the expected proportions of selected males plus selected females within each of these age classes, at the year and time-step specified. Note that the supplied vector of proportions (i.e., in this example, the 8 proportions) must sum to one (with a default tolerance of 0.001).

Otherwise, to provide proportions for multiple categories simultaneously, you need to specify which categories are aggregated and which are separate. SPM uses a space symbol to denote those categories to separate. For example, to specify that the observations are of the the proportions of individuals for both male and female simultaneously at each age class (example (iii) above), then the subcommand `categories` is,

To be removed from the code

```
categories male : female
```

To be implemented

```
categories male female
```

SPM then expects that there will be a vector of proportions supplied, with one proportion for each age class within the defined age range for males and then females. For example, if the age range was 3 to 10, then 16 proportions should be supplied, the first set of 8 corresponding to the proportions of male (out of male and female combined) and the second 8 to female. The expected values will be the expected proportions of selected males and selected females within each of these age classes, at the year and time-step specified. Note that the supplied vector of proportions (i.e., in this example, the 16 proportions) must sum to one (with a default tolerance of 0.001).

The definition of categories can be a combination of the above cases and can become more complex as the number of categories in the model increases. For example, in a model with categories male-immature, male-mature, female-immature, and female-mature, we might supply observations of males (immature and mature combined) and females (immature and mature combined) simultaneously. Here the `categories` subcommand would be;

```
categories male-immature + male-mature female-immature + female-mature
```

Assuming that we wanted to supply observations for ages 3 to 10, then SPM would expect a vector of 16 proportions for each spatial location — the first eight corresponding to the observed proportions of males aged 3–10, and the second set of eight corresponding to the proportions of females aged 3–10. Further, the proportions would sum to one. Note that the addition takes precedence on the multiple categories defined.

The observations must be supplied using all or some of the values of defined by a categorical layer. SPM calculates the expected values by summing over the defined ages (via the age range and selectivity) and categories for those spatial cells where the categorical layer has the same value as defined for each vector of observations.

For example, in a 2×2 spatial model a categorical layer (e.g., with label Area) may define that cells (1,1) and (1,2) have value *A* and cells (2,1) and (2,2) have value *B*, i.e.,

```
@layer Area
type categorical
data A A
data B B
```

Here we supply observations for those spatial cells where the categorical layer has value *A* as,

```
@observation MyProportions
...
categories male female
min_age 1
max_age 5
obs A 0.01 0.05 0.10 0.20 0.20 0.01 0.05 0.15 0.20 0.03
...
```

Or, for both *A* and *B* as,

```
@observation MyProportions
...
categories male female
min_age 1
max_age 5
obs A 0.01 0.05 0.10 0.20 0.20 0.01 0.05 0.15 0.20 0.03
obs B 0.02 0.06 0.10 0.21 0.18 0.02 0.05 0.15 0.20 0.01
...
```

Or for example, 12 observations are required to describe immature males, mature males, and all females together, for ages 1–4,

```
@observation MyProportions
...
categories male_immature male_mature female_immature + female_mature
min_age 1
max_age 4
obs A 0.05 0.15 0.15 0.05 0.02 0.03 0.08 0.04 0.05 0.15 0.15 0.08
...
```

It may be useful at times to consider grouping categories together even though the data might have been collected separately, as the model cannot dissociate the uncertainty between age classes and that between

the proportion of fish at age in each category. For example if observations have been collected for males and females separately, but very few females were caught, the uncertainty surrounding the ratio of males to females might be higher than the model applies, as it applies the same uncertainty to that surrounding the data. In this case an alternative is to provide the proportions at age for males and females together with appropriate uncertainty, and then the proportion-at-age (see Section 6.3) of males as a different observation with a different (and in this case higher) uncertainty.

To supply an observation for individual spatial cells, then define a categorical layer with a single, unique value for each spatial cell.

To be implemented

SPM always evaluates the observations at the end of a time-step (i.e., after SPM has applied all of the processes for that time-step). However, the observation can be applied to the abundance at the start of a time-step or part-way through a time-step by the use of the `proportion_time_step` subcommand. Here SPM stores the state of the partition at the beginning of a time-step, and again at the end of the time-step. The partition at some point p during the time-step is then evaluated as the weighted sum between the start and end of the time-step, i.e, for any element i in the partition, $n_i = (1 - p)n_i^{start} + pn_i^{end}$. Note that it may not be sensible to use a value other than one, depending on the processes that happen during the time-step (for example, if the time-step contains an ageing process).

6.2.1. Likelihoods for proportions-at-age observations

SPM implements two likelihoods for proportions-at-age observations, the multinomial likelihood and the lognormal likelihood.

The multinomial likelihood

For the observed proportions at age O_i for age classes i , with sample size N , and the expected proportions at the same age classes E_i , the negative log-likelihood is defined as;

$$-\log(L) = -\log(N!) + \sum_i \log((NO_i)!) - NO_i \log(Z(E_i, \delta)) \quad (6.1)$$

where $\sum_i O_i = 1$ and $\sum_i E_i = 1$. $Z(\theta, \delta)$ is a robustifying function to prevent division by zero errors, with parameter $\delta > 0$. $Z(\theta, \delta)$ is defined as,

$$Z(\theta, \delta) = \begin{cases} \theta, & \text{where } \theta \geq r \\ \delta / (2 - \theta / \delta), & \text{otherwise} \end{cases} \quad (6.2)$$

The default value of δ is 1×10^{-11} .

The lognormal likelihood

For the observed proportions at age O_i for age classes i , with c.v. c_i , and the expected proportions at the same age classes E_i , the negative log-likelihood is defined as;

$$-\log(L) = \sum_i \left(\log(\sigma_i) + 0.5 \left(\frac{\log(O_i / Z(E_i, \delta))}{\sigma_i} + 0.5 \sigma_i \right)^2 \right) \quad (6.3)$$

where

$$\sigma_i = \sqrt{\log(1 + c_i^2)} \quad (6.4)$$

and the c_i 's are the c.v.s for each age class i , and $Z(\theta, \delta)$ is a robustifying function to prevent division by zero errors, with parameter $\delta > 0$. $Z(\theta, \delta)$ is defined as,

$$Z(\theta, \delta) = \begin{cases} \theta, & \text{where } \theta \geq r \\ \delta / (2 - \theta / \delta), & \text{otherwise} \end{cases} \quad (6.5)$$

The default value of δ is 1×10^{-11} .

6.3. Proportions-by-category observations

Proportions-by-category observations are observations of either the relative number of individuals between categories within age classes, or relative biomass between categories within age classes.

The observation is supplied for a given year and time-step, for some selected age classes of the population (i.e., for a range of ages multiplied by a selectivity), for categories aggregated over a set of spatial cells.

The age range must be ages defined in the partition (i.e., between `@model.min_age` and `@model.max_age` inclusive), but the upper end of the age range can optionally be a plus group — which may or may not be the same as the plus group defined for the partition.

Proportions-by-category observations can be supplied for any set of categories as a proportion of themselves and any set of additional categories. For example, for a model with the two categories *male* and *female*, we might supply observations of the proportions of males in the population at each age class. The subcommand `categories` defines the categories for the numerator in the calculation of the proportion, and the subcommand `categories2` supplies the additional categories to be used in the denominator of the calculation. In addition, each category must have an associated selectivity, defined by `selectivities` for the numerator categories and `selectivities2` for the additional categories used in the denominator, e.g.,

```
categories male
categories2 female
selectivities male-selectivity
selectivities2 female-selectivity
```

defines that the proportion of males in each age class as a proportion of males + females. SPM then expects that there will be a vector of proportions supplied, with one proportion for each age class within the defined age range, i.e., if the age range was 3 to 10, then 8 proportions should be supplied (one proportion for each of the ages 3, 4, 5, 6, 7, 8, 9, and 10). The expected values will be the expected proportions of male to male + female within each of these age classes, after applying the selectivities at the year and time-step specified.

The observations must be supplied using all or some of the values defined by a categorical layer. SPM calculates the expected values by summing over the ages (via the age range and selectivity) and categories for those spatial cells where the categorical layer has the same value as defined for each vector of observations.

For example, in a 2×2 spatial model a categorical layer (e.g., with label *Area*) may define that cells (1,1) and (1,2) have value *A* and cells (2,1) and (2,2) have value *B*, i.e.,

```
@layer Area
type categorical
data A A
data B B
```

Here we supply observations for those spatial cells where the categorical layer has value *A* as,

```
@observation MyProportions
...
categories male
categories2 female
min_age 1
max_age 5
obs A 0.01 0.05 0.10 0.20 0.20
...
```

Or, for both *A* and *B* as,

```
@observation MyProportions
...
categories male
categories2 female
min_age 1
max_age 5
obs A 0.01 0.05 0.10 0.20 0.20
obs B 0.02 0.06 0.10 0.21 0.18
...
```

To supply an observation for individual spatial cells, then you will need to define a categorical layer with a single, unique value for each spatial cell.

To be implemented

SPM always evaluates the observations at the end of a time-step (i.e., after SPM has applied all of the processes for that time-step). However, the observation can be applied to the abundance at the start of a time-step or part-way through a time-step by the use of the `proportion.time.step` subcommand. Here SPM stores the state of the partition at the beginning of a time-step, and again at the end of the time-step. The partition at some point *p* during the time-step is then evaluated as the weighted sum between the start and end of the time-step, i.e., for any element *i* in the partition, $n_i = (1 - p)n_i^{start} + pn_i^{end}$. Note that it may not be sensible to use a value other than one, depending on the processes that happen during the time-step (for example, if the time-step contains an ageing process).

6.3.1. Likelihoods for proportions-by-category observations

SPM implements two likelihoods for proportions-by-category observations, the binomial likelihood, and the normal approximation to the binomial (binomial-approx).

The binomial likelihood

For observed proportions O_i for age class *i*, where E_i are the expected proportions for age class *i*, and N_i is the effective sample size for age class *i*, then the negative log-likelihood is defined as;

$$\begin{aligned}
 -\log(L) = & -\sum_i \log(N_i!) - \log((N_i(1 - O_i))!) - \log((N_i O_i)!) + N_i O_i \log(Z(E_i, \delta)) \\
 & + N_i(1 - O_i) \log(Z(1 - E_i, \delta))
 \end{aligned} \tag{6.6}$$

where $Z(\theta, \delta)$ is a robustifying function to prevent division by zero errors, with parameter $\delta > 0$. $Z(\theta, \delta)$ is

defined as,

$$Z(\theta, \delta) = \begin{cases} \theta, & \text{where } \theta \geq r \\ \delta / (2 - \theta / \delta), & \text{otherwise} \end{cases} \quad (6.7)$$

The default value of δ is 1×10^{-11} .

The normal approximation to the binomial likelihood

For observed proportions O_i for age class i , where E_i are the expected proportions for age class i , and N_i is the effective sample size for age class i , then the negative log-likelihood is defined as;

$$-\log(L) = \sum_i \log \left(\sqrt{Z(E_i, \delta) Z(1 - E_i, \delta) / N_i} \right) + \frac{1}{2} \left(\frac{O_i - E_i}{\sqrt{Z(E_i, \delta) Z(1 - E_i, \delta) / N_i}} \right)^2 \quad (6.8)$$

where $Z(\theta, \delta)$ is a robustifying function to prevent division by zero errors, with parameter $\delta > 0$. $Z(\theta, \delta)$ is defined as,

$$Z(\theta, \delta) = \begin{cases} \theta, & \text{where } \theta \geq r \\ \delta / (2 - \theta / \delta), & \text{otherwise} \end{cases} \quad (6.9)$$

The default value of δ is 1×10^{-11} .

6.4. Abundance or biomass observations

Abundance (or biomass) observations are observations of either a relative or absolute number (or biomass) of individuals from a set of categories after applying a selectivity. The observations classes are the same, except that a biomass observation will use the biomass as the observed (and expected) value (calculated from mean weight of individuals within each age and category) while an abundance observation is just the number of individuals.

Each observation is for a given year and time-step, for some selected age classes of the population (i.e., for a range of ages multiplied by a selectivity), for categories aggregated over a set of spatial cells. Further, you need to provide the label of the catchability coefficient q , which can either be estimated or fixed. For absolute abundance or absolute biomass observations, define a catchability where $q = 1$.

The observations can be supplied for any set of categories. For example, for a model with the two categories *male* and *female*, we might supply an observation of the total abundance/biomass (male + female) or just male abundance/biomass. The subcommand `categories` defines the categories used to aggregate the abundance/biomass. In addition, each category must have an associated selectivity, defined by `selectivities`, e.g.,

```
categories male
selectivities male-selectivity
```

defines an observation for males after applying the selectivity `male-selectivity`. SPM then expects that there will be a single observation supplied. The expected values for the observations will be the expected abundance (or biomass) of males, after applying the selectivities, at the year and time-step specified.

The observations must be supplied using all or some of the values of defined by a categorical layer. SPM calculates the expected values by summing over the defined ages (via the age range and selectivity) and

categories for those spatial cells where the categorical layer has the same value as defined for each vector of observations.

For example, in a 2×2 spatial model a categorical layer (e.g., with label Area) may define that cells (1,1) and (1,2) have value *A* and cells (2,1) and (2,2) have value *B*, i.e.,

```
@layer Area
type categorical
data A A
data B B
```

Here we supply observations for those spatial cells where the categorical layer has value *A* as,

```
@observation MyAbundance
...
categories male
obs A 1000
...
```

Or, for both *A* and *B* as,

```
@observation MyAbundance
...
categories male
obs A 1000
obs B 1200
...
```

To supply an observation for individual spatial cells, then you will need to define a categorical layer with a single, unique value for each spatial cell.

To be implemented

SPM always evaluates the observations at the end of a time-step (i.e., after SPM has applied all of the processes for that time-step). However, the observation can be applied to the abundance at the start of a time-step or part-way through a time-step by the use of the `proportion_time_step` subcommand. Here SPM stores the state of the partition at the beginning of a time-step, and again at the end of the time-step. The partition at some point p during the time-step is then evaluated as the weighted sum between the start and end of the time-step, i.e., for any element i in the partition, $n_i = (1 - p)n_i^{start} + pn_i^{end}$. Note that it may not be sensible to use a value other than one, depending on the processes that happen during the time-step (for example, if the time-step contains an ageing process).

6.4.1. Likelihoods for abundance observations

The lognormal likelihood

For observations O_i , c.v. c_i , and expected values qE_i , the negative log-likelihood is defined as;

$$-\log(L) = \sum_i \left(\log(\sigma_i) + 0.5 \left(\frac{\log(O_i/qZ(E_i, \delta))}{\sigma_i} + 0.5\sigma_i \right)^2 \right) \quad (6.10)$$

where

$$\sigma_i = \sqrt{\log(1 + c_i^2)} \quad (6.11)$$

and $Z(\theta, \delta)$ is a robustifying function to prevent division by zero errors, with parameter $\delta > 0$. $Z(\theta, \delta)$ is defined as,

$$Z(\theta, \delta) = \begin{cases} \theta, & \text{where } \theta \geq r \\ \delta / (2 - \theta / \delta), & \text{otherwise} \end{cases} \quad (6.12)$$

The default value of δ is 1×10^{-11} .

The normal likelihood

For observations O_i , c.v. c_i , and expected values qE_i , the negative log-likelihood is defined as;

$$-\log(L) = \sum_i \left(\log(c_i E_i) + 0.5 \left(\frac{O_i - E_i}{Z(c_i E_i, \delta)} \right)^2 \right) \quad (6.13)$$

and $Z(\theta, \delta)$ is a robustifying function to prevent division by zero errors, with parameter $\delta > 0$. $Z(\theta, \delta)$ is defined as,

$$Z(\theta, \delta) = \begin{cases} \theta, & \text{where } \theta \geq r \\ \delta / (2 - \theta / \delta), & \text{otherwise} \end{cases} \quad (6.14)$$

The default value of δ is 1×10^{-11} .

6.5. Process error

Additional ‘process error’ can be defined for each set of observations. Additional process error has the effect of increasing the observation error in the data, and hence of decreasing the relative weight given to the data in the fitting process.

For observations where the likelihood is parameterised by the c.v., you can specify the process error for a given set of observations as a c.v., in which case all the c.v.s c_i are changed to

$$c'_i = \sqrt{c_i^2 + c_{process_error}^2} \quad (6.15)$$

Note that $c_{process_error} \geq 0$, and that $c_{process_error} = 0$ is equivalent to no process error.

Similarly, if the likelihood is parameterised by the effective sample size N ,

$$N'_i = \frac{1}{1/N_i + 1/N_{process_error}} \quad (6.16)$$

Note that this requires that $N_{process_error} > 0$, but we allow the special case of $N_{process_error} = 0$, and define $N_{process_error} = 0$ as no process error (i.e., defined to be equivalent to $N_{process_error} = \infty$).

For both the c.v. and N process errors, the process error has more effect on small errors than on large ones. Be clear that a large value for the N process error means a small process error.

6.6. Ageing error

SPM can apply ageing error age frequency observations. Ageing error is applied to the expected values for proportions-at-age observations. The ageing error is applied as a misclassification matrix, which has the effect of 'smearing' the age frequencies. These are used in calculating the fits to the observed values, and hence the contribution to the total objective function.

Ageing error is optional, and if it is used, it may be omitted for any individual time series. Different ageing error models may be applied for different observation commands. See Section 7.12 for reporting the misclassification matrix.

The ageing error models implemented are,

1. None: The default model is to apply no ageing error.
2. Off by one: Proportion p_1 of individuals of each age a are misclassified as age $a - 1$ and proportion p_2 are misclassified as age $a + 1$. Individuals of age $a < k$ are not misclassified. If there is no plus group in the population model, then proportion p_2 of the oldest age class will 'fall off the edge' and disappear.
3. Normal: Individuals of age a are classified as ages which are normally distributed with mean a and constant c.v. c . As above, if there is no plus group in the population model, some individuals of the older age classes may disappear. If c is high enough, some of the younger age classes may 'fall off the other edge'. Individuals of age $a < k$ are not misclassified.

Note that the expected values (fits) reported by SPM for observations with ageing error will have had the ageing error applied.

6.7. Simulating observations

SPM can generate simulated observations for a given model with given parameter values (using `spm -s`). Simulated observations are randomly distributed values, generated according to the error assumptions defined for each observation, around fits calculated from one or more sets of the 'true' parameter values. Simulating from a set of parameters can be used to generate observations from an operating model or as a form of parametric bootstrap.

The procedure SPM uses for simulating observations is to first run using the 'true' parameter values and generate the expected values. Then, if a set of observations uses ageing error, ageing error is applied. Finally a random value for each observed value is generated based on (i) the expected values, (ii) the type of likelihood specified, and (iii) the variability parameters (e.g., `error_value` and `process_error`).

Methods for generating the random error, and hence simulated values, depend on the specific likelihood type of each observation.

1. Normal likelihood parameterised by c.v.: Let E_i be the fitted value for observation i , and c_i be the corresponding c.v. (adjusted by the process error if applicable). Each simulated observation value S_i is generated as an independent normal deviate with mean E_i and standard deviation $E_i c_i$.
2. Log-normal likelihood: Let E_i be the fitted value for observation i and c_i be the corresponding c.v. (adjusted by the process error if applicable). Each simulated observation value S_i is generated as an independent lognormal deviate with mean and standard deviation (on the natural scale, not the log-scale) of E_i and $E_i c_i$ respectively. The robustification parameter δ is ignored.
3. Multinomial likelihood: Let E_i be the fitted value for observation i , for i between 1 and n , and let N be the sample size (adjusted by process error if applicable, and then rounded up to the next whole number). The robustification parameter δ is ignored. Then,
 - (a) A sample of N values from 1 to n is generated using the multinomial distribution, using sample probabilities proportional to the values of E_i .
 - (b) Each simulated observation value S_i is calculated as the proportion of the N sampled values equalling i
 - (c) The simulated observation values S_i are then rescaled so that their sum is equal to 1

4. Binomial and the normal approximation to the binomial likelihoods: Let E_i be the fitted value for observation i , for i between 1 and n , and N_i the corresponding equivalent sample size (adjusted by process error if applicable, and then rounded up to the next whole number). The robustification parameter δ is ignored. Then,
 - (a) A sample of N_i independent binary variates is generated, equalling 1 with probability E_i
 - (b) The simulated observation value S_i is calculated as the sum of these binary variates divided by N_i

Note that SPM will report simulated observations using the usual observation report (`@report[label].type=observation`). The report `@report[label].type=simulated_observation` will generate simulated observations in a form suitable for use as input within a SPM input configuration file. See Section 7 for more detail.

6.8. Pseudo-observations

SPM can generate expected values for observations without them contributing to the total objective function. These are called pseudo-observations, and can be used to either generate the expected values from SPM for reporting or diagnostic purposes. To define an observation as a pseudo-observation, use the command `@observation[label].likelihood=none`. Any observation type can be used as a pseudo-observation. SPM can also generate simulated observations from pseudo-observations. Note that;

- Output will only be generated if a report command `@report[label].type=observation` is specified.
- The observed values should be supplied (even if they are ‘dummy’ observation). These will be processed by SPM as if they were actual observation values, and must conform to the validations carried out for the other types of likelihood.
- The subcommands `likelihood`, `obs`, `error_value` and `process_error` have no effect when generating the expected values for the pseudo-observation.
- When simulating observations, SPM needs the subcommand `simulation_likelihood` to tell it what sort of likelihood to use. In this case, the `obs`, `error_value` and `process_error` are used to determine the appropriate terms to use for the likelihood when simulating.

7. The report section

The report section specifies the printouts and other outputs from the model. *SPM* does not, in general, produce any output unless requested by a valid report.

Reports from *SPM* can be defined to print the spatial structure, partition and states objects at a particular point in time, as well as layers, observation summaries, estimated parameters and objective function values. See below for a more extensive list.

Reports from *SPM* all conform to a standard style (with one exception — the `estimate_values` report, see below). The standard style is that reports are prefixed with a user-defined label in square brackets (e.g., `[...]`), with the second line indicating the type of report, and the report ending with the line `*end`. For example,

```
[My-report]
report.type: ...
...
*end
```

This syntax should make it easier for external packages to be configured to read *SPM* output. The `extract` functions in the **R** *spm* package uses this information to identify and read *SPM* output.

Note that the `estimate_values` report does not print either a header (e.g., `[...]` or `*end` at the end of the report. This is as the `estimate_values` report is designed to provide a single line (or multi-line for more than one set) vector of the estimated parameter values, suitable for reading by *SPM* (with the command `spm -i`).

Reports, by default, are directed to standard out (see Section 3.3), but this default can be overwritten by specifying an output file (`@report[label].file_name`). Hence reports can be directed to separate files as required. Note that if an output file is defined, any data within it is deleted and replaced with the output from the report. To append data to an output file rather than replacing it, use the subcommand `@report[label].overwrite=false`.

Note that reports can be defined that are not valid, for example printing the partition for a year and/or time-step that does not exist or reporting the covariance matrix when not estimating — although all reports must conform to syntax requirements. In these cases, *SPM* does not generate output.

Not all reports will be generated in all run modes. Some reports are only available in some run modes. For example, when simulating, only simulation reports will be output.

7.1. Printing the model spatial map

Print the spatial co-ordinates of each spatial cell (i.e., row and column labels of each spatial cell) of the spatial structure.

7.2. Printing the partition

Print the partition for a given year or given years and time-step. This prints out, for each row and column defined as a valid cell in the base layer (see Section 4.2), the numbers of individuals in each age class in the partition for each year. Note that this report is evaluated at the end of the time-step in the given year(s).

7.3. Printing the partition at the end of an initialisation

Print the partition following an initialisation phase. This prints out, for each row and column defined as a valid cell in the base layer (see Section 4.2), the numbers of individuals in each age class in the partition at the end of that initialisation phase.

7.4. Printing a process summary

Print a summary of a process. Depending on the process, different summaries are produced. These typically detail the type of process, its parameters and other options, and any associated details.

7.5. Printing derived quantities

Print out the description of the derived parameter, and the values of the derived quantity as recorded in the model state, for each year of the model. In addition, the report prints out the values of the derived quantity at the end of each initialisation phase.

7.6. Printing the estimated parameters

Print a summary of the estimated parameters, including the parameter name, lower and upper bounds, the label of the prior, and its value.

7.7. Printing the estimated parameters in a vector format

Print the estimated parameter values out as a vector, in a format suitable for use with `spm -i`. The `estimate_values` report prints two lines — a line for the labels of the estimated parameters, and then a line of the values of the estimated parameters. For run modes that produce multi-line output (for example, MCMCs or profiles), only the first line contains the labels of the estimated parameters. All subsequent lines are the values of the estimated parameters only (with each line representing a single set of parameter values).

Note that unlike other reports, the `estimate_values` report does not print either a header (e.g., `[...]` or `*end` at the end.

7.8. Printing the objective function

Print the total objective function value, and the value of all observations, the values of all priors, and the value of any penalties that have been incurred in the model. Note that if an individual model run does not incur a penalty, then the penalty will not be reported.

7.9. Printing the covariance matrix

Print the Hessian and covariance matrices if estimating and if the covariance has been requested by `@minimiser[label].covariance=true`.

7.10. Printing observations, fits, and residuals

Prints out the area (from the observation categorical layer), observed values (as supplied in the input configuration file), expected values as calculated by the model, residuals (observed — expected), the error value (as modified by any additional process error), and the contribution to the total objective function of that individual point in the observation.

Note that constants in likelihoods are often ignored in the objective function score of individual points. Hence, the total score from an observation equals the contribution of the objective function scores from each individual point plus a constant term (if applicable). In likelihoods without a constant term, then the total score from an observation will equal the contribution of the objective function scores from each individual point.

If simulating, then the contribution to the objective function of each observation is reported as zero.

7.11. Printing simulated observations

Prints out a complete observation definition (i.e., in the form defined by `@report[label].type=observation`), but with observed values replaced by randomly generated simulated values. The output is in a form suitable for use within a SPM input configuration file, reproducing the command and subcommands from the input configuration file.

7.12. Printing the ageing error misclassification matrix

Prints out the ageing error misclassification matrix.

7.13. Printing layers and meta-layers

Prints the values in the layer (including user supplied layers, abundance and biomass layers, derived layers, meta-layers and derived meta-layers) for given year and at the end of a given time-step.

7.14. Printing a derived view via a categorical layer

Prints a summary of the partition, as seen via a categorical layer. Here, values within the spatial cells of a partition are aggregated within the regions defined by the categorical layer for a given age range and given model categories.

7.15. Printing selectivities

Prints the values of a selectivity for each age in the partition, for a given year and at then end of a given time-step.

7.16. Printing the random number seed

Prints the random number seed used by SPM to generate the random number sequence. Future runs made with the same random number seed and the same model will produce identical outputs.

7.17. Printing the size-weight relationship

Prints a summary of the size-weight relationship used by SPM for each category by printing the mean weight for a list of sizes. Useful for verifying that the choice of parameters (and their magnitude) are sensible choices.

7.18. Printing the size-at-age relationship

Prints a summary of the size-at-age relationship used by SPM for each category. For each age between `min_age` and `max_age`, prints the mean size. Useful for verifying that the choice of parameters (and their magnitude) are sensible choices.

7.19. Printing the weight-at-age relationship

Prints a summary of the mean weight-at-age relationship used by SPM for each category. For each age between `min_age` and `max_age`, prints the mean weight. Useful for verifying that the choice of parameters (and their magnitude) are sensible choices.

7.20. Printing the results of an MCMC

Print the MCMC samples, objective function values, and proposal covariance matrix following an MCMC.

8. Population command and subcommand syntax

8.1. Model structure

@model1 Define the spatial structure, population structure, annual cycle, and model years

nrows The number of rows n_{rows} in the spatial structure

Type: Integer

Default: No default

Value: A positive integer, $n_{rows} > 0$

ncols The number of columns n_{cols} in the spatial structure

Type: Integer

Default: No default

Value: A positive integer, $n_{cols} > 0$

layer The label for the base layer

Type: String

Default: No default

Value: Must be a label of a `numeric` layer defined by `@layer`

cell_length The length (distance) of one side of a cell

Type: Constant

Default: 1

Value: A positive real number

categories Labels of the categories (rows) of the population component of the partition

Type: Vector of strings, of length $1 \dots n_{categories}$

Default: No default

Value: Names of categories must be unique

min_age Minimum age of the population

Type: Integer

Default: No default

Value: A non-negative integer, $age_{min} \geq 0$ and $age_{min} \leq age_{max}$

max_age Maximum age of the population

Type: Integer

Default: No default

Value: A non-negative integer, $age_{max} \geq 0$ and $age_{min} \leq age_{max}$

age_plus_group Define the largest age as a plus group

Type: Switch

Default: True

Value: Defines the largest age as a plus group

age_size Define the label of the associated age-size relationship for each category

Type: Vector of strings, of length $n_{categories}$
Default: No default
Value: Must be labels of command @age_size

`initialisation_phases` Define the labels of the phases of the initialisation

Type: Vector of strings, of length of the number of initialisation phases
Default: No default
Value: A valid label defined by @initialisation_phase

`initial_year` Define the first year of the model, immediately following initialisation

Type: Integer
Default: No default
Value: Defines the first year of the model, ≥ 1 , e.g. 1990

`current_year` Define the current year of the model

Type: Integer
Default: No default
Value: Defines the current year of the model, i.e., the model is run from @model.first_year to @model.current_year

`time_steps` Define the @time_step labels (in order that they are applied) to form the annual cycle

Type: String vector
Default: No default
Value: Defines the labels of the time-steps that are run in each year

8.2. Initialisation

The methods for initialisation available are,

- Iterative

Each type of initialisation requires a set of subcommands and arguments specific to that type.

@initialisation_phase label Define the processes and years of the initialisation phase with label

`type` Define the type of initialisation

Type: String
Default: No default
Value: A valid type of initialisation

8.2.1. @initialisation_phase[label].type=iterative

years Define the number of years to run

Type: Integer

Default: No default

Value: A non-negative integer

processes Define the processes (in order of occurrence) to run in each year of the initialisation

Type: String vector

Default: No default

Value: A valid process label, from one of @process

8.3. time-steps

@time_step *label* Define a time-step with label

processes Define the process labels, in the order that they are applied, for the time-step

Type: String vector

Default: No default

Value: Defines the labels of the processes for that time-step

8.4. Processes

The population processes available are,

- Constant recruitment process
- Beverton-Holt stock-recruit relationship recruitment process
- Local Beverton-Holt stock-recruit relationship recruitment process
- Ageing process
- Constant relationship mortality rate process
- Annually varying relationship mortality rate process
- Mortality event (as a number) process
- Mortality event (as a biomass) process
- Category transition process
- Category shift process

The movement processes available are,

- Migration movement
- Adjacent cell movement
- Preference movement

Each type of process requires a set of subcommands and arguments specific to that process.

@process *label* Define a process with label

type Define the type of process
Type: String
Default: No default
Value: A valid type of process

8.4.1. @process[label].type=constant_recruitment

r0 Define the total amount of recruitment at equilibrium abundance levels
Type: Estimable
Default: No default
Value: Total amount (in numbers) of recruitment applied across all categories at equilibrium abundances

categories Define the categories into which recruitment occurs
Type: String vector
Default: No default
Value: Valid categories from @model.categories

proportions Define the proportion of recruitment that occurs into each category
Type: Estimable vector, of length categories
Default: No default
Value: Proportion of the annual recruitment that is applied to each category

age Define the age that receives recruitment
Type: Integer
Default: The minimum age of the population
Value: The age class that receives recruitment

layer Name of the layer used to determine where recruitment occurs
Type: String
Default: No default
Value: A valid layer as defined by @layer. If a numeric layer, then recruitment is in proportion to the layer values. Note that the layer values must be non-negative

8.4.2. @process[label].type=bh_recruitment

r0 Define the total amount of recruitment at equilibrium abundance levels
Type: Estimable
Default: No default
Value: Total amount (in numbers) of recruitment applied across all categories at equilibrium abundances

categories Define the categories into which recruitment occurs
Type: String vector
Default: No default
Value: Valid categories from @model.categories

`proportions` Define the proportion of recruitment that occurs into each category

Type: Estimable vector, of length `@process[label].categories`

Default: No default

Value: Proportion of the annual recruitment that is applied to each category

`age` Define the age that receives recruitment

Type: Integer

Default: The minimum age of the population

Value: The age class that receives recruitment

`steepness` Define the Beverton-Holt stock recruitment relationship steepness (h) parameter

Type: Estimable

Default: 1.0

Value: Steepness value between 0.2 and 1.0

`b0` Define the `@initialization_phase` label for the value of the derived quantity to use as the value of the spawning stock biomass (B_0)

Type: String

Default: No default

Value: Must be a valid `@derived_quantity` label

`ssb` Define the label of the `@derived_quantity` that defines the spawning stock biomass (SSB)

Type: String

Default: No default

Value: Must be a valid `@derived_quantity` label

To be implemented

Default changed.

`ssb_offset` Define the offset (in years) for the year of the derived quantity that is to be applied as the SSB in the stock-recruit relationship

Type: Integer

Default: Defaults to the value of `@process[label].age`

Value: Must be a value ≥ 0

`yces_years` Years for year class strength values

Type: Integer vector or integer range

Default: No default

Value: The expanded vector must be of length `YCS_values`

`yces_values` YCS values

Type: Estimable vector

Default: No default

Value: Must be vector

To be implemented

Changed name to be clearer.

`standardise_ycs_years` Years for which the year class strength values are defined to have mean 1.0

Type: Integer vector or integer range

Default: No default

Value: The expanded vector must have values of years between `@model.initial` and `@model.current`

`layer` Name of the layer used to determine where recruitment occurs

Type: String

Default: No layer

Value: A valid layer as defined by `@layer`. If a numeric layer, then recruitment is in proportion to the layer values.

8.4.3. `@process[label].type=local.bh.recruitment`

To be implemented

`r0` Define a multiplier of `r0_layer` for calculating the total amount of recruitment at equilibrium abundance levels

Type: Estimable

Default: No default

Value: Multiplier of `r0_layer` to calculate the total amount (in numbers) of recruitment applied across all categories at equilibrium abundances

`categories` Define the categories into which recruitment occurs

Type: String vector

Default: No default

Value: Valid categories from `@model.categories`

`proportions` Define the proportion of recruitment that occurs into each category

Type: Estimable vector, of length `categories`

Default: No default

Value: Proportion of the annual recruitment that is applied to each category

`age` Define the age that receives recruitment

Type: Integer

Default: No default

Value: The age class that receives recruitment

`steepness` Define the Beverton-Holt stock recruitment relationship steepness (h) parameter

Type: Estimable

Default: 1.0

Value: Steepness value between 0.2 and 1.0

`r0_layer` Define the label of the layer that defines the distribution of recruitment at equilibrium

- abundances for each cell**
 Type: String
 Default: No default
 Value: A valid layer as defined by @layer
- b0_layer** Name of the layer that defines the initial or equilibrium spawning stock biomass (B_0) for each cell
 Type: String
 Default: No layer
 Value: A valid layer as defined by @layer
- ssb_layer** Define the label of the layer that defines the spawning stock biomass (SSB) for each cell in each year
 Type: String
 Default: No default
 Value: A valid layer as defined by @layer
- ssb_offset** Define the offset (in years) for the year of the derived quantity that is to be applied as the SSB in the stock-recruit relationship
 Type: Integer
 Default: Defaults to the value of @process[label].age
 Value: Must be a value ≥ 0
- yca_years** Years for year class strength values
 Type: Integer vector or integer range
 Default: No default
 Value: The expanded vector must be valid model years
- yca_values** YCS values
 Type: Estimable vector, of length yca_years once expanded
 Default: No default
 Value: Must be vector
- standardise_yca_years** Years for which the year class strength values are defined to have mean 1.0
 Type: Integer vector or integer range
 Default: No default
 Value: The expanded vector must be valid model years

8.4.4. @process[label].type=ageing

- categories** Define the categories that ageing is applied to
 Type: String vector
 Default: No default
 Value: Valid categories from @model.categories

8.4.5. @process[label].type=constant_mortality_rate

m Define the constant mortality rate to be applied

Type: Estimable

Default: No default

Value: A positive real number

categories Define the categories that mortality is applied to

Type: String vector

Default: No default

Value: Valid categories from @model.categories

selectivities Define the selectivities applied to each category

Type: String vector, of length categories

Default: No default

Value: Valid selectivity labels defined by @selectivity

layer Name of the layer

Type: String

Default: No layer

Value: A valid layer as defined by @layer. If a numeric layer, then mortality applied is the mortality rate times the value of the layer. Note that the layer values must be non-negative

8.4.6. @process[label].type=annual_mortality_rate

years Define the years when the mortality rates are applied

Type: Integer vector or integer range

Default: No default

Value: Valid model years

m Define the mortality rate to be applied for each year

Type: Estimable vector, of length years once expanded

Default: No default

Value: A vector of positive real numbers

categories Define the categories that mortality is applied to

Type: String vector

Default: No default

Value: A vector of valid categories from @model.categories

selectivities Define the selectivities applied to each category

Type: String vector of length categories

Default: No default

Value: A vector of valid selectivity labels defined by @selectivity

layer Name of the multiplicative layer to be applied to M

Type: String

Default: No layer

Value: A valid numeric layer as defined by @layer. Note that the layer values must be non-negative

8.4.7. @process[label].type=event_mortality

categories Define the categories that the event mortality is applied to

Type: String vector

Default: No default

Value: Valid categories from @model.categories

years Define the years where the mortality even is applied

Type: Integer vector or integer range

Default: No default

Value: Valid model years

layers Define the layers that specify the event mortality (as the abundance) in each year

Type: String vector, of length years once expanded

Default: No default

Value: Valid layers as defined by @layer. Note that the layer values must be non-negative

u_max Define the maximum exploitation rate

Type: Estimable

Default: 0.99

Value: Must be > 0 and < 1

selectivities Define the selectivities applied to each category

Type: String vector, of length categories

Default: No default

Value: Valid selectivity labels defined by @selectivity

penalty Define the event mortality penalty label

Type: String

Default: No default

Value: Valid penalty label defined by @penalty

8.4.8. @process[label].type=biomass_event_mortality

categories Define the categories that the event mortality is applied to

Type: String vector

Default: No default

Value: Valid categories from @model.categories

years Define the years where the mortality event is applied

Type: Integer vector or integer range

Default: No default

Value: Valid years for the model

layers Define the layers that specify the event mortality (as a biomass) in each year

Type: String vector, of length `years` once expanded

Default: No default

Value: Valid layers defined by `@layer`. Note that the layer values must be non-negative

u_max Define the maximum exploitation rate

Type: Constant

Default: 0.99

Value: Must be > 0 and < 1

selectivities Define the selectivities applied to each category

Type: String vector, of length `categories`

Default: No default

Value: Valid selectivity labels defined by `@selectivity`

penalty Define the event mortality penalty label

Type: String

Default: No default

Value: Valid penalty label defined by `@penalty`

8.4.9. `@process[label].type=category_transition`

from Define the categories that are the source of the transition process

Type: String vector

Default: No default

Value: A valid list of categories from `@model.categories`

selectivities Define the selectivities applied to the source categories

Type: String vector, of length `from`

Default: No default

Value: A valid list of selectivity labels defined by `@selectivity`

to Define the categories that are the sink of the transition process

Type: String vector

Default: No default

Value: A valid list of categories from `@model.categories`

years Define the years where the category transition is applied

Type: Integer vector or integer range

Default: No default

Value: Valid model years

`layers` Define the layers that specify the event mortality (as N for each cell) in each year

Type: String vector, of length `years` once expanded

Default: No default

Value: Valid layers defined by `@layer`. Note that the layer values must be non-negative

`penalty` Define the penalty to encourage models parameter values away from those which result in not enough individuals to move

Type: String

Default: No default

Value: Valid penalty label defined by `@penalty`

8.4.10. `@process[label].type=category_transition_rate`

`from` Define the category that is the source of the transition process

Type: String

Default: No default

Value: A valid category from `@model.categories`

`selectivities` Define the selectivities applied to the source categories

Type: String vector, of length `from`

Default: No default

Value: A valid list of selectivity labels defined by `@selectivity`

`to` Define the category that is the sink of the transition process

Type: String

Default: No default

Value: A valid category from `@model.categories`

`proportions` Define the proportion of individuals to move

Type: Estimable

Default: No default

Value: A value ≥ 0 and ≤ 1

`layer` Name of the layer

Type: String

Default: No default

Value: A valid layer as defined by `@layer`. If a numeric layer, then rate applied to each cell is multiplied by the value of the layer. Note that the layer values must be non-negative

8.4.11. `@process[label].type=migration`

`categories` Define the categories that the migration movement event is applied to

Type: String vector

Default: No default

Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category

Type: String vector, of length `categories`

Default: No default

Value: Valid selectivity labels defined by `@selectivity`

`proportion` Define the constant multiplier for the proportion of individuals that migrate

Type: Estimable

Default: 1.0

Value: A real number between 0 and 1, inclusive

`source_layer` Define the label of a layer that defines the source cells of the migration movement event

Type: String

Default: No default

Value: A valid layer defined by `@layer`

`sink_layer` Define the label of a layer that defines the sink cells of the migration movement event

Type: String

Default: No default

Value: A valid layer defined by `@layer`

8.4.12. `@process[label].type=adjacent_cell`

`categories` Define the categories that the adjacent cell movement event is applied to

Type: String vector

Default: No default

Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category

Type: String vector, of length `categories`

Default: No default

Value: Valid selectivity labels defined by `@selectivity`

`layer` Define the label of a gradient layer that defines the the relative strength of movement to adjacent cells

Type: String

Default: Default 1 in every cell, equivalent to uniform diffusion

Value: A valid layer defined by `@layer`

`proportion` Define the constant multiplier for the proportion that moves from each cell to the neighbouring cell

Type: Estimable

Default: 1.0

Value: A real number between 0 and 1, inclusive

8.4.13. @process[label].type=preference

`categories` Define the categories that the preference function movement is applied to

Type: String vector

Default: No default

Value: Valid categories from `@model.categories`

`proportion` Define the constant multiplier for the proportion that the preference function movement is applied to

Type: Estimable

Default: 1.0

Value: A real number between 0 and 1, inclusive

`preference_functions` Define the labels of the individual preference functions that make up the total preference function

Type: String vector

Default: No default

Value: Valid preference function labels defined by `@preference_function`

8.5. Preference functions

The individual preference functions available are,

- Constant
- Normal
- Double normal
- Logistic
- Inverse logistic
- Exponential
- Threshold
- Categorical
- Monotonic categorical

Each type of preference function requires a set of subcommands and arguments specific to that function.

To be implemented

I added the requirements for layers to be positive or strictly positive below. Alistair, can you check please.

@preference_function *label* Define a preference function with label

`type` Define the type of preference function
Type: String
Default: No default
Value: A valid type of preference function

8.5.1. @preference_function[label].type=constant

`layer` Defines the layer which supplies the preference function independent variable
Type: String
Default: No default
Value: A valid layer defined by @layer

`alpha` Defines the multiplicative constant α
Type: Estimable
Default: No default

8.5.2. @preference_function[label].type=normal

`layer` Defines the layer which supplies the preference function independent variable
Type: String
Default: No default
Value: A valid layer defined by @layer

`alpha` Defines the multiplicative constant α
Type: Estimable
Default: No default

`mu` Defines the μ parameter of the normal preference function
Type: Estimable
Default: No default

`sigma` Defines the σ parameter of the normal preference function
Type: Estimable
Default: No default

8.5.3. @preference_function[label].type=double_normal

`layer` Defines the layer which supplies the preference function independent variable
Type: String
Default: No default
Value: A valid layer defined by @layer

`alpha` Defines the multiplicative constant α

Type: Estimable
Default: No default

`mu` Defines the μ parameter of the double-normal preference function
Type: Estimable
Default: No default

`sigma_l` Defines the σ_L parameter of the double-normal preference function
Type: Estimable
Default: No default

`sigma_r` Defines the σ_R parameter of the double-normal preference function
Type: Estimable
Default: No default

8.5.4. `@preference_function[label].type=logistic`

`layer` Defines the layer which supplies the preference function independent variable
Type: String
Default: No default
Value: A valid layer defined by `@layer`, with strictly positive values only

`alpha` Defines the multiplicative constant α
Type: Estimable
Default: No default

`a50` Defines the a_{50} parameter of the logistic preference function
Type: Estimable
Default: No default

`ato95` Defines the a_{to95} parameter of the logistic preference function
Type: Estimable
Default: No default

8.5.5. `@preference_function[label].type=inverse_logistic`

`layer` Defines the layer which supplies the preference function independent variable
Type: String
Default: No default
Value: A valid layer defined by `@layer`, with strictly positive values only

`alpha` Defines the multiplicative constant α
Type: Estimable
Default: No default

a50 Defines the a_{50} parameter of the inverse-logistic preference function
Type: Estimable
Default: No default

ato95 Defines the a_{to95} parameter of the inverse-logistic preference function
Type: Estimable
Default: No default

8.5.6. @preference_function[label].type=exponential

layer Defines the layer which supplies the preference function independent variable
Type: String
Default: No default
Value: A valid layer defined by @layer of positive values only

alpha Defines the multiplicative constant α
Type: Estimable
Default: No default

lambda Defines the λ parameter of the exponential preference function
Type: Estimable
Default: No default

8.5.7. @preference_function[label].type=threshold

layer Defines the layer which supplies the preference function independent variable
Type: String
Default: No default
Value: A valid layer defined by @layer

alpha Defines the multiplicative constant α
Type: Estimable
Default: No default

n Defines the N parameter of the threshold preference function
Type: Estimable
Default: No default

lambda Defines the λ parameter of the threshold preference function
Type: Estimable
Default: No default

8.5.8. @preference_function[label].type=categorical

layer Defines the layer which supplies the preference function independent variable

Type: String

Default: No default

Value: A valid layer defined by @layer

alpha Defines the multiplicative constant α

Type: Estimable

Default: No default

category_labels Defines the unique labels of layer in order of their coefficients

Type: String vector

Default: No default

Value: A complete set of unique values of labels in layer in order of category_values

category_values Defines the coefficients for each unique label of layer in order of their labels

Type: String vector

Default: No default

Value: A complete set of positive values of labels in layer in order of category_labels

8.5.9. @preference_function[label].type=monotonic_categorical

layer Defines the layer which supplies the preference function independent variable

Type: String

Default: No default

Value: A valid layer defined by @layer

alpha Defines the multiplicative constant α

Type: Estimable

Default: No default

category_labels Defines the unique labels of layer in order of their coefficients

Type: String vector

Default: No default

Value: A complete set of unique values of labels in layer in order of category_values

category_values Defines the coefficients for each unique label of layer in order of their labels

Type: Numeric vector

Default: No default

Value: A complete set of positive values of labels in layer in order of category_labels

8.6. Layers

The available layer types are,

- Numeric
- Categorical
- Distance
- Abundance
- Biomass
- Abundance density
- Biomass density
- Meta-layer
- Derived layer
- Derived meta-layer

@layer *label* Define a layer function with label

type Define the type of layer

Type: String

Default: No default

Value: A valid type of layer

8.6.1. @layer[label].type=numeric

data Define the values of the layer

Type: Constant vector, with total length @model.ncols × @model.nrows

Default: No default

Value: A vector of values of length equal to the number of elements defined for the spatial structure

8.6.2. @layer[label].type=categorical

data Define the values of the layer

Type: Constant vector, with total length @model.ncols × @model.nrows

Default: No default

Value: A vector of values of length equal to the number of elements defined for the spatial structure

8.6.3. @layer[label].type=distance

There are no other subcommands for @layer[label].type=distance.

8.6.4. @layer[label].type=abundance

`categories` Define the categories are used to calculate the abundance
Type: String vector
Default: No default
Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category
Type: String vector, of length `categories`
Default: No default
Value: Valid selectivity labels from `@selectivity`

8.6.5. @layer[label].type=biomass

`categories` Define the categories are used to calculate the biomass
Type: String vector
Default: No default
Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category
Type: String vector, of length `categories`
Default: No default
Value: Valid selectivity labels from `@selectivity`

8.6.6. @layer[label].type=abundance_density

`categories` Define the categories are used to calculate the abundance
Type: String vector
Default: No default
Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category
Type: String vector, of length `categories`
Default: No default
Value: Valid selectivity labels from `@selectivity`

8.6.7. @layer[label].type=biomass_density

`categories` Define the categories are used to calculate the biomass
Type: String vector
Default: No default
Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category

Type: String vector, of length categories
Default: No default
Value: Valid selectivity labels from @selectivity

8.6.8. @layer[label].type=meta

years Define the years

Type: Integer vector or integer range
Default: No default
Value: Must be valid model years

layers Define the layer labels for each of the years

Type: String vector, of length year once expanded
Default: No default
Condition: Listed layers cannot be @layer[label].type=meta_layer. Command has to have either layers or as_meta_layer but not both

To be implemented

data Define the values of the meta-layer directly

Type: Constant vector, with total length @model.ncols × @model.nrows × years once expanded
Default: No default
Value: A vector of values of length equal to the number of elements defined for the spatial and temporal structure
Condition: @layer[label].type=meta has to have either layers or data but not both

initialisation_layers Define the layers label to use during the initialisation

Type: String vector, of length the number of initialisation phases
Default: No default
Condition: Listed layers cannot be @layer[label].type=meta

8.6.9. @layer[label].type=derived

To be implemented

years Define the years when the calculation is performed

Type: Integer vector or integer range
Default: If not specified, calculation is carried out at ever model year
Value: Must be valid model years once expanded, including initialisation steps

time_step Define the time-step at which the calculation is performed

Type: String
Default: No default
Value: Valid label from @time_step

layers Define the layers to be used in the calculations

Type: String vector

Default: No default

Value: Valid layers as defined by `@layer` or valid meta-layers as defined by command `@layer[label].type=meta_layer`, in which case the appropriate years will be extracted

`parameters` Define the user-defined parameters within the function

Type: String vector

Default: No default

Value: Unique names of user-defined parameters

`parameter_values` Define the initial values of the user-defined parameters within the function

Type: Vector of individually estimable values, of length `parameters`

Default: No default

`formula` Define the calculation to be applied

Type: String

Default: No default

Condition: All parameters and layers used have to be defined above

8.6.10. `@layer[label].type=derived meta`

To be implemented

`time_step` Define the time-step at which the calculation is performed

Type: String

Default: No default

Value: Valid label from `@time_step`

`layers` Define the layers to be used in the calculations

Type: String vector

Default: No default

Value: Valid layers as defined by `@layer` or valid meta-layers as defined by command `@layer[label].type=meta_layer`, in which case the appropriate years will be extracted

`parameters` Define the user-defined parameters within the function

Type: String vector

Default: No default

Value: Unique names of user-defined parameters

`parameter_values` Define the initial values of the user-defined parameters within the function

Type: Vector of individually estimable values, of length `parameters`

Default: No default

`formula` Define the calculation to be applied

Type: String

Default: No default

Condition: All parameters and layers used have to be defined above

8.7. Derived quantities

The individual types of derived quantities available are,

- Abundance
- Biomass

@derived_quantity *label* Define a derived quantity with label

type Define the type of derived quantity

Type: String

Default: No default

Value: A valid type of derived quantity, either `abundance` or `biomass`

8.7.1. @derived_quantity[label].type=abundance

categories Define the categories are used to calculate the derived quantity

Type: String vector

Default: No default

Value: Valid categories from `@model.categories`

selectivities Define the selectivities

Type: String vector, of length `categories`

Default: No default

Value: Valid selectivity labels from `@selectivity`

initialisation_time_steps Define the time-steps during the initialisation phases at the end of which the derived quantity is calculated

Type: String

Default: No default

Value: A valid time-step label from `@time_step`

time_step Define the time-step at the end of which the derived quantity is calculated

Type: String

Default: No default

Value: A valid time-step label from `@time_step`

layer Name of the layer

Type: String

Default: No default

Value: A valid layer as defined by `@layer`. If a numeric layer, then value is the sum of the each cell is

multiplied by the value of the layer.

8.7.2. `@derived_quantity[label].type=biomass`

`categories` Define the categories are used to calculate the derived quantity

Type: String vector

Default: No default

Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities

Type: String vector, of length `categories`

Default: No default

Value: Valid selectivity labels from `@selectivity`

`initialisation_time_steps` Define the time-steps during the initialisation phases at the end of which the derived quantity is calculated

Type: String

Default: No default

Value: A valid time-step label from `@time_step`

`time_step` Define the time-step at the end of which the derived quantity is calculated

Type: String

Default: No default

Value: A valid time-step label from `@time_step`

`layer` Name of the layer

Type: String

Default: No default

Value: A valid layer as defined by `@layer`. If a numeric layer, then value is the sum of the each cell biomass multiplied by the value of the layer.

8.8. Age-size relationship

The individual types of size-at-age relationships available are,

- none
- von Bertalanffy
- Schnute

`@age_size label` Define an age-size relationship with label

`type` Define the type of size-at-age relationship

Type: String

Default: No default

Value: A valid type of size-at-age relationship

8.8.1. @age_size[label].type=von_bertalanffy

linf Define the L_{∞} parameter of the von Bertalanffy relationship

Type: Estimable

Default: No default

Value: A positive real number

Condition: Only define if using the von Bertalanffy relationship

k Define the k parameter of the von Bertalanffy relationship

Type: Estimable

Default: No default

Value: A positive real number

Condition: Only define if using the von Bertalanffy relationship

t0 Define the t_0 parameter of the von Bertalanffy relationship

Type: Estimable

Default: No default

Value: A real number

Condition: Only define if using the von Bertalanffy relationship

distribution Define the distribution of sizes-at-age around the mean

Type: String

Default: Normal

Value: Either normal or lognormal

Condition: Only define if using the von Bertalanffy relationship

by_length Specifies if the linear interpolation of c.v.s is a linear function of mean size or of age

Type: Logical

Default: True

Value: If true, the the c.v. is a function of length, else a function of age

cv Define the c.v. of the distribution of sizes-at-age around the mean

Type: Estimable

Default: No default

Value: A positive real number

growth_proportions Define the proportion of the year for each time-step for evaluating size

Type: Constant vector

Default: No default

Value: A vector of values, ≤ 1 of length equal to the number of time-steps

size_weight Define the label of the associated size-weight relationship

Type: String

Default: No default

Value: A valid label from @size_weight

8.8.2. @age_size[label].type=schnute

y1 Define the y_1 parameter of the Schnute relationship

Type: Estimable

Default: No default

Value: A positive real number

Condition: Only define if using the Schnute relationship

y2 Define the y_2 parameter of the Schnute relationship

Type: Estimable

Default: No default

Value: A positive real number

Condition: Only define if using the Schnute relationship

tau1 Define the τ_1 parameter of the Schnute relationship

Type: Estimable

Default: No default

Value: A real number

Condition: Only define if using the Schnute relationship

tau2 Define the τ_2 parameter of the Schnute relationship

Type: String

Default: Normal

Value: Either normal or lognormal

Condition: Only define if using the Schnute relationship

a Define the a parameter of the Schnute relationship

Type: String

Default: Normal

Value: Either normal or lognormal

Condition: Only define if using the Schnute relationship

b Define the b parameter of the Schnute relationship

Type: String

Default: Normal

Value: Either normal or lognormal

Condition: Only define if using the Schnute relationship

by_length Specifies if the linear interpolation of c.v.s is a linear function of mean size or of age

Type: Logical

Default: True

Value: If true, the c.v. is a function of length, else a function of age

cv Define the c.v. of the distribution of sizes-at-age around the mean

Type: Estimable

Default: No default

Value: A positive real number

`growth_proportions` Define the proportion of the year for each time-step for evaluating size
 Type: Constant vector
 Default: No default
 Value: A vector of values, ≤ 1 of length equal to the number of time-steps

`size_weight` Define the label of the associated size-weight relationship
 Type: String
 Default: No default
 Value: A valid label from `@size_weight`

8.9. Size-weight

The individual types of size-weight relationship available are,

- None
- Basic

`@size_weight label` Define a size-weight relationship with label

`type` Define the type of relationship
 Type: String
 Default: No default
 Value: A valid type of size-weight relationship

8.9.1. `@size_weight[label].type=none`

There are no other subcommands for `@size_weight[label].type=none`.

8.9.2. `@size_weight[label].type=basic`

a Define the *a* parameter of the basic size-weight relationship
 Type: Estimable
 Default: No default
 Value: A positive real number

b Define the *b* parameter of the basic size-weight relationship
 Type: Estimable
 Default: No default
 Value: A positive real number

8.10. Selectivities

The individual selectivity functions available are,

- Constant
- Knife edge
- All values
- All values bounded
- Increasing
- Logistic
- Inverse Logistic
- Logistic producing
- Double normal
- Double exponential

Each type of selectivity function requires a set of subcommands and arguments specific to that function.

@selectivity *label* Define a selectivity function with label

type Define the type of selectivity function

Type: String

Default: No default

Value: A valid type of selectivity function

8.10.1. @selectivity[label].type=constant

c Defines the *C* parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

8.10.2. @selectivity[label].type=knife_edge

e Defines the *E* parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

8.10.3. @selectivity[label].type=all_values

v Defines the *V* parameters (one for each age class) of the selectivity function

Type: Estimable vector

Default: No default

Value: A vector of positive real numbers, of length equal to the number of age classes

8.10.4. `@selectivity[label].type=all_values_bounded`

- l Defines the L parameter of the selectivity function
 Type: Integer
 Default: No default
 Value: A positive real number

- h Defines the H parameter of the selectivity function
 Type: Integer
 Default: No default
 Value: A positive real number, must be greater than L

- v Defines the V parameters (one for each age class from L to H) of the selectivity function
 Type: Estimable vector
 Default: No default
 Value: A vector of positive real numbers, of length equal to the number of age classes from L to H

8.10.5. `@selectivity[label].type=increasing`

- alpha Defines the α parameter of the selectivity function
 Type: Estimable
 Default: No default
 Value: A positive real number

- l Defines the L parameter of the selectivity function
 Type: Integer
 Default: No default
 Value: A positive real number

- h Defines the H parameter of the selectivity function
 Type: Integer
 Default: No default
 Value: A positive real number, must be greater than L

- v Defines the V parameters (one for each age class from L to H) of the selectivity function
 Type: Estimable vector
 Default: No default
 Value: A vector of positive real numbers, of length equal to the number of age classes from L to H

8.10.6. `@selectivity[label].type=logistic`

- alpha Defines the α parameter of the selectivity function
 Type: Estimable
 Default: No default
 Value: A positive real number

a50 Defines the a_{50} parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

ato95 Defines the a_{to95} parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

8.10.7. @selectivity[label].type=inverse_logistic

alpha Defines the α parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

a50 Defines the a_{50} parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

ato95 Defines the a_{to95} parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

8.10.8. @selectivity[label].type=logistic_producing

alpha Defines the α parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

l Defines the L parameter of the selectivity function

Type: Integer

Default: No default

Value: A positive real number

h Defines the H parameter of the selectivity function

Type: Integer

Default: No default

Value: A positive real number, must be greater than L

a50 Defines the a_{50} parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

ato95 Defines the a_{to95} parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

8.10.9. @selectivity[label].type=double_normal

alpha Defines the α parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

mu Defines the μ parameter of the selectivity function

Type: Estimable

Default: No default

sigma_l Defines the σ_L parameter of the selectivity function

Type: Estimable

Default: No default

sigma_r Defines the σ_R parameter of the selectivity function

Type: Estimable

Default: No default

8.10.10. @selectivity[label].type=double_exponential

alpha Defines the α parameter of the selectivity function

Type: Estimable

Default: No default

Value: A positive real number

x1 Defines the x_1 parameter of the selectivity function

Type: Integer

Default: No default

x2 Defines the x_2 parameter of the selectivity function

Type: Integer

Default: No default

x_0 Defines the x_0 parameter of the selectivity function

Type: Estimable

Default: No default

y_0 Defines the y_0 parameter of the selectivity function

Type: Estimable

Default: No default

y_1 Defines the y_1 parameter of the selectivity function

Type: Estimable

Default: No default

y_2 Defines the y_2 parameter of the selectivity function

Type: Estimable

Default: No default

To be implemented

Not implemented yet. A way to apply joint selectivity would be to arbitrarily fix the first selectivity to one and only estimate the second one (say using a pointer?). If the estimated selectivity is above 1, it gets fixed to 1 and the other one gets estimated. Both get reported.

@joint.selectivity *label* Define a joint selectivity

selectivities Define the labels of the selectivities to be defined as 'joint'

Type: String vector of length 2

Default: No default

Value: Valid @selectivity labels

9. Estimation command and subcommand syntax

9.1. Estimation methods

@estimation

minimiser The label of the minimiser to use, if doing a point estimate

Type: String

Default: No default

Value: A valid label from @minimiser

mcmc The label of the MCMC to use, if doing an MCMC

Type: String

Default: No default

Value: A valid label from @mcmc

profile The labels of the profiles to use, if doing a profile

Type: String

Default: No default

Value: A valid label from @mpd

9.2. Point estimation

Two methods of minimising when doing a point estimate are,

- Numerical differences minimiser
- Differential evolution minimiser

Note that point estimates are required for

- MPDs
- To generate the starting values and covariance matrix for an MCMC
- To calculate the point estimates for profiles

Each type of minimiser requires a set of subcommands and arguments specific to that minimiser. Different minimisers can be called for different model runs or for different run modes (i.e., MCMC, MPDs, or profiles).

@minimiser *label* Define the an minimiser estimator with label

type Define the type of minimiser

Type: String

Default: numerical_differences

Value: A valid type of minimiser, either numerical_differences or de_solver

9.2.1. @minimiser[label].type=numerical_differences

iterations Define the maximum number of iterations for the minimiser

Type: Integer

Default: 1000

Value: A positive integer

evaluations Define the maximum number of evaluations for the minimiser

Type: Integer

Default: 4000

Value: A positive integer

step_size Define the step-size for the minimiser

Type: Constant

Default: 1e-6

Value: A positive real number

tolerance Define the convergence criteria (tolerance) for the minimiser

Type: Constant

Default: 0.002

Value: A positive real number

covariance Specify if SPM should attempt to calculate the covariance matrix, if estimating

Type: Logical

Default: True

Value: Either true or false

9.2.2. @minimiser[label].type=de_solver

population_size Define the minimisers number of populations to generate

Type: Integer

Default: 25

Value: A positive integer

crossover_probability Define the minimisers crossover probability

Type: Integer

Default: 0.9

Value: A positive integer

difference_scale Define the scale of the difference of the parent candidates for the minimiser

Type: Constant

Default: 0.02

Value: A positive real number

max_generations Define the maximum generations for the minimiser convergence

Type: Constant
 Default: 0.002
 Value: A positive real number

`tolerance` Define the convergence criteria (tolerance) for the minimiser
 Type: Constant
 Default: 0.01
 Value: A positive real number

`covariance` Specify if SPM should attempt to calculate the covariance matrix, if estimating
 Type: Logical
 Default: True
 Value: Either true or false

9.3. Monte Carlo Markov Chain (MCMC)

Only one method of carrying out MCMCs is available, Monte Carlo Markov Chain using Metropolis-Hastings

@mcmc *label* Define the MCMC estimation arguments

`type` Define the method of MCMC
 Type: String
 Default: `metropolis_hastings`
 Value: A valid type of MCMC. Currently only Metropolis-Hastings is available

9.3.1. @mcmc.type=metropolis_hastings

`start` Covariance multiplier for the starting point of the Markov chain
 Type: Constant
 Default: 0
 Value: If 0, defines the starting point of the chain as the point estimate. If > 0 , defines the starting point as randomly generated, with covariance matrix equal to the approximate covariance (inverse Hessian) times the value of this start parameter

`length` Length of the Markov chain
 Type: Integer
 Default: No default
 Value: Defines the length of the Markov chain (as a number of iterations)

`keep` Spacing between recorded values in the chain
 Type: Integer
 Default: 1
 Value: Defines the spacing between recorded values in the chain. Samples from the posterior are written to file only if their sample number is evenly divisible by `keep`

- max_correlation** Maximum absolute correlation in the covariance matrix of the proposal distribution
Type: Constant
Default: 0.8
Value: Defines the maximum correlation in the covariance matrix of the proposal distribution. Correlations greater than `max_correlation` are decreased to `max_correlation`, and those less than `-max_correlation` are increased to `-max_correlation`
- covariance_adjustment_method** Method for adjusting small variances in the covariance proposal matrix
Type: String
Default: covariance
Value: Defines the method (either correlation or covariance) for the adjusting small variances in the covariance matrix of the proposal distribution
- correlation_adjustment_diff** Minimum non-zero variance times the range of the bounds in the covariance matrix of the proposal distribution
Type: Constant
Default: 0.0001
Value: Defines the minimum non-zero variance times the difference in the bounds of each parameter in the covariance matrix of the proposal distribution
- step_size** Initial step-size (as a multiplier of the approximate covariance matrix)
Type: Constant
Default: $2.4d^{-0.5}$ where d is the number of estimated parameters
Value: The covariance of the proposal distribution is the approximate covariance (inverse Hessian) times this step-size parameter
- proposal_distribution** The shape of the proposal distribution (either *t* or normal)
Type: String
Default: t
Value: Either `t` or `normal`. Defines whether the proposal distribution should be multivariate *t* rather than multivariate normal
- df** Degrees of freedom of the multivariate *t* proposal distribution
Type: Integer
Default: 4
Value: Defines the degrees of freedom of the multivariate *t* proposal distribution
- adapt_stepsize_at** Iterations in the chain to check and resize the MCMC step-size
Type: Vector of integers
Default: no default
Value: Defines the points during the MCMC iterations to re-evaluate the MCMC step-size argument

9.4. Profiles

@profile *label* Define the profile parameters and arguments

parameter Name of the parameter to be profiled

Type: String

Default: No default

Value: Defines the name of the parameter to be profiled

steps Number of steps (values) at which to profile the parameter

Type: Integer

Default: 10

Value: Defines the steps (number of values) at which to profile the parameter

lower_bound lower bound on parameter

Type: Integer

Default: No default

Value: Defines the lower bound on the range of the parameter to profile

upper_bound Upper bound on parameter

Type: Integer

Default: No default

Value: Defines the upper bound on the range of the parameter to profile

9.5. Defining the parameters to be estimated and their priors

@estimate *parameter_name* Estimate an estimable parameter *parameter_name*

The SPM name of the parameter to estimate

Type: string

Default: No default

Value: A valid SPM parameter name

same Names of the other parameters which are constrained to have the same value

Type: String Vector

Default: No default

Value: Defines the names of all the other parameters which are constrained to have the same value as this parameter

estimation_phase Phase at which this parameter should be estimated, in point estimation

Type: Integer

Default: 1

Value: Defines the phase at which this parameter should be freed

lower_bound Lower bounds on this parameter

Type: Constant vector, of length equal to the parameter length

Default: No default

Value: Defines the lower bound(s) on this parameter

`upper_bound` Upper bound on this parameter

Type: Constant vector, of length equal to the parameter length

Default: No default

Value: Defines the upper bound(s) on this parameter

`mcmc_fixed` Should this parameter be fixed during MCMC?

Type: Switch

Default: False

Value: Define this parameter as fixed during MCMC (i.e., considered a constant for the MCMC)

`prior` Defines the label for the prior for this parameter

Type: String

Default: No default

Value: Defines the label of the prior on this parameter

9.6. Priors

The available priors are,

- uniform
- uniform log
- normal
- normal by standard deviation
- lognormal
- Beta

@prior *label* Define the prior label

type Define the type of prior

Type: String

Default: No default

Value: A valid type of prior

9.6.1. @prior[label].type=uniform

The command `@prior[label].type=uniform` has no other subcommands.

9.6.2. @prior[label].type=uniform_log

The command `@prior[label].type=uniform_log` has no other subcommands.

9.6.3. @prior[label].type=normal

mu Defines the mean μ of the normal prior

Type: Constant

Default: No default

Value: Defines the mean of the normal prior

cv Defines the c.v. c of the normal prior

Type: Constant

Default: No default

Value: Defines the c.v. of the normal prior

9.6.4. @prior[label].type=normal_by_stdev

mu Defines the mean μ of the normal by standard deviation prior

Type: Constant

Default: No default

Value: Defines the mean of the normal by standard deviation prior

sigma Defines the standard deviation σ of the normal by standard deviation prior

Type: Constant

Default: No default

Value: Defines the standard deviation of the normal by standard deviation prior

9.6.5. @prior[label].type=lognormal

mu Defines the mean μ of the lognormal prior

Type: Constant

Default: No default

Value: Defines the mean of the lognormal prior

cv Defines the c.v. c of the lognormal prior

Type: Constant

Default: No default

Value: Defines the c.v. of the lognormal prior

9.6.6. @prior[label].type=beta

a The lower value of the range parameter A of the Beta prior

Type: Constant

Default: No default

Value: Defines the lower value of the range parameter A of the Beta prior

b The upper value of the range parameter B of the Beta prior

Type: Constant

Default: No default

Value: Defines the upper value of the range parameter B of the Beta prior

`mu` Defines the mean μ of the Beta prior

Type: Constant

Default: No default

Value: Defines the mean of the Beta prior

`sigma` Defines the standard deviation σ of the Beta prior

Type: Constant

Default: No default

Value: Defines the standard deviation of the Beta prior

9.7. Defining catchability constants

@catchability *label* Define a catchability constant with *label*

`q` Value of the q parameter

Type: Estimable

Default: No default

Value: Defines the value of the catchability q parameter, a real positive number

9.8. Defining penalties

@penalty *label* Define a penalty with *label*

`log_scale` Defines if the penalty is calculated in log space

Type: Switch

Default: False

Value: Defines if the value of the penalty is calculated as the squared difference or the squared difference in log space

`multiplier` Penalty multiplier

Type: Constant

Default: 1.0

Value: Defines the penalty multiplier

10. Observation command and subcommand syntax

10.1. Observation types

The observation types available are,

Observations of proportions of individuals by age class

Observations of proportions of individuals between categories within each age class

Relative and absolute abundance observations

Relative and absolute biomass observations

Each type of observation requires a set of subcommands and arguments specific to that process.

@observation *label* Define an observation

type Define the type of observation

Type: String

Default: No default

Value: A valid type of observation

10.1.1. @observation[label].type=proportions_at_age

year Define the year that the observation applies to

Type: Integer

Default: No default

Value: A positive integer between @model.initial_year and @model.current_year

time_step Define the time-step that the observation applies to

Type: Integer

Default: No default

Value: A valid time-step

proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to

Type: Constant

Default: 1.0

Value: A real number between 0 and 1, inclusive

categories Define the categories

Type: String vector

Default: No default

Value: Valid categories from @model.categories

selectivities Define the selectivities applied to each category

Type: String vector

Default: No default

Value: Valid selectivity labels defined by @selectivity

`min_age` Define the minimum age for the observation

Type: Integer

Default: No default

Value: A valid age in the range `@model.min_age` and `@model.max_age`

`max_age` Define the maximum age for the observation

Type: Integer

Default: No default

Value: A valid age in the range `@model.min_age` and `@model.max_age`

`age_plus_group` Define is the the maximum age for the observation is a plus group

Type: Switch

Default: True

Value: Either true or false

`ageing_error` Define the label of the ageing-error matrix to be applied (if any)

Type: String

Default: No default

Value: A valid ageing error label

`layer` Name of the categorical layer used to group the spatial cells for the observation

Type: String

Default: No default

Value: A valid layer as defined by `@layer`. Must be a layer of `type=categorical`

`obs [label]` Define the following data as observations for the categorical layer with value `[label]`

Type: Constant vector

Default: No default

Value: The label is valid value from the associated observation layer. It is followed by a vector of values giving the proportions at age. This subcommand is repeated for each unique value of label

`tolerance` Define the tolerance on the sum-to-one error check in SPM

Type: Constant

Default: 0.001

Value: The tolerance on the sum to one error check. If $abs(1 - \sum O_i) > tolerance$ then SPM will report an error

`error_value [label]` Define the following data as error values (e.g., N for multinomial likelihoods, c.v. for lognormal likelihoods, etc.) for the categorical layer with value `[label]`

Type: Constant

Default: No default

Value: A valid value from the associated observation layer. This subcommand is repeated for each unique value of label

`likelihood` Define the likelihood for the observation

Type: String

Default: No default

Value: A valid likelihood

`delta` Define the delta robustifying constant for the likelihood

Type: Constant

Default: 1e-11

Value: A non-negative real number

`process_error` Define the process error term

Type: Constant

Default: No process error

Value: A non-negative real number

`simulation_likelihood` Define the likelihood when doing simulations, if the observations is a pseudo-observation

Type: String

Default: No default

Value: A valid likelihood, except not `none`. Note that this command is ignored if the observation is not a pseudo-observation

10.1.2. `@observation[label].type=proportions.by_category`

`year` Define the year that the observation applies to

Type: Integer

Default: No default

Value: A positive integer between `@model.initial_year` and `@model.current_year`

`time_step` Define the time-step that the observation applies to

Type: Integer

Default: No default

Value: A valid time-step

`proportion_time_step` Define the interpolated proportion of the time-step passes that the observation applies to

Type: Constant

Default: 1.0

Value: A real number between 0 and 1, inclusive

`categories` Define the categories

Type: String vector

Default: No default

Value: Valid categories from `@model.categories`

`categories2` Define the categories

Type: String vector
Default: No default
Value: Valid categories from @model.categories

selectivities Define the selectivities applied to each category
Type: String vector
Default: No default
Value: Valid selectivity labels defined by @selectivity

selectivities2 Define the selectivities applied to each category
Type: String vector
Default: No default
Value: Valid selectivity labels defined by @selectivity

min_age Define the minimum age for the observation
Type: Integer
Default: No default
Value: A valid age in the range @model.min_age and @model.max_age

max_age Define the maximum age for the observation
Type: Integer
Default: No default
Value: A valid age in the range @model.min_age and @model.max_age

age_plus_group Define is the the maximum age for the observation is a plus group
Type: Switch
Default: True
Value: Either true or false

ageing_error Define the label of the ageing-error matrix to be applied
Type: String
Default: No default
Value: A valid ageing error label

layer Name of the categorical layer used to group the spacial cells for the observation
Type: String
Default: No default
Value: A valid layer as defined by @layer. Must be a categorical layer

obs [label] Define the following data as observations for the categorical layer with value [label]
Type: Constant vector
Default: No default
Value: The label is valid value from the associated observation layer. It is followed by a vector of values giving the proportions at age. This subcommand is repeated for each unique value of label

`error_value [label]` Define the following data as error values (e.g., N for multinomial likelihoods, c.v. for lognormal likelihoods, etc.) for the categorical layer with value `[label]`
Type: Constant
Default: No default
Value: A valid value from the associated observation layer. This subcommand is repeated for each unique value of `label`

`likelihood` Define the likelihood for the observation
Type: String
Default: No default
Value: A valid likelihood

`delta` Define the delta robustifying constant for the likelihood
Type: Constant
Default: $1e-11$
Value: A non-negative real number

`process_error` Define the process error term
Type: Constant
Default: No process error
Value: A non-negative real number

`simulation_likelihood` Define the likelihood when doing simulations, if the observations is a pseudo-observation
Type: String
Default: No default
Value: A valid likelihood, except not `none`. Note that this command is ignored if the observation is not a pseudo-observation

10.1.3. `@observation[label].type=abundance`

`year` Define the year that the observation applies to
Type: Integer
Default: No default
Value: A positive integer between `@model.initial_year` and `@model.current_year`

`time_step` Define the time-step that the observation applies to
Type: Integer
Default: No default
Value: A valid time-step

`proportion_time_step` Define the interpolated proportion of the time-step passes that the observation applies to
Type: Constant
Default: 1.0
Value: A real number between 0 and 1, inclusive

`catchability` Define the catchability constant label for the observation

Type: String

Default: No default

Value: A valid `@catchability` label

`categories` Define the categories for which the observations occur

Type: String vector

Default: No default

Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category

Type: String vector

Default: No default

Value: Valid selectivity labels defined by `@selectivity`

`layer` Name of the categorical layer used to group the spacial cells for the observation

Type: String

Default: No default

Value: A valid layer as defined by `@layer`. Must be a categorical layer

`obs [label]` Define the following data as observations for the categorical layer with value

[label]

Type: Constant

Default: No default

Value: The label is valid value from the associated observation layer. It is followed by a value giving the abundance. This subcommand is repeated for each unique value of label

`error_value [label]` Define the following data as error values (e.g., N for multinomial likelihoods, c.v. for lognormal likelihoods, etc.) for the categorical layer with value [label]

Type: Constant

Default: No default

Value: A valid value from the associated observation layer. This subcommand is repeated for each unique value of label

`likelihood` Define the likelihood for the observation

Type: String

Default: No default

Value: A valid likelihood

`delta` Define the delta robustifying constant for the likelihood

Type: Constant

Default: 1e-11

Value: A non-negative real number

`process_error` Define the process error term

Type: Constant

Default: No process error

Value: A non-negative real number

`simulation_likelihood` Define the likelihood when doing simulations, if the observations is a pseudo-observation

Type: String

Default: No default

Value: A valid likelihood, except not `none`. Note that this command is ignored if the observation is not a pseudo-observation

10.1.4. `@observation[label].type=biomass`

`year` Define the year that the observation applies to

Type: Integer

Default: No default

Value: A positive integer between `@model.initial_year` and `@model.current_year`

`time_step` Define the time-step that the observation applies to

Type: Integer

Default: No default

Value: A valid time-step

`proportion_time_step` Define the interpolated proportion of the time-step passes that the observation applies to

Type: Constant

Default: 1.0

Value: A real number between 0 and 1, inclusive

`catchability` Define the catchability constant label for the observation

Type: String

Default: No default

Value: A valid `@catchability` label

`categories` Define the categories into which recruitment occurs

Type: String vector

Default: No default

Value: Valid categories from `@model.categories`

`selectivities` Define the selectivities applied to each category

Type: String vector

Default: No default

Value: Valid selectivity labels defined by `@selectivity`

`layer` Name of the categorical layer used to group the spacial cells for the observation

Type: String

Default: No default

Value: A valid layer as defined by @layer. Must be a categorical layer

`obs [label]` Define the following data as observations for the categorical layer with value [label]

Type: Constant vector

Default: No default

Value: The label is valid value from the associated observation layer. It is followed by a value giving the biomass. This subcommand is repeated for each unique value of label

`error_value [label]` Define the following data as error values (e.g., N for multinomial likelihoods, c.v. for lognormal likelihoods, etc.) for the categorical layer with value [label]

Type: Constant

Default: No default

Value: A valid value from the associated observation layer. This subcommand is repeated for each unique value of label

`likelihood` Define the likelihood for the observation

Type: String

Default: No default

Value: A valid likelihood

`delta` Define the delta robustifying constant for the likelihood

Type: Constant

Default: 1e-11

Value: A non-negative real number

`process_error` Define the process error term

Type: Constant

Default: 0

Value: A non-negative real number

`simulation_likelihood` Define the likelihood when doing simulations, if the observations is a pseudo-observation

Type: String

Default: No default

Value: A valid likelihood, except not `none`. Note that this command is ignored if the observation is not a pseudo-observation

10.2. Defining ageing error

Three methods for including ageing error into estimation with observations are,

- None
- Normal

- Off-by-one

Each type of ageing error requires a set of subcommands and arguments specific to its type.

@ageing_error *label* Define ageing error with *label*

type The type of ageing error

Type: String

Default: No default

Value: Defines the type of ageing error to use

10.2.1. @ageing_error[label].type=none

The `@ageing_error[label].type=none` has no other subcommands.

10.2.2. @ageing_error[label].type=normal

cv Parameter of the normal ageing error model

Type: Constant

Default: No default

Value: Define the c.v. of misclassification

k The *k* parameter of the normal ageing error model

Type: Integer

Default: 0

Value: *cv* defines the proportions of misclassification down and up using the normal model. *k* defines the minimum age of individuals which can be misclassified, e.g., individuals under age *k* have no ageing error

10.2.3. @ageing_error[label].type=off by one

p1 The *p*₁ parameter of the off-by-one ageing error model

Type: Constant

Default: No default

Value: *p*₁ and *p*₂ define the proportions of misclassification down and up by 1 year respectively. *k* defines the minimum age of individuals which can be misclassified, e.g. individuals under age *k* have no ageing error

p2 The *p*₂ parameter of the off-by-one ageing error model

Type: Constant

Default: No default

Value: *p*₁ and *p*₂ define the proportions of misclassification down and up by 1 year respectively. *k* defines the minimum age of individuals which can be misclassified, e.g., individuals under age *k* have no ageing error

k The *k* parameter of the off-by-one ageing error model

Type: Integer

Default: 0

Value: p_1 and p_2 define the proportions of misclassification down and up by 1 year respectively. k defines the minimum age of individuals which can be misclassified, e.g., individuals under age k have no ageing error

11. Report command and subcommand syntax

11.1. Available reports

The report types available are,

1. Print the map (i.e., row and column labels of each spatial cell) of the spatial structure
2. Print the partition at a specific time-step for any number of years
3. Print the partition at the end of an initialisation
4. Print a summary of a process
5. Print a derived quantity
6. Print a summary of the estimated parameters
7. Print the estimated parameters in a vector format (suitable for use with `spm -i`)
8. Print the objective function values
9. Print the covariance matrix
10. Print an observation values, fits, and residuals
11. Print a simulated observation suitable for use in a SPM input configuration file.
12. Print the ageing error misclassification matrix
13. Print a layer
14. Print a derived view via a categorical layer
15. Print a selectivity's values
16. Print the random number seed
17. Print the age-size relationship
18. Print the age-weight relationship
19. Print the size-weight relationship
20. Printing the results of an MCMC

Each type of report requires a set of subcommands and arguments specific to that report.

11.2. Report commands and subcommands

@report *label* Define an output report

type Define the type of report

Type: String

Default: No default

Value: A valid type of report

11.2.1. @report[label].type=spatial_map

`file_name` Define the name of the output file where the report is written
Type: String
Default: No default
Value: A valid file name. If not supplied, then output is directed to the standard out

11.2.2. @report[label].type=partition

`years` Define the years that the partition report applies to
Type: Integer vector or integer range
Default: No default
Value: Valid model years between `@model.initial_year` and `@model.current_year`

`time_step` Define the time-step that the partition report applies to
Type: Integer
Default: No default
Value: A valid time-step

`file_name` Define the name of the output file where the report is written
Type: String
Default: No default
Value: A valid file name. If not supplied, then output is directed to the standard out

`overwrite` Specify if any previous file with the same name as the output file should be overwritten or appended to
Type: Switch
Default: True
Value: Either True or False

11.2.3. @report[label].type=initialisation

`initialisation_phase` Define the phase of initialisation that the partition report applies to
Type: string
Default: No default
Value: A valid phase label, from `@initialisation_phase`

`file_name` Define the name of the output file where the report is written
Type: String
Default: No default
Value: A valid file name. If not supplied, then output is directed to the standard out

`overwrite` Specify if any previous file with the same name as the output file should be

overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.4. @report[label].type=process

process Define the label of the process to summarise

Type: String

Default: No default

Value: A valid label from @process

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.5. @report[label].type=derived_quantity

derived_quantity Define the label of the derived quantity to print

Type: String

Default: No default

Value: A valid label from @derived_quantity

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.6. @report [label] .type=estimate_summary

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.7. @report [label] .type=estimate_value

Prints the estimated parameters in a format suitable for use with `spm -i`.

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

header Specify if the output contains the standard SPM style header at the start of the output

Type: Switch

Default: False

Value: Either True or False

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.8. @report [label] .type=objective_function

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.9. @report[label].type=covariance

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.10. @report[label].type=observation

observation Define the label of the observation to print

Type: String

Default: No default

Value: A valid label from @Observation

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.11. @report[label].type=simulated_observation

observation Define the label of the observation from which to simulate values

Type: String

Default: No default

Value: A valid label from @observation

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be

overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.12. @report [label] .type=ageing_error

ageing_error Define the label of the ageing_error misclassification matrix

Type: String

Default: No default

Value: A valid label from @ageing_error

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.13. @report [label] .type=layer

layer Define the label of the layer to print

Type: String

Default: No default

Value: A valid label from @layer

years Define the years for the printing of the layer

Type: Integer vector or integer range

Default: The first year of the model, @model.initial_year

Value: Valid model years between @model.initial_year and @model.current_year

time_step Define the time-step for the printing of the layer

Type: Integer

Default: The first time-step of the model

Value: A valid time-step

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

`overwrite` Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.14. @report [label] .type=layer_derived_view

`layer` Define the label of the layer to print

Type: String

Default: No default

Value: A valid label from @layer of type categorical

`years` Define the years for the printing of the layer

Type: Integer vector or integer range

Default: No default

Value: Valid model years between @model.initial_year and @model.current_year

`time_step` Define the time-step for the printing of the layer

Type: Integer

Default: The first time-step of the model

Value: A valid time-step

`file_name` Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

`overwrite` Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.15. @report [label] .type=selectivity

`selectivity` Define the label of the selectivity to print

Type: String

Default: No default

Value: A valid label from @selectivity

`year` Define the year for the printing of the selectivity

Type: Integer

Default: No default

Value: A positive integer between @model.initial_year and @model.current_year

`time_step` Define the time-step for the printing of the selectivity

Type: Integer

Default: No default

Value: A valid time-step

`file_name` Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

`overwrite` Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.16. @report [label] .type=random number seed

`file_name` Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

`overwrite` Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.17. @report [label] .type=age_size

`age_size` Define the label of the age-size relationship

Type: String

Default: No default

Value: A valid label from @age_age

`file_name` Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

`overwrite` Specify if any previous file with the same name as the output file should be

overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.18. @report [label] .type=size_weight

size_weight Define the label of the size-weight relationship

Type: String

Default: No default

Value: A valid label from @size_weight

sizes Define the sizes for which to report the mean weights

Type: Constant vector

Default: No default

Value: Values of sizes to report the mean weight

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.19. @report [label] .type=age_weight

age_size Define the label of the age-size relationship

Type: String

Default: No default

Value: A valid label from @age_size

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

11.2.20. @report [label] .type=MCMC

file_name Define the name of the output file where the report is written

Type: String

Default: No default

Value: A valid file name. If not supplied, then output is directed to the standard out

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

Type: Switch

Default: True

Value: Either True or False

12. Other commands and subcommands

@include *file* Include an external file

file The name of the external file to include

Type: string

Default: No default

Value: A valid external file

Condition: The file name must be enclosed in double quotes

Example: @include "my_file.txt"

Note: @include does not denote the end of the previous command block as is the case for all other commands

13. Examples

This simple example is provided to demonstrate syntax of the input configuration file, provide an introduction to the command calls to *SPM*, and respective outputs. Note, we reproduce only a subset of the input configuration files — for more detail, see the example files.

13.1. An example of a simple 1×1 non-spatial model

The first example implements a very simple single spatial cell model (i.e., no movement 1×1 spatial structure) with recruitment, maturation, natural and exploitation mortality, and an annual age increment. The population structure has ages $1 - 50^+$ with categories labelled immature and mature.

The model is initialised over a 200 year period, and applies the following processes,

1. A constant recruitment process, recruiting a constant number of individuals to the first age class (i.e., $age = 1$) in the category labelled immature.
2. A maturation process, where individuals are moved from the immature to the mature categories with a logistic-producing selectivity labelled ‘maturation’.
3. A constant mortality process representing natural mortality, applied as two repeats of the ‘halfM’ process. (Half M used so-as to be able to mimic a $\frac{1}{2}M + F + \frac{1}{2}M$ natural and fishing exploitation set of processes after initialisation.)
4. An ageing process, where all individuals are aged by one year, and with a plus group accumulator age class at $age = 50$.

A second phase of initialisation, of period one year, is applied to allow external validation that the initialisation process has stabilised the population to equilibrium (i.e., by confirming that there is no or at least a small difference in the partition at the end of first and second phases).

Following initialisation, the model runs from the years 1994 to 2007 iterating through two time-steps. The first time-step applies processes of constant recruitment, maturation, and $\frac{1}{2}M + F + \frac{1}{2}M$ processes. The exploitation process (fishing) is applied in the years 1998–2007, with catches defined by the layers Fishing_1998 – Fishing_2007.

The second time-step applies an age increment.

The first 50 lines of the main section of the input configuration file are,

```
# Model structure
@model
nrows 1
ncols 1
layer Base
categories immature mature
min_age 1
max_age 35
age_plus_group True
initial_year 1994
current_year 2007
final_year 2108
cell_length 1
initialisation_phases Phase1 Phase2
time_steps step_one step_two
age_size VB VB

@age_size VB
```

```
type von_bertalanffy
size_weight basic
k 0.093
t0 -0.256
linf 169.07
cv 0.102

@size_weight basic
type basic
a 1.387e-008
b 2.965

# Initialisation
@initialisation_phase Phase1
years 200
time_steps Phase1a Phase1b

@initialisation_phase Phase2
years 1
time_steps Phase1a Phase1c

@time_step Phase1a
processes BHrecruitment Maturation halfM

@time_step Phase1b
processes halfM Ageing

@time_step Phase1c
processes halfM Ageing

# Annual cycle
@time_step step_one
```

The input configuration file includes definitions of required layers and the estimation, observation, and report parameters as external files.

To carry out a run of the model (to verify that the model runs without any syntax errors), use the command `spm -r -c config.spm`. Note that as SPM looks for a file named `config.spm` by default, we can simplify the command to `spm -r`.

To run an estimate, and hence estimate the parameters defined in the file `estimation.spm` (the catchability constant q , recruitment R_0 , and the selectivity parameters a_{50} and a_{t095}), use `spm -e`. Here, we have piped the output to `estimate.log` using the command `spm -e > estimate.log`. SPM reports a the results of each iteration of the estimation, and ends with successful convergence,

```
Convergence was successful
Total elapsed time: 1 second
```

The main part of the output from the estimation run is summarised in the file `estimate.log`, and the final objective function is,

```
[Objective_Score]
report.type: objective_function
obs->CAA-year-1998: 27.8958
obs->CAA-year-1999: 33.1782
obs->CAA-year-2000: 27.5075
obs->CAA-year-2001: 27.0142
obs->CAA-year-2002: 25.7687
obs->CAA-year-2003: 31.705
obs->CAA-year-2004: 31.5322
obs->CAA-year-2005: 28.1053
```

```
obs->CAA-year-2006: 26.9789
obs->CAA-year-2007: 29.4441
obs->CPUE-1998: 0.915501
obs->CPUE-1999: 0.786657
obs->CPUE-2000: -1.61095
obs->CPUE-2001: -0.970155
obs->CPUE-2002: 1.28109
obs->CPUE-2003: -0.0542437
obs->CPUE-2004: 1.37203
obs->CPUE-2005: -0.406572
obs->CPUE-2006: 1.37489
obs->CPUE-2007: 4.79445
prior->catchability[CPUEq].q: 0
prior->process[BHrecruitment].r0: 0
prior->selectivity[FishingSel].a50: 0
prior->selectivity[FishingSel].ato95: 0
total_score: 296.612
*end
```

with parameter estimates,

```
[estimate-values]
report.type: estimate_summary
parameter: catchability[CPUEq].q
lower_bound: 1e-010
upper_bound: 0.1
prior: Uniform
value: 0.0001

parameter: process[BHrecruitment].r0
lower_bound: 10000
upper_bound: 1e+007
prior: Uniform
value: 550000

parameter: selectivity[FishingSel].a50
lower_bound: 1
upper_bound: 20
prior: Uniform
value: 8

parameter: selectivity[FishingSel].ato95
lower_bound: 0.01
upper_bound: 50
prior: Uniform
value: 3

*end
```

A profile on the R_0 parameter can also be run, using `spm -p > profile.log`.

14. Post processing output using R

The **R** package `spm` contains a set of **R** functions for reading SPM output, and is available as a precompiled binary for Microsoft Windows (.zip file) or as a source package (.gz file) for Linux. To check the version number and date of the `spm` **R** package (useful for checking that you have the most recent version), use the function `spm.version()`.

The `spm` **R** package includes a range of extract and write functions to aid post-processing of SPM input configuration files and output. The main extract functions are briefly described below. In addition, the package also has a number of undocumented helper functions, that could be useful for writing your own analysis functions. See the **R** help for more detail e.g., `help(spm)`

15. Troubleshooting

15.1. Introduction

SPM is a complex system, providing many opportunities for error — either because the parameter files do not correctly specify the model, or because the model specified does not work as expected. When in doubt, ask an experienced user. Debugging versions of SPM can also be compiled that help to track down cryptic errors.

When SPM generates an error and the error message makes no sense, please let the SPM authors know. Even if you manage to fix the problem yourself, we may be able to implement a more helpful error message and make life easier for the next person to encounter the problem. Guidelines for reporting an error are given in Section 15.3.

Some parameter values of functions or selectivities can result in either very large or very small numbers. These can, on occasion, generate internal numeric overflow errors within SPM. This is the most common cause of an overflow error, and can result in parameter estimates of NaN. The work-around to this type of error is to impose bounds on parameters that exclude the possibility of an overflow error.

15.2. Reporting errors

When reporting a bug or problem with SPM, please send a bug report to the authors. Use the text SPM: as the start of the subject line in the email. Note that following these guidelines will assist the SPM authors identify, reproduce, and hopefully solve any reported bugs.

Note that SPM is distributed as unsupported software. We are unable to provide much assistance to users — although we will usually endeavour to try. While we would appreciate being notified of any problems or errors in SPM, please note that we may not be able to provide timely solutions.

15.3. Guidelines for reporting a bug in SPM

1. Detail the version of SPM are you using? e.g., “SPM v1.1-2012-07-12 (rev. 4728) Microsoft Windows executable”
2. What operating system or environment are you using? e.g., “IBM-PC Intel CPU running Microsoft Windows XP Service Pack 3”.
3. Give a brief one-line description of the problem, e.g., “a segmentation fault was reported”.
4. If the problem is reproducible, please list the exact steps required to cause it, remembering to include the relevant SPM configuration file, other input files, and any out generated. Specify the *exact* command line arguments that were used, e.g., “Using the command `spm -e config.spm -q > logfile.out` reports a segmentation fault. The input configuration files are attached.”
5. If the problem is not reproducible (only happened once, or occasionally for no apparent reason), please describe the circumstances in which it occurred and the symptoms observed (but note it is much harder to reproduce and hence fix non-reproducible bugs, but if several reports are made over time that relate to the same thing, then this may help to track down the problem), e.g., “SPM crashed, but I cannot reproduce how I did it. It seemed to be related to a local network crash but I cannot be sure.”

6. If the problem causes any error messages to appear, please give the *exact* text displayed, e.g.,
segmentation fault (core dumped).
7. Remember to attach all relevant input and output files so that the problem can be reproduced (it can be helpful to compress these into a single file). Without these, it may not be possible to determine the cause of the problem. Note that it is helpful to be as specific as possible when describing the problem.

16. Acknowledgements

We thank Nokome Bentley (TROPHIA) and Ian Ball (Australian Antarctic Division) for their work that led to the ideas behind the development of the movement paradigm employed in this program. Thanks also to Andy McKenzie, Dave Gilbert, and Murray Smith (NIWA) for helpful discussions with the authors. The SPM logo was designed by Erika Mackay (NIWA).

Much of the structure of SPM, equations, and documentation in this manual draw heavily on similar components of the population model CASAL (Bull et al., 2012). We thank the authors of CASAL for their permission to use their work as the basis for parts of SPM and allow the use of some of the definitions, concepts, and documentation from CASAL in SPM.

The development of SPM was funded by the New Zealand Ministry for Primary Industries, the Ministry of Science and Innovation, and the National Institute of Water & Atmospheric Research Ltd. (NIWA).

17. Quick reference

17.1. Population command and subcommand syntax

@model Define the spatial structure, population structure, annual cycle, and model years

nrows The number of rows n_{rows} in the spatial structure

ncols The number of columns n_{cols} in the spatial structure

layer The label for the base layer

cell_length The length (distance) of one side of a cell

categories Labels of the categories (rows) of the population component of the partition

min_age Minimum age of the population

max_age Maximum age of the population

age_plus_group Define the largest age as a plus group

age_size Define the label of the associated age-size relationship for each category

initialisation_phases Define the labels of the phases of the initialisation

initial_year Define the first year of the model, immediately following initialisation

current_year Define the current year of the model

time_steps Define the @time_step labels (in order that they are applied) to form the annual cycle

@initialisation_phase label Define the processes and years of the initialisation phase with label

type Define the type of initialisation

@initialisation_phase[label].type=iterative

years Define the number of years to run

processes Define the processes (in order of occurrence) to run in each year of the initialisation

@time_step label Define a time-step with label

processes Define the process labels, in the order that they are applied, for the time-step

@process label Define a process with label

type Define the type of process

@process[label].type=constant_recruitment

r0 Define the total amount of recruitment at equilibrium abundance levels

categories Define the categories into which recruitment occurs

proportions Define the proportion of recruitment that occurs into each category

age Define the age that receives recruitment

layer Name of the layer used to determine where recruitment occurs

@process[label].type=bh_recruitment

r0 Define the total amount of recruitment at equilibrium abundance levels

`categories` Define the categories into which recruitment occurs
`proportions` Define the proportion of recruitment that occurs into each category
`age` Define the age that receives recruitment
`steepness` Define the Beverton-Holt stock recruitment relationship steepness (h) parameter
`b0` Define the `@initialization_phase` label for the value of the derived quantity to use as the value of the spawning stock biomass (B_0)
`ssb` Define the label of the `@derived_quantity` that defines the spawning stock biomass (SSB)
`ssb_offset` Define the offset (in years) for the year of the derived quantity that is to be applied as the SSB in the stock-recruit relationship
`yces_years` Years for year class strength values
`yces_values` YCS values
`standardise_yces_years` Years for which the year class strength values are defined to have mean 1.0
`layer` Name of the layer used to determine where recruitment occurs

@process[label].type=local_bh_recruitment

`r0` Define a multiplier of `r0_layer` for calculating the total amount of recruitment at equilibrium abundance levels
`categories` Define the categories into which recruitment occurs
`proportions` Define the proportion of recruitment that occurs into each category
`age` Define the age that receives recruitment
`steepness` Define the Beverton-Holt stock recruitment relationship steepness (h) parameter
`r0_layer` Define the label of the layer that defines the distribution of recruitment at equilibrium abundances for each cell
`b0_layer` Name of the layer that defines the initial or equilibrium spawning stock biomass (B_0) for each cell
`ssb_layer` Define the label of the layer that defines the spawning stock biomass (SSB) for each cell in each year
`ssb_offset` Define the offset (in years) for the year of the derived quantity that is to be applied as the SSB in the stock-recruit relationship
`yces_years` Years for year class strength values
`yces_values` YCS values
`standardise_yces_years` Years for which the year class strength values are defined to have mean 1.0

@process[label].type=ageing

`categories` Define the categories that ageing is applied to

@process[label].type=constant_mortality_rate

`m` Define the constant mortality rate to be applied
`categories` Define the categories that mortality is applied to
`selectivities` Define the selectivities applied to each category
`layer` Name of the layer

@process[label].type=annual_mortality_rate

`years` Define the years when the mortality rates are applied

m Define the mortality rate to be applied for each year
categories Define the categories that mortality is applied to
selectivities Define the selectivities applied to each category
layer Name of the multiplicative layer to be applied to M

@process[label].type=event_mortality

categories Define the categories that the event mortality is applied to
years Define the years where the mortality even is applied
layers Define the layers that specify the event mortality (as the abundance) in each year
u_max Define the maximum exploitation rate
selectivities Define the selectivities applied to each category
penalty Define the event mortality penalty label

@process[label].type=biomass_event_mortality

categories Define the categories that the event mortality is applied to
years Define the years where the mortality event is applied
layers Define the layers that specify the event mortality (as a biomass) in each year
u_max Define the maximum exploitation rate
selectivities Define the selectivities applied to each category
penalty Define the event mortality penalty label

@process[label].type=category_transition

from Define the categories that are the source of the transition process
selectivities Define the selectivities applied to the source categories
to Define the categories that are the sink of the transition process
years Define the years where the category transition is applied
layers Define the layers that specify the event mortality (as N for each cell) in each year
penalty Define the penalty to encourage models parameter values away from those which result in not enough individuals to move

@process[label].type=category_transition_rate

from Define the category that is the source of the transition process
selectivities Define the selectivities applied to the source categories
to Define the category that is the sink of the transition process
proportions Define the proportion of individuals to move
layer Name of the layer

@process[label].type=migration

categories Define the categories that the migration movement event is applied to
selectivities Define the selectivities applied to each category
proportion Define the constant multiplier for the proportion of individuals that migrate
source_layer Define the label of a layer that defines the source cells of the migration movement event
sink_layer Define the label of a layer that defines the sink cells of the migration movement event

@process[label].type=adjacent_cell

categories Define the categories that the adjacent cell movement event is applied to
selectivities Define the selectivities applied to each category
layer Define the label of a gradient layer that defines the the relative strength of movement to adjacent cells
proportion Define the constant multiplier for the proportion that moves from each cell to the neighbouring cell

@process[label].type=preference

categories Define the categories that the preference function movement is applied to
proportion Define the constant multiplier for the proportion that the preference function movement is applied to
preference_functions Define the labels of the individual preference functions that make up the total preference function

@preference_function label Define a preference function with label

type Define the type of preference function

@preference_function[label].type=constant

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α

@preference_function[label].type=normal

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
mu Defines the μ parameter of the normal preference function
sigma Defines the σ parameter of the normal preference function

@preference_function[label].type=double_normal

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
mu Defines the μ parameter of the double-normal preference function
sigma_l Defines the σ_L parameter of the double-normal preference function
sigma_r Defines the σ_R parameter of the double-normal preference function

@preference_function[label].type=logistic

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
a50 Defines the a_{50} parameter of the logistic preference function
ato95 Defines the a_{to95} parameter of the logistic preference function

@preference_function[label].type=inverse_logistic

layer Defines the layer which supplies the preference function independent variable

alpha Defines the multiplicative constant α
a50 Defines the a_{50} parameter of the inverse-logistic preference function
ato95 Defines the a_{to95} parameter of the inverse-logistic preference function

@preference_function[label].type=exponential

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
lambda Defines the λ parameter of the exponential preference function

@preference_function[label].type=threshold

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
n Defines the N parameter of the threshold preference function
lambda Defines the λ parameter of the threshold preference function

@preference_function[label].type=categorical

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
category_labels Defines the unique labels of layer in order of their coefficients
category_values Defines the coefficients for each unique label of layer in order of their labels

@preference_function[label].type=monotonic_categorical

layer Defines the layer which supplies the preference function independent variable
alpha Defines the multiplicative constant α
category_labels Defines the unique labels of layer in order of their coefficients
category_values Defines the coefficients for each unique label of layer in order of their labels

@layer label Define a layer function with label

type Define the type of layer

@layer[label].type=numeric

data Define the values of the layer

@layer[label].type=categorical

data Define the values of the layer

@layer[label].type=distance

@layer[label].type=abundance

categories Define the categories are used to calculate the abundance
selectivities Define the selectivities applied to each category

@layer[label].type=biomass

categories Define the categories are used to calculate the biomass
selectivities Define the selectivities applied to each category

@layer[label].type=abundance.density

categories Define the categories are used to calculate the abundance
selectivities Define the selectivities applied to each category

@layer[label].type=biomass.density

categories Define the categories are used to calculate the biomass
selectivities Define the selectivities applied to each category

@layer[label].type=meta

years Define the years
layers Define the layer labels for each of the years
data Define the values of the meta-layer directly
initialisation_layers Define the layers label to use during the initialisation

@layer[label].type=derived

years Define the years when the calculation is performed
time_step Define the time-step at which the calculation is performed
layers Define the layers to be used in the calculations
parameters Define the user-defined parameters within the function
parameter_values Define the initial values of the user-defined parameters within the function
formula Define the calculation to be applied

@layer[label].type=derived.meta

time_step Define the time-step at which the calculation is performed
layers Define the layers to be used in the calculations
parameters Define the user-defined parameters within the function
parameter_values Define the initial values of the user-defined parameters within the function
formula Define the calculation to be applied

@derived.quantity label Define a derived quantity with label

type Define the type of derived quantity

@derived.quantity[label].type=abundance

categories Define the categories are used to calculate the derived quantity
selectivities Define the selectivities
initialisation_time_steps Define the time-steps during the initialisation phases at the end of which the derived quantity is calculated
time_step Define the time-step at the end of which the derived quantity is calculated
layer Name of the layer

@derived.quantity[label].type=biomass

categories Define the categories are used to calculate the derived quantity
selectivities Define the selectivities
initialisation_time_steps Define the time-steps during the initialisation phases at the end of which the derived quantity is calculated
time_step Define the time-step at the end of which the derived quantity is calculated
layer Name of the layer

@age_size label Define an age-size relationship with label

type Define the type of size-at-age relationship

@age_size[label].type=von bertalanffy

linf Define the L_{∞} parameter of the von Bertalanffy relationship
k Define the k parameter of the von Bertalanffy relationship
t0 Define the t_0 parameter of the von Bertalanffy relationship
distribution Define the distribution of sizes-at-age around the mean
by_length Specifies if the linear interpolation of c.v.s is a linear function of mean size or of age
cv Define the c.v. of the distribution of sizes-at-age around the mean
growth_proportions Define the proportion of the year for each time-step for evaluating size
size_weight Define the label of the associated size-weight relationship

@age_size[label].type=schnute

y1 Define the y_1 parameter of the Schnute relationship
y2 Define the y_2 parameter of the Schnute relationship
tau1 Define the τ_1 parameter of the Schnute relationship
tau2 Define the τ_2 parameter of the Schnute relationship
a Define the a parameter of the Schnute relationship
b Define the b parameter of the Schnute relationship
by_length Specifies if the linear interpolation of c.v.s is a linear function of mean size or of age
cv Define the c.v. of the distribution of sizes-at-age around the mean
growth_proportions Define the proportion of the year for each time-step for evaluating size
size_weight Define the label of the associated size-weight relationship

@size_weight label Define a size-weight relationship with label

type Define the type of relationship

@size_weight[label].type=none

@size_weight[label].type=basic

a Define the a parameter of the basic size-weight relationship
b Define the b parameter of the basic size-weight relationship

@selectivity label Define a selectivity function with label

type Define the type of selectivity function

@selectivity[label].type=constant

c Defines the C parameter of the selectivity function

@selectivity[label].type=knife_edge

e Defines the E parameter of the selectivity function

@selectivity[label].type=all_values

v Defines the V parameters (one for each age class) of the selectivity function

@selectivity[label].type=all_values_bounded

l Defines the L parameter of the selectivity function

h Defines the H parameter of the selectivity function

v Defines the V parameters (one for each age class from L to H) of the selectivity function

@selectivity[label].type=increasing

alpha Defines the α parameter of the selectivity function

l Defines the L parameter of the selectivity function

h Defines the H parameter of the selectivity function

v Defines the V parameters (one for each age class from L to H) of the selectivity function

@selectivity[label].type=logistic

alpha Defines the α parameter of the selectivity function

a50 Defines the a_{50} parameter of the selectivity function

ato95 Defines the a_{to95} parameter of the selectivity function

@selectivity[label].type=inverse_logistic

alpha Defines the α parameter of the selectivity function

a50 Defines the a_{50} parameter of the selectivity function

ato95 Defines the a_{to95} parameter of the selectivity function

@selectivity[label].type=logistic_producing

alpha Defines the α parameter of the selectivity function

l Defines the L parameter of the selectivity function

h Defines the H parameter of the selectivity function

a50 Defines the a_{50} parameter of the selectivity function

ato95 Defines the a_{to95} parameter of the selectivity function

@selectivity[label].type=double_normal

alpha Defines the α parameter of the selectivity function

mu Defines the μ parameter of the selectivity function

sigma_l Defines the σ_L parameter of the selectivity function

sigma_r Defines the σ_R parameter of the selectivity function

@selectivity[label].type=double_exponential

alpha Defines the α parameter of the selectivity function
x1 Defines the x_1 parameter of the selectivity function
x2 Defines the x_2 parameter of the selectivity function
x0 Defines the x_0 parameter of the selectivity function
y0 Defines the y_0 parameter of the selectivity function
y1 Defines the y_1 parameter of the selectivity function
y2 Defines the y_2 parameter of the selectivity function

@joint_selectivity *label* Define a joint selectivity

selectivities Define the labels of the selectivities to be defined as 'joint'

17.2. Estimation command and subcommand syntax

@estimation

minimiser The label of the minimiser to use, if doing a point estimate

mcmc The label of the MCMC to use, if doing an MCMC

profile The labels of the profiles to use, if doing a profile

@minimiser *label* Define the an minimiser estimator with label

type Define the type of minimiser

@minimiser[label].type=numerical_differences

iterations Define the maximum number of iterations for the minimiser

evaluations Define the maximum number of evaluations for the minimiser

step_size Define the step-size for the minimiser

tolerance Define the convergence criteria (tolerance) for the minimiser

covariance Specify if SPM should attempt to calculate the covariance matrix, if estimating

@minimiser[label].type=de_solver

population_size Define the minimisers number of populations to generate

crossover_probability Define the minimisers crossover probability

difference_scale Define the scale of the difference of the parent candidates for the minimiser

max_generations Define the maximum generations for the minimiser convergence

tolerance Define the convergence criteria (tolerance) for the minimiser

covariance Specify if SPM should attempt to calculate the covariance matrix, if estimating

@mcmc *label* Define the MCMC estimation arguments

type Define the method of MCMC

@mcmc.type=metropolis_hastings

start Covariance multiplier for the starting point of the Markov chain

`length` Length of the Markov chain
`keep` Spacing between recorded values in the chain
`max_correlation` Maximum absolute correlation in the covariance matrix of the proposal distribution
`covariance_adjustment_method` Method for adjusting small variances in the covariance proposal matrix
`correlation_adjustment_diff` Minimum non-zero variance times the range of the bounds in the covariance matrix of the proposal distribution
`step_size` Initial step-size (as a multiplier of the approximate covariance matrix)
`proposal_distribution` The shape of the proposal distribution (either *t* or normal)
`df` Degrees of freedom of the multivariate *t* proposal distribution
`adapt_stepsize_at` Iterations in the chain to check and resize the MCMC step-size

@profile *label* Define the profile parameters and arguments

`parameter` Name of the parameter to be profiled
`steps` Number of steps (values) at which to profile the parameter
`lower_bound` lower bound on parameter
`upper_bound` Upper bound on parameter

@estimate *parameter_name* Estimate an estimable parameter

`same` Names of the other parameters which are constrained to have the same value
`estimation_phase` Phase at which this parameter should be estimated, in point estimation
`lower_bound` Lower bounds on this parameter
`upper_bound` Upper bound on this parameter
`mcmc_fixed` Should this parameter be fixed during MCMC?
`prior` Defines the label for the prior for this parameter

@prior *label* Define the prior label

`type` Define the type of prior

@prior[label].type=uniform

@prior[label].type=uniform_log

@prior[label].type=normal

`mu` Defines the mean μ of the normal prior
`cv` Defines the c.v. *c* of the normal prior

@prior[label].type=normal_by_stdev

`mu` Defines the mean μ of the normal by standard deviation prior
`sigma` Defines the standard deviation σ of the normal by standard deviation prior

@prior[label].type=lognormal

`mu` Defines the mean μ of the lognormal prior
`cv` Defines the c.v. *c* of the lognormal prior

@prior[label].type=beta

- a The lower value of the range parameter A of the Beta prior
- b The upper value of the range parameter B of the Beta prior
- mu Defines the mean μ of the Beta prior
- sigma Defines the standard deviation σ of the Beta prior

@catchability label Define a catchability constant with label

- q Value of the q parameter

@penalty label Define a penalty with label

- log_scale Defines if the penalty is calculated in log space
- multiplier Penalty multiplier

17.3. Observation command and subcommand syntax**@observation label** Define an observation

- type Define the type of observation

@observation[label].type=proportions_at_age

- year Define the year that the observation applies to
- time_step Define the time-step that the observation applies to
- proportion_time_step Define the interpolated proportion of the time-step passes that the observation applies to
- categories Define the categories
- selectivities Define the selectivities applied to each category
- min_age Define the minimum age for the observation
- max_age Define the maximum age for the observation
- age_plus_group Define if the maximum age for the observation is a plus group
- ageing_error Define the label of the ageing-error matrix to be applied (if any)
- layer Name of the categorical layer used to group the spatial cells for the observation
- obs [label] Define the following data as observations for the categorical layer with value [label]
- tolerance Define the tolerance on the sum-to-one error check in SPM
- error_value [label] Define the following data as error values (e.g., N for multinomial likelihoods, c.v. for lognormal likelihoods, etc.) for the categorical layer with value [label]
- likelihood Define the likelihood for the observation
- delta Define the delta robustifying constant for the likelihood
- process_error Define the process error term
- simulation_likelihood Define the likelihood when doing simulations, if the observations is a pseudo-observation

@observation[label].type=proportions_by_category

- year Define the year that the observation applies to

`time_step` Define the time-step that the observation applies to
`proportion_time_step` Define the interpolated proportion of the time-step passes that the observation applies to
`categories` Define the categories
`categories2` Define the categories
`selectivities` Define the selectivities applied to each category
`selectivities2` Define the selectivities applied to each category
`min_age` Define the minimum age for the observation
`max_age` Define the maximum age for the observation
`age_plus_group` Define is the the maximum age for the observation is a plus group
`ageing_error` Define the label of the ageing-error matrix to be applied
`layer` Name of the categorical layer used to group the spacial cells for the observation
`obs [label]` Define the following data as observations for the categorical layer with value [label]
`error_value [label]` Define the following data as error values (e.g., N for multinomial likelihoods, c.v. for lognormal likelihoods, etc.) for the categorical layer with value [label]
`likelihood` Define the likelihood for the observation
`delta` Define the delta robustifying constant for the likelihood
`process_error` Define the process error term
`simulation_likelihood` Define the likelihood when doing simulations, if the observations is a pseudo-observation

@observation[label].type=abundance

`year` Define the year that the observation applies to
`time_step` Define the time-step that the observation applies to
`proportion_time_step` Define the interpolated proportion of the time-step passes that the observation applies to
`catchability` Define the catchability constant label for the observation
`categories` Define the categories for which the observations occur
`selectivities` Define the selectivities applied to each category
`layer` Name of the categorical layer used to group the spacial cells for the observation
`obs [label]` Define the following data as observations for the categorical layer with value [label]
`error_value [label]` Define the following data as error values (e.g., N for multinomial likelihoods, c.v. for lognormal likelihoods, etc.) for the categorical layer with value [label]
`likelihood` Define the likelihood for the observation
`delta` Define the delta robustifying constant for the likelihood
`process_error` Define the process error term
`simulation_likelihood` Define the likelihood when doing simulations, if the observations is a pseudo-observation

@observation[label].type=biomass

`year` Define the year that the observation applies to
`time_step` Define the time-step that the observation applies to
`proportion_time_step` Define the interpolated proportion of the time-step passes that the

observation applies to

catchability Define the catchability constant label for the observation
categories Define the categories into which recruitment occurs
selectivities Define the selectivities applied to each category
layer Name of the categorical layer used to group the spacial cells for the observation
obs [label] Define the following data as observations for the categorical layer with value [label]
error_value [label] Define the following data as error values (e.g., N for multinomial likelihoods, c.v. for lognormal likelihoods, etc.) for the categorical layer with value [label]
likelihood Define the likelihood for the observation
delta Define the delta robustifying constant for the likelihood
process_error Define the process error term
simulation_likelihood Define the likelihood when doing simulations, if the observations is a pseudo-observation

@ageing_error *label* Define ageing error with *label*

type The type of ageing error

@ageing_error [label] .type=none

@ageing_error [label] .type=normal

cv Parameter of the normal ageing error model

k The k parameter of the normal ageing error model

@ageing_error [label] .type=off_by_one

p1 The p_1 parameter of the off-by-one ageing error model

p2 The p_2 parameter of the off-by-one ageing error model

k The k parameter of the off-by-one ageing error model

17.4. Report command and subcommand syntax

@report *label* Define an output report

type Define the type of report

@report [label] .type=spatial_map

file_name Define the name of the output file where the report is written

@report [label] .type=partition

years Define the years that the partition report applies to

time_step Define the time-step that the partition report applies to

file_name Define the name of the output file where the report is written

overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=initialisation

initialisation_phase Define the phase of initialisation that the partition report applies to
file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=process

process Define the label of the process to summarise
file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=derived_quantity

derived_quantity Define the label of the derived quantity to print
file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=estimate_summary

file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=estimate_value

file_name Define the name of the output file where the report is written
header Specify if the output contains the standard SPM style header at the start of the output
overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=objective_function

file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=covariance

file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=observation

observation Define the label of the observation to print
file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be overwritten or appended to

@report [label] .type=simulated_observation

observation Define the label of the observation from which to simulate values
file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be
overwritten or appended to

@report [label] .type=ageing_error

ageing_error Define the label of the ageing_error misclassification matrix
file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be
overwritten or appended to

@report [label] .type=layer

layer Define the label of the layer to print
years Define the years for the printing of the layer
time_step Define the time-step for the printing of the layer
file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be
overwritten or appended to

@report [label] .type=layer_derived_view

layer Define the label of the layer to print
years Define the years for the printing of the layer
time_step Define the time-step for the printing of the layer
file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be
overwritten or appended to

@report [label] .type=selectivity

selectivity Define the label of the selectivity to print
year Define the year for the printing of the selectivity
time_step Define the time-step for the printing of the selectivity
file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be
overwritten or appended to

@report [label] .type=random_number_seed

file_name Define the name of the output file where the report is written
overwrite Specify if any previous file with the same name as the output file should be
overwritten or appended to

@report [label] .type=age_size

age_size Define the label of the age-size relationship

`file_name` Define the name of the output file where the report is written
`overwrite` Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=size_weight

`size_weight` Define the label of the size-weight relationship
`sizes` Define the sizes for which to report the mean weights
`file_name` Define the name of the output file where the report is written
`overwrite` Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=age_weight

`age_size` Define the label of the age-size relationship
`file_name` Define the name of the output file where the report is written
`overwrite` Specify if any previous file with the same name as the output file should be overwritten or appended to

@report[label].type=MCMC

`file_name` Define the name of the output file where the report is written
`overwrite` Specify if any previous file with the same name as the output file should be overwritten or appended to

17.5. Other commands and subcommands

@include *file* Include an external file

18. References

- I. Ball and A Constable. Fish heaven: A Monte Carlo, spatially explicit single species fishery model for the testing of parameter estimation methods. Technical Report WG-FSA-00/36, Australian Antarctic Division, October 2000.
- I. Ball and A.T. Williamson. Fish heaven user's manual. Technical report, Australian Antarctic Division, August 2003.
- N. Bentley, C.R. Davies, S.E. McNeill, and N.M. Davies. A framework for evaluating spatial closures as a fisheries management tool. New Zealand Fisheries Assessment Report, Ministry of Fisheries, 2004a.
- N. Bentley, N.M. Davies, and S.E. McNeill. A spatially explicit model of the snapper (*Pagrus auratus*) fishery in SNA1. New Zealand Fisheries Assessment Report, Ministry of Fisheries, 2004b.
- R.J.H. Beverton and S.J. Holt. *On the dynamics of exploited fish populations*. Fishery investigations. HMSO, London, 1957.
- B. Bull, R.I.C.C. Francis, A. Dunn, A. McKenzie, D.J. Gilbert, M.H. Smith, R. Bian, and D. Fu. CASAL C++ Algorithmic Stock Assessment Laboratory): CASAL user manual v2.30-2012/03/21. Technical Report 135, NIWA, 2012.
- J. E. Dennis Jr and R.B. Schnabel. *Numerical methods for unconstrained optimisation and nonlinear equations*. Classics in Applied Mathematics. Prentice Hall, 1996.
- A B Gelman, J S Carlin, H S Stern, and D B Rubin. *Bayesian data analysis*. Chapman and Hall, London, 1995.
- W R Gilks, A Thomas, and D J Spiegelhalter. A language and program for complex Bayesian modelling. *The Statistician*, 43(1):169–177, 1994.
- Makoto Matsumoto and Takuji Nishimura. Mersenne twister: a 623-dimensionally equidistributed uniform pseudo-random number generator. *ACM Transactions on Modeling and Computer Simulation: Special Issue on Uniform Random Number Generation*, 8(1):3–30, January 1998.
- Andre E. Punt and Ray Hilborn. *BAYES-SA. Bayesian stock assessment methods in fisheries. User's manual. FAO Computerized information series (fisheries) 12*. Food and Agriculture Organisation of the United Nations, Rome (Italy)., 2001.
- J Schnute. A versatile growth model with statistically stable parameters. *Canadian Journal of Fisheries and Aquatic Sciences*, 38(9):1128–1140, 1981.
- Rainer Storn and Kenneth Price. Differential evolution - a simple and efficient adaptive scheme for global optimization over continuous spaces. Technical Report TR-95-012, International Computer Science Institute, Berkeley, CA, 1995. URL <http://citeseer.ist.psu.edu/182432.html>.

19. Spatial Population Model software license

THE ACCOMPANYING PROGRAM IS PROVIDED UNDER THE TERMS OF THIS COMMON PUBLIC LICENSE ("AGREEMENT"). ANY USE, REPRODUCTION OR DISTRIBUTION OF THE PROGRAM CONSTITUTES RECIPIENT'S ACCEPTANCE OF THIS AGREEMENT.

1. DEFINITIONS

"Contribution" means:

- a) in the case of the initial Contributor, the initial code and documentation distributed under this Agreement, and
- b) in the case of each subsequent Contributor:
 - i) changes to the Program, and
 - ii) additions to the Program;

where such changes and/or additions to the Program originate from and are distributed by that particular Contributor. A Contribution 'originates' from a Contributor if it was added to the Program by such Contributor itself or anyone acting on such Contributor's behalf. Contributions do not include additions to the Program which: (i) are separate modules of software distributed in conjunction with the Program under their own license agreement, and (ii) are not derivative works of the Program.

"Contributor" means any person or entity that distributes the Program.

"Licensed Patents " mean patent claims licensable by a Contributor which are necessarily infringed by the use or sale of its Contribution alone or when combined with the Program.

"Program" means the Contributions distributed in accordance with this Agreement.

"Recipient" means anyone who receives the Program under this Agreement, including all Contributors.

2. GRANT OF RIGHTS

a) Subject to the terms of this Agreement, each Contributor hereby grants Recipient a non-exclusive, worldwide, royalty-free copyright license to reproduce, prepare derivative works of, publicly display, publicly perform, distribute and sublicense the Contribution of such Contributor, if any, and such derivative works, in source code and object code form.

b) Subject to the terms of this Agreement, each Contributor hereby grants Recipient a non-exclusive, worldwide, royalty-free patent license under Licensed Patents to make, use, sell, offer to sell, import and otherwise transfer the Contribution of such Contributor, if any, in source code and object code form. This patent license shall apply to the combination of the Contribution and the Program if, at the time the Contribution is added by the Contributor, such addition of the Contribution causes such combination to be covered by the Licensed Patents. The patent license shall not apply to any other combinations which include the Contribution. No hardware per se is licensed hereunder.

c) Recipient understands that although each Contributor grants the licenses to its Contributions set forth herein, no assurances are provided by any Contributor that the Program does not infringe the patent or other intellectual property rights of any other entity. Each Contributor disclaims any liability to Recipient for claims brought by any other entity based on infringement of intellectual property rights or otherwise. As a condition to exercising the rights and licenses granted hereunder, each Recipient hereby assumes sole responsibility to secure any other intellectual property rights needed, if any. For example, if a third party patent license is required to allow Recipient to distribute the Program, it is Recipient's responsibility to acquire that license before distributing the Program.

d) Each Contributor represents that to its knowledge it has sufficient copyright rights in its Contribution, if any, to grant the copyright license set forth in this Agreement.

3. REQUIREMENTS

A Contributor may choose to distribute the Program in object code form under its own license agreement, provided that:

- a) it complies with the terms and conditions of this Agreement; and
- b) its license agreement:
 - i) effectively disclaims on behalf of all Contributors all warranties and conditions, express and implied, including warranties or conditions of title and non-infringement, and implied warranties or conditions of merchantability and fitness for a particular purpose;
 - ii) effectively excludes on behalf of all Contributors all liability for damages, including direct, indirect, special, incidental and consequential damages, such as lost profits;
 - iii) states that any provisions which differ from this Agreement are offered by that Contributor alone and not by any other party; and
 - iv) states that source code for the Program is available from such Contributor, and informs licensees how to obtain it in a reasonable manner on or through a medium customarily used for software exchange.

When the Program is made available in source code form:

- a) it must be made available under this Agreement; and
- b) a copy of this Agreement must be included with each copy of the Program.

Contributors may not remove or alter any copyright notices contained within the Program.

Each Contributor must identify itself as the originator of its Contribution, if any, in a manner that reasonably allows subsequent Recipients

to identify the originator of the Contribution.

4. COMMERCIAL DISTRIBUTION

Commercial distributors of software may accept certain responsibilities with respect to end users, business partners and the like. While this license is intended to facilitate the commercial use of the Program, the Contributor who includes the Program in a commercial product offering should do so in a manner which does not create potential liability for other Contributors. Therefore, if a Contributor includes the Program in a commercial product offering, such Contributor ("Commercial Contributor") hereby agrees to defend and indemnify every other Contributor ("Indemnified Contributor") against any losses, damages and costs (collectively "Losses") arising from claims, lawsuits and other legal actions brought by a third party against the Indemnified Contributor to the extent caused by the acts or omissions of such Commercial Contributor in connection with its distribution of the Program in a commercial product offering. The obligations in this section do not apply to any claims or Losses relating to any actual or alleged intellectual property infringement. In order to qualify, an Indemnified Contributor must: a) promptly notify the Commercial Contributor in writing of such claim, and b) allow the Commercial Contributor to control, and cooperate with the Commercial Contributor in, the defense and any related settlement negotiations. The Indemnified Contributor may participate in any such claim at its own expense.

For example, a Contributor might include the Program in a commercial product offering, Product X. That Contributor is then a Commercial Contributor. If that Commercial Contributor then makes performance claims, or offers warranties related to Product X, those performance claims and warranties are such Commercial Contributor's responsibility alone. Under this section, the Commercial Contributor would have to defend claims against the other Contributors related to those performance claims and warranties, and if a court requires any other Contributor to pay any damages as a result, the Commercial Contributor must pay those damages.

5. NO WARRANTY

EXCEPT AS EXPRESSLY SET FORTH IN THIS AGREEMENT, THE PROGRAM IS PROVIDED ON AN "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, EITHER EXPRESS OR IMPLIED INCLUDING, WITHOUT LIMITATION, ANY WARRANTIES OR CONDITIONS OF TITLE, NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Each Recipient is solely responsible for determining the appropriateness of using and distributing the Program and assumes all risks associated with its exercise of rights under this Agreement, including but not limited to the risks and costs of program errors, compliance with applicable laws, damage to or loss of data, programs or equipment, and unavailability or interruption of operations.

6. DISCLAIMER OF LIABILITY

EXCEPT AS EXPRESSLY SET FORTH IN THIS AGREEMENT, NEITHER RECIPIENT NOR ANY CONTRIBUTORS SHALL HAVE ANY LIABILITY FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING WITHOUT LIMITATION LOST PROFITS), HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OR DISTRIBUTION OF THE PROGRAM OR THE EXERCISE OF ANY RIGHTS GRANTED HEREUNDER, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

7. GENERAL

If any provision of this Agreement is invalid or unenforceable under applicable law, it shall not affect the validity or enforceability of the remainder of the terms of this Agreement, and without further action by the parties hereto, such provision shall be reformed to the minimum extent necessary to make such provision valid and enforceable.

If Recipient institutes patent litigation against a Contributor with respect to a patent applicable to software (including a cross-claim or counterclaim in a lawsuit), then any patent licenses granted by that Contributor to such Recipient under this Agreement shall terminate as of the date such litigation is filed. In addition, if Recipient institutes patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Program itself (excluding combinations of the Program with other software or hardware) infringes such Recipient's patent(s), then such Recipient's rights granted under Section 2(b) shall terminate as of the date such litigation is filed.

All Recipient's rights under this Agreement shall terminate if it fails to comply with any of the material terms or conditions of this Agreement and does not cure such failure in a reasonable period of time after becoming aware of such noncompliance. If all Recipient's rights under this Agreement terminate, Recipient agrees to cease use and distribution of the Program as soon as reasonably practicable. However, Recipient's obligations under this Agreement and any licenses granted by Recipient relating to the Program shall continue and survive.

Everyone is permitted to copy and distribute copies of this Agreement, but in order to avoid inconsistency the Agreement is copyrighted and may only be modified in the following manner. The Agreement Steward reserves the right to publish new versions (including revisions) of this Agreement from time to time. No one other than the Agreement Steward has the right to modify this Agreement. IBM is the initial Agreement Steward. IBM may assign the responsibility to serve as the Agreement Steward to a suitable separate entity. Each new version of the Agreement will be given a distinguishing version number. The Program (including Contributions) may always be distributed subject to the version of the Agreement under which it was received. In addition, after a new version of the Agreement is published, Contributor may elect to distribute the Program (including its Contributions) under the new version. Except as expressly stated in Sections 2(a) and 2(b) above, Recipient receives no rights or licenses to the intellectual property of any Contributor under this Agreement, whether expressly, by implication, estoppel or otherwise. All rights in the Program not expressly granted under this Agreement are reserved.

This Agreement is governed by the laws of the State of New York and the intellectual property laws of the United States of America. No party to this Agreement will bring a legal action under this Agreement more than one year after the cause of action arose. Each party waives its rights to a jury trial in any resulting litigation.

20. Index

- SPM source code, 2
- About SPM, 3
- Abundance layers, 16
- Abundance or biomass observations, 49
- Abundance-density layers, 16
- Adjacent cell movement, 19, 27
- Ageing, 18, 22
- Ageing error, 52
- Annual cycle, 3, 13, 17, 18
- Annual mortality, 23
- Base layer, 13, 15
- Basic size-weight relationship, 31
- Bayesian estimation, 38
- Beta prior, 41
- Beverton-Holt recruitment, 19
- Biomass layers, 16
- Biomass-density layers, 16
- BOOST C++ library, 2
- Bounds, 36
- CASAL, 4
- Categorical layers, 15
- Categorical preference function, 29
- Category transition, 18, 24
- Cell area, 13
- Citation, 1
- Citing SPM, 1
- Classification layers, 15
- Command
 - Include files, 11
- Command block format, 10
- Command line arguments, 7, 8
- Commands, 9
- Commands
 - Subcommands, 9
- Commenting input configuration file, 11
- Comments, 11
- Common Public License, 1
- Constant mortality, 23
- Constant preference function, 28
- Convergence failure, 36
- Correlation matrix, 37
- Covariance matrix, 35, 37
- Covariate layers, 15
- Derived layers and derived meta-layers, 17
- Derived layers and meta-layers, 30
- Derived meta-layers, 3
- Derived quantities, 3, 29
- Determining parameter names, 11
- Differential evolution minimiser, 2, 36
- Distance layers, 15
- Double-normal preference function, 28
- Estimable parameters, 7
- Estimated parameters, 4, 7
- Estimating parameters, 35
- Estimation section, 4
- Event mortality, 24
- Exit status value, 12
- Exponential preference function, 29
- Finite differences minimiser, 2, 36
- Getting help, 2
- Hessian, 37
- Including external files, 7
- Initialisation, 13, 17
 - phases, 17
- Input configuration file, 4, 7
- Input configuration file syntax, 9
- Inter-cell distance, 14
- Inverse-Logistic preference function, 29
- Layers, 15
- Layers
 - the base layer, 15
- Likelihoods, 43
- Linux, 1, 2, 4, 7
- local Beverton-Holt recruitment, 19
- Local minimums, 36
- Logistic preference function, 28
- Lognormal prior, 41
- Maximum exploitation rate, 24
- Maximum size of the spatial grid, 13
- MCMC, 35, 38
- Meta-layers, 16
- Microsoft Windows, 1, 2, 4, 7
- Migration, 18
- Migration movement, 26
- Mingw, 2
- Model
 - annual cycle, 3

- derived meta-layers, 3
- derived quantities, 3
- initialisation, 13
- partition, 3
- processes, 3
- state, 3
- structure, 3
- time-steps, 3
- Model overview, 3
- Model years, 18
- Monotonic categorical preference function, 29
- Monte Carlo Markov Chain, 38
- Mortality, 18, 22
- Movement, 18, 26
- Movement processes, 18, 26
- MPD, 35
- Necessary files, 2
- Normal preference function, 28
- Normal prior, 41
- Notifying errors, 2
- Numeric layers, 15
- Objective function, 36
- Objective function evaluations, 36
- Observation section, 4, 5
- Observations, 43
- Optional command line arguments, 9
- Output header information, 8
- Parameter names, 11
- Partition, 3
- Point estimation, 36
- Population processes, 18, 19
- Population section, 4, 13
- Population structure, 14
- Posterior profiles, 37
- Preference function, 27, 28
- Preference function
 - Categorical, 29
 - Constant, 28
 - Double-Normal, 28
 - Exponential, 29
 - Inverse-Logistic, 29
 - Logistic, 28
 - Monotonic categorical, 29
 - Normal, 28
 - Threshold, 29
- Preference movement, 19, 27
- Printing a derived view via a categorical layer, 57
- Printing a process summary, 56
- Printing derived quantities, 56
- Printing layers and meta-layers, 57
- Printing observations, fits, and residuals, 56
- Printing selectivities, 57
- Printing simulated observations, 57
- Printing the ageing error misclassification matrix, 57
- Printing the covariance matrix, 56
- Printing the estimated parameters, 56
- Printing the estimated parameters in a vector format, 56
- Printing the model spatial map, 55
- Printing the objective function, 56
- Printing the partition, 55
- Printing the partition at the end of an initialisation, 55
- Printing the random number seed, 57
- Printing the results of an MCMC, 58
- Printing the size-at-age relationship, 57
- Printing the size-weight relationship, 57
- Printing the weight-at-age relationship, 57
- Priors, 36
- Priors
 - Beta, 41
 - Lognormal, 41
 - Normal, 41
 - Uniform, 40
 - Uniform-log, 40
- Process error, 51
- Processes, 3, 4, 18
- Profiles, 35
- Proportions-at-age observations, 43
- Proportions-by-category observations, 47
- Pseudo-observations, 53
- Quasi-Newton iterations, 36
- Random number generator, 2
- Recruitment, 18, 19
- Recruitment
 - Beverton-Holt, 19
 - Constant, 19
 - Local Beverton-Holt, 19
- Redirecting standard error, 8
- Redirecting standard out, 8
- Redirecting standard output, 8
- Report section, 4, 5
- Reports, 55
- Reports
 - Ageing error misclassification matrix, 57
 - Covariance Matrix, 56

- Derived quantities, 56
- Derived view, 57
- Estimated parameters, 56
- Hessian, 56
- Initialisation, 55
- Layers and meta-layers, 57
- MCMC, 58
- Objective function, 56
- Observations, 56
- Partition, 55
- Processes, 56
- Random number seed, 57
- Selectivities, 57
- Simulated observations, 57
- Size-at-age, 57
- Size-weight, 57
- Spatial map, 55
- standard style, 55
- Weight-at-age, 57
- Reports section, 55
- Run years, 17
- Running SPM, 7
- Schnute growth curve, 31
- Selectivities, 32
- Simulating observations, 52
- Size-age relationship, 31
- Size-weight relationship, 31
- Software license, 1
- Spatial structure, 13
- Specifying the parameters to be estimated, 35
- standard error, 8
- standard output, 8
- State, 3
- Subcommand argument type, 10
- Successful convergence, 36
- System requirements, 1
- Tasks, 7
- Technical specifications, 2
- The differential evolution minimiser, 37
- The estimation section, 4, 35
- The numerical differences minimiser, 36
- The objective function, 35
- The observation section, 5
- The population section, 4, 13
- The report section, 5, 55
- Threshold preference function, 29
- Time sequences, 17
- time-steps, 3
- Total preference function, 27
- Uniform prior, 40
- Uniform-log prior, 40
- User assistance, 2
- Using SPM, 7
- Version number, 1
- von Bertalanffy growth curve, 31