

# WLAN Configuration

## Addressing Table

Device	Interface	IP Address
Home Wireless Router	Internet	DHCP
	LAN	192.168.6.1/27
RTR-1	G0/0/0.2	192.168.2.1/24
	G0/0/0.5	192.168.5.1/24
	G0/0/0.100	192.168.100.1/24
	G0/0/1	10.6.0.1/24
SW1	VLAN 200	192.168.100.100/24
LAP-1	G0	DHCP
WLC-1	Management	192.168.100.254/24
RADIUS Server	NIC	10.6.0.254/24
Home Admin	NIC	DHCP
Enterprise Admin	NIC	192.168.100.200/24
Web Server	NIC	203.0.113.78/24
DNS Server	NIC	10.100.100.252
Laptop	NIC	DHCP
Tablet PC	Wireless0	DHCP
Smartphone	Wireless0	DHCP
Wireless Host 1	Wireless0	DHCP
Wireless Host 2	Wireless0	DHCP

## WLAN Information

WLAN	SSID	Authentication	Username	Password
Home Network	HomeSSID	WPA2-Personal	N/A	Cisco123
WLAN VLAN 2	SSID-2	WPA-2 Personal	N/A	Cisco123
WLAN VLAN 5	SSID-5	WPA-2 Enterprise	userWLAN5	userW5pass

**Note:** It is not a good practice to reuse passwords as is done in this activity. Passwords have been reused to make it easier to work through the tasks.

### Objectives

In this activity, you will configure both a wireless home router and a WLC-based network. You will implement both WPA2-PSK and WPA2-Enterprise security.

- Configure a home router to provide Wi-Fi connectivity to a variety of devices.
- Configure WPA2-PSK security on a home router.
- Configure interfaces on a WLC.
- Configure WLANs on a WLC.
- Configure WPA2-PSK security on a WLAN and connect hosts to WLAN.
- Configure WPA2-Enterprise on a WLAN and connect hosts to the WLAN.
- Verify connectivity WLAN connectivity.

### Background / Scenario

You will apply your WLAN skills and knowledge by configuring a home wireless router and an enterprise WLC. You will implement both WPA2-PSK and WPA2-Enterprise security. Finally, you will connect hosts to each WLAN and verify connectivity.

### Instructions

#### Part 1: Configure a Home Wireless Router.

You are installing a new home wireless router at a friend's house. You will need to change settings on the router to enhance security and meet your friend's requirements.

##### Step 1: Change DHCP settings.

- a. Open the Home Wireless Router GUI and change the router IP and DHCP settings according to the information in the Addressing Table.
- b. Permit a maximum of **20** addresses to be issued by the router.
- c. Configure the DHCP server to start with IP address **.3** of the LAN network.
- d. Configure the internet interface of the router to receive its IP address over DHCP.

Verify the address. What address did it receive?

- e. Configure the static DNS server to the address in the Addressing Table.

##### Step 2: Configure the Wireless LAN.

- a. The network will use the 2.4GHz Wireless LAN interface. Configure the interface with the SSID shown in the Wireless LAN information table.
- b. Use **channel 6**.
- c. Be sure that all wireless hosts in the home will be able to see the SSID.

##### Step 3: Configure security.

- a. Configure wireless LAN security. Use WPA2 Personal and the passphrase shown in the Wireless LAN information table.
- b. Secure the router by changing the default password to the value shown in the Wireless LAN information table.

### Step 4: Connect clients to the network.

- Open the PC Wireless app on the desktop of the laptop and configure the client to connect to the network.
- Open the Config tab on the Tablet PC and Smartphone and configure the wireless interfaces to connect to the wireless network.
- Verify connectivity. The hosts should be able to ping each other and the web server. They should also be able to reach the web server URL.

## Part 2: Configure a WLC Controller Network

Configure the wireless LAN controller with two WLANs. One WLAN will use WPA2-PSK authentication. The other WLAN will use WPA2-Enterprise authentication. You will also configure the WLC to use an SNMP server and configure a DHCP scope that will be used by the wireless management network.

### Step 1: Configure VLAN interfaces.

- From the Enterprise Admin, navigate to the WLC-1 management interface via a web browser. To log into WLC-1, use **admin** as the username and **Cisco123** as the password.
- Configure an interface for the first WLAN.  
Name: **WLAN 2**  
VLAN Identifier: **2**  
Port Number: **1**  
Interface IP Address: **192.168.2.254**  
Netmask: **255.255.255.0**  
Gateway: **RTR-1 G0/0/0.2 address**  
Primary DHCP Server: **Gateway address**
- Configure an interface for the second WLAN.  
Name: **WLAN 5**  
VLAN Identifier: **5**  
Port Number: **1**  
Interface IP Address: **192.168.5.254**  
Netmask: **255.255.255.0**  
Gateway: **RTR-1 interface G0/0/0.5 address**  
Primary DHCP Server: **Gateway address**

### Step 2: Configure a DHCP scope for the wireless management network.

Configure and enable an internal DHCP scope as follows:

Scope Name: **management**  
Pool Start Address: **192.168.100.235**  
Pool End Address: **192.168.100.245**  
Network: **192.168.100.0**  
Netmask: **255.255.255.0**  
Default Routers: **192.168.100.1**

### Step 3: Configure the WLC with external server addresses.

- a. Configure the RADIUS server information as follows:  
Sever Index: **1**  
Sever Address: **10.6.0.254**  
Shared Secret: **RadiusPW**
- b. Configure the WLC to send logs information to an SNMP server.  
Community Name: **WLAN**  
IP Address: **10.6.0.254**

### Step 4: Create the WLANs.

- a. Create the first WLAN:  
Profile Name: **Wireless VLAN 2**  
WLAN SSID: **SSID-2**  
ID: **2**  
Interface: **WLAN 2**  
Security: **WPA2-PSK**  
Passphrase: **Cisco123**  
Under the Advanced tab, go to the FlexConnect section. Enable **FlexConnect Local Switching** and **FlexConnect Local Auth**.
- b. Create the second WLAN:  
Profile Name: **Wireless VLAN 5**  
WLAN SSID: **SSID-5**  
Interface: **WLAN 5**  
ID: **5**  
Security: **802.1x - WPA2-Enterprise**  
Configure the WLAN to use the RADIUS server for authentication.  
Make the **FlexConnect** settings as was done in Step 4a.

### Step 5: Configure the hosts to connect to the WLANs.

Use the desktop PC Wireless app to configure the hosts as follows:

- a. Wireless Host 1 should connect to Wireless VLAN 2.
- b. Wireless Host 2 should connect to Wireless VLAN 5 using the credentials in the WLAN information table.

### Step 6: Test connectivity.

Test connectivity between the wireless hosts and the Web Server by ping and URL.