

emftext

USER GUIDE

May 1, 2011

Contents

1	Overview	1
1.1	Generation features	1
1.2	Specification features	1
1.3	Editor features	2
1.4	Other features	2
2	Getting Started with EMFText	3
2.1	Specifying a Language Metamodel	3
2.2	Specifying the Language's Concrete Syntax	6
2.3	Generating the Language Tooling	9
2.3.1	Generating Resource Plug-ins in Eclipse	9
2.3.2	Generating Resource Plug-ins with ANT	10
2.4	Optionally Customising the Language Tooling	11
3	Concrete Syntax Specification Language (CS)	13
3.1	Configuration Block	13
3.1.1	Required General Information	13
3.1.2	Importing other Metamodels and Syntax Specifications	14
3.1.3	Code Generation Options	15
3.2	Tokens	15
3.2.1	Defining Custom Tokens	15
3.2.2	Composed Tokens	15
3.2.3	Token Priorities	16
3.3	Token Styles	17
3.4	Syntax Rules	17
3.4.1	Simple Syntax	17
3.4.2	Syntax for EAttributes	18
3.4.3	Syntax for EReferences	19
3.4.4	Syntax for Printing Instructions	20
3.4.5	Syntax for Expressions	21
3.5	Suppressing Warnings	22
4	DSL Customization	23
4.1	Customization Techniques	23
4.1.1	Overriding Generated Artifacts	23
4.1.2	Overriding Meta Information Classes	23
4.1.3	Using Generated Extension Points	23
4.2	Concrete Customizations	24
4.2.1	Customizing Token Resolving	24

4.2.2	Customizing Reference Resolving	26
4.2.3	Implementing Post Processors	27
4.2.4	Implementing Quick Fixes	29
4.2.5	Implementing Builders	30
4.2.6	Implementing Interpreters	31
4.2.7	Customizing Text Hovers	32
4.2.8	Customizing Code Completion Proposals	33
4.2.9	Adding Context Menu Items to the Outline View	33
4.2.10	Providing Custom Content for Files created by the New File Wizard . .	34
4.2.11	Implementing Launch Support	34
A	Appendix	39
A1	Code Generation Options	39
A2	Types of Warnings	56
A3	Syntax Dependent Artifacts	57
	Bibliography	59

1 Overview

EMFText is a tool for defining textual syntax for Ecore-based metamodels. It enables developers to define their own textual languages—be it domain specific languages (e.g., a language for describing forms) or general purpose languages (e.g., Java)—and generates accompanying tool support for these languages. It provides a domain specific language (DSL) for syntax specification from which it generates a full-fledged Eclipse editor and components to load and store model instances.

To give a quick overview, some of the most compelling features of EMFText are outlined in the following.

1.1 Generation features

EMFText uses a generative approach where all artifacts that form the tooling for a textual language are generated. This includes a parser for loading textual models, a printer for storing model instances and the editor with all its customizable components.

Generation of independent code The code that is generated by EMFText does not contain dependencies to EMFText and is fully customizable. This implies that generated language tooling can be deployed in environments where EMFText is not available and that future compatibility issues are completely avoided.

Generation of default syntaxes With EMFText, initial syntaxes for the textual DSL can be generated in one step for any Ecore-based metamodel. One can either generate a syntax that conforms to the HUTN standard [Obj02] or a Java-like syntax. In both cases, the initial, generated specification of the syntax can be further tailored towards specific needs (cf. Section 2.2).

Highly customizable code generation EMFText provides many options for tailoring its code generation process to specific needs. For example, manually modified code can be preserved by disabling its generation or custom license headers can be provided if needed (cf. Appendix A1).

1.2 Specification features

EMFText comes with a simple but rich syntax specification language—the *Concrete Syntax Specification Language (CS)*. It is based on EBNF and follows the concept of *convention over configuration*. This allows for very compact and intuitive syntax specifications, but still supports tweaking specifics where needed (cf. Chapter 3).

Modular specification EMFText provides an import mechanism that not only supports specification of a single text syntax for multiple related Ecore models, but also allows for modularization and extension of CS specifications (cf. Section 3.1.2).

Default reference resolving mechanisms A default name resolution mechanism for models with globally unique names is available out of the box for any syntax. Also, external references are resolved automatically, if URIs are used to point to the referenced elements. More complex resolution mechanisms can be realized by implementing generated resolving methods (cf. Section 4.2.2).

Comprehensive syntax analysis A number of analyses of CS specifications inform the developer about potential errors in the syntax—like missing syntax for certain metaclasses (cf. Appendix A2).

1.3 Editor features

Editors generated by EMFText provide many advanced features that are known from, e.g., the Eclipse Java editor. This includes code completion (with customizable completion proposals cf. Section 4.2.2 and Section 4.2.8), customizable syntax and occurrence highlighting via preference pages, advanced bracket handling, code folding, hyperlinks and text hovers for quick navigation, an outline view and instant error reporting.

1.4 Other features

EMFText provides numerous other interesting features, some of them outlined below.

ANT support Dedicated ANT tasks are provided to allow the generation of text syntax plugins in build scripts (cf. Section 2.3.2).

Support for post processors By default, registered post processors are called by the tooling after parsing. These post processors can be customized to check consistency of models or perform necessary modifications after parsing (cf. Section 4.2.3).

Generation of builder stubs EMFText generates a builder stub that can be used to process model instances on changes and to automatically produce derived resources when needed (cf. Section 4.2.5).

Generation of interpreter stubs Similarly, interpreters are used to execute model instances (cf. Section 4.2.6).

Quick fixes Quick fixes provide actions that can automatically solve problems found during analysis of model instances. EMFText provides means to attach quick fixes to reported problems which then can be fixed by the developer in a convenient way (cf. Section 4.2.4).

2 Getting Started with EMFText

Generating an advanced Eclipse editor for a new language with EMFText just requires a few specifications and a generation step. Basically, a language specification for EMFText consists of a language metamodel and a concrete syntax specification. Taking these specifications the EMFText generator derives an advanced textual editor, that uses a likewise generated parser and printer to parse language expressions to EMF models or to print EMF models to language expressions respectively.



Figure 2.1: Iterative EMFText language development process.

The basic language development process with EMFText is depicted in Fig. 2.1. It is an iterative process that can be passed several times and consists of the following basic tasks:

- (1) Specifying a Language Metamodel,
- (2) Specifying the Language's Concrete Syntax,
- (3) Generating the Language Tooling,
- (4) Optionally Customising the Language Tooling.

Each of these tasks will be explained and exemplified in the subsequent sections:

To kick-start the development of a new language you can use the EMFText project wizard. Select *File > New > Other... > EMFText Project*. In the Wizard (cf. Fig. 2.2) you just enter the language name and EMFText will initialise a new EMFText Project containing a metamodel folder that holds an initial metamodel and syntax specification.

2.1 Specifying a Language Metamodel

As EMFText is tightly integrated with the Eclipse Modeling Framework (EMF) [SBPM08] language metamodels are specified using the Ecore Metamodelling Language. The metamodel



Figure 2.2: EMFText Project wizard.

specifies the abstract syntax of a new language. It can be build from *classes* with *attributes* that are related using *references*. References are further distinguished into *containment* references and *non-containment* references. It is important to notice this difference, as both reference types have different semantics in EMF and are also handled differently in EMFText. Containment references are used to relate a parent model element and a child model element that is declared in the context of the parent element. An example which can be found for instance in object-oriented programming languages is the declaration of a method within the body of a class declaration. Non-containment references are used to relate a model element with an element that is declared elsewhere (not as one of its children). An example for programming languages is a method call (declared in a statement in the body of a method declaration) that relates to the method that it calls using a non-containment reference. The referenced method, however, is declared elsewhere: In a class the method relates to with a containment reference.

Example. To define a metamodel for a language, we have to consider the concepts this language deals with, how they interrelate and what attributes they have. In the following we discuss the concepts of an exemplary language to specify forms and how they are represented in a forms metamodel.

- A Form (class) has a caption (attribute) and contains (containment reference) a number of question Groups (class).
- Each Group has a name (attribute) and contains (containment reference) a number of question Items (class).

- Each Item has a question text (attribute) and an explanation (attribute).
- There are various Types (class) of question items with regard to the answer values they expect: e.g., Text questions (subclass), Date questions (subclass), Number questions (subclass), Choices (subclass), or Decisions (subclass).
- Choices and Decisions declare (containment reference) a number of selection Options (class).
- There may be question Items that are dependent of (non-containment reference) the selection of a particular Option in another Item, e.g., a question that asks for the age of your children, only if you previously selected that you have some.

The subsequent listing depicts a textual representation of the according EMF metamodel. Besides the mapping of forms concepts to Ecore it also refines the multiplicities and types. A new text.ecore metamodel is created by selecting *File > New > Other... > EMFText .text.ecore file*. For a detailed introduction on the basics of Ecore metamodeling we refer to [SBPM08].

```
package forms // this is the package name
  forms // this is the namespace prefix
  "http://org.emftext/language/forms.ecore" // the namespace URI
  {

    class Form {
      attribute EString caption (0..1);
      containment reference Group groups (1..-1) ;
    }

    class Group {
      attribute EString name (1..1);
      containment reference Item items (1..-1);
    }

    class Item {
      attribute EString text (0..1);
      attribute EString explanation (0..1);
      containment reference ItemType itemType (1..1);
      reference Option dependentOf (0..-1);
    }

    abstract class ItemType {}

    class FreeText extends ItemType {}
    class Date extends ItemType {}
    class Number extends ItemType {}

    class Choice extends ItemType {
      attribute EBoolean multiple (0..1);
    }
  }
```

```
        containment reference Option options (1..-1);
    }
    class Decision extends ItemType {
        containment reference Option options (2..2);
    }

    class Option {
        attribute EString id (0..1);
        attribute EString text (0..1);
    }
}
```

Each Ecore metamodel is accompanied by an `.genmodel`. You can create the `.genmodel` by selecting *File > New > Other... > EMF Generator Model*. The generator model is used to configure various options for EMF code generation (e.g., the targeted Java runtime). From the root element of the `.genmodel` you can now start the generation of Java code implementing your metamodel specification. By default the generated files can be found in the `src` folder of the metamodel plug-in, but this can also be configured in the `.genmodel`. We suggest to change the code generation folder to `src-gen` to better separate generated code from hand-written.

2.2 Specifying the Language's Concrete Syntax

After defining a metamodel, we can start specifying our *concrete syntax*. The concrete syntax specification defines the textual representation of all metamodel concepts. For that purpose, EMFText provides the `cs-language`. As a starting point, EMFText provides a syntax generator that can automatically create a `cs` specification conforming to HUTN (Human-Useable Textual Notation) [Obj02] from the language metamodel. To manually specify the concrete syntax create a new syntax specification by selecting *File > New > Other... > EMFText .cs file*.

The listing at the end of this section depicts a syntax specification for the forms language. It consists of five sections:

- In the first section the language file extension is defined, the syntax specification is bound to the metamodel, and the syntax start symbol is defined.
- In the second section various EMFText code generation options can be configured.
- In the third section basic token types used by the language lexer to tokenise language expressions are defined. If no token definitions are given, default token types are used.
- In the fourth section token styles are defined that customise syntax highlighting for specific token types in the generated editor.
- In the fifth section the syntax rules for the language are specified.

The syntax specification rules used in the `cs-language` are derived from the EBNF syntax specification language to support arbitrary context-free languages. They are meant to define syntax for EMF-based metamodels and, thus, are specifically related to the Ecore metamodeling concepts. Therefore, it provides Ecore-specific specialisations of classical EBNF constructs like terminals, and non terminals. This specialisation enables EMFText to provide advanced support during syntax specification, e.g., errors and warnings if the syntax specifica-

tion is inconsistent with the metamodel. Furthermore, it enables the EMFText parser generator to derive a parser that directly instantiates EMF models from language expressions.

In the following we conclude the most important syntax specification constructs found in the cs-language and their relation to EBNF and Ecore metamodels. For an extensive overview on the syntax specification language we refer to Sect. 3. Each syntax construct is also related to examples taken from the listing at the end of this section.

Rule An cs rule is always related (by its name) to a specific class from the metamodel. It defines the syntactic representation of this metaclass, its attributes and references. All syntax rules are collected in the rules section of the cs file. Within syntax rules various constructs like keywords, syntax terminals, non-terminals, and EBNF operators as multiplicities (`?`, `+`, `*`), alternative (`|`), or rounded brackets to nest sub-rules can be used.

Examples:

```
Form ::= ...;, Group ::= ...;
```

Keywords Keywords are purely syntactic elements that are mainly used to structure and markup particular language expressions.

Examples:

```
"FORM", "GROUP", "ONLY" "IF"
```

Attribute Terminal Attribute terminals are used in rule bodies to specify the syntactic representation for attributes of the according meta class. They can be recognised by the attribute name that is followed by square brackets. Within these square brackets a token that specifies the syntax allowed for attribute values, or a prefix and a suffix that must surround attribute values can be given. If nothing is given a default text token is assumed.

Examples:

```
name[], mulitple[MULTIPLE], name['', '']
```

Containment Reference Non-Terminals Containment reference non-terminals are used in rule bodies to specify the syntactic representation for containment references of the according metaclass. They use the reference name and are not followed by brackets. Containment reference non-terminals are derived from EBNF non-terminals, which means that during parsing the parser descends in the syntax rule specified for the class the containment reference points to. This is in line with the semantics of containment references as used in metamodels.

Examples:

```
groups, questions
```

Non-Containment Reference Terminals Non-containment reference terminals are used in rule bodies to specify the syntactic representation for non-containment references of the according metaclass. They use the reference name that is followed by square brackets. Within these square brackets a token can be given that specifies the syntax allowed for expressions in the concrete syntax that identify the element the non-containment reference relates to. This symbolic reference is later resolved to the actual element (cf. Sect. 4.2.2). If no token is given, again the default text token is used.

Examples:

dependentOf[]

Printing Markup Printing Markup is used to customise the behaviour of the generated printer.

This is useful to achieve a particular standard layout for printed language expressions.

Two forms of printing markup are supported:

- whitespace markup, prints a given number of whitespaces: #<n>
- linebreak markup, introduces a linebreak followed by a given number of tab characters: !<n>

SYNTAXDEF forms

FOR <<http://www.emftext.org/language/forms>>

START Form

OPTIONS {

 overrideBuilder = "false";

 additionalDependencies = "org.emftext.language.forms.generator";

}

TOKENS {

DEFINE MULTIPLE \$'multiple'|'MULTIPLE'\$;

}

TOKENSTYLES {

 "TEXT" **COLOR** #da0000;

 "FORM" **COLOR** #000000, **BOLD**;

 "ITEM" **COLOR** #000000, **BOLD**;

 "CHOICE" **COLOR** #000000, **BOLD**;

 "ONLY" **COLOR** #da0000, **BOLD**;

 "IF" **COLOR** #da0000, **BOLD**;

 "DATE" **COLOR** #000000, **BOLD**;

 "FREETEXT" **COLOR** #000000, **BOLD**;

 "NUMBER" **COLOR** #000000, **BOLD**;

 "DECISION" **COLOR** #000000, **BOLD**;

 "GROUP" **COLOR** #000000, **BOLD**;

}

RULES {

 Form ::= "FORM" caption['', ''] !1 groups*;

 Group ::= !0 "GROUP" name['', ''] !0 items*;

 Item ::= "ITEM" text['', ''] (explanation['', ''])?

 ("ONLY" "IF" dependentOf[])? ":" itemType !0;

 Choice ::= "CHOICE" (multiple[MULTIPLE])?

 ("(" options ("," options)* ")");

 Option ::= (id[] ":")? text['', ''];

 Date ::= "DATE";

 FreeText ::= "FREETEXT";

```

    Number ::= "NUMBER";
    Decision ::= "DECISION" "(" options "," options ")";
}

```

2.3 Generating the Language Tooling

Given a complete syntax specification the EMFText code generator can be used to derive an advanced textual editor and an accompanying customisable language infrastructure. There are two alternative ways to use the code generator: Manually within Eclipse or from an Apache Ant script.

2.3.1 Generating Resource Plug-ins in Eclipse

Manual code generation can be triggered from the context menu of the concrete syntax specification. Therefore, right click the cs file and select *Generate Text Resource*. This starts the EMF code generator that produces a number of plug-ins. Fig. 2.3 depicts the plug-ins generated for our exemplary forms language. In the following we shortly discuss their purpose:

- **org.emftext.commons.antrl3_2_0** This project contributes the ANTLR parsing runtime that the generated parser for the forms language depends on. As EMFText is meant to be runtime free the ANTLR runtime is generated for every new language, if no runtime is found in the current workspace.
- **org.emftext.language.forms** This is the basic plug-in of the language. In the folder **metamodel** it contains the Ecore metamodel and the cs specification defined previously. The **src-gen** folder contains the Java-based implementation that was generated using the **.genmodel**. This plug-in will not be altered by the EMFText code generator.
- **org.emftext.language.forms.resources.forms** This is the plug-in that contains the generated parser, printer and various infrastructure for the forms language. The project contains two source folders (**src** and **src-gen**). The contents of **src-gen** is overridden by every run of EMFText code generation. It is, thus not meant to contain manually customised code. The contents of the **src** folder contains implementation classes that are meant for manual customisation. By default it only contains reference resolvers that are used to resolve symbolic names of non-containment references to the model element actually meant. For details on reference resolving we refer to Sect. 4.2.2. Various cs options are available to tailor what language implementation artifacts shall be customised and, therefore, put into the **src** folder. For a detailed discussion of such options we refer to Sect. 4.1.2 and Appendix A1.

Besides the files implementing the language tooling, a number of extension points specific for the language are generated to the **schema** folder. They can be used to further customise language tooling. For details we refer to Sect. 4.1.3.

- **org.emftext.language.forms.resources.forms.ui** This plug-in contains all generated classes related to the Eclipse-based User Interface (UI). Such separation of implementation classes belonging to the UI or not, enables the application of the language backend detached from the Eclipse UI.




Figure 2.3: Projects generated by EMFText to implement language tooling.

2.3.2 Generating Resource Plug-ins with ANT

A second way of starting the EMFText code generator is using Apache Ant scripts. Therefore EMFText contributes a number of tasks for Apache Ant, which are automatically registered to the Eclipse platform using the naming scheme: *emftext.taskName*. The following task are shipped with EMFText:

GenerateTextResource This task can be used to generate all language implementation plug-ins. The following listing exemplifies the application of this task and its obligatory parameters:

```
<emftext.GenerateTextResource
    syntax="pathToCSSpec"
    rootFolder="path/to/project/root"
    syntaxProjectName="nameOfTheGeneratedProject"
/>
```

Further parameters are `generateANTLRPlugin="[true|false]"`, which specifies whether the additional plug-in containing the ANTLR parsing runtime should be generated, and `pre-processor="[qualified class name]"` referring to an implementation of the `org.emftext.sdk.ant.SyntaxProcessor` interface, which is provided for realising Java-based syntax specification preprocessors.

RegisterEcoreResourceFactory This task registers an Ecore model's resource factory for a certain type. This is especially useful for testing purposes without a running Eclipse platform. The following listing exemplifies its application:

```
<emftext.RegisterEcoreResourceFactory
    className="qualified.factory.class.name"
    type="qualified.ecore.type.name"
/>
```

RegisterURIMapping This task adds an URI mapping to the EMF URI map, which is useful for mapping symbolic namespace URIs to physical locations, i.e., for locating ecore models. The following listing exemplifies its application:

```
<emftext.RegisterURIMapping
    from="sourceURI"
    to="targetURI"
/>
```

RemoveURIMapping This task removes an URI mapping from the EMF's URI map, which is useful for removing unwanted symbolic URI mappings from the URI map. The following listing exemplifies its application:

```
<emftext.RemoveURIMapping
    from="sourceURI"
/>
```

To execute an Ant script that uses EMFText tasks from within your Eclipse runtime, you have to adjust the script's run configuration. Therefore, select *Run > External Tools > External Tools Configurations...* and select your Ant script's run configuration. In the *JRE* tab you have to activate the option *Run in the same JRE as the workspace* to make the EMFText tasks available to the script.

2.4 Optionally Customising the Language Tooling

The previous steps are mandatory to generate an initial implementation of basic tooling for your language. The generated text editor already comes with a number of advanced editing features that help editing language expressions a lot. However, there are various ways to make your language tooling more useful. EMFText helps you in customising your language tooling

with a number of additional functions ranging from semantic validation of language expressions, language compilation, language interpretation, or editor functions like folding, custom quickfixes, extended code completion, refactoring and more. To discover the full spectrum of possibilities please consider Sect. 4.

3 Concrete Syntax Specification Language (CS)

An EMFText syntax specification must be contained in a file with the extension `.cs` and consists of four main blocks:

1. A mandatory configuration block, which specifies the name of the syntax (i.e., the file extension), the generator model where to find the metaclasses, and the root metaclass (start symbol). Optionally, other syntaxes and metamodels can be imported and code generation options can be specified.
2. An (optional) **TOKENS** section. Here, token types like identifiers, numbers etc. for the lexical analyser can be specified.
3. An (optional) **TOKENSTYLES** section. Here, the default style (i.e., color and font style) for tokens and keywords can be specified.
4. A **RULES** section, which defines the syntax for concrete metaclasses.

In the following sections, these four main blocks will be explained in more detail.

3.1 Configuration Block

3.1.1 Required General Information

The first required piece of information is the file extension that shall be used for the files, which will contain your models:

```
SYNTAXDEF yourFileExtension
```

Note: The file extension must not contain the dot character.

Second, EMFText needs to know the EMF generator model (`.genmodel`) that contains the metaclasses for which the syntax is specified. EMFText does use the generator model rather than the Ecore model, because it requires information about the code generated from the Ecore model (e.g., the fully qualified names of the classes generated by the EMF). The `genmodel` can be referred to by its namespace URI:

```
FOR <yourGenModelNamespaceURI>
```

To find the generator model with the given namespace URI, EMFText tries to load it from the generator model registry. If it is not registered, EMFText looks for a `.genmodel` file with the same name as the syntax definition. For example, if the syntax specification is contained in a file `yourdsl.cs`, EMFText looks for a file called `yourdsl.genmodel` in the same folder.

If your `genmodel` is not contained in the same folder or is called differently from the syntax file name or if you do not want to use the one in the registry, the optional parameter `yourGenModelLocation` can be used:

```
FOR <yourGenModelNamespaceURI> <yourGenModelLocation>
```

The value of **yourGenmodelLocation** must be an URI pointing to the generator model. The URI can be absolute or relative to the syntax specification folder.

Third, the root element (start symbol) must be given. The root element must be a metaclass from the metamodel:

```
START YourRootMetaClassName
```

A CS specification can also have multiple root elements, which must be separated by a comma:

```
START RootMetaClass1, RootMetaClass2, RootMetaClass3
```

Typical candidates for root elements are metaclasses that do not have incoming containment edges.

Altogether a typical header for a **.cs** file looks something like:

```
SYNTAXDEF yourFileExtension  
FOR <yourGenModelNamespaceURI> <yourGenmodelLocation>  
START YourRootMetaClassName
```

3.1.2 Importing other Metamodels and Syntax Specifications

Sometimes it is required to import additional metamodels, e.g., if they are only referenced in the current one and a syntax for some or all of its concepts needs to be specified or reused. Metamodels and syntax specifications can be imported in a dedicated import section, which must follow after the start symbols:

```
IMPORTS {  
    // imports go here  
}
```

The list of imports must contain at least one entry. If no imports are needed the whole section must be left out. An import entry consists of a prefix, which can be used to refer to imported elements in rules, the metamodel namespace URI and optionally the name of a concrete syntax defined for that metamodel. If a syntax is imported, all its rules are reused and need not to be specified in the current **cs** specification. Importing syntax rules is optional. One can also just import the metamodel contained in the generator model.

```
prefix : <genModelURI> <locationOfTheGenmodel>  
    // next line is optional (except the semicolon)  
WITH SYNTAX syntaxURI <locationOfTheSyntax>;
```

The two locations are again optional. For resolving the generator model the same rules as for the “main” generator model (declared after the **FOR** keyword) apply. For locating the syntax, EMFText looks up the registry of registered syntax specifications. If no registered syntax is found, **locationOfTheSyntax** is used to find the **.cs** file to import. Again, **locationOfTheSyntax** must be a relative or absolute URI.

3.1.3 Code Generation Options

EMFText's code generation can be configured using various options. These are specified in a dedicated optional `OPTIONS` section:

```
OPTIONS {
    // options go here in the following form:
    optionName = "optionValue";
}
```

The list of valid options and their documentation can be found in Appendix A1.

3.2 Tokens

EMFText allows to specify custom tokens. Each token type has a name and is defined by a regular expression. This expression is used to convert characters from the DSL files to form groups (i.e., tokens). Tokens are the smallest unit processed by the generated parser. By default, EMFText implicitly uses a set of predefined standard tokens, namely:

- `TEXT` : `('A'..'Z'|'a'..'z'|'0'..'9'|'_'|'-')+`,
- `LINEBREAK` : `('r\n'|'r'|'n')`,
- `WHITESPACE` : `(' '|'\t'|'\f')`.

The predefined tokens can be explicitly excluded by using the `usePredefinedTokens` option:

```
OPTIONS {
    usePredefinedTokens = "false";
}
```

3.2.1 Defining Custom Tokens

To define custom tokens, a `TOKENS` section must be added to the `.cs` file. This section has the following form:

```
TOKENS {
    // token definitions go here in the form:
    DEFINE YOUR_TOKEN_NAME $yourRegularExpression$;
}
```

Every token name has to start with a capital letter. A regular expression must conform to the ANTLRv3 syntax for regular expressions (without semantic annotations). However, don't worry: EMFText will complain if there is a problem with your regular expressions, such as typos or overlaps of regular expressions.

3.2.2 Composed Tokens

Sometimes, regular expressions are quite repetitive and one wants to reuse simple expressions to compose them to more complex ones. To do so, one can refer to other token definitions by their name. For example:

```
TOKENS {  
    // simple token  
    DEFINE CHAR $('a'..'z'|'A'..'Z')$;  
    // simple token  
    DEFINE DIGIT $('0'..'9')$;  
    // composed token  
    DEFINE IDENTIFIER CHAR + $($ + CHAR + $|$ + DIGIT + $)*$;  
}
```

If token definitions are merely used as “helper” tokens, they can be tagged as **FRAGMENT**. This means the helper token itself is used in other token definitions, but not anywhere else in the syntax specification:

```
TOKENS {  
    // simple token  
    DEFINE CHAR $('a'..'z'|'A'..'Z')$;  
    // helper token - not used on its own  
    DEFINE FRAGMENT DIGIT $('0'..'9')$;  
    // composed token  
    DEFINE IDENTIFIER CHAR + $($ + CHAR + $|$ + DIGIT + $)*$;  
}
```

The regular expressions are composed the same way strings are composed in Java programs. Therefore, make sure to put parenthesis around expressions where it is needed.

3.2.3 Token Priorities

EMFText does automatically sort token definitions. However, sometimes token definitions might be ambiguous (i.e., the regular expressions defined for two different tokens are not disjoint). In such cases EMFText will always prefer more specific tokens over more general tokens. That is, if one token definition includes another one, the latter is preferred over the former. If the automatic token sorting fails, EMFText will report an error. In this case one must turn off the automatic sorting using the **disableTokenSorting** option and sort the tokens manually. If automatic token sorting is turned off, one can give a higher priority to imported tokens by using the following directive:

```
TOKENS {  
    PRIORITIZE NameOfImportedToken;  
    DEFINE SOME_CUSTOM_TOKEN $someCustomRegularExpression$;  
}
```

The **PRIORITIZE** directive can also be used with the predefined tokens **TEXT**, **LINEBREAK** and **WHITESPACE**.

3.3 Token Styles

To define the default syntax highlighting for a language, a special section `TOKENSTYLES` can be used. For each token or keyword the color and style (**BOLD**, **ITALIC**, **STRIKETHROUGH**, **UNDERLINE**) can be specified as follows:

```
TOKENSTYLES {
    // show YOUR_TOKEN in black
    "YOUR_TOKEN" COLOR #000000;
    // show keyword 'public' in red and bold font face
    "public" COLOR #FF0000, BOLD;
}
```

The default highlighting can still be customized at runtime by using the generated preference pages.

3.4 Syntax Rules

For each concrete metaclass you can define a syntax rule. The rule specifies what the text that represents instances of the class looks like. Rules have two sides—a left and right-hand side. The left side denotes the name of the meta class, while the right-hand side defines the syntax elements. If you have imported additional metamodels you can refer to their metaclasses using the prefix you’ve defined in the import statement. For example `pre.MetaClassA` refers to `MetaClassA` from the metamodel with the prefix `pre`.

3.4.1 Simple Syntax

The most basic form of a syntax rule is:

```
YourMetaClass ::= "someKeyword" ;
```

This rule states that whenever the text `someKeyword` is found, an instance of `YourMetaClass` must be created. Besides text elements that are expected “as is”, parts of the syntax can be optional or repeating. For example the syntax rule:

```
YourMetaClassWithOptionalSyntax ::= ("#")? "someKeyword" ;
```

states that instances of `YourMetaClassWithOptionalSyntax` can be represented both by `#someKeyword` and `someKeyword`. Similar behavior can be defined using a star instead of a question mark. The syntax enclosed in the parenthesis can then be repeated. For example,

```
YourMetaClassWithRepeatingSyntax ::= ("#")* "someKeyword" ;
```

allows to represent instances of metaclass `YourMetaClassWithRepeatingSyntax` by writing `someKeyword`, `#someKeyword`, `##someKeyword`, or any other number of hash symbols followed by `someKeyword`. One can also use a plus sign instead of a star or question mark. In this case, the syntax enclosed in the parenthesis can be repeated, but must appear at least once.

3.4.2 Syntax for EAttributes

Syntax for EAttributes Having an Arbitrary Type

If metaclasses have attributes, we can also specify syntax for their values. To do so, simply add brackets after the name of the attribute:

```
YourMetaClassWithAttribute ::= yourAttribute[] ;
```

Optionally, one can specify the name of a token inside the brackets. For example:

```
YourMetaClassWithAttribute ::= yourAttribute[MY_TOKEN] ;
```

If the token name is omitted, as in the first example, EMFText uses the predefined token `TEXT`, which includes alphanumeric characters (see Sect. 3.2). The found text is automatically converted to the type of the attribute. If this conversion is not successful, an error is raised when opening a file containing wrong syntax. For details on customizing the conversion of tokens, see Sect. 4.2.1.

Another possibility to specify the token definition that shall be used to match the text for the attribute value is to do it inline. For example

```
YourMetaClassWithAttribute ::= yourAttribute['(',')'] ;
```

can be used to express that the text for the value of the attribute `yourAttribute` must be enclosed in parenthesis. Between the parenthesis arbitrary characters (except the closing parenthesis) are allowed. Other characters can be used as prefix and suffix here as well.

By default, the suffix character (in the example above this was the closing parenthesis) can not be part of the text for the attribute value. To allow this, an escape character needs to be supplied:

```
YourMetaClassWithAttribute ::= yourAttribute['(',')','\\'] ;
```

Here the backslash can be used inside the parenthesis to escape the closing parenthesis. It must then also be used to escape itself. That is, one must write two backslash characters to represent one.

To give an example on how escaping works, consider the following text: `(text(more\\))`. After parsing, this yields the attribute value `text(more)`. The character sequence `\` is replaced by `)`. Note that the opening parenthesis does not need to be escaped.

Syntax for EAttributes of Type EBoolean

For boolean attributes, EMFText provides a special feature to ease syntax specification. All that is required is to give the two strings that represent `true` and `false`. To give an example consider the following syntax rule:

```
YourMetaClassWithAttribute ::= yourAttribute["yes" : "no"] ;
```

This rule states that `yes` represents the `true` value and `no` represents `false`. You can also use the empty string for one of the values:

```
YourMetaClassWithAttribute ::= yourAttribute["set" : ""] ;
```

This way, the attribute is set to **false** by default and set to **true** in the text **set** is found.

Syntax for EAttributes of Type EEnum

For enumeration attributes, EMFText does also provide a special feature to ease syntax specification. For each literal of the enumeration, the corresponding string representation must be given. For example, consider the following syntax rule:

```
YourMetaClassWithAttribute ::=
    yourAttribute[red : "r", green : "g", blue : "b"];
```

This rule states that **r** represents the literal **red**, **g** represents the literal **green** and **b** represents the literal **blue**. The literals of the enumeration are identified by their name. You can also use the empty string for one of the values:

```
YourMetaClassWithAttribute ::=
    yourAttribute[red : "r", green : "g", blue : ""] ;
```

This way, the attribute is set to **blue** by default.

3.4.3 Syntax for EReferences

Metaclasses can have references and consequently there is a way to specify syntax for these. EMF distinguishes between *containment* and *non-containment* references. In an EMF model, the elements that are referenced with the former type are contained in the parent elements. EMFText thus expects the text for the contained elements (children) to be also contained in the parent's text.

The latter (non-containment) references are referenced only and are contained in another (parent) element. Thus, EMFText does not expect text that represents the referenced element, but a symbolic identifier that refers to the element. This is very similar to the declaration and use of variables in Java. The declaration of a variable consists of the complete text that is required to describe a variable (e.g., its type). In contrast, when the variable is used at some other place it is simply referred to by its name. Non-containment references are similar to uses of variables.

Syntax for Containment References

A basic example for defining a rule for a meta class that has a containment reference looks like this:

```
YourContainerMetaClass ::= "CONTAINER" yourContainmentReference ;
```

It allows to represent instances of **YourContainerMetaClass** using the keyword **CONTAINER** followed by one instance of the type that **yourContainmentReference** points to. If multiple children need to be contained the following rule can be used:

```
YourContainerMetaClass ::= "CONTAINER" yourContainmentReference* ;
```

In addition, each containment reference can be restricted to allow only certain types, for example:

```
YourContainerMetaClass ::= "CONTAINER"  
                           yourContainmentReference : SubClass ;
```

does allow only instances of `SubClass` after the keyword `CONTAINER` even though the reference `yourContainmentReference` may have a more general type. One can also add multiple subclass restrictions, which must then be separated by a comma:

```
YourContainerMetaClass ::= "CONTAINER"  
                           yourContainmentReference : SubClassA, SubClassB ;
```

Syntax for Non-Containment References

A basic example for defining a rule for a metaclass that has a non-containment reference looks like this:

```
YourPointerMetaClass ::= "POINTER" yourNonContainmentReference[] ;
```

The rule is very similar to the one for containment references, but uses the additional brackets after the name of the reference. Within the brackets the token that the symbolic name must match can be defined. In the case above, the default token `TEXT` is used. Therefore, the syntax for an example instance of class `YourPointerMetaClass` can be `POINTER a`.

Since `a` is just a symbolic name that must be resolved to an actual model element, EMF-Text generates a Java class that resolves `a` to a target model element. This class can be customized to specify how symbolic names are resolved to model elements. The default implementation of the resolver looks for all model elements that have the correct type (the type of `yourNonContainmentReference`) and that have a name or id attribute that matches the symbolic name. For details on how to customize the resolving of references, see Sect. 4.2.2.

3.4.4 Syntax for Printing Instructions

By default, EMFText can print all kinds of models. It does also preserve the layout of the textual representation when models are parsed and printed later on. However, to print models that have been created in memory, additional information can be passed to EMFText to customize the print result. This (optional) information includes the number of whitespaces and line breaks to be inserted between keywords, attribute values, references and contained elements. If you do not want to print models to text, printing instructions are not needed in your `.cs` file.

Syntax for Printing Whitespace

To explicitly print whitespace characters, the `#` operator can be used on the right side of syntax rules:

```
YourMetaclass ::= "keyword" #2 attribute[];
```


It is followed by a number that determines the number of whitespaces to be printed. In the example above, two whitespace characters are printed between the keyword and the attribute value.

Syntax for Printing Line Breaks

To explicitly print line breaks, the `!` operator can be used on the right side of syntax rules:

```
YourMetaclass ::= "keyword" !0 attribute[];
```

It is followed by a number that determines the number of tab characters that shall be printed after the line break. In the example above, a line break is printed after **keyword**. The number of tabs refers to the current model element (i.e., `EObject`), which is printed. To print contained objects with an indentation of one tab, you can use a rule like this:

```
YourMetaclass ::= "keyword" "{" (!1 containmentRef)* !0 "}";
```

Here, the first line break operator (`!1`) makes sure that all the contained objects appear on a new line and that they are preceded by one tab character. The second line break operator (`!0`) tells EMFText to print the closing parenthesis (`}`) also on a new line, but without a leading tab.

3.4.5 Syntax for Expressions

When defining syntax for an expression language (e.g., arithmetic expressions) EMFText's standard mechanisms for specifying syntax can lead to structures that can not be optimally handled by an interpreter or evaluator. Furthermore, the underlying parser generator technology used by EMFText causes problems if left recursive rules are required to build an optimal expression tree, which is the case for all expression languages with left-associative binary operators (e.g., `-`). Therefore, EMFText provides a special feature called operator precedence annotations (`@Operator`). These annotations can be added to all rules, which refer to expression metaclasses with a common superclass. For example, the rule:

```
@Operator(type="binary_left_associative", weight="1", superclass="Expression")
Additive ::= left "+" right;
```

defines syntax for a metaclass **Additive**. The references **left** and **right** must be containment references and have the type **Expression**, which is the abstract supertype for all metaclasses of the expression metamodel.

The **type** attribute specifies the kind of expression at hand, which can be **binary** (either **left_associative** or **right_associative**), **unary_prefix**, **unary_postfix** or **primitive**.

The **weight** attribute specifies the priority of one expression type over another. For example, if a second rule:

```
@Operator(type="binary_left_associative", weight="2", superclass="Expression")
Multiplicative ::= left "*" right;
```

is present, EMFText will create an expression tree, where **Multiplicative** nodes are created last (i.e., multiplicative expressions take precedence over additive expressions).

Unary expressions can be defined as follows:

```
@Operator(type="unary_prefix", weight="4", superclass="Expression")
Negation ::= "-" body;
```

There is also the option to define **unary_postfix** rules.

Primitive expressions can be defined as follows:

```
@Operator(type="primitive", weight="5", superclass="Expression")
IntegerLiteralExp ::= intValue[INTEGER_LITERAL];
```

They should be used for literals (e.g., numbers, constants or variables).

One can certainly mix syntax rules that use the **@Operator** annotation with ones that do not in the same CS specification. However, one must be careful with the inheritance hierarchy in the metamodel in this case. All rules that use the **@Operator** annotation must refer to a metaclass that extends the metaclass specified with the **superclass** attribute. For subclasses of this superclass there must not be other non-**@Operator** rules. One could say that subtrees of the metaclass hierarchy must be either consistently specified as **@Operator** rules or not. Mixing is not possible.

For examples how to use **@Operator** annotations see the SimpleMath language in the EMF-Text Syntax Zoo¹ and the ThreeValuedLogic DSL². These do also come with an interpreter which shows how expression trees can be evaluated.

3.5 Suppressing Warnings

To suppress warnings issued by EMFText in **.cs** files one can use the **@SuppressWarnings** annotation. This annotation can be added to rules, token definitions or complete syntax definitions. One can either suppress all warnings or just specific types. To suppress all warnings for a syntax use the following syntax:

```
@SuppressWarnings
YourMetaClass ::= "someKeyword";
```

A list of all warning types can be found in Appendix A2. For example, to suppress warnings about features without syntax, you may use:

```
@SuppressWarnings(featureWithoutSyntax)
YourMetaClassWithAttribute ::= "someKeyword";
```

¹<http://www.emftext.org/language/simplemath>

²<http://www.emftext.org/language/threevaluedlogic>

4 DSL Customization

4.1 Customization Techniques

To adjust DSL plug-ins generated by EMFText to specific needs, there are three different customization techniques. Each of the subsequent sections describes one of them.

4.1.1 Overriding Generated Artifacts

The most simple way to customize generated artifacts is to tell EMFText that it must not override a specific class or file, which needs to be changed. For all artifacts that are generated by EMFText there is a **override** option, which can be set to **false** to preserve such manual changes (see Appendix A1 for a complete list). For example, to customize the hover text shown when the mouse arrow points at an element in the editor, the **overrideHoverTextProvider** must be set to **false**.

For all files that do not depend on the rules defined in the **.cs** file, this customization technique is fine. These files do not change, if new rules are added or existing ones are changed. Thus, manual changes will not cause conflicts if the syntax evolves. Only when EMFText is updated and the code generators are replaced, one may want to compare the manually adjusted files with the ones generated by the new EMFText version to see whether all customizations are still correct. This does particularly apply to generated manifest files and plug-in descriptors. A list of all classes that are syntax dependent can be found in Appendix A3.

4.1.2 Overriding Meta Information Classes

For all files that do depend on the rules defined in the **.cs** file, another customization technique is more appropriate. Instead of setting the **override** option to **false** for the artifact that needs to be changed, one can set the **override** option for the meta information classes to **false**.

Each of the two generated resource plug-ins contains a meta information class. These are called **XYZMetaInformation** and **XYZUIMetaInformation**. Both classes provide factory methods to create instances of some important classes (e.g., **createParser()** or **createPrinter()**). To customize these classes (e.g., the printer) one can change the **create** methods to return instances of subclasses of the original classes. By using subclasses instead of overriding the classes directly, one can regenerate the resource plug-ins and thereby obtain new up-to-date classes, but still make customizations by overriding individual methods.

4.1.3 Using Generated Extension Points

In addition to overriding generated classes—either directly or using the meta information factory methods—one can use the extension points that are generated by EMFText for all DSLs.

Currently EMFText generates two extension points for each DSL—**default_load_options** and **additional_extension_parser**.

The former can be used to customize how resources are loaded. For example, post processors can be registered which apply changes to the models that are created from their textual representation (see Sect. 4.2.3). Also, pre processors can be registered to process the input before it is actually passed to the parser. This is particularly useful to handle unicode characters (see the JaMoPP implementation¹ for an example how to use it).

The latter extension point can be used to register additional parsers which can handle a particular file extension. EMF on its own does map one file extension to one resource factory, but sometimes it is useful to have multiple resource types for the same file extension. An example for how to use this extension point can be found in the textual syntax for Ecore².

4.2 Concrete Customizations

4.2.1 Customizing Token Resolving

To create models from their textual representation, it is necessary to convert the plain text found in Domain-specific Language (DSL) documents to attribute values (i.e., data types). For example, if the string "123" is found in a text file and shall be used as value for an attribute which has type **EInt**, the string needs to be converted to an **int**. Basic conversions, such as the one just mentioned, are handled by the generated class **XYZDefaultTokenResolver** (assuming the file extension of your DSL is **xyz**). However, if you want to use custom data types in your metamodels, or if you need to customize the default conversion, there are two ways to change the conversion of text to data types.

Customizing TokenResolver Classes

The first option to customize the conversion of text, is to change the generated token resolver classes. EMFText generates one of these classes for each token that is defined in the **.cs** file. All classes end up in a package called **analysis** in the **src** folder of the generated resource plug-in.

Each token resolver class has two methods—**resolve()** and **deResolve()**. The first one is used to convert text to data types. The second one is used to perform the other way around. Consequently, **resolve()** is used when models are parsed, while **deResolve()** is used to print models to text.

The default implementation for both methods delegates calls to a default token resolver. However, this call can be replaced by custom code implementing different behavior. The code in the **resolve()** method must convert the text (given by the parameter **lexem**) to an object of the data type. This object must be set using **result.setResolvedToken()**. The **deResolve()** must implement the opposite behavior by returning a string representation of the object.

In the following a custom token resolver class is shown, which converts **TEXT** tokens to **java.util.Date** objects:

¹<http://www.jamopp.org>

²http://www.emftext.org/index.php/EMFText_Concrete_Syntax_Zoo_Ecore

```

import java.text.ParseException;
import java.text.SimpleDateFormat;
import java.util.Date;
import java.util.Map;

import org.eclipse.emf.ecore.EObject;
import org.eclipse.emf.ecore.EStructuralFeature;
import org.emftext.language.xyz.resource.xyz.IXyzTokenResolveResult;
import org.emftext.language.xyz.resource.xyz.IXyzTokenResolver;

public class XyzTEXTTokenResolver implements IXyzTokenResolver {

    private SimpleDateFormat format = new SimpleDateFormat("dd.MM.yyyy");

    public String deResolve(Object value, EStructuralFeature feature,
        EObject container) {
        return format.format(value);
    }

    public void resolve(String lexem, EStructuralFeature feature,
        IXyzTokenResolveResult result) {
        try {
            Date date = format.parse(lexem);
            result.setResolvedToken(date);
        } catch (ParseException e) {
            result.setErrorMessage(lexem + "_is_not_a_valid_date.");
        }
    }

    public void setOptions(Map<?,?> options) {
        // can be left empty
    }
}

```

The difference between this kind of customization and the one below, is that the implemented conversion is local w.r.t. the textual syntax of the DSL. If you have multiple syntax definitions for your DSL, each can use completely different algorithms to convert data types.

Customizing the EMF Data Type Handling

Alternatively, you can customize the data type handling that is built into EMF. To do so, you need to define a custom data type in the metamodel (e.g., `JavaDate`). Then, the instance type name must be set to the actual Java class, which shall be used to represent instances of the data type (e.g., `java.util.Date`). When running the EMF code generation, the `FactoryImpl` class

will contain two methods—`createJavaDateFromString()` and `convertJavaDateToString()`. These need to be customized similar to the token resolver class before.

The following code is a snippet from the `XYZFactoryImpl` class and shows how to implement the same behavior as above using EMF's own data type handling facilities.

```
private SimpleDateFormat format = new SimpleDateFormat("yyyy-MM-dd");

/**
 * <!-- begin-user-doc -->
 * <!-- end-user-doc -->
 * @generated NOT
 */
public Date createJavaDateFromString(EDatatype eDataType,
    String initialValue) {
    try {
        return format.parse(initialValue);
    } catch (ParseException e) {
        // ignore
    }
    return (Date)super.createFromString(eDataType, initialValue);
}

/**
 * <!-- begin-user-doc -->
 * <!-- end-user-doc -->
 * @generated NOT
 */
public String convertJavaDateToString(EDatatype eDataType,
    Object instanceValue) {
    return format.format(instanceValue);
}
```

4.2.2 Customizing Reference Resolving

If metamodels expose non-containment references (i.e., `EReferences` where the `containment` attribute is set to `false`), EMFText needs to resolve these references. This basically means that symbolic identifiers, which are used to reference other `EObjects` must be replaced by actual references to the respective objects.

Thus, EMFText generates one reference resolver class for each non-containment reference that is found in the metamodel of your DSL and that is actually used in the concrete syntax definition. All reference resolver classes end up in a package called `analysis` in the `src` folder of the generated resource plug-in.

The default implementation delegates calls to the `DefaultResolverDelegate` class. This class uses the following strategy to find objects that are referenced by identifiers:

1. the resource is searched for objects that have the correct type (i.e., the type of the non-containment reference)
2. if the objects having the correct type have an `ID` attribute, or a `name` attribute, or a single attribute of type `EString`, the value of this attribute is compared to the symbolic identifier. If the identifier matches the value of the attribute, the object is considered to be referenced.
3. if no matching object is found and the symbolic identifier is a valid URI, `EMFText` tries to load the resource at the URI. If the resource contains a root object with the correct type, this object is assumed to be referenced.

In cases, where this default resolving strategy is not sufficient, you can customize the resolver classes by changing the bodies of the methods `resolve()` and `deResolve()`. These methods are similar to the ones generated for the token resolver classes (see Sect. 4.2.1). The first one is used to find the object referenced by an identifier. The second one does the opposite—it creates a symbolic identifier for a referenced object. Again, the former is used after parsing. The latter is called when printing models.

The `resolve()` method must call `result.addMapping(identifier, object)` to set the referenced object, if one is found. The `deResolve()` method can simply return the textual representation of the referenced object as string.

To enable code completion for references, the `resolve()` method must be extended to take care of the `resolveFuzzy` parameter. If this parameter is `true`, the resolver class is used for code completion and must add all referenceable object to the result. Thus, instead of checking, whether `identifier` actually references an object, `resolve()` can simply add all objects that have the correct type to the result by calling `result.addMapping()`. However, in this case, the first argument, which is passed to `addMapping()` should not be `identifier`, but rather the string representation of the object.

4.2.3 Implementing Post Processors

Another quite common customization task is to implement post processors. Post processors basically provide the possibility to modify the model that is created when text is parsed. This way one can add default elements which are not represented in the model's textual representation or normalize models if multiple concrete syntax is allowed for the same DSL concept.

Registered post processors are automatically called by the generated DSL tooling whenever a model is created from text. This does also include the case where the editor parses text in the background to show errors immediately. Thus, post processors must be able to deal with partial models or explicitly abort their execution if errors (e.g., syntactical problems) have been detected beforehand.

Post processors should not be used to solely implement semantic checks (i.e., to validate models). This should rather be done using the EMF Validation Framework as this allows checks to be available in all editors rather than a single one that was generated by `EMFText`.

To register a post processor for your DSL, the generated `default_load_options` extension point must be used. This extension point allows to register classes that provide default load options, which are used whenever resources are loaded by the generated DSL tooling.

Such classes must implement the `IXyzOptionProvider` interface, which has one method—`getOptions()`. To register a post processor, this method must return a map that has an entry where the key is `IXyzOptions.RESOURCE_POSTPROCESSOR_PROVIDER` and the value is an instance of a class that implements the `IXyzResourcePostProcessorProvider` interface. The latter object is used by the generated DSL tooling to instantiate post processors by calling `getResourcePostProcessor()`.

To illustrate this procedure consider the case where you want to add some default model elements to all models that are created from text. To do so, you need a `plugin.xml` which registers the option provider using the following code snippet:

```
<extension point="org.emftext.language.xyz.resource.xyz.default_load_options">
  <provider
    class="org.emftext.language.xyz.post.PostProcessorExample"
    id="org.emftext.language.xyz.post.provider1">
  </provider>
</extension>
```

This `plugin.xml` can be part of a separate plug-in (i.e., it does not need to be part of the generated resource plug-ins). The respective post processor class can be as follows.

```
package org.emftext.language.xyz.post;

import java.util.Collections;
import java.util.Map;

import org.eclipse.emf.ecore.EObject;
import org.emftext.language.xyz.resource.xyz.IXyzOptionProvider;
import org.emftext.language.xyz.resource.xyz.IXyzOptions;
import org.emftext.language.xyz.resource.xyz.IXyzResourcePostProcessor;
import org.emftext.language.xyz.resource.xyz.IXyzResourcePostProcessorProvider;
import org.emftext.language.xyz.resource.xyz.mopp.XyzResource;

public class PostProcessorExample implements IXyzOptionProvider,
    IXyzResourcePostProcessorProvider,
    IXyzResourcePostProcessor {

    public Map<?, ?> getOptions() {
        return Collections.singletonMap(
            IXyzOptions.RESOURCE_POSTPROCESSOR_PROVIDER,
            this
        );
    }

    public IXyzResourcePostProcessor getResourcePostProcessor() {
        return this;
    }
}
```



```

public void process(XyzResource resource) {
    EObject root = resource.getContents().get(0);
    // perform model modifications here
}
}

```

One can see that this class implements all three interfaces that are required to register a post processor. The actual post processing must be implemented in the `process()` method. Here, the model can be modified in arbitrary ways. However, one must be aware that any modification will yield different textual representations when the model is printed.

4.2.4 Implementing Quick Fixes

If a problem is added to a resource (e.g., by a post processor, cf. Section 4.2.3), problem markers are automatically created in the editor. Markers are a convenient way to inspect the cause of the problem directly from the editor. By providing an instance of `IXyzQuickFix` while creating an `IXyzProblem`, actions are specified that can automatically solve the reported problem.

To implement a custom quick fix `CustomQuickFix` for a specific problem, `XyzQuickFix` must be subclassed. Normally, the context object (i.e., the object where the action is applied to) is provided as a parameter to the constructor of `CustomQuickFix`. The method `applyChanges()` performs the actual fix of the problem on the context object.

This context object is also passed to the constructor of `XyzQuickFix` along with a brief description of the quick fix and an image key that references an image for the quick fix. The image key is used by the `XyzImageProvider` and can reference images in multiple ways.

First, the key can be one of the standard Eclipse images. That is, the key can be a field from class `org.eclipse.ui.ISharedImages`, for example, `IMG_ELCL_REMOVE`. Second, the key can denote a path relative to the UI project. Or, the third option is to use an arbitrary URL as key. For example, the URL `platform:/plugin/com.xyz.plugin/icons/xyzIcon.png` indicates that the file `xyzIcon.png` is used for the quick fix.

In case a more sophisticated means for providing images is needed, the `XyzImageProvider` can be manually extended after the option `overrideImageProvider` has been set to `false`.

The following listing shows a simple quick fix, which removes a given element from the resource.

```

public class RemoveElementQuickFix extends XyzQuickFix
    implements IXyzQuickFix {

    private EObject objectToRemove;

    public RemoveElementQuickFix(String message, EObject objectToRemove) {
        super(message, "IMG_ETOOL_DELETE", objectToRemove);
        this.objectToRemove = objectToRemove;
    }
}

```

```
@Override
public void applyChanges() {
    EcoreUtil.delete(objectToRemove);
}
}
```

4.2.5 Implementing Builders

To implement a custom builder for your DSL, you can basically set the code generation option `overrideBuilder` to `false`:

```
OPTIONS {
    overrideBuilder = "false";
}
```

After regenerating the resource plug-ins (see Sect. 2.3), you will find a new class `XYZBuilder` in the `src` folder of the generated resource plug-in (assuming the file extension of your DSL is `xyz`). If you face compilation errors, make sure to delete the `XYZBuilder` class from the `src-gen` folder.

The generated builder class contains two methods—`isBuildingNeeded()` and `build()`. The first one is called to let the builder decide, which resources need to be included in the build process. The default implementation returns `false` to avoid unnecessary loading of resources. To include all textual resources that contain models of your DSL, change the method to return `true`.

The second method is called whenever the content of a resource changes. You can implement arbitrary behavior here. Usually, builders create some kind of derived artifact, for example a transformed or compiled version of the DSL model. Since `build()` retrieves the resource as method parameter, you can easily access the contents of the resource. To save the derived artifact it is good practice to use the URI of the original resource to derive a new URI. This can for example be done by removing segments and adding new ones.

The following listing shows a simple builder, which copies the contents of the resource to a new resource without making any changes.

```
import java.io.IOException;
import java.util.Collection;

import org.eclipse.core.runtime.IProgressMonitor;
import org.eclipse.core.runtime.IStatus;
import org.eclipse.core.runtime.Status;
import org.eclipse.emf.common.util.EList;
import org.eclipse.emf.common.util.URI;
import org.eclipse.emf.ecore.EObject;
import org.eclipse.emf.ecore.resource.Resource;
import org.eclipse.emf.ecore.util.EcoreUtil;
import org.eclipse.xtext.language.xyz.resource.xyz.IXYZBuilder;
```

```

public class XyzBuilder implements IXyzBuilder {

    public boolean isBuildingNeeded(URI uri) {
        return true;
    }

    public IStatus build(XyzResource resource, IProgressMonitor monitor) {
        // get contents and create copy
        EList<EObject> contents = resource.getContents();
        Collection<EObject> contentsCopy = EcoreUtil.copyAll(contents);

        // create new resource with different name
        URI newUri = URI.createURI("copy.xyz").resolve(resource.getURI());
        Resource newResource = resource.getResourceSet().createResource(newUri);
        // add copy of original content to new resource
        newResource.getContents().addAll(contentsCopy);
        // save new resource
        try {
            newResource.save(null);
        } catch (IOException e) {
            // handle exception
        }
        return Status.OK_STATUS;
    }
}

```

Alternatively, you can also register builders for your DSL in other plug-ins.

4.2.6 Implementing Interpreters

To ease the implementation of interpreters for your DSL, EMFText generates an interpreter stub. Assuming the file extension of your DSL is **xyz**, the abstract stub class will be named **AbstractXyzInterpreter**. To implement concrete interpreters, you can create subclasses of this stub class.

For each metaclass found in the metamodel of your DSL, the interpreter stub contains a **interpret_Classname** method. These methods can be overridden in concrete interpreter classes to implement the desired interpretation for the objects of each type.

After implementing the methods for the classes which shall be interpreted, the interpreter can be used in different modes. First, models can be interpreted using a stack. In this case, the **interpret_Classname** methods must perform the interpretation, but should not call other **interpret** methods. This is automatically performed by the interpreter. One can put objects on the interpretation stack by calling **addObjectToInterpret()** and then start interpretation by calling **interpret()**. Interpretation ends when all objects from the stack are consumed.

Second, the interpretation can be performed without using the stack. In this case, the **interpret_Classname** methods call other **interpret** methods to continue interpretation.

The traversal of the model is more explicit than using the interpreter with the stack in this mode.

The first, stack-based interpretation mode is useful to traverse models in a bottom-up fashion. One can simply put all models elements (using `eAllContents()` on the model root element) on the stack and then start interpretation. The second, stack-independent interpretation mode is useful to traverse models top-down.

The interpreter stub class has two type parameters—`ResultType` and `ContextType`, which concrete subclasses must bind. The former parameter (i.e., `ResultType`) specifies the return type of the `interpret` methods. The latter parameter (i.e., `ContextType`) defines the type of the parameter that is passed to the `interpret` methods. By binding the type parameters one can use arbitrary classes to pass interpretation results.

Examples for interpreters can be found in the EMFText Syntax Zoo. Both SimpleMath³ and the ThreeValuedLogic DSL⁴ use the generated interpreter stubs.

4.2.7 Customizing Text Hovers

To implement custom text hovers for your DSL, basically set the code generation option `overrideHoverTextProvider` to `false`:

```
OPTIONS {  
    overrideHoverTextProvider = "false";  
}
```

After regenerating the resource plug-ins (see Sect. 2.3), a new class `XyzHoverTextProvider` can be found in the `src` folder of the generated resource UI plug-in (assuming the file extension of your DSL is `xyz`). If you face compilation errors, make sure to delete the `XyzHoverTextProvider` class from the `src-gen` folder.

The generated hover text provider class contains one method—`getHoverText()`. The default implementation of this method delegates calls to a default provider. To customize the hover text you can inspect the `EObject` passed to the method and return arbitrary HTML code. The following listing shows a simple customized provider, which returns the type of the `EObject`.

```
import org.eclipse.emf.ecore.EObject;  
import org.emftext.language.xyz.resource.xyz.IXyzHoverTextProvider;  
  
public class XyzHoverTextProvider implements IXyzHoverTextProvider {  
  
    public String getHoverText(EObject object) {  
        return "An_object_of_type_" + object.eClass().getName();  
    }  
}
```

³<http://www.emftext.org/language/simplemath>

⁴<http://www.emftext.org/language/threevaluedlogic>

4.2.8 Customizing Code Completion Proposals

The DSL tooling generated by EMFText does equip the DSL editor with default code completion facilities. If you find the completion proposals to be not sufficient, or you want to adjust them w.r.t. the text that is displayed for specific proposals or the icons that are shown, you can customize the proposals. To do so, set the `overrideProposalPostProcessor` option to `false`. After regenerating the resource plug-ins, you will find a class `XYZProposalPostProcessor` in the `src` folder of the UI resource plug-in. The class with the same name in the `src-gen` folder can then be deleted.

The default implementation of the only method in this class (i.e., `process()`) does return the list of proposals as they are. However, you can make arbitrary changes to this list. For example, you can remove proposals if you find them not useful or modify proposals if you want to change the displayed string or icon. You can also add new proposals if needed.

The proposals that are passed to the `process()` method provide information such as which structural feature they complete (`getStructuralFeature()`), which image they are associated with (`getImage()`) or which text is inserted if the respective proposal is selected by a user (`getInsertString()`). To modify proposals, new instances of the `XYZCompletionProposal` must be created, because this class is immutable.

4.2.9 Adding Context Menu Items to the Outline View

To add new items to the context menu of the generated outline view, you can use the standard mechanism to register menu items. All that is needed, is to register a menu item (using the `org.eclipse.ui.menus` extension point), a command that is created when the menu item is selected (using the `org.eclipse.ui.commands` extension point) and a handler that can process your command (using the `org.eclipse.ui.handlers` extension point). For example, the following fragment of a `plugin.xml` file registers a new menu item that can be invoked on objects of type `org.emftext.language.xyz.XyzClass`.

```
<extension point="org.eclipse.ui.commands">
  <command
    id="org.emftext.language.xyz.resource.xyz.ui.command"
    name="Xyz_Command"
    description="This_is_a_Xyz_command">
  </command>
</extension>

<extension point="org.eclipse.ui.handlers">
  <handler
    class="org.emftext.language.xyz.resource.xyz.ui.CommandHandler"
    commandId="org.emftext.language.xyz.resource.xyz.ui.command">
  </handler>
</extension>

<extension point="org.eclipse.ui.menus">
```

```
<menuContribution
  locationURI="popup:org.emftext.language.xyz.resource.xyz.ui.outlinecontext?
  _____after=additions">
  <command
    commandId="org.emftext.language.xyz.resource.xyz.ui.command"
    label="Sample_action_registered_for_XYZ_outline_view">
    <visibleWhen checkEnabled="false">
      <iterate>
        <adapt type="org.emftext.language.xyz.XyzClass" />
      </iterate>
    </visibleWhen>
  </command>
</menuContribution>
</extension>
```

Note that you will also need a class `CommandHandler`, which must implement the interface `org.eclipse.core.commands.IHandler`.

4.2.10 Providing Custom Content for Files created by the New File Wizard

By default, EMFText generates a New File Wizard for your DSL. The content of the file that is created by this wizard, is automatically obtained by creating a minimal model that conforms to your metamodel and by printing this minimal model. However, if you would like to provide a different content for the files that are created by this wizard, you can simply create a text file with a different content. Assuming your syntax definition is stored in a file called `xyzsyntax.cs` and the file extension of your syntax is `xyz`, this text file must be called `xyzsyntax.newfile.xyz` and be stored in the folder that contains your syntax definition. When generating the text resource plug-ins, EMFText will read the content of this file and embed its content in the generated code.

If you would like to provide dynamic content for the files that are created by the New File Wizard, you can also set the `overrideNewFileContentProvider` option to `false` and change the `NewFileContentProvider` class according to your needs.

4.2.11 Implementing Launch Support

For executable DSLs it is convenient to provide users with support for launch configurations. EMFText does generate all the code that is required to obtain a custom launch configuration type and basic user interface to configure launch parameters. Also, shortcuts are registered that allow DSL users to execute (i.e., run or debug) DSL models directly from the project explorer or the active editor. Basically invoke `Run as...` or `Debug as...` on one of your DSL files to check out the default launch support.

To specify how your DSL is executed set the `overrideLaunchConfigurationDelegate` option to `false` and implement the `launch` method. The example code that is generated by EMFText shows how to obtain the root element of the model that shall be executed.

For an example on how to implement a launch configuration consider the SimpleMath language in the EMFText Syntax Zoo⁵.

⁵<http://www.emftext.org/language/simplemath>

List of Figures

2.1	Iterative EMFText language development process.	3
2.2	EMFText Project wizard.	4
2.3	Projects generated by EMFText to implement language tooling.	10

A Appendix

A1 Code Generation Options

EMFText currently supports 229 code generation options. However, most of them (194) are only used to specify which generated artifacts shall be customized. Subsequently, a list of all options and their description can be found.

additionalDependencies

A list of comma separated plug-in IDs, which will be added to the manifest of the generated resource plug-in. The default value for this option is an empty list.

additionalExports

A list of comma separated packages, which will be added as exports to the manifest of the generated resource plug-in. The default value for this option is an empty list.

additionalUIDependencies

A list of comma separated plug-in IDs, which will be added to the manifest of the generated resource UI plug-in. The default value for this option is an empty list.

additionalUIExports

A list of comma separated packages, which will be added as exports to the manifest of the generated resource UI plug-in. The default value for this option is an empty list.

antlrPluginID

Sets the ID for the generated common ANTLR runtime plug-in. The default value for this option is `org.emftext.common.antlr3_3_0`.

autofixSimpleLeftrecursion

If set to `true`, EMFText will try to fix rules that contain simple left recursion. The default value for this option is `false`. This is a non-standard option, which might be removed in future releases of EMFText.

backtracking

If set to `false`, the ANTLR-backtracking is deactivated for parser generation. The default value for this option is `true`.

basePackage

The name of the base package EMFText shall store the generated classes or the resource plug-in in. If this option is not set, the default value is determined by adding the suffix `resource.FILE_EXTENSION` to the base package of the generator model.

baseResourcePlugin

The plug-in containing the resource implementation for the DSL (if different from the generated resource plug-in). By default this option is not set, which means that the generated resource plug-in provides the resource implementation.

defaultTokenName

This option can be used to specify the name of the token that is used when no token is given for attributes or non-containment references in syntax rules. Declarations like **featureX[]** in CS rules will automatically be expanded to **featureX[TOKEN_Y]** if the value of this option is **TOKEN_Y**. The default value for this option is **TEXT**, which makes the predefined token **TEXT** the default token.

disableBuilder

If set to **true**, the builder that is generated and registered by default will not be registered anymore. The default value for this option is **false**.

disableEMFValidationConstraints

If set to **true**, constraint validation using the EMF Validation Framework is disabled. The default value for this option is **false**.

disableEValidators

If set to **false**, constraint validation using registered EValidators will be enabled. The default value for this option is **true**.

disableLaunchSupport

If set to **true**, code that is required to support launching of DSL models is not generated. The default value for this option is **false**.

disableTokenSorting

Disables the automatic sorting of tokens. The default value for this option is **false**.

forceEOF

If set to **false**, EMFText will generate a parser that does not expect an EOF signal at the end of the input stream. The default value for this option is **true**.

generateCodeFromGeneratorModel

If set to **true**, EMFText automatically generates the model code using the generator model referenced in the CS specification. The default value for this option is **false**.

generateTestAction

If set to **true**, EMFText generates a UI action that can be used to test parsing and printing of files containing textual syntax. The default value for this option is **false**. This is a non-standard option, which might be removed in future releases of EMFText.

generateUIPlugin

If set to **false**, EMFText will not generate the resource UI plug-in. The default value for this option is **true**.

licenceHeader

A URI pointing to a text file that contains a header which shall be added to all generated Java files. This option is useful to include copyright statements in the generated classes. If this option is not set, a default (empty) header is added to all generated Java classes.

memoize

If set to **false**, the ANTLR-memoize is deactivated for parser generation. The default value for this option is **true**.

overrideAbstractExpectedElement

If set to **false**, the AbstractExpectedElement class will not be overridden. The default value for this option is **true**.

overrideAbstractInterpreter

If set to **false**, the AbstractInterpreter class will not be overridden. The default value for this option is **true**.

overrideAdditionalExtensionParserExtensionPointSchema

If set to **false**, the extension point schema for additional parsers is not overridden. The default value for this option is **true**.

overrideAnnotationModel

If set to **false**, the AnnotationModel class will not be overridden. The default value for this option is **true**.

overrideAnnotationModelFactory

If set to **false**, AnnotationModelFactory class will not be overridden. The default value for this option is **true**.

overrideAntlrPlugin

If set to **false**, no ANTLR common runtime plug-in is generated. The default value for this option is **true**.

overrideAntlrTokenHelper

If set to **false**, the AntlrTokenHelper class will not be overridden. The default value for this option is **true**.

overrideAttributeValueProvider

If set to **false**, the AttributeValueProvider class will not be overridden. The default value for this option is **true**.

overrideBooleanTerminal

If set to **false**, the BooleanTerminal class will not be overridden. The default value for this option is **true**.

overrideBracketInformationProvider

If set to **false**, the BracketInformationProvider class will not be overridden. The default value for this option is **true**.

overrideBracketPreferencePage

If set to **false**, the BracketPreferencePage class will not be overridden. The default value for this option is **true**.

overrideBracketSet

If set to **false**, the BracketSet class will not be overridden. The default value for this option is **true**.

overrideBrowserInformationControl

If set to **false**, the BrowserInformationControl class will not be overridden. The default value for this option is **true**.

overrideBuildProperties

If set to **false**, the build.properties file will not be overridden. The default value for this option is **true**.

overrideBuilder

If set to **false**, the Builder class will not be overridden. The default value for this option is **true**.

overrideBuilderAdapter

If set to **false**, the BuilderAdapter class will not be overridden. The default value for this option is **true**.

overrideCardinality

If set to **false**, the Cardinality class will not be overridden. The default value for this option is **true**.

overrideCastUtil

If set to **false**, the CastUtil class will not be overridden. The default value for this option is **true**.

overrideChangeReferenceQuickFix

If set to **false**, the ChangeReferenceQuickFix class will not be overridden. The default value for this option is **true**.

overrideChoice

If set to **false**, the Choice class will not be overridden. The default value for this option is **true**.

overrideClasspath

If set to **false**, the .classpath file of the resource plug-in will not be overridden. The default value for this option is **true**.

overrideCodeCompletionHelper

If set to **false**, the CodeCompletionHelper class will not be overridden. The default value for this option is **true**.

overrideCodeFoldingManager

If set to **false**, the CodeFoldingManager class will not be overridden. The default value for this option is **true**.

overrideColorManager

If set to **false**, the ColorManager class will not be overridden. The default value for this option is **true**.

overrideCompletionProcessor

If set to **false**, the CompletionProcessor class will not be overridden. The default value for this option is **true**.

overrideCompletionProposal

If set to **false**, the CompletionProposal class will not be overridden. The default value for this option is **true**.

overrideCompound

If set to **false**, the Compound class will not be overridden. The default value for this option is **true**.

overrideContainment

If set to **false**, the Containment class will not be overridden. The default value for this option is **true**.

overrideContextDependentURIFragment

If set to **false**, the ContextDependentUriFragment class will not be overridden. The default value for this option is **true**.

overrideContextDependentURIFragmentFactory

If set to **false**, the ContextDependentUriFragmentFactory class will not be overridden. The default value for this option is **true**.

overrideCopiedEList

If set to **false**, the CopiedEList class will not be overridden. The default value for this option is **true**.

overrideCopiedEObjectInternalEList

If set to **false**, the CopiedEObjectInternalEList class will not be overridden. The default value for this option is **true**.

overrideDefaultHoverTextProvider

If set to **false**, the DefaultHoverTextProvider class will not be overridden. The default value for this option is **true**.

overrideDefaultLoadOptionsExtensionPointSchema

If set to **false**, the extension point schema for default load options is not overridden. The default value for this option is **true**.

overrideDefaultResolverDelegate

If set to **false**, the default resolver class will not be overridden. The default value for this option is **true**.

overrideDefaultTokenResolver

If set to **false**, the DefaultTokenResolver class will not be overridden. The default value for this option is **true**.

overrideDelegatingResolveResult

If set to **false**, the DelegatingResolveResult class will not be overridden. The default value for this option is **true**.

overrideDocBrowserInformationControlInput

If set to **false**, the DocBrowserInformationControlInput class will not be overridden. The default value for this option is **true**.

overrideDummyEObject

If set to **false**, the DummyEObject class will not be overridden. The default value for this option is **true**.

overrideDynamicTokenStyler

If set to **false**, the DynamicTokenStyler class will not be overridden. The default value for this option is **true**.

overrideEClassUtil

If set to **false**, the EClassUtil class will not be overridden. The default value for this option is **true**.

overrideEObjectSelection

If set to **false**, the EObjectSelection class will not be overridden. The default value for this option is **true**.

overrideEObjectUtil

If set to **false**, the EObjectUtil class will not be overridden. The default value for this option is **true**.

overrideEProblemSeverity

If set to **false**, the EProblemSeverity class will not be overridden. The default value for this option is **true**.

overrideEProblemType

If set to **false**, the EProblemType class will not be overridden. The default value for this option is **true**.

overrideEditor

If set to **false**, the Editor class will not be overridden. The default value for this option is **true**.

overrideEditorConfiguration

If set to **false**, the EditorConfiguration class will not be overridden. The default value for this option is **true**.

overrideElementMapping

If set to **false**, the ElementMapping class will not be overridden. The default value for this option is **true**.

overrideEnumerationTerminal

If set to **false**, the EnumerationTerminal class will not be overridden. The default value for this option is **true**.

overrideExpectedBooleanTerminal

If set to **false**, the ExpectedBooleanTerminal class will not be overridden. The default value for this option is **true**.

overrideExpectedCsString

If set to **false**, the ExpectedCsString class will not be overridden. The default value for this option is **true**.

overrideExpectedEnumerationTerminal

If set to **false**, the ExpectedEnumerationTerminal class will not be overridden. The default value for this option is **true**.

overrideExpectedStructuralFeature

If set to **false**, the ExpectedStructuralFeature class will not be overridden. The default value for this option is **true**.

overrideExpectedTerminal

If set to **false**, the `ExpectedTerminal` class will not be overridden. The default value for this option is **true**.

overrideFoldingInformationProvider

If set to **false**, the `FoldingInformationProvider` class will not be overridden. The default value for this option is **true**.

overrideFollowSetProvider

If set to **false**, the `FollowSetProvider` class will not be overridden. The default value for this option is **true**.

overrideFormattingElement

If set to **false**, the `FormattingElement` class will not be overridden. The default value for this option is **true**.

overrideFuzzyResolveResult

If set to **false**, the `FuzzyResolveResult` class will not be overridden. The default value for this option is **true**.

overrideGrammarInformationProvider

If set to **false**, the `GrammarInformationProvider` class will not be overridden. The default value for this option is **true**.

overrideHTMLPrinter

If set to **false**, the `HtmlPrinter` class will not be overridden. The default value for this option is **true**.

overrideHighlighting

If set to **false**, the `Highlighting` class will not be overridden. The default value for this option is **true**.

overrideHoverTextProvider

If set to **false**, the `HoverTextProvider` class will not be overridden. The default value for this option is **true**.

overrideHyperlink

If set to **false**, the `Hyperlink` class will not be overridden. The default value for this option is **true**.

overrideHyperlinkDetector

If set to **false**, the `HyperlinkDetector` class will not be overridden. The default value for this option is **true**.

overrideIAnnotationModelProvider

If set to **false**, the `IAnnotationModelProvider` class will not be overridden. The default value for this option is **true**.

overrideIBackgroundParsingListener

If set to **false**, the `IBackgroundParsingListener` class will not be overridden. The default value for this option is **true**.

overrideIBracketHandler

If set to **false**, the `IBracketHandler` class will not be overridden. The default value for this option is **true**.

overrideIBracketHandlerProvider

If set to **false**, the `IBracketHandlerProvider` class will not be overridden. The default value for this option is **true**.

overrideIBracketPair

If set to **false**, the `IBracketPair` class will not be overridden. The default value for this option is **true**.

overrideIBuilder

If set to **false**, the `IBuilder` class will not be overridden. The default value for this option is **true**.

overrideICommand

If set to **false**, the `ICommand` class will not be overridden. The default value for this option is **true**.

overrideIConfigurable

If set to **false**, the `IConfigurable` class will not be overridden. The default value for this option is **true**.

overrideIContextDependentURIFragment

If set to **false**, the `IContextDependentUriFragment` class will not be overridden. The default value for this option is **true**.

overrideIContextDependentURIFragmentFactory

If set to **false**, the `IContextDependentUriFragmentFactory` class will not be overridden. The default value for this option is **true**.

overrideIElementMapping

If set to **false**, the `IElementMapping` class will not be overridden. The default value for this option is **true**.

overrideIExpectedElement

If set to **false**, the `IExpectedElement` class will not be overridden. The default value for this option is **true**.

overrideIHoverTextProvider

If set to **false**, the `IHoverTextProvider` class will not be overridden. The default value for this option is **true**.

overrideIInputStreamProcessorProvider

If set to **false**, the `IInputStreamProcessorProvider` class will not be overridden. The default value for this option is **true**.

overrideILocationMap

If set to **false**, the `ILocationMap` class will not be overridden. The default value for this option is **true**.

overrideIMetaInformation

If set to **false**, the `IMetaInformation` class will not be overridden. The default value for this option is **true**.

overrideIOptionProvider

If set to **false**, the `IOptionProvider` class will not be overridden. The default value for this option is **true**.

overrideIOptions

If set to **false**, the `IOptions` class will not be overridden. The default value for this option is **true**.

overrideIParseResult

If set to **false**, the `IParseResult` class will not be overridden. The default value for this option is **true**.

overrideIProblem

If set to **false**, the `IProblem` class will not be overridden. The default value for this option is **true**.

overrideIQuickFix

If set to **false**, the `IQuickFix` class will not be overridden. The default value for this option is **true**.

overrideIReferenceCache

If set to **false**, the `IReferenceCache` class will not be overridden. The default value for this option is **true**.

overrideIReferenceMapping

If set to **false**, the `IReferenceMapping` class will not be overridden. The default value for this option is **true**.

overrideIReferenceResolveResult

If set to **false**, the `IReferenceResolveResult` class will not be overridden. The default value for this option is **true**.

overrideIReferenceResolver

If set to **false**, the `IReferenceResolver` class will not be overridden. The default value for this option is **true**.

overrideIReferenceResolverSwitch

If set to **false**, the `IReferenceResolverSwitch` class will not be overridden. The default value for this option is **true**.

overrideIResourcePostProcessor

If set to **false**, the `IResourcePostProcessor` class will not be overridden. The default value for this option is **true**.

overrideIResourcePostProcessorProvider

If set to **false**, the `IResourcePostProcessorProvider` class will not be overridden. The default value for this option is **true**.

overrideIResourceProvider

If set to **false**, the `IResourceProvider` class will not be overridden. The default value for this option is **true**.

overrideITextDiagnostic

If set to **false**, the `ITextDiagnostic` class will not be overridden. The default value for this option is **true**.

overrideITextParser

If set to **false**, the ITextParser class will not be overridden. The default value for this option is **true**.

overrideITextPrinter

If set to **false**, the ITextPrinter class will not be overridden. The default value for this option is **true**.

overrideITextResource

If set to **false**, the ITextResource class will not be overridden. The default value for this option is **true**.

overrideITextResourcePluginPart

If set to **false**, the ITextResourcePluginPart class will not be overridden. The default value for this option is **true**.

overrideITextScanner

If set to **false**, the ITextScanner class will not be overridden. The default value for this option is **true**.

overrideITextToken

If set to **false**, the ITextToken class will not be overridden. The default value for this option is **true**.

overrideITokenResolveResult

If set to **false**, the ITokenResolveResult class will not be overridden. The default value for this option is **true**.

overrideITokenResolver

If set to **false**, the ITokenResolver class will not be overridden. The default value for this option is **true**.

overrideITokenResolverFactory

If set to **false**, the ITokenResolverFactory class will not be overridden. The default value for this option is **true**.

overrideITokenStyle

If set to **false**, the ITokenStyle class will not be overridden. The default value for this option is **true**.

overrideIURIMapping

If set to **false**, the IUriMapping class will not be overridden. The default value for this option is **true**.

overrideImageProvider

If set to **false**, the ImageProvider class will not be overridden. The default value for this option is **true**.

overrideInputStreamProcessor

If set to **false**, the InputStreamProcessor class will not be overridden. The default value for this option is **true**.

overrideKeyword

If set to **false**, the Keyword class will not be overridden. The default value for this option is **true**.

overrideLaunchConfigurationDelegate

If set to **false**, the LaunchConfigurationDelegate class will not be overridden. The default value for this option is **true**.

overrideLaunchConfigurationMainTab

If set to **false**, the LaunchConfigurationMainTab class will not be overridden. The default value for this option is **true**.

overrideLaunchConfigurationTabGroup

If set to **false**, the LaunchConfigurationTabGroup class will not be overridden. The default value for this option is **true**.

overrideLaunchShortcut

If set to **false**, the LaunchShortcut class will not be overridden. The default value for this option is **true**.

overrideLayoutInformation

If set to **false**, the LayoutInformation class will not be overridden. The default value for this option is **true**.

overrideLayoutInformationAdapter

If set to **false**, the LayoutInformationAdapter class will not be overridden. The default value for this option is **true**.

overrideLineBreak

If set to **false**, the LineBreak class will not be overridden. The default value for this option is **true**.

overrideListUtil

If set to **false**, the ListUtil class will not be overridden. The default value for this option is **true**.

overrideLocationMap

If set to **false**, the LocationMap class will not be overridden. The default value for this option is **true**.

overrideManifest

If set to **false**, the manifest of the resource plug-in will not be overridden. The default value for this option is **true**.

overrideMapUtil

If set to **false**, the MapUtil class will not be overridden. The default value for this option is **true**.

overrideMarkerAnnotation

If set to **false**, the MarkerAnnotation class will not be overridden. The default value for this option is **true**.

overrideMarkerHelper

If set to **false**, the MarkerHelper class will not be overridden. The default value for this option is **true**.

overrideMarkerResolutionGenerator

If set to **false**, the MarkerResolutionGenerator class will not be overridden. The default value for this option is **true**.

overrideMetaInformation

If set to **false**, the MetaInformation class will not be overridden. The default value for this option is **true**.

overrideMinimalModelHelper

If set to **false**, the MinimalModelHelper class will not be overridden. The default value for this option is **true**.

overrideNature

If set to **false**, the Nature class will not be overridden. The default value for this option is **true**.

overrideNewFileContentProvider

If set to **false**, the NewFileContentProvider class will not be overridden. The default value for this option is **true**.

overrideNewFileWizard

If set to **false**, the new file wizard class will not be overridden. The default value for this option is **true**.

overrideNewFileWizardPage

If set to **false**, the NewFileWizardPage class will not be overridden. The default value for this option is **true**.

overrideOccurrence

If set to **false**, the Occurrence class will not be overridden. The default value for this option is **true**.

overrideOccurrencePreferencePage

If set to **false**, the OccurrencePreferencePage class will not be overridden. The default value for this option is **true**.

overrideOutlinePage

If set to **false**, the OutlinePage class will not be overridden. The default value for this option is **true**.

overrideOutlinePageTreeViewer

If set to **false**, the OutlinePageTreeViewer class will not be overridden. The default value for this option is **true**.

overridePair

If set to **false**, the Pair class will not be overridden. The default value for this option is **true**.

overrideParseResult

If set to **false**, the ParseResult class will not be overridden. The default value for this option is **true**.

overrideParser

If set to **false**, the Parser class will not be overridden. The default value for this option is **true**.

overrideParsingStrategy

If set to **false**, the ParsingStrategy class will not be overridden. The default value for this option is **true**.

overridePixelConverter

If set to **false**, the PixelConverter class will not be overridden. The default value for this option is **true**.

overridePlaceholder

If set to **false**, the Placeholder class will not be overridden. The default value for this option is **true**.

overridePluginActivator

If set to **false**, the PluginActivator class will not be overridden. The default value for this option is **true**.

overridePluginXML

If set to **true**, the plugin.xml file will be overridden. The default value for this option is **true**.

overridePositionCategory

If set to **false**, the PositionCategory class will not be overridden. The default value for this option is **true**.

overridePositionHelper

If set to **false**, the PositionHelper class will not be overridden. The default value for this option is **true**.

overridePreferenceConstants

If set to **false**, the PreferenceConstants class will not be overridden. The default value for this option is **true**.

overridePreferenceInitializer

If set to **false**, the PreferenceInitializer class will not be overridden. The default value for this option is **true**.

overridePreferencePage

If set to **false**, the PreferencePage class will not be overridden. The default value for this option is **true**.

overridePrinter

If set to **false**, the printer will not be overridden. The default value for this option is **true**.

overridePrinter2

If set to **false**, the Printer2 class will not be overridden. The default value for this option is **true**.

overrideProblemClass

If set to **false**, the problem class will not be overridden. The default value for this option is **true**.

overrideProjectFile

If set to **false**, the .project file of the resource plug-in will not be overridden. The default value for this option is **true**.

overridePropertySheetPage

If set to **false**, the PropertySheetPage class will not be overridden. The default value for this option is **true**.

overridePropertyTester

If set to **false**, the PropertyTester class will not be overridden. The default value for this option is **true**.

overrideProposalPostProcessor

If set to **false**, the ProposalPostProcessor class will not be overridden. The default value for this option is **true**.

overrideQuickAssistAssistant

If set to **false**, the QuickAssistAssistant class will not be overridden. The default value for this option is **true**.

overrideQuickAssistProcessor

If set to **false**, the QuickAssistProcessor class will not be overridden. The default value for this option is **true**.

overrideQuickFix

If set to **false**, the QuickFix class will not be overridden. The default value for this option is **true**.

overrideReferenceResolveResult

If set to **false**, the ReferenceResolveResult class will not be overridden. The default value for this option is **true**.

overrideReferenceResolverSwitch

If set to **false**, the reference resolver switch will not be overridden. The default value for this option is **true**.

overrideReferenceResolvers

If set to **true**, the reference resolver classes will be overridden. The default value for this option is **false**.

overrideResourceFactory

If set to **false**, the resource factory class will not be overridden. The default value for this option is **true**.

overrideResourceFactoryDelegator

If set to **false**, the ResourceFactoryDelegator class will not be overridden. The default value for this option is **true**.

overrideResourcePostProcessor

If set to **false**, the ResourcePostProcessor class will not be overridden. The default value for this option is **true**.

overrideResourceUtil

If set to **false**, the ResourceUtil class will not be overridden. The default value for this option is **true**.

overrideScanner

If set to **false**, the Scanner class will not be overridden. The default value for this option is **true**.

overrideSequence

If set to **false**, the Sequence class will not be overridden. The default value for this option is **true**.

overrideStreamUtil

If set to **false**, the StreamUtil class will not be overridden. The default value for this option is **true**.

overrideStringUtil

If set to **false**, the StringUtil class will not be overridden. The default value for this option is **true**.

overrideSyntaxColoringHelper

If set to **false**, the SyntaxColoringHelper class will not be overridden. The default value for this option is **true**.

overrideSyntaxColoringPreferencePage

If set to **false**, the SyntaxColoringPreferencePage class will not be overridden. The default value for this option is **true**.

overrideSyntaxCoverageInformationProvider

If set to **false**, the SyntaxCoverageInformationProvider class will not be overridden. The default value for this option is **true**.

overrideSyntaxElement

If set to **false**, the SyntaxElement class will not be overridden. The default value for this option is **true**.

overrideSyntaxElementDecorator

If set to **false**, the SyntaxElementDecorator class will not be overridden. The default value for this option is **true**.

overrideTerminal

If set to **false**, the Terminal class will not be overridden. The default value for this option is **true**.

overrideTerminateParsingException

If set to **false**, the TerminateParsingException class will not be overridden. The default value for this option is **true**.

overrideTextHover

If set to **false**, the TextHover class will not be overridden. The default value for this option is **true**.

overrideTextResource

If set to **false**, the text resource class will not be overridden. The default value for this option is **true**.

overrideTextResourceUtil

If set to **false**, the TextResourceUtil class will not be overridden. The default value for this option is **true**.

overrideTextToken

If set to **false**, the TextToken class will not be overridden. The default value for this option is **true**.

overrideTokenResolveResult

If set to **false**, the TokenResolveResult class will not be overridden. The default value for this option is **true**.

overrideTokenResolverFactory

If set to **false**, the token resolver factory class will not be overridden. The default value for this option is **true**.

overrideTokenResolvers

If set to **true**, the token resolver classes will be overridden. The default value for this option is **false**.

overrideTokenScanner

If set to **false**, the TokenScanner class will not be overridden. The default value for this option is **true**.

overrideTokenStyle

If set to **false**, the TokenStyle class will not be overridden. The default value for this option is **true**.

overrideTokenStyleInformationProvider

If set to **false**, the TokenStyleInformationProvider class will not be overridden. The default value for this option is **true**.

overrideUIBuildProperties

If set to **false**, the build.properties file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIDotClasspath

If set to **false**, the .classpath file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIDotProject

If set to **false**, the .project file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIManifest

If set to **false**, the manifest of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIMetaInformation

If set to **false**, the MetaInformation class of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIPluginActivator

If set to **false**, the plug-in activator class of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIPluginXML

If set to **false**, the plugin.xml file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideURIMapping

If set to **false**, the UriMapping class will not be overridden. The default value for this option is **true**.

overrideUnexpectedContentTypeException

If set to **false**, the UnexpectedContentTypeException class will not be overridden. The default value for this option is **true**.

overrideUnicodeConverter

If set to **false**, the UnicodeConverter class will not be overridden. The default value for this option is **true**.

overrideWhiteSpace

If set to **false**, the WhiteSpace class will not be overridden. The default value for this option is **true**.

parserGenerator

The name of the parser generator to use. The default value for this option is **antlr**, which is also the only valid value. This is a non-standard option, which might be removed in future releases of EMFText.

reloadGeneratorModel

If set to **true**, EMFText reloads the generator model before loading it. This is particular useful, when the meta model (i.e., the Ecore file) is changing a lot during language development. The default value for this option is **false**.

resolveProxyElementsAfterParsing

If set to **false**, the generated resource class will not resolve references after parsing. The default value for this option is **true**.

resourcePluginID

The ID of the generated resource plug-in. The resource plug-in is stored in a folder that is equal to this ID.

resourceUIPluginID

The ID of the generated resource UI plug-in. The resource UI plug-in is stored in a folder that is equal to this ID.

saveChangedResourcesOnly

If set to **true**, the generated EMF resource will save only resource when their content (text) has actually changed. The default value for this option is **false**.

srcFolder

The name of the folder where EMFText shall store the customizable classes of the resource plug-in in. All classes for which the **override** option is set to **false** will be stored in this folder.

srcGenFolder

The name of the folder where EMFText shall store the generated classes of the resource plug-in in. All classes for which the **override** option is set to **true** will be stored in this folder.

tokenspace

The (numerical) value of this option defines how many whitespace should be printed between tokens if no whitespace information is given in CS rules. This option should only be used with the classic printer. The default value of this option is **1** if the classic printer is used (see option **useClassicPrinter**) and **automatic** otherwise.

uiBasePackage

The package where to store all classes of the resource UI plug-in in. If this option is not set, the default value is determined by adding the suffix **resource.FILE_EXTENSION.ui** to the base package of the generator model.

uiSrcFolder

The name of the folder where EMFText shall store the customizable classes of the resource UI plug-in in. All classes for which the **override** option is set to **false** will be stored in this folder.

uiSrcGenFolder

The name of the folder EMFText shall store the generated classes of the resource UI plug-in in. All classes for which the **override** option is set to **true** will be stored in this folder.

useClassicPrinter

If set to **false**, the classic printer (i.e., the one used before EMFText 1.3.0) will be used. Otherwise the new printer implementation is used. In any case both printers are generated, but only one is used. The default value for this option is **false**.

usePredefinedTokens

If set to **false**, EMFText does not automatically provide predefined tokens (**TEXT**, **WHITESPACE**, **LINEBREAK**). The default value for this option is **true**.

A2 Types of Warnings

- **abstractSyntaxHasStartSymbols**
- **collectInTokenUsedInRule**
- **duplicateOptionWithSameValue**
- **duplicateTokenStyle**
- **explicitSyntaxChoice**
- **featureWithoutSyntax**
- **leftRecursiveRule**
- **licenceHeaderNotFound**
- **maxOccurenceMismatch**
- **minOccurenceMismatch**

- multipleFeatureUse
- noRuleForMetaClass
- nonContainmentOpposite
- nonStandardOption
- oppositeFeatureWithoutSyntax
- optionalKeyword
- referenceToAbstractClassWithoutConcreteSubtypesInAbstractSyntax
- styleReferenceToNonExistingToken
- tokenOverlapping
- tokenPriorizationUselessWhenTokenSortingEnabled
- unreachableRule
- unusedResolverClass
- unusedToken

A3 Syntax Dependent Artifacts

The following artifacts depend on the .cs specification. Overriding them does therefore require special care.

- ANTLR grammar
- AbstractInterpreter
- BracketInformationProvider
- BuilderAdapter
- FoldingInformationProvider
- GrammarInformationProvider
- MetaInformation
- Nature
- NewFileContentProvider
- Printer
- Printer2
- ReferenceResolverSwitch
- Resource
- ResourceUtil
- ScannerlessParser
- SyntaxCoverageInformationProvider
- TokenResolverFactory
- TokenStyleInformationProvider

Bibliography

- [Obj02] Object Management Group. Human Usable Textual Notation (HUTN) Specification. Final Adopted Specification ptc/02-12-01, 2002.
- [SBPM08] Dave Steinberg, Frank Budinsky, Marcelo Paternostro, and Ed Merks. *Eclipse Modeling Framework, 2nd Edition*. Pearson Education, 2008.