

emftext

USER GUIDE

August 17, 2010

Contents

1	Overview	1
1.1	EMFText features	1
1.1.1	Generation features	1
1.1.2	Specification features	1
1.1.3	Editor features	2
1.1.4	Other features	2
2	Development Process	3
2.1	Creating a Metamodel	3
2.2	Specifying Concrete Syntax	3
2.3	Generating Resource Plug-ins	4
2.3.1	Generating Resource Plug-ins in Eclipse	4
2.3.2	Generating Resource Plug-ins with ANT	4
2.4	Customizing the DSL Tooling	5
3	Concrete Syntax Specification Language (CS)	7
3.1	Configuration Block	7
3.1.1	Required General Information	7
3.1.2	Importing other Metamodels and Syntax Specifications	8
3.1.3	Code Generation Options	9
3.2	Tokens	9
3.2.1	Defining Custom Tokens	9
3.2.2	Composed Tokens	10
3.2.3	Token Priorities	10
3.3	Token Styles	10
3.4	Syntax Rules	11
3.4.1	Simple Syntax	11
3.4.2	Syntax for EAttributes	11
3.4.3	Syntax for EReferences	12
3.4.4	Syntax for Printing Instructions	13
3.4.5	Syntax for Expressions	14
3.5	Suppressing warnings	15
4	DSL Customization	17
4.1	Customization Techniques	17
4.1.1	Overriding Generated Classes	17
4.1.2	Using Generated Extension Points	17
4.2	Concrete Customizations	17
4.2.1	Customizing Token Resolving	17

4.2.2	Customizing Reference Resolving	19
4.2.3	Implementing Post Processors	20
4.2.4	Implementing Quick Fixes	20
4.2.5	Implementing Builders	20
4.2.6	Implementing Interpreters	22
4.2.7	Customizing Text Hovers	22
4.2.8	Customizing Code Completion Proposals	23
A	Code Generation Options	29
B	Types of Warnings	47
	Bibliography	49

1 Overview

EMFText is a tool for defining textual syntax for Ecore-based metamodels. It enables developers to define their own textual languages—be it domain specific languages (e.g., a language for describing forms) or general purpose languages (e.g., Java)—and generates accompanying tool support for these languages. It provides a domain specific language (DSL) for syntax specification from which it generates a full-fledged Eclipse editor and components to load and store model instances.

1.1 EMFText features

To give a quick overview, some of the most compelling features of EMFText are outlined in the following.

1.1.1 Generation features

Generation of independent code

The code that is generated by EMFText does not contain dependencies to EMFText and is fully customizable. This implies that generated language tooling is deployable in environments where EMFText is not available and that future compatibility issues are completely avoided.

Automatic generation of default syntax

With EMFText, an initial syntax for the textual DSL can be generated in one step for any Ecore-based metamodel. This syntax conforms to the HUTN standard. From this initial version of generated specification the syntax can be further tailored towards specific needs (cf. Sect. 2.2).

1.1.2 Specification features

Simple and precise syntax specification

EMFText comes with a simple but rich syntax specification language—the *Concrete Syntax Specification Language (CS)*. It is based on EBNF and follows the concept of *convention over configuration*. This allows for very compact and intuitive syntax specifications, but still supports tweaking specifics where needed (cf. Chap. 3).

Modular specification

EMFText provides an import mechanism that not only supports specification of a single text syntax for multiple related Ecore models, but also allows for modularization and extension of CS specifications (cf. Sect. 3.1.2).

Default reference resolving mechanisms

A default name resolution mechanism for models with globally unique names is available out of the box for any syntax. More complex resolution mechanisms can be realised by implementing generated resolving methods through which also inter-model references can be established (cf. Sect. 4.2.2).

Comprehensive syntax analysis

A number of analyses of CS specifications inform the developer about potential errors in the syntax—like missing syntax for certain metaclasses (cf. Appx. B).

1.1.3 Editor features

EMFText editors provide many advanced features like code completion, customizable syntax and occurrence highlighting, advanced bracket handling, hyperlinks and text hovers, an outline view and instant error reporting.

1.1.4 Other features

ANT support

Dedicated ANT task are provided to all the generation of text syntax plug-ins in build scripts (cf. Sect. 2.3.2).

Generation of builder and interpreter stubs

EMFText generates a builder stub that can be used to process model instances on changes and to automatically produce derived resources when needed (cf. Sect. 4.2.5). Similarly, interpreters are used to execute model instances (cf. Sect. 4.2.6).

2 Development Process

Creating parsers, printers and editors with EMFText is easy! It involves some necessary steps which are:

- creating a metamodel,
- specifying concrete syntax,
- generating resource plug-ins,
- customizing the DSL tooling.

Each of this steps will be explained in the subsequent sections.

2.1 Creating a Metamodel

The starting point usually is the *Ecore model*. It serves as abstract syntax and as a skeleton for concrete syntax. The model can be a graph or tree definition. Although Ecore models are specified as XML files, it is recommended to use the Ecore model editor or a graphical editor (e.g., the Ecore Tools). Additionally, a unique namespace (property NS URI in the .ecore file) for the models as well as a package name needs to be specified. To enable EMFText to use models at runtime, a model plug-in must be generated. For this, EMF provides a *generation metamodel* (GenModel) allowing to enrich Ecore models with specific information for code generation. The EMF Model wizard facilitates the creation of GenModels.

The next step is to define the base package name which will be the common prefix for all subsequently generated Java packages. After finishing configuration, the *EMF model plug-in* is ready to be generated. EMFText will later use these classes to construct a model instance.

2.2 Specifying Concrete Syntax

After defining a metamodel, we can start specifying our *concrete syntax*. As a starting point, EMFText provides a syntax generator that can automatically create a concrete-syntax specification using HUTN (Human-Useable Textual Notation) [Obj02] from the metamodel. To manually specify the concrete syntax, a textual specification has to be written, which has the ending `cs` (from concrete syntax).

It consists of four sections: In the first part, a unique name refers to the syntax as a specific resource type. Furthermore, the metamodel, whose textual syntax shall be defined, has to be referenced by its unique namespace URI and a start symbol must be selected from the model elements. In the second part, productions from other concrete syntax specifications can be imported. This is especially useful if the metamodel is compositionally structured, e.g. reuses large parts from other models which have an already specified concrete syntax. The third part allows for specifying token types as it is usual for parser generators, but in contrast, EMFText also allows to leave them out: If no token definitions are given, default rules are used. Another

specialty for token definitions are optional pre- and suffixes which are transparently removed (after parsing) and added (before printing) by the generated token resolvers. And last but not least, EBNF-like productions have to be defined for each non-abstract model element reachable from the start symbol. They have to be defined with respect to the attributes and references of the model element and thus do not contain nonterminals in the classic sense.

2.3 Generating Resource Plug-ins

2.3.1 Generating Resource Plug-ins in Eclipse

The context menu on concrete syntax specification files offers an item to generate the actual *resource plug-in* which contains the parser, printer and the editor for the language. In an optional last step, the generated token resolvers and the printer can be tailored to specific needs.

2.3.2 Generating Resource Plug-ins with ANT

EMFText includes its own tasks for Apache ANT. These tasks are automatically registered to the Eclipse platform via extension point and are named according to the following scheme: *emftext.taskName*. To execute the tasks in your build script, you will have to activate the *Run in the same JRE as the workspace* option in the *JRE* tab. EMFText provides the following ANT tasks:

GenerateTextResource will cause EMFText to generate the resource plugin. The following listing shows how it should be used including the task's obligatory parameters.

```
<emftext.GenerateTextResource
    syntax="pathToCSSpec"
    rootFolder="path/to/project/root"
    syntaxProjectName="nameOfTheGeneratedProject"
/>
```

Further parameters are *generateANTLRPlugin="[true|false]"*, which specifies if an additional plugin containing the required ANTLR dependencies should be generated, and *preprocessor="[qualified class name]"* referring to an implementation of the *org.emftext.sdk.ant.SyntaxProcessor* interface.

RegisterEcoreResourceFactory allows to register an ecore model's resource factory for a certain type. The following listing shows how the task should be used.

```
<emftext.RegisterEcoreResourceFactory
    className="qualified.factory.class.name"
    type="qualified.ecore.type.name"
/>
```


RegisterURIMapping adds an URI mapping to the EMF URI map. The task's usage is exemplified by the following listing.

```
<emftext.RegisterURIMapping
    from="sourceURI"
    to="targetURI"
/>
```

RemoveURIMapping removes an URI mapping from the EMF's URI map. The task's usage is shown by the following listing.

```
<emftext.RemoveURIMapping
    from="sourceURI"
/>
```

2.4 Customizing the DSL Tooling

TODO Add content

3 Concrete Syntax Specification Language (CS)

An EMFText syntax specification must be contained in a file with the extension `.cs` and consists of four main blocks:

1. A mandatory configuration block, which specifies the name of the syntax (i.e., the file extension), the generator model where to find the metaclasses, and the root metaclass (start symbol). Optionally, other syntaxes and metamodels can be imported and code generation options can be specified.
2. An (optional) `TOKENS` section. Here, token types like identifiers, numbers etc. for the lexical analyser can be specified.
3. An (optional) `TOKENSTYLES` section. Here, the default style (i.e., color and font style) for tokens and keywords can be specified.
4. A `RULES` section, which defines the syntax for concrete metaclasses.

In the following sections, these four main blocks will be explained in more detail.

3.1 Configuration Block

3.1.1 Required General Information

The first required piece of information is the file extension that shall be used for the files, which will contain your models:

```
SYNTAXDEF yourFileExtension
```

Note: The file extension must not contain the dot character.

Second, EMFText needs to know the EMF generator model (`.genmodel`) that contains the metaclasses for which the syntax is specified. EMFText does use the generator model rather than the Ecore model, because it requires information about the code generated from the Ecore model (e.g., the fully qualified names of the classes generated by the EMF). The `genmodel` can be referred by its namespace URI:

```
FOR <yourGenModelNamespaceURI>
```

To find the generator model with the given namespace URI, EMFText tries to load it from the generator model registry. If it is not registered, EMFText looks for a `.genmodel` file with the same name as the syntax definition. For example, if the syntax specification is contained in a file `yourdsl.cs`, EMFText looks for a file called `yourdsl.genmodel` in the same folder.

If your `genmodel` is not contained in the same folder or is called differently from the syntax file name or if you do not want to use the one in the registry, the optional parameter `yourGenModelLocation` can be used:

```
FOR <yourGenModelNamespaceURI> <yourGenModelLocation>
```

The value of **yourGenmodelLocation** must be an URI pointing to the generator model. The URI can be absolute or relative to the syntax specification folder.

Third, the root element (start symbol) must be given. The root element must be a metaclass from the metamodel:

```
START YourRootMetaClassName
```

A CS specification can also have multiple root elements, which must be separated by a comma:

```
START RootMetaClass1, RootMetaClass2, RootMetaClass3
```

Typical candidates for root elements are metaclasses that do not have incoming containment edges.

Altogether a typical header for a **.cs** file looks something like:

```
SYNTAXDEF yourFileExtension  
FOR <yourGenModelNamespaceURI> <yourGenmodelLocation>  
START YourRootMetaClassName
```

3.1.2 Importing other Metamodels and Syntax Specifications

Sometimes it is required to import additional metamodels, e.g., if they are only referenced in the current one and a syntax for some or all of its concepts needs to be specified or reused. Metamodels and syntax specifications can be imported in a dedicated import section, which must follow after the start symbols:

```
IMPORTS {  
    // imports go here  
}
```

The list of imports must contain at least one entry. If no imports are needed the whole section must be left out. An import entry consists of a prefix, which can be used to refer to imported elements in rules, the metamodel namespace URI and optionally the name of a concrete syntax defined for that metamodel. If a syntax is imported, all its rules are reused and need not to be specified in the current **cs** specification. Importing syntax rules is optional. One can also just import the metamodel contained in the generator model.

```
prefix : <genModelURI> <locationOfTheGenmodel>  
    // next line is option (except the semicolon)  
WITH SYNTAX syntaxURI <locationOfTheSyntax>;
```

The two locations are again optional. For resolving the generator model the same rules as for the “main” generator model (declared after the **FOR** keyword) apply. For locating the syntax, EMFText looks up the registry of registered syntax specifications. If no registered syntax is found, **locationOfTheSyntax** is used to find the **.cs** file to import. Again, **locationOfTheSyntax** must be a relative or absolute URI.

3.1.3 Code Generation Options

EMFText's code generation can be configured using various options. These are specified in a dedicated optional `OPTIONS` section:

```
OPTIONS {
    // options go here in the following form:
    optionName = "optionValue";
}
```

The list of valid options and their documentation can be found in Appendix A.

3.2 Tokens

EMFText allows to specify custom tokens. Each token type has a name and is defined by a regular expression. This expression is used to convert characters from the DSL files to form groups (i.e., tokens). Tokens are the smallest unit processed by the generated parser. By default, EMFText implicitly uses a set of predefined standard tokens, namingly:

- `TEXT` : `('A'..'Z'|'a'..'z'|'0'..'9'|'_'|'-')+`,
- `LINEBREAK` : `('r\n'|'r'|'n')`,
- `WHITESPACE` : `(' '|'\t'|'\f')`.

The predefined tokens can be excluded from the generated parser using the `usePredefinedTokens` option:

```
OPTIONS {
    usePredefinedTokens = "false";
}
```

3.2.1 Defining Custom Tokens

To define custom tokens, a `TOKENS` section must be added to the `.cs` file. This section has the following form:

```
TOKENS {
    // token definitions go here in the form:
    DEFINE YOUR_TOKEN_NAME $yourRegularExpression$;
}
```

Every token name has to start with a capital letter. A regular expression must conform to the ANTLRv3 syntax for regular expressions (without semantic annotations). However, don't worry: EMFText will complain if there is a problem with your regular expressions, such as typos or overlaps of regular expressions.

3.2.2 Composed Tokens

Sometimes, regular expressions are quite repetitive and one wants to reuse simple expressions to compose them to more complex ones. To do so, one can refer to other token definition by their name. For example:

```
TOKENS {  
    // simple token  
    DEFINE CHAR $('a'..'z'|'A'..'Z')$;  
    // simple token  
    DEFINE DIGIT $('0'..'9')$;  
    // composed token  
    DEFINE IDENTIFIER CHAR + $($ + CHAR + $|$ + DIGIT + $)*$;  
}
```

If token definitions are merely used as “helper” tokens, they can be tagged as **FRAGMENT**. This means the helper token itself is used in other token definitions, but not anywhere else in the syntax specification:

```
TOKENS {  
    // simple token  
    DEFINE CHAR $('a'..'z'|'A'..'Z')$;  
    // helper token - not used on its own  
    DEFINE FRAGMENT DIGIT $('0'..'9')$;  
    // composed token  
    DEFINE IDENTIFIER CHAR + $($ + CHAR + $|$ + DIGIT + $)*$;  
}
```

3.2.3 Token Priorities

EMFText does automatically sort token definitions. However, sometimes token definitions might be ambiguous (i.e., the regular expressions defined for two different token are not disjoint). In such cases EMFText will always prefer the token defined first in the specification. By default, the predefined tokens (**TEXT**, **WHITESPACE** and **LINEBREAK**) have lower precedence than any explicitly defined token. However, they can be given a higher priority by prioritizing them over other tokens using the following directive:

```
TOKENS {  
    PRIORITIZE NameOfPredefinedToken;  
    DEFINE SOME_CUSTOM_TOKEN $someCustomRegularExpression$;  
}
```

3.3 Token Styles

To define the default syntax highlighting for a language, a special section **TOKENSTYLES** can be used. For each token or keyword the color and style (**BOLD**, **ITALIC**, **STRIKETHROUGH**, **UNDERLINE**) can be specified as follows:

```
TOKENSTYLES {
  // show YOUR_TOKEN in black
  "YOUR_TOKEN" COLOR #000000;
  // show keyword 'public' in red and bold font face
  "public" COLOR #FF0000, BOLD;
}
```

The default highlighting can still be customized at runtime by using the generated preference pages.

3.4 Syntax Rules

For each concrete metaclass you can define a syntax rule. The rule specifies what the text that represents instances of the class looks like. Rule have two sides—a left and right-hand side. The left side denotes the name of the meta class, while the right-hand side defines the syntax elements.

3.4.1 Simple Syntax

The most basic form of a syntax rule is:

```
YourMetaClass ::= "someKeyword" ;
```

This rule states that whenever the text **someKeyword** is found, an instance of **YourMetaClass** must be created. Besides text elements that are expected “as is”, parts of the syntax can be optional or repeating. For example the syntax rule:

```
YourMetaClassWithOptionalSyntax ::= ("#")? "someKeyword" ;
```

states that instances of **YourMetaClassWithOptionalSyntax** can be represented both by **#someKeyword** and **someKeyword**. Similar behavior can be defined using a star instead of a question mark. The syntax enclosed in the parenthesis can then be repeated. For example,

```
YourMetaClassWithRepeatingSyntax ::= ("#")* "someKeyword" ;
```

allows to represent instances of metaclass **YourMetaClassWithRepeatingSyntax** by writing **someKeyword**, **#someKeyword**, **##someKeyword**, or any other number of hash symbols followed by **someKeyword**. One can also use a plus sign instead of a star or question mark. In this case, the syntax enclosed in the parenthesis can be repeated, but must appear at least once.

3.4.2 Syntax for EAttributes

If metaclasses have attributes, we can also specify syntax for their values. To do so, simply add brackets after the name of the attribute:

```
YourMetaClassWithAttribute ::= yourAttribute[] ;
```

Optionally, one can specify the name of a token inside the brackets. For example:

```
YourMetaClassWithAttribute ::= yourAttribute[MY_TOKEN] ;
```

If the token name is omitted, as in the first example, EMFText uses the predefined token `TEXT`, which includes alphanumeric characters. The found text is automatically converted to the type of the attribute. If this conversion is not successful, an error is raised when opening a file containing wrong syntax. For details on customizing the conversion of tokens, see Sect. 4.2.1.

Another possibility to specify the token definition that shall be used to match the text for the attribute value is to do it inline. For example

```
YourMetaClassWithAttribute ::= yourAttribute['(',')'] ;
```

can be used to express that the text for the value of the attribute `yourAttribute` must be enclosed in parenthesis. Between the parenthesis arbitrary characters (except the closing parenthesis) are allowed. Other characters can be used as prefix and suffix here as well.

By default, the suffix character (in the example above this was the closing parenthesis) can not be part of the text for the attribute value. To allow this, an escape character needs to be supplied:

```
YourMetaClassWithAttribute ::= yourAttribute['(',')','\'] ;
```

Here the backslash can be used inside the parenthesis to escape the closing parenthesis. It must then also be used to escape itself. That is, one must write two backslash characters to represent one.

To give an example on how escaping works, consider the following text: `(text(more\))`. After parsing, this yields the attribute value `text(more)`. The character sequence `\` is replaced by `)`. Note that the opening parenthesis does not need to be escaped.

3.4.3 Syntax for EReferences

Metaclasses can have references and consequently there is a way to specify syntax for these. EMF distinguishes between *containment* and *non-containment* references. In an EMF model, the elements that are referenced with the former type are contained in the parent elements. EMFText thus expects the text for the contained elements (children) to be also contained in the parent's text.

The latter (non-containment) references are referenced only and are contained in another (parent) element. Thus, EMFText does not expect text that represents the referenced element, but a symbolic identifier that refers to the element. This is very similar to the declaration and use of variables in Java. The declaration of a variable consists of the complete text that is required to describe a variable (e.g., its type). In contrast, when the variable is used at some other place it is simply referred to by its name. Non-containment references are similar to uses of variables.

Syntax for Containment References

A basic example for defining a rule for a meta class that has a containment reference looks like this:

```
YourContainerMetaClass ::= "CONTAINER" yourContainmentReference ;
```


It allows to represent instances of **YourContainerMetaClass** using the keyword **CONTAINER** followed by one instance of the type that **yourContainmentReference** points to. If multiple children need to be contained the following rule can be used:

```
YourContainerMetaClass ::= "CONTAINER" yourContainmentReference* ;
```

In addition, each containment reference can be restricted to allow only certain types, for example:

```
YourContainerMetaClass ::= "CONTAINER"  
yourContainmentReference : SubClass ;
```

does allow only instances of **SubClass** after the keyword **CONTAINER** even though the reference **yourContainmentReference** may have a more general type. One can also add multiple subclass restrictions, which must then be separated by a comma:

```
YourContainerMetaClass ::= "CONTAINER"  
yourContainmentReference : SubClassA, SubClassB ;
```

Syntax for Non-Containment References

A basic example for defining a rule for a metaclass that has a non-containment reference looks like this:

```
YourPointerMetaClass ::= "POINTER" yourNonContainmentReference[] ;
```

The rule is very similar to the one for containment references, but uses the additional brackets after the name of the reference. Within the brackets the token that the symbolic name must match can be defined. In the case above, the default token **TEXT** is used. Therefore, the syntax for an example instance of class **YourPointerMetaClass** can be **POINTER a**.

Since **a** is just a symbolic name that must be resolved to an actual model element, EMF-Text generates a Java class that resolves **a** to a target model element. This class be customized to specify how symbolic names are resolved to model elements. The default implementation of the resolver looks for all model elements that have the correct type (the type of **yourNonContainmentReference**) and that have a name or id attribute that matches the symbolic name. For details on how to customize the resolving of references, see Sect. 4.2.2.

3.4.4 Syntax for Printing Instructions

By default, EMFText can print all kinds of models. It does also preserve the layout of the textual representation when models are parsed and printed later on. However, to print models that have been created in memory, additional information can be passed to EMFText to customize the print result. This (optional) information includes the number of whitespaces and line breaks to be inserted between keywords, attribute values, references and contained elements. If you do not want to print models to text, printing instructions are not needed in your **.cs** file.

Syntax for Printing Whitespace

To explicitly print whitespace characters, the `#` operator can be used on the right side of syntax rules:

```
YourMetaclass ::= "keyword" #2 attribute[];
```

It is followed by a number that determines the number of whitespaces to be printed. In the example above, two whitespace characters are printed between the keyword and the attribute value.

Syntax for Printing Line Breaks

To explicitly print line breaks, the `!` operator can be used on the right side of syntax rules:

```
YourMetaclass ::= "keyword" !0 attribute[];
```

It is followed by a number that determines the number of tab characters that shall be printed after the line break. In the example above, a line break is printed after **keyword**. The number of tabs refers to the current model element (i.e., `EObject`), which is printed.

3.4.5 Syntax for Expressions

When defining syntax for an expression language (e.g., arithmetic expressions) EMFText's standard mechanisms for specifying syntax can lead to structures that can not be optimally handled by an interpreter or evaluator. Furthermore, the underlying parser generator technology used by EMFText causes problems if left recursive rules are required to build an optimal expression tree, which is the case for all expression languages with left-associative binary operators (e.g., `-`). Therefore, EMFText provides a special feature called operator precedence annotations (`@Operator`). This annotation can be added to all rules, which refer to expression metaclasses with a common superclass. For example, the rule:

```
@Operator(type="binary_left_associative", weight="1", superclass="Expression")
Additive ::= left "+" right;
```

defines syntax for a metaclass **Additive**. The references **left** and **right** must be containments and are of type **Expression**, which is the abstract supertype for all metaclasses of the expression metamodel.

The **type** attribute specifies the kind of expression at hand, which can be binary (either **left_associative** or **right_associative**), **unary_prefix**, **unary_postfix** or **primitive**.

The **weight** attribute specifies the priority of one expression type over another. For example, if a second rule:

```
@Operator(type="binary_left_associative", weight="2", superclass="Expression")
Multiplicative ::= left "*" right;
```

is present, EMFText will create an expression tree, where **Multiplicative** nodes are created last (i.e., multiplicative expressions take precedence over additive expressions).

Unary expressions can be defined as follows:

```
@Operator(type="unary_prefix", weight="4", superclass="Expression")
Negation ::= "-" body;
```

There is also the option to define `unary_postfix` rules.

Primitive expressions can be defined as follows:

```
@Operator(type="primitive", weight="5", superclass="Expression")
IntegerLiteralExp ::= intValue[INTEGER_LITERAL];
```

They should be used for literals (e.g., numbers, constants or variables).

For examples how to use `@Operator` annotations see the SimpleMath language in the EMF-Text Syntax Zoo¹ and the ThreeValuedLogic DSL². These do also come with an interpreter which shows how expression trees can be evaluated.

3.5 Suppressing warnings

To suppress warnings issued by EMFText in `.cs` files one can use the `@SuppressWarnings` annotation. This annotation can be added to rules, token definitions or complete syntax definitions. One can either suppress all warnings or just specific types. To suppress all warning for a syntax use the following syntax:

```
@SuppressWarnings
YourMetaClass ::= "someKeyword";
```

A list of all warning types can be found in Appendix ???. For example, to suppress warnings about features without syntax, you may use:

```
@SuppressWarnings(featureWithoutSyntax)
YourMetaClassWithAttribute ::= "someKeyword";
```

¹<http://www.emftext.org/language/simplemath>

²<http://www.emftext.org/language/threevaluedlogic>

4 DSL Customization

4.1 Customization Techniques

4.1.1 Overriding Generated Classes

4.1.2 Using Generated Extension Points

4.2 Concrete Customizations

4.2.1 Customizing Token Resolving

To create models from their textual representation, it is necessary to convert the plain text found in Domain-specific Language (DSL) documents to attribute values (i.e., data types). For example, if the string "123" is found in a text file and shall be used as value for an attribute which has type `EInt`, the string needs to be converted to an `int`. Basic conversions, such as the one just mentioned, are handled by the generated class `XYZDefaultTokenResolver` (assuming the file extension of your DSL is `xyz`). However, if you want to use custom data types in your metamodels, or you need to customize the default conversion, there is two ways to change to conversion of text to data types.

Customizing TokenResolver Classes

The first option to customize the conversion of text, is to change the generated token resolver classes. EMFText generates one of these classes for each token that is defined in the `.cs` file. All classes end up in a package called `analysis` in the `src` folder of the generated resource plug-in.

Each token resolver class has two methods—`resolve()` and `deResolve()`. The first one is used to convert text to data types. The second one is used to perform the other way around. Consequently, `resolve()` is used when models are parsed, while `deResolve()` is used to print models to text.

The default implementation for both methods delegates calls to a default token resolver. However, this call can be replaced by custom code implementing different behavior. The code in the `resolve()` method must convert the text (given by the parameter `lexem`) to an object of the data type. This object must be set using `result.setResolvedToken()`. The `deResolve()` must implement the opposite behavior by returning a string representation of the object.

In the following a custom token resolver class is shown, which converts `TEXT` tokens to `java.util.Date` objects:

```
import java.text.ParseException;
import java.text.SimpleDateFormat;
import java.util.Date;
```

```
import java.util.Map;

import org.eclipse.emf.ecore.EObject;
import org.eclipse.emf.ecore.EStructuralFeature;
import org.emftext.language.xyz.resource.xyz.IXyzTokenResolveResult;
import org.emftext.language.xyz.resource.xyz.IXyzTokenResolver;

public class XyzTEXTTokenResolver implements IXyzTokenResolver {

    private SimpleDateFormat format = new SimpleDateFormat("dd.MM.yyyy");

    public String deResolve(Object value, EStructuralFeature feature,
        EObject container) {
        return format.format(value);
    }

    public void resolve(String lexem, EStructuralFeature feature,
        IXyzTokenResolveResult result) {
        try {
            Date date = format.parse(lexem);
            result.setResolvedToken(date);
        } catch (ParseException e) {
            result.setErrorMessage(lexem + " is not a valid date.");
        }
    }

    public void setOptions(Map<?,?> options) {
        // can be left empty
    }
}
```

The difference between this kind of customization and the one below, is that the implemented conversion is local w.r.t. the textual syntax of the DSL. If you have multiple syntax definition for your DSL, each can use completely different algorithms to convert data types.

Customizing the EMF Data Type Handling

Alternatively, you can customize the data type handling that is built into Eclipse Modeling Framework (EMF) [SBPM08]. To do so, you need to define a custom data type in the metamodel (e.g., `JavaDate`). Then, the instance type name must be set to the actual Java class, which shall be used to represent instances of the data type (e.g., `java.util.Date`). When running the EMF code generation, the `FactoryImpl` class will contain two methods—`createJavaDateFromString()` and `convertJavaDateToString()`. These need to be customized similar to the token resolver class before.

The following code is a snippet from the `XYZFactoryImpl` class and shows how to implement the same behavior as above using EMF's own data type handling facilities.

```
private SimpleDateFormat format = new SimpleDateFormat("yyyy-MM-dd");

/**
 * <!-- begin-user-doc -->
 * <!-- end-user-doc -->
 * @generated NOT
 */
public Date createJavaDateFromString(EDatatype eDataType,
    String initialValue) {
    try {
        return format.parse(initialValue);
    } catch (ParseException e) {
        // ignore
    }
    return (Date)super.createFromString(eDataType, initialValue);
}

/**
 * <!-- begin-user-doc -->
 * <!-- end-user-doc -->
 * @generated NOT
 */
public String convertJavaDateToString(EDatatype eDataType,
    Object instanceValue) {
    return format.format(instanceValue);
}
```

4.2.2 Customizing Reference Resolving

If metamodels expose non-containment references (i.e., `EReferences` where the `containment` attribute is set to `false`), EMFText needs to resolve these references. This basically means that symbolic identifiers, which are used to reference other `EObjects` must be replaced by actual references to the respective objects.

Thus, EMFText generates one reference resolver class for each non-containment reference that is found in the metamodel of your DSL and that is actually used in the concrete syntax definition. All reference resolver classes end up in a package called `analysis` in the `src` folder of the generated resource plug-in.

The default implementation delegates calls to the `DefaultResolverDelegate` class. This class uses the following strategy to find objects that are referenced by identifiers:

1. the resource is searched for objects that have the correct type (i.e., the type of the non-containment reference)

2. if the objects having the correct type have an `ID` attribute, or a `name` attribute, or a single attribute of type `EString`, the value of this attribute is compared to the symbolic identifier. If the identifier matches the value of the attribute, the object is considered to be referenced.
3. if no matching object is found and the symbolic identifier is a valid URI, `EMFText` tries to load the resource at the URI. If the resource contains a root object with the correct type, this object is assumed to be referenced.

In cases, where this default resolving strategy is not sufficient, you can customize the resolver classes by changing the bodies of the methods `resolve()` and `deResolve()`. These methods are similar to the ones generated for the token resolver classes (see Sect. 4.2.1). The first one is used to find the object referenced by an identifier. The second one does the opposite—it creates a symbolic identifier for a referenced object. Again, the former is used after parsing. The latter is called when printing models.

The `resolve()` method must call `result.addMapping(identifier, object)` to set the reference object, if one is found. The `deResolve()` method can simply return the textual representation of the referenced object as string.

To enable code completion for references, the `resolve()` must be extended to take care of the `resolveFuzzy` parameter. If this parameter is `true`, the resolver class is used for code completion and must add all referencable object to the result. Thus, instead of checking, whether `identifier` actually references an object, `resolve()` can simply add all objects that have the correct type to the result by calling `result.addMapping()`. However, in this case, the first argument, which is passed to `addMapping()` should not be `identifier`, but rather the string representation of the object.

4.2.3 Implementing Post Processors

4.2.4 Implementing Quick Fixes

4.2.5 Implementing Builders

To implement a custom builder for your DSL, you can basically set the code generation option `overrideBuilder` to `false`:

```
OPTIONS {  
    overrideBuilder = "false";  
}
```

After regenerating the resource plug-ins (see Sect. 2.3), you will find a new class `XyzBuilder` in the `src` folder of the generated resource plug-in (assuming the file extension of your DSL is `xyz`). If you face compilation errors, make sure to delete the `XyzBuilder` class from the `src-gen` folder.

The generated builder class contains two methods—`isBuildingNeeded()` and `build()`. The first one is called to let the builder decide, which resources need to be included in the build process. The default implementation returns `false` to avoid unnecessary loading of resources. To include all textual resources that contain models of your DSL, change the method to return `true`.

The second method is called whenever the content of a resource changes. You can implement arbitrary behavior here. Usually, builders create some kind of derived artifact, for example a transformed or compiled version of the DSL model. Since `build()` retrieves the resource as method parameter, you can easily access the contents of the resource. To save the derived artifact it is good practice to use the URI of the original resource to derive a new URI. This can for example be done by removing segments and adding new ones.

The following listing shows a simple builder, which copies the contents of the resource to a new resource without making any changes.

```
import java.io.IOException;
import java.util.Collection;

import org.eclipse.core.runtime.IProgressMonitor;
import org.eclipse.core.runtime.IStatus;
import org.eclipse.core.runtime.Status;
import org.eclipse.emf.common.util.EList;
import org.eclipse.emf.common.util.URI;
import org.eclipse.emf.ecore.EObject;
import org.eclipse.emf.ecore.resource.Resource;
import org.eclipse.emf.ecore.util.EcoreUtil;
import org.eclipse.xtext.language.xyz.resource.xyz.IXyzBuilder;

public class XyzBuilder implements IXyzBuilder {

    public boolean isBuildingNeeded(URI uri) {
        return true;
    }

    public IStatus build(XyzResource resource, IProgressMonitor monitor) {
        // get contents and create copy
        EList<EObject> contents = resource.getContents();
        Collection<EObject> contentsCopy = EcoreUtil.copyAll(contents);

        // create new resource with different name
        URI newUri = URI.createURI("copy.xyz").resolve(resource.getURI());
        Resource newResource = resource.getResourceSet().createResource(newUri);
        // add copy of original content to new resource
        newResource.getContents().addAll(contentsCopy);
        // save new resource
        try {
            newResource.save(null);
        } catch (IOException e) {
            // handle exception
        }
        return Status.OK_STATUS;
    }
}
```

```
}  
}
```

Alternatively, you can also register builders for your DSL in other plug-ins.

4.2.6 Implementing Interpreters

To ease the implementation of interpreters for your DSL, EMFText generates an interpreter stub. Assuming the file extension of your DSL is `xyz` the abstract stub class will be named **AbstractXyzInterpreter**. To implement concrete interpreters, you can create subclasses of this stub class.

For each metaclass found in the metamodel of your DSL, the interpreter stub contains a **interpret_Classname** method. These methods can be overridden in concrete interpreter classes to implement the desired interpretation for the objects of each type.

After implementing the methods for the classes which shall be interpreted, the interpreter can be used in different modes. First, models can be interpreted using a stack. In this case, the **interpret_Classname** methods must perform the interpretation, but should not call other **interpret** methods. This is automatically performed by the interpreter. One can put objects on the interpretation stack by calling **addObjectToInterpret()** and then start interpretation by calling **interpret()**. Interpretation ends when all objects from the stack are consumed.

Second, the interpretation can be performed without using the stack. In this case, the **interpret_Classname** methods call other **interpret** methods to continue interpretation. The traversal of the model is more explicit than using the interpreter with the stack in this mode.

The first, stack-based interpretation mode is useful to traverse models in a bottom-up fashion. One can simply put all models elements (using **eAllContents()** on the model root element) on the stack and then start interpretation. The second, stack-independent interpretation mode is useful to traverse models top-down.

The stub class has two type parameters—**ResultType** and **ContextType**, which concrete subclasses must bind. The former parameter (i.e., **ResultType**) specifies the return type of the **interpret** methods. The latter parameter (i.e., **ContextType**) defines the type of the parameter that is passed to the **interpret** methods. By binding the type parameters one can use arbitrary classes to pass interpretation results.

Examples for interpreters can be found in the EMFText Syntax Zoo. Both SimpleMath¹ and the ThreeValuedLogic DSL² use the generated interpreter stubs.

4.2.7 Customizing Text Hovers

To implement custom text hovers for your DSL, basically set the code generation option **overrideHoverTextProvider** to **false**:

```
OPTIONS {  
    overrideHoverTextProvider = "false";  
}
```

¹<http://www.emftext.org/language/simplemath>

²<http://www.emftext.org/language/threevaluedlogic>

```
}
```

After regenerating the resource plug-ins (see Sect. 2.3), a new class `XyzHoverTextProvider` can be found in the `src` folder of the generated resource UI plug-in (assuming the file extension of your DSL is `xyz`). If you face compilation errors, make sure to delete the `XyzHoverTextProvider` class from the `src-gen` folder.

The generated hover text provider class contains one method—`getHoverText()`. The default implementation of this method delegates calls to a default provider. To customize the hover text you can inspect the `EObject` passed to the method and return arbitrary HTML code. The following listing shows a simple customized provider, which returns the type of the `EObject`.

```
import org.eclipse.emf.ecore.EObject;
import org.emftext.language.xyz.resource.xyz.IXyzHoverTextProvider;

public class XyzHoverTextProvider implements IXyzHoverTextProvider {

    public String getHoverText(EObject object) {
        return "An object of type " + object.eClass().getName();
    }
}
```

4.2.8 Customizing Code Completion Proposals

List of Figures

List of Listings

A Code Generation Options

EMFText currently supports 210 code generation options. However, most of them (177) are only used to specify which generated artifacts shall be customized. Subsequently, a list of all options and their description can be found.

additionalDependencies

A list of comma separated plug-in IDs, which will be added to the manifest of the generated resource plug-in. The default value for this option is an empty list.

additionalExports

A list of comma separated packages, which will be added as exports to the manifest of the generated resource plug-in. The default value for this option is an empty list.

additionalUIDependencies

A list of comma separated plug-in IDs, which will be added to the manifest of the generated resource UI plug-in. The default value for this option is an empty list.

additionalUIExports

A list of comma separated packages, which will be added as exports to the manifest of the generated resource UI plug-in. The default value for this option is an empty list.

antlrPluginID

Sets the ID for the generated common ANTLR runtime plug-in. The default value for this option is `org.emftext.common.antlr3_2_0`.

autofixSimpleLeftrecursion

If set to **true**, EMFText will try to fix rules that contain simple left recursion. The default value for this option is **false**. This is a non-standard option, which might be removed in future releases of EMFText.

backtracking

If set to **false**, the ANTLR-backtracking is deactivated for parser generation. The default value for this option is **true**.

basePackage

The name of the base package EMFText shall store the generated classes or the resource plug-in in. If this option is not set, the default value is determined by adding the suffix `resource.FILE_EXTENSION` to the base package of the generator model.

baseResourcePlugin

The plug-in containing the resource implementation for the DSL (if different from the generated resource plug-in). By default this option is not set, which means that the generated resource plug-in provides the resource implementation.

defaultTokenName

This option can be used to specify the name of the token that is used when no token is given for attributes or non-containment references in syntax rules. Declarations like `featureX[]` in CS rules will automatically be expanded to `featureX[TOKEN_Y]` if the value of this option is `TOKEN_Y`. The default value for this option is `TEXT`, which makes the predefined token `TEXT` the default token.

disableBuilder

If set to **true**, the builder that is generated and registered by default will not be registered anymore. The default value for this option is **false**.

disableEMFValidationConstraints

If set to **true**, constraint validation using the EMF Validation Framework is disabled. The default value for this option is **false**.

disableEValidators

If set to **false**, constraint validation using registered EValidators will be enabled. The default value for this option is **true**.

disableTokenSorting

Disables the automatic sorting of tokens. The default value for this option is **false**.

forceEOF

If set to **false**, EMFText will generate a parser that does not expect an EOF signal at the end of the input stream. The default value for this option is **true**.

generateCodeFromGeneratorModel

If set to **true**, EMFText automatically generates the model code using the generator model referenced in the CS specification. The default value for this option is **false**.

generateTestAction

If set to **true**, EMFText generates a UI action that can be used to test parsing and printing of files containing textual syntax. The default value for this option is **false**. This is a non-standard option, which might be removed in future releases of EMFText.

generateUIPlugin

If set to **false**, EMFText will not generate the resource UI plug-in. The default value for this option is **true**.

licenceHeader

A URI pointing to a text file that contains a header which shall be added to all generated Java files. This option is useful to include copyright statements in the generated classes. If this option is not set, a default (empty) header is added to all generated Java classes.

memoize

If set to **false**, the ANTLR-memoize is deactivated for parser generation. The default value for this option is **true**.

overrideAbstractExpectedElement

If set to **false**, the `AbstractExpectedElement` class will not be overridden. The default value for this option is **true**.

overrideAbstractInterpreter

If set to **false**, the `AbstractInterpreter` class will not be overridden. The default value for this option is **true**.

overrideAdditionalExtensionParserExtensionPointSchema

If set to **false**, the extension point schema for additional parsers is not overridden. The default value for this option is **true**.

overrideAnnotationModel

If set to **false**, the `AnnotationModel` class will not be overridden. The default value for this option is **true**.

overrideAnnotationModelFactory

If set to **false**, `AnnotationModelFactory` class will not be overridden. The default value for this option is **true**.

overrideAntlrPlugin

If set to **false**, no ANTLR common runtime plug-in is generated. The default value for this option is **true**.

overrideAntlrTokenHelper

If set to **false**, the `AntlrTokenHelper` class will not be overridden. The default value for this option is **true**.

overrideAttributeValueProvider

If set to **false**, the `AttributeValueProvider` class will not be overridden. The default value for this option is **true**.

overrideBracketInformationProvider

If set to **false**, the `BracketInformationProvider` class will not be overridden. The default value for this option is **true**.

overrideBracketPreferencePage

If set to **false**, the `BracketPreferencePage` class will not be overridden. The default value for this option is **true**.

overrideBracketSet

If set to **false**, the `BracketSet` class will not be overridden. The default value for this option is **true**.

overrideBrowserInformationControl

If set to **false**, the `BrowserInformationControl` class will not be overridden. The default value for this option is **true**.

overrideBuildProperties

If set to **false**, the `build.properties` file will not be overridden. The default value for this option is **true**.

overrideBuilder

If set to **false**, the `Builder` class will not be overridden. The default value for this option is **true**.

overrideBuilderAdapter

If set to **false**, the `BuilderAdapter` class will not be overridden. The default value for this option is **true**.

overrideCardinality

If set to **false**, the Cardinality class will not be overridden. The default value for this option is **true**.

overrideCastUtil

If set to **false**, the CastUtil class will not be overridden. The default value for this option is **true**.

overrideChoice

If set to **false**, the Choice class will not be overridden. The default value for this option is **true**.

overrideClasspath

If set to **false**, the .classpath file of the resource plug-in will not be overridden. The default value for this option is **true**.

overrideCodeCompletionHelper

If set to **false**, the CodeCompletionHelper class will not be overridden. The default value for this option is **true**.

overrideCodeFoldingManager

If set to **false**, the CodeFoldingManager class will not be overridden. The default value for this option is **true**.

overrideColorManager

If set to **false**, the ColorManager class will not be overridden. The default value for this option is **true**.

overrideCompletionProcessor

If set to **false**, the CompletionProcessor class will not be overridden. The default value for this option is **true**.

overrideCompletionProposal

If set to **false**, the CompletionProposal class will not be overridden. The default value for this option is **true**.

overrideCompound

If set to **false**, the Compound class will not be overridden. The default value for this option is **true**.

overrideContainment

If set to **false**, the Containment class will not be overridden. The default value for this option is **true**.

overrideContextDependentURIFragment

If set to **false**, the ContextDependentUriFragment class will not be overridden. The default value for this option is **true**.

overrideContextDependentURIFragmentFactory

If set to **false**, the ContextDependentUriFragmentFactory class will not be overridden. The default value for this option is **true**.

overrideCopiedEList

If set to **false**, the CopiedEList class will not be overridden. The default value for this option is **true**.

overrideCopiedEObjectInternalEList

If set to **false**, the CopiedEObjectInternalEList class will not be overridden. The default value for this option is **true**.

overrideDefaultHoverTextProvider

If set to **false**, the DefaultHoverTextProvider class will not be overridden. The default value for this option is **true**.

overrideDefaultLoadOptionsExtensionPointSchema

If set to **false**, the extension point schema for default load options is not overridden. The default value for this option is **true**.

overrideDefaultResolverDelegate

If set to **false**, the default resolver class will not be overridden. The default value for this option is **true**.

overrideDefaultTokenResolver

If set to **false**, the DefaultTokenResolver class will not be overridden. The default value for this option is **true**.

overrideDelegatingResolveResult

If set to **false**, the DelegatingResolveResult class will not be overridden. The default value for this option is **true**.

overrideDocBrowserInformationControllInput

If set to **false**, the DocBrowserInformationControllInput class will not be overridden. The default value for this option is **true**.

overrideDummyEObject

If set to **false**, the DummyEObject class will not be overridden. The default value for this option is **true**.

overrideEClassUtil

If set to **false**, the EClassUtil class will not be overridden. The default value for this option is **true**.

overrideEObjectSelection

If set to **false**, the EObjectSelection class will not be overridden. The default value for this option is **true**.

overrideEObjectUtil

If set to **false**, the EObjectUtil class will not be overridden. The default value for this option is **true**.

overrideEProblemType

If set to **false**, the EProblemType class will not be overridden. The default value for this option is **true**.

overrideEditor

If set to **false**, the Editor class will not be overridden. The default value for this option is **true**.

overrideEditorConfiguration

If set to **false**, the EditorConfiguration class will not be overridden. The default value for this option is **true**.

overrideElementMapping

If set to **false**, the ElementMapping class will not be overridden. The default value for this option is **true**.

overrideExpectedCsString

If set to **false**, the ExpectedCsString class will not be overridden. The default value for this option is **true**.

overrideExpectedStructuralFeature

If set to **false**, the ExpectedStructuralFeature class will not be overridden. The default value for this option is **true**.

overrideExpectedTerminal

If set to **false**, the ExpectedTerminal class will not be overridden. The default value for this option is **true**.

overrideFoldingInformationProvider

If set to **false**, the FoldingInformationProvider class will not be overridden. The default value for this option is **true**.

overrideFollowSetProvider

If set to **false**, the FollowSetProvider class will not be overridden. The default value for this option is **true**.

overrideFormattingElement

If set to **false**, the FormattingElement class will not be overridden. The default value for this option is **true**.

overrideFuzzyResolveResult

If set to **false**, the FuzzyResolveResult class will not be overridden. The default value for this option is **true**.

overrideGrammarInformationProvider

If set to **false**, the GrammarInformationProvider class will not be overridden. The default value for this option is **true**.

overrideHTMLPrinter

If set to **false**, the HtmlPrinter class will not be overridden. The default value for this option is **true**.

overrideHighlighting

If set to **false**, the Highlighting class will not be overridden. The default value for this option is **true**.

overrideHoverTextProvider

If set to **false**, the HoverTextProvider class will not be overridden. The default value for this option is **true**.

overrideHyperlink

If set to **false**, the `Hyperlink` class will not be overridden. The default value for this option is **true**.

overrideHyperlinkDetector

If set to **false**, the `HyperlinkDetector` class will not be overridden. The default value for this option is **true**.

overrideIBackgroundParsingListener

If set to **false**, the `IBackgroundParsingListener` class will not be overridden. The default value for this option is **true**.

overrideIBracketHandler

If set to **false**, the `IBracketHandler` class will not be overridden. The default value for this option is **true**.

overrideIBracketPair

If set to **false**, the `IBracketPair` class will not be overridden. The default value for this option is **true**.

overrideIBuilder

If set to **false**, the `IBuilder` class will not be overridden. The default value for this option is **true**.

overrideICommand

If set to **false**, the `ICommand` class will not be overridden. The default value for this option is **true**.

overrideIConfigurable

If set to **false**, the `IConfigurable` class will not be overridden. The default value for this option is **true**.

overrideIContextDependentURIFragment

If set to **false**, the `IContextDependentUriFragment` class will not be overridden. The default value for this option is **true**.

overrideIContextDependentURIFragmentFactory

If set to **false**, the `IContextDependentUriFragmentFactory` class will not be overridden. The default value for this option is **true**.

overrideIElementMapping

If set to **false**, the `IElementMapping` class will not be overridden. The default value for this option is **true**.

overrideIExpectedElement

If set to **false**, the `IExpectedElement` class will not be overridden. The default value for this option is **true**.

overrideIHoverTextProvider

If set to **false**, the `IHoverTextProvider` class will not be overridden. The default value for this option is **true**.

overrideIInputStreamProcessorProvider

If set to **false**, the `IInputStreamProcessorProvider` class will not be overridden. The default value for this option is **true**.

overrideILocationMap

If set to **false**, the `ILocationMap` class will not be overridden. The default value for this option is **true**.

overrideIMetaInformation

If set to **false**, the `IMetaInformation` class will not be overridden. The default value for this option is **true**.

overrideIOptionProvider

If set to **false**, the `IOptionProvider` class will not be overridden. The default value for this option is **true**.

overrideIOptions

If set to **false**, the `IOptions` class will not be overridden. The default value for this option is **true**.

overrideIParseResult

If set to **false**, the `IParseResult` class will not be overridden. The default value for this option is **true**.

overrideIProblem

If set to **false**, the `IProblem` class will not be overridden. The default value for this option is **true**.

overrideIQuickFix

If set to **false**, the `IQuickFix` class will not be overridden. The default value for this option is **true**.

overrideIReferenceCache

If set to **false**, the `IReferenceCache` class will not be overridden. The default value for this option is **true**.

overrideIReferenceMapping

If set to **false**, the `IReferenceMapping` class will not be overridden. The default value for this option is **true**.

overrideIReferenceResolveResult

If set to **false**, the `IReferenceResolveResult` class will not be overridden. The default value for this option is **true**.

overrideIReferenceResolver

If set to **false**, the `IReferenceResolver` class will not be overridden. The default value for this option is **true**.

overrideIReferenceResolverSwitch

If set to **false**, the `IReferenceResolverSwitch` class will not be overridden. The default value for this option is **true**.

overrideIResourcePostProcessor

If set to **false**, the `IResourcePostProcessor` class will not be overridden. The default value for this option is **true**.

overrideIResourcePostProcessorProvider

If set to **false**, the `IResourcePostProcessorProvider` class will not be overridden. The default value for this option is **true**.

overrideITextDiagnostic

If set to **false**, the `ITextDiagnostic` class will not be overridden. The default value for this option is **true**.

overrideITextParser

If set to **false**, the `ITextParser` class will not be overridden. The default value for this option is **true**.

overrideITextPrinter

If set to **false**, the `ITextPrinter` class will not be overridden. The default value for this option is **true**.

overrideITextResource

If set to **false**, the `ITextResource` class will not be overridden. The default value for this option is **true**.

overrideITextResourcePluginPart

If set to **false**, the `ITextResourcePluginPart` class will not be overridden. The default value for this option is **true**.

overrideITextScanner

If set to **false**, the `ITextScanner` class will not be overridden. The default value for this option is **true**.

overrideITextToken

If set to **false**, the `ITextToken` class will not be overridden. The default value for this option is **true**.

overrideITokenResolveResult

If set to **false**, the `ITokenResolveResult` class will not be overridden. The default value for this option is **true**.

overrideITokenResolver

If set to **false**, the `ITokenResolver` class will not be overridden. The default value for this option is **true**.

overrideITokenResolverFactory

If set to **false**, the `ITokenResolverFactory` class will not be overridden. The default value for this option is **true**.

overrideITokenStyle

If set to **false**, the `ITokenStyle` class will not be overridden. The default value for this option is **true**.

overrideIURIMapping

If set to **false**, the `IUriMapping` class will not be overridden. The default value for this option is **true**.

overrideImageProvider

If set to **false**, the `ImageProvider` class will not be overridden. The default value for this option is **true**.

overrideInputStreamProcessor

If set to **false**, the `InputStreamProcessor` class will not be overridden. The default value for this option is **true**.

overrideKeyword

If set to **false**, the `Keyword` class will not be overridden. The default value for this option is **true**.

overrideLayoutInformation

If set to **false**, the `LayoutInformation` class will not be overridden. The default value for this option is **true**.

overrideLayoutInformationAdapter

If set to **false**, the `LayoutInformationAdapter` class will not be overridden. The default value for this option is **true**.

overrideLineBreak

If set to **false**, the `LineBreak` class will not be overridden. The default value for this option is **true**.

overrideListUtil

If set to **false**, the `ListUtil` class will not be overridden. The default value for this option is **true**.

overrideLocationMap

If set to **false**, the `LocationMap` class will not be overridden. The default value for this option is **true**.

overrideManifest

If set to **false**, the manifest of the resource plug-in will not be overridden. The default value for this option is **true**.

overrideMapUtil

If set to **false**, the `MapUtil` class will not be overridden. The default value for this option is **true**.

overrideMarkerAnnotation

If set to **false**, the `MarkerAnnotation` class will not be overridden. The default value for this option is **true**.

overrideMarkerHelper

If set to **false**, the `MarkerHelper` class will not be overridden. The default value for this option is **true**.

overrideMarkerResolutionGenerator

If set to **false**, the `MarkerResolutionGenerator` class will not be overridden. The default value for this option is **true**.

overrideMetaInformation

If set to **false**, the `MetaInformation` class will not be overridden. The default value for this option is **true**.

overrideMinimalModelHelper

If set to **false**, the MinimalModelHelper class will not be overridden. The default value for this option is **true**.

overrideNature

If set to **false**, the Nature class will not be overridden. The default value for this option is **true**.

overrideNewFileContentProvider

If set to **false**, the NewFileContentProvider class will not be overridden. The default value for this option is **true**.

overrideNewFileWizard

If set to **false**, the new file wizard class will not be overridden. The default value for this option is **true**.

overrideNewFileWizardPage

If set to **false**, the NewFileWizardPage class will not be overridden. The default value for this option is **true**.

overrideOccurencePreferencePage

If set to **false**, the OccurencePreferencePage class will not be overridden. The default value for this option is **true**.

overrideOccurrence

If set to **false**, the Occurence class will not be overridden. The default value for this option is **true**.

overrideOutlinePage

If set to **false**, the OutlinePage class will not be overridden. The default value for this option is **true**.

overrideOutlinePageTreeView

If set to **false**, the OutlinePageTreeView class will not be overridden. The default value for this option is **true**.

overridePair

If set to **false**, the Pair class will not be overridden. The default value for this option is **true**.

overrideParseResult

If set to **false**, the ParseResult class will not be overridden. The default value for this option is **true**.

overrideParser

If set to **false**, the Parser class will not be overridden. The default value for this option is **true**.

overrideParsingStrategy

If set to **false**, the ParsingStrategy class will not be overridden. The default value for this option is **true**.

overridePixelConverter

If set to **false**, the PixelConverter class will not be overridden. The default value for this option is **true**.

overridePlaceholder

If set to **false**, the Placeholder class will not be overridden. The default value for this option is **true**.

overridePluginActivator

If set to **false**, the PluginActivator class will not be overridden. The default value for this option is **true**.

overridePluginXML

If set to **true**, the plugin.xml file will be overridden. The default value for this option is **true**.

overridePositionCategory

If set to **false**, the PositionCategory class will not be overridden. The default value for this option is **true**.

overridePositionHelper

If set to **false**, the PositionHelper class will not be overridden. The default value for this option is **true**.

overridePreferenceConstants

If set to **false**, the PreferenceConstants class will not be overridden. The default value for this option is **true**.

overridePreferenceInitializer

If set to **false**, the PreferenceInitializer class will not be overridden. The default value for this option is **true**.

overridePreferencePage

If set to **false**, the PreferencePage class will not be overridden. The default value for this option is **true**.

overridePrinter

If set to **false**, the printer will not be overridden. The default value for this option is **true**.

overridePrinter2

If set to **false**, the Printer2 class will not be overridden. The default value for this option is **true**.

overrideProblemClass

If set to **false**, the problem class will not be overridden. The default value for this option is **true**.

overrideProjectFile

If set to **false**, the .project file of the resource plug-in will not be overridden. The default value for this option is **true**.

overridePropertySheetPage

If set to **false**, the PropertySheetPage class will not be overridden. The default value for this option is **true**.

overrideProposalPostProcessor

If set to **false**, the `ProposalPostProcessor` class will not be overridden. The default value for this option is **true**.

overrideQuickAssistAssistant

If set to **false**, the `QuickAssistAssistant` class will not be overridden. The default value for this option is **true**.

overrideQuickAssistProcessor

If set to **false**, the `QuickAssistProcessor` class will not be overridden. The default value for this option is **true**.

overrideQuickFix

If set to **false**, the `QuickFix` class will not be overridden. The default value for this option is **true**.

overrideReferenceResolveResult

If set to **false**, the `ReferenceResolveResult` class will not be overridden. The default value for this option is **true**.

overrideReferenceResolverSwitch

If set to **false**, the reference resolver switch will not be overridden. The default value for this option is **true**.

overrideReferenceResolvers

If set to **true**, the reference resolver classes will be overridden. The default value for this option is **false**.

overrideResourceFactory

If set to **false**, the resource factory class will not be overridden. The default value for this option is **true**.

overrideResourceFactoryDelegator

If set to **false**, the `ResourceFactoryDelegator` class will not be overridden. The default value for this option is **true**.

overrideResourceUtil

If set to **false**, the `ResourceUtil` class will not be overridden. The default value for this option is **true**.

overrideScanner

If set to **false**, the `Scanner` class will not be overridden. The default value for this option is **true**.

overrideSequence

If set to **false**, the `Sequence` class will not be overridden. The default value for this option is **true**.

overrideStreamUtil

If set to **false**, the `StreamUtil` class will not be overridden. The default value for this option is **true**.

overrideStringUtil

If set to **false**, the `StringUtil` class will not be overridden. The default value for this option is **true**.

overrideSyntaxColoringHelper

If set to **false**, the `SyntaxColoringHelper` class will not be overridden. The default value for this option is **true**.

overrideSyntaxColoringPreferencePage

If set to **false**, the `SyntaxColoringPreferencePage` class will not be overridden. The default value for this option is **true**.

overrideSyntaxCoverageInformationProvider

If set to **false**, the `SyntaxCoverageInformationProvider` class will not be overridden. The default value for this option is **true**.

overrideSyntaxElement

If set to **false**, the `SyntaxElement` class will not be overridden. The default value for this option is **true**.

overrideSyntaxElementDecorator

If set to **false**, the `SyntaxElementDecorator` class will not be overridden. The default value for this option is **true**.

overrideTerminal

If set to **false**, the `Terminal` class will not be overridden. The default value for this option is **true**.

overrideTerminateParsingException

If set to **false**, the `TerminateParsingException` class will not be overridden. The default value for this option is **true**.

overrideTextHover

If set to **false**, the `TextHover` class will not be overridden. The default value for this option is **true**.

overrideTextResource

If set to **false**, the `TextResource` class will not be overridden. The default value for this option is **true**.

overrideTextResourceUtil

If set to **false**, the `TextResourceUtil` class will not be overridden. The default value for this option is **true**.

overrideTextToken

If set to **false**, the `TextToken` class will not be overridden. The default value for this option is **true**.

overrideTokenResolveResult

If set to **false**, the `TokenResolveResult` class will not be overridden. The default value for this option is **true**.

overrideTokenResolverFactory

If set to **false**, the `TokenResolverFactory` class will not be overridden. The default value for this option is **true**.

overrideTokenResolvers

If set to **true**, the token resolver classes will be overridden. The default value for this option is **false**.

overrideTokenScanner

If set to **false**, the TokenScanner class will not be overridden. The default value for this option is **true**.

overrideTokenStyleInformationProvider

If set to **false**, the TokenStyleInformationProvider class will not be overridden. The default value for this option is **true**.

overrideUIBuildProperties

If set to **false**, the build.properties file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIDotClasspath

If set to **false**, the .classpath file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIDotProject

If set to **false**, the .project file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIManifest

If set to **false**, the manifest of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIMetaInformation

If set to **false**, the MetaInformation class of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIPluginActivator

If set to **false**, the plug-in activator class of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideUIPluginXML

If set to **false**, the plugin.xml file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

overrideURIMapping

If set to **false**, the UriMapping class will not be overridden. The default value for this option is **true**.

overrideUnexpectedContentTypeException

If set to **false**, the UnexpectedContentTypeException class will not be overridden. The default value for this option is **true**.

overrideUnicodeConverter

If set to **false**, the UnicodeConverter class will not be overridden. The default value for this option is **true**.

overrideWhiteSpace

If set to **false**, the WhiteSpace class will not be overridden. The default value for this option is **true**.

parserGenerator

The name of the parser generator to use. The default value for this option is **antlr**, which is also the only valid value. This is a non-standard option, which might be removed in future releases of EMFText.

reloadGeneratorModel

If set to **true**, EMFText reloads the generator model before loading it. This is particular useful, when the meta model (i.e., the Ecore file) is changing a lot during language development. The default value for this option is **false**.

resourcePluginID

The ID of the generated resource plug-in. The resource plug-in is stored in a folder that is equal to this ID.

resourceUIPluginID

The ID of the generated resource UI plug-in. The resource UI plug-in is stored in a folder that is equal to this ID.

saveChangedResourcesOnly

If set to **true**, the generated EMF resource will save only resource when their content (text) has actually changed. The default value for this option is **false**.

srcFolder

The name of the folder where EMFText shall store the customizable classes of the resource plug-in in. All classes for which the **override** option is set to **false** will be stored in this folder.

srcGenFolder

The name of the folder where EMFText shall store the generated classes of the resource plug-in in. All classes for which the **override** option is set to **true** will be stored in this folder.

tokenspace

The (numerical) value of this option defines how many whitespace should be printed between tokens if no whitespace information is given in CS rules. This option should only be used with the classic printer. The default value of this option is **1** if the classic printer is used (see option **useClassicPrinter**) and **automatic** otherwise.

uiBasePackage

The package where to store all classes of the resource UI plug-in in. If this option is not set, the default value is determined by adding the suffix **resource.FILE_EXTENSION.ui** to the base package of the generator model.

uiSrcFolder

The name of the folder where EMFText shall store the customizable classes of the resource UI plug-in in. All classes for which the **override** option is set to **false** will be stored in this folder.

uiSrcGenFolder

The name of the folder EMFText shall store the generated classes of the resource UI plug-in in. All classes for which the **override** option is set to **true** will be stored in this folder.

useClassicPrinter

If set to **false**, the classic printer (i.e., the one used before EMFText 1.3.0) will be used. Otherwise the new printer implementation is used. In any case both printers are generated, but only one is used. The default value for this option is **false**.

usePredefinedTokens

If set to **false**, EMFText does not automatically provide predefined tokens (TEXT, WHITESPACE, LINEBREAK). The default value for this option is **true**.

B Types of Warnings

- `abstractSyntaxHasStartSymbols`
- `collectInTokenUsedInRule`
- `duplicateOptionWithSameValue`
- `duplicateTokenStyle`
- `explicitSyntaxChoice`
- `featureWithoutSyntax`
- `generationWarning`
- `leftRecursiveRule`
- `licenceHeaderNotFound`
- `maxOccurenceMismatch`
- `minOccurenceMismatch`
- `multipleFeatureUse`
- `noRuleForMetaClass`
- `nonContainmentOpposite`
- `nonStandardOption`
- `oppositeFeatureWithoutSyntax`
- `optionalKeyword`
- `referenceToAbstractClassWithoutConcreteSubtypesInAbstractSyntax`
- `styleReferenceToNonExistingToken`
- `tokenOverlapping`
- `tokenPriorizationUselessWhenTokenSortingEnabled`
- `unusedResolverClass`
- `unusedToken`

Bibliography

- [Obj02] Object Management Group. Human Usable Textual Notation (HUTN) Specification. Final Adopted Specification ptc/02-12-01, 2002.
- [SBPM08] Dave Steinberg, Frank Budinsky, Marcelo Paternostro, and Ed Merks. *Eclipse Modeling Framework, 2nd Edition*. Pearson Education, 2008.