



Prepare the target host

NetApp Solutions

Dorian Henderson, Ivana Devine
July 21, 2021

This PDF was generated from https://docs.netapp.com/us-en/netapp-solutions/ent-apps-db/saphana-dr-anf_prepare_the_target_host_01.html on August 03, 2021. Always check docs.netapp.com for the latest.

Table of Contents

- Prepare the target host. 1
 - Target server host name and IP address 1
 - Install required software 1
 - Configure users, ports, and SAP services 1
 - Prepare HANA log volume 2
 - Prepare log backup volume 2
 - Prepare file system mounts 2

Prepare the target host

[Previous: Disaster recovery failover.](#)

This section describes the preparation steps required at the server that is used for the disaster recovery failover.

During normal operation, the target host is typically used for other purposes, for example, as a HANA QA or test system. Therefore, most of the described steps must be executed when disaster failover testing is executed. On the other hand, the relevant configuration files, like `/etc/fstab` and `/usr/sap/sapservices`, can be prepared and then put in production by simply copying the configuration file. The disaster recovery failover procedure ensures that the relevant prepared configuration files are configured correctly.

The target host preparation also includes shutting down the HANA QA or test system as well as stopping all services using `systemctl stop sapinit`.

Target server host name and IP address

The host name of the target server must be identical to the host name of the source system. The IP address can be different.



Proper fencing of the target server must be established so that it cannot communicate with other systems. If proper fencing is not in place, then the cloned production system might exchange data with other production systems, resulting in logically corrupted data.

Install required software

The SAP host agent software must be installed at the target server. For full information, see the [SAP Host Agent](#) at the SAP help portal.



If the host is used as a HANA QA or test system, the SAP host agent software is already installed.

Configure users, ports, and SAP services

The required users and groups for the SAP HANA database must be available at the target server. Typically, central user management is used; therefore, no configuration steps are necessary at the target server. The required ports for the HANA database must be configured at the target hosts. The configuration can be copied from the source system by copying the `/etc/services` file to the target server.

The required SAP services entries must be available at the target host. The configuration can be copied from the source system by copying the `/usr/sap/sapservices` file to the target server. The following output shows the required entries for the SAP HANA database used in the lab setup.

```
vm-pr1:~ # cat /usr/sap/sapservices
#!/bin/sh
LD_LIBRARY_PATH=/usr/sap/PR1/HDB01/exe:$LD_LIBRARY_PATH;export
LD_LIBRARY_PATH;/usr/sap/PR1/HDB01/exe/sapstartsrv
pf=/usr/sap/PR1/SYS/profile/PR1_HDB01_vm-pr1 -D -u prladm
limit.descriptors=1048576
```

Prepare HANA log volume

Because the HANA log volume is not part of the replication, an empty log volume must exist at the target host. The log volume must include the same subdirectories as the source HANA system.

```
vm-pr1:~ # ls -al /hana/log/PR1/mnt00001/
total 16
drwxrwxrwx 5 root    root    4096 Feb 19 16:20 .
drwxr-xr-x 3 root    root      22 Feb 18 13:38 ..
drwxr-xr-- 2 prladm  sapsys  4096 Feb 22 10:25 hdb00001
drwxr-xr-- 2 prladm  sapsys  4096 Feb 22 10:25 hdb00002.00003
drwxr-xr-- 2 prladm  sapsys  4096 Feb 22 10:25 hdb00003.00003
vm-pr1:~ #
```

Prepare log backup volume

Because the source system is configured with a separate volume for the HANA log backups, a log backup volume must also be available at the target host. A volume for the log backups must be configured and mounted at the target host.

If log backup volume replication is part of the disaster recovery setup, the replicated log backup volume is mounted at the target host, and it is not necessary to prepare an additional log backup volume.

Prepare file system mounts

The following table shows the naming conventions used in the lab setup. The volume names at the disaster recovery site are included in `/etc/fstab`.

HANA PR1 volumes	Volume and subdirectories at disaster recovery site	Mount point at target host
Data volume	PR1-data-mnt00001-sm-dest	/hana/data/PR1/mnt00001
Shared volume	PR1-shared-sm-dest/shared PR1-shared-sm-dest/usr-sap-PR1	/hana/shared /usr/sap/PR1
Log backup volume	hanabackup-sm-dest	/hanabackup



The mount points from this table must be created at the target host.

Here are the required `/etc/fstab` entries.

```
vm-pr1:~ # cat /etc/fstab
# HANA ANF DB Mounts
10.0.2.4:/PR1-data-mnt0001-sm-dest /hana/data/PR1/mnt00001 nfs
rw,vers=4,minorversion=1,hard,timeo=600,rsiz=262144,wsiz=262144,intr,noa
time,lock,_netdev,sec=sys 0 0
10.0.2.4:/PR1-log-mnt0001-dr /hana/log/PR1/mnt00001 nfs
rw,vers=4,minorversion=1,hard,timeo=600,rsiz=262144,wsiz=262144,intr,noa
time,lock,_netdev,sec=sys 0 0
# HANA ANF Shared Mounts
10.0.2.4:/PR1-shared-sm-dest/hana-shared /hana/shared nfs
rw,vers=4,minorversion=1,hard,timeo=600,rsiz=262144,wsiz=262144,intr,noa
time,lock,_netdev,sec=sys 0 0
10.0.2.4:/PR1-shared-sm-dest/usr-sap-PR1 /usr/sap/PR1 nfs
rw,vers=4,minorversion=1,hard,timeo=600,rsiz=262144,wsiz=262144,intr,noa
time,lock,_netdev,sec=sys 0 0
# HANA file and log backup destination
10.0.2.4:/hanabackup-sm-dest /hanabackup nfs
rw,vers=3,hard,timeo=600,rsiz=262144,wsiz=262144,nconnect=8,bg,noatime,n
oalock 0 0
```

Next: [Break and delete replication peering.](#)

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at <http://www.netapp.com/TM> are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.