

HC Installation and Setup Guide for A3XAI

Introduction

A Headless Client can be used by missions to offload AI processing to a dedicated client, freeing up the dedicated server process from most AI processing. Thus more AI units can be spawned and the server process will be able to dedicate most of its processing towards communication with the clients. For a Headless Client/Dedicated Server to function together efficiently, they both need to be connected to each other via extremely low latency and high bandwidth. Effectively, they need to be on the same LAN at least, but preferably running on the same computer.

Source: https://community.bistudio.com/wiki/Arma_3_Dedicated_Server#Headless_Client

If the Arma 3 Headless Client and a Arma 3 Dedicated Server are running on the same Windows computer (VM or physical), it may be beneficial to set processor affinity to prevent execution intensive threads from being scheduled across the same (v)CPUs. The operating system will generally schedule threads efficiently, but manual CPU allocation is possible. This can be achieved by right-clicking on the process (e.g. Arma3Server.exe(*32)) in the processes tab of the Windows Task Manager and selecting Set Affinity.... Be aware that on a physical intel CPU, the odd numbered CPUs are Hyper-thread cores.

*Note: You can use automated solution for affinity assign via batch file with commandline CMD
/AFFINITY HEXvalue e.g. CMD /C START /AFFINITY 0xF3 arma3server.exe*

It has been observed that although the ARMA server and client processes will kick off multiple threads, the bulk of processing is used up by only one or two threads. For example, spawning 50 AI units does not generate 50 threads. There is one thread in the process that handles all of the AI units, irrespective of how many have been spawned. In this way, the ARMA server and client processes do not make maximal use of the processing capability found in modern processors and so AI counts do not scale easily. As such, faster CPU core speed is king and offloading the AI to multiple headless clients on the same computer will probably produce the best possible results for complex missions involving many AI units (albeit an expensive way to get the results).

Source:

https://community.bistudio.com/wiki/Arma_3_Dedicated_Server#Headless_Client_on_a_Dedicated_Server_Notes

Required/Recommended Tools:

1. Notepad ++ (Recommended): <https://notepad-plus-plus.org/download/>
2. Eliteness (Required): <https://dev.withsix.com/projects/mikero-pbodll/files>
3. PBO Manager (Required, if mission files kept as a pbo): <http://www.armaholic.com/page.php?id=16369>

Note: If you already have a basic headless client set-up, skip to Part B to set up an HC for A3XAI

Part A: Set up Headless Client

1. Edit your server's config.sqf using a text editor

- Recommended to use **Notepad++** (Notepad++ will be used in this guide).
- Typically, config.sqf is located in /@ExileServer/config.cfg

2. Add the following lines to the end of this file.

```
localClient[]={127.0.0.1};
```

```
headlessClients[] = {"127.0.0.1"};
```

```
battleeyeLicense=1;
```

- If you are running your headless client from a different physical machine on a LAN or VM, add its IP to localClient[] and headlessClients[].
- It is recommended to run your HC on the same physical machine to minimize latency and maximize bandwidth between dedicated server and HC.
- From most ideal to least ideal dedicated/headless client setup (**red** indicates setups that should be avoided)
 - HC on same physical machine and environment as dedicated server
 - Minimal added latency
 - HC running on a different physical machine on same LAN as dedicated server
 - More added latency compared to above scenarios
 - **HC running on a different physical machine, not connected to the dedicated server by a LAN**
 - Much higher latency, high bandwidth requirement may cause issues with other players compared to above scenarios

3. Using **Eliteness**, open your mission.sqm and decrypt mission.sqm using the below guide.

Follow these four steps to decrypt mission.sqm:

The screenshot shows the EliteNess x32 Version 3.25 application window. The interface is divided into three main sections: a file explorer on the left, a file list at the bottom left, and a code editor on the right.

- Step 1:** In the file explorer, the 'Exile.Altis' folder is highlighted with a red box and labeled '1. Locate unpacked mission files'.
- Step 2:** In the file list at the bottom left, the 'mission.sqm' file is highlighted with a red box and labeled '2. Select mission.sqm'.
- Step 3:** In the top toolbar, the 'DeRapify' button (represented by a padlock icon) is highlighted with a red box and labeled '3. Click DeRapify button'.
- Step 4:** A red arrow points to the 'Save' button in the top toolbar, labeled '4. Save and replace new mission.sqm when prompted.'

The code editor on the right displays the contents of the selected 'mission.sqm' file, which is a script for the 'Exile.Altis' mission. The script includes comments about the tool used (mikero's Dos Tools DII version 4.90) and the source file date (Wed Sep 02 20:17:28 2015). It defines the mission class and sets various parameters like addOns, addOnsAuto, randomSeed, and class Intel.

```
////////////////////////////////////////////////////
//DeRap: Produced from mikero's Dos Tools DII version 4.90
//Wed Sep 02 20:17:28 2015 : Source 'file' date Wed Sep 02 20:17:28 2015
//http://dev-heaven.net/projects/list_files/mikero-pbodll
////////////////////////////////////////////////////


#define _ARMA_

//Class G:\A3XAI HC Guide Example\@ExileServer-0.9.19\mpmissions\Exile.Altis\Exile.Altis\mission.sqm{
version = 12;
class Mission
{
    addOns[] = {'exile_client','a3_map_altis'};
    addOnsAuto[] = {'exile_client','a3_map_altis'};
    randomSeed = 8080942;
    class Intel
    {
        timeOfChanges = 1800.0002;
        startWeather = 0.3;
        startWind = 0.1;
        startWaves = 0.1;
        forecastWeather = 0.3;
        forecastWind = 0.1;
        forecastWaves = 0.1;
        forecastLightnings = 0.1;
        year = 2039;
        month = 6;
        day = 24;
        hour = 12;
        minute = 0;
        startFogDecay = 0.013;
        forecastFogDecay = 0.013;
    };
    class Sensors
    {
        items = 3;
        class Item0
        {
            position[] = {14599.966,22.349989,16797.193};
        };
    };
};
```

5. Using **Notepad++**, edit the decrypted mission.sqm using the below guide.

A:\ExileServer-0.9.19\mpmissions\Exile.Altis\Exile.Altis\mission.sqm - Notepad++

coding Language Settings Macro Run Plugins Window ?




```
73      b = 175;
74      rectangular = 1;
75      activationBy = "ANY";
76      repeating = 1;
77      interruptable = 1;
78      age = "UNKNOWN";
79      name = "ExileTrader";
80      expCond = "(vehicle player) in thisList";
81      expActiv = "call ExileClient_object_player_event_onEnterSafezone";
82      expDesactiv = "call ExileClient_object_player_event_onLeaveSafezone";
83      class Effects{};
84  };
85  };
86  class Groups
87  {
88      items = 1;
89      class Item0
90      {
91          side = "GUER";
92          class Vehicles
93          {
94              items = 100;
95              class Item0
96              {
97                  position[] = {13237.161,20.660374,11705.338};
98                  special = "NONE";
99                  id = 0;
100                 side = "GUER";
101                 vehicle = "Exile_Unit_GhostPlayer";
102                 player = "PLAY CDG";
103                 leader = 1;
104                 skill = 0.6;
105             };
106             class Item1
107             {
108                 position[] = {13234.718,19.578526,11705.455};
109                 special = "NONE";
110                 id = 1;
111                 side = "GUER";
112                 vehicle = "Exile_Unit_GhostPlayer";
113                 player = "PLAY CDG";
114                 skill = 0.6;
115             };
116             class Item2
117             {
```

```
!@ExileServer-0.9.19\mpmissions\Exile.Altis\Exile.Altis\mission.sqm - Notepad++
```



```
z:\@ExileServer-0.9.19\mpmissions\Exile.Altis\Exile.Altis\mission.sqm - Notepad++
```



IMPORTANT: You must have one HC slot for each addon on your server that uses an HC. Failing to do this will cause HCs after the first connected one to fail to connect.

6. If your mission files are kept in a pbo, repack the mission files into pbo format. Otherwise, installation of the HC is done. Your next step is now to set up A3XAI on your HC (Part B).

Part B: Set up A3XAI HC

1. Inside your server's Arma 3 directory, create a new folder named @A3XAI.
2. Inside the new @A3XAI folder, create a new folder named Addons
3. Copy the A3XAI.pbo from your existing A3XAI installation inside the Addons folder you created in Step 2.
4. Copy the downloaded A3XAI.pbo.A3XAI.bisign file to the Addons folder you created in Step 2.
5. Copy the downloaded A3XAI.bikey to your server's Keys folder.
6. Edit your mission.sqm and add a new HC slot (**This was done in Part A**)
7. In A3XAI_config.sqf (inside @ExileServer), set A3XAI_enableHC = true
8. Start the HC by starting arma3server with these parameters: -client -mod=@Exile;@A3XAI;

IMPORTANT: If the HC is to be installed in a different directory (or machine) than the dedicated server, there must be a folder named @ExileServer in the same directory as @A3XAI. Inside this @ExileServer folder should be your a3xai_config.sqf from your dedicated server.

Part C: Things to note

1. It should not matter whether you start your dedicated server or headless client first.
2. You may start, close, or restart your HC at any time while A3XAI is running on your dedicated server without issues.
3. A3XAI will transfer AI groups from the dedicated server to the headless client gradually (~1 per 5 seconds) until all have been transferred.
4. A3XAI's HC will only manage AI units that it has spawned, **not** AI from other mods or addons.
5. Dedicated server will handle A3XAI's background tasks, while the HC will handle AI directly.

Part D: Verifying HC is running normally

Inside your server's RPT log, you will see that the HC has successfully connected when you see this:

```
"[A3XAI] Headless client L Charlie 1-2:1 REMOTE (owner: 4) logged in successfully."
```

Inside your HC's RPT log, you will see this (it won't be this clean, but this is what you're looking for):

```
19:23:24 "Loading A3XAI configuration file..."
```

```
19:23:24 "[A3XAI] Reading A3XAI configuration file."
```

```
19:23:24 "[A3XAI] A3XAI configuration file loaded."
```

```
19:23:24 "[A3XAI] Verified all A3XAI settings in 0.000999451 seconds."
```

```
19:23:24 "Debug: A3XAI HC functions loaded."
```

```
19:23:24 "Debug: A3XAI HC PVEHs loaded."
```

```
19:23:26 "A3XAI Debug: Location configuration completed with 44 locations found in 1.636 seconds."
```

```
19:23:26 "Debug: Waiting for HC player object setup to be completed."
```

```
19:24:12 "Debug: Headless player object set up completed."
```

```
19:24:15 "Debug: HC player setup, creating HC unit."
```

```
19:24:15 "Debug: Created HC unit L Charlie 1-2:1"
```

```
19:24:15 "Attempting to connect to A3XAI server..."
```

```
19:24:16 "Debug: Headless client connection successful. HC authorization request granted."
```