

D1.1c - VISHNU A.P.I. specifications



COLLABORATORS

	<i>TITLE :</i> D1.1c - VISHNU A.P.I. specifications		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY	Benjamin Isnard, Daouda Traoré, Eugène Pamba Capo-Chichi, Kevin Coulomb, and Ibrahima Cissé	February 25, 2011	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME
0	05/01/2011	Formatting example	SysFera
1	13/01/2011	First release	SysFera
2	10/02/2011	Removed UMS::AddUserOptions, UMS::AddMachineOptions and UMS::UpdateUserOptions classes and UMS::SessionStateType. Added function UMS::reconnect, UMS::StatusType. Modified UMS::restoreConfiguration and UMS::Configuration class	SysFera
3	17/02/2011	Renamed UMS::AddVishnuUser, Modified UMS::resetPassword, UMS::reconnect, UMS::addMachine, UMS::addLocalAccount, UMS::saveConfiguration and IMS::exportCommands	SysFera

Contents

1	Document presentation	1
1.1	Document objectives	1
1.2	Document structure	1
1.3	Generic definition formats presentation	1
1.3.1	Methods definition format	2
1.3.1.1	Generic method definition format	2
1.3.1.2	C++ specific aspects	2
1.3.1.3	Python specific aspects	2
1.3.1.4	Web Services specific aspects	3
1.3.2	Data types definition format	3
1.3.2.1	Generic data definition format	3
1.3.2.2	C++ specific aspects	3
1.3.2.3	Python specific aspects	3
1.3.2.4	Web Services specific aspects	3
1.4	Web Services description	3
1.5	References	4
1.6	Glossary	4
2	API specification for User Management Service (UMS)	5
2.1	Definition of the functions of the package	5
2.1.1	Function UMS::connect	5
2.1.2	Function UMS::reconnect	6
2.1.3	Function UMS::addUser	6
2.1.4	Function UMS::updateUser	7
2.1.5	Function UMS::deleteUser	8
2.1.6	Function UMS::close	8
2.1.7	Function UMS::changePassword	9
2.1.8	Function UMS::resetPassword	9
2.1.9	Function UMS::addLocalAccount	11
2.1.10	Function UMS::updateLocalAccount	12

2.1.11	Function UMS::deleteLocalAccount	12
2.1.12	Function UMS::saveConfiguration	13
2.1.13	Function UMS::restoreConfiguration	14
2.1.14	Function UMS::addMachine	14
2.1.15	Function UMS::updateMachine	15
2.1.16	Function UMS::deleteMachine	15
2.1.17	Function UMS::listLocalAccount	16
2.1.18	Function UMS::listMachine	17
2.1.19	Function UMS::listHistoryCmd	17
2.1.20	Function UMS::listOptions	18
2.1.21	Function UMS::listUsers	19
2.1.22	Function UMS::listSessions	19
2.1.23	Function UMS::configureDefaultOption	20
2.1.24	Function UMS::configureOption	21
2.1.25	Function UMS::vishnuInitialize	21
2.1.26	Function UMS::vishnuFinalize	22
2.2	Data types definitions	22
3	API specification for Tasks Management Service (TMS)	27
3.1	Definition of the functions of the package	27
3.1.1	Function TMS::submitJob	27
3.1.2	Function TMS::getJobInfo	28
3.1.3	Function TMS::getJobProgress	29
3.1.4	Function TMS::listQueues	29
3.1.5	Function TMS::listJobs	30
3.1.6	Function TMS::getJobOutPut	31
3.1.7	Function TMS::getAllJobsOutPut	31
3.1.8	Function TMS::cancelJob	32
3.1.9	Function TMS::setMachineEnv	33
3.1.10	Function TMS::setMachineRefreshPeriod	33
3.2	Data types definitions	34
4	API specification for Information Management Service (IMS)	38
4.1	Definition of the functions of the package	38
4.1.1	Function IMS::exportCommands	38
4.1.2	Function IMS::getMetricCurrentValue	38
4.1.3	Function IMS::getMetricHistory	39
4.1.4	Function IMS::getProcesses	40
4.1.5	Function IMS::setSystemInfo	40

4.1.6	Function IMS::setSystemThreshold	41
4.1.7	Function IMS::getSystemThreshold	41
4.1.8	Function IMS::defineUserIdentifier	42
4.1.9	Function IMS::defineMachineIdentifier	42
4.1.10	Function IMS::defineJobIdentifier	43
4.1.11	Function IMS::defineTransferIdentifier	43
4.1.12	Function IMS::loadShed	44
4.1.13	Function IMS::setUpdateFrequency	44
4.1.14	Function IMS::getUpdateFrequency	45
4.2	Data types definitions	45
5	API specification for File Management Service (FMS)	47
5.1	Definition of the functions of the package	47
5.1.1	Function FMS::createFile	47
5.1.2	Function FMS::createDir	48
5.1.3	Function FMS::removeFile	48
5.1.4	Function FMS::removeDir	49
5.1.5	Function FMS::chGrp	49
5.1.6	Function FMS::chMod	50
5.1.7	Function FMS::headOfFile	51
5.1.8	Function FMS::tailOfFile	51
5.1.9	Function FMS::contentOfFile	52
5.1.10	Function FMS::listDir	52
5.1.11	Function FMS::copyFile	53
5.1.12	Function FMS::copyAsyncFile	54
5.1.13	Function FMS::moveFile	55
5.1.14	Function FMS::moveAsyncFile	55
5.1.15	Function FMS::stopFileTransfer	56
5.1.16	Function FMS::listFileTransferStatus	56
5.1.17	Function FMS::listFileTransfers	57
5.1.18	Function FMS::getFilesInfo	58
5.2	Data types definitions	58

Chapter 1

Document presentation

1.1 Document objectives

This document presents the detailed specifications of the VISHNU APIs (Application Programming Interfaces). The following APIs are included in the project:

- C++ API
- Python (v2.x) API
- Web services (WSDL 1.1) API

These specifications include the definition of all methods and all data types in a format that is common to all APIs. Therefore the description is not tied to a particular implementation and all implementations will follow the same logic and will differ only when the language that is used imposes some constraints.

Specific aspects of each implementation language are described in the section 1.3.

1.2 Document structure

The document is divided into 4 parts corresponding to the four modules that compose the VISHNU system:

- UMS: Users Management Service
- TMS: Tasks Management Service
- FMS: Files Management Service
- IMS: Information Management Service

Each module corresponds to a chapter in the document, and each chapter contains the following sections:

- A first section describing the definition of all the methods provided by the library
- A second section describing the definition of all the data types provided by the library

1.3 Generic definition formats presentation

This section presents the formats used in the following chapters to describe the methods and data types provided by the libraries. It also details the particular implementation constraints for each language.

1.3.1 Methods definition format

The following paragraphs show how all methods (or "operations" in the Web Services terminology) are specified in this document. First, the generic format used for each Vishnu module is explained, then the aspects that are specific to each implementation language are detailed.

1.3.1.1 Generic method definition format

Parameters

The following table contains all the input and output parameters of the method, along with their type and description, and their optional or required flag.

Parameter	Type	Description	Mode	Required
sessionKey	string	This is an example of a required input parameter	IN	yes
listOfJobs	ListJobs	This is an example of an output parameter	OUT	yes

Access

Here is detailed the access level of the method 'myMethod' (i.e. the privilege required to use this method)

Description

Here is detailed the purpose of the method 'myMethod'

Return Value

Here are detailed the different return codes provided by the method. Please note that these return codes may be implemented differently depending on the language, for example by using an exception mechanism. In all implementations the library will provide a way of mapping the code to a human-readable message that will contain detailed information about the context of the exception that happened.

Name	Description
VISHNU_OK	The service was performed successfully.
TMS_UNKNOWN_MACHINE	This is the human-readable generic message that will be available to the user of the API.

Signature

This shows the C++ signature of the method.

```
int myMethod(const string& sessionKey, ListJobs& listOfJobs);
```

1.3.1.2 C++ specific aspects

- The output parameters will be implemented as references in the method signature.
- The methods will always return an integer with a default value for success.
- The methods will throw exceptions for each error message specified. The exception will contain additional details provided by the server.

1.3.1.3 Python specific aspects

- The output parameters will be implemented as a Python tuple returned by the method.

1.3.1.4 Web Services specific aspects

- The input and output parameters will be implemented as Java Beans: a "Request" bean containing the input parameters and a "Response" bean containing the output parameters.
- The methods will throw exceptions for each error message specified. The exception will contain additional details provided by the server.
- The VishnuInitialize() and VishnuFinalize() methods are not applicable to the WS API.
- Methods with restricted access (administration) are not included in the WS API.

1.3.2 Data types definition format

The following paragraphs show how all data types are specified in this document. First, the generic format used for each Vishnu data type is explained, then the aspects that are specific to each implementation language are detailed.

1.3.2.1 Generic data definition format

Class Module::Class Content

Name	Type	Description
Class attribute name	Class attribute type	Description/usage of the attribute

1.3.2.2 C++ specific aspects

- All attributes of the class will be private.
- For each attribute of the class a couple of getter/setter methods will be implemented.
- The string type will be mapped to the C++ STL string type.

1.3.2.3 Python specific aspects

- For each attribute of the class a couple of getter/setter methods will be implemented.
- The string type will be mapped to standard Python strings.

1.3.2.4 Web Services specific aspects

- When a single instance of object is used as input or output parameter, the attributes of the object will be mapped respectively to attributes of the 'Request' or 'Response' Java Bean.
- When multiple instances of object are used as input or output parameters (for example list of machines or list of users) the 'Request' or 'Response' Java Bean will contain a 'data' subclass containing the instances. This follows the standard WSDL/Java mapping for Apache-CXF.

1.4 Web Services description

The Web Services are fully described by the following documents which are attached to the current document:

- **UMS.wsdl** : WSDL file for the UMS module
- **TMS.wsdl** : WSDL file for the TMS module

- **FMS.wsdl** : WSDL file for the FMS module
- **IMS.wsdl** : WSDL file for the IMS module

1.5 References

- D1.1a : VISHNU General specifications

1.6 Glossary

None

Chapter 2

API specification for User Management Service (UMS)

2.1 Definition of the functions of the package

2.1.1 Function UMS::connect

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
userId	string	userId represents the VISHNU user identifier	IN	yes
password	string	password represents the password of the user	IN	yes
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	OUT	yes
options	ConnectOptions	options is an object which encapsulates the options available for the connect method. It allows the user to choose the way for closing the session automatically on TIMEOUT or on DISCONNECT and the possibility for an admin to open a session as he/she was a specific user	IN	no

Description

The connect() function opens a session

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NOT_AUTHENTICATED	Unknown user
UNKNOWN_CLOSURE_MODE	The name of the closure mode is unknown
INCORRECT_TIMEOUT	The value of the timeout is incorrect (negative or higher than the TIMEOUT treshold)
UNKNOWN_USERID	The userId is unknown
NO_ADMIN	The user is not an administrator
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect

Name	Description
INCORRECT_USERID_SIZE	The size of the userId is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

int **connect**(const string& userId, const string& password, string& sessionId, const ConnectOptions& options = ConnectOptions());

2.1.2 Function UMS::reconnect

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
userId	string	userId represents the VISHNU user identifier	IN	yes
password	string	password represents the password of the user	IN	yes
sessionId	string	sessionId is the identifier of the session defined in the database	IN	yes
session	Session	The session object containing session information	OUT	yes

Description

The reconnect() function reconnects to a session that is still active

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NOT_AUTHENTICATED	Unknown user
INCORRECT_USERID_SIZE	The size of the userId is incorrect
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect
SESSION_INCOMPATIBILITY	This session identifier is incompatible with the authenticated user
UNKNOWN_SESSION_ID	The session Id is unknown
SESSIONKEY_EXPIRED	The sessionId is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionId is unrecognized
UNKNOWN_MACHINE_FOR_SESSION	This session has been opened with another machine
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

int **reconnect**(const string& userId, const string& password, const string& sessionId, Session& session);

2.1.3 Function UMS::addUser

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
newUser	User	Object containing the new user information	INOUT	yes

Description

The addUser() function adds a new VISHNU user

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
INCORRECT_USERID_SIZE	The size of the userId is incorrect
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
USERID_EXISTING	The userId already exists in the database
INVALID_MAIL_ADRESS	The mail address is invalid
USERID_REQUIRED	The userId must to be defined
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int addUser(const string& sessionKey, User& newUser);
```

2.1.4 Function UMS::updateUser

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
user	User	Object containing user information	IN	yes

Description

The updateUser() function updates the user information except the userId and the password

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_USERID	The userId is unknown
INVALID_MAIL_ADRESS	The mail address is invalid
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.

Name	Description
INCORRECT_USERID_SIZE	The size of the userId is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int updateUser(const string& sessionKey, const User& user);
```

2.1.5 Function UMS::deleteUser**Access**

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
userId	string	userId represents the VISHNU user identifier of the user who will be deleted from VISHNU	IN	yes

Description

The deleteUser() function removes a user from VISHNU

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
NO_ADMIN	The user is not an administrator
INCORRECT_USERID_SIZE	The size of the userId is incorrect
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int deleteUser(const string& sessionKey, const string& userId);
```

2.1.6 Function UMS::close**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes

Description

The close() function closes the session

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
COMMAND_RUNNING	Command(s) is/are running
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int close(const string& sessionKey);
```

2.1.7 Function UMS::changePassword**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
userId	string	userId represents the VISHNU user identifier	IN	yes
password	string	password represents the password of the user	IN	yes
passwordNew	string	passwordNew represents the new password of the user	IN	yes

Description

The changePassword() function changes the password

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NOT_AUTHENTICATED	Unknown user
INCORRECT_USERID_SIZE	The size of the userId is incorrect
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int changePassword(const string& userId, const string& password, const string& passwordNew);
```

2.1.8 Function UMS::resetPassword**Access**

This function can be used by ADMIN users only

Parameters



Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
userId	string	userId represents the VISHNU user identifier of the user whose password will be reset	IN	yes
tmpPassword	string	The temporary password generated by VISHNU	OUT	yes

Description

The resetPassword() function resets the password of a user

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_USERID	The userId is unknown
INCORRECT_USERID_SIZE	The size of the userId is incorrect
INCORRECT_PASSWORD_SIZE	The size of the password is incorrect
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int resetPassword(const string& sessionKey, const string& userId, string& tmpPassword);
```

2.1.9 Function UMS::addLocalAccount

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
newAccount	LocalAccount	newAccount is the object which encapsulates the new local user configuration	IN	yes
sshPublicKey	string	The SSH public key generated by VISHNU for accessing a local account	OUT	yes

Description

The addLocalAccount() function adds a new local user configuration

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
LOCAL_ACCOUNT_EXIST	The local account already exists for the given user on the given machine

Name	Description
USERID_REQUIRED	The userId must to be defined
MACHINEID_REQUIRED	The machineId must to be defined
UNKNOWN_USERID	The userId is unknown
UNKNOWN_MACHINE	The machineId is unknown
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int addLocalAccount(const string& sessionKey, const LocalAccount& newAccount, string& sshPublicKey);
```

2.1.10 Function UMS::updateLocalAccount**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
LocalAccUpd	LocalAccount	is an object which encapsulates the local user configuration changes except the machineId and the userId	IN	yes

Description

The updateLocalAccount() function updates a local user configuration

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
UNKNOWN_USERID	The userId is unknown
UNKNOWN_MACHINE	The machineId is unknown
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
UNKNOWN_LOCAL_ACCOUNT	The local configuration for the given user on the given machine is unknown
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int updateLocalAccount(const string& sessionKey, const LocalAccount& LocalAccUpd);
```

2.1.11 Function UMS::deleteLocalAccount**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
userId	string	userId represents the VISHNU user identifier of the user whose local configuration will be deleted for the given machine	IN	yes
machineId	string	machineId represents the identifier of the machine whose local configuration will be deleted for the given user	IN	yes

Description

The deleteLocalAccount() function removes a local user configuration (for a given user on a given machine) from VISHNU

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_LOCAL_ACCOUNT	The local configuration for the given user on the given machine is unknown
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

int deleteLocalAccount(const string& sessionKey, const string& userId, const string& machineId);

2.1.12 Function UMS::saveConfiguration

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
configuration	Configuration	The configuration is an object which encapsulates the configuration description	OUT	yes

Description

The saveConfiguration() function saves the configuration of VISHNU

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
SAVE_CONFIG_ERROR	A problem occurs during the configuration saving
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int saveConfiguration(const string& sessionKey, Configuration& configuration);
```

2.1.13 Function UMS::restoreConfiguration**Access**

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
filePath	string	The filePath is the path of the file used to restore VISHNU configuration	IN	yes

Description

The restoreConfiguration() function restores the configuration of VISHNU

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
RESTORE_CONFIG_ERROR	A problem occurs during the configuration restoring
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int restoreConfiguration(const string& sessionKey, const string& filePath);
```

2.1.14 Function UMS::addMachine**Access**

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
newMachine	Machine	is an object which encapsulates the information of the machine which will be added in VISHNU except the machine id which will be created automatically by VISHNU	INOUT	yes

Description

The addMachine() function adds a new machine in VISHNU

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
MACHINE_EXISTING	The machineId already exists in the database
MACHINEID_REQUIRED	The machineId must to be defined
NO_ADMIN	The user is not an administrator
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int addMachine(const string& sessionKey, Machine& newMachine);
```

2.1.15 Function UMS::updateMachine**Access**

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
machine	Machine	existing machine information	IN	yes

Description

The updateMachine() function updates machine description

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
MACHINEID_REQUIRED	The machineId must to be defined
UNKNOWN_MACHINE	The machineId is unknown
NO_ADMIN	The user is not an administrator
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int updateMachine(const string& sessionKey, const Machine& machine);
```

2.1.16 Function UMS::deleteMachine**Access**

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
machineId	string	machineId represents the identifier of the machine	IN	yes

Description

The deleteMachine() function removes a machine from VISHNU

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_MACHINE	The machineId is unknown
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int deleteMachine(const string& sessionKey, const string& machineId);
```

2.1.17 Function UMS::listLocalAccount

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
listLocalAcct	ListLocalAccounts	listLocalAccount is the list of the local user configurations	OUT	yes
options	ListLocalAccOptions	allows an admin to list all local configurations of all users or a simple user to list his/her local user configurations on a specific machine	IN	no

Description

The listLocalAccount() function lists the local user configurations

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int listLocalAccount(const string& sessionKey, ListLocalAccounts& listLocalAcct, const ListLocalAccOptions& options = ListLocalAccOptions());
```

2.1.18 Function UMS::listMachine**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
listMachine	ListMachines	listLocalAccount is the list of the local configs	OUT	yes
options	ListMachineOptions	allows a user to list all VISHNU machines or information about a specific machine and an admin to list machines used by a specific user	IN	no

Description

The listMachine() function lists the machines in which the local user configurations are defined for the given user

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int listMachine(const string& sessionKey, ListMachines& listMachine, const ListMachineOptions& options = ListMachineOptions());
```

2.1.19 Function UMS::listHistoryCmd**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
listCommands	ListCommands	listCommands is the list of commands	OUT	yes
options	ListCmdOptions	allows the user to list commands by using several optional criteria: a period, specific session and for admin to list all commands of all VISHNU users or commands from a specific user	IN	no

Description

The listHistoryCmd() function lists the commands

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int listHistoryCmd(const string& sessionKey, ListCommands& listCommands, const ListCmdOptions& options = ListCmdOptions());
```

2.1.20 Function UMS::listOptions**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
listOptValues	ListOptionsValues	listOptValues is an object which encapsulates the list of options	OUT	yes
options	ListOptOptions	allows to list a specific option or all default options values or for an admin to list options of a specific user	IN	no

Description

The listOptions() function lists the options of the user

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_USERID	The userId is unknown
UNKNOWN_OPTION	the name of the option is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature


```
int listOptions(const string& sessionKey, ListOptionsValues& listOptValues, const ListOptOptions& options = ListOptOptions());
```

2.1.21 Function UMS::listUsers

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the identifier of the session generated by VISHNU	IN	yes
listuser	ListUsers	listuser is the list of users	OUT	yes
userIdOption	string	allows an admin to get information about a specific user identified by his/her userId	IN	no

Description

The listUsers() function lists VISHNU users

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
NO_ADMIN	The user is not an administrator
UNKNOWN_USERID	The userId is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int listUsers(const string& sessionKey, ListUsers& listuser, const string& userIdOption = string());
```

2.1.22 Function UMS::listSessions

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
listsession	ListSessions	listsession is the list of sessions	OUT	yes
options	ListSessionOptions	allows the user to list sessions using several optional criteria such as: the state of sessions (actives or inactives, by default, all sessions are listed), a period, a specific session or for admin to list all sessions of all users or sessions of a specific user.	IN	no

Description

The listSessions() function lists all sessions of the user

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_USERID	The userId is unknown
UNKNOWN_SESSION_OPTION	The name of the session option is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
INCORRECT_DATE_OPTION	The date option is incorrect
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int listSessions(const string& sessionKey, ListSessions& listsession, const ListSessionOptions& options = ListSessionOptions());
```

2.1.23 Function UMS::configureDefaultOption**Access**

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
optionValue	OptionValue	The optionValue is an object which encapsulates the option information	IN	yes

Description

The configureDefaultOption() function configures a default option value

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
NO_ADMIN	The user is not an administrator
UNKNOWN_OPTION	the name of the option is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int configureDefaultOption(const string& sessionKey, const OptionValue& optionValue);
```

2.1.24 Function UMS::configureOption

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The sessionKey is the encrypted identifier of the session generated by VISHNU	IN	yes
optionValue	OptionValue	The optionValue is an object which encapsulates the option information	IN	yes

Description

The configureOption() function configures an option of the user

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
UNKNOWN_OPTION	the name of the option is unknown
SESSIONKEY_EXPIRED	The sessionKey is expired. The session is closed.
SESSIONKEY_NOT_FOUND	The sessionKey is unrecognized
DB_ERROR	A problem occurs with the database
UMS_SERVER_NOT_AVAILABLE	The server UMS is not available

Signature

```
int configureOption(const string& sessionKey, const OptionValue& optionValue);
```

2.1.25 Function UMS::vishnuInitialize

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
configPath	string	configPath is the path of VISHNU configuration file	IN	yes

Description

The vishnuInitialize() function initializes VISHNU

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
INCORRECT_CFG_PATH	The configuration file path is incorrect

Signature

```
int vishnuInitialize(const string& configPath);
```

2.1.26 Function UMS::vishnuFinalize

Access

This function can be used by any VISHNU user

Parameters

This command defines no parameters.

Description

The vishnuFinalize() function allows a user to go out properly from VISHNU

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully
VISHNU_FINALIZE_ERROR	An error occurs during vishnuFinalize

Signature

```
int vishnuFinalize();
```

2.2 Data types definitions

Class UMS::Command Content

Name	Type	Description
commandId	string	is the identifier of a command
sessionId	string	The sessionId is the identifier of the session define in the database
machineId	string	The machineId is the identifier of the machine used by the command
cmdDescription	string	cmdDescription is the description of the command
cmdStartTime	long	cmdStartTime is the date of the command beginning (the UNIX timestamps is used)
cmdEndTime	long	cmdEndTime is the date of the command end (the UNIX timestamps is used)

Class UMS::Configuration Content

Name	Type	Description
listConfUsers	List of User	is the list of users objects
listConfMachines	List of Machine	is a list of machines objects
listConfLocalAccounts	List of LocalAccount	is the list of LocalAccount objects

Class UMS::ConnectOptions Content

Name	Type	Description
closePolicy	SessionCloseType	is an option for closing session automatically
sessionInactivityDelay	int	is the maximum delay in seconds between two user requests when the CLOSE_ON_TIMEOUT policy is set
substituteUserId	string	is an admin option which allows an admin to open a session as if she was another user identified by her userId

Class UMS::ListCmdOptions Content

Name	Type	Description
adminListOption	boolean	is an admin option for listing all commands of all users
userId	string	is an admin option for listing commands launched by a specific user identified by his/her userId
sessionId	string	lists all commands launched within a specific session
startDateOption	long	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)
endDateOption	long	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day

Class UMS::ListCommands Content

Name	Type	Description
Commands	List of Command	is the list of commands objects

Class UMS::ListLocalAccOptions Content

Name	Type	Description
adminListOption	boolean	is an admin option for listing all local configurations of all users
userId	string	is an admin option for listing the local configurations of a specific user
machineId	string	is an option for listing local user configurations on a specific machine

Class UMS::ListLocalAccounts Content

Name	Type	Description
accounts	List of LocalAccount	is a list of LocalAccount objects which encapsulates local user configurations

Class UMS::ListMachineOptions Content

Name	Type	Description
userId	string	is an admin option for listing machines in which a specific user has a local configuration
listAllmachine	boolean	is an option for listing all VISHNU machines
machineId	string	is an option for listing information about a specific machine

Class UMS::ListMachines Content

Name	Type	Description
machines	List of Machine	is a list of machines objects which encapsulates the machines information

Class UMS::ListOptOptions Content

Name	Type	Description
listAllDeftValue	boolean	is an option for listing all default option values defined by VISHNU administrator
userId	string	is an admin option for listing the options of a specific user
optionName	string	allows the user to get the value of a specific option identified by its name

Class UMS::ListOptionsValues Content

Name	Type	Description
optionValues	List of OptionValue	is a list of optionValue objects which encapsulates the optionValue information

Class UMS::ListSessionOptions Content

Name	Type	Description
status	StatusType	specifies the status of the sessions which will be listed
sessionClosePolicy	SessionCloseType	specifies the closure mode of the sessions which will be listed (CLOSE_ON_TIMEOUT or CLOSE_ON_DISCONNECT)
sessionInactivityDelay	int	specifies the inactivity delay in seconds of the sessions which will be listed
machineId	string	allows the user to list sessions opened on a specific machine
adminListOption	boolean	is an admin option for listing all sessions of all users
userId	string	is an admin option for listing sessions opened by a specific user
sessionId	string	allows the user to list all commands launched within a specific session
startDateOption	long	allows the user to organize the commands listed by providing the start date (the UNIX timestamp of the start date is used)
endDateOption	long	allows the user to organize the commands listed by providing the end date (the timestamp of the end date is used). By default, the end date is the current day

Class UMS::ListSessions Content

Name	Type	Description
sessions	List of Session	is the list of session objects

Class UMS::ListUsers Content

Name	Type	Description
users	List of User	is the list of users objects

Class UMS::LocalAccount Content

Name	Type	Description
userId	string	The userId represents the VISHNU user identifier of the user of the local user configuration
machineId	string	The MachineId represents the identifier of the machine associated to the local user configuration

Name	Type	Description
acLogin	string	accLogin represents the login of the user on the associated machine
sshKeyPath	string	sshKeyPath is the path of the ssh key of the user on the associated machine
homeDirectory	string	HomeDirectory is the path of the home directory of the user on the associated machine

Class UMS::Machine Content

Name	Type	Description
machineId	string	represents the identifier of the machine
name	string	represents the name of the machine
site	string	represents the location of the machine
machineDescription	string	represents the description of the machine
language	string	represents the language used for the description of the machine
status	StatusType	represents the status of the machine
sshPublicKey	string	contains the SSH public key used by VISHNU to access local user accounts

Class UMS::OptionValue Content

Name	Type	Description
optionName	string	represents the name of an option
value	string	represents the value of an option

Class UMS::Session Content

Name	Type	Description
sessionId	string	represents the VISHNU session identifier of the session
userId	string	represents the VISHNU user identifier of the user who has opened the session
sessionKey	string	is the key of the session generated by VISHNU
dateLastConnect	long	is the date of the last connection to the session (the UNIX timestamps is used)
dateCreation	long	is the date of the first connection to the session (the UNIX timestamps is used)
dateClosure	long	is the date of the closure of the session (the UNIX timestamps is used)
status	StatusType	represents the status of the session
closePolicy	SessionCloseType	is the way to close the session
timeout	long	is the inactivity delay in seconds associated to the CLOSE_ON_TIMEOUT option

Class UMS::User Content

Name	Type	Description
userId	string	represents the VISHNU user identifier
password	string	is the password of the user. At the beginning, an admin can give a temporary password or it is automatically generated by the System.
firstname	string	is the firstname of the user
lastname	string	is the lastname of the user

Name	Type	Description
privilege	PrivilegeType	is the privilege of the user (admin or simple user)
email	string	is the email of the user
status	StatusType	represents the status of the user

Enumeration UMS::PrivilegeType Type

Name	Value
USER	0
ADMIN	1

Enumeration UMS::SessionCloseType Type

Name	Value
UNDEFINED	0
CLOSE_ON_TIMEOUT	1
CLOSE_ON_DISCONNECT	2

Enumeration UMS::StatusType Type

Name	Value
INACTIVE	0
ACTIVE	1

Chapter 3

API specification for Tasks Management Service (TMS)

3.1 Definition of the functions of the package

3.1.1 Function TMS::submitJob

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	Is the id of the machine where the job must be submitted	IN	yes
scriptFilePath	string	The path to the file containing the characteristics (job command, and batch scheduler directive required or optional) of the job to submit.	IN	yes
jobId	string	Is the returned id of the submitted job	OUT	yes
jobPath	string	Is the path to the file containing job characteristics	OUT	yes
options	SubmitOptions	Is an instance of the class SubmitOptions. Each optionnal value is associated to a set operation (e.g: setNbCpu(...)) in the class SubmitOptions. If no set operation is not called on the instance object options, the job is submitted with the options defined in the scriptFilePath. Otherwise the job is submitted with the optionnal values set by the options object and optionnal values defined in the scriptFilePath, but optionnal values set by SubmitOptions object take precedence over those in scriptFilePath. With in the object options or within the scriptFilePath, the last occurrence of an optionnal value takes precedence over earlier occurrence.	IN	no

Description

The submitJob() function submits job on a machine through the use of a script (scriptFilePath). The script is a shell script which will be executed by a command shell such as sh or csh

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully.
TMS_UNKNOWN_MACHINE	The machine is not known.
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler
TMS_INVALID_PATH	The path to the file containing the characteristics of the job to submit is not a valid path
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_SUBMIT_SERVICE_NOT_AVAILABLE	Indicates that the service to perform the submit operation is not found.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.
TMS_UNKNOWN_QUEUE	Indicates that the specified queue by the user is not known.
DB_ERROR	A problem occurs with the database

Signature

int **submitJob**(const string& sessionKey, const string& machineId, const string& scriptFilePath, string& jobId, string& jobPath, const SubmitOptions& options = SubmitOptions());

3.1.2 Function TMS::getJobInfo

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	Machine hash key	IN	yes
jobId	string	The id of the job	IN	yes
jobInfos	Job	The resulting information on the job	OUT	yes

Description

The getJobInfo() function gets information on a job from its id

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.
VISHNU_OK	The service was performed successfully.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.
TMS_UNKNOWN_MACHINE	The machine is not known.

Name	Description
DB_ERROR	A problem occurs with the database

Signature

```
int getJobInfo(const string& sessionKey, const string& machineId, const string& jobId, Job& jobInfos);
```

3.1.3 Function TMS::getJobProgress**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	Is the id of the machine to get the jobs progression.	IN	yes
progress	Progression	Is the object containing jobs progression information	OUT	yes
options	ProgressOptions	Is an object containing the available options jobs for progression .	IN	no

Description

The getJobProgress() function gets the progression status of jobs

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully.
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_UNKNOWN_MACHINE	The machine is not known.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_SUBMIT_SERVICE_NOT_AVAILABLE	Indicates that the service to perform the submit operation is not found.
DB_ERROR	A problem occurs with the database

Signature

```
int getJobProgress(const string& sessionKey, const string& machineId, Progression& progress, const ProgressOptions& options = ProgressOptions());
```

3.1.4 Function TMS::listQueues**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	Machine hash key	IN	yes
listofQueues	ListQueues	The list of queues	OUT	yes

Description

The listQueues() function gets queues information

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.
VISHNU_OK	The service was performed successfully.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.
TMS_UNKNOWN_MACHINE	The machine is not known.
DB_ERROR	A problem occurs with the database

Signature

```
int listQueues(const string& sessionKey, const string& machineId, ListQueues& listofQueues);
```

3.1.5 Function TMS::listJobs**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	Machine hash key	IN	yes
listOfJobs	ListJobs	The constructed object list of jobs	OUT	yes
options	ListJobsOptions	Additional options for jobs listing	IN	no

Description

The listJobs() function gets a list of all submitted jobs

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.
VISHNU_OK	The service was performed successfully.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.

Name	Description
TMS_UNKNOWN_MACHINE	The machine is not known.
DB_ERROR	A problem occurs with the database

Signature

```
int listJobs(const string& sessionKey, const string& machineId, ListJobs& listOfJobs, const ListJobsOptions& options = ListJobsOptions());
```

3.1.6 Function TMS::getJobOutPut

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	Machine hash key	IN	yes
jobId	string	The Id of the job	IN	yes
outputPath	string	The path of the file containing the output result of the job	OUT	yes
errorPath	string	The path of the file containing the errors that has been occurred during the execution of the job	OUT	yes

Description

The getJobOutPut() function gets outputPath and errorPath of a job from its id

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
VISHNU_OK	The service was performed successfully.
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.
TMS_UNKNOWN_MACHINE	The machine is not known.
DB_ERROR	A problem occurs with the database

Signature

```
int getJobOutPut(const string& sessionKey, const string& machineId, const string& jobId, string& outputPath, string& errorPath);
```

3.1.7 Function TMS::getAllJobsOutPut

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	Machine hash key	IN	yes
listOfResults	ListJobResults	Is the list of jobs results	OUT	yes

Description

The getAllJobsOutPut() function dynamically gets outputPath and errorPath of completed jobs

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
VISHNU_OK	The service was performed successfully.
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.
TMS_UNKNOWN_MACHINE	The machine is not known.
DB_ERROR	A problem occurs with the database

Signature

```
int getAllJobsOutPut(const string& sessionKey, const string& machineId, ListJobResults& listOfResults);
```

3.1.8 Function TMS::cancelJob

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	Machine hash key	IN	yes
jobId	string	The Id of the job	IN	yes
infoMsg	string	The information message	OUT	yes

Description

The cancelJob() function cancels a job from its id

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
TMS_BATCH_SCHEDULER_ERROR	Indicates an error caused by the underlying batch scheduler

Name	Description
TMS_INVALID_RESPONSE	Indicates that the implementation produced a response that does not match the criteria defined by the specification.
TMS_INVALID_REQUEST	Indicates that the request is not valid.
TMS_INVALID_SESSION_KEY	The session key is not valid to perform the service.
TMS_PERMISSION_DENIED	Indicates the requested operation is not allowed for provided user.
VISHNU_OK	The service was performed successfully.
TMS_SERVER_NOT_AVAILABLE	Indicates that the task management server is not available.
TMS_UNKNOWN_BATCH_SCHEDULER_TYPE	Indicates that the batch scheduler type is not known.
TMS_UNKNOWN_MACHINE	The machine is not known.
DB_ERROR	A problem occurs with the database

Signature

int **cancelJob**(const string& sessionKey, const string& machineId, const string& jobId, string& infoMsg);

3.1.9 Function TMS::setMachineEnv

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	Represents the machine id	IN	yes
listEnv	string	Represents the list environnement variables	IN	yes

Description

The setMachineEnv() function sets environment variables on a remote machine

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully.
TMS_UNKNOWN_MACHINE	The machine is not known.

Signature

int **setMachineEnv**(const string& sessionKey, const string& machineId, const string& listEnv);

3.1.10 Function TMS::setMachineRefreshPeriod

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	The id of the machine	IN	yes
value	int	Is the refresh interval value (in seconds)	IN	yes

Description

The setMachineRefreshPeriod() function sets the refresh period of output and error files contents

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service was performed successfully.
TMS_UNKNOWN_MACHINE	The machine is not known.

Signature

```
int setMachineRefreshPeriod(const string& sessionKey, const string& machineId, const int& value);
```

3.2 Data types definitions**Class TMS::Job Content**

Name	Type	Description
sessionId	string	Is the id of the session that contained the job submission command
submitMachineId	string	Is the id of the machine on which the job has been submitted.
submitMachineName	string	Is the name of the machine on which the job has been submitted.
jobId	string	Represents the id to job.
jobName	string	Represents the name assigned to the job.
jobPath	string	Is the path to the file containing job characteristics.
outputPath	string	Is the path to the job output results.
errorPath	string	Is the path to the file containing errors occurred during job's execution.
jobPrio	JobPriority	Represents the job priority.
nbCpus	int	Is the number of cpu used by the job.
jobWorkingDir	string	Indicates the directory where the job has been launched.
status	JobStatus	The current status of the job.
submitDate	long	Date and time when job was submitted (unix timestamp)
endDate	long	Represents the execution end date of the job (unix timestamp)
owner	string	Represents the job owner.
jobQueue	string	Is the name of the queue or class associated to the job.
wallClockLimit	long	Is the maximum wall-clock time during which the job can run (in seconds)
groupName	string	Represents the job owner group name.
jobDescription	string	Is the textual description of the job.
memLimit	int	Represents the memory size limit of the job.
nbNodes	int	Is the total number of nodes used by the job.
nbNodesAndCpuPerNode	string	Is the number of nodes and processors per node used by the job.

Class TMS::JobResult Content

Name	Type	Description
jobId	string	Represents the id of the job.
outputPath	string	Is the path to the job output results.

Name	Type	Description
errorPath	string	Is the path to the file containing errors occurred during job's execution.

Class TMS::ListJobResults Content

Name	Type	Description
nbJobs	string	Is the number of jobs.
Results	List of JobResult	Represents the list of completed jobs results.

Class TMS::ListJobs Content

Name	Type	Description
nbJobs	long	Represents the total number of jobs in the list.
nbRunningJobs	long	Represents of running jobs in the list.
nbWaitingJobs	long	Represents the total number of waiting jobs in the list.
jobs	List of Job	Is a list of job information (jobId, jobName, ...).

Class TMS::ListJobsOptions Content

Name	Type	Description
jobId	string	To list job which has this id.
nbCpu	int	To list jobs which have this number of cpu.
fromSubmitDate	long	List jobs submitted after this date (unix timestamp).
toSubmitDate	long	List jobs submitted before this date (unix timestamp)
owner	string	To list all jobs submitted by this owner.
status	JobStatus	To list jobs which have this status.
priority	JobPriority	To list jobs which have this priority
outPutPath	string	Gets the path and file for each job output.
errorPath	string	Gets the path and file for each job error.
queue	string	To list jobs which have this queue name.

Class TMS::ListQueues Content

Name	Type	Description
nbQueues	int	Represents the number of queues.
queues	List of Queue	Represents the list of queues.

Class TMS::ProgressOptions Content

Name	Type	Description
jobId	string	Represents the id of the job that the user wants to see the progression of.
jobOwner	string	Represents the owner of the job.

Class TMS::Progression Content

Name	Type	Description
jobId	string	Represents the job id.
jobName	string	Represents the job name.
wallTime	int	Represents the job wall time.
startTime	long	Start date and time of the job (unix timestamp)
endTime	long	End date and time of the job (unix timestamp)

Name	Type	Description
percent	double	Represent the job progression.
status	JobStatus	Represents the job status.

Class TMS::Queue Content

Name	Type	Description
name	string	Is the queue name.
maxJobCpu	int	Is the maximum number of Cups that a job can use.
maxProcCpu	int	Is the maximum number of Cpus of the queue.
memory	int	Represents the queue memory size.
wallTime	long	Is the total wallTime of the queue.
node	int	Is the maximum number of nodes of the queue.
nbRunningJobs	int	Is the total running jobs in the queue.
nbJobsInQueue	int	Is the total number of jobs in the queue.
state	QueueStatus	Is the status of the queue.
priority	QueuePriority	Represents the priority of the queue.
description	string	Is the queue description.

Class TMS::SubmitOptions Content

Name	Type	Description
name	string	Assigns a job name. The default is the path of job.
priority	JobPriority	Assigns priority of the job.
queue	string	Assigns the queue or class of the job.
wallTime	int	The maximum wall-clock time during which the job can run.
memory	int	Is the memory size that the job requires.
nbCpu	int	The number of cpu that the job requires.
nbNodesAndCpuPerNode	string	The number of nodes and processors per node.
outPutPath	string	Assigns the path and file for job output.
errorPath	string	Assigns the path and file for job error.

Enumeration TMS::JobPriority Type

Name	Value
VERY_LOW	100
LOW	200
NORMAL	300
HIGH	400
VERY_HIGH	500

Enumeration TMS::JobStatus Type

Name	Value
RUNNING	0
WAITING	1
COMPLETED	2
CANCELED	3
HELD	4
QUEUED	5
FAILED	6
NOT_SUBMITTED	7

Enumeration TMS::QueuePriority Type

Name	Value
VERY_LOW	0
LOW	1
NORMAL	2
HIGH	3
VERY_HIGH	4

Enumeration TMS::QueueStatus Type

Name	Value
STARTED	0
RUNNING	1
NOT_STARTED	2
NOT_AVAILABLE	3

Chapter 4

API specification for Information Management Service (IMS)

4.1 Definition of the functions of the package

4.1.1 Function IMS::exportCommands

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
oldSessionId	string	The id of the session to export (session has ended)	IN	yes
filename	string	The path of the output file containing the Vishnu shell commands	INOUT	yes

Description

The exportCommands() function exports all the commands made by a user during a session

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int exportCommands(const string& sessionKey, const string& oldSessionId, string& filename);
```

4.1.2 Function IMS::getMetricCurrentValue

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	The id of the machine	IN	yes
metricType	MetricType	Type of metric	IN	yes
metricValue	Metric	Value of the metric	OUT	yes

Description

The getMetricCurrentValue() function retrieve the current value of a metric on a machine

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int getMetricCurrentValue(const string& sessionKey, const string& machineId, const MetricType& metricType, Metric& metricValue);
```

4.1.3 Function IMS::getMetricHistory**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	The id of the machine	IN	yes
startTime	long	Start time of metric history	IN	yes
endTime	long	End time of metric history	IN	yes
metricType	MetricType	Type of metric	IN	yes
metricValues	ListMetric	List of metric values	OUT	yes

Description

The getMetricHistory() function retrieve the history of values of a metric on a machine

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int getMetricHistory(const string& sessionKey, const string& machineId, const long& startTime, const long& endTime, const MetricType& metricType, ListMetric& metricValues);
```

4.1.4 Function IMS::getProcesses

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	The id of the machine the user wants the running processes	IN	yes
process	ListProcesses	The list of the Vishnu processes on the machine	OUT	yes

Description

The getProcesses() function gets the list of the processes running over a front machine

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int getProcesses(const string& sessionKey, const string& machineId, ListProcesses& process);
```

4.1.5 Function IMS::setSystemInfo

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	The id of the machine	IN	yes
systemInfo	SystemInfo	Contains system information to store in Vishnu database	IN	yes

Description

The setSystemInfo() function updates the system information of a machine

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int setSystemInfo(const string& sessionKey, const string& machineId, const SystemInfo& systemInfo);
```

4.1.6 Function IMS::setSystemThreshold

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	The id of the machine	IN	yes
thresholdType	MetricType	The type of the metric to set	IN	yes
value	double	The threshold value	IN	yes

Description

The setSystemThreshold() function sets a threshold on a machine of a system

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int setSystemThreshold(const string& sessionKey, const string& machineId, const MetricType& thresholdType, const double& value);
```

4.1.7 Function IMS::getSystemThreshold

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	The id of the machine	IN	yes
type	MetricType	The threshold type desired	IN	yes
value	double	The threshold value	OUT	yes

Description

The getSystemThreshold() function gets a System threshold on a machine

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int getSystemThreshold(const string& sessionKey, const string& machineId, const MetricType& type, double& value);
```

4.1.8 Function IMS::defineUserIdentifier**Access**

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
format	string	The new format to use	IN	yes

Description

The defineUserIdentifier() function defines the shape of the identifiers automatically generated for the users

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
INVALID_PARAMETER	If a parameter is invalid
DB_ERROR	The database generated an error

Signature

```
int defineUserIdentifier(const string& sessionKey, const string& format);
```

4.1.9 Function IMS::defineMachineIdentifier**Access**

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
format	string	The new format to use	IN	yes

Description

The defineMachineIdentifier() function defines the shape of the identifiers automatically generated for the machines

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int defineMachineIdentifier(const string& sessionKey, const string& format);
```

4.1.10 Function IMS::defineJobIdentifier

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
format	string	The new format to use	IN	yes

Description

The defineJobIdentifier() function defines the shape of the identifiers automatically generated for the jobs

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int defineJobIdentifier(const string& sessionKey, const string& format);
```

4.1.11 Function IMS::defineTransferIdentifier

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
format	string	The new format to use	IN	yes

Description

The defineTransferIdentifier() function defines the shape of the identifiers automatically generated for the file transfers

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int defineTransferIdentifier(const string& sessionKey, const string& format);
```


4.1.12 Function IMS::loadShed

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
machineId	string	The id of the machine to stop	IN	yes
loadShedType	LoadShedType	Selects a load shedding mode (SOFT: stops all services and they can be restarted, HARD: stops all services, they cannot be restarted)	IN	yes

Description

The loadShed() function load sheds a machine

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
COMPONENT_ERROR	If a component is unavailable
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int loadShed(const string& sessionKey, const string& machineId, const LoadShedType& loadShedType);
```

4.1.13 Function IMS::setUpdateFrequency

Access

This function can be used by ADMIN users only

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
freq	int	Frequency the data are updated, in second	IN	yes

Description

The setUpdateFrequency() function sets the update frequency of the IMS tables

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int setUpdateFrequency(const string& sessionKey, const int& freq);
```

4.1.14 Function IMS::getUpdateFrequency

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
freq	int	Frequency the data are updated, in second	OUT	yes

Description

The getUpdateFrequency() function gets the update frequency of the IMS database

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	Error code returned if success
DB_ERROR	The database generated an error
INVALID_PARAMETER	If a parameter is invalid

Signature

```
int getUpdateFrequency(const string& sessionKey, int& freq);
```

4.2 Data types definitions

Class IMS::ListMetric Content

Name	Type	Description
metric	List of Metric	The metrics of the list

Class IMS::ListProcesses Content

Name	Type	Description
processName	List of string	The Vishnu processes of the list

Class IMS::Metric Content

Name	Type	Description
type	MetricType	The type of the metric
value	double	The value of the metric
time	int	The timestamp the metric had the value

Class IMS::SystemInfo Content

Name	Type	Description
memory	long	Amount of RAM memory available on the machine (in Bytes)

Name	Type	Description
diskSpace	long	Amount of disk space available on the machine (in Bytes)

Enumeration IMS::LoadShedType Type

Name	Value
SOFT	0
HARD	1

Enumeration IMS::MetricType Type

Name	Value
CPUNBR	0
CPUUSE	1
DISKSPACE	2
FREEDISKSPACE	3
MEMORY	4
FREEMEMORY	5

Chapter 5

API specification for File Management Service (FMS)

5.1 Definition of the functions of the package

5.1.1 Function FMS::createFile

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file to create following the pattern [host:]file path	IN	yes
mode	int	The file access permissions in octal numeral system	IN	no

Description

The createFile() function creates files on remote machines.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed succesfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

Signature

```
int createFile(const string& sessionKey, const string& path, const int& mode = 644);
```

5.1.2 Function FMS::createDir

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The directory to create following the pattern [host:]directory path	IN	yes
mode	int	the new directories permission access in octal numeral system	IN	no

Description

The createDir() function creates directories on remote machines.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed succesfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

Signature

```
int createDir(const string& sessionKey, const string& path, const int& mode = 755);
```

5.1.3 Function FMS::removeFile

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file to remove following the pattern [host:]file path	IN	yes

Description

The removeFile() function removes files from remote hosts.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed succesfully.

Name	Description
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

Signature

```
int removeFile(const string& sessionKey, const string& path);
```

5.1.4 Function FMS::removeDir**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The directory to remove following the pattern [host:]directory path	IN	yes

Description

The removeDir() function removes directories (and subdirectories) from remote machines.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed succesfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

Signature

```
int removeDir(const string& sessionKey, const string& path);
```

5.1.5 Function FMS::chGrp**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file/directory following the pattern [host:]file path	IN	yes
group	string	the new group owner of file/directory	IN	yes

Description

The chGrp() function changes group owner of remote files/directories.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed succesfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

Signature

```
int chGrp(const string& sessionKey, const string& path, const string& group);
```

5.1.6 Function FMS::chMod

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file/directory following the pattern [host:]file path	IN	yes
mode	int	the access rights of file/directory in octal system.	IN	yes

Description

The chMod() function changes access rights of remote files/directories.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed succesfully.
INVALID_SESSION_KEY	Invalid provided session key.
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.

Signature

```
int chMod(const string& sessionKey, const string& path, const int& mode);
```

5.1.7 Function FMS::headOfFile**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file following the pattern [host:]file path	IN	yes
fileContent	string	The first "nLine" lines of the file	OUT	yes
nLine	int	Number of lines to display	IN	no

Description

The headOfFile() function displays a few first lines of files located on remote machines.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed succesfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

Signature

```
int headOfFile(const string& sessionKey, const string& path, string& fileContent, const int& nLine = 10);
```

5.1.8 Function FMS::tailOfFile**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file following the pattern [host:]file path	IN	yes
fileContent	string	The last "nLine" lines of the file	OUT	yes
nLine	int	number of lines to display	IN	no

Description

The tailOfFile() function displays a few last lines of files located on remote machines

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed succesfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

Signature

```
int tailOfFile(const string& sessionKey, const string& path, string& fileContent, const int& nLine = 10);
```

5.1.9 Function FMS::contentOfFile**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The file to display following the pattern [host:]file path	IN	yes
fileContent	string	The content of the file	OUT	yes

Description

The contentOfFile() function displays content of files located on remote machines

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
VISHNU_OK	The service has been performed succesfully.
INVALID_SESSION_KEY	Invalid provided session key.
INVALID_MACHINE_ID	Invalid provided machine identifier.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
FMS_PERMISSION_DENIED	User does not have permission access.
DB_ERROR	A problem occurs with the database.

Signature

```
int contentOfFile(const string& sessionKey, const string& path, string& fileContent);
```

5.1.10 Function FMS::listDir**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
path	string	The directory to list following the pattern [host:]directory path	IN	yes
dirContent	StringList	The content of the directory (only files names with short format, all files informations with long format)	OUT	yes
options	LsDirOptions	List of options for the listDir command	IN	no

Description

The listDir() function displays the content of a remote directory.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

Signature

```
int listDir(const string& sessionKey, const string& path, StringList& dirContent, const LsDirOptions& options = LsDirOptions());
```

5.1.11 Function FMS::copyFile

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
src	string	The source file to copy following the pattern [host:]file path	IN	yes
dest	string	The path of the destination file	IN	yes
options	CopyFileOptions	the copy options	IN	no

Description

The copyFile() function executes a synchronous copy of file.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed succesfully.

Signature

```
int copyFile(const string& sessionKey, const string& src, const string& dest, const CopyFileOptions& options = CopyFileOptions());
```

5.1.12 Function FMS::copyAsyncFile

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
src	string	The source file to copy following the pattern [host:]file path	IN	yes
dest	string	The path of the destination file	IN	yes
thrId	long	A file tranfer identifier (allowing for instance to ckeck the status of a file transfer, or to cancel it)	OUT	yes
options	CopyFileOptions	the copy options	IN	no

Description

The copyAsyncFile() function executes an asynchronous copy of file.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed succesfully.

Signature

```
int copyAsyncFile(const string& sessionKey, const string& src, const string& dest, long& thrId, const CopyFileOptions& options = CopyFileOptions());
```

5.1.13 Function FMS::moveFile

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
src	string	The source file to move following the pattern [host:]file path	IN	yes
dest	string	The path of the destination file	IN	yes
options	MvFileOptions	The move command options	IN	no

Description

The moveFile() function executes a synchronous move of file.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

Signature

```
int moveFile(const string& sessionKey, const string& src, const string& dest, const MvFileOptions& options = MvFileOptions());
```

5.1.14 Function FMS::moveAsyncFile

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
src	string	The source file to move following the pattern [host:]file path	IN	yes
dest	string	The path of the destination file	IN	yes
thrId	long	The file transfer identifier (allowing for instance to check the status of a file transfer, or to cancel it)	OUT	yes
options	MvFileOptions	The mv command options	IN	no

Description

The moveAsyncFile() function executes an asynchronous move of file.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

Signature

```
int moveAsyncFile(const string& sessionKey, const string& src, const string& dest, long& thrId, const MvFileOptions& options = MvFileOptions());
```

5.1.15 Function FMS::stopFileTransfer**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
options	StopTransferOptions	The stop file transfer command options	IN	no

Description

The stopFileTransfer() function stops an execution of a set of file transfers.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

Signature

```
int stopFileTransfer(const string& sessionKey, const StopTransferOptions& options = StopTransferOptions());
```

5.1.16 Function FMS::listFileTransferStatus**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
options	LsTrStatusOptions	The filter options	IN	no

Description

The listFileTransferStatus() function displays the status of all file transfers submitted by User.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

Signature

```
int listFileTransferStatus(const string& sessionKey, const LsTrStatusOptions& options = LsTrStatusOptions());
```

5.1.17 Function FMS::listFileTransfers

Access

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
options	LsTransferOptions	The filter options	IN	no

Description

The listFileTransfers() function displays the history of all file transfers submitted by User.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.

Name	Description
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

Signature

```
int listFileTransfers(const string& sessionKey, const LsTransferOptions& options = LsTransferOptions());
```

5.1.18 Function FMS::getFilesInfo**Access**

This function can be used by any VISHNU user

Parameters

Parameter	Type	Description	Mode	Required
sessionKey	string	The session key	IN	yes
pathList	string	The file whose inode information will be displayed	IN	yes
filesinfo	FileStat	The inode information	OUT	yes

Description

The getFilesInfo() function displays the information of files.

Return Value

An error code is returned when an error occurs during the execution of the function

Name	Description
DB_ERROR	A problem occurs with the database.
FMS_INVALID_CFG_FILE	Option unknown in the config file.
FMS_INVALID_PARAMETER	an option or a parameter provided is invalid for this service.
FMS_INVALID_PATH	The path provided is invalid.
FMS_PERMISSION_DENIED	User does not have permission access.
FMS_SERVER_UNAVAILABLE	The FMS server is unavailable.
INVALID_MACHINE_ID	Invalid provided machine identifier.
INVALID_SESSION_KEY	Invalid provided session key.
VISHNU_OK	The service has been performed successfully.

Signature

```
int getFilesInfo(const string& sessionKey, const string& pathList, FileStat& filesinfo);
```

5.2 Data types definitions**Class FMS::CopyFileOptions Content**

Name	Type	Description
isRecursive	boolean	It specifies when the copy is recursive (case of directory) or not.
trCommand	TransferCommand	the command to use to perform file transfer.

Class FMS::FileStat Content

Name	Type	Description
path	string	The path of the file
owner	string	The name of the owner of the file
group	string	The group name of the owner
uid	long	The user identifier of the owner
gid	long	The group identifier of the owner
size	long	The size of the file in bytes
atime	long	The time of last access
mtime	long	The time of last modification
ctime	long	The time of the last change of the inode information
type	FileType	The file type

Class FMS::LsDirOptions Content

Name	Type	Description
longFormat	boolean	It specifies the long display format (all available file informations)
allFiles	boolean	Allows to display all files including hidden files

Class FMS::LsTrStatusOptions Content

Name	Type	Description
transferId	string	a given transfer id
fromMachineId	string	the machine that is the source of the file transfer
userId	string	allows the admin to list file transfers initiated by a specific user

Class FMS::LsTransferOptions Content

Name	Type	Description
fromMachineId	string	the machine that is the source of the file transfer
userId	string	allows the admin to list file transfers initiated by a specific user
status	Status	the file transfer status

Class FMS::MvFileOptions Content

Name	Type	Description
trCommand	TransferCommand	the command to use to perform file transfer.

Class FMS::StopTransferOptions Content

Name	Type	Description
transferId	string	a given transfer id
fromMachineId	string	the machine that is the source of the file transfer
userId	string	allows an admin to stop file transfers of a specific user

Class FMS::StringList Content

Name	Type	Description
listOfStrings	List of string	the dynamic list of strings.

Enumeration FMS::FileType Type

Name	Value
BLOCK	0
CHARACTER	1
DIRECTORY	2
SYMBOLICLINK	3
SCKT	4
FIFO	5
REGULAR	6

Enumeration FMS::Status Type

Name	Value
INPROGRESS	0
COMPLETED	1
CANCELLED	2
FAILED	3

Enumeration FMS::TransferCommand Type

Name	Value
SCP	0
RSYNC	1