


2D

You design applications in the **2D** view by opening component files and placing instances of **2D components** and **assets** into them.












When you select component instances in the **2D** view, markers appear around their edges and in their corners. Depending on the shape of the cursor, you can apply the following actions to the component instances by dragging them:

- > Move
- > Resize
- > Rotate

Summary of 2D View Buttons


The **2D** view toolbar contains the following buttons and fields.

Button/Field	Tooltip	Read More
--------------	---------	-----------

	Anchors the component instance to the component instances that it is snapped to.	Snapping to Parent and Sibling Components
	Snaps component instances to their parent or siblings when you align them.	Snapping to Parent and Sibling Components
	Hides and shows component instance boundaries.	Hiding Component Boundaries
Override Width	Shows a preview of the component using the specified width.	Previewing Component Size
Override Height	Shows a preview of the component using the specified height.	Previewing Component Size
	Sets the color of the the 2D view working area.	Setting Canvas Color
	Zooms in.	Zooming
	Zooms out.	Zooming
Zoom level	Sets the zoom level that you select from the list.	Zooming
	Zooms to fit all content.	Zooming
	Zooms to fit the current selection.	Zooming
	Refreshes the contents of the 2D view.	Refreshing 2D View Contents


Moving Components

When the move cursor is displayed, you can move the selected component instance to any position in the 2D view.



For more information about alternative ways of positioning component instances in UIs, see [Scalable Layouts](#).

Resizing 2D Components




To have the resizing done from the center of the selected component instance rather than from its edges, press **Alt** (or **Opt** on macOS).


To preserve the image aspect ratio while resizing when using the corner markers, press **Shift**. This also works on component instances that are anchored using left, right, top, or bottom anchors.

To both resize from the center of the component instance and preserve the aspect ratio, press **Alt+Shift** (or **Opt+Shift** on macOS).

For more information about alternative ways to specify the size of a component or component instance in a UI, see [2D Geometry](#).

Rotating 2D Components


When the rotation cursor  is displayed in one of the corners of a component instance, you can drag clockwise or counter-clockwise to freely rotate the component instance around its origin.





Additionally, press **Shift** or **Alt** (or **Opt** on macOS) to rotate component instances in steps of 5 or 45 degrees, respectively.

You can set the **origin** in **Properties > Geometry - 2D > Origin**. There, you can also enter the value of the **Rotation** property in degrees.


Zooming



Snapping to Parent and Sibling Components


You can use snapping to align component instances in the **2D** view. Select the  button to have the component instances snap to their parent or siblings. Snapping lines automatically appear to help you position the component instances. Click the  button to anchor the selected component instance to those that you snap to. Only one snapping button can be selected at the time. Selecting one snapping button automatically deselects the others.

Choose **Edit > Preferences > Qt Quick > Qt Quick Designer** to specify settings for snapping. In the **Parent component padding** field, specify the distance in pixels between the parent and the snapping lines. In the **Sibling component spacing** field, specify the distance in pixels between siblings and the snapping lines.



The following image shows the snapping lines (1) when **Parent component padding** is set to 5 pixels.





For alternative ways of aligning and distributing component instances by using the [Properties](#) view, see [Aligning and Distributing Components](#).


Hiding Component Boundaries

The **2D** view displays the boundaries of component instances. To hide them, select the  button.

Previewing Component Size

The width and height of the root component in a UI file determine the size of the component. You can reuse components, such as buttons, in different sizes in other UI files and design UIs for use with different device profiles, screen resolution, or screen orientation. The component size might also be zero (0,0) if its final size is determined by [property bindings](#).

To experiment with different component sizes, enter values in the **Override Width** and **Override Height** fields (1) on the toolbar. The changes are displayed in the **2D** view (2) and in the **States** view (3), but the property values are not changed permanently in the UI file. You can permanently change the property values in the **Properties** view (4).





To set the initial size of the root component, select **Edit > Preferences > Qt Quick > Qt Quick Designer** and specify the component width and height in the **Root Component Init Size** group.

Specifying Canvas Size

To change the canvas size, select **Edit > Preferences > Qt Quick > Qt Quick Designer** and specify the canvas width and height in the **Canvas** group.

Setting Canvas Color

If you set the background of the root component transparent, the color of the working area can make it difficult to see the component instance you are working on. To make component instances more visible, you can select the canvas color in the  list. By default, the color is transparent. Setting the canvas color does not affect the background color of your root component or component instances in any way.



Refreshing 2D View Contents

When you open a UI file, the component defined in the file and the component instances it contains are drawn in the **2D** view. When you edit component instance properties in **Properties**, the code and its representation in the **2D** view might get out of sync. For example, when you change the position of a component instance within a column or a row, the new position might not be displayed correctly in the **2D** view.

To refresh the contents of the **2D** view, press **R** or select the  (**Reset View**) button.

Context Menu

The following table summarizes the **Navigator** and **2D** views context menu items and provides links to more information about them.

To Learn About	Go To
Arrange	Arranging Components
Edit	Showing and Hiding Components
Anchors	Setting Anchors and Margins
Group	Organizing Components



Layout	Using Layouts
Stacked Container	Lists and Other Data Models
Timeline	Creating a Timeline
Event List	Simulating Events
Edit Color	Editing Properties Inline
Edit Annotation	Annotating Designs
Merge File with Template	Merging Files with Templates
Move Component Instances into Separate Files	Turning Component Instances into Custom Components
Add New Signal Handler	Adding Signal Handlers
Go to Implementation	Using UI Files
Go into Component	Moving Within Components

< Design Views

3D >



Contact Us

Company

- About Us
- Investors
- Newsroom
- Careers
- Office Locations

Support

- Support Services
- Professional Services
- Partners
- Training

Licensing

- Terms & Conditions
- Open Source
- FAQ

For Customers

- Support Center
- Downloads
- Qt Login
- Contact Us
- Customer Success



Community

- Contribute to Qt
- Forum
- Wiki
- Downloads
- Marketplace

© 2022 The Qt Company

[Feedback](#) [Sign In](#)