


# Detecting Memory Leaks with Heob

Qt Creator integrates the [Heob](#) heap observer for detecting buffer overruns and memory leaks. You must download and install Heob to run it from Qt Creator.



To run Heob on the currently open project:

1. Select **Analyze > Heob**.
2. Select the Heob settings profile to use, or select **New** to create a new profile.
3. In the **Heob path** field, enter the path to the Heob executable.
4. Specify additional settings for running the checks. For more information about the available options, see [Specifying Heob Settings](#).
5. Select **OK** to run Heob.


Qt Creator runs the application, and then it runs Heob in a console window.



PID: 6276

leak recording: ☒ on ☐ off  

Heob raises an access violation on buffer overruns and provides stack traces of the offending instruction and buffer allocation. The results are displayed when Heob exits normally.



## Specifying Heob Settings

To specify settings for Heob, select **Analyze > Heob**.

In the **Extra arguments** field, enter additional arguments for running Heob. To list the available arguments in the Heob console, enter `-H` in this field and press **Enter**.

For example, use the `-o leaks.html` option to record leak data in an HTML file. Together with this option, you can use the `-g2` option to group the leaks visually in the file and the `-L1024` option to record leak contents up to 1024 bytes in the file. For example, `-o leaks.html -g2 -L1024`

To save the settings profile, select **Save**.

To remove a customized settings profile, select the profile, and then select **Delete**.

The following sections describe the available options in more detail.

## Recording Results

The results of the checks are displayed in the **Memcheck** view and recorded in a file. You can specify the file name in the **XML output file** field. Heob creates the file in the project directory.

You can use the process identifier (PID) as a variable in the file name. For example, `leaks-%p.xml`. This injects Heob into the child processes, as well.

Other variables you can use are `%P` for the parent PID and `%n` for the application name.

If you use variables, Qt Creator cannot open the file automatically, but you can open it from the project directory.

## Handling Exceptions

In the **Handle exceptions** list, select **Off** to use the standard exception handler and have the debugger automatically attached if the application crashes. This works only if you register Qt Creator as a post-mortem debugger by selecting **Edit > Preferences > Debugger > General > Use Qt Creator for post-mortem debugging**.

Select **On** to use the Heob exception handler that checks the reason and location of the crash and detects whether

Select **Only** to disable all Heob functions, except installing the exception handler. If the application crashes, only a stack trace of the crash is displayed. Therefore, this option is mostly useful when using Heob on the console or running it for child processes, as well.

## Raising Exceptions on Errors

Select the **Raise breakpoint exception on error** check box to display errors when the application runs.

If the option is disabled, errors such as *double free*, *free of invalid pointer*, and *not enough memory* just write all collected data into the results file and you will only see them at the end of the application run.

If the option is enabled, the application stops at the error location. This is mostly useful when used with the **Run with debugger** option, which runs Heob under the debugger.

## Protecting Pages

In the **Page protection** list, select **Off** to use standard memory allocation functions and enable only memory leak detection.

Select **After** to place a protected page at the end of each allocated block and throw an exception if it is accessed. Select **Before** to place a protected page before each allocated block. These options consume memory and slow down the checks, and are therefore recommended only for 64-bit or short-running programs.

Select **Freed memory protection** to protect all allocation pages when freed, so that their address space can never be used again. This is useful for *use-after-free* and *double-free* detection. However, the available memory address space can run out fast for 32-bit programs.

## Handling Leak Data

In the **Leak details** list, determine how to handle the collected leak data when the process exits. Selecting **None** means that no leak data is collected. If you activate leak type detection, Heob might need more time to collect the data when the process exits.

Select **Simple** to write all memory that was not freed into the results file.

Select **Detect Leak Types** to parse all static and global memory blocks for references to the leaks. The reachable blocks are marked *reachable* and recursively checked for other references. If references are found, the blocks are marked *indirectly reachable*. The remaining blocks are checked for references to each other and marked either *indirectly lost* or *jointly lost* (if the blocks reference each other). The blocks that have no references at all are marked *lost*. Select **Detect Leak Types (Show Reachable)** to also record the the reachable blocks in the results file.

Select **Fuzzy Detect Leak Types** to mark memory blocks *reachable* or *indirectly lost* if they contain references to any address. This option is useful when used with some custom allocators (such as `av_malloc()` in `ffmpeg`) that keep only an address somewhere inside the allocation block and do not refer directly to the start of an allocated block. Select **Detect Leak Types (Show Reachable)** to also record the reachable blocks in the results file.

In the **Minimum leak size** list, select the size of leaks to detect in bytes.

In the **Control leak recording** list, select **Off** to record all leaks. You cannot change leak recording while it is running.

To start Heob without starting leak recording, select **On (Start Disabled)**. In the Heob console, turn recording **on** or **off**, **clear** all results, or select **show** to record all current leaks into the results file. Open the file to see its contents before the process exits.

To start leak recording when Heob starts and still have the option to control the recording, select **On (Start Enabled)**.



© 2022 The Qt Company Ltd. Documentation contributions included herein are the copyrights of their respective owners. The documentation provided herein is licensed under the terms of the [GNU Free Documentation License version 1.3](#) as published by the Free Software Foundation. Qt and respective logos are trademarks of The Qt Company Ltd in Finland and/or other countries worldwide. All other trademarks are property of their respective owners.



Contact Us

Company

- About Us
- Investors
- Newsroom
- Careers
- Office Locations

Licensing

- Terms & Conditions
- Open Source
- FAQ

Support

- Support Services
- Professional Services
- Partners
- Training

For Customers

- Support Center
- Downloads
- Qt Login
- Contact Us
- Customer Success

Community

- Contribute to Qt
- Forum
- Wiki
- Downloads
- Marketplace