



# Backup and Recovery Tool

Version 2.5.9

1	EDB Postgres Backup and Recovery Installation Guide	4
1.1	Installing BART	4
1.2	Configuring BART	12
1.3	Upgrading BART	27
2	Quick Start Guide for RHEL/CentOS 7	29
3	Quick Start Guide for RHEL/CentOS 8	35
4	EDB Postgres Backup and Recovery Reference Guide	40
4.1	BART Subcommand Syntax and Examples	41
4.1.1	BACKUP	43
4.1.2	CHECK-CONFIG	47
4.1.3	DELETE	48
4.1.4	INIT	51
4.1.5	MANAGE	56
4.1.6	RESTORE	61
4.1.7	SHOW-SERVERS	64
4.1.8	SHOW-BACKUPS	66
4.1.9	VERIFY-CHKSUM	68
4.1.10	Running the BART WAL Scanner	69
4.2	Additional Examples	72
4.3	Sample BART System with Local and Remote Database Servers	98
5	EDB Postgres Backup and Recovery User Guide	122
5.1	Introduction	122
5.2	Overview	124
5.2.1	Block-Level Incremental Backup	126
5.2.1.1	Incremental Backup Limitations and Requirements	126
5.2.1.2	Concept Overview	127
5.2.1.3	WAL Scanning – Preparation for an Incremental Backup	128
5.2.1.4	Performing an Incremental Backup	129
5.2.1.5	Restoring an Incremental Backup	131
5.2.2	Creating a Backup Chain	132
5.3	Using BART	133
5.3.1	BART Management Overview	133
5.3.1.1	Performing a Restore Operation	134
5.3.1.2	Point-In-Time Recovery Operation	135
5.3.2	Managing Backups Using a Retention Policy	136
5.3.2.1	Overview - Managing Backups Using a Retention Policy	137
5.3.2.2	Marking the Backup Status	138
5.3.2.3	Setting the Retention Policy	138
5.3.2.4	Managing the Backups Based on the Retention Policy	140
5.3.2.5	Managing Incremental Backups	142
5.3.3	Basic BART Subcommand Usage	143
5.3.3.1	CHECK-CONFIG	144
5.3.3.2	INIT	145
5.3.3.3	BACKUP	147
5.3.3.4	SHOW-SERVERS	150
5.3.3.5	SHOW-BACKUPS	151
5.3.3.6	VERIFY-CHKSUM	151
5.3.3.7	MANAGE	152

5.3.3.8	RESTORE	154
5.3.3.9	DELETE	156
5.3.4	Running the BART WAL Scanner	157
5.4	Using Tablespaces	159

# 1 EDB Postgres Backup and Recovery Installation Guide

This guide provides information about how to install and configure the EDB Backup and Recovery Tool (BART) 2.5.

## Requirements Overview

### Supported Platforms and Database Versions

- To view a complete list of platforms that EDB supports, visit the [EDB website](#).

!!! Note BART 2.5 does not support CentOS/RHEL/OEL 6.x platforms. EDB recommends migrating the EDB products running on these platforms to a supported platform.

- BART supports the following database versions:
  - Advanced Server versions 9.6, 10, 11, and 12.
  - PostgreSQL versions 9.6, 10, 11, and 12.

### Software Requirements

You require the following components to install BART.

- BART Host Components - Use EDB packages to add BART host components; see [Installing BART](#) for information about how to install these components.
- Additional Components - In addition to the BART host components, the following components are required:
  - The [Secure Shell \(SSH\) server daemon and Secure Copy \(SCP\) client programs](#) must be enabled and activated on the BART host as well as on the remote database server hosts on which BART will be managing backup and recovery.
  - BART uses the `pg_basebackup` utility program when taking full backups.

### Limitation

BART supports taking only a full backup of standby servers; it does not support taking incremental or parallel backups of standby servers.

## 1.1 Installing BART

This section will walk you through performing a fresh installation of BART on a host. Installation instructions are organized into the following platform/installer specific sections:

- [Installing BART on a CentOS Host](#)
- [Installing BART on a RHEL Host](#)
- [Installing BART on a RHEL/CentOS 7 PPCLE Host](#)
- [Installing BART on a Debian or Ubuntu Host](#)
- [Installing BART on an SLES 12 Host](#)

!!! Note If you are using the pdf version of this document, using the cut/paste command to copy may result in extra spaces or carriage returns in the pasted command. If a command fails, check the command carefully for additional characters.

## Installing BART on a CentOS Host

The following section demonstrates installing BART on a CentOS host using an RPM package. This section assumes that the user has some knowledge of installation and system administration procedures, and has administrative privileges on the host.

1. To install the repository configuration, assume superuser privileges and invoke one of the following platform-specific commands:

On CentOS 7:

```
yum -y install https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

On CentOS 8:

```
dnf -y install https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

2. Replace the `USERNAME:PASSWORD` in the following command with the username and password of a registered EnterpriseDB user:

```
sed -i "s@<username>:<password>@USERNAME:PASSWORD@" /etc/yum.repos.d/edb.repo
```

To request credentials for the repository, visit the [EDB website](#).

3. Before installing BART, execute the following command to install the Extra Packages for Enterprise Linux (EPEL) release package:

On CentOS 7:

```
yum -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
```

On CentOS 8:

```
dnf -y install epel-release
```

4. For CentOS 8, enable the PowerTools repository to satisfy EPEL package dependencies:

```
dnf config-manager --set-enabled PowerTools
```

5. For CentOS 8, disable the built-in PostgreSQL module:

```
dnf -qy module disable postgresql
```

6. Optionally, install the `pg_basebackup` utility program using the server client package. If you do not already have the `pg_basebackup` program installed on the BART host, you can install a limited number of files that include the `pg_basebackup` program by invoking the following command:

On CentOS 7:

```
yum install edb-as<xx>-server-client
```

On CentOS 8:

```
dnf install edb-as<xx>-server-client
```

In the above command, replace `<xx>` with the required Advanced Server version. The `pg_basebackup` version must be the same or more recent than the database server to be backed up. For example, `pg_basebackup` version 10 can be used to back up database server version 10, but cannot be used to back up database server version 11.

7. Use the following command to install BART:

On CentOS 7:

```
yum -y install edb-bart-2.5.9
```

On CentOS 8:

```
dnf -y install edb-bart-2.5.9
```

Repeat the installation process described in this section to install BART on each remote host on which an incremental backup is to be restored.

To verify the BART installation, navigate to the `/usr/edb/bart/bin` directory and execute the following command:

```
bart --version
```

The `bart --version` command should return the current BART version. If the `bart --version` command returns an error stating the PATH is not available after switching from the root user to another BART user account, adjust the setting of the `PATH` environment variable to include the directory location of the BART `bin` subdirectory in the `~/.bashrc` or `~/.bash_profile` files of the following user accounts:

- The BART user account on the BART host. See [Configuring BART](#) for details.
- The remote user account on the remote host to which incremental backups are to be restored. For details, see the *EDB Backup and Recovery User Guide* available at the [EDB website](#).

Upon successful installation, BART is installed in the `BART_HOME` directory:

```
/usr/edb/bart
```

The installation includes the following files:

File Name	Location	Description
bart	<code>&lt;BART_HOME&gt;/bin</code>	BART command line, executable program
bart-scanner	<code>&lt;BART_HOME&gt;/bin</code>	BART WAL scanner program
bart.cfg.sample	<code>&lt;BART_HOME&gt;/etc</code>	Sample BART configuration file
xlogreader_ident.so	<code>&lt;BART_HOME&gt;/lib</code>	Libraries supporting WAL versions

File Name	Location	Description
bart_license.txt	<BART_HOME>	License agreement

After BART is installed successfully, you need to [configure the installation](#).

## Installing BART on a RHEL Host

The following section demonstrates installing BART on a RHEL host using an RPM package. This section assumes that the user has some knowledge of installation and system administration procedures, and has administrative privileges on the host.

1. To install the repository configuration, assume superuser privileges and invoke one of the following platform-specific commands:

On RHEL 7:

```
yum -y install https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

On RHEL 8:

```
dnf -y install https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

2. Replace the `USERNAME:PASSWORD` in the following command with the username and password of a registered EnterpriseDB user:

```
sed -i "s@<username>:<password>@USERNAME:PASSWORD@" /etc/yum.repos.d/edb.repo
```

To request credentials for the repository, visit the [EDB website](#).

3. Before installing BART, execute the following command to install the Extra Packages for Enterprise Linux (EPEL) release package:

On RHEL 7:

```
yum -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
```

On RHEL 8:

```
dnf -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-8.noarch.rpm
```

4. Enable the repository:

On RHEL 7, enable the `optional`, `extras`, and `HA` repositories to satisfy EPEL package dependencies:

```
subscription-manager repos --enable "rhel-*-optional-rpms" --enable "rhel-*-extras-rpms" --enable "rhel-ha-for-rhel-*-server-rpms"
```

On RHEL 8, enable the `codeready-builder-for-rhel-8-*-rpms` repository to satisfy EPEL packages dependency:

```
ARCH=$( /bin/arch )
```

```
subscription-manager repos --enable "codeready-builder-for-rhel-8- $\${ARCH}$ -rpms"
```

- For RHEL 8, disable the built-in PostgreSQL module:

```
dnf -qy module disable postgresql
```

- Optionally, install the `pg_basebackup` utility program using the server client package. If you do not already have the `pg_basebackup` program installed on the BART host, you can install a limited number of files that include the `pg_basebackup` program by invoking the following command:

On RHEL 7:

```
yum install edb-as<xx>-server-client
```

On RHEL 8:

```
dnf install edb-as<xx>-server-client
```

In the above command, replace `<xx>` with the required Advanced Server version. The `pg_basebackup` version must be the same or more recent than the database server to be backed up. For example, `pg_basebackup` version 10 can be used to back up database server version 10, but cannot be used to back up database server version 11.

- Use the following command to install the BART:

On RHEL 7:

```
yum -y install edb-bart-2.5.9
```

On RHEL 8:

```
dnf -y install edb-bart-2.5.9
```

Repeat the installation process described in this section to install BART on each remote host on which an incremental backup is to be restored.

To verify the BART installation, navigate to the `/usr/edb/bart/bin` directory and execute the following command:

```
bart --version
```

The `bart --version` command should return the current BART version. If the `bart --version` command returns an error stating the PATH is not available after switching from the root user to another BART user account, adjust the setting of the `PATH` environment variable to include the directory location of the BART `bin` subdirectory in the `~/.bashrc` or `~/.bash_profile` files of the following user accounts:

- The BART user account on the BART host. See [Configuring BART](#) for details.
- The remote user account on the remote host to which incremental backups are to be restored. For details, see the *EDB Backup and Recovery User Guide* available at the [EDB website](#).

Upon successful installation, BART is installed in the `BART_HOME` directory:

```
/usr/edb/bart
```

The installation includes the following files:



File Name	Location	Description
bart	<BART_HOME>/bin	BART command line, executable program
bart-scanner	<BART_HOME>/bin	BART WAL scanner program
bart.cfg.sample	<BART_HOME>/etc	Sample BART configuration file
xlogreader_ident.so	<BART_HOME>/lib	Libraries supporting WAL versions
bart_license.txt	<BART_HOME>	License agreement

After BART is installed successfully, you need to [configure the installation](#).

## Installing BART on a RHEL/CentOS 7 PPCLE Host

The following section demonstrates installing BART on a RHEL host using an RPM package. This section assumes that the user has some knowledge of installation and system administration procedures, and has administrative privileges on the host.

1. Install Advance Toolchain:

```
rpm --import
https://public.dhe.ibm.com/software/server/POWER/Linux/toolchain/at/redhat/RHEL7/g
-pubkey-6976a827-5164221b

cat > /etc/yum.repos.d/advance-toolchain.repo <<EOF

# Beginning of the configuration file
[advance-toolchain]
name=Advance Toolchain IBM FTP
baseurl=https://public.dhe.ibm.com/software/server/POWER/Linux/toolchain/at/redhat,
7
failovermethod=priority
enabled=1
gpgcheck=1
gpgkey=ftp://public.dhe.ibm.com/software/server/POWER/Linux/toolchain/at/redhat/RHI
-pubkey-6976a827-5164221b
# End of the configuration file
```

2. To install the repository configuration, assume superuser privileges and invoke the following command:

```
yum -y install https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

3. Replace the **USERNAME:PASSWORD** in the following command with the username and password of a registered EnterpriseDB user:

```
sed -i "s@<username>:<password>@USERNAME:PASSWORD@" /etc/yum.repos.d/edb.repo
```

To request credentials for the repository, visit the [EDB website](#).

4. Before installing BART, execute the following command to install the Extra Packages for Enterprise Linux (EPEL) release package:

```
yum -y install https://dl.fedoraproject.org/pub/epel/epel-release-latest-
7.noarch.rpm
```

- On RHEL 7, enable the `optional`, `extras`, and `HA` repositories to satisfy EPEL package dependencies:

```
subscription-manager repos --enable "rhel-*-optional-rpms" --enable "rhel-*-extras-rpms" --enable "rhel-ha-for-rhel-*-server-rpms"
```

- Invoke the following command to install BART:

```
yum -y install edb-bart-2.5.9
```

## Installing BART on a Debian or Ubuntu Host

Perform the following steps to install a Debian package using the EnterpriseDB apt repository.

To request credentials for the repository, visit the [EDB website](#).

- Assume the superuser privileges.

```
sudo su -
```

- To configure the EnterpriseDB repository on Debian 9 and Ubuntu 18:

```
sh -c 'echo "deb https://username:password@apt.enterprisedb.com/$(lsb_release -cs)-edb/ $(lsb_release -cs) main" > /etc/apt/sources.list.d/edb-$(lsb_release -cs).list'
```

On Debian 10:

- Set up the EnterpriseDB repository:

```
sh -c 'echo "deb [arch=amd64] https://apt.enterprisedb.com/$(lsb_release -cs)-edb/ $(lsb_release -cs) main" > /etc/apt/sources.list.d/edb-$(lsb_release -cs).list'
```

- Substitute your EnterpriseDB credentials for the `username` and `password` placeholders in the following command:

```
sh -c 'echo "machine apt.enterprisedb.com login <username> password <password>" > /etc/apt/auth.conf.d/edb.conf'
```

- Add support to your system for secure APT repositories.

```
apt-get install apt-transport-https
```

- Add the EDB signing key; When invoking the command, replace the `username` and `password` with the credentials provided by EnterpriseDB.

```
wget -q -O - https://apt.enterprisedb.com/edb-deb.gpg.key | apt-key add -
```

- Update the repository metadata.

```
apt-get update
```

- Install the Debian package:

- a. Contact [EDB Support](#) for information about how to install the BART 2.5.9 package.
- b. Navigate to the download directory and execute the following command:

```
apt-get install ./edb-bart_2.5.9-1-deb10_amd64.deb
```

## Installing BART on an SLES 12 Host

This section provides instructions for installing BART on an SLES 12 SP4 host using the zypper package manager. BART is supported on SLES SP4 and SP5 versions.

1. Assume superuser privileges.

```
sudo su -
```

2. Use the following command to add the EDB repository to your SLES host:

```
zypper addrepo https://zypp.enterprisedb.com/suse/edb-sles.repo
```

3. Invoke the following command to refresh the metadata:

```
zypper refresh
```

4. Install **SUSEConnect** to register the host with SUSE to allow access to SUSE repositories:

```
zypper install SUSEConnect
```

5. Register the host with SUSE to allow access to SUSE repositories and replace **'REGISTRATION\_CODE'** and **'EMAIL'** with your SUSE registration information:

```
SUSEConnect -r 'REGISTRATION_CODE' -e 'EMAIL'
```

```
SUSEConnect -p PackageHub/12.4/x86_64
```

```
SUSEConnect -p sle-sdk/12.4/x86_64
```

6. Install the following repository for PEM dependencies:

```
zypper addrepo
https://download.opensuse.org/repositories/Apache:/Modules/SLE_12_SP4/Apache:Module
o
```

7. Refresh the metadata:

```
zypper refresh
```

8. Then, use the zypper utility to install BART:

```
zypper install edb-bart-2.5.9
```

## 1.2 Configuring BART

To configure BART, you must establish the BART user account, [configure the BART host](#), and [configure the database server](#) that will be backed up.

### Establishing the BART User Account

The BART user account is an operating system user that will run the BART command line program. The BART user account must:

- own the BART backup catalog.
- be able to run the `bart` program and the `bart-scanner` program.
- be able to establish a SSH/SCP connection to and from each database server managed by BART.

You can optionally use the `enterprisedb` database user as the BART user account for an Advanced Server database and `postgres` database user as the BART user account for a PostgreSQL server. If you do not wish to use an existing database user as the BART user account, you must create an operating system user to assume the role.

### Configuring BART and Database Server

As stated earlier, to configure BART, you must [configure the BART host](#) as well as the [database server](#). The following table acts as a configuration parameter reference listing the mandatory and optional parameters with default values for `[SERVER]` as well as `[BART]` sections.

- Parameters set in the `[BART]` section are applicable to all BART managed database servers.
- Parameters set in the `Server` section are applicable only to the specific server; the `Server` parameter setting overrides the `[BART]` section setting.

For information about configuring BART host parameters, see the [BART Host Parameter Reference](#) and for information about configuring the database server parameters, see the [Database Server Parameter Reference](#).

Parameter	Type	Default	[SERVER]	[BART]
<code>[BART]</code>	Mandatory	N/A	N/A	Yes
<code>&lt;bart_host&gt;</code>	Mandatory	N/A	N/A	Yes
<code>&lt;backup_path&gt;</code>	Mandatory	N/A	N/A	Yes
<code>&lt;pg_basebackup_path&gt;</code>	Mandatory	N/A	N/A	Yes
<code>retention_policy</code>	Optional	<code>&lt;max_number&gt;BACKUPS</code>	Yes	Yes
<code>wal_compression</code>	Optional	<code>Disabled</code>	Yes	Yes
<code>copy_wals_during_restore</code>	Optional	<code>Disabled</code>	Yes	Yes
<code>xlog_method</code>	Optional	<code>fetch</code>	Yes	Yes
<code>logfile</code>	Optional	<code>/tmp/bart.log</code>	N/A	Yes
<code>scanner_logfile</code>	Optional	<code>/tmp/bart_scanner.log</code>	N/A	Yes
<code>&lt;bart_socket_directory&gt;</code>	Optional	<code>/tmp</code>	N/A	Yes
<code>&lt;bart_socket_name&gt;</code>	Optional	<code>&lt;MD5 checksum&gt;</code>	N/A	Yes
<code>&lt;thread_count&gt;</code>	Optional	<code>1</code>	Yes	Yes
<code>&lt;batch_size&gt;</code>	Optional	<code>49152</code>	Yes	Yes

Parameter	Type	Default	[SERVER]	[BART]
<scan_interval>	Optional	0	Yes	Yes
<mbm_scan_timeout>	Optional	20 seconds	Yes	Yes
<workers>	Optional	1	Yes	Yes
[Server Name]	Mandatory	N/A	Yes	N/A
<backup_name>	Optional	N/A	Yes	N/A
host	Mandatory	N/A	Yes	N/A
port	Mandatory	5444 for EPAS; 5432 for Postgres	Yes	N/A
user	Mandatory	N/A	Yes	N/A
<archive_path>	Optional	BART backup catalog	Yes	N/A
<archive_command>	Optional	N/A	Yes	N/A
<cluster_owner>	Mandatory	enterprisedb for EPAS postgres for PostgreSQL	Yes	N/A
<remote_host>	Optional	N/A	Yes	N/A
<tablespace_path>	Optional	N/A	Yes	N/A
allow_incremental_backup	Optional	Disabled	Yes	N/A
description	Optional	N/A	Yes	N/A

## Configuring the BART Host

To configure the BART host, perform the following steps on the BART host as a root user:

Step 1. Navigate to the `usr/edb/bart/etc` directory and make a copy of the `bart.cfg.sample` file to create the `bart.cfg` file that will contain the parameter settings.

Step 2. Confirm that the Postgres `pg_basebackup` utility program is installed on the BART host. The `pg_basebackup` utility resides in the `bin` directory under your Postgres installation.

Step 3. Ensure the `LD_LIBRARY_PATH` environment variable includes the location of the `libpq` library. If your `libpq` library does not reside in the default location (`POSTGRES_INSTALL_HOME/lib`), you must add the library path to the `LD_LIBRARY_PATH` environment variable in the BART user account's profile (`bash_profile`) located in `/home/<bart user account>`:

```
### .bash_profile
### Get the aliases and functions
if [ -f ~/.bashrc ]; then
. ~/.bashrc
fi
### User specific environment and startup programs
export LD_LIBRARY_PATH=/usr/edb/as11/lib:$LD_LIBRARY_PATH
```

Step 4. Create the BART backup catalog and ensure the BART user account holds privileges on the BART backup catalog. In the following example, the BART configuration file specifies `/opt/backup` as the parent directory for the BART backup catalog in the `<backup_path>` parameter:

```
[BART]

bart_host = bartuser@192.168.2.22
```

```

backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

```

In the following example, `bartuser` is the BART user account. The example creates and sets the ownership and permissions on the BART backup catalog:

```

su root
mkdir /opt/backup
chown bartuser /opt/backup
chgrp bartuser /opt/backup
chmod 700 /opt/backup

```

If the subdirectory does not exist, BART creates a subdirectory for each database server listed in the configuration file when you invoke the `bart` command line program.

Step 5. Use your choice of editor to open the BART configuration file (located in the `usr/edb/bart/etc` directory) and edit the configuration as required. You must add the mandatory parameters to the `[BART]` section. Default values may be used for optional parameters.

The following table describes the `[BART]` host parameters.

Parameters/Placeholder	Type	Description
<code>[BART]</code>	Mandatory	Identifies the global section of the configuration file. It must be named BART.
<code>bart_host</code>	Mandatory	Specify the bart user name and the IP address of the bart host on which the BART utility resides. You must specify it in the form of <code>&lt;bart_user&gt;@&lt;bart_host_address&gt;</code> .
<code>backup_path</code>	Mandatory	Specify the path to the file system parent directory where all BART backups are stored.
<code>pg_basebackup_path</code>	Mandatory	Specify the path to the <code>pg_basebackup</code> program that you installed on the BART host. For information about <code>pg_basebackup</code> version-specific restrictions, see the EDB Backup and Recovery User Guide available at the <a href="#">EDB website</a> .
<code>wal_compression</code>	Optional	Set this parameter to <code>enabled</code> to compress the archived WAL files in gzip format in the BART backup catalog when the <code>MANAGE</code> subcommand is invoked. By default it is set to <code>disabled</code> . The gzip compression program must be in the BART user account's <code>PATH</code> and the WAL compression setting must not be enabled for those database servers where you need to take incremental backups.

Parameters/Placeholder	Type	Description
<code>copy_wals_during_restore</code>	Optional	Set this parameter to <code>enabled</code> to copy the archived WAL files from the BART backup catalog to the <code>restore_path/archived_wals</code> directory prior to the database server archive recovery. Enabling this option helps you save time during the restore operation. Set this parameter to <code>disabled</code> (default) to retrieve the archived WAL files directly from the BART backup catalog during the database server archive recovery. During the restore operation, recovery settings will be saved in the <code>postgresql.auto.conf</code> file. The <code>restore_command</code> in the <code>postgresql.auto.conf</code> file will be determined by the value specified in the <code>copy_wals_during_restore</code> parameter. If the <code>RESTORE</code> subcommand is invoked with the <code>-c</code> option, the archived WAL files are copied from the BART backup catalog to the <code>restore_path/archived_wals</code> directory, thus overriding any setting of the <code>copy_wals_during_restore</code> parameter. If the <code>RESTORE</code> subcommand is invoked without the <code>-c</code> option, the value specified by the <code>copy_wals_during_restore</code> parameter is used.
<code>xlog_method</code>	Optional	Specify how the transaction log is collected during the execution of <code>pg_basebackup</code> through the <code>BACKUP</code> subcommand. Set <code>xlog_method</code> to <code>fetch</code> (default) to collect the transaction log files after the backup is completed. Set to <code>stream</code> to stream the transaction log in parallel with the full backup creation.
<code>retention_policy</code>	Optional	Set this parameter to determine when an active backup should be marked as <code>obsolete</code> when the <code>MANAGE</code> subcommand is used. You can specify the retention policy either in terms of number of backups or duration (days, weeks, or months). <code>&lt;max_number&gt; BACKUPS</code> (default), <code>&lt;max_number&gt; DAYS</code> , <code>&lt;max_number&gt; WEEKS</code> , or <code>&lt;max_number&gt; MONTHS</code> where <code>&lt;max_number&gt;</code> is a positive integer. For information about managing backups using a retention policy, see the EDB Backup and Recovery User Guide available at the <a href="#">EDB website</a> .
<code>logfile</code>	Optional	Use this parameter to specify the path to the BART log file. The default log file location is <code>/tmp/bart.log</code> . The log file will be created the first time you invoke the <code>bart</code> command line program using the sample configuration file value. To change the default setting, you must delete the <code>bart.log</code> file from the <code>/tmp</code> directory and create a new log file in another directory so that a new log file will be created and owned by the new BART user account. If no path to a log file is specified, BART does not create a log file.
<code>scanner_logfile</code>	Optional	Use this parameter to specify the path to the XLOG/WAL scanner log file. The default location is <code>/tmp/bart_scanner.log</code> . The scanner log file will be created the first time you invoke the <code>bart_scanner</code> program using the sample configuration file value. To change the default setting, you must delete the <code>bart_scanner.log</code> file from the <code>/tmp</code> directory and create a new log file in another directory so that a new log file will be created and owned by the new BART user account. If no path to a log file is specified, BART does not create a WAL scanner log file.

Parameters/Placeholder	Type	Description
<code>&lt;bart_socket_directory&gt;</code>	Optional	Specify the socket directory path where all BART sockets will be stored. The default directory is <code>/tmp</code> . While specifying the <code>bart_socket_directory</code> path, you must ensure that the directory exists and the BART user has the required access permissions to the directory.
<code>&lt;bart_socket_name&gt;</code>	Optional	Specify a user-friendly BART socket file name. Using this option overrides the default BART socket name generated using MD5 checksum. You must shut down the bart-scanner before setting this option. You can view the <code>&lt;bart_socket_name&gt;</code> in the <code>sockPath</code> field after starting the bart-scanner in the debug mode. This option helps in preventing the use of MD5 during the bart-scanner startup, thus making BART more compliant in FIPS mode.
<code>&lt;thread_count&gt;</code>	Optional	Specify the number of worker threads for copying blocks (for incremental backups) or data files (for full backup) from the database server to the <code>archive_path</code> when the <code>BACKUP</code> subcommand is invoked. The default value is <code>1</code> . The same set of worker threads are used for the compression operation when taking full backups in order to provide parallel, compressed backups when the <code>BACKUP</code> subcommand is specified with the <code>-z</code> or <code>-c</code> options. The compression operation does not apply to incremental backups. See <a href="#">thread count</a> for more information.
<code>&lt;batch_size&gt;</code>	Optional	Specify the number of blocks of memory used for copying modified blocks from the database server to the <code>archive_path</code> when the <code>BACKUP</code> subcommand is invoked for incremental backups. The default value is 49152 blocks; each block is 8192 bytes. The maximum permitted value is 131072 blocks and the minimum permitted value is 1 block. Reduce the <code>&lt;batch_size&gt;</code> setting if the server runs out of memory while executing the <code>pg_read_binary_file()</code> .
<code>&lt;scan_interval&gt;</code>	Optional	Specify the number of seconds after which the WAL scanner should initiate force scanning of the new WAL files. The default value is 0, which means no brute-force scanning will be started. After upgrading to the latest version of BART, users who have set this parameter to a non-default value may see increased CPU consumption on the part of bart-scanner. If this is an issue, consider increasing the configured value of <code>scan_interval</code> parameter, or removing the setting if it is not required.
<code>&lt;mbm_scan_timeout&gt;</code>	Optional	Specify the number of seconds to wait for MBM files before timing out; this parameter is applicable only for incremental backup. You must set the <code>scan_interval</code> to a value significantly less than the MBM scan timeout. The default value is 20 seconds. The <code>mbm_scan_timeout</code> parameter value must be greater than 0. If the value is 0 or negative, then an error will be displayed during an incremental backup.
<code>&lt;workers&gt;</code>	Optional	Specify the number of parallel worker processes required to stream the modified blocks of an incremental backup to the restore host. The default value is 1.

## Thread Count

If the `BACKUP` subcommand is invoked with the `--thread-count` option, then the number of worker threads specified by this option overrides any setting of the `thread_count` parameter in the BART configuration file. If the



**BACKUP** subcommand is invoked without the `--thread-count` option, then the following determines the number of worker threads used:

- The setting of the `thread_count` parameter in the server section of the BART configuration file overrides the setting of `thread_count` in the global section for that particular database server.
- If omitted in the server section, the setting of `thread_count` in the global section is used.
- If the `thread_count` parameter is not specified in either section, the default is 1.
- When taking a full backup, if the `thread_count` in effect is only 1, then the `pg_basebackup` utility is used to take the full backup unless the `--no-pg_basebackup` option is specified with the **BACKUP** subcommand.

`<thread_count>` will not be effective if the backup is taken on a standby server.

If parallel backup is run with `N` number of worker threads, then it will initiate `N + 1` concurrent connections with the server.

Step 6 Invoke the **CHECK-CONFIG** subcommand, omitting the `-s` option to check the parameter settings in the BART configuration file. It should return the current BART version.

```
bart CHECK-CONFIG
```

The **CHECK-CONFIG** subcommand displays an error message if the required configuration is not properly set. You need to check the logfile to fix this.

## Configuring the Database Server

To configure the database server, you must:

1. [Authorize SSH/SCP access without a password prompt.](#)
2. [Create and configure a replication database user.](#)
3. [Adding the database server to the configuration file \(server section\).](#)
4. [Enable WAL archiving of the server.](#)
5. [Verify the server configuration settings.](#)

The following section will walk you through the configuration process.

!!! Note You must authorize SSH/SCP access and set up a replication database user before restarting the database server with WAL archiving enabled.

### Authorizing SSH/SCP Access

BART uses the Secure Shell (`ssh`) and Secure Copy (`scp`) Linux utility programs to copy the backup and WAL files from the BART managed database servers to the BART host as well as to restore backups.

- The client/server `ssh` and `scp` commands must not prompt for a password when establishing a connection with the target server (the server to which a passwordless connection is being made).
- A passwordless connection uses *authorized public keys* (public key of a client user account) to authenticate with the target server.
- You must add the public key of each client user account to the target user account's authorized public keys list on the target server.

For BART usage, there are two scenarios that require a passwordless SSH/SCP connection:

- When connecting from each BART managed database server (SSH/SCP client) to the BART host (target SSH/SCP server) to support WAL archiving as implemented by the `archive_command` parameter.
  - In this case, the database server user account should generate the public key file (`id_rsa.pub`) with the `ssh-`

`keygen -t rsa` command on the database server host.

- The public key file name should be appended to the `~/.ssh/authorized_keys` file on the BART host. The `authorized_keys` file is in the BART user account's home directory.
- When connecting from the BART host (SSH/SCP client) to each BART managed database server (target SSH/SCP server) for taking incremental backups and for supporting restoration of the full backup, the archived WAL files, and the modified blocks, which occurs when the BART `RESTORE` subcommand is given.
  - In this case, the BART user account should generate the public key file (`id_rsa.pub`) with the `ssh-keygen -t rsa` command on the BART host.
  - The public key file name should be appended to the `~/.ssh/authorized_keys` file on the database server host. The `authorized_keys` file is in the home directory of the user account that owns the directory where the database backup is to be restored.
- If backups are to be taken from a given database server host, but restored to a different database server host, the passwordless SSH/SCP connections must be configured from the BART host to the database server host from which the backup is to be taken as well as from the BART host to the database server host to which the backup is to be restored.

See the EDB Backup and Recovery Reference Guide available at the [EDB website](#) to view examples of creating a passwordless connection.

### Enabling Public Key Authentication

The following example enables SSH/SCP access on a CentOS 7.x host; similar (platform-specific) steps will apply to other platforms/versions.

1. In the SSH server daemon configuration file (`sshd_config`) located in the `/etc/ssh`, set the `PubkeyAuthentication` parameter to `yes`.
2. Reload the configuration file:

```
service sshd reload
```

If you get any SSH or SCP errors, examine the `/var/log/secure` log file.

### Creating a Passwordless Connection

The following general instructions will walk you through generating a client's public key file, creating the target server's authorized public keys file, and creating a passwordless connection.

Step 1. On the client system, log in as the user account that will be initiating the SSH or SCP connection.

Step 2. Navigate to the user account's home directory and check for an existing `.ssh` subdirectory. If the `.ssh` directory does not exist, create one and assign the required privileges to the user.

Step 3. Generate the public key file with the following command. Accept all prompted defaults and do not specify a passphrase when prompted for one.

```
ssh-keygen -t rsa
```

The public key file named `id_rsa.pub` is created in the `.ssh` subdirectory.

Step 4. While logged into the client where you just generated the public key file, use `SCP` to make a temporary copy of it on the target server:

```
scp ~/.ssh/id_rsa.pub <target_user>@<host_address>:tmp.pub
```

Step 5. Navigate into the target user account's home directory and check for an existing `.ssh` subdirectory. If it does not exist, create one and assign the required privileges to the user.

Step 6. Append the temporary, client's public key file, `tmp.pub`, to the `authorized_keys` file. If an `authorized_keys` file does not exist, create a new file, but do not completely replace any existing `authorized_keys` file.

```
cat tmp.pub >> ~/.ssh/authorized_keys
```

Make sure the `authorized_keys` file is only accessible by the file owner and not by groups or other users. If the `authorized_keys` file does not have the required permission setting or it was newly created, change the file permissions as follows:

```
chmod 600 ~/.ssh/authorized_keys
```

Step 7. Delete the temporary public key file:

```
rm tmp.pub
```

Now, when logged into the client system as `user` there should be no prompt for a password when commands such as the following is given:

```
ssh target_user@host_address
```

### Setting up a Replication Database User

For each database server that is to be managed by BART, a database user must be chosen to serve as the *replication database user*. The replication database user sets the Postgres `archive_command` configuration parameter when the `INIT` subcommand is invoked and creates backups when the `BACKUP` subcommand is invoked. The replication database user must be a `superuser`.

When executed with the PSQL client, the following PostgreSQL command creates a superuser to be the replication database user:

```
CREATE ROLE repuser WITH LOGIN SUPERUSER PASSWORD 'password';
```

The `pg_hba.conf` file must minimally permit the replication database user to have access to the database.

In the following example, the `pg_hba.conf` file permits the `repuser` (replication database user) to have access to the `template1` database. The IP address from which `repuser` has access to `template1` database is the location of the BART host:

For `pg_basebackup` only: If `pg_basebackup` is to be used for taking any backups (such as for standby servers), the replication database user must also be included in the `pg_hba.conf` file as a `replication` database connection as shown by the last entry in the following example.

```
### TYPE DATABASE USER ADDRESS METHOD
### "local" is for Unix domain socket connections only
local all all md5
### IPv4 local connections:
host template1 repuser 192.168.2.22/32 md5
host all enterprisedb 127.0.0.1/32 md5
### IPv6 local connections:
host all all ::1/128 md5
### Allow replication connections from localhost, by a user with the
### replication privilege.
host replication repuser 192.168.2.22/32 md5
```

The replication database user must be specified for the `user` parameter in the BART configuration file for the database server as shown in the following example:

```
[ACCTG]
host = 192.168.2.24
port = 5444
user = repuser
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
description = "Accounting"
```

There must be no password prompt when connecting to the database server with the replication database user. There are several ways to permit this; one recommended method is to use a `.pgpass` file located in the BART user account's home directory.

For example, if `bartuser` is the BART user account, then the `.pgpass` file located in the `/home/bartuser` directory must contain the following entry:

```
192.168.2.24:5444::repuser:password
```

When `bartuser` invokes a BART backup, the password for the replication database user, `repuser`, is obtained from the `.pgpass` file of `bartuser` to connect to the database server running at `192.168.2.24` on `port 5444`.

The `.pgpass` file must contain an entry for each BART managed database server and its corresponding replication database user and password.

#### Adding a Database Server to the BART Configuration File

To manage the backup and recovery of a database server, you must add entries to the `[SERVER]` section of the BART configuration file, which is located in `<BART_HOME>/etc` directory.

#### Database Server Parameter Reference

Set the following parameters in the `[SERVER]` section of the BART configuration file. The parameter setting in the `[SERVER]` section overrides the setting in the global `[BART]` section for that particular database server. If omitted, the default value will be used.

For each cluster serviced by BART, the following parameters are mandatory:

```
[HR]

host = 192.168.2.24
port = 5432
user = postgres
cluster_owner = postgres
```

!!! Note The port parameter setting is required only if the database server listens on a port other than the default (for example if Postgres listens on a port other than 5432).

The following table describes the database server parameters.

Parameters/Placeholder	Type	Description
------------------------	------	-------------

Parameters/Placeholder	Type	Description
[ServerName]	Mandatory	Specify the server name that you want to backup using BART. It is not case-sensitive when referenced with BART subcommand options. A lowercase conversion of this name is used to create a subdirectory in the BART backup catalog for storing the backups and WAL files for this database server (for eg., epas12).
<backup_name>	Optional	Specify a <a href="#">template</a> for user-defined, friendly names that will be assigned to the backups of the database server. The maximum permitted length of backup name is 49 characters. The <code>&lt;backup_name&gt;</code> parameter can be overridden by the <code>--backup-name</code> option of the <code>BACKUP</code> subcommand. If this parameter is omitted from the BART configuration file, and the <code>--backup-name</code> option with a user-defined name is not specified with the <code>BACKUP</code> subcommand, then the backup can only be referenced in BART subcommands by the BART assigned, integer backup identifier.
host	Mandatory	Specify the IP address of the database server to be configured for backup.
port	Mandatory	Specify the port number identifying the database server instance (that is, the relevant database cluster) to be backed up. The default port number for EPAS is <code>5444</code> and for Postgres it is <code>5432</code> . The port parameter setting is only required if the database server listens on a port other than the default value.
User	Mandatory	Specify the replication database user name used by BART to establish the connection to the database server for full backups. See <a href="#">Setting up a Replication Database User</a> for more information.
<archive_path>	Optional	Specify the path where archived WAL files will be stored. The default location is the BART backup catalog ( <code>&lt;backup_path&gt;/&lt;server_name&gt;/archived_wals</code> ).
<archive_command>	Optional	When the <code>INIT</code> subcommand is used, the content and variables specified in the BART <code>&lt;archive_command&gt;</code> result in the archive command string to be generated into the <code>Postgres archive_command</code> parameter in the <code>postgresql.auto.conf</code> file. To configure the BART <code>&lt;archive_command&gt;</code> parameter, enclose the command string within single quotes ( <code>'</code> ). If you do not specify the <code>&lt;archive_command&gt;</code> parameter in the configuration file, the default setting is taken as <code>'scp %p %h:%a/%f'</code> . See <a href="#">Archive Command Auto Configuration</a> for information about variables. The BART <code>&lt;archive_command&gt;</code> parameter in the BART configuration file, and the Postgres <code>&lt;archive_command&gt;</code> parameter in the <code>postgresql.conf</code> file (or the <code>postgresql.auto.conf</code> file) refer to two different parameters that are to be set in different manner.
<cluster_owner>	Mandatory	Specify the Linux operating system user account that owns the database cluster. This is typically <code>enterprisedb</code> for Advanced Server database clusters installed in the Oracle compatible mode, or <code>postgres</code> for Advanced Server database clusters installed in the PostgreSQL compatible mode and PostgreSQL database clusters.

Parameters/Placeholder	Type	Description
<code>&lt;remote_host&gt;</code>	Optional	Specify the IP address of the remote server to which a backup is to be restored. Specify this parameter in the form of <code>&lt;remote_user&gt;@&lt;remote_host_address&gt;</code> . <code>&lt;remote_user&gt;</code> is the user account on the target database server host that accepts a passwordless SSH/SCP login connection and owns the directory where the backup is to be restored. <code>&lt;remote_host_address&gt;</code> is the IP address of the remote host. For restoring a backup to a remote host or for restoring any backup where <code>&lt;remote_user&gt;</code> and the BART user account are not the same users, either this parameter must be set or it may be specified with the <code>-r</code> option with the BART <code>RESTORE</code> subcommand.
<code>&lt;tablespace_path&gt;</code>	Optional	Specify path to which tablespaces are to be restored in the format <code>OID = &lt;tablespace_path&gt;</code> ; If the backup is to be restored to a remote host specified by the <code>&lt;remote_host&gt;</code> parameter, then the tablespace paths must exist on the remote host.
<code>allow_incremental_backups</code>	Optional	Set this parameter to <code>enabled</code> to enable use of the WAL scanner and permit taking incremental backups when the <code>BACKUP</code> subcommand is invoked with the <code>--parent</code> option. Set it to <code>disabled</code> (default) to disallow incremental backups and thus permit only full backups. For information about using the <code>BACKUP</code> subcommand and running the WAL scanner, please see the EDB Backup and Recovery User Guide available at the <a href="#">EDB website</a> .
<code>Description</code>	Optional	Specify the description that will be used to identify the database server.

For information regarding the following parameters, see [configuring the BART host](#).

- `retention_policy`
- `xlog_method`
- `wal_compression`
- `copy_wals_during_restore`.
- `thread_count`.
- `batch_size`.
- `scan_interval`.
- `mbm_scan_timeout`.
- `workers`

### Backup Name Template

- The template is an alphanumeric string that may include the following variables that will be replaced with the timestamp values when the backup is taken:
  - `%year` to be replaced by 4-digit year
  - `%month` to be replaced by 2-digit month
  - `%day` to be replaced by 2-digit day
  - `%hour` to be replaced by 2-digit hour
  - `%minute` to be replaced by 2-digit minute
  - `%second` to be replaced by 2-digit second
- To include a percent sign (%) as a character in the backup name, specify `%%` in the template.
- Do not enclose the template string in quotes even if you want the template to include space characters, otherwise the enclosing quotes are stored as part of the backup name. However, when referenced with the `-i` option by BART

subcommands use of space characters in the backup name requires enclosing the backup name in quotes.

The following example shows the configuration settings of three database servers:

```
[ACCTG]

host = 127.0.0.1
port = 5444
user = enterprisedb
cluster_owner = enterprisedb
backup_name = acctg_%year-%month-%dayT%hour:%minute:%second
archive_command = 'cp %p %a/%f'
allow_incremental_backups = enabled
retention_policy = 8 BACKUPS
description = "Accounting"

[MKTG]

host = 192.168.2.24
port = 5444
user = repuser
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
allow_incremental_backups = enabled
description = "Marketing"

[HR]

host = 127.0.0.1
port = 5432
user = postgres
cluster_owner = postgres
retention_policy = 4 DAYS
description = "Human Resources"
```

## Enabling WAL Archiving

WAL archiving must be enabled for the database server for which BART is to perform backup and recovery management.

- The WAL Archiving Configuration section describes the manual WAL archiving configuration process.
- The Archive Command Auto Configuration section describes an automated WAL archiving process.

### WAL Archiving Configuration

Set the following configuration parameters in the `postgresql.conf` file to enable WAL archiving

- Set `wal_level` to `replica` or higher.
- Set `archive_mode` to `on`.
- Set the PostgreSQL `archive_command` parameter to copy the WAL files to the `archive_path`. The `archive_command` configuration parameter mentioned here is located in the `postgresql.conf` file; the PostgreSQL `archive_command` parameter is used in a different manner than the BART `archive_command`.
- Set `max_wal_senders` to a value high enough to leave at least one session available for the backup. If the `xlog_method=stream` parameter setting is to be used by this database server, the `max_wal_senders` setting must account for an additional session for the transaction log streaming (the setting must be a minimum of 2). See [Configuring the BART host](#) for information about the `xlog_method` parameter.



For detailed information about WAL archiving, see the [PostgreSQL Core Documentation](#).

The `ARCHIVE_PATH` field displayed by the BART `SHOW-SERVERS` subcommand displays the full directory path where the WAL files should be copied as specified in the `archive_command` configuration parameter in the `postgresql.conf` file:

```
-bash-4.1$ bart SHOW-SERVERS -s acctg
SERVER NAME : acctg
HOST NAME : 192.168.2.24
USER NAME : repuser
PORT : 5444
REMOTE HOST :
RETENTION POLICY : none
DISK UTILIZATION : 0.00 bytes
NUMBER OF ARCHIVES : 0
ARCHIVE PATH : /opt/backup/acctg/archived_wals
ARCHIVE COMMAND : (disabled)
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
INCREMENTAL BACKUP : DISABLED
DESCRIPTION : "Accounting"
```

The parameter settings in the following example will copy the WAL files to a directory named `/opt/backup/acctg/archived_wals` on the BART host located at `192.168.2.22` as the `bartuser` user account. Using the `bartuser` account ensures that the operation will have sufficient permissions to copy to the BART backup catalog owned by `bartuser`.

```
archive_mode = on                # allows archiving to be done
                                # (change requires restart)
archive_command = 'scp %p bartuser@192.168.2.22:/opt/backup/acctg/archived_wals/%f'
                                # command to use to archive a logfile
segment
                                # placeholders: %p = path of file to
archive
                                # %f = file name only
...
max_wal_senders = 1             # max number of walsender processes
                                # (change requires restart)
```

The database server must be restarted in order to initiate WAL archiving, but do not do so until you have verified that the full path of the BART backup catalog has been created by a prior BART subcommand or the archive operation will fail.

Start the WAL scanner by executing the following command:

```
./bart-scanner
```

### Archive Command Auto Configuration

To enable WAL archiving:

- In the `postgresql.conf` file, set the `wal_level` to `replica` or higher, `archive_mode` to `on`, and `max_wal_senders` to a value high enough to leave at least one session available for the backup. If the `xlog_method=stream` parameter setting is to be used by this database server as determined in the BART configuration file, the `max_wal_senders` setting must account for an additional session for the transaction log



streaming (that is, the setting must be a minimum of 2). See [Configuring the BART host](#) for information on the `xlog_method` parameter.

- Configure the Postgres `archive_command` parameter automatically with the `INIT` subcommand and restart the database server when you are ready to initiate WAL archiving. The `INIT` subcommand invokes the Postgres `ALTER SYSTEM` command to set the Postgres `archive_command` configuration parameter in the `postgresql.auto.conf` file located in the managed database server's `PGRES_INSTALL_HOME` data directory. For additional information about the `INIT` subcommand, see the EDB Backup and Recovery User Guide available at the [EDB website](#).

The archive command string that the `INIT` subcommand generates into the `postgresql.auto.conf` file is determined by the parameter setting of the BART `archive_command` parameter in the server section of the BART configuration file. If the BART `archive_command` parameter is not set in the server section for a given database server, the command string that is configured uses the following default format:

```
'scp %p %h:%a/%f'
```

The following table describes these variables:

Variable	Description
<code>%p</code>	The path of the file to archive used by the Postgres archiving process.
<code>%h</code>	Will be replaced by the <code>&lt;bart_user&gt;@&lt;bart_host_address&gt;</code> as specified in the <code>&lt;bart_host&gt;</code> parameter setting.
<code>%a</code>	Will be replaced by the BART <code>archived_wals</code> directory as specified in the <code>archive path</code> parameter setting. If the <code>&lt;archive_path&gt;</code> is not specified, then the default directory is <code>&lt;backup_path&gt;/&lt;server_name&gt;/archived_wals</code> . <code>&lt;server_name&gt;</code> is the lowercase conversion of the database server name.
<code>%f</code>	The archived file name used by the Postgres archiving process.

The placeholders `%h` and `%a` are replaced by the `INIT` subcommand when creating the archive command string. The placeholders `%p` and `%f` are not replaced by the `INIT` subcommand, but are kept as given to be used by the Postgres archiving process.

For example, to use the default archive command format, the BART configuration file contains the following settings where the BART `archive_command` parameter is omitted from the server section for `ACCTG`:

```
[BART]

bart_host= bartuser@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]

host = 127.0.0.1
port = 5444
user = repuser
cluster_owner = enterprisedb
description = "Accounting"
```

The `INIT` subcommand is invoked by BART user account `bartuser` as follows:

```
[bartuser@localhost ~]$ bart INIT -s acctg -o
INFO: setting archive_command for server 'acctg'
WARNING: archive_command is set. server restart is required
```

If the BART backup catalog directory is not already complete, it will be completed.

The resulting archive command string in the `postgresql.auto.conf` file located in the managed database server's `PGGRES_INSTALL_HOME/data directory` appears as follows:

```
### Do not edit this file manually!
### It will be overwritten by ALTER SYSTEM command.
archive_command = 'scp %p
bartuser@192.168.2.22:/opt/backup/acctg/archived_wals/%f'
```

Run the `INIT` subcommand with the `-o` option to override any existing `archive_command` setting in the `postgresql.conf` or the `postgresql.auto.conf` file. In addition, the `-o` option must be used to generate the command string if the `archive_mode` is set to off even if there are no existing settings of the `archive_command` in the `postgresql.conf` or `postgresql.auto.conf` files.

In this example, the following BART configuration file is used with an explicit setting of the BART `archive_command` parameter:

```
[BART]

bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]

host = 127.0.0.1
port = 5444
user = repuser
cluster_owner = enterprisedb
archive_command = 'cp %p %a/%f'
description = "Accounting"
```

The `INIT` subcommand is invoked by BART user account `enterprisedb` as follows:

```
-bash-4.1$ bart INIT -s acctg -o
INFO: setting archive_command for server 'acctg'
WARNING: archive_command is set. server restart is required
```

The resulting Postgres `archive_command` parameter in the `postgresql.auto.conf` file appears as follows:

```
### Do not edit this file manually!
### It will be overwritten by ALTER SYSTEM command.
archive_command = 'cp %p /opt/backup/acctg/archived_wals/%f'
```

When the database server has been restarted, the `ARCHIVE COMMAND` field of the `SHOW-SERVERS` subcommand displays the active Postgres archive command as shown by the following example:

```
-bash-4.1$ bart SHOW-SERVERS -s acctg
```

```

SERVER NAME : acctg
HOST NAME : 127.0.0.1
USER NAME : repuser
PORT : 5444
REMOTE HOST :
RETENTION POLICY : none
DISK UTILIZATION : 48.00 MB
NUMBER OF ARCHIVES : 0
ARCHIVE PATH : /opt/backup/acctg/archived_wals
ARCHIVE SCOMMAND : `cp %p /opt/backup/acctg/archived_wals/%f`
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
INCREMENTAL BACKUP : DISABLED
DESCRIPTION : "Accounting"

```

### Verifying Configuration Settings

To verify the parameter settings of the database server specified, execute the `CHECK-CONFIG` subcommand with the `-s` option:

```
bart CHECK-CONFIG [ -s server_name ]
```

The `CHECK-CONFIG` subcommand confirms the following:

- The `cluster_owner` parameter is set to the user account owning the database cluster directory.
- A passwordless SSH/SCP connection is set between the BART user and the user account specified by the `cluster_owner` parameter.
- The BART `user` parameter specifies a database superuser.
- The BART `user` has access to the backup directory catalog.
- The `pg_hba.conf` file contains a replication entry for the database superuser specified by the BART `user` parameter.
- The `archive_mode` parameter in the `postgresql.conf` file is enabled.
- The `archive_command` parameter in the `postgresql.auto.conf` or the `postgresql.conf` file is set.
- The `allow_incremental_backups` parameter in the BART configuration file is enabled for database servers for which incremental backups are to be taken.
- Archiving of WAL files to the `archive_path` is in process.
- The WAL scanner program is running.

After configuring the BART host and the database server(s), you can start using BART. For information about using BART, see the EDB Backup and Recovery User Guide available at the [EDB website](#).

## 1.3 Upgrading BART

This section outlines the process of upgrading BART from an existing version to the latest version.

### Upgrade Restrictions

The following restrictions apply with regard to previous BART versions.

- You can take incremental backups using the latest version only when the parent backup (full or incremental backup)

has also been taken with the latest version.

- Using the latest version, you can restore incremental backups that are taken only with the latest version of BART. However, using the latest version you can restore full backups that were taken with older versions.

## Upgrading from Older Versions of BART

Perform the following steps to upgrade from older versions of BART to the latest version:

Step 1: Assume the identity of the BART user account and invoke the following command to stop the BART WAL scanner program (`bart-scanner`):

```
bart-scanner STOP
```

Step 2: As the `root` user, upgrade to the latest BART version with the `yum upgrade` command.

- To upgrade the BART RPM package directly from the *EDB Yum Repository* website, specify only the package name:

On CentOS 7:

```
yum upgrade edb-bart
```

You can also use a downloaded RPM package file to upgrade. To use a downloaded BART RPM package file to upgrade, use the `yum` command, specifying the complete RPM package file name:

```
yum upgrade edb-bart-x.y.z rhel7.x86_64.rpm
```

Where x denotes the major version of BART, and y and z denotes the minor version.

On a Debian or Ubuntu Host: On a Debian or Ubuntu Host:

```
apt-get upgrade edb-bart
```

On a SLES Host:

```
zypper update edb-bart
```

Step 3: Repeat the process described in this section to upgrade to the latest BART version on each remote hosts where an incremental backup will be restored.

For additional information about restoration of incremental backups on remote hosts, see the EDB Backup and Recovery User Guide available at the [EDB website](#).

Step 4: If the `bart --version` command returns an error stating the `PATH` is not available after switching from `root` user to another BART user account, adjust the setting of the `PATH` environment variable to include the location of the BART x.y.z executable (the `bin` subdirectory) in the `~/.bashrc` or `~/.bash_profile` files of the following user accounts:

- The BART user account on the BART host.
- The remote user account on the remote host to which incremental backups are to be restored. For details, see the EDB Backup and Recovery User Guide available at the [EDB website](#).

The `PATH` setting should be the same as set for BART x.y.z since all versions use `/usr/edb/bart/bin`.

!!! Note After upgrading to the latest BART version, you must take a new full backup of your system before performing an incremental backup.

## --- 1.4 Uninstalling BART ---

This section walks you through uninstalling BART.

### Uninstalling BART on a RHEL/CentOS Host

To uninstall BART on a RHEL/CentOS host, assume the identity of the `root` user and invoke the following command:

On RHEL/CentOS 7:

```
yum remove edb-bart
```

On RHEL/CentOS 8:

```
dnf remove edb-bart
```

Uninstalling BART does not delete the backup files and archived WAL files that reside in the BART backup catalog. To permanently delete the backup files and archived WAL files in the BART backup catalog ( `/opt/backup` ), use one of the following commands:

- `rm -rf /opt/backup`
- BART `DELETE` subcommand

For information about the BART `DELETE` subcommand, see the *EDB Backup and Recovery User Guide* available at the [EDB website](#).

### Uninstalling BART on an SLES 12 Host

To uninstall BART on an SLES 12 host, assume the identity of the `root` user and invoke the following command:

```
zypper remove edb-bart
```

### Uninstalling BART on a Debian/Ubuntu Host

To uninstall BART on a Debian or Ubuntu host, invoke the following command:

```
apt-get remove edb-bart
```

---

## 2 Quick Start Guide for RHEL/CentOS 7

This tutorial demonstrates using `yum` to [install](#) and [configure](#) Backup and Recovery Tool (BART) 2.5 on a CentOS 7 host with minimal configuration settings. The tutorial assumes that the user has some knowledge of installation and system administration procedures, and has administrative privileges on the host.

For detailed information about BART installation and configuration, see the *BART Installation and Upgrade Guide*,

available at the [EDB website](#).

- BART is tested with the following database versions:
  - Advanced Server - 9.6, 10, 11, and 12.
  - PostgreSQL - 9.6, 10, 11, and 12.

## Installing BART

The following steps describe installing BART on CentOS 7.x OS using `yum`.

1. Assume superuser privileges and use `yum` to create the repository configuration file:

```
yum install -y https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

2. Create an EDB user account to request credentials to the EDB repository; for a user account visit the [EnterpriseDB website](#).
3. Use your choice of editor to open the repository configuration file (named `edb.repo`, located in `/etc/yum.repos.d`), and set the `enabled` parameter value to `1`, and replace the `username` and `password` placeholders in the `baseurl` specification with the username and password of a registered EnterpriseDB user.
4. Update the cache:

```
yum makecache
```

5. Install an Advanced Server or PostgreSQL database server.

To install Advanced Server, execute the following command:

```
yum -y install edb-as12-server
```

Use `sudo` to assume the identity of the `enterprisedb` database superuser

```
sudo su - enterprisedb
```

Create an Advanced Server cluster named `acctg` on listener port `5444`:

```
/usr/edb/as12/bin/initdb -D /var/lib/edb/as12/acctg
```

As the `enterprisedb` user, start the cluster:

```
/usr/edb/as12/bin/pg_ctl start -D /var/lib/edb/as12/acctg
```

You can check the status of the cluster with the following command:

```
/usr/edb/as12/bin/pg_ctl status -D /var/lib/edb/as12/acctg
```

!!! Note The BART host server is not required to have an Advanced Server or PostgreSQL installation, but must include a copy of the Postgres `libpq` library, the `pg_basebackup` utility program, and Boost Libraries 1.53 version for CentOS 7.

6. If you do not already have the `pg_basebackup` program installed on the BART host, you can use the following command to install a limited number of files that include the `pg_basebackup` program:

```
yum install edb-as<xx>-server-client
```

Where <xx> is the Advanced Server version.

7. As a root user, execute the following command to install BART:

```
yum install edb-bart
```

BART (the bart program and bart-scanner) is installed in the `/usr/edb/bart/bin` directory, referred to as `<BART_HOME>`. Repeat the installation process described in this section to install BART on all remote hosts where incremental backups are to be restored.

## Configuring BART

Before configuring BART, establish the BART user account (the operating system user) that will run the BART command line program. Then, to configure the BART host and each database server that is to be managed by BART, perform the following steps:

1. Assume superuser privileges, create the directory that will hold the BART backup catalog, and assign its ownership (with restrictive privileges) to the BART user account:

In this example, `bartuser` is the BART user account and `/opt/backup` is the BART backup catalog.

```
su root
mkdir /opt/backup
chown bartuser /opt/backup
chgrp bartuser /opt/backup
chmod 700 /opt/backup
```

2. Navigate to the `/usr/edb/bart/etc` directory and copy the `bart.cfg.sample` file to create the BART configuration file (`bart.cfg`):

```
cp bart.cfg.sample bart.cfg
```

3. Open the BART configuration file (`bart.cfg`) using an editor of your choice and scroll through the BART configuration file to edit the file as required; sample settings are included for your reference. You must add the mandatory parameters to the `[BART]` and `[ServerName]` sections. Default values may be used for optional parameters. For detailed information about parameter settings, see the *BART Installation and Upgrade Guide*, available at the [EDB website](#).

Parameters set in the `[BART]` section are applicable to all BART managed database servers, while parameters set in the `[ServerName]` section are applicable only to the specific server; `[ServerName]` settings override `[BART]` section settings.

In the following example, only mandatory parameters are set:

```
[BART]
bart_host= bartuser@192.168.169.199
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as12/bin/pg_basebackup

[EPAS12]
host = 127.0.0.1
user = repuser
cluster_owner = enterprisedb
```

The following table describes only mandatory parameters:

Parameters/Placeholder	Section	Description
<code>bart_host</code>	<code>[BART]</code>	Use this field to specify the BART user and the IP address of the host on which the BART utility is installed. Specify the value in the form of <code>&lt;bart_user&gt;@&lt;bart_host_address&gt;</code> .
<code>backup_path</code>	<code>[BART]</code>	Use this field to specify the path where all BART backups and archived WAL files will be stored. Ensure the BART user account holds privileges to create subdirectories and files within the location specified in the <code>backup_path</code> parameter. The default <code>backup_path</code> is BART backup catalog ( <code>/opt/backup</code> ).
<code>pg_basebackup_path</code>	<code>[BART]</code>	Use this field to specify the path to the <code>pg_basebackup</code> utility ( <code>/usr/edb/as&lt;xx&gt;/bin/pg_basebackup</code> ).
<code>[ServerName]</code>	<code>[ServerName]</code>	Specify the name of the database server to be backed up (for example, <code>[EPAS12]</code> ).
<code>host</code>	<code>[ServerName]</code>	Specify the IP address of the database server to be configured for backup.
<code>user</code>	<code>[ServerName]</code>	Specify the replication database user name used by BART to establish the connection to the database server for full backups.
<code>cluster_owner</code>	<code>[ServerName]</code>	Specify the Linux operating system user account that owns the database cluster.

- As a BART user, navigate to `/usr/edb/bart/bin` and invoke the following subcommand (omitting the `-s` option) to verify the `[BART]` section parameter settings:

```
bart CHECK-CONFIG
```

- Authorize [SSH/SCP access](#) between the server and the BART host without a password prompt.
- Create a [replication database user](#) for each database server that BART manages.
- To enable continuous WAL archiving for any database server for which BART is to perform a backup, modify the `postgresql.conf` file, setting:
  - `wal_level` to `replica` or higher (for Postgres 9.6 or later)
  - `archive_mode` to `on`
  - `archive_command` (if it is not set in the `bart.cfg` file)
  - `max_wal_senders` to a value high enough to leave at least one session available for the backup.

After setting the parameters, restart the database server.

- To start the WAL scanner, navigate to `/usr/edb/bart/bin` as a BART user and execute the following command:

```
./bart-scanner
```

- If you are using the default `archive_command`, then navigate to `/usr/edb/bart/bin` as a BART user, run the `INIT` subcommand without the `-o` option, and restart the database server:

```
bart INIT [ -s { <server_name> | all } ]
```

Where `<server_name>` is the name of the database server to be backed up.

If you have customized the `archive_command` setting in the `bart.cfg` file, run the `INIT` subcommand with the `-o` option to override any existing Postgresql `archive_command` setting in the `postgresql.conf` or the `postgresql.auto.conf` file, and restart the database server.



```
bart INIT [ -s { <server_name> | all } ] [ -o ]
```

10. To verify the database server parameter settings, as a BART user navigate to `/usr/edb/bart/bin` and invoke the `CHECK-CONFIG` subcommand with the `-s` option:

```
bart CHECK-CONFIG [ -s <server_name> ]
```

BART is now configured successfully. For detailed information about using BART, see the *EDB Backup and Recovery Tool User Guide*, available at the [EDB website](#).

### Creating a Passwordless Connection

The following example enables SSH/SCP access on a CentOS 7.x host; similar (platform-specific) steps will apply to other platforms/versions. You must create a passwordless connection between the BART host (SSH/SCP client) and the database server (target SSH/SCP server), as well as a passwordless connection between the database server (SSH/SCP client) and the BART host (target SSH/SCP server).

1. Log in as the user account on the BART host that will be initiating the SSH or SCP connection and navigate to the user account's home directory and check for an existing `.ssh` subdirectory. If the `.ssh` directory does not exist, create one with the required privileges.
2. As a root user navigate to `/usr/edb/bart`, open the `/etc/ssh/sshd_config` file and set the `PubkeyAuthentication` parameter to `yes`.
3. Reload the configuration file:

```
service sshd reload
```

If you get any SSH or SCP errors, examine the log file (`/var/log/secure`).

4. As a BART user, use the following command to generate the public key file; you can accept the default responses:

```
ssh-keygen -t rsa
```

The public key file named `id_rsa.pub` is created in the `.ssh` subdirectory.

5. Use `SCP` to make a temporary copy of the public key file on the target server:

```
scp ~/.ssh/id_rsa.pub target_user@host_address:tmp.pub
```

6. As a `target_user`, log into the target server using `ssh target_user@host_address` command and navigate to the user account's home directory to check if there is an existing `.ssh` subdirectory. If it does not exist, create one with the required privileges.
7. Append the client's temporary public key file, `tmp.pub`, to the `authorized_keys` file:

```
cat tmp.pub >> ~/.ssh/authorized_keys
```

If an `authorized_keys` file does not exist, create a new file, but be careful not to completely replace any existing `authorized_keys` file.

8. Ensure only the file owner (and not other groups or users) has access to `authorized_keys` file:

```
chmod 600 ~/.ssh/authorized_keys
```

9. Delete the temporary public key file:

```
rm tmp.pub
```

Now, when logged into the BART host as a user, there should be no prompt for a password when you are connecting to the target database server:

```
ssh target_user@database_server_address
```

### Creating a Passwordless Connection Between the Database Server and the BART Host

If backups are to be taken from a given database server host, but restored to a different database server host, the passwordless SSH/SCP connections must be configured from the BART host to the database server host from which the backup is to be taken as well as from the BART host to the database server host to which the backup is to be restored.

An example of how to create a passwordless connection is documented in the *EDB Backup and Recovery Reference Guide*, available at the [EDB website](#).

Even when the Advanced Server database is on the same host as BART, and the Advanced Server database cluster owner is also the BART user account, a passwordless SSH/SCP connection must be established from the same user account to itself.

1. On the database server, navigate into the target user account's home directory to check for an existing `.ssh` subdirectory. If it does not exist, create one in the user account's home directory with the required privileges.
2. As a database server user, generate the public key file:

```
ssh-keygen -t rsa
```

3. Create a temporary copy of the public key file:

```
scp ~/.ssh/id_rsa.pub target_user@host_address:tmp.pub
```

4. As a target user, log into the BART host and navigate to the user account's home directory to check if there is an existing `.ssh` subdirectory. If it does not exist, create one with the required privileges:

```
ssh target_user@host_address
```

5. Append the temporary, client's public key file to the `authorized_keys` file:

```
cat tmp.pub >> ~/.ssh/authorized_keys
```

If an `authorized_keys` file does not exist, create a new file, but do not completely replace any existing `authorized_keys` file.

6. Ensure only the file owner (and not other groups or users) has access to `authorized_keys` file:

```
chmod 600 ~/.ssh/authorized_keys
```

7. Delete the temporary public key file:

```
rm tmp.pub
```

Now, when logged into the database server as a user, there should be no prompt for a password when you are connecting to the BART host:

```
ssh bart_user@bartip_address
```

## Creating a Replication Database User

1. To create a replication database user (a superuser), connect to the database server with the `psql` client, and invoke the following PostgreSQL command:

```
CREATE ROLE <repuser> WITH LOGIN SUPERUSER PASSWORD '<password>';
```

2. Specify this replication database user in the `user` parameter of the `bart.cfg` file.
3. The `pg_hba.conf` file must minimally permit the replication database user to have access to the database. The IP address from which the replication database user has access to the database is the BART host location. The replication database user must also be included in the `pg_hba.conf` file as a replication database connection if `pg_basebackup` is to be used for taking any backups.
4. To ensure there is no password prompt when connecting to the database server with the replication database user, a recommended method is to use the `.pgpass` file located in the BART user account's home directory (if it does not exist, you need to create the `.pgpass` file with the required privileges). The `.pgpass` file must contain an entry for each BART managed database server, and its corresponding replication database user and password.

## 3 Quick Start Guide for RHEL/CentOS 8

This tutorial demonstrates using the `dnf` command to install and configure the EDB Backup and Recovery Tool (BART) 2.5 on a CentOS 8 host with minimal configuration settings. The tutorial assumes that the user has some knowledge of installation and system administration procedures and has administrative privileges on the host.

For detailed information about BART installation and configuration, see the *BART Installation and Upgrade Guide* available at the [EDB website](#).

- BART is tested with the following database versions:
  - Advanced Server - 9.6, 10, 11, and 12.
  - PostgreSQL - 9.6, 10, 11, and 12.

### Installing BART

The following steps describe installing BART on CentOS 8.x OS.

1. Assume superuser privileges and use `dnf` to create the repository configuration file:

```
dnf install -y https://yum.enterprisedb.com/edbrepos/edb-repo-latest.noarch.rpm
```

2. Create an EDB user account to request credentials to the EDB repository; for a user account visit the [EnterpriseDB website](#).
3. Use your choice of editor to open the repository configuration file (named `edb.repo`, located in `/etc/yum.repos.d`), set the `enabled` parameter value to `1`, and replace the `username` and `password` placeholders in the `baseurl` specification with the username and password of a registered EnterpriseDB user.
4. Update the cache:

```
dnf makecache
```

5. Install an Advanced Server or PostgreSQL database server.

To install Advanced Server, execute the following command:

```
dnf -y install edb-as12-server
```

Use sudo to assume the identity of the `enterprisedb` database superuser:

```
sudo su - enterprisedb
```

Create an Advanced Server cluster named `acctg` on listener port `5444`:

```
/usr/edb/as12/bin/initdb -D /var/lib/edb/as12/acctg
```

As the `enterprisedb` user, start the cluster:

```
/usr/edb/as12/bin/pg_ctl start -D /var/lib/edb/as12/acctg
```

You can check the status of the cluster with the following command:

```
/usr/edb/as12/bin/pg_ctl status -D /var/lib/edb/as12/acctg
```

!!! Note The BART host server is not required to have an Advanced Server or PostgreSQL installation, but must include a copy of the Postgres `libpq` library, the `pg_basebackup` utility program, and Boost Libraries 1.66 version for CentOS 8.

6. If you do not already have the `pg_basebackup` program installed on the BART host, you can use the following command to install a limited number of files that include the `pg_basebackup` program:

```
dnf install edb-asxx-server-client
```

7. As a root user, use the following command to install the BART RPM package:

```
dnf install edb-bart
```

BART (the `bart` program and `bart-scanner`) is installed in the `/usr/edb/bart/bin` directory, referred to as `<BART_HOME>`. Repeat the installation process described in this section to install BART on all remote hosts where incremental backups are to be restored.

### Configuring BART

Before configuring BART, establish the BART user account (the operating system user) to run the BART command line program. Then, to configure the BART host and each database server that is to be managed by BART, perform the following steps:

1. Assume superuser privileges, create the directory that will hold the BART backup catalog, and assign its ownership (with restrictive privileges) to the BART user account:

In this example, `bartuser` is the BART user account and `/opt/backup` is the BART backup catalog.

```
su root
mkdir /opt/backup
chown bartuser /opt/backup
chgrp bartuser /opt/backup
chmod 700 /opt/backup
```

- Navigate to the `/usr/edb/bart/etc` directory and copy the `bart.cfg.sample` file to create the BART configuration file (`bart.cfg`):

```
cp bart.cfg.sample bart.cfg
```

- Open the BART configuration file (`bart.cfg`) using an editor of your choice and scroll through the BART configuration file to edit the file as required; sample settings are included for your reference. You must add the mandatory parameters to the `[BART]` and `[ServerName]` sections. Default values may be used for optional parameters. For detailed information about parameter settings, see the *BART Installation and Upgrade Guide*, available at the [EDB website](#).

Parameters set in the `[BART]` section are applicable to all BART managed database servers, while parameters set in the `[ServerName]` section are applicable only to the specific server; `[ServerName]` settings override `[BART]` section settings.

In the following example, only mandatory parameters are set:

```
[BART]
bart_host= bartuser@192.168.169.199
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as12/bin/pg_basebackup

[EPAS12]
host = 127.0.0.1
user = repuser
cluster_owner = enterprisedb
```

The following table describes only mandatory parameters:

Parameters/Placeholder	Section	Description
<code>bart_host</code>	<code>[BART]</code>	Use this field to specify the BART user and the IP address of the host on which the BART utility is installed. Specify the value in the form of <code>&lt;bart_user&gt;@&lt;bart_host_address&gt;</code> .
<code>backup_path</code>	<code>[BART]</code>	Use this field to specify the path where all BART backups and archived WAL files will be stored. Ensure the BART user account holds privileges to create subdirectories and files within the location specified in the <code>backup_path</code> parameter. The default <code>backup_path</code> is BART backup catalog ( <code>/opt/backup</code> ).
<code>pg_basebackup_path</code>	<code>[BART]</code>	Use this field to specify the path to the <code>pg_basebackup</code> utility ( <code>/usr/edb/as&lt;xx&gt;/bin/pg_basebackup</code> ).
<code>[ServerName]</code>	<code>[ServerName]</code>	Specify the name of the database server to be backed up (for example, <code>[EPAS12]</code> ).
<code>host</code>	<code>[ServerName]</code>	Specify the IP address of the database server to be configured for backup.
<code>user</code>	<code>[ServerName]</code>	Specify the replication database user name used by BART to establish the connection to the database server for full backups.
<code>cluster_owner</code>	<code>[ServerName]</code>	Specify the Linux operating system user account that owns the database cluster.

- As a BART user, navigate to `/usr/edb/bart/bin` and invoke the following subcommand (omitting the `-s` option) to verify the `[BART]` section parameter settings:

```
bart CHECK-CONFIG
```

5. Authorize [SSH/SCP access](#) between the server and the BART host without a password prompt.
6. Create a [replication database user](#) for each database server that BART manages.
7. To enable continuous WAL archiving for any database server for which BART is to perform a backup, modify the `postgresql.conf` file and set it to:
  - `wal_level` to `replica` or higher (for Postgres 9.6 or later)
  - `archive_mode` to `on`
  - `archive_command` (if it is not set in the `bart.cfg` file)
  - `max_wal_senders` to a value high enough to leave at least one session available for the backup.

After setting the parameters, restart the database server.

8. To start the WAL scanner, navigate to `/usr/edb/bart/bin` as a BART user and execute the following command:

```
./bart-scanner
```

9. If you are using the default `archive_command`, then navigate to `/usr/edb/bart/bin` as a BART user, run the `INIT` subcommand without the `-o` option, and restart the database server:

```
bart INIT [ -s { <server_name> | all } ]
```

Where `<server_name>` is the name of the database server to be backed up.

If you have customized the `archive_command` setting in the `bart.cfg` file, run the `INIT` subcommand with the `-o` option to override any existing Postgresql `archive_command` setting in the `postgresql.conf` or the `postgresql.auto.conf` file, and restart the database server.

```
bart INIT [ -s { <server_name> | all } ] [ -o ]
```

10. To verify the database server parameter settings, as a BART user navigate to `/usr/edb/bart/bin` and invoke the `CHECK-CONFIG` subcommand with the `-s` option:

```
bart CHECK-CONFIG [ -s <server_name> ]
```

BART is now configured successfully. For detailed information about using BART, see the *EDB Backup and Recovery Tool User Guide* available at the [EDB website](#).

## Creating a Passwordless Connection

The following example enables SSH/SCP access on a CentOS 8.x host; similar (platform-specific) steps will apply to other platforms/versions. You must create a passwordless connection between the BART host (SSH/SCP client) and the database server (target SSH/SCP server), as well as a passwordless connection between the database server (SSH/SCP client) and the BART host (target SSH/SCP server).

1. Log in as the user account on the BART host that will be initiating the SSH or SCP connection and navigate to the user account's home directory and check for an existing `.ssh` subdirectory. If the `.ssh` directory does not exist, create one with the required privileges.
2. As a root user navigate to `/usr/edb/bart`, open the `/etc/ssh/sshd_config` file and set the `PubkeyAuthentication` parameter to `yes`.
3. Reload the configuration file:

```
service sshd reload
```

If you get any SSH or SCP errors, examine the log file (`/var/log/secure`).

- As a BART user, use the following command to generate the public key file; you can accept the default responses:

```
ssh-keygen -t rsa
```

The public key file named `id_rsa.pub` is created in the `.ssh` subdirectory.

- Use `SCP` to make a temporary copy of the public key file on the target server:

```
scp ~/.ssh/id_rsa.pub target_user@host_address:tmp.pub
```

- As a `target_user`, log into the target server using `ssh target_user@host_address` command and navigate to the user account's home directory to check if there is an existing `.ssh` subdirectory. If it does not exist, create one with the required privileges.
- Append the temporary client's public key file, `tmp.pub`, to the `authorized_keys` file:

```
cat tmp.pub >> ~/.ssh/authorized_keys
```

If an `authorized_keys` file does not exist, create a new file, but be careful not to completely replace any existing `authorized_keys` file.

- Ensure only the file owner (and not other groups or users) has access to `authorized_keys` file:

```
chmod 600 ~/.ssh/authorized_keys
```

- Delete the temporary public key file:

```
rm tmp.pub
```

Now, when logged into the BART host as a user, there should be no prompt for a password when you are connecting to the target database server:

```
ssh target_user@database_server_address
```

## Creating a Passwordless Connection Between the Database Server and the BART Host

If backups are to be taken from a given database server host, but restored to a different database server host, the passwordless SSH/SCP connections must be configured from the BART host to the database server host from which the backup is to be taken as well as from the BART host to the database server host to which the backup is to be restored.

An example of how to create a passwordless connection is documented in the *EDB Backup and Recovery Reference Guide*, available at the [EDB website](#).

Even when the Advanced Server database is on the same host as BART, and the Advanced Server database cluster owner is also the BART user account, a passwordless SSH/SCP connection must be established from the same user account to itself.

- On the database server, navigate into the target user account's home directory to check for an existing `.ssh` subdirectory. If it does not exist, create one in the user account's home directory with the required privileges.
- As a database server user, generate the public key file:

```
ssh-keygen -t rsa
```

3. Create a temporary copy of the public key file:

```
scp ~/.ssh/id_rsa.pub target_user@host_address:tmp.pub
```

4. As a target user, log into the BART host and navigate to the user account's home directory to check if there is an existing `.ssh` subdirectory. If it does not exist, create one with the required privileges:

```
ssh target_user@host_address
```

5. Append the client's temporary public key file to the `authorized_keys` file:

```
cat tmp.pub >> ~/.ssh/authorized_keys
```

If the `authorized_keys` file does not exist, create a new file, but do not completely replace any existing `authorized_keys` file.

6. Ensure that only the file owner (and not other groups or users) has access to `authorized_keys` file:

```
chmod 600 ~/.ssh/authorized_keys
```

7. Delete the temporary public key file:

```
rm tmp.pub
```

Now, when logged into the database server as a user, there should be no prompt for a password when you are connecting to the BART host:

```
ssh bart_user@bartip_address
```

### Creating a Replication Database User

1. To create a replication database user (a superuser), connect to the database server with the `psql` client, and invoke the following PostgreSQL command:

```
CREATE ROLE <repuser> WITH LOGIN SUPERUSER PASSWORD '<password>';
```

2. Specify this replication database user in the `user` parameter of the `bart.cfg` file.
3. The `pg_hba.conf` file must minimally permit the replication database user to have access to the database. The IP address from which the replication database user has access to the database is the BART host location. The replication database user must also be included in the `pg_hba.conf` file as a replication database connection if `pg_basebackup` is to be used for taking any backups.
4. To ensure there is no password prompt when connecting to the database server with the replication database user, a recommended method is to use the `.pgpass` file located in the BART user account's home directory (if it does not exist, you need to create the `.pgpass` file with the required privileges). The `.pgpass` file must contain an entry for each BART managed database server, and its corresponding replication database user and password.

## 4 EDB Postgres Backup and Recovery Reference Guide



This guide acts as a quick reference for BART subcommands and provides comprehensive examples of the following BART operations:

- Performing a full backup of database servers
- Performing a point-in-time recovery (PITR) on a remote PostgreSQL database server
- Restoring an incremental backup
- Restoring a database cluster with tablespaces
- Evaluating, marking, and deleting backups and incremental backups
- Configuring and operating local and remote database servers

For detailed information about BART subcommands and operations, see the EDB Backup and Recovery User Guide available at the [EDB website](#).

The document is organized as follows:

- See [Subcommands](#) to view BART subcommand examples.
- See [Examples](#) to view BART operations examples.
- See [Sample BART System](#) to view examples of both local and remote database server configuration and operation.

## 4.1 BART Subcommand Syntax and Examples

This section briefly describes each BART subcommand and provides an example.

Invoking BART

BART subcommands are invoked at the Linux command line as a BART user. You can invoke the `bart` program (located in the `<BART_HOME>/bin` directory) with the desired options to manage your BART installation.

The following examples demonstrate ways of invoking BART. In these examples, the BART user account is named `bartuser`.

```
$ su bartuser
Password:
$ export
LD_LIBRARY_PATH=/opt/PostgresPlus/9.6AS/lib/:$LD_LIBRARY_PATH
$ ./bart SHOW-SERVERS
```

To run BART from any current working directory:

```
$ su bartuser
Password:
$ export
LD_LIBRARY_PATH=/opt/PostgresPlus/9.6AS/lib/:$LD_LIBRARY_PATH
$ bart SHOW-SERVERS
```

Syntax for invoking BART

```
bart [ <general_option> ]... [ <subcommand> ] [<subcommand_option>]...
```

You can use either abbreviated or long option forms on the command line (for example `-h` or `--help`).

## General Options

You can specify the following general options with `bart`.

`-h` or (`--help`)

- Displays general syntax and information about BART usage.
- All subcommands support a help option (`-h`, `--help`). If the help option is specified, information is displayed regarding that particular subcommand. The subcommand, itself, is not executed.

The following code sample displays the result of invoking the `--help` option for the `BACKUP` subcommand:

```
-bash-4.2$ bart BACKUP --help
bart: backup and recovery tool

Usage:
bart BACKUP [OPTION]...

Options:
-h, --help Show this help message and exit
-s, --server Name of the server or 'all' (full backups only) to specify all servers
-F, --format=pl|t Backup output format (tar (default) or plain)
-z, --gzip Enables gzip compression of tar files
-c, --compress-level Specifies the compression level (1 through 9, 9 being
    best compression)
--backup-name Specify a friendly name for the current backup
--parent Specify parent backup for incremental backup
--check Verify checksum of required mbm files
```

`-v` (or `--version`)

The following code sample displays information returned by the `bart --version` subcommand:

```
[edb@localhost bin]$ bart --version
bart (EnterpriseDB) 2.5.2
[edb@localhost bin]$
```

`-d` (or `--debug`)

The following code sample displays debugging output returned by the `bart MANAGE` subcommand:

```
-bash-4.1$ bart -d MANAGE -n
DEBUG: Server: acctg, Now: 2015-04-17 16:34:03 EDT, RetentionWindow:
259200 (secs) ==> 72 hour(s)
DEBUG: Server: dev, Now: 2015-04-17 16:34:03 EDT, RetentionWindow:
1814400 (secs) ==> 504 hour(s)
DEBUG: Server: hr, Now: 2015-04-17 16:34:03 EDT, RetentionWindow:
7776000 (secs) ==> 2160 hour(s)
```

`-c` (or `--config-path`) `<config_file_path>`

The following code sample demonstrates using the `-c` option to specify a non-default configuration file name and installation location:

```
$ su bartuser
Password:
$ export
LD_LIBRARY_PATH=/opt/PostgresPlus/9.6AS/lib/:$LD_LIBRARY_PATH
$ bart -c /home/bartuser/bart.cfg SHOW-SERVERS
```

## 4.1.1 BACKUP

Use the **BACKUP** subcommand to create a full or incremental backup.

Syntax for a Full Backup:

```
bart BACKUP -s { <server_name> | all } [ -F { p | t } ]
[ -z ] [ -c <compression_level> ]
[ --backup-name <backup_name> ]
[ --thread-count <number_of_threads> ]
[ { --with-pg_basebackup | --no-pg_basebackup } ]
```

Syntax for an Incremental Backup:

```
bart BACKUP -s <server_name> [-Fp]
[ --parent { <backup_id> | <backup_name> } ]
[ --backup-name <backup_name> ]
[ --thread-count <number_of_threads> ]
```

Before performing an incremental backup, you must take a full backup. For more details about incremental backup, refer to *Block-Level Incremental Backup* in the *EDB Backup and Recovery User Guide* available at the [EDB website](#).

The following table describes the **BACKUP** options:

Options	Description
<code>-s { &lt;server_name&gt;   all }</code>	Use this option to specify the database server to be backed up.
<code>--server { &lt;server_name&gt;   all }</code>	Specify <code>&lt;server_name&gt;</code> to take a backup of the database server (as specified in the BART configuration file).
	Specify <code>all</code> to take a backup of all servers.

Options	Description
<pre>-F { p   t } --format { p   t }</pre>	<p>Use this option to specify the backup file format.</p> <p>Specify <b>p</b> option to take backup in plain text format and specify <b>t</b> option to take backup in tar format. If the <b>p</b> or <b>t</b> option is omitted, the default is tar format.</p> <p>Use <b>p</b> option with the <b>BACKUP</b> subcommand when streaming is used as a backup method.</p> <p>An incremental backup can only be taken in plain text format (<b>p</b>).</p>
<pre>-z (--gzip)</pre>	<p>This option is applicable only for full backup and <b>tar</b> format. Use this option to enable gzip compression of tar files using the default compression level (typically 6).</p>
<pre>-c &lt;compression_level&gt; --compress-level &lt;compression_level&gt;</pre>	<p>This is applicable only for full backup and tar format. Use this option to specify the gzip compression level on the tar file output. <b>&lt;compression_level&gt;</b> is a digit from 1 through 9, with 9 being the best compression.</p>
<pre>--backup-name &lt;backup_name&gt;</pre>	<p>Use this option to assign a user-defined, alphanumeric friendly name to the backup. The maximum permitted length of backup name is 49 characters.</p> <p>For detailed information about this parameter, see the EDB Backup and Recovery User Guide available at the <a href="#">EDB website</a>.</p> <p>If the option <b>--backup-name</b> is not specified and the <b>backup_name</b> parameter is not set for this database server in the BART configuration file, then the backup can only be referenced in other BART subcommands by the BART assigned backup identifier.</p>
<pre>--thread-count &lt;number_of_threads&gt;</pre>	<p>Use this option to specify the number of worker threads to run in parallel to copy blocks for a backup.</p> <p>For detailed information about the <b>--thread-count</b> parameter, see the EDB Backup and Recovery Installation and Upgrade Guide available at the <a href="#">EDB website</a>.</p>
<pre>--with- pg_basebackup</pre>	<p>This is applicable only for full backup. Use this option to specify the use of <b>pg_basebackup</b> to take a full backup. The number of thread counts in effect is ignored as given by the <b>thread_count</b> parameter in the BART configuration file.</p> <p>When taking a full backup, if the thread count in effect is greater than <b>1</b>, then the <b>pg_basebackup</b> utility is not used to take the full backup (parallel worker threads are used) unless the <b>--with-pg_basebackup</b> option is specified with the <b>BACKUP</b> subcommand.</p>
<pre>--no-pg_basebackup</pre>	<p>This is applicable only for full backup. Use this option to specify that <b>pg_basebackup</b> is not to be used to take a full backup.</p> <p>When taking a full backup, if the thread count in effect is only <b>1</b>, then the <b>pg_basebackup</b> utility is used to take the full backup unless the <b>--no-pg_basebackup</b> option is specified with the <b>BACKUP</b> subcommand.</p>
<pre>--parent { &lt;backup_id&gt;   &lt;backup_name&gt; }</pre>	<p>Use this option to take an incremental backup. The parent backup is a backup taken prior to the incremental backup; it can be either a full backup or an incremental backup.</p> <p><b>&lt;backup_id&gt;</b> is the backup identifier of a parent backup and <b>&lt;backup_name&gt;</b> is the user-defined alphanumeric name of a parent backup.</p>
<pre>--check</pre>	<p>This is applicable only for incremental backup. Use this option to verify if the required MBM files are present in the BART backup catalog before taking an incremental backup. However, an actual incremental backup is not taken when the <b>--check</b> option is specified.</p> <p>The <b>--parent</b> option must be used along with the <b>--check</b> option.</p>

## Examples

The following code sample demonstrates using variables with the **BACKUP** subcommand:

```
./bart backup -s ppas12 -Ft --backup-name "YEAR = %year MONTH =
```

```
%month DAY = %day"
```

```
./bart backup -s ppas12 -Ft --backup-name "YEAR = %year MONTH =  
%month DAY = %day %%"
```

```
./bart show-backups -s ppas12 -i "test backup"
```

The following code sample displays the result of creating a full backup in the default tar format with gzip compression when the **BACKUP** subcommand was invoked. Note that checksums are generated for the full backup and user-defined tablespaces for the tar format backup:

```
[edb@localhost bin]$ ./bart BACKUP -s hr -z  
INFO: DebugTarget - getVar(checkDiskSpace.bytesAvailable)  
INFO: new backup identifier generated 1567591909098  
INFO: creating 5 harvester threads  
NOTICE: all required WAL segments have been archived  
INFO: backup completed successfully  
INFO:  
BART VERSION: 2.5  
BACKUP DETAILS:  
BACKUP STATUS: active  
BACKUP IDENTIFIER: 1567591909098  
BACKUP NAME: none  
BACKUP PARENT: none  
BACKUP LOCATION: /home/edb/bkup_new/hr/1567591909098  
BACKUP SIZE: 13.91 MB  
BACKUP FORMAT: tar.gz  
BACKUP TIMEZONE: America/New_York  
XLOG METHOD: fetch  
BACKUP CHECKSUM(s): 0  
TABLESPACE(s): 3  
Oid      Name      Location  
16387    test1     /home/edb/tbl1  
16388    test2     /home/edb/tbl2  
16389    test3     /home/edb/tbl3  
  
START WAL LOCATION: 00000001000000000000000025  
STOP WAL LOCATION: 00000001000000000000000026  
BACKUP METHOD: streamed  
BACKUP FROM: master  
START TIME: 2019-09-04 06:11:49 EDT  
STOP TIME: 2019-09-04 06:11:53 EDT  
TOTAL DURATION: 4 sec(s)
```

The following code sample displays information about the directory containing the full backup:

```
[edb@localhost bin]$ number_of_threads>  
[edb@localhost bin]$ ls -l /home/edb/bkup_new/hr/  
total 8  
drwxrwxr-x. 3 edb edb   34 Aug 27 05:57 1566899819709  
drwxrwxr-x. 3 edb edb   58 Aug 27 05:57 1566899827751  
drwxrwxr-x. 3 edb edb 4096 Sep  4 06:11 1567591909098  
drwxrwxr-x. 2 edb edb 4096 Sep  4 06:11 archived_wals  
[edb@localhost bin]$
```

The following code sample displays information about the creation of a full backup while streaming the transaction log. Note that the `-Fp` option must be specified with the `BACKUP` subcommand when streaming is used as a backup method.

```
[edb@localhost bin]$ ./bart BACKUP -s ACCTG -Fp
INFO: DebugTarget - getVar(checkDiskSpace.bytesAvailable)
INFO: new backup identifier generated 1566898964200
INFO: creating 5 harvester threads
NOTICE: pg_stop_backup complete, all required WAL segments have been archived
INFO: backup completed successfully
INFO:
BART VERSION: 2.5
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1566898964200
BACKUP NAME: none
BACKUP PARENT: none
BACKUP LOCATION: /home/edb/bkup_new/acctg/1566898964200
BACKUP SIZE: 46.03 MB
BACKUP FORMAT: plain
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 0
START WAL LOCATION: 00000001000000000000000017
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2019-08-27 05:42:44 EDT
STOP TIME: 2019-08-27 05:42:46 EDT
TOTAL DURATION: 2 sec(s)
```

The following code sample displays the assignment of a user-defined backup name with the `--backup-name` option:

```
[edb@localhost bin]$ ./bart BACKUP -s acctg --backup-name acctg_%year-%month-%day
INFO: DebugTarget - getVar(checkDiskSpace.bytesAvailable)
INFO: new backup identifier generated 1566899004804
INFO: creating 5 harvester threads
NOTICE: pg_stop_backup complete, all required WAL segments have been archived
INFO: backup completed successfully
INFO:
BART VERSION: 2.5
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1566899004804
BACKUP NAME: acctg_2019-08-27
BACKUP PARENT: none
BACKUP LOCATION: /home/edb/bkup_new/acctg/1566899004804
BACKUP SIZE: 46.86 MB
BACKUP FORMAT: tar
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 0
START WAL LOCATION: 0000000100000000000000001A
BACKUP METHOD: streamed
```

```

BACKUP FROM: master
START TIME: 2019-08-27 05:43:24 EDT
STOP TIME: 2019-08-27 05:43:24 EDT
TOTAL DURATION: 0 sec(s)

```

The following code sample displays an incremental backup taken by specifying the `--parent` option. The option `-Fp` must be specified while taking an incremental backup as incremental backup can be taken only in plain text format.

```

[edb@localhost bin]$ ./bart BACKUP -s hr -Fp --parent hr_full_1 --backup-name
hr_incr_1
INFO: DebugTarget - getVar(checkDiskSpace.bytesAvailable)
INFO: checking /home/edb/bkup_new/hr/archived_wals for MBM files from 0/20000028 to
0/22000000
INFO: new backup identifier generated 1566899827751
INFO: creating 5 harvester threads
NOTICE: all required WAL segments have been archived
INFO: backup completed successfully
INFO:
BART VERSION: 2.5
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1566899827751
BACKUP NAME: hr_incr_1
BACKUP PARENT: 1566899819709
BACKUP LOCATION: /home/edb/bkup_new/hr/1566899827751
BACKUP SIZE: 7.19 MB
BACKUP FORMAT: plain
BACKUP TIMEZONE: America/New_York
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 0
START WAL LOCATION: 00000001000000000000000022
STOP WAL LOCATION: 00000001000000000000000023
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2019-08-27 05:57:07 EDT
STOP TIME: 2019-08-27 05:57:08 EDT
TOTAL DURATION: 1 sec(s)

```

## 4.1.2 CHECK-CONFIG

The `CHECK-CONFIG` subcommand checks the global parameter settings as well as the database server configuration in the BART configuration file.

The following syntax is used to check the BART configuration file global section settings.

```
bart CHECK-CONFIG
```

The following syntax is used to check the database server configuration settings.

```
bart CHECK-CONFIG [ -s <server_name> ]
```

The following table describes the **CHECK-CONFIG** option:

Option	Description
<code>-s &lt;server_name&gt; --server &lt;server_name&gt;</code>	<code>&lt;server_name&gt;</code> is the name of the database server whose configuration parameter settings are to be checked.

#### Example

The following code sample demonstrates successfully checking the BART configuration file global parameters with the **bart CHECK-CONFIG** command:

```
bash-4.1$ bart CHECK-CONFIG
INFO: Verifying that pg_basebackup is executable
INFO: success -
INFO: success - pg_basebackup(/usr/edb/as11/bin/pg_basebackup) returns
version 11.400000
```

The following code sample demonstrates successfully checking the BART configuration file database server parameters with the **bart CHECK-CONFIG** command with the `-s` option:

```
[edb@localhost bin]$ ./bart check-config -s hr
INFO: Checking server hr
INFO: Verifying cluster_owner and ssh/scp connectivity
INFO: success
INFO: Verifying user, host, and replication connectivity
INFO: success
INFO: Verifying that user is a database superuser
INFO: success
INFO: Verifying that cluster_owner can read cluster data files
INFO: success
INFO: Verifying that you have permission to write to vault
INFO: success
INFO: /home/edb/bkup_new/hr
INFO: Verifying database server configuration
INFO: success
INFO: Verifying that WAL archiving is working
INFO: waiting 30 seconds for
/home/edb/bkup_new/hr/archived_wals/0000000100000000000000001E
INFO: success
INFO: Verifying that bart-scanner is configured and running
INFO: success
```

### 4.1.3 DELETE

The **DELETE** subcommand removes the subdirectory and data files from the BART backup catalog for the specified backups along with archived WAL files.



Syntax:

```
bart DELETE -s <server_name>
-i { all | [']{ <backup_id> | <backup_name> },... }['] }
[ -n ]
```

Note that when invoking the **DELETE** subcommand, you must specify a database server.

For database servers under a retention policy, there are conditions where certain backups may not be deleted. For more information, see the EDB Backup and Recovery User Guide available at the [EDB website](#).

The following table describes the **DELETE** options:

Options	Description
<b>-s &lt;server_name&gt;</b> <b>--server &lt;server_name&gt;</b>	<b>&lt;server_name&gt;</b> is the name of the database server whose backups are to be deleted.
<b>-i { all   [']{ &lt;backup_id&gt;   &lt;backup_name&gt; },... }['] }</b> <b>--backupid { all   [']{ &lt;backup_id&gt;   &lt;backup_name&gt; },... }['] }</b>	<b>&lt;backup_id&gt;</b> is the backup identifier of the backup to be deleted. <b>&lt;backup_name&gt;</b> is the user-defined alphanumeric name for the backup. Multiple backup identifiers and backup names may be specified in a comma-separated list. The list must be enclosed within single quotes if there is any white space appearing before or after each comma (see <a href="#">Example</a> ). If <b>all</b> is specified, all backups and their archived WAL files for the specified database server are deleted.
<b>-n</b> <b>--dry-run</b>	Performs the test run and displays the results prior to physically removing files; no files are actually deleted.

### Example

The following code sample demonstrates deleting a backup from the specified database server:

```
[edb@localhost bin]$ ./bart DELETE -s acctg -i acctg_2019-08-27
INFO: deleting backup 'acctg_2019-08-27' of server 'acctg'
INFO: deleting backup '1566900093665'
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
'/home/edb/bkup_new/acctg/archived_wals/00000001000000000000000025'
is required, yet not available in archived_wals directory
INFO: backup(s) deleted
[edb@localhost bin]$
```

After the deletion, the BART backup catalog for the database server no longer contains the corresponding directory for the deleted **backup ID**. The following code sample displays information about **archived\_wals** subdirectory that no longer contains the backup WAL files:

```
[edb@localhost acctg]$ ls -l
total 16
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:03 1566900199604
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:03 1566900204377
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:03 1566900209087
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:05 1566900321228
drwxrwxr-x. 2 edb edb 6 Aug 27 06:01 archived_wals
```

The following code sample demonstrates deleting multiple backups from the database server.

```
[edb@localhost bin]$ ./bart DELETE -s acctg -i `1566988095633,1566988100760,
acctg_2019-08-28`
INFO: deleting backup `1566988095633` of server `acctg`
INFO: deleting backup `1566988095633`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup_new/acctg/archived_wals/00000000100000000000000037` is required,
yet not available in archived_wals directory
INFO: backup(s) deleted
INFO: deleting backup `1566988100760` of server `acctg`
INFO: deleting backup `1566988100760`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup_new/acctg/archived_wals/00000000100000000000000039` is
required, yet not available in archived_wals directory
INFO: backup(s) deleted
INFO: deleting backup `acctg_2019-08-28` of server `acctg`
INFO: deleting backup `1566988115512`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup_new/acctg/archived_wals/0000000010000000000000003C` is required,
yet not available in archived_wals directory
INFO: backup(s) deleted
[edb@localhost bin]$
[edb@localhost bin]$
[edb@localhost bin]$
[edb@localhost acctg]$
[edb@localhost acctg]$ ls -l
total 8
drwxrwxr-x. 3 edb edb 4096 Aug 28 06:28 1566988105086
drwxrwxr-x. 3 edb edb 4096 Aug 28 06:28 1566988109477
drwxrwxr-x. 2 edb edb 6 Aug 28 06:09 archived_wals
[edb@localhost acctg]$
```

### Deleting Multiple Backups with Space Characters

The following code sample demonstrates deleting multiple backups; since there are space characters in the comma-separated list, the entire list must be enclosed within single quotes:

```
[edb@localhost bin]$ ./bart DELETE -s acctg -i
`1566900199604,1566900204377,1566900209087`;
INFO: deleting backup `1566900199604` of server `acctg`
INFO: deleting backup `1566900199604`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup_new/acctg/archived_wals/00000000100000000000000028` is required,
yet not available in archived_wals directory
INFO: backup(s) deleted
INFO: deleting backup `1566900204377` of server `acctg`
INFO: deleting backup `1566900204377`
```

```

INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup_new/acctg/archived_wals/000000010000000000000002A` is required,
yet not available in archived_wals directory
INFO: backup(s) deleted
INFO: deleting backup `1566900209087` of server `acctg`
INFO: deleting backup `1566900209087`
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or will
be marked unused
WARNING: not marking any WALs as unused WALs, the WAL file
`/home/edb/bkup_new/acctg/archived_wals/000000010000000000000002C` is required,
yet not available in archived_wals directory
INFO: backup(s) deleted
[edb@localhost bin]$
[edb@localhost bin]$
[edb@localhost acctg]$ ls -l
total 4
drwxrwxr-x. 3 edb edb 4096 Aug 27 06:05 1566900321228
drwxrwxr-x. 2 edb edb 6 Aug 27 06:01 archived_wals
[edb@localhost acctg]$

```

## 4.1.4 INIT

The **INIT** subcommand is used to create the BART backup catalog directory, rebuild the BART **backupinfo** file, and set the **archive\_command** in the server based on the **archive\_command** setting in the **bart.cfg** file.

Syntax:

```

bart INIT [ -s { <server_name> | all } ] [ -o ]
[ -r [ -i { <backup_id> | <backup_name> | all } ] ]
[--no-configure]

```

The following table describes the **INIT** options:

Options	Description
<b>-s {</b> <b>&lt;server_name&gt;</b> <b>  all }</b> <b>--server {</b> <b>&lt;server_name&gt;</b> <b>  all }</b>	<b>&lt;server_name&gt;</b> is the name of the database server to which the <b>INIT</b> actions are to be applied. If <b>all</b> is specified or if the option is omitted, actions are applied to all servers.
<b>-o</b> <b>--override</b>	Overrides the existing Postgres <b>archive_command</b> configuration parameter setting in the <b>postgresql.conf</b> file or the <b>postgresql.auto.conf</b> file using the BART <b>archive_command</b> parameter in the BART configuration file. The <b>INIT</b> generated <b>archive command</b> string is written to the <b>postgresql.auto.conf</b> file.

Options	Description
<code>-r</code> <code>--rebuild</code>	Rebuilds the <code>backupinfo</code> file located in each backup subdirectory. If <code>all</code> is specified or if the option is omitted, the <code>backupinfo</code> files of all backups for the database servers specified by the <code>-s</code> option are recreated. This option is only intended for recovering from a situation where the <code>backupinfo</code> file has become corrupt. If the backup was initially created with a user-defined backup name, and then the <code>INIT -r</code> option is invoked to rebuild that <code>backupinfo</code> file, the user-defined backup name is no longer available. Thus, future references to the backup must use the backup identifier.
<code>-i {</code> <code>&lt;backup_id&gt;  </code> <code>&lt;backup_name&gt;</code> <code>  all }</code> <code>--backupid {</code> <code>&lt;backup_id&gt;  </code> <code>&lt;backup_name&gt;</code> <code>  all }</code>	<code>&lt;backup_id&gt;</code> is an integer, backup identifier and <code>&lt;backup_name&gt;</code> is the user-defined alphanumeric name for the backup. The <code>-i</code> option can only be used with the <code>-r</code> option.
<code>--no-configure</code>	Prevents the <code>archive_command</code> from being set in the PostgreSQL server.

## Examples

In the following code sample, you can see that `archive_mode = off` and `archive_command` is not set. After invoking the BART `INIT` subcommand, `archive_mode` is set to `on` and `archive_command` is set:

```
archive_mode = off # enables archiving; off, on, or always
### (change requires restart)
archive_command = ''
### command to use to archive a logfile segment
[edb@localhost bin]$ ./bart init -s ppas11
INFO: setting archive_mode/archive_command for server 'ppas11'
WARNING: archive_mode/archive_command is set. Restart the PostgreSQL
server using 'pg_ctl restart'
[edb@localhost bin]$
### Do not edit this file manually!
### It will be overwritten by the ALTER SYSTEM command.
archive_mode = 'on'
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f'
```

In the following code sample, you can see that `archive_mode = on`, and `archive_command` is not set. After invoking the `INIT` subcommand, `archive_command` is set:

```
archive_mode = on # enables archiving; off, on, or always
### (change requires restart)
archive_command = '' # command to use to archive a logfile segment
[edb@localhost bin]$ ./bart init -s ppas11
INFO: setting archive_mode/archive_command for server 'ppas11'
WARNING: archive_command is set. Reload the configuration in the
PostgreSQL server using pg_reload_conf() or 'pg_ctl reload'
[edb@localhost bin]$
### Do not edit this file manually!
### It will be overwritten by the ALTER SYSTEM command.
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f'
```

In the following code sample, you can see that `archive_mode = on` and `archive_command` are already set. After invoking the `INIT` subcommand, there is no change in their settings. Note that to override the existing `archive_command`, you must include the `-o` option.

```
archive_mode = on # enables archiving; off, on, or always
### (change requires restart)
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f' # command to use
to archive a logfile segment
### placeholders: %p = path of file to archive
[edb@localhost bin]$ ./bart init -s ppas11
INFO: setting archive_mode/archive_command for server 'ppas11'
WARNING: archive_command is not set for server 'ppas11'
[edb@localhost bin]$
### Do not edit this file manually!
### It will be overwritten by the ALTER SYSTEM command.
```

In the following code sample, you can see that `archive_mode = off` and `archive_command` is already set. After invoking the `INIT` subcommand `archive_mode` is set to `on`:

```
archive_mode = off # enables archiving; off, on, or always
### (change requires restart)
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f' # command to use
to archive a log file segment
[edb@localhost bin]$ ./bart init -s ppas11
INFO: setting archive_mode/archive_command for server 'ppas11'
WARNING: archive_mode/archive_command is set. Restart the PostgreSQL
server using 'pg_ctl restart'
### Do not edit this file manually!
### It will be overwritten by the ALTER SYSTEM command.
archive_mode = 'on'
archive_command = 'scp %p
edb@127.0.0.1:/home/edb/bkup/ppas11/archived_wals/%f'
```

In the following code sample an existing `archive_command` setting is overridden by resetting the `archive_command` in the PostgreSQL server with the `archive_command = 'cp %p %a/%f'` parameter from the `bart.cfg` file:

```
[BART]

bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup_edb
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]

host = 127.0.0.1
port = 5444
user = repuser
cluster_owner = enterprisedb
archive_command = 'cp %p %a/%f'
description = "Accounting"
```

The `archive_mode` and `archive_command` parameters in the database server are set as follows:

```
edb=# SHOW archive_mode;
archive_mode
-----
on
(1 row)
edb=# SHOW archive_command;
archive_command
-----
scp %p bartuser@192.168.2.22:/opt/backup/acctg/archived_wals/%f
(1 row)
```

Invoke the `INIT` subcommand with the `-o` option to override the current `archive_command` setting in the PostgreSQL server:

```
-bash-4.1$ bart INIT -s acctg -o
INFO: setting archive_mode/archive_command for server 'acctg'
WARNING: archive_command is set. Reload the configuration in the
PostgreSQL server using pg_reload_conf() or 'pg_ctl reload'
```

Reload the database server configuration; a restart of the database server is not necessary to reset only the `archive_command` parameter:

```
[root@localhost tmp]# service pps11 reload
```

The `archive_command` in the PostgreSQL server is now set as follows:

```
edb=# SHOW archive_command;
archive_command
-----
cp %p /opt/backup_edb/acctg/archived_wals/%f
(1 row)
```

The new command string is written to the `postgresql.auto.conf` file:

```
### Do not edit this file manually!
### It will be overwritten by ALTER SYSTEM command.
archive_command = 'cp %p /opt/backup_edb/acctg/archived_wals/%f'
```

When you invoke the BART `INIT` command with the `-r` option, BART rebuilds the `backupinfo` file using the content of the backup directory for the server specified or for all servers. The BART `backupinfo` file is initially created by the `BACKUP` subcommand and contains the backup information used by BART.

!!! Note If the backup was initially created with a user-defined backup name, and then the `INIT -r` option is invoked to rebuild the `backupinfo` file, the user-defined backup name is no longer available. Thus, future references to the backup must use the backup identifier.

The following code sample shows the `backupinfo` file location in a backup subdirectory:

```
[root@localhost acctg]# pwd
/opt/backup/acctg
[root@localhost acctg]# ls -l
total 4
```

```
drwx----- 2 enterprisedb enterprisedb 38 Oct 26 10:21 1477491569966
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Oct 26 10:19 archived_wals
[root@localhost acctg]# ls -l 1477491569966
total 61144
-rw-rw-r-- 1 enterprisedb enterprisedb 703 Oct 26 10:19 backupinfo
-rw-rw-r-- 1 enterprisedb enterprisedb 62603776 Oct 26 10:19 base.tar
```

The following code sample displays the `backupinfo` file content:

```
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1477491569966
BACKUP NAME: none
BACKUP PARENT: none
BACKUP LOCATION: /opt/backup/acctg/1477491569966
BACKUP SIZE: 59.70 MB
BACKUP FORMAT: tar
BACKUP TIMEZONE:
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 1
ChkSum File
84b3eeb1e3f7b3e75c2f689570d04f10 base.tar
TABLESPACE(s): 0
START WAL LOCATION: 2/A5000028 (file 000000001000000020000000A5)
STOP WAL LOCATION: 2/A50000C0 (file 000000001000000020000000A5)
CHECKPOINT LOCATION: 2/A5000028
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2016-10-26 10:19:30 EDT
LABEL: pg_basebackup base backup
STOP TIME: 2016-10-26 10:19:30 EDT
TOTAL DURATION: 0 sec(s)
```

The following code sample displays an error message if the `backupinfo` file is missing when invoking a BART subcommand:

```
-bash-4.2$ bart SHOW-BACKUPS
ERROR: 'backupinfo' file does not exist for backup '1477491569966'
please use 'INIT -r' to generate the file
```

The `backupinfo` file may be missing if the `BACKUP` subcommand did not complete successfully.

The following code sample displays information about rebuilding the `backupinfo` file of the specified backup for database server `acctg`:

```
-bash-4.1$ bart INIT -s acctg -r -i 1428346620427
INFO: rebuilding BACKUPINFO for backup '1428346620427' of server 'acctg'
INFO: backup checksum: ced59b72a7846ff8fb8afb6922c70649 of base.tar
```

The following code sample displays information about how the `backupinfo` files of all backups are rebuilt for all database servers:

```
-bash-4.1$ bart INIT -r

INFO: rebuilding BACKUPINFO for backup '1428347191544' of server 'acctg'
```

```
INFO: backup checksum: 1ac5c61f055c910db314783212f2544f of base.tar
INFO: rebuilding BACKUPINFO for backup '1428346620427' of server 'acctg'
INFO: backup checksum: ced59b72a7846ff8fb8afb6922c70649 of base.tar
INFO: rebuilding BACKUPINFO for backup '1428347198335' of server 'dev'
INFO: backup checksum: a8890dd8ab7e6be5d5bc0f38028a237b of base.tar
INFO: rebuilding BACKUPINFO for backup '1428346957515' of server 'dev'
INFO: backup checksum: ea62549cf090573625d4adeb7d919700 of base.tar
```

The following code sample displays information about invoking `BART INIT` with the `-r -i` option:

```
edb@localhost bin]$ ./bart init -s ppas11 -i 1551778898392 -r
INFO: rebuilding BACKUPINFO for backup '1551778898392' of server
'ppas11'
[edb@localhost bin]$ ls /home/edb/bkup/ppas11/1551778898392/
backupinfo backup_label base base-1.tar base-2.tar base-3.tar
base-4.tar base-5.tar base.tar
```

The following code sample displays information about invoking the `BART INIT` command with the `--no-configure` option. You can use the `--no-configure` option with the `INIT` subcommand to prevent the `archive_command` option from being set in the PostgreSQL server.

```
[edb@localhost bin]$ ./bart init -s ppas11 -o --no-configure
[edb@localhost bin]$
### Do not edit this file manually!
### It will be overwritten by the ALTER SYSTEM command.
```

## 4.1.5 MANAGE

The `MANAGE` subcommand can be invoked to:

- Evaluate backups, mark their status, and delete obsolete backups based on the `retention_policy` parameter in the BART configuration file.
- Compress the archived WAL files based on the `wal_compression` parameter in the BART configuration file.

Syntax:

```
bart MANAGE [ -s { <server_name> | all } ]
[ -l ] [ -d ]
[ -c { keep | nokeep }
-i { <backup_id> | <backup_name> | all } ]
[ -n ]
```

To view detailed information about the `MANAGE` subcommand and retention policy management, see *the EDB Backup and Recovery User Guide*. For information about setting the `wal_compression` parameter, see the *EDB Backup and Recovery Installation and Upgrade Guide*. These guides are available at the [EDB website](#).

The following table describes the `MANAGE` options:

Options	Description
---------	-------------



Options	Description
<code>-s [ &lt;server_name&gt;   all ]</code> <code>--server [ &lt;server_name&gt;   all ]</code>	<p><code>&lt;server_name&gt;</code> is the name of the database server to which the <b>MANAGE</b> actions are to be applied.</p> <p>If <b>all</b> is specified or if the <code>-s</code> option is omitted, actions are applied to all database servers.</p>
<code>-l</code> <code>--list-obsolete</code>	Lists the backups marked as obsolete.
<code>-d</code> <code>--delete-obsolete</code>	Deletes the backups marked as obsolete. This action physically deletes the backup along with its archived WAL files and any MBM files for incremental backups.
<code>-c { keep   nokeep }</code> <code>--change-status { keep   nokeep }</code>	<p>Specify <b>keep</b> to change the backup status to <b>keep</b> to retain the backup indefinitely.</p> <p>Specify <b>nokeep</b> to change the backup status back to <b>active</b>. You can then re-evaluate and possibly mark the backup as <b>obsolete</b> (according to the retention policy) using the <b>MANAGE</b> subcommand.</p> <p>The <code>-c</code> option can only be used with the <code>-i</code> option.</p>
<code>-i { &lt;backup_id&gt;   &lt;backup_name&gt;   all }</code> <code>--backupid { &lt;backup_id&gt;   &lt;backup_name&gt;   all }</code>	<p><code>&lt;backup_id&gt;</code> is a backup identifier and <code>&lt;backup_name&gt;</code> is the user-defined alphanumeric name for the backup.</p> <p>If <b>all</b> is specified, actions are applied to all backups.</p> <p>The <code>-i</code> option can only be used with the <code>-c</code> option.</p>
<code>-n</code> <code>--dry-run</code>	<p>Performs the test run and displays the results prior to actually implementing the actions as if the operation was performed, however, no changes are actually made.</p> <p>If you specify <code>-n</code> with the <code>-d</code> option, it displays which backups would be deleted, but does not actually delete the backups.</p> <p>If you specify <code>-n</code> with the <code>-c</code> option, it displays the keep or nokeep action, but does not actually change the backup status.</p> <p>If you specify <code>-n</code> alone with no other options or if you specify <code>-n</code> with only the <code>-s</code> option, it displays which active backups would be marked as obsolete, but does not actually change the backup status. In addition, no compression is performed on uncompressed, archived WAL files even if WAL compression is enabled for the database server.</p>

### Example

The following code sample performs a dry run for the specified database server displaying which active backups are evaluated as obsolete according to the retention policy, but does not actually change the backup status:

```
-bash-4.2$ bart MANAGE -s acctg -n
INFO: processing server 'acctg', backup '1482770807519'
INFO: processing server 'acctg', backup '1482770803000'
INFO: marking backup '1482770803000' as obsolete
```

```

INFO: 1 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1482770735155'
INFO: marking backup '1482770735155' as obsolete
INFO: 2 incremental(s) of backup '1482770735155' will be marked obsolete
INFO: marking incremental backup '1482770780423' as obsolete
INFO: marking incremental backup '1482770763227' as obsolete
INFO: 3 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: 2 Unused file(s) (WALs included) present, use 'MANAGE -l' for the
list

```

The following code sample marks active backups as obsolete according to the retention policy for the specified database server:

```

-bash-4.2$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1482770807519'
INFO: processing server 'acctg', backup '1482770803000'
INFO: marking backup '1482770803000' as obsolete
INFO: 1 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1482770735155'
INFO: marking backup '1482770735155' as obsolete
INFO: 2 incremental(s) of backup '1482770735155' will be marked obsolete
INFO: marking incremental backup '1482770780423' as obsolete
INFO: marking incremental backup '1482770763227' as obsolete
INFO: 3 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: 2 Unused file(s) (WALs included) present, use 'MANAGE -l' for the
list

```

The following code sample lists backups marked as obsolete for the specified database server:

```

-bash-4.2$ bart MANAGE -s acctg -l
SERVER NAME: acctg
BACKUP ID: 1482770803000
BACKUP STATUS: obsolete
BACKUP TIME: 2016-12-26 11:46:43 EST
BACKUP SIZE: 59.52 MB
WAL FILE(s): 1
WAL FILE: 00000000100000000100000055
SERVER NAME: acctg
BACKUP ID: 1482770735155
BACKUP STATUS: obsolete
BACKUP TIME: 2016-12-26 11:45:35 EST
BACKUP SIZE: 59.52 MB
INCREMENTAL BACKUP(s): 2
BACKUP ID: 1482770780423
BACKUP PARENT: 1482770735155
BACKUP STATUS: obsolete
BACKUP TIME: 2016-12-26 11:45:35 EST
BACKUP SIZE: 59.52 MB
BACKUP ID: 1482770763227
BACKUP PARENT: 1482770735155
BACKUP STATUS: obsolete
BACKUP TIME: 2016-12-26 11:45:35 EST
BACKUP SIZE: 59.52 MB

```

```

WAL FILE(s): 3
WAL FILE: 00000000100000000100000054
WAL FILE: 00000000100000000100000053
WAL FILE: 00000000100000000100000052
UNUSED FILE(s): 2
UNUSED FILE: 00000000100000000100000051
UNUSED FILE: 0000000010000000015100002800000000152000000.mbm

```

The following code sample deletes the obsolete backups for the specified database server:

```

-bash-4.2$ bart MANAGE -s acctg -d
INFO: removing all obsolete backups of server 'acctg'
INFO: removing obsolete backup '1482770803000'
INFO: 1 WAL file(s) will be removed
INFO: removing WAL file '00000000100000000100000055'
INFO: removing obsolete backup '1482770735155'
INFO: 3 WAL file(s) will be removed
INFO: 2 incremental(s) of backup '1482770735155' will be removed
INFO: removing obsolete incremental backup '1482770780423'
INFO: removing obsolete incremental backup '1482770763227'
INFO: removing WAL file '00000000100000000100000054'
INFO: removing WAL file '00000000100000000100000053'
INFO: removing WAL file '00000000100000000100000052'
INFO: 8 Unused file(s) will be removed
INFO: removing (unused) file '00000000100000000100000056.00000028.backup'
INFO: removing (unused) file '00000000100000000100000056'
INFO: removing (unused) file '00000000100000000100000055.00000028.backup'
INFO: removing (unused) file '00000000100000000100000054.00000028.backup'
INFO: removing (unused) file '00000000100000000100000053.00000028.backup'
INFO: removing (unused) file '00000000100000000100000052.00000028.backup'
INFO: removing (unused) file '00000000100000000100000051'
INFO: removing (unused) file
'0000000010000000015100002800000000152000000.mbm'

```

The following code sample changes the specified backup to keep status to retain it indefinitely:

```

-bash-4.2$ bart MANAGE -s acctg -c keep -i 1482770807519
INFO: changing status of backup '1482770807519' of server 'acctg' from
'active' to 'keep'
INFO: 1 WAL file(s) changed
-bash-4.2$ bart SHOW-BACKUPS -s acctg -i 1482770807519 -t
SERVER NAME : acctg
BACKUP ID : 1482770807519
BACKUP NAME : none
BACKUP PARENT : none
BACKUP STATUS : keep
BACKUP TIME : 2016-12-26 11:46:47 EST
BACKUP SIZE : 59.52 MB
WAL(S) SIZE : 16.00 MB
NO. OF WAL S : 1
FIRST WAL FILE : 00000000100000000100000057
CREATION TIME : 2016-12-26 11:52:47 EST
LAST WAL FILE : 00000000100000000100000057
CREATION TIME : 2016-12-26 11:52:47 EST

```

The following code sample resets the specified backup to active status:

```
-bash-4.2$ bart MANAGE -s acctg -c nokeep -i 1482770807519
INFO: changing status of backup '1482770807519' of server 'acctg' from
'keep' to 'active'
INFO: 1 WAL file(s) changed
-bash-4.2$ bart SHOW-BACKUPS -s acctg -i 1482770807519 -t
SERVER NAME : acctg
BACKUP ID : 1482770807519
BACKUP NAME : none
BACKUP PARENT : none
BACKUP STATUS : active
BACKUP TIME : 2016-12-26 11:46:47 EST
BACKUP SIZE : 59.52 MB
WAL(S) SIZE : 16.00 MB
NO. OF WAL S : 1
FIRST WAL FILE : 000000001000000001000000057
CREATION TIME : 2016-12-26 11:52:47 EST
LAST WAL FILE : 000000001000000001000000057
CREATION TIME : 2016-12-26 11:52:47 EST
```

The following code sample uses the enabled `wal_compression` parameter in the BART configuration file as shown by the following:

```
[ACCTG]

host = 127.0.0.1
port = 5445
user = enterprisedb
cluster_owner = enterprisedb
allow_incremental_backups = disabled
wal_compression = enabled
description = "Accounting"
```

When the `MANAGE` subcommand is invoked, the following message is displayed indicating that WAL file compression is performed:

```
-bash-4.2$ bart MANAGE -s acctg
INFO: 4 WAL file(s) compressed
WARNING: 'retention_policy' is not set for server 'acctg'
```

The following code sample shows the archived WAL files in compressed format:

```
-bash-4.2$ pwd
/opt/backup/acctg
-bash-4.2$ ls -l archived_wals
total 160
-rw----- 1 enterprisedb enterprisedb 27089 Dec 26 12:16
00000000100000000100000005B.gz
-rw----- 1 enterprisedb enterprisedb 305 Dec 26 12:17
00000000100000000100000005C.000000028.backup
-rw----- 1 enterprisedb enterprisedb 27112 Dec 26 12:17
00000000100000000100000005C.gz
-rw----- 1 enterprisedb enterprisedb 65995 Dec 26 12:18
00000000100000000100000005D.gz
```

```
-rw----- 1 enterprisedb enterprisedb 305 Dec 26 12:18
00000000100000000100000005E.00000028.backup
-rw----- 1 enterprisedb enterprisedb 27117 Dec 26 12:18
00000000100000000100000005E.gz
```

## 4.1.6 RESTORE

The **RESTORE** subcommand restores a backup and its archived WAL files for the designated database server to the specified directory location.

Syntax for Restore:

```
bart RESTORE -s <server_name> -p <restore_path>
[ -i { <backup_id> | <backup_name> } ]
[ -r <remote_user>@<remote_host_address> ]
[ -w <number_of_workers> ]
[ -t <timeline_id> ]
[ { -x <target_xid> | -g <target_timestamp> } ]
[ -c ]
```

To view detailed information about the **RESTORE** subcommand, see the *EDB Backup and Recovery User Guide* available at the [EDB website](#).

If the backup is restored to a different database cluster directory than where the original database cluster resided, then some operations dependent upon the database cluster location may fail. This happens if the supporting service scripts are not updated to reflect the new directory location of restored backup.

For information about the use and modification of service scripts, see the EDB Advanced Server Installation Guide available at the [EDB website](#).

The following table describes the **RESTORE** options:

Options	Description
<code>-s &lt;server_name&gt;</code> <code>--server &lt;server_name&gt;</code>	<code>&lt;server_name&gt;</code> is the name of the database server to be restored.
<code>-p --restore-path &lt;restore_path&gt;</code> <code>--restore-path &lt;restore_path&gt;</code>	<code>&lt;restore_path&gt;</code> is the directory path where the backup of the database server is to be restored. The directory must be empty and have the proper ownership and privileges assigned to it.
<code>-i { &lt;backup_id&gt;   &lt;backup_name&gt; }</code> <code>--backupid { &lt;backup_id&gt;   &lt;backup_name&gt; }</code>	<code>backup_id</code> is the backup identifier of the backup to be used for the restoration and <code>&lt;backup_name&gt;</code> is the user-defined alphanumeric name for the backup. If the option is omitted, the latest backup is restored by default.

Options	Description
<code>-r</code> <code>&lt;remote_user@remote_host_address&gt;</code>  <code>--remote-host</code> <code>&lt;remote_user@remote_host_address&gt;</code>	<p><code>&lt;remote_user&gt;</code> is the user account on the remote database server host that accepts a passwordless SSH/SCP login connection and is the owner of the directory where the backup is to be restored.</p> <p><code>&lt;remote_host_address&gt;</code> is the IP address of the remote host to which the backup is to be restored. This option must be specified if the <code>remote_host</code> parameter for this database server is not set in the BART configuration file.</p> <p>For information about the <code>remote_host</code> parameter, see the <i>EDB Backup and Recovery Installation and Upgrade Guide</i> available at the <a href="#">EDB website</a>.</p>
<code>-w &lt;number_of_workers&gt;</code> <code>--workers &lt;number_of_workers&gt;</code>	<p><code>&lt;number_of_workers&gt;</code> is the number of worker processes to run in parallel to stream the modified blocks of an incremental backup to the restore location. If the <code>-w</code> option is omitted, the default is <code>1</code> worker process.</p> <p>For example, if four worker processes are specified, four receiver processes on the restore host and four streamer processes on the BART host are used. The output of each streamer process is connected to the input of a receiver process.</p> <p>When the receiver gets to the point where it needs a modified block file, it obtains those modified blocks from its input. With this method, the modified block files are never written to the restore host disk.</p>
<code>-t &lt;timeline_id&gt;</code> <code>--target-tli &lt;timeline_id&gt;</code>	<p><code>&lt;timeline_id&gt;</code> is the integer identifier of the timeline to be used for replaying the archived WAL files for point-in-time recovery.</p>
<code>-x &lt;target_xid&gt;</code> <code>--target-xid &lt;target_xid&gt;</code>	<p><code>&lt;target_xid&gt;</code> is the integer identifier of the transaction ID that determines the transaction up to and including, which point-in-time recovery encompasses.</p>
<code>-g &lt;target_timestamp&gt;</code>  <code>--target-timestamp</code> <code>&lt;target_timestamp&gt;</code>	<p><code>&lt;target_timestamp&gt;</code> is the timestamp that determines the point in time up to and including, which point-in-time recovery encompasses.</p>
<code>-c</code>  <code>--copy-wals</code>	<p>Specify this option to copy archived WAL files from the BART backup catalog to <code>&lt;restore_path&gt;/archived_wals</code> directory. The <code>restore_command</code> retrieves the WAL files from <code>&lt;restore_path&gt;/archived_wals</code> for the database server archive recovery.</p> <p>If the <code>-c</code> option is omitted and the <code>copy_wals_during_restore</code> parameter in the BART configuration file is not enabled in a manner applicable to this database server, then the <code>restore_command</code> in the <code>postgresql.conf</code> retrieves the archived WAL files directly from the BART backup catalog.</p> <p>For information about the <code>copy_wals_during_restore</code> parameter, see the <i>EDB Backup and Recovery Installation and Upgrade Guide</i> available at the <a href="#">EDB website</a>.</p>

## Examples

The following code sample restores a database server(named `mktg`) to the `/opt/restore` directory up to timestamp `2015-12-15 10:47:00`:

```
-bash-4.1$ bart RESTORE -s mktg -i 1450194208824 -p /opt/restore -t 1 -g
```

```
'2015-12-15 10:47:00'
INFO: restoring backup '1450194208824' of server 'mktg'
INFO: restoring backup to enterprisedb@192.168.2.24:/opt/restore
INFO: base backup restored
INFO: WAL file(s) will be streamed from the BART host
INFO: writing recovery settings to postgresql.auto.conf file
INFO: archiving is disabled
INFO: tablespace(s) restored
```

The following parameters are set in the `postgresql.auto.conf` file:

```
restore_command = 'scp -o BatchMode=yes -o PasswordAuthentication=no
enterprisedb@192.168.2.22:/opt/backup/mktg/archived_wals/%f %p'
recovery_target_time = '2015-12-15 10:47:00'
recovery_target_timeline = 1
```

The following is a list of the restored files and subdirectories:

```
[root@localhost restore]# pwd
/opt/restore
[root@localhost restore]# ls -l
total 108
-rw----- 1 enterprisedb enterprisedb 208 Dec 15 10:43 backup_label
drwx----- 6 enterprisedb enterprisedb 4096 Dec 2 10:38 base
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 10:42 dbms_pipe
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 11:00 global
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_clog\
-rw----- 1 enterprisedb enterprisedb 4438 Dec 2 10:38 pg_hba.conf
-rw----- 1 enterprisedb enterprisedb 1636 Nov 10 15:38 pg_ident.conf
drwxr-xr-x 2 enterprisedb enterprisedb 4096 Dec 15 10:42 pg_log
drwx----- 4 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_multixact
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 10:42 pg_notify
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_serial
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_snapshots
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 10:42 pg_stat
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 10:43 pg_stat_tmp
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_subtrans
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 11:00 pg_tblspc
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_twophase
-rw----- 1 enterprisedb enterprisedb 4 Nov 10 15:38 PG_VERSION
drwx----- 2 enterprisedb enterprisedb 4096 Dec 15 11:00 pg_xlog
-rw----- 1 enterprisedb enterprisedb 23906 Dec 15 11:00
postgresql.conf
-rw-r--r-- 1 enterprisedb enterprisedb 217 Dec 15 11:00
postgresql.auto.conf
```

### Example

The following code sample performs a `RESTORE` operation with the `copy_wals_during_restore` parameter enabled to copy the archived WAL files to the local `<restore_path>/archived_wals` directory:

```
-bash-4.1$ bart RESTORE -s hr -i hr_2017-03-29T13:50 -p
/opt/restore_pg96 -t 1 -g '2017-03-29 14:01:00'
INFO: restoring backup 'hr_2017-03-29T13:50' of server 'hr'
INFO: base backup restored
```

```
INFO: copying WAL file(s) to
postgres@192.168.2.24:/opt/restore_pg96/archived_wals
INFO: writing recovery settings to postgresql.auto.conf file
INFO: archiving is disabled
INFO: permissions set on $PGDATA
INFO: restore completed successfully
```

The following parameters are set in the `postgresql.auto.conf` file:

```
restore_command = 'cp archived_wals/%f %p'
recovery_target_time = '2017-03-29 14:01:00'
recovery_target_timeline = 1
```

The following is a list of the restored files and subdirectories:

```
-bash-4.1$ pwd
/opt/restore_pg96
-bash-4.1$ ls -l
total 128
drwxr-xr-x  2 postgres postgres 4096 Mar 29 14:27 archived_wals
-rw-----  1 postgres postgres 206 Mar 29 13:50 backup_label
drwx-----  5 postgres postgres 4096 Mar 29 12:25 base
drwx-----  2 postgres postgres 4096 Mar 29 14:27 global
drwx-----  2 postgres postgres 4096 Mar 29 12:25 pg_clog
drwx-----  2 postgres postgres 4096 Mar 29 12:25 pg_commit_ts
drwx-----  2 postgres postgres 4096 Mar 29 12:25 pg_dynshmem
-rw-----  1 postgres postgres 4212 Mar 29 13:18 pg_hba.conf
-rw-----  1 postgres postgres 1636 Mar 29 12:25 pg_ident.conf
drwxr-xr-x  2 postgres postgres 4096 Mar 29 13:45 pg_log
drwx-----  4 postgres postgres 4096 Mar 29 12:25 pg_logical
drwx-----  4 postgres postgres 4096 Mar 29 12:25 pg_multixact
drwx-----  2 postgres postgres 4096 Mar 29 13:43 pg_notify
drwx-----  2 postgres postgres 4096 Mar 29 12:25 pg_replslot
drwx-----  2 postgres postgres 4096 Mar 29 12:25 pg_serial
drwx-----  2 postgres postgres 4096 Mar 29 12:25 pg_snapshots
drwx-----  2 postgres postgres 4096 Mar 29 13:43 pg_stat
drwx-----  2 postgres postgres 4096 Mar 29 13:50 pg_stat_tmp
drwx-----  2 postgres postgres 4096 Mar 29 12:25 pg_subtrans
drwx-----  2 postgres postgres 4096 Mar 29 12:25 pg_tblspc
drwx-----  2 postgres postgres 4096 Mar 29 12:25 pg_twophase
-rw-----  1 postgres postgres 4 Mar 29 12:25 PG_VERSION
drwx-----  3 postgres postgres 4096 Mar 29 14:27 pg_xlog
-rw-----  1 postgres postgres 169 Mar 29 13:24 postgresql.auto.conf
-rw-r--r--  1 postgres postgres 21458 Mar 29 14:27 postgresql.conf
-rw-r--r--  1 postgres postgres 118 Mar 29 14:27 postgresql.auto.conf
```

## 4.1.7 SHOW-SERVERS

The `SHOW-SERVERS` subcommand displays information for the managed database servers listed in the BART configuration file.



Syntax:

```
bart SHOW-SERVERS [ -s { <server_name> | all } ]
```

The following table describes the **SHOW-SERVERS** option:

Option	Description
<code>-s { &lt;server_name&gt;   all }</code>	<code>&lt;server_name&gt;</code> is the name of the database server to which the <b>SHOW-SERVERS</b> actions are to be applied.
<code>--server { &lt;server_name&gt;   all }</code>	If <code>all</code> is specified or if the <code>-s</code> option is omitted, the actions are applied to all database servers.

Example

The following code sample shows all the database servers managed by BART as returned by the **SHOW-SERVERS** subcommand:

```
-bash-4.2$ bart SHOW-SERVERS
SERVER NAME : acctg
BACKUP FRIENDLY NAME: acctg_%year-%month-%dayT%hour:%minute
HOST NAME : 127.0.0.1
USER NAME : enterprisedb
PORT : 5444
REMOTE HOST :
RETENTION POLICY : 6 Backups
DISK UTILIZATION : 0.00 bytes
NUMBER OF ARCHIVES : 0
ARCHIVE PATH : /opt/backup/acctg/archived_wals
ARCHIVE COMMAND : (disabled)
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
INCREMENTAL BACKUP : DISABLED
DESCRIPTION : "Accounting"
SERVER NAME : hr
BACKUP FRIENDLY NAME: hr_%year-%month-%dayT%hour:%minute
HOST NAME : 192.168.2.24
USER NAME : postgres
PORT : 5432
REMOTE HOST : postgres@192.168.2.24
RETENTION POLICY : 6 Backups
DISK UTILIZATION : 0.00 bytes
NUMBER OF ARCHIVES : 0
ARCHIVE PATH : /opt/backup/hr/archived_wals
ARCHIVE COMMAND : (disabled)
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
INCREMENTAL BACKUP : DISABLED
DESCRIPTION : "Human Resources"
SERVER NAME : mktg
BACKUP FRIENDLY NAME: mktg_%year-%month-%dayT%hour:%minute
HOST NAME : 192.168.2.24
USER NAME : repuser
```

```

PORT : 5444
REMOTE HOST : enterprisedb@192.168.2.24
RETENTION POLICY : 6 Backups
DISK UTILIZATION : 0.00 bytes
NUMBER OF ARCHIVES : 0
ARCHIVE PATH : /opt/backup/mktg/archived_wals
ARCHIVE COMMAND : (disabled)
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
INCREMENTAL BACKUP : DISABLED\
DESCRIPTION : "Marketing"

```

## 4.1.8 SHOW-BACKUPS

The **SHOW-BACKUPS** subcommand displays the backup information for the managed database servers.

Syntax:

```

bart SHOW-BACKUPS [ -s { <server_name> | all } ]
[ -i { <backup_id> | <backup_name> | all } ]
[ -t ]

```

The following table describes the **SHOW-BACKUPS** options:

Options	Description
<b>-s { &lt;server_name&gt;   all }</b>	<b>&lt;server_name&gt;</b> is the name of the database server whose backup information is to be displayed.
<b>--server { &lt;server_name&gt;   all }</b>	If <b>all</b> is specified or if the option is omitted, the backup information for all database servers is displayed.
<b>-i { &lt;backup_id&gt;   &lt;backup_name&gt;   all }</b>	<b>&lt;backup_id&gt;</b> is a backup identifier and <b>&lt;backup_name&gt;</b> is the user-defined alphanumeric name for the backup.
<b>--backupid { &lt;backup_id&gt;   &lt;backup_name&gt;   all }</b>	If <b>all</b> is specified or if the option is omitted, all backup information for the relevant database server is displayed.
<b>-t</b> <b>--toggle</b>	Displays detailed backup information in list format. If the option is omitted, the default is a tabular format.

Example

The following code sample shows the backup from database server **dev**:

```

-bash-4.2$ bart SHOW-BACKUPS -s dev
SERVER NAME      BACKUP ID      BACKUP NAME      BACKUP PARENT
BACKUP TIME      BACKUP SIZE    WAL(s) SIZE      WAL FILES STATUS
dev              1477579596637  dev_2016-10-27T10:46:36  none
2016-10-27 10:46:37 EDT 54.50 MB        96.00 MB         6          active

```

The following code sample shows detailed information using the `-t` option:

```
-bash-4.2$ bart SHOW-BACKUPS -s dev -i 1477579596637 -t
SERVER NAME : dev
BACKUP ID : 1477579596637
BACKUP NAME : dev_2016-10-27T10:46:36
BACKUP PARENT : none
BACKUP STATUS : active
BACKUP TIME : 2016-10-27 10:46:37 EDT
BACKUP SIZE : 54.50 MB
WAL(S) SIZE : 80.00 MB
NO. OF WAL S : 5
FIRST WAL FILE : 000000001000000010000000EC
CREATION TIME : 2016-10-27 10:46:37 EDT
LAST WAL FILE : 000000001000000010000000F0
CREATION TIME : 2016-10-27 11:22:01 EDT
```

The following code sample shows a listing of an incremental backup along with its parent backup:

```
-bash-4.2$ bart SHOW-BACKUPS
SERVER NAME          BACKUP ID          BACKUP NAME          BACKUP PARENT
BACKUP TIME          BACKUP SIZE        WAL(s) SIZE          WAL FILES          STATUS
acctg                1477580293193      acctg_2016-10-27     none
2016-10-27 10:58:13 EDT 16.45 MB           16.00 MB             1                  active
acctg 1477580111358 acctg_2016-10-27 none 2016-10-27 10:55:11 EDT 59.71
MB 16.00 MB 1 active
```

The following code sample shows the complete, detailed information of the incremental backup and the parent backup:

```
-bash-4.2$ bart SHOW-BACKUPS -t
SERVER NAME : acctg
BACKUP ID : 1477580293193
BACKUP NAME : none
BACKUP PARENT : acctg_2016-10-27
BACKUP STATUS : active
BACKUP TIME : 2016-10-27 10:58:13 EDT
BACKUP SIZE : 16.45 MB
WAL(S) SIZE : 16.00 MB
NO. OF WAL S : 1
FIRST WAL FILE : 000000001000000020000000D9
CREATION TIME : 2016-10-27 10:58:13 EDT
LAST WAL FILE : 000000001000000020000000D9
CREATION TIME : 2016-10-27 10:58:13 EDT
SERVER NAME : acctg
BACKUP ID : 1477580111358
BACKUP NAME : acctg_2016-10-27
BACKUP PARENT : none
BACKUP STATUS : active
BACKUP TIME : 2016-10-27 10:55:11 EDT
BACKUP SIZE : 59.71 MB
WAL(S) SIZE : 16.00 MB
NO. OF WAL S : 1
FIRST WAL FILE : 000000001000000020000000D8
CREATION TIME : 2016-10-27 10:55:12 EDT
LAST WAL FILE : 000000001000000020000000D8
```

CREATION TIME : 2016-10-27 10:55:12 EDT

## 4.1.9 VERIFY-CHKSUM

The **VERIFY-CHKSUM** subcommand verifies the MD5 checksums of the full backups and any user-defined tablespaces for the specified database server or for all database servers. The checksum is verified by comparing the current checksum of the backup against the checksum when the backup was taken.

!!! Note The **VERIFY-CHKSUM** subcommand is only used for tar format backups.

Syntax:

```
bart VERIFY-CHKSUM
[ -s { <server_name> | all } ]
[ -i { <backup_id> | <backup_name> | all } ]
```

The following table describes the **VERIFY-CHKSUM** options:

Options	Description
<b>-s</b> { <server_name>   all }	<b>&lt;server_name&gt;</b> is the name of the database server whose tar backup checksums are to be verified.
<b>--server</b> { <server_name>   all }	If <b>all</b> is specified or if the <b>-s</b> option is omitted, the checksums of all tar backups are verified for all database servers.
<b>-i</b> {<backup_id>   <backup_name>   all }	<b>&lt;backup_id&gt;</b> is the backup identifier of a tar format full backup whose checksum is to be verified along with any user-defined tablespaces. <b>&lt;backup_name&gt;</b> is the user-defined alphanumeric name for the full backup.
<b>--backupid</b> {<backup_id>   <backup_name>   all }	If <b>all</b> is specified or if the <b>-i</b> option is omitted, the checksums of all tar backups for the relevant database server are verified.

Example

The following code sample verifies the checksum of all tar format backups of the specified database server:

```
-bash-4.1$ bart VERIFY-CHKSUM -s acctg -i all
SERVER NAME    BACKUP ID      VERIFY
acctg          1430239348243 OK
acctg          1430232284202 OK
acctg          1430232016284 OK
acctg          1430231949065 OK
acctg          1429821844271 OK
```

## 4.1.10 Running the BART WAL Scanner

The BART WAL scanner is used to process each WAL file to find and record modified blocks in a corresponding MBM file. As a BART account user, use the BART WAL scanner to invoke the `bart-scanner` program located in the `<BART_HOME>/bin` directory.

For detailed information about the WAL scanner and its usage, see the EDB Backup and Recovery User Guide available at the [EDB website](#).

Syntax:

```
bart-scanner
[ -d ]
[ -c <config_file_path> ]
{ -h |
-v |
--daemon |
-p <mbm_file_path> |
<wal_file_path> |
RELOAD |
STOP
```

When the `bart-scanner` program is invoked, it forks a separate process for each database server enabled with the `allow_incremental_backups` parameter.

The WAL scanner processes can run in either the foreground or background depending upon usage of the `--daemon` option:

- If the `--daemon` option is specified, the WAL scanner process runs in the background. All output messages can be viewed in the BART log file.
- If the `--daemon` option is omitted, the WAL scanner process runs in the foreground. All output messages can be viewed from the terminal running the program as well as in the BART log file.

The following table describes the `VERIFY-CHKSUM` options.

Options	Description
<code>-h --help</code>	Displays general syntax and information on WAL scanner usage.
<code>-v --version</code>	Displays the WAL scanner version information.
<code>-d --debug</code>	Displays debugging output while executing the WAL scanner with any of its options.
<code>-c &lt;config_file_path&gt; --config-path &lt;config_file_path&gt;</code>	Specifies <code>&lt;config_file_path&gt;</code> as the full directory path to a BART configuration file. Use this option if you do not want to use the default BART configuration file <code>&lt;BART_HOME&gt;/etc/bart.cfg</code>
<code>--daemon</code>	Runs the WAL scanner as a background process.
<code>-p &lt;mbm_file_path&gt; --print &lt;mbm_file_path&gt;</code>	Specifies the full directory path to an MBM file whose content is to be printed. The <code>archived_wals</code> directory as specified in the <code>archive_path</code> parameter in the <code>bart.cfg</code> file contains the MBM files.

Options	Description
<code>&lt;wal_file_path&gt;</code>	Specifies the full directory path to a WAL file to be scanned. The archive path directory contains the WAL files. Use it if a WAL file in the archive path is missing its MBM file. This option is to be used for assisting the EnterpriseDB support team for debugging problems that may have been encountered.
<code>RELOAD</code>	Reloads the BART configuration file. The keyword <code>RELOAD</code> is case-insensitive. The <code>RELOAD</code> option is useful if you make changes to the configuration file after the WAL scanner has been started. It will reload the configuration file and adjust the WAL scanners accordingly. For example, if a server section allowing incremental backups is removed from the BART configuration file, then the process attached to that server will stop. Similarly, if a server allowing incremental backups is added, a new WAL scanner process will be launched to scan the WAL files of that server.
<code>STOP</code>	Stops the WAL scanner. The keyword <code>STOP</code> is not case-sensitive.

### Example

The following code sample demonstrates starting the WAL scanner to run interactively. The WAL scanner begins scanning existing WAL files in the archive path that have not yet been scanned (that is, there is no corresponding MBM file for the WAL file):

```
-bash-4.2$ bart-scanner
INFO: process created for server 'acctg', pid = 5287
INFO: going to parse backlog of WALs, if any.
INFO: WAL file to be processed: 000000001000000000000000ED
INFO: WAL file to be processed: 000000001000000000000000EE
INFO: WAL file to be processed: 000000001000000000000000EF
INFO: WAL file to be processed: 000000001000000000000000F0
INFO: WAL file to be processed: 000000001000000000000000F1
```

The following code sample is the content of the archive path showing the MBM files created for the WAL files. (The user name and group name of the files have been removed from the example to list the WAL files and MBM files in a more readable manner):

```
[root@localhost archived_wals]# pwd
/opt/backup/acctg/archived_wals
[root@localhost archived_wals]# ls -l
total 81944
-rw----- 1 ... 16777216 Dec 20 09:10 000000001000000000000000ED
-rw----- 1 ... 16777216 Dec 20 09:06 000000001000000000000000EE
-rw----- 1 ... 16777216 Dec 20 09:11 000000001000000000000000EF
-rw----- 1 ... 16777216 Dec 20 09:15 000000001000000000000000F0
-rw----- 1 ... 16777216 Dec 20 09:16 000000001000000000000000F1
-rw----- 1 ... 305 Dec 20 09:16 000000001000000000000000F1.00000028.backup
-rw-rw-r-- 1 ... 161 Dec 20 09:18
000000001000000000ED00002800000000EE000000.mbm
-rw-rw-r-- 1 ... 161 Dec 20 09:18
000000001000000000EE00002800000000EF000000.mbm
-rw-rw-r-- 1 ... 161 Dec 20 09:18
000000001000000000EF00002800000000F0000000.mbm
-rw-rw-r-- 1 ... 161 Dec 20 09:18
000000001000000000F000002800000000F1000000.mbm
-rw-rw-r-- 1 ... 161 Dec 20 09:18
000000001000000000F100002800000000F2000000.mbm
```

To stop the interactively running WAL scanner, either enter `ctrl-C` at the terminal running the WAL scanner or invoke the `bart-scanner` program from another terminal with the `STOP` option:

```
-bash-4.2$ bart-scanner STOP
-bash-4.2$
```

The terminal on which the WAL scanner was running interactively appears as follows after it has been stopped:

```
-bash-4.2$ bart-scanner
INFO: process created for server 'acctg', pid = 5287
INFO: going to parse backlog of WALs, if any.
INFO: WAL file to be processed: 000000001000000000000000ED
INFO: WAL file to be processed: 000000001000000000000000EE
INFO: WAL file to be processed: 000000001000000000000000EF
INFO: WAL file to be processed: 000000001000000000000000F0
INFO: WAL file to be processed: 000000001000000000000000F1
INFO: bart-scanner stopped
-bash-4.2$
```

The following code sample demonstrates invoking the WAL scanner to run as a background process with the `--daemon` option:

```
-bash-4.2$ bart-scanner --daemon
-bash-4.2$
```

The WAL scanner runs as a background process. There is also a separate background process for each database server that has been enabled for WAL scanning with the `allow_incremental_backups` parameter in the BART configuration file:

```
-bash-4.2$ ps -ef | grep bart
enterpr+  4340  1    0   09:48   ? 00:00:00 bart-scanner --daemon
enterpr+  4341 4340  0   09:48   ? 00:00:00 bart-scanner --daemon
enterpr+  4415 3673  0   09:50   pts/0 00:00:00 grep    --color=auto bart
```

To stop the WAL scanner processes, invoke the WAL scanner with the `STOP` option:

```
-bash-4.2$ bart-scanner STOP
-bash-4.2$
```

The following command demonstrates scanning an individual WAL file:

```
-bash-4.2$ bart-scanner /opt/backup/acctg/archived_wals/000000001000000000000000FF
-bash-4.2$
```

To print the content of an MBM file for assisting the EnterpriseDB support team for debugging problems that may have been encountered, use the `-p` option to specify the file as shown in the following code sample:

```
-bash-4.2$ bart-scanner -p
/opt/backup/acctg/archived_wals/000000001000000000FF000028000000001000000000.mbm

Header:
Version: 1.0:90500:1.2.0
Scan Start: 2016-12-20 10:02:11 EST, Scan End: 2016-12-20 10:02:11 EST, Diff: 0
sec(s)
Start LSN: ff000028, End LSN: 100000000, TLI: 1
```

```
flags: 0, Check Sum: f9cfe66ae2569894d6746b61503a767d
```

```
Path: base/14845/16384
```

```
NodeTag: BLOCK_CHANGE
```

```
Relation: relPath base/14845/16384, isTSNode 0, Blocks
```

```
*.....
```

```
First modified block: 0
```

```
Total modified blocks: 1
```

```
Path: base/14845/16391
```

```
NodeTag: BLOCK_CHANGE
```

```
Relation: relPath base/14845/16391, isTSNode 0, Blocks
```

```
*.....
```

```
First modified block: 0
```

```
Total modified blocks: 1
```

## 4.2 Additional Examples

This section lists examples of the following BART operations.

- Restoring a database cluster with tablespaces.
- Restoring an incremental backup.
- Managing backups.
- Managing incremental backups.

### Restoring a Database Cluster with Tablespaces

The following code sample illustrates taking a backup and restoring a database cluster on a remote host containing tablespaces. For detailed information regarding using tablespaces, see the EDB Backup and Recovery User Guide available at the [EDB website](#).

On an Advanced Server database running on a remote host, the following tablespaces are created for use by two tables:

```
edb=# CREATE TABLESPACE tblspc_1 LOCATION '/mnt/tablespace_1';
CREATE TABLESPACE
edb=# CREATE TABLESPACE tblspc_2 LOCATION '/mnt/tablespace_2';
CREATE TABLESPACE
edb=# \db
```

List of tablespaces		
Name	Owner	Location
pg_default	enterprisedb	
pg_global	enterprisedb	
tblspc_1	enterprisedb	/mnt/tablespace_1
tblspc_2	enterprisedb	/mnt/tablespace_2

(4 rows)

```
edb=# CREATE TABLE tbl_tblspc_1 (c1 TEXT) TABLESPACE tblspc_1;
CREATE TABLE
```



```
edb=# CREATE TABLE tbl_tblspc_2 (c1 TEXT) TABLESPACE tblspc_2;
CREATE TABLE
edb=# \d tbl_tblspc_1
Table "enterprisedb.tbl_tblspc_1"
Column | Type | Modifiers
-----+-----+-----
c1      | text |
Tablespace: "tblspc_1"

edb=# \d tbl_tblspc_2
Table "enterprisedb.tbl_tblspc_2"
Column | Type | Modifiers
-----+-----+-----
c1      | text |
Tablespace: "tblspc_2"
```

The following code sample shows the OIDs assigned to the tablespaces and the symbolic links to the tablespace directories:

```
-bash-4.1$ pwd
/opt/PostgresPlus/9.6AS/data/pg_tblspc
-bash-4.1$ ls -l
total 0
lrwxrwxrwx 1 enterprisedb enterprisedb 17 Nov 16 16:17 16587 ->/mnt/tablespace_1
lrwxrwxrwx 1 enterprisedb enterprisedb 17 Nov 16 16:17 16588 ->/mnt/tablespace_2
```

The BART configuration file contains the following settings. Note that the `tablespace_path` parameter does not have to be set at this point.

```
[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]
host = 192.168.2.24
port = 5444
user = repuser
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
tablespace_path =
description = "Accounting"
```

After the necessary configuration steps are performed to ensure BART manages the remote database server, a full backup is taken as shown in the following code sample:

```
-bash-4.1$ bart BACKUP -s acctg

INFO: creating backup for server 'acctg'
INFO: backup identifier: '1447709811516'
54521/54521 kB (100%), 3/3 tablespaces

INFO: backup completed successfully
```

```

INFO: backup checksum: 594f69fe7d26af991d4173d3823e174f of 16587.tar
INFO: backup checksum: 7a5507567729a21c98a15c948ff6c015 of base.tar
INFO: backup checksum: ae8c62604c409635c9d9e82b29cc0399 of 16588.tar
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1447709811516
BACKUP NAME: none
BACKUP LOCATION: /opt/backup/acctg/1447709811516
BACKUP SIZE: 53.25 MB
BACKUP FORMAT: tar
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 3
ChkSum File
594f69fe7d26af991d4173d3823e174f 16587.tar
7a5507567729a21c98a15c948ff6c015 base.tar
ae8c62604c409635c9d9e82b29cc0399 16588.tar

TABLESPACE(s): 2
Oid Name Location
16587 tblspc_1 /mnt/tablespace_1
16588 tblspc_2 /mnt/tablespace_2
START WAL LOCATION: 00000001000000000000000000F
BACKUP METHOD: streamed
BACKUP FROM: master
START TIME: 2015-11-16 16:36:51 EST
STOP TIME: 2015-11-16 16:36:52 EST
TOTAL DURATION: 1 sec(s)

```

Note that in the output from the preceding example, checksums are generated for the tablespaces as well as the full backup.

Within the backup subdirectory `1447709811516` of the BART backup catalog, the tablespace data is stored with file names `16587.tar.gz` and `16588.tar.gz` as shown below:

```

-bash-4.1$ pwd
/opt/backup/acctg
-bash-4.1$ ls -l
total 8
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 16:36 1447709811516
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 16:43 archived_wals
-bash-4.1$ ls -l 1447709811516
total 54536
-rw-rw-r-- 1 enterprisedb enterprisedb 19968 Nov 16 16:36 16587.tar
-rw-rw-r-- 1 enterprisedb enterprisedb 19968 Nov 16 16:36 16588.tar
-rw-rw-r-- 1 enterprisedb enterprisedb 949 Nov 16 17:05 backupinfo
-rw-rw-r-- 1 enterprisedb enterprisedb 55792640 Nov 16 16:36 base.tar

```

When you are ready to restore the backup, in addition to creating the directory to which the main database cluster is to be restored, you must prepare the directories to which the tablespaces are to be restored.

On the remote host, directories `/opt/restore_tblspc_1` and `/opt/restore_tblspc_2` are created and assigned the proper ownership and permissions as shown by the following example. The main database cluster is to be restored to `/opt/restore`.

```
[root@localhost opt]# mkdir restore_tblspc_1
[root@localhost opt]# chown enterprisedb restore_tblspc_1
[root@localhost opt]# chgrp enterprisedb restore_tblspc_1
[root@localhost opt]# chmod 700 restore_tblspc_1

[root@localhost opt]# mkdir restore_tblspc_2
[root@localhost opt]# chown enterprisedb restore_tblspc_2
[root@localhost opt]# chgrp enterprisedb restore_tblspc_2
[root@localhost opt]# chmod 700 restore_tblspc_2
[root@localhost opt]# ls -l
total 20
drwxr-xr-x 3 root daemon 4096 Nov 10 15:38 PostgresPlus
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:40 restore
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:40
restore_tblspc_1
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:41
restore_tblspc_2
drwxr-xr-x. 2 root root 4096 Nov 22 2013 rh
```

Set the `tablespace_path` parameter in the BART configuration file to specify the tablespace directories. The remote host user and IP address are specified by the `remote_host` configuration parameter.

```
[ACCTG]

host = 192.168.2.24
port = 5444
user = repuser
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
tablespace_path =
16587=/opt/restore_tblspc_1;16588=/opt/restore_tblspc_2

description = "Accounting"
```

The following code sample demonstrates invoking the `RESTORE` subcommand:

```
-bash-4.1$ bart RESTORE -s acctg -i 1447709811516 -p /opt/restore
INFO: restoring backup '1447709811516' of server 'acctg'
INFO: restoring backup to enterprisedb@192.168.2.24:/opt/restore
INFO: base backup restored
INFO: archiving is disabled
INFO: tablespace(s) restored
```

The following code sample shows the restored full backup (including the restored tablespaces):

```
bash-4.1$ pwd
/opt
-bash-4.1$ ls -l restore
total 104
-rw----- 1 enterprisedb enterprisedb 206 Nov 16 16:36 backup_label.old
drwx----- 6 enterprisedb enterprisedb 4096 Nov 10 15:38 base
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:46 global
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_clog
-rw----- 1 enterprisedb enterprisedb 4438 Nov 10 16:23 pg_hba.conf
-rw----- 1 enterprisedb enterprisedb 1636 Nov 10 15:38 pg_ident.conf
```

```

drwxr-xr-x 2 enterprisedb enterprisedb 4096 Nov 16 17:45 pg_log
drwx----- 4 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_multixact
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:45 pg_notify
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_serial
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_snapshots
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:47 pg_stat
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:47 pg_stat_tmp
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_subtrans
drwx----- 2 enterprisedb enterprisedb 4096 Nov 16 17:42 pg_tblspc
drwx----- 2 enterprisedb enterprisedb 4096 Nov 10 15:38 pg_twophase
-rw----- 1 enterprisedb enterprisedb 4 Nov 10 15:38 PG_VERSION
drwx----- 3 enterprisedb enterprisedb 4096 Nov 16 17:47 pg_xlog
-rw----- 1 enterprisedb enterprisedb 23906 Nov 16 17:42 postgresql.conf
-rw----- 1 enterprisedb enterprisedb 61 Nov 16 17:45 postmaster.opts
-bash-4.1$
-bash-4.1$ ls -l restore_tblspc_1
total 4
drwx----- 3 enterprisedb enterprisedb 4096 Nov 16 16:18
PG_9.6_201306121
-bash-4.1$ ls -l restore_tblspc_2
total 4
drwx----- 3 enterprisedb enterprisedb 4096 Nov 16 16:18
PG_9.6_201306121

```

The symbolic links in the `pg_tblspc` subdirectory point to the restored directory location:

```

bash-4.1$ pwd
/opt/restore/pg_tblspc
-bash-4.1$ ls -l
total 0
lrwxrwxrwx 1 enterprisedb enterprisedb 21 Nov 16 17:42 16587 ->
/opt/restore_tblspc_1
lrwxrwxrwx 1 enterprisedb enterprisedb 21 Nov 16 17:42 16588 ->
/opt/restore_tblspc_2

```

`psql` queries also show the restored tablespaces:

```

edb=# \db

```

List of tablespaces		
Name	Owner	Location
pg_default	enterprisedb	
pg_global	enterprisedb	
tblspc_1	enterprisedb	/opt/restore_tblspc_1
tblspc_2	enterprisedb	/opt/restore_tblspc_2

## Restoring an Incremental Backup

Restoring an incremental backup may require additional setup steps depending upon the host on which the incremental backup is to be restored. For more information, see the EDB Backup and Recovery User Guide available at the [EDB website](#).

This section provides an example of creating backup chains and then restoring an incremental backup.

## Creating a Backup Chain

A *backup chain* is the set of backups consisting of a full backup and all of its successive incremental backups. Tracing back on the parent backups of all incremental backups in the chain eventually leads back to that single, full backup.

In the following example, the `allow_incremental_backups` parameter is set to `enabled` in the BART configuration file to permit incremental backups on the listed database server:

```
[BART]

bart_host= enterprisedb@192.168.2.27
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]

host = 127.0.0.1
port = 5445
user = enterprisedb
cluster_owner = enterprisedb
allow_incremental_backups = enabled
description = "Accounting"
```

After the database server has been started with WAL archiving enabled to the BART backup catalog, the WAL scanner is started:

```
-bash-4.2$ bart-scanner --daemon
```

First, a full backup is taken.

```
-bash-4.2$ bart BACKUP -s acctg --backup-name full_1
INFO: creating backup for server 'acctg'
INFO: backup identifier: '1490649204327'\
63364/63364 kB (100%), 1/1 tablespace
INFO: backup completed successfully
INFO: backup checksum: aae27d4a7c09dffc82f423221154db7e of base.tar
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1490649204327
BACKUP NAME: full_1
BACKUP PARENT: none
BACKUP LOCATION: /opt/backup/acctg/1490649204327
BACKUP SIZE: 61.88 MB
BACKUP FORMAT: tar
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 1
ChkSum File
aae27d4a7c09dffc82f423221154db7e base.tar
TABLESPACE(s): 0
START WAL LOCATION: 0000000100000000000000000000000E
BACKUP METHOD: streamed
BACKUP FROM: master
```

```

START TIME: 2017-03-27 17:13:24 EDT
STOP TIME: 2017-03-27 17:13:25 EDT
TOTAL DURATION: 1 sec(s)

```

A series of incremental backups are taken. The first incremental backup specifies the full backup as the parent. Each successive incremental backup then uses the preceding incremental backup as its parent.

```

-bash-4.2$ bart BACKUP -s acctg -F p --parent full_1 --backup-name
incr_1-a
INFO: creating incremental backup for server 'acctg'
INFO: checking mbm files /opt/backup/acctg/archived_wals
INFO: new backup identifier generated 1490649255649
INFO: reading directory /opt/backup/acctg/archived_wals
INFO: all files processed
NOTICE: pg_stop_backup complete, all required WAL segments have been
archived
INFO: incremental backup completed successfully
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1490649255649
BACKUP NAME: incr_1-a
BACKUP PARENT: 1490649204327
BACKUP LOCATION: /opt/backup/acctg/1490649255649
BACKUP SIZE: 16.56 MB
BACKUP FORMAT: plain
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 0
TABLESPACE(s): 0
START WAL LOCATION: 0000000010000000000000000010
STOP WAL LOCATION: 0000000010000000000000000010
BACKUP METHOD: pg_start_backup
BACKUP FROM: master
START TIME: 2017-03-27 17:14:15 EDT
STOP TIME: 2017-03-27 17:14:16 EDT
TOTAL DURATION: 1 sec(s)
-bash-4.2$ bart BACKUP -s acctg -F p --parent incr_1-a --backup-name
incr_1-b
INFO: creating incremental backup for server 'acctg'
INFO: checking mbm files /opt/backup/acctg/archived_wals
INFO: new backup identifier generated 1490649336845
INFO: reading directory /opt/backup/acctg/archived_wals
INFO: all files processed
NOTICE: pg_stop_backup complete, all required WAL segments have been
archived
INFO: incremental backup completed successfully
.
.
.
-bash-4.2$ bart BACKUP -s acctg -F p --parent incr_1-b --backup-name
incr_1-c
INFO: creating incremental backup for server 'acctg'
INFO: checking mbm files /opt/backup/acctg/archived_wals
INFO: new backup identifier generated 1490649414316

```

```
INFO: reading directory /opt/backup/acctg/archived_wals
INFO: all files processed
NOTICE: pg_stop_backup complete, all required WAL segments have been
archived
INFO: incremental backup completed successfully
.
.
.
```

The following output of the `SHOW-BACKUPS` subcommand lists the backup chain, which are backups `full_1`, `incr_1-a`, `incr_1-b`, and `incr_1-c`.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
SERVER NAME  BACKUP ID      BACKUP NAME    BACKUP PARENT  BACKUP TIME ...
acctg        1490649414316  incr_1-c       incr_1-b       2017-03-27 17:16:55 ...
acctg        1490649336845  incr_1-b       incr_1-a       2017-03-27 17:15:37 ...
acctg        1490649255649  incr_1-a       full_1         2017-03-27 17:14:16 ...
acctg        1490649204327  full_1        none           2017-03-27 17:13:25 ...
```

For the `full backup full_1`, the `BACKUP PARENT` field contains `none`. For each incremental backup, the `BACKUP PARENT` field contains the backup identifier or name of its parent backup.

A second backup chain is created in the same manner with the `BACKUP` subcommand. The following example shows the addition of the resulting, second backup chain consisting of full backup `full_2` and incremental backups `incr_2-a` and `incr_2-b`.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
SERVER NAME  BACKUP ID      BACKUP NAME    BACKUP PARENT  BACKUP TIME ...
acctg        1490649605607  incr_2-b       incr_2-a       2017-03-27 17:20:06 ...
acctg        1490649587702  incr_2-a       full_2         2017-03-27 17:19:48 ...
acctg        1490649528633  full_2        none           2017-03-27 17:18:49 ...
acctg        1490649414316  incr_1-c       incr_1-b       2017-03-27 17:16:55 ...
acctg        1490649336845  incr_1-b       incr_1-a       2017-03-27 17:15:37 ...
acctg        1490649255649  incr_1-a       full_1         2017-03-27 17:14:16 ...
acctg        1490649204327  full_1        none           2017-03-27 17:13:25 ...
```

The following additional incremental backups starting with `incr_1-b-1`, which designates `incr_1-b` as the parent, results in the forking from that backup into a second line of backups in the chain consisting of `full_1`, `incr_1-a`, `incr_1-b`, `incr_1-b-1`, `incr_1-b-2`, and `incr_1-b-3` as shown in the following list:

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
SERVER NAME  BACKUP ID      BACKUP NAME    BACKUP PARENT  BACKUP TIME ...
acctg        1490649791430  incr_1-b-3     incr_1-b-2     2017-03-27 17:23:12 ...
acctg        1490649763929  incr_1-b-2     incr_1-b-1     2017-03-27 17:22:44 ...
acctg        1490649731672  incr_1-b-1     incr_1-b       2017-03-27 17:22:12 ...
acctg        1490649605607  incr_2-b       incr_2-a       2017-03-27 17:20:06 ...
acctg        1490649587702  incr_2-a       full_2         2017-03-27 17:19:48 ...
acctg        1490649528633  full_2        none           2017-03-27 17:18:49 ...
acctg        1490649414316  incr_1-c       incr_1-b       2017-03-27 17:16:55 ...
acctg        1490649336845  incr_1-b       incr_1-a       2017-03-27 17:15:37 ...
acctg        1490649255649  incr_1-a       full_1         2017-03-27 17:14:16 ...
acctg        1490649204327  full_1        none           2017-03-27 17:13:25 ...
```

## Restoring an Incremental Backup

Restoring an incremental backup is done with the **RESTORE** subcommand in the same manner as for restoring a full backup. Specify the backup identifier or backup name of the incremental backup to be restored as shown in the following example.

```
-bash-4.2$ bart RESTORE -s acctg -p /opt/restore -i incr_1-b
INFO: restoring incremental backup 'incr_1-b' of server 'acctg'
INFO: base backup restored
INFO: archiving is disabled
INFO: permissions set on $PGDATA
INFO: incremental restore completed successfully
```

Restoring incremental backup **incr\_1-b** as shown by the preceding example results in the restoration of full backup **full\_1**, then incremental backups **incr\_1-a** and finally, **incr\_1-b**.

## Managing Backups

This section illustrates evaluating, marking, and deleting backups using the **MANAGE** subcommand using a redundancy retention policy and a recovery window retention policy. For detailed information about the **MANAGE** subcommand, see the *EDB Backup and Recovery User Guide* available at the [EDB website](#).

### Using a Redundancy Retention Policy

The following code sample uses a redundancy retention policy to evaluate, mark, and delete backups as shown by the following server configuration:

```
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 BACKUPS
description = "Accounting"
```

The following list is the set of backups. Note that the last backup in the list has been marked as **keep**.

```
-bash-4.1$ bart SHOW-BACKUPS -s acctg
```

SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE	WAL(s) SIZE
acctg	1428768344061	2015-04-11 12:05:46 EDT	5.72 MB	48.00 MB
3	active			
acctg	1428684537299	2015-04-10 12:49:00 EDT	5.72 MB	272.00 MB
17	active			
acctg	1428589759899	2015-04-09 10:29:27 EDT	5.65 MB	96.00 MB
6	active			
acctg	1428502049836	2015-04-08 10:07:30 EDT	55.25 MB	96.00 MB
6	active			
acctg	1428422324880	2015-04-07 11:58:45 EDT	54.53 MB	32.00 MB
2	active			
acctg	1428355371389	2015-04-06 17:22:53 EDT	5.71 MB	16.00 MB
1	keep			

Invoke the **MANAGE** subcommand with the **-n** option to perform a dry run to observe which active backups would be



changed to obsolete according to the retention policy as shown in the following code sample:

```
-bash-4.1$ bart MANAGE -s acctg -n
INFO: processing server 'acctg', backup '1428768344061'
INFO: processing server 'acctg', backup '1428684537299'
INFO: processing server 'acctg', backup '1428589759899'
INFO: processing server 'acctg', backup '1428502049836'
INFO: marking backup '1428502049836' as obsolete
INFO: 6 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1428422324880'
INFO: marking backup '1428422324880' as obsolete
INFO: 2 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1428355371389'
```

The dry run shows that backups **1428502049836** and **1428422324880** would be marked as **obsolete**.

!!! Note A dry run does not change the backup status. The two backups that would be considered obsolete are still marked as **active**:

```
-bash-4.1$ bart SHOW-BACKUPS -s acctg
```

SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE	WAL(s) SIZE
acctg	1428768344061	2015-04-11 12:05:46 EDT	5.72 MB	48.00 MB
3	active			
acctg	1428684537299	2015-04-10 12:49:00 EDT	5.72 MB	272.00 MB
17	active			
acctg	1428589759899	2015-04-09 10:29:27 EDT	5.65 MB	96.00 MB
6	active			
acctg	1428502049836	2015-04-08 10:07:30 EDT	55.25 MB	96.00 MB
6	active			
acctg	1428422324880	2015-04-07 11:58:45 EDT	54.53 MB	32.00 MB
2	active			
acctg	1428355371389	2015-04-06 17:22:53 EDT	5.71 MB	16.00 MB
1	keep			

Invoke the **MANAGE** subcommand omitting the **-n** option to change and mark the status of the backups as **obsolete**:

```
-bash-4.1$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1428768344061'
INFO: processing server 'acctg', backup '1428684537299'
INFO: processing server 'acctg', backup '1428589759899'
INFO: processing server 'acctg', backup '1428502049836'
INFO: marking backup '1428502049836' as obsolete
INFO: 6 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1428422324880'
INFO: marking backup '1428422324880' as obsolete
INFO: 2 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1428355371389'
```

The obsolete backups can be observed in a number of ways. Use the **MANAGE** subcommand with the **-l** option to list the **obsolete** backups:

```
-bash-4.1$ bart MANAGE -s acctg -l
INFO: 6 WAL file(s) will be removed
SERVER NAME: acctg
```

```

BACKUP ID: 1428502049836
BACKUP STATUS: obsolete
BACKUP TIME: 2015-04-08 10:07:30 EDT
BACKUP SIZE: 55.25 MB
WAL FILE(s): 6
WAL FILE: 00000000100000000100000003
WAL FILE: 00000000100000000100000002
WAL FILE: 00000000100000000100000001
WAL FILE: 00000000100000000100000000
WAL FILE: 000000001000000000000000E3
WAL FILE: 000000001000000000000000E2
INFO: 2 WAL file(s) will be removed
SERVER NAME: acctg
BACKUP ID: 1428422324880
BACKUP STATUS: obsolete
BACKUP TIME: 2015-04-07 11:58:45 EDT
BACKUP SIZE: 54.53 MB
WAL FILE(s): 2
WAL FILE: 000000001000000000000000E1
WAL FILE: 000000001000000000000000E0

```

The **STATUS** field of the **SHOW-BACKUPS** subcommand displays the current status:

```

-bash-4.1$ bart SHOW-BACKUPS -s acctg
SERVER NAME  BACKUP ID      BACKUP TIME          BACKUP SIZE  WAL(s) SIZE
WAL FILES    STATUS
acctg        1428768344061  2015-04-11 12:05:46 EDT  5.72 MB      48.00 MB
3            active
acctg        1428684537299  2015-04-10 12:49:00 EDT  5.72 MB      272.00 MB
17           active
acctg        1428589759899  2015-04-09 10:29:27 EDT  5.65 MB      96.00 MB
6            active
acctg        1428502049836  2015-04-08 10:07:30 EDT  55.25 MB     96.00 MB
6            obsolete
acctg        1428422324880  2015-04-07 11:58:45 EDT  54.53 MB     32.00 MB
2            obsolete
acctg        1428355371389  2015-04-06 17:22:53 EDT  5.71 MB      16.00 MB
1            keep

```

The details of an individual backup can be displayed using the **SHOW-BACKUPS** subcommand with the **-t** option. Note the status in the **BACKUP STATUS** field.

```

-bash-4.1$ bart SHOW-BACKUPS -s acctg -i 1428502049836 -t
SERVER NAME : acctg
BACKUP ID : 1428502049836
BACKUP NAME : none
BACKUP STATUS : obsolete
BACKUP TIME : 2015-04-08 10:07:30 EDT
BACKUP SIZE : 55.25 MB
WAL(S) SIZE : 96.00 MB
NO. OF WAL S : 6
FIRST WAL FILE : 000000001000000000000000E2
CREATION TIME : 2015-04-08 10:07:30 EDT
LAST WAL FILE : 00000000100000000100000003
CREATION TIME : 2015-04-09 10:25:46 EDT

```

Use the **MANAGE** subcommand with the **-d** option to physically delete the **obsolete** backups including the unneeded WAL files.

```
-bash-4.1$ bart MANAGE -s acctg -d
INFO: removing all obsolete backups of server 'acctg'
INFO: removing obsolete backup '1428502049836'
INFO: 6 WAL file(s) will be removed
INFO: removing WAL file '00000000100000000100000003'
INFO: removing WAL file '00000000100000000100000002'
INFO: removing WAL file '00000000100000000100000001'
INFO: removing WAL file '00000000100000000100000000'
INFO: removing WAL file '000000001000000000000000E3'
INFO: removing WAL file '000000001000000000000000E2'
INFO: removing obsolete backup '1428422324880'
INFO: 2 WAL file(s) will be removed
INFO: removing WAL file '000000001000000000000000E1'
INFO: removing WAL file '000000001000000000000000E0'
```

The **SHOW-BACKUPS** subcommand now displays the remaining backups marked as **active** or **keep**:

```
-bash-4.1$ bart SHOW-BACKUPS -s acctg
```

SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE	WAL(s)
SIZE				
WAL FILES	STATUS			
acctg	1428768344061	2015-04-11 12:05:46 EDT	5.72 MB	48.00 MB
3	active			
acctg	1428684537299	2015-04-10 12:49:00 EDT	5.72 MB	272.00 MB
17	active			
acctg	1428589759899	2015-04-09 10:29:27 EDT	5.65 MB	96.00 MB
6	active			
acctg	1428355371389	2015-04-06 17:22:53 EDT	5.71 MB	16.00 MB
1	keep			

## Using a Recovery Window Retention Policy

This section illustrates the evaluation, marking, and deletion of backup using a recovery window retention policy. To use the recovery window retention policy, set the **retention\_policy** parameter to the desired length of time for the recovery window.

This section provides examples of the following:

- How to view the calculated recovery window.
- How to evaluate, mark, and delete backup using a recovery window retention policy.

### Viewing the Recovery Window

You can view the actual, calculated recovery window by invoking any of the following subcommands:

- **MANAGE** subcommand in debug mode (along with the **-n** option).
- **SHOW-SERVERS** subcommand.

#### Viewing the Recovery Window Using the Manage Subcommand

When invoking BART in debug mode with the `MANAGE` subcommand and the `-n` option, the length of the recovery window is calculated based on the `retention_policy` setting and the current date/time.

For example, using the following `retention_policy` settings:

[ACCTG]

```
host = 127.0.0.1
port = 5444
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 DAYS
backup-name = acctg_%year-%month-%dayT%hour:%minute:%second
description = "Accounting"
```

[DEV]

```
host = 127.0.0.1
port = 5445
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 WEEKS
description = "Development"
```

[HR]

```
host = 127.0.0.1
port = 5432
user = postgres
retention_policy = 3 MONTHS
description = "Human Resources"
```

If the `MANAGE` subcommand is invoked in debug mode along with the `-n` option on 2015-04-17, the following results are displayed:

```
-bash-4.1$ bart -d MANAGE -n
DEBUG: Server: acctg, Now: 2015-04-17 16:34:03 EDT, RetentionWindow:
259200 (secs) ==> 72 hour(s)
DEBUG: Server: dev, Now: 2015-04-17 16:34:03 EDT, RetentionWindow:
1814400 (secs) ==> 504 hour(s)
DEBUG: Server: hr, Now: 2015-04-17 16:34:03 EDT, RetentionWindow:
7776000 (secs) ==> 2160 hour(s)
```

For server `acctg`, 72 hours translates to a recovery window of 3 days.

For server `dev`, 504 hours translates to a recovery window of 21 days (3 weeks).

For server `hr`, 2160 hours translates to a recovery window of 90 days (3 months).

For a setting of `<max_number> MONTHS`, the calculated total number of days for the recovery window is dependent upon the actual number of days in the preceding months from the current date/time. Thus, `<max_number> MONTHS` is not always exactly equivalent to `<max_number> x 30 DAYS`. For example, if the current date/time is in the month of March, a 1-month recovery window would be equivalent to only 28 days because the preceding month is February. Thus, for a current date of March 31, a 1-month recovery window would start on March 3. However, the typical result is that the day of the month of the starting recovery window boundary will be the same day of the month of when the `MANAGE` subcommand is invoked.

## Viewing the Recovery Window Using the Show-Servers Subcommand

This section provides an example of viewing the recovery window using the `SHOW-SERVERS` subcommand; the `RETENTION POLICY` field displays the start of the recovery window.

In the following code sample, the recovery window retention policy setting considers the backups taken within a 3-day recovery window as the active backups.

```
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 DAYS
description = "Accounting"
```

The start of the 3-day recovery window displayed in the `RETENTION POLICY` field is `2015-04-07 14:57:36 EDT` when the `SHOW-SERVERS` subcommand is invoked on `2015-04-10`.

At this current point in time, backups taken on or after `2015-04-07 14:57:36 EDT` would be considered active. Backups taken prior to `2015-04-07 14:57:36 EDT` would be considered obsolete except for backups marked as `keep`.

```
-bash-4.1$ date
Fri Apr 10 14:57:33 EDT 2015
-bash-4.1$
-bash-4.1$ bart SHOW-SERVERS -s acctg
SERVER NAME      : acctg
HOST NAME        : 127.0.0.1
USER NAME        : enterprisedb
PORT             : 5444
REMOTE HOST      :
RETENTION POLICY  : 2015-04-07 14:57:36 EDT
DISK UTILIZATION  : 824.77 MB
NUMBER OF ARCHIVES : 37
ARCHIVE PATH      : /opt/backup/acctg/archived_wals
ARCHIVE COMMAND   : cp %p /opt/backup/acctg/archived_wals/%f
XLOG METHOD        : fetch
WAL COMPRESSION   : disabled
TABLESPACE PATH(s) :
DESCRIPTION      : "Accounting"
```

In the following code sample, the recovery window retention policy setting considers the backups taken within a 3-week recovery window as the `active` backups.

```
[DEV]
host = 127.0.0.1
port = 5445
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 WEEKS
description = "Development"
```

The start of the 3-week recovery window displayed in the `RETENTION POLICY` field is `2015-03-20 14:59:42 EDT` when the `SHOW-SERVERS` subcommand is invoked on `2015-04-10`.

At this current point in time, backups taken on or after **2015-03-20 14:59:42 EDT** would be considered **active**. Backups taken prior to **2015-03-20 14:59:42 EDT** would be considered **obsolete** except for backups marked as **keep**.

```
-bash-4.1$ date
Fri Apr 10 14:59:39 EDT 2015
-bash-4.1$
-bash-4.1$ bart SHOW-SERVERS -s dev
SERVER NAME : dev
HOST NAME : 127.0.0.1
USER NAME : enterprisedb
PORT : 5445
REMOTE HOST :
RETENTION POLICY : 2015-03-20 14:59:42 EDT
DISK UTILIZATION : 434.53 MB
NUMBER OF ARCHIVES : 22
ARCHIVE PATH : /opt/backup/dev/archived_wals
ARCHIVE COMMAND : cp %p /opt/backup/dev/archived_wals/%f
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
DESCRIPTION : "Development"
```

In the following code sample, the recovery window retention policy setting considers the backups taken within a 3-month recovery window as the **active** backups.

```
[HR]
host = 127.0.0.1
port = 5432
user = postgres
retention_policy = 3 MONTHS
description = "Human Resources"
```

The start of the 3-month recovery window displayed in the **RETENTION POLICY** field is **2015-01-10 14:04:23 EST** when the **SHOW-SERVERS** subcommand is invoked on **2015-04-10**.

At this current point in time, backups taken on or after **2015-01-10 14:04:23 EST** would be considered **active**. Backups taken prior to **2015-01-10 14:04:23 EST** would be considered **obsolete**, except for backups marked as **keep**.

```
-bash-4.1$ date
Fri Apr 10 15:04:19 EDT 2015
-bash-4.1$
-bash-4.1$ bart SHOW-SERVERS -s hr
SERVER NAME : hr
HOST NAME : 127.0.0.1
USER NAME : postgres
PORT : 5432
REMOTE HOST :
RETENTION POLICY : 2015-01-10 14:04:23 EST
DISK UTILIZATION : 480.76 MB
NUMBER OF ARCHIVES : 26
ARCHIVE PATH : /opt/backup/hr/archived_wals
ARCHIVE COMMAND : scp %p
enterprisedb@192.168.2.22:/opt/backup/hr/archived_wals/%f
```

```
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
DESCRIPTION : "Human Resources"
```

## Evaluating, Marking, and Deleting Backup Using a Recovery Window Retention Policy

The following code sample uses a recovery window retention policy to evaluate, mark, and delete backups as shown by the following server configuration:

```
[DEV]
host = 127.0.0.1
port = 5445
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 DAYS
description = "Development"
```

The following is the current set of backups. Note that the last backup in the list has been marked as **keep**.

```
-bash-4.1$ bart SHOW-BACKUPS -s dev
```

SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE	WAL(s) SIZE
dev	1428933278236	2015-04-13 09:54:40 EDT	5.65 MB	16.00 MB
1	active			
dev	1428862187757	2015-04-12 14:09:50 EDT	5.65 MB	32.00 MB
2	active			
dev	1428768351638	2015-04-11 12:05:54 EDT	5.65 MB	32.00 MB
2	active			
dev	1428684544008	2015-04-10 12:49:06 EDT	5.65 MB	224.00 MB
14	active			
dev	1428590536488	2015-04-09 10:42:18 EDT	5.65 MB	48.00 MB
3	active			
dev	1428502171990	2015-04-08 10:09:34 EDT	5.65 MB	80.00 MB
5	keep			

The current date and time is **2015-04-13 16:46:35 EDT** as shown below:

```
-bash-4.1$ date
Mon Apr 13 16:46:35 EDT 2015
```

Thus, a 3-day recovery window would evaluate backups prior to **2015-04-10 16:46:35 EDT** as **obsolete** except for those marked as **keep**.

Invoke the **MANAGE** subcommand with the **-n** option to perform a dry run to observe which active backups would be changed to **obsolete** according to the retention policy.

```
-bash-4.1$ bart MANAGE -s dev -n
INFO: processing server 'dev', backup '1428933278236'
INFO: processing server 'dev', backup '1428862187757'
INFO: processing server 'dev', backup '1428768351638'
INFO: processing server 'dev', backup '1428684544008'
INFO: marking backup '1428684544008' as obsolete
INFO: 14 WAL file(s) marked obsolete
```

```
INFO: 1 Unused WAL file(s) present
INFO: processing server 'dev', backup '1428590536488'
INFO: marking backup '1428590536488' as obsolete
INFO: 3 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: processing server 'dev', backup '1428502171990'
```

The dry run shows that backups `1428684544008` and `1428590536488` would be marked as `obsolete`.

Also note that a dry run does not change the backup status. The two backups that would be considered obsolete are still marked as `active`:

```
-bash-4.1$ bart SHOW-BACKUPS -s dev\
SERVER NAME  BACKUP ID      BACKUP TIME          BACKUP SIZE  WAL(s) SIZE
WAL FILES    STATUS
dev          1428933278236   2015-04-13 09:54:40 EDT  5.65 MB      16.00 MB
1            active
dev          1428862187757   2015-04-12 14:09:50 EDT  5.65 MB      32.00 MB
2            active
dev          1428768351638   2015-04-11 12:05:54 EDT  5.65 MB      32.00 MB
2            active
dev          1428684544008   2015-04-10 12:49:06 EDT  5.65 MB      224.00 MB
14           active
dev          1428590536488   2015-04-09 10:42:18 EDT  5.65 MB      48.00 MB
3            active
dev          1428502171990   2015-04-08 10:09:34 EDT  5.65 MB      80.00 MB
5            keep
```

Invoke the `MANAGE` subcommand omitting the `-n` option to change and mark the status of the backups as `obsolete`:

```
-bash-4.1$ bart MANAGE -s dev
INFO: processing server 'dev', backup '1428933278236'
INFO: processing server 'dev', backup '1428862187757'
INFO: processing server 'dev', backup '1428768351638'
INFO: processing server 'dev', backup '1428684544008'
INFO: marking backup '1428684544008' as obsolete
INFO: 14 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: processing server 'dev', backup '1428590536488'
INFO: marking backup '1428590536488' as obsolete
INFO: 3 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: processing server 'dev', backup '1428502171990'
```

The obsolete backups can be observed in a number of ways. Use the `MANAGE` subcommand with the `-l` option to list the `obsolete` backups:

```
-bash-4.1$ bart MANAGE -s dev -l
INFO: 14 WAL file(s) will be removed
INFO: 1 Unused WAL file(s) will be removed
SERVER NAME: dev
BACKUP ID: 1428684544008
BACKUP STATUS: obsolete
BACKUP TIME: 2015-04-10 12:49:06 EDT
BACKUP SIZE: 5.65 MB
```



```

WAL FILE(s): 14
UNUSED WAL FILE(s): 1
WAL FILE: 0000000100000000000000002E
WAL FILE: 0000000100000000000000002D
WAL FILE: 0000000100000000000000002C
WAL FILE: 0000000100000000000000002B
WAL FILE: 0000000100000000000000002A
WAL FILE: 00000001000000000000000029
WAL FILE: 00000001000000000000000028
WAL FILE: 00000001000000000000000027
WAL FILE: 00000001000000000000000026
WAL FILE: 00000001000000000000000025
WAL FILE: 00000001000000000000000024
WAL FILE: 00000001000000000000000023
WAL FILE: 00000001000000000000000022
WAL FILE: 00000001000000000000000021
UNUSED WAL FILE: 000000010000000000000000F.00000028
INFO: 3 WAL file(s) will be removed
INFO: 1 Unused WAL file(s) will be removed
SERVER NAME: dev
BACKUP ID: 1428590536488
BACKUP STATUS: obsolete
BACKUP TIME: 2015-04-09 10:42:18 EDT\
BACKUP SIZE: 5.65 MB
WAL FILE(s): 3
UNUSED WAL FILE(s): 1
WAL FILE: 00000001000000000000000020
WAL FILE: 0000000100000000000000001F
WAL FILE: 0000000100000000000000001E
UNUSED WAL FILE: 000000010000000000000000F.00000028

```

The **STATUS** field of the **SHOW-BACKUPS** subcommand displays the current status:

```

-bash-4.1$ bart SHOW-BACKUPS -s dev
SERVER NAME  BACKUP ID      BACKUP TIME      BACKUP SIZE  WAL(s) SIZE
WAL FILES   STATUS
dev          1428933278236  2015-04-13 09:54:40 EDT  5.65 MB      16.00 MB
1            active
dev          1428862187757  2015-04-12 14:09:50 EDT  5.65 MB      32.00 MB
2            active
dev          1428768351638  2015-04-11 12:05:54 EDT  5.65 MB      32.00 MB
2            active
dev          1428684544008  2015-04-10 12:49:06 EDT  5.65 MB      224.00 MB
14           obsolete
dev          1428590536488  2015-04-09 10:42:18 EDT  5.65 MB      48.00 MB
3            obsolete
dev          1428502171990  2015-04-08 10:09:34 EDT  5.65 MB      80.00 MB
5            keep

```

The details of an individual backup can be displayed using the **SHOW-BACKUPS** subcommand with the **-t** option. Note the status in the **BACKUP STATUS** field.

```

-bash-4.1$ bart SHOW-BACKUPS -s dev -i 1428684544008 -t
SERVER NAME    : dev
BACKUP ID     : 1428684544008

```

```

BACKUP NAME      : none
BACKUP STATUS    : obsolete
BACKUP TIME      : 2015-04-10 12:49:06 EDT
BACKUP SIZE      : 5.65 MB
WAL(S) SIZE      : 224.00 MB
NO. OF WAL(S)    : 14
FIRST WAL FILE   : 000000001000000000000000021
CREATION TIME    : 2015-04-10 12:49:06 EDT
LAST WAL FILE    : 00000000100000000000000002E
CREATION TIME    : 2015-04-11 12:02:15 EDT

```

Use the **MANAGE** subcommand with the **-d** option to physically delete the obsolete backups including the unneeded WAL files.

```

-bash-4.1$ bart MANAGE -s dev -d
INFO: removing all obsolete backups of server 'dev'
INFO: removing obsolete backup '1428684544008'
INFO: 14 WAL file(s) will be removed
INFO: 1 Unused WAL file(s) will be removed
INFO: removing WAL file '00000000100000000000000002E'
INFO: removing WAL file '00000000100000000000000002D'
INFO: removing WAL file '00000000100000000000000002C'
INFO: removing WAL file '00000000100000000000000002B'
INFO: removing WAL file '00000000100000000000000002A'
INFO: removing WAL file '000000001000000000000000029'
INFO: removing WAL file '000000001000000000000000028'
INFO: removing WAL file '000000001000000000000000027'
INFO: removing WAL file '000000001000000000000000026'
INFO: removing WAL file '000000001000000000000000025'
INFO: removing WAL file '000000001000000000000000024'
INFO: removing WAL file '000000001000000000000000023'
INFO: removing WAL file '000000001000000000000000022'
INFO: removing WAL file '000000001000000000000000021'
INFO: removing (unused) WAL file '0000000010000000000000000F.000000028'
INFO: removing obsolete backup '1428590536488'
INFO: 3 WAL file(s) will be removed
INFO: removing WAL file '000000001000000000000000020'
INFO: removing WAL file '00000000100000000000000001F'
INFO: removing WAL file '00000000100000000000000001E'

```

The **SHOW-BACKUPS** subcommand now displays the remaining backups marked as **active** or **keep**:

```

-bash-4.1$ bart SHOW-BACKUPS -s dev

```

SERVER NAME	BACKUP ID	BACKUP TIME	BACKUP SIZE	WAL(s) SIZE
dev	1428933278236	2015-04-13 09:54:40 EDT	5.65 MB	16.00 MB
1	active			
dev	1428862187757	2015-04-12 14:09:50 EDT	5.65 MB	32.00 MB
2	active			
dev	1428768351638	2015-04-11 12:05:54 EDT	5.65 MB	32.00 MB
2	active			
dev	1428502171990	2015-04-08 10:09:34 EDT	5.65 MB	80.00 MB
5	keep			

## Managing Incremental Backups

This section illustrates evaluating, marking, and deleting incremental backups using the `MANAGE` and `DELETE` subcommands utilizing redundancy retention policy and recovery window retention policy. For detailed information about the `MANAGE` and `DELETE` subcommands, as well as the redundancy retention and recovery window retention policy, see the *EDB Backup and Recovery User Guide* available at the [EDB website](#).

- [Using a Redundancy Retention Policy](#) provides an example of using the `MANAGE` and `DELETE` subcommands when a 3 backup redundancy retention policy is in effect.
- [Using a Recovery Window Retention Policy](#) provides an example of using the `MANAGE` and `DELETE` subcommands when a 1-day recovery window retention policy is in effect.

### Using a Redundancy Retention Policy

The following code sample uses the `MANAGE` and `DELETE` subcommands to evaluate, mark, and delete incremental backups when a 3 backup redundancy retention policy is in effect. The example uses the following server configuration:

```
[ACCTG]

host = 192.168.2.24
port = 5445
user = enterprisedb
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
allow_incremental_backups = enabled
retention_policy = 3 BACKUPS
description = "Accounting"
```

The example uses the following set of backups. In these code samples, some columns have been omitted from the `SHOW-BACKUPS` output to display the relevant information in a more observable manner.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
```

SERVER NAME	BACKUP ID	... BACKUP PARENT	BACKUP TIME	... STATUS
acctg	1481749696905	... 1481749673603	2016-12-14 16:08:17 EST	... active
acctg	1481749673603	... 1481749651927	2016-12-14 16:07:53 EST	... active
acctg	1481749651927	... 1481749619582	2016-12-14 16:07:32 EST	... active
acctg	1481749619582	... none	2016-12-14 16:07:00 EST	... active

There is one backup chain. The first backup is the initial full backup.

Backup chain: 1481749619582 => 1481749651927 => 1481749673603 => 1481749696905

The `MANAGE` subcommand is invoked as shown by the following:

```
-bash-4.2$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1481749619582'
INFO: 2 Unused WAL file(s) present
INFO: 4 Unused file(s) (WALs included) present, use 'MANAGE -l' for the list
```

The following code sample shows the resulting status of the backups:

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
```

SERVER NAME	BACKUP ID	... BACKUP PARENT	BACKUP TIME	... STATUS
acctg	1481749696905	... 1481749673603	2016-12-14 16:08:17 EST	... active
acctg	1481749673603	... 1481749651927	2016-12-14 16:07:53 EST	... active
acctg	1481749651927	... 1481749619582	2016-12-14 16:07:32 EST	... active
acctg	1481749619582	... none	2016-12-14 16:07:00 EST	... active

The status remains active for all backups. Even though the total number of backups exceeds the 3 backup redundancy retention policy, it is only the total number of full backups that is used to determine if the redundancy retention policy has been exceeded. Additional full backups are added including a second backup chain. The following example shows the resulting list of backups:

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
```

SERVER NAME	BACKUP ID	... BACKUP PARENT	BACKUP TIME	... STATUS
acctg	1481750365397	... none	2016-12-14 16:19:26 EST	... active
acctg	1481750098924	... 1481749997807	2016-12-14 16:14:59 EST	... active
acctg	1481749997807	... none	2016-12-14 16:13:18 EST	... active
acctg	1481749992003	... none	2016-12-14 16:13:12 EST	... active
acctg	1481749696905	... 1481749673603	2016-12-14 16:08:17 EST	... active
acctg	1481749673603	... 1481749651927	2016-12-14 16:07:53 EST	... active
acctg	1481749651927	... 1481749619582	2016-12-14 16:07:32 EST	... active
acctg	1481749619582	... none	2016-12-14 16:07:00 EST	... active

Second backup chain: 1481749997807 => 1481750098924

The **MANAGE** subcommand is invoked, but now with a total of four active full backups.

```
-bash-4.2$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1481750365397'
INFO: processing server 'acctg', backup '1481749997807'
INFO: processing server 'acctg', backup '1481749992003'
INFO: processing server 'acctg', backup '1481749619582'
INFO: marking backup '1481749619582' as obsolete
INFO: 3 incremental(s) of backup '1481749619582' will be marked obsolete
INFO: marking incremental backup '1481749696905' as obsolete
INFO: marking incremental backup '1481749673603' as obsolete
INFO: marking incremental backup '1481749651927' as obsolete
INFO: 4 WAL file(s) marked obsolete
INFO: 2 Unused WAL file(s) present
INFO: 4 Unused file(s) (WALs included) present, use 'MANAGE -l' for the list
```

The oldest full backup and its chain of incremental backups are now marked as obsolete.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
```

SERVER NAME	BACKUP ID	... BACKUP PARENT	BACKUP TIME	... STATUS
acctg	1481750365397	... none	2016-12-14 16:19:26 EST	... active
acctg	1481750098924	... 1481749997807	2016-12-14 16:14:59 EST	... active
acctg	1481749997807	... none	2016-12-14 16:13:18 EST	... active
acctg	1481749992003	... none	2016-12-14 16:13:12 EST	... active
acctg	1481749696905	... 1481749673603	2016-12-14 16:08:17 EST	...

```

obsolete
acctg      1481749673603    ... 1481749651927    2016-12-14 16:07:53 EST ...
obsolete
acctg      1481749651927    ... 1481749619582    2016-12-14 16:07:32 EST ...
obsolete
acctg      1481749619582    ... none            2016-12-14 16:07:00 EST ...
obsolete

```

Invoking the **MANAGE** subcommand with the **-d** option deletes the entire obsolete backup chain.

```

-bash-4.2$ bart MANAGE -s acctg -d
INFO: removing all obsolete backups of server 'acctg'
INFO: removing obsolete backup '1481749619582'
INFO: 4 WAL file(s) will be removed
INFO: 3 incremental(s) of backup '1481749619582' will be removed
INFO: removing obsolete incremental backup '1481749696905'
INFO: removing obsolete incremental backup '1481749673603'
INFO: removing obsolete incremental backup '1481749651927'
INFO: removing WAL file '0000000100000000100000000'
INFO: removing WAL file '000000010000000000000000FF'
INFO: removing WAL file '000000010000000000000000FE'
INFO: removing WAL file '000000010000000000000000FD'
INFO: 16 Unused file(s) will be removed
INFO: removing (unused) file '00000001000000001000000004.00000028.backup'
.
.
.
INFO: removing (unused) file
'0000000100000000FB00002800000000FC000000.mbm'

```

The following code sample shows the remaining full backups and the second backup chain.

```

-bash-4.2$ bart SHOW-BACKUPS -s acctg
SERVER NAME  BACKUP ID      ... BACKUP PARENT  BACKUP TIME          ... STATUS
acctg        1481750365397  ... none           2016-12-14 16:19:26 EST ... active
acctg        1481750098924  ... 1481749997807  2016-12-14 16:14:59 EST ... active
acctg        1481749997807  ... none           2016-12-14 16:13:18 EST ... active
acctg        1481749992003  ... none           2016-12-14 16:13:12 EST ... active

```

## Using a Recovery Window Retention Policy

The following example demonstrates using the **MANAGE** and **DELETE** subcommands to evaluate, mark, and delete incremental backups when a 1-day recovery window retention policy is in effect. The example uses the following server configuration:

[ACCTG]

```

host = 192.168.2.24
port = 5445
user = enterprisedb
cluster_owner = enterprisedb
remote_host = enterprisedb@192.168.2.24
allow_incremental_backups = enabled

```

```
retention_policy = 1 DAYS
description = "Accounting"
```

The example uses the following set of backups. In the samples, some columns have been omitted from the **SHOW-BACKUPS** output to display the relevant information in a more observable manner.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
SERVER NAME BACKUP ID ... BACKUP PARENT BACKUP TIME ... STATUS
acctg 1481559303348 ... 1481554203288 2016-12-12 11:15:03 EST ... active
acctg 1481559014359 ... 1481554802918 2016-12-12 11:10:14 EST ... active
acctg 1481554802918 ... 1481553914533 2016-12-12 10:00:03 EST ... active
acctg 1481554203288 ... 1481553651165 2016-12-12 09:50:03 EST ... active
acctg 1481553914533 ... 1481553088053 2016-12-12 09:45:14 EST ... active
acctg 1481553651165 ... none 2016-12-12 09:40:51 EST ... active
acctg 1481553088053 ... 1481552078404 2016-12-12 09:31:28 EST ... active
acctg 1481552078404 ... none 2016-12-12 09:14:39 EST ... active
```

There are two backup chains. In each of the following chains, the first backup is the initial full backup.

First backup chain: 1481552078404 => 1481553088053 => 1481553914533 => 1481554802918 => 1481559014359

Second backup chain: 1481553651165 => 1481554203288 => 1481559303348

The **MANAGE** subcommand is invoked when the first full backup 1481552078404 falls out of the recovery window. When the **MANAGE** subcommand is invoked, it is 2016-12-13 09:20:03 EST, thus making the start of the 1-day recovery window at 2016-12-12 09:20:03 EST exactly one day earlier. This backup was taken at 2016-12-12 09:14:39 EST, which is about 5 ½ minutes before the start of the recovery window, thus making the backup obsolete.

```
-bash-4.2$ date
Tue Dec 13 09:20:03 EST 2016
-bash-4.2$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1481553651165'
INFO: processing server 'acctg', backup '1481552078404'
INFO: marking backup '1481552078404' as obsolete
INFO: 4 incremental(s) of backup '1481552078404' will be marked obsolete
INFO: marking incremental backup '1481559014359' as obsolete
INFO: marking incremental backup '1481554802918' as obsolete
INFO: marking incremental backup '1481553914533' as obsolete
INFO: marking incremental backup '1481553088053' as obsolete
INFO: 7 WAL file(s) marked obsolete
INFO: 1 Unused WAL file(s) present
INFO: 2 Unused file(s) (WALs included) present, use 'MANAGE -l' for the list
```

The incremental backup date and time are within the recovery window since they were taken after the start of the recovery window of 2016-12-12 09:20:03 EST, but all backups in the chain are marked as **obsolete**.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg\
SERVER NAME      BACKUP ID      ... BACKUP PARENT      BACKUP TIME
... STATUS
acctg            1481559303348 ... 1481554203288          2016-12-12 11:15:03 EST
... active
acctg            1481559014359 ... 1481554802918          2016-12-12 11:10:14 EST
... obsolete
```

```

acctg      1481554802918 ... 1481553914533      2016-12-12 10:00:03 EST
... obsolete
acctg      1481554203288 ... 1481553651165      2016-12-12 09:50:03 EST
... active
acctg      1481553914533 ... 1481553088053      2016-12-12 09:45:14 EST
... obsolete
acctg      1481553651165 ... none          2016-12-12 09:40:51 EST
... active
acctg      1481553088053 ... 1481552078404      2016-12-12 09:31:28 EST
... obsolete
acctg      1481552078404 ... none          2016-12-12 09:14:39 EST
... obsolete

```

The following code sample shows how the entire backup chain is changed back to active status by invoking the **MANAGE** subcommand with the **-c nokeep** option on the full backup of the chain.

```

-bash-4.2$ bart MANAGE -s acctg -c nokeep -i 1481552078404
INFO: changing status of backup '1481552078404' of server 'acctg' from
'obsolete' to 'active'
INFO: status of 4 incremental(s) of backup '1481552078404' will be
changed
INFO: changing status of incremental backup '1481559014359' of server
'acctg' from 'obsolete' to 'active'
INFO: changing status of incremental backup '1481554802918' of server
'acctg' from 'obsolete' to 'active'
INFO: changing status of incremental backup '1481553914533' of server
'acctg' from 'obsolete' to 'active'
INFO: changing status of incremental backup '1481553088053' of server
'acctg' from 'obsolete' to 'active'
INFO: 7 WAL file(s) changed

```

The backup chain has now been reset to active status.

```

-bash-4.2$ bart SHOW-BACKUPS -s acctg
SERVER NAME      BACKUP ID      ... BACKUP PARENT      BACKUP TIME      ...
STATUS
acctg            1481559303348  ... 1481554203288      2016-12-12 11:15:03 EST ...
active
acctg            1481559014359  ... 1481554802918      2016-12-12 11:10:14 EST ...
active
acctg            1481554802918  ... 1481553914533      2016-12-12 10:00:03 EST ...
active
acctg            1481554203288  ... 1481553651165      2016-12-12 09:50:03 EST ...
active
acctg            1481553914533  ... 1481553088053      2016-12-12 09:45:14 EST ...
active
acctg            1481553651165  ... none              2016-12-12 09:40:51 EST ...
active
acctg            1481553088053  ... 1481552078404      2016-12-12 09:31:28 EST ...
active
acctg            1481552078404  ... none              2016-12-12 09:14:39 EST ...
active

```

The following code sample shows usage of the **DELETE** subcommand on an incremental backup. The specified incremental backup **1481554802918** in the first backup chain as well as its successive incremental backup



1481559014359 are deleted.

```
-bash-4.2$ bart DELETE -s acctg -i 1481554802918
INFO: deleting backup '1481554802918' of server 'acctg'
INFO: deleting backup '1481554802918'
INFO: 1 incremental backup(s) will be deleted
INFO: deleting incremental backup '1481559014359'
INFO: WALs of deleted backup(s) will belong to prior backup(if any), or
will be marked unused
INFO: 2 Unused file(s) will be removed
INFO: removing (unused) file '000000010000000000000000BA'
INFO: removing (unused) file
'0000000100000000BA00002800000000BB000000.mbm'
INFO: backup(s) deleted
```

The results show that the backups 1481554802918 and 1481559014359 are no longer listed by the SHOW-BACKUPS subcommand.

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
```

SERVER NAME	BACKUP ID	... BACKUP PARENT	BACKUP TIME	...
STATUS				
acctg	1481559303348	... 1481554203288	2016-12-12 11:15:03 EST	...
active				
acctg	1481554203288	... 1481553651165	2016-12-12 09:50:03 EST	...
active				
acctg	1481553914533	... 1481553088053	2016-12-12 09:45:14 EST	...
active				
acctg	1481553651165	... none	2016-12-12 09:40:51 EST	...
active				
acctg	1481553088053	... 1481552078404	2016-12-12 09:31:28 EST	...
active				
acctg	1481552078404	... none	2016-12-12 09:14:39 EST	...
active				

The MANAGE subcommand is invoked again. This time both backup chains are marked **obsolete** since the full backups of both chains fall out of the start of the recovery window, which is now 2016-12-12 09:55:03 EST.

```
-bash-4.2$ date
Tue Dec 13 09:55:03 EST 2016
-bash-4.2$ bart MANAGE -s acctg
INFO: processing server 'acctg', backup '1481553651165'
INFO: marking backup '1481553651165' as obsolete
INFO: 2 incremental(s) of backup '1481553651165' will be marked obsolete
INFO: marking incremental backup '1481559303348' as obsolete
INFO: marking incremental backup '1481554203288' as obsolete
INFO: 38 WAL file(s) marked obsolete
INFO: processing server 'acctg', backup '1481552078404'
INFO: marking backup '1481552078404' as obsolete
INFO: 2 incremental(s) of backup '1481552078404' will be marked obsolete
INFO: marking incremental backup '1481553914533' as obsolete
INFO: marking incremental backup '1481553088053' as obsolete
INFO: 7 WAL file(s) marked obsolete
```

The following code sample shows both backup chains marked as **obsolete**.



```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
SERVER NAME      BACKUP ID      ... BACKUP PARENT  BACKUP TIME
... STATUS
acctg            1481559303348  ... 1481554203288   2016-12-12 11:15:03 EST
... obsolete
acctg            1481554203288  ... 1481553651165   2016-12-12 09:50:03 EST
... obsolete
acctg            1481553914533  ... 1481553088053   2016-12-12 09:45:14 EST
... obsolete
acctg            1481553651165  ... none           2016-12-12 09:40:51 EST
... obsolete
acctg            1481553088053  ... 1481552078404   2016-12-12 09:31:28 EST
... obsolete
acctg            1481552078404  ... none           2016-12-12 09:14:39 EST
... obsolete
```

The following code sample demonstrates using the `MANAGE` subcommand with the `-c keep` option to keep a backup chain indefinitely. The `MANAGE` subcommand with the `-c keep` option must specify the backup identifier or backup name of the full backup of the chain, and not any incremental backup.

```
-bash-4.2$ bart MANAGE -s acctg -c keep -i 1481553651165
INFO: changing status of backup '1481553651165' of server 'acctg' from
'obsolete' to 'keep'
INFO: status of 2 incremental(s) of backup '1481553651165' will be
changed
INFO: changing status of incremental backup '1481559303348' of server
'acctg' from 'obsolete' to 'keep'
INFO: changing status of incremental backup '1481554203288' of server
'acctg' from 'obsolete' to 'keep'
INFO: 38 WAL file(s) changed
```

The full backup `1481553651165` and its successive incremental backups `1481554203288` and `1481559303348` have been changed to `keep` status:

```
-bash-4.2$ bart SHOW-BACKUPS -s acctg
SERVER NAME      BACKUP ID      ... BACKUP PARENT  BACKUP TIME
... STATUS
acctg            1481559303348  ... 1481554203288   2016-12-12 11:15:03 EST
... keep
acctg            1481554203288  ... 1481553651165   2016-12-12 09:50:03 EST
... keep
acctg            1481553914533  ... 1481553088053   2016-12-12 09:45:14 EST
... obsolete
acctg            1481553651165  ... none           2016-12-12 09:40:51 EST
... keep
acctg            1481553088053  ... 1481552078404   2016-12-12 09:31:28 EST
... obsolete
acctg            1481552078404  ... none           2016-12-12 09:14:39 EST
... obsolete
```

Finally, the `MANAGE` subcommand with the `-d` option is used to delete the `obsolete` backup chain:

```
-bash-4.2$ bart MANAGE -s acctg -d
INFO: removing all obsolete backups of server 'acctg'
INFO: removing obsolete backup '1481552078404'
```

```

INFO: 7 WAL file(s) will be removed
INFO: 2 incremental(s) of backup '1481552078404' will be removed
INFO: removing obsolete incremental backup '1481553914533'
INFO: removing obsolete incremental backup '1481553088053'
INFO: removing WAL file '000000010000000000000000C1'
INFO: removing WAL file '000000010000000000000000C0'
INFO: removing WAL file '000000010000000000000000BF'
INFO: removing WAL file '000000010000000000000000BE'
INFO: removing WAL file '000000010000000000000000BD'
INFO: removing WAL file '000000010000000000000000BC'
INFO: removing WAL file '000000010000000000000000BB'
INFO: 48 Unused file(s) will be removed
INFO: removing (unused) file '000000010000000000000000FA'
.
.
.
INFO: removing (unused) file '000000010000000000000000BB.00000028.backup'

```

Only the backup chain with the **keep** status remains as shown below:

```

-bash-4.2$ bart SHOW-BACKUPS -s acctg
SERVER NAME      BACKUP ID      ... BACKUP PARENT    BACKUP TIME
... STATUS
acctg            1481559303348  ... 1481554203288     2016-12-12 11:15:03 EST
... keep
acctg            1481554203288  ... 1481553651165     2016-12-12 09:50:03 EST
... keep
acctg            1481553651165  ... none              2016-12-12 09:40:51 EST
... keep

```

## 4.3 Sample BART System with Local and Remote Database Servers

This section describes a sample BART managed backup and recovery system consisting of both local and remote database servers. The complete steps to configure and operate the system are provided.

For detailed information about configuring a BART system, see the *EDB Backup and Recovery Installation and Upgrade Guide*. For detailed information about the operational procedures and BART subcommands, see the *EDB Backup and Recovery User Guide*. These guides are available at the [EDB website](#).

The environment for this sample system is as follows:

- BART on host **192.168.2.22** running with BART user account **enterprisedb**
- Local Advanced Server on host **192.168.2.22** running with user account **enterprisedb**
- Remote Advanced Server on host **192.168.2.24** running with user account **enterprisedb**
- Remote PostgreSQL server on host **192.168.2.24** running with user account **postgres**

Passwordless SSH/SCP connections are required between the following:

- BART on host **192.168.2.22** and the local Advanced Server on the same host **192.168.2.22**
- BART on host **192.168.2.22** and the remote Advanced Server on host **192.168.2.24**

- BART on host `192.168.2.22` and the remote PostgreSQL server on host `192.168.2.24`

The following sections demonstrate configuring and taking full backups only. To support incremental backups as well, enable the `allow_incremental_backups` parameter for the desired database servers and use the `WAL scanner` program.

- [The BART Configuration File](#) shows the settings used in the BART configuration file.
- [Establishing SSH/SCP Passwordless Connections](#) provides an example of how to establish an SSH/SCP passwordless connection.
- [Configuring a Replication Database User](#) provides an example of how to configure the replication database user.
- [WAL Archiving Configuration Parameters](#) provides an example of how to configure WAL archiving.
- [Creating the BART Backup Catalog](#) provides information about creating a BART Backup Catalog.
- [Starting the Database Servers with WAL Archiving](#) provides example of starting the database servers with WAL archiving.
- [Taking a Full Backup](#) illustrates taking the first full backup of the database servers.
- [Using Point-In-Time Recovery](#) demonstrates the point-in-time recovery operation on the remote PostgreSQL database server.

## The BART Configuration File

The following code sample shows the settings used in the BART configuration file for the examples that follow:

```
[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
retention_policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
cluster_owner = enterprisedb
backup_name = acctg_%year-%month-%dayT%hour:%minute
archive_command = 'cp %p %a/%f'
description = "Accounting"

[MKTG]

host = 192.168.2.24
port = 5444
user = repuser
cluster_owner = enterprisedb
backup_name = mktg_%year-%month-%dayT%hour:%minute
remote_host = enterprisedb@192.168.2.24
description = "Marketing"

[HR]

host = 192.168.2.24
port = 5432
user = postgres
```

```
cluster_owner = postgres
backup_name = hr_%year-%month-%dayT%hour:%minute
remote_host = postgres@192.168.2.24
copy_wals_during_restore = enabled
description = "Human Resources"
```

## Establishing SSH/SCP Passwordless Connections

This section demonstrates how passwordless SSH/SCP connections are established with the authorized public keys files.

### Generating a Public Key File for the BART User Account

The BART user account is `enterprisedb` with a home directory of `/opt/PostgresPlus/9.6AS`.

To generate the public key file, as a root user, first create the `.ssh` subdirectory in the BART user's home directory and assign ownership of this directory to the `enterprisedb` user, ensuring there are no groups or other users that can access the `.ssh` directory.

```
[root@localhost 9.6AS]# pwd
/opt/PostgresPlus/9.6AS
[root@localhost 9.6AS]# mkdir .ssh
[root@localhost 9.6AS]# chown enterprisedb .ssh
[root@localhost 9.6AS]# chgrp enterprisedb .ssh
[root@localhost 9.6AS]# chmod 700 .ssh
[root@localhost 9.6AS]# ls -la | grep ssh
drwx----- 2 enterprisedb enterprisedb 4096 Apr 23 13:02 .ssh
```

Generate the public key file:

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ pwd
/opt/PostgresPlus/9.6AS
-bash-4.1$ ssh-keygen -t rsa
Generating public/private rsa key pair.
Enter file in which to save the key
(/opt/PostgresPlus/9.6AS/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in
/opt/PostgresPlus/9.6AS/.ssh/id_rsa.
Your public key has been saved in
/opt/PostgresPlus/9.6AS/.ssh/id_rsa.pub.
The key fingerprint is:
de:65:34:d6:b1:d2:32:3c:b0:43:c6:a3:c0:9f:f4:64
enterprisedb@localhost.localdomain
The key's randomart image is:
+----[ RSA 2048]----+
|      .  .+  .  |
|      o .oE+ o o |
|      + * o.X + |
|      + .+ *   |
```

```
|      S  o      |
|      . . o      |
|      . .        |
|                  |
|      |          |
|                  |
+-----+
```

The following are the resulting files. `id_rsa.pub` is the public key file of BART user account `enterprisedb`.

```
-bash-4.1$ ls -l .ssh
total 8
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
```

## Configuring Access between Local Advanced Server and the BART Host

Even when the Advanced Server database is on the same host as the BART user account, and the Advanced Server database cluster owner is also the BART user account (`enterprisedb` is this case), a passwordless SSH/SCP connection must be established from the same user account to itself.

On the BART host where the public key file was just generated (as shown in [Generating a Public Key File for the BART User Account](#)), create the authorized keys file by appending the public key file to any existing authorized keys file.

Log into the BART host as the BART user account and append the public key file, `id_rsa.pub` onto the `authorized_keys` file in the same `.ssh` directory.

```
[user@localhost ~]$ su - enterprisedb
Password:
Last login: Thu Mar 23 10:27:35 EDT 2017 on pts/0
-bash-4.2$ pwd
/opt/PostgresPlus/9.6AS
-bash-4.2$ ls -l .ssh
total 12
-rw----- 1 enterprisedb enterprisedb 1675 Mar 23 09:54 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Mar 23 09:54 id_rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 345 Mar 23 10:05 known_hosts
-bash-4.2$ cat ~/.ssh/id_rsa.pub >> ~/.ssh/authorized_keys
-bash-4.2$ ls -l .ssh
total 16
-rw-rw-r-- 1 enterprisedb enterprisedb 416 Mar 23 10:33 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Mar 23 09:54 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Mar 23 09:54 id_rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 345 Mar 23 10:05 known_hosts
```

The `authorized_keys` file must have file permission `600` as set by the following `chmod 600` command, or the passwordless connection will fail:

```
-bash-4.2$ chmod 600 ~/.ssh/authorized_keys
-bash-4.2$ ls -l .ssh
total 16
-rw----- 1 enterprisedb enterprisedb 416 Mar 23 10:33 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Mar 23 09:54 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Mar 23 09:54 id_rsa.pub
```

```
-rw-r--r-- 1 enterprisedb enterprisedb 345 Mar 23 10:05 known_hosts
```

Test the passwordless connection. Use the `ssh` command to verify that you can access the same user account as you are currently logged in as (`enterprisedb`) without being prompted for a password:

```
-bash-4.2$ ssh enterprisedb@127.0.0.1
Last login: Thu Mar 23 10:27:50 2017
-bash-4.2$ exit
logout
Connection to 127.0.0.1 closed.
```

## Configuring Access from Remote Advanced Server to BART Host

On the remote host `192.168.2.24`, create the public key file for the remote database server user account, `enterprisedb`, for access to the BART user account, `enterprisedb`, on the BART host `192.168.2.22`.

Create the `.ssh` directory for user account `enterprisedb` on the remote host:

```
[root@localhost 9.6AS]# pwd
/opt/PostgresPlus/9.6AS
[root@localhost 9.6AS]# mkdir .ssh
[root@localhost 9.6AS]# chown enterprisedb .ssh
[root@localhost 9.6AS]# chgrp enterprisedb .ssh
[root@localhost 9.6AS]# chmod 700 .ssh
[root@localhost 9.6AS]# ls -la | grep ssh
drwx----- 2 enterprisedb enterprisedb 4096 Apr 23 13:08 .ssh
```

Generate the public key file on the remote host for user account `enterprisedb`:

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ ssh-keygen -t rsa
Generating public/private rsa key pair.
Enter file in which to save the key
(/opt/PostgresPlus/9.6AS/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in
/opt/PostgresPlus/9.6AS/.ssh/id_rsa.
Your public key has been saved in
/opt/PostgresPlus/9.6AS/.ssh/id_rsa.pub.
The key fingerprint is:
15:27:1e:1e:61:4b:48:66:67:0b:b2:be:fc:ea:ea:e6
enterprisedb@localhost.localdomain
The key's randomart image is:
+--[ RSA 2048 ]--+
|      ..=.@..    |
|      =.0 0      |
|      .  *       |
|      .  .       |
|      . S        |
|      . .        |
|      o          |
```

```
| . . |
| +Eoo.. |
+-----+
```

Copy the generated public key file, `id_rsa.pub`, to the BART user account, `enterprisedb`, on the BART host, `192.168.2.22`:

```
-bash-4.1$ scp ~/.ssh/id_rsa.pub enterprisedb@192.168.2.22:/tmp/tmp.pub
The authenticity of host '192.168.2.22 (192.168.2.22)' can't be
established.
RSA key fingerprint is b8:a9:97:31:79:16:b8:2b:b0:60:5a:91:38:d7:68:22.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.2.22' (RSA) to the list of known hosts.
enterprisedb@192.168.2.22's password:
id_rsa.pub
```

Log into the BART host as the BART user account and append the temporary public key file, `/tmp/tmp.pub` onto the `authorized_keys` file owned by the BART user account.

```
-bash-4.1$ ssh enterprisedb@192.168.2.22
enterprisedb@192.168.2.22's password:
Last login: Tue Apr 21 17:03:24 2015 from 192.168.2.22
-bash-4.1$ pwd
/opt/PostgresPlus/9.6AS
-bash-4.1$ cat /tmp/tmp.pub >> ~/.ssh/authorized_keys
-bash-4.1$ ls -l .ssh
total 12
-rw-rw-r-- 1 enterprisedb enterprisedb 416 Apr 23 13:15 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
```

The `authorized_keys` file must have file permission `600` as set by the following `chmod 600` command, otherwise the passwordless connection fails:

```
-bash-4.1$ chmod 600 ~/.ssh/authorized_keys
-bash-4.1$ ls -l .ssh
total 12
-rw----- 1 enterprisedb enterprisedb 416 Apr 23 13:15 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
-bash-4.1$ rm /tmp/tmp.pub
-bash-4.1$ exit
logout
Connection to 192.168.2.22 closed.
```

Test the passwordless connection. From the remote host, verify that you can log into the BART host with the BART user account without being prompted for a password:

```
-bash-4.1$ ssh enterprisedb@192.168.2.22
Last login: Thu Apr 23 13:14:48 2015 from 192.168.2.24
-bash-4.1$ exit
logout
Connection to 192.168.2.22 closed.
```

## Configuring Access from the BART Host to a Remote Advanced Server

On the BART host `192.168.2.22`, copy the public key file for the BART user account, `enterprisedb`, for access to the remote database server user account, `enterprisedb`, on the remote host `192.168.2.24`.

The following lists the current SSH keys files in the BART user's `.ssh` directory on the BART host:

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ pwd
/opt/PostgresPlus/9.6AS
-bash-4.1$ ls -l .ssh
total 12
-rw----- 1 enterprisedb enterprisedb 416 Apr 23 13:15 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
```

The public key file, `id_rsa.pub`, for BART user account `enterprisedb` on the BART host that was earlier generated in [Generating a Public Key File for the BART User Account](#), is now copied to the remote Advanced Server host on `192.168.2.24`:

```
-bash-4.1$ scp ~/.ssh/id_rsa.pub enterprisedb@192.168.2.24:/tmp/tmp.pub
The authenticity of host '192.168.2.24 (192.168.2.24)' can't be
established.
RSA key fingerprint is 59:41:fb:0c:ae:64:3d:3f:a2:d9:90:95:cf:2c:99:f2.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.2.24' (RSA) to the list of known
hosts.
enterprisedb@192.168.2.24's password:
id_rsa.pub
```

Log into the `enterprisedb` user account on the remote host and copy the public key file onto the `authorized_keys` file of the remote `enterprisedb` user account under its `.ssh` directory:

```
-bash-4.1$ ssh enterprisedb@192.168.2.24
enterprisedb@192.168.2.24's password:
Last login: Tue Apr 21 09:53:18 2015 from 192.168.2.22
-bash-4.1$ pwd
/opt/PostgresPlus/9.6AS
-bash-4.1$ ls -l .ssh
total 12
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:11 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:11 id_rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 394 Apr 23 13:12 known_hosts
-bash-4.1$ cat /tmp/tmp.pub >> ~/.ssh/authorized_keys
```

Adjust the file permission on `authorized_keys`:

```
-bash-4.1$ chmod 600 ~/.ssh/authorized_keys
-bash-4.1$ ls -l .ssh
total 16
-rw----- 1 enterprisedb enterprisedb 416 Apr 23 13:26 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:11 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:11 id_rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 394 Apr 23 13:12 known_hosts
```



```
-bash-4.1$ rm /tmp/tmp.pub
-bash-4.1$ exit
logout
Connection to 192.168.2.24 closed.
```

While logged into the BART host, test the passwordless connection from the BART host to the remote Advanced Server host:

```
-bash-4.1$ ssh enterprisedb@192.168.2.24
Last login: Thu Apr 23 13:25:53 2015 from 192.168.2.22
-bash-4.1$ exit
logout
Connection to 192.168.2.24 closed.
```

## Configuring Access from a Remote PostgreSQL Server to a BART Host

On the remote host (192.168.2.24), create a public key file owned by the database server user account (`postgres`), allowing access to the BART user account (`enterprisedb`) on the BART host (192.168.2.22).

Create the `.ssh` directory for the `postgres` user account on the remote host:

```
[root@localhost 9.6]# cd /opt/PostgreSQL/9.6
[root@localhost 9.6]# mkdir .ssh
[root@localhost 9.6]# chown postgres .ssh
[root@localhost 9.6]# chgrp postgres .ssh
[root@localhost 9.6]# chmod 700 .ssh
[root@localhost 9.6]# ls -la | grep ssh
drwx----- 2 postgres postgres 4096 Apr 23 13:32 .ssh
```

Create and copy the generated public key file, `id_rsa.pub`, to the BART user account (`enterprisedb`), on the BART host (192.168.2.22):

```
[user@localhost ~]$ su - postgres
Password:
-bash-4.1$ pwd
/opt/PostgreSQL/9.6
-bash-4.1$ ssh-keygen -t rsa
Generating public/private rsa key pair.
Enter file in which to save the key (/opt/PostgreSQL/9.6/.ssh/id_rsa):
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
Your identification has been saved in /opt/PostgreSQL/9.6/.ssh/id_rsa.
Your public key has been saved in /opt/PostgreSQL/9.6/.ssh/id_rsa.pub.
The key fingerprint is:
1f:f8:76:d6:fc:a5:1a:c5:5a:66:66:01:d0:a0:ca:ba
postgres@localhost.localdomain
The key's randomart image is:
+--[ RSA 2048 ]-----+
|           o+.       |
|           .  ..     |
|           .  .      |
|       .  .  .  .  .  |
|       o S .   0     |
```

```

|      .   o . @   |
|      .       + = o . |
|      .   . o . o . |
|      E       ... . |
+-----+
-bash-4.1$ ls -l .ssh
total 8
-rw----- 1 postgres postgres 1671 Apr 23 13:36 id_rsa
-rw-r--r-- 1 postgres postgres 412 Apr 23 13:36 id_rsa.pub
-bash-4.1$ scp ~/.ssh/id_rsa.pub enterprisedb@192.168.2.22:/tmp/tmp.pub
The authenticity of host '192.168.2.22 (192.168.2.22)' can't be
established.
RSA key fingerprint is b8:a9:97:31:79:16:b8:2b:b0:60:5a:91:38:d7:68:22.
Are you sure you want to continue connecting (yes/no)? yes
Warning: Permanently added '192.168.2.22' (RSA) to the list of known
hosts.
enterprisedb@192.168.2.22's password:
id_rsa.pub

```

Log into the BART host as the BART user account and append the temporary public key file, `/tmp/tmp.pub`, onto the `authorized_keys` file owned by the BART user account.

```

-bash-4.1$ ssh enterprisedb@192.168.2.22
enterprisedb@192.168.2.22's password:
Last login: Thu Apr 23 13:19:25 2015 from 192.168.2.24
-bash-4.1$ pwd
/opt/PostgresPlus/9.6AS
-bash-4.1$ cat /tmp/tmp.pub >> ~/.ssh/authorized_keys
-bash-4.1$ ls -l .ssh
total 16
-rw----- 1 enterprisedb enterprisedb 828 Apr 23 13:40 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 394 Apr 23 13:24 known_hosts
-bash-4.1$ rm /tmp/tmp.pub
-bash-4.1$ exit
logout
Connection to 192.168.2.22 closed.

```

Make sure the `authorized_keys` file has file permission 600 as shown, or the passwordless connection will fail. Test the passwordless connection; from the remote host, while logged in as user account `postgres`, verify that you can log into the BART host with the BART user account without being prompted for a password:

```

-bash-4.1$ pwd
/opt/PostgreSQL/9.6
-bash-4.1$ ssh enterprisedb@192.168.2.22
Last login: Thu Apr 23 13:40:10 2015 from 192.168.2.24
-bash-4.1$ exit
logout
Connection to 192.168.2.22 closed.

```

## Configuring Access from the BART Host to Remote PostgreSQL

Copy the public key file on the BART host that is owned by the BART user account (**enterprisedb**) to the remote database server user account (**postgres**), on the remote host (192.168.2.24).

The following lists the current SSH keys files in the BART user's **.ssh** directory on the BART host:

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ ls -l .ssh
total 16
-rw----- 1 enterprisedb enterprisedb 828 Apr 23 13:40 authorized_keys
-rw----- 1 enterprisedb enterprisedb 1675 Apr 23 13:04 id_rsa
-rw-r--r-- 1 enterprisedb enterprisedb 416 Apr 23 13:04 id_rsa.pub
-rw-r--r-- 1 enterprisedb enterprisedb 394 Apr 23 13:24 known_hosts
```

The public key file, **id\_rsa.pub**, for BART user account **enterprisedb** on the BART host that was earlier generated in [Generating a Public Key File for the BART User Account](#), now resides on the remote PostgreSQL host:

```
-bash-4.1$ scp ~/.ssh/id_rsa.pub postgres@192.168.2.24:/tmp/tmp.pub
postgres@192.168.2.24's password:
id_rsa.pub
```

Log into the **postgres** user account on the remote host and copy the public key file onto the **authorized\_keys** file of **postgres** under its **.ssh** directory:

```
-bash-4.1$ ssh postgres@192.168.2.24
postgres@192.168.2.24's password:
Last login: Mon Jan 26 18:08:36 2015 from 192.168.2.19
-bash-4.1$ pwd
/opt/PostgreSQL/9.6
-bash-4.1$ cat /tmp/tmp.pub >> ~/.ssh/authorized_keys
```

Adjust the file permissions on **authorized\_keys**:

```
-bash-4.1$ ls -l .ssh
total 16
-rw-rw-r-- 1 postgres postgres 416 Apr 23 13:52 authorized_keys
-rw----- 1 postgres postgres 1671 Apr 23 13:36 id_rsa
-rw-r--r-- 1 postgres postgres 412 Apr 23 13:36 id_rsa.pub
-rw-r--r-- 1 postgres postgres 394 Apr 23 13:36 known_hosts
-bash-4.1$ chmod 600 ~/.ssh/authorized_keys
-bash-4.1$ ls -l .ssh
total 16
-rw----- 1 postgres postgres 416 Apr 23 13:52 authorized_keys
-rw----- 1 postgres postgres 1671 Apr 23 13:36 id_rsa
-rw-r--r-- 1 postgres postgres 412 Apr 23 13:36 id_rsa.pub
-rw-r--r-- 1 postgres postgres 394 Apr 23 13:36 known_hosts
-bash-4.1$ rm /tmp/tmp.pub
-bash-4.1$ exit
logout
Connection to 192.168.2.24 closed.
```

Test the passwordless connection from the BART host to the remote PostgreSQL host:

```
[user@localhost ~]$ su - enterprisedb
Password:
```

```
-bash-4.1$ ssh postgres@192.168.2.24
Last login: Thu Apr 23 13:52:25 2015 from 192.168.2.22
-bash-4.1$ exit
logout
Connection to 192.168.2.24 closed.
```

## Configuring a Replication Database User

This section demonstrates how a replication database user is established.

All database servers must use a superuser as the replication database user.

The replication database user for each database server is specified by the `user` parameter in the BART configuration file as shown by the following:

```
[ACCTG]

host = 127.0.0.1
port = 5444
user = enterprisedb <=== Replication Database User
cluster_owner = enterprisedb
backup_name = acctg_%year-%month-%dayT%hour:%minute
archive_command = 'cp %p %a/%f'
description = "Accounting"

[MKTG]
host = 192.168.2.24
port = 5444
user = repuser <=== Replication Database User
cluster_owner = enterprisedb
backup_name = mktg_%year-%month-%dayT%hour:%minute
remote_host = enterprisedb@192.168.2.24
description = "Marketing"

[HR]

host = 192.168.2.24
port = 5432
user = postgres <=== Replication Database User
cluster_owner = enterprisedb
backup_name = hr_%year-%month-%dayT%hour:%minute
remote_host = postgres@192.168.2.24
copy_wals_during_restore = enabled
description = "Human Resources"
```

Add entries to the `.pgpass` file on each server to allow the BART user account to initiate a backup without being prompted for credentials. The `.pgpass` file is located in `/opt/PostgresPlus/9.6AS/.pgpass`:

```
127.0.0.1:5444:*:enterprisedb:password
192.168.2.24:5444:*:repuser:password
192.168.2.24:5432:*:postgres:password
```

For more information about using a `.pgpass` file, please see the [PostgreSQL documentation](#).

While connected to **MKTG** on 192.168.2.24, execute the following **CREATE ROLE** command to create the replication database superuser:

```
CREATE ROLE repuser WITH LOGIN SUPERUSER PASSWORD 'password';
```

Access is granted in the **pg\_hba.conf** file for the local Advanced Server:

```
### TYPE      DATABASE      USER      ADDRESS      METHOD
### "local" is for Unix domain socket connections only
local        all          all                md5
### IPv4      local connections:
host         template1    enterprisedb 127.0.0.1/32  md5
host         edb        enterprisedb 127.0.0.1/32  md5
#host        all          all          127.0.0.1/32  md5
### IPv6      local connections:
host         all          all          ::1/128       md5
### Allow replication connections from localhost, by a user with the
### replication privilege.
#local       replication  enterprisedb  md5
host         replication  enterprisedb 127.0.0.1/32  md5
```

Similarly, access is granted in the **pg\_hba.conf** file for the remote Advanced Server installation:

```
### TYPE      DATABASE      USER      ADDRESS      METHOD
### "local" is for Unix domain socket connections only
local        all          all                md5
### IPv4      local connections:
host         template1    repuser      192.168.2.22/32 md5
host         all          enterprisedb 127.0.0.1/32  md5
#host        all          all          127.0.0.1/32  md5
### IPv6      local connections:
host         all          all          ::1/128       md5
### Allow replication connections from localhost, by a user with the
### replication privilege.
#local       replication  enterprisedb  md5
host         replication  repuser      192.168.2.22/32 md5
```

Access is also granted in the **pg\_hba.conf** file for the remote PostgreSQL server:

```
### TYPE      DATABASE      USER      ADDRESS      METHOD
### "local" is for Unix domain socket connections only
local        all          all                md5
### IPv4      local connections:
host         template1    postgres     192.168.2.22/32 md5
host         all          all          127.0.0.1/32  md5
### IPv6      local connections:
host         all          all          ::1/128       md5
### Allow replication connections from localhost, by a user with the
q# replication privilege.
#local       replication  postgres     md5
host         replication  postgres     192.168.2.22/32 md5
```

## WAL Archiving Configuration Parameters

Use the following parameters in the `postgresql.conf` file to enable WAL archiving. The `postgresql.conf` file for the local Advanced Server database (`ACCTG`) is set as follows:

```
wal_level = archive
archive_mode = on
#archive_command = ''

max_wal_senders = 3
```

# allows archiving to be done  
# (change requires restart)  
# command to use to archive  
# a logfile segment  
# placeholders: %p = path of  
# file to archive  
# %f = file name only

When the `INIT` subcommand is invoked, the Postgres `archive_command` configuration parameter in the `postgresql.auto.conf` file will be set based on the BART `archive_command` parameter located in the BART configuration file.

!!! Note If the Postgres `archive_command` is already set, invoke the `INIT` subcommand with the `-- no-configure` option to prevent the `archive_command` from being reset. For details, see [INIT](#).

```
[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
retention_policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log

[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
cluster_owner = enterprisedb
backup_name = acctg_%year-%month-%dayT%hour:%minute
archive_command = 'cp %p %a/%f'
description = "Accounting"
```

When the `INIT` subcommand is invoked, the `postgresql.auto.conf` file contains the following:

```
### Do not edit this file manually!
### It will be overwritten by ALTER SYSTEM command.
archive_command = 'cp %p /opt/backup/acctg/archived_wals/%f'
```

The `archive_command` uses the `cp` command instead of `scp` since the BART backup catalog is local to this database cluster and the BART user account (the account that owns the backup catalog, `enterprisedb`), is the same user account running Advanced Server. The result is that there is no directory permission conflict during the archive operation.

The `postgresql.conf` file for the remote Advanced Server, `MKTG` is set as follows:

```
wal_level = archive
archive_mode = on
archive_command = ''
```

# allows archiving to be done  
# (change requires restart)  
# command to use to archive a  
# logfile segment

```

# placeholders: %p = path of
#                file to archive
# %f = file name only

max_wal_senders = 3

```

When the `INIT` subcommand is invoked, the Postgres `archive_command` configuration parameter in the `postgresql.auto.conf` file will be set by the default BART format of the BART `archive_command` parameter (since it is not explicitly set for this database server in the BART configuration file).

```

[BART]
bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
retention_policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log
.
.
.
[MKTG]

host = 192.168.2.24
port = 5444
user = repuser
cluster_owner = enterprisedb
backup_name = mktg_%year-%month-%dayT%hour:%minute
remote_host = enterprisedb@192.168.2.24
description = "Marketing"

```

The default BART `archive_command` format is:

```
archive_command = 'scp %p %h:%a/%f'
```

The `postgresql.auto.conf` file contains the following after the `INIT` subcommand is invoked:

```

### Do not edit this file manually!
### It will be overwritten by ALTER SYSTEM command.
archive_command = 'scp %p
enterprisedb@192.168.2.22:/opt/backup/hr/archived_wals/%f'

```

The `archive_command` uses the `scp` command since the BART backup catalog is remote relative to this database cluster. The BART user account, `enterprisedb`, is specified on the `scp` command since this is the user account owning the BART backup catalog where the archived WAL files are to be copied. The result is that there is no directory permission conflict during the archive operation.

The `postgresql.conf` file for the remote PostgreSQL server (`HR`) is set as follows:

```

wal_level = archive
archive_mode = on
#archive_command = ''

# allows archiving to be done
# (change requires restart)
# command to use to archive a
# logfile segment
# placeholders: %p = path of
#                file to archive
# %f = file name only

```

```
max_wal_senders = 3
```

When the `INIT` subcommand is invoked, the Postgres `archive_command` configuration parameter in the `postgresql.auto.conf` file will be set by the default BART format of the BART `archive_command` parameter (since it is not explicitly set for this database server in the BART configuration file):

```
[BART]

bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
retention_policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log
.
.
.
[HR]

host = 192.168.2.24
port = 5432
user = postgres
cluster_owner = postgres
backup_name = hr_%year-%month-%dayT%hour:%minute
remote_host = postgres@192.168.2.24
copy_wals_during_restore = enabled
description = "Human Resources"
```

The default BART `archive_command` format is:

```
archive_command = 'scp %p %h:%a/%f'
```

The `postgresql.auto.conf` file contains the following after the `INIT` subcommand is invoked:

```
### Do not edit this file manually!
### It will be overwritten by ALTER SYSTEM command.
archive_command = 'scp %p
enterprisedb@192.168.2.22:/opt/backup/hr/archived_wals/%f'
```

The `archive_command` uses the `scp` command since the BART backup catalog is remote relative to this database cluster. The BART user account, `enterprisedb`, is specified on the `scp` command since this is the user account owning the BART backup catalog where the archived WAL files are to be copied. The result is that there is no directory permission conflict during the archive operation.

## Creating the BART Backup Catalog (backup\_path)

Create the directory specified by the `backup_path` configuration parameter.

```
[BART]

bart_host= enterprisedb@192.168.2.22
backup_path = /opt/backup
pg_basebackup_path = /usr/edb/as11/bin/pg_basebackup
```



```
retention_policy = 6 BACKUPS
logfile = /tmp/bart.log
scanner_logfile = /tmp/bart_scanner.log
```

Ensure that the directory is owned by the BART user account:

```
[root@localhost opt]# pwd
/opt
[root@localhost opt]# mkdir backup
[root@localhost opt]# chown enterprisedb backup
[root@localhost opt]# chgrp enterprisedb backup
[root@localhost opt]# chmod 700 backup
[root@localhost opt]# ls -l | grep backup
drwx----- 2 enterprisedb enterprisedb 4096 Apr 23 15:36 backup
```

Use the BART **INIT** subcommand to complete the directory structure and set the Postgres **archive\_command** configuration parameter.

Before invoking any BART subcommands, set up a profile under the BART user account's home directory to set the **LD\_LIBRARY\_PATH** and **PATH** environment variables. For more information regarding setting this variable, see the EDB Backup and Recovery Installation and Upgrade Guide available at the [EDB website](#).

The **-o** option is specified with the **INIT** subcommand to force the setting of the Postgres **archive\_command** configuration parameter when **archive\_mode** is **off** or if the Postgres **archive\_command** parameter is already set and needs to be overridden.

```
[user@localhost ~]$ su - enterprisedb
Password:
-bash-4.1$ bart INIT -o
INFO: setting archive_command for server 'acctg'
WARNING: archive_command is set. server restart is required
INFO: setting archive_command for server 'hr'
WARNING: archive_command is set. server restart is required
INFO: setting archive_command for server 'mktg'
WARNING: archive_command is set. server restart is required
```

The BART **SHOW-SERVERS** subcommand displays the following:

```
-bash-4.1$ bart SHOW-SERVERS
SERVER NAME :          acctg
BACKUP FRIENDLY NAME:  acctg_%year-%month-%dayT%hour:%minute
HOST NAME :           127.0.0.1
USER NAME :           enterprisedb
PORT :                5444
REMOTE HOST :
RETENTION POLICY :     6 Backups
DISK UTILIZATION :     0.00 bytes
NUMBER OF ARCHIVES :   0
ARCHIVE PATH :         /opt/backup/acctg/archived_wals
ARCHIVE COMMAND :      (disabled)
XLOG METHOD :           fetch
WAL COMPRESSION :     disabled
TABLESPACE PATH(s) :
INCREMENTAL BACKUP :   DISABLED
DESCRIPTION :          "Accounting"
```

```

SERVER NAME : hr
BACKUP FRIENDLY NAME: hr_%year-%month-%dayT%hour:%minute
HOST NAME : 192.168.2.24
USER NAME : postgres
PORT : 5432
REMOTE HOST : postgres@192.168.2.24
RETENTION POLICY : 6 Backups
DISK UTILIZATION : 0.00 bytes
NUMBER OF ARCHIVES : 0
ARCHIVE PATH : /opt/backup/hr/archived_wals
ARCHIVE COMMAND : (disabled)
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
INCREMENTAL BACKUP : DISABLED
DESCRIPTION : "Human Resources"
SERVER NAME : mktg
BACKUP FRIENDLY NAME: mktg_%year-%month-%dayT%hour:%minute
HOST NAME : 192.168.2.24
USER NAME : repuser
PORT : 5444
REMOTE HOST : enterprisedb@192.168.2.24
RETENTION POLICY : 6 Backups
DISK UTILIZATION : 0.00 bytes
NUMBER OF ARCHIVES : 0
ARCHIVE PATH : /opt/backup/mktg/archived_wals
ARCHIVE COMMAND : (disabled)
XLOG METHOD : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
INCREMENTAL BACKUP : DISABLED
DESCRIPTION : "Marketing"
-bash-4.1$ cd /opt/backup
-bash-4.1$ pwd
/opt/backup
-bash-4.1$ ls -l
total 12
drwxrwxr-x 3 enterprisedb enterprisedb 4096 Mar 29 13:16 acctg
drwxrwxr-x 3 enterprisedb enterprisedb 4096 Mar 29 13:16 hr
drwxrwxr-x 3 enterprisedb enterprisedb 4096 Mar 29 13:16 mktg
-bash-4.1$ ls -l acctg
total 4
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:16 archived_wals
-bash-4.1$ ls -l hr
total 4
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:16 archived_wals
-bash-4.1$ ls -l mktg
total 4
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:16 archived_wals

```

The **ARCHIVE PATH** field displays the full directory path to where the WAL files are copied. This directory path must match the directory path specified in the Postgres **archive\_command** parameter of the **postgresql.conf** file or the **postgresql.auto.conf** file of each database server.

## Starting the Database Servers with WAL Archiving

After the BART backup catalog directory structure has been configured, start the archiving of WAL files from the database servers by restarting each database server.

On BART host 192.168.2.22:

```
[root@localhost data]# service ppas-9.6 restart
```

On remote host 192.168.2.24:

```
[root@localhost data]# service ppas-9.6 restart
```

```
[root@localhost data]# service postgresql-9.6 restart
```

In the BART backup catalog, verify that the WAL files are archiving.

Archived WAL files may not appear very frequently depending upon how often WAL archiving is set to switch to a new segment file with the `archive_timeout` parameter in your database server configuration settings.

Verify that there are no archiving-related errors in the database server log files.

## Taking a Full Backup

The following code sample shows the first full backup of the database servers.

```
-bash-4.1$ bart BACKUP -s acctg -z
INFO: creating backup for server 'acctg'
INFO: backup identifier: '1490809695281'
60776/60776 kB (100%), 1/1 tablespace

INFO: backup completed successfully
INFO: backup checksum: 37f3defb98ca88dcf05079815555dfc2 of base.tar.gz
INFO:
BACKUP DETAILS:
BACKUP STATUS: active
BACKUP IDENTIFIER: 1490809695281
BACKUP NAME: acctg_2017-03-29T13:48
BACKUP PARENT: none
BACKUP LOCATION: /opt/backup/acctg/1490809695281
BACKUP SIZE: 6.10 MB
BACKUP FORMAT: tar.gz
BACKUP TIMEZONE: US/Eastern
XLOG METHOD: fetch
BACKUP CHECKSUM(s): 1
ChkSum File
37f3defb98ca88dcf05079815555dfc2 base.tar.gz

TABLESPACE(s): 0
START WAL LOCATION: 00000001000000000000000004
STOP WAL LOCATION: 00000001000000000000000004
BACKUP METHOD: streamed
BACKUP FROM: primary
START TIME: 2017-03-29 13:48:15 EDT
```

STOP TIME: 2017-03-29 13:48:17 EDT

TOTAL DURATION: 2 sec(s)

-bash-4.1\$ bart BACKUP -s mktg -z

INFO: creating backup for server 'mktg'

INFO: backup identifier: '1490809751193'

61016/61016 kB (100%), 1/1 tablespace

INFO: backup completed successfully

INFO: backup checksum: 8b010e130a105e76d01346bb56dfcf14 of base.tar.gz

INFO:

BACKUP DETAILS:

BACKUP STATUS: active

BACKUP IDENTIFIER: 1490809751193

BACKUP NAME: mktg\_2017-03-29T13:49

BACKUP PARENT: none

BACKUP LOCATION: /opt/backup/mktg/1490809751193

BACKUP SIZE: 6.13 MB

BACKUP FORMAT: tar.gz

BACKUP TIMEZONE: US/Eastern

XLOG METHOD: fetch

BACKUP CHECKSUM(s): 1

ChkSum File

8b010e130a105e76d01346bb56dfcf14 base.tar.gz

TABLESPACE(s): 0

START WAL LOCATION: 0000000010000000100000085

BACKUP METHOD: streamed

BACKUP FROM: primary

START TIME: 2017-03-29 13:49:11 EDT

STOP TIME: 2017-03-29 13:49:14 EDT

TOTAL DURATION: 3 sec(s)

-bash-4.1\$ bart BACKUP -s hr -z

INFO: creating backup for server 'hr'

INFO: backup identifier: '1490809824946'

38991/38991 kB (100%), 1/1 tablespace

INFO: backup completed successfully

INFO: backup checksum: 277e8a1a80ba3474f541eb316a417c9a of base.tar.gz

INFO:

BACKUP DETAILS:

BACKUP STATUS: active

BACKUP IDENTIFIER: 1490809824946

BACKUP NAME: hr\_2017-03-29T13:50

BACKUP PARENT: none

BACKUP LOCATION: /opt/backup/hr/1490809824946

BACKUP SIZE: 2.59 MB

BACKUP FORMAT: tar.gz

BACKUP TIMEZONE: US/Eastern

XLOG METHOD: fetch

BACKUP CHECKSUM(s): 1

ChkSum File

277e8a1a80ba3474f541eb316a417c9a base.tar.gz

TABLESPACE(s): 0

```

START WAL LOCATION: 00000001000000000000000002
BACKUP METHOD: streamed
BACKUP FROM: primary
START TIME: 2017-03-29 13:50:25 EDT
STOP TIME: 2017-03-29 13:50:26 EDT
TOTAL DURATION: 1 sec(s)

```

The following code sample shows the backup directories created for each backup of each database server. The backup ID is used as the backup directory name.

```

-bash-4.1$ cd /opt/backup
-bash-4.1$ ls -l
total 12
drwxrwxr-x 4 enterprisedb enterprisedb 4096 Mar 29 13:48 acctg
drwxrwxr-x 4 enterprisedb enterprisedb 4096 Mar 29 13:50 hr
drwxrwxr-x 4 enterprisedb enterprisedb 4096 Mar 29 13:49 mktg
-bash-4.1$ ls -l acctg
total 8
drwx----- 2 enterprisedb enterprisedb 4096 Mar 29 13:48 1490809695281
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:48 archived_wals
-bash-4.1$ ls -l hr
total 8
drwx----- 2 enterprisedb enterprisedb 4096 Mar 29 13:50 1490809824946
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:50 archived_wals
-bash-4.1$ ls -l mktg
total 8
drwx----- 2 enterprisedb enterprisedb 4096 Mar 29 13:49 1490809751193
drwxrwxr-x 2 enterprisedb enterprisedb 4096 Mar 29 13:49 archived_wals

```

## Using Point-In-Time Recovery

This section demonstrates using the point-in-time recovery operation on the remote PostgreSQL database server.

The following tables were created about two minutes apart with WAL archiving enabled:

```

postgres=# \dt

```

Schema	Name	Type	Owner
public	hr_rmt_t1_1356	table	postgres
public	hr_rmt_t1_1358	table	postgres
public	hr_rmt_t1_1400	table	postgres
public	hr_rmt_t1_1402	table	postgres
public	hr_rmt_t1_1404	table	postgres
public	hr_rmt_t1_1406	table	postgres

(6 rows)

In the table name `hr_rmt_t<n>_<hhmmi>`, `n` represents the active timeline. `<hhmmi>` is the approximate time the table was created. For example, `hr_rmt_t1_1356` was created at approximately 1:56 PM while timeline #1 is active.

The PostgreSQL database server was then stopped. WAL files that have been created, but not yet archived must be identified, and then saved. The following archived WAL files are in the BART backup catalog:

```
-bash-4.1$ ls -l hr/archived_wals
total 49156
-rw----- 1 enterprisedb enterprisedb 16777216 Mar 29 13:50
00000001000000000000000001
-rw----- 1 enterprisedb enterprisedb 16777216 Mar 29 13:50
00000001000000000000000002
-rw----- 1 enterprisedb enterprisedb 302 Mar 29 13:50
00000001000000000000000002.00000028.backup
-rw----- 1 enterprisedb enterprisedb 16777216 Mar 29 14:07
00000001000000000000000003
```

The following sample lists the current PostgreSQL server WAL files. The unarchived WAL files are marked with two stars (\*\*).

```
-bash-4.1$ cd /opt/PostgreSQL/9.6/data/pg_xlog
-bash-4.1$ pwd
/opt/PostgreSQL/9.6/data/pg_xlog
-bash-4.1$ ls -l
total 49160
-rw----- 1 postgres postgres 302 Mar 29 13:50
00000001000000000000000002.00000028.backup
-rw----- 1 postgres postgres 16777216 Mar 29 14:07
00000001000000000000000003
-rw----- 1 postgres postgres 16777216 Mar 29 14:07
**00000001000000000000000004**
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
**00000001000000000000000005**
drwx----- 2 postgres postgres 4096 Mar 29 14:07 archive_status
```

Copies of the unarchived WAL files are saved to a temporary location:

```
-bash-4.1$ mkdir /tmp/unarchived_pg96_wals
-bash-4.1$ pwd
/opt/PostgreSQL/9.6/data/pg_xlog
bash-4.1$ cp -p 00000001000000000000000004 /tmp/unarchived_pg96_wals
bash-4.1$ cp -p 00000001000000000000000005 /tmp/unarchived_pg96_wals
bash-4.1$ ls -l /tmp/unarchived_pg96_wals
total 32768
-rw----- 1 postgres postgres 16777216 Mar 29 14:07 00000001000000000000000004
-rw----- 1 postgres postgres 16777216 Mar 29 13:50 00000001000000000000000005
```

On the remote host, a directory is created to which the PostgreSQL database cluster is to be restored. This restore path is named `/opt/restore_pg96` and is owned by user account `postgres`.

```
[user@localhost ~]$ su root
Password:
[root@localhost user]# cd /opt
[root@localhost opt]# mkdir restore_pg96
[root@localhost opt]# chown postgres restore_pg96
[root@localhost opt]# chgrp postgres restore_pg96
[root@localhost opt]# chmod 700 restore_pg96
[root@localhost opt]# ls -l
total 16
drwxr-xr-x 4 root daemon 4096 Mar 29 12:10 PostgresPlus
drwxr-xr-x 3 root daemon 4096 Mar 29 12:25 PostgreSQL
```

```
drwx----- 2 postgres postgres 4096 Mar 29 14:15 restore_pg96
drwxr-xr-x. 2 root root 4096 Nov 22 2013 rh
```

In the BART configuration file, the remote user and remote host IP address, `postgres@192.168.2.24`, have been set with the `remote_host` parameter. If not given in the BART configuration file, this information must then be specified by the `--remote-host` option when giving the `RESTORE` subcommand (for example, `bart RESTORE --remote-host postgres@192.168.2.24 ...`).

[HR]

```
host = 192.168.2.24
port = 5432
user = postgres
cluster_owner = postgres
backup_name = hr_%year-%month-%dayT%hour:%minute
remote_host = postgres@192.168.2.24
copy_wals_during_restore = enabled
description = "Human Resources"
```

Use the `SHOW-BACKUPS` subcommand to identify the backup to use with the `RESTORE` subcommand.

SERVER NAME	BACKUP ID	BACKUP NAME	BACKUP PARENT
acctg	1490809695281	acctg_2017-03-29T13:48	none
2017-03-29 13:48:17 EDT			
6.10 MB	32.00 MB	2	active
hr	1490809824946	hr_2017-03-29T13:50	none
2017-03-29 13:50:26 EDT			
2.59 MB	32.00 MB	2	active
mktg	1490809751193	mktg_2017-03-29T13:49	none
2017-03-29 13:49:14 EDT			
6.13 MB	64.00 MB	4	active

The `-t` option with the `SHOW-BACKUPS` subcommand displays additional backup information:

```
-bash-4.1$ bart SHOW-BACKUPS -s hr -i 1490809824946 -t
SERVER NAME      : hr
BACKUP ID       : 1490809824946
BACKUP NAME     : hr_2017-03-29T13:50
BACKUP PARENT   : none
BACKUP STATUS   : active
BACKUP TIME     : 2017-03-29 13:50:26 EDT
BACKUP SIZE     : 2.59 MB
WAL(S) SIZE    : 32.00 MB
NO. OF WAL     : 2
FIRST WAL FILE  : 00000001000000000000000002
CREATION TIME   : 2017-03-29 13:50:31 EDT
LAST WAL FILE   : 00000001000000000000000003
CREATION TIME   : 2017-03-29 14:07:35 EDT
```

A recovery is made using timeline `1` to `2017-03-29 14:01:00`.

```
-bash-4.1$ bart RESTORE -s hr -i hr_2017-03-29T13:50 -p
/opt/restore_pg96 -t 1 -g '2017-03-29 14:01:00'
```

```
INFO: restoring backup 'hr_2017-03-29T13:50' of server 'hr'
INFO: base backup restored
INFO: copying WAL file(s) to
postgres@192.168.2.24:/opt/restore_pg96/archived_wals
INFO: writing recovery settings to postgresql.auto.conf file
INFO: archiving is disabled
INFO: permissions set on $PGDATA
INFO: restore completed successfully
```

The following example shows the restored backup files in the restore path directory, `/opt/restore_pg96`:

```
-bash-4.1$ pwd
/opt/restore_pg96
-bash-4.1$ ls -l
total 128
drwxr-xr-x 2 postgres postgres 4096 Mar 29 14:27 archived_wals
-rw----- 1 postgres postgres 206 Mar 29 13:50 backup_label
drwx----- 5 postgres postgres 4096 Mar 29 12:25 base
drwx----- 2 postgres postgres 4096 Mar 29 14:27 global
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_clog
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_commit_ts
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_dynshmem
-rw----- 1 postgres postgres 4212 Mar 29 13:18 pg_hba.conf
-rw----- 1 postgres postgres 1636 Mar 29 12:25 pg_ident.conf
drwxr-xr-x 2 postgres postgres 4096 Mar 29 13:45 pg_log
drwx----- 4 postgres postgres 4096 Mar 29 12:25 pg_logical
drwx----- 4 postgres postgres 4096 Mar 29 12:25 pg_multixact
drwx----- 2 postgres postgres 4096 Mar 29 13:43 pg_notify
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_replslot
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_serial
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_snapshots
drwx----- 2 postgres postgres 4096 Mar 29 13:43 pg_stat
drwx----- 2 postgres postgres 4096 Mar 29 13:50 pg_stat_tmp
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_subtrans
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_tblspc
drwx----- 2 postgres postgres 4096 Mar 29 12:25 pg_twophase
-rw----- 1 postgres postgres 4 Mar 29 12:25 PG_VERSION
drwx----- 3 postgres postgres 4096 Mar 29 14:27 pg_xlog
-rw----- 1 postgres postgres 169 Mar 29 13:24 postgresql.auto.conf
-rw-r--r-- 1 postgres postgres 21458 Mar 29 14:27 postgresql.conf
-rw-r--r-- 1 postgres postgres 118 Mar 29 14:27 postgresql.auto.conf
```

Copy the saved, unarchived WAL files to the restore path `pg_xlog` subdirectory (`/opt/restore_pg96/pg_xlog`):

```
-bash-4.1$ pwd
/opt/restore_pg96/pg_xlog
-bash-4.1$ ls -l
total 16388
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
00000000100000000000000000000002
drwx----- 2 postgres postgres 4096 Mar 29 14:27 archive_status
-bash-4.1$ ls -l /tmp/unarchived_pg96_wals
total 32768
-rw----- 1 postgres postgres 16777216 Mar 29 14:07
00000000100000000000000000000004
```



```
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
0000000010000000000000000005
-bash-4.1$ cp -p /tmp/unarchived_pg96_wals/* .
-bash-4.1$ ls -l
total 49156
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
0000000010000000000000000002
-rw----- 1 postgres postgres 16777216 Mar 29 14:07
0000000010000000000000000004
-rw----- 1 postgres postgres 16777216 Mar 29 13:50
0000000010000000000000000005
drwx----- 2 postgres postgres 4096 Mar 29 14:27 archive_status
```

Inspect the `/opt/restore_pg96/postgresql.auto.conf` file to verify that it contains the correct recovery settings:

```
restore_command = 'cp archived_wals/%f %p'
recovery_target_time = '2017-03-29 14:01:00'
recovery_target_timeline = 1
```

Note that the command restores from the `archived_wals` subdirectory of `/opt/restore_pg96` since the `copy_wals_during_restore` parameter in the BART configuration file is set to `enabled` for database server `hr`.

Start the database server to initiate the point-in-time recovery operation:

```
[user@localhost ~]$ su postgres
Password:
bash-4.1$ cd /opt/restore_pg96
bash-4.1$ /opt/PostgreSQL/9.6/bin/pg_ctl start -D /opt/restore_pg96 -l
/opt/restore_pg96/pg_log/logfile
server starting
```

Inspect the database server log file to ensure the operation did not result in any errors:

```
2017-03-29 14:33:23 EDT LOG: database system was interrupted; last known
up at 2017-03-29 13:50:25 EDT
2017-03-29 14:33:23 EDT LOG: starting point-in-time recovery to
2017-03-29 14:01:00-04
2017-03-29 14:33:23 EDT LOG: restored log file
"0000000010000000000000000002" from archive
2017-03-29 14:33:23 EDT LOG: redo starts at 0/2000098
2017-03-29 14:33:23 EDT LOG: consistent recovery state reached at
0/20000C0
2017-03-29 14:33:23 EDT LOG: restored log file
"0000000010000000000000000003" from archive
2017-03-29 14:33:23 EDT LOG: recovery stopping before commit of
transaction 1762, time 2017-03-29 14:02:28.100072-04
2017-03-29 14:33:23 EDT LOG: redo done at 0/303F390
2017-03-29 14:33:23 EDT LOG: last completed transaction was at log time
2017-03-29 14:00:43.351333-04
cp: cannot stat `archived_wals/00000002.history': No such file or
directory
2017-03-29 14:33:23 EDT LOG: selected new timeline ID: 2
cp: cannot stat `archived_wals/00000001.history': No such file or
directory
```

```

2017-03-29 14:33:23 EDT LOG: archive recovery complete
2017-03-29 14:33:23 EDT LOG: MultiXact member wraparound protections are
now enabled
2017-03-29 14:33:23 EDT LOG: database system is ready to accept
connections
2017-03-29 14:33:23 EDT LOG: autovacuum launcher started

```

The tables that exist in the recovered database cluster are:

```

postgres=# \dt
           List of relations
Schema | Name | Type | Owner
-----+-----+-----+-----
public | hr_rmt_t1_1356 | table | postgres
public | hr_rmt_t1_1358 | table | postgres
public | hr_rmt_t1_1400 | table | postgres
(3 rows)

```

Since recovery was up to and including 2017-03-29 14:01:00, the following tables created after 14:01 are not present:

```

public | hr_rmt_t1_1402 | table | postgres
public | hr_rmt_t1_1404 | table | postgres
public | hr_rmt_t1_1406 | table | postgres

```

The BART **RESTORE** operation stops WAL archiving by adding an **archive\_mode = off** parameter at the very end of the **postgresql.conf** file. This last parameter in the file overrides any other previous setting of the same parameter in the file. Delete the last setting and restart the database server to start WAL archiving.

```

### Add settings for extensions here
archive_mode = off

```

## 5 EDB Postgres Backup and Recovery User Guide

### 5.1 Introduction

The EDB Backup and Recovery Tool (BART) is an administrative utility that provides simplified backup and recovery management for multiple local or remote EDB Advanced Server and PostgreSQL database servers.

BART provides the following features:

- Support for complete, hot, physical backups of multiple Advanced Servers and PostgreSQL database servers
- Support for two types of backups – full base backups and block-level incremental backups
- Backup and recovery management of database servers on local or remote hosts
- A single, centralized catalog for backup data
- Retention policy support for defining and managing how long backups should be kept
- The capability to store the backup data in compressed format

- Verified backup data with checksums
- Backup information displayed in an easy-to-read format
- A simplified point-in-time recovery process

This guide provides the following information about using BART:

- an [overview](#) of the BART components and concepts.
- [backup and recovery management process](#).
- [using tablespaces](#).

For information about installing BART, see the *EDB Backup and Recovery Installation and Upgrade Guide*, for examples of BART operations and subcommand usage, see the *EDB Backup and Recovery Reference Guide*. These guides are available at the [EDB website](#).

## Conventions Used in this Guide

The following is a list of conventions used throughout this document.

- Much of the information in this document applies interchangeably to the PostgreSQL and EDB Advanced Server database systems. The term *Advanced Server* is used to refer to EDB Advanced Server. The term *Postgres* is used to generically refer to both PostgreSQL and Advanced Server. When a distinction needs to be made between these two database systems, the specific names, PostgreSQL or Advanced Server are used.
- The installation directory of the PostgreSQL or Advanced Server products is referred to as `POSTGRES_INSTALL_HOME`:
  - For PostgreSQL Linux installations, this defaults to `/opt/PostgreSQL/<x.x>` for version 10 and earlier. For later versions, the installation directory is `/var/lib/pgsql/<x.x>`.
  - For Advanced Server Linux installations performed using the interactive installer for version 10 and earlier, this defaults to `/opt/PostgresPlus/<x.x>AS` or `/opt/edb/as<x.x>`. For Advanced Server Linux installations performed with an RPM package, this defaults to `/usr/ppas-<x.x>` or `/usr/edb/as<x.x>`. For Advanced Server Linux installations performed with an RPM package for version 11 or later, this defaults to `/usr/edb/as<xx>`.

## Restrictions on pg\_basebackup

BART takes full backups using the `pg_basebackup` utility program under the following conditions:

- The backup is taken on a standby server.
- The `--with-pg_basebackup` option is specified with the `BACKUP` subcommand (see [Backup](#)).
- The number of thread count in effect is 1, and the `with-pg_basebackup` option is not specified with the `BACKUP` subcommand.
- Database servers can only be backed up using `pg_basebackup` utility program of the same or later version than the database server version.

In the global section of the BART configuration file, the `pg_basebackup_path` parameter specifies the complete directory path to the `pg_basebackup` program. For information about the `pg_basebackup_path` parameter and the `thread_count`, see the *EDB Backup and Recovery Installation and Upgrade Guide* available at the [EDB website](#).

For information about `pg_basebackup`, see the [PostgreSQL Core Documentation](#).

## 5.2 Overview

BART provides a simplified interface for the continuous archiving and point-in-time recovery method provided with Postgres database servers. This consists of the following processes:

- Capturing a complete image of a database cluster as a full base backup or referred to simply as a *full backup*.
- Capturing a modified image of a database cluster called a *block-level incremental backup* or referred as *incremental backup*, which is similar to a full backup, but contains the modified blocks of the relation files that have been changed since a previous backup.
- Archiving the **Write-Ahead Log segments** (WAL files), which continuously record changes to be made to the database files.
- Performing *Point-In-Time Recovery* (PITR) to a specified transaction ID or timestamp with respect to a timeline using a full backup along with successive, **block-level incremental backups** that reside in the same backup chain, and the WAL files.

Detailed information regarding WAL files and point-in-time recovery is documented in the [PostgreSQL Core Documentation](#).

The general term *backup* refers to both full backups and incremental backups.

When taking a full backup of a standby server, BART uses the PostgreSQL **pg\_basebackup** utility program. However, it must be noted that for standby servers, you can only take a full backup, but cannot take an incremental or parallel backups. For information about standby servers, see the [PostgreSQL Documentation](#).

BART uses a centralized backup catalog, a single configuration file, and a command line interface controlling the necessary operations to simplify the management process. Reasonable defaults are automatically used for various backup and restore options. BART also performs the necessary recovery file configuration required for point-in-time recovery using its command line interface.

BART also provides the following features to enhance backup management:

- Automation of the WAL archiving command configuration.
- Usage of retention policies to evaluate, categorize, and delete obsolete backups.
- Compression of WAL files to conserve disk space.
- Customizable naming of backups to ease their usage.
- Easy access to comprehensive information about each backup.

The key components of a BART installation are:

- BART Host. The host system on which BART is installed. BART operations are invoked from this host system. The database server backups and archived WAL files are stored on this host as well.
- BART User Account. Linux operating system user account you choose to run BART. The BART user account owns the BART backup catalog directory.
- BART Configuration File. File in editable text format containing the configuration information that BART uses.
- BART Backup Catalog. File system directory structure containing all of the backups for the database servers that BART manages. It is also the default **archive\_path** to store archived WAL files.
- BART Backupinfo File. File in text format containing information for a BART backup. A **backupinfo** file resides in each backup subdirectory within the BART backup catalog.
- BART Command Line Utility Program. Single, executable file named **bart**, which is used to manage all BART operations.
- BART WAL Scanner Program. Single, executable file named **bart-scanner**, which is used to scan WAL files to locate and record the modified blocks for incremental backups.

Other concepts and terms referred to in this document include the following:

- **Postgres Database Cluster.** Also commonly called the *data directory*, this is the file system directory where all of the data files related to a particular Postgres database server instance are stored. (Each specific running instance is identified by its host and port number when connecting to a database.) The database cluster is identified by the `-D` option when it is created, started, stopped, etc. by the `Postgres initdb` and `pg_ctl` commands. A full backup is a copy of a database cluster.

The terms database cluster and database server are used somewhat interchangeably throughout this document, though a single database server can run multiple database clusters.

- **Postgres User Account.** Linux operating system user account that runs the Advanced Server or PostgreSQL database server and owns the database cluster directory.
  - By default, the database user account is `enterprisedb` when Advanced Server is installed to support compatibility with Oracle databases.
  - By default, the database user account is `postgres` when Advanced Server is installed in PostgreSQL compatible mode. For a PostgreSQL database server, the default database user account is also `postgres`.

The BART configuration parameter `cluster_owner` must be set to the database user account for each database server.

- **Replication Database User.** For each database server that BART manages, a database superuser must be selected to act as the replication database user. This database user is used to connect to the database server when backups are taken. The database superusers created with an initial Postgres database server installation (`enterprisedb` or `postgres`) may be used for this purpose. The BART configuration parameter `user` must be set to this replication database user for each database server.
- **Secure Shell (SSH)/Secure Copy (SCP).** Linux utility programs used to log into hosts (SSH) and copy files (SCP) between hosts. A valid user account must be specified that exists on the target host and in fact is the user account under which the SSH or SCP operations occur.

For information on how all of these components are configured and used with BART, see the EDB Backup and Recovery Installation and Upgrade Guide available at the [EDB website](#).

## Supported BART Operations

The following tables are not a conclusive list of the scenarios supported by BART, but instead provides an overview of some of the most common scenarios in both `pg_basebackup` (thread count=1) as well as parallel backup mode (thread count greater than 1).

	<code>-Fp-xlog-method=fetch</code>	<code>-Fp-xlog-method=stream</code>	<code>-Ft-xlog-method=fetch</code>	<code>-Ft-xlog-method=stream</code>
<b>Primary Database Server/Full backup</b>	Supported	Supported	Supported	Supported
<b>Primary Database Server/Incremental backup</b>	Supported	Supported	Not Supported	Not Supported
<b>Standby Database Server/Full backup</b>	Supported	Supported	Supported	Supported
<b>Standby Database Server/Incremental backup</b>	Not Supported	Not Supported	Not Supported	Not Supported

## Backup

Wal compression by BART      WAL scanner

	Wal compression by BART	WAL scanner
Primary Database Server/Full backup	Supported	N/A
Primary Database Server/Incremental backup	Not Supported	N/A
Standby Database Server/Full backup	Supported	N/A
Standby Database Server/Incremental backup	Not Supported	N/A

### Wal Archiving

	Wal compression = enabled	Wal compression = disabled
Restore	Supported	Supported
Parallel restore	Supported	Supported

### Restore

## 5.2.1 Block-Level Incremental Backup

This section describes the basic concepts of a block-level incremental backup (referred to as an incremental backup). An incremental backup is a unique functionality of BART.

An incremental backup provides a number of advantages when compared to using a full backup:

- The amount of time required to produce an incremental backup is generally less than a full backup, as modified relation blocks are saved instead of all full relation files of the database cluster.
- An incremental backup uses less disk space than a full backup.

Generally, all BART features (such as retention policy management) apply to incremental backups and full backups. See [Managing Incremental Backups](#) for more information.

### 5.2.1.1 Incremental Backup Limitations and Requirements

The following limitations apply to incremental backup:

- If you have restored a full or incremental backup, you must take a full backup before enabling incremental backup.
- If a standby node has been promoted to the role of a primary node, you must take a full backup before enabling incremental backup on the cluster.
- On a standby database server, you cannot take an incremental backup.

You must meet the following requirements before implementing incremental backup:

- You must create or select an operating system account to be used as the BART user account.
- You must create or select the replication database user, which must be a superuser.

- In the BART configuration file:
  - You must set the `cluster_owner` parameter to the Linux operating system user account that owns the database cluster directory from which incremental backups are to be taken.
  - You must enable the `allow_incremental_backups` parameter.
- A passwordless SSH/SCP connection must be established between the BART user account on the BART host and the `cluster_owner` user account on the database server.

It must be noted that a passwordless SSH/SCP connection must be established even if BART and the database server are running on the same host and the BART user account and the `cluster_owner` user account are the same account.

- In addition to the BART host (where the BART backup catalog resides), the BART package must also be installed on every remote database server on which incremental backups are to be restored. To restore an incremental backup, the `bart` program must be executable on the remote host by the remote user (the remote user is specified by the `remote_host` parameter in the BART configuration file or by the `-r` option when using the `RESTORE` subcommand to restore the incremental backup).
- When [restoring incremental backups on a remote database server](#), a passwordless SSH/SCP connection must be established from the BART user account on the BART host to the remote user on the remote host (the remote user is specified by the `remote_host` parameter in the BART configuration file or by the `-r` option when using the `RESTORE` subcommand to restore the incremental backup).
- Compression of archived WAL files in the BART backup catalog is not permitted for database servers on which incremental backups are to be taken. The `wal_compression` setting in the BART configuration file must be disabled for those database servers.
- The incremental backup must be on the same timeline as the parent backup. The timeline changes after each recovery operation so an incremental backup cannot use a parent backup from an earlier timeline.

For information about configuring these requirements, see the EDB Backup and Recovery Installation and Upgrade Guide available at the [EDB website](#).

The following section provides an overview of the basic incremental backup concepts.

## 5.2.1.2 Concept Overview

Using incremental backups involves the following sequence of steps:

1. Configure BART, and enable and initiate archiving of WAL files to the `archive_path` in the same manner as done for full backups.

The default `archive_path` is the BART backup catalog (`<backup_path>/<server_name>/archived_wals`). Using the `<archive_path>` parameter in the server section of the BART configuration file, you can specify the location where WAL files will be archived.

For more information about the `archive_path` parameter and configuring BART, see the EDB Backup and Recovery Installation and Upgrade Guide available at the [EDB website](#).

2. Take an initial full backup with the `BACKUP` subcommand. This full backup establishes the parent of the first



incremental backup.

3. Scan all WAL files produced by database servers on which incremental backups are to be taken. These WAL files are scanned once they have been archived to the `archive_path`.

Each scanned WAL file results in a modified block map (MBM) file that records the location of modified blocks obtained from the corresponding WAL file. The BART WAL scanner program `bart-scanner` performs this process.

4. Take incremental backups using the `BACKUP` subcommand with the `--parent` option to specify the backup identifier or name of a previous, full backup or an incremental backup. Any previous backup may be chosen as the parent as long as all backups belong to the same timeline.
5. The incremental backup process identifies which WAL files may contain changes from when the parent backup was taken to the starting point of the incremental backup. The corresponding MBM files are used to locate and copy the modified blocks to the incremental backup directory along with other database cluster directories and files. Instead of backing up all, full relation files, only the modified blocks are copied and saved. In addition, the relevant MBM files are condensed into one consolidated block map (CBM) file that is stored with the incremental backup.

Multiple block copier threads can be used to copy the modified blocks to the incremental backup directory. See the *EDB Backup and Recovery Installation and Upgrade Guide* available at the [EDB website](#) for information about setting the `thread_count` parameter in the BART configuration file. See [Backup](#) for information about using the `--thread-count` option with the `BACKUP` subcommand.

6. Invoke the restore process for an incremental backup using the `RESTORE` subcommand in the same manner as restoring a full backup. The `-i` option specifies the backup identifier or name of the incremental backup to restore. The restore process begins by going back through the chain of past, parent incremental backups until the initial full backup starting the chain is identified. This full backup provides the initial set of directories and files to be restored to the location specified with the `-p` option. Each subsequent incremental backup in the chain is then restored. Restoration of an incremental backup uses its CBM file to restore the modified blocks from the incremental backup.

The following sections provide some additional information on these procedures.

### 5.2.1.3 WAL Scanning – Preparation for an Incremental Backup

The WAL scanner program (`bart-scanner`) scans the WAL files created from the time of the parent backup up to the start of the incremental backup to determine which blocks have modified since the parent backup, and records the information in a file called the *modified block map (MBM) file*. One MBM file is created for each WAL file.

The MBM file is stored in the directory where archived\_wals will be stored, as specified in the `archive_path` parameter in the `bart.cfg` file. If the `archive_path` is not specified, the default `archived_wals` directory is:

```
<backup_path>/<server_name>/<archived_wals>
```

Where:

`<backup_path>` is the BART backup catalog parent directory specified in the global section of the BART configuration file.

`<server_name>` is the lowercase conversion of the database server name specified in the server section of the BART configuration file.



The following code snippet is the content of the archive path showing the MBM files created for the WAL files. (The user name and group name of the files have been removed from the example to list the WAL files and MBM files in a more comparable manner):

```
[root@localhost archived_wals]# pwd
/opt/backup/acctg/archived_wals
[root@localhost archived_wals]# ls -l
total 131104
-rw----- 1 ... 16777216 Oct 12 09:38 000000010000000100000078
-rw----- 1 ... 16777216 Oct 12 09:38 000000010000000100000079
-rw----- 1 ... 16777216 Oct 12 09:38 00000001000000010000007A
-rw----- 1 ... 16777216 Oct 12 09:35 00000001000000010000007B
-rw----- 1 ... 16777216 Oct 12 09:38 00000001000000010000007C
-rw----- 1 ... 16777216 Oct 12 09:39 00000001000000010000007D
-rw----- 1 ... 16777216 Oct 12 09:42 00000001000000010000007E
-rw----- 1 ... 16777216 Oct 12 09:47 00000001000000010000007F
-rw-rw-r-- 1 ... 161 Oct 12 09:49 000000010000000178000028000000001790000000.mbm
-rw-rw-r-- 1 ... 684 Oct 12 09:49 0000000100000001790000280000000017A0000000.mbm
-rw-rw-r-- 1 ... 161 Oct 12 09:49 00000001000000017A0000280000000017B0000000.mbm
-rw-rw-r-- 1 ... 161 Oct 12 09:49 00000001000000017B0000280000000017C0000000.mbm
-rw-rw-r-- 1 ... 1524 Oct 12 09:49 00000001000000017C0000280000000017D0000000.mbm
-rw-rw-r-- 1 ... 161 Oct 12 09:49 00000001000000017D0000280000000017E0000000.mbm
-rw-rw-r-- 1 ... 161 Oct 12 09:49 00000001000000017E0000280000000017F0000000.mbm
-rw-rw-r-- 1 ... 161 Oct 12 09:49 00000001000000017F00002800000000180000000.mbm
```

MBM files have the suffix, `.mbm`.

In preparation for any incremental backup, the WAL files should be scanned as soon as they are copied to the `archive_path`. Thus, the WAL scanner should be running as soon as the WAL files from the database cluster are archived to the `archive_path`. If the `archive_path` contains WAL files that have not yet been scanned, starting the WAL scanner begins scanning these files. If WAL file fails to be scanned (resulting in a missing MBM file), you can use the WAL scanner to specify an individual WAL file.

Under certain conditions such as when the Network File System (NFS) is used to copy WAL files to the `archive_path`, the WAL files may have been missed by the WAL scanner program for scanning and creation of MBM files. Use the `scan_interval` parameter in the BART configuration file to initiate force scanning of WAL files in the `archive_path` to ensure MBM files are generated. See the *EDB Backup and Recovery Installation and Upgrade Guide* available at the [EDB website](#) for more information about the `scan_interval` parameter.

See [Running the BART WAL Scanner](#) for information about using the WAL scanner.

## 5.2.1.4 Performing an Incremental Backup

The WAL files produced at the time of the parent backup up to the start of the incremental backup contain information about which blocks were modified during that time interval. That information is consolidated into an MBM file for each WAL file by the WAL scanner.

The MBM files for the relevant WAL files are read, and the information is used to copy the modified blocks from the database cluster to the `archived_wals` directory as specified in the `archive_path` parameter in the `bart.cfg` file. When compared to a full backup, the number and sizes of relation files can be significantly less for an incremental backup.

For comparison, the following is an abbreviated list of the files copied to the archived `base` subdirectory of a full backup for one database:

```
[root@localhost 14845]# pwd
/opt/backup/acctg/1476301238969/base/base/14845
[root@localhost 14845]# ls
112          13182_vm    14740  16467  16615      2608_vm    2655  2699      2995
...
113          13184      14742  16471  174        2609       2656  2701      2995_vm
...
1247        13186      14745  16473  175        2609_fsm   2657  2702      2996
...
1247_fsm    13187      14747  16474  2187       2609_vm    2658  2703      2998
...
1247_vm     13187_fsm  14748  16476  2328       2610       2659  2704      2998_vm
...
1249        13187_vm    14749  16477  2328_fsm   2610_fsm   2660  2753      2999
...
1249_fsm    13189      14752  16479  2328_vm    2610_vm    2661  2753_fsm  2999_vm
...
1249_vm     13191      14754  16488  2336       2611       2662  2753_vm   3079
...
1255        13192      14755  16490  2336_vm    2611_vm    2663  2754      3079_fsm
...
...
...
13182_fsm   14739      16465  16603  2608_fsm   2654       2696  2893_vm   3501_vm
...
```

In contrast, the following is the content of the archived `base` subdirectory of the same database from a subsequent incremental backup:

```
[root@localhost 14845]# pwd
/opt/backup/acctg/1476301835391/base/base/14845
[root@localhost 14845]# ls
1247        1249        1259        16384  17006  2608      2610      2658  2663  2678
...
1247_fsm    1249_fsm    1259_fsm    16387  17009  2608_fsm  2610_fsm  2659  2673  2679
...
1247_vm     1249_vm     1259_vm     16389  17011  2608_vm   2610_vm   2662  2674  2703
...
```

The information from the MBM files are consolidated into one file called a *consolidated block map* (CBM) file. During the restore operation for the incremental backup, the CBM file is used to identify the modified blocks to be restored for that backup. In addition, the incremental backup also stores other required subdirectories and files from the database cluster as is done for full backups.

Before taking an incremental backup, an initial full backup must be taken with the `BACKUP` subcommand. This full backup establishes the parent of the first incremental backup.

The syntax for taking a full backup is:

```
bart BACKUP -s { <server_name> | all } [ -F { p | t } ]
[ -z ] [ -c <compression_level> ]
```

```
[ --backup-name <backup_name> ]
[ --thread-count <number_of_threads> ]
[ { --with-pg_basebackup | --no-pg_basebackup } ]
```

The syntax for taking an incremental backup is:

```
bart BACKUP -s { <server_name> | all } [ -F p]
[ --parent { <backup_id> | <backup_name> } ]
[ --backup-name <backup_name> ]
[ --thread-count <number_of_threads> ]
[ --check ]
```

You must specify the following before taking an incremental backup:

- `-Fp` option for plain text format as incremental backup can only be taken in the plain text format.
- `--check` option to verify if the required MBM files are present in the `archived_wals` directory. The `--parent` option must be specified when the `--check` option is used.

See [BACKUP](#) for more information about using the `BACKUP` subcommand.

## 5.2.1.5 Restoring an Incremental Backup

Restoring an incremental backup may require additional steps depending upon the host on which the incremental backup is to be restored:

- [Restoring an Incremental Backup on a BART Host](#) - This section outlines restoring an incremental backup onto the same host where BART has been installed.
- [Restoring an Incremental Backup on a Remote Host](#) - This section outlines restoring an incremental backup onto a remote host where BART has not been installed.

### Restoring an Incremental Backup on a BART Host

Specify a backup identifier or name, and include the `-i` option when invoking the `RESTORE` subcommand to restore an incremental backup. All `RESTORE` options may be used in the same manner as when restoring a full backup. See [RESTORE](#) command for more details.

First, all files from the full backup from the beginning of the backup chain are restored. For each incremental backup, the CBM file is used to identify and restore blocks from the incremental backup. If there are new relations or databases identified in the CBM file, then relevant relation files are copied. If consolidated block map information is found indicating the drop of a relation or a database, then the relevant files are removed from the restore directory. Similarly, if there is any indication of a table truncation, then the related files are truncated.

Also note that you can use the `-w` option of the `RESTORE` subcommand to specify a multiple number of parallel worker processes to stream the modified blocks to the restore host.

### Restoring an Incremental Backup on a Remote Host

Ensure the `bart` program is available on the remote host when restoring an incremental backup on a remote host; the invocation of the `RESTORE` subcommand for an incremental backup results in the execution of the `bart` program on the remote host to restore the modified blocks to their proper location.

To restore an incremental backup onto a remote host where BART has not been installed, perform the following steps:

Step 1: Install `BART` on the remote host to which an incremental backup is to be restored.

No editing is needed in the `bart.cfg` file installed on the remote host.

Step 2: Determine the Linux operating system user account on the remote host to be used as the remote user. This user is specified by the `remote_host` parameter in the BART configuration file or by the `-r` option when using the `RESTORE` subcommand to restore the incremental backup. The remote user must be the owner of the directory where the incremental backup is to be restored on the remote host. By default, the user account is `enterprisedb` for Advanced Server or `postgres` for PostgreSQL.

Step 3: Ensure a passwordless SSH/SCP connection is established from the BART user on the BART host to the remote user on the remote host. For information about creating a passwordless SSH/SCP connection, see the *EDB Backup and Recovery Installation and Upgrade Guide*, available at the [EDB website](#).

When restoring an incremental backup, specify the backup identifier or name of the incremental backup that will be restored. See the `RESTORE` documentation for more details. To view an example of restoring an incremental backup, see the *EDB Backup and Recovery Reference Guide* available at the [EDB website](#).

## 5.2.2 Creating a Backup Chain

A *backup chain* is the set of backups consisting of a full backup and all of its successive incremental backups. Tracing back on the parent backups of all incremental backups in the chain eventually leads back to that single, full backup.

It is possible to have a *multi-forked* backup chain, which is two or more successive lines of incremental backups, all of which begin with the same, full backup. Thus, within the chain there is a backup that serves as the parent of more than one incremental backup.

Since restoration of an incremental backup is dependent upon first restoring the full backup, then all successive incremental backups up to, and including the incremental backup specified by the `RESTORE` subcommand, it is crucial to note the following:

- Deletion or corruption of the full backup destroys the entire backup chain. It is not possible to restore any of the incremental backups that were part of that chain.
- Deletion or corruption of an incremental backup within the chain results in the inability to restore any incremental backup that was added to that successive line of backups following the deleted or corrupted backup. The full backup and incremental backups prior to the deleted or corrupted backup can still be restored.

The actions of retention policy management are applied to the full backup and all of its successive incremental backups within the chain in an identical manner as if they were one backup. Thus, use of retention policy management does not result in the breakup of a backup chain.

See the *EDB Backup and Recovery Reference Guide*, available at the [EDB website](#) for examples of creating a backup chain and restoring an incremental backup.

## 5.3 Using BART

After installing and configuring the BART host and the database servers, you can start using BART.

This section describes how to perform backup and recovery management operations using BART. Review the sections that follow before proceeding with any BART operation.

### 5.3.1 BART Management Overview

After configuring BART, you can begin the backup and recovery management process. The following steps will help you get started:

1. Run the `CHECK-CONFIG` subcommand without the `-s` option. When the `CHECK-CONFIG` subcommand is used without specifying the `-s` option, it checks the parameters in the global section of the BART configuration file.
2. Run the `INIT` subcommand (if you have not already done so) to finish creation of the BART backup catalog, which results in the complete directory structure to which backups and WAL files are saved. This step must be done before restarting the database servers with enabled WAL archiving, otherwise the copy operation in the `archive_command` parameter of the `postgresql.conf` file or the `postgresql.auto.conf` file fails due to the absence of the target archive directory. When the directory structure is complete, the `archived_wals` subdirectory should exist for each database server.
3. Start the Postgres database servers with archiving enabled. Verify that the WAL files are appearing in the `archive_path`. The archiving frequency is dependent upon other `postgresql.conf` configuration parameters. Check the Postgres database server log files to ensure there are no archiving errors. Archiving should be operational before taking a backup in order to ensure that the WAL files that may be created during the backup process are archived.
4. Start the WAL scanner if you intend to take incremental backups. Since the WAL scanner processes the WAL files copied to the `archive_path`, it is advantageous to commence the WAL scanning as soon as the WAL files begin to appear in the `archive_path` in order to keep the scanning in pace with the WAL archiving.
5. Run the BART `CHECK-CONFIG` subcommand for each database server with the `-s` option specifying the server name. This ensures the database server is properly configured for taking backups.
6. Create a full backup for each database server. The full backup establishes the starting point of when point-in-time recovery can begin and also establishes the initial parent backup for any incremental backups to be taken.

There are now a number of other BART management processes you may perform:

- Execute the `BACKUP` subcommand to create additional full backups or incremental backups.
- Use the `VERIFY-CHKSUM` subcommand to verify the checksum of the full backups.
- Display database server information with the `SHOW-SERVERS` subcommand.
- Display backup information with the `SHOW-BACKUPS` subcommand.
- Compress the archived WAL files in the `archive_path` by enabling WAL compression in the BART configuration file and then invoking the `MANAGE` subcommand.
- Determine and set the retention policy for backups in the BART configuration file.

- Establish the procedure for using the `MANAGE` subcommand to enforce the retention policy for backups. This may include using `cron` jobs to schedule the `MANAGE` subcommand.

### 5.3.1.1 Performing a Restore Operation

The following steps describe the process of restoring a backup:

Step 1: Use your system-specific command to shut down the database server.

Step 2: Inspect the `pg_wal` subdirectory (inspect the `pg_xlog` subdirectory if you are using server version 9.6) of the data directory and save any WAL files that have not yet been archived to the `archive_path`. If there are files that have not been archived, save them to a temporary location.

Step 3: If you want to restore to current data directory, it is recommended to make a copy of the current data directory and then delete all files and subdirectories under the data directory if you have enough extra space. If there is not enough space, then make a copy of `pg_wal` directory (or `pg_xlog` if you are using server version 9.6) until the server is successfully restored.

If you want to restore to a new, empty directory, create the directory on which you want to restore the backed up database cluster. Ensure the data directory can be written to by the BART user account or by the user account specified by the `remote_host` configuration parameter, or by the `--remote-host` option of the `RESTORE` subcommand (if these are to be used).

Step 4: Perform the same process for tablespaces as described in Step 3. The `tablespace_path` parameter in the BART configuration file must contain the tablespace directory paths to which the tablespace data files are to be restored. See the *EDB Backup and Recovery Installation and Upgrade Guide* available at the [EDB website](#) for more information about this parameter.

Step 5: Identify the backup to use for the restore operation and obtain the backup ID or backup name.

To use the latest backup, omit the `-i` option; the `RESTORE` subcommand uses that backup by default. The backups can be listed with the `SHOW-BACKUPS` subcommand.

Step 6: Run the BART `RESTORE` subcommand.

- Minimal recovery settings will be saved in the `postgresql.auto.conf` file and archive recovery will proceed only until consistency is reached, with no restoration of files from the archive. See [Restore](#) for detailed information about `Restore` subcommand.
- If the `-c` option is specified or if the `copy_wals_during_restore` BART configuration parameter is enabled for this database server, then the following actions occur:
  - In addition to restoring the database cluster to the directory specified by the `-p restore_path` option, the archived WAL files of the backup are copied from the BART backup catalog to the subdirectory `restore_path/archived_wals`.
  - If recovery settings are saved in the `postgresql.auto.conf` file, the command string set in the `restore_command` parameter retrieves the WAL files from this `archived_wals` subdirectory relative to the `restore_path` parent directory as: `restore_command = cp archived_wals/%f %p`

You must ensure that valid options are specified when using the `RESTORE` subcommand. BART will not generate an error message if invalid option values or invalid option combinations are provided. BART will accept the invalid options

and pass them to the `postgresql.auto.conf` file, which will then be processed by the database server when it is restarted.

Step 7: Copy any saved WAL files from Step 2 to the `restore_path/pg_xlog` subdirectory.

Step 8: Inspect the restored directories and data files of the restored database cluster in directory `restore_path`.

All files and directories must be owned by the user account that you intend to use to start the database server. Recursively change the user and group ownership of the `restore_path` directory, its files, and its subdirectories if necessary. There must only be directory access privileges for the user account that will start the database server. No other groups or users can have access to the directory.

Step 9: The `postgresql.auto.conf` file should be configured to recover only until the cluster reaches consistency. In either case, the settings may be modified as desired.

Step 10: Disable WAL archiving at this point. The BART `RESTORE` subcommand adds `archive_mode = off` to the end of the `postgresql.conf` file.

- If you want to restart the database server with WAL archiving enabled, ensure that this additional parameter is deleted.
- The original `archive_mode` parameter still resides in the `postgresql.conf` file in its initial location with its last setting.

Step 11: Start the database server to initiate recovery. After completion, check the database server log file to ensure the recovery was successful.

If the backup is restored to a different location than where the original database cluster resided, operations dependent upon the database cluster location may fail if supporting service scripts are not updated to reflect the location where the backup has been restored. For information about the use and modification of service scripts, see the EDB Advanced Server Installation Guide available at the [EDB website](#).

See [Restore](#) for more information about using the BART `Restore` subcommand.

An example of a restore operation is documented in the EDB Backup and Recovery Reference Guide available at the [EDB website](#).

### 5.3.1.2 Point-In-Time Recovery Operation

The following steps outline how to perform a point-in-time recovery operation for a database cluster:

1. Use your system-specific command to shut down the database server.
2. If you want to: a. restore the database cluster and tablespace files to new, empty directories, create the new directories with the appropriate directory ownership and permissions. b. reuse the existing database cluster directories, delete all the files and subdirectories in the existing directories. We strongly recommend that you make a copy of this data before deleting it. Be sure to save any recent WAL files in the `pg_wal` subdirectory (`pg_xlog` subdirectory if you are using server version 9.6) that have not been archived to `archive_path`.
3. Run the BART `SHOW-BACKUPS -s <server_name>` subcommand to list the backup IDs and backup names of the backups for the database server. You will need to provide the appropriate backup ID or backup name with the BART `RESTORE` subcommand, unless you intend to restore the latest backup in which case the `-i` option of the



`RESTORE` subcommand for specifying the backup ID or backup name may be omitted.

4. Run the BART `RESTORE` subcommand with the appropriate options.

- The backup is restored to the directory specified by the `-p restore_path` option.
- In addition, if the `RESTORE` subcommand `-c` option is specified or if the enabled setting of the `copy_wals_during_restore` BART configuration parameter is applicable to the database server, then the required archived WAL files from the `archive_path` are copied to the `restore_path/archived_wals` subdirectory.
- Ensure the `restore_path` directory and all subdirectories and files in the `restore_path` are owned by the proper Postgres user account (for example, `enterprisedb` or `postgres`). Also ensure that only the Postgres user account has access permission to the `restore_path` directory.

Use the `chown` command to make the appropriate adjustments to file permissions; for example, the following command changes the ownership of `restore_path` to `enterprisedb`:

```
chown -R enterprisedb:enterprisedb restore_path
```

The following command restricts access to `restore_path`:

```
chmod 700 restore_path
```

5. Copy any saved WAL files from Step 2 that were not archived to the BART backup catalog to the `restore_path/pg_wal` subdirectory (`pg_xlog` subdirectory if you are using server version 9.6).

6. Identify the timeline ID you wish to use to perform the restore operation.

The available timeline IDs can be identified by the first non-zero digit of the WAL file names reading from left to right.

7. Verify that the `postgresql.auto.conf` file created in the directory specified with the `RESTORE` subcommand's `-p <restore_path>` option was generated with the correct recovery parameter settings.

If the `RESTORE` subcommand `-c` option is specified or if the enabled setting of the `copy_wals_during_restore` BART configuration parameter is applicable to the database server, then the `restore_command` parameter retrieves the archived WAL files from the `<restore_path>/archived_wals` subdirectory that was created by the `RESTORE` subcommand, otherwise the `restore_command` retrieves the archived WAL files from the BART backup catalog.

8. The BART `RESTORE` subcommand disables WAL archiving in the restored database cluster. If you want to immediately enable WAL archiving, modify the `postgresql.conf` file by deleting the `archive_mode = off` parameter that BART appends to the end of the file.

9. Start the database server, which will then perform the point-in-time recovery operation if recovery settings are saved in the `postgresql.auto.conf` file.

For a detailed description of the `RESTORE` subcommand, see [Basic BART Subcommand Usage](#). An example of a Point-in-Time Recovery operation is documented in the *EDB Backup and Recovery Reference Guide* available at the [EDB website](#). See [Restore](#) for more information about using the `Restore` subcommand.

## 5.3.2 Managing Backups Using a Retention Policy



Over the course of time when using BART, the number of backups can grow significantly. This ultimately leads to a large consumption of disk space unless an administrator periodically performs the process of deleting the oldest backups that are no longer needed. This process of determining when a backup is old enough to be deleted and then actually deleting such backups can be done and automated with the following basic steps:

1. Determine and set a retention policy in the BART configuration file. A *retention policy* is a rule that determines when a backup is considered obsolete. The retention policy can be applied globally to all servers, but each server can override the global retention policy with its own.
2. Use the `MANAGE` subcommand to categorize and manage backups according to the retention policy.
3. Create a cron job to periodically run the `MANAGE` subcommand to evaluate the backups and then list and/or delete the obsolete backups.

Retention policy management applies differently to incremental backups than to full backups. See [Managing Incremental Backups](#) for information about how retention policy management is applied to each backup type.

The following sections describe how retention policy management generally applies to backups, and its specific usage and effect on full backups.

### 5.3.2.1 Overview - Managing Backups Using a Retention Policy

The BART retention policy results in the categorization of each backup in one of three statuses – *active*, *obsolete*, and *keep*.

- **Active.** The backup satisfies the retention policy applicable to its server. Such backups would be considered necessary to ensure the recovery safety for the server and thus should be retained.
- **Obsolete.** The backup does not satisfy the retention policy applicable to its server. The backup is no longer considered necessary for the recovery safety of the server and thus can be deleted.
- **Keep.** The backup is to be retained regardless of the retention policy applicable to its server. The backup is considered vital to the recovery safety for the server and thus should not be deleted for an indefinite period of time.

There are two types of retention policies - redundancy retention policy and recovery window retention policy.

- **Redundancy Retention Policy** - The [redundancy retention policy](#) relies on a specified, maximum number of most recent backups to retain for a given server. When the number of backups exceeds that maximum number, the oldest backups are considered obsolete (except for backups marked as keep).
- **Recovery Window Retention Policy** - The [recovery window retention policy](#) relies on a time frame (the recovery window) for when a backup should be considered active. The boundaries defining the recovery window are the current date/time (the ending boundary of the recovery window) and the date/time going back in the past for a specified length of time (the starting boundary of the recovery window).
  - If the date/time the backup was taken is within the recovery window (that is, the backup date/time is on or after the starting date/time of the recovery window), then the backup is considered active, otherwise it is considered obsolete (except for backups marked as keep).
  - Thus, for the recovery window retention policy, the recovery window time frame dynamically shifts, so the end of the recovery window is always the current date/time when the `MANAGE` subcommand is run. As you run the `MANAGE` subcommand at future points in time, the starting boundary of the recovery window moves forward in time. At some future point, the date/time of when a backup was taken will be earlier than the starting boundary of the recovery window. This is when an active backup's status will be considered obsolete.
  - You can see the starting boundary of the recovery window at any point in time by running the `SHOW-SERVERS` subcommand. The `RETENTION POLICY` field of the `SHOW-SERVERS` subcommand displays the starting

boundary of the recovery window.

### 5.3.2.2 Marking the Backup Status

When a backup is initially created with the `BACKUP` subcommand, it is always recorded with active status. Use the `MANAGE` subcommand to evaluate if the backup status should be changed to obsolete in accordance with the retention policy. You can review the current status of your backups with the `SHOW-BACKUPS` subcommand.

Active backups are evaluated and also marked (that is, internally recorded by BART) as obsolete only when the `MANAGE` subcommand is invoked either with no options or with only the `-s` option.

Once a backup has been marked as obsolete, you cannot change it back to active unless you perform the following steps:

- Use the `MANAGE` subcommand with the `-c` option along with the backup identifier or name with the `-i` option. To keep this particular backup indefinitely, use `-c keep`, otherwise use `-c nokeep`.
- If you use the `-c nokeep` option, the backup status is changed back to active. When the `MANAGE` subcommand is used the next time, the backup is re-evaluated to determine if its status needs to be changed back to obsolete based on the current retention policy in the BART configuration file.

After setting the `retention_policy` parameter and running the `MANAGE` subcommand if you change the `retention_policy` parameter, the current, marked status of the backups are probably inconsistent with the new `retention_policy` setting. To modify the backup status to be consistent with the new `retention_policy` setting, you need to run the `MANAGE` subcommand with:

- the `-c nokeep` option to change the obsolete status to active status if there are backups currently marked as obsolete that would no longer be considered obsolete under a new retention policy. You can also specify the `-i all` option to change all backups back to active status, including those currently marked as keep.
- no options or with only the `-s` option to reset the marked status based on the new `retention_policy` setting in the BART configuration file.

See `MANAGE` for usage information for the `MANAGE` subcommand.

### 5.3.2.3 Setting the Retention Policy

The retention policy is determined by the `retention_policy` parameter in the BART configuration file. It can be applied globally to all servers, but each server can override the global retention policy with its own. For information about creating a global retention policy and an individual database server retention policy, see the EDB Backup and Recovery Installation and Upgrade Guide available at the [EDB website](#).

There are two types of retention policies - redundancy retention policy and the recovery window retention policy as described in the following sections.

#### Redundancy Retention Policy

To use the redundancy retention policy, set `retention_policy = max_number BACKUPS` where `max_number` is a positive integer designating the maximum number of most recent backups.

Additional Restrictions:

- The keyword `BACKUPS` must always be specified in plural form (for example, `1 BACKUPS`).
- BART will accept a maximum integer value of 2,147,483,647 for `max_number`; however, you should use a realistic, practical value based on your system environment.

The redundancy retention policy is the default type of retention policy if all keywords `BACKUPS`, `DAYS`, `WEEKS`, and `MONTHS` following the `max_number` integer are omitted as shown by the following example:

```
retention_policy = 3
```

In the following example, the redundancy retention policy setting considers the three most recent backups as the active backups. Any older backups, except those marked as `keep`, are considered obsolete:

```
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
archive_command = 'cp %p %a/%f'
retention_policy = 3 BACKUPS
description = "Accounting"
```

The `SHOW-SERVERS` subcommand displays the `3 Backups` redundancy retention policy in the `RETENTION POLICY` field:

```
-bash-4.1$ bart SHOW-SERVERS -s acctg
SERVER NAME       : acctg
HOST NAME        : 127.0.0.1
USER NAME       : enterprisedb
PORT            : 5444
REMOTE HOST      :
RETENTION POLICY : 3 Backups
DISK UTILIZATION : 627.04 MB
NUMBER OF ARCHIVES : 25
ARCHIVE PATH     : /opt/backup/acctg/archived_wals
ARCHIVE COMMAND  : cp %p /opt/backup/acctg/archived_wals/%f
XLOG METHOD      : fetch
WAL COMPRESSION : disabled
TABLESPACE PATH(s) :
DESCRIPTION      : "Accounting"
```

## Recovery Window Retention Policy

To use the recovery window retention policy, set the `retention_policy` parameter to the desired length of time for the recovery window in one of the following ways:

- Set to `max_number DAYS` to define the start date/time recovery window boundary as the number of days specified by `max_number` going back in time from the current date/time.
- Set to `max_number WEEKS` to define the start date/time recovery window boundary as the number of weeks specified by `max_number` going back in time from the current date/time.
- Set to `max_number MONTHS` to define the start date/time recovery window boundary as the number of months

specified by `max_number` going back in time from the current date/time.

Additional Restrictions:

- The keywords `DAYS`, `WEEKS`, and `MONTHS` must always be specified in plural form (for example, `1 DAYS`, `1 WEEKS`, or `1 MONTHS`).
- BART will accept a maximum integer value of `2,147,483,647` for `max_number`, however, a realistic, practical value based on your system environment must always be used.

A backup is considered active if the date/time of the backup is equal to or greater than the start of the recovery window date/time.

You can view the actual, calculated recovery window by:

- Invoking the `MANAGE` subcommand in debug mode, along with the `-n` option.
- Using the `SHOW-SERVERS` subcommand.

### 5.3.2.4 Managing the Backups Based on the Retention Policy

The `MANAGE` subcommand is used to evaluate and categorize backups according to the retention policy set in the BART configuration file. When a backup is first created with the `BACKUP` subcommand, it is `active`. You can use the `MANAGE` subcommand to change the status of an active backup to `obsolete`. Obsolete backups can then be deleted.

This section covers following aspects of backup management:

- The rules for `deleting backups` depending upon the backup status and the subcommand used.
- The process to retain a backup indefinitely by `marking it as keep`. This section also provides information about resetting backups status (that are marked as `obsolete` and `keep`) back to active status.
- The general process for `evaluating, marking, and then deleting obsolete backups`.

#### Deletions Permitted Under a Retention Policy

This section describes how and under what conditions backups may be deleted under a retention policy.

You must use the `MANAGE` subcommand to delete obsolete backups. Use the `DELETE` subcommand only for special administrative purposes.

The deletion behavior of the `MANAGE` subcommand and the `DELETE` subcommand are based on different aspects of the retention policy.

- The `MANAGE` subcommand deletion relies solely upon how a backup status is currently marked (that is, internally recorded by BART). The current setting of the `retention_policy` parameter in the BART configuration file is ignored.
- The `DELETE` subcommand relies solely upon the current setting of the `retention_policy` parameter in the BART configuration file. The current active, obsolete, or keep status of a backup is ignored.

The specific deletion rules for the `MANAGE` and `DELETE` subcommands are as follows:

- `MANAGE` subcommand: The `MANAGE` subcommand with the `-d` option can only delete backups marked as obsolete.

This deletion occurs regardless of the current `retention_policy` setting in the BART configuration file. The deletion of backups relies on the last occasion when the backups have been marked.

- **DELETE** subcommand:

- Under a redundancy retention policy currently set with the `retention_policy` parameter in the BART configuration file, any backup regardless of its marked status, can be deleted with the **DELETE** subcommand when the backup identifier or name is specified with the `-i` option and if the current total number of backups for the specified database server is greater than the maximum number of redundancy backups currently specified with the `retention_policy` parameter.

If the total number of backups is less than or equal to the specified, maximum number of redundancy backups, then no additional backups can be deleted using **DELETE** with the `-i backup` option.

- Under a recovery window retention policy currently set with the `retention_policy` parameter in the BART configuration file, any backup regardless of its marked status, can be deleted with the **DELETE** subcommand when the backup identifier or name is specified with the `-i` option, and if the backup date/time is not within the recovery window currently specified with the `retention_policy` parameter. If the backup date/time is within the recovery window, then it cannot be deleted using **DELETE** with the `-i backup` option.
- Invoking the **DELETE** subcommand with the `-i all` option results in the deletion of all backups regardless of the retention policy and regardless of whether the status is marked as active, obsolete, or keep.

The following table summarizes the deletion rules of backups according to their marked status. An entry of **Yes** indicates the backup may be deleted under the specified circumstances. An entry of **No** indicates that the backup may not be deleted.

Operation	Redundancy Retention Policy			Recovery Window Retention Policy		
	Active	Obsolete	Keep	Active	Obsolete	Keep
<b>MANAGE -d</b>	No	Yes	No	No	Yes	No
<b>DELETE -i *backup*</b>	Yes (see <a href="#">Note 1</a> )	Yes (see <a href="#">Note 1</a> )	Yes (see <a href="#">Note 1</a> )	Yes (see <a href="#">Note 2</a> )	Yes (see <a href="#">Note 2</a> )	Yes (see <a href="#">Note 2</a> )
<b>DELETE -i all</b>	Yes	Yes	Yes	Yes	Yes	Yes

!!! Note Redundancy Retention Policy (Note 1) : Deletion occurs only if the total number of backups for the specified database server is greater than the specified, maximum number of redundancy backups currently set with the `redundancy_policy` parameter in the BART configuration file.

!!! Note Recovery Window Retention Policy (Note 2): Deletion occurs only if the backup is not within the recovery window currently set with the `redundancy_policy` parameter in the BART configuration file.

## Marking Backups for Indefinite Keep Status

There may be certain backups that you wish to keep for an indefinite period of time and do not wish to delete based upon the retention policy applied to the database server. Such backups can be marked as **keep** to exclude them from being marked as obsolete. Use the **MANAGE** subcommand with the `-c keep` option to retain such backups indefinitely.

## Evaluating, Marking, and Deleting Obsolete Backups

When the `MANAGE` subcommand is invoked, BART evaluates active backups:

- If you include the `-s` option when invoking the `MANAGE` subcommand, BART evaluates backups for the database server.
- If you include the `-s all` option when invoking the `MANAGE` subcommand, BART evaluates backups for all database servers.
- If the `-s` option is omitted, the command evaluates the current number of backups for the database server based on the redundancy retention policy or the current date/time for a recovery window retention policy.

!!! Note The status of backups currently marked as `obsolete` or `keep` is not changed. To re-evaluate such backups and then classify them, their status must first be reset to `active` with the `MANAGE -c nokeep` option. See [Marking the Backup Status](#) for more information.

See the *EDB Backup and Recovery Reference Guide* available at the [EDB website](#) to review examples of how to evaluate, mark, and delete backups using a redundancy retention policy and recovery window retention policy, as well as examples of `MANAGE` subcommand.

### 5.3.2.5 Managing Incremental Backups

The following section summarizes how retention policy management affects incremental backups.

- The retention policy rules are applied to full backups.
  - A redundancy retention policy uses the number of full backups to determine if a backup is obsolete. Incremental backups are excluded from the comparison count against the `retention_policy` setting for the maximum number of backups.
  - A recovery window retention policy uses the backup date/time of any full backups to determine if a backup is obsolete. The backup date/time of any successive incremental backups in the chain are ignored when comparing with the recovery window.
- The retention status of all incremental backups in a chain is set to the same status applied to the full backup of the chain.
- The actions applied by the `MANAGE` and `DELETE` subcommands on a full backup are applied to all incremental backups in the chain in the same manner.
- Thus, a backup chain (that is, the full backup and all its successive incremental backups) are treated by retention policy management as if they are all one, single backup.
  - The status setting applied to the full backup is also applied to all incremental backups in its chain.
  - If a full backup is marked as obsolete and then deleted according to the retention policy, all incremental backups in the chain are also marked obsolete and then deleted as well.

The following are some specific points regarding the `MANAGE` and `DELETE` subcommands on incremental backups.

- `MANAGE` subcommand:
  - When the `MANAGE` subcommand is invoked, the status applied to the full backup is also applied to all successive incremental backups in the chain.
- The `MANAGE` subcommand with the `-c { keep | nokeep }` option cannot specify the backup identifier or backup name of an incremental backup with `-i` backup option. The `-i` backup option can only specify the backup identifier or backup name of a full backup.

- You can also use the `-i` all option to take a backup of all backups. When the `MANAGE` subcommand with the `-c { keep | nokeep }` option is applied to a full backup, the same status change is made to all incremental backups in the chain.
- `DELETE` subcommand:
  - The `DELETE` subcommand with the `-s server -i` backup option specifies the backup identifier or backup name of an incremental backup in which case that incremental backup along with all its successive incremental backups are deleted, thus shortening that backup chain.

## Using a Redundancy Retention Policy with Incremental Backups

When a `redundancy retention policy` is used and the `MANAGE` subcommand is invoked, the status of the oldest `active` full backup is changed to `obsolete` if the number of full backups exceeds the maximum number specified by the `retention_policy` parameter in the BART configuration file.

!!! Note When a full backup is changed from `active` to `obsolete`, all successive incremental backups in the chain of the full backup are also changed from `active` to `obsolete`.

When determining the number of backups that exceeds the number specified by the `retention_policy` parameter, only full backups are counted for the comparison. Incremental backups are not included in the count for the comparison against the `retention_policy` parameter setting.

See the *EDB Backup and Recovery Reference Guide* available at the [EDB website](#) for examples demonstrating use of the `MANAGE` and `DELETE` subcommands when a redundancy retention policy is in effect.

## Using a Recovery Window Retention Policy with Incremental Backups

If the `MANAGE` command is invoked when BART is configured to use a `recovery window retention policy`, the status of `active` full backups are changed to `obsolete` if the date/time of the full backup is outside of the recovery window.

!!! Note If a full backup is changed from `active` to `obsolete`, all successive incremental backups in the chain of the full backup are also changed from `active` to `obsolete`.

The status of an incremental backup is changed to `obsolete` regardless of whether or not the date/time of when the incremental backup was taken still lies within the recovery window.

See the *EDB Backup and Recovery Reference Guide* available at the [EDB website](#) for examples demonstrating use of the `MANAGE` and `DELETE` subcommands when a recovery window retention policy is in effect.

## 5.3.3 Basic BART Subcommand Usage

This section briefly describes the BART subcommands and options. You can invoke the `bart` program (located in the `<BART_HOME>/bin` directory) with the desired options and subcommands to manage your BART installation.

To view examples of BART subcommands, see the *EDB Backup and Recovery Reference Guide* available at the [EDB website](#).



Syntax for invoking BART:

```
bart [ general_option ]... [ subcommand ] [subcommand_option ]...
```

- When invoking a subcommand, the subcommand name is not case-sensitive (that is, the subcommand can be specified in uppercase, lowercase, or mixed case).
- Each subcommand has a number of its own applicable options that are specified following the subcommand. All options are available in both single-character and multi-character forms.
- Keywords are case-sensitive; options are generally specified in lowercase unless specified otherwise in this section.
- When invoking BART, the current user must be the BART user account (operating system user account used to run the BART command line program). For example, enterprisedb or postgres can be selected as the BART user account when the managed database servers are Advanced Server or PostgreSQL respectively.
- The chosen operating system user account must own the BART backup catalog directory, be able to run the `bart` program and the `bart scanner` program, and have a passwordless SSH/SCP connection established between database servers managed by BART.

You can specify one or more of the following general options:

Options	Description
<code>-h</code> or <code>--help</code>	Displays general syntax and information on BART usage. All subcommands support a help option ( <code>-h</code> , <code>--help</code> ). If the help option is specified, information is displayed regarding that particular subcommand. The subcommand, itself, is not executed.
<code>-v</code> or <code>--version</code>	Displays the BART version information.
<code>-d</code> or <code>--debug</code>	Displays debugging output while executing BART subcommands.
<code>-c</code> <code>&lt;config_file_path&gt;</code> or <code>--config-path</code> <code>&lt;config_file_path&gt;</code>	Specifies <code>config_file_path</code> as the full directory path to a BART configuration file. Use this option if you do not want to use the default BART configuration file <code>&lt;BART_HOME&gt;/etc/bart.cfg</code> .

#### Troubleshooting: Setting Path Environment Variable

If execution of BART subcommands fails with the following error message, then you need to set the `LD_LIBRARY_PATH` to include the `libpq` library directory:

```
./bart: symbol lookup error: ./bart: undefined symbol: PQping
```

Workaround: Set the `LD_LIBRARY_PATH` environment variable for the BART user account to include the directory containing the `libpq` library. This directory is `POSTGRES_INSTALL_HOME/lib`.

It is suggested that the `PATH` and the `LD_LIBRARY_PATH` environment variable settings be placed in the BART user account's profile. See the *EDB Backup and Recovery Installation and Upgrade Guide* available at the [EDB website](#) for details.

In the following sections, the `help` option is omitted from the syntax diagrams for the purpose of providing readability for the subcommand options.

### 5.3.3.1 CHECK-CONFIG

The `CHECK-CONFIG` subcommand checks the parameter settings in the BART configuration file as well as the database



server configuration for which the `-s` option is specified.

Syntax:

```
bart CHECK-CONFIG [ -s server_name ]
```

The following table describes the option.

Options	Description
<code>-s &lt;server_name&gt;</code> or <code>--server &lt;server_name&gt;</code>	<code>server_name</code> is the name of the database server to be checked for proper configuration. If the option is omitted, the settings of the global section of the BART configuration file are checked.
<ul style="list-style-type: none"> <li>When the <code>-s</code> option is omitted, the global section [BART] parameters including <code>bart_host</code>, <code>backup_path</code>, and <code>pg_basebackup_path</code> are checked.</li> <li>When the <code>-s</code> option is specified, the server section parameters are checked. In addition, certain database server <code>postgresql.conf</code> parameters are also checked, which include the following: <ul style="list-style-type: none"> <li>The <code>cluster_owner</code> parameter must be set to the user account owning the database cluster directory.</li> <li>A passwordless SSH/SCP connection must be set between the BART user and the user account specified by the <code>cluster_owner</code> parameter.</li> <li>A database superuser must be specified by the BART <code>user</code> parameter.</li> <li>The <code>pg_hba.conf</code> file must contain a replication entry for the database superuser specified by the BART <code>user</code> parameter.</li> <li>The <code>archive_mode</code> parameter in the <code>postgresql.conf</code> file must be enabled.</li> <li>The <code>archive_command</code> parameter in the <code>postgresql.auto.conf</code> or the <code>postgresql.conf</code> file must be set.</li> <li>The <code>allow_incremental_backups</code> parameter in the BART configuration file must be enabled for database servers for which incremental backups are to be taken.</li> <li>Archiving of WAL files to the <code>archive_path</code> must be in process.</li> <li>The WAL scanner program must be running.</li> </ul> </li> </ul>	

The `CHECK-CONFIG` subcommand displays an error message if the required configuration is not properly set.

### 5.3.3.2 INIT

The `INIT` subcommand is used to create the BART backup catalog directory, rebuild the BART `backupinfo` file, and set the `archive_command` in the PostgreSQL server based on the `archive_command` setting in the `bart.cfg` file.

!!! Note If the `archive_mode` configuration parameter is set to `off`, then the `-o` option must be used to set the Postgres `archive_command` using the BART `archive_command` parameter in the BART configuration file even if the `archive_command` is not currently set in `postgresql.conf` nor in `postgresql.auto.conf` file.

Syntax:

```
bart INIT [ -s { <server_name> | all } ] [ -o ]
[ -r [ -i { <backup_id> | <backup_name> | all } ] ]
[--no-configure]
```

All subcommand options are generally specified in lowercase. The following table describes the command options:

Options	Description
<code>-s</code> <code>{&lt;server_name&gt;   all }</code> <code>--server</code> <code>{&lt;server_name&gt;   all }</code>	<code>server_name</code> is the name of the database server to which the <code>INIT</code> actions are to be applied. If <code>all</code> is specified or if the option is omitted, the actions are applied to all servers.
<code>-o</code> <code>--override</code>	Overrides the existing, active Postgres <code>archive_command</code> configuration parameter setting in the <code>postgresql.conf</code> file or the <code>postgresql.auto.conf</code> file using the BART <code>archive_command</code> parameter in the BART configuration file. The <code>INIT</code> generated archive command string is written to the <code>postgresql.auto.conf</code> file.
<code>-r</code> <code>--rebuild</code>	Rebuilds the backupinfo file (a text file named <code>backupinfo</code> ) located in each backup subdirectory. This option is only intended for recovering from a situation where the backupinfo file has become corrupt. If the backup was initially created with a user-defined backup name, and then the <code>INIT -r</code> option is invoked to rebuild that <code>backupinfo</code> file, the user-defined backup name is no longer available. Thus, future references to the backup must use the backup identifier.
<code>-i {</code> <code>&lt;backup_id&gt;  </code> <code>&lt;backup_name&gt;</code> <code>  all }</code> <code>--backupid {</code> <code>&lt;backup_id&gt;  </code> <code>&lt;backup_name&gt;</code> <code>  all }</code>	<code>&lt;backup_id&gt;</code> is an integer, backup identifier and <code>&lt;backup_name&gt;</code> is the user-defined alphanumeric name for the backup. If <code>all</code> is specified or if the option is omitted, the backupinfo files of all backups for the database servers specified by the <code>-s</code> option are recreated. The <code>-i</code> option can only be used with the <code>-r</code> option.
<code>--no-configure</code>	Prevents the <code>archive_command</code> from being set in the PostgreSQL server.

## Archive Command Setting

After the `archive_command` is set, you need to either restart the PostgreSQL server or reload the configuration file in the PostgreSQL server based on the following conditions.

- If the `archive_mode` is set to `off` and `archive_command` is not set in the PostgreSQL server, the `archive_command` is set based on the `archive_command` setting in the `bart.cfg` and also sets the `archive_mode` to `on`. In this case, you need to restart the PostgreSQL server using `pg_ctl restart`.
- If the `archive_mode` is set to `on` and `archive_command` is not set in the PostgreSQL server, the `archive_command` is set based on the `archive_command` setting in the `bart.cfg`. In this case, you need to reload the configuration in the PostgreSQL server using `pg_reload_conf()` or `pg_ctl reload`.
- If the `archive_mode` is set to `off` and `archive_command` is already set in the PostgreSQL server, the `archive_mode` is set to `on`. In this case, you need to restart the PostgreSQL server using `pg_ctl restart`.
- If the `archive_mode` is set to `on` and `archive_command` is already set in the PostgreSQL server, then the `archive_command` is not set unless `-o` option is specified.

### 5.3.3.3 BACKUP

The `BACKUP` subcommand is used to create a full backup or an incremental backup.

Syntax for full backup:

```
bart BACKUP -s { <server_name> | all } [ -F { p | t } ]
[ -z ] [ -c <compression_level> ]
[ --backup-name <backup_name> ]
[ --thread-count <number_of_threads> ]
[ { --with-pg_basebackup | --no-pg_basebackup } ]
```

!!! Note While taking a backup, if a file (for example, database server log file) exceeding 1 GB size is stored in the `$PGDATA` directory, the backup will fail. To avoid such backup failure, you need to store large files (exceeding 1 GB) outside the `$PGDATA` directory.

Syntax for incremental Backup:

```
bart BACKUP -s { <server_name> | all } [ -F p]
[ --parent { <backup_id> | <backup_name> } ]
[ --backup-name <backup_name> ]
[ --thread-count <number_of_threads> ]
[ --check ]
```

!!! Note To take an [incremental backup](#), you must take a full backup first followed by incremental backup.

Please Note:

- While a `BACKUP` subcommand is in progress, no other subcommands must be invoked. Any subcommands invoked while a backup is in progress will skip and ignore the backups.
- For full backup, the target default format is a tar file, whereas for incremental backup, only plain format must be specified.
- The backup is saved in the `<backup_path>/<server_name>/<backup_id>` directory, where `<backup_path>` is the value assigned to the `<backup_path>` parameter in the BART configuration file, `<server_name>` is the lowercase name of the database server as listed in the configuration file, and `<backup_id>` is a backup identifier assigned by BART to the particular backup.
- MD5 checksums of the full backup and any user-defined tablespaces are saved as well for tar backups.
- Before performing the backup, BART checks to ensure if there is enough disk space to completely store the backup in the BART backup catalog.
- In the `postgresql.conf` file, ensure the `wal_keep_segments` configuration parameter is set to a sufficiently large value. A low setting of the `wal_keep_segments` configuration parameter may result in the deletion of some WAL files before the BART `BACKUP` subcommand saves them to the `archive_path`. For information about the `wal_keep_segments` parameter, see the [PostgreSQL Core Documentation](#).
- In the BART configuration file, setting `xlog_method=stream` will instruct the server to stream the transaction log in parallel with creation of the backup for a specific database server; otherwise the transaction log files are collected upon completion of the backup. See the *EDB Backup and Recovery Installation and Upgrade Guide* available at the [EDB website](#) for details about database server setting.

!!! Note If the transaction log streaming method is used, the `-Fp` option for a plain text backup format must be

specified with the `BACKUP` subcommand.

- When you use BART to take a backup of PostgreSQL server, multiple backups can be taken simultaneously and if a backup is interrupted, the backup mode is terminated automatically without the need to run `pg_stop_backup()` command manually to terminate the backup.

## Options

Along with the `BACKUP` subcommand, specify the following option:

Options	Description
<code>-s { server_name   all }</code> <code>--server { server_name   all }</code>	<code>server_name</code> is the database server name to be backed up as specified in the BART configuration file. If <code>all</code> is specified, all servers are backed up. This option is mandatory. If <code>all</code> is specified, and a connection to a database server listed in the BART configuration file cannot be opened, the backup for that database server is skipped, but the backup operation continues for the other database servers.

Specify the following options as required. If you do not specify any of the following options, the backup is created using default settings.

Options	Description
<code>-F { p   t }</code> <code>--format { p   t }</code>	Specify this option to provide the backup file format. Use <code>p</code> for plain text or <code>t</code> for tar. If the option is omitted, the default is tar format. For taking incremental backups, the option <code>-Fp</code> must be specified.
<code>-z</code> <code>--gzip</code>	This is applicable only for full backup. Specify this option to use gzip compression on the tar file output using the default compression level. This option is applicable only for the tar format.
<code>-c</code> <code>&lt;compression_level&gt;</code> <code>--compress-level</code> <code>&lt;compression_level&gt;</code>	This is applicable only for full backup. Specify this option to use the gzip compression level on the tar file output. <code>compression_level</code> is a digit from 1 through 9, with 9 being the best compression. This option is applicable only for the tar format.
<code>--parent { backup_id   backup_name }</code>	Specify this option to take an incremental backup. <code>&lt;backup_id&gt;</code> is the backup identifier of a parent backup. <code>&lt;backup_name&gt;</code> is the user-defined alphanumeric name of a parent backup. The parent is a backup taken prior to the incremental backup. The parent backup can be either a full backup or an incremental backup. The option <code>-Fp</code> must be specified since an incremental backup can only be taken in plain text format. An incremental backup cannot be taken on a standby database server. See <a href="#">Block-Level Incremental Backup</a> for additional information on incremental backups.

Options	Description
<code>--backup-name</code> <code>&lt;backup_name&gt;</code>	<p>Specify this option to assign a user-defined, alphanumeric friendly name to the backup. The maximum permitted length of backup name is 49 characters.</p> <p>The backup name may include the following variables to be substituted by the timestamp values when the backup is taken: 1) <code>%year</code> – 4-digit year, 2) <code>%month</code> – 2-digit month, 3) <code>%day</code> – 2-digit day, 4) <code>%hour</code> – 2-digit hour, 5) <code>%minute</code> – 2-digit minute, and 6) <code>%second</code> – 2-digit second.</p> <p>To include the percent sign (<code>%</code>) as a character in the backup name, specify <code>%%</code> in the alphanumeric string.</p> <p>If the backup name contains space characters (i.e. more than one word) or when referenced with the option <code>-i</code> by other subcommands (such as <code>restore</code>), enclose the string in single quotes or double quotes. See <a href="#">backup name examples</a>.</p> <p>If the <code>--backup-name</code> option is not specified, and the <code>backup_name</code> parameter is not set for this database server in the BART configuration file, then the backup can only be referenced in other BART subcommands by the BART assigned backup identifier.</p>
<code>--thread-count</code> <code>&lt;number_of_threads&gt;</code>	<p>Use this option to use the number of worker threads to run in parallel to copy blocks for a backup.</p> <p>If the option <code>--thread-count</code> is omitted, then the <code>thread_count</code> parameter in the BART configuration file applicable to this database server is used.</p> <p>If the option <code>--thread-count</code> is not enabled for this database server, then the <code>thread_count</code> setting in the global section of the BART configuration file is used.</p> <p>If the option <code>--thread-count</code> is not set in the global section as well, the default number of threads is 1.</p> <p>If parallel backup is run with N number of worker threads, then it will initiate N+ 1 concurrent connections with the server.</p> <p>Thread count will not be effective if backup is taken on a standby server.</p> <p>For more information about the <code>--thread-count</code> parameter, see the EDB Backup and Recovery Installation and Upgrade Guide available at the <a href="#">EDB website</a></p>
<code>--with-pg_basebackup</code>	<p>This is applicable only for full backup. Specify this option to use <code>pg_basebackup</code> to take a full backup. The number of thread counts in effect is ignored as given by the <code>thread_count</code> parameter in the BART configuration file.</p> <p>When taking a full backup, if the thread count in effect is greater than 1, then the <code>pg_basebackup</code> utility is not used to take the full backup (parallel worker threads are used) unless the option <code>--with-pg_basebackup</code> is specified with the <code>BACKUP</code> subcommand.</p>
<code>--no-pg_basebackup</code>	<p>This is applicable only for full backup. Specify this option if you do not want <code>pg_basebackup</code> to be used to take a full backup.</p> <p>When taking a full backup, if the thread count in effect is only 1, then the <code>pg_basebackup</code> utility is used to take the full backup unless the option <code>--no-pg_basebackup</code> is specified with the <code>BACKUP</code> subcommand.</p>
<code>--check</code>	<p>This is applicable only for incremental backup. Specify this option to verify if the required MBM files are present in the <code>archived_wals</code> directory as specified in the <code>archive_path</code> parameter in the <code>bart.cfg</code> file before taking an incremental backup. The option <code>--parent</code> must be specified when the option <code>--check</code> is used. An actual incremental backup is not taken when the option <code>--check</code> is specified.</p>

## Backup Name Examples

The following examples demonstrate using the `--backup-name` clause:

```
./bart backup -s ppas12 -Ft --backup-name "YEAR = %year
MONTH = %month DAY = %day"
```

```
./bart backup -s ppas12 -Ft --backup-name "YEAR = %year
MONTH = %month DAY = %day %"
./bart show-backups -s ppas12 -i "test backup"
```

## Error messages

The following table lists the error messages that may be encountered when using the **BACKUP** subcommand:

error message	Cause
<pre>edb@localhost bin]\$ ./bart backup -s mktg -Ft</pre> <pre>WARNING: xlog_method is empty, defaulting to global policy</pre> <pre>ERROR: backup failed for server 'mktg'</pre> <pre>free disk space is not enough to backup the server 'mktg'</pre> <pre>space available 13.35 GB, approximately required 14.65 GB</pre> <pre>ERROR: backup failed for server 'mktg'</pre>	Insufficient free disk space.
<pre>command failed with exit code 1</pre> <pre>pg_basebackup: could not get transaction log end position from server: ERROR: requested WAL segment 0000000010000000D500000006B has already been removed</pre> <pre>ERROR: backup failed for server 'mktg'</pre>	The wal_keep_segments configuration parameter is not set to a sufficiently large value in the postgresql.conf file.
<pre>connection to the server failed: could not connect to server: Connection refused</pre> <pre>Is the server running on host "172.16.114.132" and accepting TCP/IP connections on port 5444?</pre>	A connection to a database server listed in the BART configuration file fails. As a result the backup for that database server is skipped, but the backup operation continues for other database servers

## 5.3.3.4 SHOW-SERVERS

The **SHOW-SERVERS** subcommand displays the information for the managed database servers listed in the BART configuration file.

Syntax:

```
bart SHOW-SERVERS [ -s { <server_name> | all } ]
```

The following table describes the command options.

Options	Description
<code>-s { &lt;server_name&gt;   all }</code> <code>--server { &lt;server_name&gt;   all }</code>	<code>&lt;server_name&gt;</code> is the name of the database server whose BART configuration information is to be displayed. If <code>all</code> is specified or if the option is omitted, information for all database servers is displayed.

### 5.3.3.5 SHOW-BACKUPS

The `SHOW-BACKUPS` subcommand displays the backup information for the managed database servers.

Syntax:

```
bart SHOW-BACKUPS [ -s { <server_name> | all } ]
                  [ -i { <backup_id> | <backup_name> | all } ]
                  [ -t ]
```

The following table describes the command options:

Options	Description
<code>-s { &lt;server_name&gt;   all }</code> <code>--server { &lt;server_name&gt;   all }</code>	<code>&lt;server_name&gt;</code> is the name of the database server whose backup information is to be displayed. If <code>all</code> is specified or if the option is omitted, the backup information for all database servers is displayed with the exception as described by the following note: If <code>SHOW-BACKUPS</code> is invoked while the BART <code>BACKUP</code> subcommand is in progress, backups affected by the backup process are shown in progress status in the displayed backup information.
<code>-i { &lt;backup_id&gt;   &lt;backup_name&gt;   all }</code> <code>--backupid { &lt;backup_id&gt;   &lt;backup_name&gt;   all }</code>	<code>&lt;backup_id&gt;</code> is a backup identifier and <code>&lt;backup_name&gt;</code> is the user-defined alphanumeric name for the backup. If <code>all</code> is specified or if the option is omitted, all backup information for the relevant database server is displayed.
<code>-t</code> <code>--toggle</code>	Displays more backup information in a list format. If the option is omitted, the default is a tabular format.

### 5.3.3.6 VERIFY-CHKSUM

The **VERIFY-CHKSUM** subcommand verifies the MD5 checksums of the full backups and any user-defined tablespaces for the specified database server or for all database servers. The checksum is verified by comparing the current checksum of the backup against the checksum when the backup was taken.

!!! Note The **VERIFY-CHKSUM** subcommand is only used for tar format backups. It is not applicable to plain format backups.

Syntax:

```
bart VERIFY-CHKSUM
[ -s { <server_name> | all } ]
[ -i { <backup_id> | <backup_name> | all } ]
```

The following table describes the command options:

Options	Description
<code>-s { &lt;server_name&gt;   all }</code>	<code>&lt;server_name&gt;</code> is the name of the database server whose tar backup checksums are to be verified. If <code>all</code> is specified or if the <code>-s</code> option is omitted, the checksums are verified for all database servers.
<code>--server { &lt;server_name&gt;   all }</code>	
<code>-i { &lt;backup_id&gt;   &lt;backup_name&gt;   all }</code>	<code>&lt;backup_id&gt;</code> is the backup identifier of a tar format full backup whose checksum is to be verified along with any user-defined tablespaces.
<code>--backupid { &lt;backup_id&gt;   &lt;backup_name&gt;   all }</code>	<code>&lt;backup_name&gt;</code> is the user-defined alphanumeric name for the full backup. If <code>all</code> is specified or if the <code>-i</code> option is omitted, the checksums of all tar backups for the relevant database server are verified.

### 5.3.3.7 MANAGE

The **MANAGE** subcommand can be invoked to:

- Evaluate backups, mark their status, and delete obsolete backups based on the **retention\_policy** parameter in the BART configuration file (See [Managing Backups Using a Retention Policy](#) for information about retention policy management).
- Compress the archived WAL files based on the **wal\_compression** parameter in the BART configuration file (See the *EDB Backup and Recovery Installation and Upgrade Guide* available at the [EDB website](#) for information about setting this parameter).

Syntax:

```
bart MANAGE [ -s { <server_name> | all } ]
[ -l ] [ -d ]
[ -c { keep | nokeep }
-i { <backup_id> | <backup_name> | all } ]
```



```
[ -n ]
```

The following summarizes the actions performed when the `MANAGE` subcommand is invoked:

- When the `MANAGE` subcommand is invoked with no options or with only the `-s <server_name>` or `-s all` option, the following actions are performed:
  - For the server specified by the `-s` option, or for all servers (if `-s all` is specified or the `-s` option is omitted), active backups are marked as `obsolete` in accordance with the retention policy.
  - All backups that were marked `obsolete` or `keep` prior to invoking the `MANAGE` subcommand remain marked with the same prior status.
  - If WAL compression is enabled for the database server, then any uncompressed, archived WAL files in the BART backup catalog of the database server are compressed with gzip.
- When the `MANAGE` subcommand is invoked with any other option besides the `-s` option, the following actions are performed:
  - For the server specified by the `-s` option, or for all servers, the action performed is determined by the other specified options (that is, `-l` to list obsolete backups, `-d` to delete obsolete backups, `-c` to keep or to return backups to `active` status, or `-n` to perform a dry run of any action).
  - No marking of `active` backups to `obsolete` status is performed regardless of the retention policy.
  - All backups that were marked `obsolete` or `keep` prior to invoking the `MANAGE` subcommand remain marked with the same prior status unless the `-c` option (without the `-n` option) is specified to change the backup status of the particular backup or all backups referenced with the `-i` option.
  - No compression is applied to any uncompressed, archived WAL file in the BART backup catalog regardless of whether or not WAL compression is enabled.

The following are additional considerations when using WAL compression:

- Compression of archived WAL files is not permitted for database servers on which incremental backups are to be taken.
- The gzip compression program must be installed on the BART host and be accessible in the `PATH` of the BART user account.
- When the `RESTORE` subcommand is invoked, if the `-c` option is specified or if the `copy_wals_during_restore` BART configuration parameter is enabled for the database server, then the following actions occur:
  - If compressed, archived WAL files are stored in the BART backup catalog and the location to which the WAL files are to be restored is on a remote host relative to the BART host:
    - the archived WAL files are transmitted across the network to the remote host in compressed format only if the gzip compression program is accessible in the `PATH` of the remote user account that is used to log into the remote host when performing the `RESTORE` operation.
    - This remote user is specified with either the `remote_host` parameter in the BART configuration file or the `RESTORE -r` option (see `RESTORE`).
    - Transmission of compressed WAL files results in less network traffic. After the compressed WAL files are transmitted across the network, the `RESTORE` subcommand uncompresses the files for the point-in-time recovery operation.
    - If the gzip program is not accessible on the remote host in the manner described in the previous bullet point, then the compressed, archived WAL files are first uncompressed while on the BART host, then transmitted across the network to the remote host in uncompressed format.
- When the `RESTORE` subcommand is invoked without the `-c` option and the `copy_wals_during_restore` BART configuration parameter is disabled for the database server, then any compressed, archived WAL files needed for the `RESTORE` operation are uncompressed in the BART backup catalog. The uncompressed WAL files can then be saved to the remote host by the `restore_command` in the `postgresql.auto.conf` file when the database

server archive recovery begins.

The following table describes the command options:

Options	Description
<code>s {</code> <code>&lt;server_name&gt;</code> <code>  all }</code> <code>--server {</code> <code>&lt;server_name&gt;</code> <code>  all }</code>	<code>&lt;server_name&gt;</code> is the name of the database server to which the actions are to be applied. If <code>all</code> is specified or if the <code>-s</code> option is omitted, the actions are applied to all database servers.
<code>-l</code> <code>--list-</code> <code>obsolete</code>	Lists the backups marked as obsolete.
<code>-d</code> <code>--delete-</code> <code>obsolete</code>	Delete the backups marked as <code>obsolete</code> . This action physically deletes the backup along with its archived WAL files and any MBM files for incremental backups.
<code>-c { keep  </code> <code>nokeep }</code> <code>--change-</code> <code>status { keep</code> <code>  nokeep }</code>	Specify <code>keep</code> to change the status of a backup to <code>keep</code> to retain it indefinitely. Specify <code>nokeep</code> to change the status of any backup back to active status. The backup can then be re-evaluated and possibly be marked to <code>obsolete</code> according to the retention policy by subsequent usage of the <code>MANAGE</code> subcommand. The <code>-i</code> option must be included when using the <code>-c</code> option.
<code>-i {</code> <code>&lt;backup_id&gt;  </code> <code>&lt;backup_name&gt;</code> <code>  all }</code> <code>--backupid {</code> <code>&lt;backup_id&gt;  </code> <code>&lt;backup_name&gt;</code> <code>  all }</code>	<code>&lt;backup_id&gt;</code> is a backup identifier and <code>&lt;backup_name&gt;</code> is the user-defined alphanumeric name for the backup. If <code>all</code> is specified, then actions are applied to all backups. The <code>-c</code> option must be included when using the <code>-i</code> option.
<code>-n</code> <code>--dry-run</code>	Performs the test run and displays the results prior to actually implementing the actions as if the operation was performed, however, no changes are actually made. If <code>-n</code> is specified with the <code>-d</code> option, it displays which backups would be deleted, but does not actually delete the backups. If <code>-n</code> is specified with the <code>-c</code> option, it displays the keep or nokeep action, but does not actually change the backup from its current status. If <code>-n</code> is specified alone with no other options, or with only the <code>-s</code> option, it displays which active backups would be marked as obsolete, but does not actually change the backup status. In addition, no compression is performed on uncompressed, archived WAL files even if WAL compression is enabled for the database server.

### 5.3.3.8 RESTORE

The `RESTORE` subcommand restores a backup and its archived WAL files for the designated database server to the specified directory location. If the appropriate `RESTORE` options are specified, all recovery settings will be saved in the

`postgresql.auto.conf` file.

Syntax:

```
bart RESTORE -s <server_name> -p <restore_path>
[ -i { <backup_id> | <backup_name> } ]
[ -r <remote_user@remote_host_address> ]
[ -w <number_of_workers> ]
[ -t <timeline_id> ]
[ { -x <target_xid> | -g <target_timestamp> } ]
[ -c ]
```

For information about using a continuous archive backup for recovery, see the [PostgreSQL Core Documentation](#). This reference material provides detailed information about the underlying point-in-time recovery process and the meaning and usage of the restore options that are generated into the `postgresql.auto.conf` file by BART.

Please note:

- For special requirements when restoring an incremental backup to a remote database server, see [Restoring an Incremental Backup on a Remote Host](#).
- Check to ensure that the host where the backup is to be restored contains enough disk space for the backup and its archived WAL files. The `RESTORE` subcommand may result in an error while copying files if there is not enough disk space available.
- See [Performing a Restore Operation](#) to view steps on how to perform a restore operation and see [Point-In-Time Recovery Operation](#) to view steps on how to perform a point-in-time recovery operation.
- If the backup is restored to a different database cluster directory than where the original database cluster resided, certain operations dependent upon the database cluster location may fail. This happens if their supporting service scripts are not updated to reflect the new directory location of restored backup. For information about the usage and modification of service scripts, see the *EDB Advanced Server Installation Guide* available at the [EDB website](#).

The following table describes the command options:

Options	Description
<code>-s &lt;server_name&gt;</code> <code>--server &lt;server_name&gt;</code>	<code>&lt;server_name&gt;</code> is the name of the database server to be restored.
<code>-p &lt;restore_path&gt;</code> <code>--restore-path &lt;restore_path&gt;</code>	<code>&lt;restore_path&gt;</code> is the directory path where the backup of the database server is to be restored. The directory must be empty and have the proper ownership and privileges assigned to it.
<code>-i {&lt;backup_id&gt;   &lt;backup_name&gt;}</code> <code>--backupid {&lt;backup_id&gt;   &lt;backup_name&gt;}</code>	<code>&lt;backup_id&gt;</code> is the backup identifier of the backup to be used for the restoration and <code>&lt;backup_name&gt;</code> is the user-defined alphanumeric name for the backup. If the option is omitted, the default is to use the latest backup.

Options	Description
<code>-r or --remote-host &lt;remote_user&gt;@&lt;remote_host_address&gt;</code>	<p><code>&lt;remote_user&gt;</code> is the user account on the remote database server host that accepts a passwordless SSH/SCP login connection and is the owner of the directory where the backup is to be restored and <code>&lt;remote_host_address&gt;</code> is the IP address of the remote host to which the backup is to be restored. This option must be specified if the <code>&lt;remote_host&gt;</code> parameter for this database server is not set in the BART configuration file.</p> <p>If the BART user account is not the same as the operating system account owning the <code>&lt;restore_path&gt;</code> directory given with the <code>-p</code> option, use the <code>&lt;remote_host&gt;</code> BART configuration parameter or the <code>RESTORE</code> subcommand <code>-r</code> option to specify the <code>&lt;restore_path&gt;</code> directory owner even when restoring to a directory on the same host as the BART host.</p> <p>See the <i>EDB Backup and Recovery Installation and Upgrade Guide</i> available at the <a href="#">EDB website</a> for information about the <code>&lt;remote_host&gt;</code> parameter.</p>
<code>-w &lt;number_of_workers&gt; --workers &lt;number_of_workers&gt;</code>	<p><code>&lt;number_of_workers&gt;</code> is the specification of the number of worker processes to run in parallel to stream the modified blocks of an incremental backup to the restore location.</p> <p>For example, if 4 worker processes are specified, 4 receiver processes on the restore host and 4 streamer processes on the BART host are used. The output of each streamer process is connected to the input of a receiver process. When the receiver gets to the point where it needs a modified block file, it obtains those modified blocks from its input. With this method, the modified block files are never written to the restore host disk. If the <code>-w</code> option is omitted, the default is <code>1</code>   worker process.</p>
<code>-t &lt;timeline_id&gt; --target-tli &lt;timeline_id&gt;</code>	<p><code>&lt;timeline_id&gt;</code> is the integer identifier of the timeline to be used for replaying the archived WAL files for point-in-time recovery.</p>
<code>-x &lt;target_xid&gt; --target-xid &lt;target_xid&gt;</code>	<p><code>&lt;target_xid&gt;</code> is the integer identifier of the transaction ID that determines the transaction up to and including, which point-in-time recovery encompasses. Include either the <code>-x &lt;target_xid&gt;</code> or the <code>--target-xid &lt;target_xid&gt;</code> option if point-in-time recovery is desired.</p>
<code>-g &lt;target_timestamp&gt; --target-timestamp &lt;target_timestamp&gt;</code>	<p><code>&lt;target_timestamp&gt;</code> is the timestamp that determines the point in time up to and including, which point-in-time recovery encompasses. Include either the <code>--target-timestamp &lt;target_timestamp&gt;</code> or the <code>-g &lt;target_timestamp&gt;</code> option if point-in-time recovery is desired.</p>
<code>-c --copy-wals</code>	<p>Specify this option to copy archived WAL files from the BART backup catalog to <code>&lt;restore_path&gt;/archived_wals</code> directory.</p> <p>If recovery settings are saved in the <code>postgresql.auto.conf</code> file for point-in-time recovery, the <code>restore_command</code> retrieves the WAL files from <code>&lt;restore_path&gt;/archived_wals</code> for the database server archive recovery.</p> <p>If the <code>-c</code> option is omitted and the <code>copy_wals_during_restore</code> parameter in the BART configuration file is not enabled in a manner applicable to this database server, the <code>restore_command</code> in the <code>postgresql.auto.conf</code> file is generated by default to retrieve the archived WAL files directly from the BART backup catalog.</p> <p>See the <i>EDB Backup and Recovery Installation and Upgrade Guide</i> available at the <a href="#">EDB website</a> for information about the <code>copy_wals_during_restore</code> parameter.</p>

### 5.3.3.9 DELETE

The **DELETE** subcommand removes the subdirectory and data files from the BART backup catalog for the specified backups along with its archived WAL files.

Syntax:

```
bart DELETE -s <server_name>
-i { all |
    [']{ <backup_id> | <backup_name> },... }[']
}
[ -n ]
```

!!! Note While invoking the **DELETE** subcommand, you must specify a specific database server.

For database servers under a retention policy, there are conditions where certain backups may not be deleted. See [Deletions Permitted Under a Retention Policy](#) for information about permitted backup deletions.

The following table describes the command options:

Options	Description
<b>-s &lt;server_name&gt;</b>	<b>&lt;server_name&gt;</b> is the name of the database server whose backups are to be deleted.
<b>--server &lt;server_name&gt;</b>	
<b>-i { all   [']{ &lt;backup_id&gt;   &lt;backup_name&gt; },... }['] }</b>	<b>&lt;backup_id&gt;</b> is the backup identifier of the backup to be deleted and <b>&lt;backup_name&gt;</b> is the user-defined alphanumeric name for the backup. Multiple backup identifiers and backup names may be specified in a comma-separated list. The list must be enclosed within single quotes if there is any white space appearing before or after each comma.
<b>--backupid { all   [']{ &lt;backup_id&gt;   &lt;backup_name&gt; },... }['] }</b>	If <b>all</b> is specified, all of the backups and their archived WAL files for the specified database server are deleted.
<b>-n</b>	Displays the results as if the deletions were done, however, no physical removal of the files are actually performed. In other words, a test run is performed so that you can see the potential results prior to actually initiating the action.
<b>--dry-run</b>	After the deletion, the BART backup catalog for the database server no longer contains the corresponding directory for the deleted backup ID. The <b>archived_wals</b> subdirectory no longer contains the WAL files of the backup.

## 5.3.4 Running the BART WAL Scanner

Use the BART WAL scanner to invoke the **bart-scanner** program located in the **BART\_HOME/bin** directory. When invoking the WAL scanner, the current user must be the BART user account.

Syntax:

```
bart-scanner
[ -d ]
[ -c <config_file_path> ]
{ -h |
```

```

-v |
--daemon |
-p <mbm_file_path> |
  <wal_file_path> |
RELOAD |
STOP

```

!!! Note For clarity, the syntax diagram shows only the single-character option form (for example, `-d`), but the multi-character option form (for example, `--debug`) is supported as well.

The WAL scanner processes each WAL file to find and record modified blocks in a corresponding modified block map (MBM) file. The default approach is that the WAL scanner gets notified whenever a new WAL file is added to the `archived_wals` directory specified in the `archive_path` parameter of the configuration file. It then scans the WAL file and produces the MBM file.

The default approach does not work in some cases; for example when the WAL files are shipped to the `archive_path` using the Network File System (NFS) and also in case of some specific platforms. This results in the WAL files being copied to the `archived_wals` directory, but the WAL scanner does not scan them (as WAL scanner is not aware of WAL file) and produce the MBM files. This results in the failure of an incremental backup. This can be avoided by using the timer-based WAL scanning approach, which is done by using the `scan_interval` parameter in the BART configuration file. The value for `scan_interval` is the number of seconds after which the WAL scanner will initiate force scanning of the new WAL files. See the *EDB Backup and Recovery Installation and Upgrade Guide* available at the [EDB website](#) for more information about `scan_interval` parameter.

When the `bart-scanner` program is invoked, it forks a separate process for each database server enabled with the `allow_incremental_backups` parameter.

The WAL scanner processes can run in either the foreground or background depending upon usage of the `--daemon` option. Use the `--daemon` option to run the WAL scanner process in the background so that all output messages can be viewed in the BART log file. If the `--daemon` option is omitted, the WAL scanner process runs in the foreground and all output messages can be viewed from the terminal running the program as well as in the BART log file.

See the *EDB Backup and Recovery Installation and Upgrade Guide* available at the [EDB website](#) for additional information about WAL scanning, `allow_incremental_backups`, and `logfile` parameters.

!!! Note The BART user account's `LD_LIBRARY_PATH` environment variable may need to be set to include the directory containing the `libpq` library if invocation of the WAL scanner program fails. See [Basic BART Subcommand Usage](#) for information about setting the `LD_LIBRARY_PATH` environment variable.

The following table describes the scanner options:

Options	Description
<code>-h --help</code>	Displays general syntax and information on WAL scanner usage.
<code>-v --version</code>	Displays the WAL scanner version information.
<code>-d --debug</code>	Displays debugging output while executing the WAL scanner with any of its options.
<code>-c</code>	
<code>&lt;config_file_path&gt;</code>	
<code>--config-path</code>	
<code>&lt;config_file_path&gt;</code>	Use this option to specify the <code>config_file_path</code> of a BART configuration file if you do not want to use the default BART configuration file path <code>BART_HOME/etc/bart.cfg</code> .
<code>--daemon</code>	Runs the WAL scanner as a background process.

Options	Description
<code>-p</code> <code>&lt;mbm_file_path&gt; --</code> <code>print</code> <code>&lt;mbm_file_path&gt;</code>	Use this option to specify the full directory path to an MBM file whose content is to be printed. The directory specified in the <code>archive_path</code> parameter in the <code>bart.cfg</code> file contains the MBM files.
<code>&lt;wal_file_path&gt;</code>	Specify the full directory path to a WAL file to be scanned. The directory specified in the <code>archive_path</code> parameter in the <code>bart.cfg</code> file contains the WAL files. Use this option if a WAL file in the archive path is missing its MBM file. This option is to be used for assisting the EnterpriseDB support team for debugging problems that may have been encountered.
<code>RELOAD</code>	Reloads the BART configuration file. The keyword <code>RELOAD</code> is not case-sensitive. The <code>RELOAD</code> option is useful if you make changes to the configuration file after the WAL scanner has been started. It will reload the configuration file and adjust the WAL scanners accordingly. For example, if a server section allowing incremental backups is removed from the BART configuration file, then the process attached to that server will stop. Similarly, if a server allowing incremental backups is added, a new WAL scanner process will be launched to scan the WAL files of that server.
<code>STOP</code>	Stops the WAL scanner. The keyword <code>STOP</code> is not case-sensitive.

## 5.4 Using Tablespaces

If the database cluster contains user-defined tablespaces (that is, tablespaces created with the `CREATE TABLESPACE` command):

- You can take full backups with the `BACKUP` subcommand in either tar (`-Ft`) or plain text (`-Fp`) backup file format.
- You must take incremental backups in the plain text (`-Fp`) backup file format.
- You can take full backups using the transaction log streaming method (`xlog_method = stream` in the BART configuration file) `--with-pg_basebackup` and the `BACKUP` subcommand in either tar (`-Ft`) or plain text (`-Fp`) backup file format.

!!! Note If the particular database cluster you plan to back up contains tablespaces created by the `CREATE TABLESPACE` command, then you must set the `tablespace_path` parameter in the BART configuration file before you perform a BART `RESTORE` operation.

The `tablespace_path` parameter specifies the directory paths to which you want the tablespaces to be restored. It takes the following format:

```
OID_1=tablespace_path_1;OID_2=tablespace_path_2 ...
```

Where `OID_1`, `OID_2`, ... are the Object Identifiers of the tablespaces. You can find the OIDs of the tablespaces and their corresponding soft links to the directories by listing the contents of the `PGRES_INSTALL_HOME/data/pg_tblspc` subdirectory as shown in the following example:

```
[root@localhost pg_tblspc]# pwd
/opt/PostgresPlus/9.6AS/data/pg_tblspc
[root@localhost pg_tblspc]# ls -l
total 0
lrwxrwxrwx 1 enterprisedb enterprisedb 17 Aug 22 16:38 16644 -> /mnt/tablespace_1
lrwxrwxrwx 1 enterprisedb enterprisedb 17 Aug 22 16:38 16645 -> /mnt/tablespace_2
```



The OIDs are 16644 and 16645 to directories /mnt/tablespace\_1 and /mnt/tablespace\_2, respectively.

If you later wish to restore the tablespaces to the same locations as indicated in the preceding example, the BART configuration file must contain the following entry:

```
[ACCTG]
host = 127.0.0.1
port = 5444
user = enterprisedb
cluster_owner = enterprisedb
tablespace_path = 16644=/mnt/tablespace_1;16645=/mnt/tablespace_2
description = "Accounting"
```

If you later wish to restore the tablespaces to different locations, specify the new directory locations in the tablespace\_path parameter.

In either case, the directories specified in the tablespace\_path parameter must exist and be empty at the time you perform the BART RESTORE operation.

If the database server is running on a remote host (in other words you are also using the remote\_host configuration parameter or will specify the --remote-host option with the RESTORE subcommand), the specified tablespace directories must exist on the specified remote host.

To view example of backing up and restoring a database cluster on a remote host containing tablespaces, see the *EDB Backup and Recovery Reference Guide* available at the [EDB website](#).

The directories must be owned by the user account with which you intend to start the database server (typically the Postgres user account) with no access by other users or groups as is required for the directory path to which the main full backup is to be restored.

To view a sample BART managed backup and recovery system consisting of both local and remote database servers, see the *EDB Backup and Recovery Reference Guide* available at the [EDB website](#).