

GNSS

Global Navigation Satellite System (GNSS) contains satellite constellation which provides positioning, navigation, and timing (PNT) services on a global or regional basis (*Other Global Navigation Satellite Systems (GNSS)*, 2020).

GNSS operates via satellites sending information on two radio-frequency carriers to the receivers on earth as shown on *figure 1*. The GNSS receivers have both an antenna and processing unit. The antenna receives the satellite signals, and the receiver processes the information and turns it into measurements.




Figure 1: Network of the Americas (NOTA) GNSS station portraying the primary components of the platform. (Figure adapted from (UNAVCO, 2020))




Figure 2: Demonstrates how GNSS data detects fault movement along the San Andreas Fault. (Figure adapted from (USGS, n.d.))

GeoGateway's GNSS tool can be used to measure plate motion and strain accumulation across faults. *Figure 2* demonstrates how fault motion is measured along a segment of the San Andreas Fault. The top of the figure (square shape) demonstrates the initial state of the fault at the date of observation, while the bottom of figure (parallelogram) shows how at a later date of observation, the fault has moved.



Maptools UAVSAR **GNSS** Seismicity

Nowcast Magnitude Disloc Studies

3D Imaging Feedback Help

GPS Data Analysis

Select GPS data

Velocities

Draw an area on map Clear GNSS Layers

Latitude

Longitude

Width 1 degree

Height 1 degree

Ref. Site 4-letter code [Stations](#)

Scale 320 mm/yr/deg

Output Prefix

☐ Minimize Marker Size

☐ Display absolute verticals

☐ Include error ellipses

[Run](#)

Data source:
[GNSS Time Series](#)

Velocities (option 1)

Coseismic (option 2)

Postseismic (option 3)

Displacement (option 4)

Model (option 5)

Figure 3: GeoGateway's GNSS tab, which includes five options of analysis; Velocities, Coseismic, Postseismic, Displacement, and Model.

GeoGateway allows users to analyze GNSS data for velocities, coseismic, postseismic, displacement, and model. Specific parameters must be filled in order to obtain a result.

Parameters




Figure 4: Overview of the geographic coordinate system (Figure adapted from (Britannica, n.d.))

Latitude (see figure 4) in decimal degrees
Longitude (see figure 4) in decimal degrees

*Positive latitude is above the equator (N), and negative latitude is below the equator (S). Positive longitude is east of the prime meridian, while negative longitude is west of the prime meridian.

Width and **Height** are measured in degrees, allowing the user to create a specified parameter.

Ref. Site is the GPS station site that the velocity vector data will be referenced to. A map with the sites can be located through the website listed below, or users may access the list of sites by clicking on “**Stations**” in the Ref. Site section of the GNSS tab. Once a location is chosen, type the 4-letter code in the box.


<https://sideshow.jpl.nasa.gov/post/series.html>

Scale allows the user to control the velocity vector length scaling. Recommend setting to **320** mm/yr/deg.


Output Prefix allows users to name the dataset output.




☐ Minimize Marker Size
☐ Display absolute verticals
☐ Include error ellipses

“**Minimize marker size**”  allows users to make GPS site markers smaller as shown in the image below.

“**Display absolute verticals**”



Error bars are graphical tools used to illustrate the pair-wise correlation that exists between computed values (Error Ellipses). By checking the box “**Include error ellipses**,” a black ellipse at the tip of the velocity vector, representing error is displayed, as shown in the image below.



Once data is inputted, click on “Run”. There is an option to download the velocity text table and the horizontal and vertical KML files as shown in the image on the right.

Output Layers

[table.txt](#)

☒ [h.kml](#)

☒ [v.kml](#)



By selecting the “Velocities” option, the velocities of different GPS stations are seen relative to the reference frame.

As shown in *figure 5* below “CCCC” is set as the reference point.




Figure 5: Velocities Analysis

Each vector shows the velocity of a single GPS station as the Earth moves.

The tail of the vector is pinned at the GPS station, and the length of the vector shows how fast the GPS station is moving. The other end of the line, away from the marker, is the direction the GPS station is moving.

Vertical displacements are shown by red (uplift) or blue (subsidence) circles. The larger the circle, the more displacement.

By clicking on a GPS station, three time series graphs appear.




Figure 6: Time Series for WNRA station




Figure 7: Time series tables, including latitude, longitude, and height

The time series shows how far the station has moved. The top graph shows latitude (cm) versus time (years). The black dots are the data points and the red line is the best fit line to the entire dataset. In this example, we see as time progresses the station moves closer to the North. For the longitude versus time graph (middle graph) we see that the GPS station is moving to the West. The bottom graph shows the vertical height versus time which is decreasing. The green lines that intersect vertically on the graph are locations where there are jumps in the data.

Coseismic and postseismic data can be selected by specifying a time period during or after an earthquake which a user wants to focus on.




Figure 8: Crustal deformation is spatially and temporally non-uniform as strain accumulates over prolonged time scales, where its later rapidly released as earthquakes, and readjusts post-seismically. Numerous types of data from different sections of the earthquake cycle (as shown in the figure above) are required for analysis.

Figure 8 illustrates the earthquake cycle, and typical rates of deformation in the coseismic and postseismic periods.

GPS Data Analysis

Select GPS data

Coseismic

Draw an area on map
 Clear GNSS Layers

Latitude

Longitude

Width

Height

Epoch

Ref. Site

[Stations](#)

Scale

Coseismic Win.

Output Prefix

☐ Minimize Marker Size
☐ Display absolute verticals
☐ Include error ellipses

Run

Data source:
[GNSS Time Series](#)

Figure 9: Coseismic offset refers to the time during an earthquake until a rupture ends.

GPS Data Analysis

Select GPS data

Postseismic

Draw an area on map
 Clear GNSS Layers

Latitude

Longitude

Width

Height

Epoch

Ref. Site

[Stations](#)

Scale

Coseismic Win.

Postseismic Win.

Output Prefix

☐ Minimize Marker Size
☐ Display absolute verticals
☐ Include error ellipses

Run

Data source:
[GNSS Time Series](#)

Figure 10: Postseismic deformation refers to the time after a large earthquake when deformation occurs.

When considering coseismic and postseismic data, the user must consider “Epoch” and “Coseismic Window” and “Postseismic Window.” The Epoch is the time of the event and the window is any time period of choice.

Looking at displacement data, we must choose a time period for analysis.

GPS Data Analysis

Select GPS data

Displacement

Draw an area on map

Clear GNSS Layers

Latitude

Longitude

Width

1 degree

Height

1 degree

Epoch 1

YYYY-MM-DD

Epoch 2

YYYY-MM-DD

Ref. Site

4-letter code

Stations

Scale

320 mm/yr/deg

Av. Win. 1

10 days

Av. Win. 2

10 days

Output Prefix

☐ Use NGL data

☐ Minimize Marker Size

☐ Display absolute verticals

☐ Include error ellipses

Run

Data source:
GNSS Time Series


Figure 11: Displacement Analysis


GPS Data Analysis

Select GPS data

Model

▼

 Draw an area on map

 Clear GNSS Layers

Latitude

Longitude

Width

1 degree

Height

1 degree

Epoch 1

YYYY-MM-DD

Epoch 2

YYYY-MM-DD

Ref. Site

4-letter code

Stations

Scale

320 mm/yr/deg

Output Prefix

☐ Minimize Marker Size

☐ Display absolute verticals

☐ Include error ellipses

Run

Data source:
GNSS Time Series

Figure 12: Model Analysis