

---

# HDF5 Reference Manual

---

---

Release 1.8.3  
May 2009

The HDF Group  
<http://www.hdfgroup.org/>

(Printed: June 2008)

---

## Copyright Notice and License Terms for HDF5 (Hierarchical Data Format 5) Software Library and Utilities

---

HDF5 (Hierarchical Data Format 5) Software Library and Utilities  
Copyright 2006-2009 by The HDF Group.

NCSA HDF5 (Hierarchical Data Format 5) Software Library and Utilities  
Copyright 1998-2006 by the Board of Trustees of the University of Illinois.

### **All rights reserved.**

Redistribution and use in source and binary forms, with or without modification, are permitted for any purpose (including commercial purposes) provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions, and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions, and the following disclaimer in the documentation and/or materials provided with the distribution.
3. In addition, redistributions of modified forms of the source or binary code must carry prominent notices stating that the original code was changed and the date of the change.
4. All publications or advertising materials mentioning features or use of this software are asked, but not required, to acknowledge that it was developed by The HDF Group and by the National Center for Supercomputing Applications at the University of Illinois at Urbana-Champaign and credit the contributors.
5. Neither the name of The HDF Group, the name of the University, nor the name of any Contributor may be used to endorse or promote products derived from this software without specific prior written permission from The HDF Group, the University, or the Contributor, respectively.

**DISCLAIMER:** THIS SOFTWARE IS PROVIDED BY THE HDF GROUP AND THE CONTRIBUTORS "AS IS" WITH NO WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED. In no event shall The HDF Group or the Contributors be liable for any damages suffered by the users arising out of the use of this software, even if advised of the possibility of such damage.

---

---

Contributors: National Center for Supercomputing Applications (NCSA) at the University of Illinois, Fortner Software, Unidata Program Center (netCDF), The Independent JPEG Group (JPEG), Jean-loup Gailly and Mark Adler (gzip), and Digital Equipment Corporation (DEC).

---

Portions of HDF5 were developed with support from the University of California, Lawrence Livermore National Laboratory (UC LLNL). The following statement applies to those portions of the product and must be retained in any redistribution of source code, binaries, documentation, and/or accompanying materials:

This work was partially produced at the University of California, Lawrence Livermore National Laboratory (UC LLNL) under contract no. W-7405-ENG-48 (Contract 48) between the U.S. Department of Energy (DOE) and The Regents of the University of California (University) for the operation of UC LLNL.

**DISCLAIMER:** This work was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor the University of California nor any of their employees, makes any warranty, express or implied, or assumes any liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately- owned rights. Reference herein to any specific commercial products, process, or service by trade name, trademark, manufacturer, or otherwise, does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or the University of California. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or the University of California, and shall not be used for advertising or product endorsement purposes.

---

# Table of Contents

Overview	1
Fortran90 and C++ APIs	2
H5: General Library Functions	3
H5A: Attribute Interface	13
H5D: Datasets Interface	61
H5E: Error Interface	97
H5F: File Interface	135
H5G: Group Interface	173
H5I: Identifier Interface	209
H5L: Link Interface	229
H5O: Object Interface	273
H5P: Property List Interface	297
H5R: Reference Interface	529
H5S: Dataspace Interface	545
H5T: Datatype Interface	577
H5Z: Compression Interface	661
HDF5 Tools	671
h5dump	673
h5ls	679
h5diff and ph5diff	680
h5repack	682
h5repart	685
h5jam and j5unjam	686
h5copy	688
h5mkgrp	690
h5import	691
gif2h5	699
h52gif	700
Java-based tools (HDFview, etc.)	*
H4toH5 Conversion Library	*
h5toh4	701
h4toh5	703

\* Links to descriptions of these tools appear on the HDF5 Tools page:  
<http://hdfgroup.org/HDF5/doc/RM/Tools.html>

HDF5 Tools ( <i>continued</i> )	
h5stat	704
h5perf	705
h5perf_serial	710
h5redeploy	712
h5cc and h5pcc	713
h5fc and h5pfc	714
h5c++	715
HDF5 Predefined Datatypes	717
HDF5 Fortran90 Flags, Datatypes, and User's Notes	721
API Compatibility Macros in HDF5	725
HDF5 Glossary	733

# HDF5: API Specification Reference Manual

The HDF5 library provides several interfaces, each of which provides the tools required to meet specific aspects of the HDF5 data-handling requirements.

Notes regarding Fortran90 and C++ APIs appear on the next page.

## Main HDF5 Library, or Low-level APIs

The main HDF5 Library includes all of the low-level APIs, providing user applications with fine-grain control of HDF5 functionality.

Library Functions	The general-purpose <b>H5</b> functions.
Attribute Interface	The <b>H5A</b> API for attributes.
Dataset Interface	The <b>H5D</b> API for manipulating scientific datasets.
Error Interface	The <b>H5E</b> API for error handling.
File Interface	The <b>H5F</b> API for accessing HDF5 files.
Group Interface	The <b>H5G</b> API for creating physical groups of objects on disk.
Identifier Interface	The <b>H5I</b> API for working with object identifiers.
Link Interface	The <b>H5L</b> API for working with links.
Object Interface	The <b>H5O</b> API for manipulating objects and reference counts.
Property List Interface	The <b>H5P</b> API for manipulating object property lists.
Reference Interface	The <b>H5R</b> API for references.
Dataspace Interface	The <b>H5S</b> API for defining dataset dataspace.
Datatype Interface	The <b>H5T</b> API for defining dataset element information.
Filters and Compression Interface	The <b>H5Z</b> API for inline data filters and data compression.
Tools	Interactive tools for the examination of existing HDF5 files.
Predefined Datatypes	Predefined datatypes in HDF5.

---

## The Fortran90 and C++ APIs to HDF5

The HDF5 Library distribution includes FORTRAN90 and C++ APIs, which are described in the following documents.

### Fortran90 API

Fortran90 APIs in the *HDF5 Reference Manual*: The *HDF5 Reference Manual* includes descriptions of the HDF5 Fortran90 APIs. Fortran subroutines exist in the H5, H5A, H5D, H5E, H5F, H5G, H5I, H5P, H5R, H5S, H5T, and H5Z interfaces and are described on those pages. In general, each Fortran subroutine performs exactly the same task as the corresponding C function, with which it is described.

*HDF5 Fortran90 Flags, Datatypes and User's Notes* lists the flags employed in the Fortran90 interface, contains a pointer to the HDF5 Fortran90 datatypes, and includes the document *HDF5 Fortran90 User's Notes*.

*HDF5 Fortran90 User's Notes* provides important information for users regarding the Fortran90 source code and the Fortran90 API.

### C++ API

*HDF5 C++ Reference Manual* provides a complete reference for the HDF5 C++ interface.

## H5: General Library Functions

These functions serve general-purpose needs of the HDF5 library and its users.

### The C Interfaces:

- H5open
- H5close
- H5get\_libversion
- H5check\_version
- H5set\_free\_list\_limits
- H5garbage\_collect
- H5dont\_atexit

### *Alphabetical Listing*

- H5check\_version
- H5close
- H5dont\_atexit
- H5garbage\_collect
- H5get\_libversion
- H5open
- H5set\_free\_list\_limits

### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- h5open\_f
- h5close\_f
- h5get\_libversion\_f
- h5check\_version\_f
- h5set\_free\_list\_limits\_f
- h5garbage\_collect\_f
- h5dont\_atexit\_f





**Name:** H5check\_version

**Signature:**

```
herr_t H5check_version(unsigned majnum, unsigned minnum, unsigned relnum)
```

**Purpose:**

Verifies that library versions are consistent.

**Description:**

H5check\_version verifies that the arguments provided with the function call match the version numbers compiled into the library.

H5check\_version serves two slightly differing purposes.

First, the function is intended to be called by the user to verify that the version of the header files compiled into an application matches the version of the HDF5 library being used. One may look at the H5check definition in the file H5public.h as an example.

Due to the risks of data corruption or segmentation faults, H5check\_version causes the application to abort if the version numbers do not match. The abort is achieved by means of a call to the standard C function `abort()`.

Note that H5check\_version verifies only the major and minor version numbers and the release number; it does not verify the sub-release value as that should be an empty string for any official release. This means that any two incompatible library versions must have different {major,minor,release} numbers. (Notice the reverse is not necessarily true.)

Secondarily, H5check\_version verifies that the library version identifiers H5\_VERS\_MAJOR, H5\_VERS\_MINOR, H5\_VERS\_RELEASE, H5\_VERS\_SUBRELEASE, and H5\_VERS\_INFO are consistent. This is designed to catch source code inconsistencies, but does not generate the fatal error as in the first stage because this inconsistency does not cause errors in the data files. If this check reveals inconsistencies, the library issues a warning but the function does not fail.

**Parameters:**

<i>unsigned</i> majnum	IN: The major version of the library.
<i>unsigned</i> minnum	IN: The minor version of the library.
<i>unsigned</i> relnum	IN: The release number of the library.

**Returns:**

Returns a non-negative value if successful. Upon failure, this function causes the application to abort.

**Fortran90 Interface:** h5check\_version\_f

```
SUBROUTINE h5check_version_f(majnum, minnum, relnum, hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(IN)  :: majnum      ! The major version of the library
  INTEGER, INTENT(IN)  :: minnum      ! The minor version of the library
  INTEGER, INTENT(IN)  :: relnum      ! The release number
  INTEGER, INTENT(OUT) :: hdferr      ! Error code

END SUBROUTINE h5check_version_f
```

**History:**

Release	Fortran90
1.4.5	Function introduced in this release.

**Name:** H5close

**Signature:**

*herr\_t* H5close(*void*)

**Purpose:**

Flushes all data to disk, closes file identifiers, and cleans up memory.

**Description:**

H5close flushes all data to disk, closes all file identifiers, and cleans up all memory used by the library.

This function is generally called when the application calls `exit()`, but may be called earlier in event of an emergency shutdown or out of desire to free all resources used by the HDF5 library.

`h5close_f` and `h5open_f` are required calls in Fortran90 applications.

**Parameters:**

None.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** `h5close_f`

```
SUBROUTINE h5close_f(hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(OUT) :: hdferr      ! Error code

END SUBROUTINE h5close_f
```

**Name:** H5dont\_atexit

**Signature:**

*herr\_t* H5dont\_atexit(*void*)

**Purpose:**

Instructs library not to install `atexit` cleanup routine.

**Description:**

H5dont\_atexit indicates to the library that an `atexit( )` cleanup routine should not be installed. The major purpose for this is in situations where the library is dynamically linked into an application and is un-linked from the application before `exit( )` gets called. In those situations, a routine installed with `atexit( )` would jump to a routine which was no longer in memory, causing errors.

In order to be effective, this routine *must* be called before any other HDF function calls, and must be called each time the library is loaded/linked into the application (the first time and after it's been un-loaded).

**Parameters:**

None.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5dont\_atexit\_f

```
SUBROUTINE h5dont_atexit_f(hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(OUT) :: hdferr      ! Error code

END SUBROUTINE h5dont_atexit_f
```

**History:**

Release	Fortran90
1.4.5	Function introduced in this release.

**Name:** H5garbage\_collect

**Signature:**

*herr\_t* H5garbage\_collect(*void*)

**Purpose:**

Garbage collects on all free-lists of all types.

**Description:**

H5garbage\_collect walks through all the garbage collection routines of the library, freeing any unused memory.

It is not required that H5garbage\_collect be called at any particular time; it is only necessary in certain situations where the application has performed actions that cause the library to allocate many objects. The application should call H5garbage\_collect if it eventually releases those objects and wants to reduce the memory used by the library from the peak usage required.

The library automatically garbage collects all the free lists when the application ends.

**Parameters:**

None.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5garbage\_collect\_f

```
SUBROUTINE h5garbage_collect_f(hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(OUT) :: hdferr      ! Error code

END SUBROUTINE h5garbage_collect_f
```

**History:**

Release	Fortran90
---------	-----------

1.4.5	Function introduced in this release.
-------	--------------------------------------

**Name:** H5get\_libversion

**Signature:**

*herr\_t* H5get\_libversion(*unsigned* \*majnum, *unsigned* \*minnum, *unsigned* \*relnum)

**Purpose:**

Returns the HDF library release number.

**Description:**

H5get\_libversion retrieves the major, minor, and release numbers of the version of the HDF library which is linked to the application.

**Parameters:**

<i>unsigned</i> *majnum	OUT: The major version of the library.
<i>unsigned</i> *minnum	OUT: The minor version of the library.
<i>unsigned</i> *relnum	OUT: The release number of the library.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5get\_libversion\_f

```
SUBROUTINE h5get_libversion_f(hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(OUT) :: majnum      ! The major version of the library
  INTEGER, INTENT(OUT) :: minnum      ! The minor version of the library
  INTEGER, INTENT(OUT) :: relnum      ! The release number
  INTEGER, INTENT(OUT) :: hdferr      ! Error code

END SUBROUTINE h5get_libversion_f
```

**History:**

Release	Fortran90
1.4.5	Function introduced in this release.

**Name:** H5open

**Signature:**

*herr\_t* H5open(*void*)

**Purpose:**

Initializes the HDF5 library.

**Description:**

H5open initialize the library.

When the HDF5 Library is employed in a C application, this function is normally called automatically, but if you find that an HDF5 library function is failing inexplicably, try calling this function first. If you wish to eliminate this possibility, it is safe to routinely call H5open before an application starts working with the library as there are no damaging side-effects in calling it more than once.

When the HDF5 Library is employed in a Fortran90 application, h5open\_f initializes global variables (e.g. predefined types) and performs other tasks required to initialize the library. h5open\_f and h5close\_f are therefore required calls in Fortran90 applications.

**Parameters:**

None.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5open\_f

```
SUBROUTINE h5open_f(hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(OUT) :: hdferr      ! Error code

END SUBROUTINE h5open_f
```

**Name:** H5set\_free\_list\_limits

**Signature:**

```
herr_t H5set_free_list_limits(int reg_global_lim, int reg_list_lim, int
arr_global_lim, int arr_list_lim, int blk_global_lim, int blk_list_lim)
```

**Purpose:**

Sets free-list size limits.

**Description:**

H5set\_free\_list\_limits sets size limits on all types of free lists. The HDF5 library uses free lists internally to manage memory. The types of free lists used are as follows:

- ◊ Regular free lists manage memory for single internal data structures.
- ◊ Array free lists manage memory for arrays of internal data structures.
- ◊ Block free lists manage memory for arbitrarily-sized blocks of bytes.
- ◊ Factory free lists manage memory for fixed-size blocks of bytes.

The parameters specify global and per-list limits; for example, `reg_global_limit` and `reg_list_limit` limit the accumulated size of all regular free lists and the size of each individual regular free list, respectively. Therefore, if an application sets a 1Mb limit on each of the global lists, up to 4Mb of total storage might be allocated, 1Mb for each of the regular, array, block, and factory type lists.

The settings specified for block free lists are duplicated for factory free lists. Therefore, increasing the global limit on block free lists by  $x$  bytes will increase the potential free list memory usage by  $2x$  bytes.

Using a value of  $-1$  for a limit means that no limit is set for the specified type of free list.

**Parameters:**

<i>int</i> reg_global_lim	IN: The cumulative limit on all regular free list memory used
<i>int</i> reg_list_lim	IN: The limit on memory used for each regular free list
<i>int</i> arr_global_lim	IN: The cumulative limit on all array free list memory used
<i>int</i> arr_list_lim	IN: The limit on memory used for each array free list
<i>int</i> blk_global_lim	IN: The cumulative limit on each of block free list memory and factory free list memory used
<i>int</i> blk_list_lim	IN: The limit on memory used for each block or factory free list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.0	Function introduced in this release.
1.8.3	Function changed in this release to set factory free list memory limits.





## H5A: Attribute Interface

### Attribute API Functions

These functions create and manipulate attributes and information about attributes.  
In the following lists, *italic type* indicates a configurable macro.

#### The C Interfaces:

- |                     |                      |                       |
|---------------------|----------------------|-----------------------|
| • <i>H5Acreate</i>  | • H5Arename          | • H5Aget_info         |
| • H5Acreate1 *      | • H5Arename_by_name  | • H5Aget_info_by_name |
| • H5Acreate2        | • H5Awrite           | • H5Aget_info_by_idx  |
| • H5Acreate_by_name | • H5Aread            | • H5Aget_num_attrs *  |
| • H5Aopen           | • H5Aclose           | • H5Aget_name         |
| • H5Aopen_by_name   | • <i>H5Aiterate</i>  | • H5Aget_create_plist |
| • H5Aopen_name *    | • H5Aiterate1 *      | • H5Aget_space        |
| • H5Aopen_by_idx    | • H5Aiterate2        | • H5Aget_type         |
| • H5Aopen_idx *     | • H5Aiterate_by_name | • H5Aget_storage_size |
| • H5Aexists         | • H5Adelete          | • H5Aget_name_by_idx  |
| • H5Aexists_by_name | • H5Adelete_by_name  |                       |
|                     | • H5Adelete_by_idx   |                       |

*\* Use of these functions is deprecated in Release 1.8.0.*

#### Alphabetical Listing

- |                       |                       |                      |
|-----------------------|-----------------------|----------------------|
| • H5Aclose            | • H5Aget_info         | • H5Aiterate2        |
| • <i>H5Acreate</i>    | • H5Aget_info_by_idx  | • H5Aiterate_by_name |
| • H5Acreate1 *        | • H5Aget_info_by_name | • H5Aopen            |
| • H5Acreate2          | • H5Aget_name         | • H5Aopen_by_idx     |
| • H5Acreate_by_name   | • H5Aget_name_by_idx  | • H5Aopen_by_name    |
| • H5Adelete           | • H5Aget_num_attrs *  | • H5Aopen_idx *      |
| • H5Adelete_by_name   | • H5Aget_space        | • H5Aopen_name *     |
| • H5Adelete_by_idx    | • H5Aget_storage_size | • H5Aread            |
| • H5Aexists           | • H5Aget_type         | • H5Arename          |
| • H5Aexists_by_name   | • <i>H5Aiterate</i>   | • H5Arename_by_name  |
| • H5Aget_create_plist | • H5Aiterate1 *       | • H5Awrite           |

**The FORTRAN90 Interfaces:**

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- |                         |                         |                       |
|-------------------------|-------------------------|-----------------------|
| • h5aclose_f            | • h5aget_info_f         | • h5aopen_f           |
| • h5acreate_f           | • h5aget_info_by_idx_f  | • h5aopen_by_idx_f    |
| • h5acreate_by_name_f   | • h5aget_info_by_name_f | • h5aopen_by_name_f   |
| • h5adelete_f           | • h5aget_name_f         | • h5aopen_idx_f *     |
| • h5adelete_by_name_f   | • h5aget_name_by_idx_f  | • h5aopen_name_f *    |
| • h5adelete_by_idx_f    | • h5aget_num_attrs_f *  | • h5aread_f           |
| • H5Aexists_f           | • h5aget_space_f        | • h5arename_f         |
| • H5Aexists_by_name_f   | • h5aget_storage_size_f | • h5arename_by_name_f |
| • h5aget_create_plist_f | • h5aget_type_f         | • h5awrite_f          |

*\* Use of these functions is deprecated in Release 1.8.0.*

The Attribute interface, H5A, is primarily designed to easily allow small datasets to be attached to primary datasets as metadata information. Additional goals for the H5A interface include keeping storage requirement for each attribute to a minimum and easily sharing attributes among datasets.

Because attributes are intended to be small objects, large datasets intended as additional information for a primary dataset should be stored as supplemental datasets in a group with the primary dataset. Attributes can then be attached to the group containing everything to indicate a particular type of dataset with supplemental datasets is located in the group. How small is "small" is not defined by the library and is up to the user's interpretation.

See *Attributes* in the *HDF5 User's Guide* for further information.

**Name:** H5Aclose

**Signature:**

*herr\_t* H5Aclose(*hid\_t* attr\_id)

**Purpose:**

Closes the specified attribute.

**Description:**

H5Aclose terminates access to the attribute specified by attr\_id by releasing the identifier.

Further use of a released attribute identifier is illegal; a function using such an identifier will fail.

**Parameters:**

*hid\_t* attr\_id IN: Attribute to release access to.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aclose\_f

```
SUBROUTINE h5aclose_f(attr_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(OUT) :: attr_id ! Attribute identifier
  INTEGER, INTENT(OUT) :: hdferr ! Error code:
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5aclose_f
```

**Name:** H5Acreate

**Signature:**

```
hid_t H5Acreate( hid_t loc_id, const char *attr_name, [1]
hid_t type_id, hid_t space_id, hid_t acpl_id )
```

```
hid_t H5Acreate( hid_t loc_id, const char *attr_name, [2]
hid_t type_id, hid_t space_id, hid_t acpl_id, hid_t aapl_id )
```

**Purpose:**

Creates an attribute attached to a specified object.

**Description:**

H5Acreate is a macro that is mapped to either H5Acreate1 or H5Acreate2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. For example:

- ◊ The H5Acreate macro will be mapped to H5Acreate1 and will use the H5Acreate1 syntax (first signature above) if an application is coded for HDF5 Release 1.6.x.
- ◊ The H5Acreate macro mapped to H5Acreate2 and will use the H5Acreate2 syntax (second signature above) if an application is coded for HDF5 Release 1.8.x.

Macro use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Acreate is mapped to the most recent version of the function, currently H5Acreate2. If the library and/or application is compiled for Release 1.6 emulation, H5Acreate will be mapped to H5Acreate1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Acreate mapping
<u>Global settings</u>	
No compatibility flag	H5Acreate2
Enable deprecated symbols	H5Acreate2
Disable deprecated symbols	H5Acreate2
Emulate Release 1.6 interface	H5Acreate1
<u>Function-level macros</u>	
H5Acreate_vers = 2	H5Acreate2
H5Acreate_vers = 1	H5Acreate1

**Interface history:** Signature [1] above is the original H5Acreate interface and the only interface available prior to HDF5 Release 1.8.0. This signature and the corresponding function are now deprecated but will remain directly callable as H5Acreate1.

Signature [2] above was introduced with HDF5 Release 1.8.0 and is the recommended and default interface. It is directly callable as H5Acreate2.

See “API Compatibility Macros in HDF5” for circumstances under which either of these functions might not be available in an installed instance of the HDF5 Library.

#### Fortran90 Interface: h5acreate\_f

```
SUBROUTINE h5acreate_f(loc_id, name, type_id, space_id, attr_id, hdferr, &
                      acpl_id, aapl_id )

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id      ! Object identifier
  CHARACTER(LEN=*), INTENT(IN) :: name      ! Attribute name
  INTEGER(HID_T), INTENT(IN) :: type_id     ! Attribute datatype identifier
  INTEGER(HID_T), INTENT(IN) :: space_id    ! Attribute dataspace identifier
  INTEGER(HID_T), INTENT(OUT) :: attr_id    ! Attribute identifier
  INTEGER, INTENT(OUT) :: hdferr            ! Error code:
                                           ! 0 on success and -1 on failure

  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: acpl_id
                                           ! Attribute creation property
                                           ! list identifier
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: aapl_id
                                           ! Attribute access property
                                           ! list identifier

END SUBROUTINE h5acreate_f
```

#### History:

Release	C
1.8.0	<p>The function H5Acreate renamed to H5Acreate1 and deprecated in this release.</p> <p>The macro H5Acreate and the functions H5Acreate2 and H5Acreate_by_name introduced in this release.</p>

**Name:** H5Acreate1

**Signature:**

```
hid_t H5Acreate1( hid_t loc_id, const char *attr_name, hid_t type_id, hid_t space_id,
hid_t acpl_id )
```

**Purpose:**

Creates a dataset as an attribute of another group, dataset, or named datatype.

**Notice:**

*This function is deprecated in favor of the function H5Acreate2.*

**Description:**

H5Acreate1 creates the attribute `attr_name` attached to the object specified with `loc_id`. `loc_id` can be a group, dataset, or named datatype identifier.

The attribute name specified in `attr_name` must be unique. Attempting to create an attribute with the same name as an already existing attribute will fail, leaving the pre-existing attribute in place. To overwrite an existing attribute with a new attribute of the same name, first call H5Adelete then recreate the attribute with H5Acreate1.

The datatype and dataspace identifiers of the attribute, `type_id` and `space_id`, respectively, are created with the H5T and H5S interfaces, respectively.

Currently only simple dataspace are allowed for attribute dataspace.

The attribute creation property list, `acpl_id`, is currently unused; it may be used in the future for optional attribute properties. At this time, `H5P_DEFAULT` is the only accepted value.

The attribute identifier returned from this function must be released with H5Aclose or resource leaks will develop.

**Parameters:**

<code>hid_t loc_id</code>	IN: Object (dataset, group, or named datatype) to be attached to.
<code>const char *attr_name</code>	IN: Name of attribute to create.
<code>hid_t type_id</code>	IN: Identifier of datatype for attribute.
<code>hid_t space_id</code>	IN: Identifier of dataspace for attribute.
<code>hid_t acpl_id</code>	IN: Identifier of creation property list. (Currently unused; the only accepted value is <code>H5P_DEFAULT</code> .)

**Returns:**

Returns an attribute identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Acreate.

**History:**

Release	C
1.8.0	The function H5Acreate renamed to H5Acreate1 and deprecated in this release.

**Name:** H5Acreate2**Signature:**

```

hid_t H5Acreate2( hid_t loc_id, const char *attr_name, hid_t type_id, hid_t space_id,
hid_t acpl_id, hid_t aapl_id, )

```

**Purpose:**

Creates an attribute attached to a specified object.

**Description:**

H5Acreate2 creates an attribute, `attr_name`, which is attached to the object specified by the identifier `loc_id`.

The attribute name, `attr_name`, must be unique for the object.

The attribute is created with the specified datatype and dataspace, `type_id` and `space_id`, which are created with the H5T and H5S interfaces respectively.

The attribute creation and access property lists are currently unused, but will be used in the future for optional attribute creation and access properties. These property lists should currently be H5P\_DEFAULT.

The attribute identifier returned by this function must be released with H5Aclose or resource leaks will develop.

**Parameters:**

<code>hid_t loc_id</code>	IN: Location or object identifier; may be dataset or group
<code>const char *attr_name</code>	IN: Attribute name
<code>hid_t type_id</code>	IN: Attribute datatype identifier
<code>hid_t space_id</code>	IN: Attribute dataspace identifier
<code>hid_t acpl_id</code>	IN: Attribute creation property list identifier (Currently not used.)
<code>hid_t aapl_id</code>	IN: Attribute access property list identifier (Currently not used.)

**Returns:**

Returns an attribute identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Acreate.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Acreate\_by\_name

**Signature:**

```
hid_t H5Acreate_by_name( hid_t loc_id, const char *obj_name, const char *attr_name,
                        hid_t type_id, hid_t space_id, hid_t acpl_id, hid_t aapl_id, hid_t lapl_id )
```

**Purpose:**

Creates an attribute attached to a specified object.

**Description:**

H5Acreate\_by\_name creates an attribute, *attr\_name*, which is attached to the object specified by *loc\_id* and *obj\_name*.

*loc\_id* is a location identifier; *obj\_name* is the object name relative to *loc\_id*. If *loc\_id* fully specifies the object to which the attribute is to be attached, *obj\_name* should be ' .' (a dot).

The attribute name, *attr\_name*, must be unique for the object.

The attribute is created with the specified datatype and dataspace, *type\_id* and *space\_id*, which are created with the H5T and H5S interfaces respectively.

The attribute creation and access property lists are currently unused, but will be used in the future for optional attribute creation and access properties. These property lists should currently be H5P\_DEFAULT.

The link access property list, *lapl\_id*, may provide information regarding the properties of links required to access the object, *obj\_name*. See “Link Access Properties” in the H5P APIs.

The attribute identifier returned by this function must be released with H5Aclose or resource leaks will develop.

**Parameters:**

<i>hid_t loc_id</i>	IN: Location or object identifier; may be dataset or group
<i>const char *obj_name</i>	IN: Name, relative to <i>loc_id</i> , of object that attribute is to be attached to
<i>const char *attr_name</i>	IN: Attribute name
<i>hid_t type_id</i>	IN: Attribute datatype identifier
<i>hid_t space_id</i>	IN: Attribute dataspace identifier
<i>hid_t acpl_id</i>	IN: Attribute creation property list identifier (Currently not used.)
<i>hid_t aapl_id</i>	IN: Attribute access property list identifier (Currently not used.)
<i>hid_t lapl_id</i>	IN: Link access property list

**Returns:**

Returns an attribute identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5acreate\_by\_name\_f

```
SUBROUTINE h5acreate_by_name_f(loc_id, obj_name, attr_name, type_id, space_id, &
                             attr, hdferr, acpl_id, aapl_id, lapl_id)
```

```
IMPLICIT NONE
INTEGER(HID_T), INTENT(IN) :: loc_id      ! Object identifier
CHARACTER(LEN=*), INTENT(IN) :: obj_name  ! Name of object to which
                                           ! attribute is attached
CHARACTER(LEN=*), INTENT(IN) :: attr_name ! Attribute name
INTEGER(HID_T), INTENT(IN) :: type_id    ! Attribute datatype identifier
```



```

INTEGER(HID_T), INTENT(IN) :: space_id      ! Attribute dataspace identifier
INTEGER(HID_T), INTENT(OUT) :: attr         ! An attribute identifier
INTEGER, INTENT(OUT) :: hdferr              ! Error code:
                                           ! 0 on success and -1 on failure

INTEGER(HID_T), OPTIONAL, INTENT(IN) :: acpl_id
                                           ! Attribute creation property list
                                           ! identifier (Currently not used.)
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: aapl_id
                                           ! Attribute access property list
                                           ! identifier (Currently not used.)
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                           ! Link access property list

END SUBROUTINE h5acreate_by_name_f

```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Adelete

**Signature:**

```
herr_t H5Adelete(hid_t loc_id, const char *attr_name)
```

**Purpose:**

Deletes an attribute from a specified location.

**Description:**

H5Adelete removes the attribute specified by its name, *attr\_name*, from a dataset, group, or named datatype. This function should not be used when attribute identifiers are open on *loc\_id* as it may cause the internal indexes of the attributes to change and future writes to the open attributes to produce incorrect results.

**Parameters:**

<i>hid_t</i> loc_id	IN: Identifier of the dataset, group, or named datatype to have the attribute deleted from.
<i>const char</i> *attr_name	IN: Name of the attribute to delete.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5adelete\_f

```
SUBROUTINE h5adelete_f(obj_id, name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id      ! Object identifier
  CHARACTER(LEN=*), INTENT(IN) :: name      ! Attribute name
  INTEGER, INTENT(OUT) :: hdferr            ! Error code:
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5adelete_f
```

**History:**

**Release**    **C**

**Name:** H5Adelete\_by\_name

**Signature:**

```
herr_t H5Adelete_by_name(hid_t loc_id, const char *obj_name, const char *attr_name,
hid_t lapl_id)
```

**Purpose:**

Removes an attribute from a specified location.

**Description:**

H5Adelete\_by\_name removes the attribute attr\_name from an object specified by location and name, loc\_id and obj\_name, respectively.

If loc\_id fully specifies the object from which the attribute is to be removed, obj\_name should be '.' (a dot).

The link access property list, lapl\_id, may provide information regarding the properties of links required to access the object, obj\_name. See “Link Access Properties” in the H5P APIs.

**Parameters:**

<i>hid_t</i> loc_id	IN: Location or object identifier; may be dataset or group
<i>const char</i> *obj_name	IN: Name of object, relative to location, from which attribute is to be removed
<i>const char</i> *attr_name	IN: Name of attribute to delete
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5adelete\_by\_name\_f

```
SUBROUTINE h5adelete_by_name_f(loc_id, obj_name, attr_name, hdferr, lapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id      ! Identifier for object to which
                                           ! attribute is attached
  CHARACTER(LEN=*), INTENT(IN) :: obj_name
                                           ! Name of object, relative to location,
                                           ! from which attribute is to be removed
  CHARACTER(LEN=*), INTENT(IN) :: attr_name
                                           ! Name of attribute to delete
  INTEGER, INTENT(OUT) :: hdferr            ! Error code:
                                           ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                           ! Link access property list
END SUBROUTINE h5adelete_by_name_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Adelete\_by\_idx

**Signature:**

```
herr_t H5Adelete_by_idx(hid_t loc_id, const char *obj_name, H5_index_t idx_type,
H5_iter_order_t order, hsize_t n, hid_t lapl_id)
```

**Purpose:**

Deletes an attribute from an object according to index order.

**Description:**

H5Adelete\_by\_idx removes an attribute, specified by its location in an index, from an object.

The object from which the attribute is to be removed is specified by a location identifier and name, `loc_id` and `obj_name`, respectively. If `loc_id` fully specifies the object from which the attribute is to be removed, `obj_name` should be `'.'` (a dot).

The attribute to be removed is specified by a position in an index, `n`. The type of index is specified by `idx_type` and may be `H5_INDEX_NAME`, for an alpha-numeric index by name, or `H5_INDEX_CRT_ORDER`, for an index by creation order. The order in which the index is to be traversed is specified by `order` and may be `H5_ITER_INC` (increment) for top-down iteration, `H5_ITER_DEC` (decrement) for bottom-up iteration, or `H5_ITER_NATIVE`, in which case HDF5 will iterate in the fastest-available order. For example, if `idx_type`, `order`, and `n` are set to `H5_INDEX_NAME`, `H5_ITER_INC`, and 5, respectively, the fifth attribute by alpha-numeric order of attribute names will be removed.

For a discussion of `idx_type` and `order`, the valid values of those parameters, and the use of `n`, see the description of H5Aiterate2

The link access property list, `lapl_id`, may provide information regarding the properties of links required to access the object, `obj_name`. See “Link Access Properties” in the H5P APIs.

**Parameters:**

<i>hid_t</i> loc_id	IN: Location or object identifier; may be dataset or group
<i>const char</i> *obj_name	IN: Name of object, relative to location, from which attribute is to be removed
<i>H5_index_t</i> idx_type	IN: Type of index
<i>H5_iter_order_t</i> order	IN: Order in which to iterate over index
<i>hsize_t</i> n	IN: Offset within index
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5adelete\_by\_idx\_f

```
SUBROUTINE h5adelete_by_idx_f(loc_id, obj_name, idx_type, order, n, hdferr, &
    lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id
                                ! Identifier for object to which
                                ! attribute is attached
    CHARACTER(LEN=*), INTENT(IN) :: obj_name
                                ! Name of object, relative to location,
                                ! from which attribute is to be removed
    INTEGER, INTENT(IN) :: idx_type
                                ! Type of index; Possible values are:
                                !   H5_INDEX_UNKNOWN_F - Unknown index type
```

```

!      H5_INDEX_NAME_F      - Index on names
!      H5_INDEX_CRT_ORDER_F - Index on creation order
!      H5_INDEX_N_F        - Number of indices defined
INTEGER, INTENT(IN) :: order
! Order in which to iterate over index:
!      H5_ITER_UNKNOWN_F    - Unknown order
!      H5_ITER_INC_F        - Increasing order
!      H5_ITER_DEC_F        - Decreasing order
!      H5_ITER_NATIVE_F     - No particular order,
!                           whatever is fastest
!      H5_ITER_N_F          - Number of iteration orders
INTEGER(HSIZE_T), INTENT(IN) :: n
! Offset within index
INTEGER, INTENT(OUT) :: hdferr
! Error code:
! 0 on success and -1 on failure
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
! Link access property list
END SUBROUTINE h5adelete_by_idx_f

```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Aexists

**Signature:**

*htri\_t* H5Aexists(*hid\_t* obj\_id, *const char* \*attr\_name)

**Purpose:**

Determines whether an attribute with a given name exists on an object.

**Description:**

H5Aexists determines whether the attribute attr\_name exists on the object specified by obj\_id.

**Parameters:**

*hid\_t* obj\_id,                      IN: Object identifier  
*const char* \*attr\_name            IN: Attribute name

**Returns:**

When successful, returns a positive value, for TRUE, or 0 (zero), for FALSE.

Otherwise returns a negative value.

**Fortran90 Interface:** h5aexists\_f

```
SUBROUTINE h5aexists_f(obj_id, attr_name, attr_exists, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id      ! Object identifier
  CHARACTER(LEN=*), INTENT(IN) :: attr_name ! Attribute name
  LOGICAL, INTENT(OUT) :: attr_exists      ! .TRUE. if exists, .FALSE. otherwise
  INTEGER, INTENT(OUT) :: hdferr           ! Error code:
                                           ! 0 on success and -1 on failure
END SUBROUTINE
```

**History:**

**Release    C**

1.8.0        Function introduced in this release.

**Name:** H5Aexists\_by\_name

**Signature:**

```
htri_t H5Aexists_by_name( hid_t loc_id, const char *obj_name, const char *attr_name,
                        hid_t lapl_id )
```

**Purpose:**

Determines whether an attribute with a given name exists on an object.

**Description:**

H5Aexists\_by\_name determines whether the attribute attr\_name exists on an object. That object is specified by its location and name, loc\_id and obj\_name, respectively.

loc\_id specifies a location in the file containing the object. obj\_name is the name of the object to which the attribute is attached and can be a relative name, relative to loc\_id, or an absolute name, based in the root group of the file. If loc\_id fully specifies the object, obj\_name should be ' .' (a dot).

The link access property list, lapl\_id, may provide information regarding the properties of links required to access obj\_name. See “Link Access Properties” in the H5P APIs.

**Parameters:**

hid_t loc_id,	IN: Location identifier
const char *obj_name	IN: Object name Either relative to loc_id, absolute from the file’s root group, or ' .' (a dot)
const char *attr_name	IN: Attribute name
hid_t lapl_id	IN: Link access property list identifier

**Returns:**

When successful, returns a positive value, for TRUE, or 0 (zero), for FALSE.

Otherwise returns a negative value.

**Fortran90 Interface:** h5aexists\_by\_name\_f

```
SUBROUTINE h5aexists_by_name_f(loc_id, obj_name, attr_name, attr_exists, hdferr,&
    lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id ! Location identifier
    CHARACTER(LEN=*), INTENT(IN) :: obj_name
                                   ! Object name either relative to loc_id,
                                   ! absolute from the
                                   ! file’s root group, or ' .'
    CHARACTER(LEN=*), INTENT(IN) :: attr_name
                                   ! Attribute name
    LOGICAL, INTENT(OUT) :: attr_exists ! .TRUE. if exists, .FALSE. otherwise
    INTEGER, INTENT(OUT) :: hdferr      ! Error code:
                                   ! 0 on success and -1 on failure
    INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                   ! Link access property list identifier
END SUBROUTINE h5aexists_by_name_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Aget\_create\_plist

**Signature:**

*hid\_t* H5Aget\_create\_plist(*hid\_t* attr\_id)

**Purpose:**

Gets an attribute creation property list identifier.

**Description:**

H5Aget\_create\_plist returns an identifier for the attribute creation property list associated with the attribute specified by attr\_id.

The creation property list identifier should be released with H5Pclose.

**Parameters:**

*hid\_t* attr\_id    IN: Identifier of the attribute.

**Returns:**

Returns an identifier for the attribute's creation property list if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5aget\_create\_plist\_f

```
SUBROUTINE h5aget_create_plist_f(attr_id, creation_prop_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: attr_id
                                ! Identifier of the attribute
  INTEGER(HID_T), INTENT(OUT) :: creation_prop_id
                                ! Identifier for the attribute's creation property
  INTEGER, INTENT(OUT) :: hdferr
                                ! Error code:
                                ! 0 on success and -1 on failure
END SUBROUTINE h5aget_create_plist_f
```

**History:**

<b>Release</b>	<b>C</b>
----------------	----------

1.8.0	Function introduced in this release.
-------	--------------------------------------



**Name:** H5Aget\_info

**Signature:**

```
herr_t H5Aget_info(hid_t attr_id, H5A_info_t *ainfo)
```

**Purpose:**

Retrieves attribute information, by attribute identifier.

**Description:**

H5Aget\_info retrieves attribute information, locating the attribute with an attribute identifier, *attr\_id*, which is the identifier returned by H5Aopen or H5Aopen\_by\_idx. The attribute information is returned in the *ainfo* struct.

The *ainfo* struct is defined as follows:

```
typedef struct {
    hbool_t          corder_valid;
    H5O_msg_crt_idx_t corder;
    H5T_cset_t       cset;
    hsize_t          data_size;
} H5A_info_t;
```

*corder\_valid* indicates whether the creation order data is valid for this attribute. Note that if creation order is not being tracked, no creation order data will be valid. Valid values are TRUE and FALSE.

*corder* is a positive integer containing the creation order of the attribute. This value is 0-based, so, for example, the third attribute created will have a *corder* value of 2.

*cset* indicates the character set used for the attribute's name; valid values are defined in *H5Tpublic.h* and include the following:

```
H5T_CSET_ASCII      US ASCII
H5T_CSET_UTF8       UTF-8 Unicode encoding
```

This value is set with H5Pset\_char\_encoding.

*data\_size* indicates the size, in the number of characters, of the attribute.

**Parameters:**

```
hid_t attr_id      IN: Attribute identifier
H5A_info_t *ainfo  OUT: Attribute information struct
```

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aget\_info\_f

```
SUBROUTINE h5aget_info_f(attr_id, f_corder_valid, corder, cset, data_size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: attr_id ! Attribute identifier
  LOGICAL, INTENT(OUT) :: f_corder_valid ! Indicates whether the creation order
                                         ! data is valid for this attribute
  INTEGER, INTENT(OUT) :: corder         ! Is a positive integer containing the
                                         ! creation order of the attribute
  INTEGER, INTENT(OUT) :: cset           ! Indicates the character set used for
                                         ! the ! attribute's name
  INTEGER(HSIZE_T), INTENT(OUT) :: data_size
                                         ! Indicates the size, in the number
```

```
INTEGER, INTENT(OUT) :: hdferr  
  
END SUBROUTINE h5aget_info_f
```

```
! of characters, of the attribute  
! Error code:  
! 0 on success and -1 on failure
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Aget\_info\_by\_idx

**Signature:**

```
herr_t H5Aget_info_by_idx(hid_t loc_id, const char *obj_name, H5_index_t idx_type,
H5_iter_order_t order, hsize_t n, H5A_info_t *ainfo, hid_t lapl_id)
```

**Purpose:**

Retrieves attribute information, by attribute index position.

**Description:**

H5Aget\_info\_by\_idx retrieves information for an attribute that is attached to an object, which is specified by its location and name, *loc\_id* and *obj\_name*, respectively. The attribute is located by its index position and the attribute information is returned in the *ainfo* struct.

If *loc\_id* fully specifies the object to which the attribute is attached, *obj\_name* should be ' .' (a dot).

The attribute is located by means of an index type, an index traversal order, and a position in the index, *idx\_type*, *order* and *n*, respectively. These parameters and their valid values are discussed in the description of H5Aiterate2.

The *ainfo* struct, which will contain the returned attribute information, is described in H5Aget\_info.

The link access property list, *lapl\_id*, may provide information regarding the properties of links required to access the object, *obj\_name*. See “Link Access Properties” in the H5P APIs.

**Parameters:**

<i>hid_t</i> loc_id	IN: Location of object to which attribute is attached
<i>const char</i> *obj_name	IN: Name of object to which attribute is attached, relative to location
<i>H5_index_t</i> idx_type	IN: Type of index
<i>H5_iter_order_t</i> order	IN: Index traversal order
<i>hsize_t</i> n	IN: Attribute's position in index
<i>H5A_info_t</i> *ainfo	OUT: Struct containing returned attribute information
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aget\_info\_by\_idx\_f

```
SUBROUTINE h5aget_info_by_idx_f(loc_id, obj_name, idx_type, order, n, &
    f_corder_valid, corder, cset, data_size, hdferr, lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id
                                ! Object identifier
    CHARACTER(LEN=*), INTENT(IN) :: obj_name
                                ! Name of object to which attribute is attached
    INTEGER, INTENT(IN) :: idx_type
                                ! Type of index; Possible values are:
                                !   H5_INDEX_UNKNOWN_F - Unknown index type
                                !   H5_INDEX_NAME_F - Index on names
                                !   H5_INDEX_CRT_ORDER_F - Index on creation order
                                !   H5_INDEX_N_F - Number of indices defined
    INTEGER, INTENT(IN) :: order
                                ! Order in which to iterate over index:
                                !   H5_ITER_UNKNOWN_F - Unknown order
                                !   H5_ITER_INC_F - Increasing order
                                !   H5_ITER_DEC_F - Decreasing order
                                !   H5_ITER_NATIVE_F - No particular order,
```

```

!                                     whatever is fastest
INTEGER(HSIZE_T), INTENT(IN) :: n
! Attribute's position in index

LOGICAL, INTENT(OUT) :: f_corder_valid
! Indicates whether the creation order data is
! valid for this attribute
INTEGER, INTENT(OUT) :: corder
! Is a positive integer containing the creation
! order of the attribute
INTEGER, INTENT(OUT) :: cset
! Indicates the character set used for the
! attribute's name
INTEGER(HSIZE_T), INTENT(OUT) :: data_size
! Indicates the size, in the number of characters,
! of the attribute
INTEGER, INTENT(OUT) :: hdferr
! Error code:
! 0 on success and -1 on failure
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
! Link access property list
END SUBROUTINE h5aget_info_by_idx_f

```

**History:****Release    C**

1.8.0        Function introduced in this release.

**Name:** H5Aget\_info\_by\_name

**Signature:**

```
herr_t H5Aget_info_by_name(hid_t loc_id, const char *obj_name, const char *attr_name,
                           H5A_info_t *ainfo, hid_t lapl_id)
```

**Purpose:**

Retrieves attribute information, by attribute name.

**Description:**

H5Aget\_info\_by\_name retrieves information for an attribute, *attr\_name*, that is attached to an object, specified by its location and name, *loc\_id* and *obj\_name*, respectively. The attribute information is returned in the *ainfo* struct.

If *loc\_id* fully specifies the object to which the attribute is attached, *obj\_name* should be ' .' (a dot).

The *ainfo* struct is described in H5Aget\_info.

The link access property list, *lapl\_id*, may provide information regarding the properties of links required to access the object, *obj\_name*. See “Link Access Properties” in the H5P APIs.

**Parameters:**

<i>hid_t</i> loc_id	IN: Location of object to which attribute is attached
<i>const char</i> *obj_name	IN: Name of object to which attribute is attached, relative to location
<i>const char</i> *attr_name	IN: Attribute name
<i>H5A_info_t</i> *ainfo	OUT: Struct containing returned attribute information
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aget\_info\_by\_name\_f

```
SUBROUTINE h5aget_info_by_name_f(loc_id, obj_name, attr_name, &
    f_corder_valid, corder, cset, data_size, hdferr, lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id           ! Object identifier
    CHARACTER(LEN=*), INTENT(IN) :: obj_name       ! Name of object to which attribute
                                                    ! is attached
    CHARACTER(LEN=*), INTENT(IN) :: attr_name      ! Attribute name
    LOGICAL, INTENT(OUT) :: f_corder_valid         ! Indicates whether the creation
                                                    ! order data is valid for this
                                                    ! attribute
    INTEGER, INTENT(OUT) :: corder                 ! Is a positive integer containing
                                                    ! the creation order of the
                                                    ! attribute
    INTEGER, INTENT(OUT) :: cset                   ! Indicates the character set used
                                                    ! for the attribute's name
    INTEGER(HSIZE_T), INTENT(OUT) :: data_size     ! Indicates the size, in the number
                                                    ! of characters, of the attribute
    INTEGER, INTENT(OUT) :: hdferr                 ! Error code:
                                                    ! 0 on success and -1 on failure
    INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                                    ! Link access property list
END SUBROUTINE h5aget_info_by_name_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Aget\_name

**Signature:**

```
ssize_t H5Aget_name(hid_t attr_id, size_t buf_size, char *buf )
```

**Purpose:**

Gets an attribute name.

**Description:**

H5Aget\_name retrieves the name of an attribute specified by the identifier, `attr_id`. Up to `buf_size` characters are stored in `buf` followed by a `\0` string terminator. If the name of the attribute is longer than `(buf_size - 1)`, the string terminator is stored in the last position of the buffer to properly terminate the string.

If the user only wants to find out the size of this name, the values 0 and `NULL` can be passed in for the parameters `bufsize` and `buf`.

**Parameters:**

<i>hid_t</i> attr_id	IN: Identifier of the attribute.
<i>size_t</i> buf_size	IN: The size of the buffer to store the name in.
<i>char</i> *buf	OUT: Buffer to store name in.

**Returns:**

Returns the length of the attribute's name, which may be longer than `buf_size`, if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5aget\_name\_f

```
SUBROUTINE h5aget_name_f(attr_id, size, buf, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: attr_id  ! Attribute identifier
  INTEGER(SIZE_T), INTENT(IN) :: size      ! Buffer size
  CHARACTER(LEN=*), INTENT(INOUT) :: buf

                                     ! Buffer to hold attribute name
  INTEGER, INTENT(OUT) :: hdferr          ! Error code:
                                         ! name length is successful,
                                         ! -1 if fail
END SUBROUTINE h5aget_name_f
```

**Name:** H5Aget\_name\_by\_idx

**Signature:**

```
ssize_t H5Aget_name_by_idx( hid_t loc_id, const char *obj_name, H5_index_t idx_type,
H5_iter_order_t order, hsize_t n, char *name, size_t size, hid_t lapl_id )
```

**Purpose:**

Gets an attribute name, by attribute index position

**Description:**

H5Aget\_name\_by\_idx retrieves the name of an attribute that is attached to an object, which is specified by its location and name, `loc_id` and `obj_name`, respectively. The attribute is located by its index position, the size of the name is specified in `size`, and the attribute name is returned in `name`.

If `loc_id` fully specifies the object to which the attribute is attached, `obj_name` should be `'.'` (a dot).

The attribute is located by means of an index type, an index traversal order, and a position in the index, `idx_type`, `order` and `n`, respectively. These parameters and their valid values are discussed in the description of H5Aiterate2.

If the attribute name's size is unknown, the values 0 and NULL can be passed in for the parameters `size` and `name`. The function's return value will provide the correct value for `size`.

The link access property list, `lapl_id`, may provide information regarding the properties of links required to access the object, `obj_name`. See "Link Access Properties" in the H5P APIs.

**Parameters:**

<code>hid_t loc_id</code>	IN: Location of object to which attribute is attached
<code>const char *obj_name</code>	IN: Name of object to which attribute is attached, relative to location
<code>H5_index_t idx_type</code>	IN: Type of index
<code>H5_iter_order_t order</code>	IN: Index traversal order
<code>hsize_t n</code>	IN: Attribute's position in index
<code>char *name</code>	OUT: Attribute name
<code>size_t size</code>	IN: Size, in bytes, of attribute name
<code>hid_t lapl_id</code>	IN: Link access property list

**Returns:**

Returns attribute name size, in bytes, if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aget\_name\_by\_idx\_f

```
SUBROUTINE h5aget_name_by_idx_f(loc_id, obj_name, idx_type, order, &
    n, name, hdferr, size, lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id ! Identifier for object to which
        ! attribute is attached
    CHARACTER(LEN=*), INTENT(IN) :: obj_name ! Name of object, relative to
        ! location, from which attribute is to
        ! be removed
    INTEGER, INTENT(IN) :: idx_type
        ! Type of index; Possible values are:
        ! H5_INDEX_UNKNOWN_F - Unknown index type
        ! H5_INDEX_NAME_F - Index on names
        ! H5_INDEX_CRT_ORDER_F - Index on creation order
        ! H5_INDEX_N_F - Number indices defined
```



```

INTEGER, INTENT(IN) :: order ! Order in which to iterate over index:
                             ! H5_ITER_UNKNOWN_F - Unknown order
                             ! H5_ITER_INC_F     - Increasing order
                             ! H5_ITER_DEC_F     - Decreasing order
                             ! H5_ITER_NATIVE_F   - No particular order,
                             !                   whatever is fastest
                             ! H5_ITER_N_F        - Number of iteration orders

INTEGER(HSIZE_T), INTENT(IN) :: n
                             ! Attribute's position in index
CHARACTER(LEN=*), INTENT(OUT) :: name
                             ! Attribute name
INTEGER, INTENT(OUT) :: hdferr
                             ! Error code:
                             ! Returns attribute name size,
                             ! -1 if fail
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                             ! Link access property list
INTEGER(SIZE_T), OPTIONAL, INTENT(OUT) :: size
                             ! exact buffer size, in number of characters
END SUBROUTINE h5aget_name_by_idx_f

```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Aget\_num\_attrs

**Signature:**

*int* H5Aget\_num\_attrs(*hid\_t* loc\_id)

**Purpose:**

Determines the number of attributes attached to an object.

**Description:**

H5Aget\_num\_attrs returns the number of attributes attached to the object specified by its identifier, loc\_id. The object can be a group, dataset, or named datatype.

**Parameters:**

*hid\_t* loc\_id      IN: Identifier of a group, dataset, or named datatype.

**Returns:**

Returns the number of attributes if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aget\_num\_attrs\_f

```
SUBROUTINE h5aget_num_attrs_f(obj_id, attr_num, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id ! Object identifier
  INTEGER, INTENT(OUT) :: attr_num ! Number of attributes of the object
  INTEGER, INTENT(OUT) :: hdferr ! Error code:
                                   ! 0 on success and -1 on failure
END SUBROUTINE h5aget_num_attrs_f
```

**Name:** H5Aget\_space

**Signature:**

*hid\_t* H5Aget\_space(*hid\_t* attr\_id)

**Purpose:**

Gets a copy of the dataspace for an attribute.

**Description:**

H5Aget\_space retrieves a copy of the dataspace for an attribute. The dataspace identifier returned from this function must be released with H5Sclose or resource leaks will develop.

**Parameters:**

*hid\_t* attr\_id      IN: Identifier of an attribute.

**Returns:**

Returns attribute dataspace identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aget\_space\_f

```
SUBROUTINE h5aget_space_f(attr_id, space_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: attr_id    ! Attribute identifier
  INTEGER(HID_T), INTENT(OUT) :: space_id ! Attribute dataspace identifier
  INTEGER, INTENT(OUT) :: hdferr           ! Error code:
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5aget_space_f
```

**Name:** H5Aget\_storage\_size

**Signature:**

*hsize\_t* H5Aget\_storage\_size(*hid\_t* attr\_id)

**Purpose:**

Returns the amount of storage required for an attribute.

**Description:**

H5Aget\_storage\_size returns the amount of storage that is required for the specified attribute, attr\_id.

**Parameters:**

*hid\_t* attr\_id    IN: Identifier of the attribute to query.

**Returns:**

Returns the amount of storage size allocated for the attribute; otherwise returns 0 (zero).

**Fortran90 Interface:** h5aget\_storage\_size\_f

```
SUBROUTINE h5aget_storage_size_f(attr_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: attr_id    ! Attribute identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: size    ! Attribute storage requirement
  INTEGER, INTENT(OUT) :: hdferr           ! Error code:
                                           !    0 on success and -1 on failure
END SUBROUTINE h5aget_storage_size_f
```

**Name:** H5Aget\_type

**Signature:**

*hid\_t* H5Aget\_type(*hid\_t* attr\_id)

**Purpose:**

Gets an attribute datatype.

**Description:**

H5Aget\_type retrieves a copy of the datatype for an attribute.

The datatype is reopened if it is a named type before returning it to the application. The datatypes returned by this function are always read-only. If an error occurs when atomizing the return datatype, then the datatype is closed.

The datatype identifier returned from this function must be released with H5Tclose or resource leaks will develop.

**Parameters:**

*hid\_t* attr\_id      IN: Identifier of an attribute.

**Returns:**

Returns a datatype identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aget\_type\_f

```
SUBROUTINE h5aget_type_f(attr_id, type_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: attr_id ! Attribute identifier
  INTEGER(HID_T), INTENT(OUT) :: type_id ! Attribute datatype identifier
  INTEGER, INTENT(OUT) :: hdferr        ! Error code:
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5aget_type_f
```

**Name:** H5Aiterate

**Signature:**

```
herr_t H5Aiterate( hid_t loc_id, unsigned *idx, H5A_operator_t op, [1]
void *op_data )
```

```
herr_t H5Aiterate( hid_t obj_id, H5_index_t idx_type, [2]
H5_iter_order_t order, hsize_t *n, H5A_operator2_t op, void *op_data )
```

**Purpose:**

Calls a user's function for each attribute on an object.

**Description:**

H5Aiterate is a macro that is mapped to either H5Aiterate1 or H5Aiterate2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. For example:

- ◇ The H5Aiterate macro will be mapped to H5Aiterate1 and will use the H5Aiterate1 syntax (first signature above) if an application is coded for HDF5 Release 1.6.x.
- ◇ The H5Aiterate macro mapped to H5Aiterate2 and will use the H5Aiterate2 syntax (second signature above) if an application is coded for HDF5 Release 1.8.x.

Macro use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Aiterate is mapped to the most recent version of the function, currently H5Aiterate2. If the library and/or application is compiled for Release 1.6 emulation, H5Aiterate will be mapped to H5Aiterate1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Aiterate mapping
<u>Global settings</u>	
No compatibility flag	H5Aiterate2
Enable deprecated symbols	H5Aiterate2
Disable deprecated symbols	H5Aiterate2
Emulate Release 1.6 interface	H5Aiterate1
<u>Function-level macros</u>	
H5Aiterate_vers = 2	H5Aiterate2
H5Aiterate_vers = 1	H5Aiterate1

**Interface history:** Signature [1] above is the original `H5Aiterate` interface and the only interface available prior to HDF5 Release 1.8.0. This signature and the corresponding function are now deprecated but will remain directly callable as `H5Aiterate1`.

Signature [2] above was introduced with HDF5 Release 1.8.0 and is the recommended and default interface. It is directly callable as `H5Aiterate2`.

See “API Compatibility Macros in HDF5” for circumstances under which either of these functions might not be available in an installed instance of the HDF5 Library.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	The function <code>H5Aiterate</code> renamed to <code>H5Aiterate1</code> and deprecated in this release. The macro <code>H5Aiterate</code> and the functions <code>H5Aiterate2</code> and <code>H5Aiterate_by_name</code> introduced in this release.

**Name:** H5Aiterate1

**Signature:**

```
herr_t H5Aiterate1( hid_t loc_id, unsigned * idx, H5A_operator1_t op, void *op_data )
```

**Purpose:**

Calls a user's function for each attribute on an object.

**Notice:**

*This function is deprecated in favor of the function H5Aiterate2.*

**Description:**

H5Aiterate1 iterates over the attributes of the object specified by its identifier, `loc_id`. The object can be a group, dataset, or named datatype. For each attribute of the object, the `op_data` and some additional information specified below are passed to the operator function `op`. The iteration begins with the attribute specified by its index, `idx`; the index for the next attribute to be processed by the operator, `op`, is returned in `idx`. If `idx` is the null pointer, then all attributes are processed.

The prototype for `H5A_operator_t` is:

```
typedef herr_t (*H5A_operator1_t)(hid_t loc_id, const char *attr_name, void *operator_data);
```

The operation receives the identifier for the group, dataset or named datatype being iterated over, `loc_id`, the name of the current attribute about the object, `attr_name`, and the pointer to the operator data passed in to H5Aiterate1, `op_data`. The return values from an operator are:

- ◊ Zero causes the iterator to continue, returning zero when all attributes have been processed.
- ◊ Positive causes the iterator to immediately return that positive value, indicating short-circuit success. The iterator can be restarted at the next attribute.
- ◊ Negative causes the iterator to immediately return that value, indicating failure. The iterator can be restarted at the next attribute.

**Parameters:**

<code>hid_t loc_id</code>	IN: Identifier of a group, dataset or named datatype.
<code>unsigned * idx</code>	IN/OUT: Starting (IN) and ending (OUT) attribute index.
<code>H5A_operator1_t op</code>	IN: User's function to pass each attribute to
<code>void *op_data</code>	IN/OUT: User's data to pass through to iterator operator function

**Returns:**

If successful, returns the return value of the last operator if it was non-zero, or zero if all attributes were processed. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	The function H5Aiterate renamed to H5Aiterate1 and deprecated in this release.



**Name:** H5Aiterate2

**Signature:**

```
herr_t H5Aiterate2(hid_t obj_id, H5_index_t idx_type, H5_iter_order_t order, hsize_t *n,
H5A_operator2_t op, void *op_data,)
```

**Purpose:**

Calls user-defined function for each attribute on an object.

**Description:**

H5Aiterate2 iterates over the attributes attached to a dataset, named datatype, or group, as specified by *obj\_id*. For each attribute, user-provided data, *op\_data*, with additional information as defined below, is passed to a user-defined function, *op*, which operates on that attribute.

The order of the iteration and the attributes iterated over are specified by three parameters: the index type, *idx\_type*; the order in which the index is to be traversed, *order*; and the attribute's position in the index, *n*.

The type of index specified by *idx\_type* can be one of the following:

H5_INDEX_NAME	An alpha-numeric index by attribute name
H5_INDEX_CRT_ORDER	An index by creation order

The order in which the index is to be traversed, as specified by *order*, can be one of the following:

H5_ITER_INC	Iteration is from beginning to end, i.e., a top-down iteration incrementing the index position at each step.
H5_ITER_DEC	Iteration starts at the end of the index, i.e., a bottom-up iteration decrementing the index position at each step.
H5_ITER_NATIVE	HDF5 iterates in the fastest-available order. No information is provided as to the order, but HDF5 ensures that each element in the index will be visited if the iteration completes successfully.

The next attribute to be operated on is specified by *n*, a position in the index.

For example, if *idx\_type*, *order*, and *n* are set to H5\_INDEX\_NAME, H5\_ITER\_INC, and 5, respectively, the attribute in question is the fifth attribute from the beginning of the alpha-numeric index of attribute names. If *order* were set to H5\_ITER\_DEC, it would be the fifth attribute from the end of the index.

The parameter *n* is passed in on an H5Aiterate2 call with one value and may be returned with another value. The value passed in identifies the parameter to be operated on first; the value returned identifies the parameter to be operated on in the next step of the iteration.

The H5A\_operator2\_t prototype for the *op* parameter is as follows:

```
typedef herr_t (*H5A_operator2_t)(hid_t location_id/*in*/, const char
*attr_name/*in*/, const H5A_info_t *ainfo/*in*/, void *op_data/*in, out*/)
```

The operation receives the location identifier for the group or dataset being iterated over, *location\_id*; the name of the current object attribute, *attr\_name*; the attribute's *info* struct, *ainfo*; and a pointer to the operator data passed into H5Aiterate2, *op\_data*.

Valid return values from an operator and the resulting H5Aiterate2 and op behavior are as follows:

- ◊ Zero causes the iterator to continue, returning zero when all attributes have been processed.
- ◊ A positive value causes the iterator to immediately return that positive value, indicating short-circuit success. The iterator can be restarted at the next attribute, as indicated by the return value of n.
- ◊ A negative value causes the iterator to immediately return that value, indicating failure. The iterator can be restarted at the next attribute, as indicated by the return value of n.

**Parameters:**

<i>hid_t</i> obj_id	IN: Identifier for object to which attributes are attached; may be group, dataset, or named datatype.
<i>H5_index_t</i> idx_type	IN: Type of index
<i>H5_iter_order_t</i> order	IN: Order in which to iterate over index
<i>hsize_t</i> *n	IN/OUT: Initial and returned offset within index
<i>H5A_operator2_t</i> op	IN: User-defined function to pass each attribute to
<i>void</i> *op_data	IN/OUT: User data to pass through to and to be returned by iterator operator function

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

Further note that this function returns the return value of the last operator if it was non-zero, which can be a negative value, zero if all attributes were processed, or a positive value indicating short-circuit success (see above).

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Aiterate\_by\_name

**Signature:**

```
herr_t H5Aiterate_by_name(hid_t loc_id, const char *obj_name, H5_index_t idx_type,
H5_iter_order_t order, hsize_t *n, H5A_operator2_t op, void *op_data, hid_t lapd_id)
```

**Purpose:**

Calls user-defined function for each attribute on an object.

**Description:**

H5Aiterate\_by\_name iterates over the attributes attached to the dataset or group specified with loc\_id and obj\_name. For each attribute, user-provided data, op\_data, with additional information as defined below, is passed to a user-defined function, op, which operates on that attribute.

If loc\_id fully specifies the object to which these attributes are attached, obj\_name should be ' . ' (a dot).

The order of the iteration and the attributes iterated over are specified by three parameters: the index type, idx\_type; the order in which the index is to be traversed, order; and the attribute's position in the index, n.

The type of index specified by idx\_type can be one of the following:

H5_INDEX_NAME	An alpha-numeric index by attribute name
H5_INDEX_CRT_ORDER	An index by creation order

The order in which the index is to be traversed, as specified by order, can be one of the following:

H5_ITER_INC	Iteration is from beginning to end, i.e., a top-down iteration incrementing the index position at each step.
H5_ITER_DEC	Iteration starts at the end of the index, i.e., a bottom-up iteration decrementing the index position at each step.
H5_ITER_NATIVE	HDF5 iterates in the fastest-available order. No information is provided as to the order, but HDF5 ensures that each element in the index will be visited if the iteration completes successfully.

The next attribute to be operated on is specified by n, a position in the index.

For example, if idx\_type, order, and n are set to H5\_INDEX\_NAME, H5\_ITER\_INC, and 5, respectively, the attribute in question is the fifth attribute from the beginning of the alpha-numeric index of attribute names. If order were set to H5\_ITER\_DEC, it would be the fifth attribute from the end of the index.

The parameter n is passed in on an H5Aiterate\_by\_name call with one value and may be returned with another value. The value passed in identifies the parameter to be operated on first; the value returned identifies the parameter to be operated on in the next step of the iteration.

The H5A\_operator2\_t prototype for the op parameter is as follows:

```
typedef herr_t (*H5A_operator2_t)(hid_t location_id/*in*/, const char
*attr_name/*in*/, const H5A_info_t *ainfo/*in*/, void *op_data/*in, out*/)
```

The operation receives the location identifier for the group or dataset being iterated over, `location_id`; the name of the current object attribute, `attr_name`; the attribute's *info* struct, `ainfo`; and a pointer to the operator data passed into `H5Aiterate_by_name`, `op_data`.

Valid return values from an operator and the resulting `H5Aiterate_by_name` and `op` behavior are as follows:

- ◊ Zero causes the iterator to continue, returning zero when all attributes have been processed.
- ◊ A positive value causes the iterator to immediately return that positive value, indicating short-circuit success. The iterator can be restarted at the next attribute, as indicated by the return value of `n`.
- ◊ A negative value causes the iterator to immediately return that value, indicating failure. The iterator can be restarted at the next attribute, as indicated by the return value of `n`.

The link access property list, `lapl_id`, may provide information regarding the properties of links required to access the object, `obj_name`. See “Link Access Properties” in the H5P APIs.

#### Parameters:

<code>hid_t loc_id</code>	IN: Location or object identifier; may be dataset or group
<code>const char *obj_name</code>	IN: Name of object, relative to location
<code>H5_index_t idx_type</code>	IN: Type of index
<code>H5_iter_order_t order</code>	IN: Order in which to iterate over index
<code>hsize_t *n</code>	IN/OUT: Initial and returned offset within index
<code>H5A_operator2_t op</code>	IN: User-defined function to pass each attribute to
<code>void *op_data</code>	IN/OUT: User data to pass through to and to be returned by iterator operator function
<code>hid_t lapd_id</code>	IN: Link access property list

#### Returns:

Returns a non-negative value if successful; otherwise returns a negative value.

Further note that this function returns the return value of the last operator if it was non-zero, which can be a negative value, zero if all attributes were processed, or a positive value indicating short-circuit success (see above).

#### Fortran90 Interface:

None.

#### History:

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Aopen

**Signature:**

```
herr_t H5Aopen( hid_t obj_id, const char *attr_name, hid_t aapl_id )
```

**Purpose:**

Opens an attribute for an object specified by object identifier and attribute name.

**Description:**

H5Aopen opens an existing attribute, attr\_name, that is attached to an object specified an object identifier, object\_id.

The attribute access property list, aapl\_id, is currently unused and should currently be H5P\_DEFAULT.

This function, H5Aopen\_by\_idx, or H5Aopen\_by\_name must be called before an attribute can be accessed for any further purpose, including reading, writing, or any modification.

The attribute identifier returned by this function must be released with H5Aclose or resource leaks will develop.

**Parameters:**

<i>hid_t</i> obj_id	IN: Identifier for object to which attribute is attached
<i>const char</i> *attr_name	IN: Name of attribute to open
<i>hid_t</i> aapl_id	IN: Attribute access property list

**Returns:**

Returns an attribute identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aopen\_f

```
SUBROUTINE h5aopen_f(obj_id, attr_name, attr_id, hdferr, aapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id      ! Object identifier
  CHARACTER(LEN=*), INTENT(IN) :: attr_name ! Attribute name
  INTEGER(HID_T), INTENT(OUT) :: attr_id    ! Attribute identifier
  INTEGER, INTENT(OUT) :: hdferr            ! Error code:
                                           ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: aapl_id
                                           ! Attribute access property list
END SUBROUTINE h5aopen_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Aopen\_by\_idx

**Signature:**

```
herr_t H5Aopen_by_idx(hid_t loc_id, const char *obj_name, H5_index_t idx_type,
H5_iter_order_t order, hsize_t n, hid_t aapl_id, hid_t lapl_id)
```

**Purpose:**

**Description:**

H5Aopen\_by\_idx opens an existing attribute that is attached to an object specified by location and name, *loc\_id* and *obj\_name*, respectively. If *loc\_id* fully specifies the object to which the attribute is attached, *obj\_name* should be '.' (a dot).

The attribute is identified by an index type, an index traversal order, and a position in the index, *idx\_type*, *order* and *n*, respectively. These parameters and their valid values are discussed in the description of H5Aiterate2.

The attribute access property list, *aapl\_id*, is currently unused and should currently be H5P\_DEFAULT.

The link access property list, *lapl\_id*, may provide information regarding the properties of links required to access the object, *obj\_name*. See “Link Access Properties” in the H5P APIs.

This function, H5Aopen, or H5Aopen\_by\_name must be called before an attribute can be accessed for any further purpose, including reading, writing, or any modification.

The attribute identifier returned by this function must be released with H5Aclose or resource leaks will develop.

**Parameters:**

<i>hid_t</i> loc_id	IN: Location of object to which attribute is attached
<i>const char</i> *obj_name	IN: Name of object to which attribute is attached, relative to location
<i>H5_index_t</i> idx_type	IN: Type of index
<i>H5_iter_order_t</i> order	IN: Index traversal order
<i>hsize_t</i> n	IN: Attribute's position in index
<i>hid_t</i> aapl_id	IN: Attribute access property list
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns an attribute identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aopen\_by\_idx\_f

```
SUBROUTINE h5aopen_by_idx_f(loc_id, obj_name, idx_type, order, n, attr_id, &
    hdferr, aapl_id, lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id
                                ! Object identifier
    CHARACTER(LEN=*), INTENT(IN) :: obj_name
                                ! Name of object to which attribute is attached
    INTEGER, INTENT(IN) :: idx_type
                                ! Type of index; Possible values are:
                                !   H5_INDEX_UNKNOWN_F - Unknown index type
                                !   H5_INDEX_NAME_F - Index on names
                                !   H5_INDEX_CRT_ORDER_F - Index on creation order
                                !   H5_INDEX_N_F - Number of indices defined
```

```

INTEGER, INTENT(IN) :: order
! Order in which to iterate over index:
!   H5_ITER_UNKNOWN_F - Unknown order
!   H5_ITER_INC_F     - Increasing order
!   H5_ITER_DEC_F     - Decreasing order
!   H5_ITER_NATIVE_F  - No particular order,
!                       whatever is fastest

INTEGER(HSIZE_T), INTENT(IN) :: n
! Attribute's position in index
INTEGER(HID_T), INTENT(OUT) :: attr_id
! Attribute identifier
INTEGER, INTENT(OUT) :: hdferr
! Error code:
!   0 on success and -1 on failure
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: aapl_id
! Attribute access property list
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
! Link access property list
END SUBROUTINE h5aopen_by_idx_f

```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Aopen\_by\_name

**Signature:**

```
herr_t H5Aopen_by_name( hid_t loc_id, const char *obj_name, const char *attr_name, hid_t
aapl_id, hid_t lapl_id )
```

**Purpose:**

Opens an attribute for an object by object name and attribute name.

**Description:**

H5Aopen\_by\_name opens an existing attribute, attr\_name, that is attached to an object specified by location and name, loc\_id and obj\_name, respectively.

loc\_id specifies a location from which the target object can be located and obj\_name is an object name relative to loc\_id. If loc\_id fully specifies the object to which the attribute is attached, obj\_name should be '.' (a dot).

The attribute access property list, aapl\_id, is currently unused and should currently be H5P\_DEFAULT.

The link access property list, lapl\_id, may provide information regarding the properties of links required to access the object, obj\_name. See “Link Access Properties” in the H5P APIs.

This function, H5Aopen, or H5Aopen\_by\_idx must be called before an attribute can be accessed for any further purpose, including reading, writing, or any modification.

The attribute identifier returned by this function must be released with H5Aclose or resource leaks will develop.

**Parameters:**

hid_t loc_id	IN: Location from which to find object to which attribute is attached
const char *obj_name	IN: Name of object to which attribute is attached, relative to loc_id
const char *attr_name	IN: Name of attribute to open
hid_t aapl_id	IN: Attribute access property list (Currently unused; should be passed in as H5P_DEFAULT.)
hid_t lapl_id	IN: Link access property list

**Returns:**

Returns an attribute identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:**

```
SUBROUTINE h5aopen_by_name_f(loc_id, obj_name, attr_name, attr_id, hdferr, &
    aapl_id, lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id
                                ! Location identifier
    CHARACTER(LEN=*), INTENT(IN) :: obj_name
                                ! Object name either relative to loc_id,
                                ! absolute from file's root group, or '.'
    CHARACTER(LEN=*), INTENT(IN) :: attr_name
                                ! Attribute name
    INTEGER(HID_T), INTENT(OUT) :: attr_id
                                ! Attribute identifier
    INTEGER, INTENT(OUT) :: hdferr ! Error code:
                                ! 0 on success and -1 on failure
    INTEGER(HID_T), OPTIONAL, INTENT(IN) :: aapl_id
                                ! Attribute access property list
```



```
                                ! (Currently unused; set to H5P_DEFAULT_F)
    INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                ! Link access property list identifier
END SUBROUTINE
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Aopen\_idx

**Signature:**

*hid\_t* H5Aopen\_idx(*hid\_t* loc\_id, *unsigned int* idx)

**Purpose:**

Opens the attribute specified by its index.

**Description:**

H5Aopen\_idx opens an attribute which is attached to the object specified with loc\_id. The location object may be either a group, dataset, or named datatype, all of which may have any sort of attribute. The attribute specified by the index, idx, indicates the attribute to access. The value of idx is a 0-based, non-negative integer. The attribute identifier returned from this function must be released with H5Aclose or resource leaks will develop.

**Parameters:**

*hid\_t* loc\_id           IN: Identifier of the group, dataset, or named datatype attribute to be attached to.  
*unsigned int* idx       IN: Index of the attribute to open.

**Returns:**

Returns attribute identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aopen\_idx\_f

```
SUBROUTINE h5aopen_idx_f(obj_id, index, attr_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id      ! Object identifier
  INTEGER, INTENT(IN) :: index              ! Attribute index
  INTEGER(HID_T), INTENT(OUT) :: attr_id    ! Attribute identifier
  INTEGER, INTENT(OUT) :: hdferr            ! Error code:
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5aopen_idx_f
```

**Name:** H5Aopen\_name

**Signature:**

```
hid_t H5Aopen_name(hid_t loc_id, const char *name )
```

**Purpose:**

Opens an attribute specified by name.

**Description:**

H5Aopen\_name opens an attribute specified by its name, name, which is attached to the object specified with loc\_id. The location object may be either a group, dataset, or named datatype, which may have any sort of attribute. The attribute identifier returned from this function must be released with H5Aclose or resource leaks will develop.

**Parameters:**

<i>hid_t</i> loc_id	IN: Identifier of a group, dataset, or named datatype that attribute is attached to.
<i>const char</i> *name	IN: Attribute name.

**Returns:**

Returns attribute identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aopen\_name\_f

```
SUBROUTINE h5aopen_name_f(obj_id, name, attr_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id      ! Object identifier
  CHARACTER(LEN=*), INTENT(IN) :: name      ! Attribute name
  INTEGER(HID_T), INTENT(OUT) :: attr_id     ! Attribute identifier
  INTEGER, INTENT(OUT) :: hdferr             ! Error code:
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5aopen_name_f
```

**Name:** H5Aread

**Signature:**

```
herr_t H5Aread(hid_t attr_id, hid_t mem_type_id, void *buf )
```

**Purpose:**

Reads an attribute.

**Description:**

H5Aread reads an attribute, specified with `attr_id`. The attribute's memory datatype is specified with `mem_type_id`. The entire attribute is read into `buf` from the file.

Datatype conversion takes place at the time of a read or write and is automatic. See the Data Conversion section of *The Data Type Interface (H5T)* in the *HDF5 User's Guide* for a discussion of data conversion, including the range of conversions currently supported by the HDF5 libraries.

**Parameters:**

<code>hid_t attr_id</code>	IN: Identifier of an attribute to read.
<code>hid_t mem_type_id</code>	IN: Identifier of the attribute datatype (in memory).
<code>void *buf</code>	OUT: Buffer for data to be read.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5aread\_f

```
SUBROUTINE h5aread_f(attr_id, memtype_id,  buf, dims, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: attr_id      ! Attribute identifier
  INTEGER(HID_T), INTENT(IN) :: memtype_id   ! Attribute datatype
                                           ! identifier (in memory)
  TYPE, INTENT(INOUT)  :: buf                ! Data buffer; may be a scalar or
                                           ! an array
  DIMENSION(*), INTEGER(HSIZE_T), INTENT(IN) :: dims
                                           ! Array to hold corresponding
                                           ! dimension sizes of data buffer buf;
                                           ! dim(k) has value of the
                                           ! k-th dimension of buffer buf;
                                           ! values are ignored if buf is a
                                           ! scalar
  INTEGER, INTENT(OUT) :: hdferr              ! Error code:
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5aread_f
```

**History:**

Release	Fortran90
1.4.2	The <code>dims</code> parameter was added in this release.

**Name:** H5Arename

**Signature:**

```
herr_t H5Arename(hid_t loc_id, char *old_attr_name, char *new_attr_name)
```

**Purpose:**

Renames an attribute.

**Description:**

H5Arename changes the name of the attribute located at `loc_id`.

The old name, `old_attr_name`, is changed to the new name, `new_attr_name`.

**Parameters:**

<i>hid_t</i> loc_id	IN: Location of the attribute.
<i>char</i> *old_attr_name	IN: Name of the attribute to be changed.
<i>char</i> *new_attr_name	IN: New name for the attribute.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5arename\_f

```
SUBROUTINE h5arename_f(loc_id, old_attr_name, new_attr_name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id           ! Object identifier
  CHARACTER(LEN=*), INTENT(IN) :: old_attr_name ! Prior attribute name
  CHARACTER(LEN=*), INTENT(IN) :: new_attr_name ! New attribute name
  INTEGER, INTENT(OUT) :: hdferr                 ! Error code:
                                                ! 0 on success, -1 on failure
END SUBROUTINE h5arename_f
```

**Name:** H5Arename\_by\_name

**Signature:**

```
herr_t H5Arename_by_name(hid_t loc_id, const char *obj_name, const char
*old_attr_name, const char *new_attr_name, hid_t lapl_id)
```

**Purpose:**

Renames an attribute.

**Description:**

H5Arename\_by\_name changes the name of attribute that is attached to the object specified by loc\_id and obj\_name. The attribute named old\_attr\_name is renamed new\_attr\_name.

The link access property list, lapl\_id, may provide information regarding the properties of links required to access the object, obj\_name. See “Link Access Properties” in the H5P APIs.

**Parameters:**

<i>hid_t</i> loc_id	IN: Location or object identifier; may be dataset or group
<i>const char</i> *obj_name	IN: Name of object, relative to location, whose attribute is to be renamed
<i>const char</i> *old_attr_name	IN: Prior attribute name
<i>const char</i> *new_attr_name	IN: New attribute name
<i>hid_t</i> lapl_id	IN: Link access property list identifier

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5arename\_by\_name\_f

```
SUBROUTINE h5arename_by_name_f(loc_id, obj_name, old_attr_name, new_attr_name, &
    hdferr, lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id ! Object identifier
    CHARACTER(LEN=*), INTENT(IN) :: obj_name
                                   ! Name of object, relative to location,
                                   ! whose attribute is to be renamed
    CHARACTER(LEN=*), INTENT(IN) :: old_attr_name
                                   ! Prior attribute name
    CHARACTER(LEN=*), INTENT(IN) :: new_attr_name
                                   ! New attribute name
    INTEGER, INTENT(OUT) :: hdferr ! Error code:
                                   ! 0 on success and -1 on failure
    INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                   ! Link access property list identifier
END SUBROUTINE h5arename_by_name_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Awrite

**Signature:**

```
herr_t H5Awrite(hid_t attr_id, hid_t mem_type_id, const void *buf )
```

**Purpose:**

Writes data to an attribute.

**Description:**

H5Awrite writes an attribute, specified with `attr_id`. The attribute's memory datatype is specified with `mem_type_id`. The entire attribute is written from `buf` to the file.

Datatype conversion takes place at the time of a read or write and is automatic. See the Data Conversion section of *The Data Type Interface (H5T)* in the *HDF5 User's Guide* for a discussion of data conversion, including the range of conversions currently supported by the HDF5 libraries.

**Parameters:**

<code>hid_t attr_id</code>	IN: Identifier of an attribute to write.
<code>hid_t mem_type_id</code>	IN: Identifier of the attribute datatype (in memory).
<code>const void *buf</code>	IN: Data to be written.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5awrite\_f

```
SUBROUTINE h5awrite_f(attr_id, memtype_id, buf, dims, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: attr_id      ! Attribute identifier
  INTEGER(HID_T), INTENT(IN) :: memtype_id   ! Attribute datatype
                                              ! identifier (in memory)
  TYPE, INTENT(IN) :: buf                    ! Data buffer; may be a scalar or
                                              ! an array
  DIMENSION(*), INTEGER(HSIZE_T), INTENT(IN) :: dims
                                              ! Array to hold corresponding
                                              ! dimension sizes of data buffer buf;
                                              ! dim(k) has value of the k-th
                                              ! dimension of buffer buf;
                                              ! values are ignored if buf is
                                              ! a scalar
  INTEGER, INTENT(OUT) :: hdferr              ! Error code:
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5awrite_f
```

**History:**

Release	Fortran90
---------	-----------

1.4.2	The <code>dims</code> parameter was added in this release.
-------	--





## H5D: Datasets Interface

### Dataset Object API Functions

These functions create and manipulate dataset objects, and set and retrieve their constant or persistent properties.

#### The C Interfaces:

- |                  |                       |                        |
|------------------|-----------------------|------------------------|
| • H5Dcreate      | • H5Dget_space        | • H5Dvlen_get_buf_size |
| • H5Dcreate1 *   | • H5Dget_space_status | • H5Dvlen_reclaim      |
| • H5Dcreate2     | • H5Dget_type         | • H5Dread              |
| • H5Dcreate_anon | • H5Dget_create_plist | • H5Dwrite             |
| • H5Dopen        | • H5Dget_access_plist | • H5Diterate           |
| • H5Dopen1 *     | • H5Dget_offset       | • H5Dextend *          |
| • H5Dopen2       | • H5Dget_storage_size | • H5Dset_extent        |
| • H5Dclose       |                       | • H5Dfill              |

*\* Use of these functions is deprecated in Release 1.8.0.*

#### Alphabetical Listing

- |                  |                       |                        |
|------------------|-----------------------|------------------------|
| • H5Dclose       | • H5Dget_access_plist | • H5Dopen              |
| • H5Dcreate      | • H5Dget_create_plist | • H5Dopen1 *           |
| • H5Dcreate1 *   | • H5Dget_offset       | • H5Dopen2             |
| • H5Dcreate2     | • H5Dget_space        | • H5Dread              |
| • H5Dcreate_anon | • H5Dget_space_status | • H5Dset_extent        |
| • H5Dextend *    | • H5Dget_storage_size | • H5Dvlen_get_buf_size |
| • H5Dfill        | • H5Dget_type         | • H5Dvlen_reclaim      |
|                  | • H5Diterate          | • H5Dwrite             |

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- |                         |                         |                 |
|-------------------------|-------------------------|-----------------|
| • h5dclose_f            | • h5dget_type_f         | • h5dread_f     |
| • h5dcreate_f           | • h5dget_create_plist_f | • h5dread_vl_f  |
| • h5dcreate_anon_f      | • h5dget_offset_f       | • h5dwrite_f    |
| • h5dopen_f             | • h5dget_storage_size_f | • h5dwrite_vl_f |
| • h5dget_space_f        | • h5dvlen_get_max_len_f | • h5dextend_f   |
| • h5dget_space_status_f |                         | • h5dfill_f     |



**Name:** H5Dclose

**Signature:**

*herr\_t* H5Dclose(*hid\_t* dataset\_id)

**Purpose:**

Closes the specified dataset.

**Description:**

H5Dclose ends access to a dataset specified by `dataset_id` and releases resources used by it. Further use of the dataset identifier is illegal in calls to the dataset API.

**Parameters:**

*hid\_t* dataset\_id      IN: Identifier of the dataset to close access to.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5dclose\_f

```
SUBROUTINE h5dclose_f(dset_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dset_id ! Dataset identifier
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5dclose_f
```

**Name:** H5Dcreate

**Signature:**

```
hid_t H5Dcreate(hid_t loc_id, const char *name, hid_t type_id, hid_t space_id, hid_t
dcpl_id)
hid_t H5Dcreate(hid_t loc_id, const char *name, hid_t dtype_id, hid_t space_id, hid_t
lcpl_id, hid_t dcpl_id, hid_t dapl_id)
```

**Purpose:**

Creates a new dataset and links it to a location in the file.

**Description:**

H5Dcreate is a macro that is mapped to either H5Dcreate1 or H5Dcreate2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Dcreate is mapped to the most recent version of the function, currently H5Dcreate2. If the library and/or application is compiled for Release 1.6 emulation, H5Dcreate will be mapped to H5Dcreate1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Dcreate mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Dcreate2
Enable deprecated symbols	H5Dcreate2
Disable deprecated symbols	H5Dcreate2
Emulate Release 1.6 interface	H5Dcreate1
<hr/>	
<u>Function-level macros</u>	
H5Dcreate_vers = 2	H5Dcreate2
H5Dcreate_vers = 1	H5Dcreate1

**Fortran90 Interface:** h5dcreate\_f

```
SUBROUTINE h5dcreate_f(loc_id, name, type_id, space_id, dset_id, &
hdferr, dcpl_id, lcpl_id, dapl_id)
```

```
IMPLICIT NONE
INTEGER(HID_T), INTENT(IN) :: loc_id    ! File or group identifier
CHARACTER(LEN=*), INTENT(IN) :: name    ! Name of the dataset
INTEGER(HID_T), INTENT(IN) :: type_id   ! Datatype identifier
INTEGER(HID_T), INTENT(IN) :: space_id  ! Dataspace identifier
INTEGER(HID_T), INTENT(OUT) :: dset_id  ! Dataset identifier
INTEGER, INTENT(OUT) :: hdferr          ! Error code
```

```

! 0 on success and -1 on failure
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: dcpl_id
! Dataset creation property list
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lcpl_id
! Link creation property list
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: dapl_id
! Dataset access property list
END SUBROUTINE h5dcreate_f

```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	<p>The function H5Dcreate renamed to H5Dcreate1 and deprecated in this release.</p> <p>The macro H5Dcreate and the function H5Dcreate2 introduced in this release.</p>

*Last modified: 18 May 2009*

**Name:** H5Dcreate1

**Signature:**

```
hid_t H5Dcreate1( hid_t loc_id, const char *name, hid_t type_id, hid_t space_id, hid_t
dcpl_id )
```

**Purpose:**

Creates a dataset at the specified location.

**Notice:**

*This function is deprecated in favor of the function H5Dcreate2 or the macro H5Dcreate.*

**Description:**

H5Dcreate1 creates a data set with a name, name, in the file or in the group specified by the identifier loc\_id.

name can be a relative path based at loc\_id or an absolute path from the root of the file. If any of the groups specified in that path do not already exist, the dataset must be created with H5Dcreate\_anon and linked into the file structure with H5Lcreate\_hard.

The dataset's datatype and dataspace are specified by type\_id and space\_id, respectively. These are the datatype and dataspace of the dataset as it will exist in the file, which may differ from the datatype and dataspace in application memory.

Names within a group are unique: H5Dcreate1 will return an error if a link with the name specified in name already exists at the location specified in loc\_id.

As is the case for any object in a group, the length of a dataset name is not limited.

create\_plist\_id is an H5P\_DATASET\_CREATE property list created with H5Pcreate1 and initialized with various property list functions described in "H5P: Property List Interface."

H5Dcreate and H5Dcreate\_anon return an error if the dataset's datatype includes a variable-length (VL) datatype and the fill value is undefined, i.e., set to NULL in the dataset creation property list. Such a VL datatype may be directly included, indirectly included as part of a compound or array datatype, or indirectly included as part of a nested compound or array datatype.

H5Dcreate and H5Dcreate\_anon return a dataset identifier for success or a negative value for failure. The dataset identifier should eventually be closed by calling H5Dclose to release resources it uses.

See H5Dcreate\_anon for discussion of the differences between H5Dcreate and H5Dcreate\_anon.

#### **Fill values and space allocation:**

The HDF5 library provides flexible means of specifying a fill value, of specifying when space will be allocated for a dataset, and of specifying when fill values will be written to a dataset. For further information on these topics, see the document *Fill Value and Dataset Storage Allocation Issues in HDF5* and the descriptions of the following HDF5 functions in this *HDF5 Reference Manual*:

H5Dfill	H5Pset_fill_time
H5Pset_fill_value	H5Pget_fill_time

H5Pget_fill_value	H5Pset_alloc_time
H5Pfill_value_defined	H5Pget_alloc_time

This information is also included in the “HDF5 Datasets” chapter of the new *HDF5 User's Guide*, which is being prepared for release.

**Note:**

H5Dcreate and H5Dcreate\_anon can fail if there has been an error in setting up an element of the dataset creation property list. In such cases, each item in the property list must be examined to ensure that the setup satisfies all required conditions. This problem is most likely to occur with the use of filters.

For example, either function will fail without a meaningful explanation if the following conditions exist simultaneously:

- ◊ SZIP compression is being used on the dataset.
- ◊ The SZIP parameter `pixels_per_block` is set to an inappropriate value.

In such a case, one would refer to the description of `H5Pset_szip`, looking for any conditions or requirements that might affect the local computing environment.

**Parameters:**

<code>hid_t loc_id</code>	IN: Identifier of the file or group within which to create the dataset.
<code>const char *name</code>	IN: The name of the dataset to create.
<code>hid_t type_id</code>	IN: Identifier of the datatype to use when creating the dataset.
<code>hid_t space_id</code>	IN: Identifier of the dataspace to use when creating the dataset.
<code>hid_t create_plist_id</code>	IN: Identifier of the set creation property list.

**Returns:**

Returns a dataset identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Dcreate.

**History:**

Release	C
1.8.0	Function H5Dcreate renamed to H5Dcreate1 and deprecated in this release.

**Name:** H5Dcreate2

**Signature:**

```
hid_t H5Dcreate2( hid_t loc_id, const char *name, hid_t dtype_id, hid_t space_id, hid_t
lcpl_id, hid_t dcpl_id, hid_t dapl_id )
```

**Purpose:**

Creates a new dataset and links it into the file.

**Description:**

H5Dcreate2 creates a new dataset named *name* at the location specified by *loc\_id*, and associates constant and initial persistent properties with that dataset, including *dtype\_id*, the datatype of each data element as stored in the file; *space\_id*, the dataspace of the dataset; and other initial properties as defined in the dataset creation property and access property lists, *dcpl\_id* and *dapl\_id*, respectively. Once created, the dataset is opened for access.

*loc\_id* may be a file identifier, or a group identifier within that file. *name* may be either an absolute path in the file or a relative path from *loc\_id* naming the dataset.

The link creation property list, *lcpl\_id*, governs creation of the link(s) by which the new dataset is accessed and the creation of any intermediate groups that may be missing.

The datatype and dataspace properties and the dataset creation and access property lists are attached to the dataset, so the caller may derive new datatypes, dataspaces, and creation and access properties from the old ones and reuse them in calls to create additional datasets.

Once created, the dataset is ready to receive raw data. Immediately attempting to read raw data from the dataset will probably return the fill value.

To conserve and release resources, the dataset should be closed when access is no longer required.

**Parameters:**

<i>hid_t</i> loc_id	IN: Location identifier
<i>const char</i> *name	IN: Dataset name
<i>hid_t</i> dtype_id	IN: Datatype identifier
<i>hid_t</i> space_id	IN: Dataspace identifier
<i>hid_t</i> lcpl_id	IN: Link creation property list
<i>hid_t</i> dcpl_id	IN: Dataset creation property list
<i>hid_t</i> dapl_id	IN: Dataset access property list

**Returns:**

Returns a dataset identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Dcreate.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.



*Last modified: 18 May 2009***Name:** H5Dcreate\_anon**Signature:**

```
hid_t H5Dcreate_anon( hid_t loc_id, hid_t type_id, hid_t space_id, hid_t dcpl_id, hid_t
                    dapl_id )
```

**Purpose:**

Creates a dataset in a file without linking it into the file structure.

**Description:**

H5Dcreate\_anon creates a dataset in the file specified by `loc_id`.

`loc_id` may be a file identifier or a group identifier within that file.

The dataset's datatype and dataspace are specified by `type_id` and `space_id`, respectively. These are the datatype and dataspace of the dataset as it will exist in the file, which may differ from the datatype and dataspace in application memory.

Dataset creation properties are specified in the dataset creation property list `dcpl_id`. Dataset access properties are specified in the dataset access property list `dapl_id`.

H5Dcreate\_anon returns a new dataset identifier. Using this identifier, the new dataset *must* be linked into the HDF5 file structure with H5Lcreate\_hard or it will be deleted from the file when the file is closed.

See H5Dcreate for further details and considerations on the use of H5Dcreate and H5Dcreate\_anon.

The differences between this function and H5Dcreate are as follows:

- ◊ H5Dcreate\_anon explicitly includes a dataset access property list. H5Dcreate always uses default dataset access properties.
- ◊ H5Dcreate\_anon neither provides the new dataset's name nor links it into the HDF5 file structure; those actions must be performed separately through a call to H5Lcreate\_hard, which offers greater control over linking.

**Parameters:**

<code>hid_t loc_id</code>	IN: Identifier of the file or group within which to create the dataset.
<code>hid_t type_id</code>	IN: Identifier of the datatype to use when creating the dataset.
<code>hid_t space_id</code>	IN: Identifier of the dataspace to use when creating the dataset.
<code>hid_t dcpl_id</code>	IN: Dataset creation property list identifier.
<code>hid_t dapl_id</code>	IN: Dataset access property list identifier.

**Returns:**

Returns a dataset identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:**

```
SUBROUTINE h5dcreate_anon_f(loc_id, type_id, space_id, dset_id, hdferr, &
                           dcpl_id, dapl_id)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id   ! File or group identifier.
  INTEGER(HID_T), INTENT(IN) :: type_id  ! Datatype identifier.
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier.
  INTEGER(HID_T), INTENT(OUT) :: dset_id ! Dataset identifier.
```

```
INTEGER, INTENT(OUT) :: hdferr      ! Error code.  
                                   ! 0 on success and -1 on failure  
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: dcpl_id  
                                   ! Dataset creation property list  
                                   ! identifier.  
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: dapl_id  
                                   ! Dataset access property list  
                                   ! identifier.  
END SUBROUTINE h5dcreate_anon_f
```

**Name:** H5Dextend

**Signature:**

```
herr_t H5Dextend(hid_t dataset_id, const hsize_t * size)
```

**Purpose:**

Extends a dataset.

**Notice:**

*This function is deprecated in favor of the function H5Dset\_extent.*

**Description:**

H5Dextend verifies that the dataset is at least of size `size`, extending it if necessary. The dimensionality of `size` is the same as that of the dataspace of the dataset being changed.

This function can be applied to the following datasets:

- ◊ Any dataset with unlimited dimensions
- ◊ A dataset with fixed dimensions if the current dimension sizes are less than the maximum sizes set with `maxdims` (see `H5Screate_simple`)

Space on disk is immediately allocated for the new dataset extent if the dataset's space allocation time is set to `H5D_ALLOC_TIME_EARLY`. Fill values will be written to the dataset if the dataset's fill time is set to `H5D_FILL_TIME_IFSET` or `H5D_FILL_TIME_ALLOC`. (See `H5Pset_fill_time` and `H5Pset_alloc_time`.)

This function ensures that the dataset dimensions are of at least the sizes specified in `size`. The function `H5Dset_extent` must be used if the dataset dimension sizes are to be reduced.

**Parameters:**

<code>hid_t dataset_id</code>	IN: Identifier of the dataset.
<code>const hsize_t * size</code>	IN: Array containing the new magnitude of each dimension.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** `h5dextend_f`

```
SUBROUTINE h5dextend_f(dataset_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dataset_id    ! Dataset identifier
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(IN) :: size
                                              ! Array containing
                                              ! dimensions' sizes
  INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5dextend_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function deprecated in this release.

**Name:** H5Dfill

**Signature:**

```
herr_t H5Dfill( const void *fill, hid_t fill_type_id, void *buf, hid_t buf_type_id, hid_t
space_id )
```

**Purpose:**

Fills dataspace elements with a fill value in a memory buffer.

**Description:**

H5Dfill explicitly fills the dataspace selection in memory, *space\_id*, with the fill value specified in *fill*. If *fill* is NULL, a fill value of 0 (zero) is used.

*fill\_type\_id* specifies the datatype of the fill value.

*buf* specifies the buffer in which the dataspace elements will be written.

*buf\_type\_id* specifies the datatype of those data elements.

Note that if the fill value datatype differs from the memory buffer datatype, the fill value will be converted to the memory buffer datatype before filling the selection.

**Note:**

Applications sometimes write data only to portions of an allocated dataset. It is often useful in such cases to fill the unused space with a known fill value. See H5Pset\_fill\_value for further discussion. Other related functions include H5Pget\_fill\_value, H5Pfill\_value\_defined, H5Pset\_fill\_time, H5Pget\_fill\_time, H5Dcreate, and H5Dcreate\_anon.

**Parameters:**

<i>const void</i> *fill	IN: Pointer to the fill value to be used.
<i>hid_t</i> fill_type_id	IN: Fill value datatype identifier.
<i>void</i> *buf	IN/OUT: Pointer to the memory buffer containing the selection to be filled.
<i>hid_t</i> buf_type_id	IN: Datatype of dataspace elements to be filled.
<i>hid_t</i> space_id	IN: Dataspace describing memory buffer and containing the selection to be filled.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5dfill\_f

```
SUBROUTINE h5dfill_f(fill_value, space_id, buf, hdferr)
  IMPLICIT NONE
  TYPE, INTENET(IN) :: fill_value           ! Fill value; may be have one of the
                                              ! following types:
                                              ! INTEGER, REAL, DOUBLE PRECISION,
                                              ! CHARACTER
  INTEGER(HID_T), INTENT(IN) :: space_id    ! Memory dataspace selection identifier
  TYPE, DIMENSION(*) :: buf                ! Memory buffer to fill in; must have
                                              ! the same datatype as fill value
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5dfill_f
```

*Last modified: 8 May 2009***Name:** H5Dget\_access\_plist**Signature:**`hid_t H5Dget_access_plist( hid_t dataset_id )`**Purpose:**

Returns the dataset access property list associated with a dataset.

**Description:**

H5Dget\_access\_plist returns a copy of the dataset access property list used to open the specified dataset. Modifications to the returned property list will have no effect on the dataset it was retrieved from.

The chunk cache parameters in the returned property lists will be those used by the dataset. If the properties in the file access property list were used to determine the dataset's chunk cache configuration, then those properties will be present in the returned dataset access property list. If the dataset does not use a chunked layout, then the chunk cache properties will be set to the default. The chunk cache properties in the returned list are considered to be “set”, and any use of this list will override the corresponding properties in the file’s file access property list.

All link access properties in the returned list will be set to the default values.

**Parameters:**

`hid_t dataset_id`      IN: Identifier of the dataset to get access property list of.

**Returns:**

Returns a dataset access property list identifier if successful; otherwise returns a negative value.

**Example Usage:**

The following code retrieves the dataset access property list used to open the dataset `dataset_id` into `dapl_id`:

```
dapl_id = H5Dget_access_plist(dataset_id);
```

**See Also:**

“Dataset Access Properties” in the “H5P: Property List Interface” chapter of the *HDF5 Reference Manual*

**History:**

Release	Change
1.8.3	C function introduced in this release.

**Name:** H5Dget\_create\_plist

**Signature:**

*hid\_t* H5Dget\_create\_plist(*hid\_t* dataset\_id)

**Purpose:**

Returns an identifier for a copy of the dataset creation property list for a dataset.

**Description:**

H5Dget\_create\_plist returns an identifier for a copy of the dataset creation property list associated with the dataset specified by dataset\_id.

The creation property list identifier should be released with H5Pclose.

**Parameters:**

*hid\_t* dataset\_id      IN: Identifier of the dataset to query.

**Returns:**

Returns a dataset creation property list identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5dget\_create\_plist\_f

```
SUBROUTINE h5dget_create_plist_f(dataset_id, creation_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dataset_id      ! Dataset identifier
  INTEGER(HID_T), INTENT(OUT) :: creation_id    ! Dataset creation
                                                ! property list identifier
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                                ! 0 on success and -1 on failure
END SUBROUTINE h5dget_create_plist_f
```

**Name:** H5Dget\_offset

**Signature:**

*haddr\_t* H5Dget\_offset(*hid\_t* dset\_id)

**Purpose:**

Returns dataset address in file.

**Description:**

H5Dget\_offset returns the address in the file of the dataset dset\_id. That address is expressed as the offset in bytes from the beginning of the file.

**Parameters:**

*hid\_t* dset\_id      Dataset identifier.

**Returns:**

Returns the offset in bytes; otherwise returns HADDR\_UNDEF, a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.6.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Dget\_space

**Signature:**

*hid\_t* H5Dget\_space(*hid\_t* dataset\_id)

**Purpose:**

Returns an identifier for a copy of the dataspace for a dataset.

**Description:**

H5Dget\_space returns an identifier for a copy of the dataspace for a dataset. The dataspace identifier should be released with the H5Sclose function.

**Parameters:**

*hid\_t* dataset\_id      IN: Identifier of the dataset to query.

**Returns:**

Returns a dataspace identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5dget\_space\_f

```
SUBROUTINE h5dget_space_f(dataset_id, dataspace_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dataset_id      ! Dataset identifier
  INTEGER(HID_T), INTENT(OUT) :: dataspace_id    ! Dataspace identifier
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5dget_space_f
```



**Name:** H5Dget\_space\_status

**Signature:**

```
herr_t H5Dget_space_status(hid_t dset_id, H5D_space_status_t *status)
```

**Purpose:**

Determines whether space has been allocated for a dataset.

**Description:**

H5Dget\_space\_status determines whether space has been allocated for the dataset dset\_id.

Space allocation status is returned in status, which will have one of the following values:

H5D_SPACE_STATUS_NOT_ALLOCATED	Space has not been allocated for this dataset.
H5D_SPACE_STATUS_ALLOCATED	Space has been allocated for this dataset.
H5D_SPACE_STATUS_PART_ALLOCATED	Space has been partially allocated for this dataset. (Used only for datasets with chunked storage.)

**Parameters:**

<i>hid_t</i> dset_id	IN: Identifier of the dataset to query.
<i>H5D_space_status_t</i> *status	OUT: Space allocation status.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5dget\_space\_status\_f

```
SUBROUTINE h5dget_space_status_f(dset_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dset_id  ! Dataset identifier
  INTEGER, INTENET(OUT)      :: flag     ! Status flag ; possible values:
                                          ! H5D_SPACE_STS_ERROR_F
                                          ! H5D_SPACE_STS_NOT_ALLOCATED_F
                                          ! H5D_SPACE_STS_PART_ALLOCATED_F
                                          ! H5D_SPACE_STS_ALLOCATED_F
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5dget_space_status_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Dget\_storage\_size

**Signature:**

*hsize\_t* H5Dget\_storage\_size(*hid\_t* dataset\_id)

**Purpose:**

Returns the amount of storage required for a dataset.

**Description:**

H5Dget\_storage\_size returns the amount of storage that is required for the specified dataset, dataset\_id. For chunked datasets, this is the number of allocated chunks times the chunk size. The return value may be zero if no data has been stored.

**Parameters:**

*hid\_t* dataset\_id      IN: Identifier of the dataset to query.

**Returns:**

Returns the amount of storage space allocated for the dataset, not counting meta data; otherwise returns 0 (zero).

**Fortran90 Interface:** h5dget\_storage\_size\_f

```
SUBROUTINE h5dget_storage_size_f(dset_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dset_id ! Dataset identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: size ! Amount of storage required
                                         ! for dataset
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5dget_storage_size_f
```

**History:**

Release	Fortran90
1.4.5	Function introduced in this release.

**Name:** H5Dget\_type

**Signature:**

*hid\_t* H5Dget\_type(*hid\_t* dataset\_id)

**Purpose:**

Returns an identifier for a copy of the datatype for a dataset.

**Description:**

H5Dget\_type returns an identifier for a copy of the datatype for a dataset. The datatype should be released with the H5Tclose function.

If a dataset has a named datatype, then an identifier to the opened datatype is returned. Otherwise, the returned datatype is read-only. If atomization of the datatype fails, then the datatype is closed.

**Parameters:**

*hid\_t* dataset\_id      IN: Identifier of the dataset to query.

**Returns:**

Returns a datatype identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5dget\_type\_f

```
SUBROUTINE h5dget_type_f(dataset_id, datatype_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dataset_id      ! Dataset identifier
  INTEGER(HID_T), INTENT(OUT) :: datatype_id    ! Datatype identifier
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5dget_type_f
```

**Name:** H5Diterate

**Signature:**

```
herr_t H5Diterate( void *buf, hid_t type_id, hid_t space_id, H5D_operator_t operator,
                  void *operator_data )
```

**Purpose:**

Iterates over all selected elements in a dataspace.

**Description:**

H5Diterate iterates over all the data elements in the memory buffer *buf*, executing the callback function *operator* once for each such data element.

The prototype of the callback function *operator* is as follows (as defined in the source code file *H5Lpublic.h*):

```
herr_t (*H5D_operator_t)(void elem, hid_t type_id, unsigned ndim,
                        const hsize_t *point, void *operator_data)
```

The parameters of this callback function have the following values or meanings:

<i>void</i> *elem	IN/OUT: Pointer to the memory buffer containing the current data element
<i>hid_t</i> type_id	IN: Datatype identifier for the elements stored in <i>elem</i>
<i>unsigned</i> ndim	IN: Number of dimensions for the <i>point</i> array
<i>const</i> <i>hsize_t</i> *point	IN: Array containing the location of the element within the original dataspace
<i>void</i> *operator_data	IN/OUT: Pointer to any user-defined data associated with the operation

The possible return values from the callback function, and the effect of each, are as follows:

- ◊ Zero causes the iterator to continue, returning zero when all data elements have been processed.
- ◊ A positive value causes the iterator to immediately return that positive value, indicating short-circuit success.
- ◊ A negative value causes the iterator to immediately return that value, indicating failure.

The H5Diterate *operator\_data* parameter is a user-defined pointer to the data required to process dataset elements in the course of the iteration. If *operator* needs to pass data back to the application, such data can be returned in this same buffer. This pointer is passed back to each step of the iteration in the *operator* callback function's *operator\_data* parameter.

Unlike other HDF5 iterators, this iteration operation cannot be restarted at the point of exit; a second H5Diterate call will always restart at the beginning.

**Parameters:**

<code>void *buf</code>	IN/OUT: Pointer to the buffer in memory containing the elements to iterate over
<code>hid_t type_id</code>	IN: Datatype identifier for the elements stored in <code>buf</code>
<code>hid_t space_id</code>	IN: Dataspace identifier for <code>buf</code>
<code>H5D_operator_t operator</code>	IN: Function pointer to the routine to be called for each element in <code>buf</code> iterated over
<code>void *operator_data</code>	IN/OUT: Pointer to any user-defined data associated with the operation

**Returns:**

Returns the return value of the last operator if it was non-zero, or zero if all elements have been processed. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.4	The following changes occurred in the <code>H5D_operator_t</code> function in this release: <code>ndim</code> parameter type was changed to <i>unsigned</i> <code>point</code> parameter type was changed to <i>const hsize_t</i>

**Name:** H5Dopen

**Signature:**

```
hid_t H5Dopen( hid_t loc_id, const char *name )
hid_t H5Dopen( hid_t loc_id, const char *name, hid_t dapl_id )
```

**Purpose:**

Opens an existing dataset.

**Description:**

H5Dopen is a macro that is mapped to either H5Dopen1 or H5Dopen2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Dopen is mapped to the most recent version of the function, currently H5Dopen2. If the library and/or application is compiled for Release 1.6 emulation, H5Dopen will be mapped to H5Dopen1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Dopen mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Dopen2
Enable deprecated symbols	H5Dopen2
Disable deprecated symbols	H5Dopen2
Emulate Release 1.6 interface	H5Dopen1
<hr/>	
<u>Function-level macros</u>	
H5Dopen_vers = 2	H5Dopen2
H5Dopen_vers = 1	H5Dopen1

**Fortran90 Interface:** h5dopen\_f

```
SUBROUTINE h5dopen_f(loc_id, name, dset_id, hdferr, dapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id    ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name    ! Name of the dataset
  INTEGER(HID_T), INTENT(OUT) :: dset_id ! Dataset identifier
  INTEGER, INTENT(OUT) :: hdferr          ! Error code:
                                          ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: dapl_id
                                          ! Dataset access property list
END SUBROUTINE h5dopen_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	The function <code>H5Dopen</code> renamed to <code>H5Dopen1</code> and deprecated in this release. The macro <code>H5Dopen</code> and the function <code>H5Dopen2</code> introduced in this release.

**Name:** H5Dopen1

**Signature:**

*hid\_t* H5Dopen1( *hid\_t* loc\_id, *const char* \*name )

**Purpose:**

Opens an existing dataset.

**Notice:**

*This function is deprecated in favor of the function H5Dopen2 or the macro H5Dopen.*

**Description:**

H5Dopen1 opens an existing dataset for access in the file or group specified in loc\_id. name is a dataset name and is used to identify the dataset in the file.

**Parameters:**

<i>hid_t</i> loc_id	IN: Identifier of the file or group within which the dataset to be accessed will be found.
<i>const char</i> *name	IN: The name of the dataset to access.

**Returns:**

Returns a dataset identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Dopen.

**History:**

Release	C
1.8.0	Function H5Dopen renamed to H5Dopen1 and deprecated in this release.



**Name:** H5Dopen2

**Signature:**

*hid\_t* H5Dopen2( *hid\_t* loc\_id, *const char* \*name, *hid\_t* dapl\_id )

**Purpose:**

Opens an existing dataset.

**Description:**

H5Dopen2 opens the existing dataset specified by a location identifier and name, loc\_id and name, respectively.

The dataset access property list, dapl\_id, provides information regarding access to the dataset.

To conserve and release resources, the dataset should be closed when access is no longer required.

**Parameters:**

*hid\_t* loc\_id        IN: Location identifier

*const char* \*name    IN: Dataset name

*hid\_t* dapl\_id       IN: Dataset access property list

**Returns:**

Returns a dataset identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Dopen.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Dread

**Signature:**

```
herr_t H5Dread(hid_t dataset_id, hid_t mem_type_id, hid_t mem_space_id, hid_t
file_space_id, hid_t xfer_plist_id, void *buf )
```

**Purpose:**

Reads raw data from a dataset into a buffer.

**Description:**

H5Dread reads a (partial) dataset, specified by its identifier `dataset_id`, from the file into an application memory buffer `buf`. Data transfer properties are defined by the argument `xfer_plist_id`. The memory datatype of the (partial) dataset is identified by the identifier `mem_type_id`. The part of the dataset to read is defined by `mem_space_id` and `file_space_id`.

`file_space_id` is used to specify only the selection within the file dataset's dataspace. Any dataspace specified in `file_space_id` is ignored by the library and the dataset's dataspace is always used. `file_space_id` can be the constant `H5S_ALL`, which indicates that the entire file dataspace, as defined by the current dimensions of the dataset, is to be selected.

`mem_space_id` is used to specify both the memory dataspace and the selection within that dataspace. `mem_space_id` can be the constant `H5S_ALL`, in which case the file dataspace is used for the memory dataspace and the selection defined with `file_space_id` is used for the selection within that dataspace.

If raw data storage space has not been allocated for the dataset and a fill value has been defined, the returned buffer `buf` is filled with the fill value.

The behavior of the library for the various combinations of valid dataspace identifiers and `H5S_ALL` for the `mem_space_id` and the `file_space_id` parameters is described below:

<b><code>mem_space_id</code></b>	<b><code>file_space_id</code></b>	<b>Behavior</b>
valid dataspace identifier	valid dataspace identifier	<code>mem_space_id</code> specifies the memory dataspace and the selection within it. <code>file_space_id</code> specifies the selection within the file dataset's dataspace.
<code>H5S_ALL</code>	valid dataspace identifier	The file dataset's dataspace is used for the memory dataspace and the selection specified with <code>file_space_id</code> specifies the selection within it. The combination of the file dataset's dataspace and the selection from <code>file_space_id</code> is used for memory also.
valid dataspace identifier	<code>H5S_ALL</code>	<code>mem_space_id</code> specifies the memory dataspace and the selection within it. The selection within the file dataset's dataspace is set to the "all" selection.
<code>H5S_ALL</code>	<code>H5S_ALL</code>	The file dataset's dataspace is used for the memory dataspace and the selection within the memory dataspace is set to the "all" selection. The selection within the file dataset's dataspace is set to the "all" selection.

Setting an `H5S_ALL` selection indicates that the entire dataspace, as defined by the current dimensions of a dataspace, will be selected. The number of elements selected in the memory dataspace must match the

number of elements selected in the file dataspace.

`xfer_plist_id` can be the constant `H5P_DEFAULT`, in which case the default data transfer properties are used.

Data is automatically converted from the file datatype and dataspace to the memory datatype and dataspace at the time of the read. See the Data Conversion section of *The Data Type Interface (H5T)* in the *HDF5 User's Guide* for a discussion of data conversion, including the range of conversions currently supported by the HDF5 libraries.

#### Parameters:

<code>hid_t dataset_id</code>	IN: Identifier of the dataset read from.
<code>hid_t mem_type_id</code>	IN: Identifier of the memory datatype.
<code>hid_t mem_space_id</code>	IN: Identifier of the memory dataspace.
<code>hid_t file_space_id</code>	IN: Identifier of the dataset's dataspace in the file.
<code>hid_t xfer_plist_id</code>	IN: Identifier of a transfer property list for this I/O operation.
<code>void *buf</code>	OUT: Buffer to receive data read from file.

#### Returns:

Returns a non-negative value if successful; otherwise returns a negative value.

#### Fortran90 Interface: `h5dread_f`, `h5dread_vl_f`

There is no direct FORTRAN counterpart for the C function `H5Dread`. Instead, that functionality is provided by two FORTRAN functions:

<code>h5dread_f</code>	<b>Purpose:</b> Reads data other than variable-length data.
<code>h5dread_vl_f</code>	<b>Purpose:</b> Reads variable-length data.

```

SUBROUTINE h5dread_f(dset_id, mem_type_id, buf, dims, hdferr, &
                    mem_space_id, file_space_id, xfer_prp)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dset_id      ! Dataset identifier
  INTEGER(HID_T), INTENT(IN) :: mem_type_id ! Memory datatype identifier
  TYPE, INTENT(INOUT) :: buf                ! Data buffer; may be a scalar
                                           ! or an array
  DIMENSION(*), INTEGER(HSIZE_T), INTENT(IN) :: dims
                                           ! Array to hold corresponding
                                           ! dimension sizes of data
                                           ! buffer buf
                                           ! dim(k) has value of the k-th
                                           ! dimension of buffer buf
                                           ! Values are ignored if buf is
                                           ! a scalar
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
                                           ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: mem_space_id
                                           ! Memory dataspace identifier
                                           ! Default value is H5S_ALL_F
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: file_space_id
                                           ! File dataspace identifier
                                           ! Default value is H5S_ALL_F
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: xfer_prp
                                           ! Transfer property list identifier
                                           ! Default value is H5P_DEFAULT_F

END SUBROUTINE h5dread_f

```

```

SUBROUTINE h5dread_vl_f(dset_id, mem_type_id, buf, dims, len, hdferr, &
                        mem_space_id, file_space_id, xfer_prp)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dset_id      ! Dataset identifier
  INTEGER(HID_T), INTENT(IN) :: mem_type_id ! Memory datatype identifier
  TYPE, INTENT(INOUT), & DIMENSION(dims(1),dims(2)) :: buf
                                     ! Data buffer; may be a scalar
                                     ! or an array
                                     ! TYPE must be one of the following
                                     !     INTEGER
                                     !     REAL
                                     !     CHARACTER

  INTEGER(HSIZE_T), INTENT(IN), DIMENSION(2) :: dims
                                     ! Array to hold corresponding
                                     ! dimension sizes of data
                                     ! buffer buf
                                     ! dim(k) has value of the k-th
                                     ! dimension of buffer buf
                                     ! Values are ignored if buf is
                                     ! a scalar
  INTEGER(SIZE_T), INTENT(INOUT), DIMENSION(*) :: len
                                     ! Array to store length of
                                     ! each element
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: mem_space_id
                                     ! Memory dataspace identifier
                                     ! Default value is H5S_ALL_F
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: file_space_id
                                     ! File dataspace identifier
                                     ! Default value is H5S_ALL_F
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: xfer_prp
                                     ! Transfer property list identifier
                                     ! Default value is H5P_DEFAULT_F
END SUBROUTINE h5dread_vl_f

```

**History:****Release      Fortran90**

1.4.2        The dims parameter was added in this release.

Last modified: 15 May 2009

**Name:** H5Dset\_extent**Signature:**

```
herr_t H5Dset_extent( hid_t dset_id, const hsize_t *size )
```

**Purpose:**

Changes the sizes of a dataset's dimensions.

**Description:**

H5Dset\_extent sets the current dimensions of the chunked dataset dset\_id to the sizes specified in size.

size is a 1-dimensional array with  $n$  elements, where  $n$  is the rank of the dataset's current dataspace.

This function can be applied to the following datasets:

- ◇ A chunked dataset with unlimited dimensions
- ◇ A chunked dataset with fixed dimensions if the new dimension sizes are less than the maximum sizes set with maxdims (see H5Screate\_simple)
- ◇ An external dataset with unlimited dimensions
- ◇ An external dataset with fixed dimensions if the new dimension sizes are less than the maximum sizes set with maxdims

Note that external datasets are always contiguous and can be extended only along the first dimension.

Space on disk is immediately allocated for the new dataset extent if the dataset's space allocation time is set to H5D\_ALLOC\_TIME\_EARLY. Fill values will be written to the dataset if the dataset's fill time is set to H5D\_FILL\_TIME\_IFSET or H5D\_FILL\_TIME\_ALLOC. (See H5Pset\_fill\_time and H5Pset\_alloc\_time.)

**Note:**

If the sizes specified in size are smaller than the dataset's current dimension sizes, H5Dset\_extent will reduce the dataset's dimension sizes to the specified values. *It is the user's responsibility to ensure that valuable data is not lost; H5Dset\_extent does not check.*

If it is necessary to ensure that current dimension sizes are not reduced, the function H5Dextend can be used.

Except for external datasets, H5Dset\_extent is for use with chunked datasets only, not contiguous datasets.

**Parameters:**

```
hid_t dset_id      IN: Dataset identifier
const hsize_t *size IN: Array containing the new magnitude of each dimension of the dataset.
```

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** H5Dset\_extent

```
SUBROUTINE h5dset_extent_f(dataset_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dataset_id    ! Dataset identifier
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(IN) :: size
                                              ! Array containing
                                              ! dimensions' sizes
  INTEGER, INTENT(OUT) :: hdferr              ! Error code:
```

```
END SUBROUTINE h5dset_extent_f
```

```
! 0 on success and -1 on failure
```

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Dvlen\_get\_buf\_size

**Signature:**

```
herr_t H5Dvlen_get_buf_size(hid_t dataset_id, hid_t type_id, hid_t space_id, hsize_t
*size)
```

**Purpose:**

Determines the number of bytes required to store VL data.

**Description:**

H5Dvlen\_get\_buf\_size determines the number of bytes required to store the VL data from the dataset, using the *space\_id* for the selection in the dataset on disk and the *type\_id* for the memory representation of the VL data in memory.

\**size* is returned with the number of bytes required to store the VL data in memory.

**Parameters:**

<i>hid_t</i> dataset_id	IN: Identifier of the dataset to query.
<i>hid_t</i> type_id	IN: Datatype identifier.
<i>hid_t</i> space_id	IN: Dataspace identifier.
<i>hsize_t</i> * <i>size</i>	OUT: The size in bytes of the memory buffer required to store the VL data.

**Returns:**

Returns non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5dvlen\_get\_max\_len\_f

There is no direct FORTRAN counterpart for the C function H5Dvlen\_get\_buf\_size; corresponding functionality is provided by the FORTRAN function h5dvlen\_get\_max\_len\_f.

```
SUBROUTINE h5dvlen_get_max_len_f(dset_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dset_id      ! Dataset identifier
  INTEGER(HID_T), INTENT(IN) :: type_id     ! Datatype identifier
  INTEGER(HID_T), INTENT(IN) :: space_id    ! Dataspace identifier

  INTEGER(SIZE_T), INTENT(OUT) :: elem_len ! Maximum length of the element
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5dvlen_get_max_len_f
```

**History:**

Release	C	Fortran90
1.4.5		Function introduced in this release.
1.4.0	Function introduced in this release.	

**Name:** H5Dvlen\_reclaim

**Signature:**

*herr\_t* H5Dvlen\_reclaim(*hid\_t* type\_id, *hid\_t* space\_id, *hid\_t* plist\_id, *void* \*buf )

**Purpose:**

Reclaims VL datatype memory buffers.

**Description:**

H5Dvlen\_reclaim reclaims memory buffers created to store VL datatypes.

The *type\_id* must be the datatype stored in the buffer. The *space\_id* describes the selection for the memory buffer to free the VL datatypes within. The *plist\_id* is the dataset transfer property list which was used for the I/O transfer to create the buffer. And *buf* is the pointer to the buffer to be reclaimed.

The VL structures (*hvl\_t*) in the user's buffer are modified to zero out the VL information after the memory has been reclaimed.

If nested VL datatypes were used to create the buffer, this routine frees them *from the bottom up*, releasing all the memory without creating memory leaks.

**Parameters:**

<i>hid_t</i> type_id	IN: Identifier of the datatype.
<i>hid_t</i> space_id	IN: Identifier of the dataspace.
<i>hid_t</i> plist_id	IN: Identifier of the property list used to create the buffer.
<i>void</i> *buf	IN: Pointer to the buffer to be reclaimed.

**Returns:**

Returns non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.



**Name:** H5Dwrite

**Signature:**

```
herr_t H5Dwrite(hid_t dataset_id, hid_t mem_type_id, hid_t mem_space_id, hid_t
file_space_id, hid_t xfer_plist_id, const void *buf )
```

**Purpose:**

Writes raw data from a buffer to a dataset.

**Description:**

H5Dwrite writes a (partial) dataset, specified by its identifier `dataset_id`, from the application memory buffer `buf` into the file. Data transfer properties are defined by the argument `xfer_plist_id`. The memory datatype of the (partial) dataset is identified by the identifier `mem_type_id`. The part of the dataset to write is defined by `mem_space_id` and `file_space_id`.

`file_space_id` is used to specify only the selection within the file dataset's dataspace. Any dataspace specified in `file_space_id` is ignored by the library and the dataset's dataspace is always used. `file_space_id` can be the constant `H5S_ALL`, which indicates that the entire file dataspace, as defined by the current dimensions of the dataset, is to be selected.

`mem_space_id` is used to specify both the memory dataspace and the selection within that dataspace. `mem_space_id` can be the constant `H5S_ALL`, in which case the file dataspace is used for the memory dataspace and the selection defined with `file_space_id` is used for the selection within that dataspace.

The behavior of the library for the various combinations of valid dataspace IDs and `H5S_ALL` for the `mem_space_id` and the `file_space_id` parameters is described below:

<b>mem_space_id</b>	<b>file_space_id</b>	<b>Behavior</b>
valid dataspace identifier	valid dataspace identifier	<code>mem_space_id</code> specifies the memory dataspace and the selection within it. <code>file_space_id</code> specifies the selection within the file dataset's dataspace.
<code>H5S_ALL</code>	valid dataspace identifier	The file dataset's dataspace is used for the memory dataspace and the selection specified with <code>file_space_id</code> specifies the selection within it. The combination of the file dataset's dataspace and the selection from <code>file_space_id</code> is used for memory also.
valid dataspace identifier	<code>H5S_ALL</code>	<code>mem_space_id</code> specifies the memory dataspace and the selection within it. The selection within the file dataset's dataspace is set to the "all" selection.
<code>H5S_ALL</code>	<code>H5S_ALL</code>	The file dataset's dataspace is used for the memory dataspace and the selection within the memory dataspace is set to the "all" selection. The selection within the file dataset's dataspace is set to the "all" selection.

Setting an "all" selection indicates that the entire dataspace, as defined by the current dimensions of a dataspace, will be selected. The number of elements selected in the memory dataspace must match the number of elements selected in the file dataspace.

`xfer_plist_id` can be the constant `H5P_DEFAULT`, in which case the default data transfer properties are used.

Writing to an dataset will fail if the HDF5 file was not opened with write access permissions.

Data is automatically converted from the memory datatype and dataspace to the file datatype and dataspace at the time of the write. See the Data Conversion section of *The Data Type Interface (H5T)* in the *HDF5 User's Guide* for a discussion of data conversion, including the range of conversions currently supported by the HDF5 libraries.

If the dataset's space allocation time is set to `H5D_ALLOC_TIME_LATE` or `H5D_ALLOC_TIME_INCR` and the space for the dataset has not yet been allocated, that space is allocated when the first raw data is written to the dataset. Unused space in the dataset will be written with fill values at the same time if the dataset's fill time is set to `H5D_FILL_TIME_IFSET` or `H5D_FILL_TIME_ALLOC`. (Also see `H5Pset_fill_time` and `H5Pset_alloc_time`.)

If a dataset's storage layout is 'compact', care must be taken when writing data to the dataset in parallel. A compact dataset's raw data is cached in memory and may be flushed to the file from any of the parallel processes, so parallel applications should always attempt to write identical data to the dataset from all processes.

#### Parameters:

<code>hid_t dataset_id</code>	IN: Identifier of the dataset to write to.
<code>hid_t mem_type_id</code>	IN: Identifier of the memory datatype.
<code>hid_t mem_space_id</code>	IN: Identifier of the memory dataspace.
<code>hid_t file_space_id</code>	IN: Identifier of the dataset's dataspace in the file.
<code>hid_t xfer_plist_id</code>	IN: Identifier of a transfer property list for this I/O operation.
<code>const void *buf</code>	IN: Buffer with data to be written to the file.

#### Returns:

Returns a non-negative value if successful; otherwise returns a negative value.

#### Fortran90 Interface: `h5dwrite_f`, `h5dwrite_vl_f`

There is no direct FORTRAN counterpart for the C function `H5Dwrite`. Instead, that functionality is provided by two FORTRAN functions:

<code>h5dwrite_f</code>	<b>Purpose:</b> Writes data other than variable-length data.
<code>h5dwrite_vl_f</code>	<b>Purpose:</b> Writes variable-length data.

```

SUBROUTINE h5dwrite_f(dset_id, mem_type_id, buf, dims, hdferr, &
                     mem_space_id, file_space_id, xfer_prp)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dset_id      ! Dataset identifier
  INTEGER(HID_T), INTENT(IN) :: mem_type_id  ! Memory datatype identifier
  TYPE, INTENT(IN) :: buf                    ! Data buffer; may be a scalar
                                              ! or an array
  DIMENSION(*), INTEGER(HSIZE_T), INTENT(IN) :: dims
                                              ! Array to hold corresponding
                                              ! dimension sizes of data
                                              ! buffer buf; dim(k) has value
                                              ! of the k-th dimension of
                                              ! buffer buf; values are
                                              ! ignored if buf is a scalar
  INTEGER, INTENT(OUT) :: hdferr              ! Error code

```

```

                                ! 0 on success and -1 on failure

INTEGER(HID_T), OPTIONAL, INTENT(IN) :: mem_space_id
                                ! Memory dataspace identifier
                                ! Default value is H5S_ALL_F
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: file_space_id
                                ! File dataspace identifier
                                ! Default value is H5S_ALL_F

INTEGER(HID_T), OPTIONAL, INTENT(IN) :: xfer_prp
                                ! Transfer property list
                                ! identifier; default value
                                ! is H5P_DEFAULT_F

END SUBROUTINE h5dwrite_f

SUBROUTINE h5dwrite_vl_f(dset_id, mem_type_id, buf, dims, len, hdferr, &
                        mem_space_id, file_space_id, xfer_prp)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dset_id      ! Dataset identifier
  INTEGER(HID_T), INTENT(IN) :: mem_type_id ! Memory datatype identifier
  TYPE, INTENT(IN), & DIMENSION(dims(1),dims(2)) :: buf
                                              ! Data buffer; may be a scalar
                                              ! or an array
                                              ! TYPE must be one of the following
                                              !     INTEGER
                                              !     REAL
                                              !     CHARACTER
  INTEGER(HSIZE_T), INTENT(IN), DIMENSION(2) :: dims
                                              ! Array to hold corresponding
                                              ! dimension sizes of data
                                              ! buffer buf
                                              ! dim(k) has value of the k-th
                                              ! dimension of buffer buf
                                              ! Values are ignored if buf is
                                              ! a scalar
  INTEGER(SIZE_T), INTENT(IN), DIMENSION(*) :: len
                                              ! Array to store length of
                                              ! each element
  INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                              ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: mem_space_id
                                              ! Memory dataspace identifier
                                              ! Default value is H5S_ALL_F
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: file_space_id
                                              ! File dataspace identifier
                                              ! Default value is H5S_ALL_F
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: xfer_prp
                                              ! Transfer property list identifier
                                              ! Default value is H5P_DEFAULT_F

END SUBROUTINE h5dwrite_vl_f

```

**History:**

<b>Release</b>	<b>Fortran90</b>
1.4.2	A dims parameter has been added.



## H5E: Error Interface

### Error API Functions

These functions provide error handling capabilities in the HDF5 environment. In the following lists, *italic type* indicates a configurable macro.

#### The C Interfaces:

- |                   |                       |                        |
|-------------------|-----------------------|------------------------|
| • <i>H5Eclear</i> | • H5Epop              | • <i>H5Eset_auto</i>   |
| • H5Eclear1 *     | • H5Eget_num          | • H5Eset_auto1 *       |
| • H5Eclear2       | • H5Eget_major *      | • H5Eset_auto2         |
| • H5Ecreate_stack | • H5Eget_minor *      | • <i>H5Eget_auto</i>   |
| • H5Eclose_stack  | • H5Eget_msg          | • H5Eget_auto1 *       |
| • <i>H5Eprint</i> | • H5Ecreate_msg       | • H5Eget_auto2         |
| • H5Eprint1 *     | • H5Eclose_msg        | • <i>H5Ewalk</i>       |
| • H5Eprint2       | • H5Eregister_class   | • H5Ewalk1 *           |
| • <i>H5Epush</i>  | • H5Eunregister_class | • H5Ewalk2             |
| • H5Epush1 *      | • H5Eget_class_name   | • H5Eget_current_stack |
| • H5Epush2        | • H5Eauto_is_v2       | • H5Eset_current_stack |

*\* Use of these functions is deprecated in Release 1.8.0.*

#### Alphabetical Listing

- |                      |                        |                        |
|----------------------|------------------------|------------------------|
| • H5Eauto_is_v2      | • H5Eget_class_name    | • H5Epush1 *           |
| • <i>H5Eclear</i>    | • H5Eget_current_stack | • H5Epush2             |
| • H5Eclear1 *        | • H5Eget_major *       | • H5Eregister_class    |
| • H5Eclear2          | • H5Eget_minor *       | • <i>H5Eset_auto</i>   |
| • H5Eclose_msg       | • H5Eget_msg           | • H5Eset_auto1 *       |
| • H5Eclose_stack     | • H5Eget_num           | • H5Eset_auto2         |
| • H5Ecreate_msg      | • H5Epop               | • H5Eset_current_stack |
| • H5Ecreate_stack    | • <i>H5Eprint</i>      | • H5Eunregister_class  |
| • <i>H5Eget_auto</i> | • H5Eprint1 *          | • <i>H5Ewalk</i>       |
| • H5Eget_auto1 *     | • H5Eprint2            | • H5Ewalk1 *           |
| • H5Eget_auto2       | • <i>H5Epush</i>       | • H5Ewalk2             |

*\* Use of these functions is deprecated in Release 1.8.0.*

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- |              |                 |                  |
|--------------|-----------------|------------------|
| • h5eclear_f | • h5eset_auto_f | • h5eget_major_f |
| • h5eprint_f |                 | • h5eget_minor_f |

The Error interface provides error handling in the form of a stack. The `FUNC_ENTER( )` macro clears the error stack whenever an interface function is entered. When an error is detected, an entry is pushed onto the stack. As the functions unwind, additional entries are pushed onto the stack. The API function will return some indication that an error occurred and the application can print the error stack.

Certain API functions in the H5E package, such as `H5Eprint1`, do not clear the error stack. Otherwise, any function which does not have an underscore immediately after the package name will clear the error stack. For instance, `H5Fopen` clears the error stack while `H5F_open` does not.

An error stack has a fixed maximum size. If this size is exceeded then the stack will be truncated and only the inner-most functions will have entries on the stack. This is expected to be a rare condition.

Each thread has its own error stack, but since multi-threading has not been added to the library yet, this package maintains a single error stack. The error stack is statically allocated to reduce the complexity of handling errors within the H5E package.

**Name:** H5Eauto\_is\_v2

**Signature:**

*herr\_t* H5Eauto\_is\_v2(*hid\_t* estack\_id, *unsigned* \*is\_stack)

**Purpose:**

Determines type of error stack.

**Description:**

H5Eauto\_is\_v2 determines whether the error auto reporting function for an error stack conforms to the H5E\_auto2\_t typedef or the H5E\_auto1\_t typedef.

The is\_stack parameter is set to 1 if the error stack conforms to H5E\_auto2\_t and 0 if it conforms to H5E\_auto1\_t.

**Parameters:**

*hid\_t* estack\_id      The error stack identifier

*unsigned* \* is\_stack      A flag indicating which error stack typedef the specified error stack conforms to.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Eclear

**Signature:**

```
herr_t H5Eclear1(void)
herr_t H5Eclear2(hid_t estack_id)
```

**Purpose:**

Clears an error stack.

**Description:**

H5Eclear is a macro that is mapped to either H5Eclear1 or H5Eclear2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Eclear is mapped to the most recent version of the function, currently H5Eclear2. If the library and/or application is compiled for Release 1.6 emulation, H5Eclear will be mapped to H5Eclear1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Eclear mapping
<u>Global settings</u>	
No compatibility flag	H5Eclear2
Enable deprecated symbols	H5Eclear2
Disable deprecated symbols	H5Eclear2
Emulate Release 1.6 interface	H5Eclear1
<u>Function-level macros</u>	
H5Eclear_vers = 2	H5Eclear2
H5Eclear_vers = 1	H5Eclear1

**Fortran90 Interface:** h5eclear\_f

```
SUBROUTINE h5eclear_f(hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(OUT) :: hdferr ! Error code

  END SUBROUTINE h5eclear_f
```

**History:**

Release	C
1.8.0	The function H5Eclear renamed to H5Eclear1 and deprecated in this release. The macro H5Eclear and the function H5Eclear2 introduced in this release.



**Name:** H5Eclear1

**Signature:**

*herr\_t* H5Eclear1(void)

**Purpose:**

Clears the error stack for the current thread.

**Notice:**

*This function is deprecated in favor of the function `H5Eclear2` or the macro `H5Eclear`.*

**Description:**

H5Eclear1 clears the error stack for the current thread.

The stack is also cleared whenever an API function is called, with certain exceptions (for instance, H5Eprint1).

**Parameters:**

None

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5eclear\_f

See H5Eclear.

**History:**

Release	C
---------	---

1.8.0	Function H5Eclear renamed to H5Eclear1 and deprecated in this release.
-------	--

**Name:** H5Eclear2

**Signature:**

*herr\_t* H5Eclear2(*hid\_t* estack\_id)

**Purpose:**

Clears the specified error stack or the error stack for the current thread.

**Description:**

H5Eclear2 clears the error stack specified by *estack\_id*, or, if *estack\_id* is set to H5E\_DEFAULT, the error stack for the current thread.

*estack\_id* is an error stack identifier, such as that returned by H5Eget\_current\_stack.

The current error stack is also cleared whenever an API function is called, with certain exceptions (for instance, H5Eprint1 or H5Eprint2).

**Parameters:**

*hid\_t* estack\_id    IN: Error stack identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5eclear\_f

See H5Eclear.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Eclose\_msg

**Signature:**

*herr\_t* H5Eclose\_msg(*hid\_t* msg\_id)

**Purpose:**

Closes an error message identifier.

**Description:**

H5Eclose\_msg closes an error message identifier., which can be either a major or minor message.

**Parameters:**

*hid\_t* msg\_id     IN: Error message identifier.

**Returns:**

Returns a non-negative value on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Eclose\_stack

**Signature:**

*herr\_t* H5Eclose\_stack(*hid\_t* estack\_id)

**Purpose:**

Closes object handle for error stack.

**Description:**

H5Eclose\_stack closes the object handle for an error stack and releases its resources.

H5E\_DEFAULT cannot be closed.

**Parameters:**

*hid\_t* estack\_id    IN: Error stack identifier.

**Returns:**

Returns a non-negative value on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Ecreate\_msg

**Signature:**

*hid\_t* H5Ecreate\_msg(*hid\_t* class, *H5E\_type\_t* msg\_type, *const char\** msg)

**Purpose:**

Add major error message to an error class.

**Description:**

H5Ecreate\_msg adds an error message to an error class defined by client library or application program. The error message can be either major or minor which is indicated by parameter msg\_type.

**Parameters:**

<i>hid_t</i> class	IN: Error class identifier.
<i>H5E_type_t</i> msg_type	IN: The type of the error message. Valid values are H5E_MAJOR and H5E_MINOR.
<i>const char*</i> msg	IN: Major error message.

**Returns:**

Returns a message identifier on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Ecreate\_stack

**Signature:**

*hid\_t* H5Ecreate\_stack(*void*)

**Purpose:**

Creates a new empty error stack.

**Description:**

H5Ecreate\_stack creates a new empty error stack and returns the new stack's identifier.

**Parameters:**

None.

**Returns:**

Returns an error stack identifier on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Eget\_auto

**Signature:**

```
herr_t H5Eget_auto( H5E_auto_t * func, void **client_data )
herr_t H5Eget_auto( hid_t estate_id, H5E_auto_t * func, void **client_data )
```

**Purpose:**

Returns settings for automatic error stack traversal function and its data.

**Description:**

H5Eget\_auto is a macro that is mapped to either H5Eget\_auto1 or H5Eget\_auto2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Eget\_auto is mapped to the most recent version of the function, currently H5Eget\_auto2. If the library and/or application is compiled for Release 1.6 emulation, H5Eget\_auto will be mapped to H5Eget\_auto1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Eget_auto mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Eget_auto2
Enable deprecated symbols	H5Eget_auto2
Disable deprecated symbols	H5Eget_auto2
Emulate Release 1.6 interface	H5Eget_auto1
<hr/>	
<u>Function-level macros</u>	
H5Eget_auto_vers = 2	H5Eget_auto2
H5Eget_auto_vers = 1	H5Eget_auto1

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	<p>The function H5Eget_auto renamed to H5Eget_auto1 and deprecated in this release.</p> <p>The macro H5Eget_auto and the function H5Eget_auto2 introduced in this release.</p>

**Name:** H5Eget\_auto1

**Signature:**

*herr\_t* H5Eget\_auto1( *H5E\_auto1\_t* \* func, void \*\*client\_data )

**Purpose:**

Returns the current settings for the automatic error stack traversal function and its data.

**Notice:**

*This function is deprecated in favor of the function H5Eget\_auto2 or the macro H5Eget\_auto.*

**Description:**

H5Eget\_auto1 returns the current settings for the automatic error stack traversal function, func, and its data, client\_data. Either or both arguments may be null, in which case the value is not returned.

**Parameters:**

*H5E\_auto1\_t* \* func                      OUT: Current setting for the function to be called upon an error condition.

void \*\*client\_data                      OUT: Current setting for the data passed to the error function.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

**Release    C**

1.8.0        Function H5Eget\_auto renamed to H5Eget\_auto1 and deprecated in this release.



**Name:** H5Eget\_auto2

**Signature:**

*herr\_t* H5Eget\_auto2(*hid\_t* estack\_id, *H5E\_auto2\_t* \* func, *void* \*\*client\_data)

**Purpose:**

Returns the settings for the automatic error stack traversal function and its data.

**Description:**

H5Eget\_auto2 returns the settings for the automatic error stack traversal function, func, and its data, client\_data, that are associated with the error stack specified by estack\_id.

Either or both of the func and client\_data arguments may be null, in which case the value is not returned.

**Parameters:**

<i>hid_t</i> estack_id	IN: Error stack identifier. H5E_DEFAULT indicates the current stack.
<i>H5E_auto2_t</i> * func	OUT: The function currently set to be called upon an error condition.
<i>void</i> **client_data	OUT: Data currently set to be passed to the error function.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Eget\_class\_name

**Signature:**

*ssize\_t* H5Eget\_class\_name(*hid\_t* class\_id, *char\** name, *size\_t* size)

**Purpose:**

Retrieves error class name.

**Description:**

H5Eget\_class\_name retrieves the name of the error class specified by the class identifier. If non-NULL pointer is passed in for name and size is greater than zero, the class name of size long is returned. The length of the error class name is also returned. If NULL is passed in as name, only the length of class name is returned. If zero is returned, it means no name. User is responsible for allocated enough buffer for the name.

**Parameters:**

<i>hid_t</i> class_id	IN: Error class identifier.
<i>char*</i> name	OUT: The name of the class to be queried.
<i>size_t</i> size	IN: The length of class name to be returned by this function.

**Returns:**

Returns non-negative value as on success; otherwise returns negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Eget\_current\_stack

**Signature:**

*hid\_t* H5Eget\_current\_stack(*void*)

**Purpose:**

Returns copy of current error stack.

**Description:**

H5Eget\_current\_stack copies the current error stack and returns an error stack identifier for the new copy.

**Parameters:**

None.

**Returns:**

Returns an error stack identifier on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Eget\_major

**Signature:**

*const char \** H5Eget\_major(*H5E\_major\_t* n)

**Purpose:**

Returns a character string describing an error specified by a major error number.

**Notice:**

*This function has been deprecated.*

**Description:**

Given a major error number, H5Eget\_major returns a constant character string that describes the error.

**Parameters:**

*H5E\_major\_t* n      IN: Major error number.

**Returns:**

Returns a character string describing the error if successful. Otherwise returns "Invalid major error number."

**Fortran90 Interface:** h5eget\_major\_f

```
SUBROUTINE h5eget_major_f(error_no, name, hdferr)
  INTEGER, INTENT(IN) :: error_no      !Major error number
  CHARACTER(LEN=*), INTENT(OUT) :: name ! File name
  INTEGER, INTENT(OUT) :: hdferr       ! Error code

END SUBROUTINE h5eget_major_f
```

**History:**

**Release      C**

1.8.0      Function deprecated in this release.

**Name:** H5Eget\_minor

**Signature:**

*const char \**H5Eget\_minor(*H5E\_minor\_t* n)

**Purpose:**

Returns a character string describing an error specified by a minor error number.

**Notice:**

*This function has been deprecated.*

**Description:**

Given a minor error number, H5Eget\_minor returns a constant character string that describes the error.

**Parameters:**

*H5E\_minor\_t* n      IN: Minor error number.

**Returns:**

Returns a character string describing the error if successful. Otherwise returns "Invalid minor error number."

**Fortran90 Interface:** h5eget\_minor\_f

```
SUBROUTINE h5eget_minor_f(error_no, name, hdferr)
  INTEGER, INTENT(IN) :: error_no      !Major error number
  CHARACTER(LEN=*), INTENT(OUT) :: name ! File name
  INTEGER, INTENT(OUT) :: hdferr       ! Error code

END SUBROUTINE h5eget_minor_f
```

**History:**

**Release      C**

1.8.0      Function deprecated in this release.

**Name:** H5Eget\_msg

**Signature:**

*ssize\_t* H5Eget\_msg(*hid\_t* msg\_id, *H5E\_type\_t*\* msg\_type, *char*\* msg, *size\_t* size)

**Purpose:**

Retrieves an error message.

**Description:**

H5Eget\_msg retrieves the error message including its length and type. The error message is specified by msg\_id. User is responsible for passing in enough buffer for the message. If msg is not NULL and size is greater than zero, the error message of size long is returned. The length of the message is also returned. If NULL is passed in as msg, only the length and type of the message is returned. If the return value is zero, it means no message.

**Parameters:**

<i>hid_t</i> msg_id	IN: Identifier for error message to be queried.
<i>H5E_type_t</i> * msg_type	OUT: The type of the error message. Valid values are H5E_MAJOR and H5E_MINOR.
<i>char</i> * msg	OUT: Error message buffer.
<i>size_t</i> size	IN: The length of error message to be returned by this function.

**Returns:**

Returns the size of the error message in bytes on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Eget\_num

**Signature:**

*ssize\_t* H5Eget\_num(*hid\_t* estack\_id)

**Purpose:**

Retrieves the number of error messages in an error stack.

**Description:**

H5Eget\_num retrieves the number of error records in the error stack specified by *estack\_id* (including major, minor messages and description).

**Parameters:**

*hid\_t* estack\_id     IN: Error stack identifier.

**Returns:**

Returns a non-negative value on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Epop

**Signature:**

*herr\_t* H5Epop(*hid\_t* estack\_id, *size\_t* count)

**Purpose:**

Deletes specified number of error messages from the error stack.

**Description:**

H5Epop deletes the number of error records specified in *count* from the top of the error stack specified by *estack\_id* (including major, minor messages and description). The number of error messages to be deleted is specified by *count*.

**Parameters:**

*hid\_t* estack\_id      IN: Error stack identifier.

*size\_t* count          IN: The number of error messages to be deleted from the top of error stack.

**Returns:**

Returns a non-negative value on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------



**Name:** H5Eprint

**Signature:**

```
herr_t H5Eprint1( FILE *stream )
herr_t H5Eprint2( hid_t estate_id, FILE *stream )
```

**Purpose:**

Prints an error stack in a default manner.

**Description:**

H5Eprint is a macro that is mapped to either H5Eprint1 or H5Eprint2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Eprint is mapped to the most recent version of the function, currently H5Eprint2. If the library and/or application is compiled for Release 1.6 emulation, H5Eprint will be mapped to H5Eprint1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Eprint mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Eprint2
Enable deprecated symbols	H5Eprint2
Disable deprecated symbols	H5Eprint2
Emulate Release 1.6 interface	H5Eprint1
<hr/>	
<u>Function-level macros</u>	
H5Eprint_vers = 2	H5Eprint2
H5Eprint_vers = 1	H5Eprint1

**Fortran90 Interface:** h5eprint\_f

```
SUBROUTINE h5eprint_f(hdferr, name)
  CHARACTER(LEN=*), OPTIONAL, INTENT(IN) :: name ! File name
  INTEGER, INTENT(OUT) :: hdferr                ! Error code

END SUBROUTINE h5eprint_f
```

**History:**

Release	C
1.8.0	The function H5Eprint renamed to H5Eprint1 and deprecated in this release. The macro H5Eprint and the function H5Eprint2 introduced in this release.

**Name:** H5Eprint1

**Signature:**

*herr\_t* H5Eprint1(*FILE* \*stream)

**Purpose:**

Prints the current error stack in a default manner.

**Notice:**

*This function is deprecated in favor of the function H5Eprint2 or the macro H5Eprint.*

**Description:**

H5Eprint1 prints the error stack for the current thread on the specified stream, *stream*. Even if the error stack is empty, a one-line message will be printed:

HDF5-DIAG: Error detected in thread 0.

H5Eprint1 is a convenience function for H5Ewalk1 with a function that prints error messages. Users are encouraged to write their own more specific error handlers.

**Parameters:**

*FILE* \*stream      IN: File pointer, or stderr if NULL.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5eprint\_f

See H5Eprint.

**History:**

Release	C
---------	---

1.8.0	Function H5Eprint renamed to H5Eprint1 and deprecated in this release.
-------	--

**Name:** H5Eprint2

**Signature:**

*herr\_t* H5Eprint2(*hid\_t* estack\_id, *FILE* \*stream)

**Purpose:**

Prints the specified error stack in a default manner.

**Description:**

H5Eprint2 prints the error stack specified by *estack\_id* on the specified stream, *stream*. Even if the error stack is empty, a one-line message of the following form will be printed:

HDF5-DIAG: Error detected in HDF5 library version: 1.5.62 thread 0.

A similar line will appear before the error messages of each error class stating the library name, library version number, and thread identifier.

If *estack\_id* is H5E\_DEFAULT, the current error stack will be printed.

H5Eprint2 is a convenience function for H5Ewalk2 with a function that prints error messages. Users are encouraged to write their own more specific error handlers.

**Parameters:**

*hid\_t* estack\_id      IN: Identifier of the error stack to be printed. If the identifier is H5E\_DEFAULT, the current error stack will be printed.

*FILE* \*stream      IN: File pointer, or stderr if NULL.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

**Release      C**

1.8.0      Function introduced in this release.

**Name:** H5Epush

**Signature:**

```
herr_t H5Epush( const char *file, const char *func, unsigned line, H5E_major_t maj_num,
H5E_minor_t min_num, const char *str )
herr_t H5Epush( hid_t estack_id, const char *file, const char *func, unsigned line, hid_t
class_id, hid_t major_id, hid_t minor_id, const char *msg, ...)
```

**Purpose:**

Pushes a new error message onto an error stack.

**Description:**

H5Epush is a macro that is mapped to either H5Epush1 or H5Epush2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Epush is mapped to the most recent version of the function, currently H5Epush2. If the library and/or application is compiled for Release 1.6 emulation, H5Epush will be mapped to H5Epush1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Epush mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Epush2
Enable deprecated symbols	H5Epush2
Disable deprecated symbols	H5Epush2
Emulate Release 1.6 interface	H5Epush1
<hr/>	
<u>Function-level macros</u>	
H5Epush_vers = 2	H5Epush2
H5Epush_vers = 1	H5Epush1

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	The function H5Epush renamed to H5Epush1 and deprecated in this release. The macro H5Epush and the function H5Epush2 introduced in this release.

**Name:** H5Epush1**Signature:**

```
herr_t H5Epush1( const char *file, const char *func, unsigned line, H5E_major_t maj_num,
                 H5E_minor_t min_num, const char *str )
```

**Purpose:**

Pushes new error record onto error stack.

**Notice:***This function is deprecated in favor of the function H5Epush2 or the macro H5Epush.***Description:**

H5Epush1 pushes a new error record onto the error stack for the current thread.

The error has major and minor numbers `maj_num` and `min_num`, the function `func` where the error was detected, the name of the file `file` where the error was detected, the line `line` within that file, and an error description string `str`.

The function name, filename, and error description strings must be statically allocated.

**Parameters:**

<code>const char *file</code>	IN: Name of the file in which the error was detected.
<code>const char *func</code>	IN: Name of the function in which the error was detected.
<code>unsigned line</code>	IN: Line within the file at which the error was detected.
<code>H5E_major_t maj_num</code>	IN: Major error number.
<code>H5E_minor_t min_num</code>	IN: Minor error number.
<code>const char *str</code>	IN: Error description string.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.4.0	Function introduced in this release.
1.8.0	Function H5Epush renamed to H5Epush1 and deprecated in this release.

**Name:** H5Epush2

**Signature:**

```
herr_t H5Epush2(hid_t estack_id, const char *file, const char *func, unsigned line, hid_t
class_id, hid_t major_id, hid_t minor_id, const char *msg, ...)
```

**Purpose:**

Pushes new error record onto error stack.

**Description:**

H5Epush2 pushes a new error record onto the error stack specified by *estack\_id*.

The error record contains the error class identifier *class\_id*, the major and minor message identifiers *major\_id* and *minor\_id*, the function name *func* where the error was detected, the filename *file* and line number *line* within that file where the error was detected, and an error description *msg*.

The major and minor errors must be in the same error class.

The function name, filename, and error description strings must be statically allocated.

*msg* can be a format control string with additional arguments. This design of appending additional arguments is similar to the system and C functions `printf` and `fprintf`.

**Parameters:**

<i>hid_t</i> estack_id	IN: Identifier of the error stack to which the error record is to be pushed. If the identifier is H5E_DEFAULT, the error record will be pushed to the current stack.
<i>const char</i> *file	IN: Name of the file in which the error was detected.
<i>const char</i> *func	IN: Name of the function in which the error was detected.
<i>unsigned</i> line	IN: Line number within the file at which the error was detected.
<i>hid_t</i> class_id	IN: Error class identifier.
<i>hid_t</i> major_id	IN: Major error identifier.
<i>hid_t</i> minor_id	IN: Minor error identifier.
<i>const char</i> *msg	IN: Error description string.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Eregister\_class

**Signature:**

```
hid_t H5Eregister_class(const char* cls_name, const char* lib_name, const char*  
version)
```

**Purpose:**

Registers a client library or application program to the HDF5 error API.

**Description:**

H5Eregister\_class registers a client library or application program to the HDF5 error API so that the client library or application program can report errors together with HDF5 library. It receives an identifier for this error class for further error operations. The library name and version number will be printed out in the error message as preamble.

**Parameters:**

<i>const char*</i> cls_name	IN: Name of the error class.
<i>const char*</i> lib_name	IN: Name of the client library or application to which the error class belongs.
<i>const char*</i> version	IN: Version of the client library or application to which the error class belongs. A NULL can be passed in.

**Returns:**

Returns a class identifier on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Eset\_auto

**Signature:**

```
herr_t H5Eset_auto( H5E_auto_t func, void *client_data )
herr_t H5Eset_auto( hid_t estate_id, H5E_auto_t func, void *client_data )
```

**Purpose:**

Returns settings for automatic error stack traversal function and its data.

**Description:**

H5Eget\_auto is a macro that is mapped to either H5Eset\_auto1 or H5Eset\_auto2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Eset\_auto is mapped to the most recent version of the function, currently H5Eset\_auto2. If the library and/or application is compiled for Release 1.6 emulation, H5Eset\_auto will be mapped to H5Eset\_auto1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Eset_auto mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Eset_auto2
Enable deprecated symbols	H5Eset_auto2
Disable deprecated symbols	H5Eset_auto2
Emulate Release 1.6 interface	H5Eset_auto1
<hr/>	
<u>Function-level macros</u>	
H5Eset_auto_vers = 2	H5Eset_auto2
H5Eset_auto_vers = 1	H5Eset_auto1

**Fortran90 Interface:** h5eset\_auto\_f

```
SUBROUTINE h5eset_auto_f(printflag, hdferr)
  INTEGER, INTENT(IN) :: printflag  !flag to turn automatic error
                                     !printing on or off
                                     !possible values are:
                                     !printon (1)
                                     !prntoff(0)
  INTEGER, INTENT(OUT) :: hdferr    ! Error code

END SUBROUTINE h5eset_auto_f
```



**History:**

<b>Release</b>	<b>C</b>
1.8.0	<p>The function <code>H5Eset_auto</code> renamed to <code>H5Eset_auto1</code> and deprecated in this release.</p> <p>The macro <code>H5Eset_auto</code> and the function <code>H5Eset_auto2</code> introduced in this release.</p>

**Name:** H5Eset\_auto1

**Signature:**

```
herr_t H5Eset_auto1( H5E_auto1_t func, void *client_data )
```

**Purpose:**

Turns automatic error printing on or off.

**Description:**

H5Eset\_auto1 turns on or off automatic printing of errors. When turned on (non-null func pointer), any API function which returns an error indication will first call func, passing it client\_data as an argument.

When the library is first initialized the auto printing function is set to H5Eprint1 (cast appropriately) and client\_data is the standard error stream pointer, stderr.

Automatic stack traversal is always in the H5E\_WALK\_DOWNWARD direction.

**Parameters:**

<i>H5E_auto1_t</i> func	IN: Function to be called upon an error condition.
<i>void</i> *client_data	IN: Data passed to the error function.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5eset\_auto\_f

See H5Eset\_auto.

**History:**

Release	C
1.8.0	Function H5Eset_auto renamed to H5Eset_auto1 and deprecated in this release.

**Name:** H5Eset\_auto2

**Signature:**

*herr\_t* H5Eset\_auto2(*hid\_t* estack\_id, *H5E\_auto2\_t* func, *void* \*client\_data )

**Purpose:**

Turns automatic error printing on or off.

**Description:**

H5Eset\_auto2 turns on or off automatic printing of errors for the error stack specified with *estack\_id*. An *estack\_id* value of H5E\_DEFAULT indicates the current stack.

When automatic printing is turned on, by the use of a non-null *func* pointer, any API function which returns an error indication will first call *func*, passing it *client\_data* as an argument.

When the library is first initialized, the auto printing function is set to H5Eprint2 (cast appropriately) and *client\_data* is the standard error stream pointer, *stderr*.

Automatic stack traversal is always in the H5E\_WALK\_DOWNWARD direction.

Automatic error printing is turned off with a H5Eset\_auto2 call with a NULL *func* pointer.

**Parameters:**

<i>hid_t</i> estack_id	IN: Error stack identifier.
<i>H5E_auto2_t</i> func	IN: Function to be called upon an error condition.
<i>void</i> *client_data	IN: Data passed to the error function.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5eset\_auto\_f

See H5Eset\_auto.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Eset\_current\_stack

**Signature:**

*herr\_t* H5Eset\_current\_stack(*hid\_t* estack\_id)

**Purpose:**

Replaces the current error stack.

**Description:**

H5Eset\_current\_stack replaces the content of the current error stack with a copy of the content of the error stack specified by *estack\_id*.

**Parameters:**

*hid\_t* estack\_id    IN: Error stack identifier.

**Returns:**

Returns a non-negative value on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Eunregister\_class

**Signature:**

*herr\_t* H5Eunregister\_class(*hid\_t* class\_id)

**Purpose:**

Removes an error class.

**Description:**

H5Eunregister\_class removes the error class specified by `class_id`. All the major and minor errors in this class will also be closed.

**Parameters:**

*hid\_t* class\_id    IN: Error class identifier.

**Returns:**

Returns a non-negative value on success; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Ewalk

**Signature:**

```
herr_t H5Ewalk( H5E_direction_t direction, H5E_walk_t func, void * client_data )
herr_t H5Ewalk( hid_t estack_id, H5E_direction_t direction, H5E_walk_t func, void *
client_data )
```

**Purpose:**

Walks an error stack, calling a specified function.

**Description:**

H5Ewalk is a macro that is mapped to either H5Ewalk1 or H5Ewalk2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Ewalk is mapped to the most recent version of the function, currently H5Ewalk2. If the library and/or application is compiled for Release 1.6 emulation, H5Ewalk will be mapped to H5Ewalk1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Ewalk mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Ewalk2
Enable deprecated symbols	H5Ewalk2
Disable deprecated symbols	H5Ewalk2
Emulate Release 1.6 interface	H5Ewalk1
<hr/>	
<u>Function-level macros</u>	
H5Ewalk_vers = 2	H5Ewalk2
H5Ewalk_vers = 1	H5Ewalk1

**Fortran90 Interface:** h5ewalk\_f

None.

**History:**

Release	C
1.8.0	The function H5Ewalk renamed to H5Ewalk1 and deprecated in this release. The macro H5Ewalk and the function H5Ewalk2 introduced in this release.

**Name:** H5Ewalk1

**Signature:**

```
herr_t H5Ewalk1(H5E_direction_t direction, H5E_walk1_t func, void *client_data )
```

**Purpose:**

Walks the error stack for the current thread, calling a specified function.

**Notice:**

*This function is deprecated in favor of the function H5Ewalk2 or the macro H5Ewalk.*

**Description:**

H5Ewalk1 walks the error stack for the current thread and calls the specified function for each error along the way.

direction determines whether the stack is walked from the inside out or the outside in. A value of H5E\_WALK\_UPWARD means begin with the most specific error and end at the API; a value of H5E\_WALK\_DOWNWARD means to start at the API and end at the inner-most function where the error was first detected.

func will be called for each error in the error stack. Its arguments will include an index number (beginning at zero regardless of stack traversal direction), an error stack entry, and the client\_data pointer passed to H5E\_print. The H5E\_walk1\_t prototype is as follows:

```
typedef herr_t ( *H5E_walk1_t ) ( int n, H5E_error1_t *err_desc, void
    *client_data )
```

where the parameters have the following meanings:

*int* n

Indexed position of the error in the stack.

*H5E\_error1\_t* \*err\_desc

Pointer to a data structure describing the error. *(This structure is currently described only in the source code file hdf5/src/H5Epublic.h. That file also contains the definitive list of major and minor error codes. That information will eventually be presented as an appendix to this Reference Manual.)*

*void* \*client\_data

Pointer to client data in the format expected by the user-defined function.

**Parameters:**

<i>H5E_direction_t</i> direction	IN: Direction in which the error stack is to be walked.
<i>H5E_walk1_t</i> func	IN: Function to be called for each error encountered.
<i>void</i> *client_data	IN: Data to be passed with func.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function H5Ewalk renamed to H5Ewalk1 and deprecated in this release.

**Name:** H5Ewalk2

**Signature:**

```
herr_t H5Ewalk2( hid_t estack_id, H5E_direction_t direction, H5E_walk2_t func, void *
client_data )
```

**Purpose:**

Walks the specified error stack, calling the specified function.

**Description:**

H5Ewalk2 walks the error stack specified by `estack_id` for the current thread and calls the function specified in `func` for each error along the way.

If the value of `estack_id` is `H5E_DEFAULT`, then H5Ewalk2 walks the current error stack.

`direction` specifies whether the stack is walked from the inside out or the outside in. A value of `H5E_WALK_UPWARD` means to begin with the most specific error and end at the API; a value of `H5E_WALK_DOWNWARD` means to start at the API and end at the innermost function where the error was first detected.

`func`, a function compliant with the `H5E_walk2_t` prototype, will be called for each error in the error stack. Its arguments will include an index number `n` (beginning at zero regardless of stack traversal direction), an error stack entry `err_desc`, and the `client_data` pointer passed to `H5E_print`. The `H5E_walk2_t` prototype is as follows:

```
typedef herr_t ( *H5E_walk2_t ) ( unsigned n, const H5E_error2_t *err_desc, void
*client_data )
```

where the parameters have the following meanings:

*unsigned n*

Indexed position of the error in the stack.

*const H5E\_error2\_t \*err\_desc*

Pointer to a data structure describing the error. *(This structure is currently described only in the source code file `hdf5/src/H5Epublic.h`. That file also contains the definitive list of major and minor error codes; that information will eventually be presented as an appendix to this HDF5 Reference Manual.)*

*void \*client\_data*

Pointer to client data in the format expected by the user-defined function.

**Parameters:**

<i>hid_t estack_id</i>	IN: Error stack identifier.
<i>H5E_direction_t direction</i>	IN: Direction in which the error stack is to be walked.
<i>H5E_walk2_t func</i>	IN: Function to be called for each error encountered.
<i>void *client_data</i>	IN: Data to be passed with <code>func</code> .

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.







## H5F: File Interface

### File API Functions

These functions are designed to provide file-level access to HDF5 files. Further manipulation of objects inside a file is performed through one of APIs documented below.

#### The C Interfaces:

- |              |                       |                               |
|--------------|-----------------------|-------------------------------|
| • H5Fcreate  | • H5Fget_vfd_handle   | • H5Fget_obj_ids              |
| • H5Fopen    | • H5Fget_filesize     | • H5Fget_freespace            |
| • H5Freopen  | • H5Fget_create_plist | • H5Fget_mdc_config           |
| • H5Fclose   | • H5Fget_access_plist | • H5Fget_mdc_hit_rate         |
| • H5Fflush   | • H5Fget_info         | • H5Fget_mdc_size             |
| • H5Fis_hdf5 | • H5Fget_intent       | • H5Freset_mdc_hit_rate_stats |
| • H5Fmount   | • H5Fget_name         | • H5Fset_mdc_config           |
| • H5Funmount | • H5Fget_obj_count    |                               |

#### *Alphabetical Listing*

- |                       |                       |                               |
|-----------------------|-----------------------|-------------------------------|
| • H5Fclose            | • H5Fget_intent       | • H5Fis_hdf5                  |
| • H5Fcreate           | • H5Fget_mdc_config   | • H5Fmount                    |
| • H5Fflush            | • H5Fget_mdc_hit_rate | • H5Fopen                     |
| • H5Fget_access_plist | • H5Fget_mdc_size     | • H5Freopen                   |
| • H5Fget_create_plist | • H5Fget_name         | • H5Freset_mdc_hit_rate_stats |
| • H5Fget_filesize     | • H5Fget_obj_count    | • H5Fset_mdc_config           |
| • H5Fget_freespace    | • H5Fget_obj_ids      | • H5Funmount                  |
| • H5Fget_info         | • H5Fget_vfd_handle   |                               |

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- |                |                       |                         |
|----------------|-----------------------|-------------------------|
| • h5fcreate_f  | • h5fmount_f          | • h5fget_create_plist_f |
| • h5fopen_f    | • h5funmount_f        | • h5fget_access_plist_f |
| • h5freopen_f  | • h5fget_vfd_handle_f | • h5fget_name_f         |
| • h5fclose_f   | • h5fget_filesize_f   | • h5fget_obj_count_f    |
| • h5fflush_f   | • h5fget_freespace_f  | • h5fget_obj_ids_f      |
| • h5fis_hdf5_f |                       |                         |



*Last modified: 9 April 2009***Name:** H5Fclose**Signature:***herr\_t* H5Fclose(*hid\_t* file\_id)**Purpose:**

Terminates access to an HDF5 file.

**Description:**

H5Fclose terminates access to an HDF5 file by flushing all data to storage and terminating access to the file through file\_id.

If this is the last file identifier open for the file and no other access identifier is open (e.g., a dataset identifier, group identifier, or shared datatype identifier), the file will be fully closed and access will end.

**Delayed close:**

Note the following deviation from the above-described behavior. If H5Fclose is called for a file but one or more objects within the file remain open, those objects will remain accessible until they are individually closed. Thus, if the dataset data\_sample is open when H5Fclose is called for the file containing it, data\_sample will remain open and accessible (including writable) until it is explicitly closed. The file will be automatically closed once all objects in the file have been closed.

Be warned, however, that there are circumstances where it is not possible to delay closing a file. For example, an MPI-IO file close is a collective call; all of the processes that opened the file must close it collectively. The file cannot be closed at some time in the future by each process in an independent fashion. Another example is that an application using an AFS token-based file access privilege may destroy its AFS token after H5Fclose has returned successfully. This would make any future access to the file, or any object within it, illegal.

In such situations, applications must close all open objects in a file before calling H5Fclose. It is generally recommended to do so in all cases.

**Parameters:**

*hid\_t* file\_id      IN: Identifier of a file to terminate access to.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5fclose\_f

```

SUBROUTINE h5fclose_f(file_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: file_id ! File identifier
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5fclose_f
```

*Last modified: 15 May 2009***Name:** H5Fcreate**Signature:**

```
hid_t H5Fcreate( const char *name, unsigned flags, hid_t fcpl_id, hid_t fapl_id )
```

**Purpose:**

Creates an HDF5 file.

**Description:**

H5Fcreate is the primary function for creating HDF5 files; it creates a new HDF5 file with the specified name and property lists and specifies whether an existing file of same name should be overwritten.

The name parameter specifies the name of the new file.

The flags parameter specifies whether an existing file is to be overwritten. It should be set to either H5F\_ACC\_TRUNC to overwrite an existing file or H5F\_ACC\_EXCL, instructing the function to fail if the file already exists.

New files are always created in read-write mode, so the read-write and read-only flags, H5F\_ACC\_RDWR and H5F\_ACC\_RDONLY, respectively, are not relevant in this function. Further note that a specification of H5F\_ACC\_RDONLY will be ignored; the file will be created in read-write mode, regardless.

More complex behaviors of file creation and access are controlled through the file creation and file access property lists, fcpl\_id and fapl\_id, respectively. The value of H5P\_DEFAULT for any property list value indicates that the library should use the default values for that appropriate property list.

The return value is a file identifier for the newly-created file; this file identifier should be closed by calling H5Fclose when it is no longer needed.

**Special case -- File creation in the case of an already-open file:**

If a file being created is already opened, by either a previous H5Fopen or H5Fcreate call, the HDF5 library may or may not detect that the open file and the new file are the same physical file. (See H5Fopen regarding the limitations in detecting the re-opening of an already-open file.)

If the library detects that the file is already opened, H5Fcreate will return a failure, regardless of the use of H5F\_ACC\_TRUNC.

If the library does not detect that the file is already opened and H5F\_ACC\_TRUNC is not used, H5Fcreate will return a failure because the file already exists. Note that this is correct behavior.

But if the library does not detect that the file is already opened and H5F\_ACC\_TRUNC is used, H5Fcreate will truncate the existing file and return a valid file identifier. Such a truncation of a currently-opened file will almost certainly result in errors. While unlikely, the HDF5 library may not be able to detect, and thus report, such errors.

Applications should avoid calling H5Fcreate with an already opened file.

**Parameters:**

<i>const char *</i> name	IN: Name of the file to access.
<i>uintn</i> flags	IN: File access flags. Allowable values are: H5F_ACC_TRUNC

Truncate file, if it already exists, erasing all data previously stored in the file.

H5F\_ACC\_EXCL

Fail if file already exists.

- ◆ H5F\_ACC\_TRUNC and H5F\_ACC\_EXCL are mutually exclusive; use exactly one.
- ◆ An additional flag, H5F\_ACC\_DEBUG, prints debug information. This flag can be combined with one of the above values using the bit-wise OR operator ('|'), but it is used only by HDF5 Library developers; *it is neither tested nor supported* for use in applications.

*hid\_t* fcpl\_id

IN: File creation property list identifier, used when modifying default file meta-data. Use H5P\_DEFAULT to specify default file creation properties.

*hid\_t* fapl\_id

IN: File access property list identifier. If parallel file access is desired, this is a collective call according to the communicator stored in the fapl\_id. Use H5P\_DEFAULT for default file access properties.

### Returns:

Returns a file identifier if successful; otherwise returns a negative value.

### Fortran90 Interface: h5fcreate\_f

```
SUBROUTINE h5fcreate_f(name, access_flags, file_id, hdferr, &
                      creation_prp, access_prp)

  IMPLICIT NONE
  CHARACTER(LEN=*) , INTENT(IN) :: name      ! Name of the file
  INTEGER, INTENT(IN) :: access_flag         ! File access flags
                                              ! Possible values are:
                                              !     H5F_ACC_RDWR_F
                                              !     H5F_ACC_RDONLY_F
                                              !     H5F_ACC_TRUNC_F
                                              !     H5F_ACC_EXCL_F
                                              !     H5F_ACC_DEBUG_F

  INTEGER(HID_T), INTENT(OUT) :: file_id ! File identifier
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                              ! 0 on success and -1 on failure

  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: creation_prp
                                              ! File creation property
                                              ! list identifier, if not
                                              ! specified its value is
                                              ! H5P_DEFAULT_F

  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: access_prp
                                              ! File access property list
                                              ! identifier, if not
                                              ! specified its value is
                                              ! H5P_DEFAULT_F

END SUBROUTINE h5fcreate_f
```

**Name:** H5Fflush

**Signature:**

*herr\_t* H5Fflush(*hid\_t* object\_id, *H5F\_scope\_t* scope )

**Purpose:**

Flushes all buffers associated with a file to disk.

**Description:**

H5Fflush causes all buffers associated with a file to be immediately flushed to disk without removing the data from the cache.

object\_id can be any object associated with the file, including the file itself, a dataset, a group, an attribute, or a named data type.

scope specifies whether the scope of the flushing action is global or local. Valid values are

H5F_SCOPE_GLOBAL	Flushes the entire virtual file.
H5F_SCOPE_LOCAL	Flushes only the specified file.

**Note:**

HDF5 does not possess full control over buffering. H5Fflush flushes the internal HDF5 buffers then asks the operating system (the OS) to flush the system buffers for the open files. After that, the OS is responsible for ensuring that the data is actually flushed to disk.

**Parameters:**

<i>hid_t</i> object_id	IN: Identifier of object used to identify the file.
<i>H5F_scope_t</i> scope	IN: Specifies the scope of the flushing action.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5fflush\_f

```
SUBROUTINE h5fflush_f(obj_id, scope, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)  :: obj_id      ! Object identifier
  INTEGER, INTENT(IN)         :: scope       ! Flag with two possible values:
                                           !   H5F_SCOPE_GLOBAL_F
                                           !   H5F_SCOPE_LOCAL_F
  INTEGER, INTENT(OUT)        :: hdferr      ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5fflush_f
```



**Name:** H5Fget\_access\_plist

**Signature:**

`hid_t H5Fget_access_plist(hid_t file_id)`

**Purpose:**

Returns a file access property list identifier.

**Description:**

H5Fget\_access\_plist returns the file access property list identifier of the specified file.

See "File Access Properties" in H5P: Property List Interface in this reference manual and "File Access Property Lists" in *Files* in the *HDF5 User's Guide* for additional information and related functions.

**Parameters:**

`hid_t file_id`      IN: Identifier of file to get access property list of

**Returns:**

Returns a file access property list identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5fget\_access\_plist\_f

```
SUBROUTINE h5fget_access_plist_f(file_id, fcpl_id, hdferr)

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN)    :: file_id ! File identifier
    INTEGER(HID_T), INTENT(OUT)   :: fcpl_id ! File access property list identifier
    INTEGER, INTENT(OUT)          :: hdferr  ! Error code
                                     ! 0 on success and -1 on failure

END SUBROUTINE h5fget_access_plist_f
```

**Name:** H5Fget\_create\_plist

**Signature:**

`hid_t H5Fget_create_plist(hid_t file_id)`

**Purpose:**

Returns a file creation property list identifier.

**Description:**

H5Fget\_create\_plist returns a file creation property list identifier identifying the creation properties used to create this file. This function is useful for duplicating properties when creating another file.

See "File Creation Properties" in H5P: Property List Interface in this reference manual and "File Creation Properties" in *Files* in the *HDF5 User's Guide* for additional information and related functions.

The creation property list identifier should be released with H5Pclose.

**Parameters:**

`hid_t file_id`      IN: File identifier

**Returns:**

Returns a file creation property list identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5fget\_create\_plist\_f

```
SUBROUTINE h5fget_create_plist_f(file_id, fcpl_id, hdferr)

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN)    :: file_id ! File identifier
    INTEGER(HID_T), INTENT(OUT)   :: fcpl_id ! File creation property list
                                           ! identifier
    INTEGER, INTENT(OUT)          :: hdferr  ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5fget_create_plist_f
```

**Name:** H5Fget\_filesize

**Signature:**

```
herr_t H5Fget_filesize(hid_t file_id, hsize_t *size)
```

**Purpose:**

Returns the size of an HDF5 file.

**Description:**

H5Fget\_filesize returns the size of the HDF5 file specified by *file\_id*.

The returned size is that of the entire file, as opposed to only the HDF5 portion of the file. I.e., *size* includes the user block, if any, the HDF5 portion of the file, and any data that may have been appended beyond the data written through the HDF5 Library.

**Parameters:**

*hid\_t* file\_id

IN: Identifier of a currently-open HDF5 file

*hsize\_t* \*size

OUT: Size of the file, in bytes.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5fget\_freespace\_f

```
SUBROUTINE h5fget_filesize_f(file_id, size, hdferr)
```

```

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: file_id      ! file identifier
    INTEGER(HSIZE_T), INTENT(OUT) :: size      ! Size of the file
    INTEGER, INTENT(OUT) :: hdferr             ! Error code: 0 on success,
                                              ! -1 if fail
END SUBROUTINE h5fget_filesize_f
```

**History:**

**Release**    **C**

1.6.3        Function introduced in this release.  
              Fortran subroutine introduced in this release.

**Name:** H5Fget\_freespace

**Signature:**

*hssize\_t* H5Fget\_freespace(*hid\_t* file\_id)

**Purpose:**

Returns the amount of free space in a file.

**Description:**

Given the identifier of an open file, *file\_id*, H5Fget\_freespace returns the amount of space that is unused by any objects in the file.

Currently, the HDF5 library only tracks free space in a file from a file open or create until that file is closed, so this routine will only report the free space that has been created during that interval.

**Parameters:**

*hid\_t* file\_id      IN: Identifier of a currently-open HDF5 file

**Returns:**

Returns the amount of free space in the file if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5fget\_freespace\_f

```
SUBROUTINE h5fget_freespace_f(file_id, free_space, hdferr)

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN)  :: file_id          ! File identifier
    INTEGER(HSSIZE_T), INTENT(OUT) :: free_space     ! Amount of free space in file
    INTEGER, INTENT(OUT)        :: hdferr           ! Error code
                                                    ! 0 on success and -1 on failure

END SUBROUTINE h5fget_freespace_f
```

**History:**

**Release    C**

1.6.1      Function introduced in this release.

**Name:** H5Fget\_info

**Signature:**

```
herr_t H5Fget_info(hid_t obj_id, H5F_info_t *file_info)
```

**Purpose:**

Returns global information for a file.

**Description:**

H5Fget\_info returns global information for the file associated with the object identifier *obj\_id* in the *H5F\_info\_t* struct named *file\_info*.

*obj\_id* is an identifier for any object in the file of interest.

An *H5F\_info\_t* struct is defined as follows (in *H5Fpublic.h*):

```
typedef struct H5F_info_t {
    hsize_t          super_ext_size;
    struct {
        hsize_t      hdr_size;
        H5_ih_info_t msgs_info;
    } sohm;
} H5F_info_t;
```

*super\_ext\_size* is the size of the superblock extension.

The *sohm* sub-struct contains shared object header message information: *hdr\_size* is the size of shared of object header messages. *msgs\_info* is a *H5\_ih\_info\_t* struct containing the cumulative shared object header message index size and heap size; an *H5\_ih\_info\_t* struct is defined as follows (in *H5public.h*):

```
typedef struct H5_ih_info_t {
    hsize_t      index_size;
    hsize_t      heap_size;
} H5_ih_info_t;
```

*index\_size* is the summed size of all of the shared of object header indexes. Each index might be either a B-tree or a list. *heap\_size* is the size of the heap.

**Parameters:**

```
hid_t obj_id,           IN: Object identifier for any object in the file.
H5F_info_t *file_info  OUT: Struct containing global file information.
```

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Fget\_intent

**Signature:**

*herr\_t* H5Fget\_intent(*hid\_t* file\_id, *unsigned* \*intent)

**Purpose:**

Determines the read/write or read-only status of a file.

**Description:**

Given the identifier of an open file, *file\_id*, H5Fget\_intent retrieves the 'intended access mode' flag passed with H5Fopen when the file was opened.

The value of the flag is returned in *intent*. Valid values are as follows:

H5F\_ACC\_RDWR      File was opened with read/write access.

H5F\_ACC\_RDONLY    File was opened with read-only access.

The function will not return an error if *intent* is NULL; it will simply do nothing.

**Parameters:**

*hid\_t* file\_id      IN: File identifier for a currently-open HDF5 file

*unsigned* \*intent    OUT: Intended access mode flag, as originally passed with H5Fopen.

**Returns:**

Returns the amount of free space in the file if successful; otherwise returns a negative value.

**Fortran90 Interface:** None.

**History:**

**Release    C**

1.8.0      Function introduced in this release.

**Name:** H5Fget\_mdc\_config

**Signature:**

```
herr_t H5Fget_mdc_config(hid_t file_id, H5AC_cache_config_t *config_ptr)
```

**Purpose:**

Obtain current metadata cache configuration for target file.

**Description:**

H5Fget\_mdc\_config loads the current metadata cache configuration into the instance of H5AC\_cache\_config\_t pointed to by the config\_ptr parameter.

Note that the version field of \*config\_ptr must be initialized --this allows the library to support old versions of the H5AC\_cache\_config\_t structure.

See the overview of the metadata cache in the special topics section of the user manual for details on metadata cache configuration. If you haven't read and understood that documentation, the results of this call will not make much sense.

**Parameters:**

*hid\_t* file\_id

IN: Identifier of the target file

*H5AC\_cache\_config\_t* \*config\_ptr

IN/OUT: Pointer to the instance of H5AC\_cache\_config\_t in which the current metadata cache configuration is to be reported. The fields of this structure are discussed below:

**General configuration section:**

*int* version

IN: Integer field indicating the the version of the H5AC\_cache\_config\_t in use. This field should be set to H5AC\_\_CURR\_CACHE\_CONFIG\_VERSION (defined in H5ACpublic.h).

*hbool\_t* rpt\_fcn\_enabled

OUT: Boolean flag indicating whether the adaptive cache resize report function is enabled. This field should almost always be set to FALSE. Since resize algorithm activity is reported via stdout, it MUST be set to FALSE on Windows machines.

The report function is not supported code, and can be expected to change between versions of the library. Use it at your own risk.

*hbool\_t* open\_trace\_file

OUT: Boolean field indicating whether the trace\_file\_name field should be used to open a trace file for the cache. This field will always be set to FALSE in this context.

*hbool\_t* close\_trace\_file

OUT: Boolean field indicating whether the current trace file (if any) should be closed. This field will always be set to FALSE in this context.

*char* \*trace\_file\_name

OUT: Full path name of the trace file to be opened if the `open_trace_file` field is `TRUE`. This field will always be set to the empty string in this context.

*hbool\_t* evictions\_enabled

OUT: Boolean flag indicating whether metadata cache entry evictions are enabled.

*hbool\_t* set\_initial\_size

OUT: Boolean flag indicating whether the cache should be created with a user specified initial maximum size.

*size\_t* initial\_size

If the configuration is loaded from the cache, this flag will always be `FALSE`.

OUT: Initial maximum size of the cache in bytes, if applicable.

*double* min\_clean\_fraction

If the configuration is loaded from the cache, this field will contain the cache maximum size as of the time of the call.

OUT: Float value specifying the minimum fraction of the cache that must be kept either clean or empty when possible.

*size\_t* max\_size

OUT: Upper bound (in bytes) on the range of values that the adaptive cache resize code can select as the maximum cache size.

*size\_t* min\_size

OUT: Lower bound (in bytes) on the range of values that the adaptive cache resize code can select as the maximum cache size.

*long int* epoch\_length

OUT: Number of cache accesses between runs of the adaptive cache resize code.

### Increment configuration section:

*enum H5C\_cache\_incr\_mode* incr\_mode

OUT: Enumerated value indicating the operational mode of the automatic cache size increase code. At present, only the following values are legal:

`H5C_incr__off`: Automatic cache size increase is disabled.

`H5C_incr__threshold`: Automatic cache size increase is enabled using the hit rate threshold algorithm.



<i>double</i> lower_hr_threshold	OUT: Hit rate threshold used in the hit rate threshold cache size increase algorithm.
<i>double</i> increment	OUT: The factor by which the current maximum cache size is multiplied to obtain an initial new maximum cache size if a size increase is triggered in the hit rate threshold cache size increase algorithm.
<i>hbool_t</i> apply_max_increment	OUT: Boolean flag indicating whether an upper limit will be applied to the size of cache size increases.
<i>size_t</i> max_increment	OUT: The maximum number of bytes by which the maximum cache size can be increased in a single step -- if applicable.
<i>enum H5C_cache_flash_incr_mode</i> flash_incr_mode	OUT: Enumerated value indicating the operational mode of the flash cache size increase code. At present, only the following values are legal:  H5C_flash_incr__off: Flash cache size increase is disabled.  H5C_flash_incr__add_space: Flash cache size increase is enabled using the add space algorithm.
<i>double</i> flash_threshold	OUT: The factor by which the current maximum cache size is multiplied to obtain the minimum size entry / entry size increase which may trigger a flash cache size increase.
<i>double</i> flash_multiple	OUT: The factor by which the size of the triggering entry / entry size increase is multiplied to obtain the initial cache size increment. This increment may be reduced to reflect existing free space in the cache and the max_size field above.

**Decrement configuration section:**

*enum H5C\_cache\_decr\_mode* decr\_mode

OUT: Enumerated value indicating the operational mode of the automatic cache size decrease code. At present, the following values are legal:

H5C\_decr\_\_off: Automatic cache size decrease is disabled, and the remaining decrement fields are ignored.

H5C\_decr\_\_threshold: Automatic cache size decrease is enabled using the hit rate threshold algorithm.

H5C\_decr\_\_age\_out: Automatic cache size decrease is enabled using the ageout algorithm.

H5C\_decr\_\_age\_out\_with\_threshold: Automatic cache size decrease is enabled using the ageout with hit rate threshold algorithm

*double* upper\_hr\_threshold

OUT: Upper hit rate threshold. This value is only used if the decr\_mode is either H5C\_decr\_\_threshold or H5C\_decr\_\_age\_out\_with\_threshold.

*double* decrement

OUT: Factor by which the current max cache size is multiplied to obtain an initial value for the new cache size when cache size reduction is triggered in the hit rate threshold cache size reduction algorithm.

*hbool\_t* apply\_max\_decrement

OUT: Boolean flag indicating whether an upper limit should be applied to the size of cache size decreases.

*size\_t* max\_decrement

OUT: The maximum number of bytes by which cache size can be decreased if any single step, if applicable.

*int* epochs\_before\_eviction

OUT: The minimum number of epochs that an entry must reside unaccessed in cache before being evicted under either of the ageout cache size reduction algorithms.

*hbool\_t* apply\_empty\_reserve

OUT: Boolean flag indicating whether an empty reserve should be maintained under either of the ageout cache size reduction algorithms.

*double* empty\_reserve

OUT: Empty reserve for use with the ageout cache size reduction algorithms, if applicable.

**Parallel configuration section:**

*int* dirty\_bytes\_threshold

OUT: Threshold number of bytes of dirty metadata generation for triggering synchronizations of the metadata caches serving the target file in the parallel case.

Synchronization occurs whenever the number of bytes of dirty metadata created since the last synchronization exceeds this limit.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Name:** H5Fget\_mdc\_hit\_rate

**Signature:**

*herr\_t* H5Fget\_mdc\_hit\_rate(*hid\_t* file\_id, *double* \*hit\_rate\_ptr)

**Purpose:**

Obtain target file's metadata cache hit rate.

**Description:**

H5Fget\_mdc\_hit\_rate queries the metadata cache of the target file to obtain its hit rate (cache hits / (cache hits + cache misses)) since the last time hit rate statistics were reset. If the cache has not been accessed since the last time the hit rate stats were reset, the hit rate is defined to be 0.0.

The hit rate stats can be reset either manually (via H5Freset\_mdc\_hit\_rate\_stats()), or automatically. If the cache's adaptive resize code is enabled, the hit rate stats will be reset once per epoch. If they are reset manually as well, the cache may behave oddly.

See the overview of the metadata cache in the special topics section of the user manual for details on the metadata cache and its adaptive resize algorithms.

**Parameters:**

*hid\_t* file\_id           IN: Identifier of the target file.

*double* \*hit\_rate\_ptr   OUT: Pointer to the double in which the hit rate is returned. Note that \*hit\_rate\_ptr is undefined if the API call fails.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Name:** H5Fget\_mdc\_size

**Signature:**

```
herr_t H5Fget_mdc_size(hid_t file_id, size_t *max_size_ptr, size_t
*min_clean_size_ptr, size_t *cur_size_ptr, int *cur_num_entries_ptr)
```

**Purpose:**

Obtain current metadata cache size data for specified file.

**Description:**

H5Fget\_mdc\_size queries the metadata cache of the target file for the desired size information, and returns this information in the locations indicated by the pointer parameters. If any pointer parameter is NULL, the associated data is not returned.

If the API call fails, the values returned via the pointer parameters are undefined.

If adaptive cache resizing is enabled, the cache maximum size and minimum clean size may change at the end of each epoch. Current size and current number of entries can change on each cache access.

Current size can exceed maximum size under certain conditions. See the overview of the metadata cache in the special topics section of the user manual for a discussion of this.

**Parameters:**

<i>hid_t</i> file_id	IN: Identifier of the target file.
<i>size_t</i> *max_size_ptr	OUT: Pointer to the location in which the current cache maximum size is to be returned, or NULL if this datum is not desired.
<i>size_t</i> *min_clean_size_ptr	OUT: Pointer to the location in which the current cache minimum clean size is to be returned, or NULL if that datum is not desired.
<i>size_t</i> *cur_size_ptr	OUT: Pointer to the location in which the current cache size is to be returned, or NULL if that datum is not desired.
<i>int</i> *cur_num_entries_ptr	OUT: Pointer to the location in which the current number of entries in the cache is to be returned, or NULL if that datum is not desired.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Name:** H5Fget\_name

**Signature:**

```
ssize_t H5Fget_name(hid_t obj_id, char *name, size_t size)
```

**Purpose:**

Retrieves name of file to which object belongs.

**Description:**

H5Fget\_name retrieves the name of the file to which the object `obj_id` belongs. The object can be a group, dataset, attribute, or named datatype.

Up to `size` characters of the filename are returned in `name`; additional characters, if any, are not returned to the user application.

If the length of the name, which determines the required value of `size`, is unknown, a preliminary H5Fget\_name call can be made by setting `name` to NULL. The return value of this call will be the size of the filename; that value plus one (1) can then be assigned to `size` for a second H5Fget\_name call, which will retrieve the actual name. (The value passed in with the parameter `size` must be one greater than `size` in bytes of the actual name in order to accommodate the null terminator; if `size` is set to the exact size of the name, the last byte passed back will contain the null terminator and the last character will be missing from the name passed back to the calling application.)

If an error occurs, the buffer pointed to by `name` is unchanged and the function returns a negative value.

**Parameters:**

*hid\_t* `obj_id`

IN: Identifier of the object for which the associated filename is sought. The object can be a group, dataset, attribute, or named datatype.

*char \**`name`

OUT: Buffer to contain the returned filename.

*size\_t* `size`

IN: Size, in bytes, of the name buffer.

**Returns:**

Returns the length of the filename if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5fget\_name\_f

```
SUBROUTINE h5fget_name_f(obj_id, buf, size, hdferr)
```

```

IMPLICIT NONE
INTEGER(HID_T), INTENT(IN) :: obj_id      ! Object identifier
CHARACTER(LEN=*), INTENT(INOUT) :: buf    ! Buffer to hold filename
INTEGER(SIZE_T), INTENT(OUT) :: size      ! Size of the filename
INTEGER, INTENT(OUT) :: hdferr            ! Error code: 0 on success,
                                           ! -1 if fail
END SUBROUTINE h5fget_name_f
```

**History:**

**Release**    **C**

1.6.3        Function introduced in this release.  
              Fortran subroutine introduced in this release.

**Name:** H5Fget\_obj\_count

**Signature:**

```
ssize_t H5Fget_obj_count( hid_t file_id, unsigned int types )
```

**Purpose:**

Returns the number of open object identifiers for an open file.

**Description:**

Given the identifier of an open file, `file_id`, and the desired object types, `types`, `H5Fget_obj_count` returns the number of open object identifiers for the file.

To retrieve a count of open identifiers for open objects in all HDF5 application files that are currently open, pass the value `H5F_OBJ_ALL` in `file_id`.

The types of objects to be counted are specified in `types` as follows:

<code>H5F_OBJ_FILE</code>	Files only
<code>H5F_OBJ_DATASET</code>	Datasets only
<code>H5F_OBJ_GROUP</code>	Groups only
<code>H5F_OBJ_DATATYPE</code>	Named datatypes only
<code>H5F_OBJ_ATTR</code>	Attributes only
<code>H5F_OBJ_ALL</code>	All of the above (I.e., <code>H5F_OBJ_FILE   H5F_OBJ_DATASET   H5F_OBJ_GROUP   H5F_OBJ_DATATYPE   H5F_OBJ_ATTR</code> )
<code>H5F_OBJ_LOCAL</code>	Restrict search to objects opened through current file identifier.

Multiple object types can be combined with the logical OR operator (`|`). For example, the expression `(H5F_OBJ_DATASET | H5F_OBJ_GROUP)` would call for datasets and groups.

**Parameters:**

`hid_t file_id` IN: Identifier of a currently-open HDF5 file or `H5F_OBJ_ALL` for all currently-open HDF5 files.

`unsigned int types` IN: Type of object for which identifiers are to be returned.

**Returns:**

Returns the number of open objects if successful; otherwise returns a negative value.

**Fortran90 Interface:** `h5fget_obj_count_f`

```
SUBROUTINE h5fget_obj_count_f(file_id, obj_type, obj_count, hdferr)
```

```

IMPLICIT NONE
INTEGER(HID_T), INTENT(IN)  :: file_id    ! File identifier
INTEGER, INTENT(IN)        :: obj_type    ! Object types, possible values are:
                                         !   H5F_OBJ_FILE_F
                                         !   H5F_OBJ_GROUP_F
                                         !   H5F_OBJ_DATASET_F
                                         !   H5F_OBJ_DATATYPE_F
                                         !   H5F_OBJ_ALL_F
INTEGER, INTENT(OUT)        :: obj_count  ! Number of opened objects
INTEGER, INTENT(OUT)        :: hdferr    ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5fget_obj_count_f
```

**History:**

<b>Release</b>	<b>Change</b>
1.6.5	H5F_OBJ_LOCAL has been added as a qualifier on the types of objects to be counted. H5F_OBJ_LOCAL restricts the search to objects opened through current file identifier.
1.6.8 & 1.8.2	C function return type changed to <i>ssize_t</i> .



**Name:** H5Fget\_obj\_ids

**Signature:**

```
ssize_t H5Fget_obj_ids( hid_t file_id, unsigned int types, size_t max_objs, hid_t
*obj_id_list )
```

**Purpose:**

Returns a list of open object identifiers.

**Description:**

Given the file identifier `file_id` and the type of objects to be identified, `types`, `H5Fget_obj_ids` returns the list of identifiers for all open HDF5 objects fitting the specified criteria.

To retrieve identifiers for open objects in all HDF5 application files that are currently open, pass the value `H5F_OBJ_ALL` in `file_id`.

The types of object identifiers to be retrieved are specified in `types` using the codes listed for the same parameter in `H5Fget_obj_count`

To retrieve identifiers for all open objects, pass a negative value for the `max_objs`.

**Parameters:**

<code>hid_t file_id</code>	IN: Identifier of a currently-open HDF5 file or <code>H5F_OBJ_ALL</code> for all currently-open HDF5 files.
<code>unsigned int types</code>	IN: Type of object for which identifiers are to be returned.
<code>size_t max_objs</code>	IN: Maximum number of object identifiers to place into <code>obj_id_list</code> .
<code>hid_t *obj_id_list</code>	OUT: Pointer to the returned list of open object identifiers.

**Returns:**

Returns number of objects placed into `obj_id_list` if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5fget\_obj\_ids\_f

```
SUBROUTINE h5fget_obj_ids_f(file_id, obj_type, max_objs, obj_ids, hdferr)
```

```

IMPLICIT NONE
INTEGER(HID_T), INTENT(IN)    :: file_id ! File identifier
INTEGER,          INTENT(IN)  :: obj_type ! Object types, possible values are:
                                     !      H5F_OBJ_FILE_F
                                     !      H5F_OBJ_GROUP_F
                                     !      H5F_OBJ_DATASET_F
                                     !      H5F_OBJ_DATATYPE_F
                                     !      H5F_OBJ_ALL_F
INTEGER, INTENT(IN)          :: max_objs ! Maximum number of object
                                     ! identifiers to retrieve
INTEGER(HID_T), DIMENSION(*), INTENT(OUT) :: obj_ids
                                     ! Array of requested object
                                     ! identifiers
INTEGER, INTENT(OUT)          :: hdferr  ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5fget_obj_ids_f
```

**History:**

Release	Change
1.6.0	C function introduced in this release.
1.6.8 & 1.8.2	C function return type changed to <code>ssize_t</code> and <code>max_objs</code> parameter datatype changed to <code>size_t</code> .

**Name:** H5Fget\_vfd\_handle

**Signature:**

```
herr_t H5Fget_vfd_handle(hid_t file_id, hid_t fapl_id, void **file_handle)
```

**Purpose:**

Returns pointer to the file handle from the virtual file driver.

**Description:**

Given the file identifier `file_id` and the file access property list `fapl_id`, `H5Fget_vfd_handle` returns a pointer to the file handle from the low-level file driver currently being used by the HDF5 library for file I/O.

**Notes:**

Users are not supposed to modify any file through this file handle.

This file handle is dynamic and is valid only while the file remains open; it will be invalid if the file is closed and reopened or opened during a subsequent session.

**Parameters:**

<i>hid_t</i> file_id	IN: Identifier of the file to be queried.
<i>hid_t</i> fapl_id	IN: File access property list identifier. For most drivers, the value will be <code>H5P_DEFAULT</code> . For the <code>FAMILY</code> or <code>MULTI</code> drivers, this value should be defined through the property list functions: <code>H5Pset_family_offset</code> for the <code>FAMILY</code> driver and <code>H5Pset_multi_type</code> for the <code>MULTI</code> driver.
<i>void</i> **file_handle	OUT: Pointer to the file handle being used by the low-level virtual file driver.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Fis\_hdf5

**Signature:**

*htri\_t* H5Fis\_hdf5(*const char* \*name )

**Purpose:**

Determines whether a file is in the HDF5 format.

**Description:**

H5Fis\_hdf5 determines whether a file is in the HDF5 format.

**Parameters:**

*const char* \*name           IN: File name to check format.

**Returns:**

When successful, returns a positive value, for TRUE, or 0 (zero), for FALSE.

On any error, including the case that the file does not exist, returns a negative value.

**Fortran90 Interface:** h5fis\_hdf5\_f

```
SUBROUTINE h5fis_hdf5_f(name, status, hdferr)
  IMPLICIT NONE
  CHARACTER(LEN=*) , INTENT(IN) :: name      ! Name of the file
  LOGICAL , INTENT(OUT) :: status             ! This parameter indicates
                                              ! whether file is an HDF5 file
                                              ! ( TRUE or FALSE )
  INTEGER , INTENT(OUT) :: hdferr             ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5fis_hdf5_f
```

**Name:** H5Fmount

**Signature:**

```
herr_t H5Fmount(hid_t loc_id, const char *name, hid_t child_id, hid_t plist_id)
```

**Purpose:**

Mounts a file.

**Description:**

H5Fmount mounts the file specified by *child\_id* onto the group specified by *loc\_id* and name using the mount properties *plist\_id*.

Note that *loc\_id* is either a file or group identifier and name is relative to *loc\_id*.

**Parameters:**

<i>hid_t</i> loc_id	IN: Identifier for of file or group in which name is defined.
<i>const char</i> *name	IN: Name of the group onto which the file specified by <i>child_id</i> is to be mounted.
<i>hid_t</i> child_id	IN: Identifier of the file to be mounted.
<i>hid_t</i> plist_id	IN: Identifier of the property list to be used.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5fmount\_f

```
SUBROUTINE h5fmount_f(loc_id, name, child_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)  :: loc_id      ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN):: name       ! Group name at locationloc_id
  INTEGER(HID_T), INTENT(IN)  :: child_id   ! File(to be mounted) identifier
  INTEGER, INTENT(OUT)        :: hdferr     ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5fmount_f
```

*Last modified: 15 May 2009***Name:** H5Fopen**Signature:***hid\_t* H5Fopen( *const char* \*name, *unsigned* flags, *hid\_t* fapl\_id )**Purpose:**

Opens an existing HDF5 file.

**Description:**

H5Fopen is the primary function for accessing existing HDF5 files. This function opens the named file in the specified access mode and with the specified access property list.

Note that H5Fopen does not create a file if it does not already exist; see H5Fcreate.

The name parameter specifies the name of the file to be opened.

The fapl\_id parameter specifies the file access property list. Use of H5P\_DEFAULT specifies that default I/O access properties are to be used

The flags parameter specifies whether the file will be opened in read-write or read-only mode, H5F\_ACC\_RDWR or H5F\_ACC\_RDONLY, respectively. More complex behaviors of file access are controlled through the file-access property list.

The return value is a file identifier for the open file; this file identifier should be closed by calling H5Fclose when it is no longer needed.

**Special case -- Multiple opens:**

A file can often be opened with a new H5Fopen call without closing an already-open identifier established in a previous H5Fopen or H5Fcreate call. Each such H5Fopen call will return a unique identifier and the file can be accessed through any of these identifiers as long as the identifier remains valid. In such multiply-opened cases, all the open calls should use the same flags argument.

In some cases, such as files on a local Unix file system, the HDF5 library can detect that a file is multiply opened and will maintain coherent access among the file identifiers.

But in many other cases, such as parallel file systems or networked file systems, it is not always possible to detect multiple opens of the same physical file. In such cases, HDF5 will treat the file identifiers as though they are accessing different files and will be unable to maintain coherent access. Errors are likely to result in these cases. While unlikely, the HDF5 library may not be able to detect, and thus report, such errors.

It is generally recommended that applications avoid multiple opens of the same file.

**Parameters:**

<i>const char</i> *name	IN: Name of the file to be created.
<i>unsigned</i> flags	IN: File access flags. Allowable values are: <ul style="list-style-type: none"> <li>H5F_ACC_RDWR Allow read and write access to file.</li> <li>H5F_ACC_RDONLY Allow read-only access to file.</li> </ul> ◇ H5F_ACC_RDWR and H5F_ACC_RDONLY are mutually exclusive; use exactly one.

◊ An additional flag, `H5F_ACC_DEBUG`, prints debug information. This flag can be combined with one of the above values using the bit-wise OR operator (`|`), but it is used only by HDF5 Library developers; *it is neither tested nor supported* for use in applications.

`hid_t fapl_id`      IN: Identifier for the file access properties list. If parallel file access is desired, this is a collective call according to the communicator stored in the `fapl_id`. Use `H5P_DEFAULT` for default file access properties.

### Returns:

Returns a file identifier if successful; otherwise returns a negative value.

### Fortran90 Interface: h5fopen\_f

```
SUBROUTINE h5fopen_f(name, access_flags, file_id, hdferr, &
                    access_prp)

    IMPLICIT NONE
    CHARACTER(LEN=*), INTENT(IN) :: name      ! Name of the file
    INTEGER, INTENT(IN) :: access_flag        ! File access flags
                                              ! Possible values are:
                                              !      H5F_ACC_RDWR_F
                                              !      H5F_ACC_RDONLY_F
    INTEGER(HID_T), INTENT(OUT) :: file_id    ! File identifier
    INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                              ! 0 on success and -1 on failure
    INTEGER(HID_T), OPTIONAL, INTENT(IN) :: access_prp
                                              ! File access property list
                                              ! identifier

END SUBROUTINE h5fopen_f
```

**Name:** H5Freopen

**Signature:**

*hid\_t* H5Freopen(*hid\_t* file\_id)

**Purpose:**

Returns a new identifier for a previously-opened HDF5 file.

**Description:**

H5Freopen returns a new file identifier for an already-open HDF5 file, as specified by *file\_id*. Both identifiers share caches and other information. The only difference between the identifiers is that the new identifier is not mounted anywhere and no files are mounted on it.

Note that there is no circumstance under which H5Freopen can actually open a closed file; the file must already be open and have an active *file\_id*. E.g., one cannot close a file with H5Fclose (*file\_id*) then use H5Freopen (*file\_id*) to reopen it.

The new file identifier should be closed by calling H5Fclose when it is no longer needed.

**Parameters:**

*hid\_t* file\_id      IN: Identifier of a file for which an additional identifier is required.

**Returns:**

Returns a new file identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5freopen\_f

```
SUBROUTINE h5freopen_f(file_id, new_file_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)  :: file_id      ! File identifier
  INTEGER(HID_T), INTENT(OUT) :: new_file_id ! New file identifier
  INTEGER, INTENT(OUT)        :: hdferr       ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5freopen_f
```

**Name:** H5Freset\_mdc\_hit\_rate\_stats

**Signature:**

*herr\_t* H5Freset\_mdc\_hit\_rate\_stats(*hid\_t* file\_id)

**Purpose:**

Reset hit rate statistics counters for the target file.

**Description:**

H5Freset\_mdc\_hit\_rate\_stats resets the hit rate statistics counters in the metadata cache associated with the specified file.

If the adaptive cache resizing code is enabled, the hit rate statistics are reset at the beginning of each epoch. This API call allows you to do the same thing from your program.

The adaptive cache resizing code may behave oddly if you use this call when adaptive cache resizing is enabled. However, the call should be useful if you choose to control metadata cache size from your program.

See the overview of the metadata cache in the special topics section of the user manual for details of the metadata cache and the adaptive cache resizing algorithms. If you haven't read, understood, and thought about the material covered in that documentation, you shouldn't be using this API call.

**Parameters:**

*hid\_t* file\_id      IN: Identifier of the target file.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.



*Last modified: 18 May 2009***Name:** H5Fset\_mdc\_config**Signature:***herr\_t* H5Fset\_mdc\_config(*hid\_t* file\_id, *H5AC\_cache\_config\_t* \*config\_ptr)**Purpose:**

Attempt to configure metadata cache of target file.

**Description:**

H5Fset\_mdc\_config attempts to configure the file's metadata cache according configuration supplied in \*config\_ptr.

See the overview of the metadata cache in the special topics section of the user manual for details on what is being configured. If you haven't read and understood that documentation, you really shouldn't be using this API call.

**Parameters:***hid\_t* file\_id

IN: Identifier of the target file

*H5AC\_cache\_config\_t* \*config\_ptr

IN: Pointer to the instance of *H5AC\_cache\_config\_t* containing the desired configuration. The fields of this structure are discussed below:

**General configuration section:***int* version

IN: Integer field indicating the the version of the *H5AC\_cache\_config\_t* in use. This field should be set to *H5AC\_\_CURR\_CACHE\_CONFIG\_VERSION* (defined in *H5ACpublic.h*).

*hbool\_t* rpt\_fcn\_enabled

IN: Boolean flag indicating whether the adaptive cache resize report function is enabled. This field should almost always be set to *FALSE*. Since resize algorithm activity is reported via stdout, it **MUST** be set to *FALSE* on Windows machines.

The report function is not supported code, and can be expected to change between versions of the library. Use it at your own risk.

*hbool\_t* open\_trace\_File

IN: Boolean field indicating whether the *trace\_file\_name* field should be used to open a trace file for the cache.

The trace file is a debugging feature that allows the capture of top level metadata cache requests for purposes of debugging and/or optimization. This field should normally be set to *FALSE*, as trace file collection imposes considerable overhead.

This field should only be set to TRUE when the `trace_file_name` contains the full path of the desired trace file, and either there is no open trace file on the cache, or the `close_trace_file` field is also TRUE.

The trace file feature is unsupported unless used at the direction of THG. It is intended to allow THG to collect a trace of cache activity in cases of occult failures and/or poor performance seen in the field, so as to aid in reproduction in the lab. If you use it absent the direction of THG, you are on your own.

*hbool\_t* `close_trace_file`

IN: Boolean field indicating whether the current trace file (if any) should be closed.

See the above comments on the `open_trace_file` field. This field should be set to FALSE unless there is an open trace file on the cache that you wish to close.

The trace file feature is unsupported unless used at the direction of THG. It is intended to allow THG to collect a trace of cache activity in cases of occult failures and/or poor performance seen in the field, so as to aid in reproduction in the lab. If you use it absent the direction of THG, you are on your own.

*char* `trace_file_name[]`

IN: Full path of the trace file to be opened if the `open_trace_file` field is TRUE.

In the parallel case, an ascii representation of the mpi rank of the process will be appended to the file name to yield a unique trace file name for each process.

The length of the path must not exceed `H5AC__MAX_TRACE_FILE_NAME_LEN` characters.

The trace file feature is unsupported unless used at the direction of THG. It is intended to allow THG to collect a trace of cache activity in cases of occult failures and/or poor performance seen in the field, so as to aid in reproduction in the lab. If you use it absent the direction of THG, you are on your own.

*hbool\_t* `evictions_enabled`

IN: A boolean flag indicating whether evictions from the metadata cache are enabled. This flag is initially set to TRUE.

In rare circumstances, the raw data throughput requirements may be so high that the user wishes to postpone metadata writes so as to reserve I/O throughput for raw data. The `evictions_enabled` field exists to allow this. However, this is an extreme step, and you have no business doing it unless you have read the User Guide section on metadata caching, and have considered all other options carefully.

The `evictions_enabled` field may not be set to `FALSE` unless all adaptive cache resizing code is disabled via the `incr_mode`, `flash_incr_mode`, and `decr_mode` fields.

When this flag is set to `FALSE`, the metadata cache will not attempt to evict entries to make space for new entries, and thus will grow without bound.

Evictions will be re-enabled when this field is set back to `TRUE`. This should be done as soon as possible.

IN: Boolean flag indicating whether the cache should be forced to the user specified initial size.

IN: If `set_initial_size` is `TRUE`, `initial_size` must contain the desired initial size in bytes. This value must lie in the closed interval `[min_size, max_size]`. (see below)

IN: This field specifies the minimum fraction of the cache that must be kept either clean or empty.

The value must lie in the interval `[0.0, 1.0]`. 0.01 is a good place to start in the serial case. In the parallel case, a larger value is needed -- see the overview of the metadata cache in the *HDF5 Special Topics* section of the *HDF5 User's Guide* for details.

IN: Upper bound (in bytes) on the range of values that the adaptive cache resize code can select as the maximum cache size.

IN: Lower bound (in bytes) on the range of values that the adaptive cache resize code can select as the maximum cache size.

IN: Number of cache accesses between runs of the adaptive cache resize code. 50,000 is a good starting number.

`hbool_t set_initial_size`

`size_t initial_size`

`double min_clean_fraction`

`size_t max_size`

`size_t min_size`

`long int epoch_length`

**Increment configuration section:**

*enum H5C\_cache\_incr\_mode* incr\_mode

IN: Enumerated value indicating the operational mode of the automatic cache size increase code. At present, only two values are legal:

H5C\_incr\_\_off: Automatic cache size increase is disabled, and the remaining increment fields are ignored.

H5C\_incr\_\_threshold: Automatic cache size increase is enabled using the hit rate threshold algorithm.

*double* lower\_hr\_threshold

IN: Hit rate threshold used by the hit rate threshold cache size increment algorithm.

When the hit rate over an epoch is below this threshold and the cache is full, the maximum size of the cache is multiplied by increment (below), and then clipped as necessary to stay within max\_size, and possibly max\_increment.

This field must lie in the interval [0.0, 1.0]. 0.8 or 0.9 is a good starting point.

*double* increment

IN: Factor by which the hit rate threshold cache size increment algorithm multiplies the current cache max size to obtain a tentative new cache size.

The actual cache size increase will be clipped to satisfy the max\_size specified in the general configuration, and possibly max\_increment below.

The parameter must be greater than or equal to 1.0 -- 2.0 is a reasonable value.

If you set it to 1.0, you will effectively disable cache size increases.

*hbool\_t* apply\_max\_increment

IN: Boolean flag indicating whether an upper limit should be applied to the size of cache size increases.

*size\_t* max\_increment

IN: Maximum number of bytes by which cache size can be increased in a single step -- if applicable.

*enum H5C\_cache\_flash\_incr\_mode* flash\_incr\_mode

IN: Enumerated value indicating the operational mode of the flash cache size increase code. At present, only the following values are legal:

*double* flash\_threshold

*double* flash\_multiple

#### **Decrement configuration section:**

*enum* H5C\_cache\_decr\_mode decr\_mode

H5C\_flash\_incr\_\_off: Flash cache size increase is disabled.

H5C\_flash\_incr\_\_add\_space: Flash cache size increase is enabled using the add space algorithm.

IN: The factor by which the current maximum cache size is multiplied to obtain the minimum size entry / entry size increase which may trigger a flash cache size increase.

At present, this value must lie in the range [0.1, 1.0].

IN: The factor by which the size of the triggering entry / entry size increase is multiplied to obtain the initial cache size increment. This increment may be reduced to reflect existing free space in the cache and the max\_size field above.

At present, this field must lie in the range [0.1, 10.0].

IN: Enumerated value indicating the operational mode of the automatic cache size decrease code. At present, the following values are legal:

H5C\_decr\_\_off: Automatic cache size decrease is disabled.

H5C\_decr\_\_threshold: Automatic cache size decrease is enabled using the hit rate threshold algorithm.

H5C\_decr\_\_age\_out: Automatic cache size decrease is enabled using the ageout algorithm.

H5C\_decr\_\_age\_out\_with\_threshold: Automatic cache size decrease is enabled using the ageout with hit rate threshold algorithm

*double* upper\_hr\_threshold

IN: Hit rate threshold for the hit rate threshold and ageout with hit rate threshold cache size decrement algorithms.

When `decr_mode` is `H5C_decr__threshold`, and the hit rate over a given epoch exceeds the supplied threshold, the current maximum cache size is multiplied by decrement to obtain a tentative new (and smaller) maximum cache size.

When `decr_mode` is `H5C_decr__age_out_with_threshold`, there is no attempt to find and evict aged out entries unless the hit rate in the previous epoch exceeded the supplied threshold.

This field must lie in the interval [0.0, 1.0].

For `H5C_incr__threshold`, .9995 or .99995 is a good place to start.

For `H5C_decr__age_out_with_threshold`, .999 might be more useful.

*double* decrement

IN: In the hit rate threshold cache size decrease algorithm, this parameter contains the factor by which the current max cache size is multiplied to produce a tentative new cache size.

The actual cache size decrease will be clipped to satisfy the `min_size` specified in the general configuration, and possibly `max_decrement` below.

The parameter must be in the interval [0.0, 1.0].

If you set it to 1.0, you will effectively disable cache size decreases. 0.9 is a reasonable starting point.

*hbool\_t* apply\_max\_decrement

IN: Boolean flag indicating whether an upper limit should be applied to the size of cache size decreases.

*size\_t* max\_decrement

IN: Maximum number of bytes by which the maximum cache size can be decreased in any single step -- if applicable.

*int* epochs\_before\_eviction

IN: In the ageout based cache size reduction algorithms, this field contains the minimum number of epochs an entry must remain unaccessed in cache before the cache size reduction algorithm tries to evict it. 3 is a reasonable value.

*hbool\_t* apply\_empty\_reserve

IN: Boolean flag indicating whether the ageout based decrement algorithms will maintain a empty reserve when decreasing cache size.

*double* empty\_reserve

IN: Empty reserve as a fraction of maximum cache size if applicable.

When so directed, the ageout based algorithms will not decrease the maximum cache size unless the empty reserve can be met.

The parameter must lie in the interval [0.0, 1.0]. 0.1 or 0.05 is a good place to start.

**Parallel configuration section:**

*int* dirty\_bytes\_threshold

IN: Threshold number of bytes of dirty metadata generation for triggering synchronizations of the metadata caches serving the target file in the parallel case.

Synchronization occurs whenever the number of bytes of dirty metadata created since the last synchronization exceeds this limit.

This field only applies to the parallel case. While it is ignored elsewhere, it can still draw a value out of bounds error.

It must be consistent across all caches on any given file.

By default, this field is set to 256 KB. It shouldn't be more than half the current max cache size times the min clean fraction.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Name:** H5Funmount

**Signature:**

*herr\_t* H5Funmount(*hid\_t* loc\_id, *const char* \*name )

**Purpose:**

Unmounts a file.

**Description:**

Given a mount point, H5Funmount dissassociates the mount point's file from the file mounted there. This function does not close either file.

The mount point can be either the group in the parent or the root group of the mounted file (both groups have the same name). If the mount point was opened before the mount then it is the group in the parent; if it was opened after the mount then it is the root group of the child.

Note that loc\_id is either a file or group identifier and name is relative to loc\_id.

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier for the location at which the specified file is to be unmounted.
<i>const char</i> *name	IN: Name of the mount point.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5funmount\_f

```
SUBROUTINE h5funmount_f(loc_id, name, child_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)  :: loc_id      ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN):: name        ! Group name at location loc_id
  INTEGER, INTENT(OUT)        :: hdferr      ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5funmount_f
```

Last modified: 25 April 2009



## H5G: Group Interface

### Group Object API Functions

The Group interface functions create and manipulate groups of objects in an HDF5 file. In the following lists, *italic type* indicates a configurable macro.

#### The C Interfaces:

- |                    |                       |                           |
|--------------------|-----------------------|---------------------------|
| • <i>H5Gcreate</i> | • H5Gmove *           | • H5Gget_objinfo *        |
| • H5Gcreate1 *     | • H5Gmove2 *          | • H5Gget_num_objs *       |
| • H5Gcreate2       | • H5Glink *           | • H5Gget_create_plist     |
| • H5Gcreate_anon   | • H5Glink2 *          | • H5Gget_linkval *        |
| • <i>H5Gopen</i>   | • H5Gunlink *         | • H5Giterate *            |
| • H5Gopen1 *       | • H5Gset_comment *    | • H5Gget_info_by_idx      |
| • H5Gopen2         | • H5Gget_comment *    | • H5Gget_objname_by_idx * |
| • H5Gclose         | • H5Gget_info         | • H5Gget_objtype_by_idx * |
|                    | • H5Gget_info_by_name |                           |

*\* Use of these functions is deprecated in Release 1.8.0.*

#### Alphabetical Listing

- |                       |                           |                    |
|-----------------------|---------------------------|--------------------|
| • H5Gclose            | • H5Gget_info             | • H5Glink2 *       |
| • <i>H5Gcreate</i>    | • H5Gget_info_by_idx      | • H5Gmove *        |
| • H5Gcreate1 *        | • H5Gget_info_by_name     | • H5Gmove2 *       |
| • H5Gcreate2          | • H5Gget_num_objs *       | • <i>H5Gopen</i>   |
| • H5Gcreate_anon      | • H5Gget_objinfo *        | • H5Gopen1 *       |
| • H5Gget_comment *    | • H5Gget_objname_by_idx * | • H5Gopen2         |
| • H5Gget_create_plist | • H5Gget_objtype_by_idx * | • H5Gset_comment * |
| • H5Gget_linkval *    | • H5Giterate *            | • H5Gunlink *      |
|                       | • H5Glink *               |                    |

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- |                         |                         |                      |
|-------------------------|-------------------------|----------------------|
| • h5gclose_f            | • h5gget_info_f         | • h5glink2_f *       |
| • <i>h5gcreate_f</i>    | • h5gget_info_by_idx_f  | • h5gmove_f *        |
| • h5gcreate_anon_f      | • h5gget_info_by_name_f | • h5gmove2_f *       |
| • h5gget_comment_f *    | • h5giterate_f *        | • <i>h5gopen_f</i>   |
| • h5gget_create_plist_f | • h5glink_f *           | • h5gset_comment_f * |
| • h5gget_linkval_f *    |                         | • h5gunlink_f        |
|                         |                         | *                    |

*\* Use of these functions is deprecated in Release 1.8.0.*

## Groups in HDF5:

A group associates names with objects and provides a mechanism for mapping a name to an object. Since all objects appear in at least one group (with the possible exception of the root object) and since objects can have names in more than one group, the set of all objects in an HDF5 file is a directed graph. The internal nodes (nodes with out-degree greater than zero) must be groups while the leaf nodes (nodes with out-degree zero) are either empty groups or objects of some other type. Exactly one object in every non-empty file is the root object. The root object always has a positive in-degree because it is pointed to by the file super block.

## Group implementations in HDF5:

The original HDF5 group implementation provided a single indexed structure for link storage. A new group implementation, in HDF5 Release 1.8.0, enables more efficient compact storage for very small groups, improved link indexing for large groups, and other advanced features.

- The *original indexed* format remains the default. Links are stored in a B-tree in the group's local heap.
- Groups created in the new *compact-or-indexed* format, the implementation introduced with Release 1.8.0, can be tuned for performance, switching between the compact and indexed formats at thresholds set in the user application.
  - ◆ The *compact* format will conserve file space and processing overhead when working with small groups and is particularly valuable when a group contains no links. Links are stored as a list of messages in the group's header.
  - ◆ The *indexed* format will yield improved performance when working with large groups, e.g., groups containing thousands to millions of members. Links are stored in a fractal heap and indexed with an improved B-tree.
- The new implementation also enables the use of link names consisting of non-ASCII character sets (see `H5Pset_char_encoding`) and is required for all link types other than hard or soft links, e.g., external and user-defined links (see the H5L APIs).

The original group structure and the newer structures are not directly interoperable. By default, a group will be created in the original indexed format. An existing group can be changed to a compact-or-indexed format if the need arises; there is no capability to change back. As stated above, once in the compact-or-indexed format, a group can switch between compact and indexed as needed.

Groups will be initially created in the compact-or-indexed format only when one or more of the following conditions is met:

- The *low version bound* value of the *library version bounds* property has been set to Release 1.8.0 or later in the file access property list (see `H5Pset_libver_bounds`). Currently, that would require an `H5Pset_libver_bounds` call with the *low* parameter set to `H5F_LIBVER_LATEST`.

When this property is set for an HDF5 file, all objects in the file will be created using the latest available format; no effort will be made to create a file that can be read by older libraries.

- The creation order tracking property, `H5P_CRT_ORDER_TRACKED`, has been set in the group creation property list (see `H5Pset_link_creation_order`).

An existing group, currently in the original indexed format, will be converted to the compact-or-indexed format upon the occurrence of any of the following events:

- An external or user-defined link is inserted into the group.
- A link named with a string composed of non-ASCII characters is inserted into the group.

The compact-or-indexed format offers performance improvements that will be most notable at the extremes, i.e., in groups with zero members and in groups with tens of thousands of members. But measurable differences may sometimes appear at a threshold as low as eight group members. Since these performance thresholds and criteria differ from application to application, tunable settings are provided to govern the switch between the compact and indexed formats (see `H5Pset_link_phase_change`). Optimal thresholds will depend on the application and the operating environment.

Future versions of HDF5 will retain the ability to create, read, write, and manipulate all groups stored in either the original indexed format or the compact-or-indexed format.

### **Locating objects in the HDF5 file hierarchy:**

An object name consists of one or more components separated from one another by slashes. An absolute name begins with a slash and the object is located by looking for the first component in the root object, then looking for the second component in the first object, etc., until the entire name is traversed. A relative name does not begin with a slash and the traversal begins at the location specified by the create or access function.



**Name:** H5Gclose**Signature:***herr\_t* H5Gclose(*hid\_t* group\_id)**Purpose:**

Closes the specified group.

**Description:**

H5Gclose releases resources used by a group which was opened by H5Gcreate\* or H5Gopen\*. After closing a group, the group\_id cannot be used again.

Failure to release a group with this call will result in resource leaks.

**Parameters:**

*hid\_t* group\_id      IN: Group identifier to release.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5gclose\_f

```

SUBROUTINE h5gclose_f( gr_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: gr_id      ! Group identifier
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5gclose_f

```

**Name:** H5Gcreate

**Signatures:**

*hid\_t* H5Gcreate( *hid\_t* loc\_id, *const char* \*name, *size\_t* size\_hint ) [1]

*hid\_t* H5Gcreate( *hid\_t* loc\_id, *const char* \*name, *hid\_t* lcpl\_id, [2]  
*hid\_t* gcpl\_id, *hid\_t* gapl\_id )

**Purpose:**

Creates a new empty group and links it to a location in the file.

**Description:**

H5Gcreate is a macro that is mapped to either H5Gcreate1 or H5Gcreate2, depending on the HDF5 Library configuration and application compile-time Compatibility Macro Mapping Options.

This macro is provided to facilitate application compatibility. For example:

- ◊ The H5Gcreate macro will be mapped to H5Gcreate1 and will use the H5Gcreate1 syntax (first signature above) if the application is coded for HDF5 Release 1.6.x.
- ◊ The H5Gcreate macro will be mapped to H5Gcreate2 and will use the H5Gcreate2 syntax (second signature above) if the application is coded for HDF5 Release 1.8.x.

Macro use and Compatibility Macro Mapping Options are fully described in “API Compatibility Macros in HDF5”.

When both the HDF5 Library and the application are built without specific Compatibility Macro Mapping Options, the default behavior occurs and H5Gcreate is mapped to the most recent version of the function, currently H5Gcreate2. If the library and/or application is compiled for Release 1.6 emulation, H5Gcreate will be mapped to H5Gcreate1.

Function Mapping flags can be used to override these settings on a function-by-function basis when the application is compiled. The H5Gcreate Function Mapping flags are shown:

<b>h5cc flag</b>	<b>macro maps to</b>
-D H5Acreate_vers=1	H5Acreate1
-D H5Acreate_vers=2	H5Acreate2

**Interface history:** Signature [1] above is the original H5Gcreate interface and the only interface available prior to HDF5 Release 1.8.0. This signature and the corresponding function are now deprecated but will remain directly callable as H5Gcreate1.

Signature [2] above was introduced with HDF5 Release 1.8.0 and is the recommended and default interface. It is directly callable as H5Gcreate2.

Deprecated functions may not be available in all installations of the HDF5 library. See “API Compatibility Macros in HDF5” for details.

**Fortran90 Interface: h5gcreate\_f**

```

SUBROUTINE h5gcreate_f(loc_id, name, grp_id, hdferr, &
                      size_hint, lcpl_id, gcpl_id, gapl_id)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id      ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name      ! Name of the group
  INTEGER(HID_T), INTENT(OUT) :: grp_id     ! Group identifier
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
  INTEGER(SIZE_T), OPTIONAL, INTENT(IN) :: size_hint
                                           ! Parameter indicating the number of
                                           ! bytes to reserve for the names that
                                           ! will appear in the group.
                                           ! Note, set to OBJECT_NAMELEN_DEFAULT_F
                                           ! if using any of the optional
                                           ! parameters lcpl_id, gcpl_id,
                                           ! and/or gapl_id when not
                                           ! using keywords in specifying the
                                           ! optional parameters.
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lcpl_id
                                           ! Property list for link creation
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: gcpl_id
                                           ! Property list for group creation
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: gapl_id
                                           ! Property list for group access

END SUBROUTINE h5gcreate_f

```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	<p>The function H5Gcreate renamed to H5Gcreate1 and deprecated in this release.</p> <p>The macro H5Gcreate and the function H5Gcreate2 introduced in this release.</p>

*Last modified: 18 May 2009***Name:** H5Gcreate1**Signature:***hid\_t* H5Gcreate1( *hid\_t* loc\_id, *const char* \*name, *size\_t* size\_hint )**Purpose:**

Creates a new empty group and links it to a location in the file.

**Notice:***This function is renamed from H5Gcreate and deprecated in favor of the functions H5Gcreate2 and H5Gcreate\_anon, or the new macro H5Gcreate.***Description:**

H5Gcreate1 creates a new group with the specified name at the specified location, loc\_id. The location is identified by a file or group identifier. The name, name, must not already be taken by some other object and all parent groups must already exist.

name can be a relative path based at loc\_id or an absolute path from the root of the file. If any of the groups specified in that path do not already exist, the group must be created with H5Gcreate\_anon and linked into the file structure with H5Lcreate\_hard.

The length of a group name, or of the name of any object within a group, is not limited.

size\_hint is a hint for the number of bytes to reserve to store the names which will be eventually added to the new group. Passing a value of zero for size\_hint is usually adequate since the library is able to dynamically resize the name heap, but a correct hint may result in better performance. If a non-positive value is supplied for size\_hint, then a default size is chosen.

The return value is a group identifier for the open group. This group identifier should be closed by calling H5Gclose when it is no longer needed.

See H5Gcreate\_anon for a discussion of the differences between H5Gcreate1 and H5Gcreate\_anon.

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier.
<i>const char</i> *name	IN: Absolute or relative name of the o new group.
<i>size_t</i> size_hint	IN: Optional parameter indicating the number of bytes to reserve for the names that will appear in the group. A conservative estimate could result in multiple system-level I/O requests to read the group name heap; a liberal estimate could result in a single large I/O request even when the group has just a few names. HDF5 stores each name with a null terminator.

**Returns:**

Returns a valid group identifier for the open group if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Gcreate.**History:**

Release	C
1.8.0	Function H5Gcreate renamed to H5Gcreate1 and deprecated in this release.



**Name:** H5Gcreate2

**Signature:**

```
hid_t H5Gcreate2(hid_t loc_id, const char *name, hid_t lcpl_id, hid_t gcpl_id, hid_t
gapl_id)
```

**Purpose:**

Creates a new empty group and links it into the file.

**Description:**

H5Gcreate2 creates a new group named name at the location specified by loc\_id with the group creation and access properties specified in gcpl\_id and gapl\_id, respectively.

loc\_id may be a file identifier, or a group identifier within that file. name may be either an absolute path in the file or a relative path from loc\_id naming the dataset.

The link creation property list, lcpl\_id, governs creation of the link(s) by which the new dataset is accessed and the creation of any intermediate groups that may be missing.

To conserve and release resources, the group should be closed when access is no longer required.

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier
<i>const char</i> *name	IN: Absolute or relative name of the new group
<i>hid_t</i> lcpl_id	IN: Property list for link creation
<i>hid_t</i> gcpl_id	IN: Property list for group creation
<i>hid_t</i> gapl_id	IN: Property list for group access (No group access properties have been implemented at this time; use H5P_DEFAULT.)

**Returns:**

Returns a group identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Gcreate.

**History:**

Release	C
1.8.0	Function introduced in this release.

*Last modified: 18 May 2009*

**Name:** H5Gcreate\_anon

**Signature:**

```
hid_t H5Gcreate_anon( hid_t loc_id, hid_t gcpl_id, hid_t gapl_id )
```

**Purpose:**

Creates a new empty group without linking it into the file structure.

**Description:**

H5Gcreate\_anon creates a new empty group in the file specified by `loc_id`. With default settings, H5Gcreate\_anon provides similar functionality to that provided by H5Gcreate, with the differences described below.

The new group's creation and access properties are specified in `gcpl_id` and `gapl_id`, respectively.

H5Gcreate\_anon returns a new group identifier. This identifier *must* be linked into the HDF5 file structure with H5Lcreate\_hard or it will be deleted from the file when the file is closed.

The differences between this function and H5Gcreate1 are as follows:

- ◊ H5Gcreate1 does not provide for the use of custom property lists; H5Gcreate1 always uses default properties.
- ◊ H5Gcreate\_anon neither provides the new group's name nor links it into the HDF5 file structure; those actions must be performed separately through a call to H5Lcreate\_hard, which offers greater control over linking.
- ◊ H5Gcreate\_anon does not directly provide a *hint* mechanism for the group's heap size. Comparable information can be included in the group creation property list `gcpl_id` through a H5Pset\_local\_heap\_size\_hint call.

**Parameters:**

<code>hid_t loc_id</code>	File or group identifier specifying the file in which the new group is to be created
<code>hid_t gcpl_id</code>	Group creation property list identifier (H5P_DEFAULT for the default property list)
<code>hid_t gapl_id</code>	Group access property list identifier (No group access properties have been implemented at this time; use H5P_DEFAULT.)

**Returns:**

Returns a new group identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5gcreate\_anon\_f

```
SUBROUTINE h5gcreate_anon_f(loc_id, grp_id, hdferr, gcpl_id, gapl_id)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id    ! File or group identifier
  INTEGER(HID_T), INTENT(OUT) :: grp_id   ! Group identifier
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: gcpl_id
                                          ! Property list for group creation
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: gapl_id
                                          ! Property list for group access
END SUBROUTINE h5gcreate_anon_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Gget\_comment

**Signature:**

```
int H5Gget_comment(hid_t loc_id, const char *name, size_t bufsize, char *comment)
```

**Purpose:**

Retrieves comment for specified object.

**Notice:**

*This function is deprecated in favor of the function H5Oget\_comment.*

**Description:**

H5Gget\_comment retrieves the comment for the the object specified by loc\_id and name. The comment is returned in the buffer comment.

loc\_id can specify any object in the file. name can be one of the following:

- The name of the object relative to loc\_id
- An absolute name of the object, starting from /, the file's root group
- A dot (.), if loc\_id fully specifies the object

At most bufsize characters, including a null terminator, are returned in comment. The returned value is not null terminated if the comment is longer than the supplied buffer. If the size of the comment is unknown, a preliminary H5Gget\_comment call will return the size of the comment, including space for the null terminator.

If an object does not have a comment, the empty string is returned in comment.

**Parameters:**

hid_t loc_id	IN: Identifier of the file, group, dataset, or named datatype.
const char *name	IN: Name of the object in loc_id whose comment is to be retrieved. name must be '.' (dot) if loc_id fully specifies the object for which the associated comment is to be retrieved.
size_t bufsize	IN: Anticipated required size of the comment buffer.
char *comment	OUT: The comment.

**Returns:**

Returns the number of characters in the comment, counting the null terminator, if successful; the value returned may be larger than bufsize. Otherwise returns a negative value.

**Fortran90 Interface:** h5gget\_comment\_f

```
SUBROUTINE h5gget_comment_f(loc_id, name, size, buffer, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id           ! File, group, dataset, or
                                                    ! named datatype identifier
  CHARACTER(LEN=*), INTENT(IN) :: name          ! Name of the object link
  CHARACTER(LEN=size), INTENT(OUT) :: buffer    ! Buffer to hold the comment
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                                    ! 0 on success and -1 on failure
END SUBROUTINE h5gget_comment_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function deprecated in this release.

**Name:** H5Gget\_create\_plist

**Signature:**

*hid\_t* H5Gget\_create\_plist(*hid\_t* group\_id)

**Purpose:**

Gets a group creation property list identifier.

**Description:**

H5Gget\_create\_plist returns an identifier for the group creation property list associated with the group specified by group\_id.

The creation property list identifier should be released with H5Pclose.

**Parameters:**

*hid\_t* group\_id    IN: Identifier of the group.

**Returns:**

Returns an identifier for the group's creation property list if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5gget\_create\_plist\_f

```
SUBROUTINE h5gget_create_plist_f(grp_id, gcpl_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)  :: grp_id  ! Group identifier
  INTEGER(HID_T), INTENT(OUT) :: gcpl_id ! Property list for group creation
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                         ! 0 on success and -1 on failure

END SUBROUTINE h5gget_create_plist_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Gget\_info

**Signature:**

```
herr_t H5Gget_info(hid_t group_id, H5G_info_t *group_info)
```

**Purpose:**

Retrieves information about a group.

**Description:**

H5Gget\_info retrieves information about the group specified by group\_id. The information is returned in the group\_info struct.

group\_info is an *H5G\_info\_t* struct and is defined (in *H5Gpublic.h*) as follows:

<i>H5G_storage_type_t</i> storage_type	Type of storage for links in group H5G_STORAGE_TYPE_COMPACT: Compact storage H5G_STORAGE_TYPE_DENSE: Indexed storage H5G_STORAGE_TYPE_SYMBOL_TABLE: Symbol tables, the original HDF5 structure
<i>hsize_t</i> nlinks	Number of links in group
<i>int64_t</i> max_corder	Current maximum creation order value for group
<i>hbool_t</i> mounted	Whether the group has a file mounted on it

**Parameters:**

<i>hid_t</i> group_id	IN: Group identifier
<i>H5G_info_t</i> *group_info	OUT: Struct in which group information is returned

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5gget\_info\_f

```
SUBROUTINE h5gget_info_f(group_id, storage_type, nlinks, max_corder, hdferr, &
                        mounted)
```

```
IMPLICIT NONE
INTEGER(HID_T), INTENT(IN) :: group_id
                        ! Group identifier
INTEGER, INTENT(OUT) :: storage_type
                        ! Type of storage for links in group:
                        !   H5G_STORAGE_TYPE_COMPACT_F: Compact storage
                        !   H5G_STORAGE_TYPE_DENSE_F: Indexed storage
                        !   H5G_STORAGE_TYPE_SYMBOL_TABLE_F: Symbol tables
INTEGER, INTENT(OUT) :: nlinks
                        ! Number of links in group
INTEGER, INTENT(OUT) :: max_corder
                        ! Current maximum creation order value for group
INTEGER, INTENT(OUT) :: hdferr
                        ! Error code:
                        !   0 on success and -1 on failure
LOGICAL, INTENT(OUT), OPTIONAL :: mounted
                        ! Whether group has a file mounted on it
END SUBROUTINE h5gget_info_f
```

**History:**

Release	C
1.8.2	Added 'mounted' field.
1.8.0	Function introduced in this release.

**Name:** H5Gget\_info\_by\_idx

**Signature:**

```
herr_t H5Gget_info_by_idx(hid_t loc_id, const char *group_name, H5_index_t
index_type, H5_iter_order_t order, hsize_t n, H5G_info_t *group_info, hid_t lapl_id)
```

**Purpose:**

Retrieves information about a group, according to the group's position within an index.

**Description:**

H5Gget\_info\_by\_idx retrieves the same information about a group as retrieved by the function H5Gget\_info, immediately above, but the means of identifying the group differs; the group is identified by position in an index rather than by name.

loc\_id and group\_name specify the group containing the group for which information is sought. The groups in group\_name are indexed by index\_type; the group for which information is retrieved is identified in that index by index order, order, and index position, n.

If loc\_id specifies the group containing the group for which information is queried, group\_name can be a dot (.).

Valid values for index\_type are as follows:

H5_INDEX_NAME	An alpha-numeric index by group name
H5_INDEX_CRT_ORDER	An index by creation order

The order in which the index is to be examined, as specified by order, can be one of the following:

H5_ITER_INC	The count is from beginning of the index, i.e., top-down.
H5_ITER_DEC	The count is from the end of the index, i.e., bottom-up.
H5_ITER_NATIVE	HDF5 counts through the index in the fastest-available order. No information is provided as to the order, but HDF5 ensures that no element in the index will be overlooked.

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier
<i>const char</i> *group_name	IN: Name of group containing group for which information is to be retrieved
<i>H5_index_t</i> index_type	IN: Index type
<i>H5_iter_order_t</i> order	IN: Order of the count in the index
<i>hsize_t</i> n	IN: Position in the index of the group for which information is retrieved
<i>H5G_info_t</i> *group_info	OUT: Struct in which group information is returned
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5gget\_info\_by\_idx\_f

```

SUBROUTINE h5gget_info_by_idx_f(loc_id, group_name, index_type, order, n, &
    storage_type, nlinks, max_corder, hdferr, lapl_id, mounted)

IMPLICIT NONE
INTEGER(HID_T), INTENT(IN) :: loc_id
    ! File or group identifier
CHARACTER(LEN=*), INTENT(IN) :: group_name
    ! Name of group containing group for which
    ! information is to be retrieved
INTEGER, INTENT(IN) :: index_type
    ! Index type
INTEGER, INTENT(IN) :: order
    ! Order of the count in the index
INTEGER(HSIZE_T), INTENT(IN) :: n
    ! Position in the index of the group for which
    ! information is retrieved
INTEGER, INTENT(OUT) :: storage_type
    ! Type of storage for links in group:
    ! H5G_STORAGE_TYPE_COMPACT_F: Compact storage
    ! H5G_STORAGE_TYPE_DENSE_F: Indexed storage
    ! H5G_STORAGE_TYPE_SYMBOL_TABLE_F: Symbol tables
INTEGER, INTENT(OUT) :: nlinks
    ! Number of links in group
INTEGER, INTENT(OUT) :: max_corder
    ! Current maximum creation order value for group
INTEGER, INTENT(OUT) :: hdferr
    ! Error code:
    ! 0 on success and -1 on failure
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
    ! Link access property list
LOGICAL, INTENT(OUT), OPTIONAL :: mounted
    ! Whether group has a file mounted on it
END SUBROUTINE h5gget_info_by_idx_f

```

**History:**

Release	C
1.8.0	Function introduced in this release.



**Name:** H5Gget\_info\_by\_name

**Signature:**

```
herr_t H5Gget_info_by_name( hid_t loc_id, const char *group_name, H5G_info_t
*group_info, hid_t lapl_id )
```

**Purpose:**

Retrieves information about a group.

**Description:**

H5Gget\_info\_by\_name retrieves information about the group `group_name` located in the file or group specified by `loc_id`. The information is returned in the `group_info` struct.

If `loc_id` specifies the group for which information is queried, `group_name` can be a dot (.).

`group_info` is an *H5G\_info\_t* struct and is defined (in `H5Gpublic.h`) as follows:

<i>H5G_storage_type_t</i> storage_type	Type of storage for links in group H5G_STORAGE_TYPE_COMPACT: Compact storage H5G_STORAGE_TYPE_DENSE: Dense storage H5G_STORAGE_TYPE_SYMBOL_TABLE: Symbol tables, the original HDF5 structure
<i>hsize_t</i> nlinks	Number of links in group
<i>int64_t</i> max_corder	Current maximum creation order value for group
<i>hbool_t</i> mounted	Whether the group has a file mounted on it

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier
<i>const char</i> *group_name	IN: Name of group for which information is to be retrieved
<i>H5G_info_t</i> *group_info	OUT: Struct in which group information is returned
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5gget\_info\_by\_name\_f

```
SUBROUTINE h5gget_info_by_name_f(loc_id, group_name, &
    storage_type, nlinks, max_corder, hdferr, lapl_id, mounted)

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id
                                ! File or group identifier
    CHARACTER(LEN=*), INTENT(IN) :: group_name
                                ! Name of group containing group for which
                                ! information is to be retrieved
    INTEGER, INTENT(OUT) :: storage_type
                                ! Type of storage for links in group:
                                !   H5G_STORAGE_TYPE_COMPACT_F: Compact storage
                                !   H5G_STORAGE_TYPE_DENSE_F: Indexed storage
                                !   H5G_STORAGE_TYPE_SYMBOL_TABLE_F: Symbol tables
    INTEGER, INTENT(OUT) :: nlinks
                                ! Number of links in group
    INTEGER, INTENT(OUT) :: max_corder
                                ! Current maximum creation order value for group
```

```
INTEGER, INTENT(OUT) :: hdferr
                        ! Error code:
                        ! 0 on success and -1 on failure
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                        ! Link access property list
LOGICAL, INTENT(OUT), OPTIONAL :: mounted
                        ! Whether group has a file mounted on it
END SUBROUTINE h5gget_info_by_name_f
```

**History:**

Release	C
1.8.2	Added 'mounted' field.
1.8.0	Function introduced in this release.

**Name:** H5Gget\_linkval

**Signature:**

```
herr_t H5Gget_linkval( hid_t loc_id, const char *name, size_t size, char *value )
```

**Purpose:**

Returns the name of the object that the symbolic link points to.

**Notice:**

*This function is deprecated in favor of the function H5Lget\_val.*

**Description:**

H5Gget\_linkval returns `size` characters of the name of the object that the symbolic link name points to.

The parameter `loc_id` is a file or group identifier.

The parameter `name` must be a symbolic link pointing to the desired object and must be defined relative to `loc_id`.

If `size` is smaller than the size of the returned object name, then the name stored in the buffer `value` will not be null terminated.

This function fails if `name` is not a symbolic link. The presence of a symbolic link can be tested by passing zero for `size` and NULL for `value`.

This function should be used only after H5Lget\_info (or the deprecated function H5Gget\_objinfo) has been called to verify that `name` is a symbolic link.

**Parameters:**

<code>hid_t loc_id</code>	IN: Identifier of the file or group.
<code>const char *name</code>	IN: Symbolic link to the object whose name is to be returned.
<code>size_t size</code>	IN: Maximum number of characters of <code>value</code> to be returned.
<code>char *value</code>	OUT: A buffer to hold the name of the object being sought.

**Returns:**

Returns a non-negative value, with the link value in `value`, if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5gget\_linkval\_f

```
SUBROUTINE h5gget_linkval_f(loc_id, name, size, buffer, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id           ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name          ! Name of the symbolic link
  CHARACTER(LEN=size), INTENT(OUT) :: buffer    ! Buffer to hold a
                                                ! name of the object
                                                ! symbolic link points to
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                                ! 0 on success and -1 on failure
END SUBROUTINE h5gget_linkval_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function deprecated in this release.

**Name:** H5Gget\_num\_objs

**Signature:**

*herr\_t* H5Gget\_num\_objs(*hid\_t* loc\_id, *hsize\_t*\* num\_obj)

**Purpose:**

Returns number of objects in the group specified by its identifier

**Notice:**

*This function is deprecated in favor of the function H5Gget\_info.*

**Description:**

H5Gget\_num\_objs returns number of objects in a group. Group is specified by its identifier loc\_id.

If a file identifier is passed in, then the number of objects in the root group is returned.

**Parameters:**

*hid\_t* loc\_id                      IN: Identifier of the group or the file

*hsize\_t* \*num\_obj                OUT: Number of objects in the group.

**Returns:**

Returns positive value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.6.0	Function introduced in this release.
-------	--------------------------------------

1.8.0	Function deprecated in this release.
-------	--------------------------------------

**Name:** H5Gget\_objinfo

**Signature:**

```
herr_t H5Gget_objinfo(hid_t loc_id, const char *name, hbool_t follow_link, H5G_stat_t
*statbuf)
```

**Purpose:**

Returns information about an object.

**Notice:**

*This function is deprecated in favor of the function H5Oget\_info and H5Lget\_info.*

**Description:**

H5Gget\_objinfo returns information about the specified object through the statbuf argument.

A file or group identifier, loc\_id, and an object name, name, relative to loc\_id, are commonly used to specify the object. However, if the object identifier is already known to the application, an alternative approach is to use that identifier, obj\_id, in place of loc\_id, and a dot (.) in place of name. Thus, the alternative versions of the first portion of an H5Gget\_objinfo call would be as follows:

```
H5Gget_objinfo (loc_id name ...)
H5Gget_objinfo (obj_id .      ...)
```

If the object is a symbolic link and follow\_link is zero (0), then the information returned describes the link itself; otherwise the link is followed and the information returned describes the object to which the link points. If follow\_link is non-zero but the final symbolic link is dangling (does not point to anything), then an error is returned. The statbuf fields are undefined for an error. The existence of an object can be tested by calling this function with a null statbuf.

H5Gget\_objinfo fills in the following data structure (defined in H5Gpublic.h):

```
typedef struct H5G_stat_t {
    unsigned long fileno[2];
    haddr_t objno[2];
    unsigned nlink;
    H5G_obj_t type;
    time_t mtime;
    size_t linklen;
    H5O_stat_t ohdr;
} H5G_stat_t
```

where H5O\_stat\_t (defined in H5Opublic.h) is:

```
typedef struct H5O_stat_t {
    hsize_t size;
    hsize_t free;
    unsigned nmsgs;
    unsigned nchunks;
} H5O_stat_t
```

The fileno and objno fields contain four values which uniquely identify an object among those HDF5 files which are open: if all four values are the same between two objects, then the two objects are the same (provided both files are still open).

◊ Note that if a file is closed and re-opened, the value in fileno will change.

◊ If a VFL driver either does not or cannot detect that two `H5Fopen` calls referencing the same file actually open the same file, each will get a different `fileno`.

The `nlink` field is the number of hard links to the object or zero when information is being returned about a symbolic link (symbolic links do not have hard links but all other objects always have at least one).

The `type` field contains the type of the object, one of `H5G_GROUP`, `H5G_DATASET`, `H5G_LINK`, or `H5G_TYPE`.

The `mtime` field contains the modification time.

If information is being returned about a symbolic link then `linklen` will be the length of the link value (the name of the pointed-to object with the null terminator); otherwise `linklen` will be zero.

The fields in the `H5O_stat_t` struct contain information about the object header for the object queried:

<code>size</code>	The total size of all the object header information in the file (for all chunks).
<code>free</code>	The size of unused space in the object header.
<code>nmsgs</code>	The number of object header messages.
<code>nchunks</code>	The number of chunks the object header is broken up into.

Other fields may be added to this structure in the future.

#### Note:

Some systems will be able to record the time accurately but unable to retrieve the correct time; such systems (e.g., Irix64) will report an `mtime` value of 0 (zero).

#### Parameters:

<code>hid_t loc_id</code>	IN: File or group identifier. <i>Alternative:</i> An object identifier, <code>obj_id</code>
<code>const char *name</code>	IN: Name of the object for which status is being sought. <i>Alternative:</i> If the preceding parameter is the object's direct identifier, i.e., the <code>obj_id</code> , this parameter should be a dot ( <code>.</code> ).
<code>hbool_t follow_link</code>	IN: Link flag.
<code>H5G_stat_t *statbuf</code>	OUT: Buffer in which to return information about the object.

#### Returns:

Returns a non-negative value if successful, with the fields of `statbuf` (if non-null) initialized. Otherwise returns a negative value.

#### Fortran90 Interface:

None.

#### History:

Release	C
1.6.1	Two new fields were added to the <code>H5G_stat_t</code> struct in this release.
1.8.0	Function deprecated in this release.

**Name:** H5Gget\_objname\_by\_idx

**Signature:**

```
ssize_t H5Gget_objname_by_idx(hid_t loc_id, hsize_t idx, char *name, size_t size)
```

**Purpose:**

Returns a name of an object specified by an index.

**Notice:**

*This function is deprecated in favor of the function H5Lget\_name\_by\_idx.*

**Description:**

H5Gget\_objname\_by\_idx returns a name of the object specified by the index `idx` in the group `loc_id`.

The group is specified by a group identifier `loc_id`. If preferred, a file identifier may be passed in `loc_id`; that file's root group will be assumed.

`idx` is the transient index used to iterate through the objects in the group. The value of `idx` is any nonnegative number less than the total number of objects in the group, which is returned by the function H5Gget\_num\_objs. Note that this is a transient index; an object may have a different index each time a group is opened.

The object name is returned in the user-specified buffer `name`.

If the size of the provided buffer `name` is less or equal the actual object name length, the object name is truncated to `max_size - 1` characters.

Note that if the size of the object's name is unknown, a preliminary call to H5Gget\_objname\_by\_idx with `name` set to NULL will return the length of the object's name. A second call to H5Gget\_objname\_by\_idx can then be used to retrieve the actual name.

**Parameters:**

<code>hid_t loc_id</code>	IN: Group or file identifier.
<code>hsize_t idx</code>	IN: Transient index identifying object.
<code>char *name</code>	IN/OUT: Pointer to user-provided buffer the object name.
<code>size_t size</code>	IN: Name length.

**Returns:**

Returns the size of the object name if successful, or 0 if no name is associated with the group identifier. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.0	Function introduced in this release.
1.8.0	Function deprecated in this release.

**Name:** H5Gget\_objtype\_by\_idx

**Signature:**

```
int H5Gget_objtype_by_idx( hid_t loc_id, hsize_t idx )
```

**Purpose:**

Returns the type of an object specified by an index.

**Notice:**

*This function is deprecated in favor of the function H5Oget\_info.*

**Description:**

H5Gget\_objtype\_by\_idx returns the type of the object specified by the index `idx` in the group `loc_id`.

The group is specified by a group identifier `loc_id`. If preferred, a file identifier may be passed in `loc_id`; that file's root group will be assumed.

`idx` is the transient index used to iterate through the objects in the group. This parameter is described in more detail in the discussion of H5Gget\_objname\_by\_idx.

The object type is returned as the function return value:

H5G_LINK	0	Object is a symbolic link.
H5G_GROUP	1	Object is a group.
H5G_DATASET	2	Object is a dataset.
H5G_TYPE	3	Object is a named datatype.

**Parameters:**

`hid_t loc_id` IN: Group or file identifier.  
`hsize_t idx` IN: Transient index identifying object.

**Returns:**

Returns the type of the object if successful. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.0	Function introduced in this release.
1.6.0	The function return type changed from <i>int</i> to the enumerated type <i>H5G_obj_t</i> .
1.8.0	Function deprecated in this release.



**Name:** H5Giterate

**Signature:**

```
int H5Giterate(hid_t loc_id, const char *name, int *idx, H5G_iterate_t operator, void
*operator_data )
```

**Purpose:**

Iterates an operation over the entries of a group.

**Notice:**

*This function is deprecated in favor of the function H5Literate.*

**Description:**

H5Giterate iterates over the members of name in the file or group specified with loc\_id. For each object in the group, the operator\_data and some additional information, specified below, are passed to the operator function. The iteration begins with the idx object in the group and the next element to be processed by the operator is returned in idx. If idx is NULL, then the iterator starts at the first group member; since no stopping point is returned in this case, the iterator cannot be restarted if one of the calls to its operator returns non-zero. H5Giterate does not recursively follow links into subgroups of the specified group.

The prototype for H5G\_iterate\_t is:

```
typedef herr_t (*H5G_iterate_t) (hid_t group_id, const char * member_name, void
*operator_data);
```

The operation receives the group identifier for the group being iterated over, group\_id, the name of the current object within the group, member\_name, and the pointer to the operator data passed in to H5Giterate, operator\_data.

The return values from an operator are:

- ◊ Zero causes the iterator to continue, returning zero when all group members have been processed.
- ◊ Positive causes the iterator to immediately return that positive value, indicating short-circuit success. The iterator can be restarted at the next group member.
- ◊ Negative causes the iterator to immediately return that value, indicating failure. The iterator can be restarted at the next group member.

H5Giterate assumes that the membership of the group identified by name remains unchanged through the iteration. If the membership changes during the iteration, the function's behavior is undefined.

H5Giterate is not recursive. In particular, if a member of name is found to be a group, call it subgroup\_a, H5Giterate does not examine the members of subgroup\_a. When recursive iteration is required, the application must handle the recursion, explicitly calling H5Giterate on discovered subgroups.

**Parameters:**

hid_t loc_id	IN: File or group identifier.
const char *name	IN: Group over which the iteration is performed.
int *idx	IN/OUT: Location at which to begin the iteration.
H5G_iterate_t operator	IN: Operation to be performed on an object at each step of the iteration.
void *operator_data	IN/OUT: Data associated with the operation.

**Returns:**

Returns the return value of the last operator if it was non-zero, or zero if all group members were processed. Otherwise returns a negative value.

**Fortran90 Interface:**

There is no direct FORTRAN counterpart for the C function H5Giterate. Instead, that functionality is provided by two FORTRAN functions:

<pre> h5gn_members_f h5gget_obj_info_idx_f </pre>	<p><b>Purpose:</b> Returns the number of group members.</p> <p><b>Purpose:</b> Returns name and type of the group member identified by its index.</p>
---	---

```

SUBROUTINE h5gn_members_f(loc_id, name, nmembers, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id          ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name          ! Name of the group
  INTEGER, INTENT(OUT) :: nmembers              ! Number of members in the group
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5gn_members_f

SUBROUTINE h5gget_obj_info_idx_f(loc_id, name, idx, &
                                obj_name, obj_type, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id          ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name          ! Name of the group
  INTEGER, INTENT(IN) :: idx                    ! Index of member object
  CHARACTER(LEN=*), INTENT(OUT) :: obj_name     ! Name of the object
  INTEGER, INTENT(OUT) :: obj_type              ! Object type :
                                              !   H5G_LINK_F
                                              !   H5G_GROUP_F
                                              !   H5G_DATASET_F
                                              !   H5G_TYPE_F
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5gget_obj_info_idx_f

```

**History:**

<p><b>Release</b></p> <p>1.8.0</p>	<p><b>C</b></p> <p>Function deprecated in this release.</p>
------------------------------------	---

**Name:** H5Glink

**Signature:**

```
herr_t H5Glink(hid_t loc_id, H5G_link_t link_type, const char *current_name, const char
               *new_name)
```

**Purpose:**

Creates a link of the specified type from new\_name to current\_name.

**Notice:**

*This function is deprecated in favor of the functions H5Lcreate\_hard and H5Lcreate\_soft.*

**Description:**

H5Glink creates a new name for an object that has some current name, possibly one of many names it currently has.

If link\_type is H5G\_LINK\_HARD, then current\_name must specify the name of an existing object and both names are interpreted relative to loc\_id, which is either a file identifier or a group identifier.

If link\_type is H5G\_LINK\_SOFT, then current\_name can be anything and is interpreted at lookup time relative to the group which contains the final component of new\_name. For instance, if current\_name is ./foo, new\_name is ./x/y/bar, and a request is made for ./x/y/bar, then the actual object looked up is ./x/y/./foo.

**Parameters:**

hid_t loc_id	IN: File or group identifier.
H5G_link_t link_type	IN: Link type. Possible values are H5G_LINK_HARD and H5G_LINK_SOFT.
const char *current_name	IN: Name of the existing object if link is a hard link. Can be anything for the soft link.
const char *new_name	IN: New name for the object.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5glink\_f

```
SUBROUTINE h5glink_f(loc_id, link_type, current_name, new_name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id      ! File or group location identifier
  INTEGER, INTENT(IN)       :: link_type    ! Link type, possible values are:
                                           !      H5G_LINK_HARD_F
                                           !      H5G_LINK_SOFT_F
  CHARACTER(LEN=*), INTENT(IN) :: current_name
                                           ! Current object name relative
                                           ! to loc_id
  CHARACTER(LEN=*), INTENT(IN) :: new_name  ! New object name
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure

END SUBROUTINE h5glink_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function deprecated in this release.

**Name:** H5Glink2

**Signature:**

```
herr_t H5Glink2(hid_t curr_loc_id, const char *current_name, H5G_link_t link_type,
hid_t new_loc_id, const char *new_name)
```

**Notice:**

*This function is deprecated in favor of the functions H5Lcreate\_hard and H5Lcreate\_soft.*

**Purpose:**

Creates a link of the specified type from current\_name to new\_name.

**Description:**

H5Glink2 creates a new name for an object that has some current name, possibly one of many names it currently has.

If link\_type is H5G\_LINK\_HARD, then current\_name must specify the name of an existing object. In this case, current\_name and new\_name are interpreted relative to curr\_loc\_id and new\_loc\_id, respectively, which are either file or group identifiers.

If link\_type is H5G\_LINK\_SOFT, then current\_name can be anything and is interpreted at lookup time relative to the group which contains the final component of new\_name. For instance, if current\_name is ./foo, new\_name is ./x/y/bar, and a request is made for ./x/y/bar, then the actual object looked up is ./x/y/./foo.

**Parameters:**

<i>hid_t</i> curr_loc_id	IN: The file or group identifier for the original object.
<i>const char</i> *current_name	IN: Name of the existing object if link is a hard link. Can be anything for the soft link.
<i>H5G_link_t</i> link_type	IN: Link type. Possible values are H5G_LINK_HARD and H5G_LINK_SOFT.
<i>hid_t</i> new_loc_id	IN: The file or group identifier for the new link.
<i>const char</i> *new_name	IN: New name for the object.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5glink2\_f

```
SUBROUTINE h5glink2_f(cur_loc_id, cur_name, link_type, new_loc_id, new_name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: cur_loc_id ! File or group location identifier
  CHARACTER(LEN=*), INTENT(IN) :: cur_name ! Name of the existing object
                                           ! is relative to cur_loc_id
                                           ! Can be anything for the soft link
  INTEGER, INTENT(IN) :: link_type ! Link type, possible values are:
                                   !     H5G_LINK_HARD_F
                                   !     H5G_LINK_SOFT_F
  INTEGER(HID_T), INTENT(IN) :: new_loc_id ! New location identifier
  CHARACTER(LEN=*), INTENT(IN) :: new_name ! New object name
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                   ! 0 on success and -1 on failure

END SUBROUTINE h5glink2_f
```

**History:**

Release	C
1.8.0	Function deprecated in this release.

**Name:** H5Gmove

**Signature:**

```
herr_t H5Gmove(hid_t loc_id, const char *src_name, const char *dst_name )
```

**Purpose:**

Renames an object within an HDF5 file.

**Notice:**

*This function is deprecated in favor of the function H5Lmove.*

**Description:**

H5Gmove renames an object within an HDF5 file. The original name, `src_name`, is unlinked from the group graph and the new name, `dst_name`, is inserted as an atomic operation. Both names are interpreted relative to `loc_id`, which is either a file or a group identifier.

**Warning:**

Exercise care in moving groups as it is possible to render data in a file inaccessible with H5Gmove. See The Group Interface in the *HDF5 User's Guide*.

**Parameters:**

<code>hid_t loc_id</code>	IN: File or group identifier.
<code>const char *src_name</code>	IN: Object's original name.
<code>const char *dst_name</code>	IN: Object's new name.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5gmove\_f

```
SUBROUTINE h5gmove_f(loc_id, name, new_name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id      ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name      ! Original name of an object
  CHARACTER(LEN=*), INTENT(IN) :: new_name  ! New name of an object
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5gmove_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function deprecated in this release.

**Name:** H5Gmove2

**Signature:**

```
herr_t H5Gmove2( hid_t src_loc_id, const char *src_name, hid_t dst_loc_id, const char
                *dst_name )
```

**Purpose:**

Renames an object within an HDF5 file.

**Notice:**

*This function is deprecated in favor of the function H5Lmove.*

**Description:**

H5Gmove2 renames an object within an HDF5 file. The original name, `src_name`, is unlinked from the group graph and the new name, `dst_name`, is inserted as an atomic operation.

`src_name` and `dst_name` are interpreted relative to `src_loc_id` and `dst_loc_id`, respectively, which are either file or group identifiers.

**Warning:**

Exercise care in moving groups as it is possible to render data in a file inaccessible with H5Gmove. See The Group Interface in the *HDF5 User's Guide*.

**Parameters:**

<code>hid_t src_loc_id</code>	IN: Original file or group identifier.
<code>const char *src_name</code>	IN: Object's original name.
<code>hid_t dst_loc_id</code>	IN: Destination file or group identifier.
<code>const char *dst_name</code>	IN: Object's new name.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5gmove2\_f

```
SUBROUTINE h5gmove2_f(src_loc_id, src_name, dst_loc_id, dst_name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: src_loc_id      ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: src_name      ! Original name of an object
                                              ! relative to src_loc_id
  INTEGER(HID_T), INTENT(IN) :: dst_loc_id      ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: dst_name      ! New name of an object
                                              ! relative to dst_loc_id
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5gmove2_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function deprecated in this release.

**Name:** H5Gopen

**Signature:**

```
hid_t H5Gopen( hid_t loc_id, const char *name )
hid_t H5Gopen( hid_t loc_id, const char *name, hid_t gapl_id )
```

**Purpose:**

Opens an existing group in a file.

**Description:**

H5Gopen is a macro that is mapped to either H5Gopen1 or H5Gopen2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5” we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Gopen is mapped to the most recent version of the function, currently H5Gopen2. If the library and/or application is compiled for Release 1.6 emulation, H5Gopen will be mapped to H5Gopen1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Gopen mapping
<u>Global settings</u>	
No compatibility flag	H5Gopen2
Enable deprecated symbols	H5Gopen2
Disable deprecated symbols	H5Gopen2
Emulate Release 1.6 interface	H5Gopen1
<u>Function-level macros</u>	
H5Gopen_vers = 2	H5Gopen2
H5Gopen_vers = 1	H5Gopen1

**Fortran90 Interface:** h5gopen\_f

```
SUBROUTINE h5gopen_f(loc_id, name, grp_id, hdferr, gapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id      ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name      ! Name of the group
  INTEGER(HID_T), INTENT(OUT) :: grp_id     ! File identifier
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: gapl_id
                                           ! Group access property list identifier
END SUBROUTINE h5gopen_f
```

**History:****Release    C**

1.8.0        The function H5Gopen renamed to H5Gopen1 and deprecated in this release.  
The macro H5Gopen and the function H5Gopen2 introduced in this release.



**Name:** H5Gopen1

**Signature:**

*hid\_t* H5Gopen1(*hid\_t* loc\_id, *const char* \*name )

**Notice:**

*This function is deprecated in favor of the function H5GOpen2 or the macro H5GOpen.*

**Purpose:**

Opens an existing group for modification and returns a group identifier for that group.

**Description:**

H5Gopen1 opens an existing group with the specified name at the specified location, loc\_id.

The location is identified by a file or group identifier

H5Gopen1 returns a group identifier for the group that was opened. This group identifier should be released by calling H5Gclose when it is no longer needed.

**Parameters:**

*hid\_t* loc\_id                      IN: File or group identifier within which group is to be open.

*const char* \* name              IN: Name of group to open.

**Returns:**

Returns a valid group identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Gopen.

**History:**

Release	C
---------	---

1.8.0	The function H5Gopen renamed to H5Gopen1 and deprecated in this release.
-------	--

**Name:** H5Gopen2

**Signature:**

*hid\_t* H5Gopen2( *hid\_t* loc\_id, *const char \**name, *hid\_t* gapl\_id )

**Purpose:**

Opens an existing group with a group access property list.

**Description:**

H5Gopen2 opens an existing group, name, at the location specified by loc\_id.

With default settings, H5Gopen2 provides similar functionality to that provided by H5Gopen1. The only difference is that H5Gopen2 can provide a group access property list, gapl\_id.

H5Gopen2 returns a group identifier for the group that was opened. This group identifier should be released by calling H5Gclose when it is no longer needed.

**Parameters:**

<i>hid_t</i> loc_id	File or group identifier specifying the location of the group to be opened
<i>const char *</i> name	Name of the group to open
<i>hid_t</i> gapl_id	Group access property list identifier (No group access properties have been implemented at this time; use H5P_DEFAULT.)

**Returns:**

Returns a group identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Gopen.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Gset\_comment

**Signature:**

```
herr_t H5Gset_comment(hid_t loc_id, const char *name, const char *comment )
```

**Purpose:**

Sets comment for specified object.

**Notice:**

*This function is deprecated in favor of the function H5Oset\_comment.*

**Description:**

H5Gset\_comment sets the comment for the object specified by loc\_id and name to comment. Any previously existing comment is overwritten.

loc\_id can specify any object in the file. name can be one of the following:

- The name of the object relative to loc\_id
- An absolute name of the object, starting from /, the file's root group
- A dot (.), if loc\_id fully specifies the object

If comment is the empty string or a null pointer, the comment message is removed from the object.

Comments should be relatively short, null-terminated, ASCII strings.

Comments can be attached to any object that has an object header, e.g., datasets, groups, and named datatypes, but not symbolic links.

**Parameters:**

hid_t loc_id	IN: Identifier of the file, group, dataset, or named datatype.
const char *name	IN: Name of the object whose comment is to be set or reset. name must be '.' (dot) if loc_id fully specifies the object for which the comment is to be set.
const char *comment	IN: The new comment.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5gset\_comment\_f

```
SUBROUTINE h5gset_comment_f(loc_id, name, comment, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id          ! File, group, dataset, or
                                                ! named datatype identifier
  CHARACTER(LEN=*), INTENT(IN) :: name         ! Name of object
  CHARACTER(LEN=*), INTENT(IN) :: comment      ! Comment for the object
  INTEGER, INTENT(OUT) :: hdferr               ! Error code
                                                ! 0 on success and -1 on failure
END SUBROUTINE h5gset_comment_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function deprecated in this release.

**Name:** H5Gunlink

**Signature:**

```
herr_t H5Gunlink(hid_t loc_id, const char *name )
```

**Purpose:**

Removes the link to an object from a group.

**Notice:**

*This function is deprecated in favor of the function `H5Ldelete`.*

**Description:**

H5Gunlink removes the object specified by name from the group graph and decrements the link count for the object to which name points. This action eliminates any association between name and the object to which name pointed.

Object headers keep track of how many hard links refer to an object; when the link count reaches zero, the object can be removed from the file. Objects which are open are not removed until all identifiers to the object are closed.

If the link count reaches zero, all file space associated with the object will be released, i.e., identified in memory as freespace. If any object identifier is open for the object, the space will not be released until after the object identifier is closed.

Note that space identified as freespace is available for re-use only as long as the file remains open; once a file has been closed, the HDF5 library loses track of freespace. See “Freespace Management” in the *HDF5 User's Guide* for further details.

**Warning:**

Exercise care in unlinking groups as it is possible to render data in a file inaccessible with H5Gunlink. See The Group Interface in the *HDF5 User's Guide*.

**Parameters:**

<code>hid_t loc_id</code>	IN: Identifier of the file or group containing the object.
<code>const char *name</code>	IN: Name of the object to unlink.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5gunlink\_f

```
SUBROUTINE h5gunlink_f(loc_id, name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id      ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name     ! Name of the object to unlink
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5gunlink_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function deprecated in this release.

## H5I: Identifier Interface

### Identifier API Functions

These functions provides tools for working with object identifiers and object names.

#### The C Interface:

- |                    |                    |                   |
|--------------------|--------------------|-------------------|
| • H5Iget_file_id   | • H5Iget_ref       | • H5Itype_exists  |
| • H5Iget_name      | • H5Iinc_ref       | • H5Iget_type_ref |
| • H5Iget_type      | • H5Idec_ref       | • H5Idec_type_ref |
| • H5Iobject_verify | • H5Iregister      | • H5Iinc_type_ref |
| • H5Iremove_verify | • H5Iregister_type | • H5Iclear_type   |
| • H5Isearch        | • H5Idestroy_type  | • H5Inmembers     |
| • H5Iis_valid      |                    |                   |

#### *Alphabetical Listing*

- |                   |                   |                    |
|-------------------|-------------------|--------------------|
| • H5Iclear_type   | • H5Iget_ref      | • H5Iobject_verify |
| • H5Idec_ref      | • H5Iget_type     | • H5Iregister      |
| • H5Idec_type_ref | • H5Iget_type_ref | • H5Iregister_type |
| • H5Idestroy_type | • H5Iinc_ref      | • H5Iremove_verify |
| • H5Iget_file_id  | • H5Iinc_type_ref | • H5Isearch        |
| • H5Iget_name     | • H5Iis_valid     | • H5Itype_exists   |
|                   | • H5Inmembers     |                    |

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- |                 |                |                 |
|-----------------|----------------|-----------------|
| • h5iget_name_f | • h5iget_ref_f | • h5idec_ref_f  |
| • h5iget_type_f | • h5iinc_ref_f | • H5iis_valid_f |



**Name:** H5Iclear\_type

**Signature:**

*herr\_t* H5Iclear\_type( *H5I\_type\_t* type, *hbool\_t* force )

**Purpose:**

Deletes all IDs of the given type

**Description:**

H5Iclear\_type deletes all IDs of the type identified by the argument type.

The type's free function is first called on all of these IDs to free their memory, then they are removed from the type.

If the `force` flag is set to false, only those IDs whose reference counts are equal to 1 will be deleted, and all other IDs will be entirely unchanged. If the `force` flag is true, all IDs of this type will be deleted.

**Parameters:**

*H5I\_type\_t* type           IN: Identifier of ID type which is to be cleared of IDs

*hbool\_t* force            IN: Whether or not to force deletion of all IDs

**Returns:**

Returns non-negative on success, negative on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Idec\_ref

**Signature:**

```
int H5Idec_ref( hid_t obj_id )
```

**Purpose:**

Decrements the reference count for an object.

**Description:**

H5Idec\_ref decrements the reference count of the object identified by obj\_id.

The reference count for an object ID is attached to the information about an object in memory and has no relation to the number of links to an object on disk.

The reference count for a newly created object will be 1. Reference counts for objects may be explicitly modified with this function or with H5Iinc\_ref. When an object ID's reference count reaches zero, the object will be closed. Calling an object ID's 'close' function decrements the reference count for the ID which normally closes the object, but if the reference count for the ID has been incremented with H5Iinc\_ref, the object will only be closed when the reference count reaches zero with further calls to this function or the object ID's 'close' function.

If the object ID was created by a collective parallel call (such as H5Dcreate, H5Gopen, etc.), the reference count should be modified by all the processes which have copies of the ID. Generally this means that group, dataset, attribute, file and named datatype IDs should be modified by all the processes and that all other types of IDs are safe to modify by individual processes.

This function is of particular value when an application is maintaining multiple copies of an object ID. The object ID can be incremented when a copy is made. Each copy of the ID can then be safely closed or decremented and the HDF5 object will be closed when the reference count for that that object drops to zero.

**Parameters:**

*hid\_t* obj\_id      IN: Object identifier whose reference count will be modified.

**Returns:**

Returns a non-negative reference count of the object ID after decrementing it, if successful; otherwise a negative value is returned.

**Fortran90 Interface:** h5idec\_ref\_f

```
SUBROUTINE h5idec_ref_f(obj_id, ref_count, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id !Object identifier
  INTEGER, INTENT(OUT) :: ref_count !Reference count of object ID
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                   ! 0 on success, and -1 on failure
END SUBROUTINE h5idec_ref_f
```

**History:**

Release	C
1.6.2	Function introduced in this release. Fortran subroutine introduced in this release.



**Name:** H5Idec\_type\_ref

**Signature:**

*int* H5Idec\_type\_ref( *H5I\_type\_t* type )

**Purpose:**

Decrements the reference count on an ID type.

**Description:**

H5Idec\_type\_ref decrements the reference count on an ID type. The reference count is used by the library to indicate when an ID type can be destroyed. If the reference count reaches zero, this function will destroy it.

The *type* parameter is the identifier for the ID type whose reference count is to be decremented. This identifier must have been created by a call to H5Iregister\_type.

**Parameters:**

*H5I\_type\_t* type      IN: The identifier of the type whose reference count is to be decremented

**Returns:**

Returns the current reference count on success, negative on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Idestroy\_type

**Signature:**

*herr\_t* H5Idestroy\_type( *H5I\_type\_t* type )

**Purpose:**

Removes the type *type* and all IDs within that type.

**Description:**

H5Idestroy\_type deletes an entire ID type. All IDs of this type are destroyed and no new IDs of this type can be registered.

The type's free function is called on all of the IDs which are deleted by this function, freeing their memory. In addition, all memory used by this type's hash table is freed.

Since the *H5I\_type\_t* values of destroyed ID types are reused when new types are registered, it is a good idea to set the variable holding the value of the destroyed type to H5I\_UNINIT.

**Parameters:**

*H5I\_type\_t* type      IN: Identifier of ID type which is to be destroyed

**Returns:**

Returns non-negative on success, negative on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Iget\_file\_id

**Signature:**

*hid\_t* H5Iget\_file\_id( *hid\_t* obj\_id )

**Purpose:**

Retrieves an identifier for the file containing the specified object.

**Description:**

H5Iget\_file\_id returns the identifier of the file associated with the object referenced by obj\_id.

obj\_id can be a file, group, dataset, named datatype, or attribute identifier.

Note that the HDF5 Library permits an application to close a file while objects within the file remain open. If the file containing the object obj\_id is still open, H5Iget\_file\_id will retrieve the existing file identifier. If there is no existing file identifier for the file, i.e., the file has been closed, H5Iget\_file\_id will reopen the file and return a new file identifier. In either case, the file identifier must eventually be released using H5Fclose.

**Parameters:**

*hid\_t* obj\_id      IN: Identifier of the object whose associated file identifier will be returned.

**Returns:**

Returns a file identifier on success, negative on failure.

**Fortran90 Interface:**

```
SUBROUTINE h5iget_file_id_f(obj_id, file_id, hdferr)

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN)  :: obj_id      ! Object identifier
    INTEGER(HID_T), INTENT(OUT) :: file_id     ! File identifier
    INTEGER, INTENT(OUT) :: hdferr             ! Error code

END SUBROUTINE h5iget_file_id_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.3	Function introduced in this release. Fortran subroutine introduced in this release.

**Name:** H5Iget\_name

**Signature:**

```
ssize_t H5Iget_name( hid_t obj_id, char *name, size_t size )
```

**Purpose:**

Retrieves a name of an object based on the object identifier.

**Description:**

H5Iget\_name retrieves a name for the object identified by `obj_id`.

Up to `size` characters of the name are returned in `name`; additional characters, if any, are not returned to the user application.

If the length of the name, which determines the required value of `size`, is unknown, a preliminary H5Iget\_name call can be made. The return value of this call will be the size in bytes of the object name. That value, plus 1 for a NULL terminator, is then assigned to `size` for a second H5Iget\_name call, which will retrieve the actual name.

If the object identified by `obj_id` is an attribute, as determined via H5Iget\_type, H5Iget\_name retrieves the name of the object to which that attribute is attached. To retrieve the name of the attribute itself, use H5Aget\_name.

If there is no name associated with the object identifier or if the name is NULL, H5Iget\_name returns 0 (zero).

Note that an object in an HDF5 file may have multiple paths if there are multiple links pointing to it. This function may return any one of these paths. When possible, H5Iget\_name returns the path with which the object was opened.

**Parameters:**

<code>hid_t obj_id</code>	IN: Identifier of the object. This identifier can refer to a group, dataset, or named datatype.
<code>char *name</code>	OUT: A name associated with the identifier.
<code>size_t size</code>	IN: The size of the name buffer; must be the size of the name in bytes plus 1 for a NULL terminator.

**Returns:**

Returns the length of the name if successful, returning 0 (zero) if no name is associated with the identifier. Otherwise returns a negative value.

**Fortran90 Interface:** h5iget\_name\_f

```
SUBROUTINE h5iget_name_f(obj_id, buf, buf_size, name_size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)      :: obj_id      ! Object identifier
  CHARACTER(LEN=*), INTENT(OUT) :: buf          ! Buffer to hold object name
  INTEGER(SIZE_T), INTENT(IN)     :: buf_size    ! Buffer size
  INTEGER(SIZE_T), INTENT(OUT)    :: name_size   ! Name size
  INTEGER, INTENT(OUT)            :: hdferr      ! Error code
                                          ! 0 on success, and -1 on failure

END SUBROUTINE h5iget_name_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Iget\_ref

**Signature:**

```
int H5Iget_ref( hid_t obj_id )
```

**Purpose:**

Retrieves the reference count for an object.

**Description:**

H5Iget\_ref retrieves the reference count of the object identified by obj\_id.

The reference count for an object ID is attached to the information about an object in memory and has no relation to the number of links to an object on disk.

This function can also be used to check if an object ID is still valid. A non-negative return value from this function indicates that the ID is still valid.

**Parameters:**

*hid\_t* obj\_id      IN: Object identifier whose reference count will be retrieved.

**Returns:**

Returns a non-negative current reference count of the object ID if successful; otherwise a negative value is returned.

**Fortran90 Interface:** h5iget\_ref\_f

```
SUBROUTINE h5iget_ref_f(obj_id, ref_count, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id  !Object identifier
  INTEGER, INTENT(OUT) :: ref_count      !Reference count of object ID
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                          ! 0 on success, and -1 on failure
END SUBROUTINE h5iget_ref_f
```

**History:**

**Release    C**

1.6.2      Function introduced in this release.  
             Fortran subroutine introduced in this release.

**Name:** H5Iget\_type

**Signature:**

*H5I\_type\_t* H5Iget\_type( *hid\_t* obj\_id )

**Purpose:**

Retrieves the type of an object.

**Description:**

H5Iget\_type retrieves the type of the object identified by obj\_id.

Valid types returned by the function are

H5I_FILE	File
H5I_GROUP	Group
H5I_DATATYPE	Datatype
H5I_DATASPACE	Dataspace
H5I_DATASET	Dataset
H5I_ATTR	Attribute

If no valid type can be determined or the identifier submitted is invalid, the function returns

H5I_BADID	Invalid identifier
-----------	-----------------------

This function is of particular value in determining the type of object closing function (H5Dclose, H5Gclose, etc.) to call after a call to H5Rdereference.

**Parameters:**

*hid\_t* obj\_id      IN: Object identifier whose type is to be determined.

**Returns:**

Returns the object type if successful; otherwise H5I\_BADID.

**Fortran90 Interface:** h5iget\_type\_f

```

SUBROUTINE h5iget_type_f(obj_id, type, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id  !Object identifier
  INTEGER, INTENT(OUT) :: type          !type of an object.
                                          !possible values are:
                                          !H5I_FILE_F
                                          !H5I_GROUP_F
                                          !H5I_DATATYPE_F
                                          !H5I_DATASPACE_F
                                          !H5I_DATASET_F
                                          !H5I_ATTR_F
                                          !H5I_BADID_F
  INTEGER, INTENT(OUT) :: hdferr        ! E rror code
                                          ! 0 on success, and -1 on failure
END SUBROUTINE h5iget_type_f

```

**Name:** H5Iget\_type\_ref

**Signature:**

*int* H5Iget\_type\_ref( *H5I\_type\_t* type )

**Purpose:**

Retrieves the reference count on an ID type.

**Description:**

H5Iget\_type\_ref retrieves the reference count on an ID type. The reference count is used by the library to indicate when an ID type can be destroyed.

The *type* parameter is the identifier for the ID type whose reference count is to be retrieved. This identifier must have been created by a call to H5Iregister\_type.

**Parameters:**

*H5I\_type\_t* type      IN: The identifier of the type whose reference count is to be retrieved

**Returns:**

Returns the current reference count on success, negative on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5linc\_ref

**Signature:**

```
int H5Iinc_ref( hid_t obj_id )
```

**Purpose:**

Increments the reference count for an object.

**Description:**

H5Iinc\_ref increments the reference count of the object identified by obj\_id.

The reference count for an object ID is attached to the information about an object in memory and has no relation to the number of links to an object on disk.

The reference count for a newly created object will be 1. Reference counts for objects may be explicitly modified with this function or with H5Idec\_ref. When an object ID's reference count reaches zero, the object will be closed. Calling an object ID's 'close' function decrements the reference count for the ID which normally closes the object, but if the reference count for the ID has been incremented with this function, the object will only be closed when the reference count reaches zero with further calls to H5Idec\_ref or the object ID's 'close' function.

If the object ID was created by a collective parallel call (such as H5Dcreate, H5Gopen, etc.), the reference count should be modified by all the processes which have copies of the ID. Generally this means that group, dataset, attribute, file and named datatype IDs should be modified by all the processes and that all other types of IDs are safe to modify by individual processes.

This function is of particular value when an application is maintaining multiple copies of an object ID. The object ID can be incremented when a copy is made. Each copy of the ID can then be safely closed or decremented and the HDF5 object will be closed when the reference count for that that object drops to zero.

**Parameters:**

*hid\_t* obj\_id      IN: Object identifier whose reference count will be modified.

**Returns:**

Returns a non-negative reference count of the object ID after incrementing it if successful; otherwise a negative value is returned.

**Fortran90 Interface:** h5iinc\_ref\_f

```
SUBROUTINE h5iinc_ref_f(obj_id, ref_count, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id !Object identifier
  INTEGER, INTENT(OUT) :: ref_count !Reference count of object ID
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                   ! 0 on success, and -1 on failure
END SUBROUTINE h5iinc_ref_f
```

**History:**

Release	C
1.6.2	Function introduced in this release. Fortran subroutine introduced in this release.



**Name:** H5Iinc\_type\_ref

**Signature:**

*int* H5Iinc\_type\_ref( *H5I\_type\_t* type )

**Purpose:**

Increments the reference count on an ID type.

**Description:**

H5Iinc\_type\_ref increments the reference count on an ID type. The reference count is used by the library to indicate when an ID type can be destroyed.

The *type* parameter is the identifier for the ID type whose reference count is to be incremented. This identifier must have been created by a call to H5Iregister\_type.

**Parameters:**

*H5I\_type\_t* type      IN: The identifier of the type whose reference count is to be incremented

**Returns:**

Returns the current reference count on success, negative on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Inmembers

**Signature:**

*herr\_t* H5Inmembers( *H5I\_type\_t* type, *hsize\_t* \*num\_members )

**Purpose:**

Returns the number of identifiers in a given identifier type.

**Description:**

H5Inmembers returns the number of identifiers of the identifier type specified in type.

The number of identifiers is returned in num\_members. If no identifiers of this type have been registered, the type does not exist, or it has been destroyed, num\_members is returned with the value 0.

**Parameters:**

*H5I\_type\_t* type                      IN: Identifier for the identifier type whose member count will be retrieved

*hsize\_t* \*num\_members              OUT: Number of identifiers of the specified identifier type.

**Returns:**

Returns a non-negative value on success; otherwise returns negative value.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Iobject\_verify

**Signature:**

```
void *H5Iobject_verify( hid_t id, H5I_type_t id_type )
```

**Purpose:**

Returns the object referenced by id.

**Description:**

H5Iobject\_verify returns a pointer to the memory referenced by id after verifying that id is of type id\_type. This function is analogous to dereferencing a pointer in C with type checking.

H5Iregister(*H5I\_type\_t* type, void \*object) takes an *H5I\_type\_t* and a void pointer to an object, returning an *hid\_t* of that type. This *hid\_t* can then be passed to H5Iobject\_verify along with its type to retrieve the object.

H5Iobject\_verify does not change the ID it is called on in any way (as opposed to H5Iremove\_verify, which removes the ID from its type's hash table).

**Parameters:**

*hid\_t* id                      IN: ID to be dereferenced

*H5I\_type\_t* type            IN: ID type to which id should belong

**Returns:**

Pointer to the object referenced by id on success, NULL on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Iregister

**Signature:**

*hid\_t* H5Iregister( *H5I\_type\_t* type, void \*object )

**Purpose:**

Creates and returns a new ID.

**Description:**

H5Iregister allocates space for a new ID and returns an identifier for it.

The *type* parameter is the identifier for the ID type to which this new ID will belong. This identifier must have been created by a call to H5Iregister\_type.

The *object* parameter is a pointer to the memory which the new ID will be a reference to. This pointer will be stored by the library and returned to you via a call to H5Iobject\_verify.

**Parameters:**

<i>H5I_type_t</i> type	IN: The identifier of the type to which the new ID will belong
void *object	IN: Pointer to memory for the library to store

**Returns:**

Returns the new ID on success, negative on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Iregister\_type

**Signature:**

```
H5I_type_t H5Iregister_type( size_t hash_size, unsigned reserved, H5I_free_t  
free_func )
```

**Purpose:**

Creates and returns a new ID type.

**Description:**

H5Iregister\_type allocates space for a new ID type and returns an identifier for it.

The hash\_size parameter indicates the minimum size of the hash table used to store IDs in the new type.

The reserved parameter indicates the number of IDs in this new type to be reserved. Reserved IDs are valid IDs which are not associated with any storage within the library.

The free\_func parameter is a function pointer to a function which returns an *herr\_t* and accepts a *void \**. The purpose of this function is to deallocate memory for a single ID. It will be called by H5Iclear\_type and H5Idestroy\_type on each ID. This function is NOT called by H5Iremove\_verify. The *void \** will be the same pointer which was passed in to the H5Iregister function. The free\_func function should return 0 on success and -1 on failure.

**Parameters:**

<i>size_t</i> hash_size	IN: Size of the hash table (in entries) used to store IDs for the new type
<i>unsigned</i> reserved	IN: Number of reserved IDs for the new type
<i>H5I_free_t</i> free_func	IN: Function used to deallocate space for a single ID

**Returns:**

Returns the type identifier on success, negative on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Iremove\_verify

**Signature:**

*void \*H5Iremove\_verify(hid\_t id, H5I\_type\_t id\_type )*

**Purpose:**

Removes an ID from internal storage.

**Description:**

H5Iremove\_verify first ensures that *id* belongs to *id\_type*. If so, it removes *id* from internal storage and returns the pointer to the memory it referred to. This pointer is the same pointer that was placed in storage by H5Iregister. If *id* does not belong to *id\_type*, then NULL is returned.

The *id* parameter is the ID which is to be removed from internal storage. Note: this function does NOT deallocate the memory that *id* refers to. The pointer returned by H5Iregister must be deallocated by the user to avoid memory leaks.

The *type* parameter is the identifier for the ID type which *id* is supposed to belong to. This identifier must have been created by a call to H5Iregister\_type.

**Parameters:**

*hid\_t id*                      IN: The ID to be removed from internal storage

*H5I\_type\_t type*            IN: The identifier of the type whose reference count is to be retrieved

**Returns:**

Returns a pointer to the memory referred to by *id* on success, NULL on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Isearch

**Signature:**

*void* \*H5Isearch( *H5I\_type\_t* type, *H5I\_search\_func\_t* func, *void* \*key )

**Purpose:**

Finds the memory referred to by an ID within the given ID type such that some criterion is satisfied.

**Description:**

H5Isearch searches through a give ID type to find an object that satisfies the criteria defined by func. If such an object is found, the pointer to the memory containing this object is returned. Otherwise, NULL is returned. To do this, func is called on every member of type. The first member to satisfy func is returned.

The type parameter is the identifier for the ID type which is to be searched. This identifier must have been created by a call to H5Iregister\_type.

The parameter func is a function pointer to a function which takes three parameters. The first parameter is a *void* \*. It will be a pointer the object to be tested. This is the same object that was placed in storage using H5Iregister. The second parameter is a *hid\_t*. It is the ID of the object to be tested. The last parameter is a *void* \*. This is the key parameter and can be used however the user finds helpful. Or it can simply be ignored if it is not needed. func returns 0 if the object it is testing does not pass its criteria. A non-zero value should be returned if the object does pass its criteria.

The key parameter will be passed to the search function as a parameter. It can be used to further define the search at run-time.

**Parameters:**

<i>H5I_type_t</i> type	IN: The identifier of the type to be searched
<i>H5I_search_func_t</i> func	IN: The function defining the search criteria
<i>void</i> *key	IN: A key for the search function

**Returns:**

Returns a pointer to the object which satisfies the search function on success, NULL on failure.

**Fortran90 Interface:**

This function is not supported in FORTRAN 90.

**Name:** H5Itype\_exists

**Signature:**

*htri\_t* H5Itype\_exists( *H5I\_type\_t* type )

**Purpose:**

Determines whether an identifier type is registered.

**Description:**

H5Itype\_exists determines whether the given identifier type, *type*, is registered with the library.

**Parameters:**

*H5I\_type\_t* type     IN: Identifier type.

**Returns:**

Returns 1 if the type is registered and 0 if not. Returns a negative value on failure.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------



## H5L: Link Interface

### Link API Functions

The Link interface, H5L, functions create and manipulate links in an HDF5 group. This interface includes functions that enable the creation and use of user-defined link classes.

#### The C Interfaces:

- |                      |                       |                      |
|----------------------|-----------------------|----------------------|
| • H5Lcreate_hard     | • H5Lget_info         | • H5Literate         |
| • H5Lcreate_soft     | • H5Lget_val          | • H5Literate_by_name |
| • H5Lcreate_external | • H5Lunpack_elink_val | • H5Lvisit           |
| • H5Lexists          |                       | • H5Lvisit_by_name   |
| • H5Lmove            | • H5Lcreate_ud        | • H5Lget_info_by_idx |
| • H5Lcopy            | • H5Lregister         | • H5Lget_name_by_idx |
| • H5Ldelete          | • H5Lunregister       | • H5Lget_val_by_idx  |
|                      | • H5Lis_registered    | • H5Ldelete_by_idx   |

#### *Alphabetical Listing*

- |                      |                      |                       |
|----------------------|----------------------|-----------------------|
| • H5Lcopy            | • H5Lget_info        | • H5Lmove             |
| • H5Lcreate_external | • H5Lget_info_by_idx | • H5Lregister         |
| • H5Lcreate_hard     | • H5Lget_name_by_idx | • H5Lunpack_elink_val |
| • H5Lcreate_soft     | • H5Lget_val         | • H5Lunregister       |
| • H5Lcreate_ud       | • H5Lget_val_by_idx  | • H5Lvisit            |
| • H5Ldelete          | • H5Lis_registered   | • H5Lvisit_by_name    |
| • H5Ldelete_by_idx   | • H5Literate         |                       |
| • H5Lexists          | • H5Literate_by_name |                       |

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- |                        |                      |                        |
|------------------------|----------------------|------------------------|
| • h5lcopy_f            | • h5ldelete_f        | • h5lget_info_by_idx_f |
| • h5lcreate_external_f | • h5ldelete_by_idx_f | • h5lget_name_by_idx_f |
| • h5lcreate_hard_f     | • h5lexists_f        | • h5lis_registered_f   |
| • h5lcreate_soft_f     | • h5lget_info_f      | • h5lmove_f            |



**Name:** H5Lcopy**Signature:**

```
herr_t H5Lcopy(hid_t src_loc_id, const char *src_name, hid_t dest_loc_id, const char
*dest_name, hid_t lcpl_id hid_t lapl_id)
```

**Purpose:**

Copies a link from one location to another.

**Description:**

H5Lcopy copies the link specified by `src_name` from the file or group specified by `src_loc_id` to the destination location `dest_loc_id`. The new copy of the link is created with the name `dest_name`.

The destination location, as specified in `dest_loc_id`, must be either the current file or a group in the current file. If `dest_loc_id` is the file identifier, the copy is placed in the file's root group.

The new link is created with the creation and access property lists specified by `lcpl_id` and `lapl_id`. The interpretation of `lcpl_id` is limited in the manner described in the next paragraph.

H5Lcopy retains the creation time and the target of the original link. However, since the link may be renamed, the character encoding is that specified in `lcpl_id` rather than that of the original link. Other link creation properties are ignored.

If the link is a soft link, also known as a symbolic link, its target is interpreted relative to the location of the copy.

Several properties are available to govern the behavior of H5Lcopy. These properties are set in the link creation and access property lists, `lcpl_id` and `lapl_id`, respectively. The property controlling creation of missing intermediate groups is set in the link creation property list with `H5Pset_create_intermediate_group`; this function ignores any other properties in the link creation property list. Properties controlling character encoding, link traversals, and external link prefixes are set in the link access property list with `H5Pset_char_encoding`, `H5Pset_nlinks`, and `H5Pset_elink_prefix`.

H5Lcopy does not affect the object that the link points to.

H5Lcopy cannot copy links to a different file; to copy objects to a different file, see H5Ocopy.

**Parameters:**

<i>hid_t</i> src_loc_id	IN: Location identifier of the source link
<i>const char</i> *src_name	IN: Name of the link to be copied
<i>hid_t</i> dest_loc_id	IN: Location identifier specifying the destination of the copy
<i>const char</i> *dest_name	IN: Name to be assigned to the new copy
<i>hid_t</i> lcpl_id	IN: Link creation property list identifier
<i>hid_t</i> lapl_id	IN: Link access property list identifier

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface: h5lcopy\_f**

```

SUBROUTINE h5lcopy_f(src_loc_id, src_name, dest_loc_id, dest_name, hdferr, &
                    lcpl_id, lapl_id)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: src_loc_id
                                ! Location identifier of the source link
  CHARACTER(LEN=*), INTENT(IN) :: src_name
                                ! Name of the link to be copied
  INTEGER(HID_T), INTENT(IN) :: dest_loc_id
                                ! Location identifier specifying the
                                ! destination of the copy
  CHARACTER(LEN=*), INTENT(IN) :: dest_name
                                ! Name to be assigned to the new copy
  INTEGER, INTENT(OUT) :: hdferr ! Error code:
                                ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lcpl_id
                                ! Link creation property list identifier
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                ! Link access property list identifier
END SUBROUTINE h5lcopy_f

```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Lcreate\_external

**Signature:**

```
herr_t H5Lcreate_external( const char *file_name, const char *object_name, hid_t
link_loc_id, const char *link_name, hid_t lcpl_id, hid_t lapl_id )
```

**Purpose:**

Creates a soft link to an object in a different file.

**Description:**

H5Lcreate\_external creates a new soft link to an external object, which is an object in a different HDF5 file from the location of the link.

`file_name` identifies the target file containing the target object; `object_name` specifies the path of the target object within that file. `object_name` must start at the target file's root group but is not interpreted until lookup time.

`link_loc_id` and `link_name` specify the location and name, respectively, of the new link. `link_name` is interpreted relative to `link_loc_id`

`lcpl_id` is the link creation property list used in creating the new link.

`lapl_id` is the link access property list used in traversing to the place where the new link is to be created.

An external link behaves similarly to a soft link, and like a soft link in an HDF5 file, it may *dangle*: the target file and object need not exist at the time that the external link is created.

When the external link `link_name` is accessed, the library will search for the target file `file_name` as described below:

- ◊ If `file_name` is a relative pathname, the following steps are performed:
  - The library will get the prefix(es) set in the environment variable `HDF5_EXT_PREFIX` and will try prepending each prefix to `file_name` to form a new `file_name`.
  - If the new `file_name` does not exist or `HDF5_EXT_PREFIX` is not set, the library will get the prefix set via `H5Pset_elink_prefix` and prepend it to `file_name` to form a new `file_name`.
  - If the new `file_name` does not exist or no prefix is being set by `H5Pset_elink_prefix`, then the path of the file associated with `link_loc_id` is obtained. This path can be the absolute path or the current working directory+relative path of that file when it is created/opened. The library will prepend this path to `file_name` to form a new `file_name`.
  - If the new `file_name` does not exist, then the library will look for `file_name` and will return failure/success accordingly.
- ◊ If `file_name` is an absolute pathname, the library will try to find `file_name`. If `file_name` does not exist, the `file_name` is stripped of the directory paths to form a new `file_name`. See examples below on how `file_name` is stripped to form a new `file_name`. The search for the new `file_name` then follows the same steps as described above for a relative pathname.

Note that `file_name` is considered to be an absolute pathname when the following condition is true:

- ◊ For Unix, the first character of `file_name` is a '/', e.g. `"/tmp/A.h5"`.

If `file_name` does not exist, the new `file_name` after stripping `file_name` will be "A.h5".

◊ For Windows, there are 3 cases:

1. `file_name` is an absolute drive with absolute pathname, e.g. "C:\tmp\A.h5".

If `file_name` does not exist, the new `file_name` after stripping `file_name` will be "A.h5".

2. `file_name` is an absolute pathname without specifying drive name, e.g. "\tmp\A.h5".

If `file_name` does not exist, the new `file_name` after stripping `file_name` will be "A.h5".

3. `file_name` is an absolute drive with relative pathname, e.g. "C:\tmp\A.h5".

If `file_name` does not exist, the new `file_name` after stripping `file_name` will be "tmp\A.h5".

The library opens the target file `file_name` with the file access property list that is set via `H5Pset_elink_fapl()` when the external link `link_name` is accessed. If no such identifier is set, the library uses the file access property list identifier of the file associated with `link_loc_id` to open the target file.

#### Parameters:

<i>const char</i> * <code>file_name</code>	IN: Name of the target file containing the target object.
<i>const char</i> * <code>object_name</code>	IN: Path within the target file to the target object.
<i>hid_t</i> <code>link_loc_id</code>	IN: The file or group identifier for the new link.
<i>const char</i> * <code>link_name</code>	IN: The name of the new link.
<i>hid_t</i> <code>lcpl_id</code>	IN: Link creation property list identifier.
<i>hid_t</i> <code>lapl_id</code>	IN: Link access property list identifier.

#### Returns:

Returns a non-negative value if successful; otherwise returns a negative value.

#### Fortran90 Interface: h5lcreate\_external\_f

```
SUBROUTINE h5lcreate_external_f(file_name, obj_name, link_loc_id, link_name, &
                                hdferr, lcpl_id, lapl_id)

  IMPLICIT NONE
  CHARACTER(LEN=*), INTENT(IN) :: file_name
                                ! Name of the file containing the target object. Neither
                                ! the file nor the target object is required to exist.
                                ! May be the file the link is being created in.
  CHARACTER(LEN=*), INTENT(IN) :: obj_name
                                ! Name of the target object, which must already exist.
  INTEGER(HID_T), INTENT(IN) :: link_loc_id
                                ! The file or group identifier for the new link.
  CHARACTER(LEN=*), INTENT(IN) :: link_name
                                ! The name of the new link.
  INTEGER, INTENT(OUT) :: hdferr
                                ! Error code:
                                ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lcpl_id
                                ! Link creation property list identifier.
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                ! Link access property list identifier.
END SUBROUTINE h5lcreate_external_f
```

#### History:

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Lcreate\_hard

**Signature:**

```
herr_t H5Lcreate_hard(hid_t obj_loc_id, const char *obj_name, hid_t link_loc_id, const char *link_name, hid_t lcpl_id, hid_t lapl_id)
```

**Purpose:**

Creates a hard link to an object.

**Description:**

H5Lcreate\_hard creates a new hard link to a pre-existing object in an HDF5 file. The new link may be one of many that point to that object.

obj\_loc\_id and obj\_name specify the location and name, respectively, of the target object, i.e., the object that the new hard link points to.

link\_loc\_id and link\_name specify the location and name, respectively, of the new hard link.

obj\_name and link\_name are interpreted relative to obj\_loc\_id and link\_loc\_id, respectively.

The target object must already exist in the file.

lcpl\_id and lapl\_id are the link creation and access property lists associated with the new link.

Hard and soft links are for use only if the target object is in the current file. If the desired target object is in a different file from the new link, an external link may be created with H5Lcreate\_external.

The HDF5 library keeps a count of all hard links pointing to an object; if the hard link count reaches zero (0), the object will be deleted from the file. Creating new hard links to an object will prevent it from being deleted if other links are removed. The library maintains no similar count for soft links and they can dangle.

**Parameters:**

<i>hid_t</i> obj_loc_id	IN: The file or group identifier for the target object.
<i>const char</i> *obj_name	IN: Name of the target object, which must already exist.
<i>hid_t</i> link_loc_id	IN: The file or group identifier for the new link.
<i>const char</i> *link_name	IN: The name of the new link.
<i>hid_t</i> lcpl_id	IN: Link creation property list identifier.
<i>hid_t</i> lapl_id	IN: Link access property list identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5lcreate\_hard\_f

```

SUBROUTINE h5lcreate_hard_f(obj_loc_id, obj_name, link_loc_id, link_name, &
                           hdferr, lcpl_id, lapl_id)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_loc_id
                           ! The file or group identifier for the target object.
  CHARACTER(LEN=*), INTENT(IN) :: obj_name
                           ! Name of the target object, which must already exist.
  INTEGER(HID_T), INTENT(IN) :: link_loc_id
                           ! The file or group identifier for the new link.
  CHARACTER(LEN=*), INTENT(IN) :: link_name
                           ! The name of the new link.
  INTEGER, INTENT(OUT) :: hdferr
                           ! Error code:
                           ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lcpl_id
                           ! Link creation property list identifier.
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                           ! Link access property list identifier.
END SUBROUTINE h5lcreate_hard_f

```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.



**Name:** H5Lcreate\_soft

**Signature:**

```
herr_t H5Lcreate_soft( const char *target_path, hid_t link_loc_id, const char
*link_name, hid_t lcpl_id, hid_t lapl_id )
```

**Purpose:**

Creates a soft link to an object.

**Description:**

H5Lcreate\_soft creates a new soft link to an object in an HDF5 file. The new link may be one of many that point to that object.

target\_path specifies the path to the target object, i.e., the object that the new soft link points to. target\_path can be anything and is interpreted at lookup time. This path may be absolute in the file or relative to link\_loc\_id.

link\_loc\_id and link\_name specify the location and name, respectively, of the new soft link. link\_name is interpreted relative to link\_loc\_id

lcpl\_id and lapl\_id are the link creation and access property lists associated with the new link.

For instance, if target\_path is ./foo, link\_loc\_id specifies ./x/y/bar, and the name of the new link is new\_link, then a subsequent request for new\_link will look up the object ./x/y/bar/foo.

H5Lcreate\_soft is for use only if the target object is in the current file. If the desired target object is in a different file from the new link, use H5Lcreate\_external to create an external link.

Soft links and external links are also known as symbolic links as they use a name to point to an object; hard links employ an object's address in the file.

Unlike hard links, a soft link in an HDF5 file is allowed to *dangle*, meaning that the target object need not exist at the time that the link is created.

The HDF5 library does not keep a count of soft links as it does of hard links.

**Parameters:**

const char *target_path	IN: Path to the target object, which is not required to exist.
hid_t link_loc_id	IN: The file or group identifier for the new link.
const char *link_name	IN: The name of the new link.
hid_t lcpl_id	IN: Link creation property list identifier.
hid_t lapl_id	IN: Link access property list identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5lcreate\_soft\_f

```

SUBROUTINE h5lcreate_soft_f(target_path, link_loc_id, link_name, hdferr, &
                           lcpl_id, lapl_id)

  IMPLICIT NONE
  CHARACTER(LEN=*), INTENT(IN) :: target_path
                                ! Path to the target object,
                                ! which is not required to exist.
  INTEGER(HID_T), INTENT(IN) :: link_loc_id
                                ! The file or group identifier for the new link.
  CHARACTER(LEN=*), INTENT(IN) :: link_name
                                ! The name of the new link.
  INTEGER, INTENT(OUT) :: hdferr ! Error code:
                                ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lcpl_id
                                ! Link creation property list identifier.
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                ! Link access property list identifier.
END SUBROUTINE h5lcreate_soft_f

```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Lcreate\_ud

**Signature:**

```
herr_t H5Lcreate_ud(hid_t link_loc_id, const char *link_name, H5L_type_t link_type,
const char *udata, size_t udata_size, hid_t lcpl_id, hid_t lapl_id)
```

**Purpose:**

Creates a link of a user-defined type.

**Description:**

H5Lcreate\_ud creates a link of user-defined type `link_type` named `link_name` at the location specified in `link_loc_id` with user-specified data `udata`.

`link_name` is interpreted relative to `link_loc_id`.

The link class of the new link, `link_type`, must already be registered with the library. Such user-defined link classes are registered with `H5Lregister`.

The `H5L_type_t`, the `ENUM` specifying valid link classes, is defined in `H5Lpublic.h`. Valid values without registered user-defined link types include the following:

```
H5L_LINK_HARD
H5L_LINK_SOFT
H5L_LINK_EXTERNAL
```

Registering a user-defined link type with `H5Lregister` adds a user-defined symbol to the `H5L_type_t` `ENUM`; that user-defined symbol is then passed in the `link_type` parameter of `H5Lcreate_ud` and will be returned by `H5Lget_info`.

The format of the information pointed to by `udata` is defined by the user. `udata_size` specifies the size of the `udata` buffer. `udata` may be `NULL` if `udata_size` is zero (0).

The property lists specified by `lcpl_id` and `lapl_id` specify properties used to create and access the link.

**Note:**

Though the external link type is included in the HDF5 Library distribution, it is implemented as a user-defined link type. This was done, in part, to provide a model for implementation of other user-defined links.

**Parameters:**

<i>hid_t</i> link_loc_id	IN: Link location identifier
<i>const char</i> *link_name	IN: Link name
<i>H5L_type_t</i> link_type	IN: User-defined link class
<i>const char</i> *udata	IN: User-supplied link information
<i>size_t</i> udata_size	IN: Size of <code>udata</code> buffer
<i>hid_t</i> lcpl_id	IN: Link creation property list identifier
<i>hid_t</i> lapl_id	IN: Link access property list identifier

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

---

*Last modified: 10 April 2009***Name:** H5Lexists**Signature:**

```
htri_t H5Lexists( hid_t loc_id, const char *name, hid_t lapl_id )
```

**Purpose:**

Determine whether a link with the specified name exists in a group.

**Description:**

H5Lexists allows an application to determine whether the link name exists in the group or file specified with `loc_id`. The link may be of any type; only the presence of a link with that name is checked.

Note that H5Lexists verifies only that the target link exists. If name includes either a relative path or an absolute path to the target link, intermediate steps along the path must be verified before the existence of the target link can be safely checked. If the path is not verified and an intermediate element of the path does not exist, H5Lexists will fail. The example in the next paragraph illustrates one step-by-step method for verifying the existence of a link with a relative or absolute path.

**Example:** Use the following steps to verify the existence of the link `datasetD` in the group `group1/group2/softlink_to_group3/`, where `group1` is a member of the group specified by `loc_id`:

- ◇ First use H5Lexists to verify that `group1` exists.
- ◇ If `group1` exists, use H5Lexists again, this time with name set to `group1/group2`, to verify that `group2` exists.
- ◇ If `group2` exists, use H5Lexists with name set to `group1/group2/softlink_to_group3` to verify that `softlink_to_group3` exists.
- ◇ If `softlink_to_group3` exists, you can now safely use H5Lexists with name set to `group1/group2/softlink_to_group3/datasetD` to verify that the target link, `datasetD`, exists.

If the link to be verified is specified with an absolute path, the same approach should be used, but starting with the first link in the file's root group. For instance, if `datasetD` were in `/group1/group2/softlink_to_group3`, the first call to H5Lexists would have name set to `/group1`.

Note that this is an outline and does not include all necessary details. Depending on circumstances, for example, you may need to verify that an intermediate link points to a group and that a soft link points to an existing target.

**Parameters:**

<code>hid_t loc_id</code>	IN: Identifier of the file or group to query.
<code>const char *name</code>	IN: The name of the link to check.
<code>hid_t lapl_id</code>	IN: Link access property list identifier.

**Returns:**

Returns TRUE or FALSE if successful; otherwise returns a negative value.

**Failure Modes:**

H5Lexists checks the existence of only the final element in a relative or absolute path; it does not check any other path elements. The function will therefore fail when both of the following conditions

exist:

◊ name is not local to the group specified by `loc_id` or, if `loc_id` is something other than a group identifier, name is not local to the root group.

◊ Any element of the relative path or absolute path in name, except the target link, does not exist.

### Fortran90 Interface: h5lexists\_f

```
SUBROUTINE h5lexists_f(loc_id, name, link_exists, hdferr, lapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id ! Identifier of file or group to query.
  CHARACTER(LEN=*), INTENT(IN) :: name ! Link name to check.
  LOGICAL, INTENT(OUT) :: link_exists ! .TRUE. if exists, .FALSE. otherwise
  INTEGER, INTENT(OUT) :: hdferr      ! Error code:
                                     ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                     ! Link access property list identifier.
END SUBROUTINE h5lexists_f
```

### History:

**Release**    **C**

1.8.0        Function introduced in this release.

**Name:** H5Lget\_info

**Signature:**

```
herr_t H5Lget_info(hid_t link_loc_id, const char *link_name, H5L_info_t *link_buff,
hid_t lapl_id)
```

**Purpose:**

Returns information about a link.

**Description:**

H5Lget\_info returns information about the specified link through the `link_buff` argument.

A file or group identifier, `link_loc_id`, specifies the location of the link. A link name, `link_name`, interpreted relative to `loc_id`, specifies the link being queried.

`lapl_id` is the link access property list associated with the link `link_name`. In the general case, when default link access properties are acceptable, this can be passed in as `H5P_DEFAULT`. An example of a situation that requires a non-default link access property list is when the link is an external link; an external link may require that a link prefix be set in a link access property list (see `H5Pset_elink_prefix`).

H5Lget\_info returns information about `link_name` in the data structure `H5L_info_t`, which is described below and defined in `H5Lpublic.h`. This structure is returned in the buffer `link_buff`.

```
typedef struct {
    H5L_type_t      type;
    hbool_t         corder_valid;
    int64_t         corder;
    H5T_cset_t      cset;
    union {
        haddr_t     address;
        size_t       val_size;
    } u;
} H5L_info_t;
```

In the above struct, `type` specifies the link class. Valid values include the following:

<code>H5L_LINK_HARD</code>	Hard link
<code>H5L_LINK_SOFT</code>	Soft link
<code>H5L_LINK_EXTERNAL</code>	External link
<code>H5L_LINK_ERROR</code>	Error

There will be additional valid values if user-defined links have been registered.

`corder` specifies the link's creation order position while `corder_valid` indicates whether the value in `corder` is valid.

If `corder_valid` is `TRUE`, the value in `corder` is known to be valid; if `corder_valid` is `FALSE`, the value in `corder` is presumed to be invalid;

`corder` starts at zero (0) and is incremented by one (1) as new links are created. But higher-numbered entries are not adjusted when a lower-numbered link is deleted; the deleted link's creation order position is simply left vacant. In such situations, the value of `corder` for the last link created will be larger than

the number of links remaining in the group.

*cset* specifies the character set in which the link name is encoded. Valid values include the following:

H5T_CSET_ASCII	US ASCII
H5T_CSET_UTF8	UTF-8 Unicode encoding

*address* and *val\_size* are returned for hard and symbolic links, respectively. Symbolic links include soft and external links and some user-defined links.

If the link is a hard link, *address* specifies the file address that the link points to.

If the link is a symbolic link, *val\_size* will be the length of the link value, e.g., the length of the name of the pointed-to object with a null terminator.

#### Parameters:

<i>hid_t</i> link_loc_id	IN: File or group identifier.
const char *link_name	IN: Name of the link for which information is being sought.
H5L_info_t *link_buff	OUT: Buffer in which link information is returned.
<i>hid_t</i> lapl_id	IN: Link access property list identifier.

#### Returns:

Returns a non-negative value if successful, with the fields of *link\_buff* (if non-null) initialized. Otherwise returns a negative value.

#### Fortran90 Interface: h5lget\_info\_f

```

SUBROUTINE h5lget_info_f(link_loc_id, link_name, &
    cset, corder, f_corder_valid, link_type, address, val_size, &
    hdferr, lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: link_loc_id
        ! File or group identifier.
    CHARACTER(LEN=*), INTENT(IN) :: link_name
        ! Name of the link for which information is being sought.
    INTEGER, INTENT(OUT) :: cset
        ! Indicates the character set used for the link's name.
    INTEGER, INTENT(OUT) :: corder
        ! Specifies the link's creation order position.
    LOGICAL, INTENT(OUT) :: f_corder_valid
        ! Indicates whether the value in corder is valid.
    INTEGER, INTENT(OUT) :: link_type
        ! Specifies the link class:
        !   H5L_LINK_HARD_F      - Hard link
        !   H5L_LINK_SOFT_F      - Soft link
        !   H5L_LINK_EXTERNAL_F  - External link
        !   H5L_LINK_ERROR_F     - Error
    INTEGER, INTENT(OUT) :: address
        ! If the link is a hard link, address specifies the file
        ! address that the link points to
    INTEGER(HSIZE_T), INTENT(OUT) :: val_size
        ! If the link is a symbolic link, val_size will be the
        ! length of the link value
    INTEGER, INTENT(OUT) :: hdferr
        ! Error code:
        ! 0 on success and -1 on failure
    INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
        ! Link access property list
END SUBROUTINE h5lget_info_f

```



**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Lget\_info\_by\_idx

**Signature:**

```
herr_t H5Lget_info_by_idx(hid_t loc_id, const char *group_name, H5_index_t
index_field, H5_iter_order_t order, hsize_t n, H5L_info_t *link_val, hid_t lapl_id)
```

**Purpose:**

Retrieves metadata for a link in a group, according to the order within a field or index.

**Description:**

H5Lget\_info\_by\_idx returns the metadata for a link in a group according to a specified field or index and a specified order.

The link for which information is to be returned is specified by `index_field`, `order`, and `n` as follows:

- ◊ `index_field` specifies the field by which the links in `group_name` are ordered. The links may be indexed on this field, in which case operations seeking specific links are likely to complete more quickly.
- ◊ `order` specifies the order in which the links are to be referenced for the purposes of this function.
- ◊ `n` specifies the position of the subject link. Note that this count is zero-based; 0 (zero) indicates that the function will return the value of the first link; if `n` is 5, the function will return the value of the sixth link; etc.

For example, assume that `index_field`, `order`, and `n` are `H5_INDEX_NAME`, `H5_ITER_DEC`, and 5, respectively. `H5_INDEX_NAME` indicates that the links are accessed in alpha-numeric order by their names. `H5_ITER_DEC` specifies that the list be traversed in reverse order, or in decremented order. And 5 specifies that this call to the function will return the metadata for the 6th link (`n + 1`) from the end.

See `H5Literate` for a list of valid values and further discussion regarding `index_field` and `order`.

If `loc_id` specifies the group in which the link resides, `group_name` can be a dot (.).

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier specifying location of subject group
<i>const char</i> *group_name	IN: Name of subject group
<i>H5_index_t</i> index_field	IN: Index or field which determines the order
<i>H5_iter_order_t</i> order	IN: Order within field or index
<i>hsize_t</i> n	IN: Link for which to retrieve information
<i>H5L_info_t</i> *link_val	OUT: Buffer in which link value is returned
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5lget\_info\_by\_idx\_f

```

SUBROUTINE h5lget_info_by_idx_f(loc_id, group_name, index_field, order, n, &
                               f_corder_valid, corder, cset, data_size, hdferr, lapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id
                                ! File or group identifier specifying
                                ! location of subject group
  CHARACTER(LEN=*), INTENT(IN) :: group_name
                                ! Name of subject group
  INTEGER, INTENT(IN) :: index_field
                                ! Index/field which determines the order
                                !   H5_INDEX_UNKNOWN_F - Unknown index type
                                !   H5_INDEX_NAME_F - Index on names
                                !   H5_INDEX_CRT_ORDER_F - Index on creation order
                                !   H5_INDEX_N_F - Number of indices defined
  INTEGER, INTENT(IN) :: order
                                ! Order in which to iterate over index;
                                ! Possible values are:
                                !   H5_ITER_UNKNOWN_F - Unknown order
                                !   H5_ITER_INC_F - Increasing order
                                !   H5_ITER_DEC_F - Decreasing order
                                !   H5_ITER_NATIVE_F - No particular order,
                                !                   whatever is fastest
  INTEGER(HSIZE_T), INTENT(IN) :: n
                                ! Attribute's position in index
  LOGICAL, INTENT(OUT) :: f_corder_valid
                                ! Indicates whether the creation order data is
                                ! valid for this attribute
  INTEGER, INTENT(OUT) :: corder
                                ! Is a positive integer containing the creation
                                ! order of the attribute
  INTEGER, INTENT(OUT) :: cset
                                ! Indicates the character set used for the
                                ! attribute's name
  INTEGER(HSIZE_T), INTENT(OUT) :: data_size
                                ! Indicates the size, in the number of characters,
                                ! of the attribute
  INTEGER, INTENT(OUT) :: hdferr
                                ! Error code:
                                ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                ! Link access property list
END SUBROUTINE h5lget_info_by_idx_f

```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Lget\_name\_by\_idx

**Signature:**

```
ssize_t H5Lget_name_by_idx( hid_t loc_id, const char *group_name, H5_index_t
index_field, H5_iter_order_t order, hsize_t n, char *name, size_t size, hid_t lapl_id )
```

**Purpose:**

Retrieves name of the *n*th link in a group, according to the order within a specified field or index.

**Description:**

H5Lget\_name\_by\_idx retrieves the name of the *n*th link in a group, according to the specified order, order, within a specified field or index, index\_field.

If loc\_id specifies the group in which the link resides, group\_name can be a dot (.).

The size in bytes of name is specified in size. If size is unknown, it can be determined via an initial H5Lget\_name\_by\_idx call with name set to NULL; the function's return value will be the size of the name.

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier specifying location of subject group
<i>const char *</i> group_name	IN: Name of subject group
<i>H5_index_t</i> index_field	IN: Index or field which determines the order
<i>H5_iter_order_t</i> order	IN: Order within field or index
<i>hsize_t</i> n	IN: Link for which to retrieve information
<i>char *</i> name	OUT: Buffer in which link value is returned
<i>size_t</i> size	IN: Size in bytes of name
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns the size of the link name if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5lget\_name\_by\_idx\_f

```
SUBROUTINE h5lget_name_by_idx_f(loc_id, group_name, index_field, order, n, &
    name, hdferr, lapl_id, size)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id
                                ! File or group identifier specifying location of
                                ! subject group
    CHARACTER(LEN=*), INTENT(IN) :: group_name
                                ! Name of subject group
    INTEGER, INTENT(IN) :: index_field
                                ! Index or field which determines the order
                                ! H5_INDEX_UNKNOWN_F - Unknown index type
                                ! H5_INDEX_NAME_F - Index on names
                                ! H5_INDEX_CRT_ORDER_F - Index on creation order
                                ! H5_INDEX_N_F - Number of indices defined
    INTEGER, INTENT(IN) :: order
                                ! Order in which to iterate over index:
                                ! H5_ITER_UNKNOWN_F - Unknown order
                                ! H5_ITER_INC_F - Increasing order
                                ! H5_ITER_DEC_F - Decreasing order
                                ! H5_ITER_NATIVE_F - No particular order,
                                ! whatever is fastest
```

```

INTEGER(HSIZE_T), INTENT(IN) :: n
                        ! Attribute's position in index
CHARACTER(LEN=*), INTENT(OUT) :: name
                        ! Buffer in which link value is returned
INTEGER, INTENT(OUT) :: hdferr      ! Error code:
                        ! 0 on success and -1 on failure
INTEGER(SIZE_T), OPTIONAL, INTENT(OUT) :: size
                        ! Indicates the size, in the number of characters,
                        ! of the link, returns exact size
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                        ! Link access property list
END SUBROUTINE h5lget_name_by_idx_f

```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Lget\_val

**Signature:**

```
herr_t H5Lget_val(hid_t link_loc_id, const char *link_name, void *linkval_buff, size_t
size, hid_t lapl_id)
```

**Purpose:**

Returns the value of a symbolic link.

**Description:**

H5Lget\_val returns the link value of the link link\_name.

The parameter link\_loc\_id is a file or group identifier.

link\_name identifies a symbolic link and is defined relative to link\_loc\_id. Symbolic links include soft and external links and some user-defined links.

The link value is returned in the buffer linkval\_buff. For soft links, this is the path to which the link points, including the null terminator; for external and user-defined links, it is the link buffer.

size is the size of linkval\_buff and should be the size of the link value being returned. This size value can be determined through a call to H5Lget\_info; it is returned in the val\_size field of the H5L\_info\_t struct.

If size is smaller than the size of the returned value, then the string stored in linkval\_buff will be truncated to size bytes. For soft links, this means that the value will not be null terminated.

In the case of external links, the target file and object names are extracted from linkval\_buff by calling H5Lunpack\_elink\_val.

The link class of link\_name can be determined with a call to H5Lget\_info.

lapl\_id specifies the link access property list associated with the link link\_name. In the general case, when default link access properties are acceptable, this can be passed in as H5P\_DEFAULT. An example of a situation that requires a non-default link access property list is when the link is an external link; an external link may require that a link prefix be set in a link access property list (see H5Pset\_elink\_prefix).

This function should be used only after H5Lget\_info has been called to verify that link\_name is a symbolic link. This can be determined from the link\_type field of the H5L\_info\_t struct.

**Parameters:**

<i>hid_t</i> link_loc_id	IN: File or group identifier.
<i>const char</i> *link_name	IN: Link whose value is to be returned.
<i>void</i> *linkval_buff	OUT: The buffer to hold the returned link value.
<i>size_t</i> size	IN: Maximum number of characters of link value to be returned.
<i>hid_t</i> lapl_id	IN: List access property list identifier.

**Returns:**

Returns a non-negative value, with the link value in linkval\_buff, if successful. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Lget\_val\_by\_idx

**Signature:**

```
herr_t H5Lget_val_by_idx( hid_t loc_id, const char *group_name, H5_index_t
index_type, H5_iter_order_t order, hsize_t n, void *link_val, size_t size, hid_t lapl_id )
```

**Purpose:**

Retrieves value of the *n*th link in a group, according to the order within an index.

**Description:**

H5Lget\_val\_by\_idx retrieves the value of the *n*th link in a group, according to the specified order, order, within an index, index.

◊ For hard links, the value is the address of the object pointed to.

◊ For soft links, the value is the path name of the object pointed to.

◊ For external links, this is a compound value containing file and path name information; to use this external link information, it must first be decoded with H5Lunpack\_elink\_val

◊ For user-defined links, this value will be described in the definition of the user-defined link type.

If loc\_id specifies the group in which the link resides, group\_name can be a dot (.).

The size in bytes of group\_name is specified in size. If size is unknown, it can be determined via an initial H5Lget\_val\_by\_idx call with size set to NULL; size will be returned with the actual size of group\_name.

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier specifying location of subject group
<i>const char</i> *group_name	IN: Name of subject group
<i>H5_index_t</i> index_type	IN: Type of index; valid values include: NAME          Indexed by name CORDER        Indexed by creation order
<i>H5_iter_order_t</i> order	IN: Order within field or index; valid values include: H5_ITER_INC    Iterate in increasing order H5_ITER_DEC    Iterate in decreasing order H5_ITER_NATIVE Iterate in fastest order
<i>hsize_t</i> n	IN: Link for which to retrieve information
<i>void</i> *link_val	OUT: Pointer to buffer in which link value is returned
<i>size_t</i> size	IN: Size in bytes of group_name
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.



**Name:** H5Lis\_registered

**Signature:**

*htri\_t* H5Lis\_registered( *H5L\_type\_t* link\_cls\_id )

**Purpose:**

Determines whether a class of user-defined links is registered.

**Description:**

H5Lis\_registered tests whether a user-defined link class is currently registered, either by the HDF5 Library or by the user through the use of H5Lregister.

A link class must be registered to create new links of that type or to traverse existing links of that type.

**Parameters:**

*H5L\_type\_t* link\_cls\_id      IN: User-defined link class identifier

**Returns:**

Returns a positive value if the link class has been registered and zero if it is unregistered. Otherwise returns a negative value; this may mean that the identifier is not a valid user-defined class identifier.

**Fortran90 Interface:** H5Lis\_registered\_f

```
SUBROUTINE H5Lis_registered_f(link_cls_id, registered, hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(IN) :: link_cls_id ! User-defined link class identifier
  LOGICAL, INTENT(OUT) :: registered ! .TRUE. - if the link class is registered
  ! .FALSE. - if it is unregistered
  INTEGER, INTENT(OUT) :: hdferr ! Error code:
  ! 0 on success and -1 on failure
END SUBROUTINE H5Lis_registered_f
```

**History:**

**Release    C**

1.8.0      Function introduced in this release.

**Name:** H5Literate

**Signature:**

```
herr_t H5Literate( hid_t group_id, H5_index_t index_type, H5_iter_order_t order, hsize_t
*idx, H5L_iterate_t op, void *op_data )
```

**Purpose:**

Iterates through links in a group.

**Description:**

H5Literate iterates through the links in a group, specified by `group_id`, in the order of the specified index, `index_type`, using a user-defined callback routine `op`. H5Literate does not recursively follow links into subgroups of the specified group.

Three parameters are used to manage progress of the iteration: `index_type`, `order`, and `idx`.

`index_type` specifies the index to be used. If the links have not been indexed by the index type, they will first be sorted by that index then the iteration will begin; if the links have been so indexed, the sorting step will be unnecessary, so the iteration may begin more quickly. Valid values include the following:

H5_INDEX_NAME	Alpha-numeric index on name
H5_INDEX_CRT_ORDER	Index on creation order

`order` specifies the order in which objects are to be inspected along the index specified in `index_type`. Valid values include the following:

H5_ITER_INC	Increasing order
H5_ITER_DEC	Decreasing order
H5_ITER_NATIVE	Fastest available order

`idx` allows an interrupted iteration to be resumed; it is passed in by the application with a starting point and returned by the library with the point at which the iteration stopped.

The `op` callback function, the related *H5L\_info\_t* struct, and the effect of the callback function's return value on the application are described in *H5Lvisit*.

`op_data` is a user-defined pointer to the data required to process links in the course of the iteration. This pointer is passed back to each step of the iteration in the `op` callback function's `op_data` parameter.

As mentioned above, H5Literate is not recursive. In particular, if a member of `group_id` is found to be a group, call it `subgroup_a`, H5Literate does not examine the members of `subgroup_a`. When recursive iteration is required, the application can do either of the following:

- ◊ Use one of the following recursive routines instead of H5Literate:

```
H5Lvisit
H5Lvisit_by_name
H5Ovisit
H5Ovisit_by_name
```

- ◊ Handle the recursion manually, explicitly calling H5Literate on discovered subgroups.

H5Literate is the same as H5Giterate, except that H5Giterate always proceeds in alphanumeric order.

**Parameters:**

<i>hid_t</i> group_id	IN: Identifier specifying subject group
<i>H5_index_t</i> index_type	IN: Type of index which determines the order
<i>H5_iter_order_t</i> order	IN: Order within index
<i>hsize_t</i> *idx	IN: Iteration position at which to start OUT: Position at which an interrupted iteration may be restarted
<i>H5L_iterate_t</i> op	IN: Callback function passing data regarding the link to the calling application
<i>void</i> *op_data	IN: User-defined pointer to data required by the application for its processing of the link

**Returns:**

On success, returns the return value of the first operator that returns a positive value, or zero if all members were processed with no operator returning non-zero.

On failure, returns a negative value if something goes wrong within the library, or the first negative value returned by an operator.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Literate\_by\_name

**Signature:**

```
herr_t H5Literate_by_name(hid_t loc_id, const char *group_name, H5_index_t
index_type, H5_iter_order_t order, hsize_t *idx, H5L_iterate_t op, void *op_data, hid_t
*lapl_id)
```

**Purpose:**

Iterates through links in a group.

**Description:**

H5Literate\_by\_name iterates through the links in a group, specified by `loc_id` and `group_name`, in the order of the specified index, `index_type`, using a user-defined callback routine `op`. H5Literate\_by\_name does not recursively follow links into subgroups of the specified group.

`index_type` specifies the index to be used. If the links have not been indexed by the index type, they will first be sorted by that index then the iteration will begin; if the links have been so indexed, the sorting step will be unnecessary, so the iteration may begin more quickly. Valid values include the following:

H5_INDEX_NAME	Alpha-numeric index on name
H5_INDEX_CRT_ORDER	Index on creation order

`order` specifies the order in which objects are to be inspected along the index specified in `index_type`. Valid values include the following:

H5_ITER_INC	Increasing order
H5_ITER_DEC	Decreasing order
H5_ITER_NATIVE	Fastest available order

`idx` allows an interrupted iteration to be resumed; it is passed in by the application with a starting point and returned by the library with the point at which the iteration stopped.

H5Literate\_by\_name is not recursive. In particular, if a member of `group_name` is found to be a group, call it `subgroup_a`, H5Literate\_by\_name does not examine the members of `subgroup_a`. When recursive iteration is required, the application must handle the recursion, explicitly calling H5Literate\_by\_name on discovered subgroups.

H5Literate\_by\_name is the same as H5Giterate, except that H5Giterate always proceeds in alphanumeric order.

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier specifying location of subject group
<i>const char</i> *group_name	IN: Name of subject group
<i>H5_index_t</i> index_type	IN: Type of index which determines the order
<i>H5_iter_order_t</i> order	IN: Order within index
<i>hsize_t</i> *idx	IN: Iteration position at which to start OUT: Position at which an interrupted iteration may be restarted
<i>H5L_iterate_t</i> op	IN: Callback function passing data regarding the link to the calling application
<i>void</i> *op_data	IN: User-defined pointer to data required by the application for its processing of the link
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

On success, returns the return value of the first operator that returns a positive value, or zero if all members were processed with no operator returning non-zero.

On failure, returns a negative value if something goes wrong within the library, or the first negative value returned by an operator.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Lmove

**Signature:**

```
herr_t H5Lmove( hid_t src_loc_id, const char *src_name, hid_t dest_loc_id, const char
*dest_name, hid_t lcpl, hid_t lapl )
```

**Purpose:**

Renames a link within an HDF5 file.

**Description:**

H5Lmove renames a link within an HDF5 file. The original link, *src\_name*, is removed from the group graph and the new link, *dest\_name*, is inserted; this change is accomplished as an atomic operation.

*src\_loc\_id* and *src\_name* identify the existing link. *src\_loc\_id* is either a file or group identifier; *src\_name* is the path to the link and is interpreted relative to *src\_loc\_id*.

*dest\_loc\_id* and *dest\_name* identify the new link. *dest\_loc\_id* is either a file or group identifier; *dest\_name* is the path to the link and is interpreted relative to *dest\_loc\_id*.

*lcpl* and *lapl* are the link creation and link access property lists, respectively, associated with the new link, *dest\_name*.

Through these property lists, several properties are available to govern the behavior of H5Lmove. The property controlling creation of missing intermediate groups is set in the link creation property list with H5Pset\_create\_intermediate\_group; H5Lmove ignores any other properties in the link creation property list. Properties controlling character encoding, link traversals, and external link prefixes are set in the link access property list with H5Pset\_char\_encoding, H5Pset\_nlinks, and H5Pset\_elink\_prefix, respectively.

**Warning:**

Exercise care in moving links as it is possible to render data in a file inaccessible with H5Lmove. If the link being moved is on the only path leading to an HDF5 object, that object may become permanently inaccessible in the file.

**Parameters:**

<i>hid_t</i> src_loc_id	IN: Original file or group identifier.
<i>const char</i> *src_name	IN: Original link name.
<i>hid_t</i> dest_loc_id	IN: Destination file or group identifier.
<i>const char</i> *dest_name	IN: New link name.
<i>hid_t</i> lcpl_id	IN: Link creation property list identifier to be associated with the new link.
<i>hid_t</i> lapl_id	IN: Link access property list identifier to be associated with the new link.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5lmove\_f

```
SUBROUTINE h5lmove_f(src_loc_id, src_name, dest_loc_id, dest_name, hdferr, &
    lcpl_id, lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: src_loc_id
                                ! Original file or group identifier.
    CHARACTER(LEN=*), INTENT(IN) :: src_name
                                ! Original link name.
    INTEGER(HID_T), INTENT(IN) :: dest_loc_id
                                ! Destination file or group identifier.
```

```
CHARACTER(LEN=*), INTENT(IN) :: dest_name
                                ! new link name.
INTEGER(HID_T), INTENT(OUT) :: hdferr ! Error code:
                                ! 0 on success and -1 on failure
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lcpl_id
                                ! Link creation property list identifier
                                ! to be associated with the new link.
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                ! Link access property list identifier
                                ! to be associated with the new link.

END SUBROUTINE h5lmove_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Lregister

**Signature:**

```
herr_t H5Lregister( const H5L_class_t *link_class )
```

**Purpose:**

Registers user-defined link class or changes behavior of existing class.

**Description:**

H5Lregister registers a class of user-defined links, or changes the behavior of an existing class.

The struct `H5L_class_t` is defined in `H5Lpublic.h` as follows:

```
typedef struct H5L_class_t {
    int version;                /* Version number of this struct */
    H5L_type_t class_id;        /* Link class identifier */
    const char *comment;        /* Comment for debugging */
    H5L_create_func_t create_func; /* Callback during link creation */
    H5L_move_func_t move_func;    /* Callback after moving link */
    H5L_copy_func_t copy_func;    /* Callback after copying link */
    H5L_traverse_func_t trav_func; /* The main traversal function */
    H5L_delete_func_t del_func;    /* Callback for link deletion */
    H5L_query_func_t query_func;   /* Callback for queries */
} H5L_class_t;
```

The link class passed in will override any existing link class for the specified link class identifier `class_id`. The class definition must include at least a `H5L_class_t` version (which should be `H5L_LINK_CLASS_T_VERS`), a link class identifier, and a traversal function, `trav_func`.

Valid values of `class_id` include the following (defined in `H5Lpublic.h`:

<code>H5L_TYPE_HARD</code>	Hard link
<code>H5L_TYPE_SOFT</code>	Soft link
<code>H5L_TYPE_EXTERNAL</code>	External link

`class_id` must be a value between `H5L_LINK_UD_MIN` and `H5L_LINK_UD_MAX`, Note that as distributed with the HDF5 Library, the external link class is implemented as an example user-defined link class and `H5L_LINK_EXTERNAL` equals `H5L_LINK_UD_MIN`. Therefore, `class_id` should not equal `H5L_LINK_UD_MIN` unless you intend to overwrite or modify the behavior of external links. To summarize:

- `H5L_TYPE_ERROR` indicates that an error has occurred.
- `H5L_TYPE_MAX` is the maximum allowed value for a link type identifier.
- `H5L_TYPE_UD_MIN` equals `H5L_TYPE_EXTERNAL`.
- `H5L_TYPE_UD_MAX` equals `H5L_TYPE_MAX`.
- `H5L_TYPE_HARD` and `H5L_TYPE_SOFT` reside in the reserved space below `H5L_TYPE_UD_MIN`.

**Note:**

If you plan to distribute files with a new user-defined link class, please contact the Help Desk at The HDF Group to help prevent collisions between `class_id` values.



**Parameters:**

*const H5L\_class\_t* \*link\_class      IN: Struct describing user-defined link class

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Ldelete

**Signature:**

```
herr_t H5Ldelete(hid_t loc_id, const char *name, hid_t lapl_id)
```

**Purpose:**

Removes a link from a group.

**Description:**

H5Ldelete removes the link specified by name from the location loc\_id.

If the link being removed is a hard link, H5Ldelete also decrements the link count for the object to which name points. Unless there is a duplicate hard link in that group, this action removes the object to which name points from the group that previously contained it.

Object headers keep track of how many hard links refer to an object; when the hard link count, also referred to as the reference count, reaches zero, the object can be removed from the file. The file space associated will then be released, i.e., identified in memory as freespace. Objects which are open are not removed until all identifiers to the object are closed.

Note that space identified as freespace is available for re-use only as long as the file remains open; once a file has been closed, the HDF5 library loses track of freespace. See “Freespace Management” in “Performance Analysis and Issues” for further details.

**Warning:**

Exercise caution in the use of H5Ldelete; if the link being removed is on the only path leading to an HDF5 object, that object may become permanently inaccessible in the file.

**Parameters:**

<i>hid_t</i> loc_id	IN: Identifier of the file or group containing the object.
<i>const char</i> *name	IN: Name of the link to delete.
<i>hid_t</i> lapl_id	IN: Link access property list identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5ldelete\_f

```
SUBROUTINE h5ldelete_f(loc_id, name, hdferr, lapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id    ! Identifier of the file or group
                                           ! containing the object
  CHARACTER(LEN=*), INTENT(IN) :: name    ! Name of the link to delete
  INTEGER, INTENT(OUT) :: hdferr          ! Error code:
                                           ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                           ! Link access property list identifier
END SUBROUTINE h5ldelete_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Ldelete\_by\_idx

**Signature:**

```
herr_t H5Ldelete_by_idx( hid_t loc_id, const char *group_name, H5_index_t
index_field, H5_iter_order_t order, hsize_t n, hid_t lapl_id )
```

**Purpose:**

Removes the *n*th link in a group.

**Description:**

H5Ldelete\_by\_idx removes the *n*th link in a group according to the specified order, *order*, in the specified index, *index*.

If *loc\_id* specifies the group in which the link resides, *group\_name* can be a dot (.).

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier specifying location of subject group
<i>const char</i> *group_name	IN: Name of subject group
<i>H5_index_t</i> index_field	IN: Index or field which determines the order
<i>H5_iter_order_t</i> order	IN: Order within field or index
<i>hsize_t</i> n	IN: Link for which to retrieve information
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5ldelete\_by\_idx\_f

```
SUBROUTINE h5ldelete_by_idx_f(loc_id, group_name, index_field, order, n, &
    hdferr, lapl_id)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id
        ! Identifier for object to which attribute is attached.
    CHARACTER(LEN=*), INTENT(IN) :: group_name
        ! Name of object, relative to location,
        ! from which attribute is to be removed
    INTEGER, INTENT(IN) :: index_field
        ! Type of index; Possible values are:
        !     H5_INDEX_UNKNOWN_F - Unknown index type
        !     H5_INDEX_NAME_F    - Index on names
        !     H5_INDEX_CRT_ORDER_F - Index on creation order
        !     H5_INDEX_N_F       - Number of indices defined
    INTEGER, INTENT(IN) :: order
        ! Order in which to iterate over index;
        ! Possible values are:
        !     H5_ITER_UNKNOWN_F - Unknown order
        !     H5_ITER_INC_F     - Increasing order
        !     H5_ITER_DEC_F     - Decreasing order
        !     H5_ITER_NATIVE_F  - No particular order,
        !                       whatever is fastest
        !     H5_ITER_N_F      - Number of iteration orders
    INTEGER(HSIZE_T), INTENT(IN) :: n
        ! Offset within index
    INTEGER, INTENT(OUT) :: hdferr
        ! Error code:
        ! 0 on success and -1 on failure
    INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
        ! Link access property list
END SUBROUTINE h5ldelete_by_idx_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Lunpack\_elink\_val

**Signature:**

```
herr_t H5Lunpack_elink_val( char *ext_linkval, size_t link_size, unsigned *flags,
                           const char **filename, const char **obj_path )
```

**Purpose:**

Decodes external link information.

**Description:**

H5Lunpack\_elink\_val decodes the external link information returned by H5Lget\_val in the ext\_linkval buffer.

ext\_linkval should be the buffer set by H5Lget\_val and will consist of two NULL-terminated strings, the filename and object path, one after the other.

Given this buffer, H5Lunpack\_elink\_val creates pointers to the filename and object path within the buffer and returns them in filename and obj\_path, unless they are passed in as NULL.

H5Lunpack\_elink\_val requires that ext\_linkval contain a concatenated pair of null-terminated strings, so use of this function on a string that is not an external link udata buffer may result in a segmentation fault. This failure can be avoided by adhering to the following procedure:

1. Call H5Lget\_info to get the link type and the size of the link value.
2. Verify that the link is an external link, i.e., that its link type is H5L\_LINK\_EXTERNAL.
3. Call H5Lget\_val to get the link value.
4. Call H5Lunpack\_elink\_val to unpack that value.

**Parameters:**

<i>const char</i> *ext_linkval	IN: Buffer containing external link information
<i>size_t</i> link_size	IN: Size, in bytes, of the ext_linkval buffer
<i>unsigned</i> *flags	OUT: External link flags, packed as a bitmap (Reserved as a bitmap for flags; no flags are currently defined, so the only valid value is 0.)
<i>const char</i> **filename	OUT: Returned filename
<i>const char</i> **obj_path	OUT: Returned object path, relative to filename

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Lunregister

**Signature:**

*herr\_t* H5Lunregister( *H5L\_type\_t* link\_cls\_id )

**Purpose:**

Unregisters a class of user-defined links.

**Description:**

H5Lunregister unregisters a class of user-defined links, preventing them from being traversed, queried, moved, etc.

A link class can be re-registered using H5Lregister.

**Parameters:**

*H5L\_type\_t* link\_cls\_id      IN: User-defined link class identifier

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Lvisit

**Signature:**

```
herr_t H5Lvisit( hid_t group_id, H5_index_t index_type, H5_iter_order_t order,
                H5L_iterate_t op, void *op_data )
```

**Purpose:**

Recursively visits all links starting from a specified group.

**Description:**

H5Lvisit is a recursive iteration function to visit all links in and below a group in an HDF5 file, thus providing a mechanism for an application to perform a common set of operations across all of those links or a dynamically selected subset. For non-recursive iteration across the members of a group, see H5Literate.

The group serving as the root of the iteration is specified by its group identifier, `group_id`

Two parameters are used to establish the iteration: `index_type` and `order`.

`index_type` specifies the index to be used. If the links have not been indexed by the index type, they will first be sorted by that index then the iteration will begin; if the links have been so indexed, the sorting step will be unnecessary, so the iteration may begin more quickly. Valid values include the following:

H5_INDEX_NAME	Alpha-numeric index on name
H5_INDEX_CRT_ORDER	Index on creation order

Note that the index type passed in `index_type` is a *best effort* setting. If the application passes in a value indicating iteration in creation order and a group is encountered that was not tracked in creation order, that group will be iterated over in alpha-numeric order by name, or *name order*. (*Name order* is the native order used by the HDF5 Library and is always available.)

`order` specifies the order in which objects are to be inspected along the index specified in `index_type`. Valid values include the following:

H5_ITER_INC	Increasing order
H5_ITER_DEC	Decreasing order
H5_ITER_NATIVE	Fastest available order

The prototype of the callback function `op` is as follows (as defined in the source code file `H5Lpublic.h`):

```
herr_t ( *H5L_iterate_t )( hid_t g_id, const char *name, const H5L_info_t *info, void
                          *op_data )
```

The parameters of this callback function have the following values or meanings:

<code>g_id</code>	Group that serves as root of the iteration; same value as the H5Lvisit <code>group_id</code> parameter
<code>name</code>	Name of link, relative to <code>g_id</code> , being examined at current step of the iteration
<code>info</code>	<i>H5L_info_t</i> struct containing information regarding that link

`op_data` User-defined pointer to data required by the application in processing the link; a pass-through of the `op_data` pointer provided with the `H5Lvisit` function call

The `H5L_info_t` struct is defined (in `H5Lpublic.h`) as follows:

```
typedef struct {
    H5L_type_t      type;          /* Type of link                */
    hbool_t         corder_valid; /* Indicates whether creation  */
                                /* order is valid              */
    int64_t         corder;        /* Creation order              */
    H5T_cset_t      cset;          /* Character set of link name  */
    union {
        haddr_t     address;       /* Address hard link points to */
        size_t       val_size;     /* Size of soft link or        */
                                /* user-defined link value     */
    } u;
} H5L_info_t;
```

The possible return values from the callback function, and the effect of each, are as follows:

- ◊ Zero causes the visit iterator to continue, returning zero when all group members have been processed.
- ◊ A positive value causes the visit iterator to immediately return that positive value, indicating short-circuit success. The iterator can be restarted at the next group member.
- ◊ A negative value causes the visit iterator to immediately return that value, indicating failure. The iterator can be restarted at the next group member.

The `H5Lvisit` `op_data` parameter is a user-defined pointer to the data required to process links in the course of the iteration. This pointer is passed back to each step of the iteration in the `op` callback function's `op_data` parameter.

`H5Lvisit` and `H5Ovisit` are companion functions: one for examining and operating on links; the other for examining and operating on the objects that those links point to. Both functions ensure that by the time the function completes successfully, every link or object below the specified point in the file has been presented to the application for whatever processing the application requires.

#### Parameters:

<code>hid_t group_id</code>	IN: Identifier of the group at which the recursive iteration begins.
<code>H5_index_t index_type</code>	IN: Type of index; valid values include: <code>H5_INDEX_NAME</code> <code>H5_INDEX_CRT_ORDER</code>
<code>H5_iter_order_t order</code>	IN: Order in which index is traversed; valid values include: <code>H5_ITER_DEC</code> <code>H5_ITER_INC</code> <code>H5_ITER_NATIVE</code>
<code>H5L_iterate_t op</code>	IN: Callback function passing data regarding the link to the calling application
<code>void *op_data</code>	IN: User-defined pointer to data required by the application for its processing of the link

#### Returns:

On success, returns the return value of the first operator that returns a positive value, or zero if all members were processed with no operator returning non-zero.



On failure, returns a negative value if something goes wrong within the library, or the first negative value returned by an operator.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Lvisit\_by\_name

**Signature:**

```
herr_t H5Lvisit_by_name( hid_t loc_id, const char *group_name, H5_index_t index_type,
                        H5_iter_order_t order, H5L_iterate_t op, void *op_data, hid_t lapl_id )
```

**Purpose:**

Recursively visits all links starting from a specified group.

**Description:**

H5Lvisit\_by\_name is a recursive iteration function to visit all links in and below a group in an HDF5 file, thus providing a mechanism for an application to perform a common set of operations across all of those links or a dynamically selected subset. For non-recursive iteration across the members of a group, see H5Literate.

The group serving as the root of the iteration is specified by the `loc_id / group_name` parameter pair. `loc_id` specifies a file or group; `group_name` specifies either a group in the file (with an absolute name based in the file's root group) or a group relative to `loc_id`. If `loc_id` fully specifies the group that is to serve as the root of the iteration, `group_name` should be `'.'` (a dot). (Note that when `loc_id` fully specifies the the group that is to serve as the root of the iteration, the user may wish to consider using H5Lvisit instead of H5Lvisit\_by\_name.)

Two parameters are used to establish the iteration: `index_type` and `order`.

`index_type` specifies the index to be used. If the links have not been indexed by the index type, they will first be sorted by that index then the iteration will begin; if the links have been so indexed, the sorting step will be unnecessary, so the iteration may begin more quickly. Valid values include the following:

H5_INDEX_NAME	Alpha-numeric index on name
H5_INDEX_CRT_ORDER	Index on creation order

Note that the index type passed in `index_type` is a *best effort* setting. If the application passes in a value indicating iteration in creation order and a group is encountered that was not tracked in creation order, that group will be iterated over in alpha-numeric order by name, or *name order*. (*Name order* is the native order used by the HDF5 Library and is always available.)

`order` specifies the order in which objects are to be inspected along the index specified in `index_type`. Valid values include the following:

H5_ITER_INC	Increasing order
H5_ITER_DEC	Decreasing order
H5_ITER_NATIVE	Fastest available order

The `op` callback funtion, the related *H5L\_info\_t* struct, and the effect that the callback function's return value has on the application are described in H5Lvisit.

The `H5Lvisit_by_name` `op_data` parameter is a user-defined pointer to the data required to process links in the course of the iteration. This pointer is passed back to each step of the iteration in the callback function's `op_data` parameter.

`lapl_id` is a link access property list. In the general case, when default link access properties are acceptable, this can be passed in as `H5P_DEFAULT`. An example of a situation that requires a non-default link access property list is when the link is an external link; an external link may require that a link prefix be set in a link access property list (see `H5Pset_elink_prefix`).

`H5Lvisit_by_name` and `H5Ovisit_by_name` are companion functions: one for examining and operating on links; the other for examining and operating on the objects that those links point to. Both functions ensure that by the time the function completes successfully, every link or object below the specified point in the file has been presented to the application for whatever processing the application requires.

#### Parameters:

<i>hid_t</i> <code>loc_id</code>	IN: Identifier of a file or group
<i>const char *</i> <code>name</code>	IN: Name of the group, generally relative to <code>loc_id</code> , that will serve as root of the iteration
<i>H5_index_t</i> <code>index_type</code>	IN: Type of index; valid values include: <code>H5_INDEX_NAME</code> <code>H5_INDEX_CRT_ORDER</code>
<i>H5_iter_order_t</i> <code>order</code>	IN: Order in which index is traversed; valid values include: <code>H5_ITER_DEC</code> <code>H5_ITER_INC</code> <code>H5_ITER_NATIVE</code>
<i>H5L_iterate_t</i> <code>op</code>	IN: Callback function passing data regarding the link to the calling application
<i>void *</i> <code>op_data</code>	IN: User-defined pointer to data required by the application for its processing of the link
<i>hid_t</i> <code>lapl_id</code>	IN: Link access property list identifier

#### Returns:

On success, returns the return value of the first operator that returns a positive value, or zero if all members were processed with no operator returning non-zero.

On failure, returns a negative value if something goes wrong within the library, or the first negative value returned by an operator.

#### Fortran90 Interface:

None.

#### History:

Release	C
1.8.0	Function introduced in this release.



## H5O: Object Interface

### Object API Functions

The Object interface, H5O, functions manipulate objects in an HDF5 file. This interface is designed to be used in conjunction with the Links interface (H5L).

#### The C Interfaces:

- |                    |                          |                    |
|--------------------|--------------------------|--------------------|
| • H5Oopen          | • H5Oset_comment         | • H5Oopen_by_idx   |
| • H5Olink          | • H5Oset_comment_by_name | • H5Oopen_by_addr  |
| • H5Oclose         | • H5Oget_comment         |                    |
| • H5Ocopy          | • H5Oget_comment_by_name | • H5Oincr_refcount |
| • H5Ovisit         | • H5Oget_info            | • H5Odecr_refcount |
| • H5Ovisit_by_name | • H5Oget_info_by_name    |                    |
|                    | • H5Oget_info_by_idx     |                    |

#### *Alphabetical Listing*

- |                          |                       |                          |
|--------------------------|-----------------------|--------------------------|
| • H5Oclose               | • H5Oget_info_by_idx  | • H5Oopen_by_idx         |
| • H5Ocopy                | • H5Oget_info_by_name | • H5Oset_comment         |
| • H5Odecr_refcount       | • H5Oincr_refcount    | • H5Oset_comment_by_name |
| • H5Oget_comment         | • H5Olink             | • H5Ovisit               |
| • H5Oget_comment_by_name | • H5Oopen             | • H5Ovisit_by_name       |
| • H5Oget_info            | • H5Oopen_by_addr     |                          |

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- h5olink\_f
- h5oopen\_f



**Name:** H5Oclose

**Signature:**

*herr\_t* H5Oclose( *hid\_t* object\_id )

**Purpose:**

Closes an object in an HDF5 file.

**Description:**

H5Oclose closes the group, dataset, or named datatype specified by *object\_id*.

This function is the companion to H5Oopen, and has the same effect as calling H5Gclose, H5Dclose, or H5Tclose.

H5Oclose is *not* used to close a dataspace, attribute, property list, or file.

**Parameters:**

*hid\_t* object\_id      IN: Object identifier

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Ocopy

**Signature:**

```
herr_t H5Ocopy( hid_t src_loc_id, const char *src_name, hid_t dst_loc_id, const char
*dst_name, hid_t ocopypl_id, hid_t lcpl_id )
```

**Purpose:**

Copies an object in an HDF5 file.

**Description:**

H5Ocopy copies the group, dataset or named datatype specified by `src_name` from the file or group specified by `src_loc_id` to the destination location `dst_loc_id`.

The destination location, as specified in `dst_loc_id`, may be a group in the current file or a location in a different file. If `dst_loc_id` is a file identifier, the copy will be placed in that file's root group.

The new copy will be created with the name `dst_name`. `dst_name` must not pre-exist in the destination location; if `dst_name` already exists at the location `dst_loc_id`, H5Ocopy will fail.

The new copy of the object is created with the creation property lists specified by `ocpypl_id` and `lcpl_id`.

Several flags are available to govern the behavior of H5Ocopy. These flags are set in the creation property list `cplist_id` with H5Pset\_copy\_object and H5Pset\_create\_intermediate\_group. All of the available flags are described at H5Pset\_copy\_object.

**Parameters:**

<i>hid_t</i> src_loc_id	Object identifier indicating the location of the source object to be copied
<i>const char</i> *src_name	Name of the source object to be copied
<i>hid_t</i> dst_loc_id	Location identifier specifying the destination
<i>const char</i> *dst_name	Name to be assigned to the new copy
<i>hid_t</i> ocopypl_id	Object copy property list
<i>hid_t</i> lcpl_id	Link creation property list for the new hard link

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.



**Name:** H5Odecr\_refcount

**Signature:**

*herr\_t* H5Odecr\_refcount( *hid\_t* object\_id )

**Purpose:**

Decrements an object reference count.

**Description:**

H5Odecr\_refcount decrements the hard link reference count for an object. It should be used any time a user-defined link that references an object by address is deleted. In general, H5Oincr\_refcount will have been used previously, when the link was created.

An object's *reference count* is the number of hard links in the file that point to that object. See the "Programming Model" section of the "HDF5 Groups" chapter in the *HDF5 User's Guide* for a more complete discussion of reference counts.

If a user application needs to determine an object's reference count, an H5Oget\_info call is required; the reference count is returned in the `rc` field of the `H5O_info_t` struct.

**Warning:** This function must be used with care!  
Improper use can lead to inaccessible data, wasted space in the file, or *file corruption*.

**Parameters:**

*hid\_t* object\_id      IN: Object identifier

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Oget\_comment

**Signature:**

```
ssize_t H5Oget_comment( hid_t object_id, char *comment, size_t bufsize, )
```

**Purpose:**

Retrieves comment for specified object.

**Description:**

H5Oget\_comment retrieves the comment for the specified object in the buffer comment.

The target object is specified by an identifier, object\_id.

The size in bytes of the comment, including the NULL terminator, is specified in bufsize. If bufsize is unknown, a preliminary H5Oget\_comment call with the pointer comment set to NULL will return the size of the comment *without* the NULL terminator.

If bufsize is set to a smaller value than described above, only bufsize bytes of the comment, without a NULL terminator, are returned in comment.

If an object does not have a comment, the empty string is returned in comment.

**Parameters:**

hid_t object_id	IN: Identifier for the target object.
char *comment	OUT: The comment.
size_t bufsize	IN: Anticipated required size of the comment buffer.

**Returns:**

Upon success, returns the number of characters in the comment, not including the NULL terminator, or zero (0) if the object has no comment. The value returned may be larger than bufsize. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Oget\_comment\_by\_name

**Signature:**

```
ssize_t H5Oget_comment_by_name( hid_t loc_id, const char *name, char *comment, size_t
    bufsize, hid_t lapl_id )
```

**Purpose:**

Retrieves comment for specified object.

**Description:**

H5Oget\_comment\_by\_name retrieves the comment for an object in the buffer comment.

The target object is specified by `loc_id` and `name`. `loc_id` can specify any object in the file. `name` can be one of the following:

- The name of the object relative to `loc_id`
- An absolute name of the object, starting from /, the file's root group
- A dot (.), if `loc_id` fully specifies the object

The size in bytes of the comment, including the NULL terminator, is specified in `bufsize`. If `bufsize` is unknown, a preliminary H5Oget\_comment\_by\_name call with the pointer `comment` set to NULL will return the size of the comment *without* the NULL terminator.

If `bufsize` is set to a smaller value than described above, only `bufsize` bytes of the comment, without a NULL terminator, are returned in `comment`.

If an object does not have a comment, the empty string is returned in `comment`.

`lapl_id` contains a link access property list identifier. A link access property list can come into play when traversing links to access an object.

**Parameters:**

<code>hid_t loc_id</code>	IN: Identifier of a file, group, dataset, or named datatype.
<code>const char *name</code>	IN: Name of the object whose comment is to be retrieved, specified as a path relative to <code>loc_id</code> . name can be '.' (a dot) if <code>loc_id</code> fully specifies the object for which the associated comment is to be retrieved.
<code>char *comment</code>	OUT: The comment.
<code>size_t bufsize</code>	IN: Anticipated required size of the comment buffer.
<code>hid_t lapl_id</code>	IN: Link access property list identifier.

**Returns:**

Upon success, returns the number of characters in the comment, not including the NULL terminator, or zero (0) if the object has no comment. The value returned may be larger than `bufsize`. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Oget\_info

**Signature:**

```
herr_t H5Oget_info( hid_t object_id, H5O_info_t *object_info )
```

**Purpose:**

Retrieves the metadata for an object specified by an identifier.

**Description:**

H5Oget\_info specifies an object by its identifier, object\_id, and retrieves the metadata describing that object in object\_info, an *H5O\_info\_t* struct.

An *H5O\_info\_t* struct is defined (in *H5Opublic.h*) as follows :

```
typedef struct H5O_info_t {
    unsigned long    fileno;           /* File number that object is      */
                                       /* located in                       */
    haddr_t          addr;            /* Object address in file          */
    H5O_type_t       type;            /* Basic object type (group,       */
                                       /* dataset, etc.)                  */
    unsigned         rc;              /* Reference count of object       */
    time_t           atime;           /* Access time                     */
    time_t           mtime;           /* Modification time               */
    time_t           ctime;           /* Change time                     */
    time_t           btime;           /* Birth time                      */
    hsize_t          num_attrs;       /* # of attributes attached to object */
    struct {
        unsigned version;            /* Version number of header format in */
                                       /* file                                */
        unsigned nmsgs;              /* Number of object header messages   */
        unsigned nchunks;            /* Number of object header chunks     */
        unsigned flags;              /* Object header status flags         */
        struct {
            hsize_t total;            /* Total space for storing object     */
                                       /* header in file                     */
            hsize_t meta;            /* Space within header for object     */
                                       /* header metadata information        */
            hsize_t msg;             /* Space within header for actual     */
                                       /* message information                */
            hsize_t free;            /* Free space within object header    */
        } space;
        struct {
            uint64_t present;         /* Flags to indicate presence of     */
                                       /* message type in header            */
            uint64_t shared;         /* Flags to indicate message type is */
                                       /* shared in header                   */
        } msg;
    } hdr;
    /* Extra metadata storage for obj & attributes */
    struct {
        H5_ih_info_t  obj;           /* v1/v2 B-tree & local/fractal heap */
                                       /* for groups, B-tree for chunked    */
                                       /* datasets                          */
        H5_ih_info_t  attr;          /* v2 B-tree & heap for attributes   */
    } meta_size;
} H5O_info_t;
```

**Parameters:**

<i>hid_t</i> object_id	IN: Identifier for target object
<i>H5O_info_t</i> *object_info	OUT: Buffer in which to return object information

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Oget\_info\_by\_idx

**Signature:**

```
herr_t H5Oget_info_by_idx( hid_t loc_id, const char *group_name, H5_index_t
index_field, H5_iter_order_t order, hsize_t n, H5O_info_t *object_info, hid_t lapl_id )
```

**Purpose:**

Retrieves the metadata for an object, identifying the object by an index position.

**Description:**

H5Oget\_info\_by\_idx specifies a location, `loc_id`; a group name, `group_name`; an index by which objects in that group are tracked, `index_field`; the order by which the index is to be traversed, `order`; and an object's position `n` within that index and retrieves the metadata describing that object in the struct `object_info`.

`object_info`, in which the object information is returned, is a struct of type *H5O\_info\_t*. This struct type is described in the H5Oget\_info function entry.

If `loc_id` fully specifies the group in which the object resides, `group_name` can be a dot (`.`).

The link access property list, `lapl_id`, is not currently used; it should be passed in as NULL.

**Parameters:**

<i>hid_t</i> <code>loc_id</code>	IN: File or group identifier specifying location of group in which object is located
<i>const char *</i> <code>group_name</code>	IN: Name of group in which object is located
<i>H5_index_t</i> <code>index_field</code>	IN: Index or field that determines the order
<i>H5_iter_order_t</i> <code>order</code>	IN: Order within field or index
<i>hsize_t</i> <code>n</code>	IN: Object for which information is to be returned
<i>H5O_info_t *</i> <code>object_info</code>	OUT: Buffer in which to return object information
<i>hid_t</i> <code>lapl_id</code>	IN: Link access property list ( <i>Not currently used; pass as NULL.</i> )

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Oget\_info\_by\_name

**Signature:**

```
herr_t H5Oget_info_by_name( hid_t loc_id, const char *object_name, H5O_info_t
*object_info, hid_t lapl_id )
```

**Purpose:**

Retrieves the metadata for an object, identifying the object by location and relative name.

**Description:**

H5Oget\_info\_by\_name specifies an object's location and name, `loc_id` and `object_name`, respectively, and retrieves the metadata describing that object in `object_info`, an *H5O\_info\_t* struct.

The struct *H5O\_info\_t* is defined in `H5Opublic.h` and described in the `H5Oget_info` function entry.

The link access property list, `lapl_id`, is not currently used; it should be passed in as `H5P_DEFAULT`.

**Parameters:**

<i>hid_t</i> <code>loc_id</code>	IN: File or group identifier specifying location of group in which object is located
<i>const char</i> <code>*name</code>	IN: Name of group, relative to <code>loc_id</code>
<i>H5O_info_t</i> <code>*object_info</code>	OUT: Buffer in which to return object information
<i>hid_t</i> <code>lapl_id</code>	IN: Link access property list ( <i>Not currently used; pass as H5P_DEFAULT.</i> )

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Oincr\_refcount

**Signature:**

*herr\_t* H5Oincr\_refcount( *hid\_t* object\_id )

**Purpose:**

Increments an object reference count.

**Description:**

H5Oincr\_refcount increments the hard link reference count for an object. It should be used any time a user-defined link that references an object by address is added. When the link is deleted, H5Odecr\_refcount should be used.

An object's *reference count* is the number of hard links in the file that point to that object. See the "Programming Model" section of the "HDF5 Groups" chapter in the *HDF5 User's Guide* for a more complete discussion of reference counts.

If a user application needs to determine an object's reference count, an H5Oget\_info call is required; the reference count is returned in the `rc` field of the `H5O_info_t` struct.

**Warning:** This function must be used with care!  
Improper use can lead to inaccessible data, wasted space in the file, or *file corruption*.

**Parameters:**

*hid\_t* object\_id      IN: Object identifier

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.



**Name:** H5Olink

**Signature:**

```
herr_t H5Olink( hid_t object_id, hid_t new_loc_id, const char *new_link_name, hid_t
lcpl, hid_t lapl )
```

**Purpose:**

Creates a hard link to an object in an HDF5 file.

**Description:**

H5Olink creates a new hard link to an object in an HDF5 file.

*new\_loc\_id* and *new\_name* specify the location and name of the new link while *object\_id* identifies the object that the link points to.

H5Olink is designed for two purposes:

- ◆ To create the first hard link to an object that has just been created with one of the *H5\*create\_anon* functions or with *H5Tcommit\_anon*.
- ◆ To add additional structure to an existing file so that, for example, an object can be shared among multiple groups.

*lcpl* and *lapl* are the link creation and access property lists associated with the new link.

**Parameters:**

<i>hid_t</i> object_id	IN: Object to be linked.
<i>hid_t</i> new_loc_id	IN: File or group identifier specifying location at which object is to be linked.
<i>const char</i> *new_link_name	IN: Name of link to be created, relative to <i>new_loc_id</i> .
<i>hid_t</i> lcpl_id	IN: Link creation property list identifier.
<i>hid_t</i> lapl_id	IN: Link access property list identifier.

**Example:**

To create a new link to an object while simultaneously creating missing intermediate groups:

Suppose that an application must create the group C with the path /A/B01/C but may not know at run time whether the groups A and B01 exist. The following code ensures that those groups are created if they are missing:

```
hid_t lcpl_id = H5Pcreate(H5P_LINK_CREATE); /* Creates a link creation
                                           * property list (LCPL). */
int status = H5Pset_create_intermediate_group(lcpl_id, TRUE);
                                           /* Sets "create missing intermediate
                                           * groups" property in that LCPL. */
hid_t gid = H5Gcreate_anon(file_id, H5P_DEFAULT, H5P_DEFAULT);
                                           /* Creates a group without linking
                                           * it into the file structure. */
status = H5Olink(obj_id, file_id, "/A/B01/C", lcpl_id, H5P_DEFAULT);
                                           /* Links group into file structure.*/
```

Note that unless the object is intended to be temporary, the H5Olink call is mandatory if an object created with one of the *H5\*create\_anon* functions (or with *H5Tcommit\_anon*) is to be retained in the file; without an H5Olink call, the object will not be linked into the HDF5 file structure and will be deleted when the file is closed.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5olink\_f

```

SUBROUTINE h5olink_f(object_id, new_loc_id, new_link_name, hdferr, &
                    lcpl_id, lapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: object_id
                        ! Object to be linked
  INTEGER(HID_T), INTENT(IN) :: new_loc_id
                        ! File or group identifier specifying
                        ! location at which object is to be linked.
  CHARACTER(LEN=*), INTENT(IN) :: new_link_name
                        ! Name of link to be created,
                        ! relative to new_loc_id.
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                        ! Success: 0
                        ! Failure: -1
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lcpl_id
                        ! Link creation property list identifier.
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                        ! Link creation property list identifier.
END SUBROUTINE h5olink_f

```

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Oopen

**Signature:**

```
hid_t H5Oopen(hid_t loc_id, const char *name, hid_t lapl_id)
```

**Purpose:**

Opens an object in an HDF5 file by location identifier and path name.

**Description:**

H5Oopen opens a group, dataset, or named datatype specified by a location, `loc_id`, and a path name, `name`, in an HDF5 file.

This function opens the object in the same manner as H5Gopen, H5Topen, and H5Dopen. However, H5Oopen does not require the type of object to be known beforehand. This can be useful with user-defined links, for instance, when only a path may be known. H5Oopen cannot be used to open a dataspace, attribute, property list, or file.

Once an object of unknown type has been opened with H5Oopen, the type of that object can be determined by means of an H5Iget\_type call.

`loc_id` can be either a file or group identifier. `name` must be the path to that object relative to `loc_id`.

`lapl_id` is the link access property list associated with the link pointing to the object. If default link access properties are appropriate, this can be passed in as H5P\_DEFAULT.

When it is no longer needed, the opened object should be closed with H5Oclose, H5Gclose, H5Tclose, or H5Dclose.

**Parameters:**

<i>hid_t</i> loc_id	IN: File or group identifier
<i>const char</i> *name	IN: Path to the object, relative to <code>loc_id</code> .
<i>hid_t</i> lapl_id	IN: Access property list identifier for the link pointing to the object

**Returns:**

Returns an object identifier for the opened object if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5oopen\_f

```
SUBROUTINE h5oopen_f(loc_id, name, obj_id, hdferr, lapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name ! Path to the object,
                                         ! relative to loc_id
  INTEGER(HID_T), INTENT(OUT) :: obj_id ! Object identifier for opened object
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
                                         ! Success: 0
                                         ! Failure: -1
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lapl_id
                                         ! Attribute access property list
END SUBROUTINE h5oopen_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Oopen\_by\_addr

**Signature:**

```
hid_t H5Oopen_by_addr( hid_t loc_id, haddr_t addr )
```

**Purpose:**

Opens an object using its address within an HDF5 file.

**Description:**

H5Oopen\_by\_addr opens a group, dataset, or named datatype using its address within an HDF5 file, addr. The resulting opened object is identical to an object opened with H5Oopen and should be closed with H5Oclose or an object-type-specific closing function (such as H5Gclose) when no longer needed.

loc\_id can be either the file identifier or a group identifier in the file. In either case, the HDF5 Library uses the identifier only to identify the file.

The object's address within the file, addr, is the byte offset of the first byte of the object header from the beginning of the HDF5 file space, i.e., from the beginning of the super block (see the "HDF5 Storage Model" section of the "The HDF5 Data Model and File Structure" chapter of the *HDF5 User's Guide*).

addr can be obtained via either of two function calls. H5Gget\_objinfo returns the object's address in the objno field of the H5G\_stat\_t struct; H5Lget\_linkinfo returns the address in the address field of the H5L\_linkinfo\_t struct.

**Warning:** This function must be used with care!

Improper use can lead to inaccessible data, wasted space in the file, or *file corruption*.

This function is dangerous if called on an invalid address. The risk can be safely overcome by retrieving the object address with H5Gget\_objinfo or H5Lget\_linkinfo immediately before calling H5Oopen\_by\_addr. The immediacy of the operation can be important; if time has elapsed and the object has been deleted from the file, the address will be invalid and file corruption can result.

The address of the HDF5 file on a physical device has no effect on H5Oopen\_by\_addr, nor does the use of any file driver. As stated above, the object address is its offset within the HDF5 file; HDF5's file drivers will transparently map this to an address on a storage device.

**Parameters:**

hid\_t loc\_id      IN: File or group identifier

haddr\_t addr      IN: Object's address in the file

**Returns:**

Returns an object identifier for the opened object if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Oopen\_by\_idx

**Signature:**

```
hid_t H5Oopen_by_idx( hid_t loc_id, const char *group_name, H5_index_t index_type,
H5_iter_order_t order, hsize_t n, hid_t lapl_id )
```

**Purpose:**

Open the *n*th object in a group.

**Description:**

H5Oopen\_by\_idx opens the *n*th object in the group specified by *loc\_id* and *group\_name*.

*loc\_id* specifies a file or group. *group\_name* specifies the group relative to *loc\_id* in which the object can be found. If *loc\_id* fully specifies the group in which the object resides, *group\_name* can be a dot (.).

The specific object to be opened within the group is specified by *index\_type*, *order*, and *n* as follows:

- ◊ *index\_type* specifies the type of index by which objects are ordered. Valid index types include H5\_INDEX\_NAME, indexed by name, and H5\_INDEX\_CRT\_ORDER, indexed by creation order.
- ◊ *order* specifies the order in which the links are to be referenced for the purposes of this function. Valid orders include H5\_ITER\_INC for increasing order, H5\_ITER\_DEC for decreasing order, and H5\_ITER\_NATIVE. Rather than implying a particular order, H5\_ITER\_NATIVE instructs the HDF5 Library to iterate through the objects in the fastest available order, i.e., in a natural order.
- ◊ *n* specifies the position of the object within the index. Note that this count is zero-based; 0 (zero) indicates that the function will return the value of the first object; if *n* is 5, the function will return the value of the sixth object; etc.

If *lapl\_id* specifies the link access property list to be used in accessing the object.

**Parameters:**

<i>hid_t</i> loc_id	IN: A file or group identifier.
<i>const char</i> *group_name	IN: Name of group, relative to <i>loc_id</i> , in which object is located
<i>H5_index_t</i> index_type	IN: Type of index by which objects are ordered
<i>H5_iter_order_t</i> order	IN: Order of iteration within index
<i>hsize_t</i> n	IN: Object to open
<i>hid_t</i> lapl_id	IN: Link access property list

**Returns:**

Returns an object identifier for the opened object if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Oset\_comment

**Signature:**

*herr\_t* H5Oset\_comment( *hid\_t* object\_id, *const char* \*comment )

**Purpose:**

Sets comment for specified object.

**Description:**

H5Oset\_comment sets the comment for the specified object to the contents of comment. Any previously existing comment is overwritten.

The target object is specified by an identifier, object\_id.

If comment is the empty string or a null pointer, any existing comment message is removed from the object.

Comments should be relatively short, null-terminated, ASCII strings.

Comments can be attached to any object that has an object header, e.g., datasets, groups, and named datatypes, but not symbolic links.

**Parameters:**

*hid\_t* object\_id                      IN: Identifier of the target object

*const char* \*comment              IN: The new comment.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Oset\_comment\_by\_name

**Signature:**

```
herr_t H5Oset_comment_by_name(hid_t loc_id, const char *name, const char *comment, hid_t
lapl_id)
```

**Purpose:**

Sets comment for specified object.

**Description:**

H5Oset\_comment\_by\_name sets the comment for the specified object to the contents of comment. Any previously existing comment is overwritten.

The target object is specified by loc\_id and name. loc\_id can specify any object in the file. name can be one of the following:

- The name of the object relative to loc\_id
- An absolute name of the object, starting from /, the file's root group
- A dot (.), if loc\_id fully specifies the object

If comment is the empty string or a null pointer, any existing comment message is removed from the object.

Comments should be relatively short, null-terminated, ASCII strings.

Comments can be attached to any object that has an object header, e.g., datasets, groups, and named datatypes, but not symbolic links.

lapl\_id contains a link access property list identifier. A link access property list can come into play when traversing links to access an object.

**Parameters:**

<i>hid_t</i> loc_id	IN: Identifier of a file, group, dataset, or named datatype.
<i>const char</i> *name	IN: Name of the object whose comment is to be set or reset, specified as a path relative to loc_id. name can be '.' (a dot) if loc_id fully specifies the object for which the comment is to be set.
<i>const char</i> *comment	IN: The new comment.
<i>hid_t</i> lapl_id	IN: Link access property list identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Ovisit

**Signature:**

```
herr_t H5Ovisit(hid_t object_id, H5_index_t index_type, H5_iter_order_t order,
               H5O_iterate_t op, void *op_data)
```

**Purpose:**

Recursively visits all objects accessible from a specified object.

**Description:**

H5Ovisit is a recursive iteration function to visit the object `object_id` and, if `object_id` is a group, all objects in and below it in an HDF5 file, thus providing a mechanism for an application to perform a common set of operations across all of those objects or a dynamically selected subset. For non-recursive iteration across the members of a group, see `H5Literate`.

If `object_id` is a group identifier, that group serves as the root of a recursive iteration. If `object_id` is a file identifier, that file's root group serves as the root of the recursive iteration. If `object_id` is any other type of object, such as a dataset or named datatype, there is no iteration.

Two parameters are used to establish the iteration: `index_type` and `order`.

`index_type` specifies the index to be used. If the links in a group have not been indexed by the index type, they will first be sorted by that index then the iteration will begin; if the links have been so indexed, the sorting step will be unnecessary, so the iteration may begin more quickly. Valid values include the following:

H5_INDEX_NAME	Alpha-numeric index on name
H5_INDEX_CRT_ORDER	Index on creation order

Note that the index type passed in `index_type` is a *best effort* setting. If the application passes in a value indicating iteration in creation order and a group is encountered that was not tracked in creation order, that group will be iterated over in alpha-numeric order by name, or *name order*. (*Name order* is the native order used by the HDF5 Library and is always available.)

`order` specifies the order in which objects are to be inspected along the index specified in `index_type`. Valid values include the following:

H5_ITER_INC	Increasing order
H5_ITER_DEC	Decreasing order
H5_ITER_NATIVE	Fastest available order

The prototype of the callback function `op` is as follows (as defined in the source code file `H5Opublic.h`):

```
herr_t (*H5O_iterate_t)(hid_t o_id, const char *name, const H5O_info_t *object_info,
                       void *op_data)
```

The parameters of this callback function have the following values or meanings:

<code>o_id</code>	Object that serves as root of the iteration; same value as the <code>H5Ovisit</code> <code>object_id</code> parameter
<code>name</code>	



	Name of object, relative to <code>o_id</code> , being examined at current step of the iteration
<code>object_info</code>	<i>H5O_info_t</i> struct containing information regarding that object
<code>op_data</code>	User-defined pointer to data required by the application in processing the object; a pass-through of the <code>op_data</code> pointer provided with the <code>H5Ovisit_by_name</code> function call

The *H5O\_info\_t* struct is defined in `H5Opublic.h` and described in the `H5Oget_info` function entry.

The return values from an operator are:

- ◊ Zero causes the visit iterator to continue, returning zero when all group members have been processed.
- ◊ A positive value causes the visit iterator to immediately return that positive value, indicating short-circuit success. The iterator can be restarted at the next group member.
- ◊ A negative value causes the visit iterator to immediately return that value, indicating failure. The iterator can be restarted at the next group member.

The `H5Ovisit op_data` parameter is a user-defined pointer to the data required to process objects in the course of the iteration. This pointer is passed back to each step of the iteration in the callback function's `op_data` parameter.

`H5Lvisit` and `H5Ovisit` are companion functions: one for examining and operating on links; the other for examining and operating on the objects that those links point to. Both functions ensure that by the time the function completes successfully, every link or object below the specified point in the file has been presented to the application for whatever processing the application requires.

#### Parameters:

<i>hid_t</i> <code>object_id</code>	IN: Identifier of the object at which the recursive iteration begins.
<i>H5_index_t</i> <code>index_type</code>	IN: Type of index; valid values include: H5_INDEX_NAME H5_INDEX_CRT_ORDER
<i>H5_iter_order_t</i> <code>order</code>	IN: Order in which index is traversed; valid values include: H5_ITER_DEC H5_ITER_INC H5_ITER_NATIVE
<i>H5O_iterate_t</i> <code>op</code>	IN: Callback function passing data regarding the object to the calling application
<i>void *</i> <code>op_data</code>	IN: User-defined pointer to data required by the application for its processing of the object

#### Returns:

On success, returns the return value of the first operator that returns a positive value, or zero if all members were processed with no operator returning non-zero.

On failure, returns a negative value if something goes wrong within the library, or the first negative value returned by an operator.

#### Fortran90 Interface:

None.

#### History:

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Ovisit\_by\_name

**Signature:**

```
herr_t H5Ovisit_by_name( hid_t loc_id, const char *object_name, H5_index_t
index_type, H5_iter_order_t order, H5O_iterate_t op, void *op_data, hid_t lapl_id )
```

**Purpose:**

Recursively visits all objects starting from a specified object.

**Description:**

H5Ovisit\_by\_name is a recursive iteration function to visit the object specified by the `loc_id / object_name` parameter pair and, if that object is a group, all objects in and below it in an HDF5 file, thus providing a mechanism for an application to perform a common set of operations across all of those objects or a dynamically selected subset. For non-recursive iteration across the members of a group, see H5Literate.

The object serving as the root of the iteration is specified by the `loc_id / object_name` parameter pair. `loc_id` specifies a file or an object in a file; `object_name` specifies either an object in the file (with an absolute name based in the file's root group) or an object name relative to `loc_id`. If `loc_id` fully specifies the object that is to serve as the root of the iteration, `object_name` should be `'.'` (a dot). (Note that when `loc_id` fully specifies the the object that is to serve as the root of the iteration, the user may wish to consider using H5Ovisit instead of H5Ovisit\_by\_name.)

Two parameters are used to establish the iteration: `index_type` and `order`.

`index_type` specifies the index to be used. If the links in a group have not been indexed by the index type, they will first be sorted by that index then the iteration will begin; if the links have been so indexed, the sorting step will be unnecessary, so the iteration may begin more quickly. Valid values include the following:

H5_INDEX_NAME	Alpha-numeric index on name
H5_INDEX_CRT_ORDER	Index on creation order

Note that the index type passed in `index_type` is a *best effort* setting. If the application passes in a value indicating iteration in creation order and a group is encountered that was not tracked in creation order, that group will be iterated over in alpha-numeric order by name, or *name order*. (*Name order* is the native order used by the HDF5 Library and is always available.)

`order` specifies the order in which objects are to be inspected along the index specified in `index_type`. Valid values include the following:

H5_ITER_INC	Increasing order
H5_ITER_DEC	Decreasing order
H5_ITER_NATIVE	Fastest available order

The `op` callback funtion and the effect of the callback function's return value on the application are described in H5Ovisit.

The *H5O\_info\_t* struct is defined in `H5Opublic.h` and described in the `H5Oget_info` function entry.

The `H5Ovisit_by_name` `op_data` parameter is a user-defined pointer to the data required to process objects in the course of the iteration. This pointer is passed back to each step of the iteration in the callback function's `op_data` parameter.

`lapl_id` is a link access property list. In the general case, when default link access properties are acceptable, this can be passed in as `H5P_DEFAULT`. An example of a situation that requires a non-default link access property list is when the link is an external link; an external link may require that a link prefix be set in a link access property list (see `H5Pset_elink_prefix`).

`H5Lvisit_by_name` and `H5Ovisit_by_name` are companion functions: one for examining and operating on links; the other for examining and operating on the objects that those links point to. Both functions ensure that by the time the function completes successfully, every link or object below the specified point in the file has been presented to the application for whatever processing the application requires.

#### Parameters:

<i>hid_t</i> <code>loc_id</code>	IN: Identifier of a file or group
<i>const char *</i> <code>object_name</code>	IN: Name of the object, generally relative to <code>loc_id</code> , that will serve as root of the iteration
<i>H5_index_t</i> <code>index_type</code>	IN: Type of index; valid values include: <code>H5_INDEX_NAME</code> <code>H5_INDEX_CRT_ORDER</code>
<i>H5_iter_order_t</i> <code>order</code>	IN: Order in which index is traversed; valid values include: <code>H5_ITER_DEC</code> <code>H5_ITER_INC</code> <code>H5_ITER_NATIVE</code>
<i>H5O_iterate_t</i> <code>op</code>	IN: Callback function passing data regarding the object to the calling application
<i>void *</i> <code>op_data</code>	IN: User-defined pointer to data required by the application for its processing of the object
<i>hid_t</i> <code>lapl_id</code>	IN: Link access property list identifier

#### Returns:

On success, returns the return value of the first operator that returns a positive value, or zero if all members were processed with no operator returning non-zero.

On failure, returns a negative value if something goes wrong within the library, or the first negative value returned by an operator.

#### Fortran90 Interface:

None.

#### History:

Release	C
1.8.0	Function introduced in this release.



# H5P: Property List Interface

## Property List API Functions

These functions manipulate property list objects to allow objects which require many different parameters to be easily manipulated.

In the following lists, *italic type* indicates a configurable macro.

i

### The C Interfaces:

#### *General Functions*

- H5Pcreate
- H5Pget\_class
- H5Pcopy
- H5Pclose

#### *Generic Properties*

- H5Pcreate\_class
- *H5Pregister*
- H5Pregister1 \*
- H5Pregister2
- *H5Pinsert*
- H5Pinsert1 \*
- H5Pinsert2
- H5Pset
- H5Pexist
- H5Pget\_size
- H5Pget\_nprops
- H5Pget\_class\_name
- H5Pget\_class\_parent
- H5Pisa\_class
- H5Pget
- H5Pequal
- H5Piterate
- H5Pcopy\_prop
- H5Premove
- H5Punregister
- H5Pclose\_class

#### *File Access Properties*

- H5Pset\_driver
- H5Pget\_driver\_info
- H5Pset\_fcclose\_degree
- H5Pget\_fcclose\_degree
- H5Pset\_fapl\_core
- H5Pget\_fapl\_core
- H5Pset\_fapl\_direct
- H5Pget\_fapl\_direct
- H5Pset\_fapl\_family
- H5Pget\_fapl\_family
- H5Pset\_family\_offset
- H5Pget\_family\_offset
- H5Pset\_fapl\_log
- H5Pset\_fapl\_mpio ||
- H5Pget\_fapl\_mpio ||
- H5Pset\_fapl\_mpio\_six ||
- H5Pget\_fapl\_mpio\_six ||
- H5Pset\_fapl\_multi
- H5Pget\_fapl\_multi
- H5Pset\_multi\_type
- H5Pget\_multi\_type
- H5Pset\_fapl\_split
- H5Pset\_fapl\_sec2
- H5Pset\_fapl\_stdio
- H5Pset\_fapl\_windows
- H5set\_driver
- H5Pget\_driver
- H5Pget\_driver\_info
- H5Pset\_meta\_block\_size
- H5Pget\_meta\_block\_size
- H5Pset\_sieve\_buf\_size
- H5Pget\_sieve\_buf\_size
- H5Pset\_alignment
- H5Pget\_alignment
- H5Pset\_cache
- H5Pget\_cache

#### *File Access Properties (cont.)*

- H5Pget\_mdc\_config
- H5Pset\_mdc\_config
- H5Pset\_gc\_references
- H5Pget\_gc\_references
- H5Pset\_small\_data\_block\_size
- H5Pget\_small\_data\_block\_size
- H5Pset\_libver\_bounds
- H5Pget\_libver\_bounds

#### *File Creation Properties*

- H5Pget\_version
- H5Pset\_userblock
- H5Pget\_userblock
- H5Pset\_sizes
- H5Pget\_sizes
- H5Pset\_sym\_k
- H5Pget\_sym\_k
- H5Pset\_istore\_k
- H5Pget\_istore\_k
- H5Pset\_shared\_mesg\_nindexes
- H5Pget\_shared\_mesg\_nindexes
- H5Pset\_shared\_mesg\_index
- H5Pget\_shared\_mesg\_index
- H5Pset\_shared\_mesg\_phase\_change
- H5Pget\_shared\_mesg\_phase\_change

|| *Indicates functions available only in the parallel HDF5 library.*

\* *Use of these functions is deprecated in Release 1.8.0.*

*Dataset Creation Properties*

- H5Pset\_layout
- H5Pget\_layout
- H5Pset\_chunk
- H5Pget\_chunk
- H5Pset\_chunk\_cache
- H5Pget\_chunk\_cache
- H5Pset\_deflate
- H5Pset\_fill\_value
- H5Pget\_fill\_value
- H5Pfill\_value\_defined
- H5Pset\_fill\_time
- H5Pget\_fill\_time
- H5Pset\_alloc\_time
- H5Pget\_alloc\_time
- H5Pset\_filter
- H5Pall\_filters\_avail
- H5Pget\_nfilters
- *H5Pget\_filter*
- H5Pget\_filter1 \*
- H5Pget\_filter2
- *H5Pget\_filter\_by\_id*
- H5Pget\_filter\_by\_id1 \*
- H5Pget\_filter\_by\_id2
- H5Pmodify\_filter
- H5Premove\_filter
- H5Pset\_fletcher32
- H5Pset\_shuffle
- H5Pset\_szip
- H5Pset\_external
- H5Pget\_external\_count
- H5Pget\_external

*Group Creation Properties*

- H5Pset\_create\_intermediate\_group
- H5Pget\_create\_intermediate\_group
- H5Pset\_link\_creation\_order
- H5Pget\_link\_creation\_order
- H5Pset\_est\_link\_info
- H5Pget\_est\_link\_info
- H5Pset\_local\_heap\_size\_hint
- H5Pget\_local\_heap\_size\_hint
- H5Pset\_link\_phase\_change
- H5Pget\_link\_phase\_change

*Dataset Access, Memory, and Transfer Properties*

- H5Pset\_buffer
- H5Pget\_buffer
- H5Pset\_preserve \*
- H5Pget\_preserve \*
- H5Pset\_edc\_check
- H5Pget\_edc\_check
- H5Pset\_data\_transform
- H5Pget\_data\_transform
- H5Pset\_filter\_callback
- H5Pset\_hyper\_vector\_size
- H5Pget\_hyper\_vector\_size
- H5Pset\_btree\_ratios
- H5Pget\_btree\_ratios
- H5Pset\_vlen\_mem\_manager
- H5Pget\_vlen\_mem\_manager
- H5Pset\_dxpl\_mpio ||
- H5Pset\_dxpl\_mpio\_chunk\_opt ||
- H5Pset\_dxpl\_mpio\_chunk\_opt\_num ||
- H5Pset\_dxpl\_mpio\_chunk\_opt\_ratio ||
- H5Pset\_dxpl\_mpio\_collective\_opt ||
- H5Pget\_dxpl\_mpio ||
- H5Pset\_dxpl\_multi
- H5Pget\_dxpl\_multi

*Object Copy and Object Creation Properties*

- H5Pset\_create\_intermediate\_group
- H5Pget\_create\_intermediate\_group
- H5Pset\_copy\_object
- H5Pget\_copy\_object
- H5Pset\_attr\_phase\_change
- H5Pget\_attr\_phase\_change
- H5Pset\_attr\_creation\_order
- H5Pget\_attr\_creation\_order
- H5Pset\_obj\_track\_times
- H5Pget\_obj\_track\_times

*Link Access Properties*

- H5Pset\_nlinks
- H5Pget\_nlinks
- H5Pset\_elink\_cb
- H5Pget\_elink\_cb
- H5Pset\_elink\_prefix
- H5Pget\_elink\_prefix
- H5Pset\_elink\_fapl
- H5Pget\_elink\_fapl
- H5Pset\_elink\_acc\_flags
- H5Pget\_elink\_acc\_flags

*String Properties*

- H5Pset\_char\_encoding
- H5Pget\_char\_encoding

|| *Indicates functions available only in the parallel HDF5*

\* *Use of these functions is deprecated in Release 1.8.0.*

- H5Pall\_filters\_avail
- H5Pclose
- H5Pclose\_class
- H5Pcopy
- H5Pcopy\_prop
- H5Pcreate
- H5Pcreate\_class
- H5Pequal
- H5Pexist
- H5Pfill\_value\_defined
- H5Pget
- H5Pget\_alignment
- H5Pget\_alloc\_time
- H5Pget\_attr\_creation\_order
- H5Pget\_attr\_phase\_change
- H5Pget\_btree\_ratios
- H5Pget\_buffer
- H5Pget\_cache
- H5Pget\_char\_encoding
- H5Pget\_chunk
- H5Pget\_chunk\_cache
- H5Pget\_class
- H5Pget\_class\_name
- H5Pget\_class\_parent
- H5Pget\_copy\_object
- H5Pget\_create\_intermediate\_group
- H5Pget\_data\_transform
- H5Pget\_driver
- H5Pget\_driver\_info
- H5Pget\_dxpl\_mpio ||
- H5Pget\_dxpl\_multi
- H5Pget\_edc\_check
- H5Pget\_elink\_acc\_flags
- H5Pget\_elink\_cb
- H5Pget\_elink\_fapl
- H5Pget\_elink\_prefix
- H5Pget\_est\_link\_info
- H5Pget\_external
- H5Pget\_external\_count
- H5Pget\_family\_offset
- H5Pget\_fapl\_core
- H5Pget\_fapl\_direct
- H5Pget\_fapl\_family
- H5Pget\_fapl\_mpio ||
- H5Pget\_fapl\_mpio\_six ||
- H5Pget\_fapl\_multi
- H5Pget\_fclos\_degree
- H5Pget\_fill\_time
- H5Pget\_fill\_value
- *H5Pget\_filter*
- H5Pget\_filter1 \*
- H5Pget\_filter2
- *H5Pget\_filter\_by\_id*
- H5Pget\_filter\_by\_id1 \*
- H5Pget\_filter\_by\_id2
- H5Pget\_gc\_references
- H5Pget\_hyper\_vector\_size
- H5Pget\_istore\_k
- H5Pget\_layout
- H5Pget\_libver\_bounds
- H5Pget\_link\_creation\_order
- H5Pget\_link\_phase\_change
- H5Pget\_local\_heap\_size\_hint
- H5Pget\_mdc\_config
- H5Pget\_meta\_block\_size
- H5Pget\_multi\_type
- H5Pget\_nfilters
- H5Pget\_nlinks
- H5Pget\_nprops
- H5Pget\_preserve \*
- H5Pget\_obj\_track\_times
- H5Pget\_shared\_mesg\_index
- H5Pget\_shared\_mesg\_nindexes
- H5Pget\_shared\_mesg\_phase\_change
- H5Pget\_sieve\_buf\_size
- H5Pget\_size
- H5Pget\_sizes
- H5Pget\_small\_data\_block\_size
- H5Pget\_sym\_k
- H5Pget\_type\_conv\_cb
- H5Pget\_userblock
- H5Pget\_version
- H5Pget\_vlen\_mem\_manager
- *H5Pinsert*
- H5Pinsert1 \*
- H5Pinsert2
- H5Pisa\_class
- H5Piterate
- H5Pmodify\_filter

- *H5Pregister*
  - H5Pregister1 \*
  - H5Pregister2
  - H5Premove
  - H5Premove\_filter
  - H5Pset
  - H5Pset\_alignment
  - H5Pset\_alloc\_time
  - H5Pset\_attr\_creation\_order
  - H5Pset\_attr\_phase\_change
  - H5Pset\_btree\_ratios
  - H5Pset\_buffer
  - H5Pset\_cache
  - H5Pset\_char\_encoding
  - H5Pset\_chunk
  - H5Pset\_chunk\_cache
  - H5Pset\_copy\_object
  - H5Pset\_create\_intermediate\_group
  - H5Pset\_data\_transform
  - H5Pset\_deflate
  - H5Pset\_driver
  - H5Pset\_dxpl\_mpio ||
  - H5Pset\_dxpl\_mpio\_chunk\_opt ||
  - H5Pset\_dxpl\_mpio\_chunk\_opt\_num ||
  - H5Pset\_dxpl\_mpio\_chunk\_opt\_ratio ||
  - H5Pset\_dxpl\_mpio\_collective\_opt ||
  - H5Pset\_dxpl\_multi
  - H5Pset\_edc\_check
  - H5Pset\_elink\_acc\_flags
  - H5Pset\_elink\_cb
  - H5Pset\_elink\_fapl
  - H5Pset\_elink\_prefix
  - H5Pset\_est\_link\_info
  - H5Pset\_external
  - H5Pset\_family\_offset
  - H5Pset\_fapl\_core
  - H5Pset\_fapl\_family
  - H5Pset\_fapl\_direct
  - H5Pset\_fapl\_log
  - H5Pset\_fapl\_mpio ||
  - H5Pset\_fapl\_mpio\_six ||
  - H5Pset\_fapl\_multi
  - H5Pset\_fapl\_sec2
  - H5Pset\_fapl\_split
  - H5Pset\_fapl\_stdio
  - H5Pset\_fapl\_windows
  - H5Pset\_fcclose\_degree
  - H5Pset\_fill\_time
  - H5Pset\_fill\_value
  - H5Pset\_filter
  - H5Pset\_filter\_callback
  - H5Pset\_fletcher32
  - H5Pset\_gc\_references
  - H5Pset\_hyper\_vector\_size
  - H5Pset\_istore\_k
  - H5Pset\_layout
  - H5Pset\_libver\_bounds
  - H5Pset\_link\_creation\_order
  - H5Pset\_link\_phase\_change
  - H5Pset\_local\_heap\_size\_hint
  - H5Pset\_mdc\_config
  - H5Pset\_meta\_block\_size
  - H5Pset\_multi\_type
  - H5Pset\_nbit
  - H5Pset\_nlinks
  - H5Pset\_preserve \*
  - H5Pset\_obj\_track\_times
  - H5Pset\_scaleoffset
  - H5Pset\_shared\_mesg\_index
  - H5Pset\_shared\_mesg\_nindexes
  - H5Pset\_shared\_mesg\_phase\_change
  - H5Pset\_shuffle
  - H5Pset\_sieve\_buf\_size
  - H5Pset\_sizes
  - H5Pset\_small\_data\_block\_size
  - H5Pset\_sym\_k
  - H5Pset\_szip
  - H5Pset\_type\_conv\_cb
  - H5Pset\_userblock
  - H5Pset\_vlen\_mem\_manager
  - H5Punregister
- || *Indicates functions available only in the parallel HDF5 library.*
- \* *Use of these functions is deprecated in Release 1.8.0.*



**The FORTRAN90 Interfaces:**

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

*General Property List Operations*

- h5pcreate\_f
- h5pget\_class\_f
- h5pcopy\_f
- h5pclose\_f

*Generic Properties*

- h5pcreate\_class\_f
- h5pregister\_f
- h5pinsert\_f
- h5pset\_f
- h5pexist\_f
- h5pget\_size\_f
- h5pget\_nprops\_f
- h5pget\_class\_name\_f
- h5pget\_class\_parent\_f
- h5pisa\_class\_f
- h5pget\_f
- h5pequal\_f
- h5pcopy\_prop\_f
- h5premove\_f
- h5punregister\_f
- h5pclose\_class\_f

*File Creation Properties*

- H5Pget\_version\_f
- H5Pset\_userblock\_f
- H5Pget\_userblock\_f
- H5Pset\_sizes\_f
- H5Pget\_sizes\_f
- H5Pset\_sym\_k\_f
- H5Pget\_sym\_k\_f
- H5Pset\_istore\_k\_f
- H5Pget\_istore\_k\_f

*File Access Properties*

- H5Pset\_driver\_f
- H5Pget\_driver\_info\_f
- H5Pset\_fclose\_degree\_f
- H5Pget\_fclose\_degree\_f
- H5Pset\_fapl\_core\_f
- H5Pget\_fapl\_core\_f
- H5Pset\_fapl\_direct\_f
- H5Pget\_fapl\_direct\_f
- H5Pset\_fapl\_family\_f
- H5Pget\_fapl\_family\_f
- H5Pset\_family\_offset\_f
- H5Pset\_fapl\_mpio\_f ||
- H5Pget\_fapl\_mpio\_f ||
- H5Pset\_fapl\_mpio\_posix\_f ||
- H5Pget\_fapl\_mpio\_posix\_f ||
- H5Pset\_fapl\_multi\_f
- H5Pget\_fapl\_multi\_f
- H5Pset\_multi\_type\_f
- H5Pget\_multi\_type\_f
- H5Pset\_fapl\_split\_f
- H5Pset\_fapl\_sec2\_f
- H5Pset\_fapl\_stdio\_f
- H5Pget\_driver\_f
- H5Pset\_meta\_block\_size\_f
- H5Pget\_meta\_block\_size\_f
- H5Pset\_sieve\_buf\_size\_f
- H5Pget\_sieve\_buf\_size\_f
- H5Pset\_alignment\_f
- H5Pget\_alignment\_f
- H5Pset\_cache\_f
- H5Pget\_cache\_f
- H5Pset\_gc\_references\_f
- H5Pget\_gc\_references\_f
- H5Pset\_small\_data\_block\_size\_f
- H5Pget\_small\_data\_block\_size\_f
- H5Pset\_libver\_bounds\_f

*Group Creation Properties*

- H5Pset\_create\_inter\_group\_f
- H5Pget\_create\_inter\_group\_f
- H5Pset\_local\_heap\_size\_hint\_f
- H5Pget\_local\_heap\_size\_hint\_f
- H5Pset\_link\_creation\_order\_f
- H5Pget\_link\_creation\_order\_f
- H5Pset\_est\_link\_info\_f
- H5Pget\_est\_link\_info\_f
- H5Pset\_link\_phase\_change\_f
- H5Pget\_link\_phase\_change\_f

*Link Access Properties*

- H5Pset\_nlinks\_f
- H5Pget\_nlinks\_f

|| *Indicates functions available only in the parallel HDF5 library.*

### *Object Copy and Object Creation Properties*

- H5Pset\_create\_inter\_group\_f
- H5Pget\_create\_inter\_group\_f
- H5Pset\_copy\_object\_f
- H5Pget\_copy\_object\_f
- H5Pset\_attr\_phase\_change\_f
- H5Pget\_attr\_phase\_change\_f
- H5Pset\_attr\_creation\_order\_f
- H5Pget\_attr\_creation\_order\_f
- H5Pset\_obj\_track\_times\_f
- H5Pget\_obj\_track\_times\_f

### *String Properties*

- H5Pset\_char\_encoding\_f
- H5Pget\_char\_encoding\_f

|| *Indicates functions  
available only in the  
parallel HDF5 library.*

\* *Use of these functions  
is deprecated in  
Release 1.8.0.*

### *Dataset Creation Properties*

- H5Pset\_layout\_f
- H5Pget\_layout\_f
- H5Pset\_chunk\_f
- H5Pget\_chunk\_f
- H5Pset\_deflate\_f
- H5Pset\_fill\_value\_f
- H5Pget\_fill\_value\_f
- H5Pset\_fill\_time\_f
- H5Pget\_fill\_time\_f
- H5Pset\_alloc\_time\_f
- H5Pget\_alloc\_time\_f
- H5Pset\_filter\_f
- H5Pget\_nfilters\_f
- H5Pget\_filter\_f
- H5Pget\_filter\_by\_id\_f
- H5Pmodify\_filter\_f
- H5Premove\_filter\_f
- H5Pset\_fletcher32\_f
- H5Pset\_nbit\_f
- H5Pset\_scaleoffset\_f
- H5Pset\_shuffle\_f
- H5Pset\_szip\_f
- H5Pset\_external\_f
- H5Pget\_external\_count\_f
- H5Pget\_external\_f

### *Dataset Access, Memory, and Transfer Properties*

- H5Pset\_buffer\_f
- H5Pget\_buffer\_f
- H5Pset\_preserve\_f
- H5Pget\_preserve\_f
- H5Pset\_edc\_check\_f
- H5Pget\_edc\_check\_f
- H5Pset\_data\_transform\_f
- H5Pget\_data\_transform\_f
- H5Pset\_hyper\_vector\_size\_f
- H5Pget\_hyper\_vector\_size\_f
- H5Pset\_btree\_ratios\_f
- H5Pget\_btree\_ratios\_f
- H5Pset\_dxpl\_mpio\_f ||
- H5Pget\_dxpl\_mpio\_f ||

**Filter Behavior in HDF5:**

Filters can be inserted into the HDF5 pipeline to perform functions such as compression and conversion. As such, they are a very flexible aspect of HDF5; for example, a user-defined filter could provide encryption for an HDF5 dataset.

A filter can be declared as either *required* or *optional*. Required is the default status; optional status must be explicitly declared.

A required filter that fails or is not defined causes an entire output operation to fail; if it was applied when the data was written, such a filter will cause an input operation to fail.

The following table summarizes required filter behavior.

	<b>Required <code>FILTER_X</code> not available</b>	<b><code>FILTER_X</code> available</b>
<b>H5Pset_&lt;<i>FILTER_X</i>&gt;</b>	Will fail.	Will succeed.
<b>H5Dwrite with <code>FILTER_X</code> set</b>	Will fail.	Will succeed; <code>FILTER_X</code> will be applied to the data.
<b>H5Dread with <code>FILTER_X</code> set</b>	Will fail.	Will succeed.

An optional filter can be set for an HDF5 dataset even when the filter is not available. Such a filter can then be applied to the dataset when it becomes available on the original system or when the file containing the dataset is processed on a system on which it is available.

A filter can be declared as optional through the use of the `H5Z_FLAG_OPTIONAL` flag with `H5Pset_filter`.

Consider a situation where one is creating files that will normally be used only on systems where the optional (and fictional) filter `FILTER_Z` is routinely available. One can create those files on system A, which lacks `FILTER_Z`, create chunked datasets in the files with `FILTER_Z` defined in the dataset creation property list, and even write data to those datasets. The dataset object header will indicate that `FILTER_Z` has been associated with this dataset. But since system A does not have `FILTER_Z`, dataset chunks will be written without it being applied.

HDF5 has a mechanism for determining whether chunks are actually written with the filters specified in the object header, so while the filter remains unavailable, system A will be able to read the data. Once the file is moved to system B, where `FILTER_Z` is available, HDF5 will apply `FILTER_Z` to any data rewritten or new data written in these datasets. Dataset chunks that have been written on system B will then be unreadable on system A; chunks that have not been re-written since being written on system A will remain readable on system A. All chunks will be readable on system B.

The following table summarizes optional filter behavior.

	<b>FILTER_Z not available</b>	<b>FILTER_Z available with encode and decode</b>	<b>FILTER_Z available decode only</b>
<b>H5Pset_&lt;FILTER_Z&gt;</b>	Will succeed.	Will succeed.	Will succeed.
<b>H5Dwrite with FILTER_Z set</b>	Will succeed; FILTER_Z will <i>not</i> be applied to the data.	Will succeed; FILTER_Z will be applied to the data.	Will succeed; FILTER_Z will <i>not</i> be applied to the data.
<b>H5Dread with FILTER_Z set</b>	Will succeed if FILTER_Z has not actually been applied to data.	Will succeed.	Will succeed.

The above principles apply generally in the use of HDF5 optional filters insofar as HDF5 does as much as possible to complete an operation when an optional filter is unavailable. (The SZIP filter is an exception to this rule; see `H5Pset_szip` for details.)

**Notes:**

Filters can be applied only to chunked datasets; they cannot be used with other dataset storage methods, such as contiguous, compact, or external datasets.

Dataset elements of variable-length and dataset region reference datatypes are stored in separate structures in the file called heaps. Filters cannot currently be applied to these heaps.

**Name:** H5Pall\_filters\_avail

**Signature:**

*htri\_t* H5Pall\_filters\_avail(*hid\_t* dcpl\_id)

**Purpose:**

Verifies that all required filters are available.

**Description:**

H5Pall\_filters\_avail verifies that all of the filters set in the dataset creation property list dcpl\_id are currently available.

**Parameters:**

*hid\_t* dcpl\_id      IN: Dataset creation property list identifier.

**Returns:**

Returns TRUE if all filters are available and FALSE if one or more is not currently available.

Returns FAIL, a negative value, on error.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.6.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Pclose

**Signature:**

*herr\_t* H5Pclose(*hid\_t* plist)

**Purpose:**

Terminates access to a property list.

**Description:**

H5Pclose terminates access to a property list. All property lists should be closed when the application is finished accessing them. This frees resources used by the property list.

**Parameters:**

*hid\_t* plist      IN: Identifier of the property list to terminate access to.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pclose\_f

```
SUBROUTINE h5pclose_f(prp_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5pclose_f
```

**Name:** H5Pclose\_class

**Signature:**

*herr\_t* H5Pclose\_class(*hid\_t* class)

**Purpose:**

Closes an existing property list class.

**Description:**

Removes a property list class from the library.

Existing property lists of this class will continue to exist, but new ones are not able to be created.

**Parameters:**

*hid\_t* class      IN: Property list class to close

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** h5pclose\_class\_f

```
SUBROUTINE h5pclose_class_f(class, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: class ! Property list class identifier
                                      ! to close
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pclose_class_f
```

**Name:** H5Pcopy

**Signature:**

*hid\_t* H5Pcopy(*hid\_t* plist)

**Purpose:**

Copies an existing property list to create a new property list.

**Description:**

H5Pcopy copies an existing property list to create a new property list. The new property list has the same properties and values as the original property list.

**Parameters:**

*hid\_t* plist      IN: Identifier of property list to duplicate.

**Returns:**

Returns a property list identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pcopy\_f

```
SUBROUTINE h5pcopy_f(prp_id, new_prp_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id           ! Property list identifier
  INTEGER(HID_T), INTENT(OUT) :: new_prp_id      ! Identifier of property list
  ! copy
  INTEGER, INTENT(OUT) :: hdferr                 ! Error code
  ! 0 on success and -1 on failure
END SUBROUTINE h5pcopy_f
```



**Name:** H5Pcopy\_prop

**Signature:**

*herr\_t* H5Pcopy\_prop(*hid\_t* dst\_id, *hid\_t* src\_id, *const char* \*name )

**Purpose:**

Copies a property from one list or class to another.

**Description:**

H5Pcopy\_prop copies a property from one property list or class to another.

If a property is copied from one class to another, all the property information will be first deleted from the destination class and then the property information will be copied from the source class into the destination class.

If a property is copied from one list to another, the property will be first deleted from the destination list (generating a call to the `close` callback for the property, if one exists) and then the property is copied from the source list to the destination list (generating a call to the `copy` callback for the property, if one exists).

If the property does not exist in the class or list, this call is equivalent to calling `H5Pregister` or `H5Pinsert` (for a class or list, as appropriate) and the `create` callback will be called in the case of the property being copied into a list (if such a callback exists for the property).

**Parameters:**

<i>hid_t</i> dst_id	IN: Identifier of the destination property list or class
<i>hid_t</i> src_id	IN: Identifier of the source property list or class
<i>const char</i> *name	IN: Name of the property to copy

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** h5pcopy\_prop\_f

```

SUBROUTINE h5pcopy_prop_f(dst_id, src_id, name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dst_id ! Destination property list
                                         ! identifier
  INTEGER(HID_T), INTENT(IN) :: src_id ! Source property list identifier
  CHARACTER(LEN=*), INTENT(IN) :: name ! Property name
  INTEGER, INTENT(OUT) :: hdferr       ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pcopy_prop_f

```

**Name:** H5Pcreate

**Signature:**

*hid\_t* H5Pcreate(*hid\_t* cls\_id)

**Purpose:**

Creates a new property as an instance of a property list class.

**Description:**

H5Pcreate creates a new property as an instance of some property list class. The new property list is initialized with default values for the specified class. The classes are as follows; see the function index at the top of this page for a list of functions related to each class:

H5P\_OBJECT\_CREATE

Properties for object creation during the object copying process.

H5P\_FILE\_CREATE

Properties for file creation.

H5P\_FILE\_ACCESS

Properties for file access.

H5P\_DATASET\_CREATE

Properties for dataset creation.

H5P\_DATASET\_ACCESS

Properties for dataset access.

H5P\_DATASET\_XFER

Properties for raw data transfer.

H5P\_FILE\_MOUNT

Properties for file mounting.

H5P\_GROUP\_CREATE

Properties for group creation during the object copying process.

H5P\_GROUP\_ACCESS

Properties for group access during the object copying process.

H5P\_DATATYPE\_CREATE

Properties for datatype creation during the object copying process.

H5P\_DATATYPE\_ACCESS

Properties for datatype access during the object copying process.

H5P\_STRING\_CREATE

Properties for character encoding when encoding strings or object names.

H5P\_ATTRIBUTE\_CREATE

Properties for attribute creation during the object copying process.

H5P\_OBJECT\_COPY

Properties governing the object copying process.

H5P\_LINK\_CREATE

Properties governing link creation.

H5P\_LINK\_ACCESS

Properties governing link traversal when accessing objects.

This property list must eventually be closed with H5Pclose; otherwise, errors are likely to occur.

**Parameters:**

*hid\_t* cls\_id      IN: The class of the property list to create.

**Returns:**

Returns a property list identifier (*plist*) if successful; otherwise Fail (-1).

**Fortran90 Interface: h5pcreate\_f**

```

SUBROUTINE h5pcreate_f(classtype, prp_id, hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(IN) :: classtype      ! The type of the property list
                                          ! to be created
                                          ! Possible values are:
                                          !   H5P_FILE_CREATE_F
                                          !   H5P_FILE_ACCESS_F
                                          !   H5P_DATASET_CREATE_F
                                          !   H5P_DATASET_XFER_F
                                          !   H5P_MOUNT_F

  INTEGER(HID_T), INTENT(OUT) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pcreate_f

```

*Last modified: 26 March 2009*

**Name:** H5Pcreate\_class

**Signature:**

```
hid_t H5Pcreate_class( hid_t parent_class, const char *name, H5P_cls_create_func_t
create, void *create_data, H5P_cls_copy_func_t copy, void *copy_data,
H5P_cls_close_func_t close, void *close_data )
```

**Purpose:**

Creates a new property list class.

**Description:**

H5Pcreate\_class registers a new property list class with the library. The new property list class can inherit from an existing property list class, `parent_class`, or may be derived from the default “empty” class, `NULL`. New classes with inherited properties from existing classes may not remove those existing properties, only add or remove their own class properties. Property list classes defined and supported in the HDF5 Library distribution are listed and briefly described in H5Pcreate.

The `create` routine is called when a new property list of this class is being created. The `H5P_cls_create_func_t` callback function is defined as follows:

*typedef herr\_t (\*H5P\_cls\_create\_func\_t)( hid\_t prop\_id, void \* create\_data );* The parameters to this callback function are defined as follows:

<i>hid_t prop_id</i>	IN: The identifier of the property list being created
<i>void * create_data</i>	IN: User pointer to any <i>class creation</i> data required

The `create` routine is called after any registered `create` function is called for each property value. If the `create` routine returns a negative value, the new list is not returned to the user and the property list creation routine returns an error value.

The `copy` routine is called when an existing property list of this class is copied. The `H5P_cls_copy_func_t` callback function is defined as follows:

*typedef herr\_t (\*H5P\_cls\_copy\_func\_t)( hid\_t prop\_id, void \* copy\_data );* The parameters to this callback function are defined as follows:

<i>hid_t prop_id</i>	IN: The identifier of the property list created by copying
<i>void * copy_data</i>	IN: User pointer to any <i>class copy</i> data required

The `copy` routine is called after any registered `copy` function is called for each property value. If the `copy` routine returns a negative value, the new list is not returned to the user and the property list copy routine returns an error value.

The `close` routine is called when a property list of this class is being closed. The `H5P_cls_close_func_t` callback function is defined as follows:

*typedef herr\_t (\*H5P\_cls\_close\_func\_t)( hid\_t prop\_id, void \* close\_data );* The parameters to this callback function are defined as follows:

<i>hid_t prop_id</i>	IN: The identifier of the property list being closed
<i>void * close_data</i>	IN: User pointer to any <i>class close</i> data required

The `close` routine is called before any registered `close` function is called for each property value. If the `close` routine returns a negative value, the property list `close` routine returns an error value but the property list is still closed.

**Parameters:**

<i>hid_t</i> parent_class	IN: Property list class to inherit from or NULL
<i>const char</i> *name	IN: Name of property list class to register
<i>H5P_cls_create_func_t</i> create	IN: Callback routine called when a property list is created
<i>void</i> *create_data	IN: Pointer to user-defined <i>class create</i> data, to be passed along to <i>class create</i> callback
<i>H5P_cls_copy_func_t</i> copy	IN: Callback routine called when a property list is copied
<i>void</i> *copy_data	IN: Pointer to user-defined <i>class copy</i> data, to be passed along to <i>class copy</i> callback
<i>H5P_cls_close_func_t</i> close	IN: Callback routine called when a property list is being closed
<i>void</i> *close_data	IN: Pointer to user-defined <i>class close</i> data, to be passed along to <i>class close</i> callback

**Returns:**

On success, returns a valid property list class identifier; otherwise returns a negative value.

**Fortran90 Interface:** h5pcreate\_class\_f

```

SUBROUTINE h5pcreate_class_f(parent, name, class, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: parent ! Parent property list class
                                         ! identifier
                                         ! Possible values include:
                                         !   H5P_NO_CLASS_F
                                         !   H5P_FILE_CREATE_F
                                         !   H5P_FILE_ACCESS_F
                                         !   H5P_DATASET_CREATE_F
                                         !   H5P_DATASET_XFER_F
                                         !   H5P_MOUNT_F

  CHARACTER(LEN=*), INTENT(IN) :: name ! Name of property to create
  INTEGER(HID_T), INTENT(OUT) :: class ! Property list class identifier
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                         ! 0 on success and -1 on failure

END SUBROUTINE h5pcreate_class_f

```

**Name:** H5Pequal

**Signature:**

*htri\_t* H5Pequal( *hid\_t* id1, *hid\_t* id2 )

**Purpose:**

Compares two property lists or classes for equality.

**Description:**

H5Pequal compares two property lists or classes to determine whether they are equal to one another.

Either both id1 and id2 must be property lists or both must be classes; comparing a list to a class is an error.

**Parameters:**

*hid\_t* id1           IN: First property object to be compared

*hid\_t* id2           IN: Second property object to be compared

**Returns:**

Success: TRUE (positive) if equal; FALSE (zero) if unequal

Failure: a negative value

**Fortran90 Interface:** h5pequal\_f

```
SUBROUTINE h5pequal_f(plist1_id, plist2_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist1_id ! Property list identifier
  INTEGER(HID_T), INTENT(IN) :: plist2_id ! Property list identifier
  LOGICAL, INTENET(OUT)      :: flag      ! Flag
                                     !      .TRUE. if lists are equal
                                     !      .FALSE. otherwise
  INTEGER, INTENT(OUT)       :: hdferr    ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5pequal_f
```

**Name:** H5Pexist

**Signature:**

*htri\_t* H5Pexist( *hid\_t* id, *const char* \*name )

**Purpose:**

Queries whether a property name exists in a property list or class.

**Description:**

H5Pexist determines whether a property exists within a property list or class.

**Parameters:**

*hid\_t* id                      IN: Identifier for the property to query

*const char* \*name            IN: Name of property to check for

**Returns:**

Success: a positive value if the property exists in the property object; zero if the property does not exist

Failure: a negative value

**Fortran90 Interface:** h5pexist\_f

```
SUBROUTINE h5pexist_f(prp_id, name, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id   ! Property list identifier
  CHARACTER(LEN=*), INTENT(IN) :: name   ! Name of property to modify
  LOGICAL, INTENT(OUT) :: flag           ! Logical flag
                                          !   .TRUE. if exists
                                          !   .FALSE. otherwise
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pexist_f
```

**Name:** H5Pfill\_value\_defined

**Signature:**

*herr\_t* H5Pfill\_value\_defined(*hid\_t* plist\_id, *H5D\_fill\_value\_t* \*status )

**Purpose:**

Determines whether fill value is defined.

**Description:**

H5Pfill\_value\_defined determines whether a fill value is defined in the dataset creation property list *plist\_id*.

Valid values returned in *status* are as follows:

H5D_FILL_VALUE_UNDEFINED	Fill value is undefined.
H5D_FILL_VALUE_DEFAULT	Fill value is the library default.
H5D_FILL_VALUE_USER_DEFINED	Fill value is defined by the application.

**Note:**

H5Pfill\_value\_defined is designed for use in concert with the dataset fill value properties functions H5Pget\_fill\_value and H5Pget\_fill\_time.

See H5Dcreate for further cross-references.

**Parameters:**

<i>hid_t</i> plist_id	IN: Dataset creation property list identifier.
<i>H5D_fill_value_t</i> *status	OUT: Status of fill value in property list.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.



**Name:** H5Pget

**Signature:**

```
herr_t H5Pget( hid_t plid, const char *name, void *value )
```

**Purpose:**

Queries the value of a property.

**Description:**

H5Pget retrieves a copy of the value for a property in a property list. If there is a get callback routine registered for this property, the copy of the value of the property will first be passed to that routine and any changes to the copy of the value will be used when returning the property value from this routine.

This routine may be called for zero-sized properties with the value set to NULL. The get routine will be called with a NULL value if the callback exists.

The property name must exist or this routine will fail.

If the get callback routine returns an error, value will not be modified.

**Parameters:**

<i>hid_t</i> plid	IN: Identifier of the property list to query
<i>const char</i> *name	IN: Name of property to query
<i>void</i> *value	OUT: Pointer to a location to which to copy the value of of the property

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** h5pget\_f

```
SUBROUTINE h5pget_f(plid, name, value, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plid      ! Property list identifier
  CHARACTER(LEN=*), INTENT(IN) :: name    ! Name of property to get
  TYPE, INTENT(OUT) :: value              ! Property value
                                          ! Supported types are:
                                          !   INTEGER
                                          !   REAL
                                          !   DOUBLE PRECISION
                                          !   CHARACTER(LEN=*)
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pget_f
```

**Name:** H5Pget\_alignment

**Signature:**

```
herr_t H5Pget_alignment(hid_t plist, hsize_t *threshold, hsize_t *alignment )
```

**Purpose:**

Retrieves the current settings for alignment properties from a file access property list.

**Description:**

H5Pget\_alignment retrieves the current settings for alignment properties from a file access property list. The threshold and/or alignment pointers may be null pointers (NULL).

**Parameters:**

<i>hid_t</i> plist	IN: Identifier of a file access property list.
<i>hsize_t</i> *threshold	OUT: Pointer to location of return threshold value.
<i>hsize_t</i> *alignment	OUT: Pointer to location of return alignment value.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_alignment\_f

```
SUBROUTINE h5pget_alignment_f(prp_id, threshold, alignment, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id           ! Property list identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: threshold     ! Threshold value
  INTEGER(HSIZE_T), INTENT(OUT) :: alignment     ! Alignment value
  INTEGER, INTENT(OUT) :: hdferr                 ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5pget_alignment_f
```

**Name:** H5Pget\_alloc\_time

**Signature:**

```
herr_t H5Pget_alloc_time(hid_t plist_id, H5D_alloc_time_t *alloc_time)
```

**Purpose:**

Retrieves the timing for storage space allocation.

**Description:**

H5Pget\_alloc\_time retrieves the timing for allocating storage space for a dataset's raw data. This property is set in the dataset creation property list *plist\_id*.

The timing setting is returned in *alloc\_time* as one of the following values:

H5D_ALLOC_TIME_DEFAULT	Uses the default allocation time, based on the dataset storage method. See the <i>alloc_time</i> description in H5Pset_alloc_time for default allocation times for various storage methods.
H5D_ALLOC_TIME_EARLY	All space is allocated when the dataset is created.
H5D_ALLOC_TIME_INCR	Space is allocated incrementally as data is written to the dataset.
H5D_ALLOC_TIME_LATE	All space is allocated when data is first written to the dataset.

**Note:**

H5Pget\_alloc\_time is designed to work in concert with the dataset fill value and fill value write time properties, set with the functions H5Pget\_fill\_value and H5Pget\_fill\_time.

**Parameters:**

*hid\_t* plist\_id                      IN: Dataset creation property list identifier.  
*H5D\_alloc\_time\_t* \*alloc\_time      IN: When to allocate dataset storage space.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_alloc\_time\_f

```
SUBROUTINE h5pget_alloc_time_f(plist_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id      ! Dataset creation
                                              ! property list identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: flag       ! Allocation time flag
                                              ! Possible values are:
                                              !   H5D_ALLOC_TIME_ERROR_F
                                              !   H5D_ALLOC_TIME_DEFAULT_F
                                              !   H5D_ALLOC_TIME_EARLY_F
                                              !   H5D_ALLOC_TIME_LATE_F
                                              !   H5D_ALLOC_TIME_INCR_F
  INTEGER, INTENT(OUT)          :: hdferr     ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5pget_alloc_time_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Pget\_attr\_creation\_order

**Signature:**

```
herr_t H5Pget_attr_creation_order( hid_t ocpl_id, unsigned *crt_order_flags )
```

**Purpose:**

Retrieves tracking and indexing settings for attribute creation order.

**Description:**

H5Pget\_attr\_creation\_order retrieves the settings for tracking and indexing attribute creation order on an object.

ocpl\_id is a dataset or group creation property list identifier. The term ocpl, for object creation property list, is used when different types of objects may be involved.

crt\_order\_flags returns flags with the following meanings:

H5P_CRT_ORDER_TRACKED	Attribute creation order is tracked but not necessarily indexed.
H5P_CRT_ORDER_INDEXED	Attribute creation order is indexed (requires H5P_CRT_ORDER_TRACKED).

If crt\_order\_flags is returned with a value of 0 (zero), attribute creation order is neither tracked nor indexed.

**Parameters:**

<i>hid_t</i> ocpl_id	IN: Object (group or dataset) creation property list identifier
<i>unsigned</i> *crt_order_flags	OUT: Flags specifying whether to track and index attribute creation order

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_attr\_creation\_order\_f

```
SUBROUTINE h5pget_attr_creation_order_f(ocpl_id, crt_order_flags, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: ocpl_id      ! Object (group or dataset) creation
                                              ! property list identifier
  INTEGER, INTENT(OUT) :: crt_order_flags    ! Flags specifying whether to track
                                              ! and index attribute creation order
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5pget_attr_creation_order_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pget\_attr\_phase\_change

**Signature:**

```
herr_t H5Pget_attr_phase_change( hid_t ocpl_id, unsigned *max_compact, unsigned
*min_dense )
```

**Purpose:**

Retrieves attribute storage phase change thresholds.

**Description:**

H5Pget\_attr\_phase\_change retrieves threshold values for attribute storage on an object. These thresholds determine the point at which attribute storage changes from compact storage (i.e., storage in the object header) to dense storage (i.e., storage in a heap and indexed with a B-tree).

In the general case, attributes are initially kept in compact storage. When the number of attributes exceeds `max_compact`, attribute storage switches to dense storage. If the number of attributes subsequently falls below `min_dense`, the attributes are returned to compact storage.

If `max_compact` is set to 0 (zero), dense storage always used.

`ocpl_id` is a dataset or group creation property list identifier. The term `ocpl`, for object creation property list, is used when different types of objects may be involved.

**Parameters:**

<i>hid_t</i> ocpl_id	IN: Object (dataset or group) creation property list identifier
<i>unsigned</i> *max_compact	OUT: Maximum number of attributes to be stored in compact storage (Default: 8)
<i>unsigned</i> *min_dense	OUT: Minimum number of attributes to be stored in dense storage (Default: 6)

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_attr\_phase\_change\_f

```
SUBROUTINE h5pget_attr_phase_change_f(ocpl_id, max_compact, min_dense, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: ocpl_id
    ! Object (dataset or group) creation property list identifier
  INTEGER, INTENT(OUT) :: max_compact
    ! Maximum number of attributes to be stored in compact storage
    ! (Default: 8)
  INTEGER, INTENT(OUT) :: min_dense
    ! Minimum number of attributes to be stored in dense storage
    ! (Default: 6)
  INTEGER, INTENT(OUT) :: hdferr
    ! Error code:
    ! 0 on success and -1 on failure
END SUBROUTINE h5pget_attr_phase_change_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pget\_btree\_ratios

**Signature:**

*herr\_t* H5Pget\_btree\_ratios(*hid\_t* plist, *double* \*left, *double* \*middle, *double* \*right )

**Purpose:**

Gets B-tree split ratios for a dataset transfer property list.

**Description:**

H5Pget\_btree\_ratios returns the B-tree split ratios for a dataset transfer property list.

The B-tree split ratios are returned through the non-NULL arguments left, middle, and right, as set by the H5Pset\_btree\_ratios function.

**Parameters:**

<i>hid_t</i> plist	IN: The dataset transfer property list identifier.
<i>double</i> left	OUT: The B-tree split ratio for left-most nodes.
<i>double</i> right	OUT: The B-tree split ratio for right-most nodes and lone nodes.
<i>double</i> middle	OUT: The B-tree split ratio for all other nodes.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_btree\_ratios\_f

```

SUBROUTINE h5pget_btree_ratios_f(prp_id, left, middle, right, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id
                                ! Property list identifier
  REAL, INTENT(OUT) :: left      ! B-tree split ratio for left-most nodes
  REAL, INTENT(OUT) :: middle    ! B-tree split ratio for all other nodes
  REAL, INTENT(OUT) :: right     ! The B-tree split ratio for right-most
                                ! nodes and lone nodes.
  INTEGER, INTENT(OUT) :: hdferr ! Error code:
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pget_btree_ratios_f

```

**Name:** H5Pget\_buffer

**Signature:**

*hsize\_t* H5Pget\_buffer(*hid\_t* plist, *void \*\*tconv*, *void \*\*bkg* )

**Purpose:**

Reads buffer settings.

**Description:**

H5Pget\_buffer reads values previously set with H5Pset\_buffer.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier for the dataset transfer property list.
<i>void **tconv</i>	OUT: Address of the pointer to application-allocated type conversion buffer.
<i>void **bkg</i>	OUT: Address of the pointer to application-allocated background buffer.

**Returns:**

Returns buffer size, in bytes, if successful; otherwise 0 on failure.

**Fortran90 Interface:** h5pget\_buffer\_f

```

SUBROUTINE h5pget_buffer_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)      :: plist_id ! Dataset transfer
                                         ! property list identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: size      ! Conversion buffer size
  INTEGER, INTENT(OUT)           :: hdferr   ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pget_buffer_f

```

**History:**

Release	C
1.6.0	The return type changed from <i>hsize_t</i> to <i>size_t</i> .
1.4.0	The return type changed to <i>hsize_t</i> .

**Name:** H5Pget\_cache

**Signature:**

```
herr_t H5Pget_cache(hid_t plist_id, int *mdc_nelmts, size_t *rdcc_nelmts, size_t
*rdcc_nbytes, double *rdcc_w0)
```

**Purpose:**

Queries the raw data chunk cache parameters.

**Description:**

H5Pget\_cache retrieves the maximum possible number of elements in the raw data chunk cache, the maximum possible number of bytes in the raw data chunk cache, and the preemption policy value.

Any (or all) arguments may be null pointers, in which case the corresponding datum is not returned.

Note that the `*mdc_nelmts` parameter is not longer used.

**Parameters:**

<code>hid_t plist_id</code>	IN: Identifier of the file access property list.
<code>int *mdc_nelmts</code>	IN/OUT: <i>No longer used.</i>
<code>size_t *rdcc_nelmts</code>	IN/OUT: Number of elements (objects) in the raw data chunk cache.
<code>size_t *rdcc_nbytes</code>	IN/OUT: Total size of the raw data chunk cache, in bytes.
<code>double *rdcc_w0</code>	IN/OUT: Preemption policy.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_cache\_f

```
SUBROUTINE h5pget_cache_f(prp_id, mdc_nelmts, rdcc_nelmts, rdcc_nbytes,
rdcc_w0, hdferr)

IMPLICIT NONE
INTEGER(HID_T), INTENT(IN) :: prp_id           ! Property list identifier
INTEGER, INTENT(OUT) :: mdc_nelmts             ! Number of elements (objects)
                                                ! in the meta data cache
INTEGER(SIZE_T), INTENT(OUT) :: rdcc_nelmts    ! Number of elements (objects)
                                                ! in the meta data cache
INTEGER(SIZE_T), INTENT(OUT) :: rdcc_nbytes    ! Total size of the raw data
                                                ! chunk cache, in bytes
REAL, INTENT(OUT) :: rdcc_w0                  ! Preemption policy
INTEGER, INTENT(OUT) :: hdferr                 ! Error code
                                                ! 0 on success and -1 on failure

END SUBROUTINE h5pget_cache_f
```

**History:**

Release	C
1.8.0	Use of the <code>mdc_nelmts</code> parameter discontinued. Metadata cache configuration is managed with <code>H5Pset_mdc_config</code> and <code>H5Pget_mdc_config</code> .
1.6.0	The <code>rdcc_nbytes</code> and <code>rdcc_nelmts</code> parameters changed from type <i>int</i> to <i>size_t</i> .



**Name:** H5Pget\_char\_encoding

**Signature:**

*herr\_t* H5Pget\_char\_encoding(*hid\_t* plist\_id, *H5T\_cset\_t* encoding)

**Purpose:**

Retrieves the character encoding used to create a string.

**Description:**

H5Pget\_char\_encoding retrieves the character encoding used to encode strings or object names that are created with the property list *plist\_id*.

Valid values for encoding are defined in *H5Tpublic.h* and include the following:

H5T_CSET_ASCII	US ASCII
H5T_CSET_UTF8	UTF-8 Unicode encoding

**Parameters:**

<i>hid_t</i> plist_id	IN: Property list identifier
<i>H5T_cset_t</i> encoding	OUT: String encoding character set

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_char\_encoding\_f

```
SUBROUTINE h5pget_char_encoding_f(plist_id, encoding, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id
                                ! Property list identifier
  INTEGER, INTENT(OUT) :: encoding ! Valid values for encoding are:
                                ! H5T_CSET_ASCII_F -> US ASCII
                                ! H5T_CSET_UTF8_F -> UTF-8 Unicode encoding
  INTEGER, INTENT(OUT) :: hdferr ! Error code:
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pget_char_encoding_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pget\_chunk

**Signature:**

```
int H5Pget_chunk(hid_t plist, int max_ndims, hsize_t *dims )
```

**Purpose:**

Retrieves the size of chunks for the raw data of a chunked layout dataset.

**Description:**

H5Pget\_chunk retrieves the size of chunks for the raw data of a chunked layout dataset. This function is only valid for dataset creation property lists. At most, max\_ndims elements of dims will be initialized.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier of property list to query.
<i>int</i> max_ndims	IN: Size of the dims array.
<i>hsize_t</i> *dims	OUT: Array to store the chunk dimensions.

**Returns:**

Returns chunk dimensionality if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_chunk\_f

```
SUBROUTINE h5pget_chunk_f(prp_id, ndims, dims, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id  ! Property list identifier
  INTEGER, INTENT(IN) :: ndims          ! Number of chunk dimensions
  ! to return
  INTEGER(HSIZE_T), DIMENSION(ndims), INTENT(OUT) :: dims
  ! Array containing sizes of
  ! chunk dimensions
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
  ! chunk rank on success
  ! and -1 on failure
END SUBROUTINE h5pget_chunk_f
```

*Last modified: 8 May 2009***Name:** H5Pget\_chunk\_cache**Signature:**

```
herr_t H5Pget_chunk_cache( hid_t dapl_id, size_t *rdcc_nslots, size_t *rdcc_nbytes,
                          double *rdcc_w0 )
```

**Purpose:**

Retrieves the raw data chunk cache parameters.

**Description:**

H5Pget\_chunk\_cache retrieves the number of chunk slots in the raw data chunk cache hash table , the maximum possible number of bytes in the raw data chunk cache, and the preemption policy value.

These values are retrieved from a dataset access property list. If the values have not been set on the property list, then values returned will be the corresponding values from a default file access property list.

Any (or all) pointer arguments may be null pointers, in which case the corresponding data is not returned.

**Parameters:**

<i>hid_t</i> plist_id	IN: Dataset access property list identifier.
<i>size_t</i> *rdcc_nslots	OUT: Number of chunk slots in the raw data chunk cache hash table.
<i>size_t</i> *rdcc_nbytes	OUT: Total size of the raw data chunk cache, in bytes.
<i>double</i> *rdcc_w0	OUT: Preemption policy.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Example Usage:**

The following code retrieves the chunk cache settings on the dataset access property list `dapl_id` into local variables:

```
size_t nslots, nbytes;
double w0;
status = H5Pget_chunk_cache(dapl_id, &nslots, &nbytes, &w0);
```

**See Also:**

H5Pset\_chunk\_cache

**History:**

Release	Change
1.8.3	C function introduced in this release.

**Name:** H5Pget\_class

**Signature:**

*H5P\_class\_t* H5Pget\_class(*hid\_t* plist)

**Purpose:**

Returns the property list class for a property list.

**Description:**

H5Pget\_class returns the property list class for the property list identified by the *plist* parameter.

Valid property list classes are defined in the description of H5Pcreate.

**Parameters:**

*hid\_t* plist      IN: Identifier of property list to query.

**Returns:**

Returns a property list class if successful. Otherwise returns H5P\_NO\_CLASS (-1).

**Fortran90 Interface:** h5pget\_class\_f

```
SUBROUTINE h5pget_class_f(prp_id, classtype, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: classtype ! The type of the property list
                                     ! to be created
                                     ! Possible values are:
                                     !   H5P_NO_CLASS
                                     !   H5P_FILE_CREATE_F
                                     !   H5P_FILE_ACCESS_F
                                     !   H5PE_DATASET_CREATE_F
                                     !   H5P_DATASET_XFER_F
                                     !   H5P_MOUNT_F
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5pget_class_f
```

**Name:** H5Pget\_class\_name

**Purpose:**

Retrieves the name of a class.

**Signature:**

*char* \*H5Pget\_class\_name(*hid\_t* pcid)

**Description:**

H5Pget\_class\_name retrieves the name of a generic property list class. The pointer to the name must be freed by the user after each successful call.

**Parameters:**

*hid\_t* pcid      IN: Identifier of the property class to query

**Returns:**

Success: a pointer to an allocated string containing the class name

Failure: NULL

**Fortran90 Interface:** h5pget\_class\_name\_f

```

SUBROUTINE h5pget_class_name_f(prp_id, name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier to
                                           ! query
  CHARACTER(LEN=*), INTENT(OUT) :: name    ! Buffer to retrieve class name
  INTEGER, INTENT(OUT) :: hdferr           ! Error code, possible values:
                                           ! Success: Actual length of the
                                           ! class name
                                           ! If provided buffer "name" is
                                           ! smaller, than name will be
                                           ! truncated to fit into
                                           ! provided user buffer
                                           ! Failure: -1

END SUBROUTINE h5pget_class_name_f

```

**Name:** H5Pget\_class\_parent

**Signature:**

*hid\_t* H5Pget\_class\_parent(*hid\_t* pcid)

**Purpose:**

Retrieves the parent class of a property class.

**Description:**

H5Pget\_class\_parent retrieves an identifier for the parent class of a property class.

**Parameters:**

*hid\_t* pcid      IN: Identifier of the property class to query

**Returns:**

Success: a valid parent class object identifier

Failure: a negative value

**Fortran90 Interface:** h5pget\_class\_parent\_f

```
SUBROUTINE h5pget_class_parent_f(prp_id, parent_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER(HID_T), INTENT(OUT) :: parent_id ! Parent class property list
                                           ! identifier
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_class_parent_f
```

**Name:** H5Pget\_copy\_object

**Signature:**

```
herr_t H5Pget_copy_object(hid_t ocp_plist_id, unsigned *copy_options )
```

**Purpose:**

Retrieves the properties to be used when an object is copied.

**Description:**

H5Pget\_copy\_object retrieves the properties currently specified in the object copy property list ocp\_plist\_id, which will be invoked when a new copy is made of an existing object.

copy\_options is a bit map indicating the flags, or properties, governing object copying that are set in the property list ocp\_plist\_id.

The available flags are described in H5Pset\_copy\_object.

**Parameters:**

<i>hid_t</i> ocp_plist_id	Object copy property list identifier
<i>unsigned</i> *copy_options	Copy option(s) set in the object copy property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_copy\_object\_f

```
SUBROUTINE h5pset_copy_object_f(ocp_plist_id, copy_options, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: ocp_plist_id
                                ! Object copy property list identifier
  INTEGER, INTENT(IN) :: copy_options ! Copy option(s) to be set:
                                !   H5O_COPY_SHALLOW_HIERARCHY_F
                                !   H5O_COPY_EXPAND_SOFT_LINK_F
                                !   H5O_COPY_EXPAND_EXT_LINK_F
                                !   H5O_COPY_EXPAND_REFERENCE_F
                                !   H5O_COPY_WITHOUT_ATTR_FLAG_F
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_copy_object_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pget\_create\_intermediate\_group

**Signature:**

```
herr_t H5Pget_create_intermediate_group( hid_t lcpl_id, unsigned
    *crt_intermed_group )
```

**Purpose:**

Determines whether property is set to enable creating missing intermediate groups.

**Description:**

H5Pget\_create\_intermediate\_group determines whether the link creation property list `lcpl_id` is set to allow functions that create objects in groups different from the current working group to create intermediate groups that may be missing in the path of a new or moved object.

Functions that create objects in or move objects to a group other than the current working group make use of this property. H5Gcreate\_anon and H5Lmove are examples of such functions.

If `crt_intermed_group` is true, missing intermediate groups will be created; if `crt_intermed_group` is false, missing intermediate groups will *not* be created.

**Parameters:**

<i>hid_t</i> lcpl_id	Link creation property list identifier
<i>unsigned</i> *crt_intermed_group	Flag specifying whether to create intermediate groups upon creation of an object

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.



**Name:** H5Pget\_data\_transform

**Signature:**

```
ssize_t H5Pget_data_transform(hid_t plist_id, char *expression, size_t size)
```

**Purpose:**

Retrieves a data transform expression.

**Description:**

H5Pget\_data\_transform retrieves the data transform expression previously set in the dataset transfer property list `plist_id` by H5Pset\_data\_transform.

H5Pget\_data\_transform can be used to both retrieve the transform expression and to query its size.

If `expression` is non-NULL, up to `size` bytes of the data transform expression are written to the buffer. If `expression` is NULL, `size` is ignored and the function does not write anything to the buffer. The function always returns the size of the data transform expression.

If 0 is returned for the size of the expression, no data transform expression exists for the property list.

If an error occurs, the buffer pointed to by `expression` is unchanged and the function returns a negative value.

**Parameters:**

<code>hid_t plist_id</code>	IN: Identifier of the property list or class
<code>char *expression</code>	OUT: Pointer to memory where the transform expression will be copied
<code>size_t size</code>	IN: Number of bytes of the transform expression to copy to

**Returns:**

Success: size of the transform expression.

Failure: a negative value.

**Fortran90 Interface:** h5pget\_data\_transform\_f

```
SUBROUTINE h5pget_data_transform_f(plist_id, expression, hdferr, size)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id
                                ! Identifier of the property list or class
  CHARACTER(LEN=*), INTENT(OUT) :: expression
                                ! Buffer to hold transform expression
  INTEGER(SIZE_T), INTENT(OUT), OPTIONAL :: size
                                ! Registered size for transform expression
  INTEGER, INTENT(OUT) :: hdferr  ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pget_data_transform_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pget\_driver

**Signature:**

```
hid_t H5Pget_driver( hid_t plist_id )
```

**Purpose:**

Returns low-level driver identifier.

**Description:**

H5Pget\_driver returns the identifier of the low-level file driver associated with the file access property list or data transfer property list `plist_id`.

Valid driver identifiers with the standard HDF5 library distribution include the following:

```
H5FD_CORE
H5FD_DIRECT
H5FD_FAMILY
H5FD_LOG
H5FD_MPIO
H5FD_MULTI
H5FD_SEC2
H5FD_STDIO
H5FD_WINDOWS (Windows only)
```

If a user defines and registers custom drivers or if additional drivers are defined in an HDF5 distribution, this list will be longer.

The Windows driver, H5FD\_WINDOWS, is available only on Windows systems.

The returned driver identifier is only valid as long as the file driver remains registered.

**Parameters:**

`hid_t plist_id`      IN: File access or data transfer property list identifier.

**Returns:**

Returns a valid low-level driver identifier if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_driver\_f

```
SUBROUTINE h5pget_driver_f(prp_id, driver, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: driver      ! Low-level file driver identifier
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pget_driver_f
```

**History:**

**Release    C**

1.4.0      Function introduced in this release.

**Name:** H5Pget\_driver\_info

**Signature:**

```
void *H5Pget_driver_info( hid_t plist_id )
```

**Purpose:**

Returns a pointer to file driver information.

**Description:**

H5Pget\_driver\_info returns a pointer to file driver-specific information for the low-level driver associated with the file access or data transfer property list `plist_id`.

The pointer returned by this function points to an “uncopied” struct. Driver-specific versions of that struct are defined for each low-level driver in the relevant source code file `H5FD*.c`. For example, the struct used for the MULTI driver is `H5FD_multi_fapl_t` defined in `H5FDmulti.c`.

If no driver-specific properties have been registered, H5Pget\_driver\_info returns NULL.

**Note:**

H5Pget\_driver\_info and H5Pset\_driver are used only when creating a virtual file driver (VFD) in the virtual file layer (VFL). For further information, see “Virtual File Layer” and “List of VFL Functions” in the *HDF5 Technical Notes*.

**Parameters:**

`hid_t plist_id`

IN: File access or data transfer property list identifier.

**Returns:**

Returns a pointer to a struct containing low-level driver information. Otherwise returns NULL.

NULL is also returned if no driver-specific properties have been registered. No error is pushed on the stack in this case.

**Non-C API(s):**

None.

**History:**

Release	C
1.8.2	Function publicized in this release; previous releases described this function only in the virtual file driver documentation.

**Name:** H5Pget\_dxpl\_mpio

**Signature:**

```
herr_t H5Pget_dxpl_mpio( hid_t dxpl_id, H5FD_mpio_xfer_t *xfer_mode )
```

**Purpose:**

Returns the data transfer mode.

**Description:**

H5Pget\_dxpl\_mpio queries the data transfer mode currently set in the data transfer property list dxpl\_id.

Upon return, xfer\_mode contains the data transfer mode, if it is non-null.

H5Pget\_dxpl\_mpio is not a collective function.

**Parameters:**

<i>hid_t</i> dxpl_id	IN: Data transfer property list identifier.
<i>H5FD_mpio_xfer_t</i> *xfer_mode	OUT: Data transfer mode.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_dxpl\_mpio\_f

```
SUBROUTINE h5pget_dxpl_mpio_f(prp_id, data_xfer_mode, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER, INTENT(OUT) :: data_xfer_mode    ! Data transfer mode
                                           ! Possible values are:
                                           !   H5FD_MPIO_INDEPENDENT_F
                                           !   H5FD_MPIO_COLLECTIVE_F
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_dxpl_mpio_f
```

**History:**

<b>Release</b>	<b>C</b>
1.4.0	Function introduced in this release.

**Name:** H5Pget\_dxpl\_multi

**Signature:**

*herr\_t* H5Pget\_dxpl\_multi( *hid\_t* dxpl\_id, *const hid\_t* \*memb\_dxpl )

**Purpose:**

Returns multi-file data transfer property list information.

**Description:**

H5Pget\_dxpl\_multi returns the data transfer property list information for the multi-file driver.

**Parameters:**

<i>hid_t</i> dxpl_id,	IN: Data transfer property list identifier.
<i>const hid_t</i> *memb_dxpl	OUT: Array of data access property lists.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.4.0	Function introduced in this release.

**Name:** H5Pget\_edc\_check

**Signature:**

*H5Z\_EDC\_t* H5Pget\_edc\_check(*hid\_t* plist)

**Purpose:**

Determines whether error-detection is enabled for dataset reads.

**Description:**

H5Pget\_edc\_check queries the dataset transfer property list *plist* to determine whether error detection is enabled for data read operations.

**Parameters:**

*hid\_t* plist      IN: Dataset transfer property list identifier.

**Returns:**

Returns H5Z\_ENABLE\_EDC or H5Z\_DISABLE\_EDC if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_edc\_check\_f

```
SUBROUTINE h5pget_edc_check_f(prp_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Dataset transfer property list
                                     ! identifier
  INTEGER, INTENT(OUT)      :: flag    ! EDC flag; possible values
                                     !   H5Z_DISABLE_EDC_F
                                     !   H5Z_ENABLE_EDC_F
  INTEGER, INTENT(OUT)      :: hdferr ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5pget_edc_check_f
```

**History:**

**Release    C**

1.6.0      Function introduced in this release.

*Last modified: 8 May 2009***Name:** H5Pget\_elink\_acc\_flags**Signature:**

```
herr_t H5Pget_elink_acc_flags( hid_t lapl_id, unsigned *flags )
```

**Purpose:**

Retrieves the external link traversal file access flag from the specified link access property list.

**Description:**

H5Pget\_elink\_acc\_flags retrieves the file access flag used to open an external link target file from the specified link access property list.

The value returned, if it is not H5F\_ACC\_DEFAULT will override the default access flag, which is the access flag used to open the parent file.

**Parameters:**

<i>hid_t</i> lapl_id	IN: Link access property list identifier
<i>unsigned</i> *flags	OUT: File access flag for link traversal.

Valid values include:

H5F_ACC_RDWR	Files opened through external links will be opened with write access.
H5F_ACC_RDONLY	Files opened through external links will be opened with read-only access.
H5F_ACC_DEFAULT	Files opened through external links will be opened with the same access flag as the parent file.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Example Usage:**

The following code retrieves the external link access flag settings on the link access property list lapl\_id into a local variable:

```
unsigned acc_flags;
status = H5Pget_elink_acc_flags(lapl_id, &acc_flags);
```

**See Also:**

H5Pset\_elink\_acc\_flags

**History:**

Release	Change
1.8.3	C function introduced in this release.

*Last modified: 8 May 2009***Name:** H5Pget\_elink\_cb**Signature:**

```
herr_t H5Pget_elink_cb( hid_t lapl_id, H5L_elink_traverse_t **func, void **op_data )
```

**Purpose:**

Retrieves the external link traversal callback function from the specified link access property list.

**Description:**

H5Pget\_elink\_cb retrieves the user-defined external link traversal callback function defined in the specified link access property list.

The callback function may adjust the file access property list and file access flag to use when opening a file through an external link. The callback will be made immediately before opening the target file.

**Parameters:**

<i>hid_t</i> lapl_id	IN: Link access property list identifier.
<i>H5L_elink_traverse_t</i> **func	OUT: User-defined external link traversal callback function.
<i>void</i> **op_data	OUT: User-defined input data for the callback function.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Example Usage:**

The following code retrieves the external link callback settings on the link access property list lapl\_id into local variables:

```
H5L_elink_traverse_t *elink_callback_func;
void *elink_callback_udata;
status = H5Pget_elink_cb(lapl_id, &elink_callback_func, &elink_callback_udata);
```

**See Also:**

H5Pset\_elink\_cb,

H5L\_elink\_traverse\_t

**History:**

Release	Change
1.8.3	C function introduced in this release.



**Name:** H5Pget\_elink\_fapl

**Signature:**

*hid\_t* H5Pget\_elink\_fapl( *hid\_t* lapl\_id )

**Purpose:**

Retrieves the file access property list identifier associated with the link access property list.

**Description:**

H5Pget\_elink\_fapl retrieves the file access property list identifier that is set for the link access property list identifier, *lapl\_id*. The library uses this file access property list identifier to open the target file for the external link access.

When no such identifier is set, this routine returns H5P\_DEFAULT.

See also H5Pset\_elink\_fapl and H5Lcreate\_external.

**Parameters:**

*hid\_t* lapl\_id      IN: Link access property list identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.2	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Pget\_elink\_prefix

**Signature:**

```
ssize_t H5Pget_elink_prefix( hid_t lapl_id, char *prefix, size_t size )
```

**Purpose:**

Retrieves prefix applied to external link paths.

**Description:**

H5Pget\_elink\_prefix retrieves the prefix applied to the path of any external links traversed.

When an external link is traversed, the prefix is retrieved from the link access property list `lapl_id`, returned in the user-allocated buffer pointed to by `prefix`, and prepended to the filename stored in the external link.

The size in bytes of the prefix, including the NULL terminator, is specified in `size`. If `size` is unknown, a preliminary H5Pget\_elink\_prefix call with the pointer `prefix` set to NULL will return the size of the prefix *without* the NULL terminator.

**Parameters:**

<code>hid_t lapl_id</code>	IN: Link access property list identifier
<code>char *prefix</code>	OUT: Prefix applied to external link paths
<code>size_t size</code>	IN: Size of prefix, including null terminator

**Returns:**

If successful, returns a non-negative value specifying the size in bytes of the prefix *without* the NULL terminator; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pget\_est\_link\_info

**Signature:**

```
herr_t H5Pget_est_link_info(hid_t gcpl_id, unsigned *est_num_entries, unsigned
*est_name_len)
```

**Purpose:**

Queries data required to estimate required local heap or object header size.

**Description:**

H5Pget\_est\_link\_info queries a group creation property list, *gcpl\_id*, for its “estimated number of links” and “estimated average name length” settings.

The estimated number of links anticipated to be inserted into a group created with this property list is returned in *est\_num\_entries*.

The estimated average length of the anticipated link names is returned in *est\_name\_len*.

The values for these two settings are multiplied to compute the initial local heap size (for old-style groups, if the local heap size hint is not set) or the initial object header size for (new-style compact groups; see “Group implementations in HDF5”). Accurately setting these parameters will help reduce wasted file space.

A value of 0 (zero) in *est\_num\_entries* will prevent a group from being created in the compact format.

See “Group implementations in HDF5” in the H5G API introduction for a discussion of the available types of HDF5 group structures.

**Parameters:**

<i>hid_t</i> gcpl_id	IN: Group creation property list identifier
<i>unsigned</i> *est_num_entries	OUT: Estimated number of links to be inserted into group
<i>unsigned</i> *est_name_len	OUT: Estimated average length of link names

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_est\_link\_info\_f

```
SUBROUTINE h5pget_est_link_info_f(gcpl_id,est_num_entries, est_name_len,hdferr)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: gcpl_id      ! Group creation property list id
  INTEGER, INTENT(OUT) :: est_num_entries    ! Estimated number of links to be
                                              ! inserted into group
  INTEGER, INTENT(OUT) :: est_name_len       ! Estimated average length of link
                                              ! names
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5pget_est_link_info_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pget\_external

**Signature:**

```
herr_t H5Pget_external(hid_t plist, unsigned idx, size_t name_size, char *name, off_t
*offset, hsize_t *size)
```

**Purpose:**

Returns information about an external file.

**Description:**

H5Pget\_external returns information about an external file. The external file is specified by its index, `idx`, which is a number from zero to `N-1`, where `N` is the value returned by `H5Pget_external_count`. At most `name_size` characters are copied into the name array. If the external file name is longer than `name_size` with the null terminator, the return value is not null terminated (similar to `strncpy()`).

If `name_size` is zero or `name` is the null pointer, the external file name is not returned. If `offset` or `size` are null pointers then the corresponding information is not returned.

**Parameters:**

<code>hid_t plist</code>	IN: Identifier of a dataset creation property list.
<code>unsigned idx</code>	IN: External file index.
<code>size_t name_size</code>	IN: Maximum length of name array.
<code>char *name</code>	OUT: Name of the external file.
<code>off_t *offset</code>	OUT: Pointer to a location to return an offset value.
<code>hsize_t *size</code>	OUT: Pointer to a location to return the size of the external file data.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_external\_f

```
SUBROUTINE h5pget_external_f(prp_id, idx, name_size, name, offset, bytes, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER, INTENT(IN) :: idx                ! External file index.
  INTEGER(SIZE_T), INTENT(IN) :: name_size ! Maximum length of name array
  CHARACTER(LEN=*), INTENT(OUT) :: name    ! Name of an external file
  INTEGER, INTENT(OUT) :: offset            ! Offset, in bytes, from the
                                           ! beginning of the file to the
                                           ! location in the file where
                                           ! the data starts.
  INTEGER(HSIZE_T), INTENT(OUT) :: bytes    ! Number of bytes reserved in
                                           ! the file for the data
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_external_f
```

**History:**

Release	C
1.6.4	<code>idx</code> parameter type changed to <i>unsigned</i> .

**Name:** H5Pget\_external\_count

**Signature:**

*int* H5Pget\_external\_count(*hid\_t* plist)

**Purpose:**

Returns the number of external files for a dataset.

**Description:**

H5Pget\_external\_count returns the number of external files for the specified dataset.

**Parameters:**

*hid\_t* plist      IN: Identifier of a dataset creation property list.

**Returns:**

Returns the number of external files if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_external\_count\_f

```
SUBROUTINE h5pget_external_count_f (prp_id, count, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: count       ! Number of external files for
                                     ! the specified dataset
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5pget_external_count_f
```

**Name:** H5Pget\_family\_offset

**Signature:**

```
herr_t H5Pget_family_offset ( hid_t fapl_id, hsize_t *offset )
```

**Purpose:**

Retrieves a data offset from the file access property list.

**Description:**

H5Pget\_family\_offset retrieves the value of `offset` from the file access property list `fapl_id` so that the user application can retrieve a file handle for low-level access to a particular member of a family of files. The file handle is retrieved with a separate call to H5Fget\_vfd\_handle (or, in special circumstances, to H5FDget\_vfd\_handle; see *Virtual File Layer* and *List of VFL Functions* in *HDF5 Technical Notes*).

The data offset returned in `offset` is the offset of the data in the HDF5 file that is stored on disk in the selected member file in a family of files.

Use of this function is only appropriate for an HDF5 file written as a family of files with the FAMILY file driver.

**Parameters:**

<code>hid_t fapl_id</code>	IN: File access property list identifier.
<code>hsize_t *offset</code>	OUT: Offset in bytes within the HDF5 file.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.0	Function introduced in this release.

**Name:** H5Pget\_fapl\_core

**Signature:**

```
herr_t H5Pget_fapl_core( hid_t fapl_id, size_t *increment, hbool_t *backing_store )
```

**Purpose:**

Queries core file driver properties.

**Description:**

H5Pget\_fapl\_core queries the H5FD\_CORE driver properties as set by H5Pset\_fapl\_core.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>size_t</i> *increment	OUT: Size, in bytes, of memory increments.
<i>hbool_t</i> *backing_store	OUT: Boolean flag indicating whether to write the file contents to disk when the file is closed.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_fapl\_core\_f

```
SUBROUTINE h5pget_fapl_core_f(prp_id, increment, backing_store, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER(SIZE_T), INTENT(OUT) :: increment ! File block size in bytes
  LOGICAL, INTENT(OUT) :: backing_store    ! Flag to indicate that entire
                                           ! file contents are flushed to
                                           ! a file with the same name as
                                           ! this core file
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_fapl_core_f
```

**History:**

Release	C	Fortran90
1.6.0		The backing_store parameter type changed from <i>INTEGER</i> to <i>LOGICAL</i> to better match the C API
1.4.0	Function introduced in this release.	

**Name:** H5Pget\_fapl\_direct

**Signature:**

```
herr_t H5Pget_fapl_direct(hid_t fapl_id, size_t *alignment, size_t *block_size, size_t *cbuf_size)
```

**Purpose:**

Retrieves direct I/O driver settings.

**Description:**

H5Pget\_fapl\_direct retrieves the required memory alignment (*alignment*), file system block size (*block\_size*), and copy buffer size (*cbuf\_size*) settings for the direct I/O driver, H5FD\_DIRECT, from the file access property list *fapl\_id*.

See H5Pset\_fapl\_direct for discussion of these values, requirements, and important considerations.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier
<i>size_t</i> *alignment	OUT: Required memory alignment boundary
<i>size_t</i> *block_size	OUT: File system block size
<i>size_t</i> *cbuf_size	OUT: Copy buffer size

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

```
SUBROUTINE H5Pget_fapl_direct_f(fapl_id, alignment, block_size, cbuf_size, &
                                hdferr)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: fapl_id ! File access property list identifier
    INTEGER(SIZE_T), INTENT(OUT) :: alignment
                                   ! Required memory alignment boundary!
    INTEGER(SIZE_T), INTENT(OUT) :: block_size
                                   ! File system block size
    INTEGER(SIZE_T), INTENT(OUT) :: cbuf_size
                                   ! Copy buffer size
    INTEGER, INTENT(OUT) :: hdferr
                                   ! Error code
                                   ! 0 on success and -1 on failure
END SUBROUTINE H5Pget_fapl_direct_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.



**Name:** H5Pget\_fapl\_family

**Signature:**

```
herr_t H5Pget_fapl_family ( hid_t fapl_id, hsize_t *memb_size, hid_t *memb_fapl_id )
```

**Purpose:**

Returns file access property list information.

**Description:**

H5Pget\_fapl\_family returns file access property list for use with the family driver. This information is returned through the output parameters.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>hsize_t</i> *memb_size	OUT: Size in bytes of each file member.
<i>hid_t</i> *memb_fapl_id	OUT: Identifier of file access property list for each family member.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_fapl\_family\_f

```
SUBROUTINE h5pget_fapl_family_f(prp_id, imemb_size, memb_plist, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)      :: prp_id      ! Property list identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: memb_size ! Logical size, in bytes,
                                           ! of each family member
  INTEGER(HID_T), INTENT(OUT) :: memb_plist ! Identifier of the file
                                           ! access property list to be
                                           ! used for each family member
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_fapl_family_f
```

**History:**

<b>Release</b>	<b>C</b>
1.4.0	Function introduced in this release.

*Last modified: 15 May 2009***Name:** H5Pget\_fapl\_mpio**Signature:**

```
herr_t H5Pget_fapl_mpio( hid_t fapl_id, MPI_Comm *comm, MPI_Info *info )
```

**Purpose:**

Returns MPI communicator information.

**Description:**

If the file access property list is set to the H5FD\_MPIO driver, H5Pget\_fapl\_mpio returns duplicates of the stored MPI communicator and Info object through the `comm` and `info` pointers, if those values are non-null.

Since the MPI communicator and Info object are duplicates of the stored information, future modifications to the access property list will not affect them. It is the responsibility of the application to free these objects.

**Parameters:**

<code>hid_t fapl_id</code>	IN: File access property list identifier
<code>MPI_Comm *comm</code>	OUT: MPI-2 communicator
<code>MPI_Info *info</code>	OUT: MPI-2 Info object

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_fapl\_mpio\_f

```
SUBROUTINE h5pget_fapl_mpio_f(prp_id, comm, info, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: comm        ! Buffer to return communicator
  INTEGER, INTENT(IN) :: info         ! Buffer to return info object as
                                      ! defined in MPI_FILE_OPEN of MPI-2
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pget_fapl_mpio_f
```

**History:**

Release	Change
1.4.5	Handling of the MPI Communicator and Info object changed at this release. A duplicate of each of these objects is now returned instead of pointers to each object.
1.4.0	C function introduced in this release.

**Name:** H5Pget\_fapl\_mpiposix

**Signature:**

```
herr_t H5Pget_fapl_mpiposix(hid_t fapl_id, MPI_Comm *comm, hbool_t
    *use_gpfs_hints)
```

**Purpose:**

Returns MPI communicator information.

**Description:**

If the file access property list is set to the H5FD\_MPIO driver, H5Pget\_fapl\_mpiposix returns the MPI communicator through the comm pointer, if those values are non-null.

comm is not copied, so it is valid only until the file access property list is either modified or closed.

use\_gpfs\_hints specifies whether to attempt to use GPFS hints when accessing this file. A value of TRUE (or 1) indicates that the hints are being used, where possible. A value of FALSE (or 0) indicates that the hints are not being used.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>MPI_Comm</i> *comm	OUT: MPI-2 communicator.
<i>hbool_t</i> *use_gpfs_hints	OUT: Use of GPFS hints.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_fapl\_mpiposix\_f

```
SUBROUTINE h5pget_fapl_mpiposix_f(prp_id, comm, use_gpfs, hdferr)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
    INTEGER, INTENT(OUT) :: comm ! Buffer to return communicator
    LOGICAL, INTENT(OUT) :: use_gpfs
    INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5pget_fapl_mpiposix_f
```

**History:**

Release	C	Fortran90
1.6.1		Fortran subroutine introduced in this release.
1.6.0	use_gpfs_hints parameter added.	
1.6.0	Function introduced in this release.	

**Name:** H5Pget\_fapl\_multi

**Signature:**

```
herr_t H5Pget_fapl_multi(hid_t fapl_id, const H5FD_mem_t *memb_map, const hid_t
*memb_fapl, const char **memb_name, const haddr_t *memb_addr, hbool_t *relax)
```

**Purpose:**

Returns information about the multi-file access property list.

**Description:**

H5Pget\_fapl\_multi returns information about the multi-file access property list.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>const H5FD_mem_t</i> *memb_map	OUT: Maps memory usage types to other memory usage types.
<i>const hid_t</i> *memb_fapl	OUT: Property list for each memory usage type.
<i>const char</i> **memb_name	OUT: Name generator for names of member files.
<i>const haddr_t</i> *memb_addr	OUT: The offsets within the virtual address space, from 0 (zero) to HADDR_MAX, at which each type of data storage begins.
<i>hbool_t</i> *relax	OUT: Allows read-only access to incomplete file sets when TRUE.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_fapl\_multi\_f

```
SUBROUTINE h5pget_fapl_multi_f(prp_id, memb_map, memb_fapl, memb_name,
                               memb_addr, relax, hdferr)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)    :: prp_id      ! Property list identifier

  INTEGER, DIMENSION(0:H5FD_MEM_NTYPES_F-1), INTENT(OUT) :: memb_map
  INTEGER(HID_T), DIMENSION(0:H5FD_MEM_NTYPES_F-1), INTENT(OUT) :: memb_fapl
  CHARACTER(LEN=*) , DIMENSION(0:H5FD_MEM_NTYPES_F-1), INTENT(OUT) :: memb_name
  REAL, DIMENSION(0:H5FD_MEM_NTYPES_F-1), INTENT(OUT) :: memb_addr
      ! Numbers in the interval [0,1) (e.g. 0.0 0.1 0.5 0.2 0.3 0.4)
      ! real address in the file will be calculated as X*HADDR_MAX

  LOGICAL, INTENT(OUT) :: relax
  INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                              ! 0 on success and -1 on failure

END SUBROUTINE h5pget_fapl_multi_f
```

**History:**

<b>Release</b>	<b>C</b>
1.4.0	Function introduced in this release.

**Name:** H5Pget\_fcclose\_degree

**Signature:**

*herr\_t* H5Pget\_fcclose\_degree(*hid\_t* fapl\_id, *H5F\_close\_degree\_t* \*fc\_degree)

**Purpose:**

Returns the file close degree.

**Description:**

H5Pget\_fcclose\_degree returns the current setting of the file close degree property *fc\_degree* in the file access property list *fapl\_id*.

The value of *fc\_degree* determines how aggressively H5Fclose deals with objects within a file that remain open when H5Fclose is called to close that file. *fc\_degree* can have any one of four valid values as described in H5Pset\_fcclose\_degree.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>H5F_close_degree_t</i> *fc_degree	OUT: Pointer to a location to which to return the file close degree property, the value of <i>fc_degree</i> .

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_fcclose\_degree\_f

```

SUBROUTINE h5pget_fcclose_degree_f(fapl_id, degree, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: fapl_id ! File access property list identifier
  INTEGER, INTENT(OUT) :: degree        ! Info about file close behavior
                                          ! Possible values:
                                          !   H5F_CLOSE_DEFAULT_F
                                          !   H5F_CLOSE_WEAK_F
                                          !   H5F_CLOSE_SEMI_F
                                          !   H5F_CLOSE_STRONG_F
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pget_fcclose_degree_f

```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Pget\_fill\_time

**Signature:**

```
herr_t H5Pget_fill_time(hid_t plist_id, H5D_fill_time_t *fill_time)
```

**Purpose:**

Retrieves the time when fill value are written to a dataset.

**Description:**

H5Pget\_fill\_time examines the dataset creation property list `plist_id` to determine when fill values are to be written to a dataset.

Valid values returned in `fill_time` are as follows:

H5D_FILL_TIME_IFSET	Fill values are written to the dataset when storage space is allocated only if there is a user-defined fill value, i.e., one set with H5Pset_fill_value. (Default)
H5D_FILL_TIME_ALLOC	Fill values are written to the dataset when storage space is allocated.
H5D_FILL_TIME_NEVER	Fill values are never written to the dataset.

**Note:**

H5Pget\_fill\_time is designed to work in coordination with the dataset fill value and dataset storage allocation time properties, retrieved with the functions H5Pget\_fill\_value and H5Pget\_alloc\_time.

**Parameters:**

<i>hid_t</i> plist_id	IN: Dataset creation property list identifier.
<i>H5D_fill_time_t</i> *fill_time	OUT: Setting for the timing of writing fill values to the dataset.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_fill\_time\_f

```
SUBROUTINE h5pget_fill_time_f(plist_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! Dataset creation property
                                          ! list identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: flag ! Fill time flag
                                          ! Possible values are:
                                          !   H5D_FILL_TIME_ERROR_F
                                          !   H5D_FILL_TIME_ALLOC_F
                                          !   H5D_FILL_TIME_NEVER_F
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pget_fill_time_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Pget\_fill\_value

**Signature:**

```
herr_t H5Pget_fill_value(hid_t plist_id, hid_t type_id, void *value)
```

**Purpose:**

Retrieves a dataset fill value.

**Description:**

H5Pget\_fill\_value returns the dataset fill value defined in the dataset creation property list `plist_id`.

The fill value is returned through the `value` pointer and will be converted to the datatype specified by `type_id`. This datatype may differ from the fill value datatype in the property list, but the HDF5 library must be able to convert between the two datatypes.

If the fill value is undefined, i.e., set to NULL in the property list, H5Pget\_fill\_value will return an error. H5Pfill\_value\_defined should be used to check for this condition before H5Pget\_fill\_value is called.

Memory must be allocated by the calling application.

**Note:**

H5Pget\_fill\_value is designed to coordinate with the dataset storage allocation time and fill value write time properties, which can be retrieved with the functions H5Pget\_alloc\_time and H5Pget\_fill\_time, respectively.

**Parameters:**

<code>hid_t plist_id</code>	IN: Dataset creation property list identifier.
<code>hid_t type_id,</code>	IN: Datatype identifier for the value passed via <code>value</code> .
<code>void *value</code>	OUT: Pointer to buffer to contain the returned fill value.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_fill\_value\_f

```
SUBROUTINE h5pget_fill_value_f(prp_id, type_id, fillvalue, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier of fill
                                     ! value datatype (in memory)
  TYPE(VOID), INTENT(IN) :: fillvalue ! Fillvalue
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure

END SUBROUTINE h5pget_fill_value_f
```

**Name:** H5Pget\_filter

**Signatures:**

*H5Z\_filter\_t* H5Pget\_filter( *hid\_t* plist, *unsigned int* idx, [1]  
*unsigned int* \*flags, *size\_t* \*cd\_nelmts, *unsigned int* \*cd\_values,  
*size\_t* namelen, *char* name[ ] )

*H5Z\_filter\_t* H5Pget\_filter( *hid\_t* plist\_id, *unsigned int* idx, [2]  
*unsigned int* \*flags, *size\_t* \*cd\_nelmts, *unsigned int* \*cd\_values[ ],  
*size\_t* namelen, *char* name[ ], *unsigned int* \*filter\_config )

**Purpose:**

Returns information about a filter in a pipeline.

**Description:**

H5Pget\_filter is a macro that is mapped to either H5Pget\_filter1 or H5Pget\_filter2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. For example:

- ◊ The H5Pget\_filter macro will be mapped to H5Pget\_filter1 and will use the H5Pget\_filter1 syntax (first signature above) if an application is coded for HDF5 Release 1.6.x.
- ◊ The H5Pget\_filter macro mapped to H5Pget\_filter2 and will use the H5Pget\_filter2 syntax (second signature above) if an application is coded for HDF5 Release 1.8.x.

Macro use and mappings are fully described in “API Compatibility Macros in HDF5” we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Pget\_filter is mapped to the most recent version of the function, currently H5Pget\_filter2. If the library and/or application is compiled for Release 1.6 emulation, H5Pget\_filter will be mapped to H5Pget\_filter1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Pget_filter mapping
<u>Global settings</u>	
No compatibility flag	H5Pget_filter2
Enable deprecated symbols	H5Pget_filter2
Disable deprecated symbols	H5Pget_filter2
Emulate Release 1.6 interface	H5Pget_filter1



---

**Function-level macros**

```
H5Pget_filter_vers = 2      H5Pget_filter2
```

```
H5Pget_filter_vers = 1      H5Pget_filter1
```

**Interface history:** Signature [1] above is the original H5Pget\_filter interface and the only interface available prior to HDF5 Release 1.8.0. This signature and the corresponding function are now deprecated but will remain directly callable as H5Pget\_filter1.

Signature [2] above was introduced with HDF5 Release 1.8.0 and is the recommended and default interface. It is directly callable as H5Pget\_filter2.

See “API Compatibility Macros in HDF5” for circumstances under which either of these functions might not be available in an installed instance of the HDF5 Library.

**Fortran90 Interface: h5pget\_filter\_f**

```
SUBROUTINE h5pget_filter_f(prp_id, filter_number, flags, cd_nelmts,
                          cd_values, namelen, name, filter_id, hdferr)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER, INTENT(IN) :: filter_number      ! Sequence number within the filter
                                              ! pipeline of the filter for which
                                              ! information is sought
  INTEGER, DIMENSION(*), INTENT(OUT) :: cd_values
                                              ! Auxiliary data for the filter
  INTEGER, INTENT(OUT) :: flags              ! Bit vector specifying certain
                                              ! general properties of the filter
  INTEGER(SIZE_T), INTENT(INOUT) :: cd_nelmts
                                              ! Number of elements in cd_values
  INTEGER(SIZE_T), INTENT(IN) :: namelen    ! Anticipated number of characters
                                              ! in name
  CHARACTER(LEN=*), INTENT(OUT) :: name     ! Name of the filter
  INTEGER, INTENT(OUT) :: filter_id         ! Filter identification number
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                              ! 0 on success and -1 on failure

END SUBROUTINE h5pget_filter_f
```

**History:**

Release	C
1.8.0	The function H5Pget_filter renamed to H5Pget_filter1 and deprecated in this release. The macro H5Pget_filter and the function H5Pget_filter2 introduced in this release.

**Name:** H5Pget\_filter1

**Signature:**

```
H5Z_filter_t H5Pget_filter1( hid_t plist, unsigned int idx, unsigned int *flags, size_t
*cd_nelmts, unsigned int *cd_values, size_t namelen, char name[ ] )
```

**Purpose:**

Returns information about a filter in a pipeline.

**Notice:**

*This function is renamed from H5Pget\_filter and deprecated in favor of the function H5Pget\_filter2 or the new macro H5Pget\_filter.*

**Description:**

H5Pget\_filter1 returns information about a filter, specified by its filter number, in a filter pipeline, specified by the property list with which it is associated.

If `plist` is a dataset creation property list, the pipeline is a permanent filter pipeline; if `plist` is a dataset transfer property list, the pipeline is a transient filter pipeline.

`idx` is a value between zero and  $N-1$ , as described in `H5Pget_nfilters`. The function will return a negative value if the filter number is out of range.

The structure of the `flags` argument is discussed in `H5Pset_filter`.

On input, `cd_nelmts` indicates the number of entries in the `cd_values` array, as allocated by the caller; on return, `cd_nelmts` contains the number of values defined by the filter.

If `name` is a pointer to an array of at least `namelen` bytes, the filter name will be copied into that array. The name will be null terminated if `namelen` is large enough. The filter name returned will be the name appearing in the file, the name registered for the filter, or an empty string.

**Note:**

This function currently supports only the permanent filter pipeline; `plist` must be a dataset creation property list.

**Parameters:**

<code>hid_t plist</code>	IN: Property list identifier.
<code>int idx</code>	IN: Sequence number within the filter pipeline of the filter for which information is sought.
<code>unsigned int *flags</code>	OUT: Bit vector specifying certain general properties of the filter.
<code>size_t *cd_nelmts</code>	IN/OUT: Number of elements in <code>cd_values</code> .
<code>unsigned int *cd_values</code>	OUT: Auxiliary data for the filter.
<code>size_t namelen</code>	IN: Anticipated number of characters in <code>name</code> .
<code>char name[ ]</code>	OUT: Name of the filter.

**Returns:**

Returns the filter identifier if successful:

H5Z_FILTER_DEFLATE	Data compression filter, employing the gzip algorithm
H5Z_FILTER_SHUFFLE	Data shuffling filter
H5Z_FILTER_FLETCHER32	Error detection filter, employing the Fletcher32 checksum algorithm
H5Z_FILTER_SZIP	Data compression filter, employing the SZIP algorithm
H5Z_FILTER_NBIT	Data compression filter, employing the N-bit algorithm
H5Z_FILTER_SCALEOFFSET	Data compression filter, employing the scale-offset algorithm

Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_filter\_f

```

SUBROUTINE h5pget_filter_f(prp_id, filter_number, flags, cd_nelmts,
                          cd_values, namelen, name, filter_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER, INTENT(IN) :: filter_number     ! Sequence number within the filter
                                           ! pipeline of the filter for which
                                           ! information is sought
  INTEGER, DIMENSION(*), INTENT(OUT) :: cd_values
                                           ! Auxiliary data for the filter
  INTEGER, INTENT(OUT) :: flags             ! Bit vector specifying certain
                                           ! general properties of the filter
  INTEGER(SIZE_T), INTENT(INOUT) :: cd_nelmts
                                           ! Number of elements in cd_values
  INTEGER(SIZE_T), INTENT(IN) :: namelen    ! Anticipated number of characters
                                           ! in name
  CHARACTER(LEN=*), INTENT(OUT) :: name    ! Name of the filter
  INTEGER, INTENT(OUT) :: filter_id        ! Filter identification number
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_filter_f

```

**History:**

Release	C
1.6.4	filter parameter type changed to <i>unsigned</i> .
1.8.0	N-bit and scale-offset filters added.
1.8.0	Function H5Pget_filter renamed to H5Pget_filter1 and deprecated in this release.

**Name:** H5Pget\_filter2

**Signature:**

```
H5Z_filter_t H5Pget_filter2(hid_t plist_id, unsigned int idx, unsigned int *flags, size_t
*cd_nelmts, unsigned cd_values[], size_t namelen, char name[], unsigned
*filter_config)
```

**Purpose:**

Returns information about a filter in a pipeline.

**Description:**

H5Pget\_filter2 returns information about a filter, specified by its filter number, in a filter pipeline, specified by the property list with which it is associated.

If `plist` is a dataset creation property list, the pipeline is a permanent filter pipeline; if `plist` is a dataset transfer property list, the pipeline is a transient filter pipeline.

`idx` is a value between zero and  $N-1$ , as described in H5Pget\_nfilters. The function will return a negative value if the filter number is out of range.

The structure of the `flags` argument is discussed in H5Pset\_filter.

On input, `cd_nelmts` indicates the number of entries in the `cd_values` array, as allocated by the caller; on return, `cd_nelmts` contains the number of values defined by the filter.

If `name` is a pointer to an array of at least `namelen` bytes, the filter name will be copied into that array. The name will be null terminated if `namelen` is large enough. The filter name returned will be the name appearing in the file, the name registered for the filter, or an empty string.

`filter_config` is the bit field described in H5Zget\_filter\_info.

**Note:**

This function currently supports only the permanent filter pipeline; `plist` must be a dataset creation property list.

**Parameters:**

<i>hid_t</i> plist	IN: Property list identifier.
<i>int</i> idx	IN: Sequence number within the filter pipeline of the filter for which information is sought.
<i>unsigned int</i> *flags	OUT: Bit vector specifying certain general properties of the filter.
<i>size_t</i> *cd_nelmts	IN/OUT: Number of elements in <code>cd_values</code> .
<i>unsigned int</i> *cd_values	OUT: Auxiliary data for the filter.
<i>size_t</i> namelen	IN: Anticipated number of characters in <code>name</code> .
<i>char</i> name[]	OUT: Name of the filter.
<i>unsigned int</i> *filter_config	OUT: Bit field, as described in H5Zget_filter_info.

**Returns:**

Returns the filter identifier if successful:

H5Z_FILTER_DEFLATE	Data compression filter, employing the gzip algorithm
H5Z_FILTER_SHUFFLE	Data shuffling filter
H5Z_FILTER_FLETCHER32	Error detection filter, employing the Fletcher32 checksum algorithm
H5Z_FILTER_SZIP	Data compression filter, employing the SZIP algorithm
H5Z_FILTER_NBIT	Data compression filter, employing the N-bit algorithm
H5Z_FILTER_SCALEOFFSET	Data compression filter, employing the scale-offset algorithm

Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pget\_filter\_by\_id

**Signatures:**

```
herr_t H5Pget_filter_by_id(hid_t plist_id, H5Z_filter_t filter_id, unsigned int *flags, size_t *cd_nelmts, unsigned int cd_values[], size_t namelen, char name[]) [1]
```

```
herr_t H5Pget_filter_by_id(hid_t plist_id, H5Z_filter_t filter_id, unsigned int *flags, size_t *cd_nelmts, unsigned int cd_values[], size_t namelen, char name[], unsigned int *filter_config) [2]
```

**Purpose:**

Returns information about the specified filter.

**Description:**

H5Pget\_filter\_by\_id is a macro that is mapped to either H5Pget\_filter\_by\_id1 or H5Pget\_filter\_by\_id2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. For example:

- ◇ The H5Pget\_filter\_by\_id macro will be mapped to H5Pget\_filter\_by\_id1 and will use the H5Pget\_filter\_by\_id1 syntax (first signature above) if an application is coded for HDF5 Release 1.6.x.
- ◇ The H5Pget\_filter\_by\_id macro mapped to H5Pget\_filter\_by\_id2 and will use the H5Pget\_filter\_by\_id2 syntax (second signature above) if an application is coded for HDF5 Release 1.8.x.

Macro use and mappings are fully described in “API Compatibility Macros in HDF5” we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Pget\_filter\_by\_id is mapped to the most recent version of the function, currently H5Pget\_filter\_by\_id2. If the library and/or application is compiled for Release 1.6 emulation, H5Pget\_filter\_by\_id will be mapped to H5Pget\_filter\_by\_id1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Pget_filter_by_id mapping
<u>Global settings</u>	
No compatibility flag	H5Pget_filter_by_id2
Enable deprecated symbols	H5Pget_filter_by_id2
Disable deprecated symbols	H5Pget_filter_by_id2
Emulate Release 1.6 interface	H5Pget_filter_by_id1

Function-level macros

```
H5Pget_filter_by_id_vers = 2      H5Pget_filter_by_id2
```

```
H5Pget_filter_by_id_vers = 1      H5Pget_filter_by_id1
```

**Interface history:** Signature [1] above is the original H5Pget\_filter\_by\_id interface and the only interface available prior to HDF5 Release 1.8.0. This signature and the corresponding function are now deprecated but will remain directly callable as H5Pget\_filter\_by\_id1.

Signature [2] above was introduced with HDF5 Release 1.8.0 and is the recommended and default interface. It is directly callable as H5Pget\_filter\_by\_id2.

See “API Compatibility Macros in HDF5” for circumstances under which either of these functions might not be available in an installed instance of the HDF5 Library.

**Fortran90 Interface: h5pget\_filter\_by\_id\_f**

```
SUBROUTINE h5pget_filter_by_id_f(prp_id, filter_id, flags, cd_nelmts,
                                cd_values, namelen, name, hdferr)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER, INTENT(IN)       :: filter_id    ! Filter identifier
  INTEGER(SIZE_T), INTENT(INOUT) :: cd_nelmts
                                      ! Number of elements in cd_values
  INTEGER, DIMENSION(*), INTENT(OUT) :: cd_values
                                      ! Auxiliary data for the filter
  INTEGER, INTENT(OUT)       :: flags       ! Bit vector specifying certain
                                      ! general properties of the filter
  INTEGER(SIZE_T), INTENT(IN) :: namelen    ! Anticipated number of characters
                                      ! in name
  CHARACTER(LEN=*), INTENT(OUT) :: name     ! Name of the filter
  INTEGER, INTENT(OUT)       :: hdferr      ! Error code
                                      ! 0 on success and -1 on failure

END SUBROUTINE h5pget_filter_by_id_f
```

**History:**

Release	C
1.8.0	The function H5Pget_filter_by_id renamed to H5Pget_filter_by_id1 and deprecated in this release. The macro H5Pget_filter_by_id and the function H5Pget_filter_by_id2 introduced in this release.

**Name:** H5Pget\_filter\_by\_id1

**Signature:**

```
herr_t H5Pget_filter_by_id1( hid_t plist_id, H5Z_filter_t filter_id, unsigned int
    *flags, size_t *cd_nelmts, unsigned int cd_values[ ], size_t namelen, char name[ ] )
```

**Purpose:**

Returns information about the specified filter.

**Notice:**

*This function is renamed from H5Pget\_filter\_by\_id and deprecated in favor of the function H5Pget\_filter\_by\_id2 or the new macro H5Pget\_filter\_by\_id.*

**Description:**

H5Pget\_filter\_by\_id1 returns information about the filter specified in `filter_id`, a filter identifier.

`plist_id` must identify a dataset creation property list and `filter_id` will be in a permanent filter pipeline.

The `filter_id` and `flags` parameters are used in the same manner as described in the discussion of H5Pset\_filter.

Aside from the fact that they are used for output, the parameters `cd_nelmts` and `cd_values[ ]` are used in the same manner as described in the discussion of H5Pset\_filter. On input, the `cd_nelmts` parameter indicates the number of entries in the `cd_values[ ]` array allocated by the calling program; on exit it contains the number of values defined by the filter.

On input, the `name_len` parameter indicates the number of characters allocated for the filter name by the calling program in the array `name[ ]`. On exit it contains the length in characters of name of the filter. On exit `name[ ]` contains the name of the filter with one character of the name in each element of the array.

If the filter specified in `filter_id` is not set for the property list, an error will be returned and H5Pget\_filter\_by\_id1 will fail.

**Parameters:**

<code>hid_t plist_id</code>	IN: Property list identifier.
<code>H5Z_filter_t filter_id</code>	IN: Filter identifier.
<code>unsigned int *flags</code>	OUT: Bit vector specifying certain general properties of the filter.
<code>size_t cd_nelmts</code>	IN/OUT: Number of elements in <code>cd_values</code> .
<code>unsigned int *cd_values</code>	OUT: Auxiliary data for the filter.
<code>size_t namelen</code>	IN/OUT: Length of filter name and number of elements in <code>name[ ]</code> .
<code>char name[ ]</code>	OUT: Name of filter.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.



**Fortran90 Interface:** h5pget\_filter\_by\_id\_f

See the H5Pget\_filter\_by\_id macro description.

**History:**

Release	C
1.6.0	Function introduced in this release.
1.8.0	Function H5Tget_filter_by_id renamed to H5Tget_filter_by_id1 and deprecated in this release.

**Name:** H5Pget\_filter\_by\_id2

**Signature:**

```
herr_t H5Pget_filter_by_id2(hid_t plist_id, H5Z_filter_t filter_id, unsigned int
*flags, size_t *cd_nelmts, unsigned int cd_values[], size_t namelen, char name[], unsigned
int *filter_config)
```

**Purpose:**

Returns information about the specified filter.

**Description:**

H5Pget\_filter\_by\_id2 returns information about the filter specified in `filter_id`, a filter identifier.

`plist_id` must identify a dataset creation property list and `filter_id` will be in a permanent filter pipeline.

The `filter_id` and `flags` parameters are used in the same manner as described in the discussion of H5Pset\_filter.

Aside from the fact that they are used for output, the parameters `cd_nelmts` and `cd_values[]` are used in the same manner as described in the discussion of H5Pset\_filter. On input, the `cd_nelmts` parameter indicates the number of entries in the `cd_values[]` array allocated by the calling program; on exit it contains the number of values defined by the filter.

On input, the `name_len` parameter indicates the number of characters allocated for the filter name by the calling program in the array `name[]`. On exit it contains the length in characters of name of the filter. On exit `name[]` contains the name of the filter with one character of the name in each element of the array.

`filter_config` is the bit field described in H5Zget\_filter\_info.

If the filter specified in `filter_id` is not set for the property list, an error will be returned and H5Pget\_filter\_by\_id2 will fail.

**Parameters:**

<i>hid_t</i> plist_id	IN: Property list identifier.
<i>H5Z_filter_t</i> filter_id	IN: Filter identifier.
<i>unsigned int</i> *flags	OUT: Bit vector specifying certain general properties of the filter.
<i>size_t</i> cd_nelmts	IN/OUT: Number of elements in <code>cd_values</code> .
<i>unsigned int</i> *cd_values	OUT: Auxiliary data for the filter.
<i>size_t</i> namelen	IN/OUT: Length of filter name and number of elements in <code>name[]</code> .
<i>char</i> name[]	OUT: Name of filter.
<i>unsigned int</i> *filter_config	OUT: Bit field, as described in H5Zget_filter_info.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_filter\_by\_id\_f

See the H5Pget\_filter\_by\_id macro description.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pget\_gc\_references

**Signature:**

*herr\_t* H5Pget\_gc\_references(*hid\_t* plist, *unsigned* \*gc\_ref )

**Purpose:**

Returns garbage collecting references setting.

**Description:**

H5Pget\_gc\_references returns the current setting for the garbage collection references property from the specified file access property list. The garbage collection references property is set by H5Pset\_gc\_references.

**Parameters:**

<i>hid_t</i> plist	IN: File access property list identifier.
<i>unsigned</i> gc_ref	OUT: Flag returning the state of reference garbage collection. A returned value of 1 indicates that garbage collection is on while 0 indicates that garbage collection is off.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_gc\_references\_f

```

SUBROUTINE h5pget_gc_references_f (prp_id, gc_reference, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: gc_reference ! The flag for garbage collecting
                                         ! references for the file
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pget_gc_references_f

```

**Name:** H5Pget\_hyper\_vector\_size

**Signature:**

```
herr_t H5Pget_hyper_vector_size(hid_t dxpl_id, size_t *vector_size)
```

**Purpose:**

Retrieves number of I/O vectors to be read/written in hyperslab I/O.

**Description:**

H5Pset\_hyper\_vector\_size retrieves the number of I/O vectors to be accumulated in memory before being issued to the lower levels of the HDF5 library for reading or writing the actual data.

The number of I/O vectors set in the dataset transfer property list *dxpl\_id* is returned in *vector\_size*. Unless the default value is in use, *vector\_size* was previously set with a call to H5Pset\_hyper\_vector\_size.

**Parameters:**

<i>hid_t</i> dxpl_id	IN: Dataset transfer property list identifier.
<i>size_t</i> *vector_size	OUT: Number of I/O vectors to accumulate in memory for I/O operations.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_hyper\_vector\_size\_f

```
SUBROUTINE h5pget_hyper_vector_size_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! Dataset transfer property list
                                          ! identifier
  INTEGER(SIZE_T), INTENT(OUT) :: size    ! Vector size
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pget_hyper_vector_size_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Pget\_istore\_k

**Signature:**

*herr\_t* H5Pget\_istore\_k(*hid\_t* plist, *unsigned* \*ik)

**Purpose:**

Queries the 1/2 rank of an indexed storage B-tree.

**Description:**

H5Pget\_istore\_k queries the 1/2 rank of an indexed storage B-tree. The argument *ik* may be the null pointer (NULL). This function is only valid for file creation property lists.

See H5Pset\_istore\_k for details.

**Parameters:**

*hid\_t* plist           IN: Identifier of property list to query.

*unsigned* \*ik       OUT: Pointer to location to return the chunked storage B-tree 1/2 rank.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_istore\_k\_f

```
SUBROUTINE h5pget_istore_k_f(prp_id, ik, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: ik           ! 1/2 rank of chunked storage B-tree
  INTEGER, INTENT(OUT) :: hdferr       ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pget_istore_k_f
```

**History:**

**Release    C**

1.6.4       *ik* parameter type changed to *unsigned*.

**Name:** H5Pget\_layout

**Signature:**

*H5D\_layout\_t* H5Pget\_layout(*hid\_t* plist)

**Purpose:**

Returns the layout of the raw data for a dataset.

**Description:**

H5Pget\_layout returns the layout of the raw data for a dataset. This function is only valid for dataset creation property lists.

Note that a compact storage layout may affect writing data to the dataset with parallel applications. See note in H5Dwrite documentation for details.

**Parameters:**

*hid\_t* plist      IN: Identifier for property list to query.

**Returns:**

Returns the layout type (a non-negative value) of a dataset creation property list if successful. Valid return values are:

H5D\_COMPACT

Raw data is stored in the object header in the file.

H5D\_CONTIGUOUS

Raw data is stored separately from the object header in one contiguous chunk in the file.

H5D\_CHUNKED

Raw data is stored separately from the object header in chunks in separate locations in the file.

Otherwise, returns a negative value indicating failure.

**Fortran90 Interface:** h5pget\_layout\_f

```
SUBROUTINE h5pget_layout_f (prp_id, layout, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: layout      ! Type of storage layout for raw data
                                     ! possible values are:
                                     !   H5D_COMPACT_F
                                     !   H5D_CONTIGUOUS_F
                                     !   H5D_CHUNKED_F
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5pget_layout_f
```

**Name:** H5Pget\_libver\_bounds

**Signature:**

```
herr_t H5Pget_libver_bounds( hid_t fapl_id, H5F_libver_t *low, H5F_libver_t *high )
```

**Purpose:**

Retrieves library version bounds settings that indirectly control the format versions used when creating objects.

**Description:**

H5Pget\_libver\_bounds retrieves the lower and upper bounds on the HDF5 Library versions that indirectly determine the object formats versions used when creating objects in the file.

This property is retrieved from the file access property list specified by *fapl\_id*.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier
<i>H5F_libver_t</i> *low	OUT: The earliest version of the library that will be used for writing objects. The library version indirectly specifies the earliest object format version that can be used when creating objects in the file.
	Currently, H5F_LIBVER_EARLIEST and H5F_LIBVER_LATEST are the only valid values for low.
<i>H5F_libver_t</i> *high	OUT: The latest version of the library that will be used for writing objects. The library version indirectly specifies the latest object format version that can be used when creating objects in the file.
	Currently, H5F_LIBVER_LATEST is the only valid value for high.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

**History:**

Release	C
1.8.0	Function introduced in this release.



**Name:** H5Pget\_link\_creation\_order

**Signature:**

*herr\_t* H5Pget\_link\_creation\_order( *hid\_t* gcpl\_id, *unsigned* \*crt\_order\_flags )

**Purpose:**

Queries whether link creation order is tracked and/or indexed in a group.

**Description:**

H5Pget\_link\_creation\_order queries the group creation property list, gcpl\_id, and returns a flag indicating whether link creation order is tracked and/or indexed in a group.

See H5Pset\_link\_creation\_order for a list of valid creation order flags, as passed in crt\_order\_flags, and their meanings.

**Parameters:**

<i>hid_t</i> gcpl_id	IN: Group creation property list identifier
<i>unsigned</i> *crt_order_flags	OUT: Creation order flag(s)

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_link\_creation\_order\_f

```
SUBROUTINE h5pget_link_creation_order_f(gcpl_id, crt_order_flags, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: gcpl_id    ! Group creation property list id
  INTEGER, INTENT(OUT) :: crt_order_flags ! Creation order flag(s)
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pget_link_creation_order_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pget\_link\_phase\_change

**Signature:**

```
herr_t H5Pget_link_phase_change( hid_t gcpl_id, unsigned *max_compact, unsigned
                                *min_dense )
```

**Purpose:**

Queries the settings for conversion between compact and dense groups.

**Description:**

H5Pget\_link\_phase\_change queries the maximum number of entries for a *compact group* and the minimum number links to require before converting a group to a *dense* form.

In the compact format, links are stored as messages in the group's header. In the dense format, links are stored in a fractal heap and indexed with a version 2 B-tree.

max\_compact is the maximum number of links to store as header messages in the group header before converting the group to the dense format. Groups that are in the compact format and exceed this number of links are automatically converted to the dense format.

min\_dense is the minimum number of links to store in the dense format. Groups which are in dense format and in which the number of links falls below this number are automatically converted back to the compact format.

In the compact format, links are stored as messages in the group's header. In the dense format, links are stored in a fractal heap and indexed with a version 2 B-tree.

See H5Pset\_link\_phase\_change for a discussion of traditional, compact, and dense group storage.

**Parameters:**

hid_t gcpl_id	IN: Group creation property list identifier
unsigned *max_compact	OUT: Maximum number of links for compact storage
unsigned *min_dense	OUT: Minimum number of links for dense storage

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

```
SUBROUTINE h5pset_link_phase_change_f(gcpl_id, max_compact, min_dense, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: gcpl_id
                                ! Group creation property list identifier
  INTEGER, INTENT(IN) :: max_compact
                                ! Maximum number of attributes to be stored
                                ! in compact storage
  INTEGER, INTENT(IN) :: min_dense
                                ! Minimum number of attributes to be stored
                                ! in dense storage
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_link_phase_change_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pget\_local\_heap\_size\_hint

**Signature:**

```
herr_t H5Pget_local_heap_size_hint( hid_t gcpl_id, size_t *size_hint )
```

**Purpose:**

Retrieves the anticipated size of the local heap for original-style groups.

**Description:**

H5Pget\_local\_heap\_size\_hint queries the group creation property list, gcpl\_id, for the anticipated size of the local heap, size\_hint, for original-style groups, i.e., for groups of the style used prior to HDF5 Release 1.8.0.

See H5Pset\_local\_heap\_size\_hint for further discussion.

**Parameters:**

<i>hid_t</i> gcpl_id	IN: Group creation property list identifier
<i>size_t</i> *size_hint	OUT: Anticipated size of local heap

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

```
SUBROUTINE h5pget_local_heap_size_hint_f(gcpl_id, size_hint, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: gcpl_id
                                ! Group creation property list identifier
  INTEGER(SIZE_T), INTENT(OUT) :: size_hint
                                ! Hint for size of local heap
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pget_local_heap_size_hint_f
```

**History:**

Release	Change
1.8.0	Function introduced in this release.

**Name:** H5Pget\_mdc\_config

**Signature:**

```
herr_t H5Pget_mdc_config(hid_t plist_id, H5AC_cache_config_t *config_ptr)
```

**Purpose:**

Get the current initial metadata cache configuration from the indicated File Access Property List.

**Description:**

H5Pget\_mdc\_config gets the initial metadata cache configuration contained in a file access property list and loads it into the instance of *H5AC\_cache\_config\_t* pointed to by the *config\_ptr* parameter. This configuration is used when the file is opened.

Note that the version field of *\*config\_ptr* must be initialized; this allows the library to support old versions of the *H5AC\_cache\_config\_t* structure.

See the overview of the metadata cache in the special topics section of the user guide for details on the configuration data returned. If you haven't read and understood that documentation, the results of this call will not make much sense.

**Parameters:**

*hid\_t* plist\_id

IN: Identifier of the file access property list.

*H5AC\_cache\_config\_t* \*config\_ptr

IN/OUT: Pointer to the instance of *H5AC\_cache\_config\_t* in which the current metadata cache configuration is to be reported. The fields of this structure are discussed below:

**General configuration section:**

*int* version

IN: Integer field indicating the the version of the *H5AC\_cache\_config\_t* in use. This field should be set to *H5AC\_CURR\_CACHE\_CONFIG\_VERSION* (defined in *H5ACpublic.h*).

*hbool\_t* rpt\_fcn\_enabled

OUT: Boolean flag indicating whether the adaptive cache resize report function is enabled. This field should almost always be set to *FALSE*. Since resize algorithm activity is reported via stdout, it *MUST* be set to *FALSE* on Windows machines.

*hbool\_t* open\_trace\_file

The report function is not supported code, and can be expected to change between versions of the library. Use it at your own risk.

OUT: Boolean field indicating whether the *trace\_file\_name* field should be used to open a trace file for the cache. This field will always be set to *FALSE* in this context.

*hbool\_t* close\_trace\_file

OUT: Boolean field indicating whether the current trace file (if any) should be closed. This field will always be set to *FALSE* in this

*char* \*trace\_file\_name

*hbool\_t* evictions\_enabled

*hbool\_t* set\_initial\_size

*size\_t* initial\_size

*double* min\_clean\_fraction

*size\_t* max\_size

*size\_t* min\_size

*int* epoch\_length

### Increment configuration section:

*enum H5C\_cache\_incr\_mode* incr\_mode

*double* lower\_hr\_threshold

*double* increment

*hbool\_t* apply\_max\_increment

context.

OUT: Full path name of the trace file to be opened if the `open_trace_file` field is `TRUE`. This field will always be set to the empty string in this context.

OUT: Boolean flag indicating whether metadata cache entry evictions will be enabled when the file is opened / created.

OUT: Boolean flag indicating whether the cache should be created with a user specified initial maximum size.

OUT: Initial maximum size of the cache in bytes, if applicable.

OUT: Float value specifying the minimum fraction of the cache that must be kept either clean or empty when possible.

OUT: Upper bound (in bytes) on the range of values that the adaptive cache resize code can select as the maximum cache size.

OUT: Lower bound (in bytes) on the range of values that the adaptive cache resize code can select as the maximum cache size.

OUT: Number of cache accesses between runs of the adaptive cache resize code.

OUT: Enumerated value indicating the operational mode of the automatic cache size increase code. At present, only the following values are legal:

`H5C_incr__off`: Automatic cache size increase is disabled.

`H5C_incr__threshold`: Automatic cache size increase is enabled using the hit rate threshold algorithm.

OUT: Hit rate threshold used in the hit rate threshold cache size increase algorithm.

OUT: The factor by which the current maximum cache size is multiplied to obtain an initial new maximum cache size if a size increase is triggered in the hit rate threshold cache size increase algorithm.

OUT: Boolean flag indicating whether an upper limit will be applied to the size of cache size increases.

*size\_t* max\_increment

OUT: The maximum number of bytes by which the maximum cache size can be increased in a single step -- if applicable.

*enum H5C\_cache\_flash\_incr\_mode* flash\_incr\_mode

OUT: Enumerated value indicating the operational mode of the flash cache size increase code. At present, only the following values are legal:

H5C\_flash\_incr\_\_off: Flash cache size increase is disabled.

H5C\_flash\_incr\_\_add\_space: Flash cache size increase is enabled using the add space algorithm.

*double* flash\_threshold

OUT: The factor by which the current maximum cache size is multiplied to obtain the minimum size entry / entry size increase which may trigger a flash cache size increase.

*double* flash\_multiple

OUT: The factor by which the size of the triggering entry / entry size increase is multiplied to obtain the initial cache size increment. This increment may be reduced to reflect existing free space in the cache and the max\_size field above.

#### Decrement configuration section:

*enum H5C\_cache\_decr\_mode* decr\_mode

OUT: Enumerated value indicating the operational mode of the automatic cache size decrease code. At present, the following values are legal:

H5C\_decr\_\_off: Automatic cache size decrease is disabled, and the remaining decrement fields are ignored.

H5C\_decr\_\_threshold: Automatic cache size decrease is enabled using the hit rate threshold algorithm.

H5C\_decr\_\_age\_out: Automatic cache size decrease is enabled using the ageout algorithm.

H5C\_decr\_\_age\_out\_with\_threshold: Automatic cache size decrease is enabled using the ageout with hit rate threshold algorithm

*double* upper\_hr\_threshold

OUT: Upper hit rate threshold. This value is only used if the decr\_mode is either H5C\_decr\_\_threshold or H5C\_decr\_\_age\_out\_with\_threshold.

*double* decrement

OUT: Factor by which the current max cache size is multiplied to obtain an initial value for the new cache size when cache size reduction is triggered in the hit rate threshold cache size reduction algorithm.

*hbool\_t* apply\_max\_decrement

OUT: Boolean flag indicating whether an upper limit should be applied to the size of cache size decreases.

*size\_t* max\_decrement

OUT: The maximum number of bytes by which cache size can be decreased if any single step, if applicable.

*int* epochs\_before\_eviction

OUT: The minimum number of epochs that an entry must reside unaccessed in cache before being evicted under either of the ageout cache size reduction algorithms.

*hbool\_t* apply\_empty\_reserve

OUT: Boolean flag indicating whether an empty reserve should be maintained under either of the ageout cache size reduction algorithms.

*double* empty\_reserve

OUT: Empty reserve for use with the ageout cache size reduction algorithms, if applicable.

**Parallel configuration section:**

*int* dirty\_bytes\_threshold

OUT: Threshold number of bytes of dirty metadata generation for triggering synchronizations of the metadata caches serving the target file in the parallel case.

Synchronization occurs whenever the number of bytes of dirty metadata created since the last synchronization exceeds this limit.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.



**Name:** H5Pget\_meta\_block\_size

**Signature:**

```
herr_t H5Pget_meta_block_size(hid_t fapl_id, hsize_t *size)
```

**Purpose:**

Returns the current metadata block size setting.

**Description:**

H5Pget\_meta\_block\_size returns the current minimum size, in bytes, of new metadata block allocations. This setting is retrieved from the file access property list *fapl\_id*.

This value is set by H5Pset\_meta\_block\_size and is retrieved from the file access property list *fapl\_id*.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>hsize_t</i> *size	OUT: Minimum size, in bytes, of metadata block allocations.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_meta\_block\_size\_f

```
SUBROUTINE h5pget_meta_block_size_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! File access property list
                                          ! identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: size ! Metadata block size
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                  ! 0 on success and -1 on failure
END SUBROUTINE h5pget_meta_block_size_f
```

**History:**

<b>Release</b>	<b>C</b>
1.4.0	Function introduced in this release.

**Name:** H5Pget\_multi\_type

**Signature:**

*herr\_t* H5Pget\_multi\_type ( *hid\_t* fapl\_id, *H5FD\_mem\_t* \*type )

**Purpose:**

Retrieves type of data property for MULTI driver.

**Description:**

H5Pget\_multi\_type retrieves the type of data setting from the file access or data transfer property list fapl\_id. This enables a user application to specify the type of data the application wishes to access so that the application can retrieve a file handle for low-level access to the particular member of a set of MULTI files in which that type of data is stored. The file handle is retrieved with a separate call to H5Fget\_vfd\_handle (or, in special circumstances, to H5FDget\_vfd\_handle; see *Virtual File Layer* and *List of VFL Functions* in *HDF5 Technical Notes*).

The type of data returned in type will be one of those listed in the discussion of the type parameter in the the description of the function H5Pset\_multi\_type.

Use of this function is only appropriate for an HDF5 file written as a set of files with the MULTI file driver.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list or data transfer property list identifier.
<i>H5FD_mem_t</i> *type	OUT: Type of data.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.0	Function introduced in this release.

**Name:** H5Pget\_nfilters

**Signature:**

*int* H5Pget\_nfilters(*hid\_t* plist)

**Purpose:**

Returns the number of filters in the pipeline.

**Description:**

H5Pget\_nfilters returns the number of filters defined in the filter pipeline associated with the property list *plist*.

In each pipeline, the filters are numbered from 0 through  $N-1$ , where  $N$  is the value returned by this function. During output to the file, the filters are applied in increasing order; during input from the file, they are applied in decreasing order.

H5Pget\_nfilters returns the number of filters in the pipeline, including zero (0) if there are none.

**Note:**

This function currently supports only the permanent filter pipeline; *plist\_id* must be a dataset creation property list.

**Parameters:**

*hid\_t* plist      IN: Property list identifier.

**Returns:**

Returns the number of filters in the pipeline if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_nfilters\_f

```
SUBROUTINE h5pget_nfilters_f(prp_id, nfilters, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Dataset creation property
                                           ! list identifier
  INTEGER, INTENT(OUT) :: nfilters          ! The number of filters in
                                           ! the pipeline
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_nfilters_f
```

**Name:** H5Pget\_nlinks

**Signature:**

```
herr_t H5Pget_nlinks( hid_t lapl_id, size_t *nlinks )
```

**Purpose:**

Retrieves the maximum number of link traversals.

**Description:**

H5Pget\_nlinks retrieves the maximum number of soft or user-defined link traversals allowed, *nlinks*, before the library assumes it has found a cycle and aborts the traversal. This value is retrieved from the link access property list *lapl\_id*.

The limit on the number soft or user-defined link traversals is designed to terminate link traversal if one or more links form a cycle. User control is provided because some files may have legitimate paths formed of large numbers of soft or user-defined links. This property can be used to allow traversal of as many links as desired.

**Parameters:**

<i>hid_t</i> <i>fapl_id</i>	IN: File access property list identifier
<i>size_t</i> * <i>nlinks</i>	OUT: Maximum number of links to traverse

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_nlinks\_f

```
SUBROUTINE h5pget_nlinks_f(lapl_id, nlinks, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: lapl_id
                                ! File access property list identifier
  INTEGER(SIZE_T), INTENT(OUT) :: nlinks
                                ! Maximum number of links to traverse
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pget_nlinks_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pget\_nprops

**Signature:**

```
int H5Pget_nprops( hid_t id, size_t *nprops )
```

**Purpose:**

Queries number of properties in property list or class.

**Description:**

H5Pget\_nprops retrieves the number of properties in a property list or class. If a property class identifier is given, the number of registered properties in the class is returned in `nprops`. If a property list identifier is given, the current number of properties in the list is returned in `nprops`.

**Parameters:**

<code>hid_t id</code>	IN: Identifier of property object to query
<code>size_t *nprops</code>	OUT: Number of properties in object

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** h5pget\_nprops\_f

```
SUBROUTINE h5pget_nprops_f(prp_id, nprops, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER(SIZE_T), INTENT(OUT) :: nprops    ! Number of properties
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_nprops_f
```

**Name:** H5Pget\_preserve

**Signature:**

`int H5Pget_preserve(hid_t plist)`

**Purpose:**

Checks status of the dataset transfer property list.

**Notice:**

*This function is deprecated as it is no longer useful; compound datatype field preservation is now core functionality in the HDF5 Library.*

**Description:**

H5Pget\_preserve checks the status of the dataset transfer property list.

**Parameters:**

`hid_t plist`      IN: Identifier for the dataset transfer property list.

**Returns:**

Returns TRUE or FALSE if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_preserve\_f

```
SUBROUTINE h5pget_preserve_f(prp_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id    ! Dataset transfer property
                                           ! list identifier
  LOGICAL, INTENT(OUT)       :: flag      ! Status of for the dataset
                                           ! transfer property list
  INTEGER, INTENT(OUT)       :: hdferr    ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_preserve_f
```

**History:**

Release	Fortran90
1.6.0	The <code>flag</code> parameter was changed from <i>INTEGER</i> to <i>LOGICAL</i> to better match the C API.

**Name:** H5Pget\_obj\_track\_times

**Signature:**

```
herr_t H5Pget_obj_track_times(hid_t ocpl_id, hbool_t *track_times)
```

**Purpose:**

Determines whether times associated with an object are being recorded.

**Description:**

H5get\_obj\_track\_times queries the object creation property list, ocpl\_id, to determine whether object times are being recorded.

If track\_times is returned as TRUE, times are being recorded; if track\_times is returned as FALSE, times are not being recorded.

Time data can be retrieved with H5Oget\_info, which will return it in the H5O\_info\_t struct.

If times are not tracked, they will be reported as follows when queried:

```
12:00 AM UDT, Jan. 1, 1970
```

See H5Pset\_obj\_track\_times for further discussion.

**Parameters:**

<i>hid_t</i> ocpl_id	IN: Object creation property list identifier
<i>hbool_t</i> *track_times	OUT: Boolean value, TRUE or FALSE, specifying whether object times are being recorded

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_obj\_track\_times\_f

```
SUBROUTINE h5pget_obj_track_times_f(plist_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id
                                ! Dataset creation property
                                ! list identifier
  LOGICAL, INTENT(OUT) :: flag ! Object timestamp setting
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pget_obj_track_times_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pget\_shared\_mesg\_index

**Signature:**

```
herr_t H5Pget_shared_mesg_index( hid_t fcpl_id, unsigned index_num, unsigned
*mesg_type_flags, unsigned *min_mesg_size )
```

**Purpose:**

Retrieves the configuration settings for a shared message index.

**Description:**

H5Pget\_shared\_mesg\_index retrieves the message type and minimum message size settings from the file creation property list *fcpl\_id* for the shared object header message index specified by *index\_num*.

*index\_num* specifies the index. *index\_num* is zero-indexed, so in a file with three indexes, they will be numbered 0, 1, and 2.

*mesg\_type\_flags* and *min\_mesg\_size* will contain, respectively, the types of messages and the minimum size, in bytes, of messages that can be stored in this index.

Valid message types are described in H5Pset\_shared\_mesg\_index.

**Parameters:**

<i>hid_t</i> fcpl_id	IN: File creation property list identifier.
<i>unsigned</i> index_num	IN: Index being configured.
<i>unsigned</i> *mesg_type_flags	OUT: Types of messages that may be stored in this index.
<i>unsigned</i> *min_mesg_size	OUT: Minimum message size.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.



**Name:** H5Pget\_shared\_mesg\_nindexes

**Signature:**

*herr\_t* H5Pget\_shared\_mesg\_nindexes( *hid\_t* fcpl\_id, *unsigned* \*nindexes )

**Purpose:**

Retrieves number of shared object header message indexes in file creation property list.

**Description:**

H5Pget\_shared\_mesg\_nindexes retrieves the number of shared object header message indexes in the specified file creation property list *fcpl\_id*.

If the value of *nindexes* is 0 (zero), shared object header messages are disabled in files created with this property list.

**Parameters:**

<i>hid_t</i> fcpl_id	IN: File creation property list
<i>unsigned</i> *nindexes	OUT: Number of shared object header message indexes available in files created with this property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pget\_shared\_mesg\_phase\_change

**Signature:**

```
herr_t H5Pget_shared_mesg_phase_change( hid_t fcpl_id, unsigned *max_list, unsigned
*min_btree )
```

**Purpose:**

Retrieves shared object header message phase change information.

**Description:**

H5Pget\_shared\_mesg\_phase\_change retrieves the threshold values for storage of shared object header message indexes in a file. These phase change thresholds determine the point at which the index storage mechanism changes from a more compact list format to a more performance-oriented B-tree format, and vice-versa.

By default, a shared object header message index is initially stored as a compact list. When the number of messages in an index exceeds the specified `max_list` threshold, storage switches to a B-tree format for improved performance. If the number of messages subsequently falls below the `min_btree` threshold, the index will revert to the list format.

If `max_compact` is set to 0 (zero), shared object header message indexes in the file will always be stored as B-trees.

`fcpl_id` specifies the file creation property list.

**Parameters:**

<i>hid_t</i> fcpl_id	IN: File creation property list identifier
<i>unsigned</i> *max_compact	OUT: Threshold above which storage of a shared object header message index shifts from list to B-tree
<i>unsigned</i> *min_btree	OUT: Threshold below which storage of a shared object header message index reverts to list format

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pget\_sieve\_buf\_size

**Signature:**

```
herr_t H5Pget_sieve_buf_size(hid_t fapl_id, hsize_t *size)
```

**Purpose:**

Returns maximum data sieve buffer size.

**Description:**

H5Pget\_sieve\_buf\_size retrieves, size, the current maximum size of the data sieve buffer.

This value is set by H5Pset\_sieve\_buf\_size and is retrieved from the file access property list fapl\_id.

**Parameters:**

```
hid_t fapl_id      IN: File access property list identifier.
hsize_t *size      IN: Maximum size, in bytes, of data sieve buffer.
```

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_sieve\_buf\_size\_f

```
SUBROUTINE h5pget_sieve_buf_size_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! File access property list
                                          ! identifier
  INTEGER(SIZE_T), INTENT(OUT) :: size   ! Sieve buffer size
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pget_sieve_buf_size_f
```

**History:**

Release	C
1.6.0	The size parameter has changed from type <i>hsize_t</i> to <i>size_t</i> .
1.4.0	Function introduced in this release.

**Name:** H5Pget\_size

**Signature:**

```
int H5Pget_size( hid_t id, const char *name, size_t *size )
```

**Purpose:**

Queries the size of a property value in bytes.

**Description:**

H5Pget\_size retrieves the size of a property's value in bytes. This function operates on both property lists and property classes

Zero-sized properties are allowed and return 0.

**Parameters:**

<i>hid_t</i> id	IN: Identifier of property object to query
<i>const char</i> *name	IN: Name of property to query
<i>size_t</i> *size	OUT: Size of property in bytes

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** h5pget\_size\_f

```
SUBROUTINE h5pget_size_f(prp_id, name, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  CHARACTER(LEN=*), INTENT(IN) :: name ! Name of property to query
  INTEGER(SIZE_T), INTENT(OUT) :: size ! Size in bytes
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                   ! 0 on success and -1 on failure
END SUBROUTINE h5pget_size_f
```

**Name:** H5Pget\_sizes

**Signature:**

```
herr_t H5Pget_sizes(hid_t plist, size_t * sizeof_addr, size_t * sizeof_size)
```

**Purpose:**

Retrieves the size of the offsets and lengths used in an HDF5 file.

**Description:**

H5Pget\_sizes retrieves the size of the offsets and lengths used in an HDF5 file. This function is only valid for file creation property lists.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier of property list to query.
<i>size_t</i> * size	OUT: Pointer to location to return offset size in bytes.
<i>size_t</i> * size	OUT: Pointer to location to return length size in bytes.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_sizes\_f

```
SUBROUTINE h5pget_sizes_f(prp_id, sizeof_addr, sizeof_size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER(SIZE_T), DIMENSION(:), INTENT(OUT) :: sizeof_addr
                                     ! Size of an object address in bytes
  INTEGER(SIZE_T), DIMENSION(:), INTENT(OUT) :: sizeof_size
                                     ! Size of an object in bytes
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5pget_sizes_f
```

**Name:** H5Pget\_small\_data\_block\_size

**Signature:**

```
herr_t H5Pget_small_data_block_size(hid_t fapl_id, hsize_t *size)
```

**Purpose:**

Retrieves the current small data block size setting.

**Description:**

H5Pget\_small\_data\_block\_size retrieves the current setting for the size of the small data block.

If the returned value is zero (0), the small data block mechanism has been disabled for the file.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>hsize_t</i> *size	OUT: Maximum size, in bytes, of the small data block.

**Returns:**

Returns a non-negative value if successful; otherwise a negative value.

**Fortran90 Interface:** h5pget\_small\_data\_block\_size\_f

```
SUBROUTINE h5pget_small_data_block_size_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! File access property list
                                          ! identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: size ! Small raw data block size
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                  ! 0 on success and -1 on failure
END SUBROUTINE h5pget_small_data_block_size_f
```

**History:**

<b>Release</b>	<b>C</b>
1.4.4	Function introduced in this release.

**Name:** H5Pget\_sym\_k

**Signature:**

*herr\_t* H5Pget\_sym\_k(*hid\_t* plist, *unsigned* \* ik, *unsigned* \* lk)

**Purpose:**

Retrieves the size of the symbol table B-tree 1/2 rank and the symbol table leaf node 1/2 size.

**Description:**

H5Pget\_sym\_k retrieves the size of the symbol table B-tree 1/2 rank and the symbol table leaf node 1/2 size. This function is only valid for file creation property lists. If a parameter value is set to NULL, that parameter is not retrieved. See the description for H5Pset\_sym\_k for more information.

**Parameters:**

*hid\_t* plist      IN: Property list to query.  
*unsigned* \* ik      OUT: Pointer to location to return the symbol table's B-tree 1/2 rank.  
*unsigned* \* size    OUT: Pointer to location to return the symbol table's leaf node 1/2 size.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_sym\_k\_f

```
SUBROUTINE h5pget_sym_k_f(prp_id, ik, lk, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(OUT) :: ik          ! Symbol table tree rank
  INTEGER, INTENT(OUT) :: lk          ! Symbol table node size
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                      ! 0 on success and -1 on failure

  END SUBROUTINE h5pget_sym_k_f
```

**History:**

Release	C
1.6.4	ik parameter type changed to <i>unsigned</i>
1.6.0	The ik parameter has changed from type <i>int</i> to <i>unsigned</i>

**Name:** H5Pget\_type\_conv\_cb

**Signature:**

*herr\_t* H5Pget\_type\_conv\_cb(*hid\_t* plist, *H5T\_conv\_except\_func\_t* \*func, void \*\*op\_data)

**Purpose:**

Gets user-defined datatype conversion callback function.

**Description:**

H5Pget\_type\_conv\_cb gets the user-defined datatype conversion callback function *func* in the dataset transfer property list *plist*.

The parameter *op\_data* is a pointer to user-defined input data for the callback function.

The callback function *func* defines the actions an application is to take when there is an exception during datatype conversion.

Please refer to the function H5Pset\_type\_conv\_cb for more details.

**Parameters:**

<i>hid_t</i> plist	IN: Dataset transfer property list identifier.
<i>H5T_conv_except_func_t</i> *func	OUT: User-defined type conversion callback function.
void **op_data	OUT: User-defined input data for the callback function.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.



**Name:** H5Pget\_userblock

**Signature:**

*herr\_t* H5Pget\_userblock(*hid\_t* plist, *hsize\_t* \*size)

**Purpose:**

Retrieves the size of a user block.

**Description:**

H5Pget\_userblock retrieves the size of a user block in a file creation property list.

**Parameters:**

*hid\_t* plist            IN: Identifier for property list to query.

*hsize\_t* \*size        OUT: Pointer to location to return user-block size.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_userblock\_f

```
SUBROUTINE h5pget_userblock_f(prp_id, block_size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id    ! Property list identifier
  INTEGER(HSIZE_T), DIMENSION(:), INTENT(OUT) :: block_size
                                           ! Size of the user-block in bytes
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pget_userblock_f
```

**Name:** H5Pget\_version

**Signature:**

```
herr_t H5Pget_version(hid_t plist, unsigned * super, unsigned * freelist, unsigned *
stab, unsigned * shhdr)
```

**Purpose:**

Retrieves the version information of various objects for a file creation property list.

**Description:**

H5Pget\_version retrieves the version information of various objects for a file creation property list. Any pointer parameters which are passed as NULL are not queried.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier of the file creation property list.
<i>unsigned</i> * super	OUT: Pointer to location to return super block version number.
<i>unsigned</i> * freelist	OUT: Pointer to location to return global freelist version number.
<i>unsigned</i> * stab	OUT: Pointer to location to return symbol table version number.
<i>unsigned</i> * shhdr	OUT: Pointer to location to return shared object header version number.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_version\_f

```
SUBROUTINE h5pget_version_f(prp_id, boot, freelist, &
                           stab, shhdr, hdferr)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER, DIMENSION(:), INTENT(OUT) :: boot ! Array to put boot block
                                              ! version number
  INTEGER, DIMENSION(:), INTENT(OUT) :: freelist
                                              ! Array to put global
                                              ! freelist version number
  INTEGER, DIMENSION(:), INTENT(OUT) :: stab ! Array to put symbol table
                                              ! version number
  INTEGER, DIMENSION(:), INTENT(OUT) :: shhdr ! Array to put shared object
                                              ! header version number
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                              ! 0 on success and -1 on failure

END SUBROUTINE h5pget_version_f
```

**History:**

Release	C
---------	---

1.6.4	boot, freelist, stab, shhdr parameter types changed to <i>unsigned</i> .
-------	--

**Name:** H5Pget\_vlen\_mem\_manager

**Signature:**

```
herr_t H5Pget_vlen_mem_manager(hid_t plist, H5MM_allocate_t *alloc, void
**alloc_info, H5MM_free_t *free, void **free_info)
```

**Purpose:**

Gets the memory manager for variable-length datatype allocation in H5Dread and H5Dvlen\_reclaim.

**Description:**

H5Pget\_vlen\_mem\_manager is the companion function to H5Pset\_vlen\_mem\_manager, returning the parameters set by that function.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier for the dataset transfer property list.
<i>H5MM_allocate_t</i> alloc	OUT: User's allocate routine, or <code>NULL</code> for system <code>malloc</code> .
<i>void</i> *alloc_info	OUT: Extra parameter for user's allocation routine. Contents are ignored if preceding parameter is <code>NULL</code> .
<i>H5MM_free_t</i> free	OUT: User's free routine, or <code>NULL</code> for system <code>free</code> .
<i>void</i> *free_info	OUT: Extra parameter for user's free routine. Contents are ignored if preceding parameter is <code>NULL</code> .

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**Name:** H5Pinsert

**Signatures:**

```
herr_t H5Pinsert( hid_t plid, const char *name, size_t size, [1]
void *value, H5P_prp_set_func_t set, H5P_prp_get_func_t get,
H5P_prp_delete_func_t delete, H5P_prp_copy_func_t copy,
H5P_prp_close_func_t close )
```

```
herr_t H5Pinsert( hid_t plid, const char *name, size_t size, [2]
void *value, H5P_prp_set_func_t set, H5P_prp_get_func_t get,
H5P_prp_delete_func_t delete, H5P_prp_copy_func_t copy,
H5P_prp_compare_func_t compare, H5P_prp_close_func_t close )
```

**Purpose:**

Registers a temporary property with a property list.

**Description:**

H5Pinsert is a macro that is mapped to either H5Pinsert1 or H5Pinsert2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. For example:

- ◊ The H5Pinsert macro will be mapped to H5Pinsert1 and will use the H5Pinsert1 syntax (first signature above) if an application is coded for HDF5 Release 1.6.x.
- ◊ The H5Pinsert macro mapped to H5Pinsert2 and will use the H5Pinsert2 syntax (second signature above) if an application is coded for HDF5 Release 1.8.x.

Macro use and mappings are fully described in “API Compatibility Macros in HDF5” we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Pinsert is mapped to the most recent version of the function, currently H5Pinsert2. If the library and/or application is compiled for Release 1.6 emulation, H5Pinsert will be mapped to H5Pinsert1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Pinsert mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Pinsert2
Enable deprecated symbols	H5Pinsert2
Disable deprecated symbols	H5Pinsert2
Emulate Release 1.6 interface	H5Pinsert1

---

Function-level macros

```
H5Pinsert_vers = 2      H5Pinsert2
```

```
H5Pinsert_vers = 1      H5Pinsert1
```

**Interface history:** Signature [1] above is the original H5Pinsert interface and the only interface available prior to HDF5 Release 1.8.0. This signature and the corresponding function are now deprecated but will remain directly callable as H5Pinsert1.

Signature [2] above was introduced with HDF5 Release 1.8.0 and is the recommended and default interface. It is directly callable as H5Pinsert2.

See “API Compatibility Macros in HDF5” for circumstances under which either of these functions might not be available in an installed instance of the HDF5 Library.

**Fortran90 Interface: h5pinsert\_f**

```
SUBROUTINE h5pinsert_f
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist      ! Property list class identifier
  CHARACTER(LEN=*), INTENT(IN) :: name    ! Name of property to insert
  INTEGER(SIZE_T), INTENT(IN) :: size     ! Size of the property value
  TYPE,          INTENT(IN) :: value      ! Property value
                                          ! Supported types are:
                                          !   INTEGER
                                          !   REAL
                                          !   DOUBLE PRECISION
                                          !   CHARACTER(LEN=*)
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pinsert_f
```

**History:**

Release	C
1.8.0	<p>The function H5Pinsert renamed to H5Pinsert1 and deprecated in this release.</p> <p>The macro H5Pinsert and the function H5Pinsert2 introduced in this release.</p>

**Name:** H5Pinsert1

**Signature:**

```
herr_t H5Pinsert1( hid_t plid, const char *name, size_t size, void *value, H5P_prp_set_func_t
set, H5P_prp_get_func_t get, H5P_prp_delete_func_t delete, H5P_prp_copy_func_t copy,
H5P_prp_close_func_t close )
```

**Purpose:**

Registers a temporary property with a property list.

**Notice:**

*This function is renamed from H5Pinsert and deprecated in favor of the function H5Pinsert2 or the new macro H5Pinsert.*

**Description:**

H5Pinsert1 create a new property in a property list. The property will exist only in this property list and copies made from it.

The initial property value must be provided in `value` and the property value will be set accordingly.

The name of the property must not already exist in this list, or this routine will fail.

The set and get callback routines may be set to NULL if they are not needed.

Zero-sized properties are allowed and do not store any data in the property list. The default value of a zero-size property may be set to NULL. They may be used to indicate the presence or absence of a particular piece of information.

The set routine is called before a new value is copied into the property. The `H5P_prp_set_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_set_func_t)( hid_t prop_id, const char *name, size_t size, void
*new_value);
```

The parameters to the callback function are defined as follows:

<code>hid_t prop_id</code>	IN: The identifier of the property list being modified
<code>const char *name</code>	IN: The name of the property being modified
<code>size_t size</code>	IN: The size of the property in bytes
<code>void **new_value</code>	IN: Pointer to new value pointer for the property being modified

The set routine may modify the value pointer to be set and those changes will be used when setting the property's value. If the set routine returns a negative value, the new property value is not copied into the property and the set routine returns an error value. The set routine will be called for the initial value.

**Note:** The set callback function may be useful to range check the value being set for the property or may perform some transformation or translation of the value set. The get callback would then reverse the transformation or translation. A single get or set callback could handle multiple properties by performing different actions based on the property name or other properties in the property list.

The get routine is called when a value is retrieved from a property value. The `H5P_prp_get_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_get_func_t)( hid_t prop_id, const char *name, size_t size, void
*value);
```

The parameters to the above callback function are:

<i>hid_t</i> prop_id	IN: The identifier of the property list being queried
<i>const char</i> *name	IN: The name of the property being queried
<i>size_t</i> size	IN: The size of the property in bytes
<i>void</i> *value	IN: The value of the property being returned

The `get` routine may modify the value to be returned from the query and those changes will be preserved. If the `get` routine returns a negative value, the query routine returns an error value.

The `delete` routine is called when a property is being deleted from a property list. The `H5P_prp_delete_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_delete_func_t)( hid_t prop_id, const char *name, size_t
size, void *value);
```

The parameters to the above callback function are:

<i>hid_t</i> prop_id	IN: The identifier of the property list the property is being deleted from
<i>const char</i> *name	IN: The name of the property in the list
<i>size_t</i> size	IN: The size of the property in bytes
<i>void</i> *value	IN: The value for the property being deleted

The `delete` routine may modify the value passed in, but the value is not used by the library when the `delete` routine returns. If the `delete` routine returns a negative value, the property list delete routine returns an error value but the property is still deleted.

The `copy` routine is called when a new property list with this property is being created through a copy operation. The `H5P_prp_copy_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_copy_func_t)( const char *name, size_t size, void *value);
```

The parameters to the above callback function are:

<i>const char</i> *name	IN: The name of the property being copied
<i>size_t</i> size	IN: The size of the property in bytes
<i>void</i> *value	IN/OUT: The value for the property being copied

The `copy` routine may modify the value to be set and those changes will be stored as the new value of the property. If the `copy` routine returns a negative value, the new property value is not copied into the property and the `copy` routine returns an error value.

The `close` routine is called when a property list with this property is being closed. The `H5P_prp_close_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_close_func_t)( hid_t prop_id, const char *name, size_t size, void
*value);
```

The parameters to the callback function are defined as follows:

<i>hid_t</i> prop_id	IN: The identifier of the property list being closed
<i>const char</i> *name	IN: The name of the property in the list

<code>size_t size</code>	IN: The size of the property in bytes
<code>void *value</code>	IN: The value for the property being closed

The `close` routine may modify the value passed in, the value is not used by the library when the `close` routine returns. If the `close` routine returns a negative value, the property list close routine returns an error value but the property list is still closed.

**Note:** There is no `create` callback routine for temporary property list objects; the initial value is assumed to have any necessary setup already performed on it.

#### Parameters:

<code>hid_t plist</code>	IN: Property list identifier to create temporary property within
<code>const char *name</code>	IN: Name of property to create
<code>size_t size</code>	IN: Size of property in bytes
<code>void *value</code>	IN: Initial value for the property
<code>H5P_prp_set_func_t set</code>	IN: Callback routine called before a new value is copied into the property's value
<code>H5P_prp_get_func_t get</code>	IN: Callback routine called when a property value is retrieved from the property
<code>H5P_prp_delete_func_t delete</code>	IN: Callback routine called when a property is deleted from a property list
<code>H5P_prp_copy_func_t copy</code>	IN: Callback routine called when a property is copied from an existing property list
<code>H5P_prp_close_func_t close</code>	IN: Callback routine called when a property list is being closed and the property value will be disposed of

#### Returns:

Success: a non-negative value

Failure: a negative value

#### Fortran90 Interface: h5pinsert\_f

```

SUBROUTINE h5pinsert_f
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist      ! Property list class identifier
  CHARACTER(LEN=*), INTENT(IN) :: name    ! Name of property to insert
  INTEGER(SIZE_T), INTENT(IN) :: size     ! Size of the property value
  TYPE,          INTENT(IN) :: value      ! Property value
                                           ! Supported types are:
                                           !   INTEGER
                                           !   REAL
                                           !   DOUBLE PRECISION
                                           !   CHARACTER(LEN=*)
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pinsert_f

```

#### History:

Release	C
---------	---

1.8.0	Function <code>H5Pinsert</code> renamed to <code>H5Pinsert1</code> and deprecated in this release.
-------	--



**Name:** H5Pinsert2

**Signature:**

```
herr_t H5Pinsert2(hid_t plid, const char *name, size_t size, void *value, H5P_prp_set_func_t set, H5P_prp_get_func_t get, H5P_prp_delete_func_t delete, H5P_prp_copy_func_t copy, H5P_prp_compare_func_t compare, H5P_prp_close_func_t close)
```

**Purpose:**

Registers a temporary property with a property list.

**Description:**

H5Pinsert2 create a new property in a property list. The property will exist only in this property list and copies made from it.

The initial property value must be provided in value and the property value will be set accordingly.

The name of the property must not already exist in this list, or this routine will fail.

The set and get callback routines may be set to NULL if they are not needed.

Zero-sized properties are allowed and do not store any data in the property list. The default value of a zero-size property may be set to NULL. They may be used to indicate the presence or absence of a particular piece of information.

The set routine is called before a new value is copied into the property. The H5P\_prp\_set\_func\_t callback function is defined as follows:

```
typedef herr_t (*H5P_prp_set_func_t)(hid_t prop_id, const char *name, size_t size, void *new_value);
```

The parameters to the callback function are defined as follows:

<i>hid_t</i> prop_id	IN: The identifier of the property list being modified
<i>const char</i> *name	IN: The name of the property being modified
<i>size_t</i> size	IN: The size of the property in bytes
<i>void</i> **new_value	IN: Pointer to new value pointer for the property being modified

The set routine may modify the value pointer to be set and those changes will be used when setting the property's value. If the set routine returns a negative value, the new property value is not copied into the property and the set routine returns an error value. The set routine will be called for the initial value.

**Note:** The set callback function may be useful to range check the value being set for the property or may perform some transformation or translation of the value set. The get callback would then reverse the transformation or translation. A single get or set callback could handle multiple properties by performing different actions based on the property name or other properties in the property list.

The get routine is called when a value is retrieved from a property value. The H5P\_prp\_get\_func\_t callback function is defined as follows:

```
typedef herr_t (*H5P_prp_get_func_t)(hid_t prop_id, const char *name, size_t size, void *value);
```

The parameters to the above callback function are:

<i>hid_t</i> prop_id	IN: The identifier of the property list being queried
<i>const char</i> *name	IN: The name of the property being queried
<i>size_t</i> size	IN: The size of the property in bytes
<i>void</i> *value	IN: The value of the property being returned

The `get` routine may modify the value to be returned from the query and those changes will be preserved. If the `get` routine returns a negative value, the query routine returns an error value.

The `delete` routine is called when a property is being deleted from a property list. The `H5P_prp_delete_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_delete_func_t)(hid_t prop_id, const char *name, size_t
size, void *value);
```

The parameters to the above callback function are:

<i>hid_t</i> prop_id	IN: The identifier of the property list the property is being deleted from
<i>const char</i> *name	IN: The name of the property in the list
<i>size_t</i> size	IN: The size of the property in bytes
<i>void</i> *value	IN: The value for the property being deleted

The `delete` routine may modify the value passed in, but the value is not used by the library when the `delete` routine returns. If the `delete` routine returns a negative value, the property list delete routine returns an error value but the property is still deleted.

The `copy` routine is called when a new property list with this property is being created through a copy operation. The `H5P_prp_copy_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_copy_func_t)(const char *name, size_t size, void *value);
```

The parameters to the above callback function are:

<i>const char</i> *name	IN: The name of the property being copied
<i>size_t</i> size	IN: The size of the property in bytes
<i>void</i> *value	IN/OUT: The value for the property being copied

The `copy` routine may modify the value to be set and those changes will be stored as the new value of the property. If the `copy` routine returns a negative value, the new property value is not copied into the property and the copy routine returns an error value.

The `compare` routine is called when a property list with this property is compared to another property list with the same property. The `H5P_prp_compare_func_t` callback function is defined as follows:

```
typedef int (*H5P_prp_compare_func_t)(const void *value1, const void *value2, size_t
size);
```

The parameters to the callback function are defined as follows:

<i>const void</i> *value1	IN: The value of the first property to compare
<i>const void</i> *value2	IN: The value of the second property to compare
<i>size_t</i> size	IN: The size of the property in bytes

The `compare` routine may *not* modify the values. The `compare` routine should return a positive value if `value1` is greater than `value2`, a negative value if `value2` is greater than `value1` and zero if `value1` and `value2` are equal.

The `close` routine is called when a property list with this property is being closed. The `H5P_prp_close_func_t` callback function is defined as follows:

*typedef herr\_t (\*H5P\_prp\_close\_func\_t)( hid\_t prop\_id, const char \*name, size\_t size, void \*value);* The parameters to the callback function are defined as follows:

<i>hid_t prop_id</i>	IN: The identifier of the property list being closed
<i>const char *name</i>	IN: The name of the property in the list
<i>size_t size</i>	IN: The size of the property in bytes
<i>void *value</i>	IN: The value for the property being closed

The `close` routine may modify the value passed in, the value is not used by the library when the `close` routine returns. If the `close` routine returns a negative value, the property list close routine returns an error value but the property list is still closed.

**Note:** There is no `create` callback routine for temporary property list objects; the initial value is assumed to have any necessary setup already performed on it.

#### Parameters:

<i>hid_t plid</i>	IN: Property list identifier to create temporary property within
<i>const char *name</i>	IN: Name of property to create
<i>size_t size</i>	IN: Size of property in bytes
<i>void *value</i>	IN: Initial value for the property
<i>H5P_prp_set_func_t set</i>	IN: Callback routine called before a new value is copied into the property's value
<i>H5P_prp_get_func_t get</i>	IN: Callback routine called when a property value is retrieved from the property
<i>H5P_prp_delete_func_t delete</i>	IN: Callback routine called when a property is deleted from a property list
<i>H5P_prp_copy_func_t copy</i>	IN: Callback routine called when a property is copied from an existing property list
<i>H5P_prp_compare_func_t compare</i>	IN: Callback routine called when a property is compared with another property list
<i>H5P_prp_close_func_t close</i>	IN: Callback routine called when a property list is being closed and the property value will be disposed of

#### Returns:

Success: a non-negative value  
Failure: a negative value

#### Fortran90 Interface:

None.

#### History:

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

*Last modified: 20 April 2009***Name:** H5Pisa\_class**Signature:***htri\_t* H5Pisa\_class(*hid\_t* plist, *hid\_t* pclass)**Purpose:**

Determines whether a property list is a member of a class.

**Description:**H5Pisa\_class checks to determine whether the property list *plist* is a member of the property list class *pclass*.**Parameters:***hid\_t* plist      IN: Property list identifier*hid\_t* pclass    IN: Property list class identifier**Returns:**

Returns a positive value if true or zero if false; returns a negative value on failure.

**See Also:**

H5Pcreate

**Fortran90 Interface:** h5pisa\_class\_f

```

SUBROUTINE h5pisa_class_f(plist, pclass, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist      ! Property list identifier
  INTEGER(HID_T), INTENT(IN) :: pclass     ! Class identifier
  LOGICAL, INTENT(OUT) :: flag             ! Logical flag
                                           !   .TRUE. if a member
                                           !   .FALSE. otherwise
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pisa_class_f

```

**Name:** H5Piterate

**Purpose:**

Iterates over properties in a property class or list.

**Signature:**

```
int H5Piterate( hid_t id, int *idx, H5P_iterate_t iter_func, void *iter_data )
```

**Description:**

H5Piterate iterates over the properties in the property object specified in *id*, which may be either a property list or a property class, performing a specified operation on each property in turn.

For each property in the object, *iter\_func* and the additional information specified below are passed to the H5P\_iterate\_t operator function.

The iteration begins with the *idx*-th property in the object; the next element to be processed by the operator is returned in *idx*. If *idx* is NULL, the iterator starts at the first property; since no stopping point is returned in this case, the iterator cannot be restarted if one of the calls to its operator returns non-zero.

The prototype for the H5P\_iterate\_t operator is as follows:

```
typedef herr_t (*H5P_iterate_t)( hid_t id, const char *name, void *iter_data )
```

The operation receives the property list or class identifier for the object being iterated over, *id*, the name of the current property within the object, *name*, and the pointer to the operator data passed in to H5Piterate, *iter\_data*.

The valid return values from an operator are as follows:

- Zero Causes the iterator to continue, returning zero when all properties have been processed
- Positive Causes the iterator to immediately return that positive value, indicating short-circuit success. The iterator can be restarted at the index of the next property
- Negative Causes the iterator to immediately return that value, indicating failure. The iterator can be restarted at the index of the next property

H5Piterate assumes that the properties in the object identified by *id* remain unchanged through the iteration. If the membership changes during the iteration, the function's behavior is undefined.

**Parameters:**

<i>hid_t id</i>	IN: Identifier of property object to iterate over
<i>int *idx</i>	IN/OUT: Index of the property to begin with
<i>H5P_iterate_t iter_func</i>	IN: Function pointer to function to be called with each property iterated over
<i>void *iter_data</i>	IN/OUT: Pointer to iteration data from user

**Returns:**

Success: the return value of the last call to *iter\_func* if it was non-zero; zero if all properties have been processed  
 Failure: a negative value

**Fortran90 Interface:**

None.

**Name:** H5Pmodify\_filter

**Signature:**

```
herr_t H5Pmodify_filter(hid_t plist, H5Z_filter_t filter_id, unsigned int flags, size_t
cd_nelmts, const unsigned int cd_values[ ] )
```

**Purpose:**

Modifies a filter in the filter pipeline.

**Description:**

H5Pmodify\_filter modifies the specified filter\_id in the filter pipeline. plist must be a dataset creation property list and the modified filter will be in a permanent filter pipeline.

The filter\_id, flags cd\_nelmts[ ], and cd\_values parameters are used in the same manner and accept the same values as described in the discussion of H5Pset\_filter.

**Note:**

This function currently supports only the permanent filter pipeline; plist\_id must be a dataset creation property list.

**Parameters:**

<i>hid_t</i> plist_id	IN: Property list identifier.
<i>H5Z_filter_t</i> filter_id	IN: Filter to be modified.
<i>unsigned int</i> flags	IN: Bit vector specifying certain general properties of the filter.
<i>size_t</i> cd_nelmts	IN: Number of elements in cd_values.
<i>const unsigned int</i> cd_values[ ]	IN: Auxiliary data for the filter.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pmodify\_filter\_f

```
SUBROUTINE h5pmodify_filter_f(prp_id, filter, flags, cd_nelmts, &
                             cd_values, hdferr)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER, INTENT(IN)       :: filter      ! Filter to be modified
  INTEGER, INTENT(IN)       :: flags       ! Bit vector specifying certain
                                           ! general properties of the filter
  INTEGER(SIZE_T), INTENT(IN) :: cd_nelmts ! Number of elements in cd_values
  INTEGER, DIMENSION(*), INTENT(IN) :: cd_values
                                           ! Auxiliary data for the filter
  INTEGER, INTENT(OUT)      :: hdferr      ! Error code
                                           ! 0 on success and -1 on failure

END SUBROUTINE h5pmodify_filter_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Pregister

**Signatures:**

```
herr_t H5Pregister( hid_t class, const char *name, size_t size, void
*default, H5P_prp_create_func_t create, H5P_prp_set_func_t set,
H5P_prp_get_func_t get, H5P_prp_delete_func_t delete,
H5P_prp_copy_func_t copy, H5P_prp_close_func_t close ) [1]
```

```
herr_t H5Pregister( hid_t class, const char *name, size_t size,
void *default, H5P_prp_create_func_t create,
H5P_prp_set_func_t set, H5P_prp_get_func_t get,
H5P_prp_delete_func_t delete, H5P_prp_copy_func_t copy,
H5P_prp_compare_func_t compare, H5P_prp_close_func_t close ) [2]
```

**Purpose:**

Returns information about the specified filter.

**Description:**

H5Pregister is a macro that is mapped to either H5Pregister1 or H5Pregister2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. For example:

- ◊ The H5Pregister macro will be mapped to H5Pregister1 and will use the H5Pregister1 syntax (first signature above) if an application is coded for HDF5 Release 1.6.x.
- ◊ The H5Pregister macro mapped to H5Pregister2 and will use the H5Pregister2 syntax (second signature above) if an application is coded for HDF5 Release 1.8.x.

Macro use and mappings are fully described in “API Compatibility Macros in HDF5” we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Pregister is mapped to the most recent version of the function, currently H5Pregister2. If the library and/or application is compiled for Release 1.6 emulation, H5Pregister will be mapped to H5Pregister1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Pregister mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Pregister2
Enable deprecated symbols	H5Pregister2
Disable deprecated symbols	H5Pregister2
Emulate Release 1.6 interface	H5Pregister1

---

Function-level macros

```
H5Pregister_vers = 2      H5Pregister2
```

```
H5Pregister_vers = 1      H5Pregister1
```

**Interface history:** Signature [1] above is the original H5Pregister interface and the only interface available prior to HDF5 Release 1.8.0. This signature and the corresponding function are now deprecated but will remain directly callable as H5Pregister1.

Signature [2] above was introduced with HDF5 Release 1.8.0 and is the recommended and default interface. It is directly callable as H5Pregister2.

See “API Compatibility Macros in HDF5” for circumstances under which either of these functions might not be available in an installed instance of the HDF5 Library.

**Fortran90 Interface: h5pregister\_f**

```
SUBROUTINE h5pregister_f
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: class      ! Property list class identifier
  CHARACTER(LEN=*), INTENT(IN) :: name    ! Name of property to register
  INTEGER(SIZE_T), INTENT(IN) :: size     ! Size of the property value
  TYPE,          INTENT(IN) :: value      ! Property value
                                          ! Supported types are:
                                          !   INTEGER
                                          !   REAL
                                          !   DOUBLE PRECISION
                                          !   CHARACTER(LEN=*)
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pregister_f
```

**History:**

Release	C
---------	---

1.8.0	<p>The function H5Pregister renamed to H5Pregister1 and deprecated in this release.</p> <p>The macro H5Pregister and the function H5Pregister2 introduced in this release.</p>
-------	--



**Name:** H5Pregister1

**Signature:**

```
herr_t H5Pregister1( hid_t class, const char * name, size_t size, void * default,
H5P_prp_create_func_t create, H5P_prp_set_func_t set, H5P_prp_get_func_t get,
H5P_prp_delete_func_t delete, H5P_prp_copy_func_t copy, H5P_prp_close_func_t close )
```

**Purpose:**

Registers a permanent property with a property list class.

**Notice:**

*This function is renamed from H5Pregister and deprecated in favor of the function H5Pregister2 and or the new macro H5Pregister.*

**Description:**

H5Pregister1 registers a new property with a property list class. The property will exist in all property list objects of class created after this routine finishes. The name of the property must not already exist, or this routine will fail. The default property value must be provided and all new property lists created with this property will have the property value set to the default value. Any of the callback routines may be set to NULL if they are not needed.

Zero-sized properties are allowed and do not store any data in the property list. These may be used as flags to indicate the presence or absence of a particular piece of information. The default pointer for a zero-sized property may be set to NULL. The property create and close callbacks are called for zero-sized properties, but the set and get callbacks are never called.

The create routine is called when a new property list with this property is being created. The H5P\_prp\_create\_func\_t callback function is defined as follows:

```
typedef herr_t (*H5P_prp_create_func_t)( const char *name, size_t size, void
*initial_value);
```

The parameters to this callback function are defined as follows:

<code>const char *name</code>	IN: The name of the property being modified
<code>size_t size</code>	IN: The size of the property in bytes
<code>void</code>	IN/OUT: The default value for the property being created, which will
<code>*initial_value</code>	be passed to H5Pregister1

The create routine may modify the value to be set and those changes will be stored as the initial value of the property. If the create routine returns a negative value, the new property value is not copied into the property and the create routine returns an error value.

The set routine is called before a new value is copied into the property. The H5P\_prp\_set\_func\_t callback function is defined as follows:

```
typedef herr_t (*H5P_prp_set_func_t)( hid_t prop_id, const char *name, size_t size, void
*new_value);
```

The parameters to this callback function are defined as follows:

<code>hid_t prop_id</code>	IN: The identifier of the property list being modified
<code>const char *name</code>	IN: The name of the property being modified
<code>size_t size</code>	IN: The size of the property in bytes
<code>void **new_value</code>	IN/OUT: Pointer to new value pointer for the property being modified

The `set` routine may modify the value pointer to be set and those changes will be used when setting the property's value. If the `set` routine returns a negative value, the new property value is not copied into the property and the `set` routine returns an error value. The `set` routine will not be called for the initial value, only the `create` routine will be called.

**Note:** The `set` callback function may be useful to range check the value being set for the property or may perform some transformation or translation of the value set. The `get` callback would then reverse the transformation or translation. A single `get` or `set` callback could handle multiple properties by performing different actions based on the property name or other properties in the property list.

The `get` routine is called when a value is retrieved from a property value. The `H5P_prp_get_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_get_func_t)( hid_t prop_id, const char *name, size_t size, void
*value);
```

The parameters to the callback function are defined as follows:

<code>hid_t prop_id</code>	IN: The identifier of the property list being queried
<code>const char *name</code>	IN: The name of the property being queried
<code>size_t size</code>	IN: The size of the property in bytes
<code>void *value</code>	IN/OUT: The value of the property being returned

The `get` routine may modify the value to be returned from the query and those changes will be returned to the calling routine. If the `set` routine returns a negative value, the query routine returns an error value.

The `delete` routine is called when a property is being deleted from a property list. The `H5P_prp_delete_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_delete_func_t)( hid_t prop_id, const char *name, size_t size, void
*value);
```

The parameters to the callback function are defined as follows:

<code>hid_t prop_id</code>	IN: The identifier of the property list the property is being deleted from
<code>const char *name</code>	IN: The name of the property in the list
<code>size_t size</code>	IN: The size of the property in bytes
<code>void *value</code>	IN: The value for the property being deleted

The `delete` routine may modify the value passed in, but the value is not used by the library when the `delete` routine returns. If the `delete` routine returns a negative value, the property list delete routine returns an error value but the property is still deleted.

The `copy` routine is called when a new property list with this property is being created through a copy operation. The `H5P_prp_copy_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_copy_func_t)( const char *name, size_t size, void *value);
```

The parameters to the callback function are defined as follows:

<code>const char *name</code>	IN: The name of the property being copied
<code>size_t size</code>	IN: The size of the property in bytes
<code>void *value</code>	IN/OUT: The value for the property being copied

The `copy` routine may modify the value to be set and those changes will be stored as the new value of the property. If the `copy` routine returns a negative value, the new property value is not copied into the property and the `copy` routine returns an error value.

The `close` routine is called when a property list with this property is being closed. The `H5P_prp_close_func_t` callback function is defined as follows:

*typedef herr\_t (\*H5P\_prp\_close\_func\_t)( hid\_t prop\_id, const char \*name, size\_t size, void \*value);* The parameters to the callback function are defined as follows:

*hid\_t prop\_id* IN: The identifier of the property list being closed  
*const char \*name* IN: The name of the property in the list  
*size\_t size* IN: The size of the property in bytes  
*void \*value* IN: The value for the property being closed

The `close` routine may modify the value passed in, but the value is not used by the library when the `close` routine returns. If the `close` routine returns a negative value, the property list `close` routine returns an error value but the property list is still closed.

#### Parameters:

<i>hid_t class</i>	IN: Property list class to register permanent property within
<i>const char *name</i>	IN: Name of property to register
<i>size_t size</i>	IN: Size of property in bytes
<i>void *default</i>	IN: Default value for property in newly created property lists
<i>H5P_prp_create_func_t create</i>	IN: Callback routine called when a property list is being created and the property value will be initialized
<i>H5P_prp_set_func_t set</i>	IN: Callback routine called before a new value is copied into the property's value
<i>H5P_prp_get_func_t get</i>	IN: Callback routine called when a property value is retrieved from the property
<i>H5P_prp_delete_func_t delete</i>	IN: Callback routine called when a property is deleted from a property list
<i>H5P_prp_copy_func_t copy</i>	IN: Callback routine called when a property is copied from a property list
<i>H5P_prp_close_func_t close</i>	IN: Callback routine called when a property list is being closed and the property value will be disposed of

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** h5pregister\_f

```

SUBROUTINE h5pregister_f
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: class      ! Property list class identifier
  CHARACTER(LEN=*), INTENT(IN) :: name    ! Name of property to register
  INTEGER(SIZE_T), INTENT(IN) :: size     ! Size of the property value
  TYPE,          INTENT(IN) :: value      ! Property value
                                           ! Supported types are:
                                           !   INTEGER
                                           !   REAL
                                           !   DOUBLE PRECISION
                                           !   CHARACTER(LEN=*)
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pregister_f

```

**History:**

Release	C
1.8.0	Function H5Pregister renamed to H5Pregister1 and deprecated in this release.

**Name:** H5Pregister2

**Signature:**

```
herr_t H5Pregister2(hid_t class, const char * name, size_t size, void * default,
H5P_prp_create_func_t create, H5P_prp_set_func_t set, H5P_prp_get_func_t get,
H5P_prp_delete_func_t delete, H5P_prp_copy_func_t copy, H5P_prp_compare_func_t compare,
H5P_prp_close_func_t close )
```

**Purpose:**

Registers a permanent property with a property list class.

**Description:**

H5Pregister2 registers a new property with a property list class. The property will exist in all property list objects of `class` created after this routine finishes. The name of the property must not already exist, or this routine will fail. The default property value must be provided and all new property lists created with this property will have the property value set to the default value. Any of the callback routines may be set to NULL if they are not needed.

Zero-sized properties are allowed and do not store any data in the property list. These may be used as flags to indicate the presence or absence of a particular piece of information. The default pointer for a zero-sized property may be set to NULL. The property `create` and `close` callbacks are called for zero-sized properties, but the `set` and `get` callbacks are never called.

The `create` routine is called when a new property list with this property is being created. The H5P\_prp\_create\_func\_t callback function is defined as follows:

```
typedef herr_t (*H5P_prp_create_func_t)(const char *name, size_t size, void
*initial_value); The parameters to this callback function are defined as follows:
```

<i>const char</i> *name	IN: The name of the property being modified
<i>size_t</i> size	IN: The size of the property in bytes
<i>void</i>	IN/OUT: The default value for the property being created, which will
*initial_value	be passed to H5Pregister2

The `create` routine may modify the value to be set and those changes will be stored as the initial value of the property. If the `create` routine returns a negative value, the new property value is not copied into the property and the `create` routine returns an error value.

The `set` routine is called before a new value is copied into the property. The H5P\_prp\_set\_func\_t callback function is defined as follows:

```
typedef herr_t (*H5P_prp_set_func_t)(hid_t prop_id, const char *name, size_t size, void
*new_value); The parameters to this callback function are defined as follows:
```

<i>hid_t</i> prop_id	IN: The identifier of the property list being modified
<i>const char</i> *name	IN: The name of the property being modified
<i>size_t</i> size	IN: The size of the property in bytes
<i>void</i> **new_value	IN/OUT: Pointer to new value pointer for the property being modified

The `set` routine may modify the value pointer to be set and those changes will be used when setting the property's value. If the `set` routine returns a negative value, the new property value is not copied into the property and the `set` routine returns an error value. The `set` routine will not be called for the initial value, only the `create` routine will be called.

**Note:** The `set` callback function may be useful to range check the value being set for the property or may perform some transformation or translation of the value set. The `get` callback would then reverse the transformation or translation. A single `get` or `set` callback could handle multiple properties by performing different actions based on the property name or other properties in the property list.

The `get` routine is called when a value is retrieved from a property value. The `H5P_prp_get_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_get_func_t)( hid_t prop_id, const char *name, size_t size, void
*value);
```

The parameters to the callback function are defined as follows:

<code>hid_t prop_id</code>	IN: The identifier of the property list being queried
<code>const char *name</code>	IN: The name of the property being queried
<code>size_t size</code>	IN: The size of the property in bytes
<code>void *value</code>	IN/OUT: The value of the property being returned

The `get` routine may modify the value to be returned from the query and those changes will be returned to the calling routine. If the `set` routine returns a negative value, the query routine returns an error value.

The `delete` routine is called when a property is being deleted from a property list. The `H5P_prp_delete_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_delete_func_t)( hid_t prop_id, const char *name, size_t size, void
*value);
```

The parameters to the callback function are defined as follows:

<code>hid_t prop_id</code>	IN: The identifier of the property list the property is being deleted from
<code>const char *name</code>	IN: The name of the property in the list
<code>size_t size</code>	IN: The size of the property in bytes
<code>void *value</code>	IN: The value for the property being deleted

The `delete` routine may modify the value passed in, but the value is not used by the library when the `delete` routine returns. If the `delete` routine returns a negative value, the property list delete routine returns an error value but the property is still deleted.

The `copy` routine is called when a new property list with this property is being created through a copy operation. The `H5P_prp_copy_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_copy_func_t)( const char *name, size_t size, void *value);
```

The parameters to the callback function are defined as follows:

<code>const char *name</code>	IN: The name of the property being copied
<code>size_t size</code>	IN: The size of the property in bytes
<code>void *value</code>	IN/OUT: The value for the property being copied

The `copy` routine may modify the value to be set and those changes will be stored as the new value of the property. If the `copy` routine returns a negative value, the new property value is not copied into the property and the `copy` routine returns an error value.

The `compare` routine is called when a property list with this property is compared to another property list with the same property. The `H5P_prp_compare_func_t` callback function is defined as follows:

```
typedef int (*H5P_prp_compare_func_t)( const void *value1, const void *value2, size_t
size);
```

The parameters to the callback function are defined as follows:

`const void *value1` IN: The value of the first property to compare  
`const void *value2` IN: The value of the second property to compare  
`size_t size` IN: The size of the property in bytes

The `compare` routine may *not* modify the values. The `compare` routine should return a positive value if `value1` is greater than `value2`, a negative value if `value2` is greater than `value1` and zero if `value1` and `value2` are equal.

The `close` routine is called when a property list with this property is being closed. The `H5P_prp_close_func_t` callback function is defined as follows:

```
typedef herr_t (*H5P_prp_close_func_t)( hid_t prop_id, const char *name, size_t size, void
*value);
```

The parameters to the callback function are defined as follows:

`hid_t prop_id` IN: The identifier of the property list being closed  
`const char *name` IN: The name of the property in the list  
`size_t size` IN: The size of the property in bytes  
`void *value` IN: The value for the property being closed

The `close` routine may modify the value passed in, but the value is not used by the library when the `close` routine returns. If the `close` routine returns a negative value, the property list `close` routine returns an error value but the property list is still closed.

#### Parameters:

<code>hid_t class</code>	IN: Property list class to register permanent property within
<code>const char *name</code>	IN: Name of property to register
<code>size_t size</code>	IN: Size of property in bytes
<code>void *default</code>	IN: Default value for property in newly created property lists
<code>H5P_prp_create_func_t create</code>	IN: Callback routine called when a property list is being created and the property value will be initialized
<code>H5P_prp_set_func_t set</code>	IN: Callback routine called before a new value is copied into the property's value
<code>H5P_prp_get_func_t get</code>	IN: Callback routine called when a property value is retrieved from the property
<code>H5P_prp_delete_func_t delete</code>	IN: Callback routine called when a property is deleted from a property list
<code>H5P_prp_copy_func_t copy</code>	IN: Callback routine called when a property is copied from a property list

*H5P\_prp\_compare\_func\_t* compare

IN: Callback routine called when a property is compared with another property list

*H5P\_prp\_close\_func\_t* close

IN: Callback routine called when a property list is being closed and the property value will be disposed of

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------



**Name:** H5Premove

**Signature:**

```
herr_t H5Premove( hid_t plid; const char *name )
```

**Purpose:**

Removes a property from a property list.

**Description:**

H5Premove removes a property from a property list.

Both properties which were in existence when the property list was created (i.e. properties registered with H5Pregister) and properties added to the list after it was created (i.e. added with H5Pinsert1) may be removed from a property list. Properties do not need to be removed from a property list before the list itself is closed; they will be released automatically when H5Pclose is called.

If a close callback exists for the removed property, it will be called before the property is released.

**Parameters:**

<i>hid_t</i> plid	IN: Identifier of the property list to modify
<i>const char</i> *name	IN: Name of property to remove

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** h5premove\_f

```
SUBROUTINE h5premove_f(plid, name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plid    ! Property list identifier
  CHARACTER(LEN=*), INTENT(IN) :: name ! Name of property to remove
  INTEGER, INTENT(OUT) :: hdferr       ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5premove_f
```

**Name:** H5Premove\_filter

**Signature:**

*herr\_t* H5Premove\_filter(*hid\_t* plist, *H5Z\_filter\_t* filter)

**Purpose:**

Delete one or more filters in the filter pipeline.

**Description:**

H5Premove\_filter removes the specified filter from the filter pipeline in the dataset creation property list *plist*.

The *filter* parameter specifies the filter to be removed. Valid values for use in *filter* are as follows:

H5Z_FILTER_ALL	Removes all filters from the permanent filter pipeline.
H5Z_FILTER_DEFLATE	Data compression filter, employing the gzip algorithm
H5Z_FILTER_SHUFFLE	Data shuffling filter
H5Z_FILTER_FLETCHER32	Error detection filter, employing the Fletcher32 checksum algorithm
H5Z_FILTER_SZIP	Data compression filter, employing the SZIP algorithm

Additionally, user-defined filters can be removed with this routine by passing the filter identifier with which they were registered with the HDF5 Library.

Attempting to remove a filter that is not in the permanent filter pipeline is an error.

**Note:**

This function currently supports only the permanent filter pipeline; *plist* must be a dataset creation property list.

**Parameters:**

*hid\_t* plist\_id

IN: Dataset creation property list identifier.

*H5Z\_filter\_t* filter

IN: Filter to be deleted.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5premove\_filter\_f

SUBROUTINE h5premove\_filter\_f(prp\_id, filter, hdferr)

```

IMPLICIT NONE
INTEGER(HID_T), INTENT(IN) :: prp_id ! Dataset creation property
                                   ! list identifier
INTEGER, INTENT(IN) :: filter       ! Filter to be removed
                                   ! Valid values are:
                                   !   H5Z_FILTER_ALL_F
                                   !   H5Z_FILTER_DEFLATE_F
                                   !   H5Z_FILTER_SHUFFLE_F
                                   !   H5Z_FILTER_FLETCHER32_F
                                   !   H5Z_FILTER_SZIP_F
                                   !

```

```
        INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                           ! 0 on success, -1 on failure
    END SUBROUTINE h5premove_filter_f
```

**History:**

Release	C
1.6.3	Function introduced in this release. Fortran subroutine introduced in this release.

**Name:** H5Pset

**Signature:**

```
herr_t H5Pset( hid_t plid, const char *name, void *value )
```

**Purpose:**

Sets a property list value.

**Description:**

H5Pset sets a new value for a property in a property list. If there is a set callback routine registered for this property, the value will be passed to that routine and any changes to the value will be used when setting the property value. The information pointed to by the value pointer (possibly modified by the set callback) is copied into the property list value and may be changed by the application making the H5Pset call without affecting the property value.

The property name must exist or this routine will fail.

If the set callback routine returns an error, the property value will not be modified.

This routine may not be called for zero-sized properties and will return an error in that case.

**Parameters:**

<i>hid_t</i> plid;	IN: Property list identifier to modify
<i>const char</i> *name;	IN: Name of property to modify
<i>void</i> *value;	IN: Pointer to value to set the property to

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** h5pset\_f

```
SUBROUTINE h5pset_f(plid, name, value, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plid      ! Property list identifier
  CHARACTER(LEN=*), INTENT(IN) :: name    ! Name of property to set
  TYPE,          INTENT(IN) :: value      ! Property value
                                          ! Supported types are:
                                          !   INTEGER
                                          !   REAL
                                          !   DOUBLE PRECISION
                                          !   CHARACTER(LEN=*)
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pset_f
```

**Name:** H5Pset\_alignment

**Signature:**

*herr\_t* H5Pset\_alignment(*hid\_t* plist, *hsize\_t* threshold, *hsize\_t* alignment )

**Purpose:**

Sets alignment properties of a file access property list.

**Description:**

H5Pset\_alignment sets the alignment properties of a file access property list so that any file object greater than or equal in size to `threshold` bytes will be aligned on an address which is a multiple of `alignment`. The addresses are relative to the end of the user block; the alignment is calculated by subtracting the user block size from the absolute file address and then adjusting the address to be a multiple of `alignment`.

Default values for `threshold` and `alignment` are one, implying no alignment. Generally the default values will result in the best performance for single-process access to the file. For MPI IO and other parallel systems, choose an alignment which is a multiple of the disk block size.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier for a file access property list.
<i>hsize_t</i> threshold	IN: Threshold value. Note that setting the threshold value to 0 (zero) has the effect of a special case, forcing everything to be aligned.
<i>hsize_t</i> alignment	IN: Alignment value.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_alignment\_f

```

SUBROUTINE h5pset_alignment_f(prp_id, threshold, alignment, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id           ! Property list identifier
  INTEGER(HSIZE_T), INTENT(IN) :: threshold      ! Threshold value
  INTEGER(HSIZE_T), INTENT(IN) :: alignment     ! Alignment value
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5pset_alignment_f
```

**Name:** H5Pset\_alloc\_time

**Signature:**

```
herr_t H5Pset_alloc_time(hid_t plist_id, H5D_alloc_time_t alloc_time)
```

**Purpose:**

Sets the timing for storage space allocation.

**Description:**

H5Pset\_alloc\_time sets up the timing for the allocation of storage space for a dataset's raw data. This property is set in the dataset creation property list `plist_id`.

Timing is specified in `alloc_time` with one of the following values:

H5D_ALLOC_TIME_DEFAULT	Allocate dataset storage space at the default time. (Defaults differ by storage method.)
H5D_ALLOC_TIME_EARLY	Allocate all space when the dataset is created. (Default for compact datasets.)
H5D_ALLOC_TIME_INCR	Allocate space incrementally, as data is written to the dataset. (Default for chunked storage datasets.) <ul style="list-style-type: none"> <li>◆ Chunked datasets: Storage space allocation for each chunk is deferred until data is written to the chunk.</li> <li>◆ Contiguous datasets: Incremental storage space allocation for contiguous data is treated as late allocation.</li> <li>◆ Compact datasets: Incremental allocation is not allowed with compact datasets; H5Pset_alloc_time will return an error.</li> </ul>
H5D_ALLOC_TIME_LATE	Allocate all space when data is first written to the dataset. (Default for contiguous datasets.)

**Note:**

H5Pset\_alloc\_time is designed to work in concert with the dataset fill value and fill value write time properties, set with the functions H5Pset\_fill\_value and H5Pset\_fill\_time.

See H5Dcreate for further cross-references.

**Parameters:**

`hid_t plist_id` IN: Dataset creation property list identifier.  
`H5D_alloc_time_t alloc_time` IN: When to allocate dataset storage space.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_alloc\_time\_f

```
SUBROUTINE h5pset_alloc_time_f(plist_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! Dataset creation property
                                          ! list identifier
  INTEGER(HSIZE_T), INTENT(IN) :: flag ! Allocation time flag
                                          ! Possible values are:
                                          !   H5D_ALLOC_TIME_ERROR_F
                                          !   H5D_ALLOC_TIME_DEFAULT_F
                                          !   H5D_ALLOC_TIME_EARLY_F
                                          !   H5D_ALLOC_TIME_LATE_F
                                          !   H5D_ALLOC_TIME_INCR_F
```

```
INTEGER, INTENT(OUT)      :: hdferr      ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_alloc_time_f
```

**History:**

Release	C
1.6.0	Function introduced in this release.

**Name:** H5Pset\_attr\_creation\_order

**Signature:**

```
herr_t H5Pset_attr_creation_order( hid_t ocpl_id, unsigned crt_order_flags )
```

**Purpose:**

Sets tracking and indexing of attribute creation order.

**Description:**

H5Pset\_attr\_creation\_order sets flags specifying whether to track and index attribute creation order on an object.

ocpl\_id is a dataset or group creation property list identifier. The term ocpl, for object creation property list, is used when different types of objects may be involved.

crt\_order\_flags contains flags with the following meanings:

H5P_CRT_ORDER_TRACKED	Attribute creation order is tracked but not necessarily indexed.
H5P_CRT_ORDER_INDEXED	Attribute creation order is indexed (requires H5P_CRT_ORDER_TRACKED).

Default behavior is that attribute creation order is neither tracked nor indexed.

**Parameters:**

hid_t ocpl_id	IN: Object creation property list identifier
unsigned crt_order_flags	IN: Flags specifying whether to track and index attribute creation order <i>Default: No flag set; attribute creation order is neither tracked nor indexed.</i>

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pget\_attr\_creation\_order\_f

```
SUBROUTINE h5pget_attr_creation_order_f(ocpl_id, crt_order_flags, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: ocpl_id
                                ! Object (group or dataset) creation property
                                ! list identifier
  INTEGER, INTENT(OUT) :: crt_order_flags
                                ! Flags specifying whether to track
                                ! and index attribute creation order
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pget_attr_creation_order_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.



**Name:** H5Pset\_attr\_phase\_change

**Signature:**

```
herr_t H5Pset_attr_phase_change( hid_t ocpl_id, unsigned max_compact, unsigned
min_dense )
```

**Purpose:**

Sets attribute storage phase change thresholds.

**Description:**

H5Pset\_attr\_phase\_change sets threshold values for attribute storage on an object. These thresholds determine the point at which attribute storage changes from compact storage (i.e., storage in the object header) to dense storage (i.e., storage in a heap and indexed with a B-tree).

In the general case, attributes are initially kept in compact storage. When the number of attributes exceeds `max_compact`, attribute storage switches to dense storage. If the number of attributes subsequently falls below `min_dense`, the attributes are returned to compact storage.

If `max_compact` is set to 0 (zero), dense storage always used.

`ocpl_id` is a dataset or group creation property list identifier. The term `ocpl`, for object creation property list, is used when different types of objects may be involved.

**Parameters:**

<i>hid_t</i> ocpl_id	IN: Object (group or dataset) creation property list identifier
<i>unsigned</i> max_compact	IN: Maximum number of attributes to be stored in compact storage (Default: 8)
<i>unsigned</i> min_dense	IN: Minimum number of attributes to be stored in dense storage (Default: 6)

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_attr\_phase\_change\_f

```
SUBROUTINE h5pset_attr_phase_change_f(ocpl_id, max_compact, min_dense, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: ocpl_id
                                ! Object (dataset or group) creation property
                                ! list identifier
  INTEGER, INTENT(IN) :: max_compact
                                ! Maximum number of attributes to be stored in
                                ! compact storage (Default: 8)
  INTEGER, INTENT(IN) :: min_dense
                                ! Minimum number of attributes to be stored in
                                ! dense storage (Default: 6)
  INTEGER, INTENT(OUT) :: hdferr
                                ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_attr_phase_change_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pset\_btree\_ratios

**Signature:**

*herr\_t* H5Pset\_btree\_ratios(*hid\_t* plist, *double* left, *double* middle, *double* right )

**Purpose:**

Sets B-tree split ratios for a dataset transfer property list.

**Description:**

H5Pset\_btree\_ratios sets the B-tree split ratios for a dataset transfer property list. The split ratios determine what percent of children go in the first node when a node splits.

The ratio *left* is used when the splitting node is the left-most node at its level in the tree; the ratio *right* is used when the splitting node is the right-most node at its level; and the ratio *middle* is used for all other cases.

A node which is the only node at its level in the tree uses the ratio *right* when it splits.

All ratios are real numbers between 0 and 1, inclusive.

**Parameters:**

<i>hid_t</i> plist	IN: The dataset transfer property list identifier.
<i>double</i> left	IN: The B-tree split ratio for left-most nodes.
<i>double</i> right	IN: The B-tree split ratio for right-most nodes and lone nodes.
<i>double</i> middle	IN: The B-tree split ratio for all other nodes.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_btree\_ratios\_f

```

SUBROUTINE h5pset_btree_ratios_f(prp_id, left, middle, right, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id
                                ! Property list identifier
  REAL, INTENT(IN) :: left      ! The B-tree split ratio for left-most nodes
  REAL, INTENT(IN) :: middle    ! The B-tree split ratio for all other nodes
  REAL, INTENT(IN) :: right     ! The B-tree split ratio for right-most
                                ! nodes and lone nodes.
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_btree_ratios_f

```

**Name:** H5Pset\_buffer

**Signature:**

```
herr_t H5Pset_buffer(hid_t plist, hsize_t size, void *tconv, void *bkg)
```

**Purpose:**

Sets type conversion and background buffers.

**Description:**

Given a dataset transfer property list, H5Pset\_buffer sets the maximum size for the type conversion buffer and background buffer and optionally supplies pointers to application-allocated buffers. If the buffer size is smaller than the entire amount of data being transferred between the application and the file, and a type conversion buffer or background buffer is required, then strip mining will be used.

Note that there are minimum size requirements for the buffer. Strip mining can only break the data up along the first dimension, so the buffer must be large enough to accommodate a complete slice that encompasses all of the remaining dimensions. For example, when strip mining a 100x200x300 hyperslab of a simple data space, the buffer must be large enough to hold 1x200x300 data elements. When strip mining a 100x200x300x150 hyperslab of a simple data space, the buffer must be large enough to hold 1x200x300x150 data elements.

If tconv and/or bkg are null pointers, then buffers will be allocated and freed during the data transfer.

The default value for the maximum buffer is 1 Mb.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier for the dataset transfer property list.
<i>hsize_t</i> size	IN: Size, in bytes, of the type conversion and background buffers.
<i>void</i> tconv	IN: Pointer to application-allocated type conversion buffer.
<i>void</i> bkg	IN: Pointer to application-allocated background buffer.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_buffer\_f

```
SUBROUTINE h5pset_buffer_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)    :: plist_id ! Dataset transfer property
                                      ! list identifier
  INTEGER(HSIZE_T), INTENT(IN) :: size      ! Conversion buffer size
  INTEGER, INTENT(OUT)         :: hdferr   ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pset_buffer_f
```

**History:**

Release	C
1.6.0	The size parameter has changed from type <i>hsize_t</i> to <i>size_t</i> .
1.4.0	The size parameter has changed to type <i>hsize_t</i> .

*Last modified: 15 April 2009*

**Name:** H5Pset\_cache

**Signature:**

```
herr_t H5Pset_cache( hid_t plist_id, int mdc_nelmts, size_t rdcc_nelmts, size_t
rdcc_nbytes, double rdcc_w0 )
```

**Purpose:**

Sets the raw data chunk cache parameters.

**Description:**

H5Pset\_cache sets the number of elements, the total number of bytes, and the preemption policy value in the raw data chunk cache.

The *plist\_id* is a file access property list.

The number of elements (objects) in the raw data chunk cache is *rdcc\_nelmts*. The total size of the raw data chunk cache and the preemption policy are *rdcc\_nbytes* and *rdcc\_w0*, respectively.

Any (or all) of the H5Pget\_cache pointer arguments may be null pointers.

The *rdcc\_w0* value should be between 0 and 1 inclusive and indicates how much chunks that have been fully read are favored for preemption. A value of zero means fully read chunks are treated no differently than other chunks (the preemption is strictly LRU) while a value of one means fully read chunks are always preempted before other chunks.

The *\*mdc\_nelmts* parameter is no longer used; any value passed in that parameter is ignored.

**Note:**

Raw dataset chunk caching is not currently supported when using the MPI I/O and MPI POSIX file drivers in read/write mode; see H5Pset\_fapl\_mpio and H5Pset\_fapl\_mpio, respectively. When using one of these file drivers, all calls to H5Dread and H5Dwrite will access the disk directly, and H5Pset\_cache will have no effect on performance.

Raw dataset chunk caching is supported when these drivers are used in read-only mode.

**Parameters:**

<i>hid_t</i> <i>plist_id</i>	IN: Identifier of the file access property list.
<i>int</i> <i>mdc_nelmts</i>	IN: <i>No longer used; any value passed is ignored.</i>
<i>size_t</i> <i>rdcc_nelmts</i>	IN: Number of elements (objects) in the raw data chunk cache.
<i>size_t</i> <i>rdcc_nbytes</i>	IN: Total size of the raw data chunk cache, in bytes.
<i>double</i> <i>rdcc_w0</i>	IN: Preemption policy.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_cache\_f

```
SUBROUTINE h5pset_cache_f(prp_id, mdc_nelmts, rdcc_nelmts, rdcc_nbytes, rdcc_w0, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id           ! Property list identifier
  INTEGER, INTENT(IN) :: mdc_nelmts              ! Number of elements (objects)
                                                ! in the meta data cache
  INTEGER(SIZE_T), INTENT(IN) :: rdcc_nelmts     ! Number of elements (objects)
                                                ! in the meta data cache
  INTEGER(SIZE_T), INTENT(IN) :: rdcc_nbytes     ! Total size of the raw data
                                                ! chunk cache, in bytes
  REAL, INTENT(IN) :: rdcc_w0                   ! Preemption policy
  INTEGER :: hdferr
```

```
INTEGER, INTENT(OUT) :: hdferr                                ! Error code
                                                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_cache_f
```

**History:**

Release	Change
1.8.0	In C, use of the <code>mdc_nelmts</code> parameter discontinued. Metadata cache configuration is managed with <code>H5Pset_mdc_config</code> and <code>H5Pget_mdc_config</code> .
1.6.1	Fortran <code>rdcc_nbytes</code> parameter type changed to <code>INTEGER(SIZE_T)</code> .
1.6.0	In C, the <code>rdcc_nbytes</code> and <code>rdcc_nelmts</code> parameters changed from type <i>int</i> to <i>size_t</i> .

**Name:** H5Pset\_char\_encoding

**Signature:**

*herr\_t* H5Pset\_char\_encoding(*hid\_t* plist\_id, *H5T\_cset\_t* encoding)

**Purpose:**

Sets the character encoding used to encode a string.

**Description:**

H5Pset\_char\_encoding sets the character encoding used to encode strings or object names that are created with the property list *plist\_id*.

Valid values for encoding are defined in `H5Tpublic.h` and include the following:

H5T_CSET_ASCII	US ASCII
H5T_CSET_UTF8	UTF-8 Unicode encoding

**Parameters:**

<i>hid_t</i> plist_id	IN: Property list identifier
<i>H5T_cset_t</i> encoding	IN: String encoding character set

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_char\_encoding\_f

```
SUBROUTINE h5pset_char_encoding_f(plist_id, encoding, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id
                                ! Property list identifier
  INTEGER, INTENT(IN) :: encoding ! String encoding character set:
                                !   H5T_CSET_ASCII_F -> US ASCII
                                !   H5T_CSET_UTF8_F -> UTF-8 Unicode encoding
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_char_encoding_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pset\_chunk

**Signature:**

```
herr_t H5Pset_chunk(hid_t plist, int ndims, const hsize_t *dim)
```

**Purpose:**

Sets the size of the chunks used to store a chunked layout dataset.

**Description:**

H5Pset\_chunk sets the size of the chunks used to store a chunked layout dataset. This function is only valid for dataset creation property lists.

The ndims parameter currently must be the same size as the rank of the dataset.

The values of the dim array define the size of the chunks to store the dataset's raw data. The unit of measure for dim values is *dataset elements*.

As a side-effect of this function, the layout of the dataset is changed to H5D\_CHUNKED, if it is not already so set. (See H5Pset\_layout.)

*Note regarding fixed-size datasets:*

Chunk size cannot exceed the size of a fixed-size dataset. For example, a dataset consisting of a 5x4 fixed-size array cannot be defined with 10x10 chunks.

**Parameters:**

<i>hid_t</i> plist	IN: Dataset creation property list identifier.
<i>int</i> ndims	IN: The number of dimensions of each chunk.
<i>const hsize_t</i> *dim	IN: An array defining the size, in dataset elements, of each chunk.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_chunk\_f

```
SUBROUTINE h5pset_chunk_f(prp_id, ndims, dims, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN) :: ndims ! Number of chunk dimensions
  INTEGER(HSIZE_T), DIMENSION(ndims), INTENT(IN) :: dims
  ! Array containing sizes of
  ! chunk dimensions
  INTEGER, INTENT(OUT) :: hdferr ! Error code
  ! 0 on success and -1 on failure
END SUBROUTINE h5pset_chunk_f
```

*Last modified: 8 May 2009***Name:** H5Pset\_chunk\_cache**Signature:**

```
herr_t H5Pset_chunk_cache( hid_t dapl_id, size_t rdcc_nslots, size_t rdcc_nbytes,
double rdcc_w0 )
```

**Purpose:**

Sets the raw data chunk cache parameters.

**Motivation:**

H5Pset\_chunk\_cache is used to adjust the chunk cache parameters on a per-dataset basis, as opposed to a global setting for the file. The optimum chunk cache parameters vary wildly with different data layout and access patterns, so for optimal performance they must be set individually for each dataset. It may also be beneficial to reduce the size of the chunk cache for datasets whose performance is not important in order to save memory space.

**Description:**

H5Pset\_chunk\_cache sets the number of elements, the total number of bytes, and the preemption policy value in the raw data chunk cache on a dataset access property list. After calling this function, the values set in the property list will override the values in the file's file access property list.

The raw data chunk cache inserts chunks into the cache by first computing a hash value using the address of a chunk, then using that hash value as the chunk's index into the table of cached chunks. The size of this hash table, i.e., and the number of possible hash values, is determined by the `rdcc_nslots` parameter. If a different chunk in the cache has the same hash value, this causes a collision, which reduces efficiency. If inserting the chunk into cache would cause the cache to be too big, then the cache is pruned according to the `rdcc_w0` parameter.

**Parameters:**

<code>hid_t dapl_id</code>	IN: Dataset access property list identifier.
<code>size_t rdcc_nslots</code>	IN: The number of chunk slots in the raw data chunk cache for this dataset. Increasing this value reduces the number of cache collisions, but slightly increases the memory used. Due to the hashing strategy, this value should ideally be a prime number. As a rule of thumb, this value should be at least 10 times the number of chunks that can fit in <code>rdcc_nbytes</code> bytes. For maximum performance, this value should be set approximately 100 times that number of chunks.  The default value is 521. If the value passed is <code>H5D_CHUNK_CACHE_NSLOTS_DEFAULT</code> , then the property will not be set on <code>dapl_id</code> and the parameter will come from the file access property list used to open the file.
<code>size_t rdcc_nbytes</code>	IN: The total size of the raw data chunk cache for this dataset. In most cases increasing this number will improve performance, as long as you have enough free memory.  The default size is 1 MB. If the value passed is <code>H5D_CHUNK_CACHE_NBYTES_DEFAULT</code> , then the property will not be set on <code>dapl_id</code> and the parameter will come from the file access property list.
<code>double rdcc_w0</code>	IN: The chunk preemption policy for this dataset. This must be between 0 and 1 inclusive and indicates the weighting according to which chunks which have been fully read or written are penalized when determining which chunks



to flush from cache. A value of 0 means fully read or written chunks are treated no differently than other chunks (the preemption is strictly LRU) while a value of 1 means fully read or written chunks are always preempted before other chunks. If your application only reads or writes data once, this can be safely set to 1. Otherwise, this should be set lower, depending on how often you re-read or re-write the same data.

The default value is 0.75. If the value passed is `H5D_CHUNK_CACHE_W0_DEFAULT`, then the property will not be set on `dapl_id` and the parameter will come from the file access property list.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Example Usage:**

The following code sets the chunk cache to use a hash table with 12421 elements and a maximum size of 16 MB, while using the preemption policy specified for the entire file:

```
H5Pset_chunk_cache(dapl_id, 12421, 16*1024*1024, H5D_CHUNK_CACHE_W0_DEFAULT);
```

**See Also:**

`H5Pget_chunk_cache`, `H5Pset_cache`

**History:**

Release	Change
1.8.3	C function introduced in this release.

**Name:** H5Pset\_copy\_object

**Signature:**

*herr\_t* H5Pset\_copy\_object(*hid\_t* ocp\_plist\_id, *unsigned* copy\_options )

**Purpose:**

Sets properties to be used when an object is copied.

**Description:**

H5Pset\_copy\_object sets properties in the object copy property list ocp\_plist\_id that will be invoked when a new copy is made of an existing object.

ocp\_plist\_id is the object copy property list and specifies the properties governing the copying of the object.

Several flags, described in the following table, are available for inclusion in the object copy property list:

H5O_COPY_SHALLOW_HIERARCHY_FLAG	Copy only immediate members of a group. <i>Default behavior, without flag:</i> Recursively copy all objects below the group.
H5O_COPY_EXPAND_SOFT_LINK_FLAG	Expand soft links into new objects. <i>Default behavior, without flag:</i> Keep soft links as they are.
H5O_COPY_EXPAND_EXT_LINK_FLAG	Expand external link into new objects. <i>Default behavior, without flag:</i> Keep external links as they are.
H5O_COPY_EXPAND_REFERENCE_FLAG	Copy objects that are pointed to by references. <i>Default behavior, without flag:</i> Update only the values of object references.
H5O_COPY_WITHOUT_ATTR_FLAG	Copy object without copying attributes. <i>Default behavior, without flag:</i> Copy object along with all its attributes.

**Parameters:**

*hid\_t* ocp\_plist\_id      Object copy property list identifier  
*unsigned* copy\_options      Copy option(s) to be set

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_copy\_object\_f

```

SUBROUTINE h5pset_copy_object_f(ocp_plist_id, copy_options, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: ocp_plist_id
                                ! Object copy property list identifier
  INTEGER, INTENT(IN) :: copy_options
                                ! Copy option(s) to be set, valid options are:
                                !   H5O_COPY_SHALLOW_HIERARCHY_F
                                !   H5O_COPY_EXPAND_SOFT_LINK_F
                                !   H5O_COPY_EXPAND_EXT_LINK_F
                                !   H5O_COPY_EXPAND_REFERENCE_F
                                !   H5O_COPY_WITHOUT_ATTR_FLAG_F
  INTEGER, INTENT(OUT) :: hdferr
                                ! Error code

```

```
                                ! 0 on success and -1 on failure  
END SUBROUTINE h5pset_copy_object_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_create\_intermediate\_group

**Signature:**

```
herr_t H5Pset_create_intermediate_group(hid_t lcpl_id, unsigned
    crt_intermed_group)
```

**Purpose:**

Specifies in property list whether to create missing intermediate groups.

**Description:**

H5Pset\_create\_intermediate\_group specifies whether to set the link creation property list lcpl\_id so that calls to functions that create objects in groups different from the current working group will create intermediate groups that may be missing in the path of a new or moved object.

Functions that create objects in or move objects to a group other than the current working group make use of this property. H5Gcreate\_anon and H5Lmove are examples of such functions.

If crt\_intermed\_group is positive, the H5G\_CRT\_INTMD\_GROUP will be added to lcpl\_id (if it is not already there). Missing intermediate groups will be created upon calls to functions such as those listed above that use lcpl\_id.

If crt\_intermed\_group is non-positive, the H5G\_CRT\_INTMD\_GROUP, if present, will be removed from lcpl\_id. Missing intermediate groups will *not* be created upon calls to functions such as those listed above that use lcpl\_id.

**Parameters:**

<i>hid_t</i> lcpl_id	Link creation property list identifier
<i>unsigned</i> crt_intermed_group	Flag specifying whether to create intermediate groups upon the creation of an object

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Example:**

The following call sets the link creation property list lcpl\_id such that a call to H5Gcreate\_anon or other function using lcpl\_id will create any missing groups in the path to the new object:

```
herr_t ret_value = H5Pset_create_intermediate_group(lcpl_id, 1)
```

**Fortran90 Interface:**

```
SUBROUTINE h5pset_create_inter_group_f(lcpl_id, crt_intermed_group, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: lcpl_id
    ! Link creation property list identifier
  INTEGER, INTENT(IN) :: crt_intermed_group
    ! Specifying whether to create intermediate groups
    ! upon the creation of an object
  INTEGER, INTENT(OUT) :: hdferr
    ! Error code
    ! 0 on success and -1 on failure
END SUBROUTINE h5pset_create_inter_group_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_data\_transform

**Signature:**

*herr\_t* H5Pset\_data\_transform(*hid\_t* plist\_id, *const char* \*expression)

**Purpose:**

Sets a data transform expression.

**Description:**

H5Pset\_data\_transform sets the data transform to be used for reading and writing data. This function operates on the dataset transfer property lists plist\_id.

The expression parameter is a string containing an algebraic expression, such as  $(5/9.0) * (x-32)$  or  $x * (x-5)$ . When a dataset is read or written with this property list, the transform expression is applied with the  $x$  being replaced by the values in the dataset. When reading data, the values in the file are not changed and the transformed data is returned to the user.

Data transforms can only be applied to integer or floating-point datasets. Order of operations is obeyed and the only supported operations are +, -, \*, and /. Parentheses can be nested arbitrarily and can be used to change precedence.

When writing data back to the dataset, the transformed data is written to the file and there is no way to recover the original values to which the transform was applied.

**Parameters:**

<i>hid_t</i> plist_id	IN: Identifier of the property list or class
<i>const char</i> *expression	IN: Pointer to the null-terminated data transform expression

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** SUBROUTINE h5pset\_data\_transform\_f

```
SUBROUTINE h5pset_data_transform_f(plist_id, expression, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id
                                ! Identifier of the property list or class
  CHARACTER(LEN=*), INTENT(IN) :: expression
                                ! Buffer to hold transform expression
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_data_transform_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pset\_deflate

**Signature:**

```
herr_t H5Pset_deflate(hid_t plist, uint level )
```

**Purpose:**

Sets compression method and compression level.

**Description:**

H5Pset\_deflate sets the compression method for a dataset creation property list to H5D\_COMPRESS\_DEFLATE and the compression level to *level*, which should be a value from zero to nine, inclusive.

Lower compression levels are faster but result in less compression.

This is the same algorithm as used by the GNU gzip program.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier for the dataset creation property list.
<i>uint</i> level	IN: Compression level.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_deflate\_f

```
SUBROUTINE h5pset_deflate_f(prp_id, level, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN)       :: level  ! Compression level
  INTEGER, INTENT(OUT)      :: hdferr ! Error code
                                   ! 0 on success and -1 on failure
END SUBROUTINE h5pset_deflate_f
```

**Name:** H5Pset\_driver

**Signature:**

```
herr_t H5Pset_driver( hid_t plist_id, hid_t new_driver_id, const void
                    *new_driver_info )
```

**Purpose:**

Sets a file driver.

**Description:**

H5Pset\_driver sets the file driver, `new_driver_id`, for a file access or data transfer property list, `plist_id`, and supplies an optional struct containing the driver-specific properties, `new_driver_info`.

The driver properties will be copied into the property list and the reference count on the driver will be incremented, allowing the caller to close the driver identifier but still use the property list.

**Note:**

H5Pset\_driver and H5Pget\_driver\_info are used only when creating a virtual file driver (VFD) in the virtual file layer (VFL). For further information, see “Virtual File Layer” and “List of VFL Functions” in the *HDF5 Technical Notes*.

**Parameters:**

`hid_t plist_id`

IN: File access or data transfer property list identifier.

`hid_t new_driver_id`

IN: Driver identifier.

`const void *new_driver_info`

IN: Optional struct containing driver properties.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.2	Function publicized in this release; previous releases described this function only in the virtual file driver documentation.

**Name:** H5Pset\_dxpl\_mpio

**Signature:**

```
herr_t H5Pset_dxpl_mpio( hid_t dxpl_id, H5FD_mpio_xfer_t xfer_mode )
```

**Purpose:**

Sets data transfer mode.

**Description:**

H5Pset\_dxpl\_mpio sets the data transfer property list *dxpl\_id* to use transfer mode *xfer\_mode*. The property list can then be used to control the I/O transfer mode during data I/O operations.

Valid transfer modes are as follows:

```
H5FD_MPIO_INDEPENDENT
    Use independent I/O access (default).
H5FD_MPIO_COLLECTIVE
    Use collective I/O access.
```

**Parameters:**

```
hid_t dxpl_id           IN: Data transfer property list identifier.
H5FD_mpio_xfer_t xfer_mode  IN: Transfer mode.
```

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:**

```
SUBROUTINE h5pset_dxpl_mpio_f(prp_id, data_xfer_mode, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN) :: data_xfer_mode ! Data transfer mode
                                         ! Possible values are:
                                         !   H5FD_MPIO_INDEPENDENT_F
                                         !   H5FD_MPIO_COLLECTIVE_F
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pset_dxpl_mpio_f
```

**History:**

Release	C
1.4.0	Function introduced in this release.



**Name:** H5Pset\_dxpl\_mpio\_chunk\_opt

**Signature:**

*herr\_t* H5Pset\_dxpl\_mpio\_chunk\_opt (*hid\_t* dxpl\_id, *H5FD\_mpio\_chunk\_opt\_t* opt\_mode)

**Purpose:**

Sets a flag specifying linked-chunk I/O or multi-chunk I/O.

**Description:**

H5Pset\_dxpl\_mpio\_chunk\_opt specifies whether I/O is to be performed as linked-chunk I/O or as multi-chunk I/O. This function overrides the HDF5 Library's internal algorithm for determining which mechanism to use.

When an application uses collective I/O with chunked storage, the HDF5 Library normally uses an internal algorithm to determine whether that I/O activity should be conducted as one linked-chunk I/O or as multi-chunk I/O. H5Pset\_dxpl\_mpio\_chunk\_opt is provided so that an application can override the library's algorithm in circumstances where the library might lack the information needed to make an optimal decision.

H5Pset\_dxpl\_mpio\_chunk\_opt works by setting one of the following flags in the parameter *opt\_mode*:

H5FD_MPIO_CHUNK_ONE_IO	Do one link chunked I/O.
H5FD_MPIO_CHUNK_MULTI_IO	Do multi-chunked I/O.

This function works by setting a corresponding property in the dataset transfer property list *dxpl\_id*.

The library perform I/O in the specified manner *unless* it determines that the low-level MPI IO package does not support the requested behavior; in such cases, the HDF5 Library will internally use independent I/O.

Use of this function is optional.

**Parameters:**

<i>hid_t</i> dxpl_id	IN: Data transfer property list identifier
<i>H5FD_mpio_chunk_opt_t</i> opt_mode	IN: Optimization flag specifying linked-chunk I/O or multi-chunk I/O

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Name:** H5Pset\_dxpl\_mpio\_chunk\_opt\_num

**Signature:**

*herr\_t* H5Pset\_dxpl\_mpio\_chunk\_opt\_num (*hid\_t* dxpl\_id, *unsigned*  
num\_chunk\_per\_proc)

**Purpose:**

Sets a numeric threshold for linked-chunk I/O.

**Description:**

H5Pset\_dxpl\_mpio\_chunk\_opt\_num sets a numeric threshold for the use of linked-chunk I/O.

The library will calculate the average number of chunks selected by each process when doing collective access with chunked storage. If the number is greater than the threshold set in num\_chunk\_per\_proc, the library will use linked-chunk I/O; otherwise, a separate I/O process will be invoked for each chunk (multi-chunk I/O).

**Parameters:**

<i>hid_t</i> dxpl_id	IN: Data transfer property list identifier
<i>unsigned</i> num_proc_per_chunk	IN: Numeric threshold for performing linked-chunk I/O

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Name:** H5Pset\_dxpl\_mpio\_chunk\_opt\_ratio

**Signature:**

```
herr_t H5Pset_dxpl_mpio_chunk_opt_ratio (hid_t dxpl_id, unsigned  
percent_proc_per_chunk)
```

**Purpose:**

Sets a ratio threshold for collective I/O.

**Description:**

H5Pset\_dxpl\_mpio\_chunk\_opt\_ratio sets a threshold for the use of collective I/O based on the ratio of processes with collective access to a dataset with chunked storage. The decision whether to use collective I/O is made on a per-chunk basis.

The library will calculate the percentage of the total number of processes, the ratio, that hold selections in each chunk. If that percentage is greater than the threshold set in percent\_proc\_per\_chunk, the library will do collective I/O for this chunk; otherwise, independent I/O will be done for the chunk.

**Parameters:**

<i>hid_t</i> dxpl_id	IN: Data transfer property list identifier
<i>unsigned</i> percent_proc_per_chunk	IN: Percent threshold, on the number of processes holding selections per chunk, for performing linked-chunk I/O

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Name:** H5Pset\_dxpl\_mpio\_collective\_opt

**Signature:**

```
herr_t H5Pset_dxpl_mpio_collective_opt (hid_t dxpl_id, H5FD_mpio_collective_opt_t
opt_mode)
```

**Purpose:**

Sets a flag governing the use of independent versus collective I/O.

**Description:**

H5Pset\_dxpl\_mpio\_collective\_opt enables an application to specify that the HDF5 Library will use independent I/O internally when the dataset transfer property list `dxpl_id` is set for collective I/O, i.e., with `H5FD_MPIO_COLLECTIVE` specified. This allows the application greater control over low-level I/O while maintaining the collective interface at the application level.

H5Pset\_dxpl\_mpio\_collective\_opt works by setting one of the following flags in the parameter `opt_mode`:

<code>H5FD_MPIO_COLLECTIVE_IO</code>	Use collective I/O. ( <i>Default</i> )
<code>H5FD_MPIO_INDIVIDUAL_IO</code>	Use independent I/O.

This function should be used only when `H5FD_MPIO_COLLECTIVE` has been set through `H5Pset_dxpl_mpio`. In such situations, normal behavior would be to use low-level collective I/O functions, but the library will use low-level MPI independent I/O functions when `H5FD_MPIO_INDIVIDUAL_IO` is set.

Use of this function is optional.

**Parameters:**

<i>hid_t</i> dxpl_id	IN: Data transfer property list identifier
<i>H5FD_mpio_collective_opt_t</i> opt_mode	IN: Optimization flag specifying the use of independent or collective I/O

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Name:** H5Pset\_dxpl\_multi

**Signature:**

```
herr_t H5Pset_dxpl_multi( hid_t dxpl_id, const hid_t *memb_dxpl )
```

**Purpose:**

Sets the data transfer property list for the multi-file driver.

**Description:**

H5Pset\_dxpl\_multi sets the data transfer property list dxpl\_id to use the multi-file driver for each memory usage type memb\_dxpl[ ].

H5Pset\_dxpl\_multi can only be used after the member map has been set with H5Pset\_fapl\_multi.

**Parameters:**

<i>hid_t</i> dxpl_id,	IN: Data transfer property list identifier.
<i>const hid_t</i> *memb_dxpl	IN: Array of data access property lists.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.4.0	Function introduced in this release.

**Name:** H5Pset\_edc\_check

**Signature:**

*herr\_t* H5Pset\_edc\_check(*hid\_t* plist, *H5Z\_EDC\_t* check)

**Purpose:**

Sets whether to enable error-detection when reading a dataset.

**Description:**

H5Pset\_edc\_check sets the dataset transfer property list *plist* to enable or disable error detection when reading data.

Whether error detection is enabled or disabled is specified in the *check* parameter. Valid values are as follows:

H5Z\_ENABLE\_EDC (default)

H5Z\_DISABLE\_EDC

The error detection algorithm used is the algorithm previously specified in the corresponding dataset creation property list.

This function does not affect the use of error detection when writing data.

**Note:**

The initial error detection implementation, Fletcher32 checksum, supports error detection for chunked datasets only.

**Parameters:**

*hid\_t* plist

IN: Dataset transfer property list identifier.

*H5Z\_EDC\_t* check

IN: Specifies whether error checking is enabled or disabled for dataset read operations.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_edc\_check\_f

```
SUBROUTINE h5pset_edc_check_f(prp_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id    ! Dataset transfer property
                                          ! list identifier
  INTEGER, INTENT(IN)       :: flag      ! EDC flag; possible values
                                          !   H5Z_DISABLE_EDC_F
                                          !   H5Z_ENABLE_EDC_F
  INTEGER, INTENT(OUT)      :: hdferr    ! Error code
                                          ! 0 on success and -1 on failure

END SUBROUTINE h5pset_edc_check_f
```

**History:**

**Release**    **C**

1.6.0        Function introduced in this release.

*Last modified: 8 May 2009***Name:** H5Pset\_elink\_acc\_flags**Signature:***herr\_t* H5Pset\_elink\_acc\_flags(*hid\_t* lapl\_id, *unsigned* flags)**Purpose:**

Sets the external link traversal file access flag in a link access property list.

**Motivation:**

H5Pset\_elink\_acc\_flags is used to adjust the file access flag used to open files reached through external links. This may be useful to, for example, prevent modifying files accessed through an external link. Otherwise, the target file is opened with whatever flag was used to open the parent.

**Description:**

H5Pset\_elink\_acc\_flags specifies the file access flag to use to open the target file of an external link. This allows read-only access of files reached through an external link in a file opened with write access, or vice-versa.

The library will normally use the file access flag used to open the parent file as the file access flag for the target file. This function provides a way to override that behaviour. The external link traversal callback function set by H5Pset\_elink\_cb can override the setting from H5Pset\_elink\_acc\_flags.

**Parameters:**

*hid\_t* lapl\_id      IN: Link access property list identifier  
*unsigned* flags      IN: The access flag for external link traversal.

Valid values include:

H5F_ACC_RDWR	Causes files opened through external links to be opened with write access.
H5F_ACC_RDONLY	Causes files opened through external links to be opened with read-only access.
H5F_ACC_DEFAULT	Removes any external link file access flag setting from lapl_id, causing the file access flag setting to be taken from the parent file.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Example Usage:**

The following code sets the link access property list lapl\_id to open external link target files with read-only access:

```
status = H5Pset_elink_acc_flags(lapl_id, H5F_ACC_RDONLY);
```

**See Also:**

H5Pget\_elink\_acc\_flags, H5Pset\_elink\_cb, H5Fopen, H5Lcreate\_external

**History:**

Release	Change
1.8.3	C function introduced in this release.

*Last modified: 8 May 2009***Name:** H5Pset\_elink\_cb**Signature:**

```
herr_t H5Pset_elink_cb( hid_t lapl_id, H5L_elink_traverse_t func, void *op_data )
```

**Purpose:**

Sets the external link traversal callback function in a link access property list.

**Motivation:**

H5Pset\_elink\_cb is used to add a callback function that is called when traversing an external link. The callback can then set access permissions, modify the file access property list, modify the parent or target file, or take any other user defined action.

**Description:**

H5Pset\_elink\_cb sets the user-defined external link traversal callback function in the link access property list lapl\_id.

The callback function may adjust the file access property list and file access flag to use when opening a file through an external link. The callback will be made immediately before opening the target file.

The callback will be made after the file access property list set by H5Pset\_elink\_fapl and the file access flag set by H5Pset\_elink\_acc\_flags are applied, so changes made by this callback function take precedence.

**Parameters:**

<i>hid_t</i> lapl_id	IN: Link access property list identifier.
<i>H5L_elink_traverse_t</i> func	IN: User-defined external link traversal callback function.
<i>void</i> *op_data	IN: User-defined input data for the callback function.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Example Usage:**

This example defines a callback function that prints the name of the target file every time an external link is followed, and sets this callback function on lapl\_id

```
herr_t elink_callback(const char *parent_file_name, const char
    *parent_group_name, const char *child_file_name, const char
    *child_object_name, unsigned *acc_flags, hid_t fapl_id, void *op_data) {
    puts(child_file_name);
    return 0;
}

int main(void) {
    hid_t lapl_id = H5Pcreate(H5P_LINK_ACCESS);
    H5Pset_elink_cb(lapl_id, elink_callback, NULL);
    ...
}
```

**See Also:**

H5Pget\_elink\_cb, H5Pset\_elink\_fapl, H5Pset\_elink\_acc\_flags, H5Fopen, H5Lcreate\_external

H5L\_elink\_traverse\_t

**History:**

Release	Change
1.8.3	C function introduced in this release.



---

*Last modified: 2 April 2009*

**Name:** H5Pset\_elink\_fapl

**Signature:**

*herr\_t* H5Pset\_elink\_fapl(*hid\_t* lapl\_id, *hid\_t* fapl\_id)

**Purpose:**

Sets a file access property list for use in accessing a file pointed to by an external link.

**Description:**

H5Pset\_elink\_fapl sets the file access property list, fapl\_id, to be used when accessing the target file of an external link associated with lapl\_id.

**Parameters:**

*hid\_t* lapl\_id     IN: Link access property list identifier

*hid\_t* fapl\_id     IN: File access property list identifier

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**See Also:**

H5Pget\_elink\_fapl

H5Lcreate\_external

**Fortran90 Interface:**

None.

**History:**

Release	Change
1.9.0	C function introduced in this release.

**Name:** H5Pset\_elink\_prefix

**Signature:**

*herr\_t* H5Pset\_elink\_prefix(*hid\_t* lapl\_id, *const char \**prefix)

**Purpose:**

Sets prefix to be applied to external link paths.

**Description:**

H5Pset\_elink\_prefix sets the prefix to be applied to the path of any external links traversed. The prefix is prepended to the filename stored in the external link.

The prefix is specified in the user-allocated buffer `prefix` and set in the link access property list `lapl_id`. The buffer should not be freed until the property list has been closed.

**Parameters:**

<i>hid_t</i> lapl_id	IN: Link access property list identifier
<i>const char *</i> prefix	IN: Prefix to be applied to external link paths

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_est\_link\_info

**Signature:**

```
herr_t H5Pset_est_link_info(hid_t gcpl_id, unsigned est_num_entries, unsigned
est_name_len)
```

**Purpose:**

Sets estimated number of links and length of link names in a group.

**Description:**

H5Pset\_est\_link\_info inserts two settings into the group creation property list *gcpl\_id*: the estimated number of links that are expected to be inserted into a group created with the property list and the estimated average length of those link names.

The estimated number of links is passed in *est\_num\_entries*.

The estimated average length of the anticipated link names is passed in *est\_name\_len*.

The values for these two settings are multiplied to compute the initial local heap size (for old-style groups, if the local heap size hint is not set) or the initial object header size for (new-style compact groups; see “Group implementations in HDF5”). Accurately setting these parameters will help reduce wasted file space.

If a group is expected to have many links and to be stored in dense format, set *est\_num\_entries* to 0 (zero) for maximum efficiency. This will prevent the group from being created in the compact format.

See “Group implementations in HDF5” in the H5G API introduction for a discussion of the available types of HDF5 group structures.

**Parameters:**

<i>hid_t</i> gcpl_id	IN: Group creation property list identifier
<i>unsigned</i> est_num_entries	IN: Estimated number of links to be inserted into group
<i>unsigned</i> est_name_len	IN: Estimated average length of link names

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

```
SUBROUTINE H5Pset_est_link_info_f(gcpl_id, est_num_entries, est_name_len, &
                                hdferr)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: gcpl_id
                                ! Group creation property list identifier
    INTEGER, INTENT(IN) :: est_num_entries
                                ! Estimated number of links to be
                                ! inserted into group
    INTEGER, INTENT(IN) :: est_name_len
                                ! Estimated average length of link names
    INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE H5Pset_est_link_info_f
```

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pset\_external

**Signature:**

```
herr_t H5Pset_external(hid_t plist, const char *name, off_t offset, hsize_t size)
```

**Purpose:**

Adds an external file to the list of external files.

**Description:**

The first call to H5Pset\_external sets the *external storage* property in the property list, thus designating that the dataset will be stored in one or more non-HDF5 file(s) external to the HDF5 file. This call also adds the file name as the first file in the list of external files. Subsequent calls to the function add the named file as the next file in the list.

If a dataset is split across multiple files, then the files should be defined in order. The total size of the dataset is the sum of the *size* arguments for all the external files. If the total size is larger than the size of a dataset then the dataset can be extended (provided the data space also allows the extending).

The *size* argument specifies the number of bytes reserved for data in the external file. If *size* is set to H5F\_UNLIMITED, the external file can be of unlimited size and no more files can be added to the external files list.

All of the external files for a given dataset must be specified with H5Pset\_external *before* H5Dcreate is called to create the dataset. If one these files does not exist on the system when H5Dwrite is called to write data to it, the library will create the file.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier of a dataset creation property list.
<i>const char *</i> name	IN: Name of an external file.
<i>off_t</i> offset	IN: Offset, in bytes, from the beginning of the file to the location in the file where the data starts.
<i>hsize_t</i> size	IN: Number of bytes reserved in the file for the data.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_external\_f

```
SUBROUTINE h5pset_external_f(prp_id, name, offset, bytes, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  CHARACTER(LEN=*), INTENT(IN) :: name ! Name of an external file
  INTEGER, INTENT(IN) :: offset ! Offset, in bytes, from the
                                ! beginning of the file to the
                                ! location in the file where
                                ! the data starts
  INTEGER(HSIZE_T), INTENT(IN) :: bytes ! Number of bytes reserved in
                                ! the file for the data
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_external_f
```

**Name:** H5Pset\_family\_offset

**Signature:**

```
herr_t H5Pset_family_offset ( hid_t fapl_id, hsize_t offset )
```

**Purpose:**

Sets offset property for low-level access to a file in a family of files.

**Description:**

H5Pset\_family\_offset sets the offset property in the file access property list fapl\_id so that the user application can retrieve a file handle for low-level access to a particular member of a family of files. The file handle is retrieved with a separate call to H5Fget\_vfd\_handle (or, in special circumstances, to H5FDget\_vfd\_handle; see *Virtual File Layer* and *List of VFL Functions* in *HDF5 Technical Notes*).

The value of offset is an offset in bytes from the beginning of the HDF5 file, identifying a user-determined location within the HDF5 file. The file handle the user application is seeking is for the specific member-file in the associated family of files to which this offset is mapped.

Use of this function is only appropriate for an HDF5 file written as a family of files with the FAMILY file driver.

**Parameters:**

hid_t fapl_id	IN: File access property list identifier.
hsize_t offset	IN: Offset in bytes within the HDF5 file.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_family\_offset\_f

```
SUBROUTINE h5pset_family_offset_f(prp_id, offset, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)    :: prp_id    ! Property list identifier
  INTEGER(HSIZE_T), INTENT(IN)  :: offset    ! Offset in bytes
  INTEGER, INTENT(OUT)          :: hdferr    ! Error code
                                         ! 0 on success and -1 on failure

END SUBROUTINE h5pset_family_offset_f
```

**History:**

Release	C
1.6.0	Function introduced in this release.

**Name:** H5Pset\_fapl\_core

**Signature:**

```
herr_t H5Pset_fapl_core( hid_t fapl_id, size_t increment, hbool_t backing_store )
```

**Purpose:**

Modifies the file access property list to use the H5FD\_CORE driver.

**Description:**

H5Pset\_fapl\_core modifies the file access property list to use the H5FD\_CORE driver.

The H5FD\_CORE driver enables an application to work with a file in memory, speeding reads and writes as no disk access is made. File contents are stored only in memory until the file is closed. The *backing\_store* parameter determines whether file contents are ever written to disk.

*increment* specifies the increment by which allocated memory is to be increased each time more memory is required.

While using H5Fcreate to create a core file, if the *backing\_store* is set to 1 (TRUE), the file contents are flushed to a file with the same name as this core file when the file is closed or access to the file is terminated in memory.

The application is allowed to open an existing file with H5FD\_CORE driver. While using H5Fopen to open an existing file, if the *backing\_store* is set to 1 and the *flags* for H5Fopen is set to H5F\_ACC\_RDWR, any change to the file contents are saved to the file when the file is closed. If *backing\_store* is set to 0 and the *flags* for H5Fopen is set to H5F\_ACC\_RDWR, any change to the file contents will be lost when the file is closed. If the *flags* for H5Fopen is set to H5F\_ACC\_RDONLY, no change to the file is allowed either in memory or on file.

**Note:**

Currently this driver cannot create or open family or multi files.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>size_t</i> increment	IN: Size, in bytes, of memory increments.
<i>hbool_t</i> backing_store	IN: Boolean flag indicating whether to write the file contents to disk when the file is closed.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fapl\_core\_f

```
SUBROUTINE h5pset_fapl_core_f(prp_id, increment, backing_store, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER(SIZE_T), INTENT(IN) :: increment ! File block size in bytes
  LOGICAL, INTENT(IN) :: backing_store     ! Flag to indicate that entire
                                           ! file contents are flushed to
                                           ! a file with the same name as
                                           ! this core file
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pset_fapl_core_f
```

**History:****Release      C**

1.6.0

1.4.0

Function introduced  
in this release.**Fortran90**

The `backing_store` parameter has changed from  
*INTEGER* to *LOGICAL* to better match the C API.



**Name:** H5Pset\_fapl\_direct

**Signature:**

```
herr_t H5Pset_fapl_direct(hid_t fapl_id, size_t alignment, size_t block_size, size_t
    cbuf_size)
```

**Purpose:**

Sets up use of the direct I/O driver.

**Description:**

H5Pset\_fapl\_direct sets the file access property list, *fapl\_id*, to use the direct I/O driver, H5FD\_DIRECT. With this driver, data is written to or read from the file synchronously without being cached by the system.

File systems usually require the data address in memory, the file address, and the size of the data to be aligned. The HDF5 Library's direct I/O driver is able to handle unaligned data, though that will consume some additional memory resources and may slow performance. To get better performance, use the system function `posix_memalign` to align the data buffer in memory and the HDF5 function `H5Pset_alignment` to align the data in the file. Be aware, however, that aligned data I/O may cause the HDF5 file to be bigger than the actual data size would otherwise require because the alignment may leave some holes in the file.

*alignment* specifies the required alignment boundary in memory.

*block\_size* specifies the file system block size. A value of 0 (zero) means to use HDF5 Library's default value of 4KB.

*cbuf\_size* specifies the copy buffer size.

**Note:**

On an SGI Altix Linux 2.6 system, the memory alignment must be a multiple of 512 bytes, and the file system block size is 4KB. The maximum size for the copy buffer has to be a multiple of the file system block size. The HDF5 Library's default maximum copy buffer size is 16MB. This copy buffer is used by the library's internal algorithm to copy data in fragments between an application's unaligned buffer and the file. The buffer's size may affect I/O performance.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier
<i>size_t</i> alignment	IN: Required memory alignment boundary
<i>size_t</i> block_size	IN: File system block size
<i>size_t</i> cbuf_size	IN: Copy buffer size

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fapl\_direct\_f

```
SUBROUTINE h5pset_fapl_direct_f(fapl_id, alignment, block_size, cbuf_size, &
                                hdferr)
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: fapl_id ! File access property list identifier
    INTEGER(SIZE_T), INTENT(IN) :: alignment
                                   ! Required memory alignment boundary
    INTEGER(SIZE_T), INTENT(IN) :: block_size
                                   ! File system block size
    INTEGER(SIZE_T), INTENT(IN) :: cbuf_size
                                   ! Copy buffer size
```

```
      INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE H5Pset_fapl_direct_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_fapl\_family

**Signature:**

```
herr_t H5Pset_fapl_family ( hid_t fapl_id, hsize_t memb_size, hid_t memb_fapl_id )
```

**Purpose:**

Sets the file access property list to use the family driver.

**Description:**

H5Pset\_fapl\_family sets the file access property list identifier, *fapl\_id*, to use the family driver.

*memb\_size* is the size in bytes of each file member and is used only when creating a new file.

*memb\_fapl\_id* is the identifier of the file access property list to be used for each family member.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>hsize_t</i> memb_size	IN: Size in bytes of each file member.
<i>hid_t</i> memb_fapl_id	IN: Identifier of file access property list for each family member.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fapl\_family\_f

```
SUBROUTINE h5pset_fapl_family_f(prp_id, imemb_size, memb_plist, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)  :: prp_id      ! Property list identifier
  INTEGER(HSIZE_T), INTENT(IN) :: memb_size  ! Logical size, in bytes,
                                           ! of each family member
  INTEGER(HID_T), INTENT(IN) :: memb_plist  ! Identifier of the file
                                           ! access property list to be
                                           ! used for each family member
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pset_fapl_family_f
```

**History:**

<b>Release</b>	<b>C</b>
1.4.0	Function introduced in this release.

**Name:** H5Pset\_fapl\_log

**Signature:**

```
herr_t H5Pset_fapl_log( hid_t fapl_id, const char *logfile, unsigned int flags, size_t
buf_size )
```

**Purpose:**

Sets up the use of the logging driver.

**Description:**

H5Pset\_fapl\_log modifies the file access property list to use the logging driver H5FD\_LOG.

logfile is the name of the file in which the logging entries are to be recorded.

The actions to be logged are specified in the parameter flags using the pre-defined constants described in the following table. Multiple flags can be set through the use of an logical OR contained in parentheses. For example, logging read and write locations would be specified as (H5FD\_LOG\_LOC\_READ | H5FD\_LOG\_LOC\_WRITE).

Flag	Description
H5FD_LOG_LOC_READ H5FD_LOG_LOC_WRITE H5FD_LOG_LOC_SEEK H5FD_LOG_LOC_IO	Track the location and length of every read, write, or seek operation.  Track all I/O locations and lengths. The logical equivalent of the following: (H5FD_LOG_LOC_READ   H5FD_LOG_LOC_WRITE   H5FD_LOG_LOC_SEEK)
H5FD_LOG_FILE_READ H5FD_LOG_FILE_WRITE H5FD_LOG_FILE_IO	Track the number of times each byte is read or written.  Track the number of times each byte is read and written. The logical equivalent of the following: (H5FD_LOG_FILE_READ   H5FD_LOG_FILE_WRITE)
H5FD_LOG_FLAVOR	Track the type, or flavor, of information stored at each byte.
H5FD_LOG_NUM_READ H5FD_LOG_NUM_WRITE H5FD_LOG_NUM_SEEK H5FD_LOG_NUM_IO	Track the total number of read, write, or seek operations that occur.  Track the total number of all types of I/O operations. The logical equivalent of the following: (H5FD_LOG_NUM_READ   H5FD_LOG_NUM_WRITE   H5FD_LOG_NUM_SEEK)

H5FD_LOG_TIME_OPEN	Track the time spent in open, read, write, seek, or close operations.
H5FD_LOG_TIME_READ	<i>Not implemented in this release: open and read</i>
H5FD_LOG_TIME_WRITE	<i>Partially implemented: write and seek</i>
H5FD_LOG_TIME_SEEK	<i>Fully implemented: close</i>
H5FD_LOG_TIME_CLOSE	
H5FD_LOG_TIME_IO	Track the time spent in each of the above operations. The logical equivalent of the following: ( H5FD_LOG_TIME_OPEN   H5FD_LOG_TIME_READ   H5FD_LOG_TIME_WRITE   H5FD_LOG_TIME_SEEK   H5FD_LOG_TIME_CLOSE )
H5FD_LOG_ALLOC	Track the allocation of space in the file.
H5FD_LOG_ALL	Track everything. The logical equivalent of the following: ( H5FD_LOG_ALLOC   H5FD_LOG_TIME_IO   H5FD_LOG_NUM_IO   H5FD_LOG_FLAVOR   H5FD_LOG_FILE_IO   H5FD_LOG_LOC_IO )

The logging driver can track the number of times each byte in the file is read from or written to (using H5FD\_LOG\_FILE\_READ and H5FD\_LOG\_FILE\_WRITE) and what kind of data is at that location (e.g., meta data, raw data; using H5FD\_LOG\_FLAVOR). This information is tracked in a buffer of size `buf_size`, which must be at least the size in bytes of the file to be logged.

#### Parameters:

<code>hid_t fapl_id</code>	IN: File access property list identifier.
<code>char *logfile</code>	IN: Name of the log file.
<code>unsigned int flags</code>	IN: Flags specifying the types of logging activity.
<code>size_t buf_size</code>	IN: The size of the logging buffer.

#### Returns:

Returns non-negative if successful. Otherwise returns negative.

#### Fortran90 Interface:

None.

#### History:

Release	C
1.6.0	The verbosity parameter has been removed. Two new parameters have been added: <code>flags</code> of type <i>unsigned</i> and <code>buf_size</code> of type <i>size_t</i> .
1.4.0	Function introduced in this release.

*Last modified: 15 May 2009***Name:** H5Pset\_fapl\_mpio**Signature:**

```
herr_t H5Pset_fapl_mpio( hid_t fapl_id, MPI_Comm comm, MPI_Info info )
```

**Purpose:**

Stores MPI IO communicator information to the file access property list.

**Description:**

H5Pset\_fapl\_mpio stores the user-supplied MPI IO parameters `comm`, for communicator, and `info`, for information, in the file access property list `fapl_id`. That property list can then be used to create and/or open a file.

H5Pset\_fapl\_mpio is available only in the parallel HDF5 library and is not a collective function.

`comm` is the MPI communicator to be used for file open, as defined in `MPI_FILE_OPEN` of MPI-2. This function makes a duplicate of the communicator, so modifications to `comm` after this function call returns have no effect on the file access property list.

`info` is the MPI Info object to be used for file open, as defined in `MPI_FILE_OPEN` of MPI-2. This function makes a duplicate copy of the Info object, so modifications to the Info object after this function call returns will have no effect on the file access property list.

If the file access property list already contains previously-set communicator and Info values, those values will be replaced and the old communicator and Info object will be freed.

**Note:**

Raw dataset chunk caching is not currently supported when using this file driver in read/write mode. All calls to H5Dread and H5Dwrite will access the disk directly, and H5Pset\_cache and H5Pset\_chunk\_cache will have no effect on performance.

Raw dataset chunk caching is supported when this driver is used in read-only mode.

**Parameters:**

<code>hid_t fapl_id</code>	IN: File access property list identifier
<code>MPI_Comm comm</code>	IN: MPI-2 communicator
<code>MPI_Info info</code>	IN: MPI-2 info object

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fapl\_mpio\_f

```
SUBROUTINE h5pset_fapl_mpio_f(prp_id, comm, info, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN) :: comm          ! MPI communicator to be used for
                                      ! file open as defined in
                                      ! MPI_FILE_OPEN of MPI-2
  INTEGER, INTENT(IN) :: info          ! MPI info object to be used for
                                      ! file open as defined in
                                      ! MPI_FILE_OPEN of MPI-2
  INTEGER, INTENT(OUT) :: hdferr       ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pset_fapl_mpio_f
```

**History:**

<b>Release</b>	<b>Change</b>
1.4.5	Handling of the MPI Communicator and Info object changed at this release. A duplicate of each of these is now stored in the property list instead of pointers to each.
1.4.0	C function introduced in this release.

*Last modified: 15 April 2009***Name:** H5Pset\_fapl\_mpiposix**Signature:**

```
herr_t H5Pset_fapl_mpiposix( hid_t fapl_id, MPI_Comm comm, hbool_t use_gpfs_hints
)
```

**Purpose:**

Stores MPI IO communicator information to a file access property list.

**Description:**

H5Pset\_fapl\_mpiposix stores the user-supplied MPI IO parameter `comm`, for communicator, in the file access property list `fapl_id`. That property list can then be used to create and/or open the file.

H5Pset\_fapl\_mpiposix is available only in the parallel HDF5 library and is not a collective function.

`comm` is the MPI communicator to be used for file open, as defined in `MPI_FILE_OPEN` of MPI-2. This function does not create a duplicated communicator. Modifications to `comm` after this function call returns may have an undetermined effect on the file access property list. Users should not modify the communicator while it is defined in a property list.

`use_gpfs_hints` specifies whether to attempt to use GPFS hints when accessing this file. A value of `TRUE` (or 1) indicates that the hints should be used, if possible. A value of `FALSE` (or 0) indicates that the hints should not be used.

Available GPFS hints are known to the HFD5 Library and are not user configurable. They may be used *only* with GPFS file systems and may improve file access for some applications; the user of a GPFS system is encouraged to experiment by running an application with and without this parameter set.

**Note:**

Raw dataset chunk caching is not currently supported when using this file driver in read/write mode. All calls to `H5Dread` and `H5Dwrite` will access the disk directly, and `H5Pset_cache` and `H5Pset_chunk_cache` will have no effect on performance.

Raw dataset chunk caching is supported when this driver is used in read-only mode.

**Parameters:**

<code>hid_t fapl_id</code>	IN: File access property list identifier.
<code>MPI_Comm comm</code>	IN: MPI-2 communicator.
<code>hbool_t use_gpfs_hints</code>	IN: Use of GPFS hints.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fapl\_mpiposix\_f

```
SUBROUTINE h5pset_fapl_mpiposix_f(prp_id, comm, use_gpfs, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN) :: comm ! MPI communicator to be used
  ! for file open as defined in
  ! MPI_FILE_OPEN of MPI-2
  LOGICAL, INTENT(IN) :: use_gpfs
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5pset_fapl_mpiposix_f
```



**History:**

<b>Release</b>	<b>Change</b>
1.6.1	Fortran subroutine introduced in this release.
1.6.0	<code>use_gpfs_hints</code> parameter added.
1.6.0	C function introduced in this release.

**Name:** H5Pset\_fapl\_multi

**Signature:**

```
herr_t H5Pset_fapl_multi(hid_t fapl_id, const H5FD_mem_t *memb_map, const hid_t
*memb_fapl, const char *const *memb_name, const haddr_t *memb_addr, hbool_t relax)
```

**Purpose:**

Sets up use of the multi-file driver.

**Description:**

H5Pset\_fapl\_multi sets the file access property list fapl\_id to use the multi-file driver.

The multi-file driver enables different types of HDF5 data and metadata to be written to separate files. These files are viewed by the HDF5 library and the application as a single virtual HDF5 file with a single HDF5 file address space. The types of data that can be broken out into separate files include raw data, the superblock, B-tree data, global heap data, local heap data, and object headers. At the programmer's discretion, two or more types of data can be written to the same file while other types of data are written to separate files.

The array memb\_map maps memory usage types to other memory usage types and is the mechanism that allows the caller to specify how many files are created. The array contains H5FD\_MEM\_NTYPES entries, which are either the value H5FD\_MEM\_DEFAULT or a memory usage type. The number of unique values determines the number of files that are opened.

The array memb\_fapl contains a property list for each memory usage type that will be associated with a file.

The array memb\_name should be a name generator (a printf-style format with a %s which will be replaced with the name passed to H5FDopen, usually from H5Fcreate or H5Fopen).

The array memb\_addr specifies the offsets within the virtual address space, from 0 (zero) to HADDR\_MAX, at which each type of data storage begins.

If relax is set to TRUE (or 1), then opening an existing file for read-only access will not fail if some file members are missing. This allows a file to be accessed in a limited sense if just the meta data is available.

Default values for each of the optional arguments are as follows:

memb\_map

The default member map contains the value H5FD\_MEM\_DEFAULT for each element.

memb\_fapl

The default value is H5P\_DEFAULT for each element.

memb\_name

The default string is %s-X.h5 where X is one of the following letters:

- s for H5FD\_MEM\_SUPER
- b for H5FD\_MEM\_BTREE
- r for H5FD\_MEM\_DRAW
- g for H5FD\_MEM\_GHEAP
- l for H5FD\_MEM\_LHEAP
- o for H5FD\_MEM\_OHDR

`memb_addr`

The default value is `HADDR_UNDEF` for each element.

### Parameters:

<code>hid_t fapl_id</code>	IN: File access property list identifier.
<code>const H5FD_mem_t *memb_map</code>	IN: Maps memory usage types to other memory usage types.
<code>const hid_t *memb_fapl</code>	IN: Property list for each memory usage type.
<code>const char *const *memb_name</code>	IN: Name generator for names of member files.
<code>const haddr_t *memb_addr</code>	IN: The offsets within the virtual address space, from 0 (zero) to <code>HADDR_MAX</code> , at which each type of data storage begins.
<code>hbool_t relax</code>	IN: Allows read-only access to incomplete file sets when <code>TRUE</code> .

### Returns:

Returns a non-negative value if successful. Otherwise returns a negative value.

### Example:

The following code sample sets up a multi-file access property list that partitions data into meta and raw files, each being one-half of the address:

```
H5FD_mem_t mt, memb_map[H5FD_MEM_NTYPES];
hid_t memb_fapl[H5FD_MEM_NTYPES];
const char *memb[H5FD_MEM_NTYPES];
haddr_t memb_addr[H5FD_MEM_NTYPES];

// The mapping...
for (mt=0; mt<H5FD_MEM_NTYPES; mt++) {
    memb_map[mt] = H5FD_MEM_SUPER;
}
memb_map[H5FD_MEM_DRAW] = H5FD_MEM_DRAW;

// Member information
memb_fapl[H5FD_MEM_SUPER] = H5P_DEFAULT;
memb_name[H5FD_MEM_SUPER] = "%s.meta";
memb_addr[H5FD_MEM_SUPER] = 0;

memb_fapl[H5FD_MEM_DRAW] = H5P_DEFAULT;
memb_name[H5FD_MEM_DRAW] = "%s.raw";
memb_addr[H5FD_MEM_DRAW] = HADDR_MAX/2;

hid_t fapl = H5Pcreate(H5P_FILE_ACCESS);
H5Pset_fapl_multi(fapl, memb_map, memb_fapl,
                 memb_name, memb_addr, TRUE);
```

### Fortran90 Interface: h5pset\_fapl\_multi\_f

```
SUBROUTINE h5pset_fapl_multi_f(prp_id, memb_map, memb_fapl, memb_name,
                              memb_addr, relax, hdferr)

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier

    INTEGER, DIMENSION(0:H5FD_MEM_NTYPES_F-1), INTENT(IN) :: memb_map
    INTEGER(HID_T), DIMENSION(0:H5FD_MEM_NTYPES_F-1), INTENT(IN) :: memb_fapl
    CHARACTER(LEN=*) , DIMENSION(0:H5FD_MEM_NTYPES_F-1), INTENT(IN) :: memb_name
    REAL, DIMENSION(0:H5FD_MEM_NTYPES_F-1), INTENT(IN) :: memb_addr
    ! Numbers in the interval [0,1) (e.g. 0.0 0.1 0.5 0.2 0.3 0.4)
    ! real address in the file will be calculated as X*HADDR_MAX
```

```
LOGICAL, INTENT(IN)  :: relax
INTEGER, INTENT(OUT) :: hdferr
                                ! Error code
                                ! 0 on success and -1 on failure

END SUBROUTINE h5pset_fapl_multi_f
```

**History:****Release    C**

- 1.6.3       memb\_name parameter type changed to *const char\* const\**.
- 1.4.0       Function introduced in this release.

**Name:** H5Pset\_fapl\_sec2

**Signature:**

*herr\_t* H5Pset\_fapl\_sec2(*hid\_t* fapl\_id)

**Purpose:**

Sets the sec2 driver.

**Description:**

H5Pset\_fapl\_sec2 modifies the file access property list to use the H5FD\_SEC2 driver.

**Parameters:**

*hid\_t* fapl\_id      IN: File access property list identifier.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fapl\_sec2\_f

```
SUBROUTINE h5pset_fapl_sec2_f(prp_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)      :: prp_id  ! Property list identifier
  INTEGER, INTENT(OUT)            :: hdferr  ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pset_fapl_sec2_f
```

**History:**

Release	C
1.4.0	Function introduced in this release.

**Name:** H5Pset\_fapl\_split

**Signature:**

```
herr_t H5Pset_fapl_split(hid_t fapl_id, const char *meta_ext, hid_t meta_plist_id,
const char *raw_ext, hid_t raw_plist_id)
```

**Purpose:**

Emulates the old split file driver.

**Description:**

H5Pset\_fapl\_split is a compatibility function that enables the multi-file driver to emulate the split driver from HDF5 Releases 1.0 and 1.2. The split file driver stored metadata and raw data in separate files but provided no mechanism for separating types of metadata.

fapl\_id is a file access property list identifier.

meta\_ext is the filename extension for the metadata file. The extension is appended to the name passed to H5FDopen, usually from H5Fcreate or H5Fopen, to form the name of the metadata file. If the string %s is used in the extension, it works like the name generator as in H5Pset\_fapl\_multi.

meta\_plist\_id is the file access property list identifier for the metadata file.

raw\_ext is the filename extension for the raw data file. The extension is appended to the name passed to H5FDopen, usually from H5Fcreate or H5Fopen, to form the name of the rawdata file. If the string %s is used in the extension, it works like the name generator as in H5Pset\_fapl\_multi.

raw\_plist\_id is the file access property list identifier for the raw data file.

If a user wishes to check to see whether this driver is in use, the user must call H5Pget\_driver and compare the returned value to the string H5FD\_MULTI. A positive match will confirm that the multi driver is in use; HDF5 provides no mechanism to determine whether it was called as the special case invoked by H5Pset\_fapl\_split.

**Parameters:**

<i>hid_t</i> fapl_id,	IN: File access property list identifier.
<i>const char</i> *meta_ext,	IN: Metadata filename extension.
<i>hid_t</i> meta_plist_id,	IN: File access property list identifier for the metadata file.
<i>const char</i> *raw_ext,	IN: Raw data filename extension.
<i>hid_t</i> raw_plist_id	IN: File access property list identifier for the raw data file.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Example:**

```
/* Example 1: Both metadata and rawdata files are in the same */
/*    directory.    Use Station1-m.h5 and Station1-r.h5 as    */
/*    the metadata and rawdata files.                          */
hid_t fapl, fid;
fapl = H5Pcreate(H5P_FILE_ACCESS);
H5Pset_fapl_split(fapl, "-m.h5", H5P_DEFAULT, "-r.h5", H5P_DEFAULT);
fid=H5Fcreate("Station1",H5F_ACC_TRUNC,H5P_DEFAULT,fapl);

/* Example 2: metadata and rawdata files are in different    */
/*    directories.    Use PointA-m.h5 and /pfs/PointA-r.h5 as */
/*    the metadata and rawdata files.                          */
hid_t fapl, fid;
```

```
fapl = H5Pcreate(H5P_FILE_ACCESS);
H5Pset_fapl_split(fapl, "-m.h5", H5P_DEFAULT, "/pfs/%s-r.h5", H5P_DEFAULT);
fid=H5Fcreate("PointA",H5F_ACC_TRUNC,H5P_DEFAULT,fapl);
```

**Fortran90 Interface: h5pset\_fapl\_split\_f**

```
SUBROUTINE h5pset_fapl_split_f(prp_id, meta_ext, meta_plist, raw_ext, &
                               raw_plist, hdferr)

  IMPLICIT NONE
  INTEGER(HID_T),INTENT(IN)   :: prp_id      ! Property list identifier
  CHARACTER(LEN=*),INTENT(IN) :: meta_ext    ! Name of the extension for
                                              ! the metafile filename
  INTEGER(HID_T),INTENT(IN)   :: meta_plist  ! Identifier of the meta file
                                              ! access property list
  CHARACTER(LEN=*),INTENT(IN) :: raw_ext     ! Name extension for the raw
                                              ! file filename
  INTEGER(HID_T),INTENT(IN)   :: raw_plist   ! Identifier of the raw file
                                              ! access property list
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
                                              ! 0 on success and -1 on failure

END SUBROUTINE h5pset_fapl_split_f
```

**History:**

Release	C
1.4.0	Function introduced in this release.

**Name:** H5Pset\_fapl\_stdio

**Signature:**

*herr\_t* H5Pset\_fapl\_stdio(*hid\_t* fapl\_id)

**Purpose:**

Sets the standard I/O driver.

**Description:**

H5Pset\_fapl\_stdio modifies the file access property list to use the standard I/O driver, H5FD\_STDIO.

**Parameters:**

*hid\_t* fapl\_id      IN: File access property list identifier.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fapl\_stdio\_f

```
SUBROUTINE h5pset_fapl_stdio_f(prp_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)      :: prp_id   ! Property list identifier
  INTEGER, INTENT(OUT)            :: hdferr   ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pset_fapl_stdio_f
```

**History:**

**Release    C**

1.4.0      Function introduced in this release.



**Name:** H5Pset\_fapl\_windows

**Signature:**

*herr\_t* H5Pset\_fapl\_windows( *hid\_t* fapl\_id )

**Purpose:**

Sets the Windows I/O driver.

**Description:**

H5Pset\_fapl\_windows sets the default HDF5 Windows I/O driver on Windows systems.

Since the HDF5 Library uses this driver, H5FD\_WINDOWS, by default on Windows systems, it is not normally necessary for a user application to call H5Pset\_fapl\_windows. While it is not recommended, there may be times when a user chooses to set a different HDF5 driver, such as the standard I/O driver (H5FD\_STDIO) or the sec2 driver (H5FD\_SEC2), in a Windows application. H5Pset\_fapl\_windows is provided so that the application can return to the Windows I/O driver when the time comes.

Only the Windows driver is tested on Windows systems; other drivers are used at the application's and the user's risk.

Furthermore, the Windows driver is tested and available only on Windows systems; it is not available on non-Windows systems.

**Parameters:**

*hid\_t* fapl\_id      IN: File access property list identifier

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_fclose\_degree

**Signature:**

```
herr_t H5Pset_fclose_degree(hid_t fapl_id, H5F_close_degree_t fc_degree)
```

**Purpose:**

Sets the file close degree.

**Description:**

H5Pset\_fclose\_degree sets the file close degree property `fc_degree` in the file access property list `fapl_id`.

The value of `fc_degree` determines how aggressively H5Fclose deals with objects within a file that remain open when H5Fclose is called to close that file. `fc_degree` can have any one of four valid values:

Degree name	H5Fclose behavior with no open object in file	H5Fclose behavior with open object(s) in file
H5F_CLOSE_WEAK	Actual file is closed.	Access to file identifier is terminated; actual file close is delayed until all objects in file are closed
H5F_CLOSE_SEMI	Actual file is closed.	Function returns FAILURE
H5F_CLOSE_STRONG	Actual file is closed.	All open objects remaining in the file are closed then file is closed
H5F_CLOSE_DEFAULT	The VFL driver chooses the behavior. Currently, all VFL drivers set this value to H5F_CLOSE_WEAK, except for the MPI-I/O driver, which sets it to H5F_CLOSE_SEMI.	

**Parameters:**

*hid\_t* fapl\_id

IN: File access property list identifier.

*H5F\_close\_degree\_t* fc\_degree

IN: Pointer to a location containing the file close degree property, the value of `fc_degree`.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fclose\_degree\_f

```
SUBROUTINE h5pset_fclose_degree_f(fapl_id, degree, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: fapl_id ! File access property list identifier
  INTEGER, INTENT(IN) :: degree ! Info about file close behavior
  ! Possible values:
  !   H5F_CLOSE_DEFAULT_F
  !   H5F_CLOSE_WEAK_F
  !   H5F_CLOSE_SEMI_F
  !   H5F_CLOSE_STRONG_F
```

```
        INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                           ! 0 on success and -1 on failure
    END SUBROUTINE h5pset_fclose_degree_f
```

**History:**

Release	C
1.6.0	Function introduced in this release.

**Name:** H5Pset\_fill\_time

**Signature:**

```
herr_t H5Pset_fill_time(hid_t plist_id, H5D_fill_time_t fill_time)
```

**Purpose:**

Sets the time when fill values are written to a dataset.

**Description:**

H5Pset\_fill\_time sets up the timing for writing fill values to a dataset. This property is set in the dataset creation property list *plist\_id*.

Timing is specified in *fill\_time* with one of the following values:

H5D_FILL_TIME_IFSET	Write fill values to the dataset when storage space is allocated only if there is a user-defined fill value, i.e., one set with H5Pset_fill_value. (Default)
H5D_FILL_TIME_ALLOC	Write fill values to the dataset when storage space is allocated.
H5D_FILL_TIME_NEVER	Never write fill values to the dataset.

**Note:**

H5Pset\_fill\_time is designed for coordination with the dataset fill value and dataset storage allocation time properties, set with the functions H5Pset\_fill\_value and H5Pset\_alloc\_time.

See H5Dcreate for further cross-references.

**Parameters:**

<i>hid_t</i> plist_id	IN: Dataset creation property list identifier.
<i>H5D_fill_time_t</i> fill_time	IN: When to write fill values to a dataset.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fill\_time\_f

```
SUBROUTINE h5pset_fill_time_f(plist_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! Dataset creation property
                                          ! list identifier
  INTEGER(HSIZE_T), INTENT(IN) :: flag   ! File time flag
                                          ! Possible values are:
                                          !   H5D_FILL_TIME_ERROR_F
                                          !   H5D_FILL_TIME_ALLOC_F
                                          !   H5D_FILL_TIME_NEVER_F
  INTEGER, INTENT(OUT)          :: hdferr ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pset_fill_time_f
```

**History:**

Release	C
1.6.0	Function introduced in this release.

**Name:** H5Pset\_fill\_value

**Signature:**

```
herr_t H5Pset_fill_value(hid_t plist_id, hid_t type_id, const void *value )
```

**Purpose:**

Sets the fill value for a dataset.

**Description:**

H5Pset\_fill\_value sets the fill value for a dataset in the dataset creation property list.

*value* is interpreted as being of datatype *type\_id*. This datatype may differ from that of the dataset, but the HDF5 library must be able to convert *value* to the dataset datatype when the dataset is created.

The default fill value is 0 (zero), which is interpreted according to the actual dataset datatype.

Setting *value* to NULL indicates that the fill value is to be undefined.

**Notes:**

Applications sometimes write data only to portions of an allocated dataset. It is often useful in such cases to fill the unused space with a known fill value. This function allows the user application to set that fill value; the functions H5Dfill and H5Pset\_fill\_time, respectively, provide the ability to apply the fill value on demand or to set up its automatic application.

A fill value should be defined so that it is appropriate for the application. While the HDF5 default fill value is 0 (zero), it is often appropriate to use another value. It might be useful, for example, to use a value that is known to be impossible for the application to legitimately generate.

H5Pset\_fill\_value is designed to work in concert with H5Pset\_alloc\_time and H5Pset\_fill\_time. H5Pset\_alloc\_time and H5Pset\_fill\_time govern the timing of dataset storage allocation and fill value write operations and can be important in tuning application performance.

See H5Dcreate for further cross-references.

**Parameters:**

<i>hid_t</i> plist_id	IN: Dataset creation property list identifier.
<i>hid_t</i> type_id,	IN: Datatype of value.
<i>const void</i> *value	IN: Pointer to buffer containing value to use as fill value.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fill\_value\_f

```
SUBROUTINE h5pset_fill_value_f(prp_id, type_id, fillvalue, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier of fill
                                         ! value datatype (in memory)
  TYPE(VOID), INTENT(IN) :: fillvalue ! Fillvalue
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pset_fill_value_f
```

**Name:** H5Pset\_filter

**Signature:**

```
herr_t H5Pset_filter(hid_t plist, H5Z_filter_t filter_id, unsigned int flags, size_t
cd_nelmts, const unsigned int cd_values[ ] )
```

**Purpose:**

Adds a filter to the filter pipeline.

**Description:**

H5Pset\_filter adds the specified filter\_id and corresponding properties to the end of an output filter pipeline. If plist is a dataset creation property list, the filter is added to the permanent filter pipeline; if plist is a dataset transfer property list, the filter is added to the transient filter pipeline.

The array cd\_values contains cd\_nelmts integers which are auxiliary data for the filter. The integer values will be stored in the dataset object header as part of the filter information.

The flags argument is a bit vector with the following fields specifying certain general properties of the filter:

H5Z_FLAG_OPTIONAL	If this bit is set then the filter is optional. If the filter fails (see below) during an H5Dwrite operation then the filter is just excluded from the pipeline for the chunk for which it failed; the filter will not participate in the pipeline during an H5Dread of the chunk. This is commonly used for compression filters: if the filter result would be larger than the input, then the compression filter returns failure and the uncompressed data is stored in the file. If this bit is clear and a filter fails, then H5Dwrite or H5Dread also fails.
-------------------	---

This flag should not be set for the Fletcher32 checksum filter as it will bypass the checksum filter without reporting checksum errors to an application.

The filter\_id parameter specifies the filter to be set. Valid filter identifiers are as follows:

H5Z_FILTER_DEFLATE	Data compression filter, employing the gzip algorithm
H5Z_FILTER_SHUFFLE	Data shuffling filter
H5Z_FILTER_FLETCHER32	Error detection filter, employing the Fletcher32 checksum algorithm
H5Z_FILTER_SZIP	Data compression filter, employing the SZIP algorithm

Also see H5Pset\_edc\_check and H5Pset\_filter\_callback.

**Notes:**

This function currently supports only the permanent filter pipeline; `plist` must be a dataset creation property list.

If multiple filters are set for a property list, they will be applied to each chunk in the order in which they were set.

**See Also:**

For a discussion of optional versus required filter behavior, see “Filter Behavior in HDF5.”

**Parameters:**

<i>hid_t</i> <code>plist</code>	IN: Property list identifier.
<i>H5Z_filter_t</i> <code>filter_id</code>	IN: Filter identifier for the filter to be added to the pipeline.
<i>unsigned int</i> <code>flags</code>	IN: Bit vector specifying certain general properties of the filter.
<i>size_t</i> <code>cd_nelmts</code>	IN: Number of elements in <code>cd_values</code> .
<i>const unsigned int</i> <code>cd_values[ ]</code>	IN: Auxiliary data for the filter.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** `h5pset_filter_f`

```

SUBROUTINE h5pset_filter_f(prp_id, filter, flags, cd_nelmts, cd_values, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN) :: filter ! Filter to be added to the pipeline
  INTEGER, INTENT(IN) :: flags ! Bit vector specifying certain
                                ! general properties of the filter
  INTEGER(SIZE_T), INTENT(IN) :: cd_nelmts
                                ! Number of elements in cd_values
  INTEGER, DIMENSION(*), INTENT(IN) :: cd_values
                                ! Auxiliary data for the filter
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_filter_f

```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Pset\_filter\_callback

**Signature:**

```
herr_t H5Pset_filter_callback(hid_t plist, H5Z_filter_func_t func, void *op_data)
```

**Purpose:**

Sets user-defined filter callback function.

**Description:**

H5Pset\_filter\_callback sets the user-defined filter callback function *func* in the dataset transfer property list *plist*.

The parameter *op\_data* is a pointer to user-defined input data for the callback function and will be passed through to the callback function.

The callback function *func* defines the actions an application is to take when a filter fails. The function prototype is as follows:

```
typedef H5Z_cb_return_t (H5Z_filter_func_t) (H5Z_filter_t filter_id, void *buf, size_t
buf_size, void *op_data)
```

where *filter\_id* indicates which filter has failed, *buf* and *buf\_size* are used to pass in the failed data, and *op\_data* is the required input data for this callback function.

Valid callback function return values are H5Z\_CB\_FAIL and H5Z\_CB\_CONT.

**Parameters:**

<i>hid_t</i> plist	IN: Dataset transfer property list identifier.
<i>H5Z_filter_func_t</i> func	IN: User-defined filter callback function.
<i>void</i> *op_data	IN: User-defined input data for the callback function.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.0	Function introduced in this release.



**Name:** H5Pset\_fletcher32

**Signature:**

*herr\_t* H5Pset\_fletcher32(*hid\_t* plist)

**Purpose:**

Sets up use of the Fletcher32 checksum filter.

**Description:**

H5Pset\_fletcher32 sets the Fletcher32 checksum filter in the dataset creation property list *plist*.

**Note:**

The initial error detection implementation supports error detection for chunked datasets only.

**Parameters:**

*hid\_t* plist      IN: Dataset creation property list identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_fletcher32\_f

```
SUBROUTINE h5pset_fletcher32_f(prp_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Dataset creation property list
                                         ! identifier
  INTEGER, INTENT(OUT)      :: hdferr ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pset_fletcher32_f
```

**History:**

Release	C
---------	---

1.6.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Pset\_gc\_references

**Signature:**

*herr\_t* H5Pset\_gc\_reference(*hid\_t* plist, *unsigned* gc\_ref )

**Purpose:**

Sets garbage collecting references flag.

**Description:**

H5Pset\_gc\_references sets the flag for garbage collecting references for the file.

Dataset region references and other reference types use space in an HDF5 file's global heap. If garbage collection is on and the user passes in an uninitialized value in a reference structure, the heap might get corrupted. When garbage collection is off, however, and the user re-uses a reference, the previous heap block will be orphaned and not returned to the free heap space.

When garbage collection is on, the user must initialize the reference structures to 0 or risk heap corruption.

The default value for garbage collecting references is off.

**Parameters:**

*hid\_t* plist                   IN: File access property list identifier.

*unsigned* gc\_ref            IN: Flag setting reference garbage collection to on (1) or off (0).

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_gc\_references\_f

```
SUBROUTINE h5pset_gc_references_f (prp_id, gc_reference, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN) :: gc_reference ! Flag for garbage collecting
                                         ! references for the file
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pset_gc_references_f
```

**Name:** H5Pset\_hyper\_vector\_size

**Signature:**

```
herr_t H5Pset_hyper_vector_size(hid_t dxpl_id, size_t vector_size)
```

**Purpose:**

Sets number of I/O vectors to be read/written in hyperslab I/O.

**Description:**

H5Pset\_hyper\_vector\_size sets the number of I/O vectors to be accumulated in memory before being issued to the lower levels of the HDF5 library for reading or writing the actual data.

The *I/O vectors* are hyperslab offset and length pairs and are generated during hyperslab I/O.

The number of I/O vectors is passed in `vector_size` to be set in the dataset transfer property list `dxpl_id`. `vector_size` must be greater than 1 (one).

H5Pset\_hyper\_vector\_size is an I/O optimization function; increasing `vector_size` should provide better performance, but the library will use more memory during hyperslab I/O. The default value of `vector_size` is 1024.

**Parameters:**

<code>hid_t dxpl_id</code>	IN: Dataset transfer property list identifier.
<code>size_t vector_size</code>	IN: Number of I/O vectors to accumulate in memory for I/O operations. Must be greater than 1 (one). Default value: 1024.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_hyper\_vector\_size\_f

```
SUBROUTINE h5pset_hyper_vector_size_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! Dataset transfer property list
                                          ! identifier
  INTEGER(SIZE_T), INTENT(IN) :: size    ! Vector size
  INTEGER, INTENT(OUT)       :: hdferr   ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pset_hyper_vector_size_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Pset\_istore\_k

**Signature:**

*herr\_t* H5Pset\_istore\_k(*hid\_t* plist, *unsigned ik*)

**Purpose:**

Sets the size of the parameter used to control the B-trees for indexing chunked datasets.

**Description:**

H5Pset\_istore\_k sets the size of the parameter used to control the B-trees for indexing chunked datasets. This function is only valid for file creation property lists.

*ik* is one half the rank of a tree that stores chunked raw data. On average, such a tree will be 75% full, or have an average rank of 1.5 times the value of *ik*.

**Parameters:**

*hid\_t* plist           IN: Identifier of property list to query.

*unsigned ik*           IN: 1/2 rank of chunked storage B-tree.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_istore\_k\_f

```
SUBROUTINE h5pset_istore_k_f (prp_id, ik, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN) :: ik           ! 1/2 rank of chunked storage B-tree
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pset_istore_k_f
```

**History:**

**Release   C**

1.6.4       *ik* parameter type changed to *unsigned*.

**Name:** H5Pset\_layout

**Signature:**

```
herr_t H5Pset_layout(hid_t plist, H5D_layout_t layout )
```

**Purpose:**

Sets the type of storage used to store the raw data for a dataset.

**Description:**

H5Pset\_layout sets the type of storage used to store the raw data for a dataset. This function is only valid for dataset creation property lists.

Valid values for layout are:

H5D\_COMPACT

Store raw data in the dataset object header in file. This should only be used for very small amounts of raw data. The current limit is approximately 64K (HDF5 Release 1.6).

H5D\_CONTIGUOUS

Store raw data separately from the object header in one large chunk in the file.

H5D\_CHUNKED

Store raw data separately from the object header as chunks of data in separate locations in the file.

Note that a compact storage layout may affect writing data to the dataset with parallel applications. See note in H5Dwrite documentation for details.

**Parameters:**

*hid\_t* plist                      IN: Identifier of property list to query.

*H5D\_layout\_t* layout          IN: Type of storage layout for raw data.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_layout\_f

```
SUBROUTINE h5pset_layout_f (prp_id, layout, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN) :: layout        ! Type of storage layout for raw data
                                      ! Possible values are:
                                      !   H5D_COMPACT_F
                                      !   H5D_CONTIGUOUS_F
                                      !   H5D_CHUNKED_F
  INTEGER, INTENT(OUT) :: hdferr       ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pset_layout_f
```

**Name:** H5Pset\_libver\_bounds

**Signature:**

```
herr_t H5Pset_libver_bounds( hid_t fapl_id, H5F_libver_t low, H5F_libver_t high )
```

**Purpose:**

Sets bounds on library versions, and indirectly format versions, to be used when creating objects.

**Description:**

H5Pset\_libver\_bounds controls the versions of the object formats that will be used when creating objects in a file. The object format versions are determined indirectly from the HDF5 Library versions specified in the call.

This property is set in the file access property list specified by fapl\_id.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier
<i>H5F_libver_t</i> low	IN: The earliest version of the library that will be used for writing objects. The library version indirectly specifies the earliest object format version that can be used when creating objects in the file.

Currently, low must be one of two pre-defined values:

Setting low to H5F\_LIBVER\_EARLIEST will result in objects being created using the *earliest possible* format for each object. Note that *earliest possible* is different from *earliest*, as some features introduced in library versions later than 1.0.0 resulted in updates to object formats. With low=H5F\_LIBVER\_EARLIEST, if the application creates an object that requires a feature introduced in library versions later than 1.0.0, the earliest possible version that supports the requested feature will be used.

The upper bound on the range of possible library versions used to create the object is controlled by the high parameter.

This is the default behavior of the library if H5Pset\_libver\_bounds is not called.

Setting low to H5F\_LIBVER\_LATEST will result in objects being created using the *latest available* format for each object. This setting means that objects will be created with the latest format versions available (within the range of library versions specified in the call), and can take advantage of the latest features and performance enhancements. Objects written with the H5F\_LIBVER\_LATEST setting for low may be accessible to a smaller range of library versions than would be the case if the H5F\_LIBVER\_EARLIEST value had been used.

The upper bound on the range of possible library versions used to create the object is controlled by the high parameter.

<i>H5F_libver_t</i> high	IN: The latest version of the library that will be used for writing objects. The library version indirectly specifies the latest object format version that can be used when creating objects in the file.
--------------------------	--

Currently, high must be set to the pre-defined value H5F\_LIBVER\_LATEST.  
H5F\_LIBVER\_LATEST corresponds to the version of the HDF5 Library in use.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_libver\_bounds\_f

```

SUBROUTINE h5pset_libver_bounds_f(fapl_id, low, high, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: fapl_id ! File access property list identifier
  INTEGER, INTENT(IN) :: low ! The earliest version of the library that
                             ! will be used for writing objects.
                             ! Currently, low must be either:
                             !       H5F_LIBVER_EARLIEST_F
                             !       H5F_LIBVER_LATEST_F
  INTEGER, INTENT(IN) :: high
                             ! The latest version of the library that will be
                             ! used for writing objects.
                             ! Currently, high must set to:
                             !       H5F_LIBVER_LATEST_F
  INTEGER, INTENT(OUT) :: hdferr
                             ! Error code
                             ! 0 on success and -1 on failure
END SUBROUTINE h5pset_libver_bounds_f

```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_link\_creation\_order

**Signature:**

*herr\_t* H5Pset\_link\_creation\_order( *hid\_t* gcpl\_id, *unsigned* crt\_order\_flags )

**Purpose:**

Sets creation order tracking and indexing for links in a group.

**Description:**

H5Pset\_link\_creation\_order sets flags in a group creation property list, gcpl\_id, for tracking and/or indexing links on creation order.

The following flags are passed in crt\_order\_flags:

H5P\_CRT\_ORDER\_TRACKED      Specifies to track creation order.

H5P\_CRT\_ORDER\_INDEXED      Specifies to index links in the group on creation order.

If only H5P\_CRT\_ORDER\_TRACKED is set, HDF5 will track link creation order in any group created with the group creation property list gcpl\_id. If both H5P\_CRT\_ORDER\_TRACKED and H5P\_CRT\_ORDER\_INDEXED are set, HDF5 will track link creation order in the group and index links on that property.

**Parameters:**

*hid\_t* gcpl\_id                      IN: Group creation property list identifier

*unsigned* crt\_order\_flags          IN: Creation order flag(s)

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_link\_creation\_order\_f

```
SUBROUTINE h5pset_link_creation_order_f(gcpl_id, crt_order_flags, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: gcpl_id ! File access property list identifier
  INTEGER, INTENT(IN) :: crt_order_flags ! Creation order flag(s)
  INTEGER, INTENT(OUT) :: hdferr ! Error code
  ! 0 on success and -1 on failure
END SUBROUTINE h5pset_link_creation_order_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.



**Name:** H5Pset\_link\_phase\_change

**Signature:**

```
herr_t H5Pset_link_phase_change( hid_t gcpl_id, unsigned max_compact, unsigned
min_dense )
```

**Purpose:**

Sets the parameters for conversion between compact and dense groups.

**Description:**

H5Pset\_link\_phase\_change sets the maximum number of entries for a *compact* group and the minimum number of links to allow before converting a *dense* group to back to the compact format.

max\_compact is the maximum number of links to store as header messages in the group header as before converting the group to the dense format. Groups that are in compact format and in which the exceed this number of links rises above this threshold are automatically converted to dense format.

min\_dense is the minimum number of links to store in the dense format. Groups which are in dense format and in which the number of links falls below this threshold are automatically converted to compact format.

See “Group implementations in HDF5” in the H5G API introduction for a discussion of the available types of HDF5 group structures.

**Parameters:**

<i>hid_t</i> gcpl_id	IN: Group creation property list identifier
<i>unsigned</i> max_compact	IN: Maximum number of links for compact storage (Default: 8)
<i>unsigned</i> min_dense	IN: Minimum number of links for dense storage (Default: 6)

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_link\_phase\_change\_f

```
SUBROUTINE h5pset_link_phase_change_f(gcpl_id, max_compact, min_dense, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: gcpl_id ! Group creation property list id
  INTEGER, INTENT(IN) :: max_compact    ! Maximum number of attributes to be
                                         ! stored in compact storage
  INTEGER, INTENT(IN) :: min_dense      ! Minimum number of attributes to be
                                         ! stored in dense storage
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pset_link_phase_change_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_local\_heap\_size\_hint

**Signature:**

```
herr_t H5Pset_local_heap_size_hint( hid_t gcpl_id, size_t size_hint )
```

**Purpose:**

Specifies the anticipated maximum size of a local heap.

**Description:**

H5Pset\_local\_heap\_size\_hint is used with original-style HDF5 groups (see “Motivation” below) to specify the anticipated maximum local heap size, `size_hint`, for groups created with the group creation property list `gcpl_id`. The HDF5 Library then uses `size_hint` to allocate contiguous local heap space in the file for each group created with `gcpl_id`.

For groups with many members or very few members, an appropriate initial value of `size_hint` would be the anticipated number of group members times the average length of group member names, plus a small margin:

```
size_hint = max_number_of_group_members *  
            (average_length_of_group_member_link_names + 2)
```

If it is known that there will be groups with zero members, the use of a group creation property list with `size_hint` set to 1 (one) will guarantee the smallest possible local heap for each of those groups.

Setting `size_hint` to zero (0) causes the library to make a reasonable estimate for the default local heap size.

**Motivation:**

In situations where backward-compatibility is required, specifically, when libraries prior to HDF5 Release 1.8.0 may be used to read the file, groups must be created and maintained in the original style. This is HDF5’s default behavior. If backward compatibility with pre-1.8.0 libraries is not a concern, greater efficiencies can be obtained with the new-format compact and indexed groups. See “Group implementations in HDF5” in the H5G API introduction.

H5Pset\_local\_heap\_size\_hint is useful for tuning file size when files contain original-style groups with either zero members or very large numbers of members.

The original style of HDF5 groups, the only style available prior to HDF5 Release 1.8.0, was well-suited for moderate-sized groups but was not optimized for either very small or very large groups. This original style remains the default, but two new group implementations were introduced in HDF5 Release 1.8.0: compact groups to accomodate zero to small numbers of members and indexed groups for thousands or tens of thousands of members ... or millions, if that's what your application requires.

The local heap size hint, `size_hint`, is a performance tuning parameter *for original-style groups*. As indicated above, an HDF5 group may have zero, a handful, or tens of thousands of members. Since the original style of HDF5 groups stores the metadata for all of these group members in a uniform format in a local heap, the size of that metadata (and hence, the size of the local heap) can vary wildly from group to group. To intelligently allocate space and to avoid unnecessary fragmentation of the local heap, it can be valuable to provide the library with a hint as to the local heap’s likely eventual size. This can be particularly valuable when it is known that a group will eventually have a great many members. It can also be useful in conserving space in a file when it is known that certain groups will never have any members.

**Parameters:**

*hid\_t* *gcpl\_id*                   IN: Group creation property list identifier  
*size\_t* *size\_hint*               IN: Anticipated maximum size in bytes of local heap

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_local\_heap\_size\_hint\_f

```
SUBROUTINE h5pset_local_heap_size_hint_f(gcpl_id, size_hint, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: gcpl_id      ! Group creation property list id
  INTEGER(SIZE_T), INTENT(IN) :: size_hint ! Hint for size of local heap
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5pset_local_heap_size_hint_f
```

**History:**

Release	Change
1.8.0	Function introduced in this release.

*Last modified: 18 May 2009***Name:** H5Pset\_mdc\_config**Signature:**

```
herr_t H5Pset_mdc_config(hid_t plist_id, H5AC_cache_config_t *config_ptr)
```

**Purpose:**

Set the initial metadata cache configuration in the indicated File Access Property List to the supplied value.

**Description:**

H5Pset\_mdc\_config attempts to set the initial metadata cache configuration to the supplied value. It will fail if an invalid configuration is detected. This configuration is used when the file is opened.

See the overview of the metadata cache in the special topics section of the user manual for details on what is being configured. If you haven't read and understood that documentation, you really shouldn't be using this API call.

**Parameters:**

*hid\_t* plist\_id

IN: Identifier of the file access property list.

*H5AC\_cache\_config\_t* \*config\_ptr

IN: Pointer to the instance of *H5AC\_cache\_config\_t* containing the desired configuration. The fields of this structure are discussed below:

**General configuration section:**

*int* version

IN: Integer field indicating the the version of the *H5AC\_cache\_config\_t* in use. This field should be set to *H5AC\_CURR\_CACHE\_CONFIG\_VERSION* (defined in *H5ACpublic.h*).

*hbool\_t* rpt\_fcn\_enabled

IN: Boolean flag indicating whether the adaptive cache resize report function is enabled. This field should almost always be set to *FALSE*. Since resize algorithm activity is reported via stdout, it **MUST** be set to *FALSE* on Windows machines.

The report function is not supported code, and can be expected to change between versions of the library. Use it at your own risk.

*hbool\_t* open\_trace\_file

IN: Boolean field indicating whether the *trace\_file\_name* field should be used to open a trace file for the cache.

The trace file is a debugging feature that allows the capture of top level metadata cache requests for purposes of debugging and/or optimization. This field should normally be set to *FALSE*, as trace file collection imposes considerable overhead.

This field should only be set to TRUE when the `trace_file_name` contains the full path of the desired trace file, and either there is no open trace file on the cache, or the `close_trace_file` field is also TRUE.

The trace file feature is unsupported unless used at the direction of THG. It is intended to allow THG to collect a trace of cache activity in cases of occult failures and/or poor performance seen in the field, so as to aid in reproduction in the lab. If you use it absent the direction of THG, you are on your own.

*hbool\_t* `close_trace_file`

IN: Boolean field indicating whether the current trace file (if any) should be closed.

See the above comments on the `open_trace_file` field. This field should be set to FALSE unless there is an open trace file on the cache that you wish to close.

The trace file feature is unsupported unless used at the direction of THG. It is intended to allow THG to collect a trace of cache activity in cases of occult failures and/or poor performance seen in the field, so as to aid in reproduction in the lab. If you use it absent the direction of THG, you are on your own.

*char* `trace_file_name[]`

IN: Full path of the trace file to be opened if the `open_trace_file` field is TRUE.

In the parallel case, an ascii representation of the MPI rank of the process will be appended to the file name to yield a unique trace file name for each process.

The length of the path must not exceed `H5AC__MAX_TRACE_FILE_NAME_LEN` characters.

The trace file feature is unsupported unless used at the direction of THG. It is intended to allow THG to collect a trace of cache activity in cases of occult failures and/or poor performance seen in the field, so as to aid in reproduction in the lab. If you use it absent the direction of THG, you are on your own.

*hbool\_t* `evictions_enabled`

IN: A boolean flag indicating whether evictions from the metadata cache are enabled. This flag is initially set to TRUE.

In rare circumstances, the raw data throughput requirements may be so high that the user wishes to postpone metadata writes so as to reserve I/O throughput for raw data. The `evictions_enabled` field exists to allow this. However, this is an extreme step, and you have no business doing it unless you have read the User Guide section on metadata caching, and have considered all other options carefully.

The `evictions_enabled` field may not be set to `FALSE` unless all adaptive cache resizing code is disabled via the `incr_mode`, `flash_incr_mode`, and `decr_mode` fields.

When this flag is set to `FALSE`, the metadata cache will not attempt to evict entries to make space for new entries, and thus will grow without bound.

Evictions will be re-enabled when this field is set back to `TRUE`. This should be done as soon as possible.

IN: Boolean flag indicating whether the cache should be created with a user specified initial size.

IN: If `set_initial_size` is `TRUE`, `initial_size` must contain the desired initial size in bytes. This value must lie in the closed interval `[min_size, max_size]`. (see below)

IN: This field specifies the minimum fraction of the cache that must be kept either clean or empty.

The value must lie in the interval `[0.0, 1.0]`. 0.01 is a good place to start in the serial case. In the parallel case, a larger value is needed -- see the overview of the metadata cache in the “HDF5 Special Topics” section of the *HDF5 User’s Guide* for details.

IN: Upper bound (in bytes) on the range of values that the adaptive cache resize code can select as the maximum cache size.

IN: Lower bound (in bytes) on the range of values that the adaptive cache resize code can select as the maximum cache size.

IN: Number of cache accesses between runs of the adaptive cache resize code. 50,000 is a good starting number.

*hbool\_t* `set_initial_size`

*size\_t* `initial_size`

*double* `min_clean_fraction`

*size\_t* `max_size`

*size\_t* `min_size`

*long int* `epoch_length`

**Increment configuration section:**

*enum H5C\_cache\_incr\_mode* incr\_mode

IN: Enumerated value indicating the operational mode of the automatic cache size increase code. At present, only two values are legal:

H5C\_incr\_\_off: Automatic cache size increase is disabled, and the remaining increment fields are ignored.

H5C\_incr\_\_threshold: Automatic cache size increase is enabled using the hit rate threshold algorithm.

*double* lower\_hr\_threshold

IN: Hit rate threshold used by the hit rate threshold cache size increment algorithm.

When the hit rate over an epoch is below this threshold and the cache is full, the maximum size of the cache is multiplied by increment (below), and then clipped as necessary to stay within max\_size, and possibly max\_increment.

This field must lie in the interval [0.0, 1.0]. 0.8 or 0.9 is a good place to start.

*double* increment

IN: Factor by which the hit rate threshold cache size increment algorithm multiplies the current cache max size to obtain a tentative new cache size.

The actual cache size increase will be clipped to satisfy the max\_size specified in the general configuration, and possibly max\_increment below.

The parameter must be greater than or equal to 1.0 -- 2.0 is a reasonable value.

If you set it to 1.0, you will effectively disable cache size increases.

*hbool\_t* apply\_max\_increment

IN: Boolean flag indicating whether an upper limit should be applied to the size of cache size increases.

*size\_t* max\_increment

IN: Maximum number of bytes by which cache size can be increased in a single step -- if applicable.

*enum H5C\_cache\_flash\_incr\_mode* flash\_incr\_mode

IN: Enumerated value indicating the operational mode of the flash cache size increase code. At present, only the following values are legal:

*double* flash\_threshold

*double* flash\_multiple

#### **Decrement configuration section:**

*enum* H5C\_cache\_decr\_mode decr\_mode

H5C\_flash\_incr\_\_off: Flash cache size increase is disabled.

H5C\_flash\_incr\_\_add\_space: Flash cache size increase is enabled using the add space algorithm.

IN: The factor by which the current maximum cache size is multiplied to obtain the minimum size entry / entry size increase which may trigger a flash cache size increase.

At present, this value must lie in the range [0.1, 1.0].

IN: The factor by which the size of the triggering entry / entry size increase is multiplied to obtain the initial cache size increment. This increment may be reduced to reflect existing free space in the cache and the max\_size field above.

At present, this field must lie in the range [0.1, 10.0].

IN: Enumerated value indicating the operational mode of the automatic cache size decrease code. At present, the following values are legal:

H5C\_decr\_\_off: Automatic cache size decrease is disabled.

H5C\_decr\_\_threshold: Automatic cache size decrease is enabled using the hit rate threshold algorithm.

H5C\_decr\_\_age\_out: Automatic cache size decrease is enabled using the ageout algorithm.

H5C\_decr\_\_age\_out\_with\_threshold: Automatic cache size decrease is enabled using the ageout with hit rate threshold algorithm



*double* upper\_hr\_threshold

IN: Hit rate threshold for the hit rate threshold and ageout with hit rate threshold cache size decrement algorithms.

When `decr_mode` is `H5C_decr__threshold`, and the hit rate over a given epoch exceeds the supplied threshold, the current maximum cache size is multiplied by decrement to obtain a tentative new (and smaller) maximum cache size.

When `decr_mode` is `H5C_decr__age_out_with_threshold`, there is no attempt to find and evict aged out entries unless the hit rate in the previous epoch exceeded the supplied threshold.

This field must lie in the interval [0.0, 1.0].

For `H5C_incr__threshold`, .9995 or .99995 is a good place to start.

For `H5C_decr__age_out_with_threshold`, .999 might be more useful.

*double* decrement

IN: In the hit rate threshold cache size decrease algorithm, this parameter contains the factor by which the current max cache size is multiplied to produce a tentative new cache size.

The actual cache size decrease will be clipped to satisfy the `min_size` specified in the general configuration, and possibly `max_decrement` below.

The parameter must be in the interval [0.0, 1.0].

If you set it to 1.0, you will effectively disable cache size decreases. 0.9 is a reasonable starting point.

*hbool\_t* apply\_max\_decrement

IN: Boolean flag indicating whether an upper limit should be applied to the size of cache size decreases.

*size\_t* max\_decrement

IN: Maximum number of bytes by which the maximum cache size can be decreased in any single step -- if applicable.

*int* epochs\_before\_eviction

IN: In the ageout based cache size reduction algorithms, this field contains the minimum number of epochs an entry must remain unaccessed in cache before the cache size reduction algorithm tries to evict it. 3 is a reasonable value.

*hbool\_t* apply\_empty\_reserve

IN: Boolean flag indicating whether the ageout based decrement algorithms will maintain a empty reserve when decreasing cache size.

*double* empty\_reserve

IN: Empty reserve as a fraction of maximum cache size if applicable.

When so directed, the ageout based algorithms will not decrease the maximum cache size unless the empty reserve can be met.

The parameter must lie in the interval [0.0, 1.0]. 0.1 or 0.05 is a good place to start.

**Parallel configuration section:**

*int* dirty\_bytes\_threshold

IN: Threshold number of bytes of dirty metadata generation for triggering synchronizations of the metadata caches serving the target file in the parallel case.

Synchronization occurs whenever the number of bytes of dirty metadata created since the last synchronization exceeds this limit.

This field only applies to the parallel case. While it is ignored elsewhere, it can still draw a value out of bounds error.

It must be consistent across all caches on any given file.

By default, this field is set to 256 KB. It shouldn't be more than half the current max cache size times the min clean fraction.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Name:** H5Pset\_meta\_block\_size

**Signature:**

```
herr_t H5Pset_meta_block_size(hid_t fapl_id, hsize_t size)
```

**Purpose:**

Sets the minimum metadata block size.

**Description:**

H5Pset\_meta\_block\_size sets the minimum size, in bytes, of metadata block allocations when H5FD\_FEAT\_AGGREGATE\_METADATA is set by a VFL driver.

Each *raw* metadata block is initially allocated to be of the given size. Specific metadata objects (e.g., object headers, local heaps, B-trees) are then sub-allocated from this block.

The default setting is 2048 bytes, meaning that the library will attempt to aggregate metadata in at least 2K blocks in the file. Setting the value to 0 (zero) with this function will turn off metadata aggregation, even if the VFL driver attempts to use the metadata aggregation strategy.

Metadata aggregation reduces the number of small data objects in the file that would otherwise be required for metadata. The aggregated block of metadata is usually written in a single write action and always in a contiguous block, potentially significantly improving library and application performance.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>hsize_t</i> size	IN: Minimum size, in bytes, of metadata block allocations.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_meta\_block\_size\_f

```
SUBROUTINE h5pset_meta_block_size_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! File access property list
                                          ! identifier
  INTEGER(HSIZE_T), INTENT(IN) :: size    ! Metadata block size
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pset_meta_block_size_f
```

**History:**

<b>Release</b>	<b>C</b>
1.4.0	Function introduced in this release.

**Name:** H5Pset\_multi\_type

**Signature:**

```
herr_t H5Pset_multi_type ( hid_t fapl_id, H5FD_mem_t type )
```

**Purpose:**

Specifies type of data to be accessed via the MULTI driver, enabling more direct access.

**Description:**

H5Pset\_multi\_type sets the *type of data* property in the file access property list fapl\_id.

This setting enables a user application to specify the type of data the application wishes to access so that the application can retrieve a file handle for low-level access to the particular member of a set of MULTI files in which that type of data is stored. The file handle is retrieved with a separate call to H5Fget\_vfd\_handle (or, in special circumstances, to H5FDget\_vfd\_handle; see *Virtual File Layer* and *List of VFL Functions* in *HDF5 Technical Notes*).

The type of data specified in type may be one of the following:

H5FD_MEM_SUPER	Super block data
H5FD_MEM_BTREE	B-tree data
H5FD_MEM_DRAW	Dataset raw data
H5FD_MEM_GHEAP	Global heap data
H5FD_MEM_LHEAP	Local Heap data
H5FD_MEM_OHDR	Object header data

This function is for use only when accessing an HDF5 file written as a set of files with the MULTI file driver.

**Parameters:**

hid\_t fapl\_id           IN: File access property list identifier.  
H5FD\_mem\_t type        IN: Type of data to be accessed.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	Change
1.6.0	C function introduced in this release.

**Name:** H5Pset\_nbit

**Signature:**

```
herr_t H5Pset_nbit(hid_t plist_id)
```

**Purpose:**

Sets up the use of the N-Bit filter.

**Description:**

H5Pset\_nbit sets the N-Bit filter, H5Z\_FILTER\_NBIT, in the dataset creation property list `plist_id`.

The HDF5 user can create an N-Bit datatype by writing codes like:

```
hid_t nbit_datatype = H5Tcopy(H5T_STD_I32LE);
H5Tset_precision(nbit_datatype, 16);
H5Tset_offset(nbit_datatype, 4);
```

In memory, one value of the N-Bit datatype in the above example will be stored on a little-endian machine like this:

byte 3	byte 2	byte 1	byte 0
???????	???SPPP	PPPPPPPP	PPPP????

Note: S - sign bit, P - significant bit, ? - padding bit; For signed integer, the sign bit is included in the precision.

When data of the above datatype are stored on disk using N-bit filter, all padding bits are chopped off and only significant bits are stored. So, the values on disk will be something like:

1st value	2nd value	
SPPPPPPPPPPPPPPPP	SPPPPPPPPPPPPPPPP	...

The N-Bit filter is used effectively for compressing data of an N-Bit datatype as well as a compound and an array datatype with N-Bit fields. However, the datatype classes of the N-Bit datatype or the N-Bit field of the compound datatype or the array datatype are limited to integer or floating-point.

The N-Bit filter supports complex situations where a compound datatype contains member(s) of compound datatype or an array datatype that has compound datatype as the base type. However, it does not support the situation where an array datatype has variable-length or variable-length string as its base datatype. But the filter does support the situation where variable-length or variable-length string is a member of a compound datatype.

For all other HDF5 datatypes such as time, string, bitfield, opaque, reference, enum, and variable length, the N-Bit filter allows them to pass through like an no-op.

Like other I/O filters supported by the HDF5 library, application using the N-Bit filter must store data with chunked storage.

By nature, the N-Bit filter should not be used together with other I/O filters.

**Parameters:**

`hid_t plist_id` IN: Dataset creation property list identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

```
SUBROUTINE h5pset_nbit_f(plist_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! Dataset creation property list id
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pset_nbit_f
```

**Name:** H5Pset\_nlinks

**Signature:**

*herr\_t* H5Pset\_nlinks( *hid\_t* lapl\_id, *size\_t* nlinks )

**Purpose:**

Sets maximum number of soft or user-defined link traversals.

**Description:**

H5Pset\_nlinks sets the maximum number of soft or user-defined link traversals allowed, nlinks, before the library assumes it has found a cycle and aborts the traversal. This value is set in the link access property list lapl\_id.

The limit on the number soft or user-defined link traversals is designed to terminate link traversal if one or more links form a cycle. User control is provided because some files may have legitimate paths formed of large numbers of soft or user-defined links. This property can be used to allow traversal of as many links as desired.

**Parameters:**

*hid\_t* lapl\_id      IN: File access property list identifier  
*size\_t* nlinks      IN: Maximum number of links to traverse

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_nlinks\_f

```
SUBROUTINE h5pset_nlinks_f(lapl_id, nlinks, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: lapl_id ! File access property list identifier
  INTEGER(SIZE_T), INTENT(IN) :: nlinks ! Maximum number of links to traverse
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pset_nlinks_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_preserve

**Signature:**

```
herr_t H5Pset_preserve(hid_t plist, hbool_t status)
```

**Purpose:**

Sets the dataset transfer property list status to 1 (TRUE) or 0 (FALSE).

**Notice:**

*This function is deprecated as it no longer has any effect; compound datatype field preservation is now core functionality in the HDF5 Library.*

**Description:**

H5Pset\_preserve sets the dataset transfer property list status to 1 (TRUE) or 0 (FALSE).

When reading or writing compound datatypes and the destination is partially initialized and the read/write is intended to initialize the other members, one must set this property to TRUE. Otherwise the I/O pipeline treats the destination datapoints as completely uninitialized.

**Parameters:**

<code>hid_t plist</code>	IN: Identifier for the dataset transfer property list.
<code>hbool_t status</code>	IN: Status of for the dataset transfer property list (TRUE/FALSE).

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_preserve\_f

```
SUBROUTINE h5pset_preserve_f(prp_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id    ! Dataset transfer property
                                          ! list identifier
  LOGICAL, INTENT(IN)       :: flag      ! Status for the dataset
                                          ! transfer property list
  INTEGER, INTENT(OUT)      :: hdferr    ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pset_preserve_f
```

**History:**

Release	Fortran90
1.6.0	The <code>flag</code> parameter has changed from <i>INTEGER</i> to <i>LOGICAL</i> to better match the C API.



**Name:** H5Pset\_obj\_track\_times

**Signature:**

```
herr_t H5Pset_obj_track_times(hid_t ocpl_id, hbool_t track_times)
```

**Purpose:**

Sets the recording of times associated with an object.

**Description:**

H5Pset\_obj\_track\_times sets a property in the object creation property list, *ocpl\_id*, that governs the recording of times associated with an object.

If *track\_times* is TRUE, the following times will be recorded:

Birth time	The time the object was created
Access time	The last time that metadata or raw data was read from the object
Modification time	The last time data for this object was changed (by writing raw data to a dataset or inserting, modifying, or deleting a link in a group)
Change time	The last time metadata for this object was written (by adding, modifying, or deleting an attribute on an object; extending the size of a dataset; et cetera)

If *track\_times* is FALSE, time data will not be recorded.

Time data can be retrieved with H5Oget\_info, which will return it in the H5O\_info\_t struct.

If times are not tracked, they will be reported as follows when queried:

```
12:00 AM UDT, Jan. 1, 1970
```

That date and time are commonly used to represent the beginning of the UNIX epoch.

**Parameters:**

<i>hid_t</i> ocpl_id	IN: Object creation property list identifier
<i>hbool_t</i> track_times	IN: Boolean value, TRUE or FALSE, specifying whether object times are to be tracked

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_obj\_track\_times\_f

```
SUBROUTINE h5pset_obj_track_times_f(plist_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id
                                ! Dataset creation property
                                ! list identifier
  LOGICAL, INTENT(IN) :: flag   ! Object timestamp setting
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_obj_track_times_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_scaleoffset

**Signature:**

```
herr_t H5Pset_scaleoffset(hid_t plist_id, H5Z_SO_scale_type_t scale_type, int
scale_factor)
```

**Purpose:**

Sets up the use of the Scale-Offset filter.

**Description:**

H5Pset\_scaleoffset sets the Scale-Offset filter, H5Z\_FILTER\_SCALEOFFSET, for a dataset.

Generally speaking, Scale-Offset compression performs a scale and/or offset operation on each data value and truncates the resulting value to a minimum number of bits (MinBits) before storing it. The current Scale-Offset filter supports integer and floating-point datatype.

For integer datatype, the parameter `scale_type` should be set to `H5Z_SO_INT (2)`. The parameter `scale_factor` denotes MinBits. If the user sets it to `H5Z_SO_INT_MINBITS_DEFAULT (0)` or less than 0, the filter will calculate MinBits. If `scale_factor` is set to a positive integer, the filter does not do any calculation and just uses the number as MinBits. However, if the user gives a MinBits that is less than what would be generated by the filter, the compression will be lossy. Also, the MinBits supplied by the user cannot exceed the number of bits to store one value of the dataset datatype.

For floating-point datatype, the filter adopts the GRiB data packing mechanism, which offers two alternate methods: E-scaling and D-scaling. Both methods are lossy compression. If the parameter `scale_type` is set to `H5Z_SO_FLOAT_DSCALE (0)`, the filter will use the D-scaling method; if it is set to `H5Z_SO_FLOAT_ESCALE (1)`, the filter will use the E-scaling method. Since only the D-scaling method is implemented, `scale_type` should be set to `H5Z_SO_FLOAT_DSCALE` or 0.

When the D-scaling method is used, the original data is "D" scaled--multiplied by 10 to the power of `scale_factor`, and the "significant" part of the value is moved to the left of the decimal point. Care should be taken in setting the decimal `scale_factor` so that the integer part will have enough precision to contain the appropriate information of the data value. For example, if `scale_factor` is set to 2, the number 104.561 will be 10456.1 after "D" scaling. The last digit 1 is not "significant" and is thrown off in the process of rounding. The user should make sure that after "D" scaling and rounding, the data values are within the range that can be represented by the integer (same size as the floating-point type).

Valid values for `scale_type` are as follows:

H5Z_SO_FLOAT_DSCALE (0)	Floating-point type, using variable MinBits method
H5Z_SO_FLOAT_ESCALE (1)	Floating-point type, using fixed MinBits method
H5Z_SO_INT (2)	Integer type

The meaning of `scale_factor` varies according to the value assigned to `scale_type`:

<i>scale_type value</i>	<i>scale_factor description</i>
H5Z_SO_FLOAT_DSCALE	Denotes the decimal scale factor for D-scaling and can be positive, negative or zero. This is the current implementation of the library.

H5Z_SO_FLOAT_ESCALE	Denotes MinBits for E-scaling and must be a positive integer. This is not currently implemented by the library.
H5Z_SO_INT	Denotes MinBits and it should be a positive integer or H5Z_SO_INT_MINBITS_DEFAULT ( 0 ). If it is less than 0, the library will reset it to 0 since it is not implemented.

Like other I/O filters supported by the HDF5 library, application using the Scale-Offset filter must store data with chunked storage.

**Parameters:**

<i>hid_t</i> plist_id	IN: Dataset creation property list identifier.
<i>H5Z_SO_scale_type_t</i> scale_type	IN: Flag indicating compression method.
<i>int</i> scale_factor	IN: Parameter related to scale.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_scaleoffset\_f

```

SUBROUTINE h5pset_scaleoffset_f(plist_id, scale_type, scale_factor, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! Dataset creation property list id
  INTEGER, INTENT(IN) :: scale_type      ! Flag indicating compression method
  INTEGER, INTENT(IN) :: scale_factor    ! parameter related to scale.
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pset_scaleoffset_f

```

**Name:** H5Pset\_shared\_mesg\_index

**Signature:**

```
herr_t H5Pset_shared_mesg_index( hid_t fcpl_id, unsigned index_num, unsigned
mesg_type_flags, unsigned min_mesg_size )
```

**Purpose:**

Configures the specified shared object header message index.

**Description:**

H5Pset\_shared\_mesg\_index is used to configure the specified shared object header message index, setting the types of messages that may be stored in the index and the minimum size of each message.

fcpl\_id specifies the file creation property list.

index\_num specifies the index to be configured. index\_num is zero-indexed, so in a file with three indexes, they will be numbered 0, 1, and 2.

mesg\_type\_flags and min\_mesg\_size specify, respectively, the types and minimum size of messages that can be stored in this index.

Valid message types are as follows:

H5O_SHMESG_NONE_FLAG	No shared messages
H5O_SHMESG_SDSPACE_FLAG	Simple dataspace message
H5O_SHMESG_DTYPE_FLAG	Datatype message
H5O_SHMESG_FILL_FLAG	Fill value message
H5O_SHMESG_PLINE_FLAG	Filter pipeline message
H5O_SHMESG_ATTR_FLAG	Attribute message
H5O_SHMESG_ALL_FLAG	All message types; i.e., equivalent to the following: ( H5O_SHMESG_SDSPACE_FLAG   H5O_SHMESG_DTYPE_FLAG   H5O_SHMESG_FILL_FLAG   H5O_SHMESG_PLINE_FLAG   H5O_SHMESG_ATTR_FLAG )

**Parameters:**

<i>hid_t</i> fcpl_id	IN: File creation property list identifier.
<i>unsigned</i> index_num	IN: Index being configured.
<i>unsigned</i> mesg_type_flags	IN: Types of messages that should be stored in this index.
<i>unsigned</i> min_mesg_size	IN: Minimum message size.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_shared\_mesg\_nindexes

**Signature:**

*herr\_t* H5Pset\_shared\_mesg\_nindexes( *hid\_t* plist\_id, *unsigned* nindexes )

**Purpose:**

Sets number of shared object header message indexes.

**Description:**

H5Pset\_shared\_mesg\_nindexes sets the number of shared object header message indexes in the specified file creation property list.

This setting determines the number of shared object header message indexes that will be available in files created with this property list. These indexes can then be configured with H5Pset\_shared\_mesg\_index.

If nindexes is set to 0 (zero), shared object header messages are disabled in files created with this property list.

**Parameters:**

<i>hid_t</i> plist_id	IN: File creation property list
<i>unsigned</i> nindexes	IN: Number of shared object header message indexes to be available in files created with this property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Pset\_shared\_mesg\_phase\_change

**Signature:**

```
herr_t H5Pset_shared_mesg_phase_change( hid_t fcpl_id, unsigned max_list, unsigned
min_btree )
```

**Purpose:**

Sets shared object header message storage phase change thresholds.

**Description:**

H5Pset\_shared\_mesg\_phase\_change sets threshold values for storage of shared object header message indexes in a file. These phase change thresholds determine the point at which the index storage mechanism changes from a more compact list format to a more performance-oriented B-tree format, and vice-versa.

By default, a shared object header message index is initially stored as a compact list. When the number of messages in an index exceeds the threshold value of `max_list`, storage switches to a B-tree for improved performance. If the number of messages subsequently falls below the `min_btree` threshold, the index will revert to the list format.

If `max_compact` is set to 0 (zero), shared object header message indexes in the file will be created as B-trees and will never revert to lists.

`fcpl_id` specifies the file creation property list.

**Parameters:**

<i>hid_t</i> fcpl_id	IN: File creation property list identifier
<i>unsigned</i> max_list	IN: Threshold above which storage of a shared object header message index shifts from list to B-tree
<i>unsigned</i> min_btree	IN: Threshold below which storage of a shared object header message index reverts to list format

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

<b>Release</b>	<b>C</b>
1.8.0	Function introduced in this release.

**Name:** H5Pset\_shuffle

**Signature:**

*herr\_t* H5Pset\_shuffle(*hid\_t* plist\_id)

**Purpose:**

Sets up use of the shuffle filter.

**Description:**

H5Pset\_shuffle sets the shuffle filter, H5Z\_FILTER\_SHUFFLE, in the dataset creation property list *plist\_id*.

The shuffle filter de-interlaces a block of data by reordering the bytes. All the bytes from one consistent byte position of each data element are placed together in one block; all bytes from a second consistent byte position of each data element are placed together a second block; etc. For example, given three data elements of a 4-byte datatype stored as 012301230123, shuffling will re-order data as 000111222333. This can be a valuable step in an effective compression algorithm because the bytes in each byte position are often closely related to each other and putting them together can increase the compression ratio.

As implied above, the primary value of the shuffle filter lies in its coordinated use with a compression filter; it does not provide data compression when used alone. When the shuffle filter is applied to a dataset immediately prior to the use of a compression filter, the compression ratio achieved is often superior to that achieved by the use of a compression filter without the shuffle filter.

**Parameters:**

*hid\_t* plist\_id      IN: Dataset creation property list identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_shuffle\_f

```
SUBROUTINE h5pset_shuffle_f(prp_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id      ! Property list identifier
  INTEGER, INTENT(OUT)      :: hdferr      ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pset_shuffle_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Pset\_sieve\_buf\_size

**Signature:**

```
herr_t H5Pset_sieve_buf_size(hid_t fapl_id, hsize_t size)
```

**Purpose:**

Sets the maximum size of the data sieve buffer.

**Description:**

H5Pset\_sieve\_buf\_size sets *size*, the maximum size in bytes of the data sieve buffer, which is used by file drivers that are capable of using data sieving.

The data sieve buffer is used when performing I/O on datasets in the file. Using a buffer which is large enough to hold several pieces of the dataset being read in for hyperslab selections boosts performance by quite a bit.

The default value is set to 64KB, indicating that file I/O for raw data reads and writes will occur in at least 64KB blocks. Setting the value to 0 with this API function will turn off the data sieving, even if the VFL driver attempts to use that strategy.

**Parameters:**

<i>hid_t</i> fapl_id	IN: File access property list identifier.
<i>hsize_t</i> size	IN: Maximum size, in bytes, of data sieve buffer.

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_sieve\_buf\_size\_f

```
SUBROUTINE h5pset_sieve_buf_size_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! File access property list
                                          ! identifier
  INTEGER(SIZE_T), INTENT(IN) :: size    ! Sieve buffer size
  INTEGER, INTENT(OUT)       :: hdferr  ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5pset_sieve_buf_size_f
```

**History:**

Release	C
1.6.0	The <i>size</i> parameter has changed from type <i>hsize_t</i> to <i>size_t</i> .
1.4.0	Function introduced in this release.



**Name:** H5Pset\_sizes

**Signature:**

```
herr_t H5Pset_sizes(hid_t plist, size_t sizeof_addr, size_t sizeof_size)
```

**Purpose:**

Sets the byte size of the offsets and lengths used to address objects in an HDF5 file.

**Description:**

H5Pset\_sizes sets the byte size of the offsets and lengths used to address objects in an HDF5 file. This function is only valid for file creation property lists. Passing in a value of 0 for one of the sizeof\_... parameters retains the current value. The default value for both values is the same as sizeof(hsize\_t) in the library (normally 8 bytes). Valid values currently are 2, 4, 8 and 16.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier of property list to modify.
<i>size_t</i> sizeof_addr	IN: Size of an object offset in bytes.
<i>size_t</i> sizeof_size	IN: Size of an object length in bytes.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_sizes\_f

```
SUBROUTINE h5pset_sizes_f (prp_id, sizeof_addr, sizeof_size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id           ! Property list identifier
  INTEGER(SIZE_T), INTENT(IN) :: sizeof_addr      ! Size of an object offset
                                              ! in bytes
  INTEGER(SIZE_T), INTENT(IN) :: sizeof_size     ! Size of an object length
                                              ! in bytes
  INTEGER, INTENT(OUT) :: hdferr                 ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5pset_sizes_f
```

**Name:** H5Pset\_small\_data\_block\_size

**Signature:**

```
herr_t H5Pset_small_data_block_size(hid_t fapl_id, hsize_t size)
```

**Purpose:**

Sets the size of a contiguous block reserved for small data.

**Description:**

H5Pset\_small\_data\_block\_size reserves blocks of `size` bytes for the contiguous storage of the raw data portion of *small* datasets. The HDF5 library then writes the raw data from small datasets to this reserved space, thus reducing unnecessary discontinuities within blocks of meta data and improving I/O performance.

A small data block is actually allocated the first time a qualifying small dataset is written to the file. Space for the raw data portion of this small dataset is suballocated within the small data block. The raw data from each subsequent small dataset is also written to the small data block until it is filled; additional small data blocks are allocated as required.

The HDF5 library employs an algorithm that determines whether I/O performance is likely to benefit from the use of this mechanism with each dataset as storage space is allocated in the file. A larger `size` will result in this mechanism being employed with larger datasets.

The small data block size is set as an allocation property in the file access property list identified by `fapl_id`.

Setting `size` to zero (0) disables the small data block mechanism.

**Parameters:**

<code>hid_t fapl_id</code>	IN: File access property list identifier.
<code>hsize_t size</code>	IN: Maximum size, in bytes, of the small data block. The default size is 2048.

**Returns:**

Returns a non-negative value if successful; otherwise a negative value.

**Fortran90 Interface:** h5pset\_small\_data\_block\_size\_f

```
SUBROUTINE h5pset_small_data_block_size_f(plist_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: plist_id ! File access
                                         ! property list identifier
  INTEGER(HSIZE_T), INTENT(IN) :: size   ! Small raw data block size
  INTEGER, INTENT(OUT)          :: hdferr ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pset_small_data_block_size_f
```

**History:**

Release	C
1.4.4	Function introduced in this release.

**Name:** H5Pset\_sym\_k

**Signature:**

*herr\_t* H5Pset\_sym\_k(*hid\_t* plist, *unsigned ik*, *unsigned lk*)

**Purpose:**

Sets the size of parameters used to control the symbol table nodes.

**Description:**

H5Pset\_sym\_k sets the size of parameters used to control the symbol table nodes. This function is only valid for file creation property lists. Passing in a value of 0 for one of the parameters retains the current value.

*ik* is one half the rank of a tree that stores a symbol table for a group. Internal nodes of the symbol table are on average 75% full. That is, the average rank of the tree is 1.5 times the value of *ik*.

*lk* is one half of the number of symbols that can be stored in a symbol table node. A symbol table node is the leaf of a symbol table tree which is used to store a group. When symbols are inserted randomly into a group, the group's symbol table nodes are 75% full on average. That is, they contain 1.5 times the number of symbols specified by *lk*.

**Parameters:**

*hid\_t* plist           IN: File creation property list identifier.

*unsigned ik*           IN: Symbol table tree rank.

*unsigned lk*           IN: Symbol table node size.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_sym\_k\_f

```
SUBROUTINE h5pset_sym_k_f (prp_id, ik, lk, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id ! Property list identifier
  INTEGER, INTENT(IN) :: ik           ! Symbol table tree rank
  INTEGER, INTENT(IN) :: lk           ! Symbol table node size
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                      ! 0 on success and -1 on failure
END SUBROUTINE h5pset_sym_k_f
```

**History:**

**Release   C**

1.6.4       *ik* parameter type changed to *unsigned*.

1.6.0       The *ik* parameter has changed from type *int* to *unsigned*.

**Name:** H5Pset\_szip

**Signature:**

```
herr_t H5Pset_szip(hid_t plist, unsigned int options_mask, unsigned int
pixels_per_block)
```

**Purpose:**

Sets up use of the SZIP compression filter.

**Description:**

H5Pset\_szip sets an SZIP compression filter, H5Z\_FILTER\_SZIP, for a dataset. SZIP is a compression method designed for use with scientific data.

Before proceeding, be aware that there are factors that affect your rights and ability to use SZIP compression. See the documents at [SZIP Compression in HDF5](#) for *important information regarding terms of use and the SZIP copyright notice*, for further discussion of SZIP compression in HDF5, and for a list of SZIP-related references.

In the text below, the term *pixel* refers to an HDF5 data element. This terminology derives from SZIP compression's use with image data, where pixel referred to an image pixel.

The SZIP `bits_per_pixel` value (see **Notes**, below) is automatically set, based on the HDF5 datatype. SZIP can be used with atomic datatypes that may have size of 8, 16, 32, or 64 bits. Specifically, a dataset with a datatype that is 8-, 16-, 32-, or 64-bit signed or unsigned integer; char; or 32- or 64-bit float can be compressed with SZIP. See **Notes**, below, for further discussion of the the SZIP `bits_per_pixel` setting.

SZIP compression cannot be applied to compound datatypes, array datatypes, variable-length datatypes, enumerations, or any other user-defined datatypes. If an SZIP filter is set in a dataset creation property list used to create a dataset containing a non-allowed datatype, the call to `H5Dcreate` will fail; the conflict can be detected only when the property list is used.

SZIP options are passed in an options mask, `options_mask`, as follows.

Option	Description
	(Mutually exclusive; select one.)
H5_SZIP_EC_OPTION_MASK	Selects entropy coding method.
H5_SZIP_NN_OPTION_MASK	Selects nearest neighbor coding method.

The following guidelines can be used in determining which option to select:

- ◊ The entropy coding method, the EC option specified by `H5_SZIP_EC_OPTION_MASK`, is best suited for data that has been processed. The EC method works best for small numbers.
- ◊ The nearest neighbor coding method, the NN option specified by `H5_SZIP_NN_OPTION_MASK`, preprocesses the data then the applies EC method as above.

Other factors may affect results, but the above criteria provides a good starting point for optimizing data compression.

SZIP compresses data block by block, with a user-tunable block size. This block size is passed in the parameter `pixels_per_block` and must be even and not greater than 32, with typical values being 8, 10, 16, or 32. This parameter affects compression ratio; the more pixel values vary, the smaller this number should be to achieve better performance.

In HDF5, compression can be applied only to chunked datasets. If `pixels_per_block` is bigger than the total number of elements in a dataset chunk, `H5Pset_szip` will succeed but the subsequent call to `H5Dcreate` will fail; the conflict can be detected only when the property list is used.

To achieve optimal performance for SZIP compression, it is recommended that a chunk's fastest-changing dimension be equal to  $N$  times `pixels_per_block` where  $N$  is the maximum number of blocks per scan line allowed by the SZIP library. In the current version of SZIP,  $N$  is set to 128.

SZIP compression is an optional HDF5 filter. See the note below for information regarding its designed behavior, particularly under circumstances where SZIP is not available to an application.

#### Parameters:

<i>hid_t</i> plist	IN: Dataset creation property list identifier.
<i>unsigned int</i> options_mask	IN: A bit-mask conveying the desired SZIP options. Valid values are <code>H5_SZIP_EC_OPTION_MASK</code> and <code>H5_SZIP_NN_OPTION_MASK</code> .
<i>unsigned int</i> pixels_per_block	IN: The number of pixels or data elements in each data block.

#### Returns:

Returns a non-negative value if successful; otherwise returns a negative value.

#### Notes for Users Familiar with SZIP in Other Contexts:

The following notes are of interest primarily to those who have used SZIP compression outside of the HDF5 context.

In non-HDF5 applications, SZIP typically requires that the user application supply additional parameters:

- ◊ `pixels_in_object`, the number of pixels in the object to be compressed
- ◊ `bits_per_pixel`, the number of bits per pixel
- ◊ `pixels_per_scanline`, the number of pixels per scan line

These values need not be independently supplied in the HDF5 environment as they are derived from the datatype and dataspace, which are already known. In particular, HDF5 sets `pixels_in_object` to the number of elements in a chunk and `bits_per_pixel` to the size of the element or pixel datatype. The following algorithm is used to set `pixels_per_scanline`:

- ◊ If the size of a chunk's fastest-changing dimension, *size*, is greater than 4K, set `pixels_per_scanline` to 128 times `pixels_per_block`.
- ◊ If *size* is less than 4K but greater than `pixels_per_block`, set `pixels_per_scanline` to the minimum of *size* and 128 times `pixels_per_block`.
- ◊ If *size* is less than `pixels_per_block` but greater than the number elements in the chunk, set `pixels_per_scanline` to the minimum of the number elements in the chunk and 128 times `pixels_per_block`.

The HDF5 datatype may have precision that is less than the full size of the data element, e.g., an 11-bit integer can be defined using `H5Tset_precision`. To a certain extent, SZIP can take advantage of the precision of the datatype to improve compression:

- ◊ If the HDF5 datatype size is 24-bit or less and the offset of the bits in the HDF5 datatype is zero (see `H5Tset_offset` or `H5Tget_offset`), the data is the in lowest N bits of the data element. In this case, the SZIP `bits_per_pixel` is set to the precision of the HDF5 datatype.
- ◊ If the offset is not zero, the SZIP `bits_per_pixel` will be set to the number of bits in the full size of the data element.
- ◊ If the HDF5 datatype precision is 25-bit to 32-bit, the SZIP `bits_per_pixel` will be set to 32.
- ◊ If the HDF5 datatype precision is 33-bit to 64-bit, the SZIP `bits_per_pixel` will be set to 64.

HDF5 always modifies the options mask provided by the user to set up usage of `RAW_OPTION_MASK`, `ALLOW_K13_OPTION_MASK`, and one of `LSB_OPTION_MASK` or `MSB_OPTION_MASK`, depending on endianness of the datatype.

#### Fortran90 Interface: `h5pset_szip_f`

```
SUBROUTINE h5pset_szip_f(prp_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id
                                ! Dataset creation property list identifier
  INTEGER, INTENT(IN) :: options_mask
                                ! A bit-mask conveying the desired
                                ! SZIP options
                                ! Current valid values in Fortran are:
                                !   H5_SZIP_EC_OM_F
                                !   H5_SZIP_NN_OM_F
  INTEGER, INTENT(IN) :: pixels_per_block
                                ! The number of pixels or data elements
                                ! in each data block
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5pset_szip_f
```

#### History:

Release	C
1.6.0	Function introduced in this release.

*Last modified: 2 April 2009***Name:** H5Pset\_type\_conv\_cb**Signature:**

```
herr_t H5Pset_type_conv_cb(hid_t plist, H5T_conv_except_t func, void *op_data)
```

**Purpose:**

Sets user-defined datatype conversion callback function.

**Description:**

H5Pset\_type\_conv\_cb sets the user-defined datatype conversion callback function `func` in the dataset transfer property list `plist`.

The parameter `op_data` is a pointer to user-defined input data for the callback function and will be passed through to the callback function.

The callback function `func` defines the actions an application is to take when there is an exception during datatype conversion. The function prototype is as follows:

```
typedef H5T_conv_ret_t (H5T_conv_except_func_t) (H5T_conv_except_t
except_type, hid_t *src_id, hid_t *dst_id, void *src_buf, void *dst_buf, void
*op_data)
```

where `except_type` indicates what kind of exception has happened, `src_id` and `dst_id` are the source and destination datatype identifiers, `src_buf` and `dst_buf` are the source and destination data buffer, and `op_data` is the required input data for this callback function.

Valid values for `except_type` are as follows:

H5T\_CONV\_EXCEPT\_RANGE\_HI

Source value is positive and is too big to the destination. Overflow happens.

H5T\_CONV\_EXCEPT\_RANGE\_LOW

Source value is negative and its magnitude is too big to the destination. Overflow happens.

H5T\_CONV\_EXCEPT\_TRUNCATE

Source is floating-point type and destination is integer. The floating-point number has fractional part.

H5T\_CONV\_EXCEPT\_PRECISION

Source is integer and destination is floating-point type. The mantissa of floating-point type is not big enough to hold all the digits of the integer.

H5T\_CONV\_EXCEPT\_PINF

Source is floating-point type and the value is positive infinity.

H5T\_CONV\_EXCEPT\_NINF

Source is floating-point type and the value is negative infinity.

H5T\_CONV\_EXCEPT\_NAN

Source is floating-point type and the value is NaN (not a number, including QNaN and SNaN).

Valid callback function return values are H5T\_CONV\_ABORT, H5T\_CONV\_UNHANDLED and H5T\_CONV\_HANDLED.

**Parameters:**

<i>hid_t</i> plist	IN: Dataset transfer property list identifier.
<i>H5T_conv_except_func_t</i> func	IN: User-defined type conversion callback function.< /td>
<i>void</i> *op_data	IN: User-defined input data for the callback function.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.



**Name:** H5Pset\_userblock

**Signature:**

*herr\_t* H5Pset\_userblock(*hid\_t* plist, *hsize\_t* size)

**Purpose:**

Sets user block size.

**Description:**

H5Pset\_userblock sets the user block size of a file creation property list. The default user block size is 0; it may be set to any power of 2 equal to 512 or greater (512, 1024, 2048, etc.).

**Parameters:**

*hid\_t* plist           IN: Identifier of property list to modify.

*hsize\_t* size        IN: Size of the user-block in bytes.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5pset\_userblock\_f

```
SUBROUTINE h5pset_userblock_f (prp_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: prp_id   ! Property list identifier
  INTEGER(HSIZE_T), INTENT(IN) :: size   ! Size of the user-block in bytes
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5pset_userblock_f
```

**Name:** H5Pset\_vlen\_mem\_manager

**Signature:**

```
herr_t H5Pset_vlen_mem_manager(hid_t plist, H5MM_allocate_t alloc, void
*alloc_info, H5MM_free_t free, void *free_info)
```

**Purpose:**

Sets the memory manager for variable-length datatype allocation in H5Dread and H5Dvlen\_reclaim.

**Description:**

H5Pset\_vlen\_mem\_manager sets the memory manager for variable-length datatype allocation in H5Dread and free in H5Dvlen\_reclaim.

The `alloc` and `free` parameters identify the memory management routines to be used. If the user has defined custom memory management routines, `alloc` and/or `free` should be set to make those routine calls (i.e., the name of the routine is used as the value of the parameter); if the user prefers to use the system's `malloc` and/or `free`, the `alloc` and `free` parameters, respectively, should be set to `NULL`.

The prototypes for these user-defined functions would appear as follows:

```
typedef void (*H5MM_allocate_t)(size_t size, void *alloc_info);
typedef void (*H5MM_free_t)(void *mem, void *free_info);
```

The `alloc_info` and `free_info` parameters can be used to pass along any required information to the user's memory management routines.

In summary, if the user has defined custom memory management routines, the name(s) of the routines are passed in the `alloc` and `free` parameters and the custom routines' parameters are passed in the `alloc_info` and `free_info` parameters. If the user wishes to use the system `malloc` and `free` functions, the `alloc` and/or `free` parameters are set to `NULL` and the `alloc_info` and `free_info` parameters are ignored.

**Parameters:**

<i>hid_t</i> plist	IN: Identifier for the dataset transfer property list.
<i>H5MM_allocate_t</i> alloc	IN: User's allocate routine, or <code>NULL</code> for system <code>malloc</code> .
<i>void</i> *alloc_info	IN: Extra parameter for user's allocation routine. Contents are ignored if preceding parameter is <code>NULL</code> .
<i>H5MM_free_t</i> free	IN: User's free routine, or <code>NULL</code> for system <code>free</code> .
<i>void</i> *free_info	IN: Extra parameter for user's free routine. Contents are ignored if preceding parameter is <code>NULL</code> .

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**Name:** H5Punregister

**Signature:**

*herr\_t* H5Punregister( *H5P\_class\_t* class, *const char* \*name )

**Purpose:**

Removes a property from a property list class.

**Description:**

H5Punregister removes a property from a property list class.

Future property lists created of that class will not contain this property; existing property lists containing this property are not affected.

**Parameters:**

<i>H5P_class_t</i> class	IN: Property list class from which to remove permanent property
<i>const char</i> *name	IN: Name of property to remove

**Returns:**

Success: a non-negative value

Failure: a negative value

**Fortran90 Interface:** h5punregister\_f

```

SUBROUTINE h5punregister_f(class, name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: class ! Property list class identifier
  CHARACTER(LEN=*), INTENT(IN) :: name ! Name of property to remove
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5punregister_f

```



## H5R: Reference Interface

### Reference API Functions

The Reference interface allows the user to create references to specific objects and data regions in an HDF5 file. In the following lists, italic type indicates a configurable macro.

#### The C Interfaces:

- H5Rcreate
- H5Rdereference
- *H5Rget\_obj\_type*
- H5Rget\_obj\_type1 \*
- H5Rget\_obj\_type2
- H5Rget\_region
- H5Rget\_name

\* *Use of this function is deprecated in Release 1.8.0.*

#### Alphabetical Listing

- H5Rcreate
- H5Rdereference
- H5Rget\_name
- *H5Rget\_obj\_type*
- H5Rget\_obj\_type1 \*
- H5Rget\_obj\_type2
- H5Rget\_region

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- h5rcreate\_f
- h5rdereference\_f
- h5rget\_region\_f
- h5rget\_object\_type\_f
- h5rget\_name\_f



**Name:** H5Rcreate

**Signature:**

```
herr_t H5Rcreate(void *ref, hid_t loc_id, const char *name, H5R_type_t ref_type, hid_t
space_id)
```

**Purpose:**

Creates a reference.

**Description:**

H5Rcreate creates the reference, *ref*, of the type specified in *ref\_type*, pointing to the object name located at *loc\_id*.

The HDF5 library maps the *void* type specified above for *ref* to the type specified in *ref\_type*, which will be one of those appearing in the first column of the following table. The second column of the table lists the HDF5 constant associated with each reference type.

<i>hdset_reg_ref_t</i>	H5R_DATASET_REGION	Dataset region reference
<i>hobj_ref_t</i>	H5R_OBJECT	Object reference

The parameters *loc\_id* and *name* are used to locate the object.

The parameter *space\_id* identifies the dataset region that a dataset region reference points to. This parameter is used only with dataset region references and should be set to -1 if the reference is an object reference, H5R\_OBJECT.

**Parameters:**

<i>void</i> *ref	OUT: Reference created by the function call.
<i>hid_t</i> loc_id	IN: Location identifier used to locate the object being pointed to.
<i>const char</i> *name	IN: Name of object at location <i>loc_id</i> .
<i>H5R_type_t</i> ref_type	IN: Type of reference.
<i>hid_t</i> space_id	IN: Dataspace identifier with selection. Used only for dataset region references; pass as -1 if reference is an object reference, i.e., of type H5R_OBJECT.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5rcreate\_f

**To create an object reference**

```
SUBROUTINE h5rcreate_f(loc_id, name, ref, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id      ! Location identifier
  CHARACTER(LEN=*), INTENT(IN) :: name     ! Name of the object at location
                                           ! specified by loc_id identifier
  TYPE(hobj_ref_t_f), INTENT(OUT) :: ref   ! Object reference
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure

END SUBROUTINE h5rcreate_f
```

**To create a region reference**

```
SUBROUTINE h5rcreate_f(loc_id, name, space_id, ref, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id          ! Location identifier
  CHARACTER(LEN=*), INTENT(IN) :: name          ! Name of the dataset at location
                                                ! specified by loc_id identifier
  INTEGER(HID_T), INTENT(IN) :: space_id        ! Dataset's dataspace identifier
  TYPE(hdset_reg_ref_t_f), INTENT(OUT) :: ref   ! Dataset region reference
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
                                                ! 0 on success and -1 on failure

END SUBROUTINE h5rcreate_f
```



**Name:** H5Rdreference

**Signature:**

```
hid_t H5Rdreference(hid_t obj_id, H5R_type_t ref_type, void *ref )
```

**Purpose:**

Opens the HDF5 object referenced.

**Description:**

Given a reference, *ref*, to an object or a region in an object, H5Rdreference opens that object and returns an identifier.

The parameter *obj\_id* must be a valid identifier for an object in the HDF5 file containing the referenced object, including the file identifier.

The parameter *ref\_type* specifies the reference type of the reference *ref*. *ref\_type* may contain either of the following values:

```
◇ H5R_OBJECT (0)
◇ H5R_DATASET_REGION (1)
```

**Parameters:**

<i>hid_t</i> obj_id	IN: Valid identifier for the file containing the referenced object or any object in that file.
<i>H5R_type_t</i> ref_type	IN: The reference type of <i>ref</i> .
<i>void</i> *ref	IN: Reference to open.

**Returns:**

Returns identifier of referenced object if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5rdreference\_f

**To dereference an object**

```
SUBROUTINE h5rdreference_f(obj_id, ref, ref_obj_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id      ! Valid identifier
                                           ! in file
  TYPE(hobj_ref_t_f), INTENT(IN) :: ref     ! Object reference
  INTEGER(HID_T), INTENT(OUT) :: ref_obj_id ! Identifier of
                                           ! referenced object
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure

END SUBROUTINE h5rdreference_f
```

**To dereference a region**

```
SUBROUTINE h5rdreference_f(obj_id, ref, ref_obj_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id      ! Valid identifier
                                           ! in file
  TYPE(hdset_reg_ref_t_f), INTENT(IN) :: ref ! Object reference
  INTEGER(HID_T), INTENT(OUT) :: ref_obj_id ! Identifier of
                                           ! referenced object
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure

END SUBROUTINE h5rdreference_f
```

**Name:** H5Rget\_obj\_type

**Signature:**

```
H5G_obj_t H5Rget_obj_type( hid_t loc_id, H5R_type_t ref_type, void *ref )
herr_t H5Rget_obj_type( hid_t loc_id, H5R_type_t ref_type, void *ref, H5O_type_t
*obj_type )
```

**Purpose:**

Retrieves the type of object that an object reference points to.

**Description:**

H5Rget\_obj\_type is a macro that is mapped to either H5Rget\_obj\_type1 or H5Rget\_obj\_type2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Rget\_obj\_type is mapped to the most recent version of the function, currently H5Rget\_obj\_type2. If the library and/or application is compiled for Release 1.6 emulation, H5Rget\_obj\_type will be mapped to H5Rget\_obj\_type1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Rget_obj_type mapping
-----------------------	----------------------------

---

Global settings

No compatibility flag	H5Rget_obj_type2
Enable deprecated symbols	H5Rget_obj_type2
Disable deprecated symbols	H5Rget_obj_type2
Emulate Release 1.6 interface	H5Rget_obj_type1

---

Function-level macros

H5Rget_obj_type_vers = 2	H5Rget_obj_type2
H5Rget_obj_type_vers = 1	H5Rget_obj_type1

**Fortran90 Interface:** h5rget\_object\_type\_f

```
SUBROUTINE h5rget_object_type_f(dset_id, ref, obj_type, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dset_id      ! Dataset identifier
  TYPE(hobj_ref_t_f), INTENT(IN) :: ref      ! Object reference
  INTEGER, INTENT(OUT) :: obj_type           ! Object type
  !      H5G_UNKNOWN_F (-1)
  !      H5G_LINK_F      0
  !      H5G_GROUP_F     1
  !      H5G_DATASET_F   2
  !      H5G_TYPE_F      3
```

```
INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                         ! 0 on success and -1 on failure

END SUBROUTINE h5rget_object_type_f
```

**History:**

Release	C
1.8.0	The function H5Rget_obj_type renamed to H5Rget_obj_type1 and deprecated in this release. The macro H5Rget_obj_type and the function H5Rget_obj_type2 introduced in this release.

**Name:** H5Rget\_obj\_type1

**Signature:**

```
H5G_obj_t H5Rget_obj_type1( hid_t loc_id, H5R_type_t ref_type, void *ref )
```

**Purpose:**

Retrieves the type of object that an object reference points to.

**Notice:**

*This function has been renamed from H5Rget\_obj\_type and is deprecated in favor of the macro H5Rget\_obj\_type or the function H5Rget\_obj\_type2.*

**Description:**

Given an object reference, `ref`, `H5Rget_obj_type1` returns the type of the referenced object.

A *reference type* is the type of reference, either an object reference or a dataset region reference. An *object reference* points to an HDF5 object while a *dataset region reference* points to a defined region within a dataset.

The *referenced object* is the object the reference points to. The *referenced object type*, or the type of the referenced object, is the type of the object that the reference points to.

The location identifier, `loc_id`, is the identifier for either the dataset containing the object reference or the group containing that dataset.

Valid reference types, to pass in as `ref_type`, include the following:

H5R_OBJECT	Object reference
H5R_DATASET_REGION	Dataset region reference

If the application does not already know the object reference type, that can be determined with three preliminary calls:

- ◊ Call `H5Dget_type` on the dataset containing the reference to get a datatype identifier for the dataset's datatype.
- ◊ Using that datatype identifier, `H5Tget_class` returns a datatype class.
- ◊ If the datatype class is `H5T_REFERENCE`, `H5Tequal` can then be used to determine whether the reference's datatype is `H5T_STD_REF_OBJ` or `H5T_STD_REF_DSETREG`:
  - If the datatype is `H5T_STD_REF_OBJ`, the reference object type is `H5R_OBJECT`.
  - If the datatype is `H5T_STD_REF_DSETREG`, the reference object type is `H5R_DATASET_REGION`.

When the function completes successfully, it returns one of the following valid object type values (defined in `H5Gpublic.h`):

H5G_LINK	Object is a symbolic link.
H5G_GROUP	Object is a group.
H5G_DATASET	Object is a dataset.
H5G_TYPE	Object is a named datatype.

**Parameters:**

<i>hid_t</i> loc_id	IN: The dataset containing the reference object or the group containing that dataset.
<i>H5R_type_t</i> ref_type	IN: Type of reference to query.
<i>void</i> *ref	IN: Reference to query.

**Returns:**

Returns a valid object type if successful; otherwise returns H5G\_UNKNOWN.

**Fortran90 Interface:** h5rget\_object\_type\_f

See the H5Rget\_obj\_type macro description.

**History:**

Release	C
1.6.0	Function introduced in this release.
1.8.0	Function H5Rget_obj_type renamed to H5Rget_obj_type1 and deprecated in this release.

**Name:** H5Rget\_obj\_type2

**Signature:**

```
herr_t H5Rget_obj_type2( hid_t loc_id, H5R_type_t ref_type, void *ref, H5O_type_t
*obj_type )
```

**Purpose:**

Retrieves the type of object that an object reference points to.

**Description:**

Given an object reference, `ref`, `H5Rget_obj_type2` retrieves the type of the referenced object in `obj_type`.

A *reference type* is the type of reference, either an object reference or a dataset region reference. An *object reference* points to an HDF5 object while a *dataset region reference* points to a defined region within a dataset.

The *referenced object* is the object the reference points to. The *referenced object type*, or the type of the referenced object, is the type of the object that the reference points to.

The location identifier, `loc_id`, is the identifier for either the dataset containing the object reference or the group containing that dataset.

Valid reference types, to pass in as `ref_type`, include the following:

H5R_OBJECT	Object reference
H5R_DATASET_REGION	Dataset region reference

If the application does not already know the object reference type, that can be determined with three preliminary calls:

- ◊ Call `H5Dget_type` on the dataset containing the reference to get a datatype identifier for the dataset's datatype.
- ◊ Using that datatype identifier, `H5Tget_class` returns a datatype class.
- ◊ If the datatype class is `H5T_REFERENCE`, `H5Tequal` can then be used to determine whether the reference's datatype is `H5T_STD_REF_OBJ` or `H5T_STD_REF_DSETREG`:
  - If the datatype is `H5T_STD_REF_OBJ`, the reference object type is `H5R_OBJECT`.
  - If the datatype is `H5T_STD_REF_DSETREG`, the reference object type is `H5R_DATASET_REGION`.

When the function completes successfully, it returns one of the following valid object type values (defined in `H5Opublic.h`):

H5O_TYPE_GROUP	Object is a group.
H5O_TYPE_DATASET	Object is a dataset.
H5O_TYPE_NAMED_DATATYPE	Object is a named datatype.

**Parameters:**

<code>hid_t loc_id</code>	IN: The dataset containing the reference object or the group containing that dataset.
<code>H5R_type_t ref_type</code>	IN: Type of reference to query.
<code>void *ref</code>	IN: Reference to query.
<code>H5O_type_t *obj_type</code>	OUT: Type of referenced object.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5rget\_object\_type\_f

See the H5Rget\_obj\_type macro description.

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------



**Name:** H5Rget\_name**Signature:**

```
ssize_t H5Rget_name( hid_t loc_id, H5R_type_t ref_type, void *ref, char *name, size_t size )
```

**Purpose:**

Retrieves a name of a referenced object.

**Description:**

H5Rget\_name retrieves a name for the object identified by `ref`.

`loc_id` is the identifier for the dataset containing the reference or for the group containing that dataset.

`H5R_type_t` is the reference type of `ref`. Valid values include the following:

<code>H5R_OBJECT</code>	Object reference
<code>H5R_DATASET_REGION</code>	Dataset region reference

`ref` is the reference for which the target object's name is sought.

If `ref` is an object reference, `name` will be returned with the name of the referenced object. If `ref` is a dataset region reference, `name` will contain the name of the object containing the referenced region.

Up to `size` characters of the name are returned in `name`; additional characters, if any, are not returned to the user application.

If the length of the name, which determines the required value of `size`, is unknown, a preliminary H5Rget\_name call can be made. The return value of this call will be the size of the object name. That value can then be assigned to `size` for a second H5Rget\_name call, which will retrieve the actual name.

If there is no name associated with the object identifier or if the name is NULL, H5Rget\_name returns 0 (zero).

Note that an object in an HDF5 file may have multiple paths if there are multiple links pointing to it. This function may return any one of these paths.

**Parameters:**

<code>hid_t loc_id</code>	IN: Identifier for the dataset containing the reference or for the group that dataset is in.
<code>H5R_type_t ref_type</code>	IN: Type of reference.
<code>void *ref</code>	IN: An object or dataset region reference.
<code>char *name</code>	OUT: A name associated with the referenced object or dataset region.
<code>size_t size</code>	IN: The size of the name buffer.

**Returns:**

Returns the length of the name if successful, returning 0 (zero) if no name is associated with the identifier. Otherwise returns a negative value.

**Fortran90 Interface:** h5rget\_name\_object\_f**To get name of an object reference**

```

SUBROUTINE h5rget_name_object_f(loc_id, ref, name, hdferr, size)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id
                                ! Identifier for the dataset containing the reference
                                ! or for the group that dataset is in.
  TYPE(hobj_ref_t_f), INTENT(IN) :: ref
                                ! Object reference
  INTEGER(SIZE_T), OPTIONAL, INTENT(OUT) :: size
                                ! The size of the name buffer,
                                ! returning 0 (zero) if no name is associated with the
                                ! identifier
  CHARACTER(LEN=*), INTENT(OUT) :: name
                                ! A name associated with the referenced object or
                                ! dataset region.
  INTEGER, INTENT(OUT) :: hdferr
                                ! Error code
                                ! 0 on success and -1 on failure
  INTEGER(HADDR_T) :: ref_f
                                ! Local buffer to pass reference
END SUBROUTINE h5rget_name_object_f

```

**To get name of a region reference**

```

SUBROUTINE h5rget_name_region_f(loc_id, ref, name, hdferr, size)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id ! Identifier for the dataset containing
                                         ! the reference
                                         ! or for the group that dataset is in.
  TYPE(hdset_reg_ref_t_f), INTENT(IN) :: ref
                                         ! Object reference
  INTEGER(SIZE_T), OPTIONAL, INTENT(OUT) :: size
                                         ! The size of the name buffer,
                                         ! returning 0 (zero) if no name is
                                         ! associated with the identifier.
  CHARACTER(LEN=*), INTENT(OUT) :: name ! A name associated with the
                                         ! referenced object or dataset region.
  INTEGER, INTENT(OUT) :: hdferr
                                         ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5rget_name_region_f

```

**History:**

Release	C
1.8.0	Function introduced in this release.

Last modified: 30 April 2009

**Name:** H5Rget\_region**Signature:**

```
hid_t H5Rget_region( hid_t loc_id, H5R_type_t ref_type, void *ref )
```

**Purpose:**

Sets up a dataspace and selection as specified by a region reference.

**Description:**

H5Rget\_region creates a copy of the dataspace of the dataset pointed to by a region reference, *ref*, and defines a selection matching the selection pointed to by *ref* within the dataspace copy.

*loc\_id* is used to identify the file containing the referenced region; it can be a file identifier or an identifier for any object in the file.

The parameter *ref\_type* specifies the reference type of *ref* and must contain the following value:

```
◇ H5R_DATASET_REGION (1)
```

**Parameters:**

<i>hid_t loc_id</i>	IN: File identifier or identifier for any object in the file containing the referenced region
<i>H5R_type_t ref_type</i>	IN: Reference type of <i>ref</i> , which must be H5R_DATASET_REGION
<i>void *ref</i>	IN: Region reference to open

**Returns:**

Returns a valid dataspace identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5rget\_region\_f

```
SUBROUTINE h5rget_region_f(obj_id, ref, space_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id      ! Object identifier
  TYPE(hdset_reg_ref_t_f), INTENT(IN) :: ref ! Dataset region reference
  INTEGER(HID_T), INTENT(OUT) :: space_id   ! Space identifier
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure

END SUBROUTINE h5rget_region_f
```



## H5S: Dataspace Interface

### Dataspace Object API Functions

These functions create and manipulate the dataspace in which to store the elements of a dataset.

#### The C Interfaces:

- |                              |                                 |                                |
|------------------------------|---------------------------------|--------------------------------|
| • H5Screate                  | • H5Sget_simple_extent_npoints  | • H5Sget_select_elem_npoints   |
| • H5Scopy                    | • H5Sget_simple_extent_type     | • H5Sget_select_elem_pointlist |
| • H5Sclose                   | • H5Sextent_copy                | • H5Sget_select_bounds         |
| • H5Sdecode                  | • H5Sextent_equal               | • H5Sselect_elements           |
| • H5Sencode                  | • H5Sset_extent_simple          | • H5Sselect_all                |
| • H5Screate_simple           | • H5Sset_extent_none            | • H5Sselect_none               |
| • H5Sis_simple               | • H5Sget_select_type            | • H5Sselect_valid              |
| • H5Soffset_simple           | • H5Sget_select_npoints         | • H5Sselect_hyperslab          |
| • H5Sget_simple_extent_dims  | • H5Sget_select_hyper_nblocks   |                                |
| • H5Sget_simple_extent_ndims | • H5Sget_select_hyper_blocklist |                                |

#### *Alphabetical Listing*

- |                              |                                 |                        |
|------------------------------|---------------------------------|------------------------|
| • H5Sclose                   | • H5Sget_select_elem_pointlist  | • H5Soffset_simple     |
| • H5Scopy                    | • H5Sget_select_hyper_blocklist | • H5Sselect_all        |
| • H5Screate                  | • H5Sget_select_hyper_nblocks   | • H5Sselect_elements   |
| • H5Screate_simple           | • H5Sget_select_npoints         | • H5Sselect_hyperslab  |
| • H5Sdecode                  | • H5Sget_select_type            | • H5Sselect_none       |
| • H5Sencode                  | • H5Sget_simple_extent_dims     | • H5Sselect_valid      |
| • H5Sextent_copy             | • H5Sget_simple_extent_ndims    | • H5Sset_extent_none   |
| • H5Sextent_equal            | • H5Sget_simple_extent_npoints  | • H5Sset_extent_simple |
| • H5Sget_select_bounds       | • H5Sget_simple_extent_type     |                        |
| • H5Sget_select_elem_npoints | • H5Sis_simple                  |                        |

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- |                                |                                   |                                  |
|--------------------------------|-----------------------------------|----------------------------------|
| • h5screate_f                  | • h5sget_simple_extent_npoints_f  | • h5sget_select_elem_npoints_f   |
| • h5scopy_f                    | • h5sget_simple_extent_type_f     | • h5sget_select_elem_pointlist_f |
| • h5sclose_f                   | • h5sextent_copy_f                | • h5sselect_elements_f           |
| • H5Sdecode_f                  | • H5Sextent_equal_f               | • h5sselect_all_f                |
| • H5Sencode_f                  | • h5sset_extent_simple_f          | • h5sselect_none_f               |
| • h5screate_simple_f           | • h5sset_extent_none_f            | • h5sselect_valid_f              |
| • h5sis_simple_f               | • h5sget_select_type_f            | • h5sselect_hyperslab_f          |
| • h5soffset_simple_f           | • h5sget_select_npoints_f         |                                  |
| • h5sget_simple_extent_dims_f  | • h5sget_select_hyper_nblocks_f   |                                  |
| • h5sget_simple_extent_ndims_f | • h5sget_select_hyper_blocklist_f |                                  |



**Name:** H5Sclose**Signature:***herr\_t* H5Sclose(*hid\_t* space\_id)**Purpose:**

Releases and terminates access to a dataspace.

**Description:**

H5Sclose releases a dataspace. Further access through the dataspace identifier is illegal. Failure to release a dataspace with this call will result in resource leaks.

**Parameters:***hid\_t* space\_id      Identifier of dataspace to release.**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sclose\_f

```

SUBROUTINE h5sclose_f(space_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5sclose_f

```

**Name:** H5Scopy

**Signature:**

*hid\_t* H5Scopy(*hid\_t* space\_id)

**Purpose:**

Creates an exact copy of a dataspace.

**Description:**

H5Scopy creates a new dataspace which is an exact copy of the dataspace identified by space\_id. The dataspace identifier returned from this function should be released with H5Sclose or resource leaks will occur.

**Parameters:**

*hid\_t* space\_id      Identifier of dataspace to copy.

**Returns:**

Returns a dataspace identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5scopy\_f

```
SUBROUTINE h5scopy_f(space_id, new_space_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id      ! Dataspace identifier
  INTEGER(HID_T), INTENT(OUT) :: new_space_id ! Identifier of dataspace copy
  INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5scopy_f
```



Last modified: 7 April 2009

**Name:** H5Screate**Signature:***hid\_t* H5Screate(*H5S\_class\_t* type)**Purpose:**

Creates a new dataspace of a specified type.

**Description:**

H5Screate creates a new dataspace of a particular type. Currently supported types are as follows:

H5S\_SCALAR

H5S\_SIMPLE

H5S\_NULL

Further dataspace types may be added later.

A *scalar dataspace*, H5S\_SCALAR, has a single element, though that element may be of a complex datatype, such as a compound or array datatype. By convention, the rank of a scalar dataspace is always 0 (zero); think of it geometrically as a single, dimensionless point, though that point can be complex.

A *simple dataspace*, H5S\_SIMPLE, consists of a regular array of elements.

A *null dataspace*, H5S\_NULL, has no data elements.

**Parameters:***H5S\_class\_t* type      The type of dataspace to be created.**Returns:**

Returns a dataspace identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5screate\_f

```

SUBROUTINE h5screate_f(classtype, space_id, hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(IN) :: classtype           ! The type of the dataspace
                                              ! to be created. Possible values
                                              ! are:
                                              !   H5S_SCALAR_F
                                              !   H5S_SIMPLE_F
                                              !   H5S_NULL_F (Not yet implemented)
  INTEGER(HID_T), INTENT(OUT) :: space_id ! Dataspace identifier
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5screate_f

```

*Last modified: 13 April 2009***Name:** H5Screate\_simple**Signature:**

```
hid_t H5Screate_simple(int rank, const hsize_t * dims, const hsize_t * maxdims )
```

**Purpose:**

Creates a new simple dataspace and opens it for access.

**Description:**

H5Screate\_simple creates a new simple dataspace and opens it for access, returning a dataset identifier.

rank is the number of dimensions used in the dataspace.

dims is a one-dimensional array of size rank specifying the size of each dimension of the dataset.

maxdims is an array of the same size specifying the upper limit on the size of each dimension.

maxdims may be the null pointer, in which case the upper limit is the same as dims.

If an element of maxdims is H5S\_UNLIMITED, the maximum size of the corresponding dimension is unlimited. Otherwise, no element of maxdims should be smaller than the corresponding element of dims.

Note that any dataset with an unlimited dimension must also be chunked; see H5Pset\_chunk.

The dataspace identifier returned from this function must be released with H5Sclose or resource leaks will occur.

**Parameters:**

<i>int</i> rank	Number of dimensions of dataspace.
<i>const hsize_t</i> * dims	An array of the size of each dimension.
<i>const hsize_t</i> * maxdims	An array of the maximum size of each dimension.

**Returns:**

Returns a dataspace identifier if successful; otherwise returns a negative value.

**See Also:**

H5Pset\_chunk

**Fortran90 Interface:** h5screate\_simple\_f

```
SUBROUTINE h5screate_simple_f(rank, dims, space_id, hdferr, maxdims)
  IMPLICIT NONE
  INTEGER, INTENT(IN) :: rank                ! Number of dataspace dimensions
  INTEGER(HSIZE_T), INTENT(IN) :: dims(*)    ! Array with the dimension sizes
  INTEGER(HID_T), INTENT(OUT) :: space_id    ! Dataspace identifier
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
                                              ! 0 on success and -1 on failure
  INTEGER(HSIZE_T), OPTIONAL, INTENT(IN) :: maxdims(*)
                                              ! Array with the maximum
                                              ! dimension sizes
END SUBROUTINE h5screate_simple_f
```

**Name:** H5Sdecode

**Signature:**

*hid\_t* H5Sdecode (*unsigned char* \*buf)

**Purpose:**

Decode a binary object description of data space and return a new object handle.

**Description:**

Given an object description of data space in binary in a buffer, H5Sdecode reconstructs the HDF5 data type object and returns a new object handle for it. The binary description of the object is encoded by H5Sencode. User is responsible for passing in the right buffer. The types of data space we address in this function are null, scalar, and simple space. For simple data space, the information of selection, for example, hyperslab selection, is also encoded and decoded. Complex data space has not been implemented in the library.

**Parameters:**

*unsigned char* \*buf     IN: Buffer for the data space object to be decoded.

**Returns:**

Returns an object ID(non-negative) if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sdecode\_f

```
SUBROUTINE h5sdecode_f(buf, obj_id, hdferr)
  IMPLICIT NONE
  CHARACTER(LEN=*), INTENT(IN) :: buf      ! Buffer of data space object to
                                           ! be decoded.
  INTEGER(HID_T), INTENT(OUT) :: obj_id    ! Object ID
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5sdecode_f
```

**Name:** H5Sencode

**Signature:**

*herr\_t* H5Sencode(*hid\_t* obj\_id, *unsigned char* \*buf, *size\_t* \*nalloc)

**Purpose:**

Encode a data space object description into a binary buffer.

**Description:**

Given the data space ID, H5Sencode converts a data space description into binary form in a buffer. Using this binary form in the buffer, a data space object can be reconstructed using H5Sdecode to return a new object handle(*hid\_t*) for this data space.

A preliminary H5Sencode call can be made to find out the size of the buffer needed. This value is returned as *nalloc*. That value can then be assigned to *nalloc* for a second H5Sencode call, which will retrieve the actual encoded object.

If the library finds out *nalloc* is not big enough for the object, it simply returns the size of the buffer needed through *nalloc* without encoding the provided buffer.

The types of data space we address in this function are null, scalar, and simple space. For simple data space, the information of selection, for example, hyperslab selection, is also encoded and decoded. Complex data space has not been implemented in the library.

**Parameters:**

<i>hid_t</i> obj_id	IN: Identifier of the object to be encoded.
<i>unsigned char</i> *buf	IN/OUT: Buffer for the object to be encoded into. If the provided buffer is NULL, only the size of buffer needed is returned through <i>nalloc</i> .
<i>size_t</i> *nalloc	IN: The size of the allocated buffer. OUT: The size of the buffer needed.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sencode\_f

```

SUBROUTINE h5sencode_f(obj_id, buf, nalloc, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id ! Identifier of the object to be encoded
  CHARACTER(LEN=*), INTENT(OUT) :: buf ! Buffer of object to be encoded into
  INTEGER(SIZE_T), INTENT(INOUT) :: nalloc
                                     ! Size of the allocated buffer
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5sencode_f

```

**Name:** H5Sextent\_copy

**Signature:**

*herr\_t* H5Sextent\_copy(*hid\_t* dest\_space\_id, *hid\_t* source\_space\_id)

**Purpose:**

Copies the extent of a dataspace.

**Description:**

H5Sextent\_copy copies the extent from source\_space\_id to dest\_space\_id. This action may change the type of the dataspace.

**Parameters:**

<i>hid_t</i> dest_space_id	IN: The identifier for the dataspace to which the extent is copied.
<i>hid_t</i> source_space_id	IN: The identifier for the dataspace from which the extent is copied.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sextent\_copy\_f

```

SUBROUTINE h5sextent_copy_f(dest_space_id, source_space_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dest_space_id    ! Identifier of destination
                                                    ! dataspace
  INTEGER(HID_T), INTENT(IN) :: source_space_id  ! Identifier of source
                                                    ! dataspace
  INTEGER, INTENT(OUT) :: hdferr                 ! Error code
                                                    ! 0 on success and -1 on failure
END SUBROUTINE h5sextent_copy_f

```

**Name:** H5Sextent\_equal

**Signature:**

*htri\_t* H5Sextent\_equal(*hid\_t* space1\_id, *hid\_t* space2\_id)

**Purpose:**

Determines whether two dataspace extents are equal.

**Description:**

H5Sextent\_equal determines whether the dataspace extents of two dataspaces, space1\_id and space2\_id, are equal.

**Parameters:**

*hid\_t* space1\_id    First dataspace identifier.

*hid\_t* space2\_id    Second dataspace identifier.

**Returns:**

Returns TRUE if equal, FALSE if unequal, if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sextent\_equal\_f

```
SUBROUTINE h5sextent_equal_f(space1_id, space2_id, equal, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space1_id ! First dataspace identifier
  INTEGER(HID_T), INTENT(IN) :: space2_id ! Second dataspace identifier
  LOGICAL, INTENT(OUT) :: Equal           ! .TRUE. if equal, .FALSE. if unequal
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5sextent_equal_f
```

**Name:** H5Sget\_select\_bounds

**Signature:**

*herr\_t* H5Sget\_select\_bounds(*hid\_t* space\_id, *hsize\_t* \*start, *hsize\_t* \*end)

**Purpose:**

Gets the bounding box containing the current selection.

**Description:**

H5Sget\_select\_bounds retrieves the coordinates of the bounding box containing the current selection and places them into user-supplied buffers.

The *start* and *end* buffers must be large enough to hold the dataspace rank number of coordinates.

The bounding box exactly contains the selection. I.e., if a 2-dimensional element selection is currently defined as containing the points (4,5), (6,8), and (10,7), then the bounding box will be (4, 5), (10, 8).

The bounding box calculation includes the current offset of the selection within the dataspace extent.

Calling this function on a none selection will return FAIL.

**Parameters:**

<i>hid_t</i> space_id	IN: Identifier of dataspace to query.
<i>hsize_t</i> *start	OUT: Starting coordinates of the bounding box.
<i>hsize_t</i> *end	OUT: Ending coordinates of the bounding box, i.e., the coordinates of the diagonally opposite corner.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

```
SUBROUTINE h5sget_select_bounds_f(space_id, start, end, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id
                                ! Dataspace identifier
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(OUT) :: start
                                ! Starting coordinates of the bounding box
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(OUT) :: end
                                ! Ending coordinates of the bounding box,
                                ! i.e., the coordinates of the diagonally
                                ! opposite corner
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5sget_select_bounds_f
```

**History:**

Release	C
1.6.0	The <i>start</i> and <i>end</i> parameters have changed from type <i>hsize_t</i> * to <i>hssize_t</i> *.

**Name:** H5Sget\_select\_elem\_npoints

**Signature:**

*hssize\_t* H5Sget\_select\_elem\_npoints(*hid\_t* space\_id)

**Purpose:**

Gets the number of element points in the current selection.

**Description:**

H5Sget\_select\_elem\_npoints returns the number of element points in the current dataspace selection.

**Parameters:**

*hid\_t* space\_id      IN: Identifier of dataspace to query.

**Returns:**

Returns the number of element points in the current dataspace selection if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5sget\_select\_elem\_npoints\_f

```
SUBROUTINE h5sget_select_elem_npoints_f(space_id, num_points, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier
  INTEGER, INTENT(OUT) :: num_points      ! Number of points in
                                           ! the current elements selection
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
END SUBROUTINE h5sget_select_elem_npoints_f
```



**Name:** H5Sget\_select\_elem\_pointlist

**Signature:**

```
herr_t H5Sget_select_elem_pointlist(hid_t space_id, hsize_t startpoint, hsize_t
numpoints, hsize_t *buf )
```

**Purpose:**

Gets the list of element points currently selected.

**Description:**

H5Sget\_select\_elem\_pointlist returns the list of element points in the current dataspace selection. Starting with the startpoint-th point in the list of points, numpoints points are put into the user's buffer. If the user's buffer fills up before numpoints points are inserted, the buffer will contain only as many points as fit.

The element point coordinates have the same dimensionality (rank) as the dataspace they are located within. The list of element points is formatted as follows:

<coordinate>, followed by  
the next coordinate,  
etc.

until all of the selected element points have been listed.

The points are returned in the order they will be iterated through when the selection is read/written from/to disk.

**Parameters:**

<i>hid_t</i> space_id	IN: Dataspace identifier of selection to query.
<i>hsize_t</i> startpoint	IN: Element point to start with.
<i>hsize_t</i> numpoints	IN: Number of element points to get.
<i>hsize_t</i> *buf	OUT: List of element points selected.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sget\_select\_elem\_pointlist\_f

```
SUBROUTINE h5sget_select_elem_pointlist_f(space_id, startpoint, num_points,
                                          buf, hdferr)

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN)  :: space_id    ! Dataspace identifier
    INTEGER(HSIZE_T), INTENT(IN) :: startpoint ! Element point to start with
    INTEGER, INTENT(OUT) :: num_points          ! Number of points to get in
                                              ! the current element selection
    INTEGER(HSIZE_T), DIMENSION(*), INTENT(OUT) :: buf
                                              ! List of points selected
    INTEGER, INTENT(OUT) :: hdferr              ! Error code
END SUBROUTINE h5sget_select_elem_pointlist_f
```

**Name:** H5Sget\_select\_hyper\_blocklist

**Signature:**

```
herr_t H5Sget_select_hyper_blocklist(hid_t space_id, hsize_t startblock, hsize_t
numblocks, hsize_t *buf )
```

**Purpose:**

Gets the list of hyperslab blocks currently selected.

**Description:**

H5Sget\_select\_hyper\_blocklist returns a list of the hyperslab blocks currently selected. Starting with the startblock-th block in the list of blocks, numblocks blocks are put into the user's buffer. If the user's buffer fills up before numblocks blocks are inserted, the buffer will contain only as many blocks as fit.

The block coordinates have the same dimensionality (rank) as the dataspace they are located within. The list of blocks is formatted as follows:

<"start" coordinate>, immediately followed by  
 <"opposite" corner coordinate>, followed by  
 the next "start" and "opposite" coordinates,  
 etc.

until all of the selected blocks have been listed.

No guarantee is implied as the order in which blocks are listed.

**Parameters:**

<i>hid_t</i> space_id	IN: Dataspace identifier of selection to query.
<i>hsize_t</i> startblock	IN: Hyperslab block to start with.
<i>hsize_t</i> numblocks	IN: Number of hyperslab blocks to get.
<i>hsize_t</i> *buf	OUT: List of hyperslab blocks selected.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sget\_select\_hyper\_blocklist\_f

```
SUBROUTINE h5sget_select_hyper_blocklist_f(space_id, startblock, num_blocks,
                                          buf, hdferr)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN)  :: space_id    ! Dataspace identifier
  INTEGER(HSIZE_T), INTENT(IN) :: startblock ! Hyperslab block to start with
                                          ! NOTE: numbering starts at 0
  INTEGER, INTENT(OUT) :: num_blocks         ! Number of hyperslab blocks to
                                          ! get in the current hyperslab
                                          ! selection
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(OUT) :: buf
                                          ! List of hyperslab blocks selected
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
END SUBROUTINE h5sget_select_hyper_blocklist_f
```

**Name:** H5Sget\_select\_hyper\_nblocks

**Signature:**

*hssize\_t* H5Sget\_select\_hyper\_nblocks(*hid\_t* space\_id)

**Purpose:**

Get number of hyperslab blocks.

**Description:**

H5Sget\_select\_hyper\_nblocks returns the number of hyperslab blocks in the current dataspace selection.

**Parameters:**

*hid\_t* space\_id      IN: Identifier of dataspace to query.

**Returns:**

Returns the number of hyperslab blocks in the current dataspace selection if successful. Otherwise returns a negative value.

**Fortran90 Interface:** h5sget\_select\_hyper\_nblocks\_f

```
SUBROUTINE h5sget_select_hyper_nblocks_f(space_id, num_blocks, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier
  INTEGER, INTENT(OUT) :: num_blocks      ! Number of hyperslab blocks in
                                           ! the current hyperslab selection
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
END SUBROUTINE h5sget_select_hyper_nblocks_f
```

**Name:** H5Sget\_select\_npoints

**Signature:**

*hssize\_t* H5Sget\_select\_npoints(*hid\_t* space\_id)

**Purpose:**

Determines the number of elements in a dataspace selection.

**Description:**

H5Sget\_select\_npoints determines the number of elements in the current selection of a dataspace.

**Parameters:**

*hid\_t* space\_id          Dataspace identifier.

**Returns:**

Returns the number of elements in the selection if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sget\_select\_npoints\_f

```
SUBROUTINE h5sget_select_npoints_f(space_id, npoints, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id      ! Dataspace identifier
  INTEGER(HSSIZE_T), INTENT(OUT) :: npoints    ! Number of elements in the
                                              ! selection
  INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5sget_select_npoints_f
```

**Name:** H5Sget\_select\_type

**Signature:**

*H5S\_sel\_type* H5Sget\_select\_type(*hid\_t* space\_id)

**Purpose:**

Determines the type of the dataspace selection.

**Description:**

H5Sget\_select\_type retrieves the type of selection currently defined for the dataspace space\_id.

**Parameters:**

*hid\_t* space\_id          Dataspace identifier.

**Returns:**

Returns the dataspace selection type, a value of the enumerated datatype H5S\_sel\_type, if successful.

Valid return values are as follows:

H5S_SEL_NONE	No selection is defined.
H5S_SEL_POINTS	A sequence of points is selected.
H5S_SEL_HYPERSLABS	A hyperslab or compound hyperslab is selected.
H5S_SEL_ALL	The entire dataset is selected.

Otherwise returns a negative value.

**Fortran90 Interface:** h5sget\_select\_type\_f

```
SUBROUTINE h5sget_select_type_f(space_id, type, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier
  INTEGER, INTENT(OUT) :: type           ! Selection type
                                         ! Valid values are:
                                         !   H5S_SEL_ERROR_F
                                         !   H5S_SEL_NONE_F
                                         !   H5S_SEL_POINTS_F
                                         !   H5S_SEL_HYPERSLABS_F
                                         !   H5S_SEL_ALL_F
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
END SUBROUTINE h5sget_select_type_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.0	Function introduced in this release.

**Name:** H5Sget\_simple\_extent\_dims

**Signature:**

```
int H5Sget_simple_extent_dims(hid_t space_id, hsize_t *dims, hsize_t *maxdims )
```

**Purpose:**

Retrieves dataspace dimension size and maximum size.

**Description:**

H5Sget\_simple\_extent\_dims returns the size and maximum sizes of each dimension of a dataspace through the dims and maxdims parameters.

Either or both of dims and maxdims may be NULL.

If a value in the returned array maxdims is H5S\_UNLIMITED (-1), the maximum size of that dimension is unlimited.

**Parameters:**

<i>hid_t</i> space_id	IN: Identifier of the dataspace object to query
<i>hsize_t</i> *dims	OUT: Pointer to array to store the size of each dimension.
<i>hsize_t</i> *maxdims	OUT: Pointer to array to store the maximum size of each dimension.

**Returns:**

Returns the number of dimensions in the dataspace if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sget\_simple\_extent\_dims\_f

```
SUBROUTINE h5sget_simple_extent_dims_f(space_id, dims, maxdims, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id    ! Dataspace identifier
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(OUT) :: dims
                                              ! Array to store dimension sizes
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(OUT) :: maxdims
                                              ! Array to store max dimension sizes
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
                                              ! Dataspace rank on success
                                              ! and -1 on failure
END SUBROUTINE h5sget_simple_extent_dims_f
```

**Name:** H5Sget\_simple\_extent\_ndims

**Signature:**

*int* H5Sget\_simple\_extent\_ndims(*hid\_t* space\_id)

**Purpose:**

Determines the dimensionality of a dataspace.

**Description:**

H5Sget\_simple\_extent\_ndims determines the dimensionality (or rank) of a dataspace.

**Parameters:**

*hid\_t* space\_id      Identifier of the dataspace

**Returns:**

Returns the number of dimensions in the dataspace if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sget\_simple\_extent\_ndims\_f

```
SUBROUTINE h5sget_simple_extent_ndims_f(space_id, rank, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id    ! Dataspace identifier
  INTEGER, INTENT(OUT) :: rank              ! Number of dimensions
  INTEGER, INTENT(OUT) :: hdferr            ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5sget_simple_extent_ndims_f
```

**Name:** H5Sget\_simple\_extent\_npoints

**Signature:**

*hssize\_t* H5Sget\_simple\_extent\_npoints(*hid\_t* space\_id)

**Purpose:**

Determines the number of elements in a dataspace.

**Description:**

H5Sget\_simple\_extent\_npoints determines the number of elements in a dataspace. For example, a simple 3-dimensional dataspace with dimensions 2, 3, and 4 would have 24 elements.

**Parameters:**

*hid\_t* space\_id      Identifier of the dataspace object to query

**Returns:**

Returns the number of elements in the dataspace if successful; otherwise returns 0.

**Fortran90 Interface:** h5sget\_simple\_extent\_npoints\_f

```
SUBROUTINE h5sget_simple_extent_npoints_f(space_id, npoints, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id      ! Dataspace identifier
  INTEGER(HSIZE_T), INTENT(OUT) :: npoints    ! Number of elements in dataspace
  INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5sget_simple_extent_npoints_f
```



**Name:** H5Sget\_simple\_extent\_type

**Signature:**

*H5S\_class\_t* H5Sget\_simple\_extent\_type(*hid\_t* space\_id)

**Purpose:**

Determine the current class of a dataspace.

**Description:**

H5Sget\_simple\_extent\_type queries a dataspace to determine the current class of a dataspace.

The function returns a class name, one of the following: H5S\_SCALAR, H5S\_SIMPLE, or H5S\_NONE.

**Parameters:**

*hid\_t* space\_id      Dataspace identifier.

**Returns:**

Returns a dataspace class name if successful; otherwise H5S\_NO\_CLASS (-1).

**Fortran90 Interface:** h5sget\_simple\_extent\_type\_f

```
SUBROUTINE h5sget_simple_extent_type_f(space_id, classtype, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier
  INTEGER, INTENT(OUT) :: classtype      ! Class type
                                         ! Possible values are:
                                         !   H5S_NO_CLASS_F
                                         !   H5S_SCALAR_F
                                         !   H5S_SIMPLE_F
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5sget_simple_extent_type_f
```

**Name:** H5Sis\_simple

**Signature:**

*htri\_t* H5Sis\_simple(*hid\_t* space\_id)

**Purpose:**

Determines whether a dataspace is a simple dataspace.

**Description:**

H5Sis\_simple determines whether a dataspace is a simple dataspace. [Currently, all dataspace objects are simple dataspaces, complex dataspace support will be added in the future]

**Parameters:**

*hid\_t* space\_id      Identifier of the dataspace to query

**Returns:**

When successful, returns a positive value, for TRUE, or 0 (zero), for FALSE. Otherwise returns a negative value.

**Fortran90 Interface:** h5sis\_simple\_f

```
SUBROUTINE h5sis_simple_f(space_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id      ! Dataspace identifier
  LOGICAL, INTENT(OUT) :: flag                ! Flag, indicates if dataspace
                                              ! is simple or not:
                                              ! TRUE or FALSE
  INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5sis_simple_f
```

**Name:** H5Soffset\_simple

**Signature:**

```
herr_t H5Soffset_simple(hid_t space_id, const hssize_t *offset )
```

**Purpose:**

Sets the offset of a simple dataspace.

**Description:**

H5Soffset\_simple sets the offset of a simple dataspace *space\_id*. The *offset* array must be the same number of elements as the number of dimensions for the dataspace. If the *offset* array is set to NULL, the offset for the dataspace is reset to 0.

This function allows the same shaped selection to be moved to different locations within a dataspace without requiring it to be redefined.

**Parameters:**

<i>hid_t</i> space_id	IN: The identifier for the dataspace object to reset.
<i>const hssize_t</i> *offset	IN: The offset at which to position the selection.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5soffset\_simple\_f

```
SUBROUTINE h5soffset_simple_f(space_id, offset, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id      ! Dataspace identifier
  INTEGER(HSSIZE_T), DIMENSION(*), INTENT(IN) :: offset
                                              ! The offset at which to position
                                              ! the selection
  INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5soffset_simple_f
```

*Last modified: 6 April 2009***Name:** H5Sselect\_all**Signature:***herr\_t* H5Sselect\_all(*hid\_t* dspace\_id)**Purpose:**

Selects an entire dataspace.

**Description:**

H5Sselect\_all selects the entire extent of the dataspace dspace\_id.

More specifically, H5Sselect\_all sets the selection type to H5S\_SEL\_ALL, which specifies the entire dataspace anywhere it is applied.

**Parameters:***hid\_t* dspace\_id      IN: The identifier for the dataspace for which the selection is being made.**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**See Also:**

H5Sget\_select\_type

**Fortran90 Interface:** h5sselect\_all\_f

```

SUBROUTINE h5sselect_all_f(dspace_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dspace_id ! Dataspace identifier
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5sselect_all_f

```

**Name:** H5Sselect\_elements

**Signature:**

```
herr_t H5Sselect_elements(hid_t space_id, H5S_seloper_t op, size_t num_elements, const
hsize_t *coord)
```

**Purpose:**

Selects array elements to be included in the selection for a dataspace.

**Description:**

H5Sselect\_elements selects array elements to be included in the selection for the `space_id` dataspace.

The number of elements selected is set in the `num_elements` parameter.

The `coord` array is a two-dimensional array of size `num_elements` by `dataspace_rank` containing a list of zero-based values specifying the coordinates in the dataset of the selected elements. The order of the element coordinates in the `coord` array specifies the order in which the array elements are iterated through when I/O is performed. Duplicate coordinate locations are not checked for.

The selection operator `op` determines how the new selection is to be combined with the previously existing selection for the dataspace. The following operators are supported:

H5S_SELECT_SET	Replaces the existing selection with the parameters from this call. Overlapping blocks are not supported with this operator. Adds the new selection to the existing selection.
H5S_SELECT_APPEND	Adds the new selection following the last element of the existing selection.
H5S_SELECT_PREPEND	Adds the new selection preceding the first element of the existing selection.

**Parameters:**

<i>hid_t</i> space_id	Identifier of the dataspace.
<i>H5S_seloper_t</i> op	Operator specifying how the new selection is to be combined with the existing selection for the dataspace.
<i>size_t</i> num_elements	Number of elements to be selected.
<i>const hsize_t</i> *coord	A 2-dimensional array of 0-based values specifying the coordinates of the elements being selected.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sselect\_elements\_f

```
SUBROUTINE h5sselect_elements_f(space_id, operator, rank, num_elements,
                                coord, hdferr)

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: space_id    ! Dataspace identifier
    INTEGER, INTENT(IN) :: operator            ! Flag, valid values are:
                                                !   H5S_SELECT_SET_F
                                                !   H5S_SELECT_APPEND_F
                                                !   H5S_SELECT_PREPEND_F
    INTEGER, INTENT(IN) :: rank                ! Number of dataspace
                                                ! dimensions
    INTEGER(SIZE_T), INTENT(IN) :: num_elements
                                                ! Number of elements to be
                                                ! selected
```

```
INTEGER(HSIZE_T), DIMENSION(rank,num_elements), INTENT(IN) :: coord
! A 1-based array containing the
! coordinates of the selected
! elements
! NOTE: Reversed dimension declaration
! compared to the C specification
! of coord(num_elements, rank)
INTEGER, INTENT(OUT) :: hdferr
! Error code
! 0 on success and -1 on failure
END SUBROUTINE h5sselect_elements_f
```

**History:****Release    C**

1.6.4      coord parameter type changed  
to *const hsize\_t*.

**Fortran90**

coord parameter type changed to  
INTEGER(HSIZE\_T).

**Name:** H5Sselect\_hyperslab

**Signature:**

```
herr_t H5Sselect_hyperslab(hid_t space_id, H5S_seloper_t op, const hsize_t *start, const hsize_t *stride, const hsize_t *count, const hsize_t *block )
```

**Purpose:**

Selects a hyperslab region to add to the current selected region.

**Description:**

H5Sselect\_hyperslab selects a hyperslab region to add to the current selected region for the dataspace specified by space\_id.

The start, stride, count, and block arrays must be the same size as the rank of the dataspace. For example, if the dataspace is 4-dimensional, each of these parameters must be a 1-dimensional array of size 4.

The selection operator op determines how the new selection is to be combined with the already existing selection for the dataspace. The following operators are supported:

H5S_SELECT_SET	Replaces the existing selection with the parameters from this call. Overlapping blocks are not supported with this operator.
H5S_SELECT_OR	Adds the new selection to the existing selection. (Binary OR)
H5S_SELECT_AND	Retains only the overlapping portions of the new selection and the existing selection. (Binary AND)
H5S_SELECT_XOR	Retains only the elements that are members of the new selection or the existing selection, excluding elements that are members of both selections. (Binary exclusive-OR, XOR)
H5S_SELECT_NOTB	Retains only elements of the existing selection that are not in the new selection.
H5S_SELECT_NOTA	Retains only elements of the new selection that are not in the existing selection.

The start array specifies the offset of the starting element of the specified hyperslab.

The stride array chooses array locations from the dataspace with each value in the stride array determining how many elements to move in each dimension. Setting a value in the stride array to 1 moves to each element in that dimension of the dataspace; setting a value of 2 in allocation in the stride array moves to every other element in that dimension of the dataspace. In other words, the stride determines the number of elements to move from the start location in each dimension. Stride values of 0 are not allowed. If the stride parameter is NULL, a contiguous hyperslab is selected (as if each value in the stride array were set to 1).

The count array determines how many blocks to select from the dataspace, in each dimension.

The block array determines the size of the element block selected from the dataspace. If the block parameter is set to NULL, the block size defaults to a single element in each dimension (as if each value in the block array were set to 1).

For example, consider a 2-dimensional dataspace with hyperslab selection settings as follows: the `start` offset is specified as [1,1], `stride` is [4,4], `count` is [3,7], and `block` is [2,2]. In C, these settings will specify a hyperslab consisting of 21 2x2 blocks of array elements starting with location (1,1) with the selected blocks at locations (1,1), (5,1), (9,1), (1,5), (5,5), etc.; in Fortran, they will specify a hyperslab consisting of 21 2x2 blocks of array elements starting with location (2,2) with the selected blocks at locations (2,2), (6,2), (10,2), (2,6), (6,6), etc.

Regions selected with this function call default to C order iteration when I/O is performed.

#### Parameters:

<i>hid_t</i> <code>space_id</code>	IN: Identifier of dataspace selection to modify
<i>H5S_seloper_t</i> <code>op</code>	IN: Operation to perform on current selection.
<i>const hsize_t</i> * <code>start</code>	IN: Offset of start of hyperslab
<i>const hsize_t</i> * <code>count</code>	IN: Number of blocks included in hyperslab.
<i>const hsize_t</i> * <code>stride</code>	IN: Hyperslab stride.
<i>const hsize_t</i> * <code>block</code>	IN: Size of block in hyperslab.

#### Returns:

Returns a non-negative value if successful; otherwise returns a negative value.

#### Fortran90 Interface: h5sselect\_hyperslab\_f

```
SUBROUTINE h5sselect_hyperslab_f(space_id, operator, start, count,
                                hdferr, stride, block)

  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier
  INTEGER, INTENT(IN) :: op              ! Flag, valid values are:
                                         !   H5S_SELECT_SET_F
                                         !   H5S_SELECT_OR_F
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(IN) :: start
                                         ! Offset of start of hyperslab
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(IN) :: count
                                         ! Number of blocks to select
                                         ! from dataspace
  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                         ! 0 on success and -1 on failure
  INTEGER(HSIZE_T), DIMENSION(*), OPTIONAL, INTENT(IN) :: stride
                                         ! Array of how many elements to
                                         ! move in each direction
  INTEGER(HSIZE_T), DIMENSION(*), OPTIONAL, INTENT(IN) :: block
                                         ! Size of the element block
END SUBROUTINE h5sselect_hyperslab_f
```

#### History:

Release	C	Fortran90
1.6.4	<code>start[ ]</code> parameter type changed to <i>const hsize_t</i> .	<code>start</code> parameter type changed to <code>INTEGER(HSIZE_T)</code> .



**Name:** H5Sselect\_none

**Signature:**

*herr\_t* H5Sselect\_none(*hid\_t* space\_id)

**Purpose:**

Resets the selection region to include no elements.

**Description:**

H5Sselect\_none resets the selection region for the dataspace *space\_id* to include no elements.

**Parameters:**

*hid\_t* space\_id      IN: The identifier for the dataspace in which the selection is being reset.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sselect\_none\_f

```
SUBROUTINE h5sselect_none_f(space_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5sselect_none_f
```

**Name:** H5Sselect\_valid

**Signature:**

*htri\_t* H5Sselect\_valid(*hid\_t* space\_id)

**Purpose:**

Verifies that the selection is within the extent of the dataspace.

**Description:**

H5Sselect\_valid verifies that the selection for the dataspace space\_id is within the extent of the dataspace if the current offset for the dataspace is used.

**Parameters:**

*hid\_t* space\_id      The identifier for the dataspace being queried.

**Returns:**

Returns a positive value, for TRUE, if the selection is contained within the extent or 0 (zero), for FALSE, if it is not. Returns a negative value on error conditions such as the selection or extent not being defined.

**Fortran90 Interface:** h5sselect\_valid\_f

```
SUBROUTINE h5sselect_valid_f(space_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier
  LOGICAL, INTENT(OUT) :: flag           ! TRUE if the selection is
                                         ! contained within the extent,
                                         ! FALSE otherwise.
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5sselect_valid_f
```

**Name:** H5Sset\_extent\_none

**Signature:**

*herr\_t* H5Sset\_extent\_none(*hid\_t* space\_id)

**Purpose:**

Removes the extent from a dataspace.

**Description:**

H5Sset\_extent\_none removes the extent from a dataspace and sets the type to H5S\_NO\_CLASS.

**Parameters:**

*hid\_t* space\_id      The identifier for the dataspace from which the extent is to be removed.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sset\_extent\_none\_f

```
SUBROUTINE h5sset_extent_none_f(space_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: space_id ! Dataspace identifier
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5sset_extent_none_f
```

**Name:** H5Sset\_extent\_simple

**Signature:**

```
herr_t H5Sset_extent_simple(hid_t space_id, int rank, const hsize_t *current_size,
const hsize_t *maximum_size)
```

**Purpose:**

Sets or resets the size of an existing dataspace.

**Description:**

H5Sset\_extent\_simple sets or resets the size of an existing dataspace.

rank is the dimensionality, or number of dimensions, of the dataspace.

current\_size is an array of size rank which contains the new size of each dimension in the dataspace. maximum\_size is an array of size rank which contains the maximum size of each dimension in the dataspace.

Any previous extent is removed from the dataspace, the dataspace type is set to H5S\_SIMPLE, and the extent is set as specified.

**Parameters:**

<i>hid_t</i> space_id	Dataspace identifier.
<i>int</i> rank	Rank, or dimensionality, of the dataspace.
<i>const hsize_t</i> *current_size	Array containing current size of dataspace.
<i>const hsize_t</i> *maximum_size	Array containing maximum size of dataspace.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5sset\_extent\_simple\_f

```
SUBROUTINE h5sset_extent_simple_f(space_id, rank, current_size,
                                maximum_size, hdferr)

    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: space_id      ! Dataspace identifier
    INTEGER, INTENT(IN) :: rank                 ! Dataspace rank
    INTEGER(HSIZE_T), DIMENSION(rank), INTENT(IN) :: current_size
                                                ! Array with the new sizes
                                                ! of dimensions
    INTEGER(HSIZE_T), DIMENSION(rank), INTENT(IN) ::
                                                ! Array with the new maximum
                                                ! sizes of dimensions
    INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                                ! 0 on success and -1 on failure

END SUBROUTINE h5sset_extent_simple_f
```

# H5T: Datatype Interface

## Datatype Object API Functions

These functions create and manipulate the datatype which describes elements of a dataset. In the following lists, *italic type* indicates a configurable macro.

### The C Interfaces:

#### *General Datatype Operations*

- H5Tcreate
- *H5Topen*
- H5Topen1 \*
- H5Topen2
- *H5Tcommit*
- H5Tcommit1 \*
- H5Tcommit2
- H5Tcommit\_anon
- H5Tcommitted
- H5Tcopy
- H5Tequal
- H5Tlock
- H5Tget\_class
- H5Tget\_create\_plist
- H5Tget\_size
- H5Tget\_super
- H5Tget\_native\_type
- H5Tdetect\_class
- H5Tclose

#### *Conversion Functions*

- H5Tconvert
- H5Tfind
- H5Tcompiler\_conv
- H5Tregister
- H5Tunregister
- H5Tdecode
- H5Tencode

#### *Atomic Datatype Properties*

- H5Tset\_size
- H5Tget\_order
- H5Tset\_order
- H5Tget\_precision
- H5Tset\_precision
- H5Tget\_offset
- H5Tset\_offset
- H5Tget\_pad
- H5Tset\_pad
- H5Tget\_sign
- H5Tset\_sign
- H5Tget\_fields
- H5Tset\_fields
- H5Tget\_ebias
- H5Tset\_ebias
- H5Tget\_norm
- H5Tset\_norm
- H5Tget\_inpad
- H5Tset\_inpad
- H5Tget\_cset
- H5Tset\_cset
- H5Tget\_strpad
- H5Tset\_strpad

#### *Array Datatypes*

- *H5Tarray\_create*
- H5Tarray\_create1 \*
- H5Tarray\_create2
- H5Tget\_array\_ndims
- *H5Tget\_array\_dims*
- H5Tget\_array\_dims1 \*
- H5Tget\_array\_dims2

#### *Compound Datatype Properties*

- H5Tget\_nmembers
- H5Tget\_member\_class
- H5Tget\_member\_name
- H5Tget\_member\_index
- H5Tget\_member\_offset
- H5Tget\_member\_type
- H5Tinsert
- H5Tpack

#### *Variable-length Datatypes*

- H5Tvlen\_create
- H5Tis\_variable\_str

#### *Opaque Datatypes*

- H5Tset\_tag
- H5Tget\_tag

#### *Enumeration Datatypes*

- H5Tenum\_create
- H5Tenum\_insert
- H5Tenum\_nameof
- H5Tenum\_valueof
- H5Tget\_member\_value
- H5Tget\_nmembers
- H5Tget\_member\_name
- H5Tget\_member\_index

\* *Use of these functions is deprecated in Release 1.8.0.*

*Alphabetical Listing*

- *H5Tarray\_create*
- H5Tarray\_create1 \*
- H5Tarray\_create2
- H5Tclose
- *H5Tcommit*
- H5Tcommit1 \*
- H5Tcommit2
- H5Tcommit\_anon
- H5Tcommitted
- H5Tcompiler\_conv
- H5Tconvert
- H5Tcopy
- H5Tcreate
- H5Tdecode
- H5Tdetect\_class
- H5Tencode
- H5Tenum\_create
- H5Tenum\_insert
- H5Tenum\_nameof
- H5Tenum\_valueof
- H5Tequal
- H5Tfind
- *H5Tget\_array\_dims*
- H5Tget\_array\_dims1 \*
- H5Tget\_array\_dims2
- H5Tget\_array\_ndims
- H5Tget\_class
- H5Tget\_create\_plist
- H5Tget\_cset
- H5Tget\_ebias
- H5Tget\_fields
- H5Tget\_inpad
- H5Tget\_member\_class
- H5Tget\_member\_index
- H5Tget\_member\_name
- H5Tget\_member\_offset
- H5Tget\_member\_type
- H5Tget\_member\_value
- H5Tget\_native\_type
- H5Tget\_nmembers
- H5Tget\_norm
- H5Tget\_offset
- H5Tget\_order
- H5Tget\_pad
- H5Tget\_precision
- H5Tget\_sign
- H5Tget\_size
- H5Tget\_strpad
- H5Tget\_super
- H5Tget\_tag
- H5Tinsert
- H5Tis\_variable\_str
- H5Tlock
- *H5Topen*
- H5Topen1 \*
- H5Topen2
- H5Tpack
- H5Tregister
- H5Tset\_cset
- H5Tset\_ebias
- H5Tset\_fields
- H5Tset\_inpad
- H5Tset\_norm
- H5Tset\_offset
- H5Tset\_order
- H5Tset\_pad
- H5Tset\_precision
- H5Tset\_sign
- H5Tset\_size
- H5Tset\_strpad
- H5Tset\_tag
- H5Tunregister
- H5Tvlen\_create

**The FORTRAN90 Interfaces:**

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

*General Datatype Operations*

- h5tcreate\_f
- h5tdecode\_f
- h5tencode\_f
- h5topen\_f
- h5tcommit\_f
- h5tcommit\_anon\_f
- h5tcommitted\_f
- H5tcompiler\_conv\_f
- h5tcopy\_f
- h5tequal\_f
- h5tget\_create\_plist\_f
- h5tget\_class\_f
- h5tget\_size\_f
- h5tget\_super\_f
- h5tclose\_f

*Enumeration Datatypes*

- h5tenum\_create\_f
- h5tenum\_insert\_f
- h5tenum\_nameof\_f
- h5tenum\_valueof\_f
- h5tget\_member\_value\_f
- h5tget\_native\_type\_f
- h5tget\_nmembers\_f
- h5tget\_member\_name\_f
- h5tget\_member\_index\_f

*Atomic Datatype Properties*

- h5tset\_size\_f
- h5tget\_order\_f
- h5tset\_order\_f
- h5tget\_precision\_f
- h5tset\_precision\_f
- h5tget\_offset\_f
- h5tset\_offset\_f
- h5tget\_pad\_f
- h5tset\_pad\_f
- h5tget\_sign\_f
- h5tset\_sign\_f
- h5tget\_fields\_f
- h5tset\_fields\_f
- h5tget\_ebiass\_f
- h5tset\_ebiass\_f
- h5tget\_norm\_f
- h5tset\_norm\_f
- h5tget\_inpad\_f
- h5tset\_inpad\_f
- h5tget\_cset\_f
- h5tset\_cset\_f
- h5tget\_strpad\_f
- h5tset\_strpad\_f

*Array Datatypes*

- h5tarray\_create\_f
- h5tget\_array\_ndims\_f
- h5tget\_array\_dims\_f

*Compound Datatype Properties*

- h5tget\_nmembers\_f
- h5tget\_member\_class\_f
- h5tget\_member\_name\_f
- h5tget\_member\_index\_f
- h5tget\_member\_offset\_f
- h5tget\_member\_type\_f
- h5tinsert\_f
- h5tpack\_f

*Variable-length Datatypes*

- h5tvlen\_create\_f
- h5tis\_variable\_str\_f

*Opaque Datatypes*

- h5tset\_tag\_f
- h5tget\_tag\_f

The Datatype interface, H5T, provides a mechanism to describe the storage format of individual data points of a data set and is hopefully designed in such a way as to allow new features to be easily added without disrupting applications that use the data type interface. A dataset (the H5D interface) is composed of a collection or raw data points of homogeneous type organized according to the data space (the H5S interface).

A datatype is a collection of datatype properties, all of which can be stored on disk, and which when taken as a whole, provide complete information for data conversion to or from that datatype. The interface provides functions to set and query properties of a datatype.

A *data point* is an instance of a *datatype*, which is an instance of a *type class*. We have defined a set of type classes and properties which can be extended at a later time. The atomic type classes are those which describe types which cannot be decomposed at the datatype interface level; all other classes are compound.

See *The Datatype Interface (H5T)* in the *HDF5 User's Guide* for further information, including a complete list of all supported datatypes.





**Name:** H5Tarray\_create

**Signatures:**

```
hid_t H5Tarray_create( hid_t base_type_id, int rank, [1]
                      const hsize_t dims[ /*rank*/ ], const int perm[ /*rank*/ ] )
```

```
hid_t H5Tarray_create( hid_t base_type_id, unsigned rank, [2]
                      const hsize_t dims[ /*rank*/ ], )
```

**Purpose:**

Creates an array datatype object.

**Description:**

H5Tarray\_create is a macro that is mapped to either H5Tarray\_create1 or H5Tarray\_create2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. For example:

- ◇ The H5Tarray\_create macro will be mapped to H5Tarray\_create1 and will use the H5Tarray\_create1 syntax (first signature above) if an application is coded for HDF5 Release 1.6.x.
- ◇ The H5Tarray\_create macro mapped to H5Tarray\_create2 and will use the H5Tarray\_create2 syntax (second signature above) if an application is coded for HDF5 Release 1.8.x.

Macro use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Tarray\_create is mapped to the most recent version of the function, currently H5Tarray\_create2. If the library and/or application is compiled for Release 1.6 emulation, H5Tarray\_create will be mapped to H5Tarray\_create1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Tarray_create mapping
<u>Global settings</u>	
No compatibility flag	H5Tarray_create2
Enable deprecated symbols	H5Tarray_create2
Disable deprecated symbols	H5Tarray_create2
Emulate Release 1.6 interface	H5Tarray_create1
<u>Function-level macros</u>	
H5Tarray_create_vers = 2	H5Tarray_create2
H5Tarray_create_vers = 1	H5Tarray_create1

**Interface history:** Signature [1] above is the original H5Tarray\_create interface and the only interface available prior to HDF5 Release 1.8.0. This signature and the corresponding function are now deprecated but will remain directly callable as H5Tarray\_create1.

Signature [2] above was introduced with HDF5 Release 1.8.0 and is the recommended and default interface. It is directly callable as H5Tarray\_create2.

See “API Compatibility Macros in HDF5” for circumstances under which either of these functions might not be available in an installed instance of the HDF5 Library.

**Fortran90 Interface: h5tarray\_create\_f**

```
SUBROUTINE h5tarray_create_f(base_id, rank, dims, type_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: base_id    ! Identifier of array base datatype
  INTEGER, INTENT(IN)       :: rank       ! Rank of the array
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(IN) :: dims
                                           ! Sizes of each array dimension
  INTEGER(HID_T), INTENT(OUT) :: type_id  ! Identifier of the array datatype
  INTEGER, INTENT(OUT)       :: hdferr    ! Error code
END SUBROUTINE h5tarray_create_f
```

**History:**

Release	C
1.8.0	<p>The function H5Tarray_create renamed to H5Tarray_create1 and deprecated in this release.</p> <p>The macro H5Tarray_create and the function H5Tarray_create2 introduced in this release.</p>

**Name:** H5Tarray\_create1

**Signature:**

```
hid_t H5Tarray_create1(hid_t base_type_id, int rank, const hsize_t dims[/*rank*/],
                      const int perm[/*rank*/])
```

**Purpose:**

Creates an array datatype object.

**Notice:**

*This function is renamed from H5Tarray\_create and deprecated in favor of the function H5Tarray\_create2 or the new macro H5Tarray\_create.*

**Description:**

H5Tarray\_create1 creates a new array datatype object.

base\_type\_id is the datatype of every element of the array, i.e., of the number at each position in the array.

rank is the number of dimensions and the size of each dimension is specified in the array dims. The value of rank is currently limited to H5S\_MAX\_RANK and must be greater than 0 (zero). All dimension sizes specified in dims must be greater than 0 (zero).

The array perm is designed to contain the dimension permutation, i.e. C versus FORTRAN array order. *(The parameter perm is currently unused and is not yet implemented.)*

**Parameters:**

hid_t base_type_id	IN: Datatype identifier for the array base datatype.
int rank	IN: Rank of the array.
const hsize_t dims[/*rank*/]	IN: Size of each array dimension.
const int perm[/*rank*/]	IN: Dimension permutation. <i>(Currently not implemented.)</i>

**Returns:**

Returns a valid datatype identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tarray\_create\_f

```
SUBROUTINE h5tarray_create_f(base_id, rank, dims, type_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: base_id    ! Identifier of array base datatype
  INTEGER, INTENT(IN)       :: rank       ! Rank of the array
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(IN) :: dims
                                           ! Sizes of each array dimension
  INTEGER(HID_T), INTENT(OUT) :: type_id  ! Identifier of the array datatype
  INTEGER, INTENT(OUT)       :: hdferr    ! Error code
END SUBROUTINE h5tarray_create_f
```

**History:**

Release	C
1.4.0	Function introduced in this release.
1.8.0	Function H5Tarray_create renamed to H5Tarray_create1 and deprecated in this release.

*Last modified: 9 April 2009*

**Name:** H5Tarray\_create2

**Signature:**

```
hid_t H5Tarray_create2(hid_t base_type_id, unsigned rank, const hsize_t
dims[/*rank*/],)
```

**Purpose:**

Creates an array datatype object.

**Description:**

H5Tarray\_create2 creates a new array datatype object.

*base\_type\_id* is the datatype of every element of the array, i.e., of the number at each position in the array.

*rank* is the number of dimensions and the size of each dimension is specified in the array *dims*. The value of *rank* is currently limited to H5S\_MAX\_RANK and must be greater than 0 (zero). All dimension sizes specified in *dims* must be greater than 0 (zero).

**Parameters:**

<i>hid_t</i> base_type_id	IN: Datatype identifier for the array base datatype.
<i>unsigned</i> rank	IN: Rank of the array.
<i>const hsize_t</i> dims[/*rank*/]	IN: Size of each array dimension.

**Returns:**

Returns a valid datatype identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	Change
1.8.0	C function introduced in this release.

**Name:** H5Tclose

**Signature:**

*herr\_t* H5Tclose(*hid\_t* dtype\_id)

**Purpose:**

Releases a datatype.

**Description:**

H5Tclose releases a datatype. Further access through the datatype identifier is illegal. Failure to release a datatype with this call will result in resource leaks.

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to release.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tclose\_f

```
SUBROUTINE h5tclose_f(type_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(OUT) :: hdferr       ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5tclose_f
```

**Name:** H5Tcommit

**Signature:**

```
herr_t H5Tcommit( hid_t loc_id, const char *name, hid_t dtype_id )
hid_t H5Tcommit( hid_t loc_id, const char *name, hid_t dtype_id, hid_t lcpl_id, hid_t
tcpl_id, hid_t tapl_id )
```

**Purpose:**

Commits a transient datatype, linking it into the file and creating a new named datatype.

**Description:**

H5Tcommit is a macro that is mapped to either H5Tcommit1 or H5Tcommit2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Tcommit is mapped to the most recent version of the function, currently H5Tcommit2. If the library and/or application is compiled for Release 1.6 emulation, H5Tcommit will be mapped to H5Tcommit1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Tcommit mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Tcommit2
Enable deprecated symbols	H5Tcommit2
Disable deprecated symbols	H5Tcommit2
Emulate Release 1.6 interface	H5Tcommit1
<hr/>	
<u>Function-level macros</u>	
H5Tcommit_vers = 2	H5Tcommit2
H5Tcommit_vers = 1	H5Tcommit1

**Fortran90 Interface:** h5tcommit\_f

```
SUBROUTINE h5tcommit_f( loc_id, name, type_id, hdferr, &
                        lcpl_id, tcpl_id, tapl_id )
    IMPLICIT NONE
    INTEGER(HID_T), INTENT(IN) :: loc_id ! File or group identifier
    CHARACTER(LEN=*), INTENT(IN) :: name ! Datatype name within file or group
    INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
    INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
    INTEGER(HID_T), OPTIONAL, INTENT(IN) :: lcpl_id
                                ! Link creation property list
```

```
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: tcpl_id
                                ! Datatype creation property list
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: tapl_id
                                ! Datatype access property list
END SUBROUTINE h5tcommit_f
```

**History:**

Release	C
1.8.0	The function <code>H5Tcommit</code> renamed to <code>H5Tcommit1</code> and deprecated in this release. The macro <code>H5Tcommit</code> and the function <code>H5Tcommit2</code> introduced in this release.

*Last modified: 18 May 2009***Name:** H5Tcommit1**Signature:**

```
herr_t H5Tcommit1(hid_t loc_id, const char *name, hid_t dtype_id)
```

**Purpose:**

Commits a transient datatype to a file, creating a new named datatype.

**Notice:**

*This function is deprecated in favor of the function H5Tcommit2.*

**Description:**

H5Tcommit1 commits the transient datatype (not immutable) to a file, turning it into a named datatype.

The datatype `dtype_id` is committed as a named datatype at the location `loc_id`, which is either a file or group identifier, with the name `name`.

`name` can be a relative path based at `loc_id` or an absolute path from the root of the file. If any of the groups specified in that path do not already exist, the dataset must be created with `H5Tcommit_anon` and linked into the file structure with `H5Lcreate_hard`.

As is the case for any object in a group, the length of the name of a named datatype is not limited.

See `H5Tcommit_anon` for a discussion of the differences between `H5Tcommit` and `H5Tcommit_anon`.

**Parameters:**

<code>hid_t loc_id</code>	IN: A file or group identifier.
<code>const char *name</code>	IN: A datatype name.
<code>hid_t dtype_id</code>	IN: A datatype identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under `H5Tcommit`.**History:**

Release	C
1.8.0	The function <code>H5Tcommit</code> renamed to <code>H5Tcommit1</code> and deprecated in this release.



**Name:** H5Tcommit2

**Signature:**

```
herr_t H5Tcommit2(hid_t loc_id, const char *name, hid_t dtype_id, hid_t lcpl_id, hid_t
tcpl_id, hid_t tapl_id)
```

**Purpose:**

Commits a transient datatype, linking it into the file and creating a new named datatype.

**Description:**

H5Tcommit2 saves a transient datatype as an immutable named datatype in a file. The datatype specified by `dtype_id` is committed to the file with the name `name` at the location specified by `loc_id` and with the datatype creation and access property lists `tcpl_id` and `tapl_id`, respectively.

`loc_id` may be a file identifier, or a group identifier within that file. `name` may be either an absolute path in the file or a relative path from `loc_id` naming the newly-committed datatype.

The link creation property list, `lcpl_id`, governs creation of the link(s) by which the new named datatype is accessed and the creation of any intermediate groups that may be missing.

Once committed, this datatype may be used to define the datatype of any other dataset or attribute in the file.

**Parameters:**

<i>hid_t</i> loc_id	IN: Location identifier
<i>const char</i> *name	IN: Name given to committed datatype
<i>hid_t</i> dtype_id	IN: Identifier of datatype to be committed
<i>hid_t</i> lcpl_id	IN: Link creation property list
<i>hid_t</i> tcpl_id	IN: Datatype creation property list
<i>hid_t</i> tapl_id	IN: Datatype access property list

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Tcommit.

**History:**

Release	C
1.8.0	Function introduced in this release.

*Last modified: 18 May 2009*

**Name:** H5Tcommit\_anon

**Signature:**

*herr\_t* H5Tcommit\_anon(*hid\_t* loc\_id, *hid\_t* dtype\_id, *hid\_t* tcpl\_id, *hid\_t* tapl\_id)

**Purpose:**

Commits a transient datatype to a file, creating a new named datatype, but does not link it into the file structure.

**Description:**

H5Tcommit\_anon commits a transient datatype (not immutable) to a file, turning it into a named datatype with the specified creation and property lists. With default property lists, H5P\_DEFAULT, H5Tcommit\_anon provides similar functionality to that of H5Tcommit, with the differences described below.

The datatype access property list identifier, tapl\_id, is provided for future functionality and is not used at this time. This parameter should always be passed as the value H5P\_DEFAULT.

Note that H5Tcommit\_anon does not link this newly-committed datatype into the file. After the H5Tcommit\_anon call, the datatype identifier dtype\_id *must* be linked into the HDF5 file structure with H5Lcreate\_hard or it will be deleted from the file when the file is closed.

The differences between this function and H5Tcommit are as follows:

- ◇ H5Tcommit\_anon explicitly includes property lists, which provides for greater control of the creation process and of the properties of the new named datatype. H5Tcommit always uses default properties.
- ◇ H5Tcommit\_anon neither provides the new named datatype's name nor links it into the HDF5 file structure; those actions must be performed separately through a call to H5Lcreate\_hard, which offers greater control over linking.

**Parameters:**

<i>hid_t</i> loc_id	IN: A file or group identifier specifying the file in which the new named datatype is to be created.
<i>hid_t</i> dtype_id	IN: A datatype identifier.
<i>hid_t</i> tcpl_id	IN: A datatype creation property list identifier. (H5P_DEFAULT for the default property list.)
<i>hid_t</i> tapl_id	IN: A datatype access property list identifier. <i>Currently unused; should always be passed as the value H5P_DEFAULT.</i>

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tcommit\_anon\_f

```

SUBROUTINE h5tcommit_anon_f(loc_id, dtype_id, hdferr, tcpl_id, tapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id ! A file or group identifier specifying
                                         ! the file in which the new named
                                         ! datatype is to be created.
  INTEGER(HID_T), INTENT(IN) :: dtype_id
                                         ! Datatype identifier
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                         ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: tcpl_id

```

```
! A datatype creation property
! list identifier.
! H5P_DEFAULT_F = default property list
INTEGER(HID_T), OPTIONAL, INTENT(IN) :: tapl_id
! A datatype access property list id
END SUBROUTINE h5tcommit_anon_f
```

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Tcommitted

**Signature:**

*htri\_t*H5Tcommitted(*hid\_t* dtype\_id)

**Purpose:**

Determines whether a datatype is a named type or a transient type.

**Description:**

H5Tcommitted queries a type to determine whether the type specified by the dtype\_id identifier is a named type or a transient type. If this function returns a positive value, then the type is named (that is, it has been committed, perhaps by some other application). Datasets which return committed datatypes with H5Dget\_type( ) are able to share the datatype with other datasets in the same file.

**Parameters:**

*hid\_t* dtype\_id      IN: Datatype identifier.

**Returns:**

When successful, returns a positive value, for TRUE, if the datatype has been committed, or 0 (zero), for FALSE, if the datatype has not been committed. Otherwise returns a negative value.

**Fortran90 Interface:** h5tcommitted\_f

```
SUBROUTINE h5tcommitted_f(dtype_id, committed, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dtype_id
                                ! A datatype identifier
  LOGICAL, INTENT(OUT) :: committed ! .TRUE., if the datatype committed
                                ! .FALSE., if the datatype not committed.
  INTEGER, INTENT(OUT) :: hdferr    ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5tcommitted_f
```

**Name:** H5Tcompiler\_conv

**Signature:**

*htri\_t* H5Tcompiler\_conv(*hid\_t* src\_id, *hid\_t* dst\_id)

**Purpose:**

Check whether the library's default conversion is hard conversion.

**Description:**

H5Tcompiler\_conv finds out whether the library's conversion function from type *src\_id* to type *dst\_id* is a compiler (hard) conversion. A compiler conversion uses compiler's casting; a library (soft) conversion uses the library's own conversion function.

**Parameters:**

*hid\_t* src\_id     IN: Identifier for the source datatype.

*hid\_t* dst\_id     IN: Identifier for the destination datatype.

**Returns:**

Returns TRUE for compiler conversion, FALSE for library conversion, FAIL for the function's failure.

**Fortran90 Interface:** h5tcompiler\_conv\_f

```
SUBROUTINE h5tcompiler_conv_f( src_id, dst_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: src_id ! Id for the source datatype.
  INTEGER(HID_T), INTENT(IN) :: dst_id ! Id for the destination datatype.
  LOGICAL, INTENT(OUT) :: flag          !   .TRUE. for compiler conversion,
                                         !   .FALSE. for library conversion
  INTEGER, INTENT(OUT) :: hdferr        ! Error code:
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5tcompiler_conv_f
```

**Name:** H5Tconvert

**Signature:**

```
herr_t H5Tconvert(hid_t src_id, hid_t dst_id, size_t nelmts, void *buf, void *background,
hid_t plist_id)
```

**Purpose:**

Converts data from between specified datatypes.

**Description:**

H5Tconvert converts *nelmts* elements from the type specified by the *src\_id* identifier to type *dst\_id*. The source elements are packed in *buf* and on return the destination will be packed in *buf*. That is, the conversion is performed in place. The optional background buffer is an array of *nelmts* values of destination type which are merged with the converted values to fill in cracks (for instance, *background* might be an array of structs with the *a* and *b* fields already initialized and the conversion of *buf* supplies the *c* and *d* field values).

The parameter *plist\_id* contains the dataset transfer property list identifier which is passed to the conversion functions. As of Release 1.2, this parameter is only used to pass along the variable-length datatype custom allocation information.

**Parameters:**

<i>hid_t</i> src_id	Identifier for the source datatype.
<i>hid_t</i> dst_id	Identifier for the destination datatype.
<i>size_t</i> nelmts	Size of array <i>buf</i> .
<i>void</i> *buf	Array containing pre- and post-conversion values.
<i>void</i> *background	Optional background buffer.
<i>hid_t</i> plist_id	Dataset transfer property list identifier.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.3	<i>nelmts</i> parameter type changed to <i>size_t</i> .
1.4.0	<i>nelmts</i> parameter type changed to <i>hsize_t</i> .

**Name:** H5Tcopy

**Signature:**

*hid\_t* H5Tcopy(*hid\_t* dtype\_id)

**Purpose:**

Copies an existing datatype.

**Description:**

H5Tcopy copies an existing datatype. The returned type is always transient and unlocked.

The dtype\_id argument can be either a datatype identifier, a predefined datatype (defined in H5Tpublic.h), or a dataset identifier. If dtype\_id is a dataset identifier instead of a datatype identifier, then this function returns a transient, modifiable datatype which is a copy of the dataset's datatype.

The datatype identifier returned should be released with H5Tclose or resource leaks will occur.

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to copy. Can be a datatype identifier, a predefined datatype (defined in H5Tpublic.h), or a dataset identifier.

**Returns:**

Returns a datatype identifier if successful; otherwise returns a negative value

**Fortran90 Interface:** h5tcopy\_f

```
SUBROUTINE h5tcopy_f(type_id, new_type_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id      ! Datatype identifier
  INTEGER(HID_T), INTENT(OUT) :: new_type_id ! Identifier of datatype's copy
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5tcopy_f
```

**Name:** H5Tcreate

**Signature:**

```
hid_t H5Tcreate(H5T_class_t class, size_t size )
```

**Purpose:**

Creates a new datatype.

**Description:**

H5Tcreate creates a new datatype of the specified class with the specified number of bytes.

The following datatype classes are supported with this function:

```
◇ H5T_COMPOUND
◇ H5T_OPAQUE
◇ H5T_ENUM
```

Use H5Tcopy to create integer or floating-point datatypes.

The datatype identifier returned from this function should be released with H5Tclose or resource leaks will result.

**Parameters:**

<i>H5T_class_t</i> class	Class of datatype to create.
<i>size_t</i> size	The number of bytes in the datatype to create.

**Returns:**

Returns datatype identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tcreate\_f

```
SUBROUTINE h5tcreate_f(class, size, type_id, hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(IN) :: class                ! Datatype class can be one of
                                              !   H5T_COMPOUND_F (6)
                                              !   H5T_ENUM_F      (8)
                                              !   H5T_OPAQUE_F    (9)

  INTEGER(SIZE_T), INTENT(IN) :: size         ! Size of the datatype
  INTEGER(HID_T), INTENT(OUT) :: type_id      ! Datatype identifier
  INTEGER, INTENT(OUT) :: hdferr              ! Error code
                                              ! 0 on success and -1 on failure

END SUBROUTINE h5tcreate_f
```



**Name:** H5Tdecode

**Signature:**

*hid\_t* H5Tdecode (*unsigned char* \*buf)

**Purpose:**

Decode a binary object description of data type and return a new object handle.

**Description:**

Given an object description of data type in binary in a buffer, H5Tdecode reconstructs the HDF5 data type object and returns a new object handle for it. The binary description of the object is encoded by H5Tencode. User is responsible for passing in the right buffer.

**Parameters:**

*unsigned char* \*buf     IN: Buffer for the data type object to be decoded.

**Returns:**

Returns an object ID(non-negative) if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tdecode\_f

```
SUBROUTINE h5tdecode_f(buf, obj_id, hdferr)
  IMPLICIT NONE
  CHARACTER(LEN=*) , INTENT(IN) :: buf   ! Data space object buffer to be decoded
  INTEGER(HID_T) , INTENT(OUT) :: obj_id ! Object ID
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5tdecode_f
```

**Name:** H5Tdetect\_class

**Signature:**

*htri\_t* H5Tdetect\_class(*hid\_t* dtype\_id, *H5T\_class\_t* dtype\_class )

**Purpose:**

Determines whether a datatype contains any datatypes of the given datatype class.

**Description:**

H5Tdetect\_class determines whether the datatype specified in *dtype\_id* contains any datatypes of the datatype class specified in *dtype\_class*.

This function is useful primarily in recursively examining all the fields and/or base types of compound, array, and variable-length datatypes.

Valid class identifiers are as defined in H5Tget\_class.

**Parameters:**

*hid\_t* dtype\_id                      Datatype identifier.

*H5T\_class\_t* dtype\_class          Datatype class.

**Returns:**

Returns TRUE or FALSE if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
---------	---

1.6.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Tencode

**Signature:**

*herr\_t* H5Tencode(*hid\_t* obj\_id, *unsigned char* \*buf, *size\_t* \*nalloc)

**Purpose:**

Encode a data type object description into a binary buffer.

**Description:**

Given data type ID, H5Tencode converts a data type description into binary form in a buffer. Using this binary form in the buffer, a data type object can be reconstructed using H5Tdecode to return a new object handle (*hid\_t*) for this data type.

A preliminary H5Tencode call can be made to find out the size of the buffer needed. This value is returned as *nalloc*. That value can then be assigned to *nalloc* for a second H5Tencode call, which will retrieve the actual encoded object.

If the library finds out *nalloc* is not big enough for the object, it simply returns the size of the buffer needed through *nalloc* without encoding the provided buffer.

**Parameters:**

<i>hid_t</i> obj_id	IN: Identifier of the object to be encoded.
<i>unsigned char</i> *buf	IN/OUT: Buffer for the object to be encoded into. If the provided buffer is NULL, only the size of buffer needed is returned through <i>nalloc</i> .
<i>size_t</i> *nalloc	IN: The size of the allocated buffer. OUT: The size of the buffer needed.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tencode\_f

```

SUBROUTINE h5tencode_f(obj_id, buf, nalloc, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: obj_id ! Identifier of the object to be encoded
  CHARACTER(LEN=*), INTENT(OUT) :: buf ! Buffer object to be encoded into
  INTEGER(SIZE_T), INTENT(INOUT) :: nalloc
                                     ! The size of the allocated buffer
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
                                     ! 0 on success and -1 on failure
END SUBROUTINE h5tencode_f

```

**Name:** H5Tenum\_create

**Signature:**

*hid\_t* H5Tenum\_create(*hid\_t* parent\_id)

**Purpose:**

Creates a new enumeration datatype.

**Description:**

H5Tenum\_create creates a new enumeration datatype based on the specified base datatype, parent\_id, which must be an integer type.

**Parameters:**

*hid\_t* parent\_id      IN: Datatype identifier for the base datatype.

**Returns:**

Returns the datatype identifier for the new enumeration datatype if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tenum\_create\_f

```
SUBROUTINE h5tenum_create_f(parent_id, new_type_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: parent_id      ! Datatype identifier for
                                                ! the base datatype
  INTEGER(HID_T), INTENT(OUT) :: new_type_id    ! Datatype identifier for the
                                                ! new enumeration datatype
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
END SUBROUTINE h5tenum_create_f
```

**Name:** H5Tenum\_insert

**Signature:**

```
herr_t H5Tenum_insert(hid_t dtype_id, const char *name, void *value )
```

**Purpose:**

Inserts a new enumeration datatype member.

**Description:**

H5Tenum\_insert inserts a new enumeration datatype member into an enumeration datatype.

dtype\_id is the enumeration datatype, name is the name of the new member, and value points to the value of the new member.

name and value must both be unique within dtype\_id.

value points to data which is of the datatype defined when the enumeration datatype was created.

**Parameters:**

<i>hid_t</i> dtype_id	IN: Datatype identifier for the enumeration datatype.
<i>const char</i> *name	IN: Name of the new member.
<i>void</i> *value	IN: Pointer to the value of the new member.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tenum\_insert\_f

```
SUBROUTINE h5tenum_insert_f(dtype_id,  name, value, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dtype_id ! Datatype identifier
  CHARACTER(LEN=*), INTENT(IN) :: name  ! Name of the new member
  INTEGER, INTENT(IN) :: value          ! Value of the new member
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tenum_insert_f
```

**Name:** H5Tenum\_nameof

**Signature:**

```
herr_t H5Tenum_nameof( hid_t dtype_id, void *value, char *name, size_t size )
```

**Purpose:**

Returns the symbol name corresponding to a specified member of an enumeration datatype.

**Description:**

H5Tenum\_nameof finds the symbol name that corresponds to the specified value of the enumeration datatype dtype\_id.

At most *size* characters of the symbol name are copied into the name buffer. If the entire symbol name and null terminator do not fit in the name buffer, then as many characters as possible are copied (not null terminated) and the function fails.

**Parameters:**

<i>hid_t</i> dtype_id	IN: Enumeration datatype identifier.
<i>void</i> *value	IN: Value of the enumeration datatype.
<i>char</i> *name	OUT: Buffer for output of the symbol name.
<i>size_t</i> size	IN: Anticipated size of the symbol name, in bytes (characters).

**Returns:**

Returns a non-negative value if successful. Otherwise returns a negative value and, if *size* allows it, the first character of *name* is set to NULL.

**Fortran90 Interface:** h5tenum\_nameof\_f

```
SUBROUTINE h5tenum_nameof_f(type_id, value, namelen, name, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(IN) :: value ! Value of the enumeration datatype
  INTEGER(SIZE_T), INTENT(IN) :: namelen ! Length of the name
  CHARACTER(LEN=*), INTENT(OUT) :: name ! Name of the enumeration datatype
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tenum_nameof_f
```

**Name:** H5Tenum\_valueof

**Signature:**

```
herr_t H5Tenum_valueof( hid_t dtype_id, char *name, void *value )
```

**Purpose:**

Returns the value corresponding to a specified member of an enumeration datatype.

**Description:**

H5Tenum\_valueof finds the value that corresponds to the specified name of the enumeration datatype dtype\_id.

The value argument should be at least as large as the value of H5Tget\_size( type ) in order to hold the result.

**Parameters:**

<i>hid_t</i> dtype_id	IN: Enumeration datatype identifier.
<i>const char</i> *name	IN: Symbol name of the enumeration datatype.
<i>void</i> *value	OUT: Buffer for output of the value of the enumeration datatype.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tenum\_valueof\_f

```
SUBROUTINE h5tenum_valueof_f(type_id,  name, value, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  CHARACTER(LEN=*), INTENT(IN) :: name  ! Name of the enumeration datatype
  INTEGER, INTENT(OUT) :: value         ! Value of the enumeration datatype
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tenum_valueof_f
```

**Name:** H5Tequal

**Signature:**

*htri\_t* H5Tequal( *hid\_t* dtype\_id1, *hid\_t* dtype\_id2 )

**Purpose:**

Determines whether two datatype identifiers refer to the same datatype.

**Description:**

H5Tequal determines whether two datatype identifiers refer to the same datatype.

**Parameters:**

*hid\_t* dtype\_id1            Identifier of datatype to compare.

*hid\_t* dtype\_id2            Identifier of datatype to compare.

**Returns:**

When successful, returns a positive value, for TRUE, if the datatype identifiers refer to the same datatype, or 0 (zero), for FALSE. Otherwise returns a negative value.

**Fortran90 Interface:** h5tequal\_f

```
SUBROUTINE h5tequal_f(type1_id, type2_id, flag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type1_id ! Datatype identifier
  INTEGER(HID_T), INTENT(IN) :: type2_id ! Datatype identifier
  LOGICAL, INTENT(OUT) :: flag           ! TRUE/FALSE flag to indicate
                                         ! if two datatypes are equal
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
END SUBROUTINE h5tequal_f
```



**Name:** H5Tfind

**Signature:**

*H5T\_conv\_t* H5Tfind(*hid\_t* src\_id, *hid\_t* dst\_id, *H5T\_cdata\_t* \*\*pcdata )

**Purpose:**

Finds a conversion function.

**Description:**

H5Tfind finds a conversion function that can handle a conversion from type src\_id to type dst\_id. The pcdata argument is a pointer to a pointer to type conversion data which was created and initialized by the soft type conversion function of this path when the conversion function was installed on the path.

**Parameters:**

<i>hid_t</i> src_id	IN: Identifier for the source datatype.
<i>hid_t</i> dst_id	IN: Identifier for the destination datatype.
<i>H5T_cdata_t</i> **pcdata	OUT: Pointer to type conversion data.

**Returns:**

Returns a pointer to a suitable conversion function if successful. Otherwise returns NULL.

**Fortran90 Interface:**

None.

**Name:** H5Tget\_array\_dims

**Signatures:**

```
int H5Tget_array_dims( hid_t adtype_id, hsize_t dims[ ],           [1]
int perm[ ] )
int H5Tget_array_dims( hid_t adtype_id, hsize_t dims[ ] )       [2]
```

**Purpose:**

Retrieves sizes of array dimensions.

**Description:**

H5Tget\_array\_dims is a macro that is mapped to either H5Tget\_array\_dims1 or H5Tget\_array\_dims2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. For example:

- ◇ The H5Tget\_array\_dims macro will be mapped to H5Tget\_array\_dims1 and will use the H5Tget\_array\_dims1 syntax (first signature above) if an application is coded for HDF5 Release 1.6.x.
- ◇ The H5Tget\_array\_dims macro mapped to H5Tget\_array\_dims2 and will use the H5Tget\_array\_dims2 syntax (second signature above) if an application is coded for HDF5 Release 1.8.x.

Macro use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Tget\_array\_dims is mapped to the most recent version of the function, currently H5Tget\_array\_dims2. If the library and/or application is compiled for Release 1.6 emulation, H5Tget\_array\_dims will be mapped to H5Tget\_array\_dims1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Tget_array_dims mapping
<u>Global settings</u>	
No compatibility flag	H5Tget_array_dims2
Enable deprecated symbols	H5Tget_array_dims2
Disable deprecated symbols	H5Tget_array_dims2
Emulate Release 1.6 interface	H5Tget_array_dims1
<u>Function-level macros</u>	
H5Tget_array_dims_vers = 2	H5Tget_array_dims2
H5Tget_array_dims_vers = 1	H5Tget_array_dims1

**Interface history:** Signature [1] above is the original H5Tget\_array\_dims interface and the only interface available prior to HDF5 Release 1.8.0. This signature and the corresponding function are now deprecated but will remain directly callable as H5Tget\_array\_dims1.

Signature [2] above was introduced with HDF5 Release 1.8.0 and is the recommended and default interface. It is directly callable as H5Tget\_array\_dims2.

See “API Compatibility Macros in HDF5” for circumstances under which either of these functions might not be available in an installed instance of the HDF5 Library.

**Fortran90 Interface: h5tarray\_create\_f**

```
SUBROUTINE h5tarray_create_f(base_id, rank, dims, type_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: base_id    ! Identifier of array base datatype
  INTEGER, INTENT(IN)       :: rank       ! Rank of the array
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(IN) :: dims
                                           ! Sizes of each array dimension
  INTEGER(HID_T), INTENT(OUT) :: type_id  ! Identifier of the array datatype
  INTEGER, INTENT(OUT)       :: hdferr    ! Error code
END SUBROUTINE h5tarray_create_f
```

**History:**

Release	C
1.8.0	<p>The function H5Tget_array_dims renamed to H5Tget_array_dims1 and deprecated in this release.</p> <p>The macro H5Tget_array_dims and the function H5Tget_array_dims2 introduced in this release.</p>

**Name:** H5Tget\_array\_dims1

**Signature:**

```
int H5Tget_array_dims1( hid_t adtype_id, hsize_t dims[ ], int perm[ ] )
```

**Purpose:**

Retrieves sizes of array dimensions.

**Notice:**

*This function is renamed from H5Tget\_array\_dims and deprecated in favor of the function H5Tget\_array\_dims2 or the new macro H5Tget\_array\_dims.*

**Description:**

H5Tget\_array\_dims1 returns the sizes of the dimensions and the dimension permutations of the specified array datatype object.

The sizes of the dimensions are returned in the array dims.

The parameter perm is not used.

**Parameters:**

<i>hid_t</i> adtype_id	IN: Datatype identifier of array object.
<i>hsize_t</i> dims[ ]	OUT: Sizes of array dimensions.
<i>int</i> perm[ ]	OUT: Dimension permutations. (This parameter is not used.)

**Returns:**

Returns the non-negative number of dimensions of the array type if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_array\_dims\_f

```
SUBROUTINE h5tget_array_dims_f(type_id, dims, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id      ! Identifier of the array datatype
  INTEGER(HSIZE_T), DIMENSION(*), INTENT(OUT) :: dims
  ! Buffer to store array datatype
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
END SUBROUTINE h5tget_array_dims_f
```

**History:**

Release	C
1.4.0	Function introduced in this release.
1.8.0	The function H5Tget_array_dims renamed to H5Tget_array_dims1 and deprecated in this release.

**Name:** H5Tget\_array\_dims2

**Signature:**

*int* H5Tget\_array\_dims2( *hid\_t* adtype\_id, *hsize\_t* dims[ ] )

**Purpose:**

Retrieves sizes of array dimensions.

**Description:**

H5Tget\_array\_dims2 returns the sizes of the dimensions of the specified array datatype object.

The sizes of the dimensions are returned in the array `dims`.

**Parameters:**

*hid\_t* adtype\_id           IN: Datatype identifier of array object.

*hsize\_t* dims[ ]           OUT: Sizes of array dimensions.

**Returns:**

Returns the non-negative number of dimensions of the array type if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Tget\_array\_ndims

**Signature:**

*int* H5Tget\_array\_ndims(*hid\_t* adtype\_id)

**Purpose:**

Returns the rank of an array datatype.

**Description:**

H5Tget\_array\_ndims returns the rank, the number of dimensions, of an array datatype object.

**Parameters:**

*hid\_t* adtype\_id      IN: Datatype identifier of array object.

**Returns:**

Returns the rank of the array if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_array\_ndims\_f

```
SUBROUTINE h5tget_array_ndims_f(type_id, ndims, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id  ! Identifier of the array datatype
  INTEGER, INTENT(OUT)      :: ndims    ! Number of array dimensions
  INTEGER, INTENT(OUT)      :: hdferr   ! Error code
END SUBROUTINE h5tget_array_ndims_f
```

**History:**

Release	C
---------	---

1.4.0	Function introduced in this release.
-------	--------------------------------------

**Name:** H5Tget\_class

**Signature:**

```
H5T_class_t H5Tget_class( hid_t dtype_id )
```

**Purpose:**

Returns the datatype class identifier.

**Description:**

H5Tget\_class returns the datatype class identifier.

Valid class identifiers, as defined in `H5Tpublic.h`, are:

```

◇ H5T_INTEGER
◇ H5T_FLOAT
◇ H5T_STRING
◇ H5T_BITFIELD
◇ H5T_OPAQUE
◇ H5T_COMPOUND
◇ H5T_REFERENCE
◇ H5T_ENUM
◇ H5T_VLEN
◇ H5T_ARRAY

```

Note that the library returns H5T\_STRING for both fixed-length and variable-length strings.

*Unsupported datatype:* The time datatype class, H5T\_TIME, is not supported. If H5T\_TIME is used, the resulting data will be readable and modifiable only on the originating computing platform; it will not be portable to other platforms.

**Parameters:**

`hid_t dtype_id`      Identifier of datatype to query.

**Returns:**

Returns datatype class identifier if successful; otherwise H5T\_NO\_CLASS (-1).

**Fortran90 Interface:** h5tget\_class\_f

```

SUBROUTINE h5tget_class_f(type_id, class, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id  ! Datatype identifier
  INTEGER, INTENT(OUT) :: class          ! Datatype class, possible values are:
                                          !   H5T_NO_CLASS_F
                                          !   H5T_INTEGER_F
                                          !   H5T_FLOAT_F

                                          !   H5T_STRING_F
                                          !   H5T_BITFIELD_F
                                          !   H5T_OPAQUE_F
                                          !   H5T_COMPOUND_F
                                          !   H5T_REFERENCE_F
                                          !   H5T_ENUM_F

  INTEGER, INTENT(OUT) :: hdferr          ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5tget_class_f

```

**Name:** H5Tget\_create\_plist

**Signature:**

*hid\_t* H5Tget\_create\_plist(*hid\_t* dtype\_id)

**Purpose:**

Returns a copy of a datatype creation property list.

**Description:**

H5Tget\_create\_plist returns a property list identifier for the datatype creation property list associated with the datatype specified by dtype\_id.

The creation property list identifier should be released with H5Pclose.

**Parameter:**

*hid\_t* dtype\_id    IN: Datatype identifier.

**Returns:**

Returns a datatype property list identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_create\_plist\_f

```
SUBROUTINE h5tget_create_plist_f(dtype_id, dtpl_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dtype_id ! Datatype identifier
  INTEGER(HID_T), INTENT(OUT) :: dtpl_id ! Datatype property list identifier.
  INTEGER, INTENT(OUT) :: hdferr          ! Error code:
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5tget_create_plist_f
```

**History:**

Release	C
---------	---

1.8.0	Function introduced in this release.
-------	--------------------------------------



**Name:** H5Tget\_cset

**Signature:**

*H5T\_cset\_t* H5Tget\_cset( *hid\_t* dtype\_id )

**Purpose:**

Retrieves the character set type of a string datatype.

**Description:**

H5Tget\_cset retrieves the character set type of a string datatype. Valid character set types are:

H5T\_CSET\_ASCII (0) Character set is US ASCII.

**Parameters:**

*hid\_t* dtype\_id Identifier of datatype to query.

**Returns:**

Returns a valid character set type if successful; otherwise H5T\_CSET\_ERROR (-1).

**Fortran90 Interface:** h5tget\_cset\_f

```
SUBROUTINE h5tget_cset_f(type_id, cset, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(OUT) :: cset           ! Character set type of a string
                                          ! datatype
                                          ! Possible values of padding type are:
                                          !   H5T_CSET_ASCII_F = 0
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tget_cset_f
```

**Name:** H5Tget\_ebias

**Signature:**

*size\_t* H5Tget\_ebias(*hid\_t* dtype\_id)

**Purpose:**

Retrieves the exponent bias of a floating-point type.

**Description:**

H5Tget\_ebias retrieves the exponent bias of a floating-point type.

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to query.

**Returns:**

Returns the bias if successful; otherwise 0.

**Fortran90 Interface:** h5tget\_ebias\_f

```
SUBROUTINE h5tget_ebias_f(type_id, ebias, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER(SIZE_T), INTENT(OUT) :: ebias ! Datatype exponent bias
                                         ! of a floating-point type
  INTEGER, INTENT(OUT) :: hdferr      ! Error code
END SUBROUTINE h5tget_ebias_f
```

**Name:** H5Tget\_fields

**Signature:**

```
herr_t H5Tget_fields( hid_t dtype_id, size_t *spos, size_t *epos, size_t *esize, size_t
    *mpos, size_t *msize )
```

**Purpose:**

Retrieves floating point datatype bit field information.

**Description:**

H5Tget\_fields retrieves information about the locations of the various bit fields of a floating point datatype. The field positions are bit positions in the significant region of the datatype. Bits are numbered with the least significant bit number zero. Any (or even all) of the arguments can be null pointers.

**Parameters:**

<i>hid_t</i> dtype_id	IN: Identifier of datatype to query.
<i>size_t</i> *spos	OUT: Pointer to location to return floating-point sign bit.
<i>size_t</i> *epos	OUT: Pointer to location to return exponent bit-position.
<i>size_t</i> *esize	OUT: Pointer to location to return size of exponent in bits.
<i>size_t</i> *mpos	OUT: Pointer to location to return mantissa bit-position.
<i>size_t</i> *msize	OUT: Pointer to location to return size of mantissa in bits.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_fields\_f

```
SUBROUTINE h5tget_fields_f(type_id, spos, epos, esize, mpos, msize, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER(SIZE_T), INTENT(OUT) :: spos ! sign bit-position
  INTEGER(SIZE_T), INTENT(OUT) :: epos ! exponent bit-position
  INTEGER(SIZE_T), INTENT(OUT) :: esize ! size of exponent in bits
  INTEGER(SIZE_T), INTENT(OUT) :: mpos ! mantissa bit-position
  INTEGER(SIZE_T), INTENT(OUT) :: msize ! size of mantissa in bits
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tget_fields_f
```

**Name:** H5Tget\_inpad

**Signature:**

*H5T\_pad\_t* H5Tget\_inpad( *hid\_t* dtype\_id )

**Purpose:**

Retrieves the internal padding type for unused bits in floating-point datatypes.

**Description:**

H5Tget\_inpad retrieves the internal padding type for unused bits in floating-point datatypes. Valid padding types are:

H5T\_PAD\_ZERO (0)

Set background to zeros.

H5T\_PAD\_ONE (1)

Set background to ones.

H5T\_PAD\_BACKGROUND (2)

Leave background alone.

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to query.

**Returns:**

Returns a valid padding type if successful; otherwise H5T\_PAD\_ERROR (-1).

**Fortran90 Interface:** h5tget\_inpad\_f

```
SUBROUTINE h5tget_inpad_f(type_id, padtype, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(OUT) :: padtype       ! Padding type for unused bits
                                         ! in floating-point datatypes
                                         ! Possible values of padding type are:
                                         !   H5T_PAD_ZERO_F = 0
                                         !   H5T_PAD_ONE_F = 1
                                         !   H5T_PAD_BACKGROUND_F = 2
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tget_inpad_f
```

**Name:** H5Tget\_member\_class

**Signature:**

*H5T\_class\_t* H5Tget\_member\_class( *hid\_t* cdtype\_id, *unsigned* member\_no )

**Purpose:**

Returns datatype class of compound datatype member.

**Description:**

Given a compound datatype, *cdtype\_id*, the function H5Tget\_member\_class returns the datatype class of the compound datatype member specified by *member\_no*.

Valid class identifiers are as defined in H5Tget\_class.

**Parameters:**

*hid\_t* cdtype\_id      IN: Datatype identifier of compound object.

*unsigned* member\_no    IN: Compound object member number.

**Returns:**

Returns the datatype class, a non-negative value, if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_member\_class\_f

```
SUBROUTINE h5tget_member_class_f(type_id, member_no, class, hdferr)
  INTEGER(HID_T), INTENT(IN) :: type_id      ! Datatype identifier
  INTEGER, INTENT(IN) :: member_no          ! Member number
  INTEGER, INTENT(OUT) :: class              ! Member class
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
END SUBROUTINE h5tget_member_class_f
```

**History:**

**Release    C**

1.6.4      membno parameter type changed to *unsigned*.

**Name:** H5Tget\_member\_index

**Signature:**

```
int H5Tget_member_index( hid_t dtype_id, const char * field_name )
```

**Purpose:**

Retrieves the index of a compound or enumeration datatype member.

**Description:**

H5Tget\_member\_index retrieves the index of a field of a compound datatype or an element of an enumeration datatype.

The name of the target field or element is specified in `field_name`.

Fields are stored in no particular order with index values of 0 through  $N-1$ , where  $N$  is the value returned by H5Tget\_nmembers.

**Parameters:**

<code>hid_t dtype_id</code>	Identifier of datatype to query.
<code>const char * field_name</code>	Name of the field or member whose index is to be retrieved.

**Returns:**

Returns a valid field or member index if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_member\_index\_f

```
SUBROUTINE h5tget_member_index_f(type_id, name, index, hdferr)
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  CHARACTER(LEN=*), INTENT(IN) :: name ! Member name
  INTEGER, INTENT(OUT) :: index ! Member index
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tget_member_index_f
```

**History:**

Release	C	Fortran90
1.4.5		Function introduced in this release.
1.4.4	Function introduced in this release.	

**Name:** H5Tget\_member\_name

**Signature:**

```
char *H5Tget_member_name( hid_t dtype_id, unsigned field_idx )
```

**Purpose:**

Retrieves the name of a compound or enumeration datatype member.

**Description:**

H5Tget\_member\_name retrieves the name of a field of a compound datatype or an element of an enumeration datatype.

The index of the target field or element is specified in `field_idx`. Compound datatype fields and enumeration datatype elements are stored in no particular order with index values of 0 through  $N-1$ , where  $N$  is the value returned by H5Tget\_nmembers.

A buffer to receive the name of the field is allocated with `malloc()` and the caller is responsible for freeing the memory used.

**Parameters:**

`hid_t dtype_id` Identifier of datatype to query.

`unsigned field_idx` Zero-based index of the field or element whose name is to be retrieved.

**Returns:**

Returns a valid pointer to a string allocated with `malloc()` if successful; otherwise returns NULL.

**Fortran90 Interface:** h5tget\_member\_name\_f

```
SUBROUTINE h5tget_member_name_f(type_id,index, member_name, namelen, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id          ! Datatype identifier
  INTEGER, INTENT(IN) :: index                  ! Field index (0-based) of
                                                ! the field name to retrieve
  CHARACTER(LEN=*), INTENT(OUT) :: member_name ! Name of a field of
                                                ! a compound datatype
  INTEGER, INTENT(OUT) :: namelen               ! Length of the name
  INTEGER, INTENT(OUT) :: hdferr                ! Error code
END SUBROUTINE h5tget_member_name_f
```

**History:**

**Release**    **C**

1.6.4        membno parameter type changed to *unsigned*.

**Name:** H5Tget\_member\_offset

**Signature:**

```
size_t H5Tget_member_offset( hid_t dtype_id, unsigned memb_no )
```

**Purpose:**

Retrieves the offset of a field of a compound datatype.

**Description:**

H5Tget\_member\_offset retrieves the byte offset of the beginning of a field within a compound datatype with respect to the beginning of the compound data type datum.

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to query.  
*unsigned* memb\_no      Number of the field whose offset is requested.

**Returns:**

Returns the byte offset of the field if successful; otherwise returns 0 (zero). Note that zero is a valid offset and that this function will fail only if a call to H5Tget\_member\_class( ) fails with the same arguments.

**Fortran90 Interface:** h5tget\_member\_offset\_f

```
SUBROUTINE h5tget_member_offset_f(type_id, member_no, offset, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id      ! Datatype identifier
  INTEGER, INTENT(IN) :: member_no          ! Number of the field
                                              ! whose offset is requested
  INTEGER(SIZE_T), INTENT(OUT) :: offset     ! Byte offset of the the
                                              ! beginning of the field
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
END SUBROUTINE h5tget_member_offset_f
```

**History:**

<b>Release</b>	<b>C</b>
1.6.4	membno parameter type changed to <i>unsigned</i> .



**Name:** H5Tget\_member\_type

**Signature:**

```
hid_t H5Tget_member_type( hid_t dtype_id, unsigned field_idx )
```

**Purpose:**

Returns the datatype of the specified member.

**Description:**

H5Tget\_member\_type returns the datatype of the specified member. The caller should invoke H5Tclose() to release resources associated with the type.

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to query.

*unsigned* field\_idx   Field index (0-based) of the field type to retrieve.

**Returns:**

Returns the identifier of a copy of the datatype of the field if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_member\_type\_f

```
SUBROUTINE h5tget_member_type_f(type_id,  field_idx, datatype, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id    ! Datatype identifier
  INTEGER, INTENT(IN) :: field_idx         ! Field index (0-based) of the
                                           ! field type to retrieve
  INTEGER(HID_T), INTENT(OUT) :: datatype ! Identifier of a copy of
                                           ! the datatype of the field
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
END SUBROUTINE h5tget_member_type_f
```

**History:**

**Release    C**

1.6.4      membno parameter type changed to *unsigned*.

**Name:** H5Tget\_member\_value

**Signature:**

```
herr_t H5Tget_member_value( hid_t dtype_id unsigned memb_no, void *value )
```

**Purpose:**

Returns the value of an enumeration datatype member.

**Description:**

H5Tget\_member\_value returns the value of the enumeration datatype member `memb_no`.

The member value is returned in a user-supplied buffer pointed to by `value`.

**Parameters:**

<i>hid_t</i> dtype_id	IN: Datatype identifier for the enumeration datatype.
<i>unsigned</i> memb_no	IN: Number of the enumeration datatype member.
void *value	OUT: Pointer to a buffer for output of the value of the enumeration datatype member.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_member\_value\_f

```
SUBROUTINE h5tget_member_value_f(type_id,  member_no, value, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(IN) :: member_no      ! Number of the enumeration
                                         ! datatype member
  INTEGER, INTENT(OUT) :: value          ! Value of the enumeration datatype
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tget_member_value_f
```

**History:**

Release	C
1.6.4	membno parameter type changed to <i>unsigned</i> .

**Name:** H5Tget\_native\_type

**Signature:**

```
hid_t H5Tget_native_type(hid_t dtype_id, H5T_direction_t direction)
```

**Purpose:**

Returns the native datatype of a specified datatype.

**Description:**

H5Tget\_native\_type returns the equivalent native datatype for the datatype specified in dtype\_id.

H5Tget\_native\_type is a high-level function designed primarily to facilitate use of the H5Dread function, for which users otherwise must undertake a multi-step process to determine the native datatype of a dataset prior to reading it into memory. It can be used not only to determine the native datatype for atomic datatypes, but also to determine the native datatypes of the individual components of a compound datatype, an enumerated datatype, an array datatype, or a variable-length datatype. For example, if dtype\_id is a compound datatype, the returned datatype identifier will be for a similar compound datatype with each element converted to the corresponding native datatype.

H5Tget\_native\_type selects the matching native datatype from the following list:

```
H5T_NATIVE_CHAR
H5T_NATIVE_SHORT
H5T_NATIVE_INT
H5T_NATIVE_LONG
H5T_NATIVE_LLONG

H5T_NATIVE_UCHAR
H5T_NATIVE_USHORT
H5T_NATIVE_UINT
H5T_NATIVE_ULONG
H5T_NATIVE_ULLONG

H5T_NATIVE_FLOAT
H5T_NATIVE_DOUBLE
H5T_NATIVE_LDOUBLE
```

The direction parameter indicates the order in which the library searches for a native datatype match. Valid values for direction are as follows:

H5T_DIR_ASCEND	Searches the above list in ascending size of the datatype, i.e., from top to bottom. (Default)
H5T_DIR_DESCEND	Searches the above list in descending size of the datatype, i.e., from bottom to top.

H5Tget\_native\_type is designed primarily for use with integer and floating point datatypes. String, time, bitfield, opaque, and reference datatypes are returned as a copy of dtype\_id.

The identifier returned by H5Tget\_native\_type should eventually be closed by calling H5Tclose to release resources.

**Parameters:**

<i>hid_t</i> dtype_id	Datatype identifier for the dataset datatype.
<i>H5T_direction_t</i> direction	Direction of search.

**Returns:**

Returns the native datatype identifier for the specified dataset datatype if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_native\_type\_f

```

SUBROUTINE h5tget_native_type_f(dtype_id, direction, native_dtype_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: dtype_id
                                ! Datatype identifier
  INTEGER, INTENT(IN) :: direction ! Direction of search:
                                ! H5T_DIR_ASCEND_F = 1 in inscendent order
                                ! H5T_DIR_DESCEND_F= 2 in descendent order
  INTEGER(HID_T), INTENT(OUT) :: native_dtype_id
                                ! The native datatype identifier
  INTEGER, INTENT(OUT) :: hdferr ! Error code:
                                ! 0 on success and -1 on failure
END SUBROUTINE h5tget_native_type_f

```

**History:**

Release	C
1.6.0	Function introduced in this release.

**Name:** H5Tget\_nmembers

**Signature:**

*int* H5Tget\_nmembers( *hid\_t* dtype\_id )

**Purpose:**

Retrieves the number of elements in a compound or enumeration datatype.

**Description:**

H5Tget\_nmembers retrieves the number of fields in a compound datatype or the number of members of an enumeration datatype.

**Parameters:**

*hid\_t* dtype\_id          Identifier of datatype to query.

**Returns:**

Returns the number of elements if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_nmembers\_f

```
SUBROUTINE h5tget_nmembers_f(type_id, num_members, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(OUT) :: num_members ! Number of fields in a
                                     ! compound datatype
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tget_nmembers_f
```

**Name:** H5Tget\_norm

**Signature:**

*H5T\_norm\_t* H5Tget\_norm(*hid\_t* dtype\_id)

**Purpose:**

Retrieves mantissa normalization of a floating-point datatype.

**Description:**

H5Tget\_norm retrieves the mantissa normalization of a floating-point datatype. Valid normalization types are:

H5T\_NORM\_IMPLIED (0)  
 MSB of mantissa is not stored, always 1  
 H5T\_NORM\_MSBSET (1)  
 MSB of mantissa is always 1  
 H5T\_NORM\_NONE (2)  
 Mantissa is not normalized

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to query.

**Returns:**

Returns a valid normalization type if successful; otherwise H5T\_NORM\_ERROR (-1).

**Fortran90 Interface:** h5tget\_norm\_f

```
SUBROUTINE h5tget_norm_f(type_id, norm, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id
                                ! Datatype identifier
  INTEGER, INTENT(OUT) :: norm  ! Mantissa normalization of a
                                ! floating-point datatype
                                ! Valid normalization types are:
                                !   H5T_NORM_IMPLIED_F(0)
                                !     MSB of mantissa is not
                                !     stored, always 1
                                !   H5T_NORM_MSBSET_F(1)
                                !     MSB of mantissa is always 1
                                !   H5T_NORM_NONE_F(2)
                                !     Mantissa is not normalized
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tget_norm_f
```

**Name:** H5Tget\_offset

**Signature:**

```
int H5Tget_offset( hid_t dtype_id )
```

**Purpose:**

Retrieves the bit offset of the first significant bit.

**Description:**

H5Tget\_offset retrieves the bit offset of the first significant bit. The significant bits of an atomic datum can be offset from the beginning of the memory for that datum by an amount of padding. The 'offset' property specifies the number of bits of padding that appear to the "right of" the value. That is, if we have a 32-bit datum with 16-bits of precision having the value 0x1122 then it will be laid out in memory as (from small byte address toward larger byte addresses):

Byte Position	Big-Endian Offset=0	Big-Endian Offset=16	Little-Endian Offset=0	Little-Endian Offset=16
0:	[ pad]	[0x11]	[0x22]	[ pad]
1:	[ pad]	[0x22]	[0x11]	[ pad]
2:	[0x11]	[ pad]	[ pad]	[0x22]
3:	[0x22]	[ pad]	[ pad]	[0x11]

**Parameters:**

*hid\_t dtype\_id* Identifier of datatype to query.

**Returns:**

Returns an offset value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_offset\_f

```
SUBROUTINE h5tget_offset_f(type_id, offset, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER(SIZE_T), INTENT(OUT) :: offset ! Datatype bit offset of the
                                         ! first significant bit
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tget_offset_f
```

**Name:** H5Tget\_order

**Signature:**

*H5T\_order\_t* H5Tget\_order( *hid\_t* dtype\_id )

**Purpose:**

Returns the byte order of an atomic datatype.

**Description:**

H5Tget\_order returns the byte order of an atomic datatype.

Possible return values are:

H5T_ORDER_LE (0)	Little-endian byte order
H5T_ORDER_BE (1)	Big-endian byte order
H5T_ORDER_VAX (2)	VAX mixed byte order (not currently supported)
H5T_ORDER_NONE (3)	No particular order (fixed-length strings, object and region references)

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to query.

**Returns:**

Returns a byte order constant if successful; otherwise H5T\_ORDER\_ERROR (-1).

**Fortran90 Interface:** h5tget\_order\_f

```

SUBROUTINE h5tget_order_f(type_id, order, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(OUT) :: order          ! Datatype byte order
                                          ! Possible values are:
                                          !   H5T_ORDER_LE_F
                                          !   H5T_ORDER_BE_F
                                          !   H5T_ORDER_VAX_F
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5tget_order_f

```



**Name:** H5Tget\_pad

**Signature:**

```
herr_t H5Tget_pad(hid_t dtype_id, H5T_pad_t * lsb, H5T_pad_t * msb)
```

**Purpose:**

Retrieves the padding type of the least and most-significant bit padding.

**Description:**

H5Tget\_pad retrieves the padding type of the least and most-significant bit padding. Valid types are:

H5T\_PAD\_ZERO (0)

Set background to zeros.

H5T\_PAD\_ONE (1)

Set background to ones.

H5T\_PAD\_BACKGROUND (2)

Leave background alone.

**Parameters:**

*hid\_t* dtype\_id            IN: Identifier of datatype to query.

*H5T\_pad\_t* \* lsb           OUT: Pointer to location to return least-significant bit padding type.

*H5T\_pad\_t* \* msb           OUT: Pointer to location to return most-significant bit padding type.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_pad\_f

```
SUBROUTINE h5tget_pad_f(type_id, lsbpad, msbpad, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(OUT) :: lsbpad        ! Padding type of the
                                         ! least significant bit
  INTEGER, INTENT(OUT) :: msbpad        ! Padding type of the
                                         ! most significant bit
                                         ! Possible values of
                                         ! padding type are:
                                         !   H5T_PAD_ZERO_F = 0
                                         !   H5T_PAD_ONE_F = 1
                                         !   H5T_PAD_BACKGROUND_F = 2
                                         !   H5T_PAD_ERROR_F = -1
                                         !   H5T_PAD_NPAD_F = 3
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tget_pad_f
```

**Name:** H5Tget\_precision

**Signature:**

*size\_t* H5Tget\_precision(*hid\_t* dtype\_id)

**Purpose:**

Returns the precision of an atomic datatype.

**Description:**

H5Tget\_precision returns the precision of an atomic datatype. The precision is the number of significant bits which, unless padding is present, is 8 times larger than the value returned by H5Tget\_size.

**Parameters:**

*hid\_t* dtype\_id          Identifier of datatype to query.

**Returns:**

Returns the number of significant bits if successful; otherwise 0.

**Fortran90 Interface:** h5tget\_precision\_f

```
SUBROUTINE h5tget_precision_f(type_id, precision, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id      ! Datatype identifier
  INTEGER(SIZE_T), INTENT(OUT) :: precision ! Datatype precision
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
END SUBROUTINE h5tget_precision_f
```

**Name:** H5Tget\_sign

**Signature:**

*H5T\_sign\_t* H5Tget\_sign( *hid\_t* dtype\_id )

**Purpose:**

Retrieves the sign type for an integer type.

**Description:**

H5Tget\_sign retrieves the sign type for an integer type. Valid types are:

H5T\_SGN\_NONE (0)

Unsigned integer type.

H5T\_SGN\_2 (1)

Two's complement signed integer type.

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to query.

**Returns:**

Returns a valid sign type if successful; otherwise H5T\_SGN\_ERROR (-1).

**Fortran90 Interface:** h5tget\_sign\_f

```
SUBROUTINE h5tget_sign_f(type_id, sign, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id  ! Datatype identifier
  INTEGER, INTENT(OUT) :: sign           ! Sign type for an integer type
                                          ! Possible values are:
                                          !   Unsigned integer type
                                          !       H5T_SGN_NONE_F = 0
                                          !   Two's complement signed
                                          !       integer type
                                          !       H5T_SGN_2_F = 1
                                          !   or error value
                                          !       H5T_SGN_ERROR_F = -1
  INTEGER, INTENT(OUT) :: hdferr         ! Error code
END SUBROUTINE h5tget_sign_f
```

**Name:** H5Tget\_size

**Signature:**

*size\_t* H5Tget\_size( *hid\_t* dtype\_id )

**Purpose:**

Returns the size of a datatype.

**Description:**

H5Tget\_size returns the size of a datatype in bytes.

**Parameters:**

*hid\_t* dtype\_id          Identifier of datatype to query.

**Returns:**

Returns the size of the datatype in bytes if successful; otherwise 0.

**Fortran90 Interface:** h5tget\_size\_f

```
SUBROUTINE h5tget_size_f(type_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER(SIZE_T), INTENT(OUT) :: size ! Datatype size
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                   ! 0 on success and -1 on failure
END SUBROUTINE h5tget_size_f
```

**Name:** H5Tget\_strpad

**Signature:**

*H5T\_str\_t* H5Tget\_strpad(*hid\_t* dtype\_id)

**Purpose:**

Retrieves the storage mechanism for a string datatype.

**Description:**

H5Tget\_strpad retrieves the storage mechanism for a string datatype, as defined in H5Tset\_strpad.

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to query.

**Returns:**

Returns a valid string storage mechanism if successful; otherwise H5T\_STR\_ERROR (-1).

**Fortran90 Interface:** h5tget\_strpad\_f

```
SUBROUTINE h5tget_strpad_f(type_id, strpad, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id
                                ! Datatype identifier
  INTEGER, INTENT(OUT) :: strpad ! String padding method for a string datatype
                                ! Possible values of padding type are:
                                !   Pad with zeros (as C does):
                                !       H5T_STR_NULLPAD_F(0)
                                !   Pad with spaces (as FORTRAN does):
                                !       H5T_STR_SPACEPAD_F(1)
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                ! 0 on success and -1 on failure
END SUBROUTINE h5tget_strpad_f
```

**Name:** H5Tget\_super

**Signature:**

*hid\_t* H5Tget\_super( *hid\_t* dtype\_id )

**Purpose:**

Returns the base datatype from which a datatype is derived.

**Description:**

H5Tget\_super returns the base datatype from which the datatype dtype\_id is derived.

In the case of an enumeration type, the return value is an integer type.

**Parameters:**

*hid\_t* dtype\_id      Datatype identifier for the derived datatype.

**Returns:**

Returns the datatype identifier for the base datatype if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tget\_super\_f

```
SUBROUTINE h5tget_super_f(type_id, base_type_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER(HID_T), INTENT(OUT) :: type_id ! Base datatype identifier
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5tget_super_f
```

**Name:** H5Tget\_tag

**Signature:**

*char* \*H5Tget\_tag(*hid\_t* dtype\_id)

**Purpose:**

Gets the tag associated with an opaque datatype.

**Description:**

H5Tget\_tag returns the tag associated with the opaque datatype dtype\_id.

The tag is returned via a pointer to an allocated string, which the caller must free.

**Parameters:**

*hid\_t* dtype\_id      Datatype identifier for the opaque datatype.

**Returns:**

Returns a pointer to an allocated string if successful; otherwise returns NULL.

**Fortran90 Interface:** h5tget\_tag\_f

```
SUBROUTINE h5tget_tag_f(type_id, tag, taglen, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id    ! Datatype identifier
  CHARACTER(LEN=*), INTENT(OUT) :: tag     ! Unique ASCII string with which the
                                           ! opaque datatype is to be tagged
  INTEGER, INTENT(OUT) :: taglen           ! Length of tag
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5tget_tag_f
```

**Name:** H5Tinsert

**Signature:**

```
herr_t H5Tinsert(hid_t dtype_id, const char * name, size_t offset, hid_t field_id)
```

**Purpose:**

Adds a new member to a compound datatype.

**Description:**

H5Tinsert adds another member to the compound datatype `dtype_id`. The new member has a name which must be unique within the compound datatype. The `offset` argument defines the start of the member in an instance of the compound datatype, and `field_id` is the datatype identifier of the new member.

Note: Members of a compound datatype do not have to be atomic datatypes; a compound datatype can have a member which is a compound datatype.

**Parameters:**

<i>hid_t</i> dtype_id	Identifier of compound datatype to modify.
<i>const char</i> * name	Name of the field to insert.
<i>size_t</i> offset	Offset in memory structure of the field to insert.
<i>hid_t</i> field_id	Datatype identifier of the field to insert.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tinsert\_f

```
SUBROUTINE h5tinsert_f(type_id, name, offset, field_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  CHARACTER(LEN=*), INTENT(IN) :: name ! Name of the field to insert
  INTEGER(SIZE_T), INTENT(IN) :: offset ! Offset in memory structure
                                         ! of the field to insert
  INTEGER(HID_T), INTENT(IN) :: field_id ! Datatype identifier of the
                                         ! new member
  INTEGER, INTENT(OUT) :: hdferr ! Error code
                                         ! 0 on success and -1 on failure
END SUBROUTINE h5tinsert_f
```



**Name:** H5Tis\_variable\_str

**Signature:**

```
htri_t H5Tis_variable_str(hid_t dtype_id)
```

**Purpose:**

Determines whether datatype is a variable-length string.

**Description:**

H5Tis\_variable\_str determines whether the datatype identified in dtype\_id is a variable-length string.

This function can be used to distinguish between fixed and variable-length string datatypes.

**Parameters:**

*hid\_t* dtype\_id      Datatype identifier.

**Returns:**

Returns TRUE or FALSE if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tis\_variable\_str\_f

```
SUBROUTINE h5tis_variable_str_f(type_id, status, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id    ! Datatype identifier
  LOGICAL, INTENT(OUT)      :: status      ! Logical flag:
                                          !   .TRUE. if datatype is a
                                          !   variable string
                                          !   .FALSE. otherwise
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                          ! 0 on success and -1 on failure
END SUBROUTINE h5tis_variable_str_f
```

**History:**

Release	C
1.6.0	Function introduced in this release.

**Name:** H5Tlock

**Signature:**

*herr\_t* H5Tlock( *hid\_t* dtype\_id )

**Purpose:**

Locks a datatype.

**Description:**

H5Tlock locks the datatype specified by the `dtype_id` identifier, making it read-only and non-destructible. This is normally done by the library for predefined datatypes so the application does not inadvertently change or delete a predefined type. Once a datatype is locked it can never be unlocked.

**Parameters:**

*hid\_t* dtype\_id      Identifier of datatype to lock.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**Name:** H5Topen

**Signature:**

```
hid_t H5Topen( hid_t loc_id, const char * name )
hid_t H5Topen( hid_t loc_id, const char * name, hid_t tapl_id )
```

**Purpose:**

Opens a named datatype.

**Description:**

H5Topen is a macro that is mapped to either H5Topen1 or H5Topen2, depending on the needs of the application.

Such macros are provided to facilitate application compatibility. Their use and mappings are fully described in “API Compatibility Macros in HDF5”; we urge you to read that document closely.

When both the HDF5 Library and the application are built and installed with no specific compatibility flags, H5Topen is mapped to the most recent version of the function, currently H5Topen2. If the library and/or application is compiled for Release 1.6 emulation, H5Topen will be mapped to H5Topen1. Function-specific flags are available to override these settings on a function-by-function basis when the application is compiled.

Specific compile-time compatibility flags and the resulting mappings are as follows:

Compatibility setting	H5Topen mapping
<hr/>	
<u>Global settings</u>	
No compatibility flag	H5Topen2
Enable deprecated symbols	H5Topen2
Disable deprecated symbols	H5Topen2
Emulate Release 1.6 interface	H5Topen1
<hr/>	
<u>Function-level macros</u>	
H5Topen_vers = 2	H5Topen2
H5Topen_vers = 1	H5Topen1

**Fortran90 Interface:** h5topen\_f

```
SUBROUTINE h5topen_f(loc_id, name, type_id, hdferr, tapl_id)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: loc_id    ! File or group identifier
  CHARACTER(LEN=*), INTENT(IN) :: name    ! Datatype name within file or group
  INTEGER(HID_T), INTENT(OUT) :: type_id ! Datatype identifier
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure
  INTEGER(HID_T), OPTIONAL, INTENT(IN) :: tapl_id
                                           ! Datatype access property list id
END SUBROUTINE h5topen_f
```

**History:**

<b>Release</b>	<b>C</b>
----------------	----------

1.8.0	The function H5Topen renamed to H5Topen1 and deprecated in this release. The macro H5Topen and the function H5Topen2 introduced in this release.
-------	---

**Name:** H5Topen1

**Signature:**

*hid\_t* H5Topen1( *hid\_t* loc\_id, *const char \** name )

**Purpose:**

Opens a named datatype.

**Notice:**

*This function is deprecated in favor of the function H5Topen2.*

**Description:**

H5Topen1 opens a named datatype at the location specified by loc\_id and returns an identifier for the datatype. loc\_id is either a file or group identifier. The identifier should eventually be closed by calling H5Tclose to release resources.

**Parameters:**

*hid\_t* loc\_id                   IN: A file or group identifier.

*const char \** name           IN: A datatype name, defined within the file or group identified by loc\_id.

**Returns:**

Returns a named datatype identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Topen.

**History:**

Release	C
---------	---

1.8.0	The function H5Topen renamed to H5Topen1 and deprecated in this release.
-------	--

**Name:** H5Topen2

**Signature:**

*hid\_t* H5Topen2( *hid\_t* loc\_id, *const char \**name, *hid\_t* tapl\_id )

**Purpose:**

Opens a named datatype.

**Description:**

H5Topen2 opens a named datatype at the location specified by loc\_id and returns an identifier for the datatype. loc\_id is either a file or group identifier. The identifier should eventually be closed by calling H5Tclose to release resources.

The named datatype is opened with the datatype access property list tapl\_id.

**Parameters:**

<i>hid_t</i> loc_id	IN: A file or group identifier.
<i>const char *</i> name	IN: A datatype name, defined within the file or group identified by loc_id.
<i>hid_t</i> tapl_id	IN: Datatype access property list identifier.

**Returns:**

Returns a named datatype identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** See listing under H5Topen.

**History:**

Release	C
1.8.0	Function introduced in this release.

**Name:** H5Tpack

**Signature:**

*herr\_t* H5Tpack( *hid\_t* dtype\_id )

**Purpose:**

Recursively removes padding from within a compound datatype.

**Description:**

H5Tpack recursively removes padding from within a compound datatype to make it more efficient (space-wise) to store that data.

**Parameters:**

*hid\_t* dtype\_id          Identifier of datatype to modify.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tpack\_f

```
SUBROUTINE h5tpack_f(type_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tpack_f
```

**Name:** H5Tregister

**Signature:**

```
herr_t H5Tregister( H5T_pers_t pers, const char *name, hid_t src_id, hid_t dst_id,
H5T_conv_t func )
```

**Purpose:**

Registers a conversion function.

**Description:**

H5Tregister registers a hard or soft conversion function for a datatype conversion path.

The parameter *pers* indicates whether a conversion function is *hard* (H5T\_PERS\_HARD) or *soft* (H5T\_PERS\_SOFT).

A conversion path can have only one hard function. When *pers* is H5T\_PERS\_HARD, *func* replaces any previous hard function. If *pers* is H5T\_PERS\_HARD and *func* is the null pointer, then any hard function registered for this path is removed.

When *pers* is H5T\_PERS\_SOFT, H5Tregister adds the function to the end of the master soft list and replaces the soft function in all applicable existing conversion paths. Soft functions are used when determining which conversion function is appropriate for this path.

The *name* is used only for debugging and should be a short identifier for the function.

The path is specified by the source and destination datatypes *src\_id* and *dst\_id*. For soft conversion functions, only the class of these types is important.

The type of the conversion function pointer is declared as:

```
typedef herr_t (*H5T_conv_t) (hid_t src_id,
                             hid_t dst_id,
                             H5T_cdata_t *cdata,
                             size_t nelmts,
                             size_t buf_stride,
                             size_t bkg_stride,
                             void *buf,
                             void *bkg,
                             hid_t dset_xfer_plist)
```

The H5T\_cdata\_t struct is declared as:

```
typedef struct *H5T_cdata_t (H5T_cmd_t command,
                             H5T_bkg_t need_bkg,
                             hbool_t *recalc,
                             void *priv)
```

The H5T\_conv\_t parameters and the elements of the H5T\_cdata\_t struct are described more fully in the “Data Conversion” section of “The Datatype Interface (H5T)” in the *HDF5 User's Guide*.

**Parameters:**

<i>H5T_pers_t</i> pers	H5T_PERS_HARD for hard conversion functions; H5T_PERS_SOFT for soft conversion functions.
<i>const char *</i> name	Name displayed in diagnostic output.



<i>hid_t</i> <i>src_id</i>	Identifier of source datatype.
<i>hid_t</i> <i>dst_id</i>	Identifier of destination datatype.
<i>H5T_conv_t</i> <i>func</i>	Function to convert between source and destination datatypes.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.3	The following change occurred in the <code>H5Tconv_t</code> function: <i>nelmts</i> parameter type changed to <i>size_t</i> .

**Name:** H5Tset\_cset

**Signature:**

```
herr_t H5Tset_cset( hid_t dtype_id, H5T_cset_t cset )
```

**Purpose:**

Sets character set to be used.

**Description:**

H5Tset\_cset sets the character set to be used.

HDF5 is able to distinguish between character sets of different nationalities and to convert between them to the extent possible. Valid character set types are:

H5T\_CSET\_ASCII (0) Character set is US ASCII.

**Parameters:**

*hid\_t* dtype\_id Identifier of datatype to modify.

*H5T\_cset\_t* cset Character set type.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_cset\_f

```
SUBROUTINE h5tset_cset_f(type_id, cset, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id
                                ! Datatype identifier
  INTEGER, INTENT(IN) :: cset   ! Character set type of a string datatype
                                ! Possible values of padding type are:
                                !   H5T_CSET_ASCII_F = 0
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tset_cset_f
```

**Name:** H5Tset\_ebias

**Signature:**

*herr\_t* H5Tset\_ebias( *hid\_t* dtype\_id, *size\_t* ebias )

**Purpose:**

Sets the exponent bias of a floating-point type.

**Description:**

H5Tset\_ebias sets the exponent bias of a floating-point type.

**Parameters:**

<i>hid_t</i> dtype_id	Identifier of datatype to set.
<i>size_t</i> ebias	Exponent bias value.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_ebias\_f

```

SUBROUTINE h5tset_ebias_f(type_id, ebias, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER(SIZE_T), INTENT(IN) :: ebias  ! Datatype exponent bias
                                         ! of a floating-point type,
                                         ! which cannot be 0
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tset_ebias_f

```

**Name:** H5Tset\_fields

**Signature:**

```
herr_t H5Tset_fields( hid_t dtype_id, size_t spos, size_t epos, size_t esize, size_t mpos,
                     size_t msize )
```

**Purpose:**

Sets locations and sizes of floating point bit fields.

**Description:**

H5Tset\_fields sets the locations and sizes of the various floating-point bit fields. The field positions are bit positions in the significant region of the datatype. Bits are numbered with the least significant bit number zero.

Fields are not allowed to extend beyond the number of bits of precision, nor are they allowed to overlap with one another.

**Parameters:**

<i>hid_t</i> dtype_id	Identifier of datatype to set.
<i>size_t</i> spos	Sign position, i.e., the bit offset of the floating-point sign bit.
<i>size_t</i> epos	Exponent bit position.
<i>size_t</i> esize	Size of exponent in bits.
<i>size_t</i> mpos	Mantissa bit position.
<i>size_t</i> msize	Size of mantissa in bits.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_fields\_f

```
SUBROUTINE h5tset_fields_f(type_id, spos, epos, esize, mpos, msize, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER(SIZE_T), INTENT(IN) :: spos   ! sign bit-position
  INTEGER(SIZE_T), INTENT(IN) :: epos   ! exponent bit-position
  INTEGER(SIZE_T), INTENT(IN) :: esize  ! size of exponent in bits
  INTEGER(SIZE_T), INTENT(IN) :: mpos   ! mantissa bit-position
  INTEGER(SIZE_T), INTENT(IN) :: msize  ! size of mantissa in bits
  INTEGER, INTENT(OUT) :: hdferr       ! Error code
END SUBROUTINE h5tset_fields_f
```

**Name:** H5Tset\_inpad

**Signature:**

```
herr_t H5Tset_inpad(hid_t dtype_id, H5T_pad_t inpad)
```

**Purpose:**

Fills unused internal floating point bits.

**Description:**

If any internal bits of a floating point type are unused (that is, those significant bits which are not part of the sign, exponent, or mantissa), then H5Tset\_inpad will be filled according to the value of the padding value property inpad. Valid padding types are:

```
H5T_PAD_ZERO (0)
    Set background to zeros.
H5T_PAD_ONE (1)
    Set background to ones.
H5T_PAD_BACKGROUND (2)
    Leave background alone.
```

**Parameters:**

```
hid_t dtype_id    Identifier of datatype to modify.
H5T_pad_t pad     Padding type.
```

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_inpad\_f

```
SUBROUTINE h5tset_inpad_f(type_id, padtype, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id
                                ! Datatype identifier
  INTEGER, INTENT(IN) :: padtype ! Padding type for unused bits
                                ! in floating-point datatypes.
                                ! Possible values of padding type are:
                                !   H5T_PAD_ZERO_F = 0
                                !   H5T_PAD_ONE_F = 1
                                !   H5T_PAD_BACKGROUND_F = 2
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tset_inpad_f
```

**Name:** H5Tset\_norm

**Signature:**

```
herr_t H5Tset_norm( hid_t dtype_id, H5T_norm_t norm )
```

**Purpose:**

Sets the mantissa normalization of a floating-point datatype.

**Description:**

H5Tset\_norm sets the mantissa normalization of a floating-point datatype. Valid normalization types are:

```
H5T_NORM_IMPLIED (0)
    MSB of mantissa is not stored, always 1
H5T_NORM_MSBSET (1)
    MSB of mantissa is always 1
H5T_NORM_NONE (2)
    Mantissa is not normalized
```

**Parameters:**

```
hid_t dtype_id      Identifier of datatype to set.
H5T_norm_t norm    Mantissa normalization type.
```

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_norm\_f

```
SUBROUTINE h5tset_norm_f(type_id, norm, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id
                                ! Datatype identifier
  INTEGER, INTENT(IN) :: norm   ! Mantissa normalization of a
                                ! floating-point datatype
                                ! Valid normalization types are:
                                !   H5T_NORM_IMPLIED_F(0)
                                !     MSB of mantissa is not stored,
                                !     always 1
                                !   H5T_NORM_MSBSET_F(1)
                                !     MSB of mantissa is always 1
                                !   H5T_NORM_NONE_F(2)
                                !     Mantissa is not normalized
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tset_norm_f
```

**Name:** H5Tset\_offset

**Signature:**

```
herr_t H5Tset_offset( hid_t dtype_id, size_t offset )
```

**Purpose:**

Sets the bit offset of the first significant bit.

**Description:**

H5Tset\_offset sets the bit offset of the first significant bit. The significant bits of an atomic datum can be offset from the beginning of the memory for that datum by an amount of padding. The 'offset' property specifies the number of bits of padding that appear to the "right of" the value. That is, if we have a 32-bit datum with 16-bits of precision having the value 0x1122 then it will be laid out in memory as (from small byte address toward larger byte addresses):

Byte Position	Big-Endian Offset=0	Big-Endian Offset=16	Little-Endian Offset=0	Little-Endian Offset=16
0:	[ pad]	[0x11]	[0x22]	[ pad]
1:	[ pad]	[0x22]	[0x11]	[ pad]
2:	[0x11]	[ pad]	[ pad]	[0x22]
3:	[0x22]	[ pad]	[ pad]	[0x11]

If the offset is incremented then the total size is incremented also if necessary to prevent significant bits of the value from hanging over the edge of the datatype.

The offset of an H5T\_STRING cannot be set to anything but zero.

**Parameters:**

*hid\_t* dtype\_id            Identifier of datatype to set.  
*size\_t* offset            Offset of first significant bit.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_offset\_f

```
SUBROUTINE h5tset_offset_f(type_id, offset, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER(SIZE_T), INTENT(IN) :: offset ! Datatype bit offset of
                                         ! the first significant bit
  INTEGER, INTENT(OUT) :: hdferr       ! Error code
END SUBROUTINE h5tset_offset_f
```

**Name:** H5Tset\_order

**Signature:**

```
herr_t H5Tset_order( hid_t dtype_id, H5T_order_t order )
```

**Purpose:**

Sets the byte order of an atomic datatype.

**Description:**

H5Tset\_order sets the byte order of an atomic datatype.

Byte orders currently supported are:

H5T\_ORDER\_LE (0)

Little-endian byte order

H5T\_ORDER\_BE (1)

Big-endian byte order

H5T\_ORDER\_VAX (2)

VAX mixed byte order (not currently supported)

H5T\_ORDER\_NONE (3) is also a valid value for *order*, but it has no effect. It is valid only for fixed-length strings and object and region references and specifies “no particular order.”

**Parameters:**

*hid\_t* dtype\_id                      Identifier of datatype to set.

*H5T\_order\_t* order                  Byte order constant.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_order\_f

```
SUBROUTINE h5tset_order_f(type_id, order, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id      ! Datatype identifier
  INTEGER, INTENT(IN) :: order               ! Datatype byte order
                                              ! Possible values are:
                                              !   H5T_ORDER_LE_F
                                              !   H5T_ORDER_BE_F
                                              !   H5T_ORDER_VAX_F
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
                                              ! 0 on success and -1 on failure
END SUBROUTINE h5tset_order_f
```



**Name:** H5Tset\_pad

**Signature:**

```
herr_t H5Tset_pad(hid_t dtype_id, H5T_pad_t lsb, H5T_pad_t msb)
```

**Purpose:**

Sets the least and most-significant bits padding types.

**Description:**

H5Tset\_pad sets the least and most-significant bits padding types.

H5T\_PAD\_ZERO (0)

Set background to zeros.

H5T\_PAD\_ONE (1)

Set background to ones.

H5T\_PAD\_BACKGROUND (2)

Leave background alone.

**Parameters:**

*hid\_t* dtype\_id Identifier of datatype to set.

*H5T\_pad\_t* lsb Padding type for least-significant bits.

*H5T\_pad\_t* msb Padding type for most-significant bits.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_pad\_f

```
SUBROUTINE h5tset_pad_f(type_id, lsbpad, msbpad, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  INTEGER, INTENT(IN) :: lsbpad         ! Padding type of the
                                         ! least significant bit
  INTEGER, INTENT(IN) :: msbpad         ! Padding type of the
                                         ! most significant bit
                                         ! Possible values of padding
                                         ! type are:
                                         !   H5T_PAD_ZERO_F = 0
                                         !   H5T_PAD_ONE_F = 1
                                         !   H5T_PAD_BACKGROUND_F = 2
                                         !   H5T_PAD_ERROR_F = -1
                                         !   H5T_PAD_NPAD_F = 3
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tset_pad_f
```

**Name:** H5Tset\_precision

**Signature:**

```
herr_t H5Tset_precision(hid_t dtype_id, size_t precision)
```

**Purpose:**

Sets the precision of an atomic datatype.

**Description:**

H5Tset\_precision sets the precision of an atomic datatype. The precision is the number of significant bits which, unless padding is present, is 8 times larger than the value returned by H5Tget\_size.

If the precision is increased then the offset is decreased and then the size is increased to insure that significant bits do not "hang over" the edge of the datatype.

Changing the precision of an H5T\_STRING automatically changes the size as well. The precision must be a multiple of 8.

When decreasing the precision of a floating point type, set the locations and sizes of the sign, mantissa, and exponent fields first.

**Parameters:**

<i>hid_t</i> dtype_id	Identifier of datatype to set.
<i>size_t</i> precision	Number of bits of precision for datatype.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_precision\_f

```
SUBROUTINE h5tset_precision_f(type_id, precision, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id      ! Datatype identifier
  INTEGER(SIZE_T), INTENT(IN) :: precision ! Datatype precision
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
END SUBROUTINE h5tset_precision_f
```

**Name:** H5Tset\_sign

**Signature:**

```
herr_t H5Tset_sign(hid_t dtype_id, H5T_sign_t sign)
```

**Purpose:**

Sets the sign property for an integer type.

**Description:**

H5Tset\_sign sets the sign property for an integer type.

H5T\_SGN\_NONE (0)

Unsigned integer type.

H5T\_SGN\_2 (1)

Two's complement signed integer type.

**Parameters:**

*hid\_t* dtype\_id            Identifier of datatype to set.

*H5T\_sign\_t* sign        Sign type.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_sign\_f

```
SUBROUTINE h5tset_sign_f(type_id, sign, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id
                                ! Datatype identifier
  INTEGER, INTENT(IN) :: sign   ! Sign type for an integer type
                                ! Possible values are:
                                !   Unsigned integer type
                                !     H5T_SGN_NONE_F = 0
                                !   Two's complement signed integer type
                                !     H5T_SGN_2_F = 1
                                !   or error value
                                !     H5T_SGN_ERROR_F=-1
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tset_sign_f
```

**Name:** H5Tset\_size

**Signature:**

```
herr_t H5Tset_size( hid_t dtype_id, size_t size )
```

**Purpose:**

Sets the total size for an atomic datatype.

**Description:**

H5Tset\_size sets the total size in bytes, *size*, for a datatype. If the datatype is atomic and *size* is decreased so that the significant bits of the datatype extend beyond the edge of the new size, then the 'offset' property is decreased toward zero. If the 'offset' becomes zero and the significant bits of the datatype still hang over the edge of the new size, then the number of significant bits is decreased. The size set for a string should include space for the null-terminator character, otherwise it will not be stored on (or retrieved from) disk. Adjusting the size of a string automatically sets the precision to 8\**size*. A compound datatype may increase or decrease in size as long as its member field is not trailed. All datatypes must have a positive size.

**Parameters:**

<i>hid_t</i> dtype_id	Identifier of datatype to change size.
<i>size_t</i> size	Size in bytes to modify datatype.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_size\_f

```
SUBROUTINE h5tset_size_f(type_id, size, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id    ! Datatype identifier
  INTEGER(SIZE_T), INTENT(IN) :: size      ! Datatype size
  INTEGER, INTENT(OUT) :: hdferr           ! Error code
                                           ! 0 on success and -1 on failure
END SUBROUTINE h5tset_size_f
```

**Name:** H5Tset\_strpad

**Signature:**

```
herr_t H5Tset_strpad( hid_t dtype_id, H5T_str_t strpad )
```

**Purpose:**

Defines the storage mechanism for character strings.

**Description:**

H5Tset\_strpad defines the storage mechanism for the string.

The method used to store character strings differs with the programming language:

- ◊ C usually null terminates strings while
- ◊ Fortran left-justifies and space-pads strings.

Valid string padding values, as passed in the parameter *strpad*, are as follows:

```
H5T_STR_NULLTERM (0)
    Null terminate (as C does)
H5T_STR_NULLPAD (1)
    Pad with zeros
H5T_STR_SPACEPAD (2)
    Pad with spaces (as FORTRAN does)
```

When converting from a longer string to a shorter string, the behavior is as follows. If the short string is H5T\_STR\_NULLPAD or H5T\_STR\_SPACEPAD, then the string is simply truncated. If the short string is H5T\_STR\_NULLTERM, it is truncated and a null terminator is appended.

When converting from a shorter string to a longer string, the long string is padded on the end by appending nulls or spaces.

**Parameters:**

```
hid_t dtype_id      Identifier of datatype to modify.
H5T_str_t strpad    String padding type.
```

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_strpad\_f

```
SUBROUTINE h5tset_strpad_f(type_id, strpad, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id
                                ! Datatype identifier
  INTEGER, INTENT(IN) :: strpad ! String padding method for a string datatype
                                ! Possible values of padding type are:
                                !   Pad with zeros (as C does):
                                !       H5T_STR_NULLPAD_F(0)
                                !   Pad with spaces (as FORTRAN does):
                                !       H5T_STR_SPACEPAD_F(1)
  INTEGER, INTENT(OUT) :: hdferr ! Error code
END SUBROUTINE h5tset_strpad_f
```

**Name:** H5Tset\_tag

**Signature:**

```
herr_t H5Tset_tag(hid_t dtype_id const char *tag)
```

**Purpose:**

Tags an opaque datatype.

**Description:**

H5Tset\_tag tags an opaque datatype dtype\_id with a descriptive ASCII identifier, tag.

tag is intended to provide a concise description; the maximum size is hard-coded in the HDF5 Library as 256 bytes (H5T\_OPAQUE\_TAG\_MAX).

**Parameters:**

*hid\_t* dtype\_id      IN: Datatype identifier for the opaque datatype to be tagged.  
*const char* \*tag      IN: Descriptive ASCII string with which the opaque datatype is to be tagged.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tset\_tag\_f

```
SUBROUTINE h5tset_tag_f(type_id, tag, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id ! Datatype identifier
  CHARACTER(LEN=*), INTENT(IN) :: tag   ! Unique ASCII string with which the
                                         ! opaque datatype is to be tagged
  INTEGER, INTENT(OUT) :: hdferr        ! Error code
END SUBROUTINE h5tset_tag_f
```

**History:**

**Release    C**

1.6.5      The H5T\_OPAQUE\_TAG\_MAX macro constant, specifying the maximum size of an opaque datatype tag, was added in H5Tpublic.h.

**Name:** H5Tunregister

**Signature:**

```
herr_t H5Tunregister( H5T_pers_t pers, const char *name, hid_t src_id, hid_t dst_id,
                     H5T_conv_t func )
```

**Purpose:**

Removes a conversion function.

**Description:**

H5Tunregister removes a conversion function matching certain criteria, like soft or hard conversion, source and destination types, and the conversion function.

If a user is trying to remove a conversion function he registered, all parameters can be used. If he is trying to remove a library's default conversion function, there is no guarantee the name and func parameters will match user's chosen values. Passing in some values may cause this function to fail. A good practice is to pass in NULL as their values.

All parameters are optional. The missing parameters will be used to generalize the searching criteria.

The conversion function pointer type declaration is described in H5Tregister.

**Parameters:**

<i>H5T_pers_t</i> pers	H5T_PERS_HARD for hard conversion functions; H5T_PERS_SOFT for soft conversion functions.
<i>const char</i> *name	Name displayed in diagnostic output.
<i>hid_t</i> src_id	Identifier of source datatype.
<i>hid_t</i> dst_id	Identifier of destination datatype.
<i>H5T_conv_t</i> func	Function to convert between source and destination datatypes.

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:**

None.

**History:**

Release	C
1.6.3	The following change occurred in the H5Tconv_t function: nelmts parameter type changed to <i>size_t</i> .

**Name:** H5Tvlen\_create

**Signature:**

*hid\_t* H5Tvlen\_create( *hid\_t* base\_type\_id )

**Purpose:**

Creates a new variable-length datatype.

**Description:**

H5Tvlen\_create creates a new variable-length (VL) datatype.

The base datatype will be the datatype that the sequence is composed of, characters for character strings, vertex coordinates for polygon lists, etc. The base type specified for the VL datatype can be of any HDF5 datatype, including another VL datatype, a compound datatype or an atomic datatype.

When necessary, use H5Tget\_super to determine the base type of the VL datatype.

The datatype identifier returned from this function should be released with H5Tclose or resource leaks will result.

**Parameters:**

*hid\_t* base\_type\_id      Base type of datatype to create.

**See Also:**

H5Dget\_vlen\_buf\_size

H5Dvlen\_reclaim

**Returns:**

Returns datatype identifier if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5tvlen\_create\_f

```
SUBROUTINE h5tvlen_create_f(type_id, vltype_id, hdferr)
  IMPLICIT NONE
  INTEGER(HID_T), INTENT(IN) :: type_id      ! Datatype identifier of base type
                                              ! Base type can only be atomic
  INTEGER(HID_T), INTENT(OUT) :: vltype_id ! VL datatype identifier
  INTEGER, INTENT(OUT) :: hdferr             ! Error code
END SUBROUTINE h5tvlen_create_f
```

**History:**

Release	Fortran90
---------	-----------

1.4.5	Function introduced in this release.
-------	--------------------------------------



## H5Z: Filter and Compression Interface

### Filter and Compression API Functions

These functions enable the user to configure new filters for the local environment.

- H5Zfilter\_avail
- H5Zregister
- H5Zunregister
- H5Zget\_filter\_info

#### The FORTRAN90 Interfaces:

In general, each FORTRAN90 subroutine performs exactly the same task as the corresponding C function.

- h5zfilter\_avail\_f
- h5zget\_filter\_info\_f
- h5zunregister\_f

HDF5 supports a filter pipeline that provides the capability for standard and customized raw data processing during I/O operations. HDF5 is distributed with a small set of standard filters such as compression (gzip, SZIP, and a shuffling algorithm) and error checking (Fletcher32 checksum). For further flexibility, the library allows a user application to extend the pipeline through the creation and registration of customized filters.

The flexibility of the filter pipeline implementation enables the definition of additional filters by a user application. A filter

- is associated with a dataset when the dataset is created,
- can be used only with chunked data  
(i.e., datasets stored in the H5D\_CHUNKED storage layout), and
- is applied independently to each chunk of the dataset.

The HDF5 library does not support filters for contiguous datasets because of the difficulty of implementing random access for partial I/O. Compact dataset filters are not supported because it would not produce significant results.

Filter identifiers for the filters distributed with the HDF5 Library are as follows:

H5Z_FILTER_DEFLATE	The gzip compression, or deflation, filter
H5Z_FILTER_SZIP	The SZIP compression filter
H5Z_FILTER_NBIT	The N-bit compression filter
H5Z_FILTER_SCALEOFFSET	The scale-offset compression filter
H5Z_FILTER_SHUFFLE	The shuffle algorithm filter
H5Z_FILTER_FLETCHER32	The Fletcher32 checksum, or error checking, filter

Custom filters that have been registered with the library will have additional unique identifiers.

See *The Dataset Interface (H5D)* in the *HDF5 User's Guide* for further information regarding data compression.



**Name:** H5Zfilter\_avail

**Signature:**

*htri\_t* H5Zfilter\_avail(*H5Z\_filter\_t* filter)

**Purpose:**

Determines whether a filter is available.

**Description:**

H5Zfilter\_avail determines whether the filter specified in *filter* is available to the application.

**Parameters:**

*H5Z\_filter\_t* filter      IN: Filter identifier. See the introduction to this section of the reference manual for a list of valid filter identifiers.

**Returns:**

Returns a Boolean value (TRUE/FALSE) if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5zfilter\_avail\_f

```
SUBROUTINE h5zfilter_avail_f(filter, status, hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(IN)  :: filter      ! Filter
                                      ! Valid values are:
                                      !   H5Z_FILTER_DEFLATE_F
                                      !   H5Z_FILTER_SHUFFLE_F
                                      !   H5Z_FILTER_FLETCHER32_F
                                      !   H5Z_FILTER_SZIP_F
  LOGICAL, INTENT(OUT) :: status      ! Flag indicating whether
                                      ! filter is available:
                                      !   .TRUE.
                                      !   .FALSE.
END SUBROUTINE h5zfilter_avail_f
```

**History:**

**Release    C**

1.6.0      Function introduced in this release.

**Name:** H5Zget\_filter\_info

**Signature:**

```
herr_t H5Zget_filter_info(H5Z_filter_t filter, unsigned int *filter_config)
```

**Purpose:**

Retrieves information about a filter.

**Description:**

H5Zget\_filter\_info retrieves information about a filter. At present, this means that the function retrieves a filter's configuration flags, indicating whether the filter is configured to decode data, to encode data, neither, or both.

If *filter\_config* is not set to NULL prior to the function call, the returned parameter contains a bit field specifying the available filter configuration. The configuration flag values can then be determined through a series of bitwise AND operations, as described below.

Valid filter configuration flags include the following:

H5Z_FILTER_CONFIG_ENCODE_ENABLED	Encoding is enabled for this filter. In Fortran, H5Z_FILTER_ENCODE_ENABLED_F.
H5Z_FILTER_CONFIG_DECODE_ENABLED	Decoding is enabled for this filter. In Fortran, H5Z_FILTER_DECODE_ENABLED_F.

(These flags are defined for C in the HDF5 Library source code file *H5Zpublic.h*.)

A bitwise AND of the returned *filter\_config* and a valid filter configuration flag will reveal whether the related configuration option is available. For example, if the value of

*H5Z\_FILTER\_CONFIG\_ENCODE\_ENABLED* & *filter\_config*  
is true, i.e., greater than 0 (zero), the queried filter is configured to encode data; if the value is FALSE, i.e., equal to 0 (zero), the filter is not so configured.

If a filter is not encode-enabled, the corresponding H5Pset\_\* function will return an error if the filter is added to a dataset creation property list (which is required if the filter is to be used to encode that dataset). For example, if the H5Z\_FILTER\_CONFIG\_ENCODE\_ENABLED flag is not returned for the SZIP filter, H5Z\_FILTER\_SZIP, a call to H5Pset\_szip will fail.

If a filter is not decode-enabled, the application will not be able to read an existing file encoded with that filter.

This function should be called, and the returned *filter\_config* analyzed, before calling any other function, such as H5Pset\_szip, that might require a particular filter configuration.

**Parameters:**

*H5Z\_filter\_t* filter

IN: Identifier of the filter to query. See the introduction to this section of the reference manual for a list of valid filter identifiers.

*unsigned int* \*filter\_config

OUT: A bit field encoding the returned filter information

**Returns:**

Returns a non-negative value on success, a negative value on failure.

**Fortran90 Interface:**

```

SUBROUTINE h5zget_filter_info_f(filter, config_flags, hdferr)

  IMPLICIT NONE
  INTEGER, INTENT(IN)  :: filter          ! Filter, may be one of the
                                          ! following:
                                          !   H5Z_FILTER_DEFLATE_F
                                          !   H5Z_FILTER_SHUFFLE_F
                                          !   H5Z_FILTER_FLETCHER32_F
                                          !   H5Z_FILTER_SZIP_F
  INTEGER, INTENT(OUT) :: config_flags    ! Bit field indicating whether
                                          ! a filter's encoder and/or
                                          ! decoder are available
  INTEGER, INTENT(OUT) :: hdferr          ! Error code

END SUBROUTINE h5zfilter_avail_f

```

**History:**

<b>Release</b>	<b>C</b>
1.6.3	Function introduced in this release. Fortran subroutine introduced in this release.

**Name:** H5Zregister

**Signature:**

```
herr_t H5Zregister(const H5Z_class_t *filter_class)
```

**Purpose:**

Registers new filter.

**Description:**

H5Zregister registers a new filter with the HDF5 library.

Making a new filter available to an application is a two-step process. The first step is to write the three filter callback functions described below: `can_apply`, `set_local`, and `filter`. This call to H5Zregister, registering the filter with the library, is the second step. The `can_apply` and `set_local` fields can be set to NULL if they are not required for the filter being registered.

H5Zregister accepts a single parameter, a pointer to a buffer for the `filter_class` data structure. That data structure must conform to one of the following definitions:

```
typedef struct H5Z_class1_t {
    H5Z_filter_t id;
    const char *name;
    H5Z_can_apply_func_t can_apply;
    H5Z_set_local_func_t set_local;
    H5Z_func_t filter;
} H5Z_class1_t;

typedef struct H5Z_class2_t {
    int version;
    H5Z_filter_t id;
    unsigned encoder_present;
    unsigned decoder_present;
    const char *name;
    H5Z_can_apply_func_t can_apply;
    H5Z_set_local_func_t set_local;
    H5Z_func_t filter;
} H5Z_class2_t;
```

`version` is a library-defined value reporting the version number of the `H5Z_class_t` struct. This currently must be set to `H5Z_CLASS_T_VERS`.

`id` is the identifier for the new filter. This is a user-defined value between `H5Z_FILTER_RESERVED` and `H5Z_FILTER_MAX`. These values are defined in the HDF5 source file `H5Zpublic.h`, but the symbols `H5Z_FILTER_RESERVED` and `H5Z_FILTER_MAX` should always be used instead of the literal values.

`encoder_present` is a library-defined value indicating whether the filter's encoding capability is available to the application.

`decoder_present` is a library-defined value indicating whether the filter's decoding capability is available to the application.

`name` is a descriptive comment used for debugging, may contain a descriptive name for the filter, and may be the null pointer.

`can_apply`, described in detail below, is a user-defined callback function which determines whether the combination of the dataset creation property list values, the datatype, and the dataspace represent a valid combination to apply this filter to.

`set_local`, described in detail below, is a user-defined callback function which sets any parameters that are specific to this dataset, based on the combination of the dataset creation property list values, the datatype, and the dataspace.

`filter`, described in detail below, is a user-defined callback function which performs the action of the filter.

The statistics associated with a filter are not reset by this function; they accumulate over the life of the library.

`H5Z_class_t` is a macro which maps to either `H5Z_class1_t` or `H5Z_class2_t`, depending on the needs of the application. To affect only this macro, `H5Z_class_t_vers` may be defined to either 1 or 2. Otherwise, it will behave in the same manner as other API compatibility macros. See “API Compatibility Macros in HDF5” for more information. `H5Z_class1_t` matches the `H5Z_class_t` structure that is used in the 1.6.x versions of the HDF5 library.

H5Zregister will automatically detect which structure type has been passed in, regardless of the mapping of the `H5Z_class_t` macro. However, the application must make sure that the fields are filled in according to the correct structure definition if the macro is used to declare the structure.

### The callback functions

Before H5Zregister can link a filter into an application, three callback functions must be defined as described in the HDF5 Library header file `H5Zpublic.h`.

The *can apply* callback function is defined as follows:

```
typedef herr_t (*H5Z_can_apply_func_t) (hid_t dcpl_id, hid_t type_id, hid_t space_id)
```

Before a dataset is created, the *can apply* callbacks for any filters used in the dataset creation property list are called with the dataset's dataset creation property list, `dcpl_id`, the dataset's datatype, `type_id`, and a dataspace describing a chunk, `space_id`, (for chunked dataset storage).

This callback must determine whether the combination of the dataset creation property list settings, the datatype, and the dataspace represent a valid combination to which to apply this filter. For example, an invalid combination may involve the filter not operating correctly on certain datatypes, on certain datatype sizes, or on certain sizes of the chunk dataspace.

This callback can be the NULL pointer, in which case the library will assume that the filter can be applied to a dataset with any combination of dataset creation property list values, datatypes, and dataspace.

The *can apply* callback function must return a positive value for a valid combination, zero for an invalid combination, and a negative value for an error.

The *set local callback function* is defined as follows:

```
typedef herr_t (*H5Z_set_local_func_t) (hid_t dcpl_id, hid_t type_id, hid_t space_id)
```

After the *can apply* callbacks are checked for a new dataset, the *set local* callback functions for any filters used in the dataset creation property list are called. These callbacks receive *dcpl\_id*, the dataset's private copy of the dataset creation property list passed in to *H5Dcreate* (i.e. not the actual property list passed in to *H5Dcreate*); *type\_id*, the datatype identifier passed in to *H5Dcreate*, which is not copied and should not be modified; and *space\_id*, a dataspace describing the chunk (for chunked dataset storage), which should also not be modified.

The *set local* callback must set any filter parameters that are specific to this dataset, based on the combination of the dataset creation property list values, the datatype, and the dataspace. For example, some filters perform different actions based on different datatypes, datatype sizes, numbers of dimensions, or dataspace sizes.

The *set local* callback may be the NULL pointer, in which case, the library will assume that there are no dataset-specific settings for this filter.

The *set local* callback function must return a non-negative value on success and a negative value for an error.

The *filter operation callback function*, defining the filter's operation on the data, is defined as follows:

```
typedef size_t (*H5Z_func_t) (unsigned int flags, size_t cd_nelmts, const unsigned int
cd_values[], size_t nbytes, size_t *buf_size, void **buf)
```

The parameters *flags*, *cd\_nelmts*, and *cd\_values* are the same as for the function *H5Pset\_filter*. The one exception is that an additional flag, *H5Z\_FLAG\_REVERSE*, is set when the filter is called as part of the input pipeline.

The parameter *\*buf* points to the input buffer which has a size of *\*buf\_size* bytes, *nbytes* of which are valid data.

The filter should perform the transformation in place if possible. If the transformation cannot be done in place, then the filter should allocate a new buffer with *malloc()* and assign it to *\*buf*, assigning the allocated size of that buffer to *\*buf\_size*. The old buffer should be freed by calling *free()*.

If successful, the *filter operation* callback function returns the number of valid bytes of data contained in *\*buf*. In the case of failure, the return value is 0 (zero) and all pointer arguments are left unchanged.

#### Parameters:

<i>const H5Z_class_t *filter_class</i>	IN: A pointer to a buffer for the struct containing filter-definition information.
--	--

#### Returns:

Returns a non-negative value if successful; otherwise returns a negative value.

#### Fortran90 Interface:

None.



**History:**

<b>Release</b>	<b>C</b>
1.6.0	This function was substantially revised in Release 1.6.0 with a new <code>H5Z_class_t</code> struct and new <i>set local</i> and <i>can apply</i> callback functions.
1.8.0	The fields <code>version</code> , <code>encoder_present</code> , and <code>decoder_present</code> were added to the <code>H5Z_class_t</code> struct in this release.
1.8.3	<code>H5Z_class_t</code> renamed to <code>H5Z_class2_t</code> , <code>H5Z_class1_t</code> structure introduced for backwards compatibility with release 1.6.x, and <code>H5Z_class_t</code> macro introduced in this release. Function modified to accept either structure type.

**Name:** H5Zunregister

**Signature:**

*herr\_t* H5Zunregister(*H5Z\_filter\_t* filter)

**Purpose:**

Unregisters a filter.

**Description:**

H5Zunregister unregisters the filter specified in filter.

After a call to H5Zunregister, the filter specified in filter will no longer be available to the application.

**Parameters:**

<i>H5Z_filter_t</i> filter	IN: Identifier of the filter to be unregistered. See the introduction to this section of the reference manual for a list of identifiers for standard filters distributed with the HDF5 Library.
----------------------------	---

**Returns:**

Returns a non-negative value if successful; otherwise returns a negative value.

**Fortran90 Interface:** h5zunregister\_f

```

SUBROUTINE h5zunregister_f(filter, hdferr)
  IMPLICIT NONE
  INTEGER, INTENT(IN)  :: filter  ! Filter; one of the possible values:
                                   !   H5Z_FILTER_DEFLATE_F
                                   !   H5Z_FILTER_SHUFFLE_F
                                   !   H5Z_FILTER_FLETCHER32_F
                                   !   H5Z_FILTER_SZIP_F
  INTEGER, INTENT(OUT) :: hdferr  ! Error code
                                   ! 0 on success, and -1 on failure
END SUBROUTINE h5zunregister_f

```

**History:**

**Release**    **C**

1.6.0        Function introduced in this release.

# HDF5 Tools

## HDF5 Tool Interfaces

HDF5-related tools are available to assist the user in a variety of activities, including examining or managing HDF5 files, converting raw data between HDF5 and other special-purpose formats, moving data and files between the HDF4 and HDF5 formats, measuring HDF5 library performance, and managing HDF5 library and application compilation, installation and configuration. Unless otherwise specified below, these tools are distributed and installed with HDF5.

- User utilities:
  - ◆ h5dump -- Enables a user to examine the contents of an HDF5 file and dump those contents to an ASCII file.
  - ◆ h5ls -- Lists specified features of HDF5 file contents.
  - ◆ h5diff and ph5diff -- Compare two HDF5 files and report the differences.
  - ◆ h5repack -- Copies an HDF5 file to a new file with or without compression and/or chunking.
  - ◆ h5repart -- Repartitions a file, creating a family of files.
  - ◆ h5jam -- Adds a user block to the front of an HDF5 file .
  - ◆ h5unjam -- Splits an existing user block from an HDF5 file, placing it in a separate file.
  - ◆ h5copy -- Copies HDF5 objects from a file to a new file
  - ◆ h5mkgrp -- Creates a new HDF5 group in a file
  - ◆ h5stat -- Reports statistics regarding an HDF5 file and the objects in the file.
  - ◆ h5perf -- Measures Parallel HDF5 performance.
  - ◆ h5perf\_serial -- Measures HDF5 serial performance.
- Configuration and library management utilities:
  - ◆ h5redeploy -- Updates HDF5 compiler tools after an HDF5 software installation in a new location.
  - ◆ h5cc and h5pcc -- Simplify the compilation of HDF5 programs written in C.
  - ◆ h5fc and h5pfc -- Simplify the compilation of HDF5 programs written in Fortran90.
  - ◆ h5c++ -- Simplifies the compilation of HDF5 programs written in C++.
- Java-based tools for HDF5 for viewing, manipulating, and generating HDF4 and HDF5 files:  
 (*Distributed separately; external link is <http://www.hdfgroup.org/hdf-java.html/>*)
  - ◆ HDFview -- a browser that works with both HDF4 and HDF5 files and can be used to transfer data between the two formats
  - ◆ Java interfaces for both the HDF4 and HDF5 libraries
  - ◆ Other HDF4- and HDF5-related products
- Data conversion utilities:
  - ◆ h5import -- Imports data into an existing or new HDF5 file.
  - ◆ gif2h5 -- Converts a GIF file to an HDF5 file.
  - ◆ h52gif -- Converts images in an HDF5 file to a GIF file.
- HDF5/HDF4 conversion tools:  
 (*Distributed separately; external link is <http://www.hdfgroup.org/h4toh5/>*)
  - ◆ H4toH5 Conversion Library -- Provides APIs for use in tools that perform customized conversions of HDF4 files to HDF5 files.

- ◆ h5toh4 -- Converts an HDF5 file to an HDF4 file.
- ◆ h4toh5 -- Converts an HDF4 file to an HDF5 file.
- Other tools, including third-party and commercial utilities and applications:  
(*Distributed separately; external link is <http://www.hdfgroup.org/tools5.html>.)*)

**Tool Name:** h5dump

**Syntax:**

h5dump [ *OPTIONS* ] *file*

**Purpose:**

Displays HDF5 file contents.

**Description:**

h5dump enables the user to examine the contents of an HDF5 file and dump those contents, in human readable form, to an ASCII file.

h5dump dumps HDF5 file content to standard output. It can display the contents of the entire HDF5 file or selected objects, which can be groups, datasets, a subset of a dataset, links, attributes, or datatypes.

The `--header` option displays object header information only.

Names are the absolute names of the objects. h5dump displays objects in the order same as the command order. If a name does not start with a slash, h5dump begins searching for the specified object starting at the root group.

If an object is hard linked with multiple names, h5dump displays the content of the object in the first occurrence. Only the link information is displayed in later occurrences.

h5dump assigns a name for any unnamed datatype in the form of `#oid1 : oid2`, where *oid1* and *oid2* are the object identifiers assigned by the library. The unnamed types are displayed within the root group.

Datatypes are displayed with standard type names. For example, if a dataset is created with `H5T_NATIVE_INT` type and the standard type name for integer on that machine is `H5T_STD_I32BE`, h5dump displays `H5T_STD_I32BE` as the type of the dataset.

h5dump can also dump a subset of a dataset. This feature operates in much the same way as hyperslabs in HDF5; the parameters specified on the command line are passed to the function `H5Sselect_hyperslab` and the resulting selection is displayed.

The h5dump output is described in detail in the *DDL for HDF5*, the *Data Description Language* document.

*Note:* It is not permissible to specify multiple attributes, datasets, datatypes, groups, or soft links with one flag. For example, one may not issue the command

WRONG: `h5dump -a /attr1 /attr2 foo.h5` to display both `/attr1` and `/attr2`. One must issue the following command:

CORRECT: `h5dump -a /attr1 -a /attr2 foo.h5`

It's possible to select the file driver with which to open the HDF5 file by using the `--filedriver` (`-f`) command-line option. Acceptable values for the `--filedriver` option are: "sec2", "family", "split", and "multi". If the file driver flag isn't specified, then the file will be opened with each driver in turn and in the order specified above until one driver succeeds in opening the file.

One byte integer type data is displayed in decimal by default. When displayed in ASCII, a non-printable code is displayed in 3 octal digits preceeded by a back-slash unless there is a C language escape sequence for it. For example, CR and LF are printed as `\r` and `\n`. Though the NUL code is represented as `\0` in C, it

is printed as `\000` to avoid ambiguity as illustrated in the following 1 byte char data (since this is not a string, embedded NUL is possible).

```
141 142 143 000 060 061 062 012
  a   b   c  \0   0   1   2  \n
```

h5dump prints them as `"abc\000012\n"`. But if h5dump prints NUL as `\0`, the output is `"abc\0012\n"` which is ambiguous.

### XML Output:

With the `--xml` option, h5dump generates XML output. This output contains a complete description of the file, marked up in XML. The XML conforms to the HDF5 Document Type Definition (DTD) available at <http://www.hdfgroup.org/DTDs/HDF5-File.dtd>.

The XML output is suitable for use with other tools, including the HDF5 Java Tools.

### Options and Parameters:

<code>-h</code> or <code>--help</code>	Print a usage message and exit.
<code>-n</code> or <code>--contents</code>	Print a list of the file contents and exit.
<code>-B</code> or <code>--bootblock</code>	Print the content of the boot block.
<code>-H</code> or <code>--header</code>	Print the header only; no data is displayed.
<code>-A</code> or <code>--onlyattr</code>	Print the header and value of attributes; data of datasets is not displayed.
<code>-i</code> or <code>--object-ids</code>	Print the object ids.
<code>-r</code> or <code>--string</code>	Print 1-byte integer datasets as ASCII.
<code>-e</code> or <code>--escape</code>	Escape non-printing characters.
<code>-V</code> or <code>--version</code>	Print version number and exit.
<code>-a P</code> or <code>--attribute=P</code>	Print the specified attribute.
<code>-d P</code> or <code>--dataset=P</code>	Print the specified dataset.
<code>-y</code> or <code>--noindex</code>	Do not print array indices with data.
<code>-p</code> or <code>--properties</code>	Print information regarding dataset properties, including filters, storage layout, fill value, and allocation time. The filter output lists any filters used with a dataset, including the type of filter, its name, and any filter parameters. The storage layout output specifies the dataset layout (chunked, compact, or contiguous), the size in bytes of the dataset on disk, and, if a compression filter is associated with the dataset, the compression ratio. The compression ratio is computed as (uncompressed size)/(compressed size). The fill value output includes the fill value datatype and value. The allocation time output displays the allocation time as specified with <code>H5Pset_alloc_time</code> .
<code>-f D</code> or <code>--filedriver=D</code>	Specify which driver to open the file with.
<code>-g P</code> or <code>--group=P</code>	Print the specified group and all members.
<code>-l P</code> or <code>--soft-link=P</code>	Print the value(s) of the specified soft link.
<code>-o F</code> or <code>--output=F</code>	Output raw data into file F.

`-b B` or `--binary=B`

Output dataset to a binary file using the datatype specified by *B*.

*B* must have one of the following values:

LE	Little-endian
BE	Big-endian
MEMORY	Memory datatype
FILE	File datatype

Recommended usage is with the `-d` and `-o` options.

`-t P` or `--datatype=P`

Print the specified named datatype.

`-w N` or `--width=N`

Set the number of columns of output.

`-m T` or `--format=T`

Set the floating point output format.

*T* is a string defining the floating point format, e.g.,  
'%.3f'.

`-q Q` or `--sort_by=Q`

Sort groups and attributes by the specified index type, *Q*.

Valid values of *Q* are as follows:

name	Alpha-numeric index by name
------	-----------------------------

(Default)

creation_order	Index by creation order
----------------	-------------------------

`-z Z` or `--sort_order=Z`

Sort groups and attributes in the specified order, *Z*. Valid values of *Z* are as follows:

ascending	Sort in ascending order (Default)
descending	Sort in descending order

`-x` or `--xml`

Output XML using XML schema (default) instead of DDL.

`-u` or `--use-dtd`

Output XML using XML DTD instead of DDL.

`-D U` or `--xml-dtd=U`

In XML output, refer to the DTD or schema at *U* instead of the default schema/DTD.

`-X S` or `--xml-dns=S`

In XML output, (XML Schema) use qualified names in the XML:

"": no namespace, default: "hdf5:"

`-s L` or `--start=L`

Offset of start of subsetting selection.

Default: the beginning of the dataset.

`-S L` or `--stride=L`

Hyperslab stride.

Default: 1 in all dimensions.

`-c L` or `--count=L`

Number of blocks to include in the selection.

<code>-k L</code> or <code>--block=L</code>	Size of block in hyperslab. Default: 1 in all dimensions.
<code>--</code>	Indicates that the following argument is not an option. E.g., to dump a file called <code>`-f'</code> , use <code>h5dump -- -f</code> . ( <i>This option is necessary only when the name of the file to be examined starts with a dash (-), which could confuse the tool's command-line parser.</i> )
<i>file</i>	The file to be examined.

The option parameters listed above are defined as follows:

- D* which file driver to use in opening the file. Acceptable values are "sec2", "family", "split", and "multi". Without the file driver flag, the file will be opened with each driver in turn and in the order specified above until one driver succeeds in opening the file.
- P* The full path from the root group to the object
- F* A filename
- N* An integer greater than 1
- L* A list of integers, the number of which is equal to the number of dimensions in the dataspace being queried
- U* A URI (as defined in [IETF RFC 2396], updated by [IETF RFC 2732]) that refers to the DTD to be used to validate the XML
- B* The form of binary output:
  - MEMORY for a memory type
  - FILE for the file type
  - LE or BE for pre-existing little- or big-endian types

Subsetting parameters can also be expressed in a convenient compact form, as follows:

```
--dataset="/foo/mydataset[START;STRIDE;COUNT;BLOCK]"
```

All of the semicolons (;) are required, even when a parameter value is not specified. When not specified, default parameter values are used.

### Examples:

1. Dump the group `/GroupFoo/GroupBar` in the file `quux.h5`:  

```
h5dump -g /GroupFoo/GroupBar quux.h5
```
2. Dump the dataset `Fnord`, which is in the group `/GroupFoo/GroupBar` in the file `quux.h5`:  

```
h5dump -d /GroupFoo/GroupBar/Fnord quux.h5
```
3. Dump the attribute metadata of the dataset `Fnord`, which is in the group `/GroupFoo/GroupBar` in the file `quux.h5`:  

```
h5dump -a /GroupFoo/GroupBar/Fnord/metadata quux.h5
```
4. Dump the attribute metadata which is an attribute of the root group in the file `quux.h5`:  

```
h5dump -a /metadata quux.h5
```
5. Produce an XML listing of the file `bobo.h5`, saving the listing in the file `bobo.h5.xml`:  

```
h5dump --xml bobo.h5 > bobo.h5.xml
```
6. Dump a subset of the dataset `/GroupFoo/databar/` in the file `quux.h5`:  

```
h5dump -d /GroupFoo/databar --start="1,1" --stride="2,3"
--count="3,19" --block="1,1" quux.h5
```



7. The same example, using the short form to specify the subsetting parameters:

```
h5dump -d "/GroupFoo/databar[1,1;2,3;3,19;1,1]" quux.h5
```

8. Dump a binary copy of the dataset /GroupD/FreshData/ in the file quux.h5, with data written in little-endian form, to the output file FreshDataD.bin:

```
h5dump -d "/GroupD/FreshData" -b LE
-o "FreshDataD.bin" quux.h5
```

### Current Status:

The current version of h5dump displays the following information:

- ◇ Group
  - group attribute (see Attribute)
  - group member
- ◇ Dataset
  - dataset attribute (see Attribute)
  - dataset type (see Datatype)
  - dataset space (see Dataspace)
  - dataset data
- ◇ Attribute
  - attribute type (see Datatype)
  - attribute space (see Dataspace)
  - attribute data
- ◇ Datatype
  - integer type
    - H5T\_STD\_I8BE, H5T\_STD\_I8LE, H5T\_STD\_I16BE, ...
  - floating point type
    - H5T\_IEEE\_F32BE, H5T\_IEEE\_F32LE, H5T\_IEEE\_F64BE, ...
  - string type
  - compound type
    - named, unnamed and transient compound type
    - integer, floating or string type member
  - opaque types
  - reference type
    - object references
    - data regions
  - enum type
  - variable-length datatypes
    - atomic types only
    - scalar or single dimensional array of variable-length types supported
- ◇ Dataspace
  - scalar and simple space
- ◇ Soft link
- ◇ Hard link
- ◇ Loop detection

### See Also:

- ◆ HDF5 Data Description Language syntax at *DDL for HDF5*
- ◆ HDF5 XML Schema at <http://www.hdfgroup.org/DTDs/HDF5-File.xsd>
- ◆ HDF5 XML information at <http://www.hdfgroup.org/HDF5/XML/>

**History:**

<b>Release</b>	<b>Command Line Tool</b>
1.6.5	The following options added in this release: -n or --contents -e or --escape -y or --noindex -p or --properties -b or --binary
1.8.0	The following options added in this release: -q or --sort_by -z or --sort_order
1.8.1	Compression ratio added to -p option in this release.

**Tool Name:** h5ls

**Syntax:**

h5ls [*OPTIONS*] *file* [*OBJECTS...*]

**Purpose:**

Prints information about a file or dataset.

**Description:**

h5ls prints selected information about file objects in the specified format.

**Options and Parameters:**

-h or -? or --help	Print a usage message and exit.
-a or --address	Print addresses for raw data.
-d or --data	Print the values of datasets.
-e or --errors	Show all HDF5 error reporting.
-f or --full	Print full path names instead of base names.
-g or --group	Show information about a group, not its contents.
-l or --label	Label members of compound datasets.
-r or --recursive	List all groups recursively, avoiding cycles.
-s or --string	Print 1-bytes integer datasets as ASCII.
-S or --simple	Use a machine-readable output format.
-wN or --width=N	Set the number of columns of output.
-v or --verbose	Generate more verbose output.
-V or --version	Print version number and exit.
-x or --hexdump	Show raw data in hexadecimal format.
<i>file</i>	The file name may include a <code>printf(3C)</code> integer format such as <code>%%05d</code> to open a file family.
<i>objects</i>	Each object consists of an HDF5 file name optionally followed by a slash and an object name within the file (if no object is specified within the file then the contents of the root group are displayed). The file name may include a <code>printf(3C)</code> integer format such as <code>"%05d"</code> to open a file family.

*Last modified: 12 May 2009*

**Tool Name:** h5diff

**Syntax:**

```
h5diff [OPTIONS] file1 file2 [object1 [object2 ] ]
ph5diff [OPTIONS] file1 file2 [object1 [object2 ] ]
```

**Purpose:**

Compare two HDF5 files and report the differences.

**Description:**

h5diff and ph5diff are command line tools that compare two HDF5 files, *file1* and *file2*, and report the differences between them. h5diff is for serial use while ph5diff is for use in parallel environments.

Optionally, h5diff and ph5diff will compare two objects within these files. If only one object, *object1*, is specified, h5diff will compare *object1* in *file1* with *object1* in *file2*. If two objects, *object1* and *object2*, are specified, h5diff will compare *object1* in *file1* with *object2* in *file2*.

*object1* and *object2* can be groups, datasets, named datatypes, or links and must be expressed as absolute paths from the respective file's root group.

- ◊ If these objects are groups, the name string is compared.
- ◊ If these objects are datasets, array rank and dimensions, datatypes, and data values are compared.
- ◊ If these objects are named datatypes, the comparison is based on the return value of `H5Tequal`.
- ◊ If these objects are links, the link value is compared.

(The link value is the string that is often referred to as the name of the linked object.)

h5diff and ph5diff have the following output modes:

Normal mode	Prints the number of differences found and where they occurred.
Report mode (-r)	Prints the above plus the differences.
Verbose mode (-v)	Prints all of the above plus a list of objects and warnings.
Quiet mode (-q)	Prints no output. (h5diff always returns an exit code of 1 when differences are found.)

#### **h5diff and NaNs:**

h5diff detects when a value in a dataset is a NaN (a "not a number" value), but does not differentiate among various types of NaNs. Thus, when one NaN is compared with another NaN, h5diff treats them as equal; when a NaN is compared with a valid number, h5diff treats them as not equal.

Note that NaN detection is computationally expensive and slows h5diff performance dramatically. If you do not have NaNs in your files, or do not care about NaNs, use the `-N` option below to turn off NaN detection. Similarly, if h5diff `-N` produces unexpected differences, running h5diff without `-N` should reveal whether any of the differences are associated with NaN values.

#### **Difference between h5diff and ph5diff:**

With the following exception, h5diff and ph5diff behave identically. With ph5diff, the comparison of objects is shared across multiple processors, with the comparison of each pair of objects assigned to a single processor. I.e., the comparison of a single object, even a very large dataset, in each

file is not shared.

### Options and Parameters:

<code>-h</code> or <code>--help</code>	Print help message.
<code>-V</code> or <code>--version</code>	Print version number and exit.
<code>-r</code> or <code>--report</code>	Report mode — Print the differences.
<code>-v</code> or <code>--verbose</code>	Verbose mode — Print the differences, a list of objects, and warnings.
<code>-q</code> or <code>--quiet</code>	Quiet mode — Do not print output.
<code>-N</code> or <code>--nan</code>	Disables NaN detection; see “h5diff and NaNs” above.
<code>-n count</code> or <code>--count=count</code>	Print difference up to <i>count</i> differences, then stop. <i>count</i> must be a positive integer.
<code>-d delta</code> or <code>--delta=delta</code>	Print only differences that are greater than the limit <i>delta</i> . <i>delta</i> must be a positive number. The comparison criterion is whether the absolute value of the difference of two corresponding values is greater than <i>delta</i> (e.g., $ a-b  > delta$ , where <i>a</i> is a value in <i>file1</i> and <i>b</i> is a value in <i>file2</i> ).
<code>-p relative</code> or <code>--relative=relative</code>	Print only differences that are greater than a relative error. <i>relative</i> must be a positive number. The comparison criterion is whether the absolute value of the difference <i>1</i> and the ratio of two corresponding values is greater than <i>relative</i> (e.g., $ 1-(b/a)  > relative$ where <i>a</i> is a value in <i>file1</i> and <i>b</i> is a value in <i>file2</i> ).
<i>file1 file2</i>	The HDF5 files to be compared.
<i>object1 object2</i>	Specific object(s) within the files to be compared.

### Returns:

Returns 1 (one) if differences are found, 0 (zero) if no differences are found, and 2 (two) if the call fails.

### Examples:

The following h5diff call compares the object /a/b in file1 with the object /a/c in file2:

```
h5diff file1 file2 /a/b /a/c
```

This h5diff call compares the object /a/b in file1 with the same object in file2:

```
h5diff file1 file2 /a/b
```

And this h5diff call compares all objects in both files:

```
h5diff file1 file2
```

### History:

Release	Change
1.6.0	h5diff introduced in this release.
1.8.0	ph5diff introduced in this release. h5diff command line syntax changed in this release.
1.8.2 and 1.6.8	Return value on failure changed in this release.

**Tool Name:** h5repack

**Syntax:**

```
h5repack [OPTIONS] in_file out_file
h5repack -i in_file -o out_file [OPTIONS]
```

**Purpose:**

Copies an HDF5 file to a new file with or without compression and/or chunking.

**Description:**

h5repack is a command line tool that applies HDF5 filters to an input file *in\_file*, saving the output in a new output file, *out\_file*.

**Options and Parameters:**

- i *in\_file*  
Input HDF5 file
- o *out\_file*  
Output HDF5 file
- h or --help  
Print help message.
- v or --verbose  
Print verbose output.
- V or --version  
Print version number.
- n or --native  
Use native HDF5 datatypes when repacking.  
(Default behavior is to use original file datatypes.)  
*Note that this is a change in default behavior; prior to Release 1.6.6, h5repack generated files only with native datatypes.*
- L or --latest  
Use latest version of the HDF5 file format.
- c *max\_compact\_links* or --compact=*max\_compact\_links*  
Set the maximum number of links, *max\_compact\_links*, that can be stored in a group header message (compact format).
- d *min\_indexed\_links* or --indexed=*min\_indexed\_links*  
Set the minimum number of links, *min\_indexed\_links*, in the indexed format.

*max\_compact\_links* and *min\_indexed\_links* are closely related and the first must be equal to or greater than the second. In the general case, however, performance will suffer, possibly dramatically, if they are equal; performance can be improved by tuning the gap between the two values to minimize unnecessary thrashing between the compact storage and indexed storage modes as group size waxes and wanes. The relationship between *max\_compact\_links* and *min\_indexed\_links* is most important when group sizes are highly dynamic; that relationship is much less important in files with a stable structure. Compact mode is space and performance-efficient when groups have small numbers of members; indexed mode requires slightly more storage space, but provides increasingly better performance as the number of members in each group increases.

- m *number* or --threshold=*number*  
Apply filter(s) only to objects whose size in bytes is equal to or greater than *number*. If no size is specified, a threshold of 1024 bytes is assumed.
- s *min\_size[:header\_type]* or --ssize=*min\_size[:header\_type]*  
Set the minimum size of optionally specified types of shared object header messages.

*min\_size* is the minimum size, in bytes, of a shared object header message. Header messages smaller than the specified size will not be shared.

*header\_type* specifies the type(s) of header message that this minimum size is to be applied to. Valid values of *header\_type* are any of the following:

dspace for dataspace header messages  
 dtype for datatype header messages  
 fill for fill values  
 pline for property list header messages  
 attr for attribute header messages

If *header\_type* is not specified, *min\_size* will be applied to all header messages.

**-f *filter* or --filter=*filter***

Filter type

*filter* is a string of the following format:

*list\_of\_objects* : *name\_of\_filter*[=*filter\_parameters*]

*list\_of\_objects* is a comma separated list of object names meaning apply the filter(s) only to those objects. If no object names are specified, the filter is applied to all objects.

*name\_of\_filter* can be one of the following:

GZIP, to apply the HDF5 GZIP filter (GZIP compression)  
 SZIP, to apply the HDF5 SZIP filter (SZIP compression)  
 SHUF, to apply the HDF5 shuffle filter  
 FLET, to apply the HDF5 checksum filter  
 NBIT, to apply the HDF5 N-bit filter  
 SOFF, to apply the HDF5 scale/offset filter  
 NONE, to remove any filter(s)

*filter\_parameters* conveys optional compression information:

GZIP=*deflation\_level* from 1-9  
 SZIP=*pixels\_per\_block*,*coding\_method*  
     *pixels\_per\_block* is a even number in the range 2-32.  
     *coding\_method* is EC or NN.  
 SHUF (no parameter)  
 FLET (no parameter)  
 NBIT (no parameter)  
 SOFF=*scale\_factor*,*scale\_type*  
     *scale\_factor* is an integer.  
     *scale\_type* is either IN or DS.  
 NONE (no parameter)

**-l *layout* or --layout=*layout***

Layout type

*layout* is a string of the following format:

*list\_of\_objects* : *layout\_type*[=*layout\_parameters*]

*list\_of\_objects* is a comma separated list of object names, meaning that layout information is supplied for those objects. If no object names are specified, the layout is applied to all objects.

*layout\_type* can be one of the following:

CHUNK, to apply chunking layout  
 COMPA, to apply compact layout  
 CONTI, to apply continuous layout

*layout\_parameters* is present only in the CHUNK case and specifies the chunk size of each dimension in the following format with no intervening spaces:

*dim\_1* × *dim\_2* × ... *dim\_n*

*-e file*

File containing the -f and -l options (only filter and layout flags)

*in\_file*

Input HDF5 file

*out\_file*

Output HDF5 file

### Examples:

1. `h5repack -f GZIP=1 -v file1 file2`  
 Applies GZIP compression to all objects in `file1` and saves the output in `file2`. Prints verbose output.
2. `h5repack -f dset1:SZIP=8,NN file1 file2`  
 Applies SZIP compression only to object `dset1`.
3. `h5repack -l dset1,dset2:CHUNK=20x10 file1 file2`  
 Applies chunked layout to objects `dset1` and `dset2`.

### History:

Release	Command Line Tool
1.6.2	<code>h5repack</code> introduced in this release.
1.8.0	<code>h5repack</code> command line syntax changed in this release.
1.8.1	Original syntax restored; both the new and the original syntax are now supported.



**Tool Name:** h5repart

**Syntax:**

```
h5repart [-v] [-V] [-[b|m]N[g|m|k]] [-family_to_sec2] source_file dest_file
```

**Purpose:**

Repartitions a file or family of files.

**Description:**

h5repart joins a family of files into a single file, or copies one family of files to another while changing the size of the family members. h5repart can also be used to copy a single file to a single file with holes. At this stage, h5repart can not split a single non-family file into a family of file(s).

To convert a family of file(s) to a single non-family file (sec2 file), the option `-family_to_sec2` has to be used.

Sizes associated with the `-b` and `-m` options may be suffixed with `g` for gigabytes, `m` for megabytes, or `k` for kilobytes.

File family names include an integer `printf` format such as `%d`.

**Options and Parameters:**

<code>-v</code>	Produce verbose output.
<code>-V</code>	Print a version number and exit.
<code>-bN</code>	The I/O block size, defaults to 1kB
<code>-mN</code>	The destination member size or 1GB
<code>-family_to_sec2</code>	Convert file driver from family to sec2
<i>source_file</i>	The name of the source file
<i>dest_file</i>	The name of the destination files

**Tool Name:** h5jam/h5unjam

**Syntax:**

```
h5jam -u user_block -i in_file.h5 [-o out_file.h5] [--clobber]
h5jam -h

h5unjam -i in_file.h5 [-u user_block | --delete] [-o out_file.h5]
h5unjam -h
```

**Purpose:**

Adds user block to front of an HDF5 file, to create a new concatenated file.  
Splits user block and HDF5 file into two files: user block data and HDF5 data.

**Description:**

h5jam concatenates a user\_block file and an HDF5 file to create an HDF5 file with a user block. The user block can be either binary or text. The output file is padded so that the HDF5 header begins on byte 512, 1024, etc.. (See the HDF5 File Format.)

If out\_file.h5 is given, a new file is created with the user\_block followed by the contents of in\_file.h5. In this case, infile.h5 is unchanged.

If out\_file.h5 is not specified, the user\_block is added to in\_file.h5.

If in\_file.h5 already has a user block, the contents of user\_block will be added to the end of the existing user block, and the file shifted to the next boundary. If --clobber is set, any existing user block will be overwritten.

h5unjam splits an HDF5 file, writing the user block to a file or to stdout and the HDF5 file to an HDF5 file with a header at byte zero (0, i.e., with no user block).

If out\_file.h5 is given, a new file is created with the contents of in\_file.h5 without the user block. In this case, infile.h5 is unchanged.

If out\_file.h5 is not specified, the user\_block is removed and in\_file.h5 is rewritten, starting at byte 0.

If user\_block is set, the user block will be written to user\_block. If user\_block is not set, the user block, if any, will be written to stdout. If --delete is selected, the user block will not be written.

**Examples:**

Create new file, newfile.h5, with the text in file mytext.txt as the user block for the HDF5 file file.h5.

```
h5jam -u mytext.txt -i file.h5 -o newfile.h5
```

Add text in file mytext.txt to front of HDF5 dataset, file.h5.

```
h5jam -u mytext.txt -i file.h5
```

Overwrite the user block, if any, in file.h5 with the contents of mytext.txt.

```
h5jam -u mytext.txt -i file.h5 --clobber
```

For an HDF5 file, `with_ub.h5`, with a user block, extract the user block to `user_block.txt` and the HDF5 portion of the file to `wo_ub.h5`.

```
h5unjam -i with_ub.h5 -u user_block.txt -o wo_ub.h5
```

**Return Value:**

`h5jam` returns the size of the output file, or -1 if an error occurs.

`h5unjam` returns the size of the output file, or -1 if an error occurs.

**Caveats**

These tools copy all the data sequentially in the file(s) to new offsets. For a large file, this copy will take a long time.

The most efficient way to create a user block is to create the file with a user block (see `H5Pset_user_block`), and write the user block data into that space from a program.

The user block is completely opaque to the HDF5 library and to the `h5jam` and `h5unjam` tools. The user block is simply read or written as a string of bytes, which could be text or any kind of binary data; it is up to the user to know what the contents of the user block means and how to process it.

When the user block is extracted, all the data is written to the output, including any padding or unwritten data.

This tool moves the HDF5 portion of the file through byte copies; i.e., it does not read or interpret the HDF5 objects.

**Tool Name:** h5copy

**Syntax:**

```
h5copy [OPTIONS] [OBJECTS]
```

**Purpose:**

Copy an object from one HDF5 file to another HDF5 file.

**Description:**

h5copy copies an HDF5 object (dataset, named datatype, or group) from one HDF5 file to another HDF5 file, which may either already exist or not.

**Arguments:**

**Options and Parameters:**

-h or --help

Print a usage message and exit.

-v or --verbose

Produce verbose output, printing information regarding the specified options and objects.

-f flag\_type or --flag=flag\_type

Specify one or more of several copy options; flag\_type may be one of the following strings or a logical AND of two or more:

shallow Copy only immediate members of a group.

(Default: Recursively copy all objects below the group.)

soft Expand soft links to copy target objects.

(Default: Keep soft links as they are.)

ext Expand external links to copy external objects.

(Default: Keep external links as they are.)

ref Copy objects that are pointed to by references.

(Default: Update only the values of object references.)

attr Copy objects without copying attributes.

(Default: Copy objects and all attributes.)

allflags Switch each setting above from the default to the setting described in this table.

Equivalent to logical AND of all flags above.

-V or --Version

Print version information.

**Objects (all required):**

-i input\_file or --input=input\_file

Input HDF5 file name

-o output\_file or --output=output\_file

Output HDF5 file name (existing or non-existing)

-s source\_object or --source=source\_object

Input HDF5 object name within the source file

-d destination\_object or --destination=destination\_object

Output HDF5 object name within the destination file

**Example Usage**

In verbose mode, create a new file, test1.out.h5, containing the object array in the root group, copied from the existing file test1.h5 and object array.

```
h5copy -v -i "test1.h5" -o "test1.out.h5" -s "/array" -d "/array"
```

In verbose mode and using the flag `shallow` to prevent recursion in the file hierarchy, create a new file, `test1.out.h5`, containing the object array in the root group, copied from the existing file `test1.h5` and object array.

```
h5copy -v -f shallow -i "test1.h5" -s "/array" -o test1.out.h5 -d "/array"
```

**History:**

Release	Command Line Tool
1.8.0	Tool introduced in this release.

**Tool Name:** h5mkgrp

**Syntax:**

```
h5mkgrp [OPTIONS] file_name group_name...
```

**Purpose:**

Creates new group(s) in an HDF5 file.

**Description:**

h5mkgrp creates one or more new groups in an HDF5 file.

**Options and Parameters:**

*file\_name*

Name of HDF5 file within which new group is to be created.

*group\_name*

Name of group to be created; specified as full path name from the root group, i.e., starting with a slash (/).

**Options:**

-h, --help

Print a usage message and exit.

-l, --latest

Use latest version of file format to create new group.

-p, --parents

Create parent or intervening groups as needed. Issue no error if intervening groups or new group already exist.

-v, --verbose

Print verbose output, including information about file, group(s), and options.

-V, --version

Print tool version number then exit. Tool version number is that of the corresponding HDF5 Library.

**Example Usage**

Create a new group, *new\_group*, within the existing group */a/b* in the file *HDF5\_file*.

```
h5mkgrp "HDF5_file" "/a/b/new_group"
```

Create a new group, *new\_group*, within the group */a/b* in the file *HDF5\_file*. Create the groups *a* and *b* if they do not already exist. Issue no error if the intervening groups or the new group already exist.

```
h5mkgrp -p "HDF5_file" "/a/b/new_group"
```

Create the new groups */a/b/new\_c* and */a/x/new\_4* in the file *HDF5\_file*. The groups */a/b* and */a/x* must already exist.

```
h5mkgrp -p "HDF5_file" "/a/b/new_c" "/a/x/new_4"
```

**History:**

Release	Command Line Tool
1.8.0	Tool introduced in this release.

**Tool Name:** h5import

**Syntax:**

```
h5import infile in_options [infile in_options ...] -o outfile
h5import infile in_options [infile in_options ...] -outfile outfile
h5import -h
h5import -help
```

**Purpose:**

Imports data into an existing or new HDF5 file.

**Description:**

`h5import` converts data from one or more ASCII or binary files, *infile*, into the same number of HDF5 datasets in the existing or new HDF5 file, *outfile*. Data conversion is performed in accordance with the user-specified type and storage properties specified in *in\_options*.

The primary objective of `h5import` is to import floating point or integer data. The utility's design allows for future versions that accept ASCII text files and store the contents as a compact array of one-dimensional strings, but that capability is not implemented in HDF5 Release 1.6.

**Input data and options:**

Input data can be provided in one of the following forms:

- ◇ As an ASCII, or plain-text, file containing either floating point or integer data
- ◇ As a binary file containing either 32-bit or 64-bit native floating point data
- ◇ As a binary file containing native integer data, signed or unsigned and 8-bit, 16-bit, 32-bit, or 64-bit.
- ◇ As an ASCII, or plain-text, file containing text data. (This feature is not implemented in HDF5 Release 1.6.)

Each input file, *infile*, contains a single *n*-dimensional array of values of one of the above types expressed in the order of fastest-changing dimensions first.

Floating point data in an ASCII input file may be expressed either in the fixed-point form (e.g., 323.56) or in scientific notation (e.g., 3.23E+02) in an ASCII input file.

Each input file can be associated with options specifying the datatype and storage properties. These options can be specified either as *command line arguments* or in a *configuration file*. Note that exactly one of these approaches must be used with a single input file.

Command line arguments, best used with simple input files, can be used to specify the class, size, dimensions of the input data and a path identifying the output dataset.

The recommended means of specifying input data options is in a configuration file; this is also the only means of specifying advanced storage features. See further discussion in "The configuration file" below.

The only required option for input data is dimension sizes; defaults are available for all others.

`h5import` will accept up to 30 input files in a single call. Other considerations, such as the maximum length of a command line, may impose a more stringent limitation.

**Output data and options:**

The name of the output file is specified following the `-o` or `-output` option in *outfile*. The data

from each input file is stored as a separate dataset in this output file. *outfile* may be an existing file. If it does not yet exist, `h5import` will create it.

Output dataset information and storage properties can be specified only by means of a configuration file.

Dataset path	<p>If the groups in the path leading to the dataset do not exist, <code>h5import</code> will create them.</p> <p>If no group is specified, the dataset will be created as a member of the root group.</p> <p>If no dataset name is specified, the default name is <code>dataset0</code> for the first input dataset, <code>dataset1</code> for the second input dataset, <code>dataset2</code> for the third input dataset, etc.</p> <p><code>h5import</code> does not overwrite a pre-existing dataset of the specified or default name. When an existing dataset of a conflicting name is encountered, <code>h5import</code> quits with an error; the current input file and any subsequent input files are not processed.</p>
Output type	Datatype parameters for output data
Output data class	Signed or unsigned integer or floating point
Output data size	8-, 16-, 32-, or 64-bit integer 32- or 64-bit floating point
Output architecture	<p>IEEE</p> <p>STD</p> <p>NATIVE (Default)</p> <p>Other architectures are included in the <code>h5import</code> design but are not implemented in this release.</p>
Output byte order	<p>Little- or big-endian.</p> <p>Relevant only if output architecture is IEEE, UNIX, or STD; fixed for other architectures.</p>
Dataset layout and storage properties	Denote how raw data is to be organized on the disk. If none of the following are specified, the default configuration is contiguous layout and with no compression.
Layout	<p>Contiguous (Default)</p> <p>Chunked</p>
External storage	<p>Allows raw data to be stored in a non-HDF5 file or in an external HDF5 file.</p> <p>Requires contiguous layout.</p>
Compressed	<p>Sets the type of compression and the level to which the dataset must be compressed.</p> <p>Requires chunked layout.</p>
Extendable	<p>Allows the dimensions of the dataset increase over time and/or to be unlimited.</p> <p>Requires chunked layout.</p>
Compressed and extendable	Requires chunked layout.

### Command-line arguments:

The `h5import` syntax for the command-line arguments, *in\_options*, is as follows:



```
h5import infile -d dim_list [-p pathname] [-t input_class] [-s
input_size] [infile ...] -o outfile
or
h5import infile -dims dim_list [-path pathname] [-type input_class]
[-size input_size] [infile ...] -outfile outfile
or
h5import infile -c config_file [infile ...] -outfile outfile
```

Note the following: If the `-c config_file` option is used with an input file, no other argument can be used with that input file. If the `-c config_file` option is not used with an input data file, the `-d dim_list` argument (or `-dims dim_list`) must be used and any combination of the remaining options may be used. Any arguments used must appear in *exactly* the order used in the syntax declarations immediately above.

### The configuration file:

A configuration file is specified with the `-c config_file` option:

```
h5import infile -c config_file [infile -c config_file2 ...] -outfile
outfile
```

The configuration file is an ASCII file and must be organized as "Configuration\_Keyword Value" pairs, with one pair on each line. For example, the line indicating that the input data class (configuration keyword INPUT-CLASS) is floating point in a text file (value TEXTFP) would appear as follows:

```
INPUT-CLASS TEXTFP
```

A configuration file may have the following keywords each followed by one of the following defined values. One entry for each of the first two keywords, RANK and DIMENSION-SIZES, is required; all other keywords are optional.

Keyword Value	Description
RANK <i>rank</i>	The number of dimensions in the dataset. (Required) An integer specifying the number of dimensions in the dataset. Example: 4 for a 4-dimensional dataset.
DIMENSION-SIZES <i>dim_sizes</i>	Sizes of the dataset dimensions. (Required) A string of space-separated integers specifying the sizes of the dimensions in the dataset. The number of sizes in this entry must match the value in the RANK entry. The fastest-changing dimension must be listed first. Example: 4 3 4 38 for a 38x4x3x4 dataset.

---

PATH	Path of the output dataset.
<i>path</i>	<p>The full HDF5 pathname identifying the output dataset relative to the root group within the output file.</p> <p>I.e., <i>path</i> is a string consisting of optional group names, each followed by a slash, and ending with a dataset name. If the groups in the path do not exist, they will be created.</p> <p>If PATH is not specified, the output dataset is stored as a member of the root group and the default dataset name is <code>dataset0</code> for the first input dataset, <code>dataset1</code> for the second input dataset, <code>dataset2</code> for the third input dataset, etc.</p> <p>Note that <code>h5import</code> does not overwrite a pre-existing dataset of the specified or default name. When an existing dataset of a conflicting name is encountered, <code>h5import</code> quits with an error; the current input file and any subsequent input files are not processed.</p> <p>Example: The configuration file entry</p> <pre>PATH grp1/grp2/dataset1</pre> <p>indicates that the output dataset <code>dataset1</code> will be written in the group <code>grp2/</code> which is in the group <code>grp1/</code>, a member of the root group in the output file.</p>

---

INPUT-CLASS	A string denoting the type of input data.
TEXTIN	Input is signed integer data in an ASCII file.
TEXTUIN	Input is unsigned integer data in an ASCII file.
TEXTFP	Input is floating point data in either fixed-point notation (e.g., 325.34) or scientific notation (e.g., 3.2534E+02) in an ASCII file.
IN	Input is signed integer data in a binary file.
UIN	Input is unsigned integer data in a binary file.
FP	Input is floating point data in a binary file. (Default)
STR	Input is character data in an ASCII file. With this value, the configuration keywords RANK, DIMENSION-SIZES, OUTPUT-CLASS, OUTPUT-SIZE, OUTPUT-ARCHITECTURE, and OUTPUT-BYTE-ORDER will be ignored. (Not implemented in this release.)

---

INPUT-SIZE	An integer denoting the size of the input data, in bits.
8	For signed and unsigned integer data: TEXTIN, TEXTUIN, IN, or UIN. (Default: 32)
16	
32	
64	
32	For floating point data: TEXTFP or FP. (Default: 32)
64	

---

OUTPUT-CLASS	A string denoting the type of output data.
IN	Output is signed integer data. (Default if INPUT-CLASS is IN or TEXTIN)
UIN	Output is unsigned integer data. (Default if INPUT-CLASS is UIN or TEXTUIN)
FP	Output is floating point data. (Default if INPUT-CLASS is not specified or is FP or TEXTFP)
STR	Output is character data, to be written as a 1-dimensional array of strings. (Default if INPUT-CLASS is STR) (Not implemented in this release.)
OUTPUT-SIZE	An integer denoting the size of the output data, in bits.
8	For signed and unsigned integer data: IN or UIN. (Default: Same as INPUT-SIZE, else 32)
16	
32	
64	
32	For floating point data: FP. (Default: Same as INPUT-SIZE, else 32)
64	
OUTPUT-ARCHITECTURE	A string denoting the type of output architecture.
NATIVE	See the "Predefined Atomic Types" section in the "HDF5 Datatypes" chapter of the <i>HDF5 User's Guide</i> for a discussion of these architectures. Values marked with an asterisk (*) are not implemented in this release. (Default: NATIVE)
STD	
IEEE	
INTEL *	
CRAY *	
MIPS *	
ALPHA *	
UNIX *	
OUTPUT-BYTE-ORDER	A string denoting the output byte order. This entry is ignored if the OUTPUT-ARCHITECTURE is not specified or if it is not specified as IEEE, UNIX, or STD.
BE	Big-endian. (Default)
LE	Little-endian.

---

The following options are disabled by default, making the default storage properties no chunking, no compression, no external storage, and no extensible dimensions.

---

CHUNKED-DIMENSION-SIZES <i>chunk_dims</i>	<p>Dimension sizes of the chunk for chunked output data.</p> <p>A string of space-separated integers specifying the dimension sizes of the chunk for chunked output data. The number of dimensions must correspond to the value of RANK.</p> <p>The presence of this field indicates that the output dataset is to be stored in chunked layout; if this configuration field is absent, the dataset will be stored in contiguous layout.</p>
COMPRESSION-TYPE  GZIP	<p>Type of compression to be used with chunked storage. Requires that CHUNKED-DIMENSION-SIZES be specified.</p> <p>Gzip compression.</p> <p>Other compression algorithms are not implemented in this release of h5import.</p>
COMPRESSION-PARAM  1 through 9	<p>Compression level. Required if COMPRESSION-TYPE is specified.</p> <p>Gzip compression levels: 1 will result in the fastest compression while 9 will result in the best compression ratio. (Default: 6. The default gzip compression level is 6; not all compression methods will have a default level.)</p>
EXTERNAL-STORAGE  <i>external_file</i>	<p>Name of an external file in which to create the output dataset. Cannot be used with CHUNKED-DIMENSIONS-SIZES, COMPRESSION-TYPE, OR MAXIMUM-DIMENSIONS.</p> <p>A string specifying the name of an external file.</p>
MAXIMUM-DIMENSIONS  <i>max_dims</i>	<p>Maximum sizes of all dimensions. Requires that CHUNKED-DIMENSION-SIZES be specified.</p> <p>A string of space-separated integers specifying the maximum size of each dimension of the output dataset. A value of -1 for any dimension implies unlimited size for that particular dimension. The number of dimensions must correspond to the value of RANK.</p>

---

**Options and Parameters:**

<code>infile(s)</code>	Name of the Input file(s).
<code>in_options</code>	Input options. Note that while only the <code>-dims</code> argument is required, arguments must be used in the order in which they are listed below.
<code>-d dim_list</code>	
<code>-dims dim_list</code>	Input data dimensions. <i>dim_list</i> is a string of comma-separated numbers with no spaces describing the dimensions of the input data. For example, a 50 x 100 2-dimensional array would be specified as <code>-dims 50,100</code> . Required argument: if no configuration file is used, this command-line argument is mandatory.
<code>-p pathname</code>	
<code>-pathname pathname</code>	<i>pathname</i> is a string consisting of one or more strings separated by slashes (/) specifying the path of the dataset in the output file. If the groups in the path do not exist, they will be created. Optional argument: if not specified, the default path is <code>dataset1</code> for the first input dataset, <code>dataset2</code> for the second input dataset, <code>dataset3</code> for the third input dataset, etc. <code>h5import</code> does not overwrite a pre-existing dataset of the specified or default name. When an existing dataset of a conflicting name is encountered, <code>h5import</code> quits with an error; the current input file and any subsequent input files are not processed.
<code>-t input_class</code>	
<code>-type input_class</code>	<i>input_class</i> specifies the class of the input data and determines the class of the output data. Valid values are as defined in the Keyword/Values table in the section "The configuration file" above. Optional argument: if not specified, the default value is FP.
<code>-s input_size</code>	
<code>-size input_size</code>	<i>input_size</i> specifies the size in bits of the input data and determines the size of the output data. Valid values for signed or unsigned integers are 8, 16, 32, and 64. Valid values for floating point data are 32 and 64. Optional argument: if not specified, the default value is 32.
<code>-c config_file</code>	<i>config_file</i> specifies a configuration file. This argument replaces all other arguments except <i>infile</i> and <i>outfile</i>
<code>-h</code>	
<code>-help</code>	Prints the <code>h5import</code> usage summary: <code>h5import -h[elp], OR</code> <code>h5import &lt;infile&gt; &lt;options&gt; [&lt;infile&gt;</code> <code>&lt;options&gt;...] -o[utfile] &lt;outfile&gt;</code> Then exits.
<code>outfile</code>	Name of the HDF5 output file.

**Examples:****Using command-line arguments:**

```
h5import infile -dims 2,3,4 -type TEXTIN -size 32 -o out1
```

This command creates a file `out1` containing a single 2x3x4 32-bit integer dataset. Since no pathname is specified, the dataset is stored in `out1` as `/dataset1`.

```
h5import infile -dims 20,50 -path bin1/dset1 -type FP -size 64 -o out2
```

This command creates a file `out2` containing a single a 20x50 64-bit floating point dataset. The dataset is stored in `out2` as `/bin1/dset1`.

**Sample configuration files:**

The following configuration file specifies the following:

- The input data is a 5x2x4 floating point array in an ASCII file.
- The output dataset will be saved in chunked layout, with chunk dimension sizes of 2x2x2.
- The output datatype will be 64-bit floating point, little-endian, IEEE.
- The output dataset will be stored in `outfile` at `/work/h5/pkamat/First-set`.
- The maximum dimension sizes of the output dataset will be 8x8x(unlimited).

```
PATH work/h5/pkamat/First-set
INPUT-CLASS TEXTFP
RANK 3
DIMENSION-SIZES 5 2 4
OUTPUT-CLASS FP
OUTPUT-SIZE 64
OUTPUT-ARCHITECTURE IEEE
OUTPUT-BYTE-ORDER LE
CHUNKED-DIMENSION-SIZES 2 2 2
MAXIMUM-DIMENSIONS 8 8 -1
```

The next configuration file specifies the following:

- The input data is a 6x3x5x2x4 integer array in a binary file.
- The output dataset will be saved in chunked layout, with chunk dimension sizes of 2x2x2x2x2.
- The output datatype will be 32-bit integer in NATIVE format (as the output architecture is not specified).
- The output dataset will be compressed using Gzip compression with a compression level of 7.
- The output dataset will be stored in `outfile` at `/Second-set`.

```
PATH Second-set
INPUT-CLASS IN
RANK 5
DIMENSION-SIZES 6 3 5 2 4
OUTPUT-CLASS IN
OUTPUT-SIZE 32
CHUNKED-DIMENSION-SIZES 2 2 2 2 2
COMPRESSION-TYPE GZIP
COMPRESSION-PARAM 7
```

**History:**

Release	Command Line Tool
1.6.0	Tool introduced in this release.

**Tool Name:** gif2h5

**Syntax:**

`gif2h5 gif_file h5_file`

**Purpose:**

Converts a GIF file to an HDF5 file.

**Description:**

`gif2h5` accepts as input the GIF file *gif\_file* and produces the HDF5 file *h5\_file* as output.

**Options and Parameters:**

*gif\_file*    The name of the input GIF file

*h5\_file*    The name of the output HDF5 file

**Tool Name:** h52gif

**Syntax:**

```
h52gif h5_file gif_file -i h5_image [ -p h5_palette ]
```

**Purpose:**

Converts an HDF5 file to a GIF file.

**Description:**

h52gif accepts as input the HDF5 file *h5\_file* and the names of images and associated palettes within that file as input and produces the GIF file *gif\_file*, containing those images, as output.

h52gif expects *at least* one *h5\_image*. You may repeat

```
-i h5_image [ -p h5_palette ]
```

up to 50 times, for a maximum of 50 images.

**Options and Parameters:**

<i>h5_file</i>	The name of the input HDF5 file
<i>gif_file</i>	The name of the output GIF file
<i>-i h5_image</i>	Image option, specifying the name of an HDF5 image or dataset containing an image to be converted
<i>-p h5_palette</i>	Palette option, specifying the name of an HDF5 dataset containing a palette to be used in an image conversion



**Tool Name:** h5toh4

**Syntax:**

```
h5toh4 -h
h5toh4 h5file h4file
h5toh4 h5file
h5toh4 -m h5file1 h5file2 h5file3 ...
```

**Purpose:**

Converts an HDF5 file into an HDF4 file.

**Description:**

h5toh4 is an HDF5 utility which reads an HDF5 file, *h5file*, and converts all supported objects and pathways to produce an HDF4 file, *h4file*. If *h4file* already exists, it will be replaced.

If only one file name is given, the name must end in *.h5* and is assumed to represent the HDF5 input file. h5toh4 replaces the *.h5* suffix with *.hdf* to form the name of the resulting HDF4 file and proceeds as above. If a file with the name of the intended HDF4 file already exists, h5toh4 exits with an error without changing the contents of any file.

The *-m* option allows multiple HDF5 file arguments. Each file name is treated the same as the single file name case above.

The *-h* option causes the following syntax summary to be displayed:

```
h5toh4 file.h5 file.hdf
h5toh4 file.h5
h5toh4 -m file1.h5 file2.h5 ...
```

The following HDF5 objects occurring in an HDF5 file are converted to HDF4 objects in the HDF4 file:

- ◇ HDF5 group objects are converted into HDF4 Vgroup objects. HDF5 hard links and soft links pointing to objects are converted to HDF4 Vgroup references.
- ◇ HDF5 dataset objects of integer datatype are converted into HDF4 SDS objects. These datasets may have up to 32 fixed dimensions. The slowest varying dimension may be extendable. 8-bit, 16-bit, and 32-bit integer datatypes are supported.
- ◇ HDF5 dataset objects of floating point datatype are converted into HDF4 SDS objects. These datasets may have up to 32 fixed dimensions. The slowest varying dimension may be extendable. 32-bit and 64-bit floating point datatypes are supported.
- ◇ HDF5 dataset objects of single dimension and compound datatype are converted into HDF4 Vdata objects. The length of that single dimension may be fixed or extendable. The members of the compound datatype are constrained to be no more than rank 4.
- ◇ HDF5 dataset objects of single dimension and fixed length string datatype are converted into HDF4 Vdata objects. The HDF4 Vdata is a single field whose order is the length of the HDF5 string type. The number of records of the Vdata is the length of the single dimension which may be fixed or extendable.

Other objects are not converted and are not recorded in the resulting *h4file*.

Attributes associated with any of the supported HDF5 objects are carried over to the HDF4 objects. Attributes may be of integer, floating point, or fixed length string datatype and they may have up to 32 fixed dimensions.

All datatypes are converted to big-endian. Floating point datatypes are converted to IEEE format.

**Note:**

The `h5toh4` and `h4toh5` utilities are no longer part of the HDF5 product; they are distributed separately through the page [Converting between HDF \(4.x\) and HDF5](#).

**Options and Parameters:**

- `-h` Displays a syntax summary.
- `-m` Converts multiple HDF5 files to multiple HDF4 files.
- h5file* The HDF5 file to be converted.
- h4file* The HDF4 file to be created.

**Tool Name:** h4toh5

**Syntax:**

```
h4toh5 -h
h4toh5 h4file h5file
h4toh5 h4file
```

**Purpose:**

Converts an HDF4 file to an HDF5 file.

**Description:**

`h4toh5` is a file conversion utility that reads an HDF4 file, *h4file* (input `.hdf` for example), and writes an HDF5 file, *h5file* (output `.h5` for example), containing the same data.

If no output file *h5file* is specified, `h4toh5` uses the input filename to designate the output file, replacing the extension `.hdf` with `.h5`. For example, if the input file `scheme3.hdf` is specified with no output filename, `h4toh5` will name the output file `scheme3.h5`.

The `-h` option causes a syntax summary similar to the following to be displayed:

```
h4toh5 inputfile.hdf outputfile.h5
h4toh5 inputfile.hdf
```

Each object in the HDF4 file is converted to an equivalent HDF5 object, according to the mapping described in *Mapping HDF4 Objects to HDF5 Objects*.

`h4toh5` converts the following HDF4 objects:

HDF4 Object	Resulting HDF5 Object
SDS	Dataset
GR, RI8, and RI24 image	Dataset
Vdata	Dataset
Vgroup	Group
Annotation	Attribute
Palette	Dataset

**Note:**

The `h4toh5` and `h5toh4` utilities are no longer part of the HDF5 product; they are distributed separately through the page [Converting between HDF \(4.x\) and HDF5](#).

**Options and Parameters:**

```
-h      Displays a syntax summary.
h4file The HDF4 file to be converted.
h5file The HDF5 file to be created.
```

**Tool Name:** h5stat

**Syntax:**

h5stat [*OPTIONS*] *file*

**Purpose:**

Reports HDF5 file and object statistics.

**Description:**

h5stat reports statistics regarding an HDF5 file and the objects in that file.

See “RFC: h5stat tool” for a complete description of this tool.

**Options and Parameters:**

-V or --version	Print version number and exit.
-f or --file	Print file information.
-F or --filemetadata	Print file meta data.
-g or --group	Print group information.
-G or --groupmetadata	Print group meta data.
-d or --dset	Print dataset information.
-D or --dsetmetadata	Print dataset meta data.
-T or --dtypemetadata	Print datatype meta data.
-A or --attribute	Print attribute information.

**History:**

Release	Command Line Tool
1.8.0	Tool introduced in this release.

**Tool Name:** h5perf

**Syntax:**

```
h5perf [-h | --help]
h5perf [options]
```

**Purpose:**

Tests Parallel HDF5 performance.

**Description:**

h5perf is a tool for testing the performance of the Parallel HDF5 Library. The tool can perform testing with 1-dimensional and 2-dimensional buffers and datasets. For details regarding data organization and access, see “h5perf, a Parallel File System Benchmarking Tool.”

The following environment variables have the following effects on h5perf behavior:

HDF5_NOCLEANUP	If set, h5perf does not remove data files. (Default: Data files are removed.)
HDF5_MPI_INFO	Must be set to a string containing a list of semi-colon separated key=value pairs for the MPI INFO object. Example:
HDF5_PARAPREFIX	Sets the prefix for parallel output data files.

**Options and Parameters:**

These terms are used as follows in this section:

*file* A filename

*size* A size specifier, expressed as an integer greater than or equal to 0 (zero) followed by a size indicator:

K for kilobytes (1024 bytes)

M for megabytes (1048576 bytes)

G for gigabytes (1073741824 bytes)

Example: 37M specifies 37 megabytes or 38797312 bytes.

*N* An integer greater than or equal to 0 (zero)

-h, --help

Prints a usage message and exits.

-a *size*, --align=*size*

Specifies the alignment of objects in the HDF5 file.

(Default: 1)

-A *api\_list*, --api=*api\_list*

Specifies which APIs to test. *api\_list* is a comma-separated list with the following valid values:

phdf5 Parallel HDF5

mpio MPI-I/O

posix POSIX

(Default: All APIs)

Example, --api=mpio,phdf5 specifies that the MPI I/O and Parallel HDF5 APIs are to be monitored.

`-B size, --block-size=size`

Controls the block size within the transfer buffer.

(Default: Half the number of bytes per process per dataset)

Block size versus transfer buffer size:

The *transfer buffer size* is the size of a buffer in memory. The data in that buffer is broken into *block size* pieces and written to the file.

Transfer buffer size is discussed below with the `-x` (or `--min-xfer-size`) and `-X` (or `--max-xfer-size`) options.

The pattern in which the blocks are written to the file is described in the discussion of the `-I` (or `--interleaved`) option.

`-c, --chunk`

Creates HDF5 datasets in chunked layout.

(Default: Off)

`-C, --collective`

Use collective I/O for the MPI I/O and Parallel HDF5 APIs.

(Default: Off, i.e., independent I/O)

If this option is set and the MPI-I/O and PHDF5 APIs are in use, all the blocks of every process will be written at once with an MPI derived type.

`-d N, --num-dsetsN`

Sets the number of datasets per file.

(Default: 1)

`-D debug_flags, --debug=debug_flags`

Sets the debugging level. *debug\_flags* is a comma-separated list of debugging flags with the following valid values:

- 1 Minimal debugging
- 2 Moderate debugging (“not quite everything”)
- 3 Extensive debugging (“everything”)
- 4 All possible debugging (“the kitchen sink”)
- r Raw data I/O throughput information
- t Times, in additions to throughputs
- v Verify data correctness

(Default: No debugging)

Example: `--debug=2,r,t` specifies to run a moderate level of debugging while collecting raw data I/O throughput information and verifying the correctness of the data.

Throughput values are computed by dividing the total amount of transferred data (excluding metadata) over the time spent by the slowest process. Several time counters are defined to measure the data transfer time and the total elapsed time; the latter includes the time spent during file open and close operations. A number of iterations can be specified with the option `-i` (or `--num-iterations`) to create the desired population of measurements from which maximum, minimum, and average values can be obtained. The timing scheme is the following:

for each iteration

```

        initialize elapsed time counter
        initialize data transfer time counter
        for each file
            start and accumulate elapsed time counter
            file open
            start and accumulate data transfer time counter
            access entire file
            stop data transfer time counter
            file close
            stop elapsed time counter
        end file
        save elapsed time counter
        save data transfer time counter
    end iteration

```

The reported write throughput is based on the accumulated data transfer time, while the write open-close throughput uses the accumulated elapsed time.

`-e size, --num-bytes=size`

Specifies the number of bytes per process per dataset.  
(Default: 256K for 1D, 8K for 2D)

Depending on the selected geometry, each test dataset can be a linear array of size  $\text{bytes-per-process} * \text{num-processes}$  or a square array of size  $(\text{bytes-per-process} * \text{num-processes}) \times (\text{bytes-per-process} * \text{num-processes})$ . The number of processes is set by the `-p` (or `--min-num-processes`) and `-P` (or `--max-num-processes`) options.

`-F N, --num-files=N`

Specifies the number of files.  
(Default: 1)

`-g, --geometry`

Selects 2D geometry for testing.  
(Default: Off, i.e., 1D geometry)

`-i N, --num-iterations=N`

Sets the number of iterations to perform.  
(Default: 1)

`-I, --interleaved`

Sets interleaved block I/O.  
(Default: Contiguous block I/O)

Interleaved and contiguous patterns in 1D geometry:

When a contiguous access pattern is chosen, the dataset is evenly divided into *num-processes* regions and each process writes data to its assigned region. When interleaved blocks are written to a dataset, space for the first block of the first process is allocated in the dataset, then space is allocated for the first block of the second process, etc., until space is allocated for the first block of each process, then space is allocated for the second block of the first process, the second block of the second process, etc.

For example, with a three process run, 512KB bytes-per-process, 256KB transfer buffer size, and 64KB block size, each process must issue two transfer requests to complete access to the dataset.

Contiguous blocks of the first transfer request are written as follows:

1111----2222----3333----

Interleaved blocks of the first transfer request are written as follows:

123123123123-----

The actual number of I/O operations involved in a transfer request depends on the access pattern and communication mode. When using independent I/O with an interleaved access pattern, each process performs four small non-contiguous I/O operations per transfer request. If collective I/O is turned on, the combined content of the buffers of the three processes will be written using one collective I/O operation per transfer request.

For details regarding the impact of performance and access patterns in 2D, see “h5perf, a Parallel File System Benchmarking Tool.”

`-m, --mpi-posix`

Sets use of MPI-posix driver for HDF5 I/O.  
(Default: MPI-I/O driver)

`-n, --no-fill`

Specifies to not write fill values to HDF5 datasets. This option is supported only in HDF5 Release v1.6 or later.  
(Default: Off, i.e., write fill values)

`-o file, --output=file`

Sets the output file for raw data to *file*.  
(Default: None)

`-p N, --min-num-processes=N`

Sets the minimum number of processes to be used.  
(Default: 1)

`-P N, --max-num-processes=N`

Sets the maximum number of processes to be used.  
(Default: All MPI\_COMM\_WORLD processes)

`-T size, --threshold=size`

Sets the threshold for alignment of objects in the HDF5 file.  
(Default: 1)

`-w, --write-only`

Performs only write tests, not read tests.  
(Default: Read and write tests)



`-x size, --min-xfer-size=size`

Sets the minimum transfer buffer size.  
(*Default:* Half the number of bytes per processor per dataset)

This option and the `-X size` option (or `--max-xfer-size=size`) control *transfer-buffer-size*, the size of the transfer buffer in memory. In 1D geometry, the transfer buffer is a linear array of size *transfer-buffer-size*. In 2D geometry, the transfer buffer is a rectangular array of size *block-size*  $\times$  *transfer-buffer-size*, or *transfer-buffer-size*  $\times$  *block-size* if the interleaved access pattern is selected.

`-X size, --max-xfer-size=size`

Sets the maximum transfer buffer size.  
(*Default:* The number of bytes per processor per dataset)

### History:

Release	Change
1.6.0	Tool introduced in this release.
1.6.8 and 1.8.0	Option <code>-g, --geometry</code> introduced in this release.

**Tool Name:** h5perf\_serial

**Syntax:**

```
h5perf_serial [-h|--help]
h5perf_serial [options]
```

**Purpose:**

Tests HDF5 serial performance.

**Description:**

h5perf\_serial provides tools for testing the performance of the HDF5 Library in serial mode.

See “h5perf\_serial, a Serial File System Benchmarking Tool” for a complete description of this tool.

The following environment variable can be set to control the specified aspect of h5perf\_serial behavior:

HDF5_NOCLEANUP	If set, h5perf_serial does not remove data files. (Default: Data files are removed.)
HDF5_PREFIX	Sets the prefix for output data files.

**Options and Parameters:**

The term *size specifier* is used as follows in this section:

A size specifier is an integer greater than or equal to 0 (zero) followed by a size indicator:

K for kilobytes (1024 bytes)

M for megabytes (1048576 bytes)

G for gigabytes (1073741824 bytes)

Example: 37M specifies 37 megabytes or 38797312 bytes.

-A <i>api_list</i>	Specifies which APIs to test. <i>api_list</i> is a comma-separated list with the following valid values: <div> <div>hdf5</div> <div>HDF5 Library APIs</div> </div> <div> <div>posix</div> <div>POSIX APIs</div> </div> (Default: All APIs are monitored.)  Example: -A hdf5, posix specifies that the HDF5 and POSIX APIs are to be monitored.
-c <i>chunk_size_list</i>	Specifies chunked storage and defines chunks dimensions and sizes. (Default: Chunking is off.)  <i>chunk_size_list</i> is a comma-separated list of size specifiers. For example, a <i>chunk_size_list</i> value of <div> <div>2K, 4K, 6M</div> </div> specifies that chunking is turned on and that chunk size is 2 kilobytes by 4 kilobytes by 6 megabytes.
-e <i>dataset_size_list</i>	Specifies dataset dimensionality and dataset dimension sizes. (Default dataset size is 100x200, or 100, 200.)  <i>dataset_size_list</i> is a comma-separated list of size specifiers, which are defined above.

- For example, a *dataset\_size\_list* value of  
     2K, 4K, 6M  
 specifies a 2 kilobytes by 4 kilobytes by 6 megabytes dataset.
- i iterations** Specifies the number of iterations to perform.  
*(Default: A single iteration, 1, is performed.)*
- r access\_order** *iterations* is an integer specifying the number of iterations.  
 Specifies dimension access order.  
*(Default: 1, 2)*
- access\_order* is a comma-separated list of integers specifying the order of access. For example,  
     -r 1, 3, 2  
 specifies the traversal of dimension 1 first, then dimension 3, and finally dimension 2.
- t** Selects extendable HDF5 dataset dimensions.  
*(Default: Datasets are fixed size.)*
- v file\_driver** Selects HDF5 driver to be used for HDF5 file access.  
*(Default: sec2)*
- Valid values are as follows:  
     sec2  
     stdio  
     core  
     split  
     multi  
     family  
     direct
- w** Specifies the performance of write tests only, read performance will not be tested.  
*(Default: Both write and read tests are performed.)*
- x buffer\_size\_list** Specifies transfer buffer dimensions and sizes.  
*(Default: 10, 20)*

**History:**

Release	Command Line Tool
1.8.1	Tool introduced in this release.

**Tool Name:** h5redeploy

**Syntax:**

```
h5redeploy [help | -help]
h5redeploy [-echo] [-force] [-prefix=dir] [-tool=tool] [-show]
```

**Purpose:**

Updates HDF5 compiler tools after an HDF5 software installation in a new location.

**Description:**

h5redeploy updates the HDF5 compiler tools after the HDF5 software has been installed in a new location.

**Options and Parameters:**

help, -help	Prints a help message.
-echo	Shows all the shell commands executed.
-force	Performs the requested action without offering any prompt requesting confirmation.
-prefix= <i>dir</i>	Specifies a new directory in which to find the HDF5 subdirectories <code>lib/</code> and <code>include/</code> . (Default: current working directory)
-tool= <i>tool</i>	Specifies the tool to update. <i>tool</i> must be in the current directory and must be writable. (Default: <code>h5cc</code> )
-show	Shows all of the shell commands to be executed without actually executing them.

**History:**

Release	Command Line Tool
1.6.0	Tool introduced in this release.

**Tool Name:** h5cc and h5pcc

**Syntax:**

```
h5cc [OPTIONS] <compile line>
h5pcc [OPTIONS] <compile_line>
```

**Purpose:**

Helper scripts to compile HDF5 applications.

**Description:**

h5cc and h5pcc can be used in much the same way as mpicc by MPICH is used to compile an HDF5 program. These tools take care of specifying on the command line the locations of the HDF5 header files and libraries. h5cc is for use in serial computing environments; h5pcc is for parallel environments.

h5cc and h5pcc subsume all other compiler scripts in that if you have used a set of scripts to compile the HDF5 library, then h5cc and h5pcc also use those scripts. For example, when compiling an MPICH program, you use the mpicc script. If you have built HDF5 using MPICH, then h5cc uses the MPICH program for compilation.

Some programs use HDF5 in only a few modules. It is not necessary to use h5cc or h5pcc to compile those modules which do not use HDF5. In fact, since h5cc and h5pcc are only convenience scripts, you can still compile HDF5 modules in the normal manner, though you will have to specify the HDF5 libraries and include paths yourself. Use the `-show` option to see the details.

An example of how to use h5cc to compile the program `hdf_prog`, which consists of the modules `prog1.c` and `prog2.c` and uses the HDF5 shared library, would be as follows. h5pcc is used in an identical manner.

```
# h5cc -c prog1.c
# h5cc -c prog2.c
# h5cc -shlib -o hdf_prog prog1.o prog2.o
```

**Options and Parameters:**

<code>-help</code>	Prints a help message.
<code>-echo</code>	Show all the shell commands executed.
<code>-prefix=DIR</code>	Use the directory <i>DIR</i> to find the HDF5 <code>lib/</code> and <code>include/</code> subdirectories. Default: prefix specified when configuring HDF5.
<code>-show</code>	Show the commands without executing them.
<code>-shlib</code>	Compile using shared HDF5 libraries.
<code>-noshlib</code>	Compile using static HDF5 libraries [default].
<code>&lt;compile line&gt;</code>	The normal compile line options for your compiler. h5cc and h5pcc use the the same compiler you used to compile HDF5. Check your compiler's manual for more information on which options are needed.

**Environment Variables:**

When set, these environment variables override some of the built-in h5cc and h5pcc defaults.

HDF5_CC	Use a different C compiler.
HDF5_CLINKER	Use a different linker.
HDF5_USE_SHLIB=[yes no]	Use shared version of the HDF5 library [default: no].

**Tool Name:** h5fc and h5pfc

**Syntax:**

```
h5fc [OPTIONS] <compile_line>
h5pfc [OPTIONS] <compile_line>
```

**Purpose:**

Helper scripts to compile HDF5 Fortran90 applications.

**Description:**

h5fc and h5pfc can be used in much the same way mpif90 by MPICH is used to compile an HDF5 program. These tools take care of specifying on the command line the locations of the HDF5 header files and libraries. h5fc is for use in serial computing environments; h5pfc is for parallel environments.

h5fc and h5pfc subsume all other compiler scripts in that if you have used a set of scripts to compile the HDF5 Fortran library, then h5fc and h5pfc also use those scripts. For example, when compiling an MPICH program, you use the mpif90 script. If you have built HDF5 using MPICH, then h5fc uses the MPICH program for compilation.

Some programs use HDF5 in only a few modules. It is not necessary to use h5fc and h5pfc to compile those modules which do not use HDF5. In fact, since h5fc and h5pfc are only convenience scripts, you can still compile HDF5 Fortran modules in the normal manner, though you will have to specify the HDF5 libraries and include paths yourself. Use the -show option to see the details.

An example of how to use h5fc to compile the program hdf\_prog, which consists of the modules prog1.f90 and prog2.f90 and uses the HDF5 Fortran library, would be as follows. h5pfc is used in an identical manner.

```
# h5fc -c prog1.f90
# h5fc -c prog2.f90
# h5fc -o hdf_prog prog1.o prog2.o
```

**Options and Parameters:**

-help	Prints a help message.
-echo	Show all the shell commands executed.
-prefix=DIR	Use the directory DIR to find HDF5 lib/ and include/ subdirectories Default: prefix specified when configuring HDF5.
-show	Show the commands without executing them.
<compile_line>	The normal compile line options for your compiler. h5fc and h5pfc use the the same compiler you used to compile HDF5. Check your compiler's manual for more information on which options are needed.

**Environment Variables:**

When set, these environment variables override some of the built-in h5fc and h5pfc defaults.

HDF5_FC	Use a different Fortran90 compiler.
HDF5_FLINKER	Use a different linker.

**History:**

Release	Command Line Tool
1.6.0	Tool introduced in this release.

**Tool Name:** h5c++

**Syntax:**

```
h5c++ [ OPTIONS ] <compile line>
```

**Purpose:**

Helper script to compile HDF5 C++ applications.

**Description:**

h5c++ can be used in much the same way MPIch is used to compile an HDF5 program. It takes care of specifying where the HDF5 header files and libraries are on the command line.

h5c++ supersedes all other compiler scripts in that if you've used one set of compiler scripts to compile the HDF5 C++ library, then h5c++ uses those same scripts. For example, when compiling an MPIch program, you use the mpiCC script.

Some programs use HDF5 in only a few modules. It isn't necessary to use h5c++ to compile those modules which don't use HDF5. In fact, since h5c++ is only a convenience script, you are still able to compile HDF5 C++ modules in the normal way. In that case, you will have to specify the HDF5 libraries and include paths yourself.

An example of how to use h5c++ to compile the program hdf\_prog, which consists of modules prog1.cpp and prog2.cpp and uses the HDF5 C++ library, would be as follows:

```
# h5c++ -c prog1.cpp
# h5c++ -c prog2.cpp
# h5c++ -o hdf_prog prog1.o prog2.o
```

**Options and Parameters:**

-help	Prints a help message.
-echo	Show all the shell commands executed.
-prefix=DIR	Use the directory DIR to find HDF5 lib/ and include/ subdirectories Default: prefix specified when configuring HDF5.
-show	Show the commands without executing them.
<compile line>	The normal compile line options for your compiler. h5c++ uses the same compiler you used to compile HDF5. Check your compiler's manual for more information on which options are needed.

**Environment Variables:**

When set, these environment variables override some of the built-in defaults of h5c++.

HDF5_CXX	Use a different C++ compiler.
HDF5_CXXLINKER	Use a different linker.

**History:**

Release	Command Line Tool
1.6.0	Tool introduced in this release.





## HDF5 Predefined Datatypes

The following datatypes are predefined in HDF5.

### IEEE floating point datatypes

- 32-bit and 64-bit
- Big-endian and little-endian

```
H5T_IEEE_F32BE
H5T_IEEE_F32LE
H5T_IEEE_F64BE
H5T_IEEE_F64LE
```

### Standard datatypes

- Signed integer (2's complement), unsigned integer, and bitfield
- 8-bit, 16-bit, 32-bit, and 64-bit
- Big-endian and little-endian

H5T_STD_I8BE	H5T_STD_U8BE	H5T_STD_B8BE
H5T_STD_I8LE	H5T_STD_U8LE	H5T_STD_B8LE
H5T_STD_I16BE	H5T_STD_U16BE	H5T_STD_B16BE
H5T_STD_I16LE	H5T_STD_U16LE	H5T_STD_B16LE
H5T_STD_I32BE	H5T_STD_U32BE	H5T_STD_B32BE
H5T_STD_I32LE	H5T_STD_U32LE	H5T_STD_B32LE
H5T_STD_I64BE	H5T_STD_U64BE	H5T_STD_B64BE
H5T_STD_I64LE	H5T_STD_U64LE	H5T_STD_B64LE

- Object reference or dataset region reference

```
H5T_STD_REF_OBJ
H5T_STD_REF_DSETREG
```

### UNIX-specific datatypes

- 32-bit and 64-bit
- Big-endian and little-endian

```
H5T_UNIX_D32BE
H5T_UNIX_D32LE
H5T_UNIX_D64BE
H5T_UNIX_D64LE
```

### C-specific datatype

- String datatype in C (size defined in bytes rather than in bits)

```
H5T_C_S1
```

**FORTRAN-specific datatype**

- String datatype in FORTRAN (as defined for the HDF5 C library)

H5T\_FORTRAN\_S1

**Intel-specific datatypes**

- For Intel CPUs
- Little-endian
- Signed integer (2's complement), unsigned integer, bitfield, and IEEE floating point
- 8-bit, 16-bit, 32-bit, and 64-bit

H5T_INTEL_I8	H5T_INTEL_B8
H5T_INTEL_I16	H5T_INTEL_B16
H5T_INTEL_I32	H5T_INTEL_B32
H5T_INTEL_I64	H5T_INTEL_B64
H5T_INTEL_U8	H5T_INTEL_F32
H5T_INTEL_U16	H5T_INTEL_F64
H5T_INTEL_U32	
H5T_INTEL_U64	

**DEC Alpha-specific datatypes**

- For DEC Alpha CPUs
- Little-endian
- Signed integer (2's complement), unsigned integer, bitfield, and IEEE floating point
- 8-bit, 16-bit, 32-bit, and 64-bit

H5T_ALPHA_I8	H5T_ALPHA_B8
H5T_ALPHA_I16	H5T_ALPHA_B16
H5T_ALPHA_I32	H5T_ALPHA_B32
H5T_ALPHA_I64	H5T_ALPHA_B64
H5T_ALPHA_U8	H5T_ALPHA_F32
H5T_ALPHA_U16	H5T_ALPHA_F64
H5T_ALPHA_U32	
H5T_ALPHA_U64	

**OpenVMS DEC Alpha-specific datatypes**

- For OpenVMS on DEC Alpha CPUs
- VAX byte order
- 32- and 64-bit floating point

H5T\_VAX\_F32 (Corresponds to F\_Floating type)  
 H5T\_VAX\_F64 (Corresponds to G\_Floating type)

**MIPS-specific datatypes**

- For MIPS CPUs, commonly used in SGI system
- Big-endian
- Signed integer (2's complement), unsigned integer, bitfield, and IEEE floating point
- 8-bit, 16-bit, 32-bit, and 64-bit

H5T_MIPS_I8	H5T_MIPS_B8
H5T_MIPS_I16	H5T_MIPS_B16
H5T_MIPS_I32	H5T_MIPS_B32
H5T_MIPS_I64	H5T_MIPS_B64
H5T_MIPS_U8	H5T_MIPS_F32
H5T_MIPS_U16	H5T_MIPS_F64
H5T_MIPS_U32	
H5T_MIPS_U64	

**Predefined native datatypes**

These are the datatypes detected by `H5detect`. Their names differ from other HDF5 datatype names as follows:

- ◆ Instead of a class name, precision, and byte order as the last component, they have a C-like datatype name.
- ◆ If the datatype begins with U, then it is the unsigned version of the integer datatype; other integer datatypes are signed.
- ◆ The datatype `LLONG` corresponds to C's `long_long` and `LDOUBLE` is `long_double`. These datatypes might be the same as `LONG` and `DOUBLE`, respectively.

H5T_NATIVE_CHAR	H5T_NATIVE_FLOAT
H5T_NATIVE_SCHAR	H5T_NATIVE_DOUBLE
H5T_NATIVE_UCHAR	H5T_NATIVE_LDOUBLE
H5T_NATIVE_SHORT	H5T_NATIVE_B8
H5T_NATIVE_USHORT	H5T_NATIVE_B16
	H5T_NATIVE_B32
	H5T_NATIVE_B64
H5T_NATIVE_INT	
H5T_NATIVE_UINT	
	H5T_NATIVE_OPAQUE
H5T_NATIVE_LONG	H5T_NATIVE_HADDR
H5T_NATIVE_ULONG	H5T_NATIVE_HSIZE
H5T_NATIVE_LLONG	H5T_NATIVE_HSSIZE
H5T_NATIVE_ULLONG	H5T_NATIVE_HERR
	H5T_NATIVE_HBOOL

## ANSI C9x-specific native integer datatypes

- Signed integer (2's complement), unsigned integer, and bitfield
- 8-bit, 16-bit, 32-bit, and 64-bit
- LEAST -- storage to use least amount of space  
FAST -- storage to maximize performance

H5T_NATIVE_INT8	H5T_NATIVE_INT32
H5T_NATIVE_UINT8	H5T_NATIVE_UINT32
H5T_NATIVE_INT_LEAST8	H5T_NATIVE_INT_LEAST32
H5T_NATIVE_UINT_LEAST8	H5T_NATIVE_UINT_LEAST32
H5T_NATIVE_INT_FAST8	H5T_NATIVE_INT_FAST32
H5T_NATIVE_UINT_FAST8	H5T_NATIVE_UINT_FAST32
H5T_NATIVE_INT16	H5T_NATIVE_INT64
H5T_NATIVE_UINT16	H5T_NATIVE_UINT64
H5T_NATIVE_INT_LEAST16	H5T_NATIVE_INT_LEAST64
H5T_NATIVE_UINT_LEAST16	H5T_NATIVE_UINT_LEAST64
H5T_NATIVE_INT_FAST16	H5T_NATIVE_INT_FAST64
H5T_NATIVE_UINT_FAST16	H5T_NATIVE_UINT_FAST64

## FORTRAN90 API datatypes

- Datatypes defined for the FORTRAN90 APIs
- Native integer, single-precision real, double-precision real, and character

```
H5T_NATIVE_INTEGER
H5T_NATIVE_REAL
H5T_NATIVE_DOUBLE
H5T_NATIVE_CHARACTER
```

- Signed integer (2's complement), unsigned integer, and IEEE floating point
- 8-bit, 16-bit, 32-bit, and 64-bit
- Big-endian and little-endian

H5T_STD_I8BE	H5T_STD_U8BE	H5T_IEEE_F32BE
H5T_STD_I8LE	H5T_STD_U8LE	H5T_IEEE_F32LE
H5T_STD_I16BE	H5T_STD_U16BE	H5T_IEEE_F64BE
H5T_STD_I16LE	H5T_STD_U16LE	H5T_IEEE_F64LE
H5T_STD_I32BE	H5T_STD_U32BE	
H5T_STD_I32LE	H5T_STD_U32LE	
H5T_STD_I64BE	H5T_STD_U64BE	
H5T_STD_I64LE	H5T_STD_U64LE	

- Object reference or dataset region reference

```
H5T_STD_REF_OBJ
H5T_STD_REF_DSETREG
```

# HDF5 Fortran90 Flags, Datatypes and User's Notes

## Fortran90 Datatypes

The Fortran90 HDF5 datatypes are listed in HDF5 Predefined Datatypes

## Fortran90 Flags

The Fortran90 HDF5 flags have the same meanings as the C flags defined in the *HDF5 Reference Manual* and the *HDF5 User's Guide*.

### File access flags

H5F_ACC_RDWR_F	H5F_ACC_EXCL_F	H5F_SCOPE_LOCAL_F
H5F_ACC_RDONLY_F	H5F_ACC_DEBUG_F	H5F_SCOPE_GLOBAL_F
H5F_ACC_TRUNC_F		

### Group management flags

H5G_UNKNOWN_F	H5G_DATASET_F	H5G_LINK_HARD_F
H5G_LINK_F	H5G_TYPE_F	H5G_LINK_SOFT_F
H5G_GROUP_F	H5G_LINK_ERROR_F	

### Dataset format flags

H5D_COMPACT_F	H5D_CONTIGUOUS_F	H5D_CHUNKED_F
---------------	------------------	---------------

### MPI IO data transfer flags

H5FD_MPIO_INDEPENDENT_F	H5FD_MPIO_COLLECTIVE_F
-------------------------	------------------------

### Error flags

H5E_NONE_MAJOR_F	H5E_CACHE_F	H5E_STORAGE_F
H5E_ARGS_F	H5E_BTREE_F	H5E_PLIST_F
H5E_RESOURCE_F	H5E_SYM_F	H5E_ATTR_F
H5E_INTERNAL_F	H5E_HEAP_F	H5E_PLINE_F
H5E_FILE_F	H5E_OHDR_F	H5E_EFL_F
H5E_IO_F	H5E_DATATYPE_F	H5E_REFERENCE_F
H5E_FUNC_F	H5E_DATASPACE_F	H5E_VFL_F
H5E_ATOM_F	H5E_DATASET_F	H5E_TBBT_F

### Object identifier flags

H5I_FILE_F	H5I_DATASPACE_F	H5I_BADID_F
H5I_GROUP_F	H5I_DATASET_F	
H5I_DATATYPE_F	H5I_ATTR_F	

## Property list flags

H5P_FILE_CREATE_F	H5P_DATASET_CREATE_F	H5P_MOUNT_F
H5P_FILE_ACCESS_F	H5P_DATASET_XFER_F	H5P_DEFAULT_F

## Reference pointer flags

H5R_OBJECT_F	H5R_DATASET_REGION_F
--------------	----------------------

## Dataspace flags

H5S_SCALAR_F	H5S_SELECT_SET_F	H5S_UNLIMITED_F
H5S_SIMPLE_F	H5S_SELECT_OR_F	H5S_ALL_F

## Datatype flags

H5T_NO_CLASS_F	H5T_ORDER_LE_F	H5T_NORM IMPLIED_F
H5T_INTEGER_F	H5T_ORDER_BE_F	H5T_NORM_MSBSET_F
H5T_FLOAT_F	H5T_ORDER_VAX_F	H5T_NORM_NONE_F
H5T_TIME_F	H5T_PAD_ZERO_F	H5T_CSET_ASCII_F
H5T_STRING_F	H5T_PAD_ONE_F	H5T_STR_NULLTERM_F
H5T_BITFIELD_F	H5T_PAD_BACKGROUND_F	H5T_STR_NULLPAD_F
H5T_OPAQUE_F	H5T_PAD_ERROR_F	H5T_STR_SPACEPAD_F
H5T_COMPOUND_F	H5T_SGN_NONE_F	H5T_STR_ERROR_F
H5T_REFERENCE_F	H5T_SGN_2_F	
H5T_ENUM_F	H5T_SGN_ERROR_F	

# HDF5 Fortran90 User's Notes

## About the source code organization

The Fortran APIs are organized in modules parallel to the HDF5 Interfaces. Each module is in a separate file with the name `H5*ff.f`. Corresponding C stubs are in the `H5*f.c` files. For example, the Fortran File APIs are in the file `H5Fff.f` and the corresponding C stubs are in the file `H5Ff.c`.

Each module contains Fortran definitions of the constants, interfaces to the subroutines if needed, and the subroutines themselves.

Users must use constant names in their programs instead of the numerical values, as the numerical values are subject to change without notice.

## About the Fortran APIs

The Fortran APIs come in the form of Fortran subroutines with the following characteristics:

- Each Fortran subroutine name is derived from the corresponding C function name by adding `"_f"` to the name. For example, the name of the C function to create an HDF5 file is `H5Fcreate`; the corresponding Fortran subroutine is `h5fcreate_f`.
- A description of each implemented Fortran subroutine and its parameters can be found following the description of the corresponding C function in the HDF5 Reference Manual provided with this release.
- The parameter list for each Fortran subroutine has two more parameters than the corresponding C function. These additional parameters hold the return value and an error code. The order of the Fortran

subroutine parameters may differ from the order of the C function parameters. The Fortran subroutine parameters are listed in the following order:

- ◆ Required input parameters
- ◆ Output parameters, including return value and error code
- ◆ Optional input parameters

For example, the C function to create a dataset has the following prototype:

```
hid_t H5Dcreate(hid_t loc_id, char *name, hid_t type_id,
               hid_t space_id, hid_t creation_prp);
```

The corresponding Fortran subroutine has the following form:

```
SUBROUTINE h5dcreate_f(loc_id, name, type_id, space_id, dset_id,
                      hdferr, creation_prp)
```

The first four parameters of the Fortran subroutine correspond to the C function parameters. The fifth parameter, `dset_id`, is an output parameter and contains a valid dataset identifier if the value of the sixth output parameter `hdferr` indicates successful completion. (Error code descriptions are provided with the subroutine descriptions in the Reference Manual.) The seventh input parameter, `creation_prp`, is optional, and may be omitted when the default creation property list is used.

- Parameters to the Fortran subroutines have one of the following predefined datatypes (see the file `H5fortran_types.f90` for KIND definitions):

- ◆ `INTEGER(HID_T)` compares with the `hid_t` datatype in the HDF5 C APIs.
- ◆ `INTEGER(HSIZE_T)` compares with `hsize_t` in the HDF5 C APIs.
- ◆ `INTEGER(HSSIZE_T)` compares with `hssize_t` in the HDF5 C APIs.
- ◆ `INTEGER(SIZE_T)` compares with the C `size_t` datatype.

These integer types usually correspond to 4 or 8 byte integers, depending on the FORTRAN90 compiler and the corresponding HDF5 C library definitions.

The H5R module defines two types of references:

- ◆ `TYPE(HOBJ_REF_T_F)` compares to `hobj_ref_t` in the HDF5 C API.
- ◆ `TYPE(HDSET_REG_REF_T_F)` compares to `hdset_reg_ref_t` in the HDF5 C API.

- Each Fortran application must call the `h5open_f` subroutine to initialize the Fortran interface and the HDF5 C Library before calling any HDF5 Fortran subroutine. The application must call the `h5close_f` subroutine after all calls to the HDF5 Fortran Library to close the Fortran interface and HDF5 C Library.
- List of the predefined datatypes can be found in the HDF5 Reference Manual provided with this release. See HDF5 Predefined Datatypes.
- When a C application reads data stored from a Fortran program, the data will appear to be transposed due to the difference in the C and Fortran storage orders. For example, if Fortran writes a 4x6 two-dimensional dataset to the file, a C program will read it as a 6x4 two-dimensional dataset into memory. The HDF5 C utilities `h5dump` and `h5ls` will also display transposed data, if data is written from a Fortran program.
- Fortran indices are 1-based.
- Compound datatype datasets can be written or read by atomic fields only.





# API Compatibility Macros in HDF5

## Audience

The target audience for this document has existing applications that use the HDF5 Library, and is considering moving to HDF5 Release 1.8.0 to take advantage of the latest library features and enhancements.

## Compatibility Issues

HDF5 1.8.0 is a major update of the HDF5 Library. Several compatibility issues must be considered when migrating applications to the HDF5 1.8.0 release.

This document, *API Compatibility Macros in HDF5*, introduces the approach taken by The HDF Group (THG) in HDF Release 1.8.0 to help existing users of HDF5 address compatibility issues in the HDF5 API. The companion document, *New Features in HDF5 Release 1.8.0 and Format Compatibility Considerations*, discusses features introduced in HDF5 Release 1.8.0, the HDF5 API calls associated with those features, and the potential file format compatibility issues that may result if the new features are used.

## Summary and Motivation

In response to new and evolving requirements for the library and data format, several basic functions have changed since HDF5 was first released. To allow existing applications to continue to compile and run properly, all versions of these functions have been retained in the later releases of the HDF5 Library.

HDF5 Release 1.8.0 includes a number of new features that will offer many users of HDF5 substantial performance improvements and expanded capabilities. Many of these features can only be accessed via revised API calls. Given the scope of the changes, and recognizing the potentially time-consuming task of editing all the affected calls in user applications, THG has created a set of macros that can be used to flexibly and easily map existing API calls to either 1.6.x or 1.8.x (currently 1.8.0) functions. We refer to these as the *API Compatibility Macros*.

THG generally encourages users to update applications to work with the latest HDF5 library release, so that all new features and enhancements are available to them. At the same time, THG understands that under some circumstances updating applications may not be feasible or necessary. The API Compatibility Macros, described in this document, provide a bridge from old APIs to new, and can be particularly helpful in situations such as these:

- Source code is not available - only binaries are available; updating the application is not feasible.
- Source code is available, but there are no resources to update it.
- Source code is available, as are resources to update it, but the old version works quite well so updates are not a priority. At the same time, it is desirable to take advantage of certain efficiencies in the newer HDF5 release that do not require code changes.
- Source code is available, as are resources to update it, but the applications are large or complex, and must continue to run while the code updates are carried out.

## Understanding and Using the Macros

As part of HDF5 release 1.8.0, twenty-three functions that existed in previous versions of the library were updated with new calling parameters and given new names. The updated versions of the functions have a "2" at the end of the original function name. The original versions of these functions were retained and renamed to have a "1" at the end of the original function name. API Compatibility Macros, with the same names as the original function names, were created.

Concretely, consider the function `H5Acreate` in HDF5 releases prior to 1.8.0:

Original function name and signature, in releases prior to 1.8.0:

```
hid_t H5Acreate( hid_t loc_id, const char *attr_name, hid_t type_id, hid_t
space_id, hid_t acpl_id )
```

Updated function and signature, introduced in release 1.8.0:

```
hid_t H5Acreate2( hid_t loc_id, const char *attr_name, hid_t type_id, hid_t
space_id, hid_t acpl_id, hid_t aapl_id )
```

Original function and signature, renamed in release 1.8.0:

```
hid_t H5Acreate1( hid_t loc_id, const char *attr_name, hid_t type_id, hid_t
space_id, hid_t acpl_id )
```

API Compatibility Macro, introduced in release 1.8.0:

`H5Acreate` The macro, `H5Acreate`, will be mapped to either `H5Acreate1` or `H5Acreate2`. The mapping is determined by a combination of the configuration options use to build the HDF5 Library and compile-time options used to build the application. The calling parameters used with the `H5Acreate` Compatibility Macro should match the number and type of the function they will be mapped to (`H5Acreate1` or `H5Acreate2`).

The function names ending in "1" or "2" are referred to as *version-numbered names*, and the corresponding functions are referred to as *version-numbered functions*. For new code development, THG recommends use of the Compatibility Macro mapped to the latest version of the function. The original versions of these functions, with names ending in "1", should be considered deprecated and, in general, should not be used when developing new code.

### Compatibility Macro Mapping Options

To determine the mapping for a given API Compatibility Macro in a given application, a combination of user-controlled selections, collectively referred to as the *Compatibility Macro Mapping Options*, is considered in the following sequence:

1. What Compatibility Macro configuration option was used to build the HDF5 Library? We refer to this selection as the *Library Mapping*.
2. Was a Compatibility Macro global compile-time option specified when the application was built? We refer to this (optional) selection as the *Application Mapping*. If an Application Mapping exists, it overrides the Library Mapping.
3. Were any Compatibility Macro function-level compile-time options specified when the application was built? We refer to these (optional) selections as *Function Mappings*. If Function Mappings exist, they override Library and Application Mappings for the relevant API Compatibility Macros.

The tables that follow summarize the macro mapping behaviors, and the configuration and compile-time options that control the mappings. The macro `H5Gcreate` is used to demonstrate mapping behavior.

Regardless of the Macro Mapping Options used, the 1.8.x functions will always be available by explicitly calling the version-numbered functions by their version-numbered names. For example, `H5Gcreate2`. Through the Compatibility Macro Mapping Options provided, it is possible to disallow calls to the deprecated 1.6.x functions, such as `H5Gcreate1`. This capability can be used to guarantee only the most recent versions of the functions are being called.

### Library Mapping Options

When the HDF5 Library is built, `configure` flags can be used to control the API Compatibility Macro Mapping behavior exhibited by the library. This behavior can be overridden by Application and Function Mappings. One `configure` flag excludes deprecated functions from the HDF5 library, making them unavailable to applications linked with the library.

**Table 1: Library Mapping Options**

<b>configure flag</b>	<b>Macros map to Release (version-numbered function; H5Gcreate shown)</b>	<b>deprecated functions available? (H5Gcreate1)</b>
<code>--with-default-api-version=v18</code> <i>Also, default behavior if no flag specified.</i>	1.8.x (H5Gcreate2)	yes
<code>--with-default-api-version=v16</code>	1.6.x (H5Gcreate1)	yes
<code>--disable-deprecated-symbols</code>	1.8.x (H5Gcreate2)	no

Refer to the file `libhdf5.settings` in the directory where the HDF5 library is installed to determine the `configure` flags used to build the library. In particular, look for the two lines shown here:

```
Default Version of Public Symbols: v18
With Deprecated Public Symbols: Yes
```

### Application Mapping Options

When an application using HDF5 APIs is built and linked with the HDF5 Library, compile-time options to `h5cc` can be used to control the API Compatibility Macro Mapping behavior exhibited by the application. The Application Mapping overrides the behavior specified by the Library Mapping, and can be overridden on a function-by-function basis by the Function Mappings.

If the HDF5 Library was configured with the `--disable-deprecated-symbols` flag, then the deprecated functions will not be available, regardless of the Application Mapping options.

**Table 2: Application Mapping Options**

<b>h5cc option</b>	<b>Macros map to Release (version-numbered function; H5Gcreate shown)</b>	<b>deprecated functions available? (H5Gcreate1)</b>
<i>Default behavior if no option specified.</i>	1.8.x (H5Gcreate2)	yes* <i>*if available in library</i>
<code>-D H5_USE_16_API</code>	1.6.x (H5Gcreate1)	yes* <i>*if available in library</i>
<code>-D H5_NO_DEPRECATED_SYMBOLS</code>	1.8.x (H5Gcreate2)	no

### Function Mapping Options

Function Mappings are specified when the application is built. These mappings can be used to control the mapping of the API Compatibility Macros to underlying functions on a function-by-function basis. The Function Mappings override the Library and Application Mappings discussed earlier.

If the HDF5 Library was configured with the `--disable-deprecated-symbols` flag, or `-D H5_NO_DEPRECATED_SYMBOLS` is used to compile the application, then the deprecated functions will not be available, regardless of the Function Mapping options.

For every function with multiple available versions, a compile-time version flag can be defined to selectively map the function macro to the desired version-numbered function. For example, the `H5Gcreate` can be mapped to either `H5Gcreate1` or `H5Gcreate2`. When used, the value of the `H5Gcreate_vers` compile-time version flag determines which function will be called:

- When `H5Gcreate_vers` is set to 1, the macro `H5Gcreate` will be mapped to `H5Gcreate1`.  
`h5cc ... -D H5Gcreate_vers=1 ...`
- When `H5Gcreate_vers` is set to 2, the macro `H5Gcreate` will be mapped to `H5Gcreate2`.  
`h5cc ... -D H5Gcreate_vers=2 ...`
- When `H5Gcreate_vers` is not set, the macro `H5Gcreate` will be mapped to either `H5Gcreate1` or `H5Gcreate2`, based on the Application Mapping, if one was specified, or on the Library Mapping.  
`h5cc ...`

As of Release 1.8.0, the API Compatibility Macros, the Function Mapping compile-time version flags and values, and the corresponding version-numbered functions are as indicated:

**Table 3: Function Mapping Options**

Macro	h5cc version flag and value	Mapped To Function
H5Acreate	-D H5Acreate_vers=1	H5Acreate1
	-D H5Acreate_vers=2	H5Acreate2
H5Adelete	-D H5Adelete_vers=1	H5Adelete1
	-D H5Adelete_vers=2	H5Adelete2
H5Aiterate	-D H5Aiterate_vers=1	H5Aiterate1
	-D H5Aiterate_vers=2	H5Aiterate2
H5Arename	-D H5Arename_vers=1	H5Arename1
	-D H5Arename_vers=2	H5Arename2
H5Dcreate	-D H5Dcreate_vers=1	H5Dcreate1
	-D H5Dcreate_vers=2	H5Dcreate2
H5Dopen	-D H5Dopen_vers=1	H5Dopen1
	-D H5Dopen_vers=2	H5Dopen2
H5Eclear	-D H5Eclear_vers=1	H5Eclear1
	-D H5Eclear_vers=2	H5Eclear2
H5Eprint	-D H5Eprint_vers=1	H5Eprint1
	-D H5Eprint_vers=2	H5Eprint2
H5Epush	-D H5Epush_vers=1	H5Epush1
	-D H5Epush_vers=2	H5Epush2
H5Eset_auto	-D H5Eset_auto_vers=1	H5Eset_auto1
	-D H5Eset_auto_vers=2	H5Eset_auto2
H5Eget_auto	-D H5Eget_auto_vers=1	H5Eget_auto1
	-D H5Eget_auto_vers=2	H5Eget_auto2
H5Ewalk	-D H5Ewalk_vers=1	H5Ewalk1
	-D H5Ewalk_vers=2	H5Ewalk2
H5Gcreate	-D H5Gcreate_vers=1	H5Gcreate1
	-D H5Gcreate_vers=2	H5Gcreate2
H5Gopen	-D H5Gopen_vers=1	H5Gopen1
	-D H5Gopen_vers=2	H5Gopen2
H5Pget_filter	-D H5Pget_filter_vers=1	H5Pget_filter1
	-D H5Pget_filter_vers=2	H5Pget_filter2

H5Pget_filter_by_id	-D H5Pget_filter_by_id_vers=1	H5Pget_filter_by_id1
	-D H5Pget_filter_by_id_vers=2	H5Pget_filter_by_id2
H5Pinsert	-D H5Pinsert_vers=1	H5Pinsert1
	-D H5Pinsert_vers=2	H5Pinsert2
H5Pregister	-D H5Pregister_vers=1	H5Pregister1
	-D H5Pregister_vers=2	H5Pregister2
H5Rget_obj_type	-D H5Rget_obj_type_vers=1	H5Rget_obj_type1
	-D H5Rget_obj_type_vers=2	H5Rget_obj_type2
H5Tarray_create	-D H5Tarray_create_vers=1	H5Tarray_create1
	-D H5Tarray_create_vers=2	H5Tarray_create2
H5Tcommit	-D H5Tcommit_vers=1	H5Tcommit1
	-D H5Tcommit_vers=2	H5Tcommit2
H5Tget_array_dims	-D H5Tget_array_dims_vers=1	H5Tget_array_dims1
	-D H5Tget_array_dims_vers=2	H5Tget_array_dims2
H5Topen	-D H5Topen_vers=1	H5Topen1
	-D H5Topen_vers=2	H5Topen2

See the HDF5 Reference Manual for complete descriptions of all API Compatibility Macros and version-numbered functions shown in Table 3.

It is possible to specify multiple Function Mappings for a single application build:

`h5cc ... -D H5Gcreate_vers=1 -D H5Dcreate_vers=2...` As a result of the Function Mappings in this compile example, all occurrences of the macro `H5Gcreate` will be mapped to `H5Gcreate1`, and all occurrences of the macro `H5Dcreate` will be mapped to `H5Dcreate2` for the application being built.

The Function Mappings can be used to guarantee that a given API Compatibility Macro will be mapped to the desired underlying function version regardless of the Library or Application Mappings. In cases where an application may benefit greatly from features offered by some of the later APIs, or must continue to use some earlier API versions for compatibility reasons, this fine-grained control may be very important.

As noted earlier, the Function Mappings can only reference version-numbered functions that are included in the HDF5 library, as determined by the configure flag used to build the library. For example, if the HDF5 library being linked with the application was built with the `--disable-deprecated-symbols` option, version 1 of the underlying functions would not be available, and the example above that defined `H5Gcreate_ver=1` would not be supported.

The Function Mappings do not negate any available functions. If `H5Gcreate1` is available in the installed version of the HDF5 Library, and the application was not compiled with the `-D H5_NO_DEPRECATED_SYMBOLS` flag, the function `H5Gcreate1` will remain available to the application through its version-numbered name. Similarly, `H5Gcreate2` will remain available to the application as `H5Gcreate2`. The Function Mapping version flag `H5Gcreate_vers` only controls the mapping of the API Compatibility Macro `H5GCreate` to one of the two available functions.

## Compatibility Macros in HDF5 1.6.8 and Later

A series of similar compatibility macros have been introduced into the release 1.6 series of the library, starting with release 1.6.8. These macros simply alias the "1" version functions listed above, as well as the typedefs not listed, to their original non-numbered names.

This allows users to write code that can be used with any version of the library since 1.6.8 and any library compilation options except `H5_NO_DEPRECATED_SYMBOLS`, by always using the "1" version of versioned functions and types. For example, `H5Gcreate1` will always be interpreted in exactly the same manner by any version of the library since 1.6.8.

This can be especially useful in any case where the programmer does not have direct control over global macro definitions, such as when writing code meant to be copied to multiple applications or when writing code in a header file.

## Common Use Case

A common scenario where the API Compatibility Macros may be helpful is the migration of an existing application to HDF5 Release 1.8.0. An incremental migration plan is outlined here:

1. Build the HDF5 library without specifying any Library Mapping configure flag. In this default mode, both 1.6.x and 1.8.x versions of the underlying functions are available, and the API Compatibility Macros will be mapped to the 1.8.x version-numbered functions. For example, `H5Gcreate` will be mapped to `H5Gcreate2`.
2. Compile the application with the `-D H5_USE_16_API` Application Mapping option, and link with the HDF5 library built in step 1. No changes should be required to build the application. The API Compatibility Macros, for example `H5Gcreate`, replace the actual function names that were used in versions of the library prior to 1.8.0. Because the Application Mapping overrides the Library Mapping, the macros will all be mapped to the 1.6.x versions of the functions.
3. Remap one API Compatibility Macro at a time (or sets of Macros), to use the 1.8.x versions. At each stage, use the Function Mappings to map the Macros being worked on to the 1.8.x versions. For example, use the `-D H5Gcreate_vers=2` version flag setting to remap the `H5Gcreate` macro to `H5Gcreate2`, the 1.8.x version. During this step, the application code will need to be modified to change the calling parameters used with the API Compatibility Macros to match the number and type of the 1.8.x version-numbered functions. The Macro name, for example `H5Gcreate`, should continue to be used in the code, to allow for possible re-mappings to later version-numbered functions in a future release.
4. After all Macros have been migrated to the 1.8.x version-numbered functions in step 3, compile the application without any Application or Function Mappings. This build uses the Library Mappings set in step 1, and maps API Compatibility Macros to the 1.8.x versions.
5. Finally, compile the application with the Application Mapping `-D H5_NO_DEPRECATED_SYMBOLS`, and address any failures to complete the application migration process.





## HDF5 Glossary

atomic datatype	file access mode	root group
attribute	group	selection
chunked layout	member	hyperslab
chunking	root group	serialization
compound datatype	hard link	soft link
contiguous layout	hyperslab	storage layout
dataset	identifier	chunked
dataspace	link	chunking
datatype	hard	contiguous
atomic	soft	super block
compound	member	variable-length datatype
enumeration	name	
named	named datatype	
opaque	opaque datatype	
variable-length	path	
enumeration datatype	property list	
file	data transfer	
group	dataset access	
path	dataset creation	
root group	file access	
super block	file creation	

---

### **atomic datatype**

A datatype which cannot be decomposed into smaller units at the API level.

### **attribute**

A small dataset that can be used to describe the nature and/or the intended usage of the object it is attached to.

### **chunked layout**

The storage layout of a chunked dataset.

### **chunking**

A storage layout where a dataset is partitioned into fixed-size multi-dimensional chunks. Chunking tends to improve performance and facilitates dataset extensibility.

### **compound datatype**

A collection of one or more atomic types or small arrays of such types. Similar to a struct in C or a common block in Fortran.

### **contiguous layout**

The storage layout of a dataset that is not chunked, so that the entire data portion of the dataset is stored in a single contiguous block.

### **data transfer property list**

The data transfer property list is used to control various aspects of the I/O, such as caching hints or collective I/O information.

### **dataset**

A multi-dimensional array of data elements, together with supporting metadata.

**dataset access property list**

A property list containing information on how a dataset is to be accessed.

**dataset creation property list**

A property list containing information on how raw data is organized on disk and how the raw data is compressed.

**datspace**

An object that describes the dimensionality of the data array. A dataspace is either a regular N-dimensional array of data points, called a simple dataspace, or a more general collection of data points organized in another manner, called a complex dataspace.

**datatype**

An object that describes the storage format of the individual data points of a data set. There are two categories of datatypes: atomic and compound datatypes. An atomic type is a type which cannot be decomposed into smaller units at the API level. A compound datatype is a collection of one or more atomic types or small arrays of such types.

**enumeration datatype**

A one-to-one mapping between a set of symbols and a set of integer values, and an order is imposed on the symbols by their integer values. The symbols are passed between the application and library as character strings and all the values for a particular enumeration datatype are of the same integer type, which is not necessarily a native type.

**file**

A container for storing grouped collections of multi-dimensional arrays containing scientific data.

**file access mode**

Determines whether an existing file will be overwritten, opened for read-only access, or opened for read/write access. All newly created files are opened for both reading and writing.

**file access property list**

File access property lists are used to control different methods of performing I/O on files:

**file creation property list**

The property list used to control file metadata.

**group**

A structure containing zero or more HDF5 objects, together with supporting metadata. The two primary HDF5 objects are datasets and groups.

**hard link**

A direct association between a name and the object where both exist in a single HDF5 address space.

**hyperslab**

A portion of a dataset. A hyperslab selection can be a logically contiguous collection of points in a dataspace or a regular pattern of points or blocks in a dataspace.

**identifier**

A unique entity provided by the HDF5 library and used to access an HDF5 object, such as a file, group, dataset, datatype, etc.

**link**

An association between a name and the object in an HDF5 file group.

**member**

A group or dataset that is in another dataset, *dataset A*, is a member of *dataset A*.

**name**

A slash-separated list of components that uniquely identifies an element of an HDF5 file. A name begins that begins with a slash is an absolute name which is accessed beginning with the root group of the file; all other names are relative names and the associated objects are accessed beginning with the current or specified group.

**named datatype**

A datatype that is named and stored in a file. Naming is permanent; a datatype cannot be changed after being named.

**opaque datatype**

A mechanism for describing data which cannot be otherwise described by HDF5. The only properties associated with opaque types are a size in bytes and an ASCII tag.

**path**

The slash-separated list of components that forms the name uniquely identifying an element of an HDF5 file.

**property list**

A collection of name/value pairs that can be passed to other HDF5 functions to control features that are typically unimportant or whose default values are usually used.

**root group**

The group that is the entry point to the group graph in an HDF5 file. Every HDF5 file has exactly one root group.

**selection**

(1) A subset of a dataset or a dataspace, up to the entire dataset or dataspace. (2) The elements of an array or dataset that are marked for I/O.

**serialization**

The flattening of an  $N$ -dimensional data object into a 1-dimensional object so that, for example, the data object can be transmitted over the network as a 1-dimensional bitstream.

**soft link**

An indirect association between a name and an object in an HDF5 file group.

**storage layout**

The manner in which a dataset is stored, either contiguous or chunked, in the HDF5 file.

**super block**

A block of data containing the information required to portably access HDF5 files on multiple platforms, followed by information about the groups and datasets in the file. The super block contains information about the size of offsets, lengths of objects, the number of entries in group tables, and additional version information for the file.

**variable-length datatype**

A sequence of an existing datatype (atomic, variable-length (VL), or compound) which are not fixed in length from one dataset location to another.

