

# Building the Spout libraries

The Spout SDK can be built as a dll or static library. This may be preferable to using source code or if you are using a compiler other than Visual Studio. The same applies for a DirectX versions "SpoutDX", SpoutDX12", "SpoutDX9" and "SpoutLibrary" (a C-compatible dll that can be used with other compilers).

All libraries can be built using Cmake. (<https://cmake.org>).

## CMAKE build

### Installation

- 1) Download and install CMake for Windows. The easiest way is to use the installer. At the time of writing this was "cmake-3.25.1-x86-64.msi". Get it from the downloads page (<https://cmake.org/download/>).
- 2) Run the installer. Default options are OK, but it's useful to create a Desktop icon. "Finish" to complete.

### Generating a project

- 1) On the desktop, find the CMake icon and open the CMake GUI.
- 2) For "Where is the source code:", click "Browse Source", navigate to wherever you saved the Spout repository and select the root folder, usually named "Spout2".
- 3) For "Where to build the binaries:", click "Browse Build" and navigate to "Spout2\BUILD".
- 4) At bottom click "Configure" to open the configuration dialog.
- 5) For "Specify the generator for this project", select your compiler and other options you may require. "Optional platform ..." will be empty. Default build is 32 bit. Leave it at that for now and other defaults. Click "Finish".

After completion you will see various build settings in red.

- ✓ SKIP\_INSTALL\_ALL – do not generate an INSTALL project to produce header and library folders. Default is ON. The INSTALL project is a separate build. Default is off for the following two options.
- ✓ SKIP\_INSTALL\_HEADERS – do not generate header files with the INSTALL project.
- ✓ SKIP\_INSTALL\_LIBRARIES – do not generate library files with the INSTALL project.
- ✓ SPOUT\_BUILD\_ARM – build for Windows on Arm for Arm architecture processors.
- ✓ SPOUT\_BUILD\_CMT - for Visual Studio compilers, this sets a project option "C/C++ > Code Generation > Runtime Library > Multi-threaded (/MT)" to compile the Visual Studio runtime libraries into the dll. Then the user does not need to install them separately. Check it off if you require compatibility with other libraries built "/MD".
- ✓ SPOUT\_BUILD\_LIBRARY - builds a C-compatible library "SpoutLibrary" which could be of interest if you are not using Visual Studio.
- ✓ SPOUT\_BUILD\_SPOUTDX - builds the Spout DirectX11 support class "SpoutDX" as a dynamic link library. Default is off.
- ✓ SPOUT\_BUILD\_SPOUTDX\_EXAMPLES – build the examples for SpoutDX. Default is off.

Finally Click "Generate".

## Building the projects

When you see "Generating done", click "Open Project".  
In the compiler IDE you will see the following projects :

ALL_BUILD	
INSTALL	
Spout	(Spout SDK dll)
Spout_static	(Spout SDK static library)
SpoutDX	(Spout for DirectX 11 – option)
SpoutDX_static	(SpoutDX static library)
SpoutDX12	(Spout for DirectX 12 – option)
SpoutDX12_static	(SpoutDX12 static library)
SpoutDX9	(Spout for DirectX 9 – option)
SpoutDX9_static	(SpoutDX9 static library)
SpoutLibrary	(C compatible Spout library - option)
Tutorial04	(DirectX11 SpoutDX sender example - option)
Tutorial07	(DirectX11 SpoutDX receiver example - option)
WinSpoutDXreceiver	(Windows SpoutDX receiver example - option)
WinSpoutDXsender	(Windows SpoutDX sender example - option)
ZERO_CHECK	

## ALL\_BUILD

Build "ALL\_BUILD" and, when it has finished, browse to the "BUILD" folder you previously selected. In the "Binaries" folder you will find :

```
x64
  Spout.dll
  Spout.lib
  Spout_static.lib
  SpoutDX.dll
  SpoutDX.lib
  SpoutDX_static.dll
  SpoutDX9.dll
  SpoutDX9.lib
  SpoutDX9_static.dll
  SpoutDX12.dll
  SpoutDX12.lib
  SpoutDX12_static.dll
  SpoutLibrary.dll
  SpoutLibrary.lib
```

## SpoutDX examples

Note that ALL\_BUILD is the default "Startup Project". To build the SpoutDX examples individually, right click on the project you are interested in and select as "Startup Project" from the context menu.

## INSTALL

This is a separate project that produces all the files you need for the libraries in conveniently arranged folders instead of ALL\_BUILD or the separate projects :

- bin - dll files
- lib - library files
- include - header files
  - SpoutDX
  - SpoutDX9
  - SpoutDX12
  - SpoutGL
  - SpoutLibrary

## Changing the CMake options

- 1) Close compiler IDE
- 2) Start CMake GUI again if it has been closed
- 3) Select any of the options available and check ON or OFF
- 4) Click "Generate" again to set the new options.
- 5) "Open Project" and Rebuild

## Changing Platform

For example to build 64 bit instead of the default 32 bit.

- 1) From the CMake GUI select "File > Delete cache" and do it.
- 2) Click "Configure"
- 3) This time, select the "Optional platform" that you want. For Visual Studio there is a drop-down list and the "x64" option.
- 4) "Generate", "Open Project", change to "Release" and build.

In the "Binaries" folder you will find an "x64" folder with the 64 bit versions of the libraries. They have the same names so be careful not to mix them up.

## Credit

Thanks and credit for the CMake files which were first developed and contributed by Alexandre Buge (<https://github.com/Qlex42>) and revisions by Jean-Michaël Celerier (<https://github.com/jcelerier>).