

# Documentation of GMILOS

Manuel Cabrera Morales & Luis Bellot Rubio

## Contents

1	Overview .....	2
2	Compilation.....	2
2.1	Make options .....	3
2.2	Location of the code for download .....	3
3	Control files.....	4
3.1	Mtrot file.....	4
4	Input files.....	8
4.1	Observed profiles.....	8
4.2	Wavelength file.....	9
4.3	Init models file.....	9
4.4	Output files.....	10
5	Execution.....	11

# 1 Overview

This document is a user guide and short documentation of GMILOS.

The main contributions of the GMILOS code compared to IDL-MILOS are:

- Efficient memory management, using single precision by-default.
- Leveraging the parallel process of the GPU for better performance.
- Avoid many repeated calculations per iteration when making an investment.
- Calculation of convolutions are more efficient, using direct convolutions instead of FFT.
- Inversion of more than one pixel (typically the whole FOV) using more processor cores.
- Reading the input spectra from standardized FITS<sup>1</sup> files.
- Writing all output data in the standardized FITS format.

Please note that this documentation is written for a Linux runtime environment. The CUDA code is portable between platforms, but the Makefile to compile the code, as well as the tests done, have been done only under 64 bits Linux platform.

# 2 Compilation

The code must be compiled on the destination system. It was tested in two different environments: Ubuntu 18.04 64-bit and Red Hat Enterprise Linux Server release 6.8 (Santiago) 64-bit, although it may run on any 64-bit Linux system. The following libraries and programs should be installed on your system as a pre-compilation requirement:

- CUDA runtime environment and toolkit.
- [CFITSIO](#) Version 3.3.4.0 (or higher)
- [GSL](#) Version 1.13-3 (or higher)

IMPORTANT NOTE:

---

<sup>1</sup> Flexible Image Transport System, see <http://fits.gsfc.nasa.gov/>

For GSL, the version of the library specified is the minimum with which the code works correctly, but we recommend the use of version 2.6, which is the one we have found the better performance.

In addition, for CFITSIO we recommend the use of the specified versions before. Because, they are the ones we have used in our tests and are the last ones published.

## 2.1 Make options

In order to deploy the application, it must first be compiled on the target machine. To do this, you must use the command line option 'make' from same directory where the source code is located. So, the first thing is to position ourselves in the GPU-MILOS. After that you must edit the file "makefile" and edit variable CUDA\_PATH with the location of CUDA Toolkit in your machine. By default the makefile compile the code with compatibility for this generations of CUDA: 35 37 50 52 60 70 , if you want compile for a specific generation edit file "makefile", search variable SMS and modify it with the value you want.

- Compile and create executable **gmiolos**

```
make
```

- Clean objects files and executable files.

```
make clean
```

The executable **gmiolos** will be located in the same directory where you run the make command.

## 2.2 Location of the code for download

The latest stable version of GPU-MILOS is located in the GitHub repository: <https://github.com/IAA-InvCodes/GPU-MILOS>

### 3 Control files

There are two types of control files. The first one are files with extension “.mtrol”, they are to control common parameters between sequential and parallel version. They control the parameters to launch parallel version for make time series inversion.

#### 3.1 Mtrol file

The program needs to have an .mtrol file in the input to control the options to use in the execution.

The layout to the control file is 3 columns, data column between ‘:’ and ‘!’. **Both characters are mandatory to delimit the data field.** Here the detailed description of the entries:

Number of cycles	:0	! 0 = synthesis, n= max num of iterations, -1 = use classical estimates
Observed profiles	:run/init.per	!
Stray light file	:	! (none=no stray light contam)
PSF file	:	! .psf file -> read numeric psf; is a number -> Use a gaussian filter with FWHM (mA); empty -> NOT FILTER
Wavelength grid file	:run/malla.grid	! (automatic selection, grid, or wavelength file)
Atomic parameters file	:run/LINES	!
Abundances file	:	! not used
Initial guess model 1	:run/initModel.mod	!
Initial guess model 2	:	! not used for the moment
Weight for Stokes I	:1	! (DEFAULT=1; 0=not inverted)
Weight for Stokes Q	:1	! (DEFAULT=1; 0=not inverted)
Weight for Stokes U	:1	! (DEFAULT=1; 0=not inverted)
Weight for Stokes V	:1	! (DEFAULT=1; 0=not inverted)
AUTOMATIC SELECT. OF NODES?	:	! not used for the moment
Nodes for S <sub>0</sub> 1	:1	! (0 or blank=no, 1=yes)
Nodes for S <sub>1</sub> 1	:1	! (0 or blank=no, 1=yes)
Nodes for eta0 1	:1	! (0 or blank=no, 1=yes)
Nodes for magnetic field 1	:1	! (0 or blank=no, 1=yes)
Nodes for LOS velocity 1	:1	! (0 or blank=no, 1=yes)
Nodes for gamma 1	:1	! (0 or blank=no, 1=yes)
Nodes for phi 1	:1	! (0 or blank=no, 1=yes)

Nodes for lambda_doppler 1	:1	! (0 or blank=no, 1=yes)
Nodes for damping 1	:1	! (0 or blank=no, 1=yes)
Invert macroturbulence 1	:1	! (0 or blank=no, 1=yes)
Nodes for S_0 2	:0	! not used for the moment
Nodes for S_1 2	:0	! not used for the moment
Nodes for eta0 2	:0	! not used for the moment
Nodes for magnetic field 2	:0	! not used for the moment
Nodes for LOS velocity 2	:0	! not used for the moment
Nodes for gamma 2	:0	! not used for the moment
Nodes for phi 2	:0	! not used for the moment
Nodes for lambda_doppler 2	:0	! not used for the moment
Nodes for damping 2	:0	! not used for the moment
Invert macroturbulence 2?	:0	! not used for the moment
Invert filling factor?	:0	! not used for the moment
Invert stray light factor?	:0	! (0 or blank=no, 1=yes)
mu=cos (theta)	:1	! (DEFAULT: mu=1. mu<0 =>
West)		
Estimated S/N for I	:1000	!
Continuum contrast	:1e-12	! Not used for the moment
Initial diagonal element	:0.1	! (DEFAULT value: 1.e-1)
Diagonal element acceleration	:0	! (0 or blank=no, 1=yes)

Table 1: Example of an mtrol-file

- **Number of cycles:**
  - Using value -1 the program apply the classical estimates to the profile or profiles, specified in the field *Observed Profiles*. The result is stored in a file with the same root of input file and suffix: “\_ce”.
  - Using value 0 the program creates a synthesis of Initial guess model 1. The output file has the root name of observed profiles if it is present, in other case the program takes the root of Initial guess model 1.
  - With value greater than 0 the program does the inversion or pixel in the case of .per file or image in the case of .fits file. In this case, the number will be the number of iterations to find a solution. The output models file will have the suffix “\_model”, in both cases, using the root of the input observed profiles file.
- **Observed profiles:** specify the profiles to invest in case of .per file given and the image to invest in case of .fits file given.
- **Stray light file:** It can be a file of type .PER or .FITS (This will be verified by the program, if a file with one of these two extensions is not provided an error will be presented indicating that StrayLight will not be used). If a fits file is specified, it can be of dimensions 2 or 4. If it is of 2 dimensions these will be (number of wavelengths, 4). If it is a 4-dimensional file it will be

(number of wavelengths, 4, number of rows, number of columns). The order of the dimensions may be different from that indicated above, except that in the case of 4 dimensions, the dimension of the number of rows must always precede the dimension of the number of columns. For the synthesis and inversion of a profile, only 2-dimensional files will be accepted, with the program displaying an error message if this is not the case.

- **PSF file:** used to specify the name of .psf file with the filter to apply. If you want a Gaussian filter then specify the number of FWHM in mÅ. If you do not want to apply filter, just put in blank the field.
- **Wavelength grid file:** this field is mandatory. It is for specify the wavelengths to use. You can use a grid file or a fits file. Both types of files admitted will be explained later.
- **Atomic parameters file:** this field is mandatory. File with the spectral lines.
- **Abundances file:** not used at this moment.
- **Initial guess model 1:** File with the initial model for the synthesis and invest cases.
- **Initial guess model 2:** not used at this moment.
- **Weight for Stokes I:** weight of parameter I in the inversion.
- **Weight for Stokes Q:** weight of parameter Q in the inversion.
- **Weight for Stokes U:** weight of parameter U in the inversion.
- **Weight for Stokes V:** weight of parameter V in the inversion.
- **AUTOMATIC SELECT. OF NODES:** not used at this moment.
- **Nodes for S<sub>0</sub> 1:** Use 1 to indicate if invert "S0", 0 or blank for not invert.
- **Nodes for S<sub>1</sub> 1:** Use 1 to indicate if invert "S1", 0 or blank for not invert.
- **Nodes for eta0 1:** Use 1 to indicate if invert "eta0", 0 or blank for not invert.
- **Nodes for magnetic field 1:** Use 1 to indicate if invert "magnetic field", 0 or blank for not invert.
- **Nodes for LOS velocity 1:** Use 1 to indicate if invert "LOS velocity", 0 or blank for not invert.
- **Nodes for gamma 1:** Use 1 to indicate if invert "gamma", 0 or blank for not invert.
- **Nodes for phi 1:** Use 1 to indicate if invert "phi", 0 or blank for not invert.
- **Nodes for lambda\_doppler 1:** Use 1 to indicate if invert "lambda\_doppler", 0 or blank for not invert.
- **Nodes for damping 1:** Use 1 to indicate if invert "damping", 0 or blank for not invert.
- **Nodes for macroturbulence 1:** Use 1 to indicate if invert "macroturbulence", 0 or blank for not invert.
- **Nodes for S<sub>0</sub> 2:** not used at this moment.
- **Nodes for S<sub>1</sub> 2:** not used at this moment.
- **Nodes for eta0 2:** not used at this moment.
- **Nodes for magnetic field 2:** not used at this moment.
- **Nodes for LOS velocity 2:** not used at this moment.
- **Nodes for gamma 2:** not used at this moment.
- **Nodes for phi 2:** not used at this moment.

- **Nodes for lambda\_doppler 2:** not used at this moment.
- **Nodes for damping 2:** not used at this moment.
- **Nodes for macroturbulence 2:** not used at this moment.
- **Invert filling factor:** not used at this moment.
- **Invert stray light factor:** Use 1 to indicate if invert “stray light factor”, 0 or blank for not invert.
- **mu=cos(theta):** Scalar containing the cosine of the heliocentric angle. Default values is 1.
- **Estimated S/N for I:** estimated signal-to-noise ratio. Default value is 1000.
- **Continuum contrast:** not used at this moment.
- **Initial diagonal element:** Initial value for the Levenberg-Marquardt's fudge parameter. Default is 1e-3
- **Diagonal element acceleration:** By default, this parameter has value 0. If this option is activated, an acceleration process is performed in the convergence of the Levenberg-Marquardt algorithm.

## 4 Input files

### 4.1 Observed profiles

Following the standard *SOLARNET WP 20.3*, the fits files used for pass to the program the spectro image must contain four dimensions: *number\_rowsXnumber\_colsXnumber\_of\_wavelengthsXnumber\_stokes*. The order of these parameters can change and for identify each one the header of fits file must contain the type of each dimension with this correspondence:

- Number of Rows: include CTYPE with the value '**HPLN-TAN**'
- Number of Cols: include CTYPE with the value '**HPLT-TAN**'
- Number of Wavelengths: include CTYPE with the value '**WAVE-GRI**'
- Number of Stokes: include CTYPE with the value '**STOKES**'

An example can be this:

```
CTYPE1 = 'HPLN-TAN'  
CTYPE2 = 'HPLT-TAN'  
CTYPE3 = 'WAVE-GRI'  
CTYPE4 = 'STOKES'
```

In the case that these headers cannot be added to the FITS files, files that include only the 4 dimensions will also be accepted: *number\_rowsXnumber\_colsXnumber\_of\_wavelengthsXnumber\_stokes*, without headers that indicate what each one corresponds to, as long as they comply with the restriction that the number of rows and columns are specified in the order *number\_rowsXnumber\_cols*, never as *number\_colsXnumber\_rows*.

As mentioned above the order may not be as specified, but this has an impact on the read speed of the file. If the order of the dimensions of the file is the same as that specified, the reading will be 50% more efficient, since these dimensions will not have to be reordered to adapt them to the form used internally by the application.

The datatype of the images must be in `FLOAT_IMG` type, since the program will treat them with this type of data and the accuracy will be adjusted to the 32 bits used for the C float representation. The program will exit if detect one image with other datatype.



## 4.2 Wavelength file

The wavelengths can be provided with a grid file or using a FITS file containing the wavelengths and indices of the observed profiles, (the same information as in the first two columns of .per files). In both cases, the observed spectra of all pixels use the same wavelength grid. These are the two ways explained:

- For Grid format is a file with four columns. The first indicates the number of spectral line to read from the file with spectral lines. The second, third and fourth columns are for specify the range of wavelengths; the values are relative from the central wavelength. The second column is the initial lambda from range, the third the step between wavelengths and the fourth is the end of range.
- For FITS format, the FITS file must contain a single 2D array with dimension number of wavelength-points $\times$ 2. The first column must contain the index with which the spectral line is identified according to the atomic parameter file. The second column must contain the wavelengths (in mÅ). Examples of these files can be found in the repository, path *run/lambda.fits*.

An error will occur if the data in the FITS file does not fit either of these two possibilities. We recommend the usage of a wavelength grid file. If the number of wavelength points, spectral lines of the observed spectra and the wavelength grid differ, an error will occur. Either a wavelength file, or a wavelength grid file, or both of them must be used. If only a grid file is used, the wavelengths of the observed profiles are assumed exactly the ones of the grid file. If a wavelength file or a grid file is not specified, the code cannot determine the observed wavelengths and will abort with an error.

## 4.3 Init models file

The values for different initial model atmospheres have to be specified in the init models file. It is possible to use only one value for the parameters: eta\_0 (line-to-continuum absorption coefficient ratio), magnetic field (magnetic field strength), LOS velocity (line-of-sight velocity), doppler width (Doppler width), damping (damping parameter), gamma (magnetic field inclination), phi (magnetic field azimuth), S\_0 (source function constant), S\_1 (source function gradient), v\_mac (macroturbulent velocity), filling factor (filling factor of magnetic component). The values of the variables must always be as specified below and followed by ":"

eta_0:	20
magnetic field:	1100
LOS velocity:	0,2
Doppler width:	0,03

damping:	0,05
gamma:	120
phi:	150
S_0:	0,35
S_1:	0,5
v_mac:	1
filling factor:	1

#### 4.4 Output files

There are four types of outputs files depending of the option and type of files specify in the ".mtrol" file:

Synthesis case: The output in case we are making a synthesis will be the root of the observed profiles name, in case this field is not empty. If it is empty, then the program use the root of initial model atmosphere file provided. In both cases, the extension used for the output file is ".per".

Inversion of a given profile by .per file: the name of output file is compound by the root of observed profiles name (if this field is empty, the root of initial atmosphere file is used) and the suffix "\_model.mod".

Inversion of a given image FITS: in this case, the output will be another FITS image. The data is saved in FLOAT precision and the dimensions of image will be: numberOfRows X numberOfCols X 13. The number 13 comes from the eleven parameters of the model, the number of iterations used by the algorithm to found the solution in that pixel and the value of Chisqr calculated for the result model of that pixel respect the input profile. Therefore, the order of the third dimension of the file will be:

1. eta0 = line-to-continuum absorption coefficient ratio
2. B = magnetic field strength [Gauss]
3. vlos = line-of-sight velocity [km/s]
4. dopp = Doppler width [Angstroms]
5. aa = damping parameter
6. gm = magnetic field inclination [deg]
7. az = magnetic field azimuth [deg]
8. S0 = source function constant
9. S1 = source function gradient
10. mac = macroturbulent velocity [km/s]
11. alpha = filling factor of the magnetic component [0->1]

12. Number of iterations needed.
13. Value of Chisqr.

In the case of sequential execution, the name policy is identical to the one followed by the inversion of a “.per” file.

Output profiles: The files for each inversion cycle contain an array with the same dimension as the input profiles.

## 5 Execution

```
./gmilos run/gmilos.trol
```