

Hosting Environment (Daemon) Reference Manual

Generated by Doxygen 1.4.7

Sun Aug 31 00:49:29 2008

Contents

1	Hosting Environment (Daemon) Namespace Index	1
1.1	Hosting Environment (Daemon) Namespace List	1
2	Hosting Environment (Daemon) Hierarchical Index	3
2.1	Hosting Environment (Daemon) Class Hierarchy	3
3	Hosting Environment (Daemon) Class Index	7
3.1	Hosting Environment (Daemon) Class List	7
4	Hosting Environment (Daemon) Namespace Documentation	11
4.1	Arc Namespace Reference	11
5	Hosting Environment (Daemon) Class Documentation	27
5.1	acc_descriptor Struct Reference	27
5.2	Arc::ACCFactory Class Reference	28
5.3	ArcSec::AlgFactory Class Reference	29
5.4	ArcSec::ArcAttributeProxy< TheAttribute > Class Template Reference	30
5.5	Arc::ArcLocation Class Reference	31
5.6	ArcSec::Attr Struct Reference	32
5.7	ArcSec::AttributeFactory Class Reference	33
5.8	Arc::AttributeIterator Class Reference	34
5.9	ArcSec::AttributeProxy Class Reference	37
5.10	ArcSec::AttributeValue Class Reference	38
5.11	ArcSec::Attrs Class Reference	39
5.12	ArcSec::AuthzRequestSection Struct Reference	40
5.13	Arc::BaseConfig Class Reference	41
5.14	Arc::ChainContext Class Reference	43
5.15	Arc::Checksum Class Reference	44
5.16	Arc::ChecksumAny Class Reference	45
5.17	Arc::CISStringValue Class Reference	47

5.18	Arc::ClientSOAP Class Reference	49
5.19	ArcSec::CombiningAlg Class Reference	50
5.20	Arc::Config Class Reference	51
5.21	Arc::Counter Class Reference	53
5.22	Arc::CounterTicket Class Reference	60
5.23	Arc::CRC32Sum Class Reference	62
5.24	Arc::Database Class Reference	63
5.25	Arc::DataBufferPar Class Reference	65
5.26	Arc::DataCache Class Reference	72
5.27	Arc::DataCallback Class Reference	76
5.28	Arc::DataHandle Class Reference	77
5.29	Arc::DataMover Class Reference	78
5.30	Arc::DataPoint Class Reference	82
5.31	Arc::DataPointDirect Class Reference	93
5.32	Arc::DataPointIndex Class Reference	100
5.33	Arc::DataSpeed Class Reference	107
5.34	Arc::DelegationConsumer Class Reference	111
5.35	Arc::DelegationConsumerSOAP Class Reference	113
5.36	Arc::DelegationContainerSOAP Class Reference	115
5.37	Arc::DelegationProvider Class Reference	117
5.38	Arc::DelegationProviderSOAP Class Reference	119
5.39	ArcSec::DenyOverridesCombiningAlg Class Reference	121
5.40	dmc_descriptor Struct Reference	122
5.41	Arc::DMCFactory Class Reference	123
5.42	ArcSec::EqualFunction Class Reference	124
5.43	ArcSec::EvalResult Struct Reference	125
5.44	ArcSec::EvaluationCtx Class Reference	126
5.45	ArcSec::Evaluator Class Reference	127
5.46	ArcSec::EvaluatorContext Class Reference	130
5.47	ArcSec::EvaluatorLoader Class Reference	131
5.48	Arc::ExpirationReminder Class Reference	132
5.49	Arc::FileInfo Class Reference	134
5.50	ArcSec::FnFactory Class Reference	135
5.51	ArcSec::Function Class Reference	136
5.52	Arc::InfoRegister Class Reference	137
5.53	Arc::InfoRegisters Class Reference	138

5.54 Arc::InformationContainer Class Reference	139
5.55 Arc::InformationInterface Class Reference	141
5.56 Arc::InformationRequest Class Reference	143
5.57 Arc::InformationResponse Class Reference	145
5.58 Arc::IntraProcessCounter Class Reference	146
5.59 Arc::Loader Class Reference	150
5.60 Arc::loader_descriptor Struct Reference	152
5.61 Arc::LoaderFactory Class Reference	153
5.62 Arc::LogDestination Class Reference	155
5.63 Arc::Logger Class Reference	157
5.64 Arc::LogMessage Class Reference	160
5.65 Arc::LogStream Class Reference	162
5.66 ArcSec::MatchFunction Class Reference	164
5.67 Arc::MCC Class Reference	165
5.68 mcc_descriptor Struct Reference	168
5.69 Arc::MCC_Status Class Reference	169
5.70 Arc::MCCFactory Class Reference	172
5.71 Arc::MCCInterface Class Reference	173
5.72 Arc::MD5Sum Class Reference	174
5.73 Arc::Message Class Reference	175
5.74 Arc::MessageAttributes Class Reference	178
5.75 Arc::MessageAuth Class Reference	181
5.76 Arc::MessageAuthContext Class Reference	183
5.77 Arc::MessageContext Class Reference	184
5.78 Arc::MessageContextElement Class Reference	185
5.79 Arc::MessagePayload Class Reference	186
5.80 Arc::ModuleManager Class Reference	187
5.81 Arc::MultiSecAttr Class Reference	189
5.82 Arc::MySQLDatabase Class Reference	190
5.83 Arc::PayloadRaw Class Reference	192
5.84 Arc::PayloadRawInterface Class Reference	195
5.85 Arc::PayloadSOAP Class Reference	197
5.86 Arc::PayloadStream Class Reference	198
5.87 Arc::PayloadStreamInterface Class Reference	201
5.88 Arc::PayloadWSRF Class Reference	204
5.89 ArcSec::PDP Class Reference	206

5.90	pdp_descriptor Struct Reference	207
5.91	Arc::PDPFactory Class Reference	208
5.92	ArcSec::PermitOverridesCombiningAlg Class Reference	209
5.93	Arc::Plexer Class Reference	210
5.94	Arc::PlexerEntry Class Reference	212
5.95	ArcSec::Policy Class Reference	213
5.96	ArcSec::PolicyParser Class Reference	215
5.97	ArcSec::PolicyStore Class Reference	216
5.98	Arc::RegularExpression Class Reference	217
5.99	ArcSec::Request Class Reference	219
5.100	ArcSec::RequestAttribute Class Reference	221
5.101	ArcSec::RequestItem Class Reference	222
5.102	ArcSec::RequestTuple Class Reference	223
5.103	ArcSec::Response Class Reference	224
5.104	ArcSec::ResponseItem Struct Reference	225
5.105	Arc::Run Class Reference	226
5.106	Arc::SAMLToken Class Reference	230
5.107	Arc::SecAttr Class Reference	232
5.108	Arc::SecAttr::Format Class Reference	235
5.109	Arc::SecAttrValue Class Reference	236
5.110	ArcSec::SecHandler Class Reference	238
5.111	sechandler_descriptor Struct Reference	239
5.112	Arc::SecHandlerFactory Class Reference	240
5.113	ArcSec::Security Class Reference	241
5.114	Arc::Service Class Reference	242
5.115	service_descriptor Struct Reference	244
5.116	Arc::ServiceFactory Class Reference	245
5.117	Arc::SimpleCondition Class Reference	246
5.118	Arc::SOAPMessage Class Reference	248
5.119	ArcSec::Source Class Reference	250
5.120	ArcSec::SourceFile Class Reference	252
5.121	ArcSec::SourceURL Class Reference	253
5.122	Arc::Time Class Reference	254
5.123	Arc::URL Class Reference	257
5.124	Arc::URLLocation Class Reference	264
5.125	Arc::UsernameToken Class Reference	266

5.126Arc::WSAEndpointReference Class Reference	269
5.127Arc::WSAHeader Class Reference	271
5.128Arc::WSRF Class Reference	274
5.129Arc::WSRFBaseFault Class Reference	276
5.130Arc::WSRP Class Reference	278
5.131Arc::WSRPFault Class Reference	280
5.132Arc::WSRPResourcePropertyChangeFailure Class Reference	281
5.133Arc::X509Token Class Reference	282
5.134Arc::XMLNode Class Reference	284
5.135Arc::XMLNodeContainer Class Reference	293
5.136Arc::XMLSecNode Class Reference	295

Chapter 1

Hosting Environment (Daemon) Namespace Index

1.1 Hosting Environment (Daemon) Namespace List

Here is a list of all documented namespaces with brief descriptions:

Arc	11
---------------------------	----

Chapter 2

Hosting Environment (Daemon) Hierarchical Index

2.1 Hosting Environment (Daemon) Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

acc_descriptor	27
ArcSec::AlgFactory	29
Arc::ArcLocation	31
ArcSec::Attr	32
ArcSec::AttributeFactory	33
Arc::AttributeIterator	34
ArcSec::AttributeProxy	37
ArcSec::ArcAttributeProxy< TheAttribute >	30
ArcSec::AttributeValue	38
ArcSec::Attrs	39
ArcSec::AuthzRequestSection	40
Arc::BaseConfig	41
Arc::ChainContext	43
Arc::Checksum	44
Arc::ChecksumAny	45
Arc::CRC32Sum	62
Arc::MD5Sum	174
Arc::ClientSOAP	49
ArcSec::CombiningAlg	50
ArcSec::DenyOverridesCombiningAlg	121
ArcSec::PermitOverridesCombiningAlg	209
Arc::Counter	53
Arc::IntraProcessCounter	146
Arc::CounterTicket	60
Arc::Database	63
Arc::MySQLDatabase	190
Arc::DataBufferPar	65
Arc::DataCallback	76
Arc::DataCache	72

Arc::DataHandle	77
Arc::DataMover	78
Arc::DataPoint	82
Arc::DataPointDirect	93
Arc::DataPointIndex	100
Arc::DataSpeed	107
Arc::DelegationConsumer	111
Arc::DelegationConsumerSOAP	113
Arc::DelegationContainerSOAP	115
Arc::DelegationProvider	117
Arc::DelegationProviderSOAP	119
dmc_descriptor	122
ArcSec::EvalResult	125
ArcSec::EvaluationCtx	126
ArcSec::Evaluator	127
ArcSec::EvaluatorContext	130
ArcSec::EvaluatorLoader	131
Arc::ExpirationReminder	132
Arc::FileInfo	134
ArcSec::FnFactory	135
ArcSec::Function	136
ArcSec::EqualFunction	124
ArcSec::MatchFunction	164
Arc::InfoRegister	137
Arc::InfoRegisters	138
Arc::InformationInterface	141
Arc::InformationContainer	139
Arc::InformationRequest	143
Arc::InformationResponse	145
Arc::Loader	150
Arc::loader_descriptor	152
Arc::LogDestination	155
Arc::LogStream	162
Arc::Logger	157
Arc::LogMessage	160
mcc_descriptor	168
Arc::MCC_Status	169
Arc::MCCInterface	173
Arc::MCC	165
Arc::Plexer	210
Arc::Service	242
Arc::Message	175
Arc::MessageAttributes	178
Arc::MessageAuth	181
Arc::MessageAuthContext	183
Arc::MessageContext	184
Arc::MessageContextElement	185
Arc::MessagePayload	186
Arc::PayloadRawInterface	195
Arc::PayloadRaw	192
Arc::PayloadSOAP	197

Arc::PayloadStreamInterface	201
Arc::PayloadStream	198
Arc::PayloadWSRF	204
Arc::ModuleManager	187
Arc::LoaderFactory	153
Arc::ACCFactory	28
Arc::DMCFactory	123
Arc::MCCFactory	172
Arc::PDPFactory	208
Arc::SecHandlerFactory	240
Arc::ServiceFactory	245
ArcSec::PDP	206
pdp_descriptor	207
Arc::PlexerEntry	212
ArcSec::Policy	213
ArcSec::PolicyParser	215
ArcSec::PolicyStore	216
Arc::RegularExpression	217
ArcSec::Request	219
ArcSec::RequestAttribute	221
ArcSec::RequestItem	222
ArcSec::RequestTuple	223
ArcSec::Response	224
ArcSec::ResponseItem	225
Arc::Run	226
Arc::SAMLToken	230
Arc::SecAttr	232
Arc::MultiSecAttr	189
Arc::SecAttr::Format	235
Arc::SecAttrValue	236
Arc::CStringValue	47
ArcSec::SecHandler	238
sechandler_descriptor	239
ArcSec::Security	241
service_descriptor	244
Arc::SimpleCondition	246
Arc::SOAPMessage	248
ArcSec::Source	250
ArcSec::SourceFile	252
ArcSec::SourceURL	253
Arc::Time	254
Arc::URL	257
Arc::URLLocation	264
Arc::UsernameToken	266
Arc::WSAEndpointReference	269
Arc::WSAHeader	271
Arc::WSRF	274
Arc::WSRFBBaseFault	276
Arc::WSRPFault	280
Arc::WSRPResourcePropertyChangeFailure	281
Arc::WSRP	278

Arc::X509Token	282
Arc::XMLNode	284
Arc::Config	51
Arc::XMLSecNode	295
Arc::XMLNodeContainer	293

Chapter 3

Hosting Environment (Daemon) Class Index

3.1 Hosting Environment (Daemon) Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

acc_descriptor	27
Arc::ACCFactory	28
ArcSec::AlgFactory (Interface for algorithm factory class)	29
ArcSec::ArcAttributeProxy< TheAttribute > (Arc specific AttributeProxy class)	30
Arc::ArcLocation (Determines ARC installation location)	31
ArcSec::Attr (Attr contains a tuple of attribute type and value)	32
ArcSec::AttributeFactory	33
Arc::AttributeIterator (An iterator class for accessing multiple values of an attribute)	34
ArcSec::AttributeProxy (Interface for generating the AttributeValue object, it will be used by AttributeFactory)	37
ArcSec::AttributeValue (Interface for different type of <Attribute> for both policy and request)	38
ArcSec::Attrs (Attrs is a container for one or more Attr)	39
ArcSec::AuthzRequestSection	40
Arc::BaseConfig	41
Arc::ChainContext (Interface to chain specific functionality)	43
Arc::Checksum (Defines interface for variuos checksum manipulations)	44
Arc::ChecksumAny (Wrapper for Checksum class)	45
Arc::CIStrngValue (This class implements case insensitive strings as security attributes)	47
Arc::ClientSOAP	49
ArcSec::CombiningAlg (Interface for combining algorithm)	50
Arc::Config (Configuration element - represents (sub)tree of ARC configuration)	51
Arc::Counter (A class defining a common interface for counters)	53
Arc::CounterTicket (A class for "tickets" that correspond to counter reservations)	60
Arc::CRC32Sum (Implementation of CRC32 checksum)	62
Arc::Database (Interface for calling database client library)	63
Arc::DataBufferPar (Represents set of buffers)	65
Arc::DataCache	72
Arc::DataCallback	76
Arc::DataHandle (This class is a wrapper around the DataPoint class)	77
Arc::DataMover	78
Arc::DataPoint (This base class is an abstraction of URL)	82

Arc::DataPointDirect (This is a kind of generalized file handle)	93
Arc::DataPointIndex (Complements DataPoint with attributes common for Indexing Service URLs)	100
Arc::DataSpeed (Keeps track of average and instantaneous transfer speed)	107
Arc::DelegationConsumer	111
Arc::DelegationConsumerSOAP	113
Arc::DelegationContainerSOAP	115
Arc::DelegationProvider	117
Arc::DelegationProviderSOAP	119
ArcSec::DenyOverridesCombiningAlg (Implement the "Deny-Overrides" algorithm)	121
dmc_descriptor	122
Arc::DMCFactory	123
ArcSec::EqualFunction (Evaluate whether the two values are equal)	124
ArcSec::EvalResult (Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied)	125
ArcSec::EvaluationCtx (EvaluationCtx , in charge of storing some context information for evaluation, including Request , current time, etc)	126
ArcSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy)	127
ArcSec::EvaluatorContext (Context for evaluator. It includes the factories which will be used to create related objects)	130
ArcSec::EvaluatorLoader (EvaluatorLoader is implemented as a helper class for loading different Evaluator objects, like ArcEvaluator)	131
Arc::ExpirationReminder (A class intended for internal use within counters)	132
Arc::FileInfo (FileInfo stores information about files (metadata))	134
ArcSec::FnFactory (Interface for function factory, which is in charge of creating Function object according to function type)	135
ArcSec::Function (Interface for function, which is in charge of evaluating two AttributeValue)	136
Arc::InfoRegister (Registration to ISIS interface)	137
Arc::InfoRegisters (Hadling multiple registrations to ISISes)	138
Arc::InformationContainer (Information System document container and processor)	139
Arc::InformationInterface (Information System message processor)	141
Arc::InformationRequest (Request for information in InfoSystem)	143
Arc::InformationResponse (Informational response from InfoSystem)	145
Arc::IntraProcessCounter (A class for counters used by threads within a single process)	146
Arc::Loader (Creator of Message Component Chains (MCC))	150
Arc::loader_descriptor (Identifier of plugin)	152
Arc::LoaderFactory (Plugin handler)	153
Arc::LogDestination (A base class for log destinations)	155
Arc::Logger (A logger class)	157
Arc::LogMessage (A class for log messages)	160
Arc::LogStream (A class for logging to ostreams)	162
ArcSec::MatchFunction (Evaluate whether arg1 (value in regular expression) matched arg0 (lable in regular expression))	164
Arc::MCC (Message Chain Component - base class for every MCC plugin)	165
mcc_descriptor (Identifier of Message Chain Componet (MCC) plugin)	168
Arc::MCC_Status (A class for communication of MCC processing results)	169
Arc::MCCFactory (MCC Plugins handler)	172
Arc::MCCInterface (Interface for communication between MCC , Service and Plexer objects)	173
Arc::MD5Sum (Implementation of MD5 checksum)	174
Arc::Message (Object being passed through chain of MCCs)	175
Arc::MessageAttributes (A class for storage of attribute values)	178
Arc::MessageAuth (Contains authencity information, authorization tokens and decisions)	181
Arc::MessageAuthContext (Handler for content of message auth* context)	183

Arc::MessageContext (Handler for content of message context)	184
Arc::MessageContextElement (Top class for elements contained in message context)	185
Arc::MessagePayload (Base class for content of message passed through chain)	186
Arc::ModuleManager (Manager of shared libraries)	187
Arc::MultiSecAttr (Container of multiple SecAttr attributes)	189
Arc::MySQLDatabase	190
Arc::PayloadRaw (Raw byte multi-buffer)	192
Arc::PayloadRawInterface (Random Access Payload for Message objects)	195
Arc::PayloadSOAP (Payload of Message with SOAP content)	197
Arc::PayloadStream (POSIX handle as Payload)	198
Arc::PayloadStreamInterface (Stream-like Payload for Message object)	201
Arc::PayloadWSRF (This class combines MessagePayload with WSRF)	204
ArcSec::PDP (Base class for Policy Decision Point plugins)	206
pdp_descriptor (Identifier of Policy Decision Point (PDP) plugin)	207
Arc::PDPFactory (PDP Plugins handler)	208
ArcSec::PermitOverridesCombiningAlg (Implement the "Permit-Overrides" algorithm)	209
Arc::Plexer (The Plexer class, used for routing messages to services)	210
Arc::PlexerEntry (A pair of label (regex) and pointer to service)	212
ArcSec::Policy (Base class for Policy , PolicySet , or Rule)	213
ArcSec::PolicyParser (A interface which will isolate the policy object from actual policy storage (files, urls, database))	215
ArcSec::PolicyStore (Storage place for policy objects)	216
Arc::RegularExpression (A regular expression class)	217
ArcSec::Request (Base class/Interface for request, includes a container for RequestItems and some operations)	219
ArcSec::RequestAttribute (Wrapper which includes AttributeValue object which is generated according to date type of one specifc node in Request.xml)	221
ArcSec::RequestItem (Interface for request item container, <subjects, actions, objects, ctxs> tuple)	222
ArcSec::RequestTuple (RequestTuple , container which includes the)	223
ArcSec::Response (Container for the evaluation results)	224
ArcSec::ResponseItem (Evaluation result concerning one RequestTuple)	225
Arc::Run	226
Arc::SAMLToken (Interface for manipulation of WS-Security according to SAML Token Profile)	230
Arc::SecAttr (This is an abstract interface to a security attribute)	232
Arc::SecAttr::Format (Export/import format)	235
Arc::SecAttrValue (This is an abstract interface to a security attribute)	236
ArcSec::SecHandler (Base class for simple security handling plugins)	238
sechandler_descriptor (Identifier of SecHandler plugin)	239
Arc::SecHandlerFactory (SecHandler Plugins handler)	240
ArcSec::Security (Common stuff used by security related slasses)	241
Arc::Service (Service - last component in a Message Chain)	242
service_descriptor (Identifier of Service plugin)	244
Arc::ServiceFactory (Service Plugins handler)	245
Arc::SimpleCondition (Simple triggered condition)	246
Arc::SOAPMessage (Message restricted to SOAP payload)	248
ArcSec::Source (Acquires and parses XML document from specified source)	250
ArcSec::SourceFile (Convenience class for obtaining XML document from file)	252
ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL)	253
Arc::Time (A class for storing and manipulating times)	254
Arc::URL (Class to hold general URL's)	257
Arc::URLLocation (Class to hold a resolved URL location)	264
Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile)	266

Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference)	269
Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header)	271
Arc::WSRF (Base class for every WSRF message)	274
Arc::WSRFBaseFault (Base class for WSRF fault messages)	276
Arc::WSRP (Base class for WS-ResourceProperties structures)	278
Arc::WSRPFault (Base class for WS-ResourceProperties faults)	280
Arc::WSRPResourcePropertyChangeFailure	281
Arc::X509Token (Interface for manipulation of WS-Security according to X.509 Token Profile)	282
Arc::XMLNode (Wrapper for LibXML library Tree interface)	284
Arc::XMLNodeContainer	293
Arc::XMLSecNode (Extends XMLNode class to support XML security operation)	295

Chapter 4

Hosting Environment (Daemon) Namespace Documentation

4.1 Arc Namespace Reference

Classes

- class **ACC**
- class **ACCConfig**
- class **ClientInterface**
- class **ClientTCP**
- struct **HTTPClientInfo**
- class **ClientHTTP**
- class [ClientSOAP](#)
- class **DefaultBroker**
- struct **Benchmark**
- struct **ApplicationEnvironment**
- class **ExecutionTarget**
- class **Job**
- class **JobController**
- class **JobDescriptionError**
- struct **Candidate**
- class **StringManipulator**
- class **JobDescriptionParser**
- class **JSDLParser**
- class **XRSLParser**
- class **JDLParser**
- class **JobDescriptionOrderer**
- class **JobDescription**
- class **JobSupervisor**
- class **RandomBroker**
- class **SmartBroker**
- class **Submitter**
- class **TargetGenerator**
- class **TargetRetriever**

- class **UserConfig**
- class [Config](#)
Configuration element - represents (sub)tree of ARC configuration.
- struct **WSSInfo**
- class [BaseConfig](#)
- class [ArcLocation](#)
Determines ARC installation location.
- class [RegularExpression](#)
A regular expression class.
- class **Base64**
- class **MemoryAllocationException**
- class **ByteArray**
- class [Counter](#)
A class defining a common interface for counters.
- class [CounterTicket](#)
A class for "tickets" that correspond to counter reservations.
- class [ExpirationReminder](#)
A class intended for internal use within counters.
- class [IntraProcessCounter](#)
A class for counters used by threads within a single process.
- class **Period**
- class [Time](#)
A class for storing and manipulating times.
- class [Database](#)
Interface for calling database client library.
- class **Query**
- class **DItem**
- class **DBranch**
- class **DItemString**
- class **FileLock**
- class **PrintfBase**
- class **Printf**
- class **IString**
- class [LogMessage](#)
A class for log messages.
- class [LogDestination](#)
A base class for log destinations.
- class [LogStream](#)
A class for logging to ostreams.

- class [Logger](#)
A logger class.
- class [MySQLDatabase](#)
- class [MySQLQuery](#)
- class [OptionParser](#)
- class [Run](#)
- class [SimpleCondition](#)
Simple triggered condition.
- class [URL](#)
Class to hold general URL's.
- class [URLLocation](#)
Class to hold a resolved [URL](#) location.
- class [PathIterator](#)
- class [User](#)
- class [XMLNode](#)
Wrapper for LibXML library Tree interface.
- class [XMLNodeContainer](#)
- class [XMLSecNode](#)
Extends [XMLNode](#) class to support XML security operation.
- class [cache_download_handler](#)
- class [Checksum](#)
Defines interface for variuos checksum manipulations.
- class [CRC32Sum](#)
Implementation of CRC32 checksum.
- class [MD5Sum](#)
Implementation of MD5 checksum.
- class [ChecksumAny](#)
Wrapper for [Checksum](#) class.
- class [DataBufferPar](#)
Represents set of buffers.
- class [DataCache](#)
- class [DataCallback](#)
- class [DataHandle](#)
This class is a wrapper around the [DataPoint](#) class.
- class [DataMover](#)
- class [DataPoint](#)
This base class is an abstraction of [URL](#).

- class [DataPointDirect](#)
This is a kind of generalized file handle.
- class [DataPointIndex](#)
Complements [DataPoint](#) with attributes common for Indexing [Service](#) URLs.
- class [DataSpeed](#)
Keeps track of average and instantaneous transfer speed.
- class **DataStatus**
- class **DMC**
- class **DMCConfig**
- class [FileInfo](#)
[FileInfo](#) stores information about files (metadata).
- class **URLMap**
- class **XmlContainer**
- class **XmlDatabase**
- class [DelegationConsumer](#)
- class [DelegationProvider](#)
- class [DelegationConsumerSOAP](#)
- class [DelegationProviderSOAP](#)
- class [DelegationContainerSOAP](#)
- class **InfoCache**
- class **InfoCacheInterface**
- class [InfoRegister](#)
Registration to ISIS interface.
- class [InfoRegisters](#)
Handling multiple registrations to ISISes.
- class [InformationInterface](#)
Information System message processor.
- class [InformationContainer](#)
Information System document container and processor.
- class [InformationRequest](#)
Request for information in InfoSystem.
- class [InformationResponse](#)
Informational response from InfoSystem.
- class [ACCFactory](#)
- class **ClassLoader**
- class [DMCFactory](#)
- class **LoadableClass**
- class [Loader](#)
Creator of [Message](#) Component Chains ([MCC](#)).

- class [ChainContext](#)
Interface to chain specific functionality.
- struct [loader_descriptor](#)
Identifier of plugin.
- class [LoaderFactory](#)
Plugin handler.
- class [MCCFactory](#)
MCC Plugins handler.
- class [ModuleManager](#)
Manager of shared libraries.
- class [PDPFactory](#)
PDP Plugins handler.
- class [PlexerEntry](#)
A pair of label (regex) and pointer to service.
- class [Plexer](#)
The [Plexer](#) class, used for routing messages to services.
- class [SecHandlerFactory](#)
SecHandler Plugins handler.
- class [ServiceFactory](#)
Service Plugins handler.
- class [MCCInterface](#)
Interface for communication between [MCC](#), [Service](#) and [Plexer](#) objects.
- class [MCC](#)
Message Chain Component - base class for every [MCC](#) plugin.
- class [MCCConfig](#)
- class [MCC_Status](#)
A class for communication of [MCC](#) processing results.
- class [MessagePayload](#)
Base class for content of message passed through chain.
- class [MessageContextElement](#)
Top class for elements contained in message context.
- class [MessageContext](#)
Handler for content of message context.

- class [MessageAuthContext](#)
Handler for content of message auth context.*
- class [Message](#)
Object being passed through chain of MCCs.
- class [AttributeIterator](#)
An iterator class for accessing multiple values of an attribute.
- class [MessageAttributes](#)
A class for storage of attribute values.
- class [MessageAuth](#)
Contains authenticity information, authorization tokens and decisions.
- class [PayloadRawInterface](#)
Random Access Payload for [Message](#) objects.
- struct **PayloadRawBuf**
- class [PayloadRaw](#)
Raw byte multi-buffer.
- class [PayloadSOAP](#)
Payload of [Message](#) with SOAP content.
- class [PayloadStreamInterface](#)
Stream-like Payload for [Message](#) object.
- class [PayloadStream](#)
POSIX handle as Payload.
- class [CStringValue](#)
This class implements case insensitive strings as security attributes.
- class [SecAttrValue](#)
This is an abstract interface to a security attribute.
- class [SecAttr](#)
This is an abstract interface to a security attribute.
- class [MultiSecAttr](#)
Container of multiple [SecAttr](#) attributes.
- class [Service](#)
[Service](#) - last component in a [Message](#) Chain.
- class [SOAPMessage](#)
[Message](#) restricted to SOAP payload.
- class [WSAEndpointReference](#)

Interface for manipulation of WS-Addressing Endpoint Reference.

- class [WSAHeader](#)

Interface for manipulation WS-Addressing information in SOAP header.

- class [SAMLToken](#)

Interface for manipulation of WS-Security according to SAML Token Profile.

- class [UsernameToken](#)

Interface for manipulation of WS-Security according to Username Token Profile.

- class [X509Token](#)

Interface for manipulation of WS-Security according to X.509 Token Profile.

- class [PayloadWSRF](#)

This class combines [MessagePayload](#) with [WSRF](#).

- class [WSRP](#)

Base class for WS-ResourceProperties structures.

- class [WSRPFault](#)

Base class for WS-ResourceProperties faults.

- class **WSRPInvalidResourcePropertyQNameFault**
- class [WSRPResourcePropertyChangeFailure](#)
- class **WSRPUnableToPutResourcePropertyDocumentFault**
- class **WSRPInvalidModificationFault**
- class **WSRPUnableToModifyResourcePropertyFault**
- class **WSRPSetResourcePropertyRequestFailedFault**
- class **WSRPInsertResourcePropertiesRequestFailedFault**
- class **WSRPUpdateResourcePropertiesRequestFailedFault**
- class **WSRPDeleteResourcePropertiesRequestFailedFault**
- class **WSRPGetResourcePropertyDocumentRequest**
- class **WSRPGetResourcePropertyDocumentResponse**
- class **WSRPGetResourcePropertyRequest**
- class **WSRPGetResourcePropertyResponse**
- class **WSRPGetMultipleResourcePropertiesRequest**
- class **WSRPGetMultipleResourcePropertiesResponse**
- class **WSRPPutResourcePropertyDocumentRequest**
- class **WSRPPutResourcePropertyDocumentResponse**
- class **WSRPModifyResourceProperties**
- class **WSRPInsertResourceProperties**
- class **WSRPUpdateResourceProperties**
- class **WSRPDeleteResourceProperties**
- class **WSRPSetResourcePropertiesRequest**
- class **WSRPSetResourcePropertiesResponse**
- class **WSRPInsertResourcePropertiesRequest**
- class **WSRPInsertResourcePropertiesResponse**
- class **WSRPUpdateResourcePropertiesRequest**
- class **WSRPUpdateResourcePropertiesResponse**

- class **WSRPDeleteResourcePropertiesRequest**
- class **WSRPDeleteResourcePropertiesResponse**
- class **WSRPQueryResourcePropertiesRequest**
- class **WSRPQueryResourcePropertiesResponse**
- class **WSRF**

*Base class for every **WSRF** message.*

- class **WSRFBaseFault**

*Base class for **WSRF** fault messages.*

- class **WSRFResourceUnknownFault**
- class **WSRFResourceUnavailableFault**

Typedefs

- typedef std::vector< std::vector< std::string > > **QueryArrayResult**
- typedef std::vector< std::string > **QueryRowResult**
- typedef std::map< std::string, std::string > **NS**
- typedef std::list< **Arc::XMLNode** > **XMLNodeList**
- typedef std::map< std::string, std::string > **DelegationRestrictions**
- typedef **loader_descriptor** loader_descriptors []
- typedef std::map< std::string, Glib::Module * > **plugin_cache_t**
- typedef std::multimap< std::string, std::string > **AttrMap**
- typedef AttrMap::const_iterator **AttrConstIter**
- typedef AttrMap::iterator **AttrIter**

Enumerations

- enum **WSSType** {
NONE, **USERTOKEN**, **X509TOKEN**, **SAMLTOKEN**,
KERBEROSTOKEN }
- enum **TimeFormat** {
MDSTime, **ASCTime**, **UserTime**, **ISOTime**,
UTCTime, **RFC1123Time** }
- enum **PeriodBase** {
PeriodMilliseconds, **PeriodSeconds**, **PeriodMinutes**, **PeriodHours**,
PeriodDays, **PeriodWeeks** }
- enum **LogLevel** {
VERBOSE = 1, **DEBUG** = 2, **INFO** = 4, **WARNING** = 8,
ERROR = 16, **FATAL** = 32 }
- enum **StatusKind** {
STATUS_UNDEFINED = 0, **STATUS_OK** = 1, **GENERIC_ERROR** = 2, **PARSING_ERROR** = 4,
PROTOCOL_RECOGNIZED_ERROR = 8, **UNKNOWN_SERVICE_ERROR** = 16, **BUSY_ERROR** = 32, **SESSION_CLOSE** = 64 }

- enum [WSAFault](#) {
[WSAFaultNone](#), [WSAFaultUnknown](#), [WSAFaultInvalidAddressingHeader](#), [WSAFaultInvalidAddress](#),
[WSAFaultInvalidEPR](#), [WSAFaultInvalidCardinality](#), [WSAFaultMissingAddressInEPR](#),
[WSAFaultDuplicateMessageID](#),
[WSAFaultActionMismatch](#), [WSAFaultOnlyAnonymousAddressSupported](#), [WSAFaultOnlyNonAnonymousAddressSupported](#), [WSAFaultMessageAddressingHeaderRequired](#),
[WSAFaultDestinationUnreachable](#), [WSAFaultActionNotSupported](#), [WSAFaultEndpointUnavailable](#) }

Functions

- `std::ostream & operator<< (std::ostream &, const Period &)`
- `std::ostream & operator<< (std::ostream &, const Time &)`
- `std::string TimeStamp (const TimeFormat &=Time::GetFormat())`
- `std::string TimeStamp (Time, const TimeFormat &=Time::GetFormat())`
- `void GUID (std::string &guid)`
- `std::string UUID (void)`
- `const char * FindTrans (const char *p)`
- `std::ostream & operator<< (std::ostream &os, const IString &msg)`
- `std::ostream & operator<< (std::ostream &os, LogLevel level)`
- `LogLevel string_to_level (const std::string &str)`
- `template<typename T> T stringto (const std::string &s)`
- `template<typename T> bool stringto (const std::string &s, T &t)`
- `template<typename T> std::string tostring (T t, const int width=0, const int precision=0)`
- `std::string upper (const std::string &s)`
- `void tokenize (const std::string &str, std::vector< std::string > &tokens, const std::string &delimiters=" ")`
- `std::string trim (const std::string &str, const char *sep=NULL)`
- `std::string uri_unescape (const std::string &str)`
- `bool CreateThreadFunction (void(*func)(void *), void *arg)`
- `std::list< URL > ReadURLList (const URL &urllist)`
- `std::string GetEnv (const std::string &var)`
- `void SetEnv (const std::string &var, const std::string &value)`
- `std::string StrError (int errnum=errno)`
- `std::ostream & operator<< (std::ostream &out, const XMLNode &node)`
- `std::istream & operator>> (std::istream &in, XMLNode &node)`
- `bool MatchXMLName (const XMLNode &node1, const XMLNode &node2)`
- `bool MatchXMLName (const XMLNode &node, const char *name)`
- `bool MatchXMLName (const XMLNode &node, const std::string &name)`
- `bool MatchXMLNamespace (const XMLNode &node1, const XMLNode &node2)`
- `bool MatchXMLNamespace (const XMLNode &node, const char *uri)`
- `bool MatchXMLNamespace (const XMLNode &node, const std::string &uri)`
- `int passphrase_callback (char *buf, int size, int rflag, void *)`
- `bool init_xmlsec (void)`
- `bool final_xmlsec (void)`
- `std::string get_cert_str (const char *certfile)`
- `xmlSecKey * get_key_from_keystr (const std::string &value)`
- `std::string get_key_from_certfile (const char *certfile)`

- `xmlSecKey * get_key_from_certstr (const std::string &value)`
- `xmlSecKeysMngrPtr load_key_from_keyfile (xmlSecKeysMngrPtr *keys_manager, const char *keyfile)`
- `xmlSecKeysMngrPtr load_key_from_certfile (xmlSecKeysMngrPtr *keys_manager, const char *certfile)`
- `xmlSecKeysMngrPtr load_key_from_certstr (xmlSecKeysMngrPtr *keys_manager, const std::string &certstr)`
- `xmlSecKeysMngrPtr load_trusted_cert_file (xmlSecKeysMngrPtr *keys_manager, const char *cert_file)`
- `xmlSecKeysMngrPtr load_trusted_cert_str (xmlSecKeysMngrPtr *keys_manager, const std::string &cert_str)`
- `xmlSecKeysMngrPtr load_trusted_certs (xmlSecKeysMngrPtr *keys_manager, const char *cafile, const char *capath)`
- `XMLNode get_node (XMLNode &parent, const char *name)`
- `int cache_download_url_start (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, const std::string &url, const std::string &id, cache_download_handler &handler)`
- `int cache_download_file_start (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, const std::string &fname, const std::string &id, cache_download_handler &handler)`
- `int cache_download_url_end (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, const std::string &url, cache_download_handler &handler, bool success)`
- `int cache_find_url (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, const std::string &url, const std::string &id, std::string &options, std::string &fname)`
- `int cache_find_file (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, const std::string &fname, std::string &url, std::string &options)`
- `int cache_release_url (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, const std::string &url, const std::string &id, bool remove)`
- `int cache_release_url (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, const std::string &id, bool remove)`
- `int cache_release_file (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, const std::string &fname, const std::string &id, bool remove)`
- `int cache_invalidate_url (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, const std::string &fname)`
- `unsigned long long int cache_clean (const std::string &cache_path, const std::string &cache_data_path, const User &cache_user, unsigned long long int size)`
- `int cache_claiming_list (const std::string &cache_path, const std::string &fname, std::list< std::string > &ids)`
- `int cache_is_claimed_file (const std::string &cache_path, const std::string &fname)`
- `int cache_files_list (const std::string &cache_path, const User &cache_user, std::list< std::string > &files)`
- `int cache_history_lists (const std::string &cache_path, std::list< std::string > &olds, std::list< std::string > &news)`
- `int cache_history_remove (const std::string &cache_path, std::list< std::string > &olds, std::list< std::string > &news)`
- `int cache_history (const std::string &cache_path, bool enable, const User &cache_user)`
- `std::string string (StatusKind kind)`
- `const char * ContentFromPayload (const MessagePayload &payload)`
- `void WSAFaultAssign (SOAPEnvelope &message, WSAFault fid)`
- `WSAFault WSAFaultExtract (SOAPEnvelope &message)`
- `WSRF & CreateWSRP (SOAPEnvelope &soap)`
- `WSRF & CreateWSRFBaseFault (SOAPEnvelope &soap)`

Variables

- const Glib::TimeVal [ETERNAL](#)
- const Glib::TimeVal [HISTORIC](#)
- [Logger](#) stringLogger
- const char * WSRFBaseFaultAction

4.1.1 Detailed Description

Base class for bulk job control

4.1.2 Typedef Documentation

4.1.2.1 typedef [loader_descriptor](#) [Arc::loader_descriptors](#)[]

Elements are detected by presence of element with particular name of loader_descriptors type. That is an array of [loader_descriptor](#) or similar elements. To check for end of array use `ARC_LOADER_FINAL()` macro

4.1.2.2 typedef std::multimap<std::string,std::string> [Arc::AttrMap](#)

A typedef of a multimap for storage of message attributes.

This typedef is used as a shorthand for a multimap that uses strings for keys as well as values. It is used within the `MessageAttributes` class for internal storage of message attributes, but is not visible externally.

4.1.2.3 typedef AttrMap::const_iterator [Arc::AttrConstIter](#)

A typedef of a const_iterator for AttrMap.

This typedef is used as a shorthand for a const_iterator for AttrMap. It is used extensively within the [MessageAttributes](#) class as well as the `AttributesIterator` class, but is not visible externally.

4.1.2.4 typedef AttrMap::iterator [Arc::AttrIter](#)

A typedef of an (non-const) iterator for AttrMap.

This typedef is used as a shorthand for a (non-const) iterator for AttrMap. It is used in one method within the [MessageAttributes](#) class, but is not visible externally.

4.1.3 Enumeration Type Documentation

4.1.3.1 enum [Arc::WSSType](#)

Configuration information for WS-Security, including WS-Security profile type, and the information which will be used by the specific WS-Security profile.

4.1.3.2 enum [Arc::TimeFormat](#)

An enumeration that contains the possible textual timeformats.

4.1.3.3 enum [Arc::LogLevel](#)

Logging levels.

Logging levels for tagging and filtering log messages.

4.1.3.4 enum [Arc::StatusKind](#)

Status kinds (types).

This enum defines a set of possible status kinds.

Enumerator:

STATUS_OK Default status - undefined error.

GENERIC_ERROR No error.

PARSING_ERROR Error does not fit any class.

PROTOCOL_RECOGNIZED_ERROR Error detected while parsing request/response.

UNKNOWN_SERVICE_ERROR [Message](#) does not fit into expected protocol.

BUSY_ERROR There is no destination configured for this message.

SESSION_CLOSE [Message](#) can't be processed now.

4.1.3.5 enum [Arc::WSAFault](#)

WS-Addressing possible faults.

Enumerator:

WSAFaultUnknown This is not a fault

WSAFaultInvalidAddressingHeader This is not a WS-Addressing fault

4.1.4 Function Documentation**4.1.4.1 `std::ostream& Arc::operator<< (std::ostream &, const Period &)`**

Prints a Period-object to the given ostream – typically cout.

4.1.4.2 `std::ostream& Arc::operator<< (std::ostream &, const Time &)`

Prints a Time-object to the given ostream – typically cout.

4.1.4.3 `std::string Arc::TimeStamp (const TimeFormat & = Time::GetFormat())`

Returns a time-stamp of the current time in some format.

4.1.4.4 `std::string Arc::TimeStamp (Time, const TimeFormat & = Time::GetFormat ())`

Returns a time-stamp of some specified time in some format.

4.1.4.5 `void Arc::GUID (std::string & guid)`

This function generates a random identifier which is quite unique as well.

4.1.4.6 `std::string Arc::UUID (void)`

This function generates uuid.

4.1.4.7 `std::ostream& Arc::operator<< (std::ostream & os, LogLevel level)`

Printing of LogLevel values to ostreams.

Output operator so that LogLevel values can be printed in a nicer way.

4.1.4.8 `template<typename T> T Arc::stringto (const std::string & s)`

This method converts a string to any type.

4.1.4.9 `template<typename T> bool Arc::stringto (const std::string & s, T & t)`

This method converts a string to any type but lets calling function process errors.

4.1.4.10 `template<typename T> std::string Arc::tostring (T t, const int width = 0, const int precision = 0)`

This method converts any type to a string of the width given.

4.1.4.11 `std::string Arc::upper (const std::string & s)`

This method converts to upper case of the string.

4.1.4.12 `void Arc::tokenize (const std::string & str, std::vector< std::string > & tokens, const std::string & delimiters = " ")`

This method tokenize string.

4.1.4.13 `std::string Arc::trim (const std::string & str, const char * sep = NULL)`

This method removes given separators from the beginning and the end of the string.

4.1.4.14 `std::string Arc::uri_unescape (const std::string & str)`

This method unescape the URI encoded string.

4.1.4.15 bool Arc::CreateThreadFunction (void(*) (void *) *func*, void * *arg*)

Helper function to create simple thread.

It takes care of all peculiarities of Glib::Thread API. As result it runs function 'func' with argument 'arg' in a separate thread. Returns true on success.

4.1.4.16 std::list<[URL](#)> Arc::ReadURLList (const URL & *urllist*)

Reads a list of URLs from a file.

4.1.4.17 bool Arc::MatchXMLName (const XMLNode & *node1*, const XMLNode & *node2*)

Returns true if underlying XML elements have same names

4.1.4.18 bool Arc::MatchXMLName (const XMLNode & *node*, const char * *name*)

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

4.1.4.19 bool Arc::MatchXMLName (const XMLNode & *node*, const std::string & *name*)

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

4.1.4.20 bool Arc::MatchXMLNamespace (const XMLNode & *node1*, const XMLNode & *node2*)

Returns true if underlying XML elements belong to same namespaces

4.1.4.21 bool Arc::MatchXMLNamespace (const XMLNode & *node*, const char * *uri*)

Returns true if 'namespace' matches 'node's namespace.

4.1.4.22 bool Arc::MatchXMLNamespace (const XMLNode & *node*, const std::string & *uri*)

Returns true if 'namespace' matches 'node's namespace.

4.1.4.23 std::string Arc::string (StatusKind *kind*)

Conversion to string.

Conversion from StatusKind to string.

Parameters:

kind The StatusKind to convert.

4.1.4.24 const char* Arc::ContentFromPayload (const MessagePayload & *payload*)

Returns pointer to main memory chunk of [Message](#) payload.

If no buffer is present or if payload is not of [PayloadRawInterface](#) type NULL is returned.

4.1.4.25 void Arc::WSAFaultAssign (SOAPEnvelope & *message*, WSAFault *fid*)

Makes WS-Addressing fault.

It fills SOAP Fault message with WS-Addressing fault related information.

4.1.4.26 [WSAFault](#) Arc::WSAFaultExtract (SOAPEnvelope & *message*)

Gets WS-addressing fault.

Analyzes SOAP Fault message and returns WS-Addressing fault it represents.

4.1.5 Variable Documentation**4.1.5.1 const Glib::TimeVal [Arc::ETERNAL](#)**

A time very far in the future.

4.1.5.2 const Glib::TimeVal [Arc::HISTORIC](#)

A time very far in the past.

Chapter 5

Hosting Environment (Daemon) Class Documentation

5.1 acc_descriptor Struct Reference

```
#include <ACCLoader.h>
```

Public Attributes

- `const char * name`
- `int version`
- `Arc::ACC *(* get_instance)(Arc::Config *cfg, Arc::ChainContext *ctx)`

5.1.1 Detailed Description

This structure describes one of the ACCs stored in a shared library. It contains name of plugin, version number and pointer to function which creates an instance of an object inherited from the ACC class.


The documentation for this struct was generated from the following file:

- `ACCLoader.h`

5.2 Arc::ACCFactory Class Reference

```
#include <ACCFactory.h>
```

Inheritance diagram for Arc::ACCFactory::



Public Member Functions

- [ACCFactory](#) ([Config](#) *cfg)
- ACC * [get_instance](#) (const std::string &name, [Config](#) *cfg, [ChainContext](#) *ctx)
- ACC * [get_instance](#) (const std::string &name, int version, [Config](#) *cfg, [ChainContext](#) *ctx)
- ACC * [get_instance](#) (const std::string &name, int min_version, int max_version, [Config](#) *cfg, [ChainContext](#) *ctx)

5.2.1 Detailed Description

This class handles shared libraries containing ACCs

5.2.2 Constructor & Destructor Documentation

5.2.2.1 Arc::ACCFactory::ACCFactory ([Config](#) *cfg)

Constructor - accepts configuration (not yet used) meant to tune loading of module.

5.2.3 Member Function Documentation

5.2.3.1 ACC* Arc::ACCFactory::get_instance (const std::string & name, [Config](#) *cfg, [ChainContext](#) *ctx)

These methods load shared library named lib'name', locate symbol representing descriptor of ACC and calls it's constructor function. Supplied configuration tree is passed to constructor. Returns created ACC instance.

Reimplemented from [Arc::LoaderFactory](#).

The documentation for this class was generated from the following file:

- [ACCFactory.h](#)

5.3 ArcSec::AlgFactory Class Reference

Interface for algorithm factory class.

```
#include <AlgFactory.h>
```

Public Member Functions

- virtual [CombiningAlg](#) * [createAlg](#) (const std::string &type)=0

Protected Attributes

- AlgMap [algmap](#)

5.3.1 Detailed Description

Interface for algorithm factory class.

[AlgFactory](#) is in charge of creating [CombiningAlg](#) according to the algorithm type

5.3.2 Member Function Documentation

5.3.2.1 virtual [CombiningAlg](#)* [ArcSec::AlgFactory::createAlg](#) (const std::string & *type*) [pure virtual]

creat algorithm object based on the type algorithm type

The documentation for this class was generated from the following file:


- AlgFactory.h

5.4 ArcSec::ArcAttributeProxy< TheAttribute > Class Template Reference

Arc specific [AttributeProxy](#) class.

```
#include <AttributeProxy.h>
```

Inheritance diagram for ArcSec::ArcAttributeProxy< TheAttribute >::



Public Member Functions

- virtual [AttributeValue](#) * [getAttribute](#) (const [Arc::XMLNode](#) &node)

5.4.1 Detailed Description

```
template<class TheAttribute> class ArcSec::ArcAttributeProxy< TheAttribute >
```

Arc specific [AttributeProxy](#) class.

5.4.2 Member Function Documentation

5.4.2.1 `template<class TheAttribute> AttributeValue * ArcSec::ArcAttributeProxy< TheAttribute >::getAttribute (const Arc::XMLNode & node)` [virtual]

Implementation of [getAttribute](#).

Implements [ArcSec::AttributeProxy](#).

The documentation for this class was generated from the following file:

- [AttributeProxy.h](#)

5.5 Arc::ArcLocation Class Reference

Determines ARC installation location.

```
#include <ArcLocation.h>
```

Static Public Member Functions

- static void [Init](#) (std::string path)
- static const std::string & [Get](#) ()
- static std::list< std::string > [GetPlugins](#) ()

5.5.1 Detailed Description

Determines ARC installation location.

5.5.2 Member Function Documentation

5.5.2.1 static const std::string& Arc::ArcLocation::Get () [static]

Returns ARC installation location.

5.5.2.2 static std::list<std::string> Arc::ArcLocation::GetPlugins () [static]

Returns ARC plugins directory location.

Main source is value of variable ARC_PLUGIN_PATH, otherwise path is derived from installation location.

5.5.2.3 static void Arc::ArcLocation::Init (std::string *path*) [static]

Initializes location information.

Main source is value of variable ARC_LOCATION, otherwise path to executable provided in is used. If nothing works then warning message is sent to logger and initial installation prefix is used.

The documentation for this class was generated from the following file:

- ArcLocation.h

5.6 ArcSec::Attr Struct Reference

[Attr](#) contains a tuple of attribute type and value.

```
#include <Request.h>
```

Public Attributes

- `std::string value`
- `std::string type`

5.6.1 Detailed Description

[Attr](#) contains a tuple of attribute type and value.

The documentation for this struct was generated from the following file:

- `Request.h`

5.7 ArcSec::AttributeFactory Class Reference

```
#include <AttributeFactory.h>
```

Public Member Functions

- virtual [AttributeValue](#) * **createValue** (const [Arc::XMLNode](#) &node, const std::string &type)=0

Protected Attributes

- AttrProxyMap **apmap**

5.7.1 Detailed Description

Base attribute factory class

The documentation for this class was generated from the following file:

- AttributeFactory.h

5.8 Arc::AttributeIterator Class Reference

An iterator class for accessing multiple values of an attribute.

```
#include <MessageAttributes.h>
```

Public Member Functions

- [AttributeIterator](#) ()
- const std::string & [operator *](#) () const
- const std::string * [operator →](#) () const
- const std::string & [key](#) (void) const
- const [AttributeIterator](#) & [operator++](#) ()
- [AttributeIterator](#) [operator++](#) (int)
- bool [hasMore](#) () const

Protected Member Functions

- [AttributeIterator](#) ([AttrConstIter](#) begin, [AttrConstIter](#) end)

Protected Attributes

- [AttrConstIter](#) [current_](#)
- [AttrConstIter](#) [end_](#)

Friends

- class [MessageAttributes](#)

5.8.1 Detailed Description

An iterator class for accessing multiple values of an attribute.

This is an iterator class that is used when accessing multiple values of an attribute. The `getAll()` method of the [MessageAttributes](#) class returns an [AttributeIterator](#) object that can be used to access the values of the attribute.

Typical usage is:

```
Arc::MessageAttributes attributes;  
...  
for (Arc::AttributeIterator iterator=attributes.getAll("Foo:Bar");  
     iterator.hasMore(); ++iterator)  
    std::cout << *iterator << std::endl;
```

5.8.2 Constructor & Destructor Documentation

5.8.2.1 Arc::AttributeIterator::AttributeIterator ()

Default constructor.

The default constructor. Does nothing since all attributes are instances of well-behaving STL classes.

5.8.2.2 Arc::AttributeIterator::AttributeIterator ([AttrConstIter](#) *begin*, [AttrConstIter](#) *end*) [protected]

Protected constructor used by the [MessageAttributes](#) class.

This constructor is used to create an iterator for iteration over all values of an attribute. It is not supposed to be visible externally, but is only used from within the `getAll()` method of [MessageAttributes](#) class.

Parameters:

begin A `const_iterator` pointing to the first matching key-value pair in the internal multimap of the [MessageAttributes](#) class.

end A `const_iterator` pointing to the first key-value pair in the internal multimap of the [MessageAttributes](#) class where the key is larger than the key searched for.

5.8.3 Member Function Documentation

5.8.3.1 bool Arc::AttributeIterator::hasMore () const

Predicate method for iteration termination.

This method determines whether there are more values for the iterator to refer to.

Returns:

Returns true if there are more values, otherwise false.

5.8.3.2 const std::string& Arc::AttributeIterator::key (void) const

The key of attribute.

This method returns reference to key of attribute to which iterator refers.

5.8.3.3 const std::string& Arc::AttributeIterator::operator * () const

The dereference operator.

This operator is used to access the current value referred to by the iterator.

Returns:

A (constant reference to a) string representation of the current value.

5.8.3.4 [AttributeIterator](#) Arc::AttributeIterator::operator++ (int)

The postfix advance operator.

Advances the iterator to the next value. Works intuitively.

Returns:

An iterator referring to the value referred to by this iterator before the advance.

5.8.3.5 `const AttributeIterator& Arc::AttributeIterator::operator++ ()`

The prefix advance operator.

Advances the iterator to the next value. Works intuitively.

Returns:

A const reference to this iterator.

5.8.3.6 `const std::string* Arc::AttributeIterator::operator → () const`

The arrow operator.

Used to call methods for value objects (strings) conveniently.

5.8.4 Friends And Related Function Documentation

5.8.4.1 `friend class MessageAttributes` [friend]

The `MessageAttributes` class is a friend.

The constructor that creates an `AttributeIterator` that is connected to the internal multimap of the `MessageAttributes` class should not be exposed to the outside, but it still needs to be accessible from the `getAll()` method of the `MessageAttributes` class. Therefore, that class is a friend.

5.8.5 Member Data Documentation

5.8.5.1 `AttrConstIter Arc::AttributeIterator::current_` [protected]

A `const_iterator` pointing to the current key-value pair.

This iterator is the internal representation of the current value. It points to the corresponding key-value pair in the internal multimap of the `MessageAttributes` class.

5.8.5.2 `AttrConstIter Arc::AttributeIterator::end_` [protected]

A `const_iterator` pointing beyond the last key-value pair.

A `const_iterator` pointing to the first key-value pair in the internal multimap of the `MessageAttributes` class where the key is larger than the key searched for.

The documentation for this class was generated from the following file:


- `MessageAttributes.h`

5.9 ArcSec::AttributeProxy Class Reference

Interface for generating the [AttributeValue](#) object, it will be used by [AttributeFactory](#).

```
#include <AttributeProxy.h>
```

Inheritance diagram for ArcSec::AttributeProxy::



Public Member Functions

- virtual [AttributeValue](#) * **getAttribute** (const [Arc::XMLNode](#) &node)=0

5.9.1 Detailed Description

Interface for generating the [AttributeValue](#) object, it will be used by [AttributeFactory](#).

the [AttributeProxy](#) object will be insert into AttributeFactoty; and the getAttribute(node) method will be called inside AttributeFacroty.createvalue(node), in order to generate a specific [AttributeValue](#)

The documentation for this class was generated from the following file:

- [AttributeProxy.h](#)

5.10 ArcSec::AttributeValue Class Reference

Interface for different type of <Attribute> for both policy and request.

```
#include <AttributeValue.h>
```

Public Member Functions

- virtual bool [equal](#) ([AttributeValue](#) *value)=0
- virtual std::string [encode](#) ()=0
- virtual std::string [getType](#) ()=0
- virtual std::string [getId](#) ()=0

5.10.1 Detailed Description

Interface for different type of <Attribute> for both policy and request.

<Attribute> uses different "Type" definition; Each type of <Attribute> needs different approach to compare. The "Type" supported so far is: StringAttribute, DateAttribute, TimeAttribute, DurationAttribute, PeriodAttribute, AnyURIAttribute, X500NameAttribute

5.10.2 Member Function Documentation

5.10.2.1 virtual std::string ArcSec::AttributeValue::encode () [pure virtual]

encode the value in a string format

5.10.2.2 virtual bool ArcSec::AttributeValue::equal ([AttributeValue](#) * *value*) [pure virtual]

evaluate whether "this" equals to the parameter value

5.10.2.3 virtual std::string ArcSec::AttributeValue::getId () [pure virtual]

get the id of the <Attribute>

5.10.2.4 virtual std::string ArcSec::AttributeValue::getType () [pure virtual]

get the type of the <Attribute>

The documentation for this class was generated from the following file:

- AttributeValue.h

5.11 ArcSec::Attrs Class Reference

[Attrs](#) is a container for one or more [Attr](#).

```
#include <Request.h>
```

Public Member Functions

- void **addItem** ([Attr](#) attr)
- int **size** ()
- [Attr](#) & **getItem** (int n)
- [Attr](#) & **operator[]** (int n)

5.11.1 Detailed Description

[Attrs](#) is a container for one or more [Attr](#).

[Attrs](#) includes includes methods for inserting, getting items, and counting size as well

The documentation for this class was generated from the following file:

- Request.h

5.12 ArcSec::AuthzRequestSection Struct Reference

```
#include <PDP.h>
```

Public Attributes

- std::string **value**
- std::string **id**
- std::string **type**
- std::string **issuer**

5.12.1 Detailed Description

These structure are based on the request schema for [PDP](#), so far it can apply to the ArcPDP's request schema, see `src/hed/pdc/Request.xsd` and `src/hed/pdc/Request.xml`. It could also apply to the XACMLPDP's request schema, since the difference is minor.

Another approach is, the service composes/marshalls the xml structure directly, then the service should use difference code to compose for ArcPDP's request schema and XACMLPDP's schema, which is not so good.

The documentation for this struct was generated from the following file:

- `PDP.h`

5.13 Arc::BaseConfig Class Reference

```
#include <ArcConfig.h>
```

Public Member Functions

- void [AddPluginsPath](#) (const std::string &path)
- void [AddPrivateKey](#) (const std::string &path)
- void [AddCertificate](#) (const std::string &path)
- void [AddProxy](#) (const std::string &path)
- void [AddCAFile](#) (const std::string &path)
- void [AddCADir](#) (const std::string &path)
- void [AddWSSType](#) (const [Arc::WSSType](#) &type)
- void [AddWSSInfo](#) (const Arc::WSSInfo &info)
- void [AddOverlay](#) ([XMLNode](#) cfg)
- void [GetOverlay](#) (std::string fname)
- virtual [XMLNode MakeConfig](#) ([XMLNode](#) cfg) const

Public Attributes

- std::string **key**
- std::string **cert**
- std::string **proxy**
- std::string **cafile**
- std::string **cadir**
- [WSSType](#) **wsstype**
- WSSInfo **wssinfo**
- [XMLNode](#) **overlay**

Protected Attributes

- std::list< std::string > **plugin_paths**

5.13.1 Detailed Description

Configuration for client interface. It contains information which can't be expressed in class constructor arguments. Most probably common things like software installation location, identity of user, etc.

5.13.2 Member Function Documentation

5.13.2.1 void Arc::BaseConfig::AddCADir (const std::string & *path*)

Add CA directory

5.13.2.2 void Arc::BaseConfig::AddCAFile (const std::string & *path*)

Add CA file

5.13.2.3 void Arc::BaseConfig::AddCertificate (const std::string & *path*)

Add certificate

5.13.2.4 void Arc::BaseConfig::AddOverlay ([XMLNode](#) *cfg*)

Add configuration overlay

5.13.2.5 void Arc::BaseConfig::AddPluginsPath (const std::string & *path*)

Adds non-standard location of plugins

5.13.2.6 void Arc::BaseConfig::AddPrivateKey (const std::string & *path*)

Add private key

5.13.2.7 void Arc::BaseConfig::AddProxy (const std::string & *path*)

Add credentials proxy

5.13.2.8 void Arc::BaseConfig::AddWSSInfo (const Arc::WSSInfo & *info*)

Add WSS information

5.13.2.9 void Arc::BaseConfig::AddWSSType (const [Arc::WSSType](#) & *type*)

Add WSS type

5.13.2.10 void Arc::BaseConfig::GetOverlay (std::string *fname*)

Read overlay from file

5.13.2.11 virtual [XMLNode](#) Arc::BaseConfig::MakeConfig ([XMLNode](#) *cfg*) const [virtual]

Adds configuration part corresponding to stored information into common configuration tree supplied in 'cfg' argument.

The documentation for this class was generated from the following file:

- ArcConfig.h

5.14 Arc::ChainContext Class Reference

Interface to chain specific functionality.

```
#include <Loader.h>
```

Public Member Functions

- [operator ServiceFactory * \(\)](#)
- [operator MCCFactory * \(\)](#)
- [operator SecHandlerFactory * \(\)](#)
- [operator PDPFactory * \(\)](#)

Friends

- class **Loader**

5.14.1 Detailed Description

Interface to chain specific functionality.

Object of this class is associated with every [Loader](#) object. It is accessible for [MCC](#) and [Service](#) components and provides an interface to manipulate chains stored in [Loader](#). This makes it possible to modify chains dynamically - like deploying new services on demand.

5.14.2 Member Function Documentation

5.14.2.1 Arc::ChainContext::operator [MCCFactory](#) * () [inline]

Returns associated [MCCFactory](#) object

5.14.2.2 Arc::ChainContext::operator [PDPFactory](#) * () [inline]

Returns associated [PDPFactory](#) object

5.14.2.3 Arc::ChainContext::operator [SecHandlerFactory](#) * () [inline]

Returns associated [SecHandlerFactory](#) object

5.14.2.4 Arc::ChainContext::operator [ServiceFactory](#) * () [inline]

Returns associated [ServiceFactory](#) object

The documentation for this class was generated from the following file:


- [Loader.h](#)

5.15 Arc::Checksum Class Reference

Defines interface for variuos checksum manipulations.

```
#include <Checksum.h>
```

Inheritance diagram for Arc::Checksum::



Public Member Functions

- virtual void **start** (void)=0
- virtual void **add** (void *buf, unsigned long long int len)=0
- virtual void **end** (void)=0
- virtual void **result** (unsigned char *&res, unsigned int &len) const =0
- virtual int **print** (char *buf, int len) const
- virtual void **scan** (const char *buf)=0
- virtual **operator bool** (void) const
- virtual bool **operator!** (void) const

5.15.1 Detailed Description

Defines interface for variuos checksum manipulations.

This class is used during data transfers through [DataBufferPar](#) class

The documentation for this class was generated from the following file:


- CheckSum.h

5.16 Arc::ChecksumAny Class Reference

Wrapper for [Checksum](#) class.

```
#include <Checksum.h>
```

Inheritance diagram for Arc::ChecksumAny::



Public Types

- **none**
- **unknown**
- **undefined**
- **cksum**
- **md5**
- enum **type** {
 - none**, **unknown**, **undefined**, **cksum**,
 - md5** }

Public Member Functions

- **ChecksumAny** ([Checksum](#) *c=NULL)
- **ChecksumAny** (type type)
- **ChecksumAny** (const char *type)
- virtual void **start** (void)
- virtual void **add** (void *buf, unsigned long long int len)
- virtual void **end** (void)
- virtual void **result** (unsigned char *&res, unsigned int &len) const
- virtual int **print** (char *buf, int len) const
- virtual void **scan** (const char *buf)
- virtual **operator bool** (void) const
- virtual bool **operator!** (void) const
- bool **active** (void)
- type **Type** (void)
- void **operator=** (const char *type)
- bool **operator==** (const char *s)
- bool **operator==** (const [ChecksumAny](#) &ck)

Static Public Member Functions

- static type **Type** (const char *crc)

5.16.1 Detailed Description

Wrapper for [Checksum](#) class.

To be used for manipulation of any supported checksum type in a transparent way.

The documentation for this class was generated from the following file:


- CheckSum.h

5.17 Arc::CIStrngValue Class Reference

This class implements case insensitive strings as security attributes.

```
#include <CIStrngValue.h>
```

Inheritance diagram for Arc::CIStrngValue::



Public Member Functions

- [CIStrngValue](#) ()
- [CIStrngValue](#) (const char *ss)
- [CIStrngValue](#) (const std::string &ss)
- virtual [operator bool](#) ()

Protected Member Functions

- virtual bool [equal](#) ([SecAttrValue](#) &b)

Protected Attributes

- std::string s

5.17.1 Detailed Description

This class implements case insensitive strings as security attributes.

This is an example of how to inherit [SecAttrValue](#). The class is meant to implement security attributes that are case insensitive strings.

5.17.2 Constructor & Destructor Documentation

5.17.2.1 Arc::CIStrngValue::CIStrngValue ()

Default constructor

5.17.2.2 Arc::CIStrngValue::CIStrngValue (const char * ss)

This is a constructor that takes a string literal.

5.17.2.3 Arc::CIStrngValue::CIStrngValue (const std::string & ss)

This is a constructor that takes a string object.

5.17.3 Member Function Documentation

5.17.3.1 `virtual bool Arc::CStringValue::equal (SecAttrValue & b)` [protected, virtual]

This function returns true if two strings are the same apart from letter case

Reimplemented from [Arc::SecAttrValue](#).

5.17.3.2 `virtual Arc::CStringValue::operator bool ()` [virtual]

This function returns false if the string is empty or uninitialized

Reimplemented from [Arc::SecAttrValue](#).

The documentation for this class was generated from the following file:

- `CStringValue.h`

5.18 Arc::ClientSOAP Class Reference

```
#include <ClientInterface.h>
```

Public Member Functions

- [ClientSOAP](#) ()
- [ClientSOAP](#) (const [BaseConfig](#) &cfg, const std::string &host, int port, bool tls, const std::string &path)
- [MCC_Status process](#) ([PayloadSOAP](#) *request, [PayloadSOAP](#) **response)
- [MCC_Status process](#) (const std::string &action, [PayloadSOAP](#) *request, [PayloadSOAP](#) **response)
- [MCC * GetEntry](#) ()
- virtual void [Load](#) ()

Protected Attributes

- [MCC * soap_entry](#)

5.18.1 Detailed Description

Class with easy interface for sending/receiving SOAP messages over HTTP(S). It takes care of configuring [MCC](#) chain and making an entry point.

5.18.2 Constructor & Destructor Documentation

5.18.2.1 Arc::ClientSOAP::ClientSOAP () [inline]

Constructor creates [MCC](#) chain and connects to server. cfg - common configuration, host - hostname of remote server, port - TCP port of remote server, tls - true if connection to use HTTPS, false for HTTP, path - internal path of service to be contacted. TODO: use [URL](#).

5.18.3 Member Function Documentation

5.18.3.1 [MCC_Status](#) Arc::ClientSOAP::process (const std::string & action, [PayloadSOAP](#) * request, [PayloadSOAP](#) ** response)

Send SOAP request with specified SOAP action and receive response.

5.18.3.2 [MCC_Status](#) Arc::ClientSOAP::process ([PayloadSOAP](#) * request, [PayloadSOAP](#) ** response)

Send SOAP request and receive response.

The documentation for this class was generated from the following file:


- ClientInterface.h

5.19 ArcSec::CombiningAlg Class Reference

Interface for combining algrithm.

```
#include <CombiningAlg.h>
```

Inheritance diagram for ArcSec::CombiningAlg::



Public Member Functions

- virtual Result [combine](#) ([EvaluationCtx](#) *ctx, std::list< [Policy](#) * > policies)=0
- virtual std::string & [getalgId](#) (void)=0

5.19.1 Detailed Description

Interface for combining algrithm.

5.19.2 Member Function Documentation

5.19.2.1 virtual Result ArcSec::CombiningAlg::combine ([EvaluationCtx](#) * ctx, std::list< [Policy](#) * > *policies*) [pure virtual]

Evaluate request against policy, and if there are more than one policies, combine the evaluation results according to the combing algorithm implemented inside in the method combine(ctx, policies) itself.

Parameters:

- ctx* The information about request is included
- policies* The "match" and "eval" method inside policy will be called

Implemented in [ArcSec::DenyOverridesCombiningAlg](#), and [ArcSec::PermitOverridesCombiningAlg](#).

The documentation for this class was generated from the following file:


- CombiningAlg.h

5.20 Arc::Config Class Reference

Configuration element - represents (sub)tree of ARC configuration.

```
#include <ArcConfig.h>
```

Inheritance diagram for Arc::Config::



Public Member Functions

- [Config](#) ()
- [Config](#) (const NS &ns)
- [Config](#) (const char *filename)
- [Config](#) (const std::string &xml_str)
- [Config](#) ([Arc::XMLNode](#) xml)
- [Config](#) ([Arc::XMLNode](#) xml, const std::string &filename)
- [Config](#) (long cfg_ptr_addr)
- [Config](#) (const [Config](#) &cfg)
- void [print](#) (void)
- void [parse](#) (const char *filename)
- const std::string & [getFileName](#) (void)
- void [setFileName](#) (const std::string &filename)
- void [save](#) (const char *filename)

5.20.1 Detailed Description

Configuration element - represents (sub)tree of ARC configuration.

This class is intended to be used to pass configuration details to various parts of HED and external modules. Currently it's just a wrapper over XML tree. But than may change in a future, although interface should be preserved. Currently it is capable of loading XML configuration document from file. In future it will be capable of loading more user-readable format and process it into tree-like structure convenient for machine processing (XML-like). So far there are no schema and/or namespaces assigned.

5.20.2 Constructor & Destructor Documentation

5.20.2.1 Arc::Config::Config () [inline]

Dummy constructor - produces invalid structure

5.20.2.2 Arc::Config::Config (const NS & ns) [inline]

Creates empty XML tree

5.20.2.3 Arc::Config::Config (const char **filename*)

Loads configuration document from file '*filename*'

5.20.2.4 Arc::Config::Config (const std::string &*xml_str*) [inline]

Parse configuration document from memory

5.20.2.5 Arc::Config::Config ([Arc::XMLNode](#) *xml*) [inline]

Acquire existing XML (sub)tree. Content is not copied. Make sure XML tree is not destroyed while in use by this object.

5.20.2.6 Arc::Config::Config (long *cfg_ptr_addr*)

Copy constructor used by language bindings

5.20.2.7 Arc::Config::Config (const [Config](#) &*cfg*)

Copy constructor used by language bindings

5.20.3 Member Function Documentation**5.20.3.1 const std::string& Arc::Config::getFileName (void)** [inline]

Gives back file name of config file or empty string if it was generated from the [XMLNode](#) subtree

5.20.3.2 void Arc::Config::parse (const char **filename*)

Parse configuration document from file '*filename*'

5.20.3.3 void Arc::Config::print (void)

Print structure of document. For debugging purposes. Printed content is not an XML document.

5.20.3.4 void Arc::Config::save (const char **filename*)

Save to file

5.20.3.5 void Arc::Config::setFileName (const std::string &*filename*) [inline]

Set the file name of config file

The documentation for this class was generated from the following file:


- ArcConfig.h

5.21 Arc::Counter Class Reference

A class defining a common interface for counters.

```
#include <Counter.h>
```

Inheritance diagram for Arc::Counter::



Public Member Functions

- virtual `~Counter ()`
- virtual int `getLimit ()=0`
- virtual int `setLimit (int newLimit)=0`
- virtual int `changeLimit (int amount)=0`
- virtual int `getExcess ()=0`
- virtual int `setExcess (int newExcess)=0`
- virtual int `changeExcess (int amount)=0`
- virtual int `getValue ()=0`
- virtual `CounterTicket reserve (int amount=1, Glib::TimeVal duration=ETERNAL, bool prioritized=false, Glib::TimeVal timeOut=ETERNAL)=0`

Protected Types

- typedef unsigned long long int `IDType`

Protected Member Functions

- `Counter ()`
- virtual void `cancel (IDType reservationID)=0`
- virtual void `extend (IDType &reservationID, Glib::TimeVal &expiryTime, Glib::TimeVal duration=ETERNAL)=0`
- Glib::TimeVal `getCurrentTime ()`
- Glib::TimeVal `getExpiryTime (Glib::TimeVal duration)`
- `CounterTicket getCounterTicket (Counter::IDType reservationID, Glib::TimeVal expiryTime, Counter *counter)`
- `ExpirationReminder getExpirationReminder (Glib::TimeVal expTime, Counter::IDType resID)`

Friends

- class `CounterTicket`
- class `ExpirationReminder`

5.21.1 Detailed Description

A class defining a common interface for counters.

This class defines a common interface for counters as well as some common functionality.

The purpose of a counter is to provide housekeeping some resource such as e.g. disk space, memory or network bandwidth. The counter itself will not be aware of what kind of resource it limits the use of. Neither will it be aware of what unit is being used to measure that resource. Counters are thus very similar to semaphores. Furthermore, counters are designed to handle concurrent operations from multiple threads/processes in a consistent manner.

Every counter has a limit, an excess limit and a value. The limit is a number that specify how many units are available for reservation. The value is the number of units that are currently available for reservation, i.e. has not allready been reserved. The excess limit specify how many extra units can be reserved for high priority needs even if there are no normal units available for reservation. The excess limit is similar to the credit limit of e.g. a VISA card.

The users of the resource must thus first call the counter in order to make a reservation of an appropriate amount of the resource, then allocate and use the resource and finally call the counter again to cancel the reservation.

Typical usage is:

```
// Declare a counter. Replace XYZ by some appropriate kind of
// counter and provide required parameters. Unit is MB.
Arc::XYZCounter memory(...);
...
// Make a reservation of memory for 2000000 doubles.
Arc::CounterTicket tick = memory.reserve(2*sizeof(double));
// Use the memory.
double* A=new double[2000000];
doSomething(A);
delete[] A;
// Cancel the reservation.
tick.cancel();
```

There are also alternative ways to make reservations, including self-expiring reservations, prioritized reservations and reservations that fail if they cannot be made fast enough.

For self expiring reservations, a duration is provided in the reserve call:

```
tick = memory.reserve(2*sizeof(double), Glib::TimeVal(1,0));
```

A self-expiring reservation can be cancelled explicitly before it expires, but if it is not cancelled it will expire automatically when the duration has passed. The default value for the duration is [Arc::ETERNAL](#), which means that the reservation will not be cancelled automatically.

Prioritized reservations may use the excess limit and succeed immediately even if there are no normal units available for reservation. The value of the counter will in this case become negative. A prioritized reservation looks like this:

```
tick = memory.reserve(2*sizeof(double), Glib::TimeVal(1,0), true);
```

Finally, a time out option can be provided for a reservation. If some task should be performed within two seconds or not at all, the reservation can look like this:

```
tick = memory.reserve(2*sizeof(double), Glib::TimeVal(1,0),
                    true, Glib::TimeVal(2,0));
if (tick.isValid())
    doSomething(...);
```

5.21.2 Member Typedef Documentation

5.21.2.1 typedef unsigned long long int Arc::Counter::IDType [protected]

A typedef of identification numbers for reservation.

This is a type that is used as identification numbers (keys) for referencing of reservations. It is used internally in counters for book keeping of reservations as well as in the [CounterTicket](#) class in order to be able to cancel and extend reservations.

5.21.3 Constructor & Destructor Documentation

5.21.3.1 Arc::Counter::Counter () [protected]

Default constructor.

This is the default constructor. Since [Counter](#) is an abstract class, it should only be used by subclasses. Therefore it is protected. Furthermore, since the [Counter](#) class has no attributes, nothing needs to be initialized and thus this constructor is empty.

5.21.3.2 virtual Arc::Counter::~~Counter () [virtual]

The destructor.

This is the destructor of the [Counter](#) class. Since the [Counter](#) class has no attributes, nothing needs to be cleaned up and thus the destructor is empty.

5.21.4 Member Function Documentation

5.21.4.1 virtual void Arc::Counter::cancel (IDType reservationID) [protected, pure virtual]

Cancellation of a reservation.

This method cancels a reservation. It is called by the [CounterTicket](#) that corresponds to the reservation.

Parameters:

reservationID The identity number (key) of the reservation to cancel.

5.21.4.2 virtual int Arc::Counter::changeExcess (int amount) [pure virtual]

Changes the excess limit of the counter.

Changes the excess limit of the counter by adding a certain amount to the current excess limit.

Parameters:

amount The amount by which to change the excess limit.

Returns:

The new excess limit.

Implemented in [Arc::IntraProcessCounter](#).

5.21.4.3 `virtual int Arc::Counter::changeLimit (int amount)` [pure virtual]

Changes the limit of the counter.

Changes the limit of the counter by adding a certain amount to the current limit.

Parameters:

amount The amount by which to change the limit.

Returns:

The new limit.

Implemented in [Arc::IntraProcessCounter](#).

5.21.4.4 `virtual void Arc::Counter::extend (IDType & reservationID, Glib::TimeVal & expiryTime, Glib::TimeVal duration = ETERNAL)` [protected, pure virtual]

Extension of a reservation.

This method extends a reservation. It is called by the [CounterTicket](#) that corresponds to the reservation.

Parameters:

reservationID Used for input as well as output. Contains the identification number of the original reservation on entry and the new identification number of the extended reservation on exit.

expiryTime Used for input as well as output. Contains the expiry time of the original reservation on entry and the new expiry time of the extended reservation on exit.

duration The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

5.21.4.5 `CounterTicket Arc::Counter::getCounterTicket (Counter::IDType reservationID, Glib::TimeVal expiryTime, Counter * counter)` [protected]

A "relay method" for a constructor of the [CounterTicket](#) class.

This method acts as a relay for one of the constructors of the [CounterTicket](#) class. That constructor is private, but needs to be accessible from the subclasses of [Counter](#) (but not from anywhere else). In order not to have to declare every possible subclass of [Counter](#) as a friend of [CounterTicket](#), only the base class [Counter](#) is a friend and its subclasses access the constructor through this method. (If C++ had supported "package access", as Java does, this trick would not have been necessary.)

Parameters:

reservationID The identity number of the reservation corresponding to the [CounterTicket](#).

expiryTime the expiry time of the reservation corresponding to the [CounterTicket](#).

counter The [Counter](#) from which the reservation has been made.

Returns:

The counter ticket that has been created.

5.21.4.6 Glib::TimeVal Arc::Counter::getCurrentTime () [protected]

Get the current time.

Returns the current time. An "adapter method" for the assign_current_time() method in the Glib::TimeVal class. return The current time.

5.21.4.7 virtual int Arc::Counter::getExcess () [pure virtual]

Returns the excess limit of the counter.

Returns the excess limit of the counter, i.e. by how much the usual limit may be exceeded by prioritized reservations.

Returns:

The excess limit.

Implemented in [Arc::IntraProcessCounter](#).

5.21.4.8 ExpirationReminder Arc::Counter::getExpirationReminder (Glib::TimeVal *expTime*, Counter::IDType *resID*) [protected]

A "relay method" for the constructor of [ExpirationReminder](#).

This method acts as a relay for one of the constructors of the [ExpirationReminder](#) class. That constructor is private, but needs to be accessible from the subclasses of [Counter](#) (but not from anywhere else). In order not to have to declare every possible subclass of [Counter](#) as a friend of [ExpirationReminder](#), only the base class [Counter](#) is a friend and its subclasses access the constructor through this method. (If C++ had supported "package access", as Java does, this trick would not have been necessary.)

Parameters:

expTime the expiry time of the reservation corresponding to the [ExpirationReminder](#).

resID The identity number of the reservation corresponding to the [ExpirationReminder](#).

Returns:

The [ExpirationReminder](#) that has been created.

5.21.4.9 Glib::TimeVal Arc::Counter::getExpiryTime (Glib::TimeVal *duration*) [protected]

Computes an expiry time.

This method computes an expiry time by adding a duration to the current time.

Parameters:

duration The duration.

Returns:

The expiry time.

5.21.4.10 virtual int Arc::Counter::getLimit () [pure virtual]

Returns the current limit of the counter.

This method returns the current limit of the counter, i.e. how many units can be reserved simultaneously by different threads without claiming high priority.

Returns:

The current limit of the counter.

Implemented in [Arc::IntraProcessCounter](#).

5.21.4.11 virtual int Arc::Counter::getValue () [pure virtual]

Returns the current value of the counter.

Returns the current value of the counter, i.e. the number of unreserved units. Initially, the value is equal to the limit of the counter. When a reservation is made, the value is decreased. Normally, the value should never be negative, but this may happen if there are prioritized reservations. It can also happen if the limit is decreased after some reservations have been made, since reservations are never revoked.

Returns:

The current value of the counter.

Implemented in [Arc::IntraProcessCounter](#).

5.21.4.12 virtual CounterTicket Arc::Counter::reserve (int amount = 1, Glib::TimeVal duration = ETERNAL, bool prioritized = false, Glib::TimeVal timeOut = ETERNAL) [pure virtual]

Makes a reservation from the counter.

This method makes a reservation from the counter. If the current value of the counter is too low to allow for the reservation, the method blocks until the reservation is possible or times out.

Parameters:

amount The amount to reserve, default value is 1.

duration The duration of a self expiring reservation, default is that it lasts forever.

prioritized Whether this reservation is prioritized and thus allowed to use the excess limit.

timeOut The maximum time to block if the value of the counter is too low, default is to allow "eternal" blocking.

Returns:

A [CounterTicket](#) that can be queried about the status of the reservation as well as for cancellations and extensions.

Implemented in [Arc::IntraProcessCounter](#).

5.21.4.13 virtual int Arc::Counter::setExcess (int newExcess) [pure virtual]

Sets the excess limit of the counter.

This method sets a new excess limit for the counter.

Parameters:

newExcess The new excess limit, an absolute number.

Returns:

The new excess limit.

Implemented in [Arc::IntraProcessCounter](#).

5.21.4.14 virtual int Arc::Counter::setLimit (int *newLimit*) [pure virtual]

Sets the limit of the counter.

This method sets a new limit for the counter.

Parameters:

newLimit The new limit, an absolute number.

Returns:

The new limit.

Implemented in [Arc::IntraProcessCounter](#).

5.21.5 Friends And Related Function Documentation**5.21.5.1 friend class [CounterTicket](#)** [friend]

The [CounterTicket](#) class needs to be a friend.

5.21.5.2 friend class [ExpirationReminder](#) [friend]

The [ExpirationReminder](#) class needs to be a friend.

The documentation for this class was generated from the following file:

- Counter.h

5.22 Arc::CounterTicket Class Reference

A class for "tickets" that correspond to counter reservations.

```
#include <Counter.h>
```

Public Member Functions

- [CounterTicket](#) ()
- bool [isValid](#) ()
- void [extend](#) (Glib::TimeVal duration)
- void [cancel](#) ()

Friends

- class [Counter](#)

5.22.1 Detailed Description

A class for "tickets" that correspond to counter reservations.

This is a class for reservation tickets. When a reservation is made from a [Counter](#), a [ReservationTicket](#) is returned. This ticket can then be queried about the validity of a reservation. It can also be used for cancelation and extension of reservations.

Typical usage is:

```
// Declare a counter. Replace XYZ by some appropriate kind of
// counter and provide required parameters. Unit is MB.
Arc::XYZCounter memory(...);
...
// Make a reservation of memory for 2000000 doubles.
Arc::CounterTicket tick = memory.reserve(2*sizeof(double));
// Use the memory.
double* A=new double[2000000];
doSomething(A);
delete[] A;
// Cancel the reservation.
tick.cancel();
```

5.22.2 Constructor & Destructor Documentation

5.22.2.1 Arc::CounterTicket::CounterTicket ()

The default constructor.

This is the default constructor. It creates a [CounterTicket](#) that is not valid. The ticket object that is created can later be assigned a ticket that is returned by the [reserve\(\)](#) method of a [Counter](#).

5.22.3 Member Function Documentation

5.22.3.1 void Arc::CounterTicket::cancel ()

Cancels a reservation.

This method is called to cancel a reservation. It may be called also for self-expiring reservations, which will then be cancelled before they were originally planned to expire.

5.22.3.2 void Arc::CounterTicket::extend (Glib::TimeVal *duration*)

Extends a reservation.

Extends a self-expiring reservation. In order to succeed the extension should be made before the previous reservation expires.

Parameters:

duration The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

5.22.3.3 bool Arc::CounterTicket::isValid ()

Returns the validity of a [CounterTicket](#).

This method checks whether a [CounterTicket](#) is valid. The ticket was probably returned earlier by the `reserve()` method of a [Counter](#) but the corresponding reservation may have expired.

Returns:

The validity of the ticket.

5.22.4 Friends And Related Function Documentation

5.22.4.1 friend class [Counter](#) [friend]

The [Counter](#) class needs to be a friend.

The documentation for this class was generated from the following file:


- Counter.h

5.23 Arc::CRC32Sum Class Reference

Implementation of CRC32 checksum.

```
#include <CheckSum.h>
```

Inheritance diagram for Arc::CRC32Sum::



Public Member Functions

- virtual void **start** (void)
- virtual void **add** (void *buf, unsigned long long int len)
- virtual void **end** (void)
- virtual void **result** (unsigned char *&res, unsigned int &len) const
- virtual int **print** (char *buf, int len) const
- virtual void **scan** (const char *buf)
- virtual **operator bool** (void) const
- virtual bool **operator!** (void) const
- uint32_t **crc** (void) const

5.23.1 Detailed Description

Implementation of CRC32 checksum.

The documentation for this class was generated from the following file:


- CheckSum.h

5.24 Arc::Database Class Reference

Interface for calling database client library.

```
#include <DBInterface.h>
```

Inheritance diagram for Arc::Database::



Public Member Functions

- [Database](#) ()
- [Database](#) (std::string &server, int port)
- [Database](#) (const [Database](#) &other)
- virtual [~Database](#) ()
- virtual bool [connect](#) (std::string &dbname, std::string &user, std::string &password)=0
- virtual bool [isconnected](#) () const =0
- virtual void [close](#) ()=0
- virtual bool [enable_ssl](#) (const std::string keyfile="", const std::string certfile="", const std::string cafile="", const std::string capath="")=0
- virtual bool [shutdown](#) ()=0

5.24.1 Detailed Description

Interface for calling database client library.

For different types of database client library, different classes should be implemented by implementing this interface.

5.24.2 Constructor & Destructor Documentation

5.24.2.1 Arc::Database::Database () [inline]

Default constructor

5.24.2.2 Arc::Database::Database (std::string & server, int port) [inline]

Constructor which uses the server's name(or IP address) and port as parametes

5.24.2.3 Arc::Database::Database (const [Database](#) & other) [inline]

Copy constructor

5.24.2.4 virtual Arc::Database::~~Database () [inline, virtual]

Deconstructor

5.24.3 Member Function Documentation

5.24.3.1 virtual void Arc::Database::close () [pure virtual]

Close the connection with database server

Implemented in [Arc::MySQLDatabase](#).

5.24.3.2 virtual bool Arc::Database::connect (std::string & *dbname*, std::string & *user*, std::string & *password*) [pure virtual]

Do connection with database server

Parameters:

dbname The database name which will be used.

user The username which will be used to access database.

password The password which will be used to access database.

Implemented in [Arc::MySQLDatabase](#).

5.24.3.3 virtual bool Arc::Database::enable_ssl (const std::string *keyfile* = "", const std::string *certfile* = "", const std::string *cafile* = "", const std::string *capath* = "") [pure virtual]

Enable ssl communication for the connection

Parameters:

keyfile The location of key file.

certfile The location of certificate file.

cafile The location of ca file.

capath The location of ca directory

Implemented in [Arc::MySQLDatabase](#).

5.24.3.4 virtual bool Arc::Database::isconnected () const [pure virtual]

Get the connection status

Implemented in [Arc::MySQLDatabase](#).

5.24.3.5 virtual bool Arc::Database::shutdown () [pure virtual]

Ask database server to shutdown

Implemented in [Arc::MySQLDatabase](#).

The documentation for this class was generated from the following file:

- DBInterface.h

5.25 Arc::DataBufferPar Class Reference

Represents set of buffers.

```
#include <DataBufferPar.h>
```

Public Member Functions

- [operator bool](#) ()
- [DataBufferPar](#) (unsigned int size=65536, int blocks=3)
- [DataBufferPar](#) ([Checksum](#) *cksum, unsigned int size=65536, int blocks=3)
- [~DataBufferPar](#) ()
- [bool set](#) ([Checksum](#) *cksum=NULL, unsigned int size=65536, int blocks=3)
- [char * operator\[\]](#) (int n)
- [bool for_read](#) (int &handle, unsigned int &length, bool wait)
- [bool for_read](#) ()
- [bool is_read](#) (int handle, unsigned int length, unsigned long long int offset)
- [bool is_read](#) (char *buf, unsigned int length, unsigned long long int offset)
- [bool for_write](#) (int &handle, unsigned int &length, unsigned long long int &offset, bool wait)
- [bool for_write](#) ()
- [bool is_written](#) (int handle)
- [bool is_written](#) (char *buf)
- [bool is_notwritten](#) (int handle)
- [bool is_notwritten](#) (char *buf)
- [void eof_read](#) (bool v)
- [void eof_write](#) (bool v)
- [void error_read](#) (bool v)
- [void error_write](#) (bool v)
- [bool eof_read](#) ()
- [bool eof_write](#) ()
- [bool error_read](#) ()
- [bool error_write](#) ()
- [bool error_transfer](#) ()
- [bool error](#) ()
- [bool wait](#) ()
- [bool wait_used](#) ()
- [bool checksum_valid](#) ()
- [const CheckSum * checksum_object](#) ()
- [bool wait_eof_read](#) ()
- [bool wait_read](#) ()
- [bool wait_eof_write](#) ()
- [bool wait_write](#) ()
- [bool wait_eof](#) ()
- [unsigned long long int eof_position](#) () const
- [unsigned int buffer_size](#) ()

Public Attributes

- [DataSpeed speed](#)

Classes

- struct `buf_desc`

5.25.1 Detailed Description

Represents set of buffers.

This class is used during data transfer using [DataPoint](#) classes.

5.25.2 Constructor & Destructor Documentation

5.25.2.1 `Arc::DataBufferPar::DataBufferPar (unsigned int size = 65536, int blocks = 3)`

Constructor

Parameters:

size size of every buffer in bytes.

blocks number of buffers.

5.25.2.2 `Arc::DataBufferPar::DataBufferPar (Checksum * cksum, unsigned int size = 65536, int blocks = 3)`

Constructor

Parameters:

size size of every buffer in bytes.

blocks number of buffers.

cksum object which will compute checksum. Should not be destroyed till [DataBufferPar](#) itself.

5.25.2.3 `Arc::DataBufferPar::~~DataBufferPar ()`

Destructor.

5.25.3 Member Function Documentation

5.25.3.1 `unsigned int Arc::DataBufferPar::buffer_size ()`

Returns size of buffer in object. If not initialized then this number represents size of default buffer.

5.25.3.2 `const Checksum* Arc::DataBufferPar::checksum_object ()`

Returns [Checksum](#) object specified in constructor.

5.25.3.3 `bool Arc::DataBufferPar::checksum_valid ()`

Returns true if checksum was successfully computed.

5.25.3.4 unsigned long long int Arc::DataBufferPar::eof_position () const [inline]

Returns offset following last piece of data transfered.

5.25.3.5 bool Arc::DataBufferPar::eof_read ()

Returns true if object was informed about end of transfer on 'read' side.

5.25.3.6 void Arc::DataBufferPar::eof_read (bool v)

Informs object if there will be no more request for 'read' buffers. v true if no more requests.

5.25.3.7 bool Arc::DataBufferPar::eof_write ()

Returns true if object was informed about end of transfer on 'write' side.

5.25.3.8 void Arc::DataBufferPar::eof_write (bool v)

Informs object if there will be no more request for 'write' buffers. v true if no more requests.

5.25.3.9 bool Arc::DataBufferPar::error ()

Returns true if object was informed about error or internal error occurred.

5.25.3.10 bool Arc::DataBufferPar::error_read ()

Returns true if object was informed about error on 'read' side.

5.25.3.11 void Arc::DataBufferPar::error_read (bool v)

Informs object if error occurred on 'read' side.

Parameters:

v true if error.

5.25.3.12 bool Arc::DataBufferPar::error_transfer ()

Returns true if error occurred inside object.

5.25.3.13 bool Arc::DataBufferPar::error_write ()

Returns true if object was informed about error on 'write' side.

5.25.3.14 void Arc::DataBufferPar::error_write (bool *v*)

Informs object if error accured on 'write' side.

Parameters:

v true if error.

5.25.3.15 bool Arc::DataBufferPar::for_read ()

Check if there are buffers which can be taken by [for_read\(\)](#). This function checks only for buffers and does not take eof and error conditions into account.

5.25.3.16 bool Arc::DataBufferPar::for_read (int & *handle*, unsigned int & *length*, bool *wait*)

Request buffer for READING INTO it.

Parameters:

handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one.

Returns:

true on success

5.25.3.17 bool Arc::DataBufferPar::for_write ()

Check if there are buffers which can be taken by [for_write\(\)](#). This function checks only for buffers and does not take eof and error conditions into account.

5.25.3.18 bool Arc::DataBufferPar::for_write (int & *handle*, unsigned int & *length*, unsigned long long int & *offset*, bool *wait*)

Request buffer for WRITING FROM it.

Parameters:

handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one.

5.25.3.19 bool Arc::DataBufferPar::is_notwritten (char * *buf*)

Informs object that data was NOT written from buffer (and releases buffer).

Parameters:

buf - address of buffer

5.25.3.20 bool Arc::DataBufferPar::is_notwritten (int *handle*)

Informs object that data was NOT written from buffer (and releases buffer).

Parameters:

handle buffer's number.

5.25.3.21 bool Arc::DataBufferPar::is_read (char * *buf*, unsigned int *length*, unsigned long long int *offset*)

Informs object that data was read into buffer.

Parameters:

buf - address of buffer

length amount of data.

offset offset in stream, file, etc.

5.25.3.22 bool Arc::DataBufferPar::is_read (int *handle*, unsigned int *length*, unsigned long long int *offset*)

Informs object that data was read into buffer.

Parameters:

handle buffer's number.

length amount of data.

offset offset in stream, file, etc.

5.25.3.23 bool Arc::DataBufferPar::is_written (char * *buf*)

Informs object that data was written from buffer.

Parameters:

buf - address of buffer

5.25.3.24 bool Arc::DataBufferPar::is_written (int *handle*)

Informs object that data was written from buffer.

Parameters:

handle buffer's number.

5.25.3.25 Arc::DataBufferPar::operator bool (void) [inline]

Check if [DataBufferPar](#) object is initialized.

5.25.3.26 `]`

`char* Arc::DataBufferPar::operator[] (int n)`

Direct access to buffer by number.

5.25.3.27 `bool Arc::DataBufferPar::set (Checksum * cksum = NULL, unsigned int size = 65536, int blocks = 3)`

Reinitialize buffers with different parameters.

Parameters:

size size of every buffer in bytes.

blocks number of buffers.

cksum object which will compute checksum. Should not be destroyed till [DataBufferPar](#) itself.

5.25.3.28 `bool Arc::DataBufferPar::wait ()`

Wait (max 60 sec.) till any action happens in object. Returns true if action is eof on any side.

5.25.3.29 `bool Arc::DataBufferPar::wait_eof ()`

Wait till end of transfer happens on any side.

5.25.3.30 `bool Arc::DataBufferPar::wait_eof_read ()`

Wait till end of transfer happens on 'read' side.

5.25.3.31 `bool Arc::DataBufferPar::wait_eof_write ()`

Wait till end of transfer happens on 'write' side.

5.25.3.32 `bool Arc::DataBufferPar::wait_read ()`

Wait till end of transfer or error happens on 'read' side.

5.25.3.33 `bool Arc::DataBufferPar::wait_used ()`

Wait till there are no more used buffers left in object.

5.25.3.34 `bool Arc::DataBufferPar::wait_write ()`

Wait till end of transfer or error happens on 'write' side.

5.25.4 Member Data Documentation

5.25.4.1 [DataSpeed Arc::DataBufferPar::speed](#)

This object controls transfer speed.


The documentation for this class was generated from the following file:

- DataBufferPar.h

5.26 Arc::DataCache Class Reference

```
#include <DataCache.h>
```

Inheritance diagram for Arc::DataCache::



Public Types

- `file_no_error = 0`
- `file_download_failed = 1`
- `file_not_valid = 2`
- `file_keep = 4`
- enum `file_state_t` { `file_no_error = 0`, `file_download_failed = 1`, `file_not_valid = 2`, `file_keep = 4` }

Public Member Functions

- `DataCache ()`
- `DataCache` (const std::string &cache_path, const std::string &cache_data_path, const std::string &cache_link_path, const std::string &id, const User &cache_user)
- `DataCache` (const `DataCache` &cache)
- virtual `~DataCache ()`
- bool `start` (const `URL` &base_url, bool &available)
- const std::string & `file` () const
- bool `stop` (int file_state=file_no_error)
- bool `link` (const std::string &link_path)
- bool `link` (const std::string &link_path, const User &user)
- bool `copy` (const std::string &link_path)
- bool `copy` (const std::string &link_path, const User &user)
- bool `clean` (unsigned long long int size=1)
- virtual bool `cb` (unsigned long long int size)
- `operator bool` ()
- bool `CheckCreated` ()
- void `SetCreated` (`Time` val)
- `Time` `GetCreated` ()
- bool `CheckValid` ()
- void `SetValid` (`Time` val)
- `Time` `GetValid` ()

5.26.1 Detailed Description

High level interface to cache operations (same functionality :)) and additional functionality to integrate into grid-manager environment.

5.26.2 Constructor & Destructor Documentation

5.26.2.1 Arc::DataCache::DataCache ()

Default constructor (non-functional cache).

5.26.2.2 Arc::DataCache::DataCache (const std::string & *cache_path*, const std::string & *cache_data_path*, const std::string & *cache_link_path*, const std::string & *id*, const User & *cache_user*)

Constructor

Parameters:

cache_path path to directory with cache info files

cache_data_path path to directory with cache data files

cache_link_path path used to create link in case *cache_directory* is visible under different name during actual usage

id identifier used to claim files in cache

cache_user owner of cahce (0 for public cache)

5.26.2.3 Arc::DataCache::DataCache (const [DataCache](#) & *cache*)

Copy constructor.

5.26.2.4 virtual Arc::DataCache::~~DataCache () [virtual]

and destructor

5.26.3 Member Function Documentation

5.26.3.1 virtual bool Arc::DataCache::cb (unsigned long long int *size*) [virtual]

Callback implementation to clean at least 1 byte.

Reimplemented from [Arc::DataCallback](#).

5.26.3.2 bool Arc::DataCache::CheckCreated () [inline]

Check if there is an information about creation time.

5.26.3.3 bool Arc::DataCache::CheckValid () [inline]

Check if there is an information about invalidation time.

5.26.3.4 `bool Arc::DataCache::clean (unsigned long long int size = 1)`

Remove some amount of oldest information from cache. Returns true on success.

Parameters:

size amount to be removed (bytes)

5.26.3.5 `bool Arc::DataCache::copy (const std::string & link_path)`

Do same as [link\(\)](#) but always create copy.

5.26.3.6 `const std::string& Arc::DataCache::file () const` `[inline]`

Returns path to file which contains/will contain content of assigned url.

5.26.3.7 `Time Arc::DataCache::GetCreated ()` `[inline]`

Get creation time.

5.26.3.8 `Time Arc::DataCache::GetValid ()` `[inline]`

Get invalidation time.

5.26.3.9 `bool Arc::DataCache::link (const std::string & link_path, const User & user)`**Parameters:**

user set owner of soft-link

5.26.3.10 `bool Arc::DataCache::link (const std::string & link_path)`

Must be called to create soft-link to cache file or to copy it. It's behavior depends on configuration. All necessary directories will be created. Returns false on error (usually that means soft-link already exists).

Parameters:

link_path path for soft-link or new file.

5.26.3.11 `Arc::DataCache::operator bool (void)` `[inline]`

Returns true if object is useable.

5.26.3.12 `void Arc::DataCache::SetCreated (Time val)` `[inline]`

Set creation time.

Parameters:

val creation time

5.26.3.13 void Arc::DataCache::SetValid (Time *val*) [inline]

Set invalidation time.

Parameters:

val validity time

5.26.3.14 bool Arc::DataCache::start (const URL & *base_url*, bool & *available*)

Prepare cache for downloading file. On success returns true. This function can block for long time if there is another process downloading same url.

Parameters:

base_url url to assign to file in cache (file's identifier)

available contains true on exit if file is already in cache

5.26.3.15 bool Arc::DataCache::stop (int *file_state* = file_no_error)

This method must be called after file was downloaded or download failed.

Parameters:

failure true if download failed


The documentation for this class was generated from the following file:

- DataCache.h

5.27 Arc::DataCallback Class Reference

```
#include <DataCallback.h>
```

Inheritance diagram for Arc::DataCallback::



Public Member Functions

- virtual bool **cb** (int)
- virtual bool **cb** (unsigned int)
- virtual bool **cb** (long long int)
- virtual bool **cb** (unsigned long long int)

5.27.1 Detailed Description

This class is used by [DataHandle](#) to report missing space on local filesystem. One of 'cb' functions here will be called if operation initiated by DataHandle::start_reading runs out of disk space.

The documentation for this class was generated from the following file:

- DataCallback.h

5.28 Arc::DataHandle Class Reference

This class is a wrapper around the [DataPoint](#) class.

```
#include <DataHandle.h>
```

Public Member Functions

- **DataHandle** (const [URL](#) &url)
- **DataHandle** & **operator=** (const [URL](#) &url)
- void **Clear** ()
- **DataPoint** * **operator** → ()
- const **DataPoint** * **operator** → () const
- **DataPoint** & **operator** * ()
- const **DataPoint** & **operator** * () const
- bool **operator!** () const
- **operator bool** () const

5.28.1 Detailed Description

This class is a wrapper around the [DataPoint](#) class.

It simplifies the construction, use and destruction of [DataPoint](#) objects.

The documentation for this class was generated from the following file:

- DataHandle.h

5.29 Arc::DataMover Class Reference

```
#include <DataMover.h>
```

Public Types

- typedef void(*) **callback** ([DataMover](#) *, [DataStatus](#), const std::string &, void *)

Public Member Functions

- [DataMover](#) ()
- [~DataMover](#) ()
- [DataStatus](#) [Transfer](#) ([DataPoint](#) &source, [DataPoint](#) &destination, [DataCache](#) &cache, const [URLMap](#) &map, std::string &failure_description, callback cb=NULL, void *arg=NULL, const char *prefix=NULL)
- [DataStatus](#) [Transfer](#) ([DataPoint](#) &source, [DataPoint](#) &destination, [DataCache](#) &cache, const [URLMap](#) &map, unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, std::string &failure_description, callback cb=NULL, void *arg=NULL, const char *prefix=NULL)
- [DataStatus](#) [Delete](#) ([DataPoint](#) &url, bool errcont=false)
- bool [verbose](#) ()
- void [verbose](#) (bool)
- void [verbose](#) (const std::string &prefix)
- bool [retry](#) ()
- void [retry](#) (bool)
- void [secure](#) (bool)
- void [passive](#) (bool)
- void [force_to_meta](#) (bool)
- bool [checks](#) ()
- void [checks](#) (bool v)
- void [set_default_min_speed](#) (unsigned long long int min_speed, time_t min_speed_time)
- void [set_default_min_average_speed](#) (unsigned long long int min_average_speed)
- void [set_default_max_inactivity_time](#) (time_t max_inactivity_time)
- void [set_progress_indicator](#) ([DataSpeed](#)::show_progress_t func=NULL)

5.29.1 Detailed Description

A purpose of this class is to provide an interface that moves data between two locations specified by URLs. It's main action is represented by methods [DataMover::Transfer](#). Instance represents only attributes used during transfer.

5.29.2 Constructor & Destructor Documentation

5.29.2.1 Arc::DataMover::DataMover ()

Constructor.

5.29.2.2 Arc::DataMover::~~DataMover ()

Destructor.

5.29.3 Member Function Documentation

5.29.3.1 void Arc::DataMover::checks (bool *v*)

Set if to make check for existence of remote file (and probably other checks too) before initiating 'reading' and 'writing' operations.

Parameters:

v true if allowed (default is true).

5.29.3.2 bool Arc::DataMover::checks ()

Check if check for existence of remote file is done before initiating 'reading' and 'writing' operations.

5.29.3.3 void Arc::DataMover::force_to_meta (bool)

Set if file should be transfered and registered even if such LFN is already registered and source is not one of registered locations.

5.29.3.4 void Arc::DataMover::passive (bool)

Set if passive transfer should be used for FTP-like transfers.

5.29.3.5 void Arc::DataMover::retry (bool)

Set if transfer will be retried in case of failure.

5.29.3.6 bool Arc::DataMover::retry ()

Check if transfer will be retried in case of failure.

5.29.3.7 void Arc::DataMover::secure (bool)

Set if high level of security (encryption) will be used during transfer if available.

5.29.3.8 void Arc::DataMover::set_default_max_inactivity_time (time_t *max_inactivity_time*) [inline]

Set maximal allowed time for waiting for any data. For more information see description of [DataSpeed](#) class.

5.29.3.9 void Arc::DataMover::set_default_min_average_speed (unsigned long long int *min_average_speed*) [inline]

Set minimal allowed average transfer speed (default is 0 averaged over whole time of transfer. For more information see description of [DataSpeed](#) class.

5.29.3.10 void Arc::DataMover::set_default_min_speed (unsigned long long int *min_speed*, time_t *min_speed_time*) [inline]

Set minimal allowed transfer speed (default is 0) to 'min_speed'. If speed drops below for time longer than 'min_speed_time' error is raised. For more information see description of [DataSpeed](#) class.

5.29.3.11 DataStatus Arc::DataMover::Transfer ([DataPoint](#) & *source*, [DataPoint](#) & *destination*, [DataCache](#) & *cache*, const URLMap & *map*, unsigned long long int *min_speed*, time_t *min_speed_time*, unsigned long long int *min_average_speed*, time_t *max_inactivity_time*, std::string & *failure_description*, callback *cb* = NULL, void * *arg* = NULL, const char * *prefix* = NULL)

Initiates transfer from 'source' to 'destination'.

Parameters:

min_speed minimal allowed current speed.

min_speed_time time for which speed should be less than 'min_speed' before transfer fails.

min_average_speed minimal allowed average speed.

max_inactivity_time time for which should be no activity before transfer fails.

5.29.3.12 DataStatus Arc::DataMover::Transfer ([DataPoint](#) & *source*, [DataPoint](#) & *destination*, [DataCache](#) & *cache*, const URLMap & *map*, std::string & *failure_description*, callback *cb* = NULL, void * *arg* = NULL, const char * *prefix* = NULL)

Initiates transfer from 'source' to 'destination'.

Parameters:

source source [URL](#).

destination destination [URL](#).

cache controls caching of downloaded files (if destination url is "file:///"). If caching is not needed default constructor DataCache() can be used.

map [URL](#) mapping/conversion table (for 'source' [URL](#)).

cb if not NULL, transfer is done in separate thread and 'cb' is called after transfer completes/fails.

arg passed to 'cb'.

prefix if 'verbose' is activated this information will be printed before each line representing current transfer status.

5.29.3.13 void Arc::DataMover::verbose (const std::string & *prefix*)

Activate printing information about transfer status.

Parameters:

prefix use this string if 'prefix' in [DataMover::Transfer](#) is NULL.

5.29.3.14 void Arc::DataMover::verbose (bool)

Activate printing information about transfer status.

5.29.3.15 bool Arc::DataMover::verbose ()

Check if printing information about transfer status is activated.

The documentation for this class was generated from the following file:


- DataMover.h

5.30 Arc::DataPoint Class Reference

This base class is an abstraction of [URL](#).

```
#include <DataPoint.h>
```

Inheritance diagram for Arc::DataPoint::



Public Member Functions

- [DataPoint](#) (const [URL](#) &url)
- virtual [~DataPoint](#) ()
- virtual const [URL](#) & [GetURL](#) () const
- virtual std::string [str](#) () const
- virtual [operator bool](#) () const
- virtual bool [operator!](#) () const
- virtual [DataStatus](#) [StartReading](#) ([DataBufferPar](#) &buffer)=0
- virtual [DataStatus](#) [StartWriting](#) ([DataBufferPar](#) &buffer, [DataCallback](#) *space_cb=NULL)=0
- virtual [DataStatus](#) [StopReading](#) ()=0
- virtual [DataStatus](#) [StopWriting](#) ()=0
- virtual [DataStatus](#) [Check](#) ()=0
- virtual [DataStatus](#) [Remove](#) ()=0
- virtual [DataStatus](#) [ListFiles](#) (std::list< [FileInfo](#) > &files, bool resolve=true)=0
- virtual void [ReadOutOfOrder](#) (bool v)=0
- virtual bool [WriteOutOfOrder](#) ()=0
- virtual void [SetAdditionalChecks](#) (bool v)=0
- virtual bool [GetAdditionalChecks](#) () const =0
- virtual void [SetSecure](#) (bool v)=0
- virtual bool [GetSecure](#) () const =0
- virtual void [Passive](#) (bool v)=0
- virtual void [Range](#) (unsigned long long int start=0, unsigned long long int end=0)=0
- virtual [DataStatus](#) [Resolve](#) (bool source)=0
- virtual bool [Registered](#) () const =0
- virtual [DataStatus](#) [PreRegister](#) (bool replication, bool force=false)=0
- virtual [DataStatus](#) [PostRegister](#) (bool replication)=0
- virtual [DataStatus](#) [PreUnregister](#) (bool replication)=0
- virtual [DataStatus](#) [Unregister](#) (bool all)=0
- virtual bool [CheckSize](#) () const
- virtual void [SetSize](#) (const unsigned long long int val)
- virtual unsigned long long int [GetSize](#) () const
- virtual bool [CheckChecksum](#) () const
- virtual void [SetChecksum](#) (const std::string &val)
- virtual const std::string & [GetChecksum](#) () const
- virtual bool [CheckCreated](#) () const

- virtual void [SetCreated](#) (const [Time](#) &val)
- virtual const [Time](#) & [GetCreated](#) () const
- virtual bool [CheckValid](#) () const
- virtual void [SetValid](#) (const [Time](#) &val)
- virtual const [Time](#) & [GetValid](#) () const
- virtual unsigned long long int [BufSize](#) () const =0
- virtual int [BufNum](#) () const =0
- virtual bool [Cache](#) () const =0
- virtual bool [Local](#) () const =0
- virtual bool [ReadOnly](#) () const =0
- virtual int [GetTries](#) () const
- virtual void [SetTries](#) (const int n)
- virtual bool [IsIndex](#) () const =0
- virtual bool [AcceptsMeta](#) ()=0
- virtual bool [ProvidesMeta](#) ()=0
- virtual void [SetMeta](#) (const [DataPoint](#) &p)
- virtual bool [CompareMeta](#) (const [DataPoint](#) &p) const
- virtual const [URL](#) & [CurrentLocation](#) () const =0
- virtual const std::string & [CurrentLocationMetadata](#) () const =0
- virtual bool [NextLocation](#) ()=0
- virtual bool [LocationValid](#) () const =0
- virtual bool [HaveLocations](#) () const =0
- virtual DataStatus [AddLocation](#) (const [URL](#) &url, const std::string &meta)=0
- virtual DataStatus [RemoveLocation](#) ()=0
- virtual DataStatus [RemoveLocations](#) (const [DataPoint](#) &p)=0

Protected Attributes

- [URL](#) **url**
- unsigned long long int **size**
- std::string **checksum**
- [Time](#) **created**
- [Time](#) **valid**
- int **triesleft**

Static Protected Attributes

- static [Logger](#) **logger**

5.30.1 Detailed Description

This base class is an abstraction of [URL](#).

Specializations should be provided for different kind of direct access URLs (file://, ftp://, gsiftp://, http://, https://, httpg://, ...) or indexing service URLs (rls://, lfc://, ...). [DataPoint](#) provides means to resolve an indexing service [URL](#) into multiple URLs and to loop through them.

5.30.2 Constructor & Destructor Documentation

5.30.2.1 `Arc::DataPoint::DataPoint (const URL & url)`

Constructor requires [URL](#) to be provided.

5.30.2.2 `virtual Arc::DataPoint::~~DataPoint ()` [virtual]

Destructor.

5.30.3 Member Function Documentation

5.30.3.1 `virtual bool Arc::DataPoint::AcceptsMeta ()` [pure virtual]

If endpoint can have any use from meta information.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.2 `virtual DataStatus Arc::DataPoint::AddLocation (const URL & url, const std::string & meta)` [pure virtual]

Add [URL](#) to list.

Parameters:

url Location [URL](#) to add.

meta Location meta information.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.3 `virtual int Arc::DataPoint::BufNum () const` [pure virtual]

Get suggested number of buffers for transfers.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.4 `virtual unsigned long long int Arc::DataPoint::BufSize () const` [pure virtual]

Get suggested buffer size for transfers.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.5 `virtual bool Arc::DataPoint::Cache () const` [pure virtual]

Returns true if file is cacheable.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.6 virtual DataStatus Arc::DataPoint::Check () [pure virtual]

Query the [DataPoint](#) to check if object is accessible.

If possible this method will also try to provide meta information about the object.

Implemented in [Arc::DataPointIndex](#).

5.30.3.7 virtual bool Arc::DataPoint::CheckChecksum () const [virtual]

Check if meta-information 'checksum' is available.

5.30.3.8 virtual bool Arc::DataPoint::CheckCreated () const [virtual]

Check if meta-information 'creation/modification time' is available.

5.30.3.9 virtual bool Arc::DataPoint::CheckSize () const [virtual]

Check if meta-information 'size' is available.

5.30.3.10 virtual bool Arc::DataPoint::CheckValid () const [virtual]

Check if meta-information 'validity time' is available.

5.30.3.11 virtual bool Arc::DataPoint::CompareMeta (const [DataPoint](#) & *p*) const [virtual]

Compare meta information from another object.

Undefined values are not used for comparison.

Parameters:

p object to which to compare.

5.30.3.12 virtual const [URL](#)& Arc::DataPoint::CurrentLocation () const [pure virtual]

Returns current (resolved) [URL](#).

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.13 virtual const std::string& Arc::DataPoint::CurrentLocationMetadata () const [pure virtual]

Returns meta information used to create current [URL](#).

Usage differs between different indexing services.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.14 `virtual bool Arc::DataPoint::GetAdditionalChecks () const` [pure virtual]

Check if additional checks before will be performed.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.15 `virtual const std::string& Arc::DataPoint::GetChecksum () const` [virtual]

Get value of meta-information 'checksum'.

5.30.3.16 `virtual const Time& Arc::DataPoint::GetCreated () const` [virtual]

Get value of meta-information 'creation/modification time'.

5.30.3.17 `virtual bool Arc::DataPoint::GetSecure () const` [pure virtual]

Check if heavy security during data transfer is allowed.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.18 `virtual unsigned long long int Arc::DataPoint::GetSize () const` [virtual]

Get value of meta-information 'size'.

5.30.3.19 `virtual int Arc::DataPoint::GetTries () const` [virtual]

Returns number of retries left.

5.30.3.20 `virtual const URL& Arc::DataPoint::GetURL () const` [virtual]

Returns the [URL](#) that was passed to the constructor.

5.30.3.21 `virtual const Time& Arc::DataPoint::GetValid () const` [virtual]

Get value of meta-information 'validity time'.

5.30.3.22 `virtual bool Arc::DataPoint::HaveLocations () const` [pure virtual]

Returns true if number of resolved URLs is not 0.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.23 `virtual bool Arc::DataPoint::IsIndex () const` [pure virtual]

Check if [URL](#) is an Indexing [Service](#).

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.24 `virtual DataStatus Arc::DataPoint::ListFiles (std::list< FileInfo > &files, bool resolve = true) [pure virtual]`

List file(s).

If the [DataPoint](#) represents a directory its contents will be listed.

Parameters:

files will contain list of file names and optionally their attributes.

resolve if false, do not try to obtain properties of objects.

5.30.3.25 `virtual bool Arc::DataPoint::Local () const [pure virtual]`

Returns true if file is local, e.g. file:// urls.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.26 `virtual bool Arc::DataPoint::LocationValid () const [pure virtual]`

Returns false if out of retries.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.27 `virtual bool Arc::DataPoint::NextLocation () [pure virtual]`

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.28 `virtual Arc::DataPoint::operator bool () const [virtual]`

Is [DataPoint](#) valid?

5.30.3.29 `virtual bool Arc::DataPoint::operator! () const [virtual]`

Is [DataPoint](#) valid?

5.30.3.30 `virtual void Arc::DataPoint::Passive (bool v) [pure virtual]`

Request passive transfers for FTP-like protocols.

Parameters:

true to request.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.31 virtual DataStatus Arc::DataPoint::PostRegister (bool *replication*) [pure virtual]

Index [Service](#) postregistration.

Used for same purpose as meta_preregister. Should be called after actual transfer of file successfully finished.

Parameters:

replication if true, the file is being replicated between two locations registered in Indexing [Service](#) under same name.

Implemented in [Arc::DataPointDirect](#).

5.30.3.32 virtual DataStatus Arc::DataPoint::PreRegister (bool *replication*, bool *force* = false) [pure virtual]

Index service preregistration.

This function registers the physical location of a file into an indexing service. It should be called **before** the actual transfer to that location happens.

Parameters:

replication if true, the file is being replicated between two locations registered in the indexing service under same name.

force if true, perform registration of a new file even if it already exists. Should be used to fix failures in Indexing [Service](#).

Implemented in [Arc::DataPointDirect](#).

5.30.3.33 virtual DataStatus Arc::DataPoint::PreUnregister (bool *replication*) [pure virtual]

Index [Service](#) preunregistration.

Should be called if file transfer failed. It removes changes made by PreRegister.

Parameters:

replication if true, the file is being replicated between two locations registered in Indexing [Service](#) under same name.

Implemented in [Arc::DataPointDirect](#).

5.30.3.34 virtual bool Arc::DataPoint::ProvidesMeta () [pure virtual]

If endpoint can provide at least some meta information directly.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.35 virtual void Arc::DataPoint::Range (unsigned long long int *start* = 0, unsigned long long int *end* = 0) [pure virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.36 virtual void Arc::DataPoint::ReadOutOfOrder (bool *v*) [pure virtual]

Parameters:

v true if allowed (default is false).

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.37 virtual bool Arc::DataPoint::Registered () const [pure virtual]

Check if file is registered in Indexing [Service](#).

Proper value is obtainable only after Resolve.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.38 virtual DataStatus Arc::DataPoint::Remove () [pure virtual]

Remove/delete object at [URL](#).

Implemented in [Arc::DataPointIndex](#).

5.30.3.39 virtual DataStatus Arc::DataPoint::RemoveLocation () [pure virtual]

Remove current [URL](#) from list.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.40 virtual DataStatus Arc::DataPoint::RemoveLocations (const [DataPoint](#) & *p*) [pure virtual]

Remove locations present in another [DataPoint](#) object.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.41 virtual DataStatus Arc::DataPoint::Resolve (bool *source*) [pure virtual]

Resolves index service [URL](#) into list of ordinary URLs.

Also obtains meta information about the file.

Parameters:

source true if [DataPoint](#) object represents source of information.

Implemented in [Arc::DataPointDirect](#).

5.30.3.42 virtual void Arc::DataPoint::SetAdditionalChecks (bool *v*) [pure virtual]

Allow/disallow additional checks.

Check for existence of remote file (and probably other checks too) before initiating reading and writing operations.

Parameters:

v true if allowed (default is true).

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.43 virtual void Arc::DataPoint::SetChecksum (const std::string & *val*) [virtual]

Set value of meta-information 'checksum'.

5.30.3.44 virtual void Arc::DataPoint::SetCreated (const Time & *val*) [virtual]

Set value of meta-information 'creation/modification time'.

5.30.3.45 virtual void Arc::DataPoint::SetMeta (const DataPoint & *p*) [virtual]

Copy meta information from another object.

Already defined values are not overwritten.

Parameters:

p object from which information is taken.

5.30.3.46 virtual void Arc::DataPoint::SetSecure (bool *v*) [pure virtual]

Allow/disallow heavy security during data transfer.

Parameters:

v true if allowed (default depends on protocol).

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

5.30.3.47 virtual void Arc::DataPoint::SetSize (const unsigned long long int *val*) [virtual]

Set value of meta-information 'size'.

5.30.3.48 virtual void Arc::DataPoint::SetTries (const int *n*) [virtual]

Set number of retries.

Reimplemented in [Arc::DataPointIndex](#).

5.30.3.49 virtual void Arc::DataPoint::SetValid (const Time & val) [virtual]

Set value of meta-information 'validity time'.

5.30.3.50 virtual DataStatus Arc::DataPoint::StartReading (DataBufferPar & buffer) [pure virtual]

Start reading data from [URL](#).

Separate thread to transfer data will be created. No other operation can be performed while reading is in progress.

Parameters:

buffer operation will use this buffer to put information into. Should not be destroyed before stop_reading was called and returned.

Implemented in [Arc::DataPointIndex](#).

5.30.3.51 virtual DataStatus Arc::DataPoint::StartWriting (DataBufferPar & buffer, DataCallback * space_cb = NULL) [pure virtual]

Start writing data to [URL](#).

Separate thread to transfer data will be created. No other operation can be performed while writing is in progress.

Parameters:

buffer operation will use this buffer to get information from. Should not be destroyed before stop_writing was called and returned.

space_cb callback which is called if there is not enough space to store data. May not implemented for all protocols.

Implemented in [Arc::DataPointIndex](#).

5.30.3.52 virtual DataStatus Arc::DataPoint::StopReading () [pure virtual]

Stop reading.

Must be called after corresponding start_reading method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implemented in [Arc::DataPointIndex](#).

5.30.3.53 virtual DataStatus Arc::DataPoint::StopWriting () [pure virtual]

Stop writing.

Must be called after corresponding start_writing method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implemented in [Arc::DataPointIndex](#).

5.30.3.54 `virtual std::string Arc::DataPoint::str () const` [virtual]

Returns a string representation of the [DataPoint](#).

5.30.3.55 `virtual DataStatus Arc::DataPoint::Unregister (bool all)` [pure virtual]

Index [Service](#) unregistration.

Remove information about file registered in Indexing [Service](#).

Parameters:

all if true, information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Implemented in [Arc::DataPointDirect](#).

5.30.3.56 `virtual bool Arc::DataPoint::WriteOutOfOrder ()` [pure virtual]

Returns true if [URL](#) can accept scattered data for *writing* operation.

Implemented in [Arc::DataPointDirect](#), and [Arc::DataPointIndex](#).

The documentation for this class was generated from the following file:


- [DataPoint.h](#)

5.31 Arc::DataPointDirect Class Reference

This is a kind of generalized file handle.

```
#include <DataPointDirect.h>
```

Inheritance diagram for Arc::DataPointDirect::



Public Member Functions

- **DataPointDirect** (const [URL](#) &url)
- virtual bool [IsIndex](#) () const
- virtual unsigned long long int [BufSize](#) () const
- virtual int [BufNum](#) () const
- virtual bool [Cache](#) () const
- virtual bool [Local](#) () const
- virtual bool [ReadOnly](#) () const
- virtual void [ReadOutOfOrder](#) (bool v)
- virtual bool [WriteOutOfOrder](#) ()
- virtual void [SetAdditionalChecks](#) (bool v)
- virtual bool [GetAdditionalChecks](#) () const
- virtual void [SetSecure](#) (bool v)
- virtual bool [GetSecure](#) () const
- virtual void [Passive](#) (bool v)
- virtual void [Range](#) (unsigned long long int start=0, unsigned long long int end=0)
- virtual [DataStatus](#) [Resolve](#) (bool source)
- virtual bool [Registered](#) () const
- virtual [DataStatus](#) [PreRegister](#) (bool replication, bool force=false)
- virtual [DataStatus](#) [PostRegister](#) (bool replication)
- virtual [DataStatus](#) [PreUnregister](#) (bool replication)
- virtual [DataStatus](#) [Unregister](#) (bool all)
- virtual bool [AcceptsMeta](#) ()
- virtual bool [ProvidesMeta](#) ()
- virtual const [URL](#) & [CurrentLocation](#) () const
- virtual const std::string & [CurrentLocationMetadata](#) () const
- virtual bool [NextLocation](#) ()
- virtual bool [LocationValid](#) () const
- virtual bool [HaveLocations](#) () const
- virtual [DataStatus](#) [AddLocation](#) (const [URL](#) &url, const std::string &meta)
- virtual [DataStatus](#) [RemoveLocation](#) ()
- virtual [DataStatus](#) [RemoveLocations](#) (const [DataPoint](#) &p)

Protected Attributes

- [DataBufferPar](#) * **buffer**
- unsigned long long int **bufsize**
- int **bufnum**
- bool **cache**
- bool **local**
- bool **readonly**
- bool **linkable**
- bool **is_secure**
- bool **force_secure**
- bool **force_passive**
- bool **additional_checks**
- bool **allow_out_of_order**
- unsigned long long int **range_start**
- unsigned long long int **range_end**

5.31.1 Detailed Description

This is a kind of generalized file handle.

Differently from file handle it does not support operations `read()` and `write()`. Instead it initiates operation and uses object of class [DataBufferPar](#) to pass actual data. It also provides other operations like querying parameters of remote object. It is used by higher-level classes `DataMove` and `DataMovePar` to provide data transfer service for application.

5.31.2 Member Function Documentation

5.31.2.1 virtual bool Arc::DataPointDirect::AcceptsMeta () [virtual]

If endpoint can have any use from meta information.

Implements [Arc::DataPoint](#).

5.31.2.2 virtual DataStatus Arc::DataPointDirect::AddLocation (const [URL](#) & *url*, const std::string & *meta*) [virtual]

Add [URL](#) to list.

Parameters:

url Location [URL](#) to add.

meta Location meta information.

Implements [Arc::DataPoint](#).

5.31.2.3 virtual int Arc::DataPointDirect::BufNum () const [virtual]

Get suggested number of buffers for transfers.

Implements [Arc::DataPoint](#).

5.31.2.4 virtual unsigned long long int Arc::DataPointDirect::BufSize () const [virtual]

Get suggested buffer size for transfers.

Implements [Arc::DataPoint](#).

5.31.2.5 virtual bool Arc::DataPointDirect::Cache () const [virtual]

Returns true if file is cacheable.

Implements [Arc::DataPoint](#).

5.31.2.6 virtual const URL & Arc::DataPointDirect::CurrentLocation () const [virtual]

Returns current (resolved) [URL](#).

Implements [Arc::DataPoint](#).

5.31.2.7 virtual const std::string & Arc::DataPointDirect::CurrentLocationMetadata () const
[virtual]

Returns meta information used to create current [URL](#).

Usage differs between different indexing services.

Implements [Arc::DataPoint](#).

5.31.2.8 virtual bool Arc::DataPointDirect::GetAdditionalChecks () const [virtual]

Check if additional checks before will be performed.

Implements [Arc::DataPoint](#).

5.31.2.9 virtual bool Arc::DataPointDirect::GetSecure () const [virtual]

Check if heavy security during data transfer is allowed.

Implements [Arc::DataPoint](#).

5.31.2.10 virtual bool Arc::DataPointDirect::HaveLocations () const [virtual]

Returns true if number of resolved URLs is not 0.

Implements [Arc::DataPoint](#).

5.31.2.11 virtual bool Arc::DataPointDirect::IsIndex () const [virtual]

Check if [URL](#) is an Indexing [Service](#).

Implements [Arc::DataPoint](#).

5.31.2.12 virtual bool Arc::DataPointDirect::Local () const [virtual]

Returns true if file is local, e.g. file:// urls.

Implements [Arc::DataPoint](#).

5.31.2.13 virtual bool Arc::DataPointDirect::LocationValid () const [virtual]

Returns false if out of retries.

Implements [Arc::DataPoint](#).

5.31.2.14 virtual bool Arc::DataPointDirect::NextLocation () [virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implements [Arc::DataPoint](#).

5.31.2.15 virtual void Arc::DataPointDirect::Passive (bool v) [virtual]

Request passive transfers for FTP-like protocols.

Parameters:

true to request.

Implements [Arc::DataPoint](#).

5.31.2.16 virtual DataStatus Arc::DataPointDirect::PostRegister (bool replication) [virtual]

Index [Service](#) postregistration.

Used for same purpose as meta_preregister. Should be called after actual transfer of file successfully finished.

Parameters:

replication if true, the file is being replicated between two locations registered in Indexing [Service](#) under same name.

Implements [Arc::DataPoint](#).

5.31.2.17 virtual DataStatus Arc::DataPointDirect::PreRegister (bool replication, bool force = false) [virtual]

Index service preregistration.

This function registers the physical location of a file into an indexing service. It should be called **before** the actual transfer to that location happens.

Parameters:

replication if true, the file is being replicated between two locations registered in the indexing service under same name.

force if true, perform registration of a new file even if it already exists. Should be used to fix failures in Indexing [Service](#).

Implements [Arc::DataPoint](#).

5.31.2.18 virtual DataStatus Arc::DataPointDirect::PreUnregister (bool *replication*) [virtual]

Index [Service](#) preunregistration.

Should be called if file transfer failed. It removes changes made by PreRegister.

Parameters:

replication if true, the file is being replicated between two locations registered in Indexing [Service](#) under same name.

Implements [Arc::DataPoint](#).

5.31.2.19 virtual bool Arc::DataPointDirect::ProvidesMeta () [virtual]

If endpoint can provide at least some meta information directly.

Implements [Arc::DataPoint](#).

5.31.2.20 virtual void Arc::DataPointDirect::Range (unsigned long long int *start* = 0, unsigned long long int *end* = 0) [virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implements [Arc::DataPoint](#).

5.31.2.21 virtual void Arc::DataPointDirect::ReadOutOfOrder (bool *v*) [virtual]

Parameters:

v true if allowed (default is false).

Implements [Arc::DataPoint](#).

5.31.2.22 virtual bool Arc::DataPointDirect::Registered () const [virtual]

Check if file is registered in Indexing [Service](#).

Proper value is obtainable only after Resolve.

Implements [Arc::DataPoint](#).

5.31.2.23 virtual DataStatus Arc::DataPointDirect::RemoveLocation () [virtual]

Remove current [URL](#) from list.

Implements [Arc::DataPoint](#).

5.31.2.24 virtual DataStatus Arc::DataPointDirect::RemoveLocations (const [DataPoint](#) & *p*)
[virtual]

Remove locations present in another [DataPoint](#) object.

Implements [Arc::DataPoint](#).

5.31.2.25 virtual DataStatus Arc::DataPointDirect::Resolve (bool *source*) [virtual]

Resolves index service [URL](#) into list of ordinary URLs.

Also obtains meta information about the file.

Parameters:

source true if [DataPoint](#) object represents source of information.

Implements [Arc::DataPoint](#).

5.31.2.26 virtual void Arc::DataPointDirect::SetAdditionalChecks (bool *v*) [virtual]

Allow/disallow additional checks.

Check for existence of remote file (and probably other checks too) before initiating reading and writing operations.

Parameters:

v true if allowed (default is true).

Implements [Arc::DataPoint](#).

5.31.2.27 virtual void Arc::DataPointDirect::SetSecure (bool *v*) [virtual]

Allow/disallow heavy security during data transfer.

Parameters:

v true if allowed (default depends on protocol).

Implements [Arc::DataPoint](#).

5.31.2.28 virtual DataStatus Arc::DataPointDirect::Unregister (bool *all*) [virtual]

Index [Service](#) unregistration.

Remove information about file registered in Indexing [Service](#).

Parameters:

all if true, information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Implements [Arc::DataPoint](#).

5.31.2.29 virtual bool Arc::DataPointDirect::WriteOutOfOrder () [virtual]

Returns true if [URL](#) can accept scattered data for *writing* operation.

Implements [Arc::DataPoint](#).

The documentation for this class was generated from the following file:


- DataPointDirect.h

5.32 Arc::DataPointIndex Class Reference

Complements [DataPoint](#) with attributes common for Indexing [Service](#) URLs.

```
#include <DataPointIndex.h>
```

Inheritance diagram for Arc::DataPointIndex::



Public Member Functions

- **DataPointIndex** (const [URL](#) &url)
- virtual const [URL](#) & **CurrentLocation** () const
- virtual const std::string & **CurrentLocationMetadata** () const
- virtual bool **NextLocation** ()
- virtual bool **LocationValid** () const
- virtual bool **HaveLocations** () const
- virtual DataStatus **RemoveLocation** ()
- virtual DataStatus **RemoveLocations** (const [DataPoint](#) &p)
- virtual DataStatus **AddLocation** (const [URL](#) &url, const std::string &meta)
- virtual bool **IsIndex** () const
- virtual bool **AcceptsMeta** ()
- virtual bool **ProvidesMeta** ()
- virtual bool **Registered** () const
- virtual void **SetTries** (const int n)
- virtual unsigned long long int **BufSize** () const
- virtual int **BufNum** () const
- virtual bool **Cache** () const
- virtual bool **Local** () const
- virtual bool **ReadOnly** () const
- virtual DataStatus **StartReading** ([DataBufferPar](#) &buffer)
- virtual DataStatus **StartWriting** ([DataBufferPar](#) &buffer, [DataCallback](#) *space_cb=NULL)
- virtual DataStatus **StopReading** ()
- virtual DataStatus **StopWriting** ()
- virtual DataStatus **Check** ()
- virtual DataStatus **Remove** ()
- virtual void **ReadOutOfOrder** (bool v)
- virtual bool **WriteOutOfOrder** ()
- virtual void **SetAdditionalChecks** (bool v)
- virtual bool **GetAdditionalChecks** () const
- virtual void **SetSecure** (bool v)
- virtual bool **GetSecure** () const
- virtual void **Passive** (bool v)
- virtual void **Range** (unsigned long long int start=0, unsigned long long int end=0)

Protected Attributes

- `std::list< URLLocation > locations`
- `std::list< URLLocation >::iterator location`
- `DataHandle h`
- `bool resolved`
- `bool registered`

5.32.1 Detailed Description

Complements [DataPoint](#) with attributes common for Indexing [Service](#) URLs.

It should never be used directly. Instead inherit from it to provide a class for specific a Indexing [Service](#).

5.32.2 Member Function Documentation

5.32.2.1 `virtual bool Arc::DataPointIndex::AcceptsMeta ()` [virtual]

If endpoint can have any use from meta information.

Implements [Arc::DataPoint](#).

5.32.2.2 `virtual DataStatus Arc::DataPointIndex::AddLocation (const URL & url, const std::string & meta)` [virtual]

Add [URL](#) to list.

Parameters:

url Location [URL](#) to add.

meta Location meta information.

Implements [Arc::DataPoint](#).

5.32.2.3 `virtual int Arc::DataPointIndex::BufNum () const` [virtual]

Get suggested number of buffers for transfers.

Implements [Arc::DataPoint](#).

5.32.2.4 `virtual unsigned long long int Arc::DataPointIndex::BufSize () const` [virtual]

Get suggested buffer size for transfers.

Implements [Arc::DataPoint](#).

5.32.2.5 `virtual bool Arc::DataPointIndex::Cache () const` [virtual]

Returns true if file is cacheable.

Implements [Arc::DataPoint](#).

5.32.2.6 virtual DataStatus Arc::DataPointIndex::Check () [virtual]

Query the [DataPoint](#) to check if object is accessible.

If possible this method will also try to provide meta information about the object.

Implements [Arc::DataPoint](#).

5.32.2.7 virtual const URL& Arc::DataPointIndex::CurrentLocation () const [virtual]

Returns current (resolved) [URL](#).

Implements [Arc::DataPoint](#).

5.32.2.8 virtual const std::string& Arc::DataPointIndex::CurrentLocationMetadata () const [virtual]

Returns meta information used to create current [URL](#).

Usage differs between different indexing services.

Implements [Arc::DataPoint](#).

5.32.2.9 virtual bool Arc::DataPointIndex::GetAdditionalChecks () const [virtual]

Check if additional checks before will be performed.

Implements [Arc::DataPoint](#).

5.32.2.10 virtual bool Arc::DataPointIndex::GetSecure () const [virtual]

Check if heavy security during data transfer is allowed.

Implements [Arc::DataPoint](#).

5.32.2.11 virtual bool Arc::DataPointIndex::HaveLocations () const [virtual]

Returns true if number of resolved URLs is not 0.

Implements [Arc::DataPoint](#).

5.32.2.12 virtual bool Arc::DataPointIndex::IsIndex () const [virtual]

Check if [URL](#) is an Indexing [Service](#).

Implements [Arc::DataPoint](#).

5.32.2.13 virtual bool Arc::DataPointIndex::Local () const [virtual]

Returns true if file is local, e.g. file:// urls.

Implements [Arc::DataPoint](#).

5.32.2.14 virtual bool Arc::DataPointIndex::LocationValid () const [virtual]

Returns false if out of retries.

Implements [Arc::DataPoint](#).

5.32.2.15 virtual bool Arc::DataPointIndex::NextLocation () [virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implements [Arc::DataPoint](#).

5.32.2.16 virtual void Arc::DataPointIndex::Passive (bool v) [virtual]

Request passive transfers for FTP-like protocols.

Parameters:

true to request.

Implements [Arc::DataPoint](#).

5.32.2.17 virtual bool Arc::DataPointIndex::ProvidesMeta () [virtual]

If endpoint can provide at least some meta information directly.

Implements [Arc::DataPoint](#).

5.32.2.18 virtual void Arc::DataPointIndex::Range (unsigned long long int start = 0, unsigned long long int end = 0) [virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implements [Arc::DataPoint](#).

5.32.2.19 virtual void Arc::DataPointIndex::ReadOutOfOrder (bool v) [virtual]**Parameters:**

v true if allowed (default is false).

Implements [Arc::DataPoint](#).

5.32.2.20 virtual bool Arc::DataPointIndex::Registered () const [virtual]

Check if file is registered in Indexing [Service](#).

Proper value is obtainable only after Resolve.

Implements [Arc::DataPoint](#).

5.32.2.21 virtual DataStatus Arc::DataPointIndex::Remove () [virtual]

Remove/delete object at [URL](#).

Implements [Arc::DataPoint](#).

5.32.2.22 virtual DataStatus Arc::DataPointIndex::RemoveLocation () [virtual]

Remove current [URL](#) from list.

Implements [Arc::DataPoint](#).

5.32.2.23 virtual DataStatus Arc::DataPointIndex::RemoveLocations (const [DataPoint](#) & *p*) [virtual]

Remove locations present in another [DataPoint](#) object.

Implements [Arc::DataPoint](#).

5.32.2.24 virtual void Arc::DataPointIndex::SetAdditionalChecks (bool *v*) [virtual]

Allow/disallow additional checks.

Check for existence of remote file (and probably other checks too) before initiating reading and writing operations.

Parameters:

v true if allowed (default is true).

Implements [Arc::DataPoint](#).

5.32.2.25 virtual void Arc::DataPointIndex::SetSecure (bool *v*) [virtual]

Allow/disallow heavy security during data transfer.

Parameters:

v true if allowed (default depends on protocol).

Implements [Arc::DataPoint](#).

5.32.2.26 virtual void Arc::DataPointIndex::SetTries (const int *n*) [virtual]

Set number of retries.

Reimplemented from [Arc::DataPoint](#).

5.32.2.27 virtual DataStatus Arc::DataPointIndex::StartReading ([DataBufferPar](#) & *buffer*) [virtual]

Start reading data from [URL](#).

Separate thread to transfer data will be created. No other operation can be performed while reading is in progress.

Parameters:

buffer operation will use this buffer to put information into. Should not be destroyed before stop_-reading was called and returned.

Implements [Arc::DataPoint](#).

5.32.2.28 virtual DataStatus Arc::DataPointIndex::StartWriting ([DataBufferPar](#) & *buffer*, [DataCallback](#) * *space_cb* = NULL) [virtual]

Start writing data to [URL](#).

Separate thread to transfer data will be created. No other operation can be performed while writing is in progress.

Parameters:

buffer operation will use this buffer to get information from. Should not be destroyed before stop_-writing was called and returned.

space_cb callback which is called if there is not enough space to store data. May not implemented for all protocols.

Implements [Arc::DataPoint](#).

5.32.2.29 virtual DataStatus Arc::DataPointIndex::StopReading () [virtual]

Stop reading.

Must be called after corresponding start_reading method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implements [Arc::DataPoint](#).

5.32.2.30 virtual DataStatus Arc::DataPointIndex::StopWriting () [virtual]

Stop writing.

Must be called after corresponding start_writing method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implements [Arc::DataPoint](#).

5.32.2.31 virtual bool Arc::DataPointIndex::WriteOutOfOrder () [virtual]

Returns true if [URL](#) can accept scattered data for *writing* operation.

Implements [Arc::DataPoint](#).

5.32.3 Member Data Documentation

5.32.3.1 `std::list<URLLocation> Arc::DataPointIndex::locations` [protected]

List of locations at which file can be probably found.

The documentation for this class was generated from the following file:

- DataPointIndex.h

5.33 Arc::DataSpeed Class Reference

Keeps track of average and instantaneous transfer speed.

```
#include <DataSpeed.h>
```

Public Types

- typedef void(*) **show_progress_t** (FILE *o, const char *s, unsigned int t, unsigned long long int all, unsigned long long int max, double instant, double average)

Public Member Functions

- [DataSpeed](#) (time_t base=DATASPEED_AVERAGING_PERIOD)
- [DataSpeed](#) (unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, time_t base=DATASPEED_AVERAGING_PERIOD)
- [~DataSpeed](#) (void)
- void [verbose](#) (bool val)
- void [verbose](#) (const std::string &prefix)
- bool [verbose](#) (void)
- void [set_min_speed](#) (unsigned long long int min_speed, time_t min_speed_time)
- void [set_min_average_speed](#) (unsigned long long int min_average_speed)
- void [set_max_inactivity_time](#) (time_t max_inactivity_time)
- void [set_base](#) (time_t base_=DATASPEED_AVERAGING_PERIOD)
- void [set_max_data](#) (unsigned long long int max=0)
- void [set_progress_indicator](#) (show_progress_t func=NULL)
- void [reset](#) (void)
- bool [transfer](#) (unsigned long long int n=0)
- void [hold](#) (bool disable)
- bool [min_speed_failure](#) ()
- bool [min_average_speed_failure](#) ()
- bool [max_inactivity_time_failure](#) ()
- unsigned long long int [transferred_size](#) (void)

5.33.1 Detailed Description

Keeps track of average and instantaneous transfer speed.

Also detects data transfer inactivity and other transfer timeouts.

5.33.2 Constructor & Destructor Documentation

5.33.2.1 Arc::DataSpeed::DataSpeed (time_t base = DATASPEED_AVERAGING_PERIOD)

Constructor

Parameters:

base time period used to average values (default 1 minute).

5.33.2.2 Arc::DataSpeed::DataSpeed (unsigned long long int *min_speed*, time_t *min_speed_time*, unsigned long long int *min_average_speed*, time_t *max_inactivity_time*, time_t *base* = DATASPEED_AVERAGING_PERIOD)

Constructor

Parameters:

base time period used to average values (default 1 minute).

min_speed minimal allowed speed (Butes per second). If speed drops and holds below threshold for *min_speed_time_* seconds error is triggered.

min_speed_time

min_average_speed_ minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

max_inactivity_time - if no data is passing for specified amount of time (seconds), error is triggered.

5.33.2.3 Arc::DataSpeed::~DataSpeed (void)

Destructor.

5.33.3 Member Function Documentation

5.33.3.1 void Arc::DataSpeed::hold (bool *disable*)

Turn off speed control.

Parameters:

disable true to turn off.

5.33.3.2 bool Arc::DataSpeed::max_inactivity_time_failure () [inline]

Check if maximal inactivity time error was triggered.

5.33.3.3 bool Arc::DataSpeed::min_average_speed_failure () [inline]

Check if minimal average speed error was triggered.

5.33.3.4 bool Arc::DataSpeed::min_speed_failure () [inline]

Check if minimal speed error was triggered.

5.33.3.5 void Arc::DataSpeed::reset (void)

Reset all counters and triggers.

5.33.3.6 void Arc::DataSpeed::set_base (time_t *base_* = DATASPEED_AVERAGING_PERIOD)

Set averaging time period.

Parameters:

base time period used to average values (default 1 minute).

5.33.3.7 void Arc::DataSpeed::set_max_data (unsigned long long int *max* = 0)

Set amount of data to be transfered. Used in verbose messages.

Parameters:

max amount of data in bytes.

5.33.3.8 void Arc::DataSpeed::set_max_inactivity_time (time_t *max_inactivity_time*)

Set inactivity timeout.

Parameters:

max_inactivity_time - if no data is passing for specified amount of time (seconds), error is triggered.

5.33.3.9 void Arc::DataSpeed::set_min_average_speed (unsigned long long int *min_average_speed*)

Set minimal average speed.

Parameters:

min_average_speed minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

5.33.3.10 void Arc::DataSpeed::set_min_speed (unsigned long long int *min_speed*, time_t *min_speed_time*)

Set minimal allowed speed.

Parameters:

min_speed minimal allowed speed (Bytes per second). If speed drops and holds below threshold for *min_speed_time* seconds error is triggered.

min_speed_time

5.33.3.11 void Arc::DataSpeed::set_progress_indicator (show_progress_t *func* = NULL)

Specify which external function will print verbose messages. If not specified internal one is used.

Parameters:

pointer to function which prints information.

5.33.3.12 bool Arc::DataSpeed::transfer (unsigned long long int *n* = 0)

Inform object, about amount of data has been transfered. All errors are triggered by this method. To make them work application must call this method periodically even with zero value.

Parameters:

n amount of data transfered (bytes).

5.33.3.13 unsigned long long int Arc::DataSpeed::transferred_size (void) [inline]

Returns amount of data this object knows about.

5.33.3.14 bool Arc::DataSpeed::verbose (void)

Check if speed information is going to be printed.

5.33.3.15 void Arc::DataSpeed::verbose (const std::string & *prefix*)

Print information about current speed and amount of data.

Parameters:

'prefix' add this string at the beginning of every string.

5.33.3.16 void Arc::DataSpeed::verbose (bool *val*)

Activate printing information about current time speeds, amount of transfered data.


The documentation for this class was generated from the following file:

- DataSpeed.h

5.34 Arc::DelegationConsumer Class Reference

```
#include <DelegationInterface.h>
```

Inheritance diagram for Arc::DelegationConsumer::



Public Member Functions

- [DelegationConsumer](#) (void)
- [DelegationConsumer](#) (const std::string &content)
- **operator bool** (void)
- **bool operator!** (void)
- const std::string & [ID](#) (void)
- bool [Backup](#) (std::string &content)
- bool [Restore](#) (const std::string &content)
- bool [Request](#) (std::string &content)
- bool [Acquire](#) (std::string &content)

Protected Member Functions

- bool [Generate](#) (void)
- void [LogError](#) (void)

Protected Attributes

- void * [key_](#)

5.34.1 Detailed Description

A consumer of delegated X509 credentials. During delegation procedure this class acquires delegated credentials aka proxy - certificate, private key and chain of previous certificates. Delegation procedure consists of calling [Request\(\)](#) method for generating certificate request followed by call to [Acquire\(\)](#) method for making complete credentials from certificate chain.

5.34.2 Constructor & Destructor Documentation

5.34.2.1 Arc::DelegationConsumer::DelegationConsumer (void)

Creates object with new private key

5.34.2.2 Arc::DelegationConsumer::DelegationConsumer (const std::string & content)

Creates object with provided private key

5.34.3 Member Function Documentation

5.34.3.1 `bool Arc::DelegationConsumer::Acquire (std::string & content)`

Ads private key into certificates chain in 'content' On exit content contains complete delegated credentials.

5.34.3.2 `bool Arc::DelegationConsumer::Backup (std::string & content)`

Stores content of this object into a string

5.34.3.3 `bool Arc::DelegationConsumer::Generate (void)` [protected]

Private key

5.34.3.4 `const std::string& Arc::DelegationConsumer::ID (void)`

Return identifier of this object - not implemented

5.34.3.5 `void Arc::DelegationConsumer::LogError (void)` [protected]

Creates private key

5.34.3.6 `bool Arc::DelegationConsumer::Request (std::string & content)`

Make X509 certificate request from internal private key

5.34.3.7 `bool Arc::DelegationConsumer::Restore (const std::string & content)`

Restores content of object from string


The documentation for this class was generated from the following file:

- DelegationInterface.h

5.35 Arc::DelegationConsumerSOAP Class Reference

```
#include <DelegationInterface.h>
```

Inheritance diagram for Arc::DelegationConsumerSOAP::



Public Member Functions

- [DelegationConsumerSOAP](#) (void)
- [DelegationConsumerSOAP](#) (const std::string &content)
- bool [DelegateCredentialsInit](#) (const std::string &id, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool [UpdateCredentials](#) (std::string &credentials, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool [DelegatedToken](#) (std::string &credentials, const [XMLNode](#) &token)

5.35.1 Detailed Description

This class extends [DelegationConsumer](#) to support SOAP message exchange. Implements WS interface <http://www.nordugrid.org/schemas/delegation> described in delegation.wsdl.

5.35.2 Constructor & Destructor Documentation

5.35.2.1 Arc::DelegationConsumerSOAP::DelegationConsumerSOAP (void)

Creates object with new private key

5.35.2.2 Arc::DelegationConsumerSOAP::DelegationConsumerSOAP (const std::string &content)

Creates object with specified private key

5.35.3 Member Function Documentation

5.35.3.1 bool Arc::DelegationConsumerSOAP::DelegateCredentialsInit (const std::string &id, const SOAPEnvelope &in, SOAPEnvelope &out)

Process SOAP message which starts delagation. Generated message in 'out' is meant to be sent back to DelagationProviderSOAP. Argument 'id' contains identifier of procedure and is used only to produce SOAP message.

5.35.3.2 **bool Arc::DelegationConsumerSOAP::DelegatedToken** (std::string & *credentials*, const XMLNode & *token*)

Similar to UpdateCredentials but takes only DelegatedToken XML element

5.35.3.3 **bool Arc::DelegationConsumerSOAP::UpdateCredentials** (std::string & *credentials*, const SOAPEnvelope & *in*, SOAPEnvelope & *out*)

Accepts delegated credentials. Process 'in' SOAP message and stores full proxy credentials in 'credentials'. 'out' message is generated for sending to DelagationProviderSOAP.

The documentation for this class was generated from the following file:

- DelegationInterface.h

5.36 Arc::DelegationContainerSOAP Class Reference

```
#include <DelegationInterface.h>
```

Public Member Functions

- bool [DelegateCredentialsInit](#) (const SOAPEnvelope &in, SOAPEnvelope &out)
- bool [UpdateCredentials](#) (std::string &credentials, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool [DelegatedToken](#) (std::string &credentials, const [XMLNode](#) &token)

Protected Attributes

- Glib::Mutex [lock_](#)
- int [max_size_](#)
- int [max_duration_](#)
- int [max_usage_](#)
- bool [context_lock_](#)
- bool [restricted_](#)

5.36.1 Detailed Description

Manages multiple delegated credentials. Delegation consumers are created automatically with DelegateCredentialsInit method up to max_size_ and assigned unique identifier. It's methods are similar to those of [DelegationConsumerSOAP](#) with identifier included in SOAP message used to route execution to one of managed [DelegationConsumerSOAP](#) instances.

5.36.2 Member Function Documentation

5.36.2.1 bool Arc::DelegationContainerSOAP::DelegateCredentialsInit (const SOAPEnvelope &in, SOAPEnvelope &out)

See [DelegationConsumerSOAP::DelegateCredentialsInit](#)

5.36.2.2 bool Arc::DelegationContainerSOAP::DelegatedToken (std::string &credentials, const [XMLNode](#) &token)

See [DelegationConsumerSOAP::DelegatedToken](#)

5.36.2.3 bool Arc::DelegationContainerSOAP::UpdateCredentials (std::string &credentials, const SOAPEnvelope &in, SOAPEnvelope &out)

See [DelegationConsumerSOAP::UpdateCredentials](#)

5.36.3 Member Data Documentation

5.36.3.1 bool [Arc::DelegationContainerSOAP::context_lock_](#) [protected]

If true delegation consumer is deleted when connection context is destroyed

5.36.3.2 `int` [`Arc::DelegationContainerSOAP::max_duration_`](#) [protected]

Lifetime of unused delegation consumer

5.36.3.3 `int` [`Arc::DelegationContainerSOAP::max_size_`](#) [protected]

Max. number of delegation consumers

5.36.3.4 `int` [`Arc::DelegationContainerSOAP::max_usage_`](#) [protected]

Max. times same delegation consumer may accept credentials

5.36.3.5 `bool` [`Arc::DelegationContainerSOAP::restricted_`](#) [protected]

If true all delegation phases must be performed by same identity


The documentation for this class was generated from the following file:

- `DelegationInterface.h`

5.37 Arc::DelegationProvider Class Reference

```
#include <DelegationInterface.h>
```

Inheritance diagram for Arc::DelegationProvider::



Public Member Functions

- [DelegationProvider](#) (const std::string &credentials)
- [DelegationProvider](#) (const std::string &cert_file, const std::string &key_file, std::istream *inpwd=NULL)
- **operator bool** (void)
- **bool operator!** (void)
- std::string [Delegate](#) (const std::string &request, const DelegationRestrictions &restrictions=DelegationRestrictions())

5.37.1 Detailed Description

A provider of delegated credentials. During delegation procedure this class generates new credential to be used in proxy/delegated credential.

5.37.2 Constructor & Destructor Documentation

5.37.2.1 Arc::DelegationProvider::DelegationProvider (const std::string & credentials)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain PEM-encoded certificate, private key and optionally certificates chain.

5.37.2.2 Arc::DelegationProvider::DelegationProvider (const std::string & cert_file, const std::string & key_file, std::istream * inpwd = NULL)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain filesystem path to PEM-encoded certificate and private key. Optionally cert_file may contain certificates chain.

5.37.3 Member Function Documentation

5.37.3.1 std::string Arc::DelegationProvider::Delegate (const std::string & request, const DelegationRestrictions & restrictions = DelegationRestrictions())

Perform delegation. Takes X509 certificate request and creates proxy credentials excluding private key. Result is then fed into [DelegationConsumer::Acquire](#)


The documentation for this class was generated from the following file:

- [DelegationInterface.h](#)

5.38 Arc::DelegationProviderSOAP Class Reference

```
#include <DelegationInterface.h>
```

Inheritance diagram for Arc::DelegationProviderSOAP::



Public Member Functions

- [DelegationProviderSOAP](#) (const std::string &credentials)
- [DelegationProviderSOAP](#) (const std::string &cert_file, const std::string &key_file)
- bool [DelegateCredentialsInit](#) ([MCCInterface](#) &mcc_interface, [MessageContext](#) *context)
- bool [DelegateCredentialsInit](#) ([MCCInterface](#) &mcc_interface, [MessageAttributes](#) *attributes_in, [MessageAttributes](#) *attributes_out, [MessageContext](#) *context)
- bool [UpdateCredentials](#) ([MCCInterface](#) &mcc_interface, [MessageContext](#) *context)
- bool [UpdateCredentials](#) ([MCCInterface](#) &mcc_interface, [MessageAttributes](#) *attributes_in, [MessageAttributes](#) *attributes_out, [MessageContext](#) *context)
- bool [DelegatedToken](#) ([XMLNode](#) &parent)

Protected Attributes

- std::string [request_](#)
- std::string [id_](#)

5.38.1 Detailed Description

Extension of [DelegationProvider](#) with SOAP exchange interface. This class is also a temporary container for intermediate information used during delegation procedure.

5.38.2 Constructor & Destructor Documentation

5.38.2.1 Arc::DelegationProviderSOAP::DelegationProviderSOAP (const std::string & credentials)

Creates instance from provided credentials. Credentials are used to sign delegated credentials.

5.38.2.2 Arc::DelegationProviderSOAP::DelegationProviderSOAP (const std::string & cert_file, const std::string & key_file)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain filesystem path to PEM-encoded certificate and private key. Optionally cert_file may contain certificates chain.

5.38.3 Member Function Documentation

5.38.3.1 `bool Arc::DelegationProviderSOAP::DelegateCredentialsInit (MCCInterface & mcc_interface, MessageAttributes * attributes_in, MessageAttributes * attributes_out, MessageContext * context)`

Extended version of `DelegateCredentialsInit(MCCInterface&,MessageContext*)`. Additionally takes attributes for request and response message to make fine control on message processing possible.

5.38.3.2 `bool Arc::DelegationProviderSOAP::DelegateCredentialsInit (MCCInterface & mcc_interface, MessageContext * context)`

Performs DelegateCredentialsInit SOAP operation. As result request for delegated credentials is received by this instance and stored internally. Call to UpdateCredentials should follow.

5.38.3.3 `bool Arc::DelegationProviderSOAP::DelegatedToken (XMLNode & parent)`

Generates DelegatedToken element. Element is created as child of provided XML element and contains structure described in delegation.wsdl.

5.38.3.4 `bool Arc::DelegationProviderSOAP::UpdateCredentials (MCCInterface & mcc_interface, MessageAttributes * attributes_in, MessageAttributes * attributes_out, MessageContext * context)`

Extended version of `UpdateCredentials(MCCInterface&,MessageContext*)`. Additionally takes attributes for request and response message to make fine control on message processing possible.

5.38.3.5 `bool Arc::DelegationProviderSOAP::UpdateCredentials (MCCInterface & mcc_interface, MessageContext * context)`

Performs UpdateCredentials SOAP operation. This concludes delegation procedure and passes delegated credentials to `DelegationConsumerSOAP` instance.

The documentation for this class was generated from the following file:


- DelegationInterface.h

5.39 ArcSec::DenyOverridesCombiningAlg Class Reference

Implement the "Deny-Overrides" algorithm.

```
#include <DenyOverridesAlg.h>
```

Inheritance diagram for ArcSec::DenyOverridesCombiningAlg::



Public Member Functions

- virtual Result **combine** (EvaluationCtx *ctx, std::list< Policy * > policies)
- virtual std::string & **getalgId** (void)

Static Public Member Functions

- static const std::string & **Identifier** (void)

5.39.1 Detailed Description

Implement the "Deny-Overrides" algorithm.

5.39.2 Member Function Documentation

5.39.2.1 virtual Result ArcSec::DenyOverridesCombiningAlg::combine (EvaluationCtx * ctx, std::list< Policy * > policies) [virtual]

If there is one policy which return negative evaluation result, then omit the other policies and return DECISION_DENY

Implements [ArcSec::CombiningAlg](#).

The documentation for this class was generated from the following file:

- DenyOverridesAlg.h

5.40 dmc_descriptor Struct Reference

```
#include <DMCLoader.h>
```

Public Attributes

- const char * **name**
- int **version**
- Arc::DMC *(* **get_instance**)(Arc::Config *cfg, Arc::ChainContext *ctx)

5.40.1 Detailed Description

This structure describes one of the DMCs stored in a shared library. It contains name of plugin, version number and pointer to function which creates an instance of an object inherited from the DMC class.


The documentation for this struct was generated from the following file:

- DMCLoader.h

5.41 Arc::DMCFactory Class Reference

```
#include <DMCFactory.h>
```

Inheritance diagram for Arc::DMCFactory::



Public Member Functions

- [DMCFactory](#) ([Config](#) *cfg)
- DMC * [get_instance](#) (const std::string &name, [Config](#) *cfg, [ChainContext](#) *ctx)
- DMC * [get_instance](#) (const std::string &name, int version, [Config](#) *cfg, [ChainContext](#) *ctx)
- DMC * [get_instance](#) (const std::string &name, int min_version, int max_version, [Config](#) *cfg, [ChainContext](#) *ctx)

5.41.1 Detailed Description

This class handles shared libraries containing DMCs

5.41.2 Constructor & Destructor Documentation

5.41.2.1 Arc::DMCFactory::DMCFactory ([Config](#) * *cfg*)

Constructor - accepts configuration (not yet used) meant to tune loading of module.

5.41.3 Member Function Documentation

5.41.3.1 DMC* Arc::DMCFactory::get_instance (const std::string & *name*, [Config](#) * *cfg*, [ChainContext](#) * *ctx*)

These methods load shared library named lib'name', locate symbol representing descriptor of DMC and calls it's constructor function. Supplied configuration tree is passed to constructor. Returns created DMC instance.

Reimplemented from [Arc::LoaderFactory](#).

The documentation for this class was generated from the following file:


- DMCFactory.h

5.42 ArcSec::EqualFunction Class Reference

Evaluate whether the two values are equal.

```
#include <EqualFunction.h>
```

Inheritance diagram for ArcSec::EqualFunction::



Public Member Functions

- **EqualFunction** (std::string functionName, std::string argumentType)
- virtual bool **evaluate** ([AttributeValue](#) *arg0, [AttributeValue](#) *arg1)

Static Public Member Functions

- static std::string [getFunctionName](#) (std::string datatype)

5.42.1 Detailed Description

Evaluate whether the two values are equal.

5.42.2 Member Function Documentation

5.42.2.1 static std::string ArcSec::EqualFunction::getFunctionName (std::string *datatype*)
[static]

help function to get the FunctionName

The documentation for this class was generated from the following file:

- EqualFunction.h

5.43 ArcSec::EvalResult Struct Reference

Struct to record the xml node and effect, which will be used by [Evaluator](#) to get the information about which rule/policy(in xmlnode) is satisfied.

```
#include <Result.h>
```

Public Attributes

- [Arc::XMLNode](#) **node**
- std::string **effect**

5.43.1 Detailed Description

Struct to record the xml node and effect, which will be used by [Evaluator](#) to get the information about which rule/policy(in xmlnode) is satisfied.

The documentation for this struct was generated from the following file:

- Result.h

5.44 ArcSec::EvaluationCtx Class Reference

[EvaluationCtx](#), in charge of storing some context information for evaluation, including [Request](#), current time, etc.

```
#include <EvaluationCtx.h>
```

Public Member Functions

- [EvaluationCtx](#) ([Request](#) *request)
- virtual [Request](#) * **getRequest** () const
- virtual void **setRequestItem** ([RequestItem](#) *reqit)
- virtual [RequestItem](#) * **getRequestItem** () const
- virtual void **split** ()
- virtual std::list< [RequestTuple](#) * > **getRequestTuples** () const
- virtual void **setEvalTuple** ([RequestTuple](#) *tuple)
- virtual [RequestTuple](#) * **getEvalTuple** () const

5.44.1 Detailed Description

[EvaluationCtx](#), in charge of storing some context information for evaluation, including [Request](#), current time, etc.

5.44.2 Constructor & Destructor Documentation

5.44.2.1 ArcSec::EvaluationCtx::EvaluationCtx ([Request](#) *request)

Construct a new [EvaluationCtx](#) based on the given request

5.44.3 Member Function Documentation

5.44.3.1 virtual void ArcSec::EvaluationCtx::split () [virtual]

Convert/split one [RequestItem](#) (one tuple <SubList, ResList, ActList, CtxList>) into a few <Subject, Resource, Action, Context> tuples. The purpose is for evaluation. The evaluator will evaluate each [RequestTuple](#) one by one, not the [RequestItem](#) because it includes some independent <Subject, Resource, Action, Context>s and the evaluator should deal with them independently.

The documentation for this class was generated from the following file:

- EvaluationCtx.h

5.45 ArcSec::Evaluator Class Reference

Interface for policy evaluation. Execute the policy evaluation, based on the request and policy.

```
#include <Evaluator.h>
```

Public Member Functions

- **Evaluator** ([Arc::XMLNode](#) *)
- **Evaluator** (const char *)
- virtual [Response](#) * **evaluate** ([Request](#) *request)=0
- virtual [Response](#) * **evaluate** (const [Source](#) &request)=0
- virtual [Response](#) * **evaluate** ([Request](#) *request, const [Source](#) &policy)=0
- virtual [Response](#) * **evaluate** (const [Source](#) &request, const [Source](#) &policy)=0
- virtual [Response](#) * **evaluate** ([Request](#) *request, [Policy](#) *policyobj)=0
- virtual [Response](#) * **evaluate** (const [Source](#) &request, [Policy](#) *policyobj)=0
- virtual [AttributeFactory](#) * **getAttrFactory** ()=0
- virtual [FnFactory](#) * **getFnFactory** ()=0
- virtual [AlgFactory](#) * **getAlgFactory** ()=0
- virtual void **addPolicy** (const [Source](#) &policy, const std::string &id="")=0
- virtual void **addPolicy** ([Policy](#) *policy, const std::string &id="")=0
- virtual void **setCombiningAlg** ([EvaluatorCombiningAlg](#) alg)=0

Protected Member Functions

- virtual [Response](#) * **evaluate** ([EvaluationCtx](#) *ctx)=0

Static Protected Attributes

- static [Arc::Logger](#) **logger**

5.45.1 Detailed Description

Interface for policy evaluation. Execute the policy evaluation, based on the request and policy.

5.45.2 Member Function Documentation

5.45.2.1 virtual void [ArcSec::Evaluator::addPolicy](#) ([Policy](#) **policy*, const std::string &*id* = "")
[pure virtual]

Add policy to the evaluator. [Policy](#) will be marked with id.

5.45.2.2 virtual void [ArcSec::Evaluator::addPolicy](#) (const [Source](#) &*policy*, const std::string &*id* = "")
[pure virtual]

Add policy from specified source to the evaluator. [Policy](#) will be marked with id.

5.45.2.3 `virtual Response* ArcSec::Evaluator::evaluate (EvaluationCtx * ctx)` [protected, pure virtual]

Evaluate the request by using the [EvaluationCtx](#) object (which includes the information about request)

5.45.2.4 `virtual Response* ArcSec::Evaluator::evaluate (const Source & request, Policy * policyobj)` [pure virtual]

Evaluate the request from specified source against the specified policy. All of the existing policy inside the evaluator will be replaced by the policy argument

5.45.2.5 `virtual Response* ArcSec::Evaluator::evaluate (Request * request, Policy * policyobj)` [pure virtual]

Evaluate the specified request against the specified policy. All of the existing policy inside the evaluator will be replaced by the policy argument

5.45.2.6 `virtual Response* ArcSec::Evaluator::evaluate (const Source & request, const Source & policy)` [pure virtual]

Evaluate the request from specified source against the policy from specified source. All of the existing policy inside the evaluator will be replaced by the policy argument

5.45.2.7 `virtual Response* ArcSec::Evaluator::evaluate (Request * request, const Source & policy)` [pure virtual]

Evaluate the specified request against the policy from specified source. All of the existing policy inside the evaluator will be replaced by the policy argument

5.45.2.8 `virtual Response* ArcSec::Evaluator::evaluate (const Source & request)` [pure virtual]

Evaluates the request by using a specified source

5.45.2.9 `virtual Response* ArcSec::Evaluator::evaluate (Request * request)` [pure virtual]

Evaluates the request by using a [Request](#) object. Evaluation is done till at least one of policies is satisfied.

5.45.2.10 `virtual AlgFactory* ArcSec::Evaluator::getAlgFactory ()` [pure virtual]

Get the [AlgFactory](#) object

5.45.2.11 `virtual AttributeFactory* ArcSec::Evaluator::getAttrFactory ()` [pure virtual]

Get the [AttributeFactory](#) object

5.45.2.12 virtual [FnFactory](#)* ArcSec::Evaluator::getFnFactory () [pure virtual]

Get the [FnFactory](#) object

The documentation for this class was generated from the following file:

- Evaluator.h

5.46 ArcSec::EvaluatorContext Class Reference

Context for evaluator. It includes the factories which will be used to create related objects.

```
#include <Evaluator.h>
```

Public Member Functions

- **EvaluatorContext** ([Evaluator](#) *evaluator)
- **operator AttributeFactory** * ()
- **operator FnFactory** * ()
- **operator AlgFactory** * ()

5.46.1 Detailed Description

Context for evaluator. It includes the factories which will be used to create related objects.

5.46.2 Member Function Documentation

5.46.2.1 ArcSec::EvaluatorContext::operator [AlgFactory](#) * () [inline]

Returns associated [AlgFactory](#) object

5.46.2.2 ArcSec::EvaluatorContext::operator [AttributeFactory](#) * () [inline]

Returns associated [AttributeFactory](#) object

5.46.2.3 ArcSec::EvaluatorContext::operator [FnFactory](#) * () [inline]

Returns associated [FnFactory](#) object

The documentation for this class was generated from the following file:

- [Evaluator.h](#)

5.47 ArcSec::EvaluatorLoader Class Reference

[EvaluatorLoader](#) is implemented as a helper class for loading different [Evaluator](#) objects, like ArcEvaluator.

```
#include <EvaluatorLoader.h>
```

Public Member Functions

- [Evaluator](#) * [getEvaluator](#) (const std::string &classname)
- [Request](#) * [getRequest](#) (const std::string &classname, const [Source](#) &requestsource)
- [Policy](#) * [getPolicy](#) (const std::string &classname, const [Source](#) &polycysource)

Static Protected Attributes

- static [Arc::Logger](#) **logger**

5.47.1 Detailed Description

[EvaluatorLoader](#) is implemented as a helper class for loading different [Evaluator](#) objects, like ArcEvaluator.

The object loading is based on the configuration information about evaluator, including information for factory class, request, policy and evaluator itself

5.47.2 Member Function Documentation

5.47.2.1 [Evaluator](#)* ArcSec::EvaluatorLoader::getEvaluator (const std::string & *classname*)

Get evaluator object according to the class name

5.47.2.2 [Policy](#)* ArcSec::EvaluatorLoader::getPolicy (const std::string & *classname*, const [Source](#) & *polycysource*)

Get policy object according to the class name, based on the policy source

5.47.2.3 [Request](#)* ArcSec::EvaluatorLoader::getRequest (const std::string & *classname*, const [Source](#) & *requestsource*)

Get request object according to the class name, based on the request source

The documentation for this class was generated from the following file:

- EvaluatorLoader.h

5.48 Arc::ExpirationReminder Class Reference

A class intended for internal use within counters.

```
#include <Counter.h>
```

Public Member Functions

- bool [operator<](#) (const [ExpirationReminder](#) &other) const
- Glib::TimeVal [getExpiryTime](#) () const
- Counter::IDType [getReservationID](#) () const

Friends

- class [Counter](#)

5.48.1 Detailed Description

A class intended for internal use within counters.

This class is used for "reminder objects" that are used for automatic deallocation of self-expiring reservations.

5.48.2 Member Function Documentation

5.48.2.1 Glib::TimeVal Arc::ExpirationReminder::getExpiryTime () const

Returns the expiry time.

This method returns the expiry time of the reservation that this [ExpirationReminder](#) is associated with.

Returns:

The expiry time.

5.48.2.2 Counter::IDType Arc::ExpirationReminder::getReservationID () const

Returns the identification number of the reservation.

This method returns the identification number of the self-expiring reservation that this [ExpirationReminder](#) is associated with.

Returns:

The identification number.

5.48.2.3 bool Arc::ExpirationReminder::operator< (const [ExpirationReminder](#) & other) const

Less than operator, compares "soonness".

This is the less than operator for the [ExpirationReminder](#) class. It compares the priority of such objects with respect to which reservation expires first. It is used when reminder objects are inserted in a priority queue in order to allways place the next reservation to expire at the top.

5.48.3 Friends And Related Function Documentation

5.48.3.1 friend class [Counter](#) [friend]

The [Counter](#) class needs to be a friend.

The documentation for this class was generated from the following file:

- Counter.h

5.49 Arc::FileInfo Class Reference

[FileInfo](#) stores information about files (metadata).

```
#include <FileInfo.h>
```

Public Types

- `file_type_unknown = 0`
- `file_type_file = 1`
- `file_type_dir = 2`
- `enum Type { file_type_unknown = 0, file_type_file = 1, file_type_dir = 2 }`

Public Member Functions

- `FileInfo (const std::string &name="")`
- `const std::string & GetName () const`
- `std::string GetLastName () const`
- `const std::list< URL > & GetURLs () const`
- `void AddURL (const URL &u)`
- `bool CheckSize () const`
- `unsigned long long int GetSize () const`
- `void SetSize (const unsigned long long int s)`
- `bool CheckChecksum () const`
- `const std::string & GetChecksum () const`
- `void SetChecksum (const std::string &c)`
- `bool CheckCreated () const`
- `Time GetCreated () const`
- `void SetCreated (const Time &t)`
- `bool CheckValid () const`
- `Time GetValid () const`
- `void SetValid (const Time &t)`
- `bool CheckType () const`
- `Type GetType () const`
- `void SetType (const Type t)`

5.49.1 Detailed Description

[FileInfo](#) stores information about files (metadata).

The documentation for this class was generated from the following file:

- `FileInfo.h`

5.50 ArcSec::FnFactory Class Reference

Interface for function factory, which is in charge of creating [Function](#) object according to function type.

```
#include <FnFactory.h>
```

Public Member Functions

- virtual [Function](#) * **createFn** (const std::string &type)=0

Protected Attributes

- FnMap **fnmap**

5.50.1 Detailed Description

Interface for function factory, which is in charge of creating [Function](#) object according to function type.

The documentation for this class was generated from the following file:


- FnFactory.h

5.51 ArcSec::Function Class Reference

Interface for function, which is in charge of evaluating two [AttributeValue](#).

```
#include <Function.h>
```

Inheritance diagram for ArcSec::Function::



Public Member Functions

- **Function** (std::string, std::string)
- virtual bool **evaluate** ([AttributeValue](#) *arg0, [AttributeValue](#) *arg1)=0

5.51.1 Detailed Description

Interface for function, which is in charge of evaluating two [AttributeValue](#).

The documentation for this class was generated from the following file:

- Function.h

5.52 Arc::InfoRegister Class Reference

Registration to ISIS interface.

```
#include <InfoRegister.h>
```

Public Member Functions

- **InfoRegister** ([Arc::XMLNode](#) &node, [Arc::Service](#) *service_)
- long int **getPeriod** (void)
- void **registration** (void)

5.52.1 Detailed Description

Registration to ISIS interface.

This class provides an interface for service to register itself in Information Indexing [Service](#).

The documentation for this class was generated from the following file:

- InfoRegister.h

5.53 Arc::InfoRegisters Class Reference

Hadling multiple registrations to ISISes.

```
#include <InfoRegister.h>
```

Public Member Functions

- [InfoRegisters](#) ([Arc::XMLNode](#) &cfg, [Arc::Service](#) *service_)

5.53.1 Detailed Description

Hadling multiple registrations to ISISes.

5.53.2 Constructor & Destructor Documentation

5.53.2.1 Arc::InfoRegisters::InfoRegisters ([Arc::XMLNode](#) & *cfg*, [Arc::Service](#) * *service_*)

Constructor creates [InfoRegister](#) objects according to configuration.

Inside cfg elements isis:[InfoRegister](#) are found and for each corresponding [InfoRegister](#) object is created. Those objects are destroyed in destructor of this class.

The documentation for this class was generated from the following file:


- InfoRegister.h

5.54 Arc::InformationContainer Class Reference

Information System document container and processor.

```
#include <InformationInterface.h>
```

Inheritance diagram for Arc::InformationContainer::



Public Member Functions

- [InformationContainer](#) ([XMLNode](#) doc, bool copy=false)
- [XMLNode Acquire](#) (void)
- void **Release** (void)
- void [Assign](#) ([XMLNode](#) doc, bool copy=false)

Protected Member Functions

- virtual void [Get](#) (const std::list< std::string > &path, [XMLNodeContainer](#) &result)
- virtual void **Get** ([XMLNode](#) xpath, [XMLNodeContainer](#) &result)

Protected Attributes

- [XMLNode doc_](#)

5.54.1 Detailed Description

Information System document container and processor.

This class inherits from [InformationInterface](#) and offers container for storing informational XML document.

5.54.2 Constructor & Destructor Documentation

5.54.2.1 Arc::InformationContainer::InformationContainer ([XMLNode](#) doc, bool copy = false)

Creates an instance with XML document . If is true this method makes a copy of for internal use.

5.54.3 Member Function Documentation

5.54.3.1 [XMLNode](#) Arc::InformationContainer::Acquire (void)

Get a lock on contained XML document. To be used in multi-threaded environment. Do not forget to release it with Release()

5.54.3.2 void Arc::InformationContainer::Assign ([XMLNode](#) *doc*, bool *copy* = false)

Replaces internal XML document with *.* If *is true* this method makes a copy of *for internal use*.

5.54.3.3 virtual void Arc::InformationContainer::Get (const std::list< std::string > & *path*, [XMLNodeContainer](#) & *result*) [protected, virtual]

This method is called by this object's Process method. Real implementation of this class should return (sub)tree of XML document. This method may be called multiple times per single Process call. Here is a set on XML element names specifying how to reach requested node(s).

Reimplemented from [Arc::InformationInterface](#).

5.54.4 Member Data Documentation**5.54.4.1 [XMLNode](#) Arc::InformationContainer::doc_** [protected]

Either link or container of XML document

The documentation for this class was generated from the following file:


- [InformationInterface.h](#)

5.55 Arc::InformationInterface Class Reference

Information System message processor.

```
#include <InformationInterface.h>
```

Inheritance diagram for Arc::InformationInterface::



Public Member Functions

- [InformationInterface](#) (bool safe=true)
- SOAPEnvelope * **Process** (SOAPEnvelope &in)

Protected Member Functions

- virtual void [Get](#) (const std::list< std::string > &path, [XMLNodeContainer](#) &result)
- virtual void **Get** ([XMLNode](#) xpath, [XMLNodeContainer](#) &result)

Protected Attributes

- Glib::Mutex [lock_](#)
- bool **to_lock_**

5.55.1 Detailed Description

Information System message processor.

This class provides callback for 2 operations of WS-ResourceProperties and convenient parsing/generation of corresponding SOAP messages. In a future it may extend range of supported specifications.

5.55.2 Constructor & Destructor Documentation

5.55.2.1 Arc::InformationInterface::InformationInterface (bool *safe* = true)

Constructor. If 'safe' is true all calls to Get will be locked.

5.55.3 Member Function Documentation

5.55.3.1 virtual void Arc::InformationInterface::Get (const std::list< std::string > & *path*, [XMLNodeContainer](#) & *result*) [protected, virtual]

This method is called by this object's Process method. Real implementation of this class should return (sub)tree of XML document. This method may be called multiple times per single Process call. Here is a set on XML element names specifying how to reach requested node(s).

Reimplemented in [Arc::InformationContainer](#).

5.55.4 Member Data Documentation

5.55.4.1 Glib::Mutex [Arc::InformationInterface::lock_](#) [protected]

Mutex used to protect access to Get methods in multi-threaded env.

The documentation for this class was generated from the following file:

- InformationInterface.h

5.56 Arc::InformationRequest Class Reference

Request for information in InfoSystem.

```
#include <InformationInterface.h>
```

Public Member Functions

- [InformationRequest](#) (void)
- [InformationRequest](#) (const std::list< std::string > &path)
- [InformationRequest](#) (const std::list< std::list< std::string > > &paths)
- [InformationRequest](#) ([XMLNode](#) query)
- **operator bool** (void)
- **bool operator!** (void)
- SOAPEnvelope * [SOAP](#) (void)

5.56.1 Detailed Description

Request for information in InfoSystem.

This is a convenience wrapper creating proper WS-ResourceProperties request targeted InfoSystem interface of service.

5.56.2 Constructor & Destructor Documentation

5.56.2.1 Arc::InformationRequest::InformationRequest (void)

Dummy constructor

5.56.2.2 Arc::InformationRequest::InformationRequest (const std::list< std::string > &path)

Request for attribute specified by elements of path. Currently only first element is used.

5.56.2.3 Arc::InformationRequest::InformationRequest (const std::list< std::list< std::string > > &paths)

Request for attribute specified by elements of paths. Currently only first element of every path is used.

5.56.2.4 Arc::InformationRequest::InformationRequest ([XMLNode](#) query)

Request for attributes specified by XPath query.

5.56.3 Member Function Documentation

5.56.3.1 SOAPEnvelope* Arc::InformationRequest::SOAP (void)

Returns generated SOAP message

The documentation for this class was generated from the following file:

- [InformationInterface.h](#)

5.57 Arc::InformationResponse Class Reference

Informational response from InfoSystem.

```
#include <InformationInterface.h>
```

Public Member Functions

- [InformationResponse](#) (SOAPEnvelope &soap)
- **operator bool** (void)
- **bool operator!** (void)
- std::list< [XMLNode](#) > [Result](#) (void)

5.57.1 Detailed Description

Informational response from InfoSystem.

This is a convenience wrapper analyzing WS-ResourceProperties response from InfoSystem interface of service.

5.57.2 Constructor & Destructor Documentation

5.57.2.1 Arc::InformationResponse::InformationResponse (SOAPEnvelope & soap)

Constructor parses WS-ResourceProperties response. Provided SOAPEnvelope object must be valid as long as this object is in use.

5.57.3 Member Function Documentation

5.57.3.1 std::list<[XMLNode](#)> Arc::InformationResponse::Result (void)

Returns set of attributes which were in SOAP message passed to constructor.

The documentation for this class was generated from the following file:


- InformationInterface.h

5.58 Arc::IntraProcessCounter Class Reference

A class for counters used by threads within a single process.

```
#include <IntraProcessCounter.h>
```

Inheritance diagram for Arc::IntraProcessCounter::



Public Member Functions

- [IntraProcessCounter](#) (int limit, int excess)
- virtual [~IntraProcessCounter](#) ()
- virtual int [getLimit](#) ()
- virtual int [setLimit](#) (int newLimit)
- virtual int [changeLimit](#) (int amount)
- virtual int [getExcess](#) ()
- virtual int [setExcess](#) (int newExcess)
- virtual int [changeExcess](#) (int amount)
- virtual int [getValue](#) ()
- virtual [CounterTicket reserve](#) (int amount=1, Glib::TimeVal duration=[ETERNAL](#), bool prioritized=false, Glib::TimeVal timeOut=[ETERNAL](#))

Protected Member Functions

- virtual void [cancel](#) (IDType reservationID)
- virtual void [extend](#) (IDType &reservationID, Glib::TimeVal &expiryTime, Glib::TimeVal duration=[ETERNAL](#))

5.58.1 Detailed Description

A class for counters used by threads within a single process.

This is a class for shared among different threads within a single process. See the [Counter](#) class for further information about counters and examples of usage.

5.58.2 Constructor & Destructor Documentation

5.58.2.1 Arc::IntraProcessCounter::IntraProcessCounter (int *limit*, int *excess*)

Creates an [IntraProcessCounter](#) with specified limit and excess.

This constructor creates a counter with the specified limit (amount of resources available for reservation) and excess limit (an extra amount of resources that may be used for prioritized reservations).

Parameters:

limit The limit of the counter.

excess The excess limit of the counter.

5.58.2.2 virtual Arc::IntraProcessCounter::~~IntraProcessCounter () [virtual]

Destructor.

This is the destructor of the [IntraProcessCounter](#) class. Does not need to do anything.

5.58.3 Member Function Documentation**5.58.3.1 virtual void Arc::IntraProcessCounter::cancel (IDType reservationID) [protected, virtual]**

Cancellation of a reservation.

This method cancels a reservation. It is called by the [CounterTicket](#) that corresponds to the reservation.

Parameters:

reservationID The identity number (key) of the reservation to cancel.

5.58.3.2 virtual int Arc::IntraProcessCounter::changeExcess (int amount) [virtual]

Changes the excess limit of the counter.

Changes the excess limit of the counter by adding a certain amount to the current excess limit.

Parameters:

amount The amount by which to change the excess limit.

Returns:

The new excess limit.

Implements [Arc::Counter](#).

5.58.3.3 virtual int Arc::IntraProcessCounter::changeLimit (int amount) [virtual]

Changes the limit of the counter.

Changes the limit of the counter by adding a certain amount to the current limit.

Parameters:

amount The amount by which to change the limit.

Returns:

The new limit.

Implements [Arc::Counter](#).

5.58.3.4 **virtual void Arc::IntraProcessCounter::extend (IDType & reservationID, Glib::TimeVal & expiryTime, Glib::TimeVal duration = ETERNAL)** [protected, virtual]

Extension of a reservation.

This method extends a reservation. It is called by the [CounterTicket](#) that corresponds to the reservation.

Parameters:

reservationID Used for input as well as output. Contains the identification number of the original reservation on entry and the new identification number of the extended reservation on exit.

expiryTime Used for input as well as output. Contains the expiry time of the original reservation on entry and the new expiry time of the extended reservation on exit.

duration The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

5.58.3.5 **virtual int Arc::IntraProcessCounter::getExcess ()** [virtual]

Returns the excess limit of the counter.

Returns the excess limit of the counter, i.e. by how much the usual limit may be exceeded by prioritized reservations.

Returns:

The excess limit.

Implements [Arc::Counter](#).

5.58.3.6 **virtual int Arc::IntraProcessCounter::getLimit ()** [virtual]

Returns the current limit of the counter.

This method returns the current limit of the counter, i.e. how many units can be reserved simultaneously by different threads without claiming high priority.

Returns:

The current limit of the counter.

Implements [Arc::Counter](#).

5.58.3.7 **virtual int Arc::IntraProcessCounter::getValue ()** [virtual]

Returns the current value of the counter.

Returns the current value of the counter, i.e. the number of unreserved units. Initially, the value is equal to the limit of the counter. When a reservation is made, the value is decreased. Normally, the value should never be negative, but this may happen if there are prioritized reservations. It can also happen if the limit is decreased after some reservations have been made, since reservations are never revoked.

Returns:

The current value of the counter.

Implements [Arc::Counter](#).

5.58.3.8 `virtual CounterTicket Arc::IntraProcessCounter::reserve (int amount = 1, Glib::TimeVal duration = ETERNAL, bool prioritized = false, Glib::TimeVal timeOut = ETERNAL) [virtual]`

Makes a reservation from the counter.

This method makes a reservation from the counter. If the current value of the counter is too low to allow for the reservation, the method blocks until the reservation is possible or times out.

Parameters:

amount The amount to reserve, default value is 1.

duration The duration of a self expiring reservation, default is that it lasts forever.

prioritized Whether this reservation is prioritized and thus allowed to use the excess limit.

timeOut The maximum time to block if the value of the counter is too low, default is to allow "eternal" blocking.

Returns:

A [CounterTicket](#) that can be queried about the status of the reservation as well as for cancellations and extensions.

Implements [Arc::Counter](#).

5.58.3.9 `virtual int Arc::IntraProcessCounter::setExcess (int newExcess) [virtual]`

Sets the excess limit of the counter.

This method sets a new excess limit for the counter.

Parameters:

newExcess The new excess limit, an absolute number.

Returns:

The new excess limit.

Implements [Arc::Counter](#).

5.58.3.10 `virtual int Arc::IntraProcessCounter::setLimit (int newLimit) [virtual]`

Sets the limit of the counter.

This method sets a new limit for the counter.

Parameters:

newLimit The new limit, an absolute number.

Returns:

The new limit.

Implements [Arc::Counter](#).

The documentation for this class was generated from the following file:

- IntraProcessCounter.h

5.59 Arc::Loader Class Reference

Creator of [Message](#) Component Chains ([MCC](#)).

```
#include <Loader.h>
```

Public Types

- typedef std::map< std::string, [MCC](#) * > **mcc_container_t**
- typedef std::map< std::string, [Service](#) * > **service_container_t**
- typedef std::map< std::string, [ArcSec::SecHandler](#) * > **sechandler_container_t**
- typedef std::map< std::string, [DMC](#) * > **dmc_container_t**
- typedef std::map< std::string, [ACC](#) * > **acc_container_t**
- typedef std::map< std::string, [Plexer](#) * > **plexer_container_t**

Public Member Functions

- [Loader](#) ([Config](#) *cfg)
- [~Loader](#) ()
- [MCC](#) * [operator\[\]](#) (const std::string &id)
- [ACC](#) * [getACC](#) (const std::string &id)

Static Public Attributes

- static [Logger](#) **logger**

Friends

- class **ChainContext**

5.59.1 Detailed Description

Creator of [Message](#) Component Chains ([MCC](#)).

This class processes XML configuration and creates message chains. Accepted configuration is defined by XML schema mcc.xsd. Supported components are of types [MCC](#), [Service](#) and [Plexer](#). [MCC](#) and [Service](#) are loaded from dynamic libraries. For [Plexer](#) only internal implementation is supported. This object is also a container for loaded componets. All components and chains are destroyed if this object is destroyed. Chains are created in 2 steps. First all components are loaded and corresponding objects are created. Constructors are supplied with corresponding configuration subtrees. During next step components are linked together by calling their Next() methods. Each call creates labeled link to next component in a chain. 2 step method has an advantage over single step because it allows loops in chains and makes loading procedure more simple. But that also means during short period of time components are only partly configured. Components in such state must produce proper error response if [Message](#) arrives. Note: Current implementation requires all components and links to be labeled. All labels must be unique. Future implementation will be able to assign labels automatically.

5.59.2 Constructor & Destructor Documentation

5.59.2.1 Arc::Loader::Loader ([Config](#) * *cfg*)

Constructor that takes whole XML configuration and creates component chains

5.59.2.2 Arc::Loader::~~Loader ()

Destructor destroys all components created by constructor

5.59.3 Member Function Documentation

5.59.3.1 ACC* Arc::Loader::getACC (const std::string & *id*)

Access entry ACCs. Those are components exposed for external access using 'entry' attribute

5.59.3.2]

[MCC](#)* Arc::Loader::operator[] (const std::string & *id*)

Access entry MCCs in chains. Those are components exposed for external access using 'entry' attribute

The documentation for this class was generated from the following file:

- Loader.h

5.60 Arc::loader_descriptor Struct Reference

Identifier of plugin.

```
#include <LoaderFactory.h>
```

Public Attributes

- const char * **name**
- int **version**
- void *(* **get_instance**)(Arc::Config *cfg, Arc::ChainContext *ctx)

5.60.1 Detailed Description

Identifier of plugin.

This structure describes set of elements stored in shared library. It contains name of plugin, version number and pointer to function which creates an instance of object.

The documentation for this struct was generated from the following file:


- LoaderFactory.h

5.61 Arc::LoaderFactory Class Reference

Plugin handler.

```
#include <LoaderFactory.h>
```

Inheritance diagram for Arc::LoaderFactory::



Public Member Functions

- void [load_all_instances](#) (const std::string &libname)

Protected Member Functions

- [LoaderFactory](#) ([Config](#) *cfg, const std::string &id)
- void * [get_instance](#) (const std::string &name, [Arc::Config](#) *cfg, [Arc::ChainContext](#) *ctx)
- void * [get_instance](#) (const std::string &name, int version, [Arc::Config](#) *cfg, [Arc::ChainContext](#) *ctx)
- void * [get_instance](#) (const std::string &name, int min_version, int max_version, [Arc::Config](#) *cfg, [Arc::ChainContext](#) *ctx)

5.61.1 Detailed Description

Plugin handler.

This class handles shared libraries containing loadable classes

5.61.2 Constructor & Destructor Documentation

5.61.2.1 Arc::LoaderFactory::LoaderFactory ([Config](#) *cfg, const std::string &id) [protected]

Constructor - accepts configuration (not yet used) meant to tune loading of modules.

5.61.3 Member Function Documentation

5.61.3.1 void* Arc::LoaderFactory::get_instance (const std::string &name, [Arc::Config](#) *cfg, [Arc::ChainContext](#) *ctx) [protected]

These methods load shared library named lib' name', locates symbol named 'id_' representing descriptor of elements and calls it's constructor function. Supplied configuration tree and context are passed to constructor. Returns created instance. This classes must not be used directly. Inheriting classes must implement it with proper type casting.

Reimplemented in [Arc::ACCFactory](#), [Arc::DMCFactory](#), [Arc::MCCFactory](#), [Arc::PDPFactory](#), [Arc::SecHandlerFactory](#), and [Arc::ServiceFactory](#).

5.61.3.2 void Arc::LoaderFactory::load_all_instances (const std::string & libname)

Loads shared library named 'libname' and identifies all elements it provides. Subsequent calls to [get_instance\(\)](#) methods will be able to locate needed elements even if they are not stored in library named after element name.

The documentation for this class was generated from the following file:


- LoaderFactory.h

5.62 Arc::LogDestination Class Reference

A base class for log destinations.

```
#include <Logger.h>
```

Inheritance diagram for Arc::LogDestination::



Public Member Functions

- virtual void [log](#) (const [LogMessage](#) &message)=0

Protected Member Functions

- [LogDestination](#) ()
- [LogDestination](#) (const std::string &locale)

Protected Attributes

- std::string [locale](#)

5.62.1 Detailed Description

A base class for log destinations.

This class defines an interface for LogDestinations. [LogDestination](#) objects will typically contain synchronization mechanisms and should therefore never be copied.

5.62.2 Constructor & Destructor Documentation

5.62.2.1 Arc::LogDestination::LogDestination () [protected]

Default constructor.

This destination will use the default locale.

5.62.2.2 Arc::LogDestination::LogDestination (const std::string & *locale*) [protected]

Constructor with specific locale.

This destination will use the specified locale.

5.62.3 Member Function Documentation

5.62.3.1 `virtual void Arc::LogDestination::log (const LogMessage & message)` [pure virtual]

Logs a [LogMessage](#) to this [LogDestination](#).

Implemented in [Arc::LogStream](#).

The documentation for this class was generated from the following file:

- `Logger.h`

5.63 Arc::Logger Class Reference

A logger class.

```
#include <Logger.h>
```

Public Member Functions

- [Logger](#) ([Logger](#) &parent, const std::string &subdomain)
- [Logger](#) ([Logger](#) &parent, const std::string &subdomain, [LogLevel](#) threshold)
- void [addDestination](#) ([LogDestination](#) &destination)
- void [removeDestinations](#) (void)
- void [setThreshold](#) ([LogLevel](#) threshold)
- [LogLevel](#) [getThreshold](#) () const
- void [msg](#) ([LogMessage](#) message)
- void [msg](#) ([LogLevel](#) level, const std::string &str)
- template<class T0> void [msg](#) ([LogLevel](#) level, const std::string &str, const T0 &t0)
- template<class T0, class T1> void [msg](#) ([LogLevel](#) level, const std::string &str, const T0 &t0, const T1 &t1)
- template<class T0, class T1, class T2> void [msg](#) ([LogLevel](#) level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2)
- template<class T0, class T1, class T2, class T3> void [msg](#) ([LogLevel](#) level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3)
- template<class T0, class T1, class T2, class T3, class T4> void [msg](#) ([LogLevel](#) level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3, const T4 &t4)
- template<class T0, class T1, class T2, class T3, class T4, class T5> void [msg](#) ([LogLevel](#) level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3, const T4 &t4, const T5 &t5)
- template<class T0, class T1, class T2, class T3, class T4, class T5, class T6> void [msg](#) ([LogLevel](#) level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3, const T4 &t4, const T5 &t5, const T6 &t6)
- template<class T0, class T1, class T2, class T3, class T4, class T5, class T6, class T7> void [msg](#) ([LogLevel](#) level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3, const T4 &t4, const T5 &t5, const T6 &t6, const T7 &t7)

Static Public Member Functions

- static [Logger](#) & [getRootLogger](#) ()

5.63.1 Detailed Description

A logger class.

This class defines a [Logger](#) to which LogMessages can be sent.

Every [Logger](#) (except for the rootLogger) has a parent [Logger](#). The domain of a [Logger](#) (a string that indicates the origin of LogMessages) is composed by adding a subdomain to the domain of its parent [Logger](#).

A [Logger](#) also has a threshold. Every [LogMessage](#) that have a level that is greater than or equal to the threshold is forwarded to any [LogDestination](#) connected to this [Logger](#) as well as to the parent [Logger](#).

Typical usage of the [Logger](#) class is to declare a global [Logger](#) object for each library/module/component to be used by all classes and methods there.

5.63.2 Constructor & Destructor Documentation

5.63.2.1 Arc::Logger::Logger ([Logger](#) & *parent*, const std::string & *subdomain*)

Creates a logger.

Creates a logger. The threshold is inherited from its parent [Logger](#).

Parameters:

parent The parent [Logger](#) of the new [Logger](#).

subdomain The subdomain of the new logger.

5.63.2.2 Arc::Logger::Logger ([Logger](#) & *parent*, const std::string & *subdomain*, [LogLevel](#) *threshold*)

Creates a logger.

Creates a logger.

Parameters:

parent The parent [Logger](#) of the new [Logger](#).

subdomain The subdomain of the new logger.

threshold The threshold of the new logger.

5.63.3 Member Function Documentation

5.63.3.1 void Arc::Logger::addDestination ([LogDestination](#) & *destination*)

Adds a [LogDestination](#).

Adds a [LogDestination](#) to which to forward LogMessages sent to this logger (if they pass the threshold). Since LogDestinatoin should not be copied, the new [LogDestination](#) is passed by reference and a pointer to it is kept for later use. It is therefore important that the [LogDestination](#) passed to this [Logger](#) exists at least as long as the [Logger](#) itself.

5.63.3.2 static [Logger](#)& Arc::Logger::getRootLogger () [static]

The root [Logger](#).

This is the root [Logger](#). It is an ancestor of any other [Logger](#) and allways exists.

5.63.3.3 [LogLevel](#) Arc::Logger::getThreshold () const

Returns the threshold.

Returns the threshold.

Returns:

The threshold of this [Logger](#).

5.63.3.4 void Arc::Logger::msg (LogLevel level, const std::string & str) [inline]

Logs a message text.

Logs a message text string at the specified LogLevel. This is a convenience method to save some typing. It simply creates a [LogMessage](#) and sends it to the other [msg\(\)](#) method.

Parameters:

level The level of the message.

str The message text.

5.63.3.5 void Arc::Logger::msg (LogMessage message)

Sends a [LogMessage](#).

Sends a [LogMessage](#).

Parameters:

The [LogMessage](#) to send.

5.63.3.6 void Arc::Logger::removeDestinations (void)

Removes all LogDestinations.

5.63.3.7 void Arc::Logger::setThreshold (LogLevel threshold)

Sets the threshold.

This method sets the threshold of the [Logger](#). Any message sent to this [Logger](#) that has a level below this threshold will be discarded.

Parameters:

The threshold

The documentation for this class was generated from the following file:

- [Logger.h](#)

5.64 Arc::LogMessage Class Reference

A class for log messages.

```
#include <Logger.h>
```

Public Member Functions

- [LogMessage](#) ([LogLevel](#) level, const [IString](#) &message)
- [LogMessage](#) ([LogLevel](#) level, const [IString](#) &message, const [std::string](#) &identifier)
- [LogLevel](#) [getLevel](#) () const

Protected Member Functions

- void [setIdentifier](#) ([std::string](#) identifier)

Friends

- class [Logger](#)
- [std::ostream](#) & [operator<<](#) ([std::ostream](#) &os, const [LogMessage](#) &message)

5.64.1 Detailed Description

A class for log messages.

This class is used to represent log messages internally. It contains the time the message was created, its level, from which domain it was sent, an identifier and the message text itself.

5.64.2 Constructor & Destructor Documentation

5.64.2.1 Arc::LogMessage::LogMessage ([LogLevel](#) level, const [IString](#) & message)

Creates a [LogMessage](#) with the specified level and message text.

This constructor creates a [LogMessage](#) with the specified level and message text. The time is set automatically, the domain is set by the [Logger](#) to which the [LogMessage](#) is sent and the identifier is composed from the process ID and the address of the Thread object corresponding to the calling thread.

Parameters:

level The level of the [LogMessage](#).

message The message text.

5.64.2.2 Arc::LogMessage::LogMessage ([LogLevel](#) level, const [IString](#) & message, const [std::string](#) & identifier)

Creates a [LogMessage](#) with the specified attributes.

This constructor creates a [LogMessage](#) with the specified level, message text and identifier. The time is set automatically and the domain is set by the [Logger](#) to which the [LogMessage](#) is sent.

Parameters:

- level* The level of the [LogMessage](#).
message The message text.
ident The identifier of the [LogMessage](#).

5.64.3 Member Function Documentation**5.64.3.1 [LogLevel](#) Arc::LogMessage::getLevel () const**

Returns the level of the [LogMessage](#).

Returns the level of the [LogMessage](#).

Returns:

The level of the [LogMessage](#).

5.64.3.2 void Arc::LogMessage::setIdentifier (std::string *identifier*) [protected]

Sets the identifier of the [LogMessage](#).

The purpose of this method is to allow subclasses (in case there are any) to set the identifier of a [LogMessage](#).

Parameters:

The identifier.

5.64.4 Friends And Related Function Documentation**5.64.4.1 friend class [Logger](#) [friend]**

The [Logger](#) class is a friend.

The [Logger](#) class must have some privileges (e.g. ability to call the setDomain() method), therefore it is a friend.

5.64.4.2 std::ostream& operator<< (std::ostream & *os*, const [LogMessage](#) & *message*) [friend]

Printing of LogMessages to ostreams.

Output operator so that LogMessages can be printed conveniently by LogDestinations.

The documentation for this class was generated from the following file:


- [Logger.h](#)

5.65 Arc::LogStream Class Reference

A class for logging to ostreams.

```
#include <Logger.h>
```

Inheritance diagram for Arc::LogStream::



Public Member Functions

- [LogStream](#) (std::ostream &destination)
- [LogStream](#) (std::ostream &destination, const std::string &locale)
- virtual void [log](#) (const [LogMessage](#) &message)

5.65.1 Detailed Description

A class for logging to ostreams.

This class is used for logging to ostreams (cout, cerr, files). It provides synchronization in order to prevent different LogMessages to appear mixed with each other in the stream. In order not to break the synchronization, LogStreams should never be copied. Therefore the copy constructor and assignment operator are private. Furthermore, it is important to keep a [LogStream](#) object as long as the [Logger](#) to which it has been registered.

5.65.2 Constructor & Destructor Documentation

5.65.2.1 Arc::LogStream::LogStream (std::ostream & *destination*)

Creates a [LogStream](#) connected to an ostream.

Creates a [LogStream](#) connected to the specified ostream. In order not to break synchronization, it is important not to connect more than one [LogStream](#) object to a certain stream.

Parameters:

destination The ostream to which to write LogMessages.

5.65.2.2 Arc::LogStream::LogStream (std::ostream & *destination*, const std::string & *locale*)

Creates a [LogStream](#) connected to an ostream.

Creates a [LogStream](#) connected to the specified ostream. The output will be localised to the specified locale.

5.65.3 Member Function Documentation

5.65.3.1 virtual void Arc::LogStream::log (const [LogMessage](#) & *message*) [virtual]

Writes a [LogMessage](#) to the stream.

This method writes a [LogMessage](#) to the ostream that is connected to this [LogStream](#) object. It is synchronized so that not more than one [LogMessage](#) can be written at a time.

Parameters:

message The [LogMessage](#) to write.

Implements [Arc::LogDestination](#).

The documentation for this class was generated from the following file:


- [Logger.h](#)

5.66 ArcSec::MatchFunction Class Reference

Evaluate whether arg1 (value in regular expression) matched arg0 (lable in regular expression).

```
#include <MatchFunction.h>
```

Inheritance diagram for ArcSec::MatchFunction::



Public Member Functions

- **MatchFunction** (std::string functionName, std::string argumentType)
- virtual bool **evaluate** ([AttributeValue](#) *arg0, [AttributeValue](#) *arg1)

Static Public Member Functions

- static std::string [getFunctionName](#) (std::string datatype)

5.66.1 Detailed Description

Evaluate whether arg1 (value in regular expression) matched arg0 (lable in regular expression).

5.66.2 Member Function Documentation

5.66.2.1 static std::string ArcSec::MatchFunction::getFunctionName (std::string *datatype*)
[static]

help function to get the FunctionName

The documentation for this class was generated from the following file:


- MatchFunction.h

5.67 Arc::MCC Class Reference

[Message](#) Chain Component - base class for every [MCC](#) plugin.

```
#include <MCC.h>
```

Inheritance diagram for Arc::MCC::



Public Member Functions

- [MCC](#) ([Arc::Config](#) *)
- virtual void [Next](#) ([Arc::MCCInterface](#) *next, const std::string &label="")
- virtual void [AddSecHandler](#) ([Arc::Config](#) *cfg, [ArcSec::SecHandler](#) *sechandler, const std::string &label="")
- virtual void [Unlink](#) ()
- virtual [Arc::MCC_Status](#) process ([Arc::Message](#) &, [Arc::Message](#) &)

Protected Member Functions

- [Arc::MCCInterface](#) * [Next](#) (const std::string &label="")
- bool [ProcessSecHandlers](#) ([Arc::Message](#) &message, const std::string &label="")

Protected Attributes

- std::map< std::string, [Arc::MCCInterface](#) * > [next_](#)
- std::map< std::string, std::list< [ArcSec::SecHandler](#) * > > [sechandlers_](#)

Static Protected Attributes

- static [Arc::Logger](#) [logger](#)

5.67.1 Detailed Description

[Message](#) Chain Component - base class for every [MCC](#) plugin.

This is partially virtual class which defines interface and common functionality for every [MCC](#) plugin needed for managing of component in a chain.

5.67.2 Constructor & Destructor Documentation

5.67.2.1 `Arc::MCC::MCC (Arc::Config *)` [inline]

Example contructor - [MCC](#) takes at least it's configuration subtree

5.67.3 Member Function Documentation

5.67.3.1 `virtual void Arc::MCC::AddSecHandler (Arc::Config * cfg, ArcSec::SecHandler * sechandler, const std::string & label = "")` [virtual]

Add security components/handlers to this [MCC](#). Security handlers are stacked into a few queues with each queue identified by its label. The queue labelled 'incoming' is executed for every 'request' message after the message is processed by the [MCC](#) on the service side and before processing on the client side. The queue labelled 'outgoing' is run for response message before it is processed by [MCC](#) algorithms on the service side and after processing on the client side. Those labels are just a matter of agreement and some MCCs may implement different queues executed at various message processing steps.

5.67.3.2 `virtual void Arc::MCC::Next (Arc::MCCInterface * next, const std::string & label = "")` [virtual]

Add reference to next [MCC](#) in chain. This method is called by [Loader](#) for every potentially labeled link to next component which implements [MCCInterface](#). If next is NULL corresponding link is removed.

Reimplemented in [Arc::Plexer](#).

5.67.3.3 `virtual Arc::MCC_Status Arc::MCC::process (Arc::Message &, Arc::Message &)` [inline, virtual]

Dummy [Message](#) processing method. Just a placeholder.

Implements [Arc::MCCInterface](#).

Reimplemented in [Arc::Plexer](#).

5.67.3.4 `bool Arc::MCC::ProcessSecHandlers (Arc::Message & message, const std::string & label = "")` [protected]

Executes security handlers of specified queue. Returns true if the message is authorized for further processing or if there are no security handlers which implement authorization functionality. This is a convenience method and has to be called by the implementation of the [MCC](#).

5.67.3.5 `virtual void Arc::MCC::Unlink ()` [virtual]

Removing all links. Useful for destroying chains.

5.67.4 Member Data Documentation

5.67.4.1 `Arc::Logger Arc::MCC::logger` [static, protected]

A logger for MCCs.

A logger intended to be the parent of loggers in the different MCCs.

Reimplemented in [Arc::Plexer](#).

5.67.4.2 `std::map<std::string, Arc::MCCInterface *> Arc::MCC::next_` [protected]

Set of labeled "next" components. Each implemented [MCC](#) must call `process()` method of corresponding [MCCInterface](#) from this set in own `process()` method.

5.67.4.3 `std::map<std::string, std::list<ArcSec::SecHandler *> > Arc::MCC::sechandlers_` [protected]

Set of labeled authentication and authorization handlers. [MCC](#) calls sequence of handlers at specific point depending on associated identifier. In most cases those are "in" and "out" for incoming and outgoing messages correspondingly.

The documentation for this class was generated from the following file:

- `MCC.h`

5.68 mcc_descriptor Struct Reference

Identifier of Message Chain Componet (MCC) plugin.

```
#include <MCCLoader.h>
```

Public Attributes

- const char * **name**
- int **version**
- [Arc::MCC](#) *(* **get_instance**)([Arc::Config](#) *cfg, [Arc::ChainContext](#) *ctx)

5.68.1 Detailed Description

Identifier of Message Chain Componet (MCC) plugin.

This structure describes one of the MCCs stored in a shared library. It contains name of plugin, version number and pointer to function which creates an instance of an object inherited from the MCC class.

The documentation for this struct was generated from the following file:

- MCCLoader.h

5.69 Arc::MCC_Status Class Reference

A class for communication of [MCC](#) processing results.

```
#include <MCC_Status.h>
```

Public Member Functions

- [MCC_Status](#) ([StatusKind](#) kind=STATUS_UNDEFINED, const std::string &origin="???", const std::string &explanation="No explanation.")
- bool [isOk](#) () const
- [StatusKind](#) [getKind](#) () const
- const std::string & [getOrigin](#) () const
- const std::string & [getExplanation](#) () const
- [operator std::string](#) () const
- [operator bool](#) (void) const
- bool [operator!](#) (void) const

5.69.1 Detailed Description

A class for communication of [MCC](#) processing results.

This class is used to communicate result status between MCCs. It contains a status kind, a string specifying the origin ([MCC](#)) of the status object and an explanation.

5.69.2 Constructor & Destructor Documentation

5.69.2.1 Arc::MCC_Status::MCC_Status ([StatusKind](#) kind = STATUS_UNDEFINED, const std::string & origin = "???", const std::string & explanation = "No explanation.")

The constructor.

Creates a [MCC_Status](#) object.

Parameters:

- kind* The StatusKind (default: STATUS_UNDEFINED)
origin The origin [MCC](#) (default: "??")
explanation An explanation (default: "No explanation.")

5.69.3 Member Function Documentation

5.69.3.1 const std::string& Arc::MCC_Status::getExplanation () const

Returns an explanation.

This method returns an explanation of this object.

Returns:

An explanation of this object.

5.69.3.2 StatusKind Arc::MCC_Status::getKind () const

Returns the status kind.

Returns the status kind of this object.

Returns:

The status kind of this object.

5.69.3.3 const std::string& Arc::MCC_Status::getOrigin () const

Returns the origin.

This method returns a string specifying the origin [MCC](#) of this object.

Returns:

A string specifying the origin [MCC](#) of this object.

5.69.3.4 bool Arc::MCC_Status::isOk () const

Is the status kind ok?

This method returns true iff the status kind of this object is STATUS_OK

Returns:

true iff kind==STATUS_OK

5.69.3.5 Arc::MCC_Status::operator bool (void) const [inline]

Is the status kind ok?

This method returns true iff the status kind of this object is STATUS_OK

Returns:

true iff kind==STATUS_OK

5.69.3.6 Arc::MCC_Status::operator std::string () const

Conversion to string.

This operator converts a [MCC_Status](#) object to a string.

5.69.3.7 bool Arc::MCC_Status::operator! (void) const [inline]

not operator

Returns true if the status kind is not OK

Returns:

true if kind!=STATUS_OK

The documentation for this class was generated from the following file:


- MCC_Status.h

5.70 Arc::MCCFactory Class Reference

MCC Plugins handler.

```
#include <MCCFactory.h>
```

Inheritance diagram for Arc::MCCFactory::



Public Member Functions

- [MCCFactory](#) ([Config](#) *cfg)
- [MCC](#) * [get_instance](#) (const std::string &name, [Config](#) *cfg, [ChainContext](#) *ctx)
- [MCC](#) * [get_instance](#) (const std::string &name, int version, [Config](#) *cfg, [ChainContext](#) *ctx)
- [MCC](#) * [get_instance](#) (const std::string &name, int min_version, int max_version, [Config](#) *cfg, [ChainContext](#) *ctx)

5.70.1 Detailed Description

MCC Plugins handler.

This class handles shared libraries containing MCCs

5.70.2 Constructor & Destructor Documentation

5.70.2.1 Arc::MCCFactory::MCCFactory ([Config](#) * *cfg*)

Constructor - accepts configuration (not yet used) meant to tune loading of module.

5.70.3 Member Function Documentation

5.70.3.1 [MCC](#)* Arc::MCCFactory::get_instance (const std::string & *name*, [Config](#) * *cfg*, [ChainContext](#) * *ctx*)

These methods load shared library named lib'name', locate symbol representing descriptor of [MCC](#) and calls it's constructor function. Supplied configuration tree is passed to constructor. Returns created [MCC](#) instance.

Reimplemented from [Arc::LoaderFactory](#).

The documentation for this class was generated from the following file:


- MCCFactory.h

5.71 Arc::MCCInterface Class Reference

Interface for communication between [MCC](#), [Service](#) and [Plexer](#) objects.

```
#include <MCC.h>
```

Inheritance diagram for Arc::MCCInterface::



Public Member Functions

- virtual [Arc::MCC_Status](#) process ([Arc::Message](#) &request, [Arc::Message](#) &response)=0

5.71.1 Detailed Description

Interface for communication between [MCC](#), [Service](#) and [Plexer](#) objects.

The Interface consists of the method [process\(\)](#) which is called by the previous [MCC](#) in the chain. For memory management policies please read the description of the [Message](#) class.

5.71.2 Member Function Documentation

5.71.2.1 virtual [Arc::MCC_Status](#) Arc::MCCInterface::process ([Arc::Message](#) & request, [Arc::Message](#) & response) [pure virtual]

Method for processing of requests and responses. This method is called by preceeding [MCC](#) in chain when a request needs to be processed. This method must call similar method of next [MCC](#) in chain unless any failure happens. Result returned by call to next [MCC](#) should be processed and passed back to previous [MCC](#). In case of failure this method is expected to generate valid error response and return it back to previous [MCC](#) without calling the next one.

Parameters:

request The request that needs to be processed.

response A [Message](#) object that will contain the response of the request when the method returns.

Returns:

An object representing the status of the call.

Implemented in [Arc::Plexer](#), and [Arc::MCC](#).

The documentation for this class was generated from the following file:


- MCC.h

5.72 Arc::MD5Sum Class Reference

Implementation of MD5 checksum.

```
#include <CheckSum.h>
```

Inheritance diagram for Arc::MD5Sum::



Public Member Functions

- virtual void **start** (void)
- virtual void **add** (void *buf, unsigned long long int len)
- virtual void **end** (void)
- virtual void **result** (unsigned char *&res, unsigned int &len) const
- virtual int **print** (char *buf, int len) const
- virtual void **scan** (const char *buf)
- virtual **operator bool** (void) const
- virtual bool **operator!** (void) const

5.72.1 Detailed Description

Implementation of MD5 checksum.

The documentation for this class was generated from the following file:

- CheckSum.h

5.73 Arc::Message Class Reference

Object being passed through chain of MCCs.

```
#include <Message.h>
```

Public Member Functions

- [Message](#) (void)
- [Message](#) ([Message](#) &msg)
- [Message](#) (long msg_ptr_addr)
- [~Message](#) (void)
- [Message](#) & [operator=](#) ([Message](#) &msg)
- [MessagePayload](#) * [Payload](#) (void)
- [MessagePayload](#) * [Payload](#) ([MessagePayload](#) *payload)
- [MessageAttributes](#) * [Attributes](#) (void)
- void [Attributes](#) ([MessageAttributes](#) *attr)
- [MessageAuth](#) * [Auth](#) (void)
- void [Auth](#) ([MessageAuth](#) *auth)
- [MessageContext](#) * [Context](#) (void)
- [MessageAuthContext](#) * [AuthContext](#) (void)
- void [Context](#) ([MessageContext](#) *ctx)
- void [AuthContext](#) ([MessageAuthContext](#) *auth_ctx)

5.73.1 Detailed Description

Object being passed through chain of MCCs.

An instance of this class refers to objects with main content ([MessagePayload](#)), authentication/authorization information ([MessageAuth](#)) and common purpose attributes ([MessageAttributes](#)). [Message](#) class does not manage pointers to objects and their content. It only serves for grouping those objects. [Message](#) objects are supposed to be processed by MCCs and Services implementing [MCCInterface](#) method process(). All objects constituting content of [Message](#) object are subject to following policies:

1. All objects created inside call to process() method using new command must be explicitly destroyed within same call using delete command with following exceptions. a) Objects which are assigned to 'response' [Message](#). b) Objects whose management is completely acquired by objects assigned to 'response' [Message](#).
2. All objects not created inside call to process() method are not explicitly destroyed within that call with following exception. a) Objects which are part of 'response' Method returned from call to next's process() method. Unless those objects are passed further to calling process(), of course.
3. It is not allowed to make 'response' point to same objects as 'request' does on entry to process() method. That is needed to avoid double destruction of same object. (Note: if in a future such need arises it may be solved by storing additional flags in [Message](#) object).
4. It is allowed to change content of pointers of 'request' [Message](#). Calling process() method must not rely on that object to stay intact.
5. Called process() method should either fill 'response' [Message](#) with pointers to valid objects or to keep them intact. This makes it possible for calling process() to preload 'response' with valid error message.

5.73.2 Constructor & Destructor Documentation

5.73.2.1 `Arc::Message::Message (void)` [inline]

Dummy constructor

5.73.2.2 `Arc::Message::Message (Message & msg)` [inline]

Copy constructor. Ensures shallow copy.

5.73.2.3 `Arc::Message::Message (long msg_ptr_addr)`

Copy constructor. Used by language bindings

5.73.2.4 `Arc::Message::~~Message (void)` [inline]

Destructor does not affect referred objects except those created internally

5.73.3 Member Function Documentation

5.73.3.1 `MessageAttributes* Arc::Message::Attributes (void)` [inline]

Returns a pointer to the current attributes object or creates it if no attributes object has been assigned.

5.73.3.2 `MessageAuth* Arc::Message::Auth (void)` [inline]

Returns a pointer to the current authentication/authorization object or creates it if no object has been assigned.

5.73.3.3 `void Arc::Message::AuthContext (MessageAuthContext * auth_ctx)` [inline]

Assigns auth* context object

5.73.3.4 `MessageAuthContext* Arc::Message::AuthContext (void)` [inline]

Returns a pointer to the current auth* context object or creates it if no object has been assigned.

5.73.3.5 `void Arc::Message::Context (MessageContext * ctx)` [inline]

Assigns message context object

5.73.3.6 `MessageContext* Arc::Message::Context (void)` [inline]

Returns a pointer to the current context object or creates it if no object has been assigned. Last case should happen only if first [MCC](#) in a chain is connectionless like one implementing UDP protocol.

5.73.3.7 Message& Arc::Message::operator= (Message & msg) [inline]

Assignment. Ensures shallow copy.

5.73.3.8 MessagePayload* Arc::Message::Payload (MessagePayload * payload) [inline]

Replaces payload with new one. Returns the old one.

5.73.3.9 MessagePayload* Arc::Message::Payload (void) [inline]

Returns pointer to current payload or NULL if no payload assigned.

The documentation for this class was generated from the following file:

- Message.h

5.74 Arc::MessageAttributes Class Reference

A class for storage of attribute values.

```
#include <MessageAttributes.h>
```

Public Member Functions

- [MessageAttributes](#) ()
- void [set](#) (const std::string &key, const std::string &value)
- void [add](#) (const std::string &key, const std::string &value)
- void [removeAll](#) (const std::string &key)
- void [remove](#) (const std::string &key, const std::string &value)
- int [count](#) (const std::string &key) const
- const std::string & [get](#) (const std::string &key) const
- [AttributeIterator](#) [getAll](#) (const std::string &key) const
- [AttributeIterator](#) [getAll](#) (void) const

Protected Attributes

- [AttrMap](#) [attributes_](#)

5.74.1 Detailed Description

A class for storage of attribute values.

This class is used to store attributes of messages. All attribute keys and their corresponding values are stored as strings. Any key or value that is not a string must thus be represented as a string during storage. Furthermore, an attribute is usually a key-value pair with a unique key, but there may also be multiple such pairs with equal keys.

The key of an attribute is composed by the name of the [Message](#) Chain Component ([MCC](#)) which produce it and the name of the attribute itself with a colon (:) in between, i.e. MCC_Name:Attribute_Name. For example, the key of the "Content-Length" attribute of the HTTP [MCC](#) is thus "HTTP:Content-Length".

There are also "global attributes", which may be produced by different MCCs depending on the configuration. The keys of such attributes are NOT prefixed by the name of the producing [MCC](#). Before any new global attribute is introduced, it must be agreed upon by the core development team and added below. The global attributes decided so far are:

- Request-URI Identifies the service to which the message shall be sent. This attribute is produced by e.g. the HTTP [MCC](#) and used by the plexer for routing the message to the appropriate service.

5.74.2 Constructor & Destructor Documentation

5.74.2.1 Arc::MessageAttributes::MessageAttributes ()

The default constructor.

This is the default constructor of the [MessageAttributes](#) class. It constructs an empty object that initially contains no attributes.

5.74.3 Member Function Documentation

5.74.3.1 void Arc::MessageAttributes::add (const std::string & *key*, const std::string & *value*)

Adds a value to an attribute.

This method adds a new value to an attribute. Any previous value will be preserved, i.e. the attribute may become multiple valued.

Parameters:

key The key of the attribute.

value The (new) value of the attribute.

5.74.3.2 int Arc::MessageAttributes::count (const std::string & *key*) const

Returns the number of values of an attribute.

Returns the number of values of an attribute that matches a certain key.

Parameters:

key The key of the attribute for which to count values.

Returns:

The number of values that corresponds to the key.

5.74.3.3 const std::string& Arc::MessageAttributes::get (const std::string & *key*) const

Returns the value of a single-valued attribute.

This method returns the value of a single-valued attribute. If the attribute is not single valued (i.e. there is no such attribute or it is a multiple-valued attribute) an empty string is returned.

Parameters:

key The key of the attribute for which to return the value.

Returns:

The value of the attribute.

5.74.3.4 [AttributeIterator](#) Arc::MessageAttributes::getAll (void) const

Access all value and attributes.

5.74.3.5 [AttributeIterator](#) Arc::MessageAttributes::getAll (const std::string & *key*) const

Access the value(s) of an attribute.

This method returns an [AttributeIterator](#) that can be used to access the values of an attribute.

Parameters:

key The key of the attribute for which to return the values.

Returns:

An [AttributeIterator](#) for access of the values of the attribute.

5.74.3.6 void Arc::MessageAttributes::remove (const std::string & key, const std::string & value)

Removes one value of an attribute.

This method removes a certain value from the attribute that matches a certain key.

Parameters:

key The key of the attribute from which the value shall be removed.

value The value to remove.

5.74.3.7 void Arc::MessageAttributes::removeAll (const std::string & key)

Removes all attributes with a certain key.

This method removes all attributes that match a certain key.

Parameters:

key The key of the attributes to remove.

5.74.3.8 void Arc::MessageAttributes::set (const std::string & key, const std::string & value)

Sets a unique value of an attribute.

This method removes any previous value of an attribute and sets the new value as the only value.

Parameters:

key The key of the attribute.

value The (new) value of the attribute.

5.74.4 Member Data Documentation**5.74.4.1 [AttrMap Arc::MessageAttributes::attributes_](#) [protected]**

Internal storage of attributes.

An AttrMap (multimap) in which all attributes (key-value pairs) are stored.

The documentation for this class was generated from the following file:


- MessageAttributes.h

5.75 Arc::MessageAuth Class Reference

Contains authenticity information, authorization tokens and decisions.

```
#include <MessageAuth.h>
```

Inheritance diagram for Arc::MessageAuth::



Public Member Functions

- void [set](#) (const std::string &key, [SecAttr](#) *value)
- void [remove](#) (const std::string &key)
- [SecAttr](#) * [get](#) (const std::string &key)
- [SecAttr](#) * [operator\[\]](#) (const std::string &key)
- bool [Export](#) ([SecAttr::Format](#) format, [XMLNode](#) &val) const
- [MessageAuth](#) * [Filter](#) (const std::list< std::string > selected_keys, const std::list< std::string > rejected_keys) const

5.75.1 Detailed Description

Contains authenticity information, authorization tokens and decisions.

This class only supports string keys and [SecAttr](#) values.

5.75.2 Member Function Documentation

5.75.2.1 bool Arc::MessageAuth::Export ([SecAttr::Format](#) format, [XMLNode](#) & val) const

Returns properly catenated attributes in specified format.

Content of XML node at is replaced with generated information if XML tree is empty. If tree at is not empty then [Export\(\)](#) tries to merge generated information to already existing like everything would be generated inside same [Export\(\)](#) method.

5.75.2.2 [MessageAuth](#)* Arc::MessageAuth::Filter (const std::list< std::string > selected_keys, const std::list< std::string > rejected_keys) const

Creates new instance of [MessageAuth](#) with attributes filtered.

In new instance all attributes with keys listed in are removed. If is not empty only corresponding attributes are transferred to new instance. Created instance does not own referred attributes. Hence parent instance must not be deleted as long as this one is in use.

5.75.2.3 [SecAttr](#)* Arc::MessageAuth::get (const std::string & key)

Retrieves reference to security attribute stored under specified key.

5.75.2.4]

[SecAttr](#)* Arc::MessageAuth::operator[] (const std::string & *key*) [inline]

Same as [MessageAuth::get](#).

5.75.2.5 void Arc::MessageAuth::remove (const std::string & *key*)

Deletes security attribute stored under specified key.

5.75.2.6 void Arc::MessageAuth::set (const std::string & *key*, [SecAttr](#) * *value*)

Adds/overwrites security attribute stored under specified key.

The documentation for this class was generated from the following file:


- MessageAuth.h

5.76 Arc::MessageAuthContext Class Reference

Handler for content of message auth* context.

```
#include <Message.h>
```

Inheritance diagram for Arc::MessageAuthContext::



5.76.1 Detailed Description

Handler for content of message auth* context.

This class is a container for authorization and authentication information. It gets associated with [Message](#) object usually by first [MCC](#) in a chain and is kept as long as connection persists.

The documentation for this class was generated from the following file:

- Message.h

5.77 Arc::MessageContext Class Reference

Handler for content of message context.

```
#include <Message.h>
```

Public Member Functions

- void [Add](#) (const std::string &name, [MessageContextElement](#) *element)
- [MessageContextElement](#) * [operator\[\]](#) (const std::string &id)

5.77.1 Detailed Description

Handler for content of message context.

This class is a container for objects derived from [MessageContextElement](#). It gets associated with [Message](#) object usually by first [MCC](#) in a chain and is kept as long as connection persists.

5.77.2 Member Function Documentation

5.77.2.1 void Arc::MessageContext::Add (const std::string & *name*, [MessageContextElement](#) * *element*)

Provided element is taken over by this class. It is remembered by it and destroyed when this class is destroyed.

The documentation for this class was generated from the following file:

- Message.h

5.78 Arc::MessageContextElement Class Reference

Top class for elements contained in message context.

```
#include <Message.h>
```

5.78.1 Detailed Description

Top class for elements contained in message context.

Objects of classes inherited with this one may be stored in [MessageContext](#) container.

The documentation for this class was generated from the following file:


- Message.h

5.79 Arc::MessagePayload Class Reference

Base class for content of message passed through chain.

```
#include <Message.h>
```

Inheritance diagram for Arc::MessagePayload::



5.79.1 Detailed Description

Base class for content of message passed through chain.

It's not intended to be used directly. Instead functional classes must be derived from it.

The documentation for this class was generated from the following file:


- Message.h

5.80 Arc::ModuleManager Class Reference

Manager of shared libraries.

```
#include <ModuleManager.h>
```

Inheritance diagram for Arc::ModuleManager::



Public Member Functions

- [ModuleManager](#) ([Arc::Config](#) *cfg)
- [Glib::Module](#) * [load](#) (const std::string &name, bool load_local=true, bool reload=false)
- std::string [findLocation](#) (const std::string &name)
- void [setCfg](#) ([Arc::Config](#) *cfg)

5.80.1 Detailed Description

Manager of shared libraries.

This class loads shared libraries/modules. There supposed to be created one instance of it per executable. In such circumstances it would cache handles to loaded modules and not load them multiple times.

5.80.2 Constructor & Destructor Documentation

5.80.2.1 Arc::ModuleManager::ModuleManager ([Arc::Config](#) *cfg)

Constructor. It is supposed to process corresponding configuration subtree and tune module loading parameters accordingly. Currently it only sets modlur directory to current one.

5.80.3 Member Function Documentation

5.80.3.1 std::string Arc::ModuleManager::findLocation (const std::string &name)

Finds shared library corresponding to module 'name' and returns path to it

5.80.3.2 [Glib::Module](#)* Arc::ModuleManager::load (const std::string &name, bool load_local = true, bool reload = false)

Finds module 'name' in cache or loads corresponding shared library

5.80.3.3 void Arc::ModuleManager::setCfg ([Arc::Config](#) *cfg)

Input the configuration subtree, and trigger the module loading (do almost the same as the Constructor); It is function desgined for ClassLoader to adopt the singleton pattern

The documentation for this class was generated from the following file:


- ModuleManager.h

5.81 Arc::MultiSecAttr Class Reference

Container of multiple [SecAttr](#) attributes.

```
#include <SecAttr.h>
```

Inheritance diagram for Arc::MultiSecAttr::



Public Member Functions

- virtual [operator bool](#) () const
- virtual bool **Export** (Format format, [XMLNode](#) &val) const
- virtual bool **Import** (Format format, const [XMLNode](#) &val)

Protected Member Functions

- virtual bool **equal** (const [SecAttr](#) &b) const
- virtual bool **Add** (Format format, [XMLNode](#) &val)

Protected Attributes

- std::list< [SecAttr](#) * > **attrs_**

5.81.1 Detailed Description

Container of multiple [SecAttr](#) attributes.

This class combines multiple attributes. It's export/import methods catenate results of underlying objects. Primary meaning of this class is to serve as base for classes implementing multi level hierarchical tree-like descriptions of user identity. It may also be used for collecting information of same source or kind. Like all information extracted from X509 certificate.

5.81.2 Member Function Documentation

5.81.2.1 virtual Arc::MultiSecAttr::operator bool () const [virtual]

This function should return false if the value is to be considered null, e.g. if it hasn't been set or initialized. In other cases it should return true.

Reimplemented from [Arc::SecAttr](#).


The documentation for this class was generated from the following file:

- SecAttr.h

5.82 Arc::MySQLDatabase Class Reference

```
#include <MysqlWrapper.h>
```

Inheritance diagram for Arc::MySQLDatabase::



Public Member Functions

- **MySQLDatabase** (std::string &server, int port)
- **MySQLDatabase** (const [MySQLDatabase](#) &other)
- virtual bool [connect](#) (std::string &dbname, std::string &user, std::string &password)
- virtual bool [isconnected](#) () const
- virtual void [close](#) ()
- virtual bool [enable_ssl](#) (const std::string keyfile="", const std::string certfile="", const std::string cafile="", const std::string capath="")
- virtual bool [shutdown](#) ()

Friends

- class [MySQLQuery](#)

5.82.1 Detailed Description

Implement the database accessing interface in [DBInterface.h](#) by using mysql client library for accessing mysql database

5.82.2 Member Function Documentation

5.82.2.1 virtual void Arc::MySQLDatabase::close () [virtual]

Close the connection with database server

Implements [Arc::Database](#).

5.82.2.2 virtual bool Arc::MySQLDatabase::connect (std::string & dbname, std::string & user, std::string & password) [virtual]

Do connection with database server

Parameters:

dbname The database name which will be used.

user The username which will be used to access database.

password The password which will be used to access database.

Implements [Arc::Database](#).

5.82.2.3 `virtual bool Arc::MySQLDatabase::enable_ssl (const std::string keyfile = "", const std::string certfile = "", const std::string cafile = "", const std::string capath = "")` [virtual]

Enable ssl communication for the connection

Parameters:

keyfile The location of key file.

certfile The location of certificate file.

cafile The location of ca file.

capath The location of ca directory

Implements [Arc::Database](#).

5.82.2.4 `virtual bool Arc::MySQLDatabase::isconnected () const` [inline, virtual]

Get the connection status

Implements [Arc::Database](#).

5.82.2.5 `virtual bool Arc::MySQLDatabase::shutdown ()` [virtual]

Ask database server to shutdown

Implements [Arc::Database](#).

The documentation for this class was generated from the following file:


- MysqlWrapper.h

5.83 Arc::PayloadRaw Class Reference

Raw byte multi-buffer.

```
#include <PayloadRaw.h>
```

Inheritance diagram for Arc::PayloadRaw::



Public Member Functions

- [PayloadRaw](#) (void)
- virtual [~PayloadRaw](#) (void)
- virtual char [operator\[\]](#) (int pos) const
- virtual char * [Content](#) (int pos=-1)
- virtual int [Size](#) (void) const
- virtual char * [Insert](#) (int pos=0, int size=0)
- virtual char * [Insert](#) (const char *s, int pos=0, int size=0)
- virtual char * [Buffer](#) (unsigned int num=0)
- virtual int [BufferSize](#) (unsigned int num=0) const
- virtual int [BufferPos](#) (unsigned int num=0) const
- virtual bool [Truncate](#) (unsigned int size)

Protected Attributes

- int [offset_](#)
- int [size_](#)
- std::vector< PayloadRawBuf > [buf_](#)

5.83.1 Detailed Description

Raw byte multi-buffer.

This is implementation of [PayloadRawInterface](#). Buffers are memory blocks logically placed one after another.

5.83.2 Constructor & Destructor Documentation

5.83.2.1 Arc::PayloadRaw::PayloadRaw (void) [inline]

Constructor. Created object contains no buffers.

5.83.2.2 virtual Arc::PayloadRaw::~~PayloadRaw (void) [virtual]

Destructor. Frees allocated buffers.

5.83.3 Member Function Documentation**5.83.3.1 virtual char* Arc::PayloadRaw::Buffer (unsigned int *num* = 0) [virtual]**

Returns pointer to num'th buffer

Implements [Arc::PayloadRawInterface](#).

5.83.3.2 virtual int Arc::PayloadRaw::BufferPos (unsigned int *num* = 0) const [virtual]

Returns position of num'th buffer

Implements [Arc::PayloadRawInterface](#).

5.83.3.3 virtual int Arc::PayloadRaw::BufferSize (unsigned int *num* = 0) const [virtual]

Returns length of num'th buffer

Implements [Arc::PayloadRawInterface](#).

5.83.3.4 virtual char* Arc::PayloadRaw::Content (int *pos* = -1) [virtual]

Get pointer to buffer content at global position 'pos'. By default to beginning of main buffer whatever that means.

Implements [Arc::PayloadRawInterface](#).

5.83.3.5 virtual char* Arc::PayloadRaw::Insert (const char * *s*, int *pos* = 0, int *size* = 0) [virtual]

Create new buffer at global position 'pos' of size 'size'. Created buffer is filled with content of memory at 's'. If 'size' is 0 content at 's' is expected to be null-terminated.

Implements [Arc::PayloadRawInterface](#).

5.83.3.6 virtual char* Arc::PayloadRaw::Insert (int *pos* = 0, int *size* = 0) [virtual]

Create new buffer at global position 'pos' of size 'size'.

Implements [Arc::PayloadRawInterface](#).

5.83.3.7]

virtual char Arc::PayloadRaw::operator[] (int *pos*) const [virtual]

Returns content of byte at specified position. Specified position 'pos' is treated as global one and goes through all buffers placed one after another.

Implements [Arc::PayloadRawInterface](#).

5.83.3.8 `virtual int Arc::PayloadRaw::Size (void) const` [virtual]

Returns logical size of whole structure.

Implements [Arc::PayloadRawInterface](#).

5.83.3.9 `virtual bool Arc::PayloadRaw::Truncate (unsigned int size)` [virtual]

Change size of stored information. If size exceeds end of allocated buffer, buffers are not re-allocated, only logical size is extended. Buffers with location behind new size are deallocated.

Implements [Arc::PayloadRawInterface](#).

The documentation for this class was generated from the following file:


- PayloadRaw.h

5.84 Arc::PayloadRawInterface Class Reference

Random Access Payload for [Message](#) objects.

```
#include <PayloadRaw.h>
```

Inheritance diagram for Arc::PayloadRawInterface::



Public Member Functions

- virtual char [operator\[\]](#) (int pos) const =0
- virtual char * [Content](#) (int pos=-1)=0
- virtual int [Size](#) (void) const =0
- virtual char * [Insert](#) (int pos=0, int size=0)=0
- virtual char * [Insert](#) (const char *s, int pos=0, int size=0)=0
- virtual char * [Buffer](#) (unsigned int num)=0
- virtual int [BufferSize](#) (unsigned int num) const =0
- virtual int [BufferPos](#) (unsigned int num) const =0
- virtual bool [Truncate](#) (unsigned int size)=0

5.84.1 Detailed Description

Random Access Payload for [Message](#) objects.

This class is a virtual interface for managing [Message](#) payload with arbitrarily accessible content. Inheriting classes are supposed to implement memory-resident or memory-mapped content made of optionally multiple chunks/buffers. Every buffer has own size and offset. This class is purely virtual.

5.84.2 Member Function Documentation

5.84.2.1 virtual char* Arc::PayloadRawInterface::Buffer (unsigned int *num*) [pure virtual]

Returns pointer to num'th buffer

Implemented in [Arc::PayloadRaw](#).

5.84.2.2 virtual int Arc::PayloadRawInterface::BufferPos (unsigned int *num*) const [pure virtual]

Returns position of num'th buffer

Implemented in [Arc::PayloadRaw](#).

5.84.2.3 `virtual int Arc::PayloadRawInterface::BufferSize (unsigned int num) const` [pure virtual]

Returns length of *num*'th buffer

Implemented in [Arc::PayloadRaw](#).

5.84.2.4 `virtual char* Arc::PayloadRawInterface::Content (int pos = -1)` [pure virtual]

Get pointer to buffer content at global position '*pos*'. By default to beginning of main buffer whatever that means.

Implemented in [Arc::PayloadRaw](#).

5.84.2.5 `virtual char* Arc::PayloadRawInterface::Insert (const char * s, int pos = 0, int size = 0)` [pure virtual]

Create new buffer at global position '*pos*' of size '*size*'. Created buffer is filled with content of memory at '*s*'. If '*size*' is 0 content at '*s*' is expected to be null-terminated.

Implemented in [Arc::PayloadRaw](#).

5.84.2.6 `virtual char* Arc::PayloadRawInterface::Insert (int pos = 0, int size = 0)` [pure virtual]

Create new buffer at global position '*pos*' of size '*size*'.

Implemented in [Arc::PayloadRaw](#).

5.84.2.7]

`virtual char Arc::PayloadRawInterface::operator[] (int pos) const` [pure virtual]

Returns content of byte at specified position. Specified position '*pos*' is treated as global one and goes through all buffers placed one after another.

Implemented in [Arc::PayloadRaw](#).

5.84.2.8 `virtual int Arc::PayloadRawInterface::Size (void) const` [pure virtual]

Returns logical size of whole structure.

Implemented in [Arc::PayloadRaw](#).

5.84.2.9 `virtual bool Arc::PayloadRawInterface::Truncate (unsigned int size)` [pure virtual]

Change size of stored information. If size exceeds end of allocated buffer, buffers are not re-allocated, only logical size is extended. Buffers with location behind new size are deallocated.

Implemented in [Arc::PayloadRaw](#).

The documentation for this class was generated from the following file:


- PayloadRaw.h

5.85 Arc::PayloadSOAP Class Reference

Payload of [Message](#) with SOAP content.

```
#include <PayloadSOAP.h>
```

Inheritance diagram for Arc::PayloadSOAP::



Public Member Functions

- [PayloadSOAP](#) (const Arc::NS &ns, bool fault=false)
- [PayloadSOAP](#) (const Arc::SOAPEnvelope &soap)
- [PayloadSOAP](#) (const [Arc::MessagePayload](#) &source)

5.85.1 Detailed Description

Payload of [Message](#) with SOAP content.

This class combines [MessagePayload](#) with SOAPEnvelope to make it possible to pass SOAP messages through [MCC](#) chain.

5.85.2 Constructor & Destructor Documentation

5.85.2.1 Arc::PayloadSOAP::PayloadSOAP (const Arc::NS & ns, bool *fault* = false)

Constructor - creates new [Message](#) payload

5.85.2.2 Arc::PayloadSOAP::PayloadSOAP (const Arc::SOAPEnvelope & soap)

Constructor - creates [Message](#) payload from SOAP document. Provided SOAP document is copied to new object.

5.85.2.3 Arc::PayloadSOAP::PayloadSOAP (const [Arc::MessagePayload](#) & source)

Constructor - creates SOAP message from payload. [PayloadRawInterface](#) and derived classes are supported.

The documentation for this class was generated from the following file:


- PayloadSOAP.h

5.86 Arc::PayloadStream Class Reference

POSIX handle as Payload.

```
#include <PayloadStream.h>
```

Inheritance diagram for Arc::PayloadStream::



Public Member Functions

- [PayloadStream](#) (int h=-1)
- virtual [~PayloadStream](#) (void)
- virtual bool [Get](#) (char *buf, int &size)
- virtual bool [Get](#) (std::string &buf)
- virtual std::string [Get](#) (void)
- virtual bool [Put](#) (const char *buf, int size)
- virtual bool [Put](#) (const std::string &buf)
- virtual bool [Put](#) (const char *buf)
- virtual [operator bool](#) (void)
- virtual bool [operator!](#) (void)
- virtual int [Timeout](#) (void) const
- virtual void [Timeout](#) (int to)
- virtual int [GetHandle](#) (void)

Protected Attributes

- int [timeout_](#)
- int [handle_](#)
- bool [seekable_](#)

5.86.1 Detailed Description

POSIX handle as Payload.

This is an implementation of [PayloadStreamInterface](#) for generic POSIX handle.

5.86.2 Constructor & Destructor Documentation

5.86.2.1 Arc::PayloadStream::PayloadStream (int h = -1)

Constructor. Attaches to already open handle. Handle is not managed by this class and must be closed by external code.

5.86.2.2 virtual Arc::PayloadStream::~~PayloadStream (void) [inline, virtual]

Destructor.

5.86.3 Member Function Documentation**5.86.3.1 virtual std::string Arc::PayloadStream::Get (void)** [inline, virtual]

Read as many as possible (sane amount) of bytes.

Implements [Arc::PayloadStreamInterface](#).

5.86.3.2 virtual bool Arc::PayloadStream::Get (std::string & buf) [virtual]

Read as many as possible (sane amount) of bytes into buf.

Implements [Arc::PayloadStreamInterface](#).

5.86.3.3 virtual bool Arc::PayloadStream::Get (char * buf, int & size) [virtual]

Extracts information from stream up to 'size' bytes. 'size' contains number of read bytes on exit. Returns true in case of success.

Implements [Arc::PayloadStreamInterface](#).

5.86.3.4 virtual int Arc::PayloadStream::GetHandle (void) [inline, virtual]

Returns POSIX handle of the stream. This method is deprecated and will be removed soon. Currently it is only used by Transport Layer Security [MCC](#).

5.86.3.5 virtual Arc::PayloadStream::operator bool (void) [inline, virtual]

Returns true if stream is valid.

Implements [Arc::PayloadStreamInterface](#).

5.86.3.6 virtual bool Arc::PayloadStream::operator! (void) [inline, virtual]

Returns true if stream is invalid.

Implements [Arc::PayloadStreamInterface](#).

5.86.3.7 virtual bool Arc::PayloadStream::Put (const char * buf) [inline, virtual]

Push null terminated information from 'buf' into stream. Returns true on success.

Implements [Arc::PayloadStreamInterface](#).

5.86.3.8 virtual bool Arc::PayloadStream::Put (const std::string & buf) [inline, virtual]

Push information from 'buf' into stream. Returns true on success.

Implements [Arc::PayloadStreamInterface](#).

5.86.3.9 virtual bool Arc::PayloadStream::Put (const char * *buf*, int *size*) [virtual]

Push 'size' bytes from 'buf' into stream. Returns true on success.

Implements [Arc::PayloadStreamInterface](#).

5.86.3.10 virtual void Arc::PayloadStream::Timeout (int *to*) [inline, virtual]

Set current timeout for [Get\(\)](#) and [Put\(\)](#) operations.

Implements [Arc::PayloadStreamInterface](#).

5.86.3.11 virtual int Arc::PayloadStream::Timeout (void) const [inline, virtual]

Query current timeout for [Get\(\)](#) and [Put\(\)](#) operations.

Implements [Arc::PayloadStreamInterface](#).

5.86.4 Member Data Documentation

5.86.4.1 int Arc::PayloadStream::handle_ [protected]

Timeout for read/write operations

5.86.4.2 bool Arc::PayloadStream::seekable_ [protected]

Handle for operations

The documentation for this class was generated from the following file:


- PayloadStream.h

5.87 Arc::PayloadStreamInterface Class Reference

Stream-like Payload for [Message](#) object.

```
#include <PayloadStream.h>
```

Inheritance diagram for Arc::PayloadStreamInterface::



Public Member Functions

- virtual bool [Get](#) (char *buf, int &size)=0
- virtual bool [Get](#) (std::string &buf)=0
- virtual std::string [Get](#) (void)=0
- virtual bool [Put](#) (const char *buf, int size)=0
- virtual bool [Put](#) (const std::string &buf)=0
- virtual bool [Put](#) (const char *buf)=0
- virtual [operator bool](#) (void)=0
- virtual bool [operator!](#) (void)=0
- virtual int [Timeout](#) (void) const =0
- virtual void [Timeout](#) (int to)=0

5.87.1 Detailed Description

Stream-like Payload for [Message](#) object.

This class is a virtual interface for managing stream-like source and destination. It's supposed to be passed through [MCC](#) chain as payload of [Message](#). It must be treated by MCCs and Services as dynamic payload. This class is purely virtual.

5.87.2 Member Function Documentation

5.87.2.1 virtual std::string Arc::PayloadStreamInterface::Get (void) [pure virtual]

Read as many as possible (sane amount) of bytes.

Implemented in [Arc::PayloadStream](#).

5.87.2.2 virtual bool Arc::PayloadStreamInterface::Get (std::string & buf) [pure virtual]

Read as many as possible (sane amount) of bytes into buf.

Implemented in [Arc::PayloadStream](#).

5.87.2.3 virtual bool Arc::PayloadStreamInterface::Get (char * *buf*, int & *size*) [pure virtual]

Extracts information from stream up to 'size' bytes. 'size' contains number of read bytes on exit. Returns true in case of success.

Implemented in [Arc::PayloadStream](#).

5.87.2.4 virtual Arc::PayloadStreamInterface::operator bool (void) [pure virtual]

Returns true if stream is valid.

Implemented in [Arc::PayloadStream](#).

5.87.2.5 virtual bool Arc::PayloadStreamInterface::operator! (void) [pure virtual]

Returns true if stream is invalid.

Implemented in [Arc::PayloadStream](#).

5.87.2.6 virtual bool Arc::PayloadStreamInterface::Put (const char * *buf*) [pure virtual]

Push null terminated information from 'buf' into stream. Returns true on success.

Implemented in [Arc::PayloadStream](#).

5.87.2.7 virtual bool Arc::PayloadStreamInterface::Put (const std::string & *buf*) [pure virtual]

Push information from 'buf' into stream. Returns true on success.

Implemented in [Arc::PayloadStream](#).

5.87.2.8 virtual bool Arc::PayloadStreamInterface::Put (const char * *buf*, int *size*) [pure virtual]

Push 'size' bytes from 'buf' into stream. Returns true on success.

Implemented in [Arc::PayloadStream](#).

5.87.2.9 virtual void Arc::PayloadStreamInterface::Timeout (int *to*) [pure virtual]

Set current timeout for [Get\(\)](#) and [Put\(\)](#) operations.

Implemented in [Arc::PayloadStream](#).

5.87.2.10 virtual int Arc::PayloadStreamInterface::Timeout (void) const [pure virtual]

Query current timeout for [Get\(\)](#) and [Put\(\)](#) operations.

Implemented in [Arc::PayloadStream](#).

The documentation for this class was generated from the following file:


- PayloadStream.h

5.88 Arc::PayloadWSRF Class Reference

This class combines [MessagePayload](#) with [WSRF](#).

```
#include <PayloadWSRF.h>
```

Inheritance diagram for Arc::PayloadWSRF::



Public Member Functions

- [PayloadWSRF](#) (const SOAPEnvelope &soap)
- [PayloadWSRF](#) ([WSRF](#) &wsrp)
- [PayloadWSRF](#) (const [MessagePayload](#) &source)
- **operator WSRF &** (void)
- **operator bool** (void)

Protected Attributes

- [WSRF](#) & **wsrf_**
- bool **owner_**

5.88.1 Detailed Description

This class combines [MessagePayload](#) with [WSRF](#).

It's intention is to make it possible to pass [WSRF](#) messages through [MCC](#) chain as one more Payload type.

5.88.2 Constructor & Destructor Documentation

5.88.2.1 Arc::PayloadWSRF::PayloadWSRF (const SOAPEnvelope & soap)

Constructor - creates [Message](#) payload from SOAP message. Returns invalid [WSRF](#) if SOAP does not represent WS-ResourceProperties

5.88.2.2 Arc::PayloadWSRF::PayloadWSRF ([WSRF](#) & *wsrp*)

Constructor - creates [Message](#) payload with acquired [WSRF](#) message. [WSRF](#) message will be destroyed by destructor of this object.

5.88.2.3 Arc::PayloadWSRF::PayloadWSRF (const [MessagePayload](#) & *source*)

Constructor - creates [WSRF](#) message from payload. All classes derived from SOAPEnvelope are supported.

The documentation for this class was generated from the following file:

- PayloadWSRF.h

5.89 ArcSec::PDP Class Reference

Base class for [Policy](#) Decision Point plugins.

```
#include <PDP.h>
```

Public Member Functions

- **PDP** ([Arc::Config](#) *cfg)
- virtual bool **isPermitted** ([Arc::Message](#) *msg)=0
- void **SetId** (std::string &id)
- std::string **GetId** ()

Protected Attributes

- std::string **id_**

Static Protected Attributes

- static [Arc::Logger](#) **logger**

5.89.1 Detailed Description

Base class for [Policy](#) Decision Point plugins.

This virtual class defines method isPermitted() which processes security related information/attributes in Message and makes security decision - permit (true) or deny (false). Configuration of [PDP](#) is consumed during creation of instance through XML subtree fed to constructor.

The documentation for this class was generated from the following file:

- PDP.h

5.90 pdp_descriptor Struct Reference

Identifier of Policy Decision Point (PDP) plugin.

```
#include <PDPLoader.h>
```

Public Attributes

- `const char * name`
- `int version`
- `ArcSec::PDP *(* get_instance)(Arc::Config *cfg, Arc::ChainContext *ctx)`

5.90.1 Detailed Description

Identifier of Policy Decision Point (PDP) plugin.

This structure describes one of the PDPs stored in a shared library. It contains name of plugin, version number and pointer to function which creates an instance of an object inherited from the PDP class.

The documentation for this struct was generated from the following file:


- PDPLoader.h

5.91 Arc::PDPFactory Class Reference

PDP Plugins handler.

```
#include <PDPFactory.h>
```

Inheritance diagram for Arc::PDPFactory::



Public Member Functions

- [PDPFactory](#) ([Config](#) *cfg)
- [ArcSec::PDP](#) * [get_instance](#) (const std::string &name, [Config](#) *cfg, [ChainContext](#) *ctx)
- [ArcSec::PDP](#) * [get_instance](#) (const std::string &name, int version, [Config](#) *cfg, [ChainContext](#) *ctx)
- [ArcSec::PDP](#) * [get_instance](#) (const std::string &name, int min_version, int max_version, [Config](#) *cfg, [ChainContext](#) *ctx)

5.91.1 Detailed Description

PDP Plugins handler.

This class handles shared libraries containing PDPs

5.91.2 Constructor & Destructor Documentation

5.91.2.1 Arc::PDPFactory::PDPFactory ([Config](#) * cfg)

Constructor - accepts configuration (not yet used) meant to tune loading of module.

5.91.3 Member Function Documentation

5.91.3.1 [ArcSec::PDP](#)* Arc::PDPFactory::get_instance (const std::string & name, [Config](#) * cfg, [ChainContext](#) * ctx)

These methods load shared library named lib'name', locate symbol representing descriptor of PDP and calls it's constructor function. Supplied configuration tree is passed to constructor. Returns created PDP instance.

Reimplemented from [Arc::LoaderFactory](#).

The documentation for this class was generated from the following file:


- PDPFactory.h

5.92 ArcSec::PermitOverridesCombiningAlg Class Reference

Implement the "Permit-Overrides" algorithm.

```
#include <PermitOverridesAlg.h>
```

Inheritance diagram for ArcSec::PermitOverridesCombiningAlg::



Public Member Functions

- virtual Result [combine](#) (EvaluationCtx *ctx, std::list< [Policy](#) * > policies)
- virtual std::string & [getalgId](#) (void)

Static Public Member Functions

- static const std::string & [Identifier](#) (void)

5.92.1 Detailed Description

Implement the "Permit-Overrides" algorithm.

5.92.2 Member Function Documentation

5.92.2.1 virtual Result ArcSec::PermitOverridesCombiningAlg::combine ([EvaluationCtx](#) * ctx, std::list< [Policy](#) * > *policies*) [virtual]

If there is one policy which return positive evaluation result, then omit the other policies and return DECISION_PERMIT

Implements [ArcSec::CombiningAlg](#).

The documentation for this class was generated from the following file:


- PermitOverridesAlg.h

5.93 Arc::Plexer Class Reference

The [Plexer](#) class, used for routing messages to services.

```
#include <Plexer.h>
```

Inheritance diagram for Arc::Plexer::



Public Member Functions

- [Plexer](#) ([Config](#) *cfg)
- virtual [~Plexer](#) ()
- virtual void [Next](#) ([MCCInterface](#) *next, const std::string &label)
- virtual [MCC_Status process](#) ([Message](#) &request, [Message](#) &response)

Static Public Attributes

- static [Arc::Logger logger](#)

5.93.1 Detailed Description

The [Plexer](#) class, used for routing messages to services.

This is the [Plexer](#) class. Its purpose is to route incoming messages to appropriate Services and [MCC](#) chains.

5.93.2 Constructor & Destructor Documentation

5.93.2.1 Arc::Plexer::Plexer ([Config](#) * cfg)

The constructor.

This is the constructor. Since all member variables are instances of "well-behaving" STL classes, nothing needs to be done.

5.93.2.2 virtual Arc::Plexer::~~Plexer () [virtual]

The destructor.

This is the destructor. Since all member variables are instances of "well-behaving" STL classes, nothing needs to be done.

5.93.3 Member Function Documentation

5.93.3.1 virtual void Arc::Plexer::Next ([MCCInterface](#) * *next*, const std::string & *label*) [virtual]

Add reference to next [MCC](#) in chain.

This method is called by [Loader](#) for every potentially labeled link to next component which implements [MCCInterface](#). If next is set NULL corresponding link is removed.

Reimplemented from [Arc::MCC](#).

5.93.3.2 virtual [MCC_Status](#) Arc::Plexer::process ([Message](#) & *request*, [Message](#) & *response*) [virtual]

Route request messages to appropriate services.

Routes the request message to the appropriate service. Routing is based on the path part of value of the ENDPOINT attribute. Routed message is assigned following attributes: PLEXER:PATTERN - matched pattern, PLEXER:EXTENSION - last unmatched part of ENDPOINT path.

Reimplemented from [Arc::MCC](#).

5.93.4 Member Data Documentation

5.93.4.1 [Arc::Logger](#) Arc::Plexer::logger [static]

A logger for MCCs.

A logger intended to be the parent of loggers in the different MCCs.

Reimplemented from [Arc::MCC](#).

The documentation for this class was generated from the following file:

- [Plexer.h](#)

5.94 Arc::PlexerEntry Class Reference

A pair of label (regex) and pointer to service.

```
#include <Plexer.h>
```

Friends

- class **Plexer**

5.94.1 Detailed Description

A pair of label (regex) and pointer to service.

A helper class that stores a label (regex) and a pointer to a service.

The documentation for this class was generated from the following file:

- Plexer.h

5.95 ArcSec::Policy Class Reference

Base class for [Policy](#), PolicySet, or Rule.

```
#include <Policy.h>
```

Public Member Functions

- [Policy](#) ([Arc::XMLNode](#) *)
- [Policy](#) ([Arc::XMLNode](#) *, [EvaluatorContext](#) *)
- virtual MatchResult [match](#) ([EvaluationCtx](#) *)=0
- virtual Result [eval](#) ([EvaluationCtx](#) *)=0
- virtual void [addPolicy](#) ([Policy](#) *pl)
- virtual void [setEvaluatorContext](#) ([EvaluatorContext](#) *)
- virtual void [make_policy](#) ()
- virtual std::string [getEffect](#) ()=0
- virtual [EvalResult](#) & [getEvalResult](#) ()=0
- virtual void [setEvalResult](#) ([EvalResult](#) &res)=0

Protected Attributes

- std::list< [Policy](#) * > [subelements](#)

Static Protected Attributes

- static [Arc::Logger](#) [logger](#)

5.95.1 Detailed Description

Base class for [Policy](#), PolicySet, or Rule.

5.95.2 Member Function Documentation

5.95.2.1 virtual void ArcSec::Policy::addPolicy ([Policy](#) *pl) [inline, virtual]

Add a policy element to into "this" object

5.95.2.2 virtual std::string ArcSec::Policy::getEffect () [pure virtual]

Get the "Effect" attribute

5.95.2.3 virtual [EvalResult](#)& ArcSec::Policy::getEvalResult () [pure virtual]

Get eveluation result

5.95.2.4 virtual void ArcSec::Policy::make_policy () [inline, virtual]

Parse XMLNode, and construct the low-level Rule object

5.95.2.5 `virtual MatchResult ArcSec::Policy::match (EvaluationCtx *)` [pure virtual]

Evaluate whether the two targets to be evaluated match to each other.

5.95.2.6 `virtual void ArcSec::Policy::setEvalResult (EvalResult & res)` [pure virtual]

Set evaluation result

5.95.2.7 `virtual void ArcSec::Policy::setEvaluatorContext (EvaluatorContext *)` [inline, virtual]

set [Evaluator](#) Context for the usage in creating low-level policy object

The documentation for this class was generated from the following file:

- Policy.h

5.96 ArcSec::PolicyParser Class Reference

A interface which will isolate the policy object from actual policy storage (files, urls, database).

```
#include <PolicyParser.h>
```

Public Member Functions

- virtual [Policy](#) * [parsePolicy](#) (const [Source](#) &source, std::string policyclassname, [EvaluatorContext](#) *ctx)

5.96.1 Detailed Description

A interface which will isolate the policy object from actual policy storage (files, urls, database).

Parse the policy from policy source (e.g. files, urls, database, etc.).

5.96.2 Member Function Documentation

5.96.2.1 virtual [Policy](#)* ArcSec::PolicyParser::parsePolicy (const [Source](#) & *source*, std::string *policyclassname*, [EvaluatorContext](#) * *ctx*) [virtual]

Parse policy

Parameters:

- source* location of the policy
- policyclassname* name of the policy for ClassLoader
- ctx* [EvaluatorContext](#) which includes the **Factory

The documentation for this class was generated from the following file:

- PolicyParser.h

5.97 ArcSec::PolicyStore Class Reference

Storage place for policy objects.

```
#include <PolicyStore.h>
```

Public Member Functions

- [PolicyStore](#) (const std::string &alg, const std::string &policyclassname, [EvaluatorContext](#) *ctx)
- virtual std::list< PolicyElement > **findPolicy** ([EvaluationCtx](#) *context)
- virtual void **addPolicy** (const [Source](#) &policy, [EvaluatorContext](#) *ctx, const std::string &id)
- virtual void **addPolicy** ([Policy](#) *policyobj, [EvaluatorContext](#) *ctx, const std::string &id)
- virtual void **removePolicies** ()

Classes

- class [PolicyElement](#)

5.97.1 Detailed Description

Storage place for policy objects.

5.97.2 Constructor & Destructor Documentation

5.97.2.1 ArcSec::PolicyStore::PolicyStore (const std::string & *alg*, const std::string & *policyclassname*, [EvaluatorContext](#) * *ctx*)

Creates policy store with specified combing algorithm (alg - not used yet), policy name (policyclassname) and context (ctx)

The documentation for this class was generated from the following file:

- PolicyStore.h

5.98 Arc::RegularExpression Class Reference

A regular expression class.

```
#include <ArcRegex.h>
```

Public Member Functions

- [RegularExpression](#) ()
- [RegularExpression](#) (std::string pattern)
- [RegularExpression](#) (const [RegularExpression](#) ®ex)
- [~RegularExpression](#) ()
- const [RegularExpression](#) & operator= (const [RegularExpression](#) ®ex)
- bool [isOk](#) ()
- bool [hasPattern](#) (std::string str)
- bool [match](#) (const std::string &str) const
- bool [match](#) (const std::string &str, std::list< std::string > &unmatched, std::list< std::string > &matched) const
- std::string [getPattern](#) ()

5.98.1 Detailed Description

A regular expression class.

This class is a wrapper around the functions provided in regex.h.

5.98.2 Constructor & Destructor Documentation

5.98.2.1 Arc::RegularExpression::RegularExpression () [inline]

default constructor

5.98.2.2 Arc::RegularExpression::RegularExpression (std::string *pattern*)

Creates a regex from a pattern string.

5.98.2.3 Arc::RegularExpression::RegularExpression (const [RegularExpression](#) & *regex*)

Copy constructor.

5.98.2.4 Arc::RegularExpression::~~RegularExpression ()

Destructor.

5.98.3 Member Function Documentation

5.98.3.1 std::string Arc::RegularExpression::getPattern ()

Returns patter.

5.98.3.2 `bool Arc::RegularExpression::hasPattern (std::string str)`

Returns true if this regex has the pattern provided.

5.98.3.3 `bool Arc::RegularExpression::isOk ()`

Returns true if the pattern of this regex is ok.

5.98.3.4 `bool Arc::RegularExpression::match (const std::string & str, std::list< std::string > & unmatched, std::list< std::string > & matched) const`

Returns true if this regex matches the string provided. Unmatched parts of the string are stored in 'unmatched'. Matched parts of the string are stored in 'matched'.

5.98.3.5 `bool Arc::RegularExpression::match (const std::string & str) const`

Returns true if this regex matches whole string provided.

5.98.3.6 `const RegularExpression& Arc::RegularExpression::operator= (const RegularExpression & regex)`

Assignment operator.

The documentation for this class was generated from the following file:

- ArcRegex.h

5.99 ArcSec::Request Class Reference

Base class/Interface for request, includes a container for RequestItems and some operations.

```
#include <Request.h>
```

Public Member Functions

- virtual ReqItemList [getRequestItems](#) () const =0
- virtual void [setRequestItems](#) (ReqItemList sl)=0
- virtual void [addRequestItem](#) (Attrs &sub, Attrs &res, Attrs &act, Attrs &ctx)=0
- virtual void [setAttributeFactory](#) (AttributeFactory *attributefactory)=0
- virtual void [make_request](#) ()=0
- [Request](#) ()
- [Request](#) (const Source &)

Protected Attributes

- ReqItemList **rlist**

5.99.1 Detailed Description

Base class/Interface for request, includes a container for RequestItems and some operations.

A [Request](#) object can has a few <subjects, actions, objects> tuples, i.e. [RequestItem](#) The [Request](#) class and any customized class which inherit from it, should be loadable, which means these classes can be dynamically loaded according to the configuration information, see the example configuration below: <Service name="pdp.service" id="pdp_service"> <pdp:PDPCfg> <.....> <pdp:[Request](#) name="arc.request" /> <.....> </pdp:PDPCfg> </Service>

There can be different types of subclass which inherit [Request](#), such like XACMLRequest, ArcRequest, GACLRequest

5.99.2 Constructor & Destructor Documentation

5.99.2.1 ArcSec::Request::Request () [inline]

Default constructor

5.99.2.2 ArcSec::Request::Request (const Source &) [inline]

Constructor: Parse request information from a xml stucture in memory

5.99.3 Member Function Documentation

5.99.3.1 virtual void ArcSec::Request::addRequestItem (Attrs & sub, Attrs & res, Attrs & act, Attrs & ctx) [pure virtual]

Add request tuple from non-XMLNode

5.99.3.2 virtual ReqItemList ArcSec::Request::getRequestItems () const [pure virtual]

Get all the [RequestItem](#) inside [RequestItem](#) container

5.99.3.3 virtual void ArcSec::Request::make_request () [pure virtual]

Create the objects included in [Request](#) according to the node attached to the [Request](#) object

5.99.3.4 virtual void ArcSec::Request::setAttributeFactory ([AttributeFactory](#) * *attributefactory*)
[pure virtual]

Set the attribute factory for the usage of [Request](#)

5.99.3.5 virtual void ArcSec::Request::setRequestItems (ReqItemList *sl*) [pure virtual]

Set the content of the container

The documentation for this class was generated from the following file:

- Request.h

5.100 ArcSec::RequestAttribute Class Reference

Wrapper which includes [AttributeValue](#) object which is generated according to date type of one spetic node in Request.xml.

```
#include <RequestAttribute.h>
```

Public Member Functions

- [RequestAttribute](#) ([Arc::XMLNode](#) &node, [AttributeFactory](#) *attrfactory)
- [Arc::XMLNode](#) [getNode](#) ()
- std::string [getAttributeId](#) () const
- void [setAttributeId](#) (const std::string attributeId)
- std::string [getDataType](#) () const
- void [setDataType](#) (const std::string dataType)
- std::string [getIssuer](#) () const
- void [setIssuer](#) (const std::string issuer)
- virtual [AttributeValue](#) * [getAttributeValue](#) () const
- virtual [AttributeFactory](#) * [getAttributeFactory](#) () const
- [RequestAttribute](#) & [duplicate](#) ([RequestAttribute](#) &)

5.100.1 Detailed Description

Wrapper which includes [AttributeValue](#) object which is generated according to date type of one spetic node in Request.xml.

5.100.2 Constructor & Destructor Documentation

5.100.2.1 ArcSec::RequestAttribute::RequestAttribute ([Arc::XMLNode](#) & node, [AttributeFactory](#) * attrfactory)

Constructor - create attribute value object according to the "Type" in the node <Attribute attributeid="urn:arc:subject:voms-attribute" type="string">urn:mace:shibboleth:examples</Attribute>

5.100.3 Member Function Documentation

5.100.3.1 [RequestAttribute](#)& ArcSec::RequestAttribute::duplicate ([RequestAttribute](#) &)

Duplicate the parameter into "this"

The documentation for this class was generated from the following file:

- RequestAttribute.h

5.101 ArcSec::RequestItem Class Reference

Interface for request item container, <subjects, actions, objects, ctxs> tuple.

```
#include <RequestItem.h>
```

Public Member Functions

- [RequestItem](#) ([Arc::XMLNode](#) &, [AttributeFactory](#) *)
- virtual SubList **getSubjects** () const =0
- virtual void **setSubjects** (const SubList &sl)=0
- virtual ResList **getResources** () const =0
- virtual void **setResources** (const ResList &rl)=0
- virtual ActList **getActions** () const =0
- virtual void **setActions** (const ActList &al)=0
- virtual CtxList **getContexts** () const =0
- virtual void **setContexts** (const CtxList &ctx)=0

Protected Attributes

- SubList **subjects**
- ResList **actions**
- ActList **resources**
- CtxList **contexts**

5.101.1 Detailed Description

Interface for request item container, <subjects, actions, objects, ctxs> tuple.

5.101.2 Constructor & Destructor Documentation

5.101.2.1 ArcSec::RequestItem::RequestItem ([Arc::XMLNode](#) &, [AttributeFactory](#) *) [inline]

Constructor

Parameters:

- node* The XMLNode structure of the request item
- attributeFactory* The [AttributeFactory](#) which will be used to generate [RequestAttribute](#)

The documentation for this class was generated from the following file:

- RequestItem.h

5.102 ArcSec::RequestTuple Class Reference

[RequestTuple](#), container which includes the.

```
#include <EvaluationCtx.h>
```

Public Member Functions

- [RequestTuple](#) & **duplicate** (const [RequestTuple](#) &)
- [Arc::XMLNode](#) & **getNode** ()
- void **erase** ()

Public Attributes

- Subject **sub**
- Resource **res**
- Action **act**
- Context **ctx**

5.102.1 Detailed Description

[RequestTuple](#), container which includes the.

The documentation for this class was generated from the following file:

- EvaluationCtx.h

5.103 ArcSec::Response Class Reference

Container for the evaluation results.

```
#include <Response.h>
```

Public Member Functions

- void **setRequestSize** (int size)
- int **getRequestSize** ()
- virtual ResponseList & **getResponseItems** ()
- virtual void **setResponseItems** (const ResponseList &rl)
- virtual void **addResponseItem** ([ResponseItem](#) *respitem)

Protected Attributes

- ResponseList **rlist**

5.103.1 Detailed Description

Container for the evaluation results.

The documentation for this class was generated from the following file:

- Response.h

5.104 ArcSec::ResponseItem Struct Reference

Evaluation result concerning one [RequestTuple](#).

```
#include <Response.h>
```

Public Attributes

- [RequestTuple](#) * **reqtp**
- Result **res**
- [Arc::XMLNode](#) **reqxml**
- Policies **pls**
- std::list< [Arc::XMLNode](#) > **plsxml**

5.104.1 Detailed Description

Evaluation result concerning one [RequestTuple](#).

Include the [RequestTuple](#), related XMLNode, the set of policy objects which give positive evaluation result, and the related XMLNode

The documentation for this struct was generated from the following file:

- Response.h

5.105 Arc::Run Class Reference

```
#include <Run.h>
```

Public Member Functions

- [Run](#) (const std::string &cmdline)
- [Run](#) (const std::list< std::string > &argv)
- [~Run](#) (void)
- [operator bool](#) (void)
- [bool operator!](#) (void)
- [bool Start](#) (void)
- [bool Wait](#) (int timeout)
- [bool Wait](#) (void)
- [int Result](#) (void)
- [bool Running](#) (void)
- [int ReadStdout](#) (int timeout, char *buf, int size)
- [int ReadStderr](#) (int timeout, char *buf, int size)
- [int WriteStdin](#) (int timeout, const char *buf, int size)
- [void AssignStdout](#) (std::string &str)
- [void AssignStderr](#) (std::string &str)
- [void AssignStdin](#) (std::string &str)
- [void KeepStdout](#) (bool keep=true)
- [void KeepStderr](#) (bool keep=true)
- [void KeepStdin](#) (bool keep=true)
- [void CloseStdout](#) (void)
- [void CloseStderr](#) (void)
- [void CloseStdin](#) (void)
- [void AssignInitializer](#) (void(*initializer_func)(void *), void *initializer_arg)
- [void AssignKicker](#) (void(*kicker_func)(void *), void *kicker_arg)
- [void AssignWorkingDirectory](#) (std::string &wd)
- [void Kill](#) (int timeout)

Protected Member Functions

- [bool stdout_handler](#) (Glib::IOCondition cond)
- [bool stderr_handler](#) (Glib::IOCondition cond)
- [bool stdin_handler](#) (Glib::IOCondition cond)
- [void child_handler](#) (Glib::Pid pid, int result)

Protected Attributes

- std::string [working_directory](#)
- int [stdout_](#)
- int [stderr_](#)
- int [stdin_](#)
- std::string * [stdout_str_](#)
- std::string * [stderr_str_](#)
- std::string * [stdin_str_](#)

- bool **stdout_keep_**
- bool **stderr_keep_**
- bool **stdin_keep_**
- sigc::connection **stdout_conn_**
- sigc::connection **stderr_conn_**
- sigc::connection **stdin_conn_**
- sigc::connection **child_conn_**
- Arc::Pid * **pid_**
- Glib::ArrayHandle< std::string > **argv_**
- void(* **initializer_func_**)(void *)
- void * **initializer_arg_**
- void(* **kicker_func_**)(void *)
- void * **kicker_arg_**
- bool **started_**
- bool **running_**
- int **result_**
- Glib::Mutex **lock_**
- Glib::Cond **cond_**

Friends

- class **RunPump**

5.105.1 Detailed Description

This class runs external executable. It is possible to read/write it's standard handles or to redirect then to std::string elements.

5.105.2 Constructor & Destructor Documentation

5.105.2.1 Arc::Run::Run (const std::string & *cmdline*)

Constructor preapres object to run cmdline

5.105.2.2 Arc::Run::Run (const std::list< std::string > & *argv*)

Constructor preapres object to run executable and arguments specified in argv

5.105.2.3 Arc::Run::~~Run (void)

Destructor kill running executable and releases associated resources

5.105.3 Member Function Documentation

5.105.3.1 void Arc::Run::AssignStderr (std::string & *str*)

Associate stderr handle of executable with string. This method must be called before [Start\(\)](#). str object must be valid as long as this object exists.

5.105.3.2 void Arc::Run::AssignStdin (std::string & *str*)

Associate stdin handle of executable with string. This method must be called before [Start\(\)](#). *str* object must be valid as long as this object exists.

5.105.3.3 void Arc::Run::AssignStdout (std::string & *str*)

Associate stdout handle of executable with string. This method must be called before [Start\(\)](#). *str* object must be valid as long as this object exists.

5.105.3.4 void Arc::Run::AssignWorkingDirectory (std::string & *wd*) `[inline]`

Assign working directory of the running process

5.105.3.5 void Arc::Run::CloseStderr (void)

Closes pipe associated with stderr handle

5.105.3.6 void Arc::Run::CloseStdin (void)

Closes pipe associated with stdin handle

5.105.3.7 void Arc::Run::CloseStdout (void)

Closes pipe associated with stdout handle

5.105.3.8 void Arc::Run::KeepStderr (bool *keep* = true)

Keep stderr same as parent's if *keep* = true

5.105.3.9 void Arc::Run::KeepStdin (bool *keep* = true)

Keep stdin same as parent's if *keep* = true

5.105.3.10 void Arc::Run::KeepStdout (bool *keep* = true)

Keep stdout same as parent's if *keep* = true

5.105.3.11 void Arc::Run::Kill (int *timeout*)

Kill running executable. First soft kill signal (SIGTERM) is sent to executable. If after *timeout* seconds executable is still running it's killed completely. Currently this method does not work for Windows OS

5.105.3.12 Arc::Run::operator bool (void) `[inline]`

Returns true if object is valid

5.105.3.13 bool Arc::Run::operator! (void) [inline]

Returns true if object is invalid

5.105.3.14 int Arc::Run::ReadStderr (int *timeout*, char * *buf*, int *size*)

Read from stderr handle of running executable. This method may be used while stderr is directed to string. But result is unpredictable.

5.105.3.15 int Arc::Run::ReadStdout (int *timeout*, char * *buf*, int *size*)

Read from stdout handle of running executable. This method may be used while stdout is directed to string. But result is unpredictable.

5.105.3.16 int Arc::Run::Result (void) [inline]

Returns exit code of execution.

5.105.3.17 bool Arc::Run::Running (void)

Return true if execution is going on.

5.105.3.18 bool Arc::Run::Start (void)

Starts running executable. This method may be called only once.

5.105.3.19 bool Arc::Run::Wait (void)

Wait till execution finished

5.105.3.20 bool Arc::Run::Wait (int *timeout*)

Wait till execution finished or till timeout seconds expires. Returns true if execution is complete.

5.105.3.21 int Arc::Run::WriteStdin (int *timeout*, const char * *buf*, int *size*)

Write to stdin handle of running executable. This method may be used while stdin is directed to string. But result is unpredictable.

The documentation for this class was generated from the following file:

- Run.h

5.106 Arc::SAMLToken Class Reference

Interface for manipulation of WS-Security according to SAML Token Profile.

```
#include <SAMLToken.h>
```

Public Types

- **SAML1**
- **SAML2**
- enum **SAMLTokenVersion** { **SAML1**, **SAML2** }

Public Member Functions

- [SAMLToken](#) (SOAPEnvelope &soap, SAMLTokenVersion samlversion)
- [SAMLToken](#) (SOAPEnvelope &soap, const std::string &certfile, const std::string &keyfile, SAMLTokenVersion samlversion)
- [operator bool](#) (void)
- bool [Authenticate](#) (const std::string &cafile, const std::string &capath)
- bool [Authenticate](#) (void)

5.106.1 Detailed Description

Interface for manipulation of WS-Security according to SAML Token Profile.

5.106.2 Constructor & Destructor Documentation

5.106.2.1 Arc::SAMLToken::SAMLToken (SOAPEnvelope & soap, SAMLTokenVersion *samlversion*)

Link to existing SOAP header and parse SAML Token information. SAML Token related information is extracted from SOAP header and stored in class variables.

5.106.2.2 Arc::SAMLToken::SAMLToken (SOAPEnvelope & soap, const std::string & *certfile*, const std::string & *keyfile*, SAMLTokenVersion *samlversion*)

Add SAML Token information into the SOAP header. Generated token contains elements SAML token and signature, and is meant to be used for authentication.

Parameters:

soap the SOAP message

certfile

keyfile

tokentype

5.106.3 Member Function Documentation

5.106.3.1 bool Arc::SAMLToken::Authenticate (void)

Check signature by using the cert information in soap message

5.106.3.2 bool Arc::SAMLToken::Authenticate (const std::string & *cafile*, const std::string & *capath*)

Check signature by using the trusted certificates

Parameters:

cafile ca file

capath ca directory

5.106.3.3 Arc::SAMLToken::operator bool (void)

Returns true of constructor succeeded

The documentation for this class was generated from the following file:


- SAMLToken.h

5.107 Arc::SecAttr Class Reference

This is an abstract interface to a security attribute.

```
#include <SecAttr.h>
```

Inheritance diagram for Arc::SecAttr::



Public Member Functions

- [SecAttr](#) ()
- bool [operator==](#) (const [SecAttr](#) &b) const
- bool [operator!=](#) (const [SecAttr](#) &b) const
- virtual [operator bool](#) () const
- virtual bool [Export](#) ([Format](#) format, std::string &val) const
- virtual bool [Export](#) ([Format](#) format, [XMLNode](#) &val) const
- virtual bool [Import](#) ([Format](#) format, const std::string &val)
- virtual bool [Import](#) ([Format](#) format, const [XMLNode](#) &val)

Static Public Attributes

- static [Format](#) **UNDEFINED**
- static [Format](#) **ARCAuth**
- static [Format](#) **XACML**
- static [Format](#) **SAML**

Protected Member Functions

- virtual bool **equal** (const [SecAttr](#) &b) const

Classes

- class [Format](#)
Export/import format.

5.107.1 Detailed Description

This is an abstract interface to a security attribute.

This class is meant to be inherited to implement security attributes. Depending on what data it needs to store inheriting classes may need to implement constructor and destructor. They must however override the equality and the boolean operators. The equality is meant to compare security attributes. The prototype

implies that all attributes are comparable to all others. This behaviour should be modified as needed by using `dynamic_cast` operations. The boolean cast operation is meant to embody "nullness" if that is applicable to the particular type.

5.107.2 Constructor & Destructor Documentation

5.107.2.1 Arc::SecAttr::SecAttr () [inline]

suitable for inclusion into SAML structures

5.107.3 Member Function Documentation

5.107.3.1 virtual bool Arc::SecAttr::Export (Format format, XMLNode & val) const [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute. XML node referenced by is turned into top level element of specified format.

5.107.3.2 virtual bool Arc::SecAttr::Export (Format format, std::string & val) const [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute.

5.107.3.3 virtual bool Arc::SecAttr::Import (Format format, const std::string & val) [virtual]

Fills internal structure from external object of specified format. Returns false if failed to do. The usage pattern for this method is not defined and it is provided only to make class symmetric. Hence its implementation is not required yet.

5.107.3.4 virtual Arc::SecAttr::operator bool () const [virtual]

This function should return false if the value is to be considered null, e.g. if it hasn't been set or initialized. In other cases it should return true.

Reimplemented in [Arc::MultiSecAttr](#).

5.107.3.5 bool Arc::SecAttr::operator!= (const SecAttr & b) const [inline]

This is a convenience function to allow the usage of "not equal" conditions and need not be overridden.

5.107.3.6 bool Arc::SecAttr::operator== (const SecAttr & b) const [inline]

This function should (in inheriting classes) return true if this and b are considered to represent same content. Identifying and restricting the type of b should be done using `dynamic_cast` operations. Currently it is not defined how comparison methods to be used. Hence their implementation is not required.

5.107.4 Member Data Documentation

5.107.4.1 [Format Arc::SecAttr::ARCAuth](#) [static]

own serialization/deserialization format

5.107.4.2 [Format Arc::SecAttr::SAML](#) [static]

representation for XACML policy

5.107.4.3 [Format Arc::SecAttr::XACML](#) [static]

representation for ARC authorization policy

The documentation for this class was generated from the following file:

- SecAttr.h

5.108 Arc::SecAttr::Format Class Reference

Export/import format.

```
#include <SecAttr.h>
```

Public Member Functions

- **Format** (const [Format](#) &format)
- **Format** (const char *format="")
- **Format operator=** ([Format](#) format)
- **Format operator=** (const char *format)
- **bool operator==** ([Format](#) format)
- **bool operator==** (const char *format)
- **bool operator!=** ([Format](#) format)
- **bool operator!=** (const char *format)

5.108.1 Detailed Description

Export/import format.

[Format](#) is identified by textual identity string. Class description includes basic formats only. That list may be extended.

The documentation for this class was generated from the following file:


- SecAttr.h

5.109 Arc::SecAttrValue Class Reference

This is an abstract interface to a security attribute.

```
#include <SecAttrValue.h>
```

Inheritance diagram for Arc::SecAttrValue::



Public Member Functions

- bool `operator==` (SecAttrValue &b)
- bool `operator!=` (SecAttrValue &b)
- virtual `operator bool` ()

Protected Member Functions

- virtual bool `equal` (SecAttrValue &b)

5.109.1 Detailed Description

This is an abstract interface to a security attribute.

This class is meant to be inherited to implement security attributes. Depending on what data it needs to store inheriting classes may need to implement constructor and destructor. They must however override the equality and the boolean operators. The equality is meant to compare security attributes. The prototype implies that all attributes are comparable to all others. This behaviour should be modified as needed by using `dynamic_cast` operations. The boolean cast operation is meant to embody "nullness" if that is applicable to the particular type.

5.109.2 Member Function Documentation

5.109.2.1 virtual Arc::SecAttrValue::operator bool () [virtual]

This function should return false if the value is to be considered null, e g if it hasn't been set or initialized. In other cases it should return true.

Reimplemented in [Arc::CIStrStringValue](#).

5.109.2.2 bool Arc::SecAttrValue::operator!= (SecAttrValue & b)

This is a convenience function to allow the usage of "not equal" conditions and need not be overridden.

5.109.2.3 bool Arc::SecAttrValue::operator== ([SecAttrValue](#) & *b*)

This function should (in inheriting classes) return true if this and *b* are considered to be the same. Identifying and restricting the type of *b* should be done using `dynamic_cast` operations.

The documentation for this class was generated from the following file:

- SecAttrValue.h

5.110 ArcSec::SecHandler Class Reference

Base class for simple security handling plugins.

```
#include <SecHandler.h>
```

Public Member Functions

- **SecHandler** ([Arc::Config](#) *)
- virtual bool **Handle** ([Arc::Message](#) *msg)=0

Static Protected Attributes

- static [Arc::Logger](#) **logger**

5.110.1 Detailed Description

Base class for simple security handling plugins.

This virtual class defines method `Handle()` which processes security related information/attributes in `Message` and optionally makes security decision. Instances of such classes are normally arranged in chains and are called on incoming and outgoing messages in various MCC and Service plugins. Return value of `Handle()` defines either processing should continue (true) or stop with error (false). Configuration of [SecHandler](#) is consumed during creation of instance through XML subtree fed to constructor.

The documentation for this class was generated from the following file:

- `SecHandler.h`

5.111 sechandler_descriptor Struct Reference

Identifier of SecHandler plugin.

```
#include <SecHandlerLoader.h>
```

Public Attributes

- const char * **name**
- int **version**
- [ArcSec::SecHandler](#) *(* **get_instance**)([Arc::Config](#) *cfg, [Arc::ChainContext](#) *ctx)

5.111.1 Detailed Description

Identifier of SecHandler plugin.

This structure describes one of the SecHandlers stored in a shared library. It contains name of plugin, version number and pointer to function which creates an instance of an object inherited from the SecHandler class.

The documentation for this struct was generated from the following file:


- SecHandlerLoader.h

5.112 Arc::SecHandlerFactory Class Reference

SecHandler Plugins handler.

```
#include <SecHandlerFactory.h>
```

Inheritance diagram for Arc::SecHandlerFactory::



Public Member Functions

- [SecHandlerFactory](#) ([Config](#) *cfg)
- [ArcSec::SecHandler](#) * [get_instance](#) (const std::string &name, [Config](#) *cfg, [ChainContext](#) *ctx)
- [ArcSec::SecHandler](#) * [get_instance](#) (const std::string &name, int version, [Config](#) *cfg, [ChainContext](#) *ctx)
- [ArcSec::SecHandler](#) * [get_instance](#) (const std::string &name, int min_version, int max_version, [Config](#) *cfg, [ChainContext](#) *ctx)

5.112.1 Detailed Description

SecHandler Plugins handler.

This class handles shared libraries containing SecHandlers

5.112.2 Constructor & Destructor Documentation

5.112.2.1 Arc::SecHandlerFactory::SecHandlerFactory ([Config](#) *cfg)

Constructor - accepts configuration (not yet used) meant to tune loading of module.

5.112.3 Member Function Documentation

5.112.3.1 [ArcSec::SecHandler](#)* Arc::SecHandlerFactory::get_instance (const std::string & name, [Config](#) *cfg, [ChainContext](#) *ctx)

These methods load shared library named lib'name', locate symbol representing descriptor of SecHandler and calls it's constructor function. Supplied configuration tree is passed to constructor. Returns created SecHandler instance.

Reimplemented from [Arc::LoaderFactory](#).

The documentation for this class was generated from the following file:

- SecHandlerFactory.h

5.113 ArcSec::Security Class Reference

Common stuff used by security related slasses.

```
#include <Security.h>
```

Friends

- class **SecHandler**
- class **PDP**

5.113.1 Detailed Description

Common stuff used by security related slasses.

This class is just a place where to put common stuff that is used by security related slasses. So far it only contains a logger.

The documentation for this class was generated from the following file:


- Security.h

5.114 Arc::Service Class Reference

[Service](#) - last component in a [Message](#) Chain.

```
#include <Service.h>
```

Inheritance diagram for Arc::Service::



Public Member Functions

- [Service](#) ([Arc::Config](#) *)
- virtual void [AddSecHandler](#) ([Arc::Config](#) *cfg, [ArcSec::SecHandler](#) *sechandler, const std::string &label="")
- virtual bool [RegistrationCollector](#) ([Arc::XMLNode](#) &doc)
- virtual std::string [getID](#) ()

Protected Member Functions

- bool [ProcessSecHandlers](#) ([Arc::Message](#) &message, const std::string &label="")

Protected Attributes

- std::map< std::string, std::list< [ArcSec::SecHandler](#) * > > [sechandlers_](#)

Static Protected Attributes

- static [Logger](#) [logger](#)

5.114.1 Detailed Description

[Service](#) - last component in a [Message](#) Chain.

This class which defines interface and common functionality for every [Service](#) plugin. Interface is made of method [process\(\)](#) which is called by [Plexer](#) or [MCC](#) class. There is one [Service](#) object created for every service description processed by [Loader](#) class objects. Classes derived from [Service](#) class must implement [process\(\)](#) method of [MCCInterface](#). It is up to developer how internal state of service is stored and communicated to other services and external utilities. [Service](#) is free to expect any type of payload passed to it and generate any payload as well. Useful types depend on MCCs in chain which leads to that service. For example if service is expected to be linked to SOAP [MCC](#) it must accept and generate messages with [PayloadSOAP](#) payload. Method [process\(\)](#) of class derived from [Service](#) class may be called concurrently in multiple threads. Developers must take that into account and write thread-safe implementation. Simple example of service is provided in /src/tests/echo/echo.cpp of source tree. The way to write client counterpart of corresponding service is undefined yet. For example see /src/tests/echo/test.cpp .

5.114.2 Constructor & Destructor Documentation

5.114.2.1 Arc::Service::Service ([Arc::Config](#) *) [inline]

Example contructor - Server takes at least it's configuration subtree

5.114.3 Member Function Documentation

5.114.3.1 virtual void Arc::Service::AddSecHandler ([Arc::Config](#) * *cfg*, [ArcSec::SecHandler](#) * *sechandler*, const std::string & *label* = "") [virtual]

Add security components/handlers to this [MCC](#). For more information please see description of [MCC::AddSecHandler](#)

5.114.3.2 virtual std::string Arc::Service::getID () [inline, virtual]

[Service](#) may implement own service identitifer gathering method. This method return identifier of service which is used for registering it Information Services.

5.114.3.3 bool Arc::Service::ProcessSecHandlers ([Arc::Message](#) & *message*, const std::string & *label* = "") [protected]

Executes security handlers of specified queue. For more information please see description of [MCC::ProcessSecHandlers](#)

5.114.3.4 virtual bool Arc::Service::RegistrationCollector ([Arc::XMLNode](#) & *doc*) [virtual]

[Service](#) specific registartion collector, used for generate service registartions. In implemented service this method should generate GLUE2 document with part of service description which service wishes to advertise to Information Services.

5.114.4 Member Data Documentation

5.114.4.1 [Logger](#) Arc::Service::logger [static, protected]

[Logger](#) object used to print messages generated by this class.

5.114.4.2 std::map<std::string, std::list<[ArcSec::SecHandler](#)*> > Arc::Service::sechandlers_ [protected]

Set of labeled authentication and authorization handlers. [MCC](#) calls sequence of handlers at specific point depending on associated identifier. in most aces those are "in" and "out" for incoming and outgoing messages correspondingly.

The documentation for this class was generated from the following file:

- Service.h

5.115 service_descriptor Struct Reference

Identifier of Service plugin.

```
#include <ServiceLoader.h>
```

Public Attributes

- const char * **name**
- int **version**
- [Arc::Service](#) *(* **get_instance**)([Arc::Config](#) *cfg, [Arc::ChainContext](#) *ctx)

5.115.1 Detailed Description

Identifier of Service plugin.

This structure describes one of the Services stored in a shared library. It contains name of plugin, version number and pointer to function which creates an instance of an object inherited from the Service class.

The documentation for this struct was generated from the following file:


- ServiceLoader.h

5.116 Arc::ServiceFactory Class Reference

[Service](#) Plugins handler.

```
#include <ServiceFactory.h>
```

Inheritance diagram for Arc::ServiceFactory::



Public Member Functions

- [ServiceFactory](#) ([Config](#) *cfg)
- [Service](#) * [get_instance](#) (const std::string &name, [Config](#) *cfg, [ChainContext](#) *ctx)
- [Service](#) * [get_instance](#) (const std::string &name, int version, [Config](#) *cfg, [ChainContext](#) *ctx)
- [Service](#) * [get_instance](#) (const std::string &name, int min_version, int max_version, [Config](#) *cfg, [ChainContext](#) *ctx)

5.116.1 Detailed Description

[Service](#) Plugins handler.

This class handles shared libraries containing Services

5.116.2 Constructor & Destructor Documentation

5.116.2.1 Arc::ServiceFactory::ServiceFactory ([Config](#) * cfg)

Constructor - accepts configuration (not yet used) meant to tune loading of module.

5.116.3 Member Function Documentation

5.116.3.1 [Service](#)* Arc::ServiceFactory::get_instance (const std::string & name, [Config](#) * cfg, [ChainContext](#) * ctx)

These methods load shared library named lib'name', locate symbol representing descriptor of [Service](#) and calls it's constructor function. Supplied configuration tree is passed to constructor. Returns created [Service](#) instance.

Reimplemented from [Arc::LoaderFactory](#).

The documentation for this class was generated from the following file:

- ServiceFactory.h

5.117 Arc::SimpleCondition Class Reference

Simple triggered condition.

```
#include <Thread.h>
```

Public Member Functions

- void [lock](#) (void)
- void [unlock](#) (void)
- void [signal](#) (void)
- void [signal_nonblock](#) (void)
- void [broadcast](#) (void)
- void [wait](#) (void)
- void [wait_nonblock](#) (void)
- bool [wait](#) (int t)
- void [reset](#) (void)

5.117.1 Detailed Description

Simple triggered condition.

Provides condition and semaphor objects in one element.

5.117.2 Member Function Documentation

5.117.2.1 void Arc::SimpleCondition::broadcast (void) [inline]

Signal about condition to all waiting threads

5.117.2.2 void Arc::SimpleCondition::lock (void) [inline]

Acquire semaphor

5.117.2.3 void Arc::SimpleCondition::reset (void) [inline]

Reset object to initial state

5.117.2.4 void Arc::SimpleCondition::signal (void) [inline]

Signal about condition

5.117.2.5 void Arc::SimpleCondition::signal_nonblock (void) [inline]

Signal about condition without using semaphor

5.117.2.6 void Arc::SimpleCondition::unlock (void) [inline]

Release semaphor

5.117.2.7 bool Arc::SimpleCondition::wait (int *t*) [inline]

Wait for condition no longer than *t* milliseconds

5.117.2.8 void Arc::SimpleCondition::wait (void) [inline]

Wait for condition

5.117.2.9 void Arc::SimpleCondition::wait_nonblock (void) [inline]

Wait for condition without using semaphor

The documentation for this class was generated from the following file:

- Thread.h

5.118 Arc::SOAPMessage Class Reference

[Message](#) restricted to SOAP payload.

```
#include <SOAPMessage.h>
```

Public Member Functions

- [SOAPMessage](#) (void)
- [SOAPMessage](#) (long msg_ptr_addr)
- [SOAPMessage](#) ([Arc::Message](#) &msg)
- [~SOAPMessage](#) (void)
- [Arc::SOAPEnvelope](#) * [Payload](#) (void)
- void [Payload](#) ([Arc::SOAPEnvelope](#) *new_payload)
- [Arc::MessageAttributes](#) * [Attributes](#) (void)
- void [Attributes](#) ([Arc::MessageAttributes](#) *attributes)
- [Arc::MessageAuth](#) * [Auth](#) (void)
- void [Auth](#) ([Arc::MessageAuth](#) *auth)
- [Arc::MessageContext](#) * [Context](#) (void)
- void [Context](#) ([Arc::MessageContext](#) *context)

5.118.1 Detailed Description

[Message](#) restricted to SOAP payload.

This is a special [Message](#) intended to be used in language bindings for programming languages which are not flexible enough to support all kinds of Payloads. It is passed through chain of MCCs and works like the [Message](#) but can carry only SOAP content.

5.118.2 Constructor & Destructor Documentation

5.118.2.1 Arc::SOAPMessage::SOAPMessage (void) [inline]

Dummy constructor

5.118.2.2 Arc::SOAPMessage::SOAPMessage (long msg_ptr_addr)

Copy constructor. Used by language bindings

5.118.2.3 Arc::SOAPMessage::SOAPMessage ([Arc::Message](#) & msg)

Copy constructor. Ensures shallow copy.

5.118.2.4 Arc::SOAPMessage::~~SOAPMessage (void)

Destructor does not affect referred objects

5.118.3 Member Function Documentation

5.118.3.1 [Arc::MessageAttributes](#)* Arc::SOAPMessage::Attributes (void) [inline]

Returns a pointer to the current attributes object or NULL if no attributes object has been assigned.

5.118.3.2 void Arc::SOAPMessage::Payload (Arc::SOAPEnvelope * *new_payload*)

Replace payload with a COPY of new one

5.118.3.3 Arc::SOAPEnvelope* Arc::SOAPMessage::Payload (void)

Returns pointer to current payload or NULL if no payload assigned.

The documentation for this class was generated from the following file:


- SOAPMessage.h

5.119 ArcSec::Source Class Reference

Acquires and parses XML document from specified source.

```
#include <Source.h>
```

Inheritance diagram for ArcSec::Source::



Public Member Functions

- [Source](#) (const [Source](#) &s)
- [Source](#) ([Arc::XMLNode](#) &xml)
- [Source](#) (std::istream &stream)
- [Source](#) ([Arc::URL](#) &url)
- [Source](#) (const std::string &str)
- [Arc::XMLNode Get](#) (void) const
- [operator bool](#) (void)
- [operator Arc::XMLNode](#) (void)

5.119.1 Detailed Description

Acquires and parses XML document from specified source.

This class is to be used to provide easy way to specify different sources for XML Authorization Policies and Requests.

5.119.2 Constructor & Destructor Documentation

5.119.2.1 ArcSec::Source::Source (const [Source](#) & s) [inline]

Copy constructor.

Use this constructor only for temporary objects. Parsed XML document is still owned by copied source and hence lifetime of create object should not exceed that of copied one.

5.119.2.2 ArcSec::Source::Source ([Arc::XMLNode](#) & xml)

Copy XML tree from XML subtree referred by xml.

5.119.2.3 ArcSec::Source::Source (std::istream & stream)

Read XML document from stream and parse it.

5.119.2.4 ArcSec::Source::Source ([Arc::URL](#) & *url*)

Fetch XML document from specified url and parse it.

This constructor is not implemented yet.

5.119.2.5 ArcSec::Source::Source (const std::string & *str*)

Read XML document from string.

5.119.3 Member Function Documentation

5.119.3.1 [Arc::XMLNode](#) ArcSec::Source::Get (void) const [inline]

Get reference to parsed document.

5.119.3.2 ArcSec::Source::operator bool (void) [inline]

Returns true if valid document is available.

The documentation for this class was generated from the following file:


- Source.h

5.120 ArcSec::SourceFile Class Reference

Convenience class for obtaining XML document from file.

```
#include <Source.h>
```

Inheritance diagram for ArcSec::SourceFile::



Public Member Functions

- [SourceFile](#) (const [SourceFile](#) &s)
- [SourceFile](#) (const char *name)
- [SourceFile](#) (const std::string &name)

5.120.1 Detailed Description

Convenience class for obtaining XML document from file.

5.120.2 Constructor & Destructor Documentation

5.120.2.1 ArcSec::SourceFile::SourceFile (const [SourceFile](#) & s) [inline]

See corresponding constructor of [Source](#) class.

5.120.2.2 ArcSec::SourceFile::SourceFile (const char * name)

Read XML document from file named name and store it.

5.120.2.3 ArcSec::SourceFile::SourceFile (const std::string & name)

Read XML document from file named name and store it.

The documentation for this class was generated from the following file:


- Source.h

5.121 ArcSec::SourceURL Class Reference

Convenience class for obtaining XML document from remote URL.

```
#include <Source.h>
```

Inheritance diagram for ArcSec::SourceURL::



Public Member Functions

- [SourceURL](#) (const [SourceURL](#) &s)
- [SourceURL](#) (const char *url)
- [SourceURL](#) (const std::string &url)

5.121.1 Detailed Description

Convenience class for obtaining XML document from remote URL.

5.121.2 Constructor & Destructor Documentation

5.121.2.1 ArcSec::SourceURL::SourceURL (const [SourceURL](#) & s) [inline]

See corresponding constructor of [Source](#) class.

5.121.2.2 ArcSec::SourceURL::SourceURL (const char * url)

Read XML document from URL url and store it.

5.121.2.3 ArcSec::SourceURL::SourceURL (const std::string & url)

Read XML document from URL url and store it.

The documentation for this class was generated from the following file:

- Source.h

5.122 Arc::Time Class Reference

A class for storing and manipulating times.

```
#include <DateTime.h>
```

Public Member Functions

- [Time](#) ()
- [Time](#) (const time_t &)
- [Time](#) (const std::string &)
- [Time](#) & [operator=](#) (const time_t &)
- [Time](#) & [operator=](#) (const [Time](#) &)
- void [SetTime](#) (const time_t &)
- time_t [GetTime](#) () const
- [operator std::string](#) () const
- std::string [str](#) (const [TimeFormat](#) &=time_format) const
- bool [operator<](#) (const [Time](#) &) const
- bool [operator>](#) (const [Time](#) &) const
- bool [operator<=](#) (const [Time](#) &) const
- bool [operator>=](#) (const [Time](#) &) const
- bool [operator==](#) (const [Time](#) &) const
- bool [operator!=](#) (const [Time](#) &) const
- [Time](#) [operator+](#) (const Period &) const
- [Time](#) [operator-](#) (const Period &) const
- Period [operator-](#) (const [Time](#) &) const

Static Public Member Functions

- static void [SetFormat](#) (const [TimeFormat](#) &)
- static [TimeFormat](#) [GetFormat](#) ()

5.122.1 Detailed Description

A class for storing and manipulating times.

5.122.2 Constructor & Destructor Documentation

5.122.2.1 Arc::Time::Time ()

Default constructor. The time is put equal the current time.

5.122.2.2 Arc::Time::Time (const time_t &)

Constructor that takes a time_t variable and stores it.

5.122.2.3 Arc::Time::Time (const std::string &)

Constructor that tries to convert a string into a time_t.

5.122.3 Member Function Documentation

5.122.3.1 static TimeFormat Arc::Time::GetFormat () [static]

Gets the default format for time strings.

5.122.3.2 time_t Arc::Time::GetTime () const

gets the time

5.122.3.3 Arc::Time::operator std::string () const

Returns a string representation of the time, using the default format.

5.122.3.4 bool Arc::Time::operator!= (const Time &) const

Comparing two Time objects.

5.122.3.5 Time Arc::Time::operator+ (const Period &) const

Adding Time object with Period object.

5.122.3.6 Period Arc::Time::operator- (const Time &) const

Subtracting Time object from the other Time object.

5.122.3.7 Time Arc::Time::operator- (const Period &) const

Subtracting Period object from Time object.

5.122.3.8 bool Arc::Time::operator< (const Time &) const

Comparing two Time objects.

5.122.3.9 bool Arc::Time::operator<= (const Time &) const

Comparing two Time objects.

5.122.3.10 Time& Arc::Time::operator= (const Time &)

Assignment operator from a Time.

5.122.3.11 Time& Arc::Time::operator= (const time_t &)

Assignment operator from a time_t.

5.122.3.12 `bool Arc::Time::operator==(const Time &) const`

Comparing two `Time` objects.

5.122.3.13 `bool Arc::Time::operator>(const Time &) const`

Comparing two `Time` objects.

5.122.3.14 `bool Arc::Time::operator>=(const Time &) const`

Comparing two `Time` objects.

5.122.3.15 `static void Arc::Time::SetFormat(const TimeFormat &) [static]`

Sets the default format for time strings.

5.122.3.16 `void Arc::Time::SetTime(const time_t &)`

sets the time

5.122.3.17 `std::string Arc::Time::str(const TimeFormat &= time_format) const`

Returns a string representation of the time, using the specified format.

The documentation for this class was generated from the following file:


- `DateTime.h`

5.123 Arc::URL Class Reference

Class to hold general URL's.

```
#include <URL.h>
```

Inheritance diagram for Arc::URL::



Public Types

- **base**
- **onelevel**
- **subtree**
- enum [Scope](#) { **base**, **onelevel**, **subtree** }

Public Member Functions

- [URL](#) ()
- [URL](#) (const std::string &url)
- virtual [~URL](#) ()
- const std::string & [Protocol](#) () const
- void [ChangeProtocol](#) (const std::string &newprot)
- const std::string & [Username](#) () const
- const std::string & [Passwd](#) () const
- const std::string & [Host](#) () const
- void [ChangeHost](#) (const std::string &newhost)
- int [Port](#) () const
- void [ChangePort](#) (int newport)
- const std::string & [Path](#) () const
- void [ChangePath](#) (const std::string &newpath)
- const std::map< std::string, std::string > & [HTTPOptions](#) () const
- const std::string & [HTTPOption](#) (const std::string &option, const std::string &undefined="") const
- const std::list< std::string > & [LDAPAttributes](#) () const
- void [AddLDAPAttribute](#) (const std::string &attribute)
- [Scope](#) [LDAPScope](#) () const
- void [ChangeLDAPScope](#) (const [Scope](#) newscope)
- const std::string & [LDAPFilter](#) () const
- void [ChangeLDAPFilter](#) (const std::string &newfilter)
- const std::map< std::string, std::string > & [Options](#) () const
- const std::string & [Option](#) (const std::string &option, const std::string &undefined="") const
- void [AddOption](#) (const std::string &option, const std::string &value, bool overwrite=true)
- const std::list< [URLLocation](#) > & [Locations](#) () const
- const std::map< std::string, std::string > & [CommonLocOptions](#) () const

- `const std::string & CommonLocOption (const std::string &option, const std::string &undefined="") const`
- `virtual std::string str () const`
- `virtual std::string fullstr () const`
- `virtual std::string ConnectionURL () const`
- `bool operator< (const URL &url) const`
- `bool operator== (const URL &url) const`
- `operator bool () const`
- `bool operator! () const`

Static Protected Member Functions

- `static std::string BaseDN2Path (const std::string &)`
- `static std::string Path2BaseDN (const std::string &)`

Protected Attributes

- `std::string protocol`
- `std::string username`
- `std::string passwd`
- `std::string host`
- `int port`
- `std::string path`
- `std::map< std::string, std::string > httpoptions`
- `std::list< std::string > ldapattributes`
- `Scope ldapscope`
- `std::string ldapfilter`
- `std::map< std::string, std::string > urloptions`
- `std::list< URLLocation > locations`
- `std::map< std::string, std::string > commonlocoptions`

Friends

- `std::ostream & operator<< (std::ostream &out, const URL &u)`

5.123.1 Detailed Description

Class to hold general URL's.

The [URL](#) is split into protocol, hostname, port and path.

5.123.2 Member Enumeration Documentation

5.123.2.1 enum [Arc::URL::Scope](#)

Scope for LDAP URLs

5.123.3 Constructor & Destructor Documentation

5.123.3.1 Arc::URL::URL ()

Empty constructor. Necessary when the class is part of another class and the like.

5.123.3.2 Arc::URL::URL (const std::string & *url*)

Constructs a new [URL](#) from a string representation.

5.123.3.3 virtual Arc::URL::~~URL () [virtual]

[URL](#) Destructor

5.123.4 Member Function Documentation

5.123.4.1 void Arc::URL::AddLDAPAttribute (const std::string & *attribute*)

Adds an LDAP attribute.

5.123.4.2 void Arc::URL::AddOption (const std::string & *option*, const std::string & *value*, bool *overwrite* = true)

Adds a [URL](#) option.

5.123.4.3 static std::string Arc::URL::BaseDN2Path (const std::string &) [static, protected]

a private method that converts an ldap basedn to a path.

5.123.4.4 void Arc::URL::ChangeHost (const std::string & *newhost*)

Changes the hostname of the [URL](#).

5.123.4.5 void Arc::URL::ChangeLDAPFilter (const std::string & *newfilter*)

Changes the LDAP filter.

5.123.4.6 void Arc::URL::ChangeLDAPScope (const [Scope](#) *newscope*)

Changes the LDAP scope.

5.123.4.7 void Arc::URL::ChangePath (const std::string & *newpath*)

Changes the path of the [URL](#).

5.123.4.8 void Arc::URL::ChangePort (int *newport*)

Changes the port of the [URL](#).

5.123.4.9 void Arc::URL::ChangeProtocol (const std::string & *newprot*)

Changes the protocol of the [URL](#).

5.123.4.10 const std::string& Arc::URL::CommonLocOption (const std::string & *option*, const std::string & *undefined* = "") const

Returns the value of a common location option.

Parameters:

option The option whose value is returned.

undefined This value is returned if the common location option is not defined.

5.123.4.11 const std::map<std::string, std::string>& Arc::URL::CommonLocOptions () const

Returns the common location options if any.

5.123.4.12 virtual std::string Arc::URL::ConnectionURL () const [virtual]

Returns a string representation with protocol, host and port only

5.123.4.13 virtual std::string Arc::URL::fullstr () const [virtual]

Returns a string representation including options and locations

Reimplemented in [Arc::URLLocation](#).

5.123.4.14 const std::string& Arc::URL::Host () const

Returns the hostname of the [URL](#).

5.123.4.15 const std::string& Arc::URL::HTTPOption (const std::string & *option*, const std::string & *undefined* = "") const

Returns the value of an HTTP option.

Parameters:

option The option whose value is returned.

undefined This value is returned if the HTTP option is not defined.

5.123.4.16 const std::map<std::string, std::string>& Arc::URL::HTTPOptions () const

Returns HTTP options if any.

5.123.4.17 `const std::list<std::string>& Arc::URL::LDAPAttributes () const`

Returns the LDAP attributes if any.

5.123.4.18 `const std::string& Arc::URL::LDAPFilter () const`

Returns the LDAP filter.

5.123.4.19 `Scope Arc::URL::LDAPScope () const`

Returns the LDAP scope.

5.123.4.20 `const std::list<URLLocation>& Arc::URL::Locations () const`

Returns the locations if any.

5.123.4.21 `Arc::URL::operator bool () const`

Check if instance holds valid [URL](#)

5.123.4.22 `bool Arc::URL::operator< (const URL & url) const`

Compares one [URL](#) to another

5.123.4.23 `bool Arc::URL::operator== (const URL & url) const`

Is one [URL](#) equal to another?

5.123.4.24 `const std::string& Arc::URL::Option (const std::string & option, const std::string & undefined = "") const`

Returns the value of a [URL](#) option.

Parameters:

option The option whose value is returned.

undefined This value is returned if the [URL](#) option is not defined.

5.123.4.25 `const std::map<std::string, std::string>& Arc::URL::Options () const`

Returns [URL](#) options if any.

5.123.4.26 `const std::string& Arc::URL::Passwd () const`

Returns the password of the [URL](#).

5.123.4.27 `const std::string& Arc::URL::Path () const`

Returns the path of the [URL](#).

5.123.4.28 `static std::string Arc::URL::Path2BaseDN (const std::string &) [static, protected]`

a private method that converts an ldap path to a basedn.

5.123.4.29 `int Arc::URL::Port () const`

Returns the port of the [URL](#).

5.123.4.30 `const std::string& Arc::URL::Protocol () const`

Returns the protocol of the [URL](#).

5.123.4.31 `virtual std::string Arc::URL::str () const [virtual]`

Returns a string representation of the [URL](#).

Reimplemented in [Arc::URLLocation](#).

5.123.4.32 `const std::string& Arc::URL::Username () const`

Returns the username of the [URL](#).

5.123.5 Friends And Related Function Documentation**5.123.5.1** `std::ostream& operator<< (std::ostream & out, const URL & u) [friend]`

Overloaded operator << to print a [URL](#).

5.123.6 Member Data Documentation**5.123.6.1** `std::map<std::string, std::string> Arc::URL::commonlocoptions [protected]`

common location options for index server URLs.

5.123.6.2 `std::string Arc::URL::host [protected]`

hostname of the url.

5.123.6.3 `std::map<std::string, std::string> Arc::URL::httpoptions [protected]`

HTTP options of the url.

5.123.6.4 `std::list<std::string>` [Arc::URL::ldapattributes](#) [protected]

LDAP attributes of the url.

5.123.6.5 `std::string` [Arc::URL::ldapfilter](#) [protected]

LDAP filter of the url.

5.123.6.6 `Scope` [Arc::URL::ldapscope](#) [protected]

LDAP scope of the url.

5.123.6.7 `std::list<URLLocation>` [Arc::URL::locations](#) [protected]

locations for index server URLs.

5.123.6.8 `std::string` [Arc::URL::passwd](#) [protected]

password of the url.

5.123.6.9 `std::string` [Arc::URL::path](#) [protected]

the url path.

5.123.6.10 `int` [Arc::URL::port](#) [protected]

portnumber of the url.

5.123.6.11 `std::string` [Arc::URL::protocol](#) [protected]

the url protocol.

5.123.6.12 `std::map<std::string, std::string>` [Arc::URL::urloptions](#) [protected]

options of the url.

5.123.6.13 `std::string` [Arc::URL::username](#) [protected]

username of the url.

The documentation for this class was generated from the following file:


- URL.h

5.124 Arc::URLLocation Class Reference

Class to hold a resolved [URL](#) location.

```
#include <URL.h>
```

Inheritance diagram for Arc::URLLocation::



Public Member Functions

- [URLLocation](#) (const std::string &url)
- [URLLocation](#) (const std::string &url, const std::string &name)
- [URLLocation](#) (const [URL](#) &url)
- [URLLocation](#) (const [URL](#) &url, const std::string &name)
- [URLLocation](#) (const std::map< std::string, std::string > &options, const std::string &name)
- virtual ~[URLLocation](#) ()
- const std::string & [Name](#) () const
- virtual std::string [str](#) () const
- virtual std::string [fullstr](#) () const

Protected Attributes

- std::string [name](#)

5.124.1 Detailed Description

Class to hold a resolved [URL](#) location.

It is specific to file indexing service registrations.

5.124.2 Constructor & Destructor Documentation

5.124.2.1 Arc::URLLocation::URLLocation (const std::string & url)

Creates a [URLLocation](#) from a string representaion.

5.124.2.2 Arc::URLLocation::URLLocation (const std::string & url, const std::string & name)

Creates a [URLLocation](#) from a string representaion and a name.

5.124.2.3 Arc::URLLocation::URLLocation (const [URL](#) & url)

Creates a [URLLocation](#) from a [URL](#).

5.124.2.4 Arc::URLLocation::URLLocation (const [URL](#) & *url*, const std::string & *name*)

Creates a [URLLocation](#) from a [URL](#) and a name.

5.124.2.5 Arc::URLLocation::URLLocation (const std::map< std::string, std::string > & *options*, const std::string & *name*)

Creates a [URLLocation](#) from options and a name.

5.124.2.6 virtual Arc::URLLocation::~~URLLocation () [virtual]

[URLLocation](#) destructor.

5.124.3 Member Function Documentation**5.124.3.1 virtual std::string Arc::URLLocation::fullstr () const [virtual]**

Returns a string representation including options and locations

Reimplemented from [Arc::URL](#).

5.124.3.2 const std::string& Arc::URLLocation::Name () const

Returns the [URLLocation](#) name.

5.124.3.3 virtual std::string Arc::URLLocation::str () const [virtual]

Returns a string representation of the [URLLocation](#).

Reimplemented from [Arc::URL](#).

5.124.4 Member Data Documentation**5.124.4.1 std::string [Arc::URLLocation::name](#) [protected]**

the [URLLocation](#) name as registered in the indexing service.

The documentation for this class was generated from the following file:

- [URL.h](#)

5.125 Arc::UsernameToken Class Reference

Interface for manipulation of WS-Security according to Username Token Profile.

```
#include <UsernameToken.h>
```

Public Types

- **PasswordText**
- **PasswordDigest**
- enum [PasswordType](#) { **PasswordText**, **PasswordDigest** }

Public Member Functions

- [UsernameToken](#) (SOAPEnvelope &soap)
- [UsernameToken](#) (SOAPEnvelope &soap, const std::string &username, const std::string &password, const std::string &uid, [PasswordType](#) pwdtype)
- [UsernameToken](#) (SOAPEnvelope &soap, const std::string &username, const std::string &id, bool mac, int iteration)
- [operator bool](#) (void)
- std::string [Username](#) (void)
- bool [Authenticate](#) (const std::string &password, std::string &derived_key)
- bool [Authenticate](#) (std::istream &password, std::string &derived_key)

Protected Attributes

- [XMLNode](#) header_

5.125.1 Detailed Description

Interface for manipulation of WS-Security according to Username Token Profile.

5.125.2 Member Enumeration Documentation

5.125.2.1 enum [Arc::UsernameToken::PasswordType](#)

SOAP header element

5.125.3 Constructor & Destructor Documentation

5.125.3.1 [Arc::UsernameToken::UsernameToken](#) (SOAPEnvelope & *soap*)

Link to existing SOAP header and parse Username Token information. Username Token related information is extracted from SOAP header and stored in class variables.

5.125.3.2 Arc::UsernameToken::UsernameToken (SOAPEnvelope & *soap*, const std::string & *username*, const std::string & *password*, const std::string & *uid*, PasswordType *pwdtype*)

Add Username Token information into the SOAP header. Generated token contains elements Username and Password and is meant to be used for authentication.

Parameters:

soap the SOAP message

username <wsse:Username>...</wsse:Username> - if empty it is entered interactively from stdin

password <wsse:Password Type="...">...</wsse:Password> - if empty it is entered interactively from stdin

uid <wsse:UsernameToken wsu:ID="...">

pwdtype <wsse:Password Type="...">...</wsse:Password>

5.125.3.3 Arc::UsernameToken::UsernameToken (SOAPEnvelope & *soap*, const std::string & *username*, const std::string & *id*, bool *mac*, int *iteration*)

Add Username Token information into the SOAP header. Generated token contains elements Username and Salt and is meant to be used for deriving Key Derivation.

Parameters:

soap the SOAP message

username <wsse:Username>...</wsse:Username>

mac if derived key is meant to be used for Message Authentication Code

iteration <wsse11:Iteration>...</wsse11:Iteration>

5.125.4 Member Function Documentation

5.125.4.1 bool Arc::UsernameToken::Authenticate (std::istream & *password*, std::string & *derived_key*)

Checks parsed token against password stored in specified stream. If token is meant to be used for deriving a key then key is returned in *derived_key*

5.125.4.2 bool Arc::UsernameToken::Authenticate (const std::string & *password*, std::string & *derived_key*)

Checks parsed/generated token against specified password. If token is meant to be used for deriving a key then key is returned in *derived_key*. In that case authentication is performed outside of UsernameToken class using obtained *derived_key*.

5.125.4.3 Arc::UsernameToken::operator bool (void)

Returns true of constructor succeeded

5.125.4.4 std::string Arc::UsernameToken::Username (void)

Returns username associated with this instance

The documentation for this class was generated from the following file:

- UsernameToken.h

5.126 Arc::WSAEndpointReference Class Reference

Interface for manipulation of WS-Adressing Endpoint Reference.

```
#include <WSA.h>
```

Public Member Functions

- [WSAEndpointReference](#) ([XMLNode](#) epr)
- [WSAEndpointReference](#) (const std::string &address)
- [WSAEndpointReference](#) (void)
- [~WSAEndpointReference](#) (void)
- std::string [Address](#) (void) const
- void [Address](#) (const std::string &uri)
- [WSAEndpointReference](#) & [operator=](#) (const std::string &address)
- [XMLNode](#) [ReferenceParameters](#) (void)
- [XMLNode](#) [MetaData](#) (void)
- [operator XMLNode](#) (void)

Protected Attributes

- [XMLNode](#) epr_

5.126.1 Detailed Description

Interface for manipulation of WS-Adressing Endpoint Reference.

It works on Endpoint Reference stored in XML tree. No information is stored in this object except reference to corresponding XML subtree.

5.126.2 Constructor & Destructor Documentation

5.126.2.1 Arc::WSAEndpointReference::WSAEndpointReference ([XMLNode](#) epr)

Linking to existing EPR in XML tree

5.126.2.2 Arc::WSAEndpointReference::WSAEndpointReference (const std::string & address)

Creating independent EPR - not implemented

5.126.2.3 Arc::WSAEndpointReference::WSAEndpointReference (void)

Dummy constructor - creates invalid instance

5.126.2.4 Arc::WSAEndpointReference::~~WSAEndpointReference (void)

Destructor. All empty elements of EPR XML are destroyed here too

5.126.3 Member Function Documentation

5.126.3.1 `void Arc::WSAEndpointReference::Address (const std::string & uri)`

Assigns new Address value. If EPR had no Address element it is created.

5.126.3.2 `std::string Arc::WSAEndpointReference::Address (void) const`

Returns Address ([URL](#)) encoded in EPR

5.126.3.3 [XMLNode](#) Arc::WSAEndpointReference::MetaData (void)

Access to MetaData element of EPR. Obtained XML element should be manipulated directly in application-dependent way. If EPR had no MetaData element it is created.

5.126.3.4 `Arc::WSAEndpointReference::operator XMLNode (void)`

Returns reference to EPR top XML node

5.126.3.5 [WSAEndpointReference&](#) Arc::WSAEndpointReference::operator= (const std::string & address)

Same as Address(uri)

5.126.3.6 [XMLNode](#) Arc::WSAEndpointReference::ReferenceParameters (void)

Access to ReferenceParameters element of EPR. Obtained XML element should be manipulated directly in application-dependent way. If EPR had no ReferenceParameters element it is created.

The documentation for this class was generated from the following file:

- WSA.h

5.127 Arc::WSAHeader Class Reference

Interface for manipulation WS-Addressing information in SOAP header.

```
#include <WSA.h>
```

Public Member Functions

- [WSAHeader](#) (SOAPEnvelope &soap)
- [WSAHeader](#) (const std::string &action)
- std::string [To](#) (void) const
- void [To](#) (const std::string &uri)
- [WSAEndpointReference From](#) (void)
- [WSAEndpointReference ReplyTo](#) (void)
- [WSAEndpointReference FaultTo](#) (void)
- std::string [Action](#) (void) const
- void [Action](#) (const std::string &uri)
- std::string [MessageID](#) (void) const
- void [MessageID](#) (const std::string &uri)
- std::string [RelatesTo](#) (void) const
- void [RelatesTo](#) (const std::string &uri)
- std::string [RelationshipType](#) (void) const
- void [RelationshipType](#) (const std::string &uri)
- [XMLNode ReferenceParameter](#) (int n)
- [XMLNode ReferenceParameter](#) (const std::string &name)
- [XMLNode NewReferenceParameter](#) (const std::string &name)
- [operator XMLNode](#) (void)

Static Public Member Functions

- static bool [Check](#) (SOAPEnvelope &soap)

Protected Attributes

- [XMLNode header_](#)
- bool [header_allocated_](#)

5.127.1 Detailed Description

Interface for manipulation WS-Addressing information in SOAP header.

It works on Endpoint Reference stored in XML tree. No information is stored in this object except reference to corresponding XML subtree.

5.127.2 Constructor & Destructor Documentation

5.127.2.1 Arc::WSAHeader::WSAHeader (SOAPEnvelope & soap)

Linking to a header of existing SOAP message

5.127.2.2 Arc::WSAHeader::WSAHeader (const std::string & action)

Creating independent SOAP header - not implemented

5.127.3 Member Function Documentation**5.127.3.1 void Arc::WSAHeader::Action (const std::string & uri)**

Set content of Action element of SOAP Header. If such element does not exist it's created.

5.127.3.2 std::string Arc::WSAHeader::Action (void) const

Returns content of Action element of SOAP Header.

5.127.3.3 static bool Arc::WSAHeader::Check (SOAPEnvelope & soap) [static]

Tells if specified SOAP message has WSA header

5.127.3.4 [WSAEndpointReference](#) Arc::WSAHeader::FaultTo (void)

Returns FaultTo element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulated.

5.127.3.5 [WSAEndpointReference](#) Arc::WSAHeader::From (void)

Returns From element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulated.

5.127.3.6 void Arc::WSAHeader::MessageID (const std::string & uri)

Set content of MessageID element of SOAP Header. If such element does not exist it's created.

5.127.3.7 std::string Arc::WSAHeader::MessageID (void) const

Returns content of MessageID element of SOAP Header.

5.127.3.8 [XMLNode](#) Arc::WSAHeader::NewReferenceParameter (const std::string & name)

Creates new ReferenceParameter element with specified name. Returns reference to created element.

5.127.3.9 Arc::WSAHeader::operator [XMLNode](#) (void)

Returns reference to SOAP Header - not implemented

5.127.3.10 [XMLNode](#) Arc::WSAHeader::ReferenceParameter (const std::string & name)

Returns first ReferenceParameter element with specified name

5.127.3.11 [XMLNode](#) Arc::WSAHeader::ReferenceParameter (int *n*)

Return n-th ReferenceParameter element

5.127.3.12 void Arc::WSAHeader::RelatesTo (const std::string & *uri*)

Set content of RelatesTo element of SOAP Header. If such element does not exist it's created.

5.127.3.13 std::string Arc::WSAHeader::RelatesTo (void) const

Returns content of RelatesTo element of SOAP Header.

5.127.3.14 void Arc::WSAHeader::RelationshipType (const std::string & *uri*)

Set content of RelationshipType element of SOAP Header. If such element does not exist it's created.

5.127.3.15 std::string Arc::WSAHeader::RelationshipType (void) const

Returns content of RelationshipType element of SOAP Header.

5.127.3.16 [WSAEndpointReference](#) Arc::WSAHeader::ReplyTo (void)

Returns ReplyTo element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulated.

5.127.3.17 void Arc::WSAHeader::To (const std::string & *uri*)

Set content of To element of SOAP Header. If such element does not exist it's created.

5.127.3.18 std::string Arc::WSAHeader::To (void) const

Returns content of To element of SOAP Header.

5.127.4 Member Data Documentation**5.127.4.1 bool [Arc::WSAHeader::header_allocated_](#) [protected]**

SOAP header element

The documentation for this class was generated from the following file:


- WSA.h

5.128 Arc::WSRF Class Reference

Base class for every [WSRF](#) message.

```
#include <WSRF.h>
```

Inheritance diagram for Arc::WSRF::



Public Member Functions

- [WSRF](#) (SOAPEnvelope &soap, const std::string &action="")
- [WSRF](#) (bool fault=false, const std::string &action="")
- virtual SOAPEnvelope & [SOAP](#) (void)
- virtual [operator bool](#) (void)
- virtual bool **operator!** (void)

Protected Member Functions

- void [set_namespaces](#) (void)

Protected Attributes

- SOAPEnvelope & [soap_](#)
- bool [allocated_](#)
- bool [valid_](#)

5.128.1 Detailed Description

Base class for every [WSRF](#) message.

This class is not intended to be used directly. Use it like reference while passing through unknown [WSRF](#) message or use classes derived from it.

5.128.2 Constructor & Destructor Documentation

5.128.2.1 Arc::WSRF::WSRF (SOAPEnvelope & soap, const std::string & action = "")

Constructor - creates object out of supplied SOAP tree.

5.128.2.2 Arc::WSRF::WSRF (bool *fault* = false, const std::string & *action* = "")

Constructor - creates new [WSRF](#) object

5.128.3 Member Function Documentation

5.128.3.1 virtual Arc::WSRF::operator bool (void) [inline, virtual]

Returns true if instance is valid

5.128.3.2 void Arc::WSRF::set_namespaces (void) [protected]

set WS Resource namespaces and default prefixes in SOAP message

Reimplemented in [Arc::WSRP](#), and [Arc::WSRFBBaseFault](#).

5.128.3.3 virtual SOAPEnvelope& Arc::WSRF::SOAP (void) [inline, virtual]

Direct access to underlying SOAP element

5.128.4 Member Data Documentation

5.128.4.1 bool Arc::WSRF::allocated_ [protected]

Associated SOAP message - it's SOAP message after all

5.128.4.2 bool Arc::WSRF::valid_ [protected]

true if soap_ needs to be deleted in destructor

The documentation for this class was generated from the following file:


- WSRF.h

5.129 Arc::WSRFBaseFault Class Reference

Base class for [WSRF](#) fault messages.

```
#include <WSRFBaseFault.h>
```

Inheritance diagram for Arc::WSRFBaseFault::



Public Member Functions

- [WSRFBaseFault](#) (SOAPEnvelope &soap)
- [WSRFBaseFault](#) (const std::string &type)
- std::string **Type** (void)
- [Time](#) **Timestamp** (void)
- void **Timestamp** ([Time](#))
- [WSAEndpointReference](#) **Originator** (void)
- void **ErrorCode** (const std::string &dialect, const [XMLNode](#) &error)
- [XMLNode](#) **ErrorCode** (void)
- std::string **ErrorCodeDialect** (void)
- void **Description** (int pos, const std::string &desc, const std::string &lang)
- std::string **Description** (int pos)
- std::string **DescriptionLang** (int pos)
- void **FaultCause** (int pos, const [XMLNode](#) &cause)
- [XMLNode](#) **FaultCause** (int pos)

Protected Member Functions

- void [set_namespaces](#) (void)

5.129.1 Detailed Description

Base class for [WSRF](#) fault messages.

Use classes inherited from it for specific faults.

5.129.2 Constructor & Destructor Documentation

5.129.2.1 Arc::WSRFBaseFault::WSRFBaseFault (SOAPEnvelope & soap)

Constructor - creates object out of supplied SOAP tree.

5.129.2.2 Arc::WSRFBASEFault::WSRFBASEFault (const std::string & *type*)

Constructor - creates new [WSRF](#) fault

5.129.3 Member Function Documentation

5.129.3.1 void Arc::WSRFBASEFault::set_namespaces (void) [protected]

set WS-ResourceProperties namespaces and default prefixes in SOAP message

Reimplemented from [Arc::WSRF](#).

The documentation for this class was generated from the following file:


- WSRFBASEFault.h

5.130 Arc::WSRP Class Reference

Base class for WS-ResourceProperties structures.

```
#include <WSResourceProperties.h>
```

Inheritance diagram for Arc::WSRP::



Public Member Functions

- [WSRP](#) (bool fault=false, const std::string &action="")
- [WSRP](#) (SOAPEnvelope &soap, const std::string &action="")

Protected Member Functions

- void [set_namespaces](#) (void)

5.130.1 Detailed Description

Base class for WS-ResourceProperties structures.

Inheriting classes implement specific WS-ResourceProperties messages and their properties/elements. Refer to WS-ResourceProperties specifications for things specific to every message.

5.130.2 Constructor & Destructor Documentation

5.130.2.1 Arc::WSRP::WSRP (bool *fault* = false, const std::string & *action* = "")

Constructor - prepares object for creation of new [WSRP](#) request/response/fault

5.130.2.2 Arc::WSRP::WSRP (SOAPEnvelope & *soap*, const std::string & *action* = "")

Constructor - creates object out of supplied SOAP tree. It does not check if 'soap' represents valid WS-ResourceProperties structure. Actual check for validity of structure has to be done by derived class.

5.130.3 Member Function Documentation

5.130.3.1 void Arc::WSRP::set_namespaces (void) [protected]

set WS-ResourceProperties namespaces and default prefixes in SOAP message

Reimplemented from [Arc::WSRF](#).

The documentation for this class was generated from the following file:


- WSResourceProperties.h

5.131 Arc::WSRPFault Class Reference

Base class for WS-ResourceProperties faults.

```
#include <WSResourceProperties.h>
```

Inheritance diagram for Arc::WSRPFault::



Public Member Functions

- [WSRPFault](#) (SOAPEnvelope &soap)
- [WSRPFault](#) (const std::string &type)

5.131.1 Detailed Description

Base class for WS-ResourceProperties faults.

5.131.2 Constructor & Destructor Documentation

5.131.2.1 Arc::WSRPFault::WSRPFault (SOAPEnvelope & soap)

Constructor - creates object out of supplied SOAP tree.

5.131.2.2 Arc::WSRPFault::WSRPFault (const std::string & type)

Constructor - creates new [WSRP](#) fault


The documentation for this class was generated from the following file:

- WSResourceProperties.h

5.132 Arc::WSRPResourcePropertyChangeFailure Class Reference

```
#include <WSResourceProperties.h>
```

Inheritance diagram for Arc::WSRPResourcePropertyChangeFailure::



Public Member Functions

- [WSRPResourcePropertyChangeFailure](#) (SOAPEnvelope &soap)
- [WSRPResourcePropertyChangeFailure](#) (const std::string &type)
- [XMLNode CurrentProperties](#) (bool create=false)
- [XMLNode RequestedProperties](#) (bool create=false)

5.132.1 Detailed Description

Base class for WS-ResourceProperties faults which contain ResourcePropertyChangeFailure

5.132.2 Constructor & Destructor Documentation

5.132.2.1 Arc::WSRPResourcePropertyChangeFailure::WSRPResourcePropertyChangeFailure (SOAPEnvelope & soap) [inline]

Constructor - creates object out of supplied SOAP tree.

5.132.2.2 Arc::WSRPResourcePropertyChangeFailure::WSRPResourcePropertyChangeFailure (const std::string & type) [inline]

Constructor - creates new [WSRP](#) fault

The documentation for this class was generated from the following file:

- WSResourceProperties.h

5.133 Arc::X509Token Class Reference

Interface for manipulation of WS-Security according to X.509 Token Profile.

```
#include <X509Token.h>
```

Public Types

- **Signature**
- **Encryption**
- enum **X509TokenType** { **Signature**, **Encryption** }

Public Member Functions

- [X509Token](#) (SOAPEnvelope &soap, X509TokenType tokentype=Signature)
- [X509Token](#) (SOAPEnvelope &soap, const std::string &certfile, const std::string &keyfile, X509TokenType tokentype=Signature)
- [operator bool](#) (void)
- bool [Authenticate](#) (const std::string &cafile, const std::string &capath)
- bool [Authenticate](#) (void)

5.133.1 Detailed Description

Interface for manipulation of WS-Security according to X.509 Token Profile.

5.133.2 Constructor & Destructor Documentation

5.133.2.1 Arc::X509Token::X509Token (SOAPEnvelope & soap, X509TokenType tokentype = Signature)

Link to existing SOAP header and parse X509 Token information. X509 Token related information is extracted from SOAP header and stored in class variables.

5.133.2.2 Arc::X509Token::X509Token (SOAPEnvelope & soap, const std::string & certfile, const std::string & keyfile, X509TokenType tokentype = Signature)

Add X509 Token information into the SOAP header. Generated token contains elements X509 token and signature, and is meant to be used for authentication.

Parameters:

soap the SOAP message

certfile

keyfile

tokentype

5.133.3 Member Function Documentation

5.133.3.1 bool Arc::X509Token::Authenticate (void)

Check signature by using the cert information in soap message

5.133.3.2 bool Arc::X509Token::Authenticate (const std::string & *cafile*, const std::string & *capath*)

Check signature by using the trusted certificates

Parameters:

cafile ca file

capath ca directory

5.133.3.3 Arc::X509Token::operator bool (void)

Returns true of constructor succeeded

The documentation for this class was generated from the following file:


- X509Token.h

5.134 Arc::XMLNode Class Reference

Wrapper for LibXML library Tree interface.

```
#include <XMLNode.h>
```

Inheritance diagram for Arc::XMLNode::



Public Member Functions

- [XMLNode](#) (void)
- [XMLNode](#) (const [XMLNode](#) &node)
- [XMLNode](#) (const std::string &xml)
- [XMLNode](#) (const char *xml, int len=-1)
- [XMLNode](#) (const Arc::NS &ns, const char *name)
- [~XMLNode](#) (void)
- void [New](#) ([XMLNode](#) &new_node) const
- [operator bool](#) (void) const
- bool [operator!](#) (void) const
- [XMLNode Child](#) (int n=0) const
- [XMLNode operator\[\]](#) (const char *name) const
- [XMLNode operator\[\]](#) (const std::string &name) const
- [XMLNode operator\[\]](#) (int n) const
- void [operator++](#) (void)
- void [operator--](#) (void)
- int [Size](#) (void) const
- [XMLNode Get](#) (const std::string &name) const
- std::string [Name](#) (void) const
- std::string [Prefix](#) (void) const
- std::string [FullName](#) (void) const
- std::string [Namespace](#) (void) const
- void [Name](#) (const char *name)
- void [Name](#) (const std::string &name)
- void [GetXML](#) (std::string &out_xml_str, bool user_friendly=false) const
- void [GetDoc](#) (std::string &out_xml_str, bool user_friendly=false) const
- [operator std::string](#) (void) const
- [XMLNode & operator=](#) (const char *content)
- [XMLNode & operator=](#) (const std::string &content)
- void [Set](#) (const std::string &content)
- [XMLNode & operator=](#) (const [XMLNode](#) &node)
- [XMLNode Attribute](#) (int n=0) const
- [XMLNode Attribute](#) (const char *name) const
- [XMLNode Attribute](#) (const std::string &name) const
- [XMLNode NewAttribute](#) (const char *name)

- [XMLNode NewAttribute](#) (const std::string &name)
- int [AttributesSize](#) (void) const
- void [Namespaces](#) (const NS &namespaces)
- NS [Namespaces](#) (void)
- std::string [NamespacePrefix](#) (const char *urn)
- [XMLNode NewChild](#) (const char *name, int n=-1, bool global_order=false)
- [XMLNode NewChild](#) (const std::string &name, int n=-1, bool global_order=false)
- [XMLNode NewChild](#) (const char *name, const NS &namespaces, int n=-1, bool global_order=false)
- [XMLNode NewChild](#) (const std::string &name, const NS &namespaces, int n=-1, bool global_order=false)
- [XMLNode NewChild](#) (const [XMLNode](#) &node, int n=-1, bool global_order=false)
- void [Replace](#) (const [XMLNode](#) &node)
- void [Destroy](#) (void)
- XMLNodeList [XPathLookup](#) (const std::string &xpathExpr, const Arc::NS &nsList)
- [XMLNode GetRoot](#) (void)
- [XMLNode Parent](#) (void)
- bool [SaveToFile](#) (const std::string &file_name) const
- bool [SaveToStream](#) (std::ostream &out) const
- bool [ReadFromFile](#) (const std::string &file_name)
- bool [ReadFromStream](#) (std::istream &in)

Protected Member Functions

- [XMLNode](#) (xmlNodePtr node)

Protected Attributes

- xmlNodePtr [node_](#)
- bool [is_owner_](#)
- bool [is_temporary_](#)

Friends

- class [XMLNodeContainer](#)
- bool [MatchXMLName](#) (const [XMLNode](#) &node1, const [XMLNode](#) &node2)
- bool [MatchXMLName](#) (const [XMLNode](#) &node, const char *name)
- bool [MatchXMLName](#) (const [XMLNode](#) &node, const std::string &name)
- bool [MatchXMLNamespace](#) (const [XMLNode](#) &node1, const [XMLNode](#) &node2)
- bool [MatchXMLNamespace](#) (const [XMLNode](#) &node, const char *uri)
- bool [MatchXMLNamespace](#) (const [XMLNode](#) &node, const std::string &uri)

5.134.1 Detailed Description

Wrapper for LibXML library Tree interface.

This class wraps XML Node, Document and Property/Attribute structures. Each instance serves as pointer to actual LibXML element and provides convenient (for chosen purpose) methods for manipulating it. This class has no special ties to LibXML library and may be easily rewritten for any XML parser which provides interface similar to LibXML Tree. It implements only small subset of XML capabilities, which is probably enough for performing most of useful actions. This class also filters out (usually) useless textual nodes which are often used to make XML documents human-readable.

5.134.2 Constructor & Destructor Documentation

5.134.2.1 `Arc::XMLNode::XMLNode (xmlNodePtr node)` `[inline, protected]`

Private constructor for inherited classes Creates instance and links to existing LibXML structure. Acquired structure is not owned by class instance. If there is need to completely pass control of LibXML document to then instance's `is_owner_` variable has to be set to true.

5.134.2.2 `Arc::XMLNode::XMLNode (void)` `[inline]`

Constructor of invalid node Created instance does not point to XML element. All methods are still allowed for such instance but produce no results.

5.134.2.3 `Arc::XMLNode::XMLNode (const XMLNode & node)` `[inline]`

Copies existing instance. Underlying XML element is NOT copied. Ownership is NOT inherited.

5.134.2.4 `Arc::XMLNode::XMLNode (const std::string & xml)`

Creates XML document structure from textual representation of XML document. Created structure is pointed and owned by constructed instance

5.134.2.5 `Arc::XMLNode::XMLNode (const char * xml, int len = -1)`

Same as previous

5.134.2.6 `Arc::XMLNode::XMLNode (const Arc::NS & ns, const char * name)`

Creates empty XML document structure with specified namespaces. Created XML contains only root element named '*name*'. Created structure is pointed and owned by constructed instance

5.134.2.7 `Arc::XMLNode::~~XMLNode (void)`

Destructor Also destroys underlying XML document if owned by this instance

5.134.3 Member Function Documentation

5.134.3.1 `XMLNode Arc::XMLNode::Attribute (const std::string & name) const` `[inline]`

Returns [XMLNode](#) instance representing first attribute of node with specified by name

5.134.3.2 `XMLNode Arc::XMLNode::Attribute (const char * name) const`

Returns [XMLNode](#) instance representing first attribute of node with specified by name

5.134.3.3 XMLNode Arc::XMLNode::Attribute (int *n* = 0) const

Returns list of all attributes of node.

Returns XMLNode instance representing n-th attribute of node.

5.134.3.4 int Arc::XMLNode::AttributesSize (void) const

Returns number of attributes of node

5.134.3.5 XMLNode Arc::XMLNode::Child (int *n* = 0) const

Returns XMLNode instance representing n-th child of XML element. If such does not exist invalid XMLNode instance is returned

5.134.3.6 void Arc::XMLNode::Destroy (void)

Destroys underlying XML element. XML element is unlinked from XML tree and destroyed. After this operation XMLNode instance becomes invalid

5.134.3.7 std::string Arc::XMLNode::FullName (void) const [inline]

Returns prefix:name of XML node

5.134.3.8 XMLNode Arc::XMLNode::Get (const std::string & *name*) const [inline]

Same as operator[]

5.134.3.9 void Arc::XMLNode::GetDoc (std::string & *out_xml_str*, bool *user_friendly* = false) const

Fills argument with whole XML document textual representation

5.134.3.10 XMLNode Arc::XMLNode::GetRoot (void)

Get the root node from any child node of the tree

5.134.3.11 void Arc::XMLNode::GetXML (std::string & *out_xml_str*, bool *user_friendly* = false) const

Fills argument with this instance XML subtree textual representation

5.134.3.12 void Arc::XMLNode::Name (const std::string & *name*) [inline]

Assigns new name to XML node

5.134.3.13 void Arc::XMLNode::Name (const char * *name*)

Assigns new name to XML node

5.134.3.14 std::string Arc::XMLNode::Name (void) const

Returns name of XML node

5.134.3.15 std::string Arc::XMLNode::Namespace (void) const

Returns namespace URI of XML node

5.134.3.16 std::string Arc::XMLNode::NamespacePrefix (const char * *urn*)

Returns prefix of specified namespace. Empty string if no such namespace.

5.134.3.17 NS Arc::XMLNode::Namespaces (void)

Returns namespaces known at this node

5.134.3.18 void Arc::XMLNode::Namespaces (const NS & *namespaces*)

Assigns namespaces of XML document at point specified by this instance. If namespace already exists it gets new prefix. New namespaces are added. It is useful to apply this method to XML being processed in order to refer to its elements by known prefix.

5.134.3.19 void Arc::XMLNode::New ([XMLNode](#) & *new_node*) const

Creates a copy of XML (sub)tree. If object does not represent whole document - top level document is created. 'new_node' becomes a pointer owning new XML document.

5.134.3.20 [XMLNode](#) Arc::XMLNode::NewAttribute (const std::string & *name*) [inline]

Creates new attribute with specified name.

5.134.3.21 [XMLNode](#) Arc::XMLNode::NewAttribute (const char * *name*)

Creates new attribute with specified name.

5.134.3.22 [XMLNode](#) Arc::XMLNode::NewChild (const [XMLNode](#) & *node*, int *n* = -1, bool *global_order* = false)

Link a copy of supplied XML node as child. Returns instance referring to new child. XML element is a copy of supplied one but not owned by returned instance

5.134.3.23 [XMLNode](#) Arc::XMLNode::NewChild (const std::string & *name*, const NS & *namespaces*, int *n* = -1, bool *global_order* = false) [inline]

Same as [NewChild\(const char*,const NS&,int,bool\)](#)

5.134.3.24 [XMLNode](#) Arc::XMLNode::NewChild (const char * *name*, const NS & *namespaces*, int *n* = -1, bool *global_order* = false)

Creates new child XML element at specified position with specified name and namespaces. For more information look at [NewChild\(const char*,int,bool\)](#)

5.134.3.25 [XMLNode](#) Arc::XMLNode::NewChild (const std::string & *name*, int *n* = -1, bool *global_order* = false) [inline]

Same as [NewChild\(const char*,int,bool\)](#)

5.134.3.26 [XMLNode](#) Arc::XMLNode::NewChild (const char * *name*, int *n* = -1, bool *global_order* = false)

Creates new child XML element at specified position with specified name. Default is to put it at end of list. If global order is true position applies to whole set of children, otherwise only to children of same name

5.134.3.27 Arc::XMLNode::operator bool (void) const [inline]

Returns true if instance points to XML element - valid instance

5.134.3.28 Arc::XMLNode::operator std::string (void) const

Returns textual content of node excluding content of children nodes

5.134.3.29 bool Arc::XMLNode::operator! (void) const [inline]

Returns true if instance does not point to XML element - invalid instance

5.134.3.30 void Arc::XMLNode::operator++ (void)

Convenience operator to switch to next element of same name. If there is no such node this object becomes invalid.

5.134.3.31 void Arc::XMLNode::operator-- (void)

Convenience operator to switch to previous element of same name. If there is no such node this object becomes invalid.

5.134.3.32 [XMLNode&](#) Arc::XMLNode::operator= (const [XMLNode](#) & *node*)

Make instance refer to another XML node. Ownership is not inherited.

5.134.3.33 [XMLNode](#)& Arc::XMLNode::operator= (const std::string & *content*) [inline]

Sets textual content of node. All existing children nodes are discarded.

5.134.3.34 [XMLNode](#)& Arc::XMLNode::operator= (const char * *content*)

Sets textual content of node. All existing children nodes are discarded.

5.134.3.35]

[XMLNode](#) Arc::XMLNode::operator[] (int *n*) const

Returns [XMLNode](#) instance representing n-th node in sequence of siblings of same name. It's main purpose is to be used to retrieve element in array of children of same name like node["name"][5]

5.134.3.36]

[XMLNode](#) Arc::XMLNode::operator[] (const std::string & *name*) const [inline]

Similar to previous method

5.134.3.37]

[XMLNode](#) Arc::XMLNode::operator[] (const char * *name*) const

Returns [XMLNode](#) instance representing first child element with specified name. Name may be "namespace_prefix:name" or simply "name". In last case namespace is ignored. If such node does not exist invalid [XMLNode](#) instance is returned

5.134.3.38 [XMLNode](#) Arc::XMLNode::Parent (void)

Get the parent node from any child node of the tree

5.134.3.39 std::string Arc::XMLNode::Prefix (void) const

Returns namespace prefix of XML node

5.134.3.40 bool Arc::XMLNode::ReadFromFile (const std::string & *file_name*)

Read XML document from file and associate it with this node

5.134.3.41 bool Arc::XMLNode::ReadFromStream (std::istream & *in*)

Read XML document from stream and associate it with this node

5.134.3.42 void Arc::XMLNode::Replace (const [XMLNode](#) & *node*)

Makes a copy of supplied XML node and makes this instance refer to it

5.134.3.43 bool Arc::XMLNode::SaveToFile (const std::string & *file_name*) const

Save string representation of node to file

5.134.3.44 bool Arc::XMLNode::SaveToStream (std::ostream & *out*) const

Save string representation of node to stream

5.134.3.45 void Arc::XMLNode::Set (const std::string & *content*) [inline]

Same as operator=. Used for bindings.

5.134.3.46 int Arc::XMLNode::Size (void) const

Returns number of children nodes

5.134.3.47 XMLNodeList Arc::XMLNode::XPathLookup (const std::string & *xpathExpr*, const Arc::NS & *nsList*)

Uses xPath to look up the whole xml structure, Returns a list of [XMLNode](#) points. The xpathExpr should be like "//xx:child1/" which indicates the namespace and node that you would like to find; The nsList is the namespace the result should belong to (e.g. xx="uri:test"). Query is run on whole XML document but only the elements belonging to this XML subtree are returned.

5.134.4 Friends And Related Function Documentation**5.134.4.1 bool MatchXMLName (const [XMLNode](#) & *node*, const std::string & *name*)** [friend]

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

5.134.4.2 bool MatchXMLName (const [XMLNode](#) & *node*, const char * *name*) [friend]

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

5.134.4.3 bool MatchXMLName (const [XMLNode](#) & *node1*, const [XMLNode](#) & *node2*) [friend]

Returns true if underlying XML elements have same names

5.134.4.4 bool MatchXMLNamespace (const [XMLNode](#) & *node*, const std::string & *uri*)
[friend]

Returns true if 'namespace' matches 'node's namespace.

5.134.4.5 bool MatchXMLNamespace (const [XMLNode](#) & *node*, const char * *uri*) [friend]

Returns true if 'namespace' matches 'node's namespace.

5.134.4.6 `bool MatchXMLNamespace (const XMLNode & node1, const XMLNode & node2)`
[friend]

Returns true if underlying XML elements belong to same namespaces

5.134.5 Member Data Documentation

5.134.5.1 `bool Arc::XMLNode::is_owner_` [protected]

If true node is owned by this instance - hence released in destructor. Normally that may be true only for top level node of XML document.

5.134.5.2 `bool Arc::XMLNode::is_temporary_` [protected]

This variable is for future

The documentation for this class was generated from the following file:

- XMLNode.h

5.135 Arc::XMLNodeContainer Class Reference

```
#include <XMLNode.h>
```

Public Member Functions

- [XMLNodeContainer](#) (void)
- [XMLNodeContainer](#) (const [XMLNodeContainer](#) &)
- [XMLNodeContainer](#) & [operator=](#) (const [XMLNodeContainer](#) &)
- void [Add](#) (const [XMLNode](#) &)
- void [Add](#) (const std::list< [XMLNode](#) > &)
- void [AddNew](#) (const [XMLNode](#) &)
- void [AddNew](#) (const std::list< [XMLNode](#) > &)
- int [Size](#) (void)
- [XMLNode](#) [operator\[\]](#) (int)
- std::list< [XMLNode](#) > [Nodes](#) (void)

5.135.1 Detailed Description

Container for multiple [XMLNode](#) elements

5.135.2 Constructor & Destructor Documentation

5.135.2.1 Arc::XMLNodeContainer::XMLNodeContainer (void)

Default constructor

5.135.2.2 Arc::XMLNodeContainer::XMLNodeContainer (const [XMLNodeContainer](#) &)

Copy constructor. Add nodes from argument. Nodes owning XML document are copied using [AddNew\(\)](#). Not owning nodes are linked using [Add\(\)](#) method.

5.135.3 Member Function Documentation

5.135.3.1 void Arc::XMLNodeContainer::Add (const std::list< [XMLNode](#) > &)

Link multiple XML subtrees to container.

5.135.3.2 void Arc::XMLNodeContainer::Add (const [XMLNode](#) &)

Link XML subtree referred by node to container. XML tree must be available as long as this object is used.

5.135.3.3 void Arc::XMLNodeContainer::AddNew (const std::list< [XMLNode](#) > &)

Copy multiple XML subtrees to container.

5.135.3.4 void Arc::XMLNodeContainer::AddNew (const XMLNode &)

Copy XML subtree referenced by node to container. After this operation container refers to independent XML document. This document is deleted when container is destroyed.

5.135.3.5 std::list<XMLNode> Arc::XMLNodeContainer::Nodes (void)

Returns all stored nodes.

5.135.3.6 XMLNodeContainer& Arc::XMLNodeContainer::operator= (const XMLNodeContainer &)

Same as copy constructor with current nodes being deleted first.

5.135.3.7]

XMLNode Arc::XMLNodeContainer::operator[] (int)

Returns n-th node in a store.

5.135.3.8 int Arc::XMLNodeContainer::Size (void)

Return number of refered/stored nodes.

The documentation for this class was generated from the following file:


- XMLNode.h

5.136 Arc::XMLSecNode Class Reference

Extends [XMLNode](#) class to support XML security operation.

```
#include <XMLSecNode.h>
```

Inheritance diagram for Arc::XMLSecNode::



Public Types

- **RSA_SHA1**
- **DSA_SHA1**
- enum **SignatureMethod** { **RSA_SHA1**, **DSA_SHA1** }

Public Member Functions

- **XMLSecNode** ([XMLNode](#) &node)
- void **AddSignatureTemplate** (std::string &id_name, SignatureMethod sign_method)
- bool **SignNode** (std::string &privkey_file, std::string &cert_file)
- bool **VerifyNode** (std::string &id_name, std::string &ca_file, std::string &ca_path)
- bool **EncryptNode** (std::string &cert_file, SymEncryptionType encrypt_type)
- bool **DecryptNode** (std::string &privkey_file)

5.136.1 Detailed Description

Extends [XMLNode](#) class to support XML security operation.

All [XMLNode](#) methods are exposed by inheriting from [XMLNode](#). [XMLSecNode](#) itself does not own node, instead it uses the node from [XMLNode](#).

5.136.2 Constructor & Destructor Documentation

5.136.2.1 Arc::XMLSecNode::XMLSecNode ([XMLNode](#) & node)

Create a object based on an [XMLNode](#) instance.

The documentation for this class was generated from the following file:

- XMLSecNode.h

Index

- ~Counter
 - Arc::Counter, [55](#)
- ~DataBufferPar
 - Arc::DataBufferPar, [66](#)
- ~DataCache
 - Arc::DataCache, [73](#)
- ~DataMover
 - Arc::DataMover, [78](#)
- ~DataPoint
 - Arc::DataPoint, [84](#)
- ~DataSpeed
 - Arc::DataSpeed, [108](#)
- ~Database
 - Arc::Database, [63](#)
- ~IntraProcessCounter
 - Arc::IntraProcessCounter, [147](#)
- ~Loader
 - Arc::Loader, [151](#)
- ~Message
 - Arc::Message, [176](#)
- ~PayloadRaw
 - Arc::PayloadRaw, [192](#)
- ~PayloadStream
 - Arc::PayloadStream, [198](#)
- ~Plexer
 - Arc::Plexer, [210](#)
- ~RegularExpression
 - Arc::RegularExpression, [217](#)
- ~Run
 - Arc::Run, [227](#)
- ~SOAPMessage
 - Arc::SOAPMessage, [248](#)
- ~URL
 - Arc::URL, [259](#)
- ~URLLocation
 - Arc::URLLocation, [265](#)
- ~WSAEndpointReference
 - Arc::WSAEndpointReference, [269](#)
- ~XMLNode
 - Arc::XMLNode, [286](#)
- acc_descriptor, [27](#)
- AcceptsMeta
 - Arc::DataPoint, [84](#)
 - Arc::DataPointDirect, [94](#)
 - Arc::DataPointIndex, [101](#)
- ACCFactory
 - Arc::ACCFactory, [28](#)
- Acquire
 - Arc::DelegationConsumer, [112](#)
 - Arc::InformationContainer, [139](#)
- Action
 - Arc::WSAHeader, [272](#)
- Add
 - Arc::MessageContext, [184](#)
 - Arc::XMLNodeContainer, [293](#)
- add
 - Arc::MessageAttributes, [179](#)
- AddCADir
 - Arc::BaseConfig, [41](#)
- AddCAFile
 - Arc::BaseConfig, [41](#)
- AddCertificate
 - Arc::BaseConfig, [41](#)
- addDestination
 - Arc::Logger, [158](#)
- AddLDAPAttribute
 - Arc::URL, [259](#)
- AddLocation
 - Arc::DataPoint, [84](#)
 - Arc::DataPointDirect, [94](#)
 - Arc::DataPointIndex, [101](#)
- AddNew
 - Arc::XMLNodeContainer, [293](#)
- AddOption
 - Arc::URL, [259](#)
- AddOverlay
 - Arc::BaseConfig, [42](#)
- AddPluginsPath
 - Arc::BaseConfig, [42](#)
- addPolicy
 - ArcSec::Evaluator, [127](#)
 - ArcSec::Policy, [213](#)
- AddPrivateKey
 - Arc::BaseConfig, [42](#)
- AddProxy
 - Arc::BaseConfig, [42](#)
- addRequestItem
 - ArcSec::Request, [219](#)
- Address

- Arc::WSAEndpointReference, 270
- AddSecHandler
 - Arc::MCC, 166
 - Arc::Service, 243
- AddWSSInfo
 - Arc::BaseConfig, 42
- AddWSSType
 - Arc::BaseConfig, 42
- allocated_
 - Arc::WSRF, 275
- Arc, 11
 - AttrConstIter, 21
 - AttrIter, 21
 - AttrMap, 21
 - BUSY_ERROR, 22
 - ContentFromPayload, 24
 - CreateThreadFunction, 23
 - ETERNAL, 25
 - GENERIC_ERROR, 22
 - GUID, 23
 - HISTORIC, 25
 - loader_descriptors, 21
 - LogLevel, 22
 - MatchXMLName, 24
 - MatchXMLNamespace, 24
 - operator<=, 22, 23
 - PARSING_ERROR, 22
 - PROTOCOL_RECOGNIZED_ERROR, 22
 - ReadURLList, 24
 - SESSION_CLOSE, 22
 - STATUS_OK, 22
 - StatusKind, 22
 - string, 24
 - stringto, 23
 - TimeFormat, 21
 - TimeStamp, 22
 - tokenize, 23
 - tostring, 23
 - trim, 23
 - UNKNOWN_SERVICE_ERROR, 22
 - upper, 23
 - uri_unescape, 23
 - UUID, 23
 - WSAFault, 22
 - WSAFaultAssign, 24
 - WSAFaultExtract, 25
 - WSAFaultInvalidAddressingHeader, 22
 - WSAFaultUnknown, 22
 - WSSType, 21
- Arc::ACCFactory, 28
 - ACCFactory, 28
 - get_instance, 28
- Arc::ArcLocation, 31
- Arc::ArcLocation
 - Get, 31
 - GetPlugins, 31
 - Init, 31
- Arc::AttributeIterator, 34
- Arc::AttributeIterator
 - AttributeIterator, 34
 - current_, 36
 - end_, 36
 - hasMore, 35
 - key, 35
 - MessageAttributes, 36
 - operator *, 35
 - operator++, 35
 - operator->, 36
- Arc::BaseConfig, 41
- Arc::BaseConfig
 - AddCADir, 41
 - AddCAFile, 41
 - AddCertificate, 41
 - AddOverlay, 42
 - AddPluginsPath, 42
 - AddPrivateKey, 42
 - AddProxy, 42
 - AddWSSInfo, 42
 - AddWSSType, 42
 - GetOverlay, 42
 - MakeConfig, 42
- Arc::ChainContext, 43
- Arc::ChainContext
 - operator MCCFactory *, 43
 - operator PDPFactory *, 43
 - operator SecHandlerFactory *, 43
 - operator ServiceFactory *, 43
- Arc::Checksum, 44
- Arc::ChecksumAny, 45
- Arc::CIStrString Value, 47
- Arc::CIStrString Value
 - CIStrString Value, 47
 - equal, 48
 - operator bool, 48
- Arc::ClientSOAP, 49
- Arc::ClientSOAP
 - ClientSOAP, 49
 - process, 49
- Arc::Config, 51
 - Config, 51, 52
 - getFileName, 52
 - parse, 52
 - print, 52
 - save, 52
 - setFileName, 52
- Arc::Counter, 53
 - ~Counter, 55
 - cancel, 55

- changeExcess, 55
- changeLimit, 55
- Counter, 55
- CounterTicket, 59
- ExpirationReminder, 59
- extend, 56
- getCounterTicket, 56
- getCurrentTime, 56
- getExcess, 57
- getExpirationReminder, 57
- getExpiryTime, 57
- getLimit, 57
- getValue, 58
- IDType, 55
- reserve, 58
- setExcess, 58
- setLimit, 59
- Arc::CounterTicket, 60
- Arc::CounterTicket
 - cancel, 60
 - Counter, 61
 - CounterTicket, 60
 - extend, 61
 - isValid, 61
- Arc::CRC32Sum, 62
- Arc::Database, 63
 - ~Database, 63
 - close, 64
 - connect, 64
 - Database, 63
 - enable_ssl, 64
 - isconnected, 64
 - shutdown, 64
- Arc::DataBufferPar, 65
- Arc::DataBufferPar
 - ~DataBufferPar, 66
 - buffer_size, 66
 - checksum_object, 66
 - checksum_valid, 66
 - DataBufferPar, 66
 - eof_position, 66
 - eof_read, 67
 - eof_write, 67
 - error, 67
 - error_read, 67
 - error_transfer, 67
 - error_write, 67
 - for_read, 68
 - for_write, 68
 - is_notwritten, 68
 - is_read, 69
 - is_written, 69
 - operator bool, 69
 - operator[], 69
- set, 70
- speed, 71
- wait, 70
- wait_eof, 70
- wait_eof_read, 70
- wait_eof_write, 70
- wait_read, 70
- wait_used, 70
- wait_write, 70
- Arc::DataCache, 72
- Arc::DataCache
 - ~DataCache, 73
 - cb, 73
 - CheckCreated, 73
 - CheckValid, 73
 - clean, 73
 - copy, 74
 - DataCache, 73
 - file, 74
 - GetCreated, 74
 - GetValid, 74
 - link, 74
 - operator bool, 74
 - SetCreated, 74
 - SetValid, 74
 - start, 75
 - stop, 75
- Arc::DataCallback, 76
- Arc::DataHandle, 77
- Arc::DataMover, 78
- Arc::DataMover
 - ~DataMover, 78
 - checks, 79
 - DataMover, 78
 - force_to_meta, 79
 - passive, 79
 - retry, 79
 - secure, 79
 - set_default_max_inactivity_time, 79
 - set_default_min_average_speed, 79
 - set_default_min_speed, 80
 - Transfer, 80
 - verbose, 80, 81
- Arc::DataPoint, 82
- Arc::DataPoint
 - ~DataPoint, 84
 - AcceptsMeta, 84
 - AddLocation, 84
 - BufNum, 84
 - BufSize, 84
 - Cache, 84
 - Check, 84
 - CheckChecksum, 85
 - CheckCreated, 85

- CheckSize, 85
- CheckValid, 85
- CompareMeta, 85
- CurrentLocation, 85
- CurrentLocationMetadata, 85
- DataPoint, 84
- GetAdditionalChecks, 85
- GetChecksum, 86
- GetCreated, 86
- GetSecure, 86
- GetSize, 86
- GetTries, 86
- GetURL, 86
- GetValid, 86
- HaveLocations, 86
- IsIndex, 86
- ListFiles, 86
- Local, 87
- LocationValid, 87
- NextLocation, 87
- operator bool, 87
- operator!, 87
- Passive, 87
- PostRegister, 87
- PreRegister, 88
- PreUnregister, 88
- ProvidesMeta, 88
- Range, 88
- ReadOutOfOrder, 89
- Registered, 89
- Remove, 89
- RemoveLocation, 89
- RemoveLocations, 89
- Resolve, 89
- SetAdditionalChecks, 89
- SetChecksum, 90
- SetCreated, 90
- SetMeta, 90
- SetSecure, 90
- SetSize, 90
- SetTries, 90
- SetValid, 90
- StartReading, 91
- StartWriting, 91
- StopReading, 91
- StopWriting, 91
- str, 91
- Unregister, 92
- WriteOutOfOrder, 92
- Arc::DataPointDirect, 93
- Arc::DataPointDirect
 - AcceptsMeta, 94
 - AddLocation, 94
 - BufNum, 94
 - BufSize, 94
 - Cache, 95
 - CurrentLocation, 95
 - CurrentLocationMetadata, 95
 - GetAdditionalChecks, 95
 - GetSecure, 95
 - HaveLocations, 95
 - IsIndex, 95
 - Local, 95
 - LocationValid, 96
 - NextLocation, 96
 - Passive, 96
 - PostRegister, 96
 - PreRegister, 96
 - PreUnregister, 97
 - ProvidesMeta, 97
 - Range, 97
 - ReadOutOfOrder, 97
 - Registered, 97
 - RemoveLocation, 97
 - RemoveLocations, 97
 - Resolve, 98
 - SetAdditionalChecks, 98
 - SetSecure, 98
 - Unregister, 98
 - WriteOutOfOrder, 98
- Arc::DataPointIndex, 100
- Arc::DataPointIndex
 - AcceptsMeta, 101
 - AddLocation, 101
 - BufNum, 101
 - BufSize, 101
 - Cache, 101
 - Check, 101
 - CurrentLocation, 102
 - CurrentLocationMetadata, 102
 - GetAdditionalChecks, 102
 - GetSecure, 102
 - HaveLocations, 102
 - IsIndex, 102
 - Local, 102
 - locations, 106
 - LocationValid, 102
 - NextLocation, 103
 - Passive, 103
 - ProvidesMeta, 103
 - Range, 103
 - ReadOutOfOrder, 103
 - Registered, 103
 - Remove, 103
 - RemoveLocation, 104
 - RemoveLocations, 104
 - SetAdditionalChecks, 104
 - SetSecure, 104

- SetTries, 104
- StartReading, 104
- StartWriting, 105
- StopReading, 105
- StopWriting, 105
- WriteOutOfOrder, 105
- Arc::DataSpeed, 107
- Arc::DataSpeed
 - ~DataSpeed, 108
 - DataSpeed, 107
 - hold, 108
 - max_inactivity_time_failure, 108
 - min_average_speed_failure, 108
 - min_speed_failure, 108
 - reset, 108
 - set_base, 108
 - set_max_data, 109
 - set_max_inactivity_time, 109
 - set_min_average_speed, 109
 - set_min_speed, 109
 - set_progress_indicator, 109
 - transfer, 109
 - transferred_size, 110
 - verbose, 110
- Arc::DelegationConsumer, 111
- Arc::DelegationConsumer
 - Acquire, 112
 - Backup, 112
 - DelegationConsumer, 111
 - Generate, 112
 - ID, 112
 - LogError, 112
 - Request, 112
 - Restore, 112
- Arc::DelegationConsumerSOAP, 113
- Arc::DelegationConsumerSOAP
 - DelegateCredentialsInit, 113
 - DelegatedToken, 113
 - DelegationConsumerSOAP, 113
 - UpdateCredentials, 114
- Arc::DelegationContainerSOAP, 115
- Arc::DelegationContainerSOAP
 - context_lock_, 115
 - DelegateCredentialsInit, 115
 - DelegatedToken, 115
 - max_duration_, 115
 - max_size_, 116
 - max_usage_, 116
 - restricted_, 116
 - UpdateCredentials, 115
- Arc::DelegationProvider, 117
- Arc::DelegationProvider
 - Delegate, 117
 - DelegationProvider, 117
- Arc::DelegationProviderSOAP, 119
- Arc::DelegationProviderSOAP
 - DelegateCredentialsInit, 120
 - DelegatedToken, 120
 - DelegationProviderSOAP, 119
 - UpdateCredentials, 120
- Arc::DMCFactory, 123
- DMCFactory, 123
- get_instance, 123
- Arc::ExpirationReminder, 132
- Arc::ExpirationReminder
 - Counter, 133
 - getExpiryTime, 132
 - getReservationID, 132
 - operator<, 132
- Arc::FileInfo, 134
- Arc::InfoRegister, 137
- Arc::InfoRegisters, 138
- Arc::InfoRegisters
 - InfoRegisters, 138
- Arc::InformationContainer, 139
- Arc::InformationContainer
 - Acquire, 139
 - Assign, 139
 - doc_, 140
 - Get, 140
 - InformationContainer, 139
- Arc::InformationInterface, 141
- Arc::InformationInterface
 - Get, 141
 - InformationInterface, 141
 - lock_, 142
- Arc::InformationRequest, 143
- Arc::InformationRequest
 - InformationRequest, 143
 - SOAP, 143
- Arc::InformationResponse, 145
- Arc::InformationResponse
 - InformationResponse, 145
 - Result, 145
- Arc::IntraProcessCounter, 146
- Arc::IntraProcessCounter
 - ~IntraProcessCounter, 147
 - cancel, 147
 - changeExcess, 147
 - changeLimit, 147
 - extend, 147
 - getExcess, 148
 - getLimit, 148
 - getValue, 148
 - IntraProcessCounter, 146
 - reserve, 148
 - setExcess, 149
 - setLimit, 149

- Arc::Loader, 150
 - ~Loader, 151
 - getACC, 151
 - Loader, 151
 - operator[], 151
- Arc::loader_descriptor, 152
- Arc::LoaderFactory, 153
- Arc::LoaderFactory
 - get_instance, 153
 - load_all_instances, 153
 - LoaderFactory, 153
- Arc::LogDestination, 155
- Arc::LogDestination
 - log, 156
 - LogDestination, 155
- Arc::Logger, 157
 - addDestination, 158
 - getRootLogger, 158
 - getThreshold, 158
 - Logger, 158
 - msg, 158, 159
 - removeDestinations, 159
 - setThreshold, 159
- Arc::LogMessage, 160
- Arc::LogMessage
 - getLevel, 161
 - Logger, 161
 - LogMessage, 160
 - operator<=, 161
 - setIdentifier, 161
- Arc::LogStream, 162
- Arc::LogStream
 - log, 163
 - LogStream, 162
- Arc::MCC, 165
 - AddSecHandler, 166
 - logger, 166
 - MCC, 166
 - Next, 166
 - next_, 167
 - process, 166
 - ProcessSecHandlers, 166
 - sechandlers_, 167
 - Unlink, 166
- Arc::MCC_Status, 169
 - getExplanation, 169
 - getKind, 169
 - getOrigin, 170
 - isOk, 170
 - MCC_Status, 169
 - operator bool, 170
 - operator std::string, 170
 - operator!, 170
- Arc::MCCFactory, 172
 - get_instance, 172
 - MCCFactory, 172
- Arc::MCCInterface, 173
 - process, 173
- Arc::MD5Sum, 174
- Arc::Message, 175
 - ~Message, 176
 - Attributes, 176
 - Auth, 176
 - AuthContext, 176
 - Context, 176
 - Message, 176
 - operator=, 176
 - Payload, 177
- Arc::MessageAttributes, 178
- Arc::MessageAttributes
 - add, 179
 - attributes_, 180
 - count, 179
 - get, 179
 - getAll, 179
 - MessageAttributes, 178
 - remove, 180
 - removeAll, 180
 - set, 180
- Arc::MessageAuth, 181
- Arc::MessageAuth
 - Export, 181
 - Filter, 181
 - get, 181
 - operator[], 181
 - remove, 182
 - set, 182
- Arc::MessageAuthContext, 183
- Arc::MessageContext, 184
- Arc::MessageContext
 - Add, 184
- Arc::MessageContextElement, 185
- Arc::MessagePayload, 186
- Arc::ModuleManager, 187
- Arc::ModuleManager
 - findLocation, 187
 - load, 187
 - ModuleManager, 187
 - setCfg, 187
- Arc::MultiSecAttr, 189
- Arc::MultiSecAttr
 - operator bool, 189
- Arc::MySQLDatabase, 190
- Arc::MySQLDatabase
 - close, 190
 - connect, 190
 - enable_ssl, 191
 - isconnected, 191

- shutdown, 191
- Arc::PayloadRaw, 192
- Arc::PayloadRaw
 - ~PayloadRaw, 192
 - Buffer, 193
 - BufferPos, 193
 - BufferSize, 193
 - Content, 193
 - Insert, 193
 - operator[], 193
 - PayloadRaw, 192
 - Size, 193
 - Truncate, 194
- Arc::PayloadRawInterface, 195
- Arc::PayloadRawInterface
 - Buffer, 195
 - BufferPos, 195
 - BufferSize, 195
 - Content, 196
 - Insert, 196
 - operator[], 196
 - Size, 196
 - Truncate, 196
- Arc::PayloadSOAP, 197
- Arc::PayloadSOAP
 - PayloadSOAP, 197
- Arc::PayloadStream, 198
- Arc::PayloadStream
 - ~PayloadStream, 198
 - Get, 199
 - GetHandle, 199
 - handle_, 200
 - operator bool, 199
 - operator!, 199
 - PayloadStream, 198
 - Put, 199, 200
 - seekable_, 200
 - Timeout, 200
- Arc::PayloadStreamInterface, 201
- Arc::PayloadStreamInterface
 - Get, 201
 - operator bool, 202
 - operator!, 202
 - Put, 202
 - Timeout, 202
- Arc::PayloadWSRF, 204
- Arc::PayloadWSRF
 - PayloadWSRF, 204
- Arc::PDFactory, 208
 - get_instance, 208
 - PDFactory, 208
- Arc::Plexer, 210
 - ~Plexer, 210
 - logger, 211
 - Next, 211
 - Plexer, 210
 - process, 211
- Arc::PlexerEntry, 212
- Arc::RegularExpression, 217
- Arc::RegularExpression
 - ~RegularExpression, 217
 - getPattern, 217
 - hasPattern, 217
 - isOk, 218
 - match, 218
 - operator=, 218
 - RegularExpression, 217
- Arc::Run, 226
 - ~Run, 227
 - AssignStderr, 227
 - AssignStdin, 227
 - AssignStdout, 228
 - AssignWorkingDirectory, 228
 - CloseStderr, 228
 - CloseStdin, 228
 - CloseStdout, 228
 - KeepStderr, 228
 - KeepStdin, 228
 - KeepStdout, 228
 - Kill, 228
 - operator bool, 228
 - operator!, 228
 - ReadStderr, 229
 - ReadStdout, 229
 - Result, 229
 - Run, 227
 - Running, 229
 - Start, 229
 - Wait, 229
 - WriteStdin, 229
- Arc::SAMLToken, 230
 - Authenticate, 231
 - operator bool, 231
 - SAMLToken, 230
- Arc::SecAttr, 232
- Arc::SecAttr
 - ARCAuth, 234
 - Export, 233
 - Import, 233
 - operator bool, 233
 - operator!=, 233
 - operator==, 233
 - SAML, 234
 - SecAttr, 233
 - XACML, 234
- Arc::SecAttr::Format, 235
- Arc::SecAttrValue, 236
- Arc::SecAttrValue

- operator bool, 236
- operator!=, 236
- operator==, 236
- Arc::SecHandlerFactory, 240
- Arc::SecHandlerFactory
 - get_instance, 240
 - SecHandlerFactory, 240
- Arc::Service, 242
 - AddSecHandler, 243
 - getID, 243
 - logger, 243
 - ProcessSecHandlers, 243
 - RegistrationCollector, 243
 - sechandlers_, 243
 - Service, 243
- Arc::ServiceFactory, 245
- Arc::ServiceFactory
 - get_instance, 245
 - ServiceFactory, 245
- Arc::SimpleCondition, 246
- Arc::SimpleCondition
 - broadcast, 246
 - lock, 246
 - reset, 246
 - signal, 246
 - signal_nonblock, 246
 - unlock, 246
 - wait, 247
 - wait_nonblock, 247
- Arc::SOAPMessage, 248
 - ~SOAPMessage, 248
 - Attributes, 249
 - Payload, 249
 - SOAPMessage, 248
- Arc::Time, 254
 - GetFormat, 255
 - GetTime, 255
 - operator std::string, 255
 - operator!=, 255
 - operator+, 255
 - operator-, 255
 - operator<, 255
 - operator<=, 255
 - operator=, 255
 - operator==, 255
 - operator>, 256
 - operator>=, 256
 - SetFormat, 256
 - SetTime, 256
 - str, 256
 - Time, 254
- Arc::URL, 257
 - ~URL, 259
 - AddLDAPAttribute, 259
 - AddOption, 259
 - BaseDN2Path, 259
 - ChangeHost, 259
 - ChangeLDAPFilter, 259
 - ChangeLDAPScope, 259
 - ChangePath, 259
 - ChangePort, 259
 - ChangeProtocol, 260
 - CommonLocOption, 260
 - CommonLocOptions, 260
 - commonlocoptions, 262
 - ConnectionURL, 260
 - fullstr, 260
 - Host, 260
 - host, 262
 - HTTPOption, 260
 - HTTPOptions, 260
 - httpoptions, 262
 - LDAPAttributes, 260
 - ldapattributes, 262
 - LDAPFilter, 261
 - ldapfilter, 263
 - LDAPScope, 261
 - ldapscope, 263
 - Locations, 261
 - locations, 263
 - operator bool, 261
 - operator<, 261
 - operator<<, 262
 - operator==, 261
 - Option, 261
 - Options, 261
 - Passwd, 261
 - passwd, 263
 - Path, 261
 - path, 263
 - Path2BaseDN, 262
 - Port, 262
 - port, 263
 - Protocol, 262
 - protocol, 263
 - Scope, 258
 - str, 262
 - URL, 259
 - urloptions, 263
 - Username, 262
 - username, 263
- Arc::URLLocation, 264
 - ~URLLocation, 265
 - fullstr, 265
 - Name, 265
 - name, 265
 - str, 265
 - URLLocation, 264, 265

- Arc::UsernameToken, 266
- Arc::UsernameToken
 - Authenticate, 267
 - operator bool, 267
 - PasswordType, 266
 - Username, 267
 - UsernameToken, 266, 267
- Arc::WSAEndpointReference, 269
- Arc::WSAEndpointReference
 - ~WSAEndpointReference, 269
 - Address, 270
 - MetaData, 270
 - operator XMLNode, 270
 - operator=, 270
 - ReferenceParameters, 270
 - WSAEndpointReference, 269
- Arc::WSAHeader, 271
 - Action, 272
 - Check, 272
 - FaultTo, 272
 - From, 272
 - header_allocated_, 273
 - MessageID, 272
 - NewReferenceParameter, 272
 - operator XMLNode, 272
 - ReferenceParameter, 272
 - RelatesTo, 273
 - RelationshipType, 273
 - ReplyTo, 273
 - To, 273
 - WSAHeader, 271
- Arc::WSRF, 274
 - allocated_, 275
 - operator bool, 275
 - set_namespaces, 275
 - SOAP, 275
 - valid_, 275
 - WSRF, 274
- Arc::WSRFBBaseFault, 276
- Arc::WSRFBBaseFault
 - set_namespaces, 277
 - WSRFBBaseFault, 276
- Arc::WSRP, 278
 - set_namespaces, 278
 - WSRP, 278
- Arc::WSRPFault, 280
 - WSRPFault, 280
- Arc::WSRPResourcePropertyChangeFailure, 281
- Arc::WSRPResourcePropertyChangeFailure
 - WSRPResourcePropertyChangeFailure, 281
- Arc::X509Token, 282
 - Authenticate, 283
 - operator bool, 283
 - X509Token, 282
- Arc::XMLNode, 284
 - ~XMLNode, 286
 - Attribute, 286
 - AttributesSize, 287
 - Child, 287
 - Destroy, 287
 - FullName, 287
 - Get, 287
 - GetDoc, 287
 - GetRoot, 287
 - GetXML, 287
 - is_owner_, 292
 - is_temporary_, 292
 - MatchXMLName, 291
 - MatchXMLNamespace, 291
 - Name, 287, 288
 - Namespace, 288
 - NamespacePrefix, 288
 - Namespaces, 288
 - New, 288
 - NewAttribute, 288
 - NewChild, 288, 289
 - operator bool, 289
 - operator std::string, 289
 - operator!, 289
 - operator++, 289
 - operator-, 289
 - operator=, 289, 290
 - operator[], 290
 - Parent, 290
 - Prefix, 290
 - ReadFromFile, 290
 - ReadFromStream, 290
 - Replace, 290
 - SaveToFile, 290
 - SaveToStream, 291
 - Set, 291
 - Size, 291
 - XMLNode, 286
 - XPathLookup, 291
- Arc::XMLNodeContainer, 293
- Arc::XMLNodeContainer
 - Add, 293
 - AddNew, 293
 - Nodes, 294
 - operator=, 294
 - operator[], 294
 - Size, 294
 - XMLNodeContainer, 293
- Arc::XMLSecNode, 295
- Arc::XMLSecNode
 - XMLSecNode, 295
- ARCAuth
 - Arc::SecAttr, 234

- ArcSec::AlgFactory, 29
- ArcSec::AlgFactory
 - createAlg, 29
- ArcSec::ArcAttributeProxy, 30
- ArcSec::ArcAttributeProxy
 - getAttribute, 30
- ArcSec::Attr, 32
- ArcSec::AttributeFactory, 33
- ArcSec::AttributeProxy, 37
- ArcSec::AttributeValue, 38
- ArcSec::AttributeValue
 - encode, 38
 - equal, 38
 - getId, 38
 - getType, 38
- ArcSec::Attrs, 39
- ArcSec::AuthzRequestSection, 40
- ArcSec::CombiningAlg, 50
- ArcSec::CombiningAlg
 - combine, 50
- ArcSec::DenyOverridesCombiningAlg, 121
- ArcSec::DenyOverridesCombiningAlg
 - combine, 121
- ArcSec::EqualFunction, 124
- ArcSec::EqualFunction
 - getFunctionName, 124
- ArcSec::EvalResult, 125
- ArcSec::EvaluationCtx, 126
- ArcSec::EvaluationCtx
 - EvaluationCtx, 126
 - split, 126
- ArcSec::Evaluator, 127
- ArcSec::Evaluator
 - addPolicy, 127
 - evaluate, 127, 128
 - getAlgFactory, 128
 - getAttrFactory, 128
 - getFnFactory, 128
- ArcSec::EvaluatorContext, 130
- ArcSec::EvaluatorContext
 - operator AlgFactory *, 130
 - operator AttributeFactory *, 130
 - operator FnFactory *, 130
- ArcSec::EvaluatorLoader, 131
- ArcSec::EvaluatorLoader
 - getEvaluator, 131
 - getPolicy, 131
 - getRequest, 131
- ArcSec::FnFactory, 135
- ArcSec::Function, 136
- ArcSec::MatchFunction, 164
- ArcSec::MatchFunction
 - getFunctionName, 164
- ArcSec::PDP, 206
- ArcSec::PermitOverridesCombiningAlg, 209
- ArcSec::PermitOverridesCombiningAlg
 - combine, 209
- ArcSec::Policy, 213
- ArcSec::Policy
 - addPolicy, 213
 - getEffect, 213
 - getEvalResult, 213
 - make_policy, 213
 - match, 213
 - setEvalResult, 214
 - setEvaluatorContext, 214
- ArcSec::PolicyParser, 215
- ArcSec::PolicyParser
 - parsePolicy, 215
- ArcSec::PolicyStore, 216
- ArcSec::PolicyStore
 - PolicyStore, 216
- ArcSec::Request, 219
- ArcSec::Request
 - addRequestItem, 219
 - getRequestItems, 219
 - make_request, 220
 - Request, 219
 - setAttributeFactory, 220
 - setRequestItems, 220
- ArcSec::RequestAttribute, 221
- ArcSec::RequestAttribute
 - duplicate, 221
 - RequestAttribute, 221
- ArcSec::RequestItem, 222
- ArcSec::RequestItem
 - RequestItem, 222
- ArcSec::RequestTuple, 223
- ArcSec::Response, 224
- ArcSec::ResponseItem, 225
- ArcSec::SecHandler, 238
- ArcSec::Security, 241
- ArcSec::Source, 250
- ArcSec::Source
 - Get, 251
 - operator bool, 251
 - Source, 250, 251
- ArcSec::SourceFile, 252
- ArcSec::SourceFile
 - SourceFile, 252
- ArcSec::SourceURL, 253
- ArcSec::SourceURL
 - SourceURL, 253
- Assign
 - Arc::InformationContainer, 139
- AssignStderr
 - Arc::Run, 227
- AssignStdin

- Arc::Run, 227
- AssignStdout
 - Arc::Run, 228
- AssignWorkingDirectory
 - Arc::Run, 228
- AttrConstIter
 - Arc, 21
- Attribute
 - Arc::XMLNode, 286
- AttributeIterator
 - Arc::AttributeIterator, 34
- Attributes
 - Arc::Message, 176
 - Arc::SOAPMessage, 249
- attributes_
 - Arc::MessageAttributes, 180
- AttributesSize
 - Arc::XMLNode, 287
- AttrIter
 - Arc, 21
- AttrMap
 - Arc, 21
- Auth
 - Arc::Message, 176
- AuthContext
 - Arc::Message, 176
- Authenticate
 - Arc::SAMLToken, 231
 - Arc::UsernameToken, 267
 - Arc::X509Token, 283
- Backup
 - Arc::DelegationConsumer, 112
- BaseDN2Path
 - Arc::URL, 259
- broadcast
 - Arc::SimpleCondition, 246
- Buffer
 - Arc::PayloadRaw, 193
 - Arc::PayloadRawInterface, 195
- buffer_size
 - Arc::DataBufferPar, 66
- BufferPos
 - Arc::PayloadRaw, 193
 - Arc::PayloadRawInterface, 195
- BufferSize
 - Arc::PayloadRaw, 193
 - Arc::PayloadRawInterface, 195
- BufNum
 - Arc::DataPoint, 84
 - Arc::DataPointDirect, 94
 - Arc::DataPointIndex, 101
- BufSize
 - Arc::DataPoint, 84
- Arc::DataPointDirect, 94
- Arc::DataPointIndex, 101
- BUSY_ERROR
 - Arc, 22
- Cache
 - Arc::DataPoint, 84
 - Arc::DataPointDirect, 95
 - Arc::DataPointIndex, 101
- cancel
 - Arc::Counter, 55
 - Arc::CounterTicket, 60
 - Arc::IntraProcessCounter, 147
- cb
 - Arc::DataCache, 73
- changeExcess
 - Arc::Counter, 55
 - Arc::IntraProcessCounter, 147
- ChangeHost
 - Arc::URL, 259
- ChangeLDAPFilter
 - Arc::URL, 259
- ChangeLDAPScope
 - Arc::URL, 259
- changeLimit
 - Arc::Counter, 55
 - Arc::IntraProcessCounter, 147
- ChangePath
 - Arc::URL, 259
- ChangePort
 - Arc::URL, 259
- ChangeProtocol
 - Arc::URL, 260
- Check
 - Arc::DataPoint, 84
 - Arc::DataPointIndex, 101
 - Arc::WSAHeader, 272
- CheckChecksum
 - Arc::DataPoint, 85
- CheckCreated
 - Arc::DataCache, 73
 - Arc::DataPoint, 85
- checks
 - Arc::DataMover, 79
- CheckSize
 - Arc::DataPoint, 85
- checksum_object
 - Arc::DataBufferPar, 66
- checksum_valid
 - Arc::DataBufferPar, 66
- CheckValid
 - Arc::DataCache, 73
 - Arc::DataPoint, 85
- Child

- Arc::XMLNode, 287
- CIStrngValue
 - Arc::CIStrngValue, 47
- clean
 - Arc::DataCache, 73
- ClientSOAP
 - Arc::ClientSOAP, 49
- close
 - Arc::Database, 64
 - Arc::MySQLDatabase, 190
- CloseStderr
 - Arc::Run, 228
- CloseStdin
 - Arc::Run, 228
- CloseStdout
 - Arc::Run, 228
- combine
 - ArcSec::CombiningAlg, 50
 - ArcSec::DenyOverridesCombiningAlg, 121
 - ArcSec::PermitOverridesCombiningAlg, 209
- CommonLocOption
 - Arc::URL, 260
- CommonLocOptions
 - Arc::URL, 260
- commonlocoptions
 - Arc::URL, 262
- CompareMeta
 - Arc::DataPoint, 85
- Config
 - Arc::Config, 51, 52
- connect
 - Arc::Database, 64
 - Arc::MySQLDatabase, 190
- ConnectionURL
 - Arc::URL, 260
- Content
 - Arc::PayloadRaw, 193
 - Arc::PayloadRawInterface, 196
- ContentFromPayload
 - Arc, 24
- Context
 - Arc::Message, 176
- context_lock_
 - Arc::DelegationContainerSOAP, 115
- copy
 - Arc::DataCache, 74
- count
 - Arc::MessageAttributes, 179
- Counter
 - Arc::Counter, 55
 - Arc::CounterTicket, 61
 - Arc::ExpirationReminder, 133
- CounterTicket
 - Arc::Counter, 59
- Arc::CounterTicket, 60
- createAlg
 - ArcSec::AlgFactory, 29
- CreateThreadFunction
 - Arc, 23
- current_
 - Arc::AttributeIterator, 36
- CurrentLocation
 - Arc::DataPoint, 85
 - Arc::DataPointDirect, 95
 - Arc::DataPointIndex, 102
- CurrentLocationMetadata
 - Arc::DataPoint, 85
 - Arc::DataPointDirect, 95
 - Arc::DataPointIndex, 102
- Database
 - Arc::Database, 63
- DataBufferPar
 - Arc::DataBufferPar, 66
- DataCache
 - Arc::DataCache, 73
- DataMover
 - Arc::DataMover, 78
- DataPoint
 - Arc::DataPoint, 84
- DataSpeed
 - Arc::DataSpeed, 107
- Delegate
 - Arc::DelegationProvider, 117
- DelegateCredentialsInit
 - Arc::DelegationConsumerSOAP, 113
 - Arc::DelegationContainerSOAP, 115
 - Arc::DelegationProviderSOAP, 120
- DelegatedToken
 - Arc::DelegationConsumerSOAP, 113
 - Arc::DelegationContainerSOAP, 115
 - Arc::DelegationProviderSOAP, 120
- DelegationConsumer
 - Arc::DelegationConsumer, 111
- DelegationConsumerSOAP
 - Arc::DelegationConsumerSOAP, 113
- DelegationProvider
 - Arc::DelegationProvider, 117
- DelegationProviderSOAP
 - Arc::DelegationProviderSOAP, 119
- Destroy
 - Arc::XMLNode, 287
- dmc_descriptor, 122
- DMCFactory
 - Arc::DMCFactory, 123
- doc_
 - Arc::InformationContainer, 140
- duplicate

- ArcSec::RequestAttribute, 221
- enable_ssl
 - Arc::Database, 64
 - Arc::MySQLDatabase, 191
- encode
 - ArcSec::AttributeValue, 38
- end_
 - Arc::AttributeIterator, 36
- eof_position
 - Arc::DataBufferPar, 66
- eof_read
 - Arc::DataBufferPar, 67
- eof_write
 - Arc::DataBufferPar, 67
- equal
 - Arc::CStringValue, 48
 - ArcSec::AttributeValue, 38
- error
 - Arc::DataBufferPar, 67
- error_read
 - Arc::DataBufferPar, 67
- error_transfer
 - Arc::DataBufferPar, 67
- error_write
 - Arc::DataBufferPar, 67
- ETERNAL
 - Arc, 25
- evaluate
 - ArcSec::Evaluator, 127, 128
- EvaluationCtx
 - ArcSec::EvaluationCtx, 126
- ExpirationReminder
 - Arc::Counter, 59
- Export
 - Arc::MessageAuth, 181
 - Arc::SecAttr, 233
- extend
 - Arc::Counter, 56
 - Arc::CounterTicket, 61
 - Arc::IntraProcessCounter, 147
- FaultTo
 - Arc::WSAHeader, 272
- file
 - Arc::DataCache, 74
- Filter
 - Arc::MessageAuth, 181
- findLocation
 - Arc::ModuleManager, 187
- for_read
 - Arc::DataBufferPar, 68
- for_write
 - Arc::DataBufferPar, 68
- force_to_meta
 - Arc::DataMover, 79
- From
 - Arc::WSAHeader, 272
- FullName
 - Arc::XMLNode, 287
- fullstr
 - Arc::URL, 260
 - Arc::URLLocation, 265
- Generate
 - Arc::DelegationConsumer, 112
- GENERIC_ERROR
 - Arc, 22
- Get
 - Arc::ArcLocation, 31
 - Arc::InformationContainer, 140
 - Arc::InformationInterface, 141
 - Arc::PayloadStream, 199
 - Arc::PayloadStreamInterface, 201
 - Arc::XMLNode, 287
 - ArcSec::Source, 251
- get
 - Arc::MessageAttributes, 179
 - Arc::MessageAuth, 181
- get_instance
 - Arc::ACCFactory, 28
 - Arc::DMCFactory, 123
 - Arc::LoaderFactory, 153
 - Arc::MCCFactory, 172
 - Arc::PDPFactory, 208
 - Arc::SecHandlerFactory, 240
 - Arc::ServiceFactory, 245
- getACC
 - Arc::Loader, 151
- GetAdditionalChecks
 - Arc::DataPoint, 85
 - Arc::DataPointDirect, 95
 - Arc::DataPointIndex, 102
- getAlgFactory
 - ArcSec::Evaluator, 128
- getAll
 - Arc::MessageAttributes, 179
- getAttrFactory
 - ArcSec::Evaluator, 128
- getAttribute
 - ArcSec::ArcAttributeProxy, 30
- GetChecksum
 - Arc::DataPoint, 86
- getCounterTicket
 - Arc::Counter, 56
- GetCreated
 - Arc::DataCache, 74
 - Arc::DataPoint, 86

- getCurrentTime
 - Arc::Counter, 56
- GetDoc
 - Arc::XMLNode, 287
- getEffect
 - ArcSec::Policy, 213
- getEvalResult
 - ArcSec::Policy, 213
- getEvaluator
 - ArcSec::EvaluatorLoader, 131
- getExcess
 - Arc::Counter, 57
 - Arc::IntraProcessCounter, 148
- getExpirationReminder
 - Arc::Counter, 57
- getExpiryTime
 - Arc::Counter, 57
 - Arc::ExpirationReminder, 132
- getExplanation
 - Arc::MCC_Status, 169
- getFileName
 - Arc::Config, 52
- getFnFactory
 - ArcSec::Evaluator, 128
- GetFormat
 - Arc::Time, 255
- getFunctionName
 - ArcSec::EqualFunction, 124
 - ArcSec::MatchFunction, 164
- GetHandle
 - Arc::PayloadStream, 199
- getID
 - Arc::Service, 243
- getId
 - ArcSec::AttributeValue, 38
- getKind
 - Arc::MCC_Status, 169
- getLevel
 - Arc::LogMessage, 161
- getLimit
 - Arc::Counter, 57
 - Arc::IntraProcessCounter, 148
- getOrigin
 - Arc::MCC_Status, 170
- GetOverlay
 - Arc::BaseConfig, 42
- getPattern
 - Arc::RegularExpression, 217
- GetPlugins
 - Arc::ArcLocation, 31
- getPolicy
 - ArcSec::EvaluatorLoader, 131
- getRequest
 - ArcSec::EvaluatorLoader, 131
- getRequestItems
 - ArcSec::Request, 219
- getReservationID
 - Arc::ExpirationReminder, 132
- GetRoot
 - Arc::XMLNode, 287
- getRootLogger
 - Arc::Logger, 158
- GetSecure
 - Arc::DataPoint, 86
 - Arc::DataPointDirect, 95
 - Arc::DataPointIndex, 102
- GetSize
 - Arc::DataPoint, 86
- getThreshold
 - Arc::Logger, 158
- GetTime
 - Arc::Time, 255
- GetTries
 - Arc::DataPoint, 86
- getType
 - ArcSec::AttributeValue, 38
- GetURL
 - Arc::DataPoint, 86
- GetValid
 - Arc::DataCache, 74
 - Arc::DataPoint, 86
- getValue
 - Arc::Counter, 58
 - Arc::IntraProcessCounter, 148
- GetXML
 - Arc::XMLNode, 287
- GUID
 - Arc, 23
- handle_
 - Arc::PayloadStream, 200
- hasMore
 - Arc::AttributeIterator, 35
- hasPattern
 - Arc::RegularExpression, 217
- HaveLocations
 - Arc::DataPoint, 86
 - Arc::DataPointDirect, 95
 - Arc::DataPointIndex, 102
- header_allocated_
 - Arc::WSAHeader, 273
- HISTORIC
 - Arc, 25
- hold
 - Arc::DataSpeed, 108
- Host
 - Arc::URL, 260
- host

- Arc::URL, 262
- HTTPOption
 - Arc::URL, 260
- HTTPOptions
 - Arc::URL, 260
- httpoptions
 - Arc::URL, 262
- ID
 - Arc::DelegationConsumer, 112
- IDType
 - Arc::Counter, 55
- Import
 - Arc::SecAttr, 233
- InfoRegisters
 - Arc::InfoRegisters, 138
- InformationContainer
 - Arc::InformationContainer, 139
- InformationInterface
 - Arc::InformationInterface, 141
- InformationRequest
 - Arc::InformationRequest, 143
- InformationResponse
 - Arc::InformationResponse, 145
- Init
 - Arc::ArcLocation, 31
- Insert
 - Arc::PayloadRaw, 193
 - Arc::PayloadRawInterface, 196
- IntraProcessCounter
 - Arc::IntraProcessCounter, 146
- is_notwritten
 - Arc::DataBufferPar, 68
- is_owner_
 - Arc::XMLNode, 292
- is_read
 - Arc::DataBufferPar, 69
- is_temporary_
 - Arc::XMLNode, 292
- is_written
 - Arc::DataBufferPar, 69
- isconnected
 - Arc::Database, 64
 - Arc::MySQLDatabase, 191
- IsIndex
 - Arc::DataPoint, 86
 - Arc::DataPointDirect, 95
 - Arc::DataPointIndex, 102
- isOk
 - Arc::MCC_Status, 170
 - Arc::RegularExpression, 218
- isValid
 - Arc::CounterTicket, 61
- KeepStderr
 - Arc::Run, 228
- KeepStdin
 - Arc::Run, 228
- KeepStdout
 - Arc::Run, 228
- key
 - Arc::AttributeIterator, 35
- Kill
 - Arc::Run, 228
- LDAPAttributes
 - Arc::URL, 260
- ldapattributes
 - Arc::URL, 262
- LDAPFilter
 - Arc::URL, 261
- ldapfilter
 - Arc::URL, 263
- LDAPScope
 - Arc::URL, 261
- ldapscope
 - Arc::URL, 263
- link
 - Arc::DataCache, 74
- ListFiles
 - Arc::DataPoint, 86
- load
 - Arc::ModuleManager, 187
- load_all_instances
 - Arc::LoaderFactory, 153
- Loader
 - Arc::Loader, 151
- loader_descriptors
 - Arc, 21
- LoaderFactory
 - Arc::LoaderFactory, 153
- Local
 - Arc::DataPoint, 87
 - Arc::DataPointDirect, 95
 - Arc::DataPointIndex, 102
- Locations
 - Arc::URL, 261
- locations
 - Arc::DataPointIndex, 106
 - Arc::URL, 263
- LocationValid
 - Arc::DataPoint, 87
 - Arc::DataPointDirect, 96
 - Arc::DataPointIndex, 102
- lock
 - Arc::SimpleCondition, 246
- lock_
 - Arc::InformationInterface, 142

- log
 - Arc::LogDestination, 156
 - Arc::LogStream, 163
- LogDestination
 - Arc::LogDestination, 155
- LogError
 - Arc::DelegationConsumer, 112
- Logger
 - Arc::Logger, 158
 - Arc::LogMessage, 161
- logger
 - Arc::MCC, 166
 - Arc::Plexer, 211
 - Arc::Service, 243
- LogLevel
 - Arc, 22
- LogMessage
 - Arc::LogMessage, 160
- LogStream
 - Arc::LogStream, 162
- make_policy
 - ArcSec::Policy, 213
- make_request
 - ArcSec::Request, 220
- MakeConfig
 - Arc::BaseConfig, 42
- match
 - Arc::RegularExpression, 218
 - ArcSec::Policy, 213
- MatchXMLName
 - Arc, 24
 - Arc::XMLNode, 291
- MatchXMLNamespace
 - Arc, 24
 - Arc::XMLNode, 291
- max_duration_
 - Arc::DelegationContainerSOAP, 115
- max_inactivity_time_failure
 - Arc::DataSpeed, 108
- max_size_
 - Arc::DelegationContainerSOAP, 116
- max_usage_
 - Arc::DelegationContainerSOAP, 116
- MCC
 - Arc::MCC, 166
- mcc_descriptor, 168
- MCC_Status
 - Arc::MCC_Status, 169
- MCCFactory
 - Arc::MCCFactory, 172
- Message
 - Arc::Message, 176
- MessageAttributes
 - Arc::AttributeIterator, 36
 - Arc::MessageAttributes, 178
- MessageID
 - Arc::WSAHeader, 272
- MetaData
 - Arc::WSAEndpointReference, 270
- min_average_speed_failure
 - Arc::DataSpeed, 108
- min_speed_failure
 - Arc::DataSpeed, 108
- ModuleManager
 - Arc::ModuleManager, 187
- msg
 - Arc::Logger, 158, 159
- Name
 - Arc::URLLocation, 265
 - Arc::XMLNode, 287, 288
- name
 - Arc::URLLocation, 265
- Namespace
 - Arc::XMLNode, 288
- NamespacePrefix
 - Arc::XMLNode, 288
- Namespaces
 - Arc::XMLNode, 288
- New
 - Arc::XMLNode, 288
- NewAttribute
 - Arc::XMLNode, 288
- NewChild
 - Arc::XMLNode, 288, 289
- NewReferenceParameter
 - Arc::WSAHeader, 272
- Next
 - Arc::MCC, 166
 - Arc::Plexer, 211
- next_
 - Arc::MCC, 167
- NextLocation
 - Arc::DataPoint, 87
 - Arc::DataPointDirect, 96
 - Arc::DataPointIndex, 103
- Nodes
 - Arc::XMLNodeContainer, 294
- operator *
 - Arc::AttributeIterator, 35
- operator AlgFactory *
 - ArcSec::EvaluatorContext, 130
- operator AttributeFactory *
 - ArcSec::EvaluatorContext, 130
- operator bool
 - Arc::CStringValue, 48

- Arc::DataBufferPar, 69
- Arc::DataCache, 74
- Arc::DataPoint, 87
- Arc::MCC_Status, 170
- Arc::MultiSecAttr, 189
- Arc::PayloadStream, 199
- Arc::PayloadStreamInterface, 202
- Arc::Run, 228
- Arc::SAMLToken, 231
- Arc::SecAttr, 233
- Arc::SecAttrValue, 236
- Arc::URL, 261
- Arc::UsernameToken, 267
- Arc::WSRF, 275
- Arc::X509Token, 283
- Arc::XMLNode, 289
- ArcSec::Source, 251
- operator FnFactory *
 - ArcSec::EvaluatorContext, 130
- operator MCCFactory *
 - Arc::ChainContext, 43
- operator PDPFactory *
 - Arc::ChainContext, 43
- operator SecHandlerFactory *
 - Arc::ChainContext, 43
- operator ServiceFactory *
 - Arc::ChainContext, 43
- operator std::string
 - Arc::MCC_Status, 170
 - Arc::Time, 255
 - Arc::XMLNode, 289
- operator XMLNode
 - Arc::WSAEndpointReference, 270
 - Arc::WSAHeader, 272
- operator!
 - Arc::DataPoint, 87
 - Arc::MCC_Status, 170
 - Arc::PayloadStream, 199
 - Arc::PayloadStreamInterface, 202
 - Arc::Run, 228
 - Arc::XMLNode, 289
- operator!=
 - Arc::SecAttr, 233
 - Arc::SecAttrValue, 236
 - Arc::Time, 255
- operator+
 - Arc::Time, 255
- operator++
 - Arc::AttributeIterator, 35
 - Arc::XMLNode, 289
- operator-
 - Arc::Time, 255
- operator-
 - Arc::XMLNode, 289
- operator->
 - Arc::AttributeIterator, 36
- operator<
 - Arc::ExpirationReminder, 132
 - Arc::Time, 255
 - Arc::URL, 261
- operator<<
 - Arc, 22, 23
 - Arc::LogMessage, 161
 - Arc::URL, 262
- operator<=
 - Arc::Time, 255
- operator=
 - Arc::Message, 176
 - Arc::RegularExpression, 218
 - Arc::Time, 255
 - Arc::WSAEndpointReference, 270
 - Arc::XMLNode, 289, 290
 - Arc::XMLNodeContainer, 294
- operator==
 - Arc::SecAttr, 233
 - Arc::SecAttrValue, 236
 - Arc::Time, 255
 - Arc::URL, 261
- operator>
 - Arc::Time, 256
- operator>=
 - Arc::Time, 256
- operator[]
 - Arc::DataBufferPar, 69
 - Arc::Loader, 151
 - Arc::MessageAuth, 181
 - Arc::PayloadRaw, 193
 - Arc::PayloadRawInterface, 196
 - Arc::XMLNode, 290
 - Arc::XMLNodeContainer, 294
- Option
 - Arc::URL, 261
- Options
 - Arc::URL, 261
- Parent
 - Arc::XMLNode, 290
- parse
 - Arc::Config, 52
- parsePolicy
 - ArcSec::PolicyParser, 215
- PARSING_ERROR
 - Arc, 22
- Passive
 - Arc::DataPoint, 87
 - Arc::DataPointDirect, 96
 - Arc::DataPointIndex, 103
- passive

- Arc::DataMover, 79
- Passwd
 - Arc::URL, 261
- passwd
 - Arc::URL, 263
- PasswordType
 - Arc::UsernameToken, 266
- Path
 - Arc::URL, 261
- path
 - Arc::URL, 263
- Path2BaseDN
 - Arc::URL, 262
- Payload
 - Arc::Message, 177
 - Arc::SOAPMessage, 249
- PayloadRaw
 - Arc::PayloadRaw, 192
- PayloadSOAP
 - Arc::PayloadSOAP, 197
- PayloadStream
 - Arc::PayloadStream, 198
- PayloadWSRF
 - Arc::PayloadWSRF, 204
- pdp_descriptor, 207
- PDPFactory
 - Arc::PDPFactory, 208
- Plexer
 - Arc::Plexer, 210
- PolicyStore
 - ArcSec::PolicyStore, 216
- Port
 - Arc::URL, 262
- port
 - Arc::URL, 263
- PostRegister
 - Arc::DataPoint, 87
 - Arc::DataPointDirect, 96
- Prefix
 - Arc::XMLNode, 290
- PreRegister
 - Arc::DataPoint, 88
 - Arc::DataPointDirect, 96
- PreUnregister
 - Arc::DataPoint, 88
 - Arc::DataPointDirect, 97
- print
 - Arc::Config, 52
- process
 - Arc::ClientSOAP, 49
 - Arc::MCC, 166
 - Arc::MCCInterface, 173
 - Arc::Plexer, 211
- ProcessSecHandlers
 - Arc::MCC, 166
 - Arc::Service, 243
- Protocol
 - Arc::URL, 262
- protocol
 - Arc::URL, 263
- PROTOCOL_RECOGNIZED_ERROR
 - Arc, 22
- ProvidesMeta
 - Arc::DataPoint, 88
 - Arc::DataPointDirect, 97
 - Arc::DataPointIndex, 103
- Put
 - Arc::PayloadStream, 199, 200
 - Arc::PayloadStreamInterface, 202
- Range
 - Arc::DataPoint, 88
 - Arc::DataPointDirect, 97
 - Arc::DataPointIndex, 103
- ReadFromFile
 - Arc::XMLNode, 290
- ReadFromStream
 - Arc::XMLNode, 290
- ReadOutOfOrder
 - Arc::DataPoint, 89
 - Arc::DataPointDirect, 97
 - Arc::DataPointIndex, 103
- ReadStderr
 - Arc::Run, 229
- ReadStdout
 - Arc::Run, 229
- ReadURLList
 - Arc, 24
- ReferenceParameter
 - Arc::WSAHeader, 272
- ReferenceParameters
 - Arc::WSAEndpointReference, 270
- Registered
 - Arc::DataPoint, 89
 - Arc::DataPointDirect, 97
 - Arc::DataPointIndex, 103
- RegistrationCollector
 - Arc::Service, 243
- RegularExpression
 - Arc::RegularExpression, 217
- RelatesTo
 - Arc::WSAHeader, 273
- RelationshipType
 - Arc::WSAHeader, 273
- Remove
 - Arc::DataPoint, 89
 - Arc::DataPointIndex, 103
- remove

- Arc::MessageAttributes, 180
 - Arc::MessageAuth, 182
- removeAll
 - Arc::MessageAttributes, 180
- removeDestinations
 - Arc::Logger, 159
- RemoveLocation
 - Arc::DataPoint, 89
 - Arc::DataPointDirect, 97
 - Arc::DataPointIndex, 104
- RemoveLocations
 - Arc::DataPoint, 89
 - Arc::DataPointDirect, 97
 - Arc::DataPointIndex, 104
- Replace
 - Arc::XMLNode, 290
- ReplyTo
 - Arc::WSAHeader, 273
- Request
 - Arc::DelegationConsumer, 112
 - ArcSec::Request, 219
- RequestAttribute
 - ArcSec::RequestAttribute, 221
- RequestItem
 - ArcSec::RequestItem, 222
- reserve
 - Arc::Counter, 58
 - Arc::IntraProcessCounter, 148
- reset
 - Arc::DataSpeed, 108
 - Arc::SimpleCondition, 246
- Resolve
 - Arc::DataPoint, 89
 - Arc::DataPointDirect, 98
- Restore
 - Arc::DelegationConsumer, 112
- restricted_
 - Arc::DelegationContainerSOAP, 116
- Result
 - Arc::InformationResponse, 145
 - Arc::Run, 229
- retry
 - Arc::DataMover, 79
- Run
 - Arc::Run, 227
- Running
 - Arc::Run, 229
- SAML
 - Arc::SecAttr, 234
- SAMLTOKEN
 - Arc::SAMLToken, 230
- save
 - Arc::Config, 52
- SaveToFile
 - Arc::XMLNode, 290
- SaveToStream
 - Arc::XMLNode, 291
- Scope
 - Arc::URL, 258
- SecAttr
 - Arc::SecAttr, 233
- sechandler_descriptor, 239
- SecHandlerFactory
 - Arc::SecHandlerFactory, 240
- sechandlers_
 - Arc::MCC, 167
 - Arc::Service, 243
- secure
 - Arc::DataMover, 79
- seekable_
 - Arc::PayloadStream, 200
- Service
 - Arc::Service, 243
- service_descriptor, 244
- ServiceFactory
 - Arc::ServiceFactory, 245
- SESSION_CLOSE
 - Arc, 22
- Set
 - Arc::XMLNode, 291
- set
 - Arc::DataBufferPar, 70
 - Arc::MessageAttributes, 180
 - Arc::MessageAuth, 182
- set_base
 - Arc::DataSpeed, 108
- set_default_max_inactivity_time
 - Arc::DataMover, 79
- set_default_min_average_speed
 - Arc::DataMover, 79
- set_default_min_speed
 - Arc::DataMover, 80
- set_max_data
 - Arc::DataSpeed, 109
- set_max_inactivity_time
 - Arc::DataSpeed, 109
- set_min_average_speed
 - Arc::DataSpeed, 109
- set_min_speed
 - Arc::DataSpeed, 109
- set_namespaces
 - Arc::WSRF, 275
 - Arc::WSRFBASEFAULT, 277
 - Arc::WSRP, 278
- set_progress_indicator
 - Arc::DataSpeed, 109
- SetAdditionalChecks

- Arc::DataPoint, 89
- Arc::DataPointDirect, 98
- Arc::DataPointIndex, 104
- setAttributeFactory
 - ArcSec::Request, 220
- setCfg
 - Arc::ModuleManager, 187
- SetChecksum
 - Arc::DataPoint, 90
- SetCreated
 - Arc::DataCache, 74
 - Arc::DataPoint, 90
- setEvalResult
 - ArcSec::Policy, 214
- setEvaluatorContext
 - ArcSec::Policy, 214
- setExcess
 - Arc::Counter, 58
 - Arc::IntraProcessCounter, 149
- setFileName
 - Arc::Config, 52
- SetFormat
 - Arc::Time, 256
- setIdentifier
 - Arc::LogMessage, 161
- setLimit
 - Arc::Counter, 59
 - Arc::IntraProcessCounter, 149
- SetMeta
 - Arc::DataPoint, 90
- setRequestItems
 - ArcSec::Request, 220
- SetSecure
 - Arc::DataPoint, 90
 - Arc::DataPointDirect, 98
 - Arc::DataPointIndex, 104
- SetSize
 - Arc::DataPoint, 90
- setThreshold
 - Arc::Logger, 159
- SetTime
 - Arc::Time, 256
- SetTries
 - Arc::DataPoint, 90
 - Arc::DataPointIndex, 104
- SetValid
 - Arc::DataCache, 74
 - Arc::DataPoint, 90
- shutdown
 - Arc::Database, 64
 - Arc::MySQLDatabase, 191
- signal
 - Arc::SimpleCondition, 246
- signal_nonblock
 - Arc::SimpleCondition, 246
- Size
 - Arc::PayloadRaw, 193
 - Arc::PayloadRawInterface, 196
 - Arc::XMLNode, 291
 - Arc::XMLNodeContainer, 294
- SOAP
 - Arc::InformationRequest, 143
 - Arc::WSRF, 275
- SOAPMessage
 - Arc::SOAPMessage, 248
- Source
 - ArcSec::Source, 250, 251
- SourceFile
 - ArcSec::SourceFile, 252
- SourceURL
 - ArcSec::SourceURL, 253
- speed
 - Arc::DataBufferPar, 71
- split
 - ArcSec::EvaluationCtx, 126
- Start
 - Arc::Run, 229
- start
 - Arc::DataCache, 75
- StartReading
 - Arc::DataPoint, 91
 - Arc::DataPointIndex, 104
- StartWriting
 - Arc::DataPoint, 91
 - Arc::DataPointIndex, 105
- STATUS_OK
 - Arc, 22
- StatusKind
 - Arc, 22
- stop
 - Arc::DataCache, 75
- StopReading
 - Arc::DataPoint, 91
 - Arc::DataPointIndex, 105
- StopWriting
 - Arc::DataPoint, 91
 - Arc::DataPointIndex, 105
- str
 - Arc::DataPoint, 91
 - Arc::Time, 256
 - Arc::URL, 262
 - Arc::URLLocation, 265
- string
 - Arc, 24
- stringto
 - Arc, 23
- Time

- Arc::Time, 254
- TimeFormat
 - Arc, 21
- Timeout
 - Arc::PayloadStream, 200
 - Arc::PayloadStreamInterface, 202
- TimeStamp
 - Arc, 22
- To
 - Arc::WSAHeader, 273
- tokenize
 - Arc, 23
- tostring
 - Arc, 23
- Transfer
 - Arc::DataMover, 80
- transfer
 - Arc::DataSpeed, 109
- transferred_size
 - Arc::DataSpeed, 110
- trim
 - Arc, 23
- Truncate
 - Arc::PayloadRaw, 194
 - Arc::PayloadRawInterface, 196
- UNKNOWN_SERVICE_ERROR
 - Arc, 22
- Unlink
 - Arc::MCC, 166
- unlock
 - Arc::SimpleCondition, 246
- Unregister
 - Arc::DataPoint, 92
 - Arc::DataPointDirect, 98
- UpdateCredentials
 - Arc::DelegationConsumerSOAP, 114
 - Arc::DelegationContainerSOAP, 115
 - Arc::DelegationProviderSOAP, 120
- upper
 - Arc, 23
- uri_unescape
 - Arc, 23
- URL
 - Arc::URL, 259
- URLLocation
 - Arc::URLLocation, 264, 265
- urloptions
 - Arc::URL, 263
- Username
 - Arc::URL, 262
 - Arc::UsernameToken, 267
- username
 - Arc::URL, 263
- UsernameToken
 - Arc::UsernameToken, 266, 267
- UUID
 - Arc, 23
- valid_
 - Arc::WSRF, 275
- verbose
 - Arc::DataMover, 80, 81
 - Arc::DataSpeed, 110
- Wait
 - Arc::Run, 229
- wait
 - Arc::DataBufferPar, 70
 - Arc::SimpleCondition, 247
- wait_eof
 - Arc::DataBufferPar, 70
- wait_eof_read
 - Arc::DataBufferPar, 70
- wait_eof_write
 - Arc::DataBufferPar, 70
- wait_nonblock
 - Arc::SimpleCondition, 247
- wait_read
 - Arc::DataBufferPar, 70
- wait_used
 - Arc::DataBufferPar, 70
- wait_write
 - Arc::DataBufferPar, 70
- WriteOutOfOrder
 - Arc::DataPoint, 92
 - Arc::DataPointDirect, 98
 - Arc::DataPointIndex, 105
- WriteStdin
 - Arc::Run, 229
- WSAEndpointReference
 - Arc::WSAEndpointReference, 269
- WSAFault
 - Arc, 22
- WSAFaultAssign
 - Arc, 24
- WSAFaultExtract
 - Arc, 25
- WSAFaultInvalidAddressingHeader
 - Arc, 22
- WSAFaultUnknown
 - Arc, 22
- WSAHeader
 - Arc::WSAHeader, 271
- WSRF
 - Arc::WSRF, 274
- WSRFBBaseFault
 - Arc::WSRFBBaseFault, 276

WSRP
 Arc::WSRP, [278](#)
WSRPFault
 Arc::WSRPFault, [280](#)
WSRPResourcePropertyChangeFailure
 Arc::WSRPResourcePropertyChangeFailure,
 [281](#)
WSSType
 Arc, [21](#)

X509Token
 Arc::X509Token, [282](#)
XACML
 Arc::SecAttr, [234](#)
XMLNode
 Arc::XMLNode, [286](#)
XMLNodeContainer
 Arc::XMLNodeContainer, [293](#)
XMLSecNode
 Arc::XMLSecNode, [295](#)
XPathLookup
 Arc::XMLNode, [291](#)