

Userspace verbs access

The `ib_uverbs` module, built by enabling `CONFIG_INFINIBAND_USER_VERBS`, enables direct userspace access to IB hardware via "verbs," as described in chapter 11 of the InfiniBand Architecture Specification.

To use the verbs, the `libibverbs` library, available from <https://github.com/linux-rdma/rdma-core>, is required. `libibverbs` contains a device-independent API for using the `ib_uverbs` interface. `libibverbs` also requires appropriate device-dependent kernel and userspace driver for your InfiniBand hardware. For example, to use a Mellanox HCA, you will need the `ib_mthca` kernel module and the `libmthca` userspace driver be installed.

User-kernel communication

Userspace communicates with the kernel for slow path, resource management operations via the `/dev/infiniband/uverbsN` character devices. Fast path operations are typically performed by writing directly to hardware registers `mmap()`ed into userspace, with no system call or context switch into the kernel.

Commands are sent to the kernel via `write()`s on these device files. The ABI is defined in `drivers/infiniband/include/ib_user_verbs.h`. The structs for commands that require a response from the kernel contain a 64-bit field used to pass a pointer to an output buffer. Status is returned to userspace as the return value of the `write()` system call.

Resource management

Since creation and destruction of all IB resources is done by commands passed through a file descriptor, the kernel can keep track of which resources are attached to a given userspace context. The `ib_uverbs` module maintains `idr` tables that are used to translate between kernel pointers and opaque userspace handles, so that kernel pointers are never exposed to userspace and userspace cannot trick the kernel into following a bogus pointer.

This also allows the kernel to clean up when a process exits and prevent one process from touching another process's resources.

Memory pinning

Direct userspace I/O requires that memory regions that are potential I/O targets be kept resident at the same physical address. The `ib_uverbs` module manages pinning and unpinning memory regions via `get_user_pages()` and `put_page()` calls. It also accounts for the amount of memory pinned in the process's `pinned_vm`, and checks that unprivileged processes do not exceed their `RLIMIT_MEMLOCK` limit.

Pages that are pinned multiple times are counted each time they are pinned, so the value of `pinned_vm` may be an overestimate of the number of pages pinned by a process.

/dev files

To create the appropriate character device files automatically with `udev`, a rule like:

```
KERNEL=="uverbs*", NAME="infiniband/%k"
```

can be used. This will create device nodes named:

```
/dev/infiniband/uverbs0
```

and so on. Since the InfiniBand userspace verbs should be safe for use by non-privileged processes, it may be useful to add an appropriate `MODE` or `GROUP` to the `udev` rule.