

StackProf

Logiciel de mesures sur profils empilés

version 1.02 (11 juin 2021)

ASCII export file format

English description

- Indentation is made using space characters; two space characters for one indentation.
- For better readability, lines about key-value pair of object with close description are described only one time in tables below.

Project input file and parameters

Line	Value description and details	Value example
GeneratedByAppRelease;<value> bIncludeProfilesCurvesData;<value> bUseGeoRef;<value> bWarningFlagByUser_setLinearRegressionData_asEmpty;<value> bWarningFlagByUser_setProfilesCurvesData_asEmpty;<value> boxContent;<value> contentType;resultExport exportDate;<value> exportDateFormat;yyyy.MM.dd hh:mm:ss	string string: true false. File content state about profile curves data. string: true false. Indicates if the project uses georeferencing. string: true false. Content state of linear regression data for flagged profiles. string: true false. Content state of profiles curve data for flagged profiles. string: allBoxes onlyOneBox. Indicates that the file contains data for all boxes or only one.	1.02 false true true false allBoxes 2020.12.31 12:54:53
imagesSet_geoRefInfos coordRefSys_coordTrans EPSG_code;EPSG;<value> imageGeoRef pathAndFilename absolutePath;<value> filename;<value> worldFileContent 0_A_xScale;<value> 1_D_rotationTerms_1;<value> 2_B_rotationTerms_2;<value> 3_E_yScale;<value> 4_C_xTranslationTerm;<value> 5_F_yTranslationTerm;<value>	Georeferencing data used by the project Integer value of the EPSG Code; or "notSet" string for project not using georeferencing Not used by project: oath and filename of the background image, set at project creation. string of the absolute path to the file with '/' character separating directories string of the filename World file data used in project like described here: https://en.wikipedia.org/wiki/World_file decimal value of x scale decimal value of rotationTerms_1 decimal value of rotationTerms_2 decimal value of y scale decimal value of x translationTerm decimal value of y translationTerm	32633 /home/user2/reftest Px1_Num5_LeChantier.tif 0.5 0 0 -0.5 350697.75 4754094.75
versionFormat;<value>	string	0.8
computationMainMode;1	Constant value set at 1 (one)	
computationParameters baseComputationMethod;<value> correlationScoreMapParameters PX1_PX2 bUse;<value> option_thresholdRejection bUse;<value> rejectValueIfBelow;<value> option_weighting bUse; <value> weightExponent;<value> ZOther bUse;<value> option_thresholdRejection bUse;<value> rejectValueIfBelow;<value> option_weighting bUse;<value> weightExponent;<value>	<i>Stacked profiles computation parameters</i> string : mean median <i>Parameters for Px1 and Px2 correlation score map usage</i> string : true false. Indicates if the file is used as weighting. string : true false decimal value string : true false integer value. Range from 2 to 6 <i>Parameters for DeltaZ correlation score map usage.</i> " " " " " "	median true true 170 true 2 true false 180 false 6

Line	Value description and details	Value example
pixelExtractionMethod; <value>	string : nearestPixel biLinearInterpolation2x2 (2x2 means: four surrounding pixels)	
profilOrientation; <value>	string : progressDirectionAlongTraceIsFromFirstToLastPoint progressDirectionAlongTraceIsFromLastToFirstPoint	

Line	Value description and details	Value example
inputFiles	<i>Project input files</i>	
inputCorrelationScoreMaps	<i>Correlation score map files</i>	
PX1_PX2		
attributes	<i>attributes of the correlation score map file for Px1 and Px2</i>	
basetype;<value>	integer value describing the value type contained in the file (see Basetype table)	2
fileSize;<value>	integer value of the file size in byte	812652858
height;<value>	integer value of the image height in pixel	31000
nchannels;<value>	integer value of the image channels amount	1
width;<value>	integer value of the image width in pixel	24673
pathAndFilename		
absolutePath;<value>	string of the absolute path to the file with '/' character separating directories	/home/user2/reftest
filename;<value>	string of the filename	Correl_LeChantier_Num_5.tif
ZOther		
attributes	<i>attributes of the correlation score map file for DeltaZ</i>	
basetype;<value>	''	2
fileSize;<value>	''	812652858
height;<value>	''	31000
nchannels;<value>	''	1
width;<value>	''	24673
pathAndFilename		
absolutePath;<value>	''	/home/user2/reftest
filename;<value>	''	DeltaZ_correlScore.tif
inputDisplacementMaps	<i>Displacement map files</i>	
PX1		
attributes	<i>attributes of the input displacement map for Px1</i>	
basetype;<value>	''	5
fileSize;<value>	''	1567121002
height;<value>	''	31000
nchannels;<value>	''	1
width;<value>	''	24673
pathAndFilename		
absolutePath;<value>	''	/home/user2/reftest
filename;<value>	''	Px1_Num5_LeChantier.tif
PX2		
attributes	<i>attributes of the input displacement map for Px1</i>	
basetype;<value>	''	5
fileSize;<value>	''	1567121002
height;<value>	''	31000
nchannels;<value>	''	1
width;<value>	''	24673
pathAndFilename		
absolutePath;<value>	''	/home/user2/reftest
filename;<value>	''	Px2_Num5_LeChantier.tif
ZOther		
attributes	<i>attributes of the input displacement map for DeltaZ</i>	
basetype;<value>	''	5
fileSize;<value>	''	1567121002
height;<value>	''	31000
nchannels;<value>	''	1
width;<value>	''	24673
pathAndFilename		
absolutePath;<value>	''	/home/user2/reftest
filename;<value>	''	DetalZ.tif

Line	Value description and details	Value example
pixelValueResolution	Pixel factors values for each input component	
PX1	values for Px1	
micmacStep;<value>	decimal value	0.1
spatialResolution;<value>	decimal value	1
PX2	values for Px2	
micmacStep;<value>	' '	0.1
spatialResolution;<value>	' '	1
ZOther	values for DeltaZ	
micmacStep;<value>	' '	0.1
spatialResolution;<value>	' '	1
routeName;<value>	string. Name of the trace used in the project	trace 2
Boxes are ordered along the trace, taking into account the selected profil orientation. Azimuth degree and unit vector direction values also.	One comment line about the lines order of the following table.	

Measures values

Measures values are joined by component. One table per component (Perpendicular, Parallelele, deltaZ)

- If the project only uses Px1 and Px2, deltaZ component table will not appear.

- If the project only uses deltaZ, Perpendicular and Parallelele components tables will not appear.

In component table, measures values for a box fit in one line.

The box order takes into account the selected profile orientation.

Line	Value description and details
component;<value>	string : Perp
<columns titles. see table below>	Columns titles (<boxId;linearRegression_isComputed;yOffsetAtX0;...>)
boxId;<i>;<...>	measures values for box i
boxId;<j>;<...>	measures values for box j
boxId;<k>;<...>	measures values for box k
	empty line, separating the different component tables
component;<value>	string : Parall
<columns titles. see table below>	Columns titles (<boxId;linearRegression_isComputed;yOffsetAtX0;...>)
boxId;<i>;<...>	measures values for box i
boxId;<j>;<...>	measures values for box j
boxId;<k>;<...>	measures values for box k
	empty line, separating the different component tables
component;<value>	string : deltaZ
<columns titles. see table below>	Columns titles (<boxId;linearRegression_isComputed;yOffsetAtX0;...>)
boxId;<i>;<...>	measures values for box i
boxId;<j>;<...>	measures values for box j
boxId;<k>;<...>	measures values for box k
	empty line

Example with three boxes (with boxIds i, j and k)

Table describing the box values of the table, by column, from left to right

Line	Value description and details
boxId	Box Id. First boxId along the trace is 1 (one)
bNoWarningFlagByUser	string : true false. Indicates if the user has not flagged the profile ("true" means that the flag is off)
linearRegression_isComputed	string : true false N/A. Indicates if the linear regression model on the two sides was computed with valid result for yOffsetAtX0 and sigmabSum Flagged profile and bWarningFlagByUser setLinearRegressionData asEmpty at true leads to value at "N/A"
yOffsetAtX0	decimal. The offset measure at the profile center position (see X0 below) Flagged profile and with bWarningFlagByUser setLinearRegressionData asEmpty at true leads to an empty value.
sigmabSum	decimal. Sum of leftSide_stdErrorOfIntercept and rightSide_stdErrorOfIntercept Flagged profile and bWarningFlagByUser setLinearRegressionData asEmpty at true leads to an empty value.
leftSide_isComputed	About the computed linear regression on the left side of the profile center. string : true false. Indicates if the linear regression was computed Flagged profile and bWarningFlagByUser setLinearRegressionData asEmpty at true leads to an empty value.
leftSide_a_slope	About the computed linear regression on the left side of the profile center. decimal. Slope of the line equation of the computed linear regression model Flagged profile and bWarningFlagByUser setLinearRegressionData asEmpty at true leads to an empty value.
leftSide_b_intercept	About the computed linear regression on the left side of the profile center. decimal. Intercept of the line equation of the computed linear regression model Flagged profile and bWarningFlagByUser setLinearRegressionData asEmpty at true leads to an empty value.
leftSide_stdErrorOfSlope	About the computed linear regression on the left side of the profile center. decimal. Estimated standard deviation of the error in estimating the slope. See used formula below. Flagged profile and bWarningFlagByUser setLinearRegressionData asEmpty at true leads to an empty value.
leftSide_stdErrorOfIntercept	About the computed linear regression on the left side of the profile center. Decimal. Estimated standard deviation of the error in estimating the intercept. See used formula below. Flagged profile and bWarningFlagByUser setLinearRegressionData asEmpty at true leads to an empty value.
leftSide_stdErrorOfTheRegression	About the computed linear regression on the left side of the profile center. Decimal. Standard error of the regression. See used formula below. Flagged profile and bWarningFlagByUser setLinearRegressionData asEmpty at true leads to an empty value.
leftSide_sumsq	About the computed linear regression on the left side of the profile center. decimal. Sum of squares of the residuals from the best-fit line Flagged profile and bWarningFlagByUser setLinearRegressionData asEmpty at true leads to an empty value.
rightSide_isComputed	About the computed linear regression on the right side of the profile center. '' '' ''
rightSide_a_slope	'' '' '' ''
rightSide_b_intercept	'' '' '' ''


Line	Value description and details
rightSide_stdErrorOfSlope	'' '' '' ''
rightSide_stdErrorOfIntercept	'' '' '' ''
rightSide_stdErrorOfTheRegression	'' '' '' ''
rightSide_sumsq	'' '' '' ''

Line	Value description and details
oddPixelLength	Box length in pixel
oddPixelWidth	Box width in pixel
centerPoint_lat	Decimal or "N/A" string. WGS84 Latitude decimal degree of the box center point If the project does not used georeferencing, the value is "N/A"
centerPoint_lon	Decimal or "N/A" string. WGS84 Longitude decimal degree of the box center point If the project does not used georeferencing, the value is "N/A"
distanceFromFirstPointOfTrace_in_meter distanceFromFirstPointOfTrace_in_pixel	decimal. Distance, along the trace, between the box center and the first point of the trace. If the project uses georeferencing, the field is distanceFromFirstPointOfTrace_in_meter (unit is meter) If the project does not use georeferencing, the field is distanceFromFirstPointOfTrace in pixel (unit is image pixel)
azimuthDegree	Decimal. see below
centerPoint_pixel_x	decimal. Image pixel x location of the box center point
centerPoint_pixel_y	decimal. Image pixel y location of the box center point
unitVectorDirection_x	decimal. x component of the unit vector direction of the box (value increases going to right)
unitVectorDirection_y	decimal. y component of the unit vector direction of the box (value increases going to down)
leftSide_xMin	decimal. x min position of the range used to compute the regression linear model at left side of the profile center
leftSide_xMax	decimal. x max position of the range used to compute the regression linear model at left side of the profile center
rightSide_xMin	decimal. x min position of the range used to compute the regression linear model at right side of the profile center
rightSide_xMax	decimal. x max position of the range used to compute the regression linear model at right side of the profile center
X0	decimal. x location of the profile center to compute yOffsetAtX0


Azimuth degree

Azimuth degree indicates the box orientation from a vertical axis. This value is an angle in decimal degree.

The angle is measured clockwise from a vertical axis (value zero is North and goes up). This value depends of the profile orientation.



Ranges and X0 locations



Example of ranges and X0 locations

Formulas of the linear regression standard deviations values

Estimated standard deviation of the error in estimating the slope

$$\text{stdErrorOfTheSlope} = \frac{\text{stdErrorOfTheRegression}}{\sqrt{x \text{ values count}}} * \frac{1}{\text{stdDev}[X]}$$

Estimated standard deviation of the error in estimating the intercept

$$\text{stdErrorOfIntercept} = \frac{\text{stdErrorOfTheRegression}}{\sqrt{x \text{ values count}}} * \sqrt{1 + \frac{\text{Mean}[X] * \text{Mean}[X]}{\text{Variance}[X]}}$$

Standard error of the regression

$$\text{stdErrorOfTheRegression} = \sqrt{(1/(x \text{ values count} - 2) * \text{sumsq})}$$

Profil curves data

- Export file with bIncludeProfilesCurvesData at true contains profiles curves data.
- Flagged profile with bWarningFlagByUser_setProfilesCurvesData_asEmpty at true leads to empty value for each data point.

Table containing the points of the different profiles components by box

Line	Value description and details
profilCurves	Section title
	empty line
boxId;<value>	Integer
<columns titles line #1. See table below>	Columns titles (<methodMajorMinor by component;N/A;...>)
<columns titles line #2. See table below>	Columns titles (<title by component;x;...>)
<point values data. See table below >	

Columns titles line #1 and #2

methodMajorMinor_by_component	N/A	string. y meaning of major curve: mean weightedMean median weightedMedian	String. minor : meaning of the absolute deviation around y : absDevAroundMean absDevAroundWeightedMean absDevAroundMedian absDevAroundWeightedMedian	''	''	''	''
title by component	x	Perp	Perp	Parall	Parall	deltaZ	deltaZ

Values are ordered by component following this order: Perpendicular, Parallele, deltaZ.

- If the project only uses Px1 and Px2, deltaZ component columns will not appear.
- If the project only uses deltaZ, Perpendicular and Parallele components columns will not appear.

baseComputationMethod	correlationScoreMapParameters used as weight	y meaning of major curve	meaning of the absolute deviation around y
mean	false	mean	absDevAroundMean
mean	true	weightedMean	absDevAroundWeightedMean
median	false	median	absDevAroundMedian
median	true	weightedMedian	absDevAroundWeightedMedian

Points data values

<empty column>	$-\left((\text{box pixel length} - 1)/2\right)$
<empty column>	$-\left((\text{box pixel length} - 1)/2\right) + 1$
<empty column>	$-\left((\text{box pixel length} - 1)/2\right) + 2$
<empty column>
<empty column>
<empty column>	-1
<empty column>	0
<empty column>	+1
<empty column>
<empty column>
<empty column>	$\left((\text{box pixel length} - 1)/2\right) - 2$
<empty column>	$\left((\text{box pixel length} - 1)/2\right) - 1$
<empty column>	$\left((\text{box pixel length} - 1)/2\right)$

Basetype description table

Data type integer values come from OpenImageIO (include/OpenImageIO/typedesc.h)

Value in export file	Input file data type
2	unsigned byte
4	16 bits unsigned integer
5	16 bits signed integer
11	32 bits float (decimal)

[end of document]