

1. make qemu

```
qemu-system-riscv64 \  
-machine virt \  
-nographic \  
-bios default \  
-device loader,file=bin/ucore.bin,addr=0x80200000
```

- `qemu-system-riscv64`: The command to start the QEMU emulator for a RISC-V 64-bit system.
- `-machine virt`: Set the machine type to `virt`, which is `RISC-V virtIO board`
- `-nographic`: Disable the graphical output of the emulator and redirects the console output to the terminal.
- `-bios default`: Use the default BIOS of OpenSBI.
- `-device loader,file=bin/ucore.bin,addr=0x80200000`: This option add a device to the virtual machine that loads a binary file into memory at the specified address. In this case, the binary file `bin/ucore.bin` will be loaded into memory at address `0x80200000`.

2. kernal.ld

- `SECTIONS`: It describe the memory layout of the output file, followed by a series of symbol assignments and output section descriptions enclosed in curly braces.
- `. = BASE_ADDRESS`: Load the kernel at this address: "." means the current address.
- `.text : { *(...) }`: Obtain the .text section of all input files and place it in a contiguous address space. The first address is determined by the **BASE_ADDRESS** symbol in the previous command.
- `PROVIDE(etext = .)`: Define the **etext** symbol to the current address.
- `.rodata : { ... }`: Define the read only data. Obtain the .rodata section of all input files and place it in a contiguous address space.
- `. = ALIGN(0x1000)`: Adjust the address for the data segment to the next page.

3. memset(edata, 0, end - edata)

This command clears the memory space of **.bss** segment in kernal.ld. **bss** Stands for Block Started by Symbol, whose space stores the global variables and static variables. `edata` is the beginning address of .bss segment. `end` is the end address of .bss segment.

4. cputs()

- `cputs()` receives a pointer of a string.
- `cputs()` calls `cputch()` recurrently and sends a char to `cputch()`.
- `cputs()` calls `cons_putc()`.
- `cons_putc()` calls `sbi_console_putchar((unsigned char)c)`.

- `sbi_console_putchar()` calls `sbi_call(SBI_CONSOLE_PUTCHAR, ch, 0, 0)` and send the command type `SBI_CONSOLE_PUTCHAR` to `sbi_call`.
- `sbi_call` use **inline assembly** to encapsulate and execute `ecall` operations. In this case, it prints a char in terminal.

5. shutdown()

```

    cputs("Power by 12110817");
    cputs("The system will close.\n");
    shutdown();

    // -----end-----

    while (1)
    {
        ;
    }

```

```

2  void shutdown(void) {
3      sbi_call(SBI_SHUTDOWN, 0, 0, 0);
4  }
5

```

```

MIDELEG : 0x0000000000000222
MEDELEG : 0x0000000000000b109
PMP0     : 0x0000000080000000-0x000000008001ffff (A)
PMP1     : 0x0000000000000000-0xffffffffffffffff (A,R,W,X)
os is loading ...

Power by 12110817
The system will close.

○ root@Bill:~/codes/CS334-OS/lab03#

```

