

File created: 11-Jan-89 14:52:06 {NB:PARC:XEROX}<NFS>SOURCES>RPCDECLS.;2

changes to: (IL:VARS IL:RPCDECLSCOMS)  
(IL:VARIABLES \*RPC-ACCEPT-PROGRAM-UNAVAILABLE\* \*PORTMAPPER-SOCKET\*)

previous date: 19-Oct-88 18:29:59 {NB:PARC:XEROX}<NFS>SOURCES>RPCDECLS.;1

Read Table: XCL

Package: RPC2

Format: XCCS

; Copyright (c) 1988, 1989 by Xerox Corporation. All rights reserved.

```
(IL:RPAQQ IL:RPCDECLSCOMS
  ;; Macros useful for low-level RPC hacking.
  (IL:PROPS (IL:RPCDECLS IL:MAKEFILE-ENVIRONMENT IL:FILETYPE))
  (IL:FUNCTIONS GETBASE-INTEGER GETBASE-UNSIGNED INTEGER-FROM-BYTES UNSIGNED-FROM-BYTES
    UNSIGNED-FROM-SIGNED PUTBASE-INTEGER FOLDLO UNFOLD VECTOR-BASE VECTOR-OFFSET PADDING-BYTES)
    ; Call methods
  (IL:FUNCTIONS RPC-METHOD RPC-CALL-METHOD REINITIALIZE-RPCSTREAM GETBYTE GETRAWBYTES SKIPBYTES GETCELL
    GETOFFSET PUTBYTE PUTRAWBYTES ZEROBYTES PUTCELL GETUNSIGNED PUTUNSIGNED)
  (IL:VARIABLES *WORDS-PER-CELL* *BYTES-PER-CELL* *BYTES-PER-WORD*)
    ; Well-known RPC constants
  (IL:VARIABLES *RPC-MSG-CALL* *RPC-MSG-REPLY* *RPC-REPLY-ACCEPTED* *RPC-REPLY-REJECTED*
    *RPC-ACCEPT-SUCCESS* *RPC-ACCEPT-PROGRAM-UNAVAILABLE* *RPC-VERSION*
    *INTERNAL-TIME-UNITS-PER-MSEC* *PORTMAPPER-SOCKET*)
    ; For those that need IP/TCP stuff
  (IL:FUNCTIONS LOAD-TCP-EXPORTS)))
```

;; Macros useful for low-level RPC hacking.

```
(IL:PUTPROPS IL:RPCDECLS IL:MAKEFILE-ENVIRONMENT (:READTABLE "XCL" :PACKAGE "RPC2"))
```

```
(IL:PUTPROPS IL:RPCDECLS IL:FILETYPE :COMPILE-FILE)
```

```
(DEFMACRO GETBASE-INTEGER (BASE BYTEOFFSET)
  "Interpret 32 bits at BYTEOFFSET from BASE as a signed integer."
  `(LET ((BASE (IL:\\ADDBASE ,BASE (FOLDLO ,BYTEOFFSET *BYTES-PER-WORD*))))
    (IL:\\MAKENUMBER (IL:\\GETBASE BASE 0)
      (IL:\\GETBASE BASE 1))))
```

```
(DEFMACRO GETBASE-UNSIGNED (BASE BYTEOFFSET)
  "Interpret 32 bits at BYTEOFFSET from BASE as an unsigned integer."
  ;; This differs from GETBASE-INTEGER only when the high bit is on, in which case we are forced to make (choke) a bignum, which we try to do
  ;; efficiently.
  `(LET* ((BASE (IL:\\ADDBASE ,BASE (FOLDLO ,BYTEOFFSET *BYTES-PER-WORD*)))
    (HI (IL:\\GETBASE BASE 0)))
    (IF (> HI 32767)
      (BIGNUM-MAKE-NUMBER HI (IL:\\GETBASE BASE 1))
      (IL:\\MAKENUMBER HI (IL:\\GETBASE BASE 1)))))
```

```
(DEFMACRO INTEGER-FROM-BYTES (BYTE0 BYTE1 BYTE2 BYTE3)
  "Interprets these 32 bits as a signed integer"
  `(IL:\\MAKENUMBER (+ (UNFOLD ,BYTE0 256)
    ,BYTE1)
    (+ (UNFOLD ,BYTE2 256)
      ,BYTE3)))
```

```
(DEFMACRO UNSIGNED-FROM-BYTES (BYTE0 BYTE1 BYTE2 BYTE3)
  "Interprets these 32 bits as an unsigned integer"
  `(LET* ((HI (+ (UNFOLD ,BYTE0 256)
    ,BYTE1))
    (LO (+ (UNFOLD ,BYTE2 256)
      ,BYTE3)))
    (IF (> HI 32767)
      (BIGNUM-MAKE-NUMBER HI LO)
      (IL:\\MAKENUMBER HI LO))))
```

```
(DEFMACRO UNSIGNED-FROM-SIGNED (VALUE)
  "Interpret the 32 bits of VALUE's representation as an unsigned integer."
  `(LET ((VALUE ,VALUE))
    (IF (> 0 VALUE)
      (+ VALUE TWOTO32ND)
      VALUE)))
```

```
(DEFMACRO PUTBASE-INTEGER (BASE BYTEOFFSET VALUE)
  "Store integer VALUE at BYTEOFFSET bytes beyond BASE."
```

;; Note this handles both "signed" and "unsigned" numbers. We do type analysis here to avoid gratuitous consing when handling anything large.

```
'(LET ((BASE (IL:\\ADDBASE ,BASE (FOLDLO ,BYTEOFFSET *BYTES-PER-WORD*)))
      (VALUE ,VALUE))
  (COND
    ((IL:SMALLP VALUE) ; An immediate value
     (IL:\\PUTBASE BASE 0 (IF (< VALUE 0)
                             65535
                             0))
     (IL:\\PUTBASE BASE 1 (IL:\\LOLOC VALUE)))
    ((EQ (IL:NTYPX VALUE)
         IL:\\FIXP) ; A 32-bit integer box--just blt it
     (IL:\\BLT BASE VALUE 2))
    (T (PUTBASE-BIGNUM BASE VALUE))))
```

```
(DEFMACRO FOLDLO (FORM DIVISOR)
  (LET ((DIV (IF (CONSTANTP DIVISOR)
                 (EVAL DIVISOR)
                 DIVISOR)))
    (OR (AND DIV (IL:POWEROFTWOP DIV))
        (IL:\\ILLEGAL.ARG DIV))
    (LIST 'IL:LRSH FORM (IL:SUB1 (IL:INTEGERLENGTH DIV)))))
```

```
(DEFMACRO UNFOLD (FORM DIVISOR)
  (LET ((DIV (IF (CONSTANTP DIVISOR)
                 (EVAL DIVISOR)
                 DIVISOR)))
    (OR (AND DIV (IL:POWEROFTWOP DIV))
        (IL:\\ILLEGAL.ARG DIV))
    (LIST 'IL:LLSH FORM (IL:SUB1 (IL:INTEGERLENGTH DIV)))))
```

```
(DEFMACRO VECTOR-BASE (VECTOR)
  "Get raw string/vector base address. Use VECTOR-OFFSET, too, unless you know this is a brand new one without displacement."
  '(IL:|fetch| (IL:ONED-ARRAY IL:BASE) IL:|of| ,VECTOR))
```

```
(DEFMACRO VECTOR-OFFSET (VECTOR)
  "Get raw vector offset. Interpretation depends on element type, of course."
  '(IL:|fetch| (IL:ONED-ARRAY IL:OFFSET) IL:|of| ,VECTOR))
```

```
(DEFMACRO PADDING-BYTES (BYTECOUNT)
  "Returns number of bytes needed to pad BYTECOUNT bytes out to a multiple of 32 bits."
  '(LET ((N ,BYTECOUNT))
      (- (LOGAND (+ N 3)
                  -4)
         N)))
```

;; Call methods

```
(DEFMACRO RPC-METHOD (OP STREAM)
  "Returns the function that implements OP (unevaluated) on STREAM."
  '(, (INTERN (CONCATENATE 'STRING "RPC-METHODS-" (STRING OP))
            "RPC2")
    (RPC-STREAM-METHODS ,STREAM)))
```

```
(DEFMACRO RPC-CALL-METHOD (OP &REST ARGS)
  "Invoke the OP method on ARGS, the first of which must be the RPC-STREAM that defines the method"
  '(FUNCALL (RPC-METHOD ,OP , (FIRST ARGS))
    ,@ARGS))
```

```
(DEFMACRO REINITIALIZE-RPCSTREAM (STREAM DESTADDR DESTSOCKET)
  "Reuse an existing RPC Stream to send a new packet. Resets length counters, reinitializes packets, etc."
  '(RPC-CALL-METHOD INITIALIZE ,STREAM ,DESTADDR ,DESTSOCKET))
```

```
(DEFMACRO GETBYTE (XDRSTREAM)
  "Applies the GETBYTE method of an RPC Stream to read in and return the next byte of the stream."
  '(RPC-CALL-METHOD GETBYTE ,XDRSTREAM))
```

```
(DEFMACRO GETRAWBYTES (XDRSTREAM BASE OFFSET NBYTES)
  "Applies the GETRAWBYTES method of an RPC stream to read NBYTES bytes from the stream to BASE,OFFSET."
  '(RPC-CALL-METHOD GETRAWBYTES ,XDRSTREAM ,BASE ,OFFSET ,NBYTES))
```

```
(DEFMACRO SKIPBYTES (RPCSTREAM NBYTES)
  "Applies the SKIPBYTES method of an RPC stream to skip NBYTES bytes of input."
  '(RPC-CALL-METHOD SKIPBYTES ,RPCSTREAM ,NBYTES))
```

```

(DEFMACRO GETCELL (XDRSTREAM)
  "Applies the GETCELL method of an RPC Stream to read in and return the next cell of the stream. A cell is a
  32-bit two's complement integer."
  `(RPC-CALL-METHOD GETCELL ,XDRSTREAM))

(DEFMACRO GETOFFSET (XDRSTREAM)
  "Returns dotted pair (base . byteoffset), pointing at current position in incoming packet"
  `(RPC-CALL-METHOD GETOFFSET ,XDRSTREAM))

(DEFMACRO PUTBYTE (RPCSTREAM VALUE)
  "Applies the PUTBYTE method of an RPC Stream to write the byte VALUE on that stream. VALUE is an integer
  between 0 and 255 inclusive."
  `(RPC-CALL-METHOD PUTBYTE ,RPCSTREAM ,VALUE))

(DEFMACRO PUTRAWBYTES (RPCSTREAM BASE OFFSET NBYTES)
  "Applies the PUTRAWBYTES method of an RPC stream to write the NBYTES bytes from BASE,OFFSET to the stream."
  `(RPC-CALL-METHOD PUTRAWBYTES ,RPCSTREAM ,BASE ,OFFSET ,NBYTES))

(DEFMACRO ZEROBYTES (RPCSTREAM NBYTES)
  "Applies the ZEROBYTES method of an RPC stream to write NBYTES bytes of zero to the output."
  `(RPC-CALL-METHOD ZEROBYTES ,RPCSTREAM ,NBYTES))

(DEFMACRO PUTCELL (RPCSTREAM VALUE)
  "Applies the PUTCELL method of an RPC Stream to write the cell VALUE on that stream. A cell is a 32-bit two's
  complement integer."
  `(RPC-CALL-METHOD PUTCELL ,RPCSTREAM ,VALUE))

(DEFMACRO GETUNSIGNED (RPCSTREAM)
  "Fetch an unsigned 32-bit integer from RPCSTREAM. Uses the GETUNSIGNED method."
  `(RPC-CALL-METHOD GETUNSIGNED ,RPCSTREAM))

(DEFMACRO PUTUNSIGNED (RPCSTREAM VALUE)
  "Write a 32-bit unsigned integer to RPCSTREAM. Uses PUTCELL method."
  ;; Note that no coercion is need here, because the bits of the bignum are the same as the bits of the signed integer.
  `(PUTCELL ,RPCSTREAM ,VALUE))

(DEFCONSTANT *WORDS-PER-CELL* 2
  "The number of words (16 bits) per cell.")

(DEFCONSTANT *BYTES-PER-CELL* 4
  "Number of 8-bit bytes per RPC cell.")

(DEFCONSTANT *BYTES-PER-WORD* 2)

;; Well-known RPC constants

(DEFCONSTANT *RPC-MSG-CALL* 0
  "Constant 0 in packet means RPC call, 1 means reply")

(DEFCONSTANT *RPC-MSG-REPLY* 1)

(DEFCONSTANT *RPC-REPLY-ACCEPTED* 0
  "Switch in reply body")

(DEFCONSTANT *RPC-REPLY-REJECTED* 1
  "Switch in reply body")

(DEFCONSTANT *RPC-ACCEPT-SUCCESS* 0
  "Switch in accepted reply.")

(DEFCONSTANT *RPC-ACCEPT-PROGRAM-UNAVAILABLE* 1)

(DEFCONSTANT *RPC-VERSION* 2
  "This code will only work for SUN RPC Version 2")

(DEFCONSTANT *INTERNAL-TIME-UNITS-PER-MSEC* (/ INTERNAL-TIME-UNITS-PER-SECOND 1000)
  "This gets used in EXCHANGE-UDP-PACKETS.")

```

```
(DEFCONSTANT *PORTMAPPER-SOCKET* 111
  "Well-known socket for portmapper")
```

:: For those that need IP/TCP stuff

```
(DEFUN LOAD-TCP-EXPORTS ()
  (PROG1 (IL:FILESLOAD (IL:SOURCE)
    IL:TCPEXPORTS)
    (OR (GET 'IL:TCPEXPORTS 'IL:FILEDATES)
      (SETF (GET 'IL:TCPEXPORTS 'IL:FILEDATES)
        T))))
  ; Now stop us from loading it again (This really ought to be on
  ; TCPEXPORTS)

(IL:PUTPROPS IL:RPCDECLS IL:COPYRIGHT ("Xerox Corporation" 1988 1989))
```

FUNCTION INDEX

LOAD-TCP-EXPORTS .....4

MACRO INDEX

FOLDLO .....2	GETUNSIGNED .....3	PUTUNSIGNED .....3	UNSIGNED-FROM-SIGNED ....1
GETBASE-INTEGER .....1	INTEGER-FROM-BYTES .....1	REINITIALIZE-RPCSTREAM ..2	VECTOR-BASE .....2
GETBASE-UNSIGNED .....1	PADDING-BYTES .....2	RPC-CALL-METHOD .....2	VECTOR-OFFSET .....2
GETBYTE .....2	PUTBASE-INTEGER .....1	RPC-METHOD .....2	ZEROBYTES .....3
GETCELL .....3	PUTBYTE .....3	SKIPBYTES .....2	
GETOFFSET .....3	PUTCELL .....3	UNFOLD .....2	
GETRAWBYTES .....2	PUTRAWBYTES .....3	UNSIGNED-FROM-BYTES .....1	

CONSTANT INDEX

*BYTES-PER-CELL* .....3	*RPC-ACCEPT-PROGRAM-UNAVAILABLE* .3	*RPC-REPLY-ACCEPTED* .....3
*BYTES-PER-WORD* .....3	*RPC-ACCEPT-SUCCESS* .....3	*RPC-REPLY-REJECTED* .....3
*INTERNAL-TIME-UNITS-PER-MSEC* ...3	*RPC-MSG-CALL* .....3	*RPC-VERSION* .....3
*PORTMAPPER-SOCKET* .....4	*RPC-MSG-REPLY* .....3	*WORDS-PER-CELL* .....3

PROPERTY INDEX

IL:RPCDECLS .....1