

## Grid to Obs Use Case

### Purpose:

Performs grid-to-obs verification using the MET tools. First, pb2nc is applied to prepBUFR files (observation files) to stratify and convert those files into NetCDF files that MET can recognize. Then, using the pb2nc output as input, along with gridded forecast files (model data) to the MET point\_stat tool to calculate statistics at observation points.

### Overview:

The configuration files provided in the METplus/parm/use\_cases/grid\_to\_obs directory allow you to perform a grid-to-obs verification using MET tools for two specific examples: upper air and conus surface. The configurations can be run after the user replaces */path/to* with the full path to the directories and files in her/his running environment. The user can customize/experiment by modifying the dates, message types, variables, etc. which are highlighted as **red text** (illustrated below in the configuration file description).

The grid\_to\_obs.conf file is the 'default' configuration file for performing a grid\_to\_obs verification on for conus surface data. For an example of performing a grid-to-obs verification for upper air data, refer to the upper\_air.conf configuration file in the METplus/parm/use\_cases/grid\_to\_obs/examples directory. The conus\_sfc.conf file in the METplus/parm/use\_cases/grid\_to\_obs/examples directory is identical to the grid\_to\_obs.conf file.

To run the conus surface grid\_to\_obs verification, run the following:

```
master_metplus.py -c  
<your/path/to/METplus/code>/METplus/parm/use_cases/grid_to_obs/grid_to_obs.conf
```

To run the upper air grid\_to\_obs verification, run the following:

```
master_metplus.py -c <your/path/to/METplus/code>/METplus/parm/use_cases/grid_to_obs/examples/  
upper_air.conf
```

You may also override any of these setting by creating your own configuration file, and call this last. Following the example for running the upper air grid\_to\_obs verification, one can simply leave the original settings in the upper\_air.conf file and define custom begin and end times in a custom configuration file\*:

```
master_metplus.py -c <your/path/to/METplus/code>/METplus/parm/use_cases/grid_to_obs/examples/  
upper_air.conf  
<your/full/path/to/your/custom/config>/my_custom_overriding_upper_air.conf
```

*\*Make sure your key-value settings are under the same section header that correspond to the section where you are overriding values:*

```
[config]  
START_HOUR - 0  
END_HOUR   - 18  
BEG_TIME   - 20170605  
END_TIME   = 20170615  
INTERVAL_TIME=12
```

## Configuration file description:

For the directory section, indicated by [\[dir\]](#), replace any '/path/to' text with the full path for that associated value:

### **[dir]**

PROJ\_DIR - where you want your project files to reside

TMP\_DIR - where you want your temporary files to reside

OUTPUT\_BASE - the base directory for all output files

METPLUS\_BASE - the base directory where MET+ is installed

MET\_INSTALL\_DIR - the location of the MET installation

PARM\_BASE - the base directory where all parameter files are located (MET and MET+ param files)

### For pb2nc:

PREPBUFR\_DATA\_DIR – directory where prepBUFR files reside

**PB2NC\_OUTPUT\_DIR** – directory where pb2nc output (in NetCDF) is to be saved.

### For point\_stat:

FCST\_INPUT\_DIR - the directory where your model data resides

OBS\_INPUT\_DIR - the directory where your pb2nc output files (in NetCDF) are located

**POINT\_STAT\_OUTPUT\_DIR** – location for all point\_stat output files to reside, based on the OUTPUT\_BASE value:  
{OUTPUT\_BASE}/path/to

For the configuration section, indicated by [\[config\]](#), set the following values to meet your specifications:

### **[config]**

LOOP\_METHOD – 'processes' is currently supported, 'time' to be implemented later.

### **LOG\_LEVEL** -

DEBUG is the most verbose and is valuable for debugging (provides all error, warning, and info messages in addition to debug messages)

INFO is the next least verbose (provides all error, warning and info messages)

WARN is the next least verbose (provides only error and warning messages)

ERROR is the least verbose (provides only error messages)

OVERWRITE\_NC\_OUTPUT – yes or no; overwrite the pb2nc output if it already exists in the specified output directory

TIME\_METHOD – BY\_VALID or BY\_INIT selects times based on either valid times or initialization times. For this use case, BY\_VALID is used.

**START\_HOUR** - The beginning hour defining your time window of interest

**END\_HOUR** - The ending hour defining hour time window of interest

**BEG\_TIME** – The year, month, day (YYYYMMDD) defining the start of your time window of interest  
**END\_TIME** – The year, month, day (YYYYMMDD) defining the end of your time window of interest.  
**INTERVAL\_TIME** – The interval time in hours/time step, used by the pb2nc wrapper.

**VERTICAL\_LOCATION** – upper\_air for the upper air example, or conus\_sfc for the conus surface example

For pb2nc:

**PB2NC\_CONFIG\_FILE** - the location of your MET pb2nc config file, this is relative to the PARM\_BASE you defined in the directory section of the MET+ grid\_to\_obs.conf or one of the example configuration files (conus\_sfc.conf, upper\_air.conf).

**PB2NC\_GRID** - corresponds to *grid* in the verification masking regions in the MET pb2nc config file.

**PB2NC\_POLY** – corresponds to *poly* in the verification masking regions in the MET pb2nc config file. If you are defining a long list of poly masking files, you may need to define these in the MET pb2nc config file, as there is a limit to the string length of environment variables.

**PB2NC\_STATION\_ID** – corresponds to the prepBufr station id, *station\_id* in the MET pb2nc config file.

**PB2NC\_MESSAGE\_TYPE** – corresponds to the prepBufr message type, *message\_type* in the MET pb2nc config file.

**TIME\_SUMMARY\_FLAG** – set to False to skip performing time summary. There is a bug in met-6.1 that will produce undesirable results if set to True.

For point\_stat:

**POINT\_STAT\_CONFIG\_FILE** – the location of your MET point\_stat config file, this is relative to the PARM\_BASE you defined in the directory section of the MET+ grid\_to\_obs.conf or one of the example configuration files (conus\_sfc.conf, upper\_air.conf).

**FCST\_HR\_START** – the starting hour of the forecast hour of interest.

**FCST\_HR\_END** - the ending hour of the forecast hour of interest.

**FCST\_HR\_INTERVAL** – the step size/interval in hours used to define all the forecast hours of interest.

**MODEL\_NAME** - the name of the model/fcst data (e.g. GFS)

**OBS\_NAME** - the name of the observation data (e.g. NAM, GDAS)

**REGRID\_TO\_GRID** – the verification grid. Corresponds to *to\_grid* in the regrid dictionary of the MET point\_stat config file.

**POINT\_STAT\_GRID** – the verification masking region, corresponds to *grid* in the mask dictionary of the MET point\_stat config file.

**POINT\_STAT\_POLY** – the verification masking region, corresponds to *poly* in the mask dictionary of the MET point\_stat config file.

**POINT\_STAT\_STATION\_ID** – corresponds to *sid* in the mask dictionary used for the verification masking regions.

**POINT\_STAT\_MESSAGE\_TYPE** - corresponds to *message\_type* in the point observation filtering options in the MET point\_stat config file.

The following represent the field names, levels, and options in the fcst dictionary where forecast and observation fields to be verified are located in the MET point\_stat config file. Options can be cat\_thresholds or GRIB\_lvl\_val1 = ###, where ### represents a numerical grib level value.

**FCST\_VAR1\_NAME** – variable name for the first variable

**FCST\_VAR1\_LEVELS** – a list of levels for the first variable

**FCST\_VAR1\_OPTIONS** – optional, options such as cat\_thresh or GRIB\_lvl\_val1, or unit conversion definitions

...

**FCST\_VARn\_NAME** – variable name for the nth variable

**FCST\_VARn\_LEVELS** – variable name for the nth variable

**FCST\_VARn\_OPTIONS** – optional. Options for the nth variable

#### **[filename\_templates]**

**NC\_FILE\_TMPL** – the output NetCDF filename template from the output generated from running pb2nc.

For the configuration section, indicated by **[regex\_pattern]**, set the following values to meet your specifications:

#### **[regex\_pattern]**

**PREPBUFR\_DIR\_REGEX** – the regular expression describing the directory where prepBUFR input files reside.

**PREPBUFR\_FILE\_REGEX** – the regular expression describing the format of the prepBUFR input files.