

The MOSEK C optimizer API manual

Version 7.1 (Revision 14)

support@mosek.com



www.mosek.com

- Published by MOSEK ApS, Denmark.
- Copyright © MOSEK ApS, Denmark. All rights reserved.

Contents

1	Changes and new features in MOSEK	5
1.1	Platform support	5
1.2	General changes	5
1.3	Optimizers	6
1.3.1	Interior point optimizer	6
1.3.2	The simplex optimizers	6
1.3.3	Mixed-integer optimizer	7
1.4	API changes	7
1.5	Optimization toolbox for MATLAB	7
1.6	License system	7
1.7	Other changes	7
1.8	Interfaces	7
1.9	Platform changes	8
1.10	Summary of API changes	8
1.10.1	Parameters	8
1.10.2	Functions	10
2	About this manual	15
3	Getting support and help	17
3.1	MOSEK documentation	17
3.2	Bug reporting	17
3.3	Additional reading	17
4	Testing installation and compiling examples	19
4.1	Setting up MOSEK	19
4.1.1	Windows: Checking the MOSEK installation	19
4.1.2	Linux: Checking the MOSEK installation	20
4.1.3	MacOSX: Checking the MOSEK installation	21
4.2	Compiling and linking	22
4.2.1	Compiling under Microsoft Windows	22
4.2.2	UNIX versions	25
5	Basic API tutorial	29
5.1	The basics	29
5.1.1	The environment and the task	29

5.1.2	Example: Simple working example	30
5.2	Linear optimization	33
5.2.1	Example: Linear optimization	34
5.2.2	Row-wise input	41
5.3	Conic quadratic optimization	45
5.3.1	Example: Conic quadratic optimization	46
5.4	Semidefinite optimization	51
5.4.1	Example: Semidefinite optimization	51
5.5	Quadratic optimization	58
5.5.1	Example: Quadratic objective	59
5.5.2	Example: Quadratic constraints	64
5.6	The solution summary	69
5.7	Integer optimization	70
5.7.1	Example: Mixed integer linear optimization	70
5.7.2	Specifying an initial solution	75
5.7.3	Example: Specifying an integer solution	75
5.8	The solution summary for mixed integer problems	78
5.9	Response handling	78
5.10	Problem modification and reoptimization	81
5.10.1	Example: Production planning	81
5.10.2	Changing the A matrix	84
5.10.3	Appending variables	84
5.10.4	Reoptimization	85
5.10.5	Appending constraints	85
5.11	Solution analysis	86
5.11.1	Retrieving solution quality information with the API	86
5.12	Efficiency considerations	90
5.13	Conventions employed in the API	91
5.13.1	Naming conventions for arguments	91
5.13.2	Vector formats	94
5.13.3	Matrix formats	95
5.14	The license system	97
5.14.1	Waiting for a free license	97
6	Nonlinear API tutorial	99
6.1	Separable convex optimization	100
6.1.1	The separable problem	100
6.1.2	An example	101
6.1.3	The interface for separable convex optimization	102
6.2	Exponential optimization	130
6.2.1	The problem	130
6.2.2	Source code	131
6.2.3	Solving from the command line	131
6.2.4	Choosing primal or dual form	133
6.2.5	An example	133
6.2.6	Solving from your C code	134

6.2.7	A warning about exponential optimization problems	137
6.3	General convex optimization	137
6.3.1	A warning	137
6.3.2	The problem	137
6.3.3	Assumptions about a nonlinear optimization problem	138
6.3.4	Specifying general convex terms	138
6.4	Dual geometric optimization	139
6.4.1	The problem	139
6.4.2	A numerical example	140
6.4.3	<code>dgopt</code> : A program for dual geometric optimization	141
6.4.4	The source code: <code>dgopt</code>	142
7	Advanced API tutorial	145
7.1	The progress call-back	145
7.1.1	Source code example	145
7.2	Solving linear systems involving the basis matrix	148
7.2.1	Identifying the basis	149
7.2.2	An example	150
7.2.3	Solving arbitrary linear systems	154
7.3	Calling BLAS/LAPACK routines from MOSEK	158
7.3.1	A working example	161
7.4	Automatic reformulation of QCQP problems in conic form	163
7.4.1	Quadratic constraint reformulation	164
7.4.2	Objective function reformulation	165
7.4.3	A complete example	165
7.5	Customizing the warning and error reporting	165
7.6	Unicode strings	167
7.6.1	A source code example	167
7.6.2	Limitations	169
8	A case study	171
8.1	Portfolio optimization	171
8.1.1	Introduction	171
8.1.2	A basic portfolio optimization model	172
8.1.3	The efficient frontier	181
8.1.4	Improving the computational efficiency	184
8.1.5	Slippage cost	185
9	Usage guidelines	197
9.1	Verifying the results	197
9.1.1	Verifying primal feasibility	198
9.1.2	Verifying optimality	198
9.2	Turn on logging	198
9.3	Writing task data to a file	199
9.4	Error handling	199
9.5	Fatal error handling	199
9.6	Checking for memory leaks and overwrites	200

9.7	Important API limitations	200
9.7.1	Thread safety	200
9.7.2	Unicode strings	200
10	Problem formulation and solutions	201
10.1	Linear optimization	201
10.1.1	Duality for linear optimization	202
10.1.2	Infeasibility for linear optimization	204
10.2	Conic quadratic optimization	205
10.2.1	Duality for conic quadratic optimization	206
10.2.2	Infeasibility for conic quadratic optimization	207
10.3	Semidefinite optimization	208
10.3.1	Duality for semidefinite optimization	208
10.3.2	Infeasibility for semidefinite optimization	209
10.4	Quadratic and quadratically constrained optimization	210
10.4.1	Duality for quadratic and quadratically constrained optimization	210
10.4.2	Infeasibility for quadratic and quadratically constrained optimization	211
10.5	General convex optimization	211
10.5.1	Duality for general convex optimization	212
11	The optimizers for continuous problems	215
11.1	How an optimizer works	215
11.1.1	Presolve	216
11.1.2	Dualizer	217
11.1.3	Scaling	218
11.1.4	Using multiple threads	218
11.2	Linear optimization	218
11.2.1	Optimizer selection	218
11.2.2	The interior-point optimizer	219
11.2.3	The simplex based optimizer	224
11.2.4	The interior-point or the simplex optimizer?	225
11.2.5	The primal or the dual simplex variant?	225
11.3	Linear network optimization	226
11.3.1	Network flow problems	226
11.4	Conic optimization	226
11.4.1	The interior-point optimizer	226
11.5	Nonlinear convex optimization	227
11.5.1	The interior-point optimizer	227
11.6	Solving problems in parallel	228
11.6.1	Thread safety	228
11.6.2	The parallelized interior-point optimizer	229
11.6.3	The concurrent optimizer	229
11.6.4	A more flexible concurrent optimizer	231
12	The optimizers for mixed-integer problems	235
12.1	Some concepts and facts related to mixed-integer optimization	235
12.2	The mixed-integer optimizers	236

12.3	The mixed-integer conic optimizer	237
12.3.1	Presolve	237
12.3.2	Heuristic	237
12.3.3	The optimization phase	238
12.3.4	Caveats	238
12.4	The mixed-integer optimizer	238
12.4.1	Presolve	238
12.4.2	Heuristic	238
12.4.3	The optimization phase	239
12.5	Termination criterion	239
12.5.1	Relaxed termination	239
12.5.2	Important parameters	240
12.6	How to speed up the solution process	240
12.7	Understanding solution quality	241
13	The analyzers	243
13.1	The problem analyzer	243
13.1.1	General characteristics	244
13.1.2	Objective	246
13.1.3	Linear constraints	246
13.1.4	Constraint and variable bounds	247
13.1.5	Quadratic constraints	247
13.1.6	Conic constraints	247
13.2	Analyzing infeasible problems	247
13.2.1	Example: Primal infeasibility	248
13.2.2	Locating the cause of primal infeasibility	249
13.2.3	Locating the cause of dual infeasibility	250
13.2.4	The infeasibility report	250
13.2.5	Theory concerning infeasible problems	254
13.2.6	The certificate of primal infeasibility	254
13.2.7	The certificate of dual infeasibility	255
14	Primal feasibility repair	257
14.1	Manual repair	257
14.2	Automatic repair	258
14.2.1	Caveats	259
14.3	Feasibility repair in MOSEK	260
14.3.1	An example using the command line tool	260
14.3.2	Feasibility repair using the API	263
15	Sensitivity analysis	265
15.1	Introduction	265
15.2	Restrictions	265
15.3	References	265
15.4	Sensitivity analysis for linear problems	266
15.4.1	The optimal objective value function	266
15.4.2	The basis type sensitivity analysis	267

15.4.3	The optimal partition type sensitivity analysis	268
15.4.4	Example: Sensitivity analysis	269
15.5	Sensitivity analysis from the MOSEK API	272
15.6	Sensitivity analysis with the command line tool	276
15.6.1	Sensitivity analysis specification file	276
15.6.2	Example: Sensitivity analysis from command line	277
15.6.3	Controlling log output	278
A	API reference	279
A.1	API type definitions	284
A.2	All functions by name	292
A.2.1	MSK_analyzenames()	316
A.2.2	MSK_analyzeproblem()	317
A.2.3	MSK_analyzesolution()	317
A.2.4	MSK_appendbarvars()	318
A.2.5	MSK_appendcone()	319
A.2.6	MSK_appendconeseq()	320
A.2.7	MSK_appendconesseq()	321
A.2.8	MSK_appendcons()	321
A.2.9	MSK_appendsparsesymmat()	322
A.2.10	MSK_appendstat()	323
A.2.11	MSK_appendvars()	323
A.2.12	MSK_axpy()	324
A.2.13	MSK_basiscond()	324
A.2.14	MSK_bktostr()	325
A.2.15	MSK_callbackcodetostr()	326
A.2.16	MSK_calloctdbgenenv()	326
A.2.17	MSK_calloctdbgtask()	327
A.2.18	MSK_calloctenv()	327
A.2.19	MSK_callocttask()	328
A.2.20	MSK_checkconvexity()	328
A.2.21	MSK_checkinlicense()	329
A.2.22	MSK_checkmemenv()	329
A.2.23	MSK_checkmemtask()	330
A.2.24	MSK_checkoutlicense()	330
A.2.25	MSK_checkversion()	331
A.2.26	MSK_chgbound()	331
A.2.27	MSK_clonetask()	333
A.2.28	MSK_commitchanges()	333
A.2.29	MSK_conetypetostr()	333
A.2.30	MSK_deleteenv()	334
A.2.31	MSK_deletesolution()	334
A.2.32	MSK_deletetask()	335
A.2.33	MSK_dot()	335
A.2.34	MSK_dualsensitivity()	336
A.2.35	MSK_echoenv()	337

A.2.36	MSK_echointro()	337
A.2.37	MSK_echotask()	338
A.2.38	MSK_freedbgenv()	338
A.2.39	MSK_freedbgtask()	339
A.2.40	MSK_freeenv()	339
A.2.41	MSK_freetask()	340
A.2.42	MSK_gemm()	340
A.2.43	MSK_gemv()	341
A.2.44	MSK_getacol()	343
A.2.45	MSK_getacolnumnz()	343
A.2.46	MSK_getacolslicetrip()	344
A.2.47	MSK_getaij()	345
A.2.48	MSK_getapiecenumnz()	346
A.2.49	MSK_getarow()	347
A.2.50	MSK_getarownumnz()	347
A.2.51	MSK_getarowslicetrip()	348
A.2.52	MSK_getaslice()	349
A.2.53	MSK_getaslice64()	350
A.2.54	MSK_getaslicenumnz()	351
A.2.55	MSK_getaslicenumnz64()	352
A.2.56	MSK_getbarablocktriplet()	352
A.2.57	MSK_getbaraidx()	353
A.2.58	MSK_getbaraidxij()	354
A.2.59	MSK_getbaraidxinfo()	355
A.2.60	MSK_getbarasparsity()	355
A.2.61	MSK_getbarcbblocktriplet()	356
A.2.62	MSK_getbarcidx()	357
A.2.63	MSK_getbarcidxinfo()	358
A.2.64	MSK_getbarcidxj()	358
A.2.65	MSK_getbarcsparsity()	359
A.2.66	MSK_getbarsj()	359
A.2.67	MSK_getbarvarname()	360
A.2.68	MSK_getbarvarnameindex()	360
A.2.69	MSK_getbarvarnamelen()	361
A.2.70	MSK_getbarxj()	362
A.2.71	MSK_getbound()	362
A.2.72	MSK_getboundslice()	363
A.2.73	MSK_getbuildinfo()	364
A.2.74	MSK_getc()	364
A.2.75	MSK_getcallbackfunc()	365
A.2.76	MSK_getcfix()	365
A.2.77	MSK_getcj()	366
A.2.78	MSK_getcodedesc()	366
A.2.79	MSK_getconbound()	367
A.2.80	MSK_getconboundslice()	367
A.2.81	MSK_getcone()	368

A.2.82 MSK_getconeinfo()	369
A.2.83 MSK_getconename()	369
A.2.84 MSK_getconenameindex()	370
A.2.85 MSK_getconenamelen()	370
A.2.86 MSK_getconname()	371
A.2.87 MSK_getconnameindex()	372
A.2.88 MSK_getconnamelen()	372
A.2.89 MSK_getcslice()	373
A.2.90 MSK_getdbi()	373
A.2.91 MSK_getdcni()	374
A.2.92 MSK_getdeqi()	375
A.2.93 MSK_getdimbarvarj()	376
A.2.94 MSK_getdouinf()	376
A.2.95 MSK_getdoupam()	377
A.2.96 MSK_getdualobj()	377
A.2.97 MSK_getdviolbarvar()	378
A.2.98 MSK_getdviolcon()	379
A.2.99 MSK_getdviolcones()	379
A.2.100 MSK_getdviolvar()	380
A.2.101 MSK_getenv()	381
A.2.102 MSK_getglbdlname()	382
A.2.103 MSK_getinfeasiblesubproblem()	382
A.2.104 MSK_getinfindex()	383
A.2.105 MSK_getinfmax()	383
A.2.106 MSK_getinfname()	384
A.2.107 MSK_getinti()	384
A.2.108 MSK_getintinf()	385
A.2.109 MSK_getintparam()	386
A.2.110 MSK_getlasterror()	386
A.2.111 MSK_getlasterror64()	387
A.2.112 MSK_getlenbarvarj()	387
A.2.113 MSK_getlintinf()	388
A.2.114 MSK_getmaxnamelen()	389
A.2.115 MSK_getmaxnumanz()	389
A.2.116 MSK_getmaxnumanz64()	389
A.2.117 MSK_getmaxnumbarvar()	390
A.2.118 MSK_getmaxnumcon()	390
A.2.119 MSK_getmaxnumcone()	391
A.2.120 MSK_getmaxnumqnz()	391
A.2.121 MSK_getmaxnumqnz64()	392
A.2.122 MSK_getmaxnumvar()	392
A.2.123 MSK_getmemusagetask()	392
A.2.124 MSK_getnadouinf()	393
A.2.125 MSK_getnadoupam()	393
A.2.126 MSK_getnaintinf()	394
A.2.127 MSK_getnaintparam()	394

A.2.128MSK_getnastrparam()	395
A.2.129MSK_getnastrparamal()	396
A.2.130MSK_getnlfunc()	396
A.2.131MSK_getnumanz()	397
A.2.132MSK_getnumanz64()	397
A.2.133MSK_getnumbarablocktriplets()	398
A.2.134MSK_getnumbaranz()	398
A.2.135MSK_getnumbarcblocktriplets()	398
A.2.136MSK_getnumbarcnz()	399
A.2.137MSK_getnumbarvar()	399
A.2.138MSK_getnumcon()	400
A.2.139MSK_getnumcone()	400
A.2.140MSK_getnumconemem()	400
A.2.141MSK_getnumintvar()	401
A.2.142MSK_getnumparam()	401
A.2.143MSK_getnumqconknz()	402
A.2.144MSK_getnumqconknz64()	402
A.2.145MSK_getnumqobjnz()	403
A.2.146MSK_getnumqobjnz64()	403
A.2.147MSK_getnumsymmat()	404
A.2.148MSK_getnumvar()	404
A.2.149MSK_getobjname()	404
A.2.150MSK_getobjnamelen()	405
A.2.151MSK_getobjsense()	405
A.2.152MSK_getparammax()	406
A.2.153MSK_getparamname()	406
A.2.154MSK_getpbi()	407
A.2.155MSK_getpcni()	408
A.2.156MSK_getpeqi()	408
A.2.157MSK_getprimalobj()	409
A.2.158MSK_getprobtype()	410
A.2.159MSK_getprosta()	410
A.2.160MSK_getpviolbarvar()	411
A.2.161MSK_getpviolcon()	411
A.2.162MSK_getpviolcones()	412
A.2.163MSK_getpviolvar()	413
A.2.164MSK_getqconk()	414
A.2.165MSK_getqconk64()	414
A.2.166MSK_getqobj()	415
A.2.167MSK_getqobj64()	416
A.2.168MSK_getqobjij()	417
A.2.169MSK_getreducedcosts()	418
A.2.170MSK_getresponseclass()	418
A.2.171MSK_getskc()	419
A.2.172MSK_getskcslice()	419
A.2.173MSK_getskx()	420

A.2.174MSK_getskxslice()	421
A.2.175MSK_getslc()	421
A.2.176MSK_getslcslice()	422
A.2.177MSK_getslx()	423
A.2.178MSK_getslxslice()	423
A.2.179MSK_getsnx()	424
A.2.180MSK_getsnxslice()	424
A.2.181MSK_getsolsta()	425
A.2.182MSK_getsolution()	426
A.2.183MSK_getsolutioni()	428
A.2.184MSK_getsolutionincallback()	429
A.2.185MSK_getsolutioninf()	431
A.2.186MSK_getsolutioninfo()	432
A.2.187MSK_getsolutionslice()	434
A.2.188MSK_getsparsesymmat()	436
A.2.189MSK_getstrparam()	437
A.2.190MSK_getstrparamal()	437
A.2.191MSK_getstrparamlen()	438
A.2.192MSK_getsuc()	438
A.2.193MSK_getsucslice()	439
A.2.194MSK_getsux()	440
A.2.195MSK_getsuxslice()	440
A.2.196MSK_getsymbcon()	441
A.2.197MSK_getsymbcondim()	441
A.2.198MSK_getsymmatinfo()	442
A.2.199MSK_gettaskname()	443
A.2.200MSK_gettasknamelen()	443
A.2.201MSK_getvarbound()	444
A.2.202MSK_getvarboundslice()	444
A.2.203MSK_getvarbranchdir()	445
A.2.204MSK_getvarbranchorder()	445
A.2.205MSK_getvarbranchpri()	446
A.2.206MSK_getvarname()	446
A.2.207MSK_getvarnameindex()	447
A.2.208MSK_getvarnamelen()	448
A.2.209MSK_getvartype()	448
A.2.210MSK_getvartypelist()	449
A.2.211MSK_getversion()	449
A.2.212MSK_getxc()	450
A.2.213MSK_getxcslice()	450
A.2.214MSK_getxx()	451
A.2.215MSK_getxxslice()	452
A.2.216MSK_gety()	452
A.2.217MSK_getyslice()	453
A.2.218MSK_initbasissolve()	454
A.2.219MSK_initenv()	454

A.2.220MSK_inputdata()	455
A.2.221MSK_inputdata64()	456
A.2.222MSK_iparvaltosymnam()	458
A.2.223MSK_isdoupname()	458
A.2.224MSK_isinfinity()	459
A.2.225MSK_isintpname()	459
A.2.226MSK_isstrpname()	459
A.2.227MSK_licensecleanup()	460
A.2.228MSK_linkfiletoenvstream()	460
A.2.229MSK_linkfiletotaskstream()	461
A.2.230MSK_linkfunctoenvstream()	461
A.2.231MSK_linkfunctotaskstream()	462
A.2.232MSK_makeemptytask()	462
A.2.233MSK_makeenv()	463
A.2.234MSK_makeenvalloc()	463
A.2.235MSK_maketask()	464
A.2.236MSK_onesolutionsummary()	465
A.2.237MSK_optimize()	465
A.2.238MSK_optimizeconcurrent()	466
A.2.239MSK_optimizersummary()	467
A.2.240MSK_optimizetrm()	467
A.2.241MSK_potrf()	468
A.2.242MSK_primalrepair()	469
A.2.243MSK_primalsensitivity()	470
A.2.244MSK_printdata()	473
A.2.245MSK_printparam()	474
A.2.246MSK_probtypetostr()	474
A.2.247MSK_prostatostr()	475
A.2.248MSK_putacol()	475
A.2.249MSK_putacollist()	476
A.2.250MSK_putacollist64()	477
A.2.251MSK_putacolslice()	478
A.2.252MSK_putacolslice64()	479
A.2.253MSK_putaij()	480
A.2.254MSK_putaijlist()	481
A.2.255MSK_putaijlist64()	482
A.2.256MSK_putarow()	483
A.2.257MSK_putarowlist()	484
A.2.258MSK_putarowlist64()	485
A.2.259MSK_putarowslice()	486
A.2.260MSK_putarowslice64()	487
A.2.261MSK_putbarablocktriplet()	488
A.2.262MSK_putbaraij()	488
A.2.263MSK_putbarcbblocktriplet()	489
A.2.264MSK_putbarcj()	490
A.2.265MSK_putbarsj()	491

A.2.266MSK_putbarvarname()	491
A.2.267MSK_putbarxj()	492
A.2.268MSK_putbound()	492
A.2.269MSK_putboundlist()	493
A.2.270MSK_putboundslice()	494
A.2.271MSK_putcallbackfunc()	495
A.2.272MSK_putcfix()	496
A.2.273MSK_putcj()	496
A.2.274MSK_putclist()	497
A.2.275MSK_putconbound()	497
A.2.276MSK_putconboundlist()	498
A.2.277MSK_putconboundslice()	499
A.2.278MSK_putcone()	500
A.2.279MSK_putconename()	500
A.2.280MSK_putconname()	501
A.2.281MSK_putcslice()	501
A.2.282MSK_putdllpath()	502
A.2.283MSK_putdoupam()	502
A.2.284MSK_putexitfunc()	503
A.2.285MSK_putintparam()	503
A.2.286MSK_putkeepdlls()	504
A.2.287MSK_putlicensecode()	504
A.2.288MSK_putlicensedebug()	505
A.2.289MSK_putlicensepath()	505
A.2.290MSK_putlicensewait()	506
A.2.291MSK_putmaxnumanz()	506
A.2.292MSK_putmaxnumbarvar()	507
A.2.293MSK_putmaxnumcon()	507
A.2.294MSK_putmaxnumcone()	508
A.2.295MSK_putmaxnumqnz()	508
A.2.296MSK_putmaxnumvar()	509
A.2.297MSK_putnadoupam()	509
A.2.298MSK_putnaintparam()	510
A.2.299MSK_putnastrparam()	510
A.2.300MSK_putnlfunc()	511
A.2.301MSK_putobjname()	511
A.2.302MSK_putobjsense()	512
A.2.303MSK_putparam()	512
A.2.304MSK_putqcon()	513
A.2.305MSK_putqconk()	514
A.2.306MSK_putqobj()	515
A.2.307MSK_putqobjij()	516
A.2.308MSK_putresponsefunc()	517
A.2.309MSK_putskc()	518
A.2.310MSK_putskcslice()	518
A.2.311MSK_putskx()	519

A.2.312MSK_putskxslice()	519
A.2.313MSK_putslc()	520
A.2.314MSK_putslcslice()	521
A.2.315MSK_putslx()	521
A.2.316MSK_putslxslice()	522
A.2.317MSK_putsnx()	523
A.2.318MSK_putsnxslice()	523
A.2.319MSK_putsolution()	524
A.2.320MSK_putsolutioni()	525
A.2.321MSK_putsolutionyi()	526
A.2.322MSK_putstrparam()	527
A.2.323MSK_putsuc()	527
A.2.324MSK_putsucslice()	528
A.2.325MSK_putsux()	528
A.2.326MSK_putsuxslice()	529
A.2.327MSK_puttaskname()	530
A.2.328MSK_putvarbound()	530
A.2.329MSK_putvarboundlist()	531
A.2.330MSK_putvarboundslice()	532
A.2.331MSK_putvarbranchorder()	532
A.2.332MSK_putvarname()	533
A.2.333MSK_putvartype()	533
A.2.334MSK_putvartypelist()	534
A.2.335MSK_putxc()	535
A.2.336MSK_putxcslice()	535
A.2.337MSK_putxx()	536
A.2.338MSK_putxxslice()	537
A.2.339MSK_puty()	537
A.2.340MSK_putyslice()	538
A.2.341MSK_readbranchpriorities()	539
A.2.342MSK_readdata()	539
A.2.343MSK_readdataautoformat()	540
A.2.344MSK_readdataformat()	540
A.2.345MSK_readparamfile()	541
A.2.346MSK_readsolution()	541
A.2.347MSK_readsummary()	542
A.2.348MSK_readtask()	542
A.2.349MSK_reformqcqotosocp()	543
A.2.350MSK_relaxprimal()	543
A.2.351MSK_removebarvars()	544
A.2.352MSK_removecones()	545
A.2.353MSK_removecons()	545
A.2.354MSK_removevars()	546
A.2.355MSK_resizetask()	547
A.2.356MSK_sensitivityreport()	548
A.2.357MSK_setdefaults()	548

A.2.358	MSK_sktostr()	549
A.2.359	MSK_solstatostr()	549
A.2.360	MSK_solutiondef()	550
A.2.361	MSK_solutionsummary()	550
A.2.362	MSK_solvewithbasis()	551
A.2.363	MSK_startstat()	552
A.2.364	MSK_stopstat()	552
A.2.365	MSK_strdupdbgenv()	553
A.2.366	MSK_strdupdbgtask()	553
A.2.367	MSK_strdupenv()	554
A.2.368	MSK_strduptask()	554
A.2.369	MSK_strtoconetype()	555
A.2.370	MSK_strtosk()	555
A.2.371	MSK_sy eig()	556
A.2.372	MSK_syevd()	556
A.2.373	MSK_symnamtovalue()	557
A.2.374	MSK_syrk()	558
A.2.375	MSK_toconic()	559
A.2.376	MSK_unlinkfuncfromenvstream()	559
A.2.377	MSK_unlinkfuncfromtaskstream()	560
A.2.378	MSK_updatesolutioninfo()	560
A.2.379	MSK_utf8towchar()	561
A.2.380	MSK_wchartoutf8()	561
A.2.381	MSK_whichparam()	562
A.2.382	MSK_writebranchpriorities()	562
A.2.383	MSK_writedata()	563
A.2.384	MSK_writeparamfile()	564
A.2.385	MSK_writesolution()	564
A.2.386	MSK_writetask()	565
A.2.387	Task()	566
B	Parameters	567
B.1	MSKdparame: Double parameters	581
B.1.1	MSK_DPAR_ANA_SOL_INFEAS_TOL	581
B.1.2	MSK_DPAR_BASIS_REL_TOL_S	581
B.1.3	MSK_DPAR_BASIS_TOL_S	582
B.1.4	MSK_DPAR_BASIS_TOL_X	582
B.1.5	MSK_DPAR_CHECK_CONVEXITY_REL_TOL	582
B.1.6	MSK_DPAR_DATA_TOL_AIJ	583
B.1.7	MSK_DPAR_DATA_TOL_AIJ_HUGE	583
B.1.8	MSK_DPAR_DATA_TOL_AIJ_LARGE	584
B.1.9	MSK_DPAR_DATA_TOL_BOUND_INF	584
B.1.10	MSK_DPAR_DATA_TOL_BOUND_WRN	584
B.1.11	MSK_DPAR_DATA_TOL_C_HUGE	585
B.1.12	MSK_DPAR_DATA_TOL_CJ_LARGE	585
B.1.13	MSK_DPAR_DATA_TOL_QIJ	585

B.1.14	MSK_DPAR_DATA_TOL_X	586
B.1.15	MSK_DPAR_FEASREPAIR_TOL	586
B.1.16	MSK_DPAR_INTPNT_CO_TOL_DFEAS	586
B.1.17	MSK_DPAR_INTPNT_CO_TOL_INFEAS	587
B.1.18	MSK_DPAR_INTPNT_CO_TOL_MU_RED	587
B.1.19	MSK_DPAR_INTPNT_CO_TOL_NEAR_REL	587
B.1.20	MSK_DPAR_INTPNT_CO_TOL_PFEAS	588
B.1.21	MSK_DPAR_INTPNT_CO_TOL_REL_GAP	588
B.1.22	MSK_DPAR_INTPNT_NL_MERIT_BAL	588
B.1.23	MSK_DPAR_INTPNT_NL_TOL_DFEAS	589
B.1.24	MSK_DPAR_INTPNT_NL_TOL_MU_RED	589
B.1.25	MSK_DPAR_INTPNT_NL_TOL_NEAR_REL	589
B.1.26	MSK_DPAR_INTPNT_NL_TOL_PFEAS	590
B.1.27	MSK_DPAR_INTPNT_NL_TOL_REL_GAP	590
B.1.28	MSK_DPAR_INTPNT_NL_TOL_REL_STEP	590
B.1.29	MSK_DPAR_INTPNT_TOL_DFEAS	591
B.1.30	MSK_DPAR_INTPNT_TOL_DSAFE	591
B.1.31	MSK_DPAR_INTPNT_TOL_INFEAS	591
B.1.32	MSK_DPAR_INTPNT_TOL_MU_RED	592
B.1.33	MSK_DPAR_INTPNT_TOL_PATH	592
B.1.34	MSK_DPAR_INTPNT_TOL_PFEAS	592
B.1.35	MSK_DPAR_INTPNT_TOL_PSAFE	593
B.1.36	MSK_DPAR_INTPNT_TOL_REL_GAP	593
B.1.37	MSK_DPAR_INTPNT_TOL_REL_STEP	593
B.1.38	MSK_DPAR_INTPNT_TOL_STEP_SIZE	594
B.1.39	MSK_DPAR_LOWER_OBJ_CUT	594
B.1.40	MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH	594
B.1.41	MSK_DPAR_MIO_DISABLE_TERM_TIME	595
B.1.42	MSK_DPAR_MIO_HEURISTIC_TIME	595
B.1.43	MSK_DPAR_MIO_MAX_TIME	596
B.1.44	MSK_DPAR_MIO_MAX_TIME_APRX_OPT	596
B.1.45	MSK_DPAR_MIO_NEAR_TOL_ABS_GAP	597
B.1.46	MSK_DPAR_MIO_NEAR_TOL_REL_GAP	597
B.1.47	MSK_DPAR_MIO_REL_ADD_CUT_LIMITED	598
B.1.48	MSK_DPAR_MIO_REL_GAP_CONST	598
B.1.49	MSK_DPAR_MIO_TOL_ABS_GAP	598
B.1.50	MSK_DPAR_MIO_TOL_ABS_RELAX_INT	599
B.1.51	MSK_DPAR_MIO_TOL_FEAS	599
B.1.52	MSK_DPAR_MIO_TOL_MAX_CUT_FRAC_RHS	599
B.1.53	MSK_DPAR_MIO_TOL_MIN_CUT_FRAC_RHS	600
B.1.54	MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT	600
B.1.55	MSK_DPAR_MIO_TOL_REL_GAP	600
B.1.56	MSK_DPAR_MIO_TOL_REL_RELAX_INT	601
B.1.57	MSK_DPAR_MIO_TOL_X	601
B.1.58	MSK_DPAR_NONCONVEX_TOL_FEAS	601
B.1.59	MSK_DPAR_NONCONVEX_TOL_OPT	602

B.1.60	MSK_DPAR_OPTIMIZER_MAX_TIME	602
B.1.61	MSK_DPAR_PREOLVE_TOL_ABS_LINDEP	602
B.1.62	MSK_DPAR_PREOLVE_TOL_AIJ	603
B.1.63	MSK_DPAR_PREOLVE_TOL_REL_LINDEP	603
B.1.64	MSK_DPAR_PREOLVE_TOL_S	603
B.1.65	MSK_DPAR_PREOLVE_TOL_X	604
B.1.66	MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL	604
B.1.67	MSK_DPAR_SIM_LU_TOL_REL_PIV	604
B.1.68	MSK_DPAR_SIMPLEX_ABS_TOL_PIV	605
B.1.69	MSK_DPAR_UPPER_OBJ_CUT	605
B.1.70	MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH	605
B.2	MSKiparame: Integer parameters	606
B.2.1	MSK_IPAR_ALLOC_ADD_QNZ	606
B.2.2	MSK_IPAR_ANA_SOL_BASIS	606
B.2.3	MSK_IPAR_ANA_SOL_PRINT_VIOLATED	606
B.2.4	MSK_IPAR_AUTO_SORT_A_BEFORE_OPT	607
B.2.5	MSK_IPAR_AUTO_UPDATE_SOL_INFO	607
B.2.6	MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE	608
B.2.7	MSK_IPAR_BI_CLEAN_OPTIMIZER	608
B.2.8	MSK_IPAR_BI_IGNORE_MAX_ITER	609
B.2.9	MSK_IPAR_BI_IGNORE_NUM_ERROR	609
B.2.10	MSK_IPAR_BI_MAX_ITERATIONS	609
B.2.11	MSK_IPAR_CACHE_LICENSE	610
B.2.12	MSK_IPAR_CHECK_CONVEXITY	610
B.2.13	MSK_IPAR_COMPRESS_STATFILE	611
B.2.14	MSK_IPAR_CONCURRENT_NUM_OPTIMIZERS	611
B.2.15	MSK_IPAR_CONCURRENT_PRIORITY_DUAL_SIMPLEX	611
B.2.16	MSK_IPAR_CONCURRENT_PRIORITY_FREE_SIMPLEX	612
B.2.17	MSK_IPAR_CONCURRENT_PRIORITY_INTPNT	612
B.2.18	MSK_IPAR_CONCURRENT_PRIORITY_PRIMAL_SIMPLEX	612
B.2.19	MSK_IPAR_FEASREPAIR_OPTIMIZE	613
B.2.20	MSK_IPAR_INFEAS_GENERIC_NAMES	613
B.2.21	MSK_IPAR_INFEAS_PREFER_PRIMAL	613
B.2.22	MSK_IPAR_INFEAS_REPORT_AUTO	614
B.2.23	MSK_IPAR_INFEAS_REPORT_LEVEL	614
B.2.24	MSK_IPAR_INTPNT_BASIS	615
B.2.25	MSK_IPAR_INTPNT_DIFF_STEP	615
B.2.26	MSK_IPAR_INTPNT_FACTOR_DEBUG_LVL	616
B.2.27	MSK_IPAR_INTPNT_FACTOR_METHOD	616
B.2.28	MSK_IPAR_INTPNT_HOTSTART	616
B.2.29	MSK_IPAR_INTPNT_MAX_ITERATIONS	617
B.2.30	MSK_IPAR_INTPNT_MAX_NUM_COR	617
B.2.31	MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS	617
B.2.32	MSK_IPAR_INTPNT_OFF_COL_TRH	618
B.2.33	MSK_IPAR_INTPNT_ORDER_METHOD	618
B.2.34	MSK_IPAR_INTPNT_REGULARIZATION_USE	619

B.2.35	MSK_IPAR_INTPNT_SCALING	619
B.2.36	MSK_IPAR_INTPNT_SOLVE_FORM	619
B.2.37	MSK_IPAR_INTPNT_STARTING_POINT	620
B.2.38	MSK_IPAR_LIC_TRH_EXPIRY_WRN	620
B.2.39	MSK_IPAR_LICENSE_DEBUG	621
B.2.40	MSK_IPAR_LICENSE_PAUSE_TIME	621
B.2.41	MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS	621
B.2.42	MSK_IPAR_LICENSE_WAIT	622
B.2.43	MSK_IPAR_LOG	622
B.2.44	MSK_IPAR_LOG_BI	623
B.2.45	MSK_IPAR_LOG_BIFREQ	623
B.2.46	MSK_IPAR_LOG_CHECK_CONVEXITY	623
B.2.47	MSK_IPAR_LOG_CONCURRENT	624
B.2.48	MSK_IPAR_LOG_CUT_SECOND_OPT	624
B.2.49	MSK_IPAR_LOG_EXPAND	625
B.2.50	MSK_IPAR_LOG_FACTOR	625
B.2.51	MSK_IPAR_LOG_FEAS_REPAIR	625
B.2.52	MSK_IPAR_LOG_FILE	626
B.2.53	MSK_IPAR_LOG_HEAD	626
B.2.54	MSK_IPAR_LOG_INFEAS_ANA	626
B.2.55	MSK_IPAR_LOG_INTPNT	627
B.2.56	MSK_IPAR_LOG_MIO	627
B.2.57	MSK_IPAR_LOG_MIO_FREQ	627
B.2.58	MSK_IPAR_LOG_NONCONVEX	628
B.2.59	MSK_IPAR_LOG_OPTIMIZER	628
B.2.60	MSK_IPAR_LOG_ORDER	628
B.2.61	MSK_IPAR_LOG_PARAM	629
B.2.62	MSK_IPAR_LOG_PRESOLVE	629
B.2.63	MSK_IPAR_LOG_RESPONSE	629
B.2.64	MSK_IPAR_LOG_SENSITIVITY	630
B.2.65	MSK_IPAR_LOG_SENSITIVITY_OPT	630
B.2.66	MSK_IPAR_LOG_SIM	630
B.2.67	MSK_IPAR_LOG_SIM_FREQ	631
B.2.68	MSK_IPAR_LOG_SIM_MINOR	631
B.2.69	MSK_IPAR_LOG_SIM_NETWORK_FREQ	631
B.2.70	MSK_IPAR_LOG_STORAGE	632
B.2.71	MSK_IPAR_MAX_NUM_WARNINGS	632
B.2.72	MSK_IPAR_MIO_BRANCH_DIR	632
B.2.73	MSK_IPAR_MIO_BRANCH_PRIORITIES_USE	633
B.2.74	MSK_IPAR_MIO_CONSTRUCT_SOL	633
B.2.75	MSK_IPAR_MIO_CONT_SOL	633
B.2.76	MSK_IPAR_MIO_CUT_CG	634
B.2.77	MSK_IPAR_MIO_CUT_CMIR	634
B.2.78	MSK_IPAR_MIO_CUT_LEVEL_ROOT	635
B.2.79	MSK_IPAR_MIO_CUT_LEVEL_TREE	635
B.2.80	MSK_IPAR_MIO_FEASPUMP_LEVEL	636

B.2.81	MSK_IPAR_MIO_HEURISTIC_LEVEL	636
B.2.82	MSK_IPAR_MIO_HOTSTART	636
B.2.83	MSK_IPAR_MIO_KEEP_BASIS	637
B.2.84	MSK_IPAR_MIO_LOCAL_BRANCH_NUMBER	637
B.2.85	MSK_IPAR_MIO_MAX_NUM_BRANCHES	637
B.2.86	MSK_IPAR_MIO_MAX_NUM_RELAXS	638
B.2.87	MSK_IPAR_MIO_MAX_NUM_SOLUTIONS	638
B.2.88	MSK_IPAR_MIO_MODE	639
B.2.89	MSK_IPAR_MIO_MT_USER_CB	639
B.2.90	MSK_IPAR_MIO_NODE_OPTIMIZER	640
B.2.91	MSK_IPAR_MIO_NODE_SELECTION	640
B.2.92	MSK_IPAR_MIO_OPTIMIZER_MODE	641
B.2.93	MSK_IPAR_MIO_PRESOLVE_AGGREGATE	641
B.2.94	MSK_IPAR_MIO_PRESOLVE_PROBING	642
B.2.95	MSK_IPAR_MIO_PRESOLVE_USE	642
B.2.96	MSK_IPAR_MIO_PROBING_LEVEL	642
B.2.97	MSK_IPAR_MIO_RINS_MAX_NODES	643
B.2.98	MSK_IPAR_MIO_ROOT_OPTIMIZER	643
B.2.99	MSK_IPAR_MIO_STRONG_BRANCH	644
B.2.100	MSK_IPAR_MIO_USE_MULTITHREADED_OPTIMIZER	644
B.2.101	MSK_IPAR_MT_SPINCOUNT	645
B.2.102	MSK_IPAR_NONCONVEX_MAX_ITERATIONS	645
B.2.103	MSK_IPAR_NUM_THREADS	645
B.2.104	MSK_IPAR_OPF_MAX_TERMS_PER_LINE	646
B.2.105	MSK_IPAR_OPF_WRITE_HEADER	646
B.2.106	MSK_IPAR_OPF_WRITE_HINTS	646
B.2.107	MSK_IPAR_OPF_WRITE_PARAMETERS	647
B.2.108	MSK_IPAR_OPF_WRITE_PROBLEM	647
B.2.109	MSK_IPAR_OPF_WRITE_SOL_BAS	647
B.2.110	MSK_IPAR_OPF_WRITE_SOL_ITG	648
B.2.111	MSK_IPAR_OPF_WRITE_SOL_ITR	648
B.2.112	MSK_IPAR_OPF_WRITE_SOLUTIONS	648
B.2.113	MSK_IPAR_OPTIMIZER	649
B.2.114	MSK_IPAR_PARAM_READ_CASE_NAME	649
B.2.115	MSK_IPAR_PARAM_READ_IGNORE_ERROR	650
B.2.116	MSK_IPAR_PRESOLVE_ELIM_FILL	650
B.2.117	MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_NUM_TRIES	651
B.2.118	MSK_IPAR_PRESOLVE_ELIMINATOR_USE	651
B.2.119	MSK_IPAR_PRESOLVE_LEVEL	651
B.2.120	MSK_IPAR_PRESOLVE_LINDEP_ABS_WORK_TRH	652
B.2.121	MSK_IPAR_PRESOLVE_LINDEP_REL_WORK_TRH	652
B.2.122	MSK_IPAR_PRESOLVE_LINDEP_USE	652
B.2.123	MSK_IPAR_PRESOLVE_MAX_NUM_REDUCATIONS	653
B.2.124	MSK_IPAR_PRESOLVE_USE	653
B.2.125	MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER	653
B.2.126	MSK_IPAR_QO_SEPARABLE_REFORMULATION	654

B.2.127MSK_IPAR_READ_ANZ	654
B.2.128MSK_IPAR_READ_CON	655
B.2.129MSK_IPAR_READ_CONE	655
B.2.130MSK_IPAR_READ_DATA_COMPRESSED	655
B.2.131MSK_IPAR_READ_DATA_FORMAT	656
B.2.132MSK_IPAR_READ_DEBUG	656
B.2.133MSK_IPAR_READ_KEEP_FREE_CON	657
B.2.134MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOU	657
B.2.135MSK_IPAR_READ_LP_QUOTED_NAMES	657
B.2.136MSK_IPAR_READ_MPS_FORMAT	658
B.2.137MSK_IPAR_READ_MPS_KEEP_INT	658
B.2.138MSK_IPAR_READ_MPS_OBJ_SENSE	658
B.2.139MSK_IPAR_READ_MPS_RELAX	659
B.2.140MSK_IPAR_READ_MPS_WIDTH	659
B.2.141MSK_IPAR_READ_QNZ	660
B.2.142MSK_IPAR_READ_TASK_IGNORE_PARAM	660
B.2.143MSK_IPAR_READ_VAR	660
B.2.144MSK_IPAR_SENSITIVITY_ALL	661
B.2.145MSK_IPAR_SENSITIVITY_OPTIMIZER	661
B.2.146MSK_IPAR_SENSITIVITY_TYPE	662
B.2.147MSK_IPAR_SIM_BASIS_FACTOR_USE	662
B.2.148MSK_IPAR_SIM_DEGEN	662
B.2.149MSK_IPAR_SIM_DUAL_CRASH	663
B.2.150MSK_IPAR_SIM_DUAL_PHASEONE_METHOD	663
B.2.151MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION	664
B.2.152MSK_IPAR_SIM_DUAL_SELECTION	664
B.2.153MSK_IPAR_SIM_EXPLOIT_DUPVEC	665
B.2.154MSK_IPAR_SIM_HOTSTART	665
B.2.155MSK_IPAR_SIM_HOTSTART_LU	665
B.2.156MSK_IPAR_SIM_INTEGER	666
B.2.157MSK_IPAR_SIM_MAX_ITERATIONS	666
B.2.158MSK_IPAR_SIM_MAX_NUM_SETBACKS	666
B.2.159MSK_IPAR_SIM_NON_SINGULAR	667
B.2.160MSK_IPAR_SIM_PRIMAL_CRASH	667
B.2.161MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD	668
B.2.162MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION	668
B.2.163MSK_IPAR_SIM_PRIMAL_SELECTION	668
B.2.164MSK_IPAR_SIM_REFACTOR_FREQ	669
B.2.165MSK_IPAR_SIM_REFORMULATION	669
B.2.166MSK_IPAR_SIM_SAVE_LU	670
B.2.167MSK_IPAR_SIM_SCALING	670
B.2.168MSK_IPAR_SIM_SCALING_METHOD	671
B.2.169MSK_IPAR_SIM_SOLVE_FORM	671
B.2.170MSK_IPAR_SIM_STABILITY_PRIORITY	671
B.2.171MSK_IPAR_SIM_SWITCH_OPTIMIZER	672
B.2.172MSK_IPAR_SOL_FILTER_KEEP_BASIC	672

B.2.173	MSK_IPAR_SOL_FILTER_KEEP_RANGED	672
B.2.174	MSK_IPAR_SOL_READ_NAME_WIDTH	673
B.2.175	MSK_IPAR_SOL_READ_WIDTH	673
B.2.176	MSK_IPAR_SOLUTION_CALLBACK	674
B.2.177	MSK_IPAR_TIMING_LEVEL	674
B.2.178	MSK_IPAR_WARNING_LEVEL	674
B.2.179	MSK_IPAR_WRITE_BAS_CONSTRAINTS	675
B.2.180	MSK_IPAR_WRITE_BAS_HEAD	675
B.2.181	MSK_IPAR_WRITE_BAS_VARIABLES	675
B.2.182	MSK_IPAR_WRITE_DATA_COMPRESSED	676
B.2.183	MSK_IPAR_WRITE_DATA_FORMAT	676
B.2.184	MSK_IPAR_WRITE_DATA_PARAM	677
B.2.185	MSK_IPAR_WRITE_FREE_CON	677
B.2.186	MSK_IPAR_WRITE_GENERIC_NAMES	677
B.2.187	MSK_IPAR_WRITE_GENERIC_NAMES_IO	678
B.2.188	MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_CONIC_ITEMS	678
B.2.189	MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS	678
B.2.190	MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_NL_ITEMS	679
B.2.191	MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_PSD_ITEMS	679
B.2.192	MSK_IPAR_WRITE_INT_CONSTRAINTS	679
B.2.193	MSK_IPAR_WRITE_INT_HEAD	680
B.2.194	MSK_IPAR_WRITE_INT_VARIABLES	680
B.2.195	MSK_IPAR_WRITE_LP_LINE_WIDTH	680
B.2.196	MSK_IPAR_WRITE_LP_QUOTED_NAMES	681
B.2.197	MSK_IPAR_WRITE_LP_STRICT_FORMAT	681
B.2.198	MSK_IPAR_WRITE_LP_TERMS_PER_LINE	681
B.2.199	MSK_IPAR_WRITE_MPS_INT	682
B.2.200	MSK_IPAR_WRITE_PRECISION	682
B.2.201	MSK_IPAR_WRITE_SOL_BAR_VARIABLES	682
B.2.202	MSK_IPAR_WRITE_SOL_CONSTRAINTS	683
B.2.203	MSK_IPAR_WRITE_SOL_HEAD	683
B.2.204	MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES	683
B.2.205	MSK_IPAR_WRITE_SOL_VARIABLES	684
B.2.206	MSK_IPAR_WRITE_TASK_INC_SOL	684
B.2.207	MSK_IPAR_WRITE_XML_MODE	684
B.3	MSKsparame: String parameter types	685
B.3.1	MSK_SPAR_BAS_SOL_FILE_NAME	685
B.3.2	MSK_SPAR_DATA_FILE_NAME	685
B.3.3	MSK_SPAR_DEBUG_FILE_NAME	685
B.3.4	MSK_SPAR_FEASREPAIR_NAME_PREFIX	686
B.3.5	MSK_SPAR_FEASREPAIR_NAME_SEPARATOR	686
B.3.6	MSK_SPAR_FEASREPAIR_NAME_WSUMVIOL	686
B.3.7	MSK_SPAR_INT_SOL_FILE_NAME	687
B.3.8	MSK_SPAR_ITR_SOL_FILE_NAME	687
B.3.9	MSK_SPAR_MIO_DEBUG_STRING	687
B.3.10	MSK_SPAR_PARAM_COMMENT_SIGN	688

B.3.11	MSK_SPAR_PARAM_READ_FILE_NAME	688
B.3.12	MSK_SPAR_PARAM_WRITE_FILE_NAME	688
B.3.13	MSK_SPAR_READ_MPS_BOU_NAME	689
B.3.14	MSK_SPAR_READ_MPS_OBJ_NAME	689
B.3.15	MSK_SPAR_READ_MPS_RAN_NAME	689
B.3.16	MSK_SPAR_READ_MPS_RHS_NAME	690
B.3.17	MSK_SPAR_SENSITIVITY_FILE_NAME	690
B.3.18	MSK_SPAR_SENSITIVITY_RES_FILE_NAME	690
B.3.19	MSK_SPAR_SOL_FILTER_XC_LOW	691
B.3.20	MSK_SPAR_SOL_FILTER_XC_UPR	691
B.3.21	MSK_SPAR_SOL_FILTER_XX_LOW	691
B.3.22	MSK_SPAR_SOL_FILTER_XX_UPR	692
B.3.23	MSK_SPAR_STAT_FILE_NAME	692
B.3.24	MSK_SPAR_STAT_KEY	692
B.3.25	MSK_SPAR_STAT_NAME	693
B.3.26	MSK_SPAR_WRITE_LP_GEN_VAR_NAME	693
C	Response codes	695
D	API constants	727
D.1	Constraint or variable access modes	727
D.2	Basis identification	727
D.3	Bound keys	728
D.4	Specifies the branching direction.	728
D.5	Progress call-back codes	728
D.6	Types of convexity checks.	737
D.7	Compression types	737
D.8	Cone types	737
D.9	Data format types	737
D.10	Double information items	738
D.11	Feasibility repair types	743
D.12	License feature	743
D.13	Integer information items.	744
D.14	Information item types	751
D.15	Hot-start type employed by the interior-point optimizers.	751
D.16	Input/output modes	751
D.17	Language selection constants	752
D.18	Long integer information items.	752
D.19	Mark	753
D.20	Continuous mixed-integer solution type	753
D.21	Integer restrictions	753
D.22	Mixed-integer node selection types	754
D.23	MPS file format type	754
D.24	Message keys	754
D.25	Cone types	755
D.26	Objective sense types	755

D.27	On/off	755
D.28	Optimizer types	755
D.29	Ordering strategies	756
D.30	Parameter type	757
D.31	Presolve method.	757
D.32	Problem data items	757
D.33	Problem types	757
D.34	Problem status keys	758
D.35	Response code type	759
D.36	Scaling type	759
D.37	Scaling type	759
D.38	Sensitivity types	760
D.39	Degeneracy strategies	760
D.40	Exploit duplicate columns.	760
D.41	Hot-start type employed by the simplex optimizer	761
D.42	Problem reformulation.	761
D.43	Simplex selection strategy	761
D.44	Solution items	762
D.45	Solution status keys	762
D.46	Solution types	764
D.47	Solve primal or dual form	764
D.48	Status keys	764
D.49	Starting point types	765
D.50	Stream types	765
D.51	Cone types	765
D.52	Transposed matrix.	766
D.53	Triangular part of a symmetric matrix.	766
D.54	Integer values	766
D.55	Variable types	766
D.56	XML writer output mode	766
E	Mosek file formats	767
E.1	The MPS file format	767
E.1.1	MPS file structure	767
E.1.2	Integer variables	777
E.1.3	General limitations	778
E.1.4	Interpretation of the MPS format	778
E.1.5	The free MPS format	778
E.2	The LP file format	778
E.2.1	The sections	779
E.2.2	LP format peculiarities	783
E.2.3	The strict LP format	784
E.2.4	Formatting of an LP file	785
E.3	The OPF format	785
E.3.1	Intended use	786
E.3.2	The file format	786

E.3.3	Parameters section	791
E.3.4	Writing OPF files from MOSEK	791
E.3.5	Examples	792
E.4	The Task format	795
E.5	The XML (OSiL) format	796
E.6	The ORD file format	796
E.6.1	An example	796
E.7	The solution file format	797
E.7.1	The basic and interior solution files	797
E.7.2	The integer solution file	798
F	Problem analyzer examples	799
F.1	air04	799
F.2	arki001	800
F.3	Problem with both linear and quadratic constraints	802
F.4	Problem with both linear and conic constraints	803

Contact information

Phone	+45 3917 9907	
Fax	+45 3917 9823	
WEB	http://www.mosek.com	
Email	sales@mosek.com	Sales, pricing, and licensing.
	support@mosek.com	Technical support, questions and bug reports.
	info@mosek.com	Everything else.
Mail	MOSEK ApS C/O Symbion Science Park Fruebjergvej 3, Box 16 2100 Copenhagen Ø Denmark	

License agreement

Before using the MOSEK software, please read the license agreement available in the distribution at
`mosek\7\license.pdf`

Chapter 1

Changes and new features in MOSEK

The section presents improvements and new features added to MOSEK in version 7.

1.1 Platform support

In Table 1.1 the supported platform and compiler used to build MOSEK shown. Although RedHat is explicitly mentioned as the supported Linux distribution then MOSEK will work on most other variants of Linux. However, the license manager tools requires Linux Standard Base 3 or newer is installed.

1.2 General changes

- The interior-point optimizer has been extended to semi-definite optimization problems. Hence, MOSEK can optimize over the positive semi-definite cone.
- The network detection has been completely redesigned. MOSEK no longer try detect partial networks. The problem must be a pure primal network for the network optimizer to be used.
- The parameter `iparam.objective_sense` has been removed.
- The parameter `iparam.intpnt_num_threads` has been removed. Use the parameter `iparam.num_threads` instead.
- MOSEK now automatically exploit multiple CPUs i.e. the parameter `iparam.num_threads` is set to 0 be default. Note the amount memory that MOSEK uses grows with the number of threads employed.

Platform	OS version	C compiler
linux32x86	Redhat 5 or newer (LSB 3+)	Intel C 13.0 (gcc 4.3, glibc 2.3.4)
linux64x86	RedHat 5 or newer (LSB 3+)	Intel C 13.0 (gcc 4.3, glibc 2.3.4)
osx64x86	OSX 10.7 Lion or newer	Intel C 13.0 (llvm-gcc-4.2)
win32x86	Windows Vista, Server 2003 or newer	Intel C 13.0 (VS 2008)
win64x86	Windows Vista, Server 2003 or newer	Intel C 13.0 (VS 2008)

Interface	Supported versions
Java	Sun Java 1.6+
Microsoft.NET	2.1+
Python 2	2.6+
Python 3	3.1+

Table 1.1: Supported platforms

- The MBT file format has been replaced by a new task format. The new format supports semi-definite optimization.
- the HTML version of the documentation is no longer included in the downloads to save space. It is still available online.
- MOSEK is more restrictive about the allowed names on variables etc. This is in particular the case when writing LP files.
- MOSEK no longer tries to detect the cache sizes and is in general less sensitive to the hardware.
- The parameter `iparam.auto_update_sol_info` is default off. In previous version it was by default on.
- The function `relaxprimal` has been deprecated and replaced by the function `primalrepair`.

1.3 Optimizers

1.3.1 Interior point optimizer

- The factorization routines employed by the interior-point optimizer for linear and conic optimization problems has been completely rewritten. In particular the dense column detection and handling is improved. The factorization routine will also exploit vendor tuned BLAS routines.

1.3.2 The simplex optimizers

- No major changes.

1.3.3 Mixed-integer optimizer

- A new mixed-integer for linear and conic problems has been introduced. It is from run-to-run deterministic and is parallelized. It is particularly suitable for conic problems.

1.4 API changes

- Added support for semidefinite optimization.
- Some clean up has been performed implying some functions have been renamed.

1.5 Optimization toolbox for MATLAB

- A MOSEK equivalent of `bintprog` has been introduced.
- The functionality of the MOSEK version of `linprog` has been improved. It is now possible to employ the simplex optimizer in `linprog`.
- `mosekopt` now accepts a dense A matrix.
- A new method for specification of cones that is more efficient when the problem has many cones has been introduced. The old method is still allowed but is deprecated.
- Support for semidefinite optimization problems has been added to the toolbox.

1.6 License system

- Flexlm has been upgraded to version 11.11.

1.7 Other changes

- The documentation has been improved.

1.8 Interfaces

- Semi-definite optimization capabilities have been added to the optimizer APIs.
- A major clean up has occurred in the optimizer APIs. This should have little effect for most users.
- A new object oriented interface called Fusion has been added. Fusion is available in Java, MATLAB, .NET and Python.
- The AMPL command line tool has been updated to the latest version.

1.9 Platform changes

- 32 bit MAC OSX on Intel x86 (osx32x86) is no longer supported.
- 32 and 64 bit Solaris on Intel x86 (solaris32x86,solaris64x86) is no longer supported.

1.10 Summary of API changes

1.10.1 Parameters

- `MSK_DPAR_CALLBACK_FREQ` removed.
- `MSK_DPAR_MIO_TOL_MAX_CUT_FRAC_RHS` added.
- `MSK_DPAR_MIO_TOL_MIN_CUT_FRAC_RHS` added.
- `MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT` added.
- `MSK_DPAR_PRESOLVE_TOL_ABS_LINDEP` added.
- `MSK_DPAR_PRESOLVE_TOL_LIN_DEP` removed.
- `MSK_DPAR_PRESOLVE_TOL_REL_LINDEP` added.
- `MSK_IPAR_BI_CLEAN_OPTIMIZER` Valid parameter values changed.
- `MSK_IPAR_CACHE_SIZE_L1` removed.
- `MSK_IPAR_CACHE_SIZE_L2` removed.
- `MSK_IPAR_CHECK_TASK_DATA` removed.
- `MSK_IPAR_CPU_TYPE` removed.
- `MSK_IPAR_DATA_CHECK` removed.
- `MSK_IPAR_INTPNT_BASIS` Valid parameter values changed.
- `MSK_IPAR_INTPNT_NUM_THREADS` removed.
- `MSK_IPAR_INTPNT_ORDER_METHOD` Valid parameter values changed.
- `MSK_IPAR_LICENSE_ALLOW_OVERUSE` removed.
- `MSK_IPAR_LICENSE.CACHE.TIME` removed.
- `MSK_IPAR_LICENSE.CHECK.TIME` removed.
- `MSK_IPAR_LOG_EXPAND` added.
- `MSK_IPAR_LOG_FEASREPAIR` removed.

- `MSK_IPAR_LOG_FEAS_REPAIR` added.
- `MSK_IPAR_LP_WRITE_IGNORE_INCOMPATIBLE_ITEMS` removed.
- `MSK_IPAR_MIO_CUT_CG` added.
- `MSK_IPAR_MIO_CUT_CMIR` added.
- `MSK_IPAR_MIO_NODE_OPTIMIZER` Valid parameter values changed.
- `MSK_IPAR_MIO_PROBING_LEVEL` added.
- `MSK_IPAR_MIO_RINS_MAX_NODES` added.
- `MSK_IPAR_MIO_ROOT_OPTIMIZER` Valid parameter values changed.
- `MSK_IPAR_MIO_USE_MULTITHREADED_OPTIMIZER` added.
- `MSK_IPAR_NUM_THREADS` added.
- `MSK_IPAR_OBJECTIVE_SENSE` removed.
- `MSK_IPAR_OPTIMIZER` Valid parameter values changed.
- `MSK_IPAR_PRESOLVE_LINDEP_ABS_WORK_TRH` added.
- `MSK_IPAR_PRESOLVE_LINDEP_REL_WORK_TRH` added.
- `MSK_IPAR_PRESOLVE_LINDEP_WORK_LIM` removed.
- `MSK_IPAR_PRESOLVE_MAX_NUM_REDUCTIONS` added.
- `MSK_IPAR_READ_ADD_ANZ` removed.
- `MSK_IPAR_READ_ADD_CON` removed.
- `MSK_IPAR_READ_ADD_CONE` removed.
- `MSK_IPAR_READ_ADD_QNZ` removed.
- `MSK_IPAR_READ_ADD_VAR` removed.
- `MSK_IPAR_READ_MPS_QUOTED_NAMES` removed.
- `MSK_IPAR_READ_Q_MODE` removed.
- `MSK_IPAR_SIM_NETWORK_DETECT` removed.
- `MSK_IPAR_SIM_NETWORK_DETECT_HOTSTART` removed.
- `MSK_IPAR_SIM_NETWORK_DETECT_METHOD` removed.
- `MSK_IPAR_SOL_QUOTED_NAMES` removed.
- `MSK_IPAR_WRITE_MPS_OBJ_SENSE` removed.
- `MSK_IPAR_WRITE_MPS_QUOTED_NAMES` removed.
- `MSK_IPAR_WRITE_MPS_STRICT` removed.
- `MSK_SPAR_MIO_DEBUG_STRING` added.

1.10.2 Functions

- `MSK_axpy` added.
- `MSK_dot` added.
- `MSK_gemm` added.
- `MSK_gemv` added.
- `MSK_getcodedisc` removed.
- `MSK_licensecleanup` added.
- `MSK_makeenv` changed.
- `MSK_potrf` added.
- `MSK_putcpudefaults` removed.
- `MSK_putlicensedebug` added.
- `MSK_putlicensedefaults` removed.
- `MSK_putlicensepath` added.
- `MSK_putlicensewait` added.
- `MSK_replacefileext` removed.
- `MSK_syeig` added.
- `MSK_syevd` added.
- `MSK_syrk` added.
- `MSK_append` removed.
- `MSK_appendbarvars` added.
- `MSK_appendcons` changed.
- `MSK_appendsparsesymmat` added.
- `MSK_appendvars` changed.
- `MSK_checkdata` removed.
- `MSK_core_append` removed.
- `MSK_core_appendcones` removed.
- `MSK_core_removecones` removed.
- `MSK_exceptiontask` removed.

- `MSK_getaslicetrip` removed.
- `MSK_getavec` removed.
- `MSK_getavecnunz` removed.
- `MSK_getbarsj` added.
- `MSK_getbarxj` added.
- `MSK_getconname64` removed.
- `MSK_getdviolbarvar` added.
- `MSK_getdviolcon` added.
- `MSK_getdviolcones` added.
- `MSK_getdviolvar` added.
- `MSK_getintpntnumthreads` removed.
- `MSK_getmemusagetask64` removed.
- `MSK_getname` removed.
- `MSK_getname64` removed.
- `MSK_getnameapi64` removed.
- `MSK_getnameindex` removed.
- `MSK_getnamelen64` removed.
- `MSK_getobjname64` removed.
- `MSK_getprosta` added.
- `MSK_getpviolbarvar` added.
- `MSK_getpviolcon` added.
- `MSK_getpviolcones` added.
- `MSK_getpviolvar` added.
- `MSK_getskcslice` added.
- `MSK_getskxslice` added.
- `MSK_getslcslice` added.
- `MSK_getslxslice` added.
- `MSK_getsnxslice` added.

- `MSK_getsolsta` added.
- `MSK_getsolutioninfo` added.
- `MSK_getsolutionstatus` removed.
- `MSK_getsolutionstatuskeyslice` removed.
- `MSK_getstrparam64` removed.
- `MSK_getsucslice` added.
- `MSK_getsuxslice` added.
- `MSK_gettaskname64` removed.
- `MSK_getvarname64` removed.
- `MSK_getxcslice` added.
- `MSK_getxxslice` added.
- `MSK_getyslice` added.
- `MSK_makesolutionstatusunknown` removed.
- `MSK_netextraction` removed.
- `MSK_netoptimize` removed.
- `MSK_primalrepair` added.
- `MSK_putacol` added.
- `MSK_putarow` added.
- `MSK_putavec` removed.
- `MSK_putaveclist` removed.
- `MSK_putaveclist64` removed.
- `MSK_putbaraij` added.
- `MSK_putbarcj` added.
- `MSK_putbarsj` added.
- `MSK_putbarvarname` added.
- `MSK_putbarxj` added.
- `MSK_putconbound` added.
- `MSK_putconboundlist` added.

- `MSK_putconename` added.
- `MSK_putconname` added.
- `MSK_putmaxnumanz64` removed.
- `MSK_putmaxnumqnz64` removed.
- `MSK_putname` removed.
- `MSK_putskcslice` added.
- `MSK_putskxslice` added.
- `MSK_putslcslice` added.
- `MSK_putslxslice` added.
- `MSK_putsnxslice` added.
- `MSK_putsucslice` added.
- `MSK_putsuxslice` added.
- `MSK_putvarbound` added.
- `MSK_putvarboundlist` added.
- `MSK_putvarname` added.
- `MSK_putxcslice` added.
- `MSK_putxxslice` added.
- `MSK_putyslice` added.
- `MSK_readtask` added.
- `MSK_reformqcqotosocp` added.
- `MSK_remove` removed.
- `MSK_removecone` removed.
- `MSK_removecones` added.
- `MSK_removecons` added.
- `MSK_removevars` added.
- `MSK_toconic` added.
- `MSK_undefsolution` removed.
- `MSK_unlinkfuncfromtaskstream` changed.
- `MSK_updatesolutioninfo` added.
- `MSK_writetask` added.

Chapter 2

About this manual

This manual covers the general functionality of MOSEK and the usage of the MOSEK C API.

The MOSEK C Application Programming Interface allows access to the full functionality of MOSEK from C and C++.

The C API consists of a header file `mosek.h` and a dynamic link library which an application can link to. This manual covers usage of the dynamic link library.

New users of the MOSEK C API are encouraged to read:

- Chapter 4 on compiling and running the distributed examples.
- The relevant parts of Chapter 5, i.e. at least the general introduction and the linear optimization section.
- Chapter 9 for a set of guidelines about developing, testing, and debugging applications employing MOSEK.

This should introduce most of the data structures and functionality necessary to implement and solve an optimization problem.

Chapter 10 contains general material about the mathematical formulations of optimization problems compatible with MOSEK, as well as common tips and tricks for reformulating problems so that they can be solved by MOSEK.

Hence, Chapter 10 is useful when trying to find a good formulation of a specific model.

More advanced examples of modeling and model debugging are located in

- Chapter 14 which deals with analysis of infeasible problems,
- Chapter 15 about the sensitivity analysis interface, and

Finally, the C API reference material is located in

- Chapter [A](#) which lists all types and functions,
- Chapter [B](#) which lists all available parameters,
- Chapter [C](#) which lists all response codes, and
- Chapter [D](#) which lists all symbolic constants.

Chapter 3

Getting support and help

3.1 MOSEK documentation

For an overview of the available MOSEK documentation please see

`mosek/7/docs/`

in the distribution.

3.2 Bug reporting

If you think MOSEK is solving your problem incorrectly, please contact MOSEK support at

support@mosek.com

providing a detailed description of the problem. MOSEK support may ask for the task file which is produced as follows

```
MSK_writedata(task, "data.task.gz");  
MSK_optimize(task);
```

The task data will then be written to a binary file named `data.task.gz` which is useful when reproducing a problem.

3.3 Additional reading

In this manual it is assumed that the reader is familiar with mathematics and in particular mathematical optimization. Some introduction to linear programming is found in books such as "Linear programming" by Chvátal [1] or "Computer Solution of Linear Programs" by Nazareth [2]. For more theoretical aspects see e.g. "Nonlinear programming: Theory and algorithms" by Bazaraa, Shetty,

and Serali [3]. Finally, the book "Model building in mathematical programming" by Williams [4] provides an excellent introduction to modeling issues in optimization.

Another useful resource is "Mathematical Programming Glossary" available at

<http://glossary.computing.society.informs.org>

Chapter 4

Testing installation and compiling examples

This chapter describes how to verify that MOSEK has been installed and set up correctly, and how to compile, link and execute the C examples distributed with MOSEK.

4.1 Setting up MOSEK

Usage of the MOSEK C API requires a working installation of MOSEK and the installation of a valid license file — see the MOSEK Installation Manual for instructions.

If MOSEK is installed correctly, you should be able to execute the MOSEK command line tool.

4.1.1 Windows: Checking the MOSEK installation

If MOSEK was installed using the automatic installer, the default location is

```
C:\Program Files\mosek\7
```

unless a different path was specified.

To check that MOSEK is installed correctly, please do the following.

- Open a DOS command prompt (DOS box).
- Enter

```
mosek.exe -f
```

This will execute the MOSEK command line tool and print some relevant information. For example:

```
MOSEK Version 7.0.0.15(BETA) (Build date: 2012-10-22 17:23:48)
Copyright (c) 1998-2012 MOSEK ApS, Denmark. WWW: http://www.mosek.com
```

```
Global optimizer version: 8.0.3.171. Global optimizer build date: Oct 11 2012 12:34:07
Barrier Solver Version 7.0.0.015,
Platform Windows 64x86 (B).
Using FLEXlm version: 11.11.
Hostname: 'croston' Hostid: '000c29f1fb49'
```

```
Operating system variables
MOSEKLM_LICENSE_FILE      :
PATH                      :
    C:\Python26\
    C:\Python26\Scripts
    C:\Windows\system32
    C:\Windows
    C:\Windows\System32\Wbem
    C:\Windows\System32\WindowsPowerShell\v1.0\
    x:\windows\64-x86\python24
    x:\windows\64-x86\bin
    c:\Program Files (x86)\Microsoft SQL Server\90\Tools\bin\
    c:\local\bin
    C:\Program Files\Microsoft Windows Performance Toolkit\
```

```
*** No input file specified. No optimization is performed.
```

```
Return code - 0 [MSK_RES_OK]
```

- Verify that
 - The program is executed. If the system was unable to recognize `mosek.exe` as a valid command, then the PATH environment variable has not been set correctly.
 - The MOSEK version printed matches the expected version.
 - The MOSEKLM_LICENSE_PATH points to the correct license file or to the directory containing it. Note that if it points to a directory containing several license files, there is a risk that it will use the wrong one.
 - The PATH contains the path to the correct MOSEK installation.

4.1.2 Linux: Checking the MOSEK installation

There is no automatic installer for MOSEK on Linux, thus installation is performed manually: See MOSEK Installation Manual for details.

To check that MOSEK is installed correctly, please do the following:

- Open a command prompt.
- Enter

```
mosek -f
```

This will execute the MOSEK command line tool and print some relevant information. For example:

```
MOSEK Version 7.0.0.13(BETA) (Build date: 2012-10-11 10:10:32)
Copyright (c) 1998-2012 MOSEK ApS, Denmark. WWW: http://www.mosek.com
Global optimizer version: 8.0.3.132. Global optimizer build date: Sep 17 2012 06:49:16
```

```

Barrier Solver Version 7.0.0.013,
Platform Linux 64x86 (D).
Using FLEXlm version: 11.10.
Hostname: 'skive' Hostid: '"001ec9aecea9 001ec9aeceab"'

Operating system variables
MOSEKLM_LICENSE_FILE      : /home/ulfw/mosekprj/stable/bld/skive/devel/default/intelc-12.0.2/runbin/1000.lic
LD_LIBRARY_PATH           :
                           /home/ulfw/mosekprj/stable/bld/skive/devel/default/intelc-12.0.2/runbin

*** No input file specified. No optimization is performed.

Return code - 0  [MSK_RES_OK]

```

- Verify that
 - The program is executed. If the system was unable to locate `mosek`, then the `PATH` environment variable has not been set correctly.
 - The MOSEK version printed matches the expected version.
 - The `MOSEKLM_LICENSE_PATH` points to the correct license file or to the directory containing it. If it points to a directory containing several license files, there is a risk that it will use the wrong one.
 - The `LD_LIBRARY_PATH` contains the path to the correct MOSEK installation.

4.1.3 MacOSX: Checking the MOSEK installation

There is no automatic installer for MOSEK on Linux. Installation is performed manually: See MOSEK Installation Manual for details.

To check that MOSEK is correctly installed, go through the following steps.

- Open a command prompt.
- Enter

```
mosek -f
```

This will execute the MOSEK command line tool and print some relevant information.

```

MOSEK Version 7.0.0.13(BETA) (Build date: 2012-10-11 10:10:32)
Copyright (c) 1998-2012 MOSEK ApS, Denmark. WWW: http://www.mosek.com
Global optimizer version: 8.0.3.132. Global optimizer build date: Sep 17 2012 06:49:16
Barrier Solver Version 7.0.0.013,
Platform Linux 64x86 (D).
Using FLEXlm version: 11.10.
Hostname: 'skive' Hostid: '"001ec9aecea9 001ec9aeceab"'

Operating system variables
MOSEKLM_LICENSE_FILE      : /home/ulfw/mosekprj/stable/bld/skive/devel/default/intelc-12.0.2/runbin/1000.lic
LD_LIBRARY_PATH           :
                           /home/ulfw/mosekprj/stable/bld/skive/devel/default/intelc-12.0.2/runbin

*** No input file specified. No optimization is performed.

Return code - 0  [MSK_RES_OK]

```

- Verify that
 - The program was executed. If the system was unable to locate `mosek`, then the `PATH` environment variable was not correctly set.
 - The MOSEK version printed matches the expected version.
 - The `MOSEKLM_LICENSE_PATH` points to the correct license file or the directory containing it. If it points to a directory containing several license files, there is a risk that it will use to wrong one.
 - The `DYLD_LIBRARY_PATH` should contain the path to the correct MOSEK installation.

4.2 Compiling and linking

This section demonstrates how to compile, link and run the examples included with MOSEK. The general requirements for any other program linking to the MOSEK library are the same as for these examples.

It is assumed that MOSEK is installed, and that there is a working C compiler on the system.

4.2.1 Compiling under Microsoft Windows

We assume that MOSEK is installed under the default path

```
C:\Program Files\mosek\7
```

and that the platform-specific files are located in

```
C:\Program Files\mosek\7\tools\platform\<platform>\
```

where `<platform>` is `win32x86` (32-bit Windows), `win64x86` (64-bit Windows AMD64 or Intel64).

4.2.1.1 Compiling examples using NMake

The example directory contains makefiles for use with Microsoft NMake. This requires that paths and environment are set up for the Visual Studio tool chain (usually, the submenu containing Visual Studio also contains a *Visual Studio Command Prompt* which does the necessary setup).

To build the examples, open a DOS box and change directory to the examples directory. For Windows with default installation directories, the example directory is

```
C:\Program Files\mosek\7\tools\examples\c
```

The directory contains a makefile named `"Makefile-win64x86"` (or `"Makefile-win32x86"` for 32-bit Windows). To compile all examples, run the command

```
nmake /f Makefile-win64x86 all
```

To only build a single example instead of all examples, replace `"all"` by the corresponding executable name. For example, to build `lo1.exe` type

```
nmake /f Makefile-win64x86 lo1.exe
```


4.2.1.2 Compiling from command line

To compile and run a C example using the MOSEK `dll`, the following files are required:

- `mosek.h`. The header file defining all functions and constants in MOSEK

```
C:\Program Files\mosek\7\tools\platform\win64x86\h\mosek.h
C:\Program Files\mosek\7\tools\platform\win32x86\h\mosek.h
```

- The MOSEK `lib` file located in

```
C:\Program Files\mosek\7\tools\platform\win64x86\bin
C:\Program Files\mosek\7\tools\platform\win32x86\bin
```

The relevant `lib` file is

- on 64-bit Microsoft Windows (AMD x64 or Intel EMT64)
`mosek64_7_0.lib`
- on 32-bit Microsoft Windows
`mosek7_0.lib`

- The MOSEK solver `dll` located in

```
C:\Program Files\mosek\7\tools\platform\win64x86\bin
C:\Program Files\mosek\7\tools\platform\win32x86\bin
```

The relevant `dll` file is

- on 64-bit Microsoft Windows (AMD x64 or Intel EMT64)
`mosek64_7_0.dll`
- on 32-bit Microsoft Windows
`mosek7_0.dll`

Finally, the distributed C examples are located in the directory

```
C:\Program Files\mosek\7\tools\examples\c
```

To compile and execute the distributed example `lo1.c`, do the following:

- Change directory:

```
C:
cd "\Program Files\mosek\7\tools"
```

- Compile the example into an executable `lo1.exe` (we assume that the Visual Studio C compiler `cl.exe` is available). For 64-bit Windows

```
cl examples\c\lo1.c /I platform\win64x86\h /link platform\win64x86\bin\mosek64_7_0.lib
```

For 32-bit Windows:

```
cl examples\c\lo1.c /I platform\win32x86\h /link platform\win32x86\bin\mosek7_0.lib
```

- To run the compiled examples, enter

```
.\lo1.exe
```

4.2.1.3 Adding MOSEK to a Visual Studio Project

The following walk-through is specific for Microsoft Visual Studio 2012, but may work for other versions too.

To compile a project linking to MOSEK in Visual Studio, the following steps are necessary:

- Create a project or open an existing project in Visual Studio.
- In the **Solution Explorer** right-click on the relevant project and select **Properties**. This will open the **Property pages** dialog.
- In the selection box **Configuration:** select **All Configurations**.
- In the tree-view open **Configuration Properties**→ **C/C++**→ **General**.
- In the properties click the **Additional Include Directories** field and select edit.
- Click on the **New Folder** button and write the *full path* to the `mosek.h` header file or browse for the file. For example, for 64-bit Windows enter
`C:\Program Files\mosek\7\tools\platform\win64x86\h`
- Click **OK**.
- Back in the **Property Pages** dialog select from the tree-view **Configuration Properties**→ **Linker**→**Input**.
- In the properties view click in the **Additional Dependencies** field and select edit. This will open the **Additional Dependencies** dialog.
- Add the full path of the MOSEK lib. For example, for 64-bit Windows
`C:\Program Files\mosek\7\tools\platform\win32x86\bin\mosek647.1.lib`
- Click **OK**.
- Back in the **Property Pages** dialog click **OK**.

If you have selected to link with the 64 bit version of MOSEK you must also target the 64-bit platform. To to this follow the steps below:

- Open the **property pages** for that project.
- Click **Configuration Manager** to open the Configuration Manager Dialog Box.
- Click the **Active Solution Platform** list, and then select the **New** option to open the New Solution Platform Dialog Box.
- Click the Type or select the new platform drop-down arrow, and then select the x64 platform.
- Click **OK**. The platform you selected in the preceding step will appear under Active Solution Platform in the Configuration Manager dialog box.

4.2.2 UNIX versions

The `mosek.h` header file, which must be included in all files that uses MOSEK functions, is located in the directory

```
mosek/7/tools/platform/<platform>/h/mosek.h
```

and the MOSEK shared (or dynamic) library is located in

- for 64-bit architectures:

```
mosek/7/tools/platform/<platform>/bin/libmosek64.so.7.1
```

- for 32-bit architectures:

```
mosek/7/tools/platform/<platform>/bin/libmosek.so.7.1
```

where `<platform>` represents a particular UNIX platform, e.g.

- `linux32x86`,
- `linux64x86`,
- `osx64x86`,
- `solaris64x86`.

Programs linking with MOSEK must also be linked to several other libraries. The examples directory

```
mosek/7/tools/examples/c
```

contains a `Makefile-linux64x86` (or `Makefile-linux32x86` for 32-bit linux) that can be used to build the examples.

4.2.2.1 Compiling examples using GNU Make

The example directory contains makefiles for use with GNU Make.

To build the examples, open a prompt and change directory to the examples directory

```
mosek/7/tools/examples/c
```

The directory contains a makefile for GNU Make and gcc. To build all examples, go to the examples and enter

```
make -f Makefile-linux64x86 all
```

or use `Makefile-linux32x86` for 32-bit linux.

To build one example instead of all examples, replace "all" by the corresponding executable name. For example, to build the `lo1` executable type

```
make -f Makefile-linux64x86 lo1
```

4.2.2.2 Example: Linking with GNU C under Linux

The following example shows how to link to the MOSEK shared library on a 64-bit platform:

```
#!/usr/bin/env bash
# The -L. tells gcc to look for shared libraries in the directory ./
# The -lmosek tells gcc to link to the mosek library
# The -Wl,-rpath-link=... tells the linker where to look for other
#     library dependencies.

# Replace -lmosek64 with -lmosek if you are linking on a 32-bit platform.

gcc lo1.c -o lo1 \
  -I../platform/linux64x86/h \
  -L../platform/linux64x86/bin \
  -Wl,-rpath-link=../platform/linux64x86/bin \
  -lmosek64 -pthread

# Run lo1 executable
./lo1
```

Please note that linking with the "-pthread" flag is required by Intel's OpenMP library.

The distribution contains a MOSEK library built without OpenMP; to use this instead of the normal MOSEK library, replace "-lmosek" by "-lmoseknoomp", and "-lmosek64" by "-lmoseknoomp64".

4.2.2.3 Example: Linking with GNU C under Mac OS X

The following example shows how to link to the MOSEK shared library on a 64bit platform:

```
#!/usr/bin/env bash
# The -L. tells gcc to look for shared libraries in the directory ./
# The -lmosek64 tells gcc to link to the mosek library

gcc lo1.c -o lo1 \
  -I../platform/osx64x86/h \
  -L../platform/osx64x86/bin \
  -lmosek64 -pthread

# By default the newly built binary will look for libmosek64 in
# the directory where it was built. Instead make binary look for
# the mosek library in a path relative to the binary:
install_name_tool -change \
  @loader_path/libmosek64.7.0.dylib \
  @loader_path/../../platform/osx64x86/bin/libmosek64.7.0.dylib

# Run lo1 executable
./lo1
```

Please note that linking with the "-pthread" flag is required by Intel's OpenMP library.

Since OpenMP sometimes cause problems, the distribution contains a MOSEK library built without it; to use this instead of the normal MOSEK library, replace "-lmosek64" by "-lmosek64noomp".

4.2.2.4 Example: Linking with Sun C on Solaris

The following example shows how to link to the MOSEK shared library.

```
#!/usr/bin/env bash
# The -L. tells gcc to look for shared libraries in the directory ./
# The -lmosek tells gcc to link to the mosek library
# The -Wl,-rpath-link=... tells the linker where to look for other
#     library dependencies.

# Replace -lmosek64 with -lmosek if you are linking on a 32-bit platform.
cc -m64 -o lo1 lo1.c \
  -L../platform/solaris64x86/bin \
  -I../platform/solaris64x86/h \
  -lmoseknoomp64 -lfsu

# Set environment variable so the MOSEK shared library
# can be located. Must be done at both link time and run time.
# Here we assume that MOSEK was installed in the users home directory.
export LD_LIBRARY_PATH=../platform/solaris64x86/bin

# Run lo1 executable
./lo1
```


Chapter 5

Basic API tutorial

In this chapter the reader will learn how to build a simple application that uses MOSEK.

A number of examples is provided to demonstrate the functionality required for solving linear, conic, semidefinite and quadratic problems as well as mixed integer problems.

Please note that the section on linear optimization also describes most of the basic functionality needed to specify optimization problems. Hence, it is recommended to read [Section 5.2](#) before reading about other optimization problems.

5.1 The basics

A typical program using the MOSEK C interface can be described shortly:

- Create an environment object.
- Set up some environment specific data and initialize the environment object.
- Create a task object.
- Load a problem into the task object.
- Optimize the problem.
- Fetch the result.
- Delete the environment and task objects.

5.1.1 The environment and the task

The first MOSEK related step in any program that employs MOSEK is to create an environment object. The environment contains environment specific data such as information about the license file,

streams for environment messages etc. When this is done one or more task objects can be created. Each task is associated with a single environment and defines a complete optimization problem as well as task message streams and optimization parameters.

In C, the creation of an environment and a task would look something like this:

```

MSKenv_t env = NULL;
MSKtask_t task = NULL;
MSKrescodee res;

/* Create an environment */
res = MSK_makeenv(&env, NULL);

/* You may connect streams and other callbacks to env here */

/* Create a task */
if (res == MSK_RES_OK)
    res = MSK_maketask(env, 0,0, &task);

/* Load a problem into the task, optimize etc. */

MSK_deletetask(&task);
MSK_deleteenv(&env);

```

Please note that multiple tasks should, if possible, share the same environment.

5.1.2 Example: Simple working example

The following simple example shows a working C program which

- creates an environment and a task,
- reads a problem from a file,
- optimizes the problem, and
- writes the solution to a file.

```

1  /* [ simple.c ]
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File:    simple.c
5
6  Purpose: To demonstrate a very simple example using MOSEK by
7           reading a problem file, solving the problem and
8           writing the solution to a file.
9  */
10
11 #include "mosek.h"
12
13 static void MSKAPI printstr(void *handle, MSKCONST char str[])
14 {

```



```

15     printf("%s",str);
16 }
17
18 int main (int argc, char * argv[])
19 {
20     MSKenv_t    env  = NULL;
21     MSKtask_t   task = NULL;
22     MSKrescodee res  = MSK_RES_OK;
23
24     if (argc <= 1)
25     {
26         printf ("Missing argument, syntax is:\n");
27         printf ("  simple inputfile [ solutionfile ]\n");
28     }
29     else
30     {
31         // Create the mosek environment.
32         // The 'NULL' arguments here, are used to specify customized
33         // memory allocators and a memory debug file. These can
34         // safely be ignored for now.
35         res = MSK_makeenv (&env,NULL);
36
37         // Create a task object linked with the environment env.
38         // We create it with 0 variables and 0 constraints initially,
39         // since we do not know the size of the problem.
40         if ( res==MSK_RES_OK )
41             res = MSK_maketask (env, 0, 0, &task);
42
43         // Direct the task log stream to a user specified function
44         if ( res==MSK_RES_OK )
45             res = MSK_linkfunctotaskstream (task, MSK_STREAM_LOG, NULL, printstr);
46
47         // We assume that a problem file was given as the first command
48         // line argument (received in 'argv')
49         if ( res==MSK_RES_OK )
50             res = MSK_readdata (task, argv[1]);
51
52         // Solve the problem
53         if ( res==MSK_RES_OK )
54             res = MSK_optimize (task);
55
56         // Print a summary of the solution.
57         if ( res==MSK_RES_OK )
58             res = MSK_solutionsummary (task, MSK_STREAM_LOG);
59
60         // If an output file was specified, write a solution
61         if ( res==MSK_RES_OK && argc >= 3 )
62         {
63             // We define the output format to be OPF, and tell MOSEK to
64             // leave out parameters and problem data from the output file.
65             MSK_putintparam (task, MSK_IPAR_WRITE_DATA_FORMAT,    MSK_DATA_FORMAT_OP);
66             MSK_putintparam (task, MSK_IPAR_OPF_WRITE_SOLUTIONS,  MSK_ON);
67             MSK_putintparam (task, MSK_IPAR_OPF_WRITE_HINTS,     MSK_OFF);
68             MSK_putintparam (task, MSK_IPAR_OPF_WRITE_PARAMETERS, MSK_OFF);
69             MSK_putintparam (task, MSK_IPAR_OPF_WRITE_PROBLEM,   MSK_OFF);
70
71             res = MSK_writedata (task, argv[2]);
72         }

```

```

73
74     // Delete task and environment
75     MSK_deletetask (&task);
76     MSK_deleteenv (&env);
77 }
78 return res;
79 }

```

5.1.2.1 Reading and writing problems

Use the `MSK_writedata` function to write a problem to a file. By default, when not choosing any specific file format for the parameter `MSK_IPAR_WRITE_DATA_FORMAT`, MOSEK will determine the output file format by the extension of the file name:

```

_____ [ simple.c ] _____
71 res = MSK_writedata (task, argv[2]);
_____

```

Similarly, controlled by `MSK_IPAR_READ_DATA_FORMAT`, the function `MSK_readdata` can read a problem from a file:

```

_____ [ simple.c ] _____
50 res = MSK_readdata (task, argv[1]);
_____

```

5.1.2.2 Working with the problem data

An optimization problem consists of several components; objective, objective sense, constraints, variable bounds etc. Therefore, the interface provides a number of methods to operate on the task specific data, all of which are listed in Section [A](#).

5.1.2.3 Setting parameters

Apart from the problem data, the task contains a number of parameters defining the behavior of MOSEK. For example the `MSK_IPAR_OPTIMIZER` parameter defines which optimizer to use. There are three kinds of parameters in MOSEK

- Integer parameters that can be set with `MSK_putintparam`,
- Double parameters that can be set with `MSK_putdouparam`, and
- string parameters that can be set with `MSK_putstrparam`,

The values for integer parameters are either simple integer values or enum values.

A complete list of all parameters is found in Chapter [B](#).

5.2 Linear optimization

The simplest optimization problem is a purely linear problem. A *linear optimization problem* is a problem of the following form:

Minimize or maximize the objective function

$$\sum_{j=0}^{n-1} c_j x_j + c^f \quad (5.1)$$

subject to the linear constraints

$$l_k^c \leq \sum_{j=0}^{n-1} a_{kj} x_j \leq u_k^c, \quad k = 0, \dots, m-1, \quad (5.2)$$

and the bounds

$$l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1, \quad (5.3)$$

where we have used the problem elements:

m and n

which are the number of constraints and variables respectively,

x

which is the variable vector of length n ,

c

which is a coefficient vector of size n

$$c = \begin{bmatrix} c_0 \\ \vdots \\ c_{n-1} \end{bmatrix},$$

c^f

which is a constant,

A

which is a $m \times n$ matrix of coefficients is given by

$$A = \begin{bmatrix} a_{0,0} & \cdots & a_{0,(n-1)} \\ \vdots & \ddots & \vdots \\ a_{(m-1),0} & \cdots & a_{(m-1),(n-1)} \end{bmatrix},$$

l^c and u^c

which specify the lower and upper bounds on constraints respectively, and

l^x and u^x

which specifies the lower and upper bounds on variables respectively.

Please note the unconventional notation using 0 as the first index rather than 1. Hence, x_0 is the first element in variable vector x . This convention has been adapted from C arrays which are indexed from 0.

5.2.1 Example: Linear optimization

The following is an example of a linear optimization problem:

$$\begin{array}{rcllclclcl} \text{maximize} & 3x_0 & + & 1x_1 & + & 5x_2 & + & 1x_3 & & \\ \text{subject to} & 3x_0 & + & 1x_1 & + & 2x_2 & & & = & 30, \\ & 2x_0 & + & 1x_1 & + & 3x_2 & + & 1x_3 & \geq & 15, \\ & & & 2x_1 & & & + & 3x_3 & \leq & 25, \end{array}$$

having the bounds

$$\begin{array}{rclclcl} 0 & \leq & x_0 & \leq & \infty, \\ 0 & \leq & x_1 & \leq & 10, \\ 0 & \leq & x_2 & \leq & \infty, \\ 0 & \leq & x_3 & \leq & \infty. \end{array}$$

5.2.1.1 Solving the problem

To solve the problem above we go through the following steps:

- Create an environment.
- Create an optimization task.
- Load a problem into the task object.
- Optimization.
- Extracting the solution.

Below we explain each of these steps. For the complete source code see section [5.2.1.2](#).

Create an environment.

Before setting up the optimization problem, a MOSEK environment must be created. All tasks in the program should share the same environment.

```
55  r = MSK_makeenv(&env,NULL);
```

Create an optimization task.

Next, an empty task object is created:

```

59  /* Create the optimization task. */
60  r = MSK_maketask(env,numcon,numvar,&task);
61
62  /* Directs the log task stream to the 'printstr' function. */
63  if ( r==MSK_RES_OK )
64      r = MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);

```

We also connect a call-back function to the task log stream. Messages related to the task are passed to the call-back function. In this case the stream call-back function writes its messages to the standard output stream.

Load a problem into the task object.

Before any problem data can be set, variables and constraints must be added to the problem via calls to the functions **MSK_appendcons** and **MSK_appendvars**.

```

66  /* Append 'numcon' empty constraints.
67   The constraints will initially have no bounds. */
68  if ( r == MSK_RES_OK )
69      r = MSK_appendcons(task,numcon);
70
71  /* Append 'numvar' variables.
72   The variables will initially be fixed at zero (x=0). */
73  if ( r == MSK_RES_OK )
74      r = MSK_appendvars(task,numvar);

```

New variables can now be referenced from other functions with indexes in $0, \dots, \text{numvar} - 1$ and new constraints can be referenced with indexes in $0, \dots, \text{numcon} - 1$. More variables / constraints can be appended later as needed, these will be assigned indexes from $\text{numvar}/\text{numcon}$ and up.

Next step is to set the problem data. We loop over each variable index $j = 0, \dots, \text{numvar} - 1$ calling functions to set problem data. We first set the objective coefficient $c_j = c[j]$ by calling the function **MSK_putcj**.

```

78  /* Set the linear term c_j in the objective.*/
79  if(r == MSK_RES_OK)
80      r = MSK_putcj(task,j,c[j]);

```

The bounds on variables are stored in the arrays

```

46  MSKboundkeye bkr[] = {MSK_BK_LO,      MSK_BK_RA, MSK_BK_LO,      MSK_BK_LO      };
47  double       blx[] = {0.0,           0.0,      0.0,           0.0           };
48  double       bux[] = {+MSK_INFINITY, 10.0,      +MSK_INFINITY, +MSK_INFINITY };

```

and are set with calls to **MSK_putvarbound**.

```

82  /* Set the bounds on variable j.

```

Bound key	Type of bound	Lower bound	Upper bound
MSK_BK_FX	$\dots = l_j$	Finite	Identical to the lower bound
MSK_BK_FR	Free	Minus infinity	Plus infinity
MSK_BK_LO	$l_j \leq \dots$	Finite	Plus infinity
MSK_BK_RA	$l_j \leq \dots \leq u_j$	Finite	Finite
MSK_BK_UP	$\dots \leq u_j$	Minus infinity	Finite

Table 5.1: Interpretation of the bound keys.

```

83  blx[j] <= x_j <= bux[j] /*
84  if(r == MSK_RES_OK)
85      r = MSK_putvarbound(task,
86                          j,          /* Index of variable.*/
87                          bxx[j],     /* Bound key.*/
88                          blx[j],     /* Numerical value of lower bound.*/
89                          bux[j]);    /* Numerical value of upper bound.*/

```

The *Bound key* stored in `bxx` specify the type of the bound according to Table 5.1. For instance `bxx[0]=MSK_BK_LO` means that $x_0 \geq l_0^x$. Finally, the numerical values of the bounds on variables are given by

$$l_j^x = \text{blx}[j]$$

and

$$u_j^x = \text{bux}[j].$$

Recall that in our example the A matrix is given by

$$A = \begin{bmatrix} 3 & 1 & 2 & 0 \\ 2 & 1 & 3 & 1 \\ 0 & 2 & 0 & 3 \end{bmatrix}.$$

This matrix is stored in sparse format in the arrays:

```

30  MSKint32t  ptrb[] = {0, 2, 5, 7},
31              ptre[] = {2, 5, 7, 9},
32              asub[] = { 0, 1,
33                      0, 1, 2,
34                      0, 1,
35                      1, 2};
36  double     aval[] = { 3.0, 2.0,
37                      1.0, 1.0, 2.0,
38                      2.0, 3.0,
39                      1.0, 3.0};

```

The `ptrb`, `ptre`, `asub`, and `aval` arguments define the constraint matrix A in the column ordered sparse format (for details, see Section 5.13.3.2).

Using the function `MSK_putacol` we set column j of A

```

93  r = MSK_putacol(task,
94                      j,                /* Variable (column) index.*/
95                      aptre[j]-aptrb[j], /* Number of non-zeros in column j.*/
96                      asub+aptrb[j],     /* Pointer to row indexes of column j.*/
97                      aval+aptrb[j]);    /* Pointer to Values of column j.*/

```

Alternatively, the same A matrix can be set one row at a time; please see section 5.2.2 for an example.

Finally, the bounds on each constraint are set by looping over each constraint index $i = 0, \dots, \text{numcon} - 1$

```

100 /* Set the bounds on constraints.
101     for i=1, ..., numcon : blc[i] <= constraint i <= buc[i] */
102 for(i=0; i<numcon && r==MSK_RES_OK; ++i)
103     r = MSK_putconbound(task,
104                          i,                /* Index of constraint.*/
105                          bkc[i],          /* Bound key.*/
106                          blc[i],          /* Numerical value of lower bound.*/
107                          buc[i]);         /* Numerical value of upper bound.*/

```

Optimization:

After the problem is set-up the task can be optimized by calling the function `MSK_optimizetrm`.

```

118 r = MSK_optimizetrm(task,&trmcode);

```

Extracting the solution.

After optimizing the status of the solution is examined with a call to `MSK_getsolsta`. If the solution status is reported as `MSK_SOL_STA_OPTIMAL` or `MSK_SOL_STA_NEAR_OPTIMAL` the solution is extracted in the lines below:

```

140 MSK_getxx(task,
141           MSK_SOL_BAS, /* Request the basic solution. */
142           xx);

```

The `MSK_getxx` function obtains the solution. MOSEK may compute several solutions depending on the optimizer employed. In this example the *basic solution* is requested by setting the first argument to `MSK_SOL_BAS`.

5.2.1.2 Source code for lo1

```

1  /*
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3

```

```

4   File:      lol.c
5
6   Purpose:   To demonstrate how to solve a small linear
7               optimization problem using the MOSEK C API,
8               and handle the solver result and the problem
9               solution.
10  */
11
12  #include <stdio.h>
13  #include "mosek.h"
14
15  /* This function prints log output from MOSEK to the terminal. */
16  static void MSKAPI printstr(void *handle,
17                             MSKCONST char str[])
18  {
19      printf("%s",str);
20  } /* printstr */
21
22  int main(int argc,char *argv[])
23  {
24      const MSKint32t numvar = 4,
25                numcon = 3;
26
27      double      c[]      = {3.0, 1.0, 5.0, 1.0};
28      /* Below is the sparse representation of the A
29         matrix stored by column. */
30      MSKint32t   aptrb[] = {0, 2, 5, 7},
31                aptre[] = {2, 5, 7, 9},
32                asub[]  = { 0, 1,
33                          0, 1, 2,
34                          0, 1,
35                          1, 2};
36      double      aval[]  = { 3.0, 2.0,
37                          1.0, 1.0, 2.0,
38                          2.0, 3.0,
39                          1.0, 3.0};
40
41      /* Bounds on constraints. */
42      MSKboundkeye bkc[] = {MSK_BK_FX, MSK_BK_LO,      MSK_BK_UP      };
43      double       blc[] = {30.0,      15.0,      -MSK_INFINITY};
44      double       buc[] = {30.0,      +MSK_INFINITY, 25.0      };
45      /* Bounds on variables. */
46      MSKboundkeye bkx[] = {MSK_BK_LO,      MSK_BK_RA, MSK_BK_LO,      MSK_BK_LO      };
47      double       blx[] = {0.0,      0.0,      0.0,      0.0      };
48      double       bux[] = {+MSK_INFINITY, 10.0,      +MSK_INFINITY, +MSK_INFINITY };
49      MSKenv_t     env = NULL;
50      MSKtask_t    task = NULL;
51      MSKrescodee  r;
52      MSKint32t    i,j;
53
54      /* Create the mosek environment. */
55      r = MSK_makeenv(&env,NULL);
56
57      if ( r==MSK_RES_OK )
58      {
59          /* Create the optimization task. */
60          r = MSK_maketask(env,numcon,numvar,&task);
61

```



```

62      /* Directs the log task stream to the 'printstr' function. */
63      if ( r==MSK_RES_OK )
64          r = MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
65
66      /* Append 'numcon' empty constraints.
67       The constraints will initially have no bounds. */
68      if ( r == MSK_RES_OK )
69          r = MSK_appendcons(task,numcon);
70
71      /* Append 'numvar' variables.
72       The variables will initially be fixed at zero (x=0). */
73      if ( r == MSK_RES_OK )
74          r = MSK_appendvars(task,numvar);
75
76      for(j=0; j<numvar && r == MSK_RES_OK; ++j)
77      {
78          /* Set the linear term c_j in the objective.*/
79          if(r == MSK_RES_OK)
80              r = MSK_putcj(task,j,c[j]);
81
82          /* Set the bounds on variable j.
83             blx[j] <= x_j <= bux[j] */
84          if(r == MSK_RES_OK)
85              r = MSK_putvarbound(task,
86                                  j,          /* Index of variable.*/
87                                  bkc[j],     /* Bound key.*/
88                                  blx[j],     /* Numerical value of lower bound.*/
89                                  bux[j]);    /* Numerical value of upper bound.*/
90
91          /* Input column j of A */
92          if(r == MSK_RES_OK)
93              r = MSK_putacol(task,
94                              j,          /* Variable (column) index.*/
95                              aptre[j]-aptrb[j], /* Number of non-zeros in column j.*/
96                              asub+aptrb[j], /* Pointer to row indexes of column j.*/
97                              aval+aptrb[j]); /* Pointer to Values of column j.*/
98      }
99
100     /* Set the bounds on constraints.
101        for i=1, ...,numcon : blc[i] <= constraint i <= buc[i] */
102     for(i=0; i<numcon && r==MSK_RES_OK; ++i)
103         r = MSK_putconbound(task,
104                             i,          /* Index of constraint.*/
105                             bkc[i],     /* Bound key.*/
106                             blc[i],     /* Numerical value of lower bound.*/
107                             buc[i]);    /* Numerical value of upper bound.*/
108
109     /* Maximize objective function. */
110     if (r == MSK_RES_OK)
111         r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE);
112
113     if ( r==MSK_RES_OK )
114     {
115         MSKrescodee trmcode;
116
117         /* Run optimizer */
118         r = MSK_optimizetrm(task,&trmcode);
119

```

```

120      /* Print a summary containing information
121         about the solution for debugging purposes. */
122      MSK_solutionsummary (task,MSK_STREAM_LOG);
123
124      if ( r==MSK_RES_OK )
125      {
126          MSKsolstae solsta;
127
128          if ( r==MSK_RES_OK )
129              r = MSK_getsolsta (task,
130                               MSK_SOL_BAS,
131                               &solsta);
132
133          switch(solsta)
134          {
135              case MSK_SOL_STA_OPTIMAL:
136              case MSK_SOL_STA_NEAR_OPTIMAL:
137              {
138                  double *xx = (double*) calloc(numvar,sizeof(double));
139                  if ( xx )
140                  {
141                      MSK_getxx(task,
142                               MSK_SOL_BAS,      /* Request the basic solution. */
143                               xx);
144
145                      printf("Optimal primal solution\n");
146                      for(j=0; j<numvar; ++j)
147                          printf("x[%d]: %e\n",j,xx[j]);
148
149                      free(xx);
150                  }
151                  else
152                      r = MSK_RES_ERR_SPACE;
153
154                  break;
155              }
156              case MSK_SOL_STA_DUAL_INFEAS_CER:
157              case MSK_SOL_STA_PRIM_INFEAS_CER:
158              case MSK_SOL_STA_NEAR_DUAL_INFEAS_CER:
159              case MSK_SOL_STA_NEAR_PRIM_INFEAS_CER:
160                  printf("Primal or dual infeasibility certificate found.\n");
161                  break;
162              case MSK_SOL_STA_UNKNOWN:
163              {
164                  char symname[MSK_MAX_STR_LEN];
165                  char desc[MSK_MAX_STR_LEN];
166
167                  /* If the solutions status is unknown, print the termination code
168                     indicating why the optimizer terminated prematurely. */
169
170                  MSK_getcodedesc(trmcode,
171                                 symname,
172                                 desc);
173
174                  printf("The solution status is unknown.\n");
175                  printf("The optimizer terminated with code: %s\n",symname);
176                  break;
177              }
178          }
179      }
180      default:

```

```

178         printf("Other solution status.\n");
179         break;
180     }
181 }
182 }
183
184 if (r != MSK_RES_OK)
185 {
186     /* In case of an error print error code and description. */
187     char symname[MSK_MAX_STR_LEN];
188     char desc[MSK_MAX_STR_LEN];
189
190     printf("An error occurred while optimizing.\n");
191     MSK_getcodedesc (r,
192                     symname,
193                     desc);
194     printf("Error %s - '%s'\n", symname, desc);
195 }
196
197 /* Delete the task and the associated data. */
198 MSK_deletetask(&task);
199 }
200
201 /* Delete the environment and the associated data. */
202 MSK_deleteenv(&env);
203
204 return r;
205 }

```

5.2.2 Row-wise input

In the previous example the A matrix is set one column at a time. Alternatively the same matrix can be set one row at a time or the two methods can be mixed as in the example in section 5.10. The following example show how to set the A matrix by rows.

```

1  /*
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File:      lo2.c
5
6  Purpose:   To demonstrate how to solve a small linear
7             optimization problem using the MOSEK C API,
8             and handle the solver result and the problem
9             solution.
10 */
11
12 #include <stdio.h>
13 #include "mosek.h"
14
15 /* This function prints log output from MOSEK to the terminal. */
16 static void MSKAPI printstr(void *handle,
17                             MSKCONST char str[])
18 {
19     printf("%s", str);

```

```

20 } /* printstr */
21
22 int main(int argc, char *argv[])
23 {
24     const int numvar = 4,
25             numcon = 3;
26
27     double c[] = {3.0, 1.0, 5.0, 1.0};
28     /* Below is the sparse representation of the A
29        matrix stored by row. */
30     MSKlidx_t aptrb[] = {0, 3, 7};
31     MSKlidx_t aptre[] = {3, 7, 9};
32     MSKidx_t asub[] = { 0,1,2,
33                       0,1,2,3,
34                       1,3};
35     double aval[] = { 3.0, 1.0, 2.0,
36                     2.0, 1.0, 3.0, 1.0,
37                     2.0, 3.0};
38
39     /* Bounds on constraints. */
40     MSKboundkey bkc[] = {MSK_BK_FX, MSK_BK_LO, MSK_BK_UP };
41     double blc[] = {30.0, 15.0, -MSK_INFINITY};
42     double buc[] = {30.0, +MSK_INFINITY, 25.0 };
43     /* Bounds on variables. */
44     MSKboundkey bkc[] = {MSK_BK_LO, MSK_BK_RA, MSK_BK_LO, MSK_BK_LO };
45     double blx[] = {0.0, 0.0, 0.0, 0.0 };
46     double bux[] = {+MSK_INFINITY, 10.0, +MSK_INFINITY, +MSK_INFINITY };
47     MSKenv_t env = NULL;
48     MSKtask_t task = NULL;
49     MSKrescode_t r;
50     MSKidx_t i,j;
51
52     /* Create the mosek environment. */
53     r = MSK_makeenv(&env, NULL);
54
55     if ( r==MSK_RES_OK )
56     {
57         /* Create the optimization task. */
58         r = MSK_maketask(env, numcon, numvar, &task);
59
60         /* Directs the log task stream to the 'printstr' function. */
61         if ( r==MSK_RES_OK )
62             r = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);
63
64         /* Append 'numcon' empty constraints.
65            The constraints will initially have no bounds. */
66         if ( r == MSK_RES_OK )
67             r = MSK_appendcons(task, numcon);
68
69         /* Append 'numvar' variables.
70            The variables will initially be fixed at zero (x=0). */
71         if ( r == MSK_RES_OK )
72             r = MSK_appendvars(task, numvar);
73
74         for(j=0; j<numvar && r == MSK_RES_OK; ++j)
75         {
76             /* Set the linear term c_j in the objective.*/
77             if(r == MSK_RES_OK)

```

```

78     r = MSK_putcj(task,j,c[j]);
79
80     /* Set the bounds on variable j.
81     blx[j] <= x_j <= bux[j] */
82     if(r == MSK_RES_OK)
83         r = MSK_putvarbound(task,
84                               j,          /* Index of variable.*/
85                               bkc[j],     /* Bound key.*/
86                               blx[j],     /* Numerical value of lower bound.*/
87                               bux[j]);    /* Numerical value of upper bound.*/
88     }
89
90     /* Set the bounds on constraints.
91     for i=1, ..., numcon : blc[i] <= constraint i <= buc[i] */
92     for(i=0; i<numcon && r==MSK_RES_OK; ++i)
93     {
94         r = MSK_putconbound(task,
95                               i,          /* Index of constraint.*/
96                               bkc[i],     /* Bound key.*/
97                               blc[i],     /* Numerical value of lower bound.*/
98                               buc[i]);    /* Numerical value of upper bound.*/
99
100        /* Input row i of A */
101        if(r == MSK_RES_OK)
102            r = MSK_putarow(task,
103                            i,          /* Row index.*/
104                            aptre[i]-aptrb[i], /* Number of non-zeros in row i.*/
105                            asub+aptrb[i], /* Pointer to column indexes of row i.*/
106                            aval+aptrb[i]); /* Pointer to values of row i.*/
107    }
108
109    /* Maximize objective function. */
110    if (r == MSK_RES_OK)
111        r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE);
112
113    if ( r==MSK_RES_OK )
114    {
115        MSKrescodee trmcode;
116
117        /* Run optimizer */
118        r = MSK_optimizetrm(task,&trmcode);
119
120        /* Print a summary containing information
121        about the solution for debugging purposes. */
122        MSK_solutionsummary (task,MSK_STREAM_LOG);
123
124        if ( r==MSK_RES_OK )
125        {
126            MSKsolstae solsta;
127
128            if (r == MSK_RES_OK)
129                r = MSK_getsolsta (task,MSK_SOL_BAS,&solsta);
130            switch(solsta)
131            {
132                case MSK_SOL_STA_OPTIMAL:
133                case MSK_SOL_STA_NEAR_OPTIMAL:
134                {
135                    double **xx = (double*) calloc(numvar,sizeof(double));

```

```

136         if ( xx )
137         {
138             MSK_getxx(task,
139                     MSK_SOL_BAS,    /* Request the basic solution. */
140                     xx);
141
142             printf("Optimal primal solution\n");
143             for(j=0; j<numvar; ++j)
144                 printf("x[%d]: %e\n",j,xx[j]);
145         }
146         else
147         {
148             r = MSK_RES_ERR_SPACE;
149         }
150
151         free(xx);
152         break;
153     }
154     case MSK_SOL_STA_DUAL_INFEAS_CER:
155     case MSK_SOL_STA_PRIM_INFEAS_CER:
156     case MSK_SOL_STA_NEAR_DUAL_INFEAS_CER:
157     case MSK_SOL_STA_NEAR_PRIM_INFEAS_CER:
158         printf("Primal or dual infeasibility certificate found.\n");
159         break;
160     case MSK_SOL_STA_UNKNOWN:
161     {
162         char symname[MSK_MAX_STR_LEN];
163         char desc[MSK_MAX_STR_LEN];
164
165         /* If the solutions status is unknown, print the termination code
166            indicating why the optimizer terminated prematurely. */
167
168         MSK_getcodedesc(trmcode,
169                         symname,
170                         desc);
171
172         printf("The solution status is unknown.\n");
173         printf("The optimizer terminated with code: %s\n",symname);
174         break;
175     }
176     default:
177         printf("Other solution status.\n");
178         break;
179 }
180 }
181 }
182
183 if (r != MSK_RES_OK)
184 {
185     /* In case of an error print error code and description. */
186     char symname[MSK_MAX_STR_LEN];
187     char desc[MSK_MAX_STR_LEN];
188
189     printf("An error occurred while optimizing.\n");
190     MSK_getcodedesc (r,
191                     symname,
192                     desc);
193     printf("Error %s - '%s'\n",symname,desc);

```

```

194     }
195
196     /* Delete the task and the associated data. */
197     MSK_deletetask(&task);
198 }
199
200 /* Delete the environment and the associated data. */
201 MSK_deleteenv(&env);
202
203 return r;
204 }

```

5.3 Conic quadratic optimization

Conic optimization is a generalization of linear optimization, allowing constraints of the type

$$x^t \in \mathcal{C}_t,$$

where x^t is a subset of the problem variables and \mathcal{C}_t is a convex cone. Actually, since the set \mathbb{R}^n of real numbers is also a convex cone, all variables can in fact be partitioned into subsets belonging to separate convex cones, simply stated $x \in \mathcal{C}$.

MOSEK can solve conic quadratic optimization problems of the form

$$\begin{aligned}
 & \text{minimize} && c^T x + c^f \\
 & \text{subject to} && l^c \leq Ax \leq u^c, \\
 & && l^x \leq x \leq u^x, \\
 & && x \in \mathcal{C},
 \end{aligned} \tag{5.4}$$

where the domain restriction, $x \in \mathcal{C}$, implies that all variables are partitioned into convex cones

$$x = (x^0, x^1, \dots, x^{p-1}), \text{ with } x^t \in \mathcal{C}_t \subseteq \mathbb{R}^{n_t}.$$

For convenience, the user only specify subsets of variables x^t belonging to cones \mathcal{C}_t different from the set \mathbb{R}^{n_t} of real numbers. These cones can be a:

- Quadratic cone:

$$\mathcal{Q}_n = \left\{ x \in \mathbb{R}^n : x_0 \geq \sqrt{\sum_{j=1}^{n-1} x_j^2} \right\}.$$

- Rotated quadratic cone:

$$\mathcal{Q}_n^r = \left\{ x \in \mathbb{R}^n : 2x_0x_1 \geq \sum_{j=2}^{n-1} x_j^2, \ x_0 \geq 0, \ x_1 \geq 0 \right\}.$$

From these definition it follows that

$$(x_4, x_0, x_2) \in \mathcal{Q}_3,$$

is equivalent to

$$x_4 \geq \sqrt{x_0^2 + x_2^2}.$$

Furthermore, each variable may belong to one cone at most. The constraint $x_i - x_j = 0$ would however allow x_i and x_j to belong to different cones with same effect.

5.3.1 Example: Conic quadratic optimization

The problem

$$\begin{aligned} & \text{minimize} && x_3 + x_4 + x_5 \\ & \text{subject to} && x_0 + x_1 + 2x_2 = 1, \\ & && x_0, x_1, x_2 \geq 0, \\ & && x_3 \geq \sqrt{x_0^2 + x_1^2}, \\ & && 2x_4x_5 \geq x_2^2. \end{aligned} \tag{5.5}$$

is an example of a conic quadratic optimization problem. The problem includes a set of linear constraints, a quadratic cone and a rotated quadratic cone.

5.3.1.1 Source code

```

1  /*
2      Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4      File:      cqo1.c
5
6      Purpose:   To demonstrate how to solve a small conic quadratic
7                  optimization problem using the MOSEK API.
8  */
9
10 #include <stdio.h>
11
12 #include "mosek.h" /* Include the MOSEK definition file. */
13
14 static void MSKAPI printstr(void *handle,
15                             MSKCONST char str[])
16 {
17     printf("%s", str);
18 } /* printstr */
19
20 int main(int argc, char *argv[])
21 {
22     MSKrescodee r;
```



```

23
24     const MSKint32t numvar = 6,
25               numcon = 1;
26
27     MSKboundkeye bkc[] = { MSK_BK_FX };
28     double      blc[] = { 1.0 };
29     double      buc[] = { 1.0 };
30
31     MSKboundkeye bkc[] = {MSK_BK_LO,
32                           MSK_BK_LO,
33                           MSK_BK_LO,
34                           MSK_BK_FR,
35                           MSK_BK_FR,
36                           MSK_BK_FR};
37     double      blx[] = {0.0,
38                          0.0,
39                          0.0,
40                          -MSK_INFINITY,
41                          -MSK_INFINITY,
42                          -MSK_INFINITY};
43     double      bux[] = {+MSK_INFINITY,
44                          +MSK_INFINITY,
45                          +MSK_INFINITY,
46                          +MSK_INFINITY,
47                          +MSK_INFINITY,
48                          +MSK_INFINITY};
49
50     double      c[] = {0.0,
51                       0.0,
52                       0.0,
53                       1.0,
54                       1.0,
55                       1.0};
56
57     MSKint32t   aptrb[] = {0, 1, 2, 3, 3, 3},
58                   aptre[] = {1, 2, 3, 3, 3, 3},
59                   asub[] = {0, 0, 0, 0};
60     double      aval[] = {1.0, 1.0, 2.0};
61
62
63     MSKint32t   i,j,csub[3];
64
65     MSKenv_t     env = NULL;
66     MSKtask_t    task = NULL;
67
68     /* Create the mosek environment. */
69     r = MSK_makeenv(&env,NULL);
70
71     if ( r==MSK_RES_OK )
72     {
73         /* Create the optimization task. */
74         r = MSK_maketask(env,numcon,numvar,&task);
75
76         if ( r==MSK_RES_OK )
77         {
78             MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
79
80             /* Append 'numcon' empty constraints.

```

```

81 The constraints will initially have no bounds. */
82 if ( r == MSK_RES_OK )
83     r = MSK_appendcons(task,numcon);
84
85 /* Append 'numvar' variables.
86 The variables will initially be fixed at zero (x=0). */
87 if ( r == MSK_RES_OK )
88     r = MSK_appendvars(task,numvar);
89
90 for(j=0; j<numvar && r == MSK_RES_OK; ++j)
91 {
92     /* Set the linear term c_j in the objective.*/
93     if(r == MSK_RES_OK)
94         r = MSK_putcj(task,j,c[j]);
95
96     /* Set the bounds on variable j.
97     blx[j] <= x_j <= bux[j] */
98     if(r == MSK_RES_OK)
99         r = MSK_putvarbound(task,
100                                j,          /* Index of variable.*/
101                                bkc[j],     /* Bound key.*/
102                                blc[j],     /* Numerical value of lower bound.*/
103                                buc[j]);    /* Numerical value of upper bound.*/
104
105     /* Input column j of A */
106     if(r == MSK_RES_OK)
107         r = MSK_putacol(task,
108                                j,          /* Variable (column) index.*/
109                                aptre[j]-aptrb[j], /* Number of non-zeros in column j.*/
110                                asub+aptrb[j], /* Pointer to row indexes of column j.*/
111                                aval+aptrb[j]); /* Pointer to Values of column j.*/
112
113 }
114
115 /* Set the bounds on constraints.
116 for i=1, ..., numcon : blc[i] <= constraint i <= buc[i] */
117 for(i=0; i<numcon && r==MSK_RES_OK; ++i)
118     r = MSK_putconbound(task,
119                            i,          /* Index of constraint.*/
120                            bkc[i],     /* Bound key.*/
121                            blc[i],     /* Numerical value of lower bound.*/
122                            buc[i]);    /* Numerical value of upper bound.*/
123
124 if ( r==MSK_RES_OK )
125 {
126     /* Append the first cone. */
127     csub[0] = 3;
128     csub[1] = 0;
129     csub[2] = 1;
130     r = MSK_appendcone(task,
131                        MSK_CT_QUAD,
132                        0.0, /* For future use only, can be set to 0.0 */
133                        3,
134                        csub);
135 }
136
137 if ( r==MSK_RES_OK )
138 {

```

```

139      /* Append the second cone. */
140      csub[0] = 4;
141      csub[1] = 5;
142      csub[2] = 2;
143
144      r = MSK_appendcone(task,
145                          MSK_CT_RQUAD,
146                          0.0,
147                          3,
148                          csub);
149  }
150
151  if ( r==MSK_RES_OK )
152  {
153      MSKrescodee trmcode;
154
155      /* Run optimizer */
156      r = MSK_optimizetrm(task,&trmcode);
157
158
159      /* Print a summary containing information
160       about the solution for debugging purposes*/
161      MSK_solutionsummary (task,MSK_STREAM_MSG);
162
163      if ( r==MSK_RES_OK )
164      {
165          MSKsolstae solsta;
166
167          MSK_getsolsta (task,MSK_SOL_ITR,&solsta);
168
169          switch(solsta)
170          {
171              case MSK_SOL_STA_OPTIMAL:
172              case MSK_SOL_STA_NEAR_OPTIMAL:
173                  {
174                      double *xx = NULL;
175
176                      xx = calloc(numvar,sizeof(double));
177                      if ( xx )
178                      {
179                          MSK_getxx (task,
180                                      MSK_SOL_ITR,    /* Request the interior solution. */
181                                      xx);
182
183                          printf("Optimal primal solution\n");
184                          for(j=0; j<numvar; ++j)
185                              printf("x[%d]: %e\n",j,xx[j]);
186                      }
187                      else
188                      {
189                          r = MSK_RES_ERR_SPACE;
190                      }
191                      free(xx);
192                  }
193                  break;
194              case MSK_SOL_STA_DUAL_INFEAS_CER:
195              case MSK_SOL_STA_PRIM_INFEAS_CER:
196              case MSK_SOL_STA_NEAR_DUAL_INFEAS_CER:

```

```

197         case MSK_SOL_STA_NEAR_PRIM_INFEAS_CER:
198             printf("Primal or dual infeasibility certificate found.\n");
199             break;
200         case MSK_SOL_STA_UNKNOWN:
201             printf("The status of the solution could not be determined.\n");
202             break;
203         default:
204             printf("Other solution status.");
205             break;
206     }
207 }
208 else
209 {
210     printf("Error while optimizing.\n");
211 }
212 }
213
214 if (r != MSK_RES_OK)
215 {
216     /* In case of an error print error code and description. */
217     char symname[MSK_MAX_STR_LEN];
218     char desc[MSK_MAX_STR_LEN];
219
220     printf("An error occurred while optimizing.\n");
221     MSK_getcodedesc (r,
222                     symname,
223                     desc);
224     printf("Error %s - '%s'\n", symname, desc);
225 }
226 }
227 /* Delete the task and the associated data. */
228 MSK_deletetask(&task);
229 }
230
231 /* Delete the environment and the associated data. */
232 MSK_deleteenv(&env);
233
234 return ( r );
235 } /* main */

```

5.3.1.2 Source code comments

The only new function introduced in the example is `MSK_appendcone`, which is called here:

```

130 r = MSK_appendcone(task,
131                   MSK_CT_QUAD,
132                   0.0, /* For future use only, can be set to 0.0 */
133                   3,
134                   csub);

```

The first argument selects the type of quadratic cone. Either `MSK_CT_QUAD` for a *quadratic cone* or `MSK_CT_RQUAD` for a *rotated quadratic cone*. The cone parameter 0.0 is currently not used by MOSEK — simply passing 0.0 will work.

The next argument denotes the number of variables in the cone, in this case 3, and the last argument is a list of indexes of the variables in the cone.

5.4 Semidefinite optimization

Semidefinite optimization is a generalization of conic quadratic optimization, allowing the use of matrix variables belonging to the convex cone of positive semidefinite matrices

$$\mathcal{S}_r^+ = \{X \in \mathcal{S}_r : z^T X z \geq 0, \forall z \in \mathbb{R}^r\},$$

where \mathcal{S}_r is the set of $r \times r$ real-valued symmetric matrices.

MOSEK can solve semidefinite optimization problems of the form

$$\begin{aligned} \text{minimize} \quad & \sum_{j=0}^{n-1} c_j x_j + \sum_{j=0}^{p-1} \langle \overline{C}_j, \overline{X}_j \rangle + c^f \\ \text{subject to} \quad & l_i^c \leq \sum_{j=0}^{n-1} a_{ij} x_j + \sum_{j=0}^{p-1} \langle \overline{A}_{ij}, \overline{X}_j \rangle \leq u_i^c, \quad i = 0, \dots, m-1, \\ & l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1, \\ & x \in \mathcal{C}, \overline{X}_j \in \mathcal{S}_{r_j}^+, \quad j = 0, \dots, p-1 \end{aligned}$$

where the problem has p symmetric positive semidefinite variables $\overline{X}_j \in \mathcal{S}_{r_j}^+$ of dimension r_j with symmetric coefficient matrices $\overline{C}_j \in \mathcal{S}_{r_j}$ and $\overline{A}_{i,j} \in \mathcal{S}_{r_j}$. We use standard notation for the matrix inner product, i.e., for $A, B \in \mathbb{R}^{m \times n}$ we have

$$\langle A, B \rangle := \sum_{i=0}^{m-1} \sum_{j=0}^{n-1} A_{ij} B_{ij}.$$

5.4.1 Example: Semidefinite optimization

The problem

$$\begin{aligned}
& \text{minimize} && \left\langle \begin{bmatrix} 2 & 1 & 0 \\ 1 & 2 & 1 \\ 0 & 1 & 2 \end{bmatrix}, \bar{X} \right\rangle + x_0 \\
& \text{subject to} && \left\langle \begin{bmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{bmatrix}, \bar{X} \right\rangle + x_0 &= 1, \\
& && \left\langle \begin{bmatrix} 1 & 1 & 1 \\ 1 & 1 & 1 \\ 1 & 1 & 1 \end{bmatrix}, \bar{X} \right\rangle + x_1 + x_2 &= 1/2, \\
& && x_0 \geq \sqrt{x_1^2 + x_2^2}, \\
& && \bar{X} \succeq 0,
\end{aligned} \tag{5.6}$$

is a mixed semidefinite and conic quadratic programming problem with a 3-dimensional semidefinite variable

$$\bar{X} = \begin{bmatrix} \bar{x}_{00} & \bar{x}_{10} & \bar{x}_{20} \\ \bar{x}_{10} & \bar{x}_{11} & \bar{x}_{21} \\ \bar{x}_{20} & \bar{x}_{21} & \bar{x}_{22} \end{bmatrix} \in \mathcal{S}_3^+,$$

and a conic quadratic variable $(x_0, x_1, x_2) \in \mathcal{Q}_3$. The objective is to minimize

$$2(\bar{x}_{00} + \bar{x}_{10} + \bar{x}_{11} + \bar{x}_{21} + \bar{x}_{22}) + x_0,$$

subject to the two linear constraints

$$\bar{x}_{00} + \bar{x}_{11} + \bar{x}_{22} + x_0 = 1,$$

and

$$\bar{x}_{00} + \bar{x}_{11} + \bar{x}_{22} + 2(\bar{x}_{10} + \bar{x}_{20} + \bar{x}_{21}) + x_1 + x_2 = 1/2.$$

5.4.1.1 Source code

```

1  /*
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File:      sdo1.c
5
6  Purpose:   Solves the following small semidefinite optimization problem
7             using the MOSEK API.
8
9  minimize   Tr [2, 1, 0; 1, 2, 1; 0, 1, 2]*X + x0
10
11  subject to Tr [1, 0, 0; 0, 1, 0; 0, 0, 1]*X + x0          = 1
12             Tr [1, 1, 1; 1, 1, 1; 1, 1, 1]*X          + x1 + x2 = 0.5
13             (x0,x1,x2) \in Q,  X \in PSD
14  */

```

```

15
16
17 #include <stdio.h>
18
19 #include "mosek.h"      /* Include the MOSEK definition file. */
20
21 #define NUMCON    2      /* Number of constraints. */
22 #define NUMVAR    3      /* Number of conic quadratic variables */
23 #define NUMANZ    3      /* Number of non-zeros in A */
24 #define NUMBARVAR 1      /* Number of semidefinite variables */
25
26 static void MSKAPI printstr(void *handle,
27                             MSKCONST char str[])
28 {
29     printf("%s",str);
30 } /* printstr */
31
32 int main(int argc,char *argv[])
33 {
34     MSKrescodee r;
35
36     MSKint32t    DIMBARVAR[] = {3};          /* Dimension of semidefinite cone */
37     MSKint64t    LENBARVAR[] = {3*(3+1)/2}; /* Number of scalar SD variables */
38
39     MSKboundkeye bkc[] = { MSK_BK_FX, MSK_BK_FX };
40     double       blc[] = { 1.0, 0.5 };
41     double       buc[] = { 1.0, 0.5 };
42
43     MSKint32t    barc_i[] = {0, 1, 1, 2, 2},
44                 barc_j[] = {0, 0, 1, 1, 2};
45     double       barc_v[] = {2.0, 1.0, 2.0, 1.0, 2.0};
46
47     MSKint32t    aptrb[] = {0, 1},
48                 aptre[] = {1, 3},
49                 asub[] = {0, 1, 2}; /* column subscripts of A */
50     double       aval[] = {1.0, 1.0, 1.0};
51
52     MSKint32t    bara_i[] = {0, 1, 2, 0, 1, 2, 1, 2, 2},
53                 bara_j[] = {0, 1, 2, 0, 0, 0, 1, 1, 2};
54     double       bara_v[] = {1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0};
55     MSKint32t    conesub[] = {0, 1, 2};
56
57     MSKint32t    i,j;
58     MSKint64t    idx;
59     double       falpha = 1.0;
60
61     double       *xx;
62     double       *barx;
63     MSKenv_t     env = NULL;
64     MSKtask_t    task = NULL;
65
66     /* Create the mosek environment. */
67     r = MSK_makeenv(&env,NULL);
68
69     if ( r==MSK_RES_OK )
70     {
71         /* Create the optimization task. */
72         r = MSK_maketask(env,NUMCON,0,&task);

```

```

73
74     if ( r==MSK_RES_OK )
75     {
76         MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
77
78         /* Append 'NUMCON' empty constraints.
79          The constraints will initially have no bounds. */
80         if ( r == MSK_RES_OK )
81             r = MSK_appendcons(task,NUMCON);
82
83         /* Append 'NUMVAR' variables.
84          The variables will initially be fixed at zero (x=0). */
85         if ( r == MSK_RES_OK )
86             r = MSK_appendvars(task,NUMVAR);
87
88         /* Append 'NUMBARVAR' semidefinite variables. */
89         if ( r == MSK_RES_OK ) {
90             r = MSK_appendbarvars(task, NUMBARVAR, DIMBARVAR);
91         }
92
93         /* Optionally add a constant term to the objective. */
94         if ( r ==MSK_RES_OK )
95             r = MSK_putcfix(task,0.0);
96
97         /* Set the linear term c_j in the objective.*/
98         if ( r ==MSK_RES_OK )
99             r = MSK_putcj(task,0,1.0);
100
101         for (j=0; j<NUMVAR && r==MSK_RES_OK; ++j)
102             r = MSK_putvarbound( task,
103                                 j,
104                                 MSK_BK_FR,
105                                 -MSK_INFINITY,
106                                 MSK_INFINITY);
107
108         /* Set the linear term barc_j in the objective.*/
109         if ( r == MSK_RES_OK )
110             r = MSK_appendsparsesymmat(task,
111                                     DIMBARVAR[0],
112                                     5,
113                                     barc_i,
114                                     barc_j,
115                                     barc_v,
116                                     &idx);
117
118         if ( r == MSK_RES_OK )
119             r = MSK_putbarcj(task, 0, 1, &idx, &falpha);
120
121         /* Set the bounds on constraints.
122          for i=1, ...,NUMCON : blc[i] <= constraint i <= buc[i] */
123         for(i=0; i<NUMCON && r==MSK_RES_OK; ++i)
124             r = MSK_putconbound(task,
125                                 i,          /* Index of constraint.*/
126                                 bkc[i],     /* Bound key.*/
127                                 blc[i],     /* Numerical value of lower bound.*/
128                                 buc[i]);    /* Numerical value of upper bound.*/
129
130         /* Input A row by row */

```



```

131     for (i=0; i<NUMCON && r==MSK_RES_OK; ++i)
132         r = MSK_putarow(task,
133             i,
134             aptre[i] - aptrb[i],
135             asub      + aptrb[i],
136             aval      + aptrb[i]);
137
138     /* Append the conic quadratic cone */
139     if ( r==MSK_RES_OK )
140         r = MSK_appendcone(task,
141             MSK_CT_QUAD,
142             0.0,
143             3,
144             conesub);
145
146     /* Add the first row of barA */
147     if ( r==MSK_RES_OK )
148         r = MSK_appendsparsesymmat(task,
149             DIMBARVAR[0],
150             3,
151             bara_i,
152             bara_j,
153             bara_v,
154             &idx);
155
156     if ( r==MSK_RES_OK )
157         r = MSK_putbaraij(task, 0, 0, 1, &idx, &falpha);
158
159     /* Add the second row of barA */
160     if ( r==MSK_RES_OK )
161         r = MSK_appendsparsesymmat(task,
162             DIMBARVAR[0],
163             6,
164             bara_i + 3,
165             bara_j + 3,
166             bara_v + 3,
167             &idx);
168
169     if ( r==MSK_RES_OK )
170         r = MSK_putbaraij(task, 1, 0, 1, &idx, &falpha);
171
172     if ( r==MSK_RES_OK )
173     {
174         MSKrescodee trmcode;
175
176         /* Run optimizer */
177         r = MSK_optimizetrm(task,&trmcode);
178
179         /* Print a summary containing information
180            about the solution for debugging purposes*/
181         MSK_solutionsummary (task,MSK_STREAM_MSG);
182
183         if ( r==MSK_RES_OK )
184         {
185             MSKsolstae solsta;
186
187             MSK_getsolsta (task,MSK_SOL_ITR,&solsta);
188

```

```

189     switch(solsta)
190     {
191     case MSK_SOL_STA_OPTIMAL:
192     case MSK_SOL_STA_NEAR_OPTIMAL:
193         xx = (double*) MSK_calloc(task, NUMVAR, sizeof(MSKrealt));
194         barx = (double*) MSK_calloc(task, LENBARVAR[0], sizeof(MSKrealt));
195
196         MSK_getxx(task,
197                   MSK_SOL_ITR,
198                   xx);
199         MSK_getbarxj(task,
200                     MSK_SOL_ITR, /* Request the interior solution. */
201                     0,
202                     barx);
203
204         printf("Optimal primal solution\n");
205         for(i=0; i<NUMVAR; ++i)
206             printf("x[%d] : % e\n", i, xx[i]);
207
208         for(i=0; i<LENBARVAR[0]; ++i)
209             printf("barx[%d]: % e\n", i, barx[i]);
210
211         MSK_freetask(task, xx);
212         MSK_freetask(task, barx);
213
214         break;
215     case MSK_SOL_STA_DUAL_INFEAS_CER:
216     case MSK_SOL_STA_PRIM_INFEAS_CER:
217     case MSK_SOL_STA_NEAR_DUAL_INFEAS_CER:
218     case MSK_SOL_STA_NEAR_PRIM_INFEAS_CER:
219         printf("Primal or dual infeasibility certificate found.\n");
220         break;
221
222     case MSK_SOL_STA_UNKNOWN:
223         printf("The status of the solution could not be determined.\n");
224         break;
225     default:
226         printf("Other solution status.");
227         break;
228     }
229 }
230 else
231 {
232     printf("Error while optimizing.\n");
233 }
234 }
235
236 if (r != MSK_RES_OK)
237 {
238     /* In case of an error print error code and description. */
239     char symname[MSK_MAX_STR_LEN];
240     char desc[MSK_MAX_STR_LEN];
241
242     printf("An error occurred while optimizing.\n");
243     MSK_getcodedesc (r,
244                     symname,
245                     desc);
246     printf("Error %s - '%s'\n", symname, desc);

```

```

247     }
248   }
249   /* Delete the task and the associated data. */
250   MSK_deletetask(&task);
251 }
252
253 /* Delete the environment and the associated data. */
254 MSK_deleteenv(&env);
255
256 return ( r );
257 } /* main */

```

5.4.1.2 Source code comments

This example introduces several new functions. The first new function `MSK_appendbarvars` is used to append the semidefinite variable:

```

_____ [ sdo1.c ] _____
90  r = MSK_appendbarvars(task, NUMBARVAR, DIMBARVAR);
_____

```

Symmetric matrices are created using the function `MSK_appendsparsesymmat`:

```

_____ [ sdo1.c ] _____
110  r = MSK_appendsparsesymmat(task,
111                               DIMBARVAR[0],
112                               5,
113                               barc_i,
114                               barc_j,
115                               barc_v,
116                               &idx);
_____

```

The second argument specifies the dimension of the symmetric variable and the third argument gives the number of non-zeros in the lower triangular part of the matrix. The next three arguments specify the non-zeros in the lower-triangle in triplet format, and the last argument will be updated with a unique index of the created symmetric matrix.

After one or more symmetric matrices have been created using `MSK_appendsparsesymmat`, we can combine them to setup a objective matrix coefficient \bar{c}_j using `MSK_putbarcj`, which forms a linear combination of one more symmetric matrices:

```

_____ [ sdo1.c ] _____
119  r = MSK_putbarcj(task, 0, 1, &idx, &falpha);
_____

```

The second argument specify the semidefinite variable index j ; in this example there is only a single variable, so the index is 0. The next three arguments give the number of matrices used in the linear combination, their indices (as returned by `MSK_appendsparsesymmat`), and the weights for the individual matrices, respectively. In this example, we form the objective matrix coefficient directly from a single symmetric matrix.

Similary, a constraint matrix coefficient \bar{A}_{ij} is setup by the function `MSK_putbaraij`:

```

157  r = MSK_putbaraij(task, 0, 0, 1, &idx, &falpha);

```

where the second argument specifies the constraint number (the corresponding row of \bar{A}), and the third argument specifies the semidefinite variable index (the corresponding column of \bar{A}). The next three arguments specify a weighted combination of symmetric matrices used to form the constraint matrix coefficient.

After the problem is solved, we read the solution using `MSK_getbarxj`:

```

199  MSK_getbarxj(task,
200              MSK_SOL_ITR, /* Request the interior solution. */
201              0,
202              barx);

```

The function returns the half-vectorization of \bar{x}_j (the lower triangular part stacked as a column vector), where the semidefinite variable index j is given in the second argument, and the third argument is a pointer to an array for storing the numerical values.

5.5 Quadratic optimization

MOSEK can solve quadratic and quadratically constrained convex problems. This class of problems can be formulated as follows:

$$\begin{aligned}
 & \text{minimize} && \frac{1}{2}x^T Q^o x + c^T x + c^f \\
 & \text{subject to} && l_k^c \leq \frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j \leq u_k^c, \quad k = 0, \dots, m-1, \\
 & && l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1.
 \end{aligned} \tag{5.7}$$

Without loss of generality it is assumed that Q^o and Q^k are all symmetric because

$$x^T Q x = 0.5 x^T (Q + Q^T) x.$$

This implies that a non-symmetric Q can be replaced by the symmetric matrix $\frac{1}{2}(Q + Q^T)$.

The problem is required to be convex. More precisely, the matrix Q^o must be positive semi-definite and the k th constraint must be of the form

$$l_k^c \leq \frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j \tag{5.8}$$

with a negative semi-definite Q^k or of the form

$$\frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j \leq u_k^c. \quad (5.9)$$

with a positive semi-definite Q^k . This implies that quadratic equalities are *not* allowed. Specifying a non-convex problem will result in an error when the optimizer is called.

5.5.1 Example: Quadratic objective

The following is an example of a quadratic, linearly constrained problem:

$$\begin{array}{ll} \text{minimize} & x_1^2 + 0.1x_2^2 + x_3^2 - x_1x_3 - x_2 \\ \text{subject to} & 1 \leq x_1 + x_2 + x_3 \\ & x \geq 0 \end{array}$$

This can be written equivalently as

$$\begin{array}{ll} \text{minimize} & 1/2x^T Q^o x + c^T x \\ \text{subject to} & Ax \geq b \\ & x \geq 0, \end{array}$$

where

$$Q^o = \begin{bmatrix} 2 & 0 & -1 \\ 0 & 0.2 & 0 \\ -1 & 0 & 2 \end{bmatrix}, c = \begin{bmatrix} 0 \\ -1 \\ 0 \end{bmatrix}, A = \begin{bmatrix} 1 & 1 & 1 \end{bmatrix}, \text{ and } b = 1.$$

Please note that MOSEK always assumes that there is a $1/2$ in front of the $x^T Q x$ term in the objective. Therefore, the 1 in front of x_0^2 becomes 2 in Q , i.e. $Q_{0,0}^o = 2$.

5.5.1.1 Source code

```

1  /*
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File:      qo1.c
5
6  Purpose: To demonstrate how to solve a quadratic optimization
7           problem using the MOSEK API.
8  */
9
10 #include <stdio.h>
11
12 #include "mosek.h" /* Include the MOSEK definition file. */
13
14 #define NUMCON 1    /* Number of constraints.          */
15 #define NUMVAR 3    /* Number of variables.          */
16 #define NUMANZ 3    /* Number of non-zeros in A.     */

```

```

17 #define NUMQNZ 4    /* Number of non-zeros in Q.          */
18
19 static void MSKAPI printstr(void *handle,
20                             MSKCONST char str[])
21 {
22     printf("%s",str);
23 } /* printstr */
24
25 int main(int argc,char *argv[])
26 {
27
28     double      c[]    = {0.0,-1.0,0.0};
29
30     MSKboundkeye bkc[] = {MSK_BK_LO};
31     double      blc[] = {1.0};
32     double      buc[] = {+MSK_INFINITY};
33
34     MSKboundkeye bkc[] = {MSK_BK_LO,
35                           MSK_BK_LO,
36                           MSK_BK_LO};
37     double      blx[] = {0.0,
38                           0.0,
39                           0.0};
40     double      bux[] = {+MSK_INFINITY,
41                           +MSK_INFINITY,
42                           +MSK_INFINITY};
43
44     MSKint32t    aptrb[] = {0, 1, 2},
45                         aptre[] = {1, 2, 3},
46                         asub[] = {0, 0, 0};
47     double      aval[] = {1.0, 1.0, 1.0};
48
49     MSKint32t    qsubi[NUMQNZ];
50     MSKint32t    qsubj[NUMQNZ];
51     double      qval[NUMQNZ];
52
53     MSKint32t    i,j;
54     double      xx[NUMVAR];
55
56     MSKenv_t     env = NULL;
57     MSKtask_t    task = NULL;
58     MSKrescodee  r;
59
60     /* Create the mosek environment. */
61     r = MSK_makeenv(&env,NULL);
62
63     if ( r==MSK_RES_OK )
64     {
65         /* Create the optimization task. */
66         r = MSK_maketask(env,NUMCON,NUMVAR,&task);
67
68         if ( r==MSK_RES_OK )
69         {
70             r = MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
71
72             /* Append 'NUMCON' empty constraints.
73              The constraints will initially have no bounds. */
74             if ( r == MSK_RES_OK )

```

```

75     r = MSK_appendcons(task,NUMCON);
76
77     /* Append 'NUMVAR' variables.
78     The variables will initially be fixed at zero (x=0). */
79     if ( r == MSK_RES_OK )
80         r = MSK_appendvars(task,NUMVAR);
81
82     /* Optionally add a constant term to the objective. */
83     if ( r ==MSK_RES_OK )
84         r = MSK_putcfix(task,0.0);
85     for(j=0; j<NUMVAR && r == MSK_RES_OK; ++j)
86     {
87         /* Set the linear term c_j in the objective.*/
88         if(r == MSK_RES_OK)
89             r = MSK_putcj(task,j,c[j]);
90
91         /* Set the bounds on variable j.
92         blx[j] <= x_j <= bux[j] */
93         if(r == MSK_RES_OK)
94             r = MSK_putvarbound(task,
95                                 j,           /* Index of variable.*/
96                                 bkc[j],      /* Bound key.*/
97                                 blx[j],       /* Numerical value of lower bound.*/
98                                 bux[j]);      /* Numerical value of upper bound.*/
99
100        /* Input column j of A */
101        if(r == MSK_RES_OK)
102            r = MSK_putacol(task,
103                            j,           /* Variable (column) index.*/
104                            aptre[j]-aptrb[j], /* Number of non-zeros in column j.*/
105                            asub+aptrb[j], /* Pointer to row indexes of column j.*/
106                            aval+aptrb[j]); /* Pointer to Values of column j.*/
107    }
108
109    /* Set the bounds on constraints.
110    for i=1, ...,NUMCON : blc[i] <= constraint i <= buc[i] */
111    for(i=0; i<NUMCON && r==MSK_RES_OK; ++i)
112        r = MSK_putconbound(task,
113                            i,           /* Index of constraint.*/
114                            bkc[i],      /* Bound key.*/
115                            blc[i],       /* Numerical value of lower bound.*/
116                            buc[i]);      /* Numerical value of upper bound.*/
117
118    if ( r==MSK_RES_OK )
119    {
120        /*
121        * The lower triangular part of the Q
122        * matrix in the objective is specified.
123        */
124
125        qsubi[0] = 0;   qsubj[0] = 0;   qval[0] = 2.0;
126        qsubi[1] = 1;   qsubj[1] = 1;   qval[1] = 0.2;
127        qsubi[2] = 2;   qsubj[2] = 0;   qval[2] = -1.0;
128        qsubi[3] = 2;   qsubj[3] = 2;   qval[3] = 2.0;
129
130        /* Input the Q for the objective. */
131
132

```

```

133     r = MSK_putqobj(task, NUMQNZ, qsubi, qsubj, qval);
134 }
135
136 if ( r==MSK_RES_OK )
137 {
138     MSKrescodeee trmcode;
139
140     /* Run optimizer */
141     r = MSK_optimizetrm(task, &trmcode);
142
143     /* Print a summary containing information
144        about the solution for debugging purposes*/
145     MSK_solutionsummary (task, MSK_STREAM_MSG);
146
147     if ( r==MSK_RES_OK )
148     {
149         MSKsolstae solsta;
150         int j;
151
152         MSK_getsolsta (task, MSK_SOL_ITR, &solsta);
153
154         switch(solsta)
155         {
156             case MSK_SOL_STA_OPTIMAL:
157             case MSK_SOL_STA_NEAR_OPTIMAL:
158                 MSK_getxx(task,
159                     MSK_SOL_ITR, /* Request the interior solution. */
160                     xx);
161
162                 printf("Optimal primal solution\n");
163                 for(j=0; j<NUMVAR; ++j)
164                     printf("x[%d]: %e\n", j, xx[j]);
165
166                 break;
167             case MSK_SOL_STA_DUAL_INFEAS_CER:
168             case MSK_SOL_STA_PRIM_INFEAS_CER:
169             case MSK_SOL_STA_NEAR_DUAL_INFEAS_CER:
170             case MSK_SOL_STA_NEAR_PRIM_INFEAS_CER:
171                 printf("Primal or dual infeasibility certificate found.\n");
172                 break;
173
174             case MSK_SOL_STA_UNKNOWN:
175                 printf("The status of the solution could not be determined.\n");
176                 break;
177             default:
178                 printf("Other solution status.");
179                 break;
180         }
181     }
182     else
183     {
184         printf("Error while optimizing.\n");
185     }
186 }
187
188 if (r != MSK_RES_OK)
189 {
190     /* In case of an error print error code and description. */

```



```

191     char symname[MSK_MAX_STR_LEN];
192     char desc[MSK_MAX_STR_LEN];
193
194     printf("An error occurred while optimizing.\n");
195     MSK_getcodedesc (r,
196                     symname,
197                     desc);
198     printf("Error %s - '%s'\n",symname,desc);
199 }
200 }
201 MSK_deletetask(&task);
202 }
203 MSK_deleteenv(&env);
204
205 return (r);
206 } /* main */

```

5.5.1.2 Example code comments

Most of the functionality in this example has already been explained for the linear optimization example in Section 5.2 and it will not be repeated here.

This example introduces one new function, `MSK_putqobj`, which is used to input the quadratic terms of the objective function.

Since Q^o is symmetric only the lower triangular part of Q^o is inputted. The upper part of Q^o is computed by MOSEK using the relation

$$Q_{ij}^o = Q_{ji}^o.$$

Entries from the upper part may *not* appear in the input.

The lower triangular part of the matrix Q^o is specified using an unordered sparse triplet format (for details, see Section 5.13.3):

```

126 qsubi[0] = 0;   qsubj[0] = 0;   qval[0] = 2.0;
127 qsubi[1] = 1;   qsubj[1] = 1;   qval[1] = 0.2;
128 qsubi[2] = 2;   qsubj[2] = 0;   qval[2] = -1.0;
129 qsubi[3] = 2;   qsubj[3] = 2;   qval[3] = 2.0;

```

Please note that

- only non-zero elements are specified (any element not specified is 0 by definition),
- the order of the non-zero elements is insignificant, and
- *only* the lower triangular part should be specified.

Finally, the matrix Q^o is loaded into the task:

```

133 r = MSK_putqobj(task, NUMQNZ, qsubi, qsubj, qval);

```

5.5.2 Example: Quadratic constraints

In this section describes how to solve a problem with quadratic constraints. Please note that quadratic constraints are subject to the convexity requirement (5.8).

Consider the problem:

$$\begin{aligned}
 & \text{minimize} && x_1^2 + 0.1x_2^2 + x_3^2 - x_1x_3 - x_2 \\
 & \text{subject to} && 1 \leq x_1 + x_2 + x_3 - x_1^2 - x_2^2 - 0.1x_3^2 + 0.2x_1x_3, \\
 & && x \geq 0.
 \end{aligned}$$

This is equivalent to

$$\begin{aligned}
 & \text{minimize} && 1/2x^T Q^o x + c^T x \\
 & \text{subject to} && 1/2x^T Q^0 x + Ax \geq b,
 \end{aligned}$$

where

$$Q^o = \begin{bmatrix} 2 & 0 & -1 \\ 0 & 0.2 & 0 \\ -1 & 0 & 2 \end{bmatrix}, c = \begin{bmatrix} 0 \\ -1 \\ 0 \end{bmatrix}, A = \begin{bmatrix} 1 & 1 & 1 \end{bmatrix}, b = 1.$$

$$Q^0 = \begin{bmatrix} -2 & 0 & 0.2 \\ 0 & -2 & 0 \\ 0.2 & 0 & -0.2 \end{bmatrix}.$$

5.5.2.1 Source code

```

1  /*
2   Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4   File:      qcqo1.c
5
6   Purpose:   To demonstrate how to solve a quadratic
7               optimization problem using the MOSEK API.
8
9               minimize x_1^2 + 0.1 x_2^2 + x_3^2 - x_1 x_3 - x_2
10              s.t 1 <= x_1 + x_2 + x_3 - x_1^2 - x_2^2 - 0.1 x_3^2 + 0.2 x_1 x_3
11              x >= 0
12
13  */
14
15  #include <stdio.h>
16
17  #include "mosek.h" /* Include the MOSEK definition file. */

```

```

18
19 #define NUMCON 1    /* Number of constraints.          */
20 #define NUMVAR 3    /* Number of variables.          */
21 #define NUMANZ 3    /* Number of non-zeros in A.     */
22 #define NUMQNZ 4    /* Number of non-zeros in Q.     */
23
24 static void MSKAPI printstr(void *handle,
25                             MSKCONST char str[])
26 {
27     printf("%s",str);
28 } /* printstr */
29
30 int main(int argc,char *argv[])
31 {
32
33     MSKrescodee r;
34
35     double      c[]      = {0.0,-1.0,0.0};
36
37     MSKboundkeye bkc[]   = {MSK_BK_LO};
38     double      blc[]    = {1.0};
39     double      buc[]    = {+MSK_INFINITY};
40
41     MSKboundkeye bkx[]   = {MSK_BK_LO,
42                             MSK_BK_LO,
43                             MSK_BK_LO};
44     double      blx[]    = {0.0,
45                             0.0,
46                             0.0};
47     double      bux[]    = {+MSK_INFINITY,
48                             +MSK_INFINITY,
49                             +MSK_INFINITY};
50
51     MSKint32t    aptrb[] = {0, 1, 2 },
52                         aptre[] = {1, 2, 3},
53                         asub[] = { 0,  0,  0};
54     double      aval[] = { 1.0, 1.0, 1.0};
55     MSKint32t    qsubi[ NUMQNZ ],
56                 qsubj[ NUMQNZ ];
57     double      qval[ NUMQNZ ];
58
59     MSKint32t    j,i;
60     double      xx[ NUMVAR ];
61     MSKenv_t     env;
62     MSKtask_t    task;
63
64     /* Create the mosek environment. */
65     r = MSK_makeenv(&env,NULL);
66
67     if ( r==MSK_RES_OK )
68     {
69         /* Create the optimization task. */
70         r = MSK_maketask(env,NUMCON,NUMVAR,&task);
71
72         if ( r==MSK_RES_OK )
73         {
74             r = MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
75

```

```

76      /* Append 'NUMCON' empty constraints.
77      The constraints will initially have no bounds. */
78      if ( r == MSK_RES_OK )
79          r = MSK_appendcons(task, NUMCON);
80
81      /* Append 'NUMVAR' variables.
82      The variables will initially be fixed at zero (x=0). */
83      if ( r == MSK_RES_OK )
84          r = MSK_appendvars(task, NUMVAR);
85
86      /* Optionally add a constant term to the objective. */
87      if ( r == MSK_RES_OK )
88          r = MSK_putcfix(task, 0.0);
89      for(j=0; j<NUMVAR && r == MSK_RES_OK; ++j)
90      {
91          /* Set the linear term c_j in the objective.*/
92          if(r == MSK_RES_OK)
93              r = MSK_putcj(task, j, c[j]);
94
95          /* Set the bounds on variable j.
96          blx[j] <= x_j <= bux[j] */
97          if(r == MSK_RES_OK)
98              r = MSK_putvarbound(task,
99                                  j,          /* Index of variable.*/
100                                 bkx[j],      /* Bound key.*/
101                                 blx[j],      /* Numerical value of lower bound.*/
102                                 bux[j]);     /* Numerical value of upper bound.*/
103
104          /* Input column j of A */
105          if(r == MSK_RES_OK)
106              r = MSK_putacol(task,
107                                  j,          /* Variable (column) index.*/
108                                  aptre[j]-aptrb[j], /* Number of non-zeros in column j.*/
109                                  asub+aptrb[j], /* Pointer to row indexes of column j.*/
110                                  aval+aptrb[j]); /* Pointer to Values of column j.*/
111      }
112
113
114      /* Set the bounds on constraints.
115      for i=1, ..., NUMCON : blc[i] <= constraint i <= buc[i] */
116      for(i=0; i<NUMCON && r==MSK_RES_OK; ++i)
117          r = MSK_putconbound(task,
118                                  i,          /* Index of constraint.*/
119                                  bkc[i],      /* Bound key.*/
120                                  blc[i],      /* Numerical value of lower bound.*/
121                                  buc[i]);     /* Numerical value of upper bound.*/
122
123      if ( r==MSK_RES_OK )
124      {
125          /*
126          * The lower triangular part of the Q^o
127          * matrix in the objective is specified.
128          */
129
130          qsubi[0] = 0;   qsubj[0] = 0;   qval[0] = 2.0;
131          qsubi[1] = 1;   qsubj[1] = 1;   qval[1] = 0.2;
132          qsubi[2] = 2;   qsubj[2] = 0;   qval[2] = -1.0;
133          qsubi[3] = 2;   qsubj[3] = 2;   qval[3] = 2.0;

```

```

134
135     /* Input the Q^o for the objective. */
136
137     r = MSK_putqobj(task, NUMQNZ, qsubi, qsubj, qval);
138 }
139
140 if ( r==MSK_RES_OK )
141 {
142     /*
143     * The lower triangular part of the Q^0
144     * matrix in the first constraint is specified.
145     This corresponds to adding the term
146     - x_1^2 - x_2^2 - 0.1 x_3^2 + 0.2 x_1 x_3
147     */
148
149     qsubi[0] = 0;   qsubj[0] = 0;   qval[0] = -2.0;
150     qsubi[1] = 1;   qsubj[1] = 1;   qval[1] = -2.0;
151     qsubi[2] = 2;   qsubj[2] = 2;   qval[2] = -0.2;
152     qsubi[3] = 2;   qsubj[3] = 0;   qval[3] = 0.2;
153
154     /* Put Q^0 in constraint with index 0. */
155
156     r = MSK_putqconk(task,
157                      0,
158                      4,
159                      qsubi,
160                      qsubj,
161                      qval);
162 }
163
164 if ( r==MSK_RES_OK )
165     r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MINIMIZE);
166
167 if ( r==MSK_RES_OK )
168 {
169     MSKrescodee trmcode;
170
171     /* Run optimizer */
172     r = MSK_optimizetrm(task, &trmcode);
173
174     /* Print a summary containing information
175     about the solution for debugging purposes*/
176     MSK_solutionsummary (task, MSK_STREAM_LOG);
177
178     if ( r==MSK_RES_OK )
179     {
180         MSKsolstae solsta;
181         int j;
182
183         MSK_getsolsta (task, MSK_SOL_ITR, &solsta);
184
185         switch(solsta)
186         {
187             case MSK_SOL_STA_OPTIMAL:
188             case MSK_SOL_STA_NEAR_OPTIMAL:
189                 MSK_getxx(task,
190                          MSK_SOL_ITR,      /* Request the interior solution. */
191                          xx);

```

```

192         printf("Optimal primal solution\n");
193         for(j=0; j<NUMVAR; ++j)
194             printf("x[%d]: %e\n",j,xx[j]);
195
196         break;
197     case MSK_SOL_STA_DUAL_INFEAS_CER:
198     case MSK_SOL_STA_PRIM_INFEAS_CER:
199     case MSK_SOL_STA_NEAR_DUAL_INFEAS_CER:
200     case MSK_SOL_STA_NEAR_PRIM_INFEAS_CER:
201         printf("Primal or dual infeasibility certificate found.\n");
202         break;
203
204     case MSK_SOL_STA_UNKNOWN:
205         printf("The status of the solution could not be determined.\n");
206         break;
207     default:
208         printf("Other solution status.");
209         break;
210 }
211 }
212 }
213 else
214 {
215     printf("Error while optimizing.\n");
216 }
217 }
218
219 if (r != MSK_RES_OK)
220 {
221     /* In case of an error print error code and description. */
222     char symname[MSK_MAX_STR_LEN];
223     char desc[MSK_MAX_STR_LEN];
224
225     printf("An error occurred while optimizing.\n");
226     MSK_getcodedesc (r,
227                     symname,
228                     desc);
229     printf("Error %s - '%s'\n",symname,desc);
230 }
231 }
232
233     MSK_deletetask(&task);
234 }
235     MSK_deleteenv(&env);
236
237     return ( r );
238 } /* main */

```

The only new function introduced in this example is `MSK_putqconk`, which is used to add quadratic terms to the constraints. While `MSK_putqconk` add quadratic terms to a specific constraint, it is also possible to input all quadratic terms in all constraints in one chunk using the `MSK_putqcon` function.

5.6 The solution summary

All computations inside MOSEK are performed using finite precision floating point numbers. This implies the reported solution is only an approximate optimal solution. Therefore after solving an optimization problem it is important to investigate how good an approximation the solution is. This can easily be done using the function `MSK.solutionsummary` which reports how much the solution violates the primal and dual constraints and the primal and dual objective values. Recall for a convex optimization problem the optimality conditions are:

- The primal solution must satisfy all the primal constraints.
- The dual solution must satisfy all the dual constraints.
- The primal and dual objective values must be identical.

Thus the solution summary reports information that makes it possible to evaluate the quality of the solution obtained.

In case of a linear optimization problem the solution summary may look like

```
Basic solution summary
Problem status : PRIMAL_AND_DUAL_FEASIBLE
Solution status : OPTIMAL
Primal.  obj: -4.6475314286e+002  Viol.  con: 2e-014  var: 0e+000
Dual.    obj: -4.6475316001e+002  Viol.  con: 7e-009  var: 4e-016
```

The summary reports information for the basic solution. In this case we see:

- The problem status is primal and dual feasible which means the problem has an optimal solution. The problem status can be obtained using `MSK.getprosta`.
- The solution status is optimal. The solution status can be obtained using `MSK.getsolsta`.
- Next information about the primal solution is reported. The information consists of the objective value and violation measures for the primal solution. In this case violations for the constraints and variables are small meaning the solution is very close to being an exact feasible solution. The violation measure for the variables is the worst violation of the solution in any of the bounds on the variables.
The constraint and variable violations are computed with `MSK.getpviolcon` and `MSK.getpviolvar`.
- Similarly for the dual solution the violations are small and hence the dual solution is feasible. The constraint and variable violations are computed with `MSK.getdviolcon` and `MSK.getdviolvar` respectively.
- Finally, it can be seen that the primal and dual objective values are almost identical. Using `MSK.getprimalobj` and `MSK.getdualobj` the primal and dual objective values can be obtained.

To summarize in this case a primal and a dual solution with small feasibility violations are available. Moreover, the primal and dual objective values are almost identical and hence it can be concluded that the reported solution is a good approximation to the optimal solution.

Now what happens if the problem does not have an optimal solution e.g. it is primal infeasible. In that case the solution summary may look like

```
Basic solution summary
Problem status : PRIMAL_INFEASIBLE
Solution status : PRIMAL_INFEASIBLE_CER
Dual.   obj: 3.5894503823e+004   Viol.   con: 0e+000   var: 2e-008
```

i.e. MOSEK reports that the solution is a certificate of primal infeasibility. Since the problem is primal infeasible it does not make sense to report any information about the primal solution. However, the dual solution should be a certificate of the primal infeasibility. If the problem is a minimization problem then the dual objective value should be positive and in the case of a maximization problem it should be negative. The quality of the certificate can be evaluated by comparing the dual objective value to the violations. Indeed if the objective value is large compared to the largest violation then the certificate is highly accurate. Here is an example

```
Basic solution summary
Problem status : PRIMAL_INFEASIBLE
Solution status : PRIMAL_INFEASIBLE_CER
Dual.   obj: 3.0056574100e-005   Viol.   con: 9e-013   var: 2e-011
```

of a not so strong infeasibility certificate because the dual objective value is small compared to largest violation.

In the case a problem is dual infeasible then the solution summary may look like

```
Basic solution summary
Problem status : DUAL_INFEASIBLE
Solution status : DUAL_INFEASIBLE_CER
Primal. obj: -1.4500853392e+001   Viol.   con: 0e+000   var: 0e+000
```

Observe when a solution is a certificate of dual infeasibility then the primal solution contains the certificate. Moreover, given the problem is a minimization problem the objective value should be negative and the objective should be large compared to the worst violation if the certificate is strong.

5.7 Integer optimization

An optimization problem where one or more of the variables are constrained to integer values is denoted an integer optimization problem.

5.7.1 Example: Mixed integer linear optimization

In this section the example

$$\begin{aligned}
 &\text{maximize} && x_0 + 0.64x_1 \\
 &\text{subject to} && 50x_0 + 31x_1 \leq 250, \\
 & && 3x_0 - 2x_1 \geq -4, \\
 & && x_0, x_1 \geq 0 \quad \text{and integer}
 \end{aligned} \tag{5.10}$$

is used to demonstrate how to solve a problem with integer variables.

5.7.1.1 Source code

The example (5.10) is almost identical to a linear optimization problem except for some variables being integer constrained. Therefore, only the specification of the integer constraints requires something new compared to the linear optimization problem discussed previously. In MOSEK these constraints are specified using the function `MSK_putvartype` as shown in the code:

```

106 for(j=0; j<numvar && r == MSK_RES_OK; ++j)
107     r = MSK_putvartype(task,j,MSK_VAR_TYPE_INT);

```

The complete source for the example is listed below.

```

1  /*
2   Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4   File:      milo1.c
5
6   Purpose:   To demonstrate how to solve a small mixed
7             integer linear optimization problem using
8             the MOSEK API.
9  */
10
11 #include <stdio.h>
12
13 #include "mosek.h" /* Include the MOSEK definition file. */
14
15 static void MSKAPI printstr(void *handle,
16                             MSKCONST char str[])
17 {
18     printf("%s",str);
19 } /* printstr */
20
21 int main(int argc,char *argv[])
22 {
23     const MSKint32t numvar = 2,
24               numcon = 2;
25
26     double      c[] = { 1.0, 0.64 };
27     MSKboundkeye bkc[] = { MSK_BK_UP,    MSK_BK_LO };
28     double      blc[] = { -MSK_INFINITY,-4.0 };
29     double      buc[] = { 250.0,        MSK_INFINITY };
30
31     MSKboundkeye bkx[] = { MSK_BK_LO,    MSK_BK_LO };
32     double      blx[] = { 0.0,          0.0 };
33     double      bux[] = { MSK_INFINITY, MSK_INFINITY };
34
35
36     MSKint32t    aptrb[] = { 0, 2 },
37                 aptre[] = { 2, 4 },
38                 asub[] = { 0, 1, 0, 1 };
39     double      aval[] = { 50.0, 3.0, 31.0, -2.0 };
40     MSKint32t    i,j;
41
42     MSKenv_t      env = NULL;

```

```

43     MSKtask_t    task = NULL;
44     MSKrescodee  r;
45
46     /* Create the mosek environment. */
47     r = MSK_makeenv(&env,NULL);
48
49     /* Check if return code is ok. */
50     if ( r==MSK_RES_OK )
51     {
52         /* Create the optimization task. */
53         r = MSK_maketask(env,0,0,&task);
54
55         if ( r==MSK_RES_OK )
56             r = MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
57
58         /* Append 'numcon' empty constraints.
59          The constraints will initially have no bounds. */
60         if ( r == MSK_RES_OK )
61             r = MSK_appendcons(task,numcon);
62
63         /* Append 'numvar' variables.
64          The variables will initially be fixed at zero (x=0). */
65         if ( r == MSK_RES_OK )
66             r = MSK_appendvars(task,numvar);
67
68         /* Optionally add a constant term to the objective. */
69         if ( r ==MSK_RES_OK )
70             r = MSK_putcfix(task,0.0);
71         for(j=0; j<numvar && r == MSK_RES_OK; ++j)
72         {
73             /* Set the linear term c_j in the objective.*/
74             if(r == MSK_RES_OK)
75                 r = MSK_putcj(task,j,c[j]);
76
77             /* Set the bounds on variable j.
78              blx[j] <= x_j <= bux[j] */
79             if(r == MSK_RES_OK)
80                 r = MSK_putvarbound(task,
81                                     j,          /* Index of variable.*/
82                                     bkx[j],     /* Bound key.*/
83                                     blx[j],     /* Numerical value of lower bound.*/
84                                     bux[j]);    /* Numerical value of upper bound.*/
85
86             /* Input column j of A */
87             if(r == MSK_RES_OK)
88                 r = MSK_putacol(task,
89                                     j,          /* Variable (column) index.*/
90                                     aptre[j]-aptrb[j], /* Number of non-zeros in column j.*/
91                                     asub+aptrb[j],    /* Pointer to row indexes of column j.*/
92                                     aval+aptrb[j]);    /* Pointer to Values of column j.*/
93         }
94
95         /* Set the bounds on constraints.
96          for i=1, ...,numcon : blc[i] <= constraint i <= buc[i] */
97         for(i=0; i<numcon && r==MSK_RES_OK; ++i)
98             r = MSK_putconbound(task,
99                                     i,          /* Index of constraint.*/

```

```

101             bkc[i],      /* Bound key.*/
102             blc[i],      /* Numerical value of lower bound.*/
103             buc[i]);     /* Numerical value of upper bound.*/
104
105     /* Specify integer variables. */
106     for(j=0; j<numvar && r == MSK_RES_OK; ++j)
107         r = MSK_putvartype(task,j,MSK_VAR_TYPE_INT);
108
109     if ( r==MSK_RES_OK )
110         r = MSK_putobjsense(task,
111                             MSK_OBJECTIVE_SENSE_MAXIMIZE);
112
113     if ( r==MSK_RES_OK )
114     {
115         MSKrescodee trmcode;
116
117         /* Run optimizer */
118         r = MSK_optimizetrm(task,&trmcode);
119
120         /* Print a summary containing information
121          about the solution for debugging purposes*/
122         MSK_solutionsummary (task,MSK_STREAM_MSG);
123
124         if ( r==MSK_RES_OK )
125         {
126             MSKint32t j;
127             MSKsolstae solsta;
128             double *xx = NULL;
129
130             MSK_getsolsta (task,MSK_SOL_ITG,&solsta);
131
132             xx = calloc(numvar,sizeof(double));
133             if ( xx )
134             {
135                 switch(solsta)
136                 {
137                     case MSK_SOL_STA_INTEGER_OPTIMAL:
138                     case MSK_SOL_STA_NEAR_INTEGER_OPTIMAL :
139                         MSK_getxx(task,
140                                 MSK_SOL_ITG,      /* Request the integer solution. */
141                                 xx);
142
143                         printf("Optimal solution.\n");
144                         for(j=0; j<numvar; ++j)
145                             printf("x[%d]: %e\n",j,xx[j]);
146                         break;
147                     case MSK_SOL_STA_PRIM_FEAS:
148                         /* A feasible but not necessarily optimal solution was located. */
149                         MSK_getxx(task,MSK_SOL_ITG,xx);
150
151                         printf("Feasible solution.\n");
152                         for(j=0; j<numvar; ++j)
153                             printf("x[%d]: %e\n",j,xx[j]);
154                         break;
155                     case MSK_SOL_STA_UNKNOWN:
156                     {
157                         MSKprosta prosta;
158                         MSK_getprosta(task,MSK_SOL_ITG,&prosta);

```

```

159         switch (prosta)
160         {
161             case MSK_PRO_STA_PRIM_INFEAS_OR_UNBOUNDED:
162                 printf("Problem status Infeasible or unbounded\n");
163                 break;
164             case MSK_PRO_STA_PRIM_INFEAS:
165                 printf("Problem status Infeasible.\n");
166                 break;
167             case MSK_PRO_STA_UNKNOWN:
168                 printf("Problem status unknown.\n");
169                 break;
170             default:
171                 printf("Other problem status.");
172                 break;
173         }
174     }
175     break;
176 default:
177     printf("Other solution status.");
178     break;
179 }
180 }
181 else
182 {
183     r = MSK_RES_ERR_SPACE;
184 }
185 free(xx);
186 }
187 }
188
189 if (r != MSK_RES_OK)
190 {
191     /* In case of an error print error code and description. */
192     char symname[MSK_MAX_STR_LEN];
193     char desc[MSK_MAX_STR_LEN];
194
195     printf("An error occurred while optimizing.\n");
196     MSK_getcodedesc (r,
197                     symname,
198                     desc);
199     printf("Error %s - '%s'\n", symname, desc);
200 }
201
202 MSK_deletetask(&task);
203 }
204 MSK_deleteenv(&env);
205
206 printf("Return code: %d.\n", r);
207 return ( r );
208 } /* main */

```

5.7.1.2 Code comments

Please note that when `MSK_getsolutionslice` is called, the integer solution is requested by using `MSK_SOL_ITG`. No dual solution is defined for integer optimization problems.

5.7.2 Specifying an initial solution

Integer optimization problems are generally hard to solve, but the solution time can often be reduced by providing an initial solution for the solver. Solution values can be set using `MSK_putsolution` (for inputting a whole solution) or `MSK_putsolution_i` (for inputting solution values related to a single variable or constraint).

It is not necessary to specify the whole solution. By setting the `MSK_IPAR_MIO_CONSTRUCT_SOL` parameter to `MSK_ON` and inputting values for the integer variables only, will force MOSEK to compute the remaining continuous variable values.

If the specified integer solution is infeasible or incomplete, MOSEK will simply ignore it.

5.7.3 Example: Specifying an integer solution

Consider the problem

$$\begin{aligned} &\text{maximize} && 7x_0 + 10x_1 + x_2 + 5x_3 \\ &\text{subject to} && x_0 + x_1 + x_2 + x_3 \leq 2.5 \\ &&& x_0, x_1, x_2 \text{ integer}, x_0, x_1, x_2, x_3 \geq 0 \end{aligned}$$

The following example demonstrates how to optimize the problem using a feasible starting solution generated by selecting the integer values as $x_0 = 0, x_1 = 2, x_2 = 0$.

```

1  /*-----[mioinitsol.c]-----
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File:      mioinitsol.c
5
6  Purpose:   To demonstrate how to solve a MIP with a start guess.
7
8  */
9
10 #include "mosek.h"
11 #include <stdio.h>
12
13 static void MSKAPI printstr(void *handle,
14                             MSKCONST char str[])
15 {
16     printf("%s",str);
17 } /* printstr */
18
19
20 int main(int argc,char *argv[])
21 {
22     char          buffer[512];
23
24     const MSKint32t numvar      = 4,
25                  numcon        = 1,
26                  numintvar     = 3;
27
28     MSKrescodee r;
29

```

```

30     MSKenv_t      env;
31     MSKtask_t     task;
32
33     double        c[] = { 7.0, 10.0, 1.0, 5.0 };
34
35     MSKboundkeye bkc[] = {MSK_BK_UP};
36     double       blc[] = {-MSK_INFINITY};
37     double       buc[] = {2.5};
38
39     MSKboundkeye bkc[] = {MSK_BK_LO, MSK_BK_LO, MSK_BK_LO, MSK_BK_LO};
40     double       blx[] = {0.0, 0.0, 0.0, 0.0 };
41     double       bux[] = {MSK_INFINITY, MSK_INFINITY, MSK_INFINITY, MSK_INFINITY};
42
43     MSKint32t     ptrb[] = {0,1,2,3},
44                   ptre[] = {1,2,3,4},
45                   asub[] = {0, 0, 0, 0 };
46
47     double        aval[] = {1.0, 1.0, 1.0, 1.0};
48     MSKint32t     intsub[] = {0,1,2};
49     MSKint32t     j;
50
51     r = MSK_makeenv(&env, NULL);
52
53     if ( r==MSK_RES_OK )
54         r = MSK_maketask(env, 0, 0, &task);
55
56     if ( r==MSK_RES_OK )
57         r = MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);
58
59     if (r == MSK_RES_OK)
60         r = MSK_inputdata(task,
61                             numcon, numvar,
62                             numcon, numvar,
63                             c,
64                             0.0,
65                             ptrb,
66                             ptre,
67                             asub,
68                             aval,
69                             bkc,
70                             blc,
71                             buc,
72                             bkc,
73                             blx,
74                             bux);
75
76     if (r == MSK_RES_OK)
77         r = MSK_putobjsense(task, MSK_OBJECTIVE_SENSE_MAXIMIZE);
78
79     for(j=0; j<numintvar && r == MSK_RES_OK; ++j)
80         r = MSK_putvartype(task, intsub[j], MSK_VAR_TYPE_INT);
81
82     /* Construct an initial feasible solution from the
83        values of the integer variables specified */
84
85     if (r == MSK_RES_OK)
86         r = MSK_putintparam(task, MSK_IPAR_MIO_CONSTRUCT_SOL, MSK_ON);
87

```

```

88     if (r == MSK_RES_OK)
89     {
90         double xx[]={0.0, 2.0, 0.0};
91
92         /* Assign values 0,2,0 to integer variables */
93         r = MSK_putxxslice(task,MSK_SOL_ITG,0,3,xx);
94     }
95
96     /* solve */
97
98     if (r == MSK_RES_OK)
99     {
100         MSKrescodee trmcode;
101         r = MSK_optimizetrm(task,&trmcode);
102     }
103
104
105     {
106         double obj;
107         int     isok;
108
109         /* Did mosek construct a feasible initial solution ? */
110         if (r == MSK_RES_OK)
111             r = MSK_getintinf(task,MSK_IINF_MIO_CONSTRUCT_SOLUTION,&isok);
112
113         if (r == MSK_RES_OK )
114             r = MSK_getdouinf(task,MSK_DINF_MIO_CONSTRUCT_SOLUTION_OBJ,&obj);
115
116         if (r == MSK_RES_OK)
117         {
118             if ( isok>0 )
119                 printf("Objective of constructed solution : %24.12e\n",obj);
120             else
121                 printf("Construction of an initial integer solution failed\n");
122         }
123     }
124
125     MSK_deletetask(&task);
126
127     MSK_deleteenv(&env);
128
129     if (r != MSK_RES_OK)
130     {
131         /* In case of an error print error code and description. */
132         char symname[MSK_MAX_STR_LEN];
133         char desc[MSK_MAX_STR_LEN];
134
135         printf("An error occurred while optimizing.\n");
136         MSK_getcodedesc (r,
137                         symname,
138                         desc);
139         printf("Error %s - '%s'\n",symname,desc);
140     }
141
142     return (r);
143 }

```

5.8 The solution summary for mixed integer problems

The solution summary for a mixed-integer problem may look like

```
Integer solution summary
Problem status : PRIMAL_FEASIBLE
Solution status : INTEGER_OPTIMAL
Primal. obj: 4.0593518000e+005   Viol. con: 4e-015   var: 3e-014   itg: 3e-014
```

The main difference compared to continuous case covered previously is that no information about the dual solution is provided. Simply because there is no dual solution available for a mixed integer problem. In this case it can be seen that the solution is highly feasible because the violations are small. Moreover, the solution is denoted integer optimal. Observe `itg: 3e-014` implies that all the integer constrained variables are at most $3e-014$ from being an exact integer.

5.9 Response handling

After solving an optimization problem with MOSEK an appropriate action must be taken depending on the outcome. Usually, the expected outcome is an optimal solution, but there may be several situations where this is not the result. E.g., if the problem is infeasible or nearly so or if the solver ran out of memory or stalled while optimizing, the result may not be as expected.

This section discusses what should be considered when an optimization has ended unsuccessfully.

Before continuing, let us consider the four status codes available in MOSEK that is relevant for the error handling:

The termination code:

The termination provides information about why the optimizer terminated. For instance if a time limit has been specified (this is common for mixed integer problems), the termination code will tell if this termination limit was the cause of the termination. Note that reaching a prespecified time limit is not considered an exceptional case. It must be expected that this occurs occasionally.

Response code:

The response code is the return value from MOSEK function that provides information about the system status. This code is used to report the unexpected failures such as out of space.

Solution status:

The solution status contains information about the status of the solution, e.g., whether the solution is optimal or a certificate of infeasibility.

Problem status:

The problem status describes what MOSEK knows about the feasibility of the problem, i.e., if the problem is feasible or infeasible.

The problem status is mostly used for integer problems. For continuous problems a problem status of, say, *infeasible* will always mean that the solution is a certificate of infeasibility. For integer problems it is not possible to provide a certificate, and thus a separate problem status is useful.

Note that if we want to report, e.g., that the optimizer terminated due to a time limit or because it stalled but with a feasible solution, we have to consider *both* the termination code, *and* the solution status.

The following pseudo code demonstrates a best practice way of dealing with the status codes.

```

if ( the solution status is as expected )
{
    The normal case:
    Do whatever that was planned. Note the response code is
    ignored because the solution has the expected status.
    Of course we may check the response anyway if we like.
}
else
{
    Exceptional case:
    Based on solution status, response and termination codes take
    appropriate action.
}

```

In the following example the pseudo code has implemented. The idea of the example is to read an optimization problem from a file, e.g., an MPS file and optimize it. Based on status codes an appropriate action is taken, which in this case is to print a suitable message.

[response.c]

```

1  /*
2   Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4   File:      response.c
5
6   Purpose:   This examples demonstrates proper response handling.
7  */
8
9
10 #include <stdio.h>
11 #include <stdlib.h>
12 #include <string.h>
13
14 #include "mosek.h"
15
16 void MSKAPI printlog(void *ptr,
17                     MSKCONST char s[])
18 {
19     printf("%s",s);
20 } /* printlog */
21
22 int main(int argc,char const *argv[])
23 {
24     MSKenv_t    env;
25     MSKrescodee r;
26     MSKtask_t   task;
27
28     if ( argc<2 )
29     {
30         printf("No input file specified\n");
31         exit(0);
32     }
33     else

```

```

34     printf("Inputfile:  %s\n",argv[1]);
35
36     r = MSK_makeenv(&env,NULL);
37
38     if ( r==MSK_RES_OK )
39     {
40         r = MSK_makeemptytask(env,&task);
41         if ( r==MSK_RES_OK )
42             MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL,      printlog);
43
44         r = MSK_readdata(task,argv[1]);
45         if ( r==MSK_RES_OK )
46         {
47             MSKrescodee trmcode;
48             MSKsolstae  solsta;
49
50             r = MSK_optimizetrm(task,&trmcode); /* Do the optimization. */
51
52             /* Expected result: The solution status of the basic solution is optimal. */
53
54             if ( MSK_RES_OK==MSK_getsolsta(task,MSK_SOL_ITR,&solsta) )
55             {
56                 switch( solsta )
57                 {
58                     case MSK_SOL_STA_OPTIMAL:
59                     case MSK_SOL_STA_NEAR_OPTIMAL:
60                         printf("An optimal basic solution is located.\n");
61
62                         MSK_solutionsummary(task,MSK_STREAM_MSG);
63                         break;
64                     case MSK_SOL_STA_DUAL_INFEAS_CER:
65                     case MSK_SOL_STA_NEAR_DUAL_INFEAS_CER:
66                         printf("Dual infeasibility certificate found.\n");
67                         break;
68                     case MSK_SOL_STA_PRIM_INFEAS_CER:
69                     case MSK_SOL_STA_NEAR_PRIM_INFEAS_CER:
70                         printf("Primal infeasibility certificate found.\n");
71                         break;
72                     case MSK_SOL_STA_UNKNOWN:
73                     {
74                         char symname[MSK_MAX_STR_LEN];
75                         char desc[MSK_MAX_STR_LEN];
76
77                         /* The solutions status is unknown. The termination code
78                          indicating why the optimizer terminated prematurely. */
79
80                         printf("The solution status is unknown.\n");
81                         if ( r!=MSK_RES_OK )
82                         {
83                             /* A system failure e.g. out of space. */
84
85                             MSK_getcodedesc(r,symname,desc);
86
87                             printf("  Response code: %s\n",symname);
88                         }
89                         else
90                         {
91                             /* No system failure e.g. an iteration limit is reached. */

```

```

92         MSK_getcodedesc(trmcode,symname,desc);
93
94         printf("  Termination code: %s\n",symname);
95     }
96     break;
97 }
98 default:
99     printf("An unexpected solution status is obtained.\n");
100    break;
101 }
102 }
103 }
104 else
105     printf("Could not obtain the solution status for the requested solution.\n");
106 }
107 MSK_deletetask(&task);
108 }
109
110 MSK_deleteenv(&env);
111 printf("Return code: %d (0 means no error occurred.)\n",r);
112
113 return ( r );
114 } /* main */

```

5.10 Problem modification and reoptimization

Often one might want to solve not just a single optimization problem, but a sequence of problem, each differing only slightly from the previous one. This section demonstrates how to modify and re-optimize an existing problem. The example we study is a simple production planning model.

5.10.1 Example: Production planning

A company manufactures three types of products. Suppose the stages of manufacturing can be split into three parts, namely Assembly, Polishing and Packing. In the table below we show the time required for each stage as well as the profit associated with each product.

Product no.	Assembly (minutes)	Polishing (minutes)	Packing (minutes)	Profit (\$)
0	2	3	2	1.50
1	4	2	3	2.50
2	3	3	2	3.00

With the current resources available, the company has 100,000 minutes of assembly time, 50,000 minutes of polishing time and 60,000 minutes of packing time available per year.

Now the question is how many items of each product the company should produce each year in order to maximize profit?

Denoting the number of items of each type by x_0, x_1 and x_2 , this problem can be formulated as the linear optimization problem:

$$\begin{array}{llllll}
\text{maximize} & 1.5x_0 & + & 2.5x_1 & + & 3.0x_2 \\
\text{subject to} & 2x_0 & + & 4x_1 & + & 3x_2 & \leq & 100000, \\
& 3x_0 & + & 2x_1 & + & 3x_2 & \leq & 50000, \\
& 2x_0 & + & 3x_1 & + & 2x_2 & \leq & 60000,
\end{array}$$

and

$$x_0, x_1, x_2 \geq 0.$$

The following code loads this problem into the optimization task.

```

25  const MSKint32t numvar = 3,
26      numcon = 3;
27  MSKint32t      i,j;
28  double         c[]  = {1.5, 2.5, 3.0};
29  MSKint32t      ptrb[] = {0, 3, 6},
30      ptre[] = {3, 6, 9},
31      asub[] = { 0, 1, 2,
32              0, 1, 2,
33              0, 1, 2};
34
35  double         aval[] = { 2.0, 3.0, 2.0,
36                          4.0, 2.0, 3.0,
37                          3.0, 3.0, 2.0};
38
39  MSKboundkeye   bkc[]  = {MSK_BK_UP, MSK_BK_UP, MSK_BK_UP   };
40  double         blc[]  = {-MSK_INFINITY, -MSK_INFINITY, -MSK_INFINITY};
41  double         buc[]  = {100000, 50000, 60000};
42
43  MSKboundkeye   bkc[]  = {MSK_BK_LO,      MSK_BK_LO,      MSK_BK_LO};
44  double         blx[]  = {0.0,      0.0,      0.0,};
45  double         bux[]  = {+MSK_INFINITY, +MSK_INFINITY,+MSK_INFINITY};
46
47  double         *xx=NULL;
48  MSKenv_t       env;
49  MSKtask_t      task;
50  MSKint32t      varidx,conidx;
51  MSKrescodee    r;
52
53  /* Create the mosek environment. */
54  r = MSK_makeenv(&env,NULL);
55
56  if ( r==MSK_RES_OK )
57  {
58      /* Create the optimization task. */
59      r = MSK_maketask(env,numcon,numvar,&task);
60
61      /* Directs the log task stream to the
62       'printstr' function. */
63
64      MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
65
66      /* Append the constraints. */
67      if (r == MSK_RES_OK)
68          r = MSK_appendcons(task,numcon);

```

```

69
70  /* Append the variables. */
71  if (r == MSK_RES_OK)
72      r = MSK_appendvars(task,numvar);
73
74  /* Put C. */
75  if (r == MSK_RES_OK)
76      r = MSK_putcfix(task, 0.0);
77
78  if (r == MSK_RES_OK)
79      for(j=0; j<numvar; ++j)
80          r = MSK_putcj(task,j,c[j]);
81
82  /* Put constraint bounds. */
83  if (r == MSK_RES_OK)
84      for(i=0; i<numcon; ++i)
85          r = MSK_putconbound(task,i,bkc[i],blc[i],buc[i]);
86
87  /* Put variable bounds. */
88  if (r == MSK_RES_OK)
89      for(j=0; j<numvar; ++j)
90          r = MSK_putvarbound(task,j,bkx[j],blx[j],bux[j]);
91
92  /* Put A. */
93  if (r == MSK_RES_OK)
94      if ( numcon>0 )
95          for(j=0; j<numvar; ++j)
96              r = MSK_putacol(task,
97                              j,
98                              ptrb[j]-ptrb[j],
99                              asub+ptrb[j],
100                             aval+ptrb[j]);
101
102  if (r == MSK_RES_OK)
103      r = MSK_putobjsense(task,
104                          MSK_OBJECTIVE_SENSE_MAXIMIZE);
105
106  if (r == MSK_RES_OK)
107      r = MSK_optimizetrm(task,NULL);
108
109  if (r == MSK_RES_OK)
110  {
111      xx = calloc(numvar,sizeof(double));
112      if ( !xx )
113          r = MSK_RES_ERR_SPACE;
114  }
115
116  if (r == MSK_RES_OK)
117      r = MSK_getxx(task,
118                  MSK_SOL_BAS,      /* Basic solution.      */
119                  xx);

```

5.10.2 Changing the A matrix

Suppose we want to change the time required for assembly of product 0 to 3 minutes. This corresponds to setting $a_{0,0} = 3$, which is done by calling the function `MSK_putaij` as shown below.

```

122  if (r == MSK_RES_OK)
123      r = MSK_putaij(task, 0, 0, 3.0);

```

The problem now has the form:

$$\begin{aligned}
 &\text{maximize} && 1.5x_0 + 2.5x_1 + 3.0x_2 \\
 &\text{subject to} && 3x_0 + 4x_1 + 3x_2 \leq 100000, \\
 & && 3x_0 + 2x_1 + 3x_2 \leq 50000, \\
 & && 2x_0 + 3x_1 + 2x_2 \leq 60000,
 \end{aligned} \tag{5.11}$$

and

$$x_0, x_1, x_2 \geq 0.$$

After changing the A matrix we can find the new optimal solution by calling `MSK_optimize` again.

5.10.3 Appending variables

We now want to add a new product with the following data:

Product no.	Assembly (minutes)	Polishing (minutes)	Packing (minutes)	Profit (\$)
3	4	0	1	1.00

This corresponds to creating a new variable x_3 , appending a new column to the A matrix and setting a new value in the objective. We do this in the following code.

```

127  /* Get index of new variable, this should be 3 */
128  if (r == MSK_RES_OK)
129      r = MSK_getnumvar(task,&varidx);
130
131  /* Append a new variable x_3 to the problem */
132  if (r == MSK_RES_OK)
133      r = MSK_appendvars(task,1);
134
135  /* Set bounds on new variable */
136  if (r == MSK_RES_OK)
137      r = MSK_putvarbound(task,
138                          varidx,
139                          MSK_BK_LO,
140                          0,
141                          +MSK_INFINITY);
142
143  /* Change objective */
144  if (r == MSK_RES_OK)

```

```

145     r = MSK_putcj(task,varidx,1.0);
146
147     /* Put new values in the A matrix */
148     if (r == MSK_RES_OK)
149     {
150         MSKint32t acolsub[] = {0, 2};
151         double     acolval[] = {4.0, 1.0};
152
153         r = MSK_putacol(task,
154                         varidx, /* column index */
155                         2, /* num nz in column*/
156                         acolsub,
157                         acolval);
158     }

```

After this operation the problem looks this way:

$$\begin{array}{llllllll}
 \text{maximize} & 1.5x_0 & + & 2.5x_1 & + & 3.0x_2 & + & 1.0x_3 \\
 \text{subject to} & 3x_0 & + & 4x_1 & + & 3x_2 & + & 4x_3 & \leq & 100000, \\
 & 3x_0 & + & 2x_1 & + & 3x_2 & & & \leq & 50000, \\
 & 2x_0 & + & 3x_1 & + & 2x_2 & + & 1x_3 & \leq & 60000,
 \end{array} \tag{5.12}$$

and

$$x_0, x_1, x_2, x_3 \geq 0.$$

5.10.4 Reoptimization

When `MSK_optimize` is called MOSEK will store the optimal solution internally. After a task has been modified and `MSK_optimize` is called again the solution will automatically be used to reduce solution time of the new problem, if possible.

In this case an optimal solution to problem (5.11) was found and then added a column was added to get (5.12). The simplex optimizer is well suited for exploiting an existing primal or dual feasible solution. Hence, the subsequent code instructs MOSEK to choose the simplex optimizer freely when optimizing.

```

160     /* Change optimizer to free simplex and reoptimize */
161     if (r == MSK_RES_OK)
162     {
163         r = MSK_putintparam(task,MSK_IPAR_OPTIMIZER,MSK_OPTIMIZER_FREE_SIMPLEX);
164
165         if (r == MSK_RES_OK)
166         {
167             r = MSK_optimizetrm(task,NULL);
168         }
169     }

```

5.10.5 Appending constraints

Now suppose we want to add a new stage to the production called "Quality control" for which 30000 minutes are available. The time requirement for this stage is shown below:

Product no.	Quality control (minutes)
0	1
1	2
2	1
3	1

This corresponds to adding the constraint

$$x_0 + 2x_1 + x_2 + x_3 \leq 30000$$

to the problem which is done in the following code:

[production.c]

```

167  /* Get index of new constraint */
168  if (r == MSK_RES_OK)
169      r = MSK_getnumcon(task,&conidx);
170
171  /* Append a new constraint */
172  if (r == MSK_RES_OK)
173      r = MSK_appendcons(task,1);
174
175  /* Set bounds on new constraint */
176  if (r == MSK_RES_OK)
177      r = MSK_putconbound(task,
178                          conidx,
179                          MSK_BK_UP,
180                          -MSK_INFINITY,
181                          30000);
182
183  /* Put new values in the A matrix */
184  if (r == MSK_RES_OK)
185      {
186          MSKidx_t arowsub[] = {0, 1, 2, 3 };
187          double arowval[] = {1.0, 2.0, 1.0, 1.0};
188
189          r = MSK_putarow(task,
190                          conidx, /* row index */
191                          4,      /* num nz in row*/
192                          arowsub,
193                          arowval);
194      }

```

5.11 Solution analysis

5.11.1 Retrieving solution quality information with the API

Information about the solution quality may be retrieved in the API with the help of the following functions:

- **MSK_getsolutioninfo**: Obtains information about objective values and the solution violations of the constraints.

- **MSK_analyzesolution**: Print additional information about the solution, e.g basis condition number and optionally a list of violated constraints.
- **MSK_getpviolcon**, **MSK_getpviolvar**, **MSK_getpviolbarvar**, **MSK_getpviolcones**, **MSK_getdviolcon**, **MSK_getdviolvar**, **MSK_getdviolbarvar**, **MSK_getdviolcones**. Obtains violation of the individual constraints.

The example below shows how to use these function to determine the quality of the solution.

```
/*
Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.

File:    solutionquality.c

Purpose: To demonstrate how to examine the quality of a solution.
*/

#include <math.h>

#include "mosek.h"

static void MSKAPI printstr(void *handle,
                           MSKCONST char str[])
{
    printf("%s",str);
} /* printstr */

double double_min(double arg1,double arg2)
{
    return arg1>arg2 ? arg2 : arg1;
}

double double_max(double arg1,double arg2)
{
    return arg1<arg2 ? arg2 : arg1;
}

int main (int argc, char * argv[])
{
    MSKrescodee r  = MSK_RES_OK;

    if ( argc<=1)
    {
        printf ("Missing argument. The syntax is:\n");
        printf (" simple inputfile [ solutionfile ]\n");
    }
    else
    {
        MSKtask_t    task = NULL;
        MSKenv_t     env  = NULL;

        r = MSK_makeenv(&env,NULL);

        if ( r==MSK_RES_OK )
            r = MSK_makeemptytask(env,&task);

        if ( r==MSK_RES_OK )
```

```

MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);

/* We assume that a problem file was given as the first command
   line argument (received in 'argv'). */
if ( r==MSK_RES_OK )
    r = MSK_readdata(task,argv[1]);

/* Solve the problem */
if ( r==MSK_RES_OK )
{
    MSKrescodee trmcode;

    r = MSK_optimizetrm(task,&trmcode);
}

/* Print a summary of the solution. */
MSK_solutionsummary(task, MSK_STREAM_MSG);

if ( r==MSK_RES_OK )
{
    MSKsolstae solsta;
    MSKrealt primalobj,pviolcon,pviolvar,pviolbarvar,pviolcones,pviolitg,
    dualobj,dviolcon,dviolvar,dviolbarvar,dviolcones;
    MSKsoltypee whichsol=MSK_SOL_BAS;
    int accepted=0;

    MSK_getsolsta(task,whichsol,&solsta);

    r = MSK_getsolutioninfo(task,
                            whichsol,
                            &primalobj,
                            &pviolcon,
                            &pviolvar,
                            &pviolbarvar,
                            &pviolcones,
                            &pviolitg,
                            &dualobj,
                            &dviolcon,
                            &dviolvar,
                            &dviolbarvar,
                            &dviolcones);

    switch( solsta )
    {
        case MSK_SOL_STA_OPTIMAL:
        case MSK_SOL_STA_NEAR_OPTIMAL:
        {
            double max_primal_viol, /* maximal primal violation */
                   max_dual_viol, /* maximal dual violation */
                   abs_obj_gap,
                   rel_obj_gap;

            abs_obj_gap = fabs(dualobj-primalobj);
            rel_obj_gap = abs_obj_gap/(1.0+double_min(fabs(primalobj),fabs(dualobj)));
            max_primal_viol = double_max(pviolcon,pviolvar);
            max_primal_viol = double_max(max_primal_viol ,pviolbarvar);
            max_primal_viol = double_max(max_primal_viol ,pviolcones);
        }
    }
}

```

```

max_dual_viol = double_max(dviolcon,dviolvar);
max_dual_viol = double_max(max_dual_viol ,dviolbarvar);
max_dual_viol = double_max(max_dual_viol ,dviolcones);

/* Assume the application needs the solution to be within
   1e-6 of optimality in an absolute sense. Another approach
   would be looking at the relative objective gap */

printf("\n\n");
printf("Customized solution information.\n");
printf(" Absolute objective gap: %e\n",abs_obj_gap);
printf(" Relative objective gap: %e\n",rel_obj_gap);
printf(" Max primal violation : %e\n",max_primal_viol);
printf(" Max dual violation   : %e\n",max_dual_viol);

if ( rel_obj_gap>1e-6 )
{
    printf("Warning: The relative objective gap is LARGE.\n");
    accepted = 0;
}

/* We will accept a primal infeasibility of 1e-8 and
   dual infeasibility of 1e-6. These number should chosen problem
   dependent.
   */

if ( max_primal_viol>1e-8 )
{
    printf("Warning: Primal violation is too LARGE.\n");
    accepted = 0;
}

if ( max_dual_viol>1e-6 )
{
    printf("Warning: Dual violation is too LARGE.\n");
    accepted = 0;
}

if ( accepted )
{
    MSKint32t numvar,j;
    MSKrealt xj;

    if ( MSK_RES_OK==MSK_getnumvar(task,&numvar) )
    {
        printf("Optimal primal solution\n");
        for(j=0; j<numvar && r==MSK_RES_OK; ++j)
        {
            r = MSK_getxxslice(task,whchsol,j,j+1,&xj);
            if ( r==MSK_RES_OK )
                printf("x[%d]: %e\n",j,xj);
        }
    }
}
else if ( r==MSK_RES_OK )
{
    /* Print detailed information about the solution */

```

```

        r = MSK_analyzesolution(task,MSK_STREAM_LOG,whichsol);
    }
    break;
}
case MSK_SOL_STA_DUAL_INFEAS_CER:
case MSK_SOL_STA_PRIM_INFEAS_CER:
case MSK_SOL_STA_NEAR_DUAL_INFEAS_CER:
case MSK_SOL_STA_NEAR_PRIM_INFEAS_CER:
    printf("Primal or dual infeasibility certificate found.\n");
    break;
case MSK_SOL_STA_UNKNOWN:
    printf("The status of the solution is unknown.\n");
    break;
default:
    printf("Other solution status");
    break;
}
}
}

MSK_deletetask(&task);
MSK_deleteenv(&env);
}
return ( r );
}

```

5.12 Efficiency considerations

Although MOSEK is implemented to handle memory efficiently, the user may have valuable knowledge about a problem, which could be used to improve the performance of MOSEK. This section discusses some tricks and general advice that hopefully make MOSEK process your problem faster.

Avoiding memory fragmentation:

MOSEK stores the optimization problem in internal data structures in the memory. Initially MOSEK will allocate structures of a certain size, and as more items are added to the problem the structures are reallocated. For large problems the same structures may be reallocated many times causing memory fragmentation. One way to avoid this is to give MOSEK an estimated size of your problem using the functions:

- **MSK_putmaxnumvar**. Estimate for the number of variables.
- **MSK_putmaxnumcon**. Estimate for the number of constraints.
- **MSK_putmaxnumcone**. Estimate for the number of cones.
- **MSK_putmaxnumbarvar**. Estimate for the number of semidefinite matrix variables.
- **MSK_putmaxnumanz**. Estimate for the number of non-zeros in A .
- **MSK_putmaxnumqnz**. Estimate for the number of non-zeros in the quadratic terms.

None of these functions change the problem, they only give hints to the eventual dimension of the problem. If the problem ends up growing larger than this, the estimates are automatically increased.

Do not mix `put-` and `get-` functions:

For instance, the functions `MSK.putacol` and `MSK.getacol`. MOSEK will queue `put-` commands internally until a `get-` function is called. If every `put-` function call is followed by a `get-` function call, the queue will have to be flushed often, decreasing efficiency.

In general `get-` commands should not be called often during problem setup.

Use the LIFO principle when removing constraints and variables:

MOSEK can more efficiently remove constraints and variables with a high index than a small index.

An alternative to removing a constraint or a variable is to fix it at 0, and set all relevant coefficients to 0. Generally this will not have any impact on the optimization speed.

Add more constraints and variables than you need (now):

The cost of adding one constraint or one variable is about the same as adding many of them. Therefore, it may be worthwhile to add many variables instead of one. Initially fix the unused variable at zero, and then later unfix them as needed. Similarly, you can add multiple free constraints and then use them as needed.

Use one environment (`env`) only:

If possible share the environment (`env`) between several tasks. For most applications you need to create only a single `env`.

Do not remove basic variables:

When doing re-optimizations, instead of removing a basic variable it may be more efficient to fix the variable at zero and then remove it when the problem is re-optimized and it has left the basis. This makes it easier for MOSEK to restart the simplex optimizer.

5.13 Conventions employed in the API

5.13.1 Naming conventions for arguments

In the definition of the MOSEK C API a consistent naming convention has been used. This implies that whenever for example `numcon` is an argument in a function definition it indicates the number of constraints.

In Table 5.2 the variable names used to specify the problem parameters are listed. The relation between the variable names and the problem parameters is as follows:

- The quadratic terms in the objective:

$$q_{qosubi[t], qosubj[t]}^o = qoval[t], \quad t = 0, \dots, numqonz - 1. \quad (5.13)$$

- The linear terms in the objective:

$$c_j = c[j], \quad j = 0, \dots, numvar - 1 \quad (5.14)$$

C name	C type	Dimension	Related problem parameter
numcon	int		m
numvar	int		n
numcone	int		t
numqonz	int		q_{ij}^o
qosubi	int[]	numqonz	q_{ij}^o
qosubj	int[]	numqonz	q_{ij}^o
qoval			
qoval	double*	numqonz	q_{ij}^o
c	double[]	numvar	c_j
cfix	double		c^f
numqcnz	int		q_{ij}^k
qcsubk	int[]	qcnz	q_{ij}^k
qcsubi	int[]	qcnz	q_{ij}^k
qcsubj	int[]	qcnz	q_{ij}^k
qcval	double*	qcnz	q_{ij}^k
aptrb	int[]	numvar	a_{ij}
aptre	int[]	numvar	a_{ij}
asub	int[]	aptre[numvar-1]	a_{ij}
aval	double[]	aptre[numvar-1]	a_{ij}
bkc	MSKboundkeye*	numcon	l_k^c and u_k^c
blc	double[]	numcon	l_k^c
buc	double[]	numcon	u_k^c
bkx	MSKboundkeye*	numvar	l_k^x and u_k^x
blx	double[]	numvar	l_k^x
bux	double[]	numvar	u_k^x

Table 5.2: Naming conventions used in the MOSEK C API.

Symbolic constant	Lower bound	Upper bound
MSK_BK_FX	finite	identical to the lower bound
MSK_BK_FR	minus infinity	plus infinity
MSK_BK_LO	finite	plus infinity
MSK_BK_RA	finite	finite
MSK_BK_UP	minus infinity	finite

Table 5.3: Interpretation of the bound keys.

- The fixed term in the objective:

$$c^f = \mathbf{cfix}.$$

- The quadratic terms in the constraints:

$$q_{qcsubi[t], qcsbj[t]}^{qcsbk[t]} = \mathbf{qcval}[t], \quad t = 0, \dots, \mathbf{numqcnz} - 1. \quad (5.15)$$

- The linear terms in the constraints:

$$a_{asub[t], j} = \mathbf{aval}[t], \quad t = \mathbf{ptrb}[j], \dots, \mathbf{ptre}[j] - 1, \\ j = 0, \dots, \mathbf{numvar} - 1. \quad (5.16)$$

- The bounds on the constraints are specified using the variables **bkc**, **blc**, and **buc**. The components of the integer array **bkc** specify the bound type according to Table 5.3. For instance **bkc**[2]=**MSK_BK_LO** means that $-\infty < l_2^c$ and $u_2^c = \infty$. Finally, the numerical values of the bounds are given by

$$l_k^c = \mathbf{blc}[k], \quad k = 0, \dots, \mathbf{numcon} - 1$$

and

$$u_k^c = \mathbf{buc}[k], \quad k = 0, \dots, \mathbf{numcon} - 1.$$

- The bounds on the variables are specified using the variables **bkx**, **blx**, and **bux**. The components in the integer array **bkx** specify the bound type according to Table 5.3. The numerical values for the lower bounds on the variables are given by

$$l_j^x = \mathbf{blx}[j], \quad j = 0, \dots, \mathbf{numvar} - 1.$$

The numerical values for the upper bounds on the variables are given by

$$u_j^x = \mathbf{bux}[j], \quad j = 0, \dots, \mathbf{numvar} - 1.$$

5.13.1.1 Bounds

A bound on a variable or on a constraint in MOSEK consists of a *bound key*, as defined in Table 5.3, a lower bound value and an upper bound value. Even if a variable or constraint is bounded only from below, e.g. $x \geq 0$, both bounds are inputted or extracted; the value inputted as upper bound for ($x \geq 0$) is ignored.

5.13.2 Vector formats

Three different vector formats are used in the MOSEK API:

Full vector:

This is simply an array where the first element corresponds to the first item, the second element to the second item etc. For example to get the linear coefficients of the objective in `task`, one would write

```
MSKrealt * c = MSK_calloc(task, numvar, sizeof(MSKrealt));

if ( c )
    res = MSK_getc(task,c);
else
    printf("Out of space\n");
```

where `numvar` is the number of variables in the problem.

Vector slice:

A vector slice is a range of values. For example, to get the bounds associated constraint 3 through 10 (both inclusive) one would write

```
MSKrealt * upper_bound = MSK_calloc(task,8,sizeof(MSKrealt));
MSKrealt * lower_bound = MSK_calloc(task,8,sizeof(MSKrealt));
MSKboundkey * bound_key = MSK_calloc(task,8,sizeof(MSKboundkey));
res = MSK_getboundslice(task,MSK_ACC_CON, 2,10,
                        bound_key,lower_bound,upper_bound);
```

Please note that items in MOSEK are numbered from 0, so that the index of the first item is 0, and the index of the n 'th item is $n - 1$.

Sparse vector:

A sparse vector is given as an array of indexes and an array of values. For example, to input a set of bounds associated with constraints number 1, 6, 3, and 9, one might write

```
MSKint32t   bound_index[] = {      1,      6,      3,      9 };
MSKboundkey bound_key[]   = { MSK_BK_FR, MSK_BK_LO, MSK_BK_UP, MSK_BK_FX };
MSKrealt    lower_bound[] = {    0.0,   -10.0,    0.0,    5.0 };
MSKrealt    upper_bound[] = {    0.0,    0.0,    6.0,    5.0 };
```

```
res = MSK_putconboundlist(task, 4, bound_index,
                          bound_key, lower_bound, upper_bound);
```

Note that the list of indexes need not be ordered.

5.13.3 Matrix formats

The coefficient matrices in a problem are inputted and extracted in a sparse format, either as complete or a partial matrices. Basically there are two different formats for this.

5.13.3.1 Unordered triplets

In unordered triplet format each entry is defined as a row index, a column index and a coefficient. For example, to input the A matrix coefficients for $a_{1,2} = 1.1$, $a_{3,3} = 4.3$, and $a_{5,4} = 0.2$, one would write as follows:

```
MSKint32t subi[] = { 1, 3, 5 },
               subj[] = { 2, 3, 4 };
MSKrealt cof[] = { 1.1, 4.3, 0.2 };

res = MSK_putaijlist(task, 3, subi, subj, cof);
```

Please note that in some cases (like [MSK.putaijlist64](#)) *only* the specified indexes remain modified — all other are unchanged. In other cases (such as [MSK.putqconk](#)) the triplet format is used to modify *all* entries — entries that are not specified are set to 0.

5.13.3.2 Row or column ordered sparse matrix

In a sparse matrix format only the non-zero entries of the matrix are stored. MOSEK uses a sparse packed matrix format ordered either by rows or columns. In the column-wise format the position of the non-zeros are given as a list of row indexes. In the row-wise format the position of the non-zeros are given as a list of column indexes. Values of the non-zero entries are given in column or row order.

A sparse matrix in column ordered format consists of:

asub:

List of row indexes.

aval:

List of non-zero entries of A ordered by columns.

ptrb:

Where $\text{ptrb}[j]$ is the position of the first value/index in **aval** / **asub** for column j .

ptre:

Where $\text{ptre}[j]$ is the position of the last value/index plus one in **aval** / **asub** for column j .




Figure 5.1: The matrix A (5.17) represented in column ordered packed sparse matrix format.

The values of a matrix A with `numcol` columns are assigned so that for

$$j = 0, \dots, \text{numcol} - 1.$$

We define

$$a_{\text{asub}[k],j} = \text{aval}[k], k = \text{ptrb}[j], \dots, \text{ptre}[j] - 1.$$

As an example consider the matrix

$$A = \begin{bmatrix} 1.1 & & 1.3 & 1.4 & & \\ & 2.2 & & & 2.5 & \\ 3.1 & & & 3.4 & & \\ & & 4.4 & & & \end{bmatrix}. \quad (5.17)$$

which can be represented in the column ordered sparse matrix format as

$$\begin{aligned} \text{ptrb} &= [0, 2, 3, 5, 7], \\ \text{ptre} &= [2, 3, 5, 7, 8], \\ \text{asub} &= [0, 2, 1, 0, 3, 0, 2, 1], \\ \text{aval} &= [1.1, 3.1, 2.2, 1.3, 4.4, 1.4, 3.4, 2.5]. \end{aligned}$$

Fig. 5.1 illustrates how the matrix A (5.17) is represented in column ordered sparse matrix format.

5.13.3.3 Row ordered sparse matrix

The matrix A (5.17) can also be represented in the row ordered sparse matrix format as:

```

ptrb  = [0, 3, 5, 7],
ptre  = [3, 5, 7, 8],
asub  = [0, 2, 3, 1, 4, 0, 3, 2],
aval  = [1.1, 1.3, 1.4, 2.2, 2.5, 3.1, 3.4, 4.4].

```

5.14 The license system

By default a license token is checked out when `MSK_optimizetrm` is first called and is returned when the MOSEK environment is deleted. Calling `MSK_optimizetrm` from different threads using the same MOSEK environment only consumes one license token.

To change the license systems behavior to returning the license token after each call to `MSK_optimizetrm` set the parameter `MSK_IPAR_CACHE_LICENSE` to `MSK_OFF`. Please note that there is a small overhead associated with setting this parameter, since checking out a license token from the license server can take a small amount of time.

Additionally license checkout and checkin can be controlled manually with the functions `MSK_checkinlicense` and `MSK_checkoutlicense`.

5.14.1 Waiting for a free license

By default an error will be returned if no license token is available. By setting the parameter `MSK_IPAR_LICENSE_WAIT` MOSEK can be instructed to wait until a license token is available.

Chapter 6

Nonlinear API tutorial

This chapter provides information about how to solve general convex nonlinear optimization problems using MOSEK. By general nonlinear problems it is meant problems that cannot be formulated as a conic quadratic optimization or a convex quadratically constrained optimization problem.

In general it is recommended not to use nonlinear optimizer unless needed. The reasons are

- MOSEK has no way of checking whether the formulated problem is convex and if this assumption is not satisfied the optimizer will not work.
- The nonlinear optimizer requires 1st and 2nd order derivative information which is hard to provide correctly i.e. it is nontrivial to program the code that computes the derivative information.
- The specification of nonlinear problems requires C function callbacks. Such C function callbacks cannot be dump to disk and that makes it hard to report issues to MOSEK support.
- The algorithm employed for nonlinear optimization problems is not as good as the one employed for conic problems i.e. conic problems has special that can be exploited to make the optimizer faster and more robust.

This leads to following advices in decreasing order of importance.

- Consider reformulating the problem to a conic quadratic optimization problem if at all possible. In particular many problems involving polynomial terms can easily be reformulated to conic quadratic form.
- Consider reformulating the problem to a separable optimization problem because that simplifies the issue with verifying convexity and computing 1st and 2nd order derivatives significantly. In most cases problems on separable form also solves faster because of the simpler structure of the functions. In [Section 6.1](#) some utility code that makes it easy to solve separable problems is discussed.
- Finally, if the problem cannot be reformulated to separable form then use a modelling language like AMPL or GAMS. The reason is the modeling language will do all the computing of function

values and derivatives. This eliminates an important source of errors. Therefore, it is strongly recommended to use a modelling language at the prototype stage.

6.1 Separable convex optimization

In this section we will discuss solution of nonlinear **separable** convex optimization problems using MOSEK. We allow both nonlinear constraints and objective, but restrict ourselves to separable functions. A separable function is a function that has the form

$$f(x) = \sum_j g_j(x_j)$$

and hence it is sum a single variable functions.

6.1.1 The separable problem

A general separable nonlinear optimization problem can be specified as follows:

$$\begin{array}{ll} \text{minimize} & f(x) + c^T x \\ \text{subject to} & \begin{array}{ll} l^c & \leq g(x) + Ax & \leq u^c, \\ l^x & \leq x & \leq u^x, \end{array} \end{array} \quad (6.1)$$

where

- m is the number of constraints.
- n is the number of decision variables.
- $x \in \mathbb{R}^n$ is a vector of decision variables.
- $c \in \mathbb{R}^n$ is the linear part of the objective function.
- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.
- $f : \mathbb{R}^n \rightarrow \mathbb{R}$ is a nonlinear function.
- $g : \mathbb{R}^n \rightarrow \mathbb{R}^m$ is a nonlinear vector function.

This implies that the i th constraint essentially has the form

$$l_i^c \leq g_i(x) + \sum_{j=1}^n a_{ij}x_j \leq u_i^c.$$

The problem (6.1) must satisfy the three important requirements:

- Separability: This requirement implies that all nonlinear functions can be written on the form

$$f(x) = \sum_{j=1}^n f^j(x_j)$$

and

$$g_i(x) = \sum_{j=1}^n g_i^j(x_j)$$

where

$$f^j : \mathbb{R} \rightarrow \mathbb{R} \text{ and } g_i^j : \mathbb{R} \rightarrow \mathbb{R}.$$

Hence, the nonlinear functions can be written as a sum of functions which depends only on one variable.

- Differentiability: All functions should be twice differentiable for all x_j satisfying

$$l_j^x < x < u_j^x$$

if x_j occurs in at least one nonlinear function.

- Convexity: The problem should be a convex optimization problem. See Section 10.5 for a discussion of this requirement.

6.1.2 An example

Subsequently, we will use the following example to demonstrate the solution of a separable convex optimization problem using MOSEK

$$\begin{aligned} & \text{minimize} && x_1 - \ln(x_1 + 2x_2) \\ & \text{subject to} && x_1^2 + x_2^2 \leq 1. \end{aligned} \tag{6.2}$$

First note that the problem (6.2) is not a separable optimization problem because the logarithmic term in the objective is not a function of a single variable. However, by introducing a constraint and a variable the problem can be made separable as follows

$$\begin{aligned}
& \text{minimize} && x_1 - \ln(x_3) \\
& \text{subject to} && x_1^2 + x_2^2 \leq 1, \\
& && x_1 + 2x_2 - x_3 = 0, \\
& && x_3 \geq 0.
\end{aligned} \tag{6.3}$$

This problem is obviously separable and equivalent to the previous problem. Moreover, note that all nonlinear functions are well defined for x values satisfying the variable bounds strictly, i.e.

$$x_3 > 0.$$

This assures that function evaluation errors will not occur during the optimization process because MOSEK will only evaluate $\ln(x_3)$ for $x_3 > 0$.

The method employed above can often be used to make convex optimization problems separable even if these are not formulated as such initially. The reader might object that this approach is inefficient because additional constraints and variables are introduced to make the problem separable. However, in our experience this drawback is offset largely by the much simpler structure of the nonlinear functions. Particularly, the evaluation of the nonlinear functions, their gradients and Hessians is much easier in the separable case.

6.1.3 The interface for separable convex optimization

`scopt` is an easy-to-use interface to the nonlinear optimizer when solving separable convex problems. As currently implemented, `scopt` is not capable of handling arbitrary nonlinear expressions. In fact `scopt` can handle only the nonlinear expressions $x \log(x)$, e^x , $\log(x)$, and x^g . However, it should be fairly easy to extend the interface to other nonlinear function of a single variable if needed.

6.1.3.1 Design principles of `scopt`

All the linear data of the problem, such as c and A , is inputted to MOSEK as usual, i.e. using the relevant functions in the MOSEK API.

The nonlinear part of the problem is specified using some arrays which indicate the type of the nonlinear expressions and where these should be added.

For example given the three `int` arrays — `oprc`, `opric`, and `oprjc` — and the three `double` arrays — `oprffc`, `oprfgc` and `oprhc` — the nonlinear expressions in the constraints can be coded in those arrays using the following table:

<code>oprc[k]</code>	<code>opric[k]</code>	<code>oprjc[k]</code>	<code>oprffc[k]</code>	<code>oprfgc[k]</code>	<code>oprhc[k]</code>	Expression added to constraint i
0	i	j	f	g	h	$f x_j \ln(x_j)$
1	i	j	f	g	h	$f e^{g x_j + h}$
2	i	j	f	g	h	$f \ln(g x_j + h)$
3	i	j	f	g	h	$f (x_j + h)^g$

Hence, `oprc[k]` specifies the nonlinear expression type, `opric[k]` indicates to which constraint the nonlinear expression should be added. `oprfc[k]`, `oprgc[k]` and `oprhc[k]` are parameters used when the nonlinear expression is evaluated. This implies that nonlinear expressions can be added to an arbitrary constraint and hence you can create multiple nonlinear constraints.

Using the same method all the nonlinear terms in the objective can be specified using `opro[k]`, `oprjo[k]`, `oprfo[k]`, `oprgo[k]` and `oprho[k]` as shown below:

<code>opro[k]</code>	<code>oprjo[k]</code>	<code>oprfo[k]</code>	<code>oprgo[k]</code>	<code>oprho[k]</code>	Expression added in objective
0	j	f	g	h	$fx_j \ln(x_j)$
1	j	f	g	h	fe^{gx_j+h}
2	j	f	g	h	$f \ln(gx_j + h)$
3	j	f	g	h	$f(x_j + h)^g$

6.1.3.2 Example

Suppose we want to add the nonlinear expression $-\ln(x_3)$ to the objective. This is an expression on the form $f \ln(gx_j + h)$ where $f = -1$, $g = 1$, $h = 0$ and $j = 3$. This can be represented by:

```
opro[0] = 2
oprjo[0] = 3
oprfo[0] = -1.0
oprgo[0] = 1.0
oprho[0] = 0.0
```

Similarly, the nonlinear terms in constraints are defined by

```
oprc[0] = 3
opric[0] = 0
oprjc[0] = 0
oprfc[0] = 1.0
oprgc[0] = 2.0
oprhc[0] = 0.0
```

```
oprc[1] = 3
opric[1] = 0
oprjc[1] = 1
oprfc[1] = 1.0
oprgc[1] = 2.0
oprhc[1] = 0.0
```

The solution of the example (6.3) has been implemented in

```

1  /*
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File      : tstscopt.c
5
6  Purpose   : To solve the problem
7
8              minimize    x_1 - log(x_3)
9              subject to  x_1^2 + x_2^2 <= 1
10                       x_1 + 2*x_2 - x_3 = 0

```

```

11             x_3 >=0
12     */
13
14     #include "scopt-ext.h"
15
16     #define NUMOPRO 1 /* Number of nonlinear expressions in the obj. */
17     #define NUMOPRC 2 /* Number of nonlinear expressions in the con. */
18     #define NUMVAR 3 /* Number of variables. */
19     #define NUMCON 2 /* Number of constraints. */
20     #define NUMANZ 3 /* Number of non-zeros in A. */
21
22     static void MSKAPI printstr(void *handle,
23                               MSKCONST char str[])
24     {
25         printf("%s",str);
26     } /* printstr */
27
28     int main()
29     {
30         char          buffer[MSK_MAX_STR_LEN];
31         double        oprfo[NUMOPRO], oprgo[NUMOPRO], oprho[NUMOPRO],
32                     oprfc[NUMOPRC], oprgc[NUMOPRC], oprhc[NUMOPRC],
33                     c[NUMVAR], aval[NUMANZ],
34                     blc[NUMCON], buc[NUMCON], blx[NUMVAR], bux[NUMVAR];
35         int           numopro, numoprc,
36                     numcon=NUMCON, numvar=NUMVAR,
37                     opro[NUMOPRO], oprjo[NUMOPRO],
38                     oprc[NUMOPRC], opric[NUMOPRC], oprjc[NUMOPRC],
39                     aptrb[NUMVAR], aptre[NUMVAR], asub[NUMANZ];
40         MSKboundkeye bkc[NUMCON], bkx[NUMVAR];
41         MSKenv_t      env;
42         MSKrescodee   r;
43         MSKtask_t     task;
44         schand_t       sch;
45
46         /* Specify nonlinear terms in the objective. */
47         numopro = NUMOPRO;
48         opro[0] = MSK_OPR_LOG; /* Defined in scopt.h */
49         oprjo[0] = 2;
50         oprfo[0] = -1.0;
51         oprgo[0] = 1.0; /* This value is never used. */
52         oprho[0] = 0.0;
53
54         /* Specify nonlinear terms in the constraints. */
55         numoprc = NUMOPRC;
56
57         oprc[0] = MSK_OPR_POW;
58         opric[0] = 0;
59         oprjc[0] = 0;
60         oprfc[0] = 1.0;
61         oprgc[0] = 2.0;
62         oprhc[0] = 0.0;
63
64         oprc[1] = MSK_OPR_POW;
65         opric[1] = 0;
66         oprjc[1] = 1;
67         oprfc[1] = 1.0;
68         oprgc[1] = 2.0;

```

```

69     oprhc[1] = 0.0;
70
71     /* Specify c */
72     c[0] = 1.0; c[1] = 0.0; c[2] = 0.0;
73
74     /* Specify a. */
75     aptrb[0] = 0;   aptrb[1] = 1;   aptrb[2] = 2;
76     aptre[0] = 1;   aptre[1] = 2;   aptre[2] = 3;
77     asub[0] = 1;   asub[1] = 1;   asub[2] = 1;
78     aval[0] = 1.0; aval[1] = 2.0; aval[2] = -1.0;
79
80     /* Specify bounds for constraints. */
81     bkc[0] = MSK_BK_UP;   bkc[1] = MSK_BK_FX;
82     blc[0] = -MSK_INFINITY; blc[1] = 0.0;
83     buc[0] = 1.0;   buc[1] = 0.0;
84
85     /* Specify bounds for variables. */
86     bkc[0] = MSK_BK_FR;   bkc[1] = MSK_BK_FR;   bkc[2] = MSK_BK_LO;
87     blx[0] = -MSK_INFINITY; blx[1] = -MSK_INFINITY; blx[2] = 0.0;
88     bux[0] = MSK_INFINITY; bux[1] = MSK_INFINITY; bux[2] = MSK_INFINITY;
89
90     /* Create the mosek environment. */
91     r = MSK_makeenv(&env, NULL);
92
93     if ( r==MSK_RES_OK )
94     {
95         /* Make the optimization task. */
96         r = MSK_makeemptytask(env, &task);
97         if ( r==MSK_RES_OK )
98             MSK_linkfunctotaskstream(task, MSK_STREAM_LOG, NULL, printstr);
99
100        if ( r==MSK_RES_OK )
101        {
102            /* Setup the linear part of the problem. */
103            r = MSK_inputdata(task,
104                               numcon, numvar,
105                               numcon, numvar,
106                               c, 0.0,
107                               aptrb, aptre,
108                               asub, aval,
109                               bkc, blc, buc,
110                               bkc, blx, bux);
111        }
112
113        if ( r== MSK_RES_OK )
114        {
115            /* Set-up of nonlinear expressions. */
116            r = MSK_scbegin(task,
117                           numopro, opro, oprjo, oprfo, oprgo, oprho,
118                           numoprc, oprc, opric, oprjc, oprfc, oprgc, oprhc,
119                           &sch);
120
121            if ( r==MSK_RES_OK )
122            {
123                printf("Start optimizing\n");
124
125                r = MSK_optimize(task);
126

```

```

127     printf("Done optimizing\n");
128
129     MSK_solutionsummary(task,MSK_STREAM_MSG);
130 }
131
132     /* The nonlinear expressions are no longer needed. */
133     MSK_scend(task,&sch);
134 }
135     MSK_deletetask(&task);
136 }
137     MSK_deleteenv(&env);
138
139     printf("Return code: %d\n",r);
140     if ( r!=MSK_RES_OK )
141     {
142         MSK_getcodedesc(r,buffer,NULL);
143         printf("Description: %s\n",buffer);
144     }
145
146     return r;
147 } /* main */

```

. tstscopt.c is a driver program where the main setup is performed in `scopt-ext.c` which has the content

```

                                     [scopt-ext.c]
1  /*
2      Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4      File      : scopt-ext.c
5
6      */
7
8  #include <math.h>
9  #include <stdio.h>
10 #include <stdlib.h>
11 #include <string.h>
12
13 #include "scopt-ext.h"
14
15 #define DEBUG 0
16
17 typedef struct
18 {
19     /*
20      * Data structure for storing
21      * data about the nonlinear
22      * functions.
23      */
24
25     int    numcon;      /* Number of constraints. */
26     int    numvar;      /* Number of variables.  */
27     int    numopro;
28     int    *opro;
29     int    *oprjo;
30     double *oprfo;
31     double *oprgo;

```

```

32         double *oprho;
33
34         int    numoprc;
35         int    *oprc;
36         int    *opric;
37         int    *oprjc;
38         double *oprfc;
39         double *oprgc;
40         double *oprhc;
41
42         /* */
43         int    *ptrc;
44         int    *subc;
45
46         /* Work storage employed when evaluating the functions. */
47         int    *ibuf;
48         int    *zibuf;
49         double *zdbuf;
50
51     } nlhandt;
52
53     typedef nlhandt *nlhand_t;
54
55     static void scgrdobjstruc(nlhand_t nlh,
56                             int        *nz,
57                             int        *sub)
58     /* Purpose: Compute number of nonzeros and sparsity
59        pattern of the gradient of the objective function.
60        */
61     {
62         int j,k,
63             *zibuf;
64
65         zibuf = nlh->zibuf;
66
67         #if DEBUG
68         printf("scgrdobjstruc: begin\n");
69         #endif
70
71         if ( nz )
72         {
73             nz[0] = 0;
74             for(k=0; k<nlh->numopro; ++k)
75             {
76                 j = nlh->oprjo[k];
77
78                 if ( !zibuf[j] )
79                 {
80                     /* A new nonzero in the gradient of the objective has been located. */
81
82                     if ( sub )
83                         sub[nz[0]] = j;
84
85                     ++ nz[0];
86                     zibuf[j] = 1;
87                 }
88             }
89

```

```

90
91     /* Zero zibuf again. */
92     for(k=0; k<nlh->numopro; ++k)
93     {
94         j          = nlh->oprjo[k];
95         zibuf[j] = 0;
96     }
97 }
98
99 #if DEBUG>5
100 printf("grdnz: %d\n",nz[0]);
101 #endif
102 #if DEBUG
103 printf("scgrdobjstruc: end\n");
104 #endif
105
106 } /* scgrdobjstruc */
107
108 static void scgrdconistruc(nlhand_t nlh,
109                          int      i,
110                          int      *nz,
111                          int      *sub)
112 {
113     int j,k,
114         *zibuf;
115
116     #if DEBUG
117     printf("scgrdconistruc: begin\n");
118     #endif
119
120     zibuf = nlh->zibuf;
121
122     nz[0] = 0;
123     if ( nlh->ptrc )
124     {
125         for(k=nlh->ptrc[i]; k<nlh->ptrc[i+1]; ++k)
126         {
127             j = nlh->oprjc[nlh->subc[k]];
128
129             if ( !zibuf[j] )
130             {
131                 /* A new nonzero in the gradient of the ith
132                    constraint has been located. */
133
134                 if ( sub )
135                     sub[nz[0]] = j;
136
137                 ++ nz[0];
138                 zibuf[j] = 1;
139             }
140         }
141
142         /* Zero zibuf again. */
143         for(k=nlh->ptrc[i]; k<nlh->ptrc[i+1]; ++k)
144         {
145             j          = nlh->oprjc[nlh->subc[k]];
146             zibuf[j] = 0;
147         }

```

```

148     }
149
150     #if DEBUG>5
151     printf("i: %d nz: %d\n",i,nz[0]);
152     #endif
153     #if DEBUG
154     printf("scgrdconistruc: end\n");
155     #endif
156 } /* scgrdconistruc */
157
158 static int schesstruc(nlh_t      nlh,
159                     int         yo,
160                     int         numycnz,
161                     MSKCONST int *ybsub,
162                     int         *nz,
163                     int         *sub)
164 /* Computes the number nonzeros the lower triangular part of
165    the Hessian of the Lagrange function and sparsity pattern.
166
167    nz: Number of nonzeros in the Hessian of the Lagrange function.
168    sub: List of nonzero diagonal elements in the Hessian.
169    The separable structure is exploited.
170 */
171 {
172     int i,j,k,p,
173         *zibuf;
174
175     #if DEBUG
176     printf("schesstruc: begin\n");
177     #endif
178
179     zibuf = nlh->zibuf;
180
181     nz[0] = 0;
182
183     if ( yo )
184     {
185         /* Information about the objective function should be computed. */
186         for(k=0; k<nlh->numopro; ++k)
187         {
188             j = nlh->oprjo[k];
189
190             if ( !zibuf[j] )
191             {
192                 /* A new nonzero in the gradient has been located. */
193
194                 if ( sub )
195                     sub[nz[0]] = j;
196
197                 ++ nz[0];
198                 zibuf[j] = 1;
199             }
200         }
201     }
202
203     if ( nlh->ptrc )
204     {
205         /* Evaluate the sparsity of the Hessian. Only constraints specified

```

```

206         by ycsb should be included.
207     */
208     for(p=0; p<numycnz; ++p)
209     {
210         i = ycsb[p]; /* Constraint index. */
211         for(k=nlh->ptrc[i]; k<nlh->ptrc[i+1]; ++k)
212         {
213             j = nlh->oprjc[nlh->subc[k]];
214
215             if ( !zibuf[j] )
216             {
217                 /* A new nonzero diagonal element in the Hessian has been located. */
218                 if ( sub )
219                     sub[nz[0]] = j;
220
221                 ++ nz[0];
222                 zibuf[j] = 1;
223             }
224         }
225     }
226 }
227
228 /*
229  * Zero work vectors.
230  */
231
232 if ( yo )
233 {
234     for(k=0; k<nlh->numopro; ++k)
235     {
236         j = nlh->oprjo[k];
237         zibuf[j] = 0;
238     }
239 }
240
241 if ( nlh->ptrc )
242 {
243     for(p=0; p<numycnz; ++p)
244     {
245         i = ycsb[p];
246         for(k=nlh->ptrc[i]; k<nlh->ptrc[i+1]; ++k)
247         {
248             j = nlh->oprjc[nlh->subc[k]];
249             zibuf[j] = 0;
250         }
251     }
252 }
253
254 #if DEBUG>5
255 printf("Hessian size: %d\n",nz[0]);
256 #endif
257 #if DEBUG
258 printf("schesstruc: end\n");
259 #endif
260
261 return ( MSK_RES_OK );
262 } /* schesstruc */
263

```



```

264 static int MSKAPI scstruc(void      *nlhandle,
265                             int      *numgrdobjnz,
266                             int      *grdobjsub,
267                             int      i,
268                             int      *convali,
269                             int      *grdconinz,
270                             int      *grdconisub,
271                             int      yo,
272                             int      numycnz,
273                             MSKCONST int *ycsub,
274                             int      maxnumhesnz,
275                             int      *numhesnz,
276                             int      *hessubi,
277                             int      *hessubj)
278 /* Purpose: Provide information to MOSEK about the
279    problem structure and sparsity.
280 */
281 {
282     int k, itemp;
283     nlhand_t nlh;
284
285     #if DEBUG
286     printf("scstruc: begin\n");
287     #endif
288
289     nlh = (nlhand_t) nlhandle;
290
291     if ( numgrdobjnz )
292         scgrdobjstruc(nlh,numgrdobjnz,grdobjsub);
293
294     if ( convali || grdconinz )
295     {
296         scgrdconistruc(nlh,i,&itemp,grdconisub);
297
298         if ( convali )
299             convali[0] = itemp>0;
300
301         if ( grdconinz )
302             grdconinz[0] = itemp;
303     }
304
305     if ( numhesnz )
306     {
307         #if DEBUG
308         printf("Evaluate Hessian structure yo: %d\n",yo);
309         #endif
310
311         schesstruc(nlh,yo,numycnz,ycsub,numhesnz,hessubi);
312
313         if ( numhesnz[0]>maxnumhesnz && hessubi )
314         {
315             printf("%s(%d): Hessian size error. %d %d\n",__FILE__,__LINE__,numhesnz[0],maxnumhesnz);
316             exit(0);
317         }
318
319         if ( hessubi )
320         {
321             /* In this case the Hessian is diagonal matrix. */

```

```

322
323     for(k=0; k<numhesnz[0]; ++k)
324         hessubj[k] = hessubi[k];
325     }
326 }
327
328 #if DEBUG>5
329 if ( numhesnz )
330 {
331     printf("Number of Hessian nonzeros: %d\n",numhesnz[0]);
332 }
333 #endif
334
335 #if DEBUG
336 printf("scstruc: end\n");
337 #endif
338
339 return ( MSK_RES_OK );
340 } /* scstruc */
341
342 static int evalopr(int    opr,
343                   double f,
344                   double g,
345                   double h,
346                   double xj,
347                   double *fxj,
348                   double *grdfxj,
349                   double *hesfxj)
350 /* Purpose: Evaluates an operator and its derivatives.
351    fxj:      Is the function value
352    grdfxj:   Is the first derivative.
353    hesfxj:   Is the second derivative.
354    */
355 {
356     double rtemp;
357
358     switch ( opr )
359     {
360     case MSK_OPR_ENT:
361         if ( xj<=0.0 ) {
362             return ( 1 );
363         }
364
365         if ( fxj )
366             fxj[0] = f*xj*log(xj);
367
368         if ( grdfxj )
369             grdfxj[0] = f*(1.0+log(xj));
370
371         if ( hesfxj )
372             hesfxj[0] = f/xj;
373         break;
374     case MSK_OPR_EXP:
375         rtemp = exp(g*xj+h);
376
377         if ( fxj )
378             fxj[0] = f*rtemp;
379

```

```

380         if ( grdfxj )
381             grdfxj[0] = f*g*rtemp;
382
383         if ( hesfxj )
384             hesfxj[0] = f*g*g*rtemp;
385         break;
386     case MSK_OPR_LOG:
387         rtemp = g*xj+h;
388         if ( rtemp<=0.0 ) {
389             return ( 1 );
390         }
391
392         if ( fxj )
393             fxj[0] = f*log(rtemp);
394
395         if ( grdfxj )
396             grdfxj[0] = (g*f)/(rtemp);
397
398         if ( hesfxj )
399             hesfxj[0] = -(f*g*g)/(rtemp*rtemp);
400         break;
401     case MSK_OPR_POW:
402         if ( fxj )
403             fxj[0] = f*pow(xj+h,g);
404
405         if ( grdfxj )
406             grdfxj[0] = f*g*pow(xj+h,g-1.0);
407
408         if ( hesfxj )
409             hesfxj[0] = f*g*(g-1.0)*pow(xj+h,g-2.0);
410         break;
411     case MSK_OPR_SQRT: /* handle operator f * sqrt(gx + h) */
412         rtemp = g*xj+h;
413         if ( rtemp<=0.0 ) {
414             return ( 1 );
415         }
416
417         if ( fxj )
418             fxj[0] = f*sqrt(rtemp); /* The function value. */
419
420         if ( grdfxj )
421             grdfxj[0] = 0.5*f*g/sqrt(rtemp); /* The gradient. */
422
423         if ( hesfxj )
424             hesfxj[0] = -0.25*f*g*g*pow(rtemp,-1.5);
425         break;
426     default:
427         printf("scopt.c: Unknown operator %d\n",opr);
428         exit(0);
429 }
430
431 return ( MSK_RES_OK );
432 } /* evalopr */
433
434 static int scobjeval(nlhand_t      nlh,
435                     MSKCONST double *x,
436                     double         *objval,
437                     int             *grdnz,

```

```

438             int             *grdsub,
439             double          *grdval)
440 /* Purpose: Compute number objective value and the gradient. */
441 {
442     int     j,k,
443     *zibuf;
444     int     r = 0;
445     double  fx,grdfx,
446     *zdbuf;
447
448     #if DEBUG
449     printf("scobjeval: begin\n");
450     #endif
451
452     zibuf = nlh->zibuf;
453     zdbuf = nlh->zdbuf;
454
455     if ( objval )
456         objval[0] = 0.0;
457
458     if ( grdnz )
459         grdnz[0] = 0;
460
461     for(k=0; k<nlh->numopro && r==MSK_RES_OK; ++k)
462     {
463         j = nlh->oprjo[k];
464
465         r = evalopr(nlh->opro[k],nlh->oprfo[k],nlh->oprgo[k],nlh->oprho[k],x[j],&fx,&grdfx,NULL);
466         if ( r )
467         {
468             #if DEBUG
469             printf("Failure for variable j: %d\n",j);
470             #endif
471         }
472         else
473         {
474             if ( objval )
475                 objval[0] += fx;
476
477             if ( grdnz )
478             {
479                 zdbuf[j] += grdfx;
480
481                 if ( !zibuf[j] )
482                 {
483                     /* A new nonzero in the gradient has been located. */
484                     grdsub[grdnz[0]] = j;
485                     zibuf[j] = 1;
486                     ++ grdnz[0];
487                 }
488             }
489         }
490     }
491
492     if ( grdnz!=NULL )
493     {
494         /* Buffers should be zeroed. */
495         for(k=0; k<grdnz[0]; ++k)

```

```

496     {
497         j = grdsub[k];
498
499         if ( grdval )
500             grdval[k] = zdbuf[j];
501
502         zibuf[j] = 0;
503         zdbuf[j] = 0.0;
504     }
505 }
506
507 #if DEBUG>5
508 if ( objval!=NULL )
509     printf("objval: %e\n",objval[0]);
510
511 if ( grdnz!=NULL )
512     printf("grdnz: %d\n",grdnz[0]);
513
514 if ( grdsub && grdval )
515 {
516     printf("grdobj:");
517     for (k=0; k<grdnz[0]; ++k)
518         printf(" %e[%d]",grdval[k],grdsub[k]);
519     printf("\n");
520 }
521 #endif
522
523 #if DEBUG
524 printf("scobjeval: end\n");
525 #endif
526
527 return ( r );
528 } /* scobjeval */
529
530 static int scgrdconeval(nlh_t      nlh,
531                        int         i,
532                        MSKCONST double *x,
533                        double       *fval,
534                        int          grdnz,
535                        MSKCONST int  *grdsub,
536                        double        *grdval)
537 /* Purpose: Compute number value and the gradient of constraint i.
538    grdsub[0,...,grdnz-1] tells which values are needed in gradient
539    that is required. */
540 {
541     int    r=0,
542           j,k,p,gnz,
543           *ibuf,*zibuf;
544     double fx,grdfx,
545           *zdbuf;
546
547     #if DEBUG
548     printf("scgrdconeval: begin\n");
549     #endif
550
551     ibuf = nlh->ibuf;
552     zibuf = nlh->zibuf;
553     zdbuf = nlh->zdbuf;

```

```

554
555     if ( fval )
556         fval[0] = 0.0;
557
558     if ( nlh->ptrc )
559     {
560         gnz = 0;
561         for(p=nlh->ptrc[i]; p<nlh->ptrc[i+1] && !r; ++p)
562         {
563             k = nlh->subc[p];
564             j = nlh->oprjc[k];
565
566             r = evalopr(nlh->oprc[k],nlh->oprfc[k],nlh->oprgc[k],nlh->oprhc[k],x[j],&fx,&grdfx,NULL);
567
568             if ( r )
569             {
570                 #if DEBUG
571                 printf("Failure for variable j: %d\n",j);
572                 #endif
573             }
574             else
575             {
576                 if ( fval )
577                     fval[0] += fx;
578
579                 if ( grdnz>0 )
580                 {
581                     zdbuf[j] += grdfx;
582
583                     if ( !zibuf[j] )
584                     {
585                         /* A new nonzero in the gradient has been located. */
586
587                         ibuf[gnz] = j;
588                         zibuf[j] = 1;
589                         ++ gnz;
590                     }
591                 }
592             }
593         }
594
595         if ( grdval!=NULL )
596         {
597             /* Setup gradient. */
598             for(k=0; k<grdnz; ++k)
599             {
600                 j = grdsub[k];
601                 grdval[k] = zdbuf[j];
602             }
603         }
604
605         for(k=0; k<gnz; ++k)
606         {
607             j = ibuf[k];
608             zibuf[j] = 0;
609             zdbuf[j] = 0.0;
610         }
611     }

```

```

612     else if ( grdval )
613     {
614         for(k=0; k<grdnz; ++k)
615             grdval[k] = 0.0;
616     }
617
618
619     #if DEBUG>5
620     printf("i: %d\n",i);
621     if ( fval!=NULL )
622         printf("fval: %e\n",fval[0]);
623
624     if ( grdnz )
625     {
626         printf("grdnz: %d\n", grdnz);
627
628         if ( grdsub && grdval )
629         {
630             printf("grd:");
631             for(k=0; k<grdnz; ++k)
632                 printf(" %e[%d]",grdval[k],grdsub[k]);
633             printf("\n");
634         }
635     }
636     #endif
637
638     #if DEBUG
639     printf("scgrdconeval: end\n");
640     #endif
641
642     return ( r );
643 } /* scgrdconeval */
644
645 static int MSKAPI sceval(void *nlhandle,
646                          MSKCONST double *xx,
647                          double yo,
648                          MSKCONST double *yc,
649                          double *objval,
650                          int *numgrdobjnz,
651                          int *grdobjsub,
652                          double *grdobjval,
653                          int numi,
654                          MSKCONST int *subi,
655                          double *conval,
656                          MSKCONST int *grdconptrb,
657                          MSKCONST int *grdconptre,
658                          MSKCONST int *grdconsub,
659                          double *grdconval,
660                          double *grdlag,
661                          int maxnumhesnz,
662                          int *numhesnz,
663                          int *hessubi,
664                          int *hessubj,
665                          double *hesval)
666 /* Purpose: Evaluate the nonlinear function and return the
667    requested information to MOSEK.
668 */
669 {

```

```

670     double   fx,grdfx,hesfx;
671     int       r;
672     int       i,j,k,l,p,numvar,numcon,
673             *zibuf;
674     nlhand_t nlh;
675
676     #if DEBUG
677     printf("sceval: begin\n");
678     #endif
679
680     nlh = (nlhand_t) nlhandle;
681
682     numcon = nlh->numcon;
683     numvar = nlh->numvar;
684
685     r = scobjeval(nlh,xx,objval,numgrdobjnz,grdobjsub,grdobjval);
686
687     for(k=0; k<numi && !r; ++k)
688     {
689         i = subi[k];
690         r = scgrdconeval(nlh,i,xx,
691                         conval==NULL ? NULL : conval+k,
692                         grdconsub==NULL ? 0 : grdconptre[k]-grdconptrb[k],
693                         grdconsub==NULL ? NULL : grdconsub+grdconptrb[k],
694                         grdconval==NULL ? NULL : grdconval+grdconptrb[k]);
695     }
696
697     if ( grdlag && !r )
698     {
699         /* Compute and store the gradient of the Lagrangian.
700          * Note it is stored as a dense vector.
701          */
702
703         for(j=0; j<numvar; ++j)
704             grdlag[j] = 0.0;
705
706         if ( yo!=0.0 )
707         {
708             for(k=0; k<nlh->numopro && !r; ++k)
709             {
710                 j = nlh->oprjo[k];
711                 r = evalopr(nlh->opro[k],nlh->oprfo[k],nlh->oprgo[k],nlh->oprho[k],xx[j],NULL,&grdfx,NULL);
712                 if ( r )
713                 {
714                     #if DEBUG
715                     printf("Failure for variable j: %d\n",j);
716                     #endif
717                 }
718                 else
719                     grdlag[j] += yo*grdfx;
720             }
721         }
722
723         if ( nlh->ptrc )
724         {
725             for(l=0; l<numi && r==MSK_RES_OK; ++l)
726             {
727                 i = subi[l];

```



```

728     for(p=nlh->ptrc[i]; p<nlh->ptrc[i+1] && r==MSK_RES_OK; ++p)
729     {
730         k = nlh->subc[p];
731         j = nlh->oprjc[k];
732
733         r = evalopr(nlh->oprc[k],nlh->oprfc[k],nlh->oprhc[k],nlh->oprhc[k],xx[j],NULL,&grdfx,NULL);
734
735         grdlag[j] -= yc[i]*grdfx;
736     }
737 }
738 }
739 }
740
741 if ( maxnumhesnz && r==MSK_RES_OK )
742 {
743     /* Compute and store the Hessian of the Lagrange function. */
744
745     #if DEBUG
746     printf("x: \n");
747     for(j=0; j<numvar; ++j)
748         printf(" %e\n",xx[j]);
749
750     printf("yc: \n");
751     for(i=0; i<numcon; ++i)
752         printf(" %e\n",yc[i]);
753     #endif
754
755     zibuf = nlh->zibuf;
756     numhesnz[0] = 0;
757     if ( yo!=0.0 )
758     {
759         for(k=0; k<nlh->numopro && r==MSK_RES_OK; ++k)
760         {
761             j = nlh->oprjo[k];
762             r = evalopr(nlh->opro[k],nlh->oprfo[k],nlh->oprfo[k],nlh->oprfo[k],xx[j],NULL,NULL,&hesfx);
763             if ( !zibuf[j] )
764             {
765                 ++ numhesnz[0];
766                 zibuf[j] = numhesnz[0];
767                 hessubi[zibuf[j]-1] = j;
768                 hesval[zibuf[j]-1] = 0.0;
769             }
770             hesval[zibuf[j]-1] += yo*hesfx;
771         }
772     }
773
774     if ( nlh->ptrc )
775     {
776         for(l=0; l<numi && r==MSK_RES_OK; ++l)
777         {
778             i = subi[l];
779             for(p=nlh->ptrc[i]; p<nlh->ptrc[i+1] && r==MSK_RES_OK; ++p)
780             {
781                 k = nlh->subc[p];
782                 j = nlh->oprjc[k];
783
784                 r = evalopr(nlh->oprc[k],nlh->oprfc[k],nlh->oprhc[k],nlh->oprhc[k],xx[j],NULL,NULL,&hesfx);
785

```

```

786         if ( !zibuf[j] )
787         {
788             ++ numhesnz[0];
789             zibuf[j] = numhesnz[0];
790             hesval[zibuf[j]-1] = 0.0;
791             hessubi[zibuf[j]-1] = j;
792         }
793         hesval[zibuf[j]-1] -= yc[i]*hesfx;
794     }
795 }
796 }
797
798 if ( numhesnz[0]>maxnumhesnz )
799 {
800     printf("Hessian evalauation error\n");
801     exit(0);
802 }
803
804 for(k=0; k<numhesnz[0]; ++k)
805 {
806     j = hessubi[k];
807     hessubj[k] = j;
808     zibuf[j] = 0;
809 }
810
811 }
812
813 #if DEBUG>5
814 if ( conval!=NULL )
815 {
816     printf("conval:");
817     for(k=0; k<numi; ++k)
818         printf(" %e[%d]",conval[k],subi[k]);
819     printf("\n");
820 }
821 if ( grdlag!=NULL )
822 {
823     printf("grdlag:");
824     for(j=0; j<numvar; ++j)
825         printf(" %e",grdlag[j]);
826     printf("\n");
827 }
828
829 if ( numhesnz!=NULL )
830 {
831     printf("Hessian: ");
832     for(k=0; k<numhesnz[0]; ++k)
833         printf(" %e[%d,%d]",hesval[k],hessubi[k],hessubj[k]);
834     printf("\n");
835 }
836 #endif
837
838
839 #if DEBUG
840 printf("sceval: end\n");
841 #endif
842
843 return ( r );

```

```

844 } /* sceval */
845
846 MSKrescodee MSK_scbegin(MSKtask_t task,
847                         int      numopro,
848                         int      *opro,
849                         int      *oprjo,
850                         double   *oprfo,
851                         double   *oprgo,
852                         double   *oprho,
853                         int      numoprc,
854                         int      *oprc,
855                         int      *opric,
856                         int      *oprjc,
857                         double   *oprfc,
858                         double   *oprhc,
859                         schand_t *sch)
860 {
861     int      itemp,k,p,sum;
862     MSKrescodee r=MSK_RES_OK;
863     nlhand_t nlh;
864
865     #if DEBUG
866     printf("MSK_scbegin: begin\n");
867     #endif
868
869     nlh = (nlhand_t) MSK_calloc(task,1,sizeof(nlhand_t));
870     if ( nlh )
871     {
872         sch[0] = (void *) nlh;
873
874         MSK_getnumcon(task,&nlh->numcon);
875         MSK_getnumvar(task,&nlh->numvar);
876
877         nlh->numopro = numopro;
878         nlh->opro     = (int *) MSK_calloc(task,numopro,sizeof(int));
879         nlh->oprjo     = (int *) MSK_calloc(task,numopro,sizeof(int));
880         nlh->oprfo     = (double *) MSK_calloc(task,numopro,sizeof(double));
881         nlh->oprgo     = (double *) MSK_calloc(task,numopro,sizeof(double));
882         nlh->oprho     = (double *) MSK_calloc(task,numopro,sizeof(double));
883
884         nlh->numoprc = numoprc;
885         nlh->oprc     = (int *) MSK_calloc(task,numoprc,sizeof(int));
886         nlh->opric     = (int *) MSK_calloc(task,numoprc,sizeof(int));
887         nlh->oprjc     = (int *) MSK_calloc(task,numoprc,sizeof(int));
888         nlh->oprhc     = (double *) MSK_calloc(task,numoprc,sizeof(double));
889         nlh->oprfc     = (double *) MSK_calloc(task,numoprc,sizeof(double));
890         nlh->oprhc     = (double *) MSK_calloc(task,numoprc,sizeof(double));
891
892         if ( ( !numopro || ( nlh->opro && nlh->oprjo && nlh->oprfo && nlh->oprgo && nlh->oprho ) ) &&
893             ( !numoprc || ( nlh->oprc && nlh->opric && nlh->oprjc && nlh->oprhc && nlh->oprfc && nlh->oprhc ) ) )
894         )
895         {
896             p = 0;
897             for(k=0; k<numopro; ++k)
898             {
899                 nlh->opro[p] = opro[k];
900             }

```

```

901     nlh->oprjo[p] = oprjo[k];
902     nlh->oprfo[p] = oprfo[k];
903     nlh->oprgo[p] = oprgo[k];
904     nlh->oprho[p] = oprho[k];
905     ++p;
906 }
907
908 nlh->numopro = p;
909
910 for(k=0; k<numoprc; ++k)
911 {
912     nlh->oprc[k] = oprc[k];
913     nlh->opric[k] = opric[k];
914     nlh->oprjc[k] = oprjc[k];
915     nlh->oprfc[k] = oprfc[k];
916     nlh->oprkc[k] = oprkc[k];
917     nlh->oprhc[k] = oprhc[k];
918 }
919
920 #if DEBUG
921 /*
922  * Check if data is valid.
923  */
924
925 for(k=0; k<numopro; ++k)
926 {
927     if ( oprjo[k]<0 || oprjo[k]>=nlh->numvar )
928     {
929         printf("oprjo[%d]=%d is invalid.\n",k,oprjo[k]);
930         exit(0);
931     }
932 }
933
934 for(k=0; k<numoprc; ++k)
935 {
936     if ( opric[k]<0 || opric[k]>=nlh->numcon )
937     {
938         printf("opric[%d]=%d is invalid. numcon: %d\n",k,opric[k],nlh->numcon);
939         exit(0);
940     }
941
942     if ( oprjc[k]<0 || oprjc[k]>=nlh->numvar )
943     {
944         printf("oprjc[%d]=%d is invalid.\n",k,oprjc[k]);
945         exit(0);
946     }
947 }
948 #endif
949
950 /*
951  * Allocate work vectors.
952  */
953
954 nlh->ibuf = (int *) MSK_calloctask(task,nlh->numvar,sizeof(int));
955 nlh->zibuf = (int *) MSK_calloctask(task,nlh->numvar,sizeof(int));
956 nlh->zdbuf = (double *) MSK_calloctask(task,nlh->numvar,sizeof(double));
957 if ( numoprc )
958 {

```

```

959     nlh->ptrc = (int *) MSK_calloc(task,nlh->numcon+1,sizeof(int));
960     nlh->subc = (int *) MSK_calloc(task,numoprc,sizeof(int));
961 }
962
963 if ( ( !nlh->numvar || ( nlh->ibuf && nlh->zibuf && nlh->zdbuf ) ) &&
964     ( !numoprc || ( nlh->ptrc && nlh->subc ) ) )
965 {
966     if ( nlh->numcon && numoprc>0 )
967     {
968         /*
969          Setup of ptrc and sub. After the setup then
970          1) ptrc[i+1]-ptrc[i]: Is the number of nonlinear terms in the ith constraint.
971          2) subc[ptrc[i],...,ptrc[i+1]-1]: List the nonlinear terms in the ith constraint.
972          */
973
974         for(k=0; k<numoprc; ++k)
975             ++ nlh->ptrc[oprc[k]];
976
977         sum = 0;
978         for(k=0; k<=nlh->numcon; ++k)
979         {
980             itemp      = nlh->ptrc[k];
981             nlh->ptrc[k] = sum;
982             sum        += itemp;
983         }
984
985         for(k=0; k<numoprc; ++k)
986         {
987             nlh->subc[nlh->ptrc[oprc[k]]] = k;
988             ++ nlh->ptrc[oprc[k]];
989         }
990
991         for(k=nlh->numcon; k; --k)
992             nlh->ptrc[k] = nlh->ptrc[k-1];
993
994         nlh->ptrc[0] = 0;
995
996         #if DEBUG
997         {
998             int p;
999             for(k=0; k<nlh->numcon; ++k)
1000             {
1001                 printf("ptrc[%d]: %d subc: \n",k,nlh->ptrc[k]);
1002                 for(p=nlh->ptrc[k]; p<nlh->ptrc[k+1]; ++p)
1003                     printf(" %d",nlh->subc[p]);
1004                 printf("\n");
1005             }
1006         }
1007         #endif
1008     }
1009     r = MSK_putnfunc(task,(void *) nlh,scstruc,sceval);
1010 }
1011 else
1012     r = MSK_RES_ERR_SPACE;
1013 }
1014 else
1015     r = MSK_RES_ERR_SPACE;
1016 }

```

```

1017     else
1018         r = MSK_RES_ERR_SPACE;
1019
1020     #if DEBUG
1021     printf("MSC_begin: end\n");
1022     #endif
1023
1024     return ( r );
1025 } /* MSK_scbegin */
1026
1027 MSKrescodee MSK_scwrite(MSKtask_t task,
1028                        schand_t sch,
1029                        char filename[])
1030 {
1031     char *fn;
1032     int k;
1033     FILE *f;
1034     MSKrescodee r=MSK_RES_OK;
1035     nlhand_t nlh;
1036     size_t l;
1037
1038     nlh = (nlhand_t) sch;
1039     l = strlen(filename);
1040     fn = (char*) MSK_calloc(task,l+5,sizeof(char));
1041     if ( fn )
1042     {
1043         for(l=0; filename[l] && filename[l]!='.'; ++l)
1044             fn[l] = filename[l];
1045
1046         strcpy(fn+l, ".mps");
1047
1048         r = MSK_writedata(task,fn);
1049         if ( r==MSK_RES_OK )
1050         {
1051             strcpy(fn+l, ".sco");
1052
1053             f = fopen(fn,"wt");
1054             if ( f )
1055             {
1056                 printf("Writing: %s\n",fn);
1057
1058                 fprintf(f,"%d\n",nlh->numopro);
1059
1060                 for(k=0; k<nlh->numopro; ++k)
1061                     fprintf(f,"%-8d %-8d %-24.16e %-24.16e %-24.16e\n",
1062                             nlh->opro[k],
1063                             nlh->oprjo[k],
1064                             nlh->oprfo[k],
1065                             nlh->oprgo[k],
1066                             nlh->oprho[k]);
1067
1068                 fprintf(f,"%d\n",nlh->numoprc);
1069                 for(k=0; k<nlh->numoprc; ++k)
1070                     fprintf(f,"%-8d %-8d %-8d %-24.16e %-24.16e %-24.16e\n",
1071                             nlh->oprc[k],
1072                             nlh->opric[k],
1073                             nlh->oprjc[k],
1074                             nlh->oprfc[k],

```

```

1075         nlh->oprhc[k],
1076         nlh->oprhc[k]);
1077     }
1078     else
1079     {
1080         printf("Could not open file: '%s'\n",filename);
1081         r = MSK_RES_ERR_FILE_OPEN;
1082     }
1083     fclose(f);
1084 }
1085 }
1086 else
1087     r = MSK_RES_ERR_SPACE;
1088
1089 MSK_freetask(task, fn);
1090
1091 #if DEBUG
1092 printf("MSK_scwrite: end\n");
1093 #endif
1094
1095 return ( r );
1096 } /* MSK_scwrite */
1097
1098 MSKrescodee MSK_scread(MSKtask_t task,
1099                       schand_t *sch,
1100                       char filename[])
1101 {
1102     char buffer[1024],fbuf[80],hbuf[80],gbuf[80],
1103          *fn;
1104     double *oprfo=NULL,*oprfo=NULL,*oprfo=NULL,*oprfo=NULL,*oprfo=NULL,*oprfo=NULL;
1105     int k,p,
1106         numopro,numoprc,
1107         *opro=NULL,*oprjo=NULL,*oprc=NULL,*opric=NULL,*oprjc=NULL;
1108     FILE *f;
1109     MSKrescodee r;
1110     size_t l;
1111
1112     #if DEBUG
1113     printf("MSK_scread: begin\n");
1114     #endif
1115
1116     sch[0] = NULL;
1117     l = strlen(filename);
1118     fn = (char*) MSK_calloc(task,l+5,sizeof(char));
1119     if ( fn )
1120     {
1121         strcpy(fn, filename);
1122         for(k=0; fn[k] && fn[k]!='.'; ++k);
1123
1124         strcpy(fn+k, ".mps");
1125
1126         {
1127             r = MSK_readdata(task,fn);
1128             if ( r==MSK_RES_OK )
1129             {
1130                 strcpy(fn+k, ".sco");
1131
1132                 printf("Opening: %s\n",fn);

```

```

1133
1134     f = fopen(fn,"rt");
1135     if ( f )
1136     {
1137         printf("Reading.\n");
1138
1139         fgets(buffer,sizeof(buffer),f);
1140         sscanf(buffer,"%d",&numopro);
1141
1142         if ( numopro )
1143         {
1144             opro = (int*) MSK_calloc(task, numopro, sizeof(int));
1145             oprjo = (int*) MSK_calloc(task, numopro, sizeof(int));
1146             oprfo = (double*) MSK_calloc(task, numopro, sizeof(double));
1147             oprgo = (double*) MSK_calloc(task, numopro, sizeof(double));
1148             oprho = (double*) MSK_calloc(task, numopro, sizeof(double));
1149
1150             if ( opro && oprjo && oprfo && oprgo && oprho )
1151             {
1152                 for(k=0; k<numopro; ++k)
1153                 {
1154                     fgets(buffer,sizeof(buffer),f);
1155
1156                     for(p=0; buffer[p]; ++p)
1157                         if ( buffer[p]==' ' )
1158                             buffer[p] = '\n';
1159
1160                     sscanf(buffer,"%d %d %s %s %s",
1161                            opro+k,
1162                            oprjo+k,
1163                            fbuf,
1164                            gbuf,
1165                            hbuf);
1166
1167                     oprfo[k] = atof(fbuf);
1168                     oprgo[k] = atof(gbuf);
1169                     oprho[k] = atof(hbuf);
1170                 }
1171             }
1172             else
1173                 r = MSK_RES_ERR_SPACE;
1174         }
1175
1176
1177         if ( r==MSK_RES_OK )
1178         {
1179             fgets(buffer,sizeof(buffer),f);
1180             sscanf(buffer,"%d",&numoprc);
1181
1182             if ( numoprc )
1183             {
1184                 oprc = (int*) MSK_calloc(task,numoprc,sizeof(int));
1185                 opric = (int*) MSK_calloc(task,numoprc,sizeof(int));
1186                 oprjc = (int*) MSK_calloc(task,numoprc,sizeof(int));
1187                 oprfc = (double*) MSK_calloc(task,numoprc,sizeof(double));
1188                 oprgc = (double*) MSK_calloc(task,numoprc,sizeof(double));
1189                 oprhc = (double*) MSK_calloc(task,numoprc,sizeof(double));
1190

```



```

1191         if ( oprc && oprjc && oprfc && oprgc && oprhc )
1192         {
1193             for(k=0; k<numoprc; ++k)
1194             {
1195                 fgets(buffer,sizeof(buffer),f);
1196
1197                 for(p=0; buffer[p]; ++p)
1198                     if ( buffer[p]==' ' )
1199                         buffer[p] = '\n';
1200
1201                 sscanf(buffer,"%d %d %d %s %s %s",
1202                        oprc+k,
1203                        opric+k,
1204                        oprjc+k,
1205                        fbuf,
1206                        gbuf,
1207                        hbuf);
1208
1209                 oprfc[k] = atof(fbuf);
1210                 oprgc[k] = atof(gbuf);
1211                 oprhc[k] = atof(hbuf);
1212             }
1213         }
1214         else
1215             r = MSK_RES_ERR_SPACE;
1216     }
1217     else
1218         printf("No nonlinear terms in constraints\n");
1219 }
1220
1221 fclose(f);
1222 }
1223 else
1224 {
1225     printf("Could not open file: '%s'\n",fn);
1226     r = MSK_RES_ERR_FILE_OPEN;
1227 }
1228
1229 if ( r==MSK_RES_OK )
1230     r = MSK_scbegin(task,
1231                     numopro,
1232                     opro,
1233                     oprjo,
1234                     oprfo,
1235                     oprgo,
1236                     oprho,
1237                     numoprc,
1238                     oprc,
1239                     opric,
1240                     oprjc,
1241                     oprfc,
1242                     oprgc,
1243                     oprhc,
1244                     sch);
1245
1246 MSK_freetask(task, opro);
1247 MSK_freetask(task, oprjo);
1248 MSK_freetask(task, oprfo);

```

```

1249     MSK_freetask(task, oprgo);
1250     MSK_freetask(task, oprho);
1251
1252     MSK_freetask(task, oprc);
1253     MSK_freetask(task, opric);
1254     MSK_freetask(task, oprjc);
1255     MSK_freetask(task, oprfc);
1256     MSK_freetask(task, oprgc);
1257     MSK_freetask(task, oprhc);
1258 }
1259 else
1260 {
1261     printf("Could not open file: '%s'\n",filename);
1262     r = MSK_RES_ERR_FILE_OPEN;
1263 }
1264 }
1265 }
1266 else
1267     r = MSK_RES_ERR_SPACE;
1268
1269 MSK_freetask(task,fn);
1270
1271 #if DEBUG
1272 printf("MSK_scread: end r: %d\n",r);
1273 #endif
1274
1275 return ( r );
1276 } /* MSK_scread */
1277
1278
1279 MSKrescodee MSK_scend(MSKtask_t task,
1280                      schand_t *sch)
1281 /* Purpose: Free all data associated with nlh. */
1282 {
1283     nlhand_t nlh;
1284
1285     #if DEBUG
1286     printf("MSK_scend: begin\n");
1287     #endif
1288
1289     if ( sch[0] )
1290     {
1291         /* Remove nonlinear function data. */
1292         MSK_putnlfunc(task,NULL,NULL,NULL);
1293
1294         nlh = (nlhand_t) sch[0];
1295         sch[0] = nlh;
1296
1297         #if DEBUG
1298         printf("MSK_scend: deallocate\n");
1299         #endif
1300
1301         MSK_freetask(task,nlh->opro);
1302         MSK_freetask(task,nlh->oprjo);
1303         MSK_freetask(task,nlh->oprfo);
1304         MSK_freetask(task,nlh->oprgo);
1305         MSK_freetask(task,nlh->oprho);
1306

```

```

1307     MSK_freetask(task,nlh->oprc);
1308     MSK_freetask(task,nlh->opric);
1309     MSK_freetask(task,nlh->oprjc);
1310     MSK_freetask(task,nlh->oprfc);
1311     MSK_freetask(task,nlh->oprgc);
1312     MSK_freetask(task,nlh->oprhc);
1313
1314     MSK_freetask(task,nlh->ptrc);
1315     MSK_freetask(task,nlh->subc);
1316     MSK_freetask(task,nlh->ibuf);
1317     MSK_freetask(task,nlh->zibuf);
1318     MSK_freetask(task,nlh->zdbuf);
1319
1320     MSK_freetask(task,nlh);
1321 }
1322
1323 #if DEBUG
1324 printf("MSK_scend: end\n");
1325 #endif
1326
1327 return ( MSK_RES_OK );
1328 } /* MSK_scend */

```

In the lines

[*tstscopt.c*]

```

103  r = MSK_inputdata(task,
104                      numcon,numvar,
105                      numcon,numvar,
106                      c,0.0,
107                      aptrb,aptrc,
108                      asub,aval,
109                      bkc,blc,buc,
110                      bkx,blx,bux);

```

the linear part of the problem is setup whereas in the lines

[*tstscopt.c*]

```

116  r = MSK_scbegin(task,
117                  numopro,opro,oprjo,oprfo,oprgo,oprho,
118                  numoprc,oprc,opric,oprjc,oprfc,oprgc,oprhc,
119                  &sch);

```

the nonlinear part of the problem is setup. The function `MSK_scbegin` is implemented in `scopt-ext.c`. The central function call

[*scopt-ext.c*]

```

1009  r = MSK_putnlfnc(task,(void *) nlh,scstruc,sceval);

```

that inputs the nonlinear callback functions

- `scstruc`: Provides structural information about the nonlinearities in the problem e.g. sparsity patterns.

- sceval: Computes numerical information about the nonlinear functions e.g. function values and in addition 1st and 2nd order derivative information.

6.2 Exponential optimization

6.2.1 The problem

An exponential optimization problem has the form

$$\begin{aligned}
 & \text{minimize} && \sum_{k \in J_0} c_k e^{(\sum_{j=0}^{n-1} a_{k,j} x_j)} \\
 & \text{subject to} && \sum_{k \in J_i} c_k e^{(\sum_{j=0}^{n-1} a_{k,j} x_j)} \leq 1, \quad i = 1, \dots, m, \\
 & && x \in \mathbb{R}^n
 \end{aligned} \tag{6.4}$$

where it is assumed that

$$\cup_{i=0}^m J_i = \{1, \dots, T\}$$

and

$$J_i \cap J_j = \emptyset$$

if $i \neq j$.

Given

$$c_i > 0, \quad i = 1, \dots, T$$

the problem (6.4) is a convex optimization problem which can be solved using MOSEK. We will call

$$c_t e^{(\sum_{j=0}^{n-1} a_{t,j} x_j)} = e^{(\log(c_t) + \sum_{j=0}^{n-1} a_{t,j} x_j)}$$

for a term and hence the number of terms is T .

As stated the problem (6.4) is a nonseparable problem. However, using

$$v_t = \log(c_t) + \sum_{j=0}^{n-1} a_{t,j} x_j$$

we obtain the separable problem

$$\begin{aligned}
& \text{minimize} && \sum_{t \in J_0} e^{v_t} \\
& \text{subject to} && \sum_{t \in J_i} e^{v_t} \leq 1, && i = 1, \dots, m, \\
& && \sum_{j=0}^{n-1} a_{t,j} x_j - v_t = -\log(c_t), && t = 0, \dots, T,
\end{aligned} \tag{6.5}$$

which could be solved using the `scopt` interface discussed in Section 6.1. A warning about this approach is that computing the function

$$e^x$$

using double-precision floating point numbers is only possible for small values of x in absolute value. Indeed e^x grows very rapidly for larger x values, and numerical problems may arise when solving the problem on this form.

It is also possible to reformulate the exponential optimization problem (6.4) as a dual geometric optimization problem (6.10). This is often the preferred solution approach because it is computationally more efficient and the numerical problems associated with evaluating e^x for moderately large x values are avoided.

6.2.2 Source code

The MOSEK distribution includes the source code for a program that enables you to:

- Read (and write) a data file stating an exponential optimization problem.
- Verify that the input data is reasonable.
- Solve the problem via the exponential optimization problem (6.5) or the dual geometric optimization problem (6.10).
- Write a solution file.

6.2.3 Solving from the command line.

In the following we will discuss the program `mskexpopt`, which is included in the MOSEK distribution, in both source code and compiled form. Hence, you can solve exponential optimization problems using the operating system command line or directly from your own C program.

6.2.3.1 The input format

First we will define a text input format for specifying an exponential optimization problem. This is as follows:

```

* This is a comment
  numcon
  numvar
  number
    c1
    c2

  cnumber
    i1
    i2

  inumber
    t1  j1  at1,j1
    t2  j2  at2,j2

```

The first line is an optional comment line. In general everything occurring after a `*` is considered a comment. Lines 2 to 4 inclusive define the number of constraints (m), the number of variables (n), and the number of terms T in the problem. Then follows three sections containing the problem data.

The first section

```

  c1
  c2

  cnumber

```

lists the coefficients c_t of each term t in their natural order.

The second section

```

  i1
  i2

  inumber

```

specifies to which constraint each term belongs. Hence, for instance $i_2 = 5$ means that the term number 2 belongs to constraint 5. $i_t = 0$ means that term number t belongs to the objective.

The third section

```

  t1  j1  at1,j1
  t2  j2  at2,j2

```

defines the non-zero $a_{t,j}$ values. For instance the entry

```

1  3  3.3

```

implies that $a_{t,j} = 3.3$ for $t = 1$ and $j = 3$.

Please note that each $a_{t,j}$ should be specified only once.

6.2.4 Choosing primal or dual form

One can choose to solve the exponential optimization problem directly in the primal form (6.5) or on the dual form. By default `mskexpopt` solves a problem on the dual form since usually this is more efficient. The command line option

`-primal`

chooses the primal form.

6.2.5 An example

Consider the problem:

$$\begin{aligned} &\text{minimize} && 40e^{-x_1-1/2x_2-x_3} + 20e^{x_1+x_3} + 40e^{x_1+x_2+x_3} \\ &\text{subject to} && \frac{1}{3}e^{-2x_1-2x_2} + \frac{4}{3}e^{1/2x_2-x_3} \leq 1. \end{aligned} \quad (6.6)$$

This small problem can be specified as follows using the input format:

```

1  * File : expopt1.eo
2
3  1  * numcon
4  3  * numvar
5  5  * numter
6
7  * Coefficients of terms
8
9  40
10 20
11 40
12 0.3333333
13 1.3333333
14
15 * For each term, the index of the
16 * constraints to the term belongs
17
18 0
19 0
20 0
21 1
22 1
23
24 * Section defining a_kj
25
26 0 0 -1
27 0 1 -0.5
28 0 2 -1
29 1 0 1.0

```

```

30  1 2 1.0
31  2 0 1.0
32  2 1 1.0
33  2 2 1.0
34  3 0 -2
35  3 1 -2
36  4 1 0.5
37  4 2 -1.0

```

Using the program `mskexpopt` included in the MOSEK distribution the example can be solved. Indeed the command line

```
mskexpopt expopt1.eo
```

will produce the solution file `expopt1.sol` shown below.

```

PROBLEM STATUS      : PRIMAL_AND_DUAL_FEASIBLE
SOLUTION STATUS     : OPTIMAL
PRIMAL OBJECTIVE    : 1.331371e+02

```

```

VARIABLES
INDEX  ACTIVITY
1      6.931471e-01
2      -6.931472e-01
3      3.465736e-01

```

6.2.6 Solving from your C code

The C source code for solving an exponential optimization problem is included in the MOSEK distribution. The relevant source code consists of the files:

`expopt.h`:

Defines prototypes for the functions:

`MSK_expoptread`:

Reads a problem from a file.

`MSK_expoptsetup`:

Sets up a problem. The function takes the arguments:

- `expopttask`: A MOSEK task structure.
- `solveform`: If 0, then the optimizer will choose whether the problem is solved on primal or dual form. If -1 the primal form is used and if 1 the dual form.
- `numcon`: Number of constraints.
- `numvar`: Number of variables.
- `numter`: Number of terms T .
- `*subi`: Array of length `numter` defining which constraint a term belongs to or zero for the objective.
- `*c`: Array of length `numter` containing coefficients for the terms.

- numanz: Length of subk, subj, and akj.
- *subk: Term indexes.
- *subj: Variable indexes.
- *akj: akj[i] is coefficient of variable subj[i] in term subk[i], i.e.

$$a_{\text{subk}[i], \text{subj}[i]} = \text{akj}[i].$$

- *expoptthnd: Data structure containing nonlinear information.

MSK.exptoptimize:

Solves the problem and returns the problem status and the optimal primal solution.

MSK.exptfree:

Frees data structures allocated by MSK.exptsetup.

expopt.c:

Implements the functions specified in expopt.h.

mskexpopt.c:

A command line interface.

As a demonstration of the interface a C program that solves (6.6) is included below.

```

1  /*
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File      : tstexpopt.c
5
6  Purpose   : To demonstrate a simple interface for exponential optimization.
7  */
8
9  #include <string.h>
10
11 #include "expopt.h"
12
13 void MSKAPI printcb(void* handle, MSKCONST char str[])
14 {
15     printf("%s", str);
16 }
17
18
19 int main (int argc, char **argv)
20 {
21     int          r = MSK_RES_OK, numcon = 1, numvar = 3 , numter = 5;
22
23     int          subk[]  = {0,0,0,1,1};
24     int          subk[]  = {0,0,0,1,1,2,2,2,3,3,4,4};
25     double       c[]     = {40.0,20.0,40.0,0.333333,1.333333};
26     int          subj[]  = {0,1,2,0,2,0,1,2,0,1,1,2};
27     double       akj[]   = {-1,-0.5,-1.0,1.0,1.0,1.0,1.0,1.0,-2.0,-2.0,0.5,-1.0};
28     int          numanz  = 12;
29     double       objval;
30     double       xx[3];

```

```

31     double      y[5];
32     MSKenv_t     env;
33     MSKprosta_t  prosta;
34     MSKsolsta_t  solsta;
35     MSKtask_t    expopttask;
36     expopthnd_t  expopthnd = NULL;
37     /* Pointer to data structure that holds nonlinear information */
38
39     if (r == MSK_RES_OK)
40         r = MSK_makeenv (&env, NULL);
41
42     if (r == MSK_RES_OK)
43         MSK_makeemptytask(env, &expopttask);
44
45     if (r == MSK_RES_OK)
46         r = MSK_linkfunctotaskstream(expopthnd, MSK_STREAM_LOG, NULL, printcb);
47
48     if (r == MSK_RES_OK)
49     {
50         /* Initialize expopttask with problem data */
51         r = MSK_exoptsetup(expopthnd,
52                             1, /* Solve the dual formulation */
53                             numcon,
54                             numvar,
55                             numter,
56                             sub1,
57                             c,
58                             subk,
59                             subj,
60                             akj,
61                             numanz,
62                             &expopthnd
63                             /* Pointer to data structure holding nonlinear data */
64                             );
65     }
66
67     /* Any parameter can now be changed with standard mosek function calls */
68     if (r == MSK_RES_OK)
69         r = MSK_putintparam(expopthnd, MSK_IPAR_INTPNT_MAX_ITERATIONS, 200);
70
71     /* Optimize, xx holds the primal optimal solution,
72      y holds solution to the dual problem if the dual formulation is used
73      */
74
75     if (r == MSK_RES_OK)
76         r = MSK_exptoptimize(expopthnd,
77                             &prosta,
78                             &solsta,
79                             &objval,
80                             xx,
81                             y,
82                             &expopthnd);
83
84     /* Free data allocated by expoptsetup */
85     if (expopthnd)
86         MSK_exptfree(expopthnd,
87                     &expopthnd);
88

```

```

89     MSK_deletetask(&expopttask);
90     MSK_deleteenv(&env);
91 }
92

```

6.2.7 A warning about exponential optimization problems

Exponential optimization problem may in some cases have a final optimal objective value for a solution containing infinite values. Consider the simple example

$$\begin{array}{ll} \text{minimize} & e^x \\ \text{such that} & x \in \mathbb{R}, \end{array}$$

which has the optimal objective value 0 at $x = -\infty$. Similar problems can occur in constraints.

Such a solution can not in general be obtained by numerical methods, which means that MOSEK will act unpredictably in these situations — possibly failing to find a meaningful solution or simply stalling.

6.3 General convex optimization

MOSEK provides an interface for general convex optimization which is discussed in this section.

6.3.1 A warning

Using the general convex optimization interface in MOSEK is complicated. It is recommended to use the conic solver, the quadratic solver or the `scopt` interface whenever possible. Alternatively GAMS or AMPL with MOSEK as solver are well-suited for general convex optimization problems.

6.3.2 The problem

A general nonlinear convex optimization problem is to minimize or maximize an objective function of the form

$$f(x) + \frac{1}{2} \sum_{i=0}^{n-1} \sum_{j=0}^{n-1} q_{i,j}^o x_i x_j + \sum_{j=0}^{n-1} c_j x_j + c^f \quad (6.7)$$

subject to the functional constraints

$$l_k^c \leq g_k(x) + \frac{1}{2} \sum_{i=0}^{n-1} \sum_{j=0}^{n-1} q_{i,j}^k x_i x_j + \sum_{j=0}^{n-1} a_{k,j} x_j \leq u_k^c, \quad k = 0, \dots, m-1, \quad (6.8)$$

and the bounds

$$l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1. \quad (6.9)$$

Please note that this problem is a generalization of linear and quadratic optimization. This implies that the parameters c , A , Q^o , Q , and so forth denote the same as in the case of linear and quadratic optimization. All linear and quadratic terms should be inputted to MOSEK as described for these problem classes. The general convex part of the problems is defined by the functions $f(x)$ and $g_k(x)$, which must be general nonlinear, twice differentiable functions.

6.3.3 Assumptions about a nonlinear optimization problem

MOSEK makes two assumptions about the optimization problem.

The first assumption is that all functions are at least twice differentiable on their domain. More precisely, $f(x)$ and $g(x)$ must be at least twice differentiable for all x so that

$$l^x < x < u^x.$$

The second assumption is that

$$f(x) + \frac{1}{2}x^T Q^o x$$

must be a convex function if the objective is minimized. Otherwise if the objective is maximized it must be a concave function. Moreover,

$$g_k(x) + \frac{1}{2}x^T Q^k x$$

must be a convex function if

$$u_k^c < \infty$$

and a concave function if

$$l_k^c > -\infty.$$

Note in particular that nonlinear equalities are not allowed. **If these two assumptions are not satisfied, then it cannot be guaranteed that MOSEK produces correct results or works at all.**

6.3.4 Specifying general convex terms

MOSEK receives information about the general convex terms via two call-back functions implemented by the user:

- **MSKnlgetspfunc**: For parsing information on structural information about f and g .

- **MSKnlgetvafunc**: For parsing information on numerical information about f and g .

The call-back functions are passed to MOSEK with the function **MSK_putnlfunc**.

For an example of using the general convex framework see Section 6.4.

6.4 Dual geometric optimization

Dual geometric is a special class of nonlinear optimization problems involving a nonlinear and non-separable objective function. In this section we will show how to solve dual geometric optimization problems using MOSEK

6.4.1 The problem

Consider the dual geometric optimization problem

$$\begin{aligned} & \text{maximize} && f(x) \\ & \text{subject to} && Ax = b, \\ & && x \geq 0, \end{aligned} \tag{6.10}$$

where $A \in \mathbb{R}^{m \times n}$ and all other quantities have conforming dimensions. Let t be an integer and p be a vector of $t + 1$ integers satisfying the conditions

$$\begin{aligned} p_0 &= 0, \\ p_i &< p_{i+1}, \quad i = 1, \dots, t, \\ p_t &= n. \end{aligned}$$

Then f can be stated as follows

$$f(x) = \sum_{j=0}^{n-1} x_j \ln \left(\frac{v_j}{x_j} \right) + \sum_{i=1}^t \left(\sum_{j=p_i}^{p_{i+1}-1} x_j \right) \ln \left(\sum_{j=p_i}^{p_{i+1}-1} x_j \right)$$

where $v \in \mathbb{R}^n$ is a vector positive positive values.

Given these assumptions, it can be proven that f is a concave function and therefore the dual geometric optimization problem can be solved using MOSEK.

For a thorough discussion of geometric optimization see [3].

We will introduce the following definitions:

$$x^i := \begin{bmatrix} x_{p_i} \\ x_{p_{i+1}} \\ x_{p_{i+1}-1} \end{bmatrix}, X^i := \text{diag}(x^i), \text{ and } e^i := \begin{bmatrix} 1 \\ 1 \end{bmatrix} \in \mathbb{R}^{p_{i+1}-p_i}.$$

which make it possible to state f on the form

$$f(x) = \sum_{j=0}^{n-1} x_j \ln\left(\frac{v_j}{x_j}\right) + \sum_{i=1}^t ((e^i)^T x^i) \ln((e^i)^T x^i).$$

Furthermore, we have that

$$\nabla f(x) = \begin{bmatrix} \ln(v_0) - 1 - \ln(x_0) \\ \ln(v_j) - 1 - \ln(x_j) \\ \ln(v_{n-1}) - 1 - \ln(x_{n-1}) \end{bmatrix} + \begin{bmatrix} 0e^0 \\ (1 + \ln((e^1)^T x^1))e^1 \\ (1 + \ln((e^i)^T x^i))e^i \\ (1 + \ln((e^t)^T x^t))e^t \end{bmatrix}$$

and

$$\nabla^2 f(x) = \begin{bmatrix} -(X^0)^{-1} & 0 & 0 & \dots & 0 \\ 0 & \frac{e^1(e^1)^T}{(e^1)^T x^1} - (X^1)^{-1} & 0 & \dots & 0 \\ 0 & 0 & \dots & \dots & 0 \\ 0 & 0 & 0 & 0 & \frac{e^t(e^t)^T}{(e^t)^T x^t} - (X^t)^{-1} \end{bmatrix}.$$

Please note that the Hessian is a block diagonal matrix and, especially if t is large, it is very sparse — MOSEK will automatically exploit these features to speed up computations. Moreover, the Hessian can be computed cheaply, specifically in

$$O\left(\sum_{i=0}^t (p_{i+1} - p_i)^2\right)$$

operations.

6.4.2 A numerical example

In the following we will use the data

$$A = \begin{bmatrix} -1 & 1 & 1 & -2 & 0 \\ -0.5 & 0 & 1 & -2 & 0.5 \\ -1 & 1 & 1 & 0 & -1 \\ 1 & 1 & 1 & 0 & 0 \end{bmatrix}, b = \begin{bmatrix} 0 \\ 0 \\ 0 \\ 1 \end{bmatrix}, v = \begin{bmatrix} 40 \\ 20 \\ 40 \\ \frac{1}{3} \\ \frac{3}{4} \\ \frac{1}{3} \end{bmatrix}$$

and the function f given by

$$f(x) = \sum_{j=0}^4 x_j \ln\left(\frac{v_j}{x_j}\right) + (x_3 + x_4) \ln(x_3 + x_4)$$

for demonstration purposes.

6.4.3 dgopt: A program for dual geometric optimization

The generic dual geometric optimization problem and a numerical example have been presented and we will now develop a program which can solve the dual geometric optimization problem using the MOSEK API.

6.4.3.1 Data input

The first problem is how to feed the problem data into MOSEK. Since the constraints of the optimization problem are linear, they can be specified fully using an MPS file as in the purely linear case. The MPS file for the numerical data above will look as follows:

```

NAME
ROWS
 N  obj
 E  c1
 E  c2
 E  c3
 E  c4
COLUMNS
 x1  obj      0
    x1  c1     -1
    x1  c2    -0.5
    x1  c3     -1
    x1  c4      1
 x2  obj      0
    x2  c1      1
    x2  c3      1
    x2  c4      1
 x3  obj      0
    x3  c1      1
    x3  c2      1
    x3  c3      1
    x3  c4      1
 x4  obj      0
    x4  c1     -2
    x4  c2     -2
 x5  obj      0
    x5  c2     0.5
    x5  c3     -1
RHS
   rhs      c4      1
RANGES
BOUNDS

```

ENDATA

Moreover, a file specifying f is required so for that purpose we define a file:

$$\begin{aligned}
 &t \\
 &v_0 \\
 &v_1 \\
 & \\
 &v_{n-1} \\
 &p_1 - p_0 \\
 &p_2 - p_1 \\
 & \\
 &p_t - p_{t-1}
 \end{aligned}$$

Hence, for the numerical example this file has the format:

```

2
40.0
20.0
40.0
0.3333333333333333
1.3333333333333333
3
2

```

6.4.3.2 Solving the numerical example

The example is solved by executing the command line

```
mskdgopt examp/data/dgo.mps examples/data/dgo.f
```

6.4.4 The source code: dgopt

The source code for the **dgopt** consists of the files:

- **dgopt.h** and **dgopt.c**: Functions for reading and solving the dual geometric optimization problem.
- **mskdgopt.c** : The command line interface.

These files are available in the MOSEK distribution in the directory:

```
tools/examples/c
```

The basic functionality of **dgopt** can be gathered by studying the function **main** in **mskdgopt.c**. This function first loads the linear part of the problem from an MPS file into the task. Next, the nonlinear part of the problem is read from a file with the function **MSK_dgoptread**. Finally, the nonlinear function

is created and inputted with `MSK_dgoptsetup` and the problem is solved. The solution is written to the file `dgopt.sol`.

The following functions in `dgopt.c` are used to set up the information about the evaluation of the nonlinear objective function:

`MSK_dgoread`

The purpose of this function is to read data from a file which specifies the nonlinear function f in the objective.

`MSK_dgosetup`

This function creates the problem in the task. The information parsed to the function is stored in a data structure called `nlhandt`, defined in the program. This structure is later passed to the functions `gostruc` and `goeval` which are used to compute the gradient and the Hessian of f .

`gostruc`

This function is a call-back function used by MOSEK. The function reports structural information about f such as the number of non-zeros in the Hessian and the sparsity pattern of the Hessian.

`goeval`

This function is a call-back function used by MOSEK. It reports numerical information about f such as the objective value and gradient for a particular x value.

Chapter 7

Advanced API tutorial

This chapter provides information about additional problem classes and functionality provided in the C API.

7.1 The progress call-back

Some of the API function calls, notably `MSK_optimize`, may take a long time to complete. Therefore, during the optimization a call-back function is called frequently, to provide information on the progress of the call. From the call-back function it is possible

- to obtain information on the solution process,
- to report of the optimizer's progress, and
- to ask MOSEK to terminate, if desired.

7.1.1 Source code example

The following source code example documents how the progress call-back function can be used.

[callback.c]

```
1  #include <stdio.h>
2  #include <stdlib.h>
3  #include <string.h>
4
5  /*
6   Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
7
8   File:      callback.c
9
10  Purpose:   To demonstrate how to use the progress
11             callback.
12
```

```

13         Compile and link the file with MOSE, then
14         use as follows:
15
16         callback psim 25fv47.mps
17         callback dsim 25fv47.mps
18         callback intpnt 25fv47.mps
19
20         The first argument tells which optimizer to use
21         i.e. psim is primal simplex, dsim is dual simplex
22         and intpnt is interior-point.
23     */
24
25
26     #include "mosek.h"
27
28
29     /* Note: This function is declared using MSKAPI,
30        so the correct calling convention is
31        employed. */
32     static int MSKAPI usercallback(MSKtask_t      task,
33                                   MSKuserhandle_t handle,
34                                   MSKcallbackcode caller,
35                                   MSKCONST MSKrealt * douinf,
36                                   MSKCONST MSKint32t * intinf,
37                                   MSKCONST MSKint64t * lintinf)
38     {
39         double *maxtime=(double *) handle;
40
41         switch ( caller )
42         {
43             case MSK_CALLBACK_BEGIN_INTPNT:
44                 printf("Starting interior-point optimizer\n");
45                 break;
46             case MSK_CALLBACK_INTPNT:
47                 printf("Iterations: %-3d Time: %6.2f(%.2f) ",
48                       intinf[MSK_IINF_INTPNT_ITER],douinf[MSK_DINF_OPTIMIZER_TIME],douinf[MSK_DINF_INTPNT_TIME]);
49                 printf("Primal obj.: %-18.6e Dual obj.: %-18.6e\n",
50                       douinf[MSK_DINF_INTPNT_PRIMAL_OBJ],douinf[MSK_DINF_INTPNT_DUAL_OBJ]);
51                 break;
52             case MSK_CALLBACK_END_INTPNT:
53                 printf("Interior-point optimizer finished.\n");
54                 break;
55             case MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX:
56                 printf("Primal simplex optimizer started.\n");
57                 break;
58             case MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX:
59                 printf("Iterations: %-3d ",
60                       intinf[MSK_IINF_SIM_PRIMAL_ITER]);
61                 printf(" Elapsed time: %6.2f(%.2f)\n",
62                       douinf[MSK_DINF_OPTIMIZER_TIME],douinf[MSK_DINF_SIM_TIME]);
63                 printf("Obj.: %-18.6e\n",
64                       douinf[MSK_DINF_SIM_OBJ]);
65                 break;
66             case MSK_CALLBACK_END_PRIMAL_SIMPLEX:
67                 printf("Primal simplex optimizer finished.\n");
68                 break;
69             case MSK_CALLBACK_BEGIN_DUAL_SIMPLEX:
70                 printf("Dual simplex optimizer started.\n");

```

```

71     break;
72     case MSK_CALLBACK_UPDATE_DUAL_SIMPLEX:
73         printf("Iterations: %-3d ",intinf[MSK_IINF_SIM_DUAL_ITER]);
74         printf(" Elapsed time: %6.2f(%.2f)\n",
75             douinf[MSK_DINF_OPTIMIZER_TIME],douinf[MSK_DINF_SIM_TIME]);
76         printf("Obj.: %e\n",douinf[MSK_DINF_SIM_OBJ]);
77         break;
78     case MSK_CALLBACK_END_DUAL_SIMPLEX:
79         printf("Dual simplex optimizer finished.\n");
80         break;
81     case MSK_CALLBACK_BEGIN_BI:
82         printf("Basis identification started.\n");
83         break;
84     case MSK_CALLBACK_END_BI:
85         printf("Basis identification finished.\n");
86         break;
87 }
88
89 if ( douinf[MSK_DINF_OPTIMIZER_TIME]>=maxtime[0] )
90 {
91     /* mosek is spending too much time.
92        Terminate it. */
93     return ( 1 );
94 }
95
96 return ( 0 );
97 } /* usercallback */
98
99 static void MSKAPI printtxt(void      *info,
100                             MSKCONST char *buffer)
101 {
102     printf("%s",buffer);
103 } /* printtxt */
104
105 int main(int argc, char *argv[])
106 {
107     double    maxtime,
108             *xx,*y;
109     int       r,j,i,numcon,numvar;
110     FILE      *f;
111     MSKenv_t  env;
112     MSKtask_t task;
113
114     if ( argc<3 )
115     {
116         printf("Too few input arguments. mosek intpnt myfile.mps\n");
117         exit(0);
118     }
119
120     /* Create mosek environment. */
121     r = MSK_makeenv(&env,NULL);
122
123     /* Check the return code. */
124     if ( r==MSK_RES_OK )
125     {
126         /* Create an (empty) optimization task. */
127         r = MSK_makeemptytask(env,&task);
128

```

```

129     if ( r==MSK_RES_OK )
130     {
131         MSK_linkfunctotaskstream(task,MSK_STREAM_MSG,NULL, printtxt);
132         MSK_linkfunctotaskstream(task,MSK_STREAM_ERR,NULL, printtxt);
133     }
134
135     /* Specifies that data should be read from the
136        file argv[2].
137        */
138
139     if ( r==MSK_RES_OK )
140         r = MSK_readdata(task,argv[2]);
141
142     if ( r==MSK_RES_OK )
143     {
144         if ( 0==strcmp(argv[1],"psim") )
145             MSK_putintparam(task,MSK_IPAR_OPTIMIZER,MSK_OPTIMIZER_PRIMAL_SIMPLEX);
146         else if ( 0==strcmp(argv[1],"dsim") )
147             MSK_putintparam(task,MSK_IPAR_OPTIMIZER,MSK_OPTIMIZER_DUAL_SIMPLEX);
148         else if ( 0==strcmp(argv[1],"intpnt") )
149             MSK_putintparam(task,MSK_IPAR_OPTIMIZER,MSK_OPTIMIZER_INTPNT);
150
151
152         /* Tell mosek about the call-back function. */
153         maxtime = 3600;
154         MSK_putcallbackfunc(task,
155                             usercallback,
156                             (void *) &maxtime);
157
158         /* Turn all MOSEK logging off. */
159         MSK_putintparam(task,
160                         MSK_IPAR_LOG,
161                         0);
162
163         r = MSK_optimize(task);
164
165         MSK_solutionsummary(task,MSK_STREAM_MSG);
166     }
167
168
169     MSK_deletetask(&task);
170 }
171 MSK_deleteenv(&env);
172
173 printf("Return code - %d\n",r);
174
175 return ( r );
176 } /* main */

```

7.2 Solving linear systems involving the basis matrix

A linear optimization problem always has an optimal solution which is also a basic solution. In an optimal basic solution there are exactly m basic variables where m is the number of rows in the

constraint matrix A . Define

$$B \in \mathbb{R}^{m \times m}$$

as a matrix consisting of the columns of A corresponding to the basic variables.

The basis matrix B is always non-singular, i.e.

$$\det(B) \neq 0$$

or equivalently that B^{-1} exists. This implies that the linear systems

$$B\bar{x} = w \tag{7.1}$$

and

$$B^T \bar{x} = w \tag{7.2}$$

each has a unique solution for all w .

MOSEK provides functions for solving the linear systems (7.1) and (7.2) for an arbitrary w .

7.2.1 Identifying the basis

To use the solutions to (7.1) and (7.2) it is important to know how the basis matrix B is constructed.

Internally MOSEK employs the linear optimization problem

$$\begin{array}{ll} \text{maximize} & c^T x \\ \text{subject to} & Ax - x^c = 0, \\ & l^x \leq x \leq u^x, \\ & l^c \leq x^c \leq u^c. \end{array} \tag{7.3}$$

where

$$x^c \in \mathbb{R}^m \text{ and } x \in \mathbb{R}^n.$$

The basis matrix is constructed of m columns taken from

$$[A \quad -I].$$

If variable x_j is a basis variable, then the j 'th column of A denoted $a_{:,j}$ will appear in B . Similarly, if x_i^c is a basis variable, then the i 'th column of $-I$ will appear in the basis. The ordering of the basis variables and therefore the ordering of the columns of B is arbitrary. The ordering of the basis variables may be retrieved by calling the function

```
MSK_initbasissolve(task,basis);
```

where **basis** is an array of variable indexes.

This function initializes data structures for later use and returns the indexes of the basic variables in the array **basis**. The interpretation of the **basis** is as follows. If

$$\mathbf{basis}[i] < \mathbf{numcon},$$

then the i 'th basis variable is x_i^c . Moreover, the i 'th column in B will be the i 'th column of $-I$. On the other hand if

$$\mathbf{basis}[i] \geq \mathbf{numcon},$$

then the i 'th basis variable is variable

$$x_{\mathbf{basis}[i] - \mathbf{numcon}}$$

and the i 'th column of B is the column

$$A_{\cdot, (\mathbf{basis}[i] - \mathbf{numcon})}.$$

For instance if **basis**[0] = 4 and **numcon** = 5, then since **basis**[0] < **numcon**, the first basis variable is x_4^c . Therefore, the first column of B is the fourth column of $-I$. Similarly, if **basis**[1] = 7, then the second variable in the basis is $x_{\mathbf{basis}[1] - \mathbf{numcon}} = x_2$. Hence, the second column of B is identical to $a_{\cdot, 2}$.

7.2.2 An example

Consider the linear optimization problem:

$$\begin{aligned} &\text{minimize} && x_0 + x_1 \\ &\text{subject to} && x_0 + 2x_1 \leq 2, \\ & && x_0 + x_1 \leq 6, \\ & && x_0, x_1 \geq 0. \end{aligned} \tag{7.4}$$

Suppose a call to **MSK_initbasissolve** returns an array **basis** so that

```
basis[0] = 1,
basis[1] = 2.
```

Then the basis variables are x_1^c and x_0 and the corresponding basis matrix B is

$$\begin{bmatrix} 0 & 1 \\ -1 & 1 \end{bmatrix}.$$

Please note the ordering of the columns in B .

The following program demonstrates the use of **MSK_solvewithbasis**.

```
1  /*
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
```



```

4   File:      solvebasis.c
5
6   Purpose:   To demonstrate the usage of
7               MSK_solvewithbasis on the problem:
8
9               maximize  x0 + x1
10              st.
11
12                  x0 + 2.0 x1 <= 2
13                  x0 +    x1 <= 6
14                  x0 >= 0, x1 >= 0
15
16              The problem has the slack variables
17              xc0, xc1 on the constraints
18              and the variables x0 and x1.
19
20              maximize  x0 + x1
21              st.
22                  x0 + 2.0 x1 -xc1      = 2
23                  x0 +    x1      -xc2 = 6
24                  x0 >= 0, x1 >= 0,
25                  xc1 <= 0 , xc2 <= 0
26
27   Syntax:    solvebasis
28
29   */
30   #include "mosek.h"
31
32   static void MSKAPI printstr(void *handle,
33                               MSKCONST char str[])
34   {
35       printf("%s",str);
36   } /* printstr */
37
38   int main(int argc,char **argv)
39   {
40       MSKenv_t      env;
41       MSKtask_t      task;
42       MSKint32t      numcon=2,numvar=2;
43       double         c[]   = {1.0, 1.0};
44       MSKint32t      ptrb[] = {0, 2},
45                       ptre[] = {2, 3};
46       MSKint32t      asub[] = {0, 1,
47                               0, 1};
48       double         aval[] = {1.0, 1.0,
49                               2.0, 1.0};
50       MSKboundkeye   bkc[]  = {MSK_BK_UP,
51                               MSK_BK_UP};
52
53       double         blc[]  = {-MSK_INFINITY,
54                               -MSK_INFINITY};
55       double         buc[]  = {2.0,6.0};
56
57       MSKboundkeye   bkc[]  = {MSK_BK_LO,MSK_BK_LO};
58       double         blx[]  = {0.0,0.0};
59       double         bux[]  = {+MSK_INFINITY,+MSK_INFINITY};
60       MSKrescodee     r      = MSK_RES_OK;
61       MSKint32t       i,nz;
62       double         w[]    = {2.0,6.0};

```

```

62     MSKint32t    sub[] = {0,1};
63     MSKint32t    *basis;
64
65     if (r == MSK_RES_OK)
66         r = MSK_makeenv(&env,NULL);
67
68     if ( r==MSK_RES_OK )
69         r = MSK_makeemptytask(env,&task);
70
71     if ( r==MSK_RES_OK )
72         MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
73
74     if ( r == MSK_RES_OK)
75         r = MSK_inputdata(task,numcon,numvar,numcon,numvar,
76                           c,0.0,
77                           ptrb, ptre, asub, aval, bkc, blc, buc, bkc, blx, bux);
78
79     if (r == MSK_RES_OK)
80         r = MSK_putobjsense(task,MSK_OBJECTIVE_SENSE_MAXIMIZE);
81
82     if (r == MSK_RES_OK)
83         r = MSK_optimize(task);
84
85     if (r == MSK_RES_OK)
86         basis = MSK_calloc(task,numcon,sizeof(MSKint32t));
87
88     if (r == MSK_RES_OK)
89         r = MSK_initbasissolve(task,basis);
90
91     /* List basis variables corresponding to columns of B */
92     for (i=0;i<numcon && r == MSK_RES_OK;++i)
93     {
94         printf("basis[%d] = %d\n",i,basis[i]);
95         if (basis[sub[i]] < numcon)
96             printf ("Basis variable no %d is xc%d.\n",i, basis[i]);
97         else
98             printf ("Basis variable no %d is x%d.\n",i,basis[i] - numcon);
99     }
100
101     nz = 2;
102     /* solve Bx = w */
103     /* sub contains index of non-zeros in w.
104        On return w contains the solution x and sub
105        the index of the non-zeros in x.
106     */
107     if (r == MSK_RES_OK)
108         r = MSK_solvewithbasis(task,0,&nz,sub,w);
109
110     if (r == MSK_RES_OK)
111     {
112         printf("\nSolution to Bx = w:\n\n");
113
114         /* Print solution and b. */
115
116         for (i=0;i<nz;++i)
117         {
118             if (basis[sub[i]] < numcon)
119                 printf ("xc%d = %e\n",basis[sub[i]] , w[sub[i]] );

```

```

120         else
121             printf ("x%d = %e\n",basis[sub[i]] - numcon , w[sub[i]] );
122         }
123     }
124
125     /* Solve B^T y = w */
126     nz      = 1;      /* Only one element in sub is nonzero. */
127     sub[0] = 1;      /* Only w[1] is nonzero. */
128     w[0]   = 0.0;
129     w[1]   = 1.0;
130
131     if (r == MSK_RES_OK)
132         r = MSK_solvewithbasis(task,1,&nz,sub,w);
133
134     if (r == MSK_RES_OK)
135     {
136         printf("\nSolution to B^T y = w:\n\n");
137         /* Print solution and y. */
138         for (i=0;i<nz;++i)
139             printf ("y%d = %e\n",sub[i] , w[sub[i]] );
140     }
141
142     return ( r );
143 }/* main */

```

In the example above the linear system is solved using the optimal basis for (7.4) and the original right-hand side of the problem. Thus the solution to the linear system is the optimal solution to the problem. When running the example program the following output is produced.

```

basis[0] = 1
Basis variable no 0 is xc1.
basis[1] = 2
Basis variable no 1 is x0.

```

Solution to Bx = b:

```

x0 = 2.000000e+00
xc1 = -4.000000e+00

```

Solution to B^Tx = c:

```

x1 = -1.000000e+00
x0 = 1.000000e+00

```

Please note that the ordering of the basis variables is

$$\begin{bmatrix} x_1^c \\ x_0 \end{bmatrix}$$

and thus the basis is given by:

$$B = \begin{bmatrix} 0 & 1 \\ -1 & 1 \end{bmatrix}$$

It can be verified that

$$\begin{bmatrix} x_1^c \\ x_0 \end{bmatrix} = \begin{bmatrix} -4 \\ 2 \end{bmatrix}$$

is a solution to

$$\begin{bmatrix} 0 & 1 \\ -1 & 1 \end{bmatrix} \begin{bmatrix} x_1^c \\ x_0 \end{bmatrix} = \begin{bmatrix} 2 \\ 6 \end{bmatrix}.$$

7.2.3 Solving arbitrary linear systems

MOSEK can be used to solve an arbitrary (rectangular) linear system

$$Ax = b$$

using the `MSK_solvewithbasis` function without optimizing the problem as in the previous example. This is done by setting up an A matrix in the task, setting all variables to basic and calling the `MSK_solvewithbasis` function with the b vector as input. The solution is returned by the function.

Below we demonstrate how to solve the linear system

$$\begin{bmatrix} 0 & 1 \\ -1 & 1 \end{bmatrix} \begin{bmatrix} x_0 \\ x_1 \end{bmatrix} = \begin{bmatrix} b_1 \\ b_2 \end{bmatrix} \quad (7.5)$$

with $b = (1, -2)$ and $b = (7, 0)$.

```

1  /*-----[ solvelinear.c ]-----
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File      :  solvelinear.c
5
6  Purpose   :  To demonstrate the usage of MSK_solvewithbasis
7                to solve the linear system:
8
9                1.0  x1                = b1
10               -1.0 x0 + 1.0 x1 = b2
11
12               with two different right hand sides
13
14               b = (1.0, -2.0)
15
16               and
17
18               b = (7.0, 0.0)
19  */
20
21  #include "mosek.h"
22
23  static void MSKAPI printstr(void *handle,
24                             MSKCONST char str[])
25  {
26      printf("%s",str);

```

```

27 } /* printstr */
28
29
30 MSKrescodee put_a(MSKtask_t task,
31                 double *aval,
32                 MSKidx_t *asub,
33                 MSKidx_t *ptrb,
34                 MSKidx_t *ptre,
35                 int numvar,
36                 MSKidx_t *basis
37                 )
38
39 {
40     MSKrescodee r = MSK_RES_OK;
41     int i;
42     MSKstakeye *skx = NULL , *skc = NULL;
43
44
45     skx = (MSKstakeye *) calloc(numvar,sizeof(MSKstakeye));
46     if (skx == NULL && numvar)
47         r = MSK_RES_ERR_SPACE;
48
49     skc = (MSKstakeye *) calloc(numvar,sizeof(MSKstakeye));
50     if (skc == NULL && numvar)
51         r = MSK_RES_ERR_SPACE;
52
53     for (i=0;i<numvar && r == MSK_RES_OK;++i)
54     {
55         skx[i] = MSK_SK_BAS;
56         skc[i] = MSK_SK_FIX;
57     }
58
59
60     /* Create a coefficient matrix and right hand
61     side with the data from the linear system */
62     if (r == MSK_RES_OK)
63         r = MSK_appendvars(task,numvar);
64
65     if (r == MSK_RES_OK)
66         r = MSK_appendcons(task,numvar);
67
68     for (i=0;i<numvar && r == MSK_RES_OK;++i)
69         r = MSK_putacol(task,i,ptre[i]-ptrb[i],asub+ptrb[i],aval+ptrb[i]);
70
71     for (i=0;i<numvar && r == MSK_RES_OK;++i)
72         r = MSK_putbound(task,MSK_ACC_CON,i,MSK_BK_FX,0,0);
73
74     for (i=0;i<numvar && r == MSK_RES_OK;++i)
75         r = MSK_putbound(task,MSK_ACC_VAR,i,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY);
76
77     /* Allocate space for the solution and set status to unknown */
78
79     if (r == MSK_RES_OK)
80         r = MSK_deletesolution(task, MSK_SOL_BAS);
81
82     /* Define a basic solution by specifying
83     status keys for variables & constraints. */
84     for (i=0; i<numvar && r==MSK_RES_OK;++i)

```

```

85         r = MSK_putsolutioni (
86             task,
87             MSK_ACC_VAR,
88             i,
89             MSK_SOL_BAS,
90             skx[i],
91             0.0,
92             0.0,
93             0.0,
94             0.0);
95
96     for (i=0;i<numvar && r == MSK_RES_OK;++i)
97         r = MSK_putsolutioni (
98             task,
99             MSK_ACC_CON,
100            i,
101            MSK_SOL_BAS,
102            skc[i],
103            0.0,
104            0.0,
105            0.0,
106            0.0);
107
108     if (r == MSK_RES_OK)
109         r = MSK_initbasissolve(task,basis);
110
111     free (skx);
112     free (skc);
113
114     return ( r );
115 }
116
117 #define NUMCON 2
118 #define NUMVAR 2
119
120
121
122 int main(int argc,char **argv)
123 {
124     MSKenv_t  env;
125     MSKtask_t task;
126     MSKrescodee r = MSK_RES_OK;
127     MSKintt    numvar = NUMCON;
128     MSKintt    numcon = NUMVAR; /* we must have numvar == numcon */
129     int        i,nz;
130     double     aval[] = {-1.0,1.0,1.0};
131     MSKidx_t   asub[] = {1,0,1};
132     MSKidx_t   ptrb[] = {0,1};
133     MSKidx_t   ptre[] = {1,3};
134
135     MSKidx_t   bsub[NUMCON];
136     double     b[NUMCON];
137
138     MSKidx_t   *basis = NULL;
139
140     if (r == MSK_RES_OK)
141         r = MSK_makeenv(&env,NULL);
142

```

```

143     if ( r==MSK_RES_OK )
144         r = MSK_makeemptytask(env,&task);
145
146     if ( r==MSK_RES_OK )
147         MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
148
149     basis = (MSKidx_t *) calloc(numcon,sizeof(MSKidx_t));
150     if ( basis == NULL && numvar)
151         r = MSK_RES_ERR_SPACE;
152
153
154     /* Put A matrix and factor A.
155        Call this function only once for a given task. */
156     if (r == MSK_RES_OK)
157         r = put_a( task,
158                 aval,
159                 asub,
160                 ptrb,
161                 ptre,
162                 numvar,
163                 basis
164                 );
165
166     /* now solve rhs */
167     b[0] = 1;
168     b[1] = -2;
169     bsub[0] = 0;
170     bsub[1] = 1;
171     nz = 2;
172
173     if (r == MSK_RES_OK)
174         r = MSK_solvewithbasis(task,0,&nz,bsub,b);
175
176     if (r == MSK_RES_OK)
177     {
178         printf("\nSolution to Bx = b:\n\n");
179         /* Print solution and show correspondents
180            to original variables in the problem */
181         for (i=0;i<nz;++i)
182         {
183             if (basis[bsub[i]] < numcon)
184                 printf("This should never happen\n");
185             else
186                 printf ("x%d = %e\n",basis[bsub[i]] - numcon , b[bsub[i]] );
187         }
188     }
189
190     b[0] = 7;
191     bsub[0] = 0;
192     nz = 1;
193
194     if (r == MSK_RES_OK)
195         r = MSK_solvewithbasis(task,0,&nz,bsub,b);
196
197     if (r == MSK_RES_OK)
198     {
199         printf("\nSolution to Bx = b:\n\n");
200         /* Print solution and show correspondents

```

```

201         to original variables in the problem */
202     for (i=0;i<nz;++i)
203     {
204         if (basis[bsub[i]] < numcon)
205             printf("This should never happen\n");
206         else
207             printf ("x%d = %e\n",basis[bsub[i]] - numcon , b[bsub[i]] );
208     }
209 }
210
211 free (basis);
212 return r;
213 }

```

The most important step in the above example is the definition of the basic solution using the `MSK.putsolutioni` function, where we define the status key for each variable. The actual values of the variables are not important and can be selected arbitrarily, so we set them to zero. All variables corresponding to columns in the linear system we want to solve are set to basic and the slack variables for the constraints, which are all non-basic, are set to their bound.

The program produces the output:

Solution to Bx = b:

x1 = 1
x0 = 3

Solution to Bx = b:

x1 = 7
x0 = 7

and we can verify that $x_0 = 2, x_1 = -4$ is indeed a solution to (7.5).

7.3 Calling BLAS/LAPACK routines from MOSEK

Sometimes users need to perform linear algebra operations that involve dense matrices and vectors. Also MOSEK uses extensively high-performance linear algebra routines from the BLAS and LAPACK packages and some of this routine are included in the package shipped to the users.

MOSEK makes available to the user some BLAS and LAPACK routines by MOSEK functions that

- use MOSEK data types and response code;
- keep BLAS/LAPACK naming convention.

Therefore the user can leverage on efficient linear algebra routines, with a simplified interface, with no need for additional packages. In the following table we list BLAS functions:

Name	MOSEK name	Expression
AXPY	MSK_axpy	$y = \alpha x + y$
DOT	MSK_dot	$x^T y$
GEMV	MSK_gemv	$y = \alpha Ax + \beta y$
GEMM	MSK_gemm	$C = \alpha AB + \beta C$
SYRK	MSK_syrk	$C = \alpha AA^T + \beta C$

Function from LAPACK are listed below:

Name	MOSEK name	Description
POTRF	MSK_potrf	Cholesky factorization
SYEVD	MSK_syevd	Eigen-values of a symmetric matrix
SYEIG	MSK_syeig	Eigen-values and eigen-vectors of a symmetric matrix

A detailed list of the available routines follows. All code snippets are taken from the example **blas-lapack** distributed with MOSEK and listed below. All code snippets assume a valid MOSEK environment named **env** is available. For more details please refer to Section 7.3.1.

Scaled Vectors Addition (AXPY)

It computes the sum of a scaled vector x with a second vector y , i.e.

$$y = \alpha x + y, \quad (7.6)$$

where α are two scalars and $x, y \in \mathbb{R}^n$. It is available through the **MSK_axpy**. This routine may use optimized loop unrolling. Note that the results overwrites y . For example, we may use the following code:

```
58  r= MSK_axpy(env, n, alpha,x,y);
```

Inner Product (DOT)

Given two vectors $x, y \in \mathbb{R}^n$, it computes the inner product (or dot product) defined as

$$x^T \cdot y = \sum_{i=0}^{n-1} x_i y_i = y^T \cdot x. \quad (7.7)$$

The inner product is a special case of the generalized matrix-vector multiplication. MOSEK provide access to BLAS implementation by the **MSK_dot** function.

For example we may want to perform the dot product among two arrays x, y of the same dimension we can write

```
51  r= MSK_dot(env,n,x,y,&xy);
```

Generalized Matrix-Vector Multiplication (GEMV)

This function performs matrix-vector operations of the form

$$y = \alpha Ax + \beta y, \quad (7.8)$$

or

$$y = \alpha A^T x + \beta y. \quad (7.9)$$

where α, β are two scalars and $A \in \mathbb{R}^{m \times n}$, Dimension of x and y must be compatible with those of A depending whether it is transpose or not. MOSEK provides access to GEMV by the **MSK.gemv** function. Please note that the result overwrites the vector y . Expression (7.8) can be calculated as

```
63  r= MSK_gemv(env, MSK_TRANSPOSE_NO, m, n, alpha, A, x, beta,z);
```

Generalized Matrix-Matrix Multiplication (GEMM)

This function perform a matrix-matrix multiplication followed by an addition. Given matrices A, B and C of compatible dimensions, and two scalars α, β it performs the following

$$C = \alpha AB + \beta C. \quad (7.10)$$

Matrices A and B can be considered transposed or not, and their dimensions must be compatible accordingly.

MOSEK provides access to GEMM by the **MSK.gemm** function. Please note that the result overwrites the matrix C .

```
67  r= MSK_gemm(env,MSK_TRANSPOSE_NO,MSK_TRANSPOSE_NO,m,n,k,alpha,A,B,beta,C);
```

Symmetric rank-k update (SYRK)

Given a symmetric matrix $\in \mathbb{R}^{n \times n}$, two scalars α, β and a matrix A of rank k , this function computes either

$$C = \beta C + \alpha A^T A, \quad (7.11)$$

withfor $A \in \mathbb{R}^{k \times n}$, or

$$C = \beta C + \alpha A A^T, \quad (7.12)$$

for $A \in \mathbb{R}^{k \times n}$. The corresponding routine provided by MOSEK is **MSK.syrk**. The matrix C only needs to be specified as triangular. Note also that the result overwrites C in the relevant upper or lower triangular part, accordingly with the way it has been input.

```
71  r= MSK_syrk(env, MSK_UPLO_LO, MSK_TRANSPOSE_NO, m,k,1., A, beta,D);
```

Eigenvalue Computation (SYEIG)

This function returns the eigenvalues of a given square matrix A . MOSEK provides access to SYEIG by the **MSK_syeig** function.

```
81  r= MSK_syeig(env,MSK_UPLO_LO,m,Q,v);
```

Eigenvalue Decomposition (SYEVD)

Given a symmetric matrix A , this function returns its eigenvalue decomposition, i.e. a diagonal matrix V and a lower triangular matrix U , of the same dimension as A , such that

$$A = UVU^T.$$

The diagonal of V contains the eigenvalues of A , while U is formed by the orthonormal eigenvectors of A stored column-wise. Note that U will overwrite A . MOSEK provides access to SYEVD by the **MSK_syevd** function.

```
85  r= MSK_syevd(env,MSK_UPLO_LO,m,Q,v);
```

Cholesky Factorization (POTRF)

This function computes the Cholesky factorization of a symmetric positive-definite matrix $A \in \mathbb{R}^{n \times n}$, i.e. it return a lower triangular matrix U such that

$$A = U^T U.$$

It is available through the function **MSK_potrf**. Note that The result will overwrite the lower triangle of A .

```
77  r= MSK_potrf(env,MSK_BLAS_UPLO_LO,m,Q);
```

7.3.1 A working example

The following code shows how to call the BLAS/LAPACK routines provided by MOSEK. The code has no practical purpose and it is only meant to show which kind of input the routines accept.

```
1  #include "mosek.h"
2
3  /*
4   Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
5
6   File: blas-lapack.c
7
8   Purpose: To demonstrate how to call BLAS/LAPACK routines for whose MOSEK provides simplified interfaces.
9
10  */
```

```

11
12 void print_matrix(MSKrealt* x, MSKint32t r, MSKint32t c)
13 {
14     MSKint32t i,j;
15     for(i=0;i<r;i++)
16     {
17         for(j=0;j<c;j++)
18             printf("%f ",x[j*r + i]);
19
20         printf("\n");
21     }
22 }
23
24
25 int main(int argc, char* argv[])
26 {
27
28     MSKrescodee r=MSK_RES_OK;
29     MSKenv_t     env = NULL;
30
31     const MSKint32t n=3,m=2,k=3;
32
33     MSKrealt alpha=2.0,beta=0.5;
34     MSKrealt x[]={1.,1.,1.}, y[]={1.,2.,3.}, z[m]={1.0,1.0};
35
36     /*A has m=2 rows and k=3 cols*/
37     MSKrealt A[m*k]={ 1.,1., 2.,2., 3.,3. };
38     /*B has k=3 rows and n=3 cols*/
39     MSKrealt B[k*n]={ 1.,1.,1.,1.,1.,1.,1.,1.,1. };
40     MSKrealt C[m*n]={ 1.,2.,3.,4.,5.,6. }, D[m*m]={1.0,1.0,1.0,1.0}, Q[m*m]={1.0,0.0,0.0,2.0};
41     MSKrealt v[m];
42
43     MSKrealt xy;
44
45     /* BLAS routines*/
46     r= MSK_makeenv(&env,NULL);
47     printf("n=%d m=%d k=%d\n",m,n,k);
48     printf("alpha=%f\n",alpha);
49     printf("beta=%f\n",beta);
50
51     r= MSK_dot(env,n,x,y,&xy);
52     printf("dot results= %f r=%d\n",xy,r);
53
54
55     print_matrix(x,1,n);
56     print_matrix(y,1,n);
57
58     r= MSK_axpy(env, n, alpha,x,y);
59     puts("axpy results is");
60     print_matrix(y,1,n);
61
62
63     r= MSK_gemv(env, MSK_TRANSPOSE_NO, m, n, alpha, A, x, beta,z);
64     printf("gemv results is (r=%d) \n",r);
65     print_matrix(z,1,m);
66
67     r= MSK_gemm(env,MSK_TRANSPOSE_NO,MSK_TRANSPOSE_NO,m,n,k,alpha,A,B,beta,C);
68     printf("gemm results is (r=%d) \n",r);

```

```

69     print_matrix(C,m,n);
70
71     r= MSK_syrk(env, MSK_UPLO_LO, MSK_TRANSPOSE_NO, m,k,1., A, beta,D);
72     printf("syrk results is (r=%d) \n",r);
73     print_matrix(D,m,m);
74
75     /* LAPACK routines*/
76
77     r= MSK_potrf(env,MSK_BLAS_UPLO_LO,m,Q);
78     printf("potrf results is (r=%d) \n",r);
79     print_matrix(Q,m,m);
80
81     r= MSK_syevr(env,MSK_UPLO_LO,m,Q,v);
82     printf("syevr results is (r=%d) \n",r);
83     print_matrix(v,1,m);
84
85     r= MSK_syevd(env,MSK_UPLO_LO,m,Q,v);
86
87     /* Delete the environment and the associated data. */
88     MSK_deleteenv(&env);
89     printf("syevd results is (r=%d) \n",r);
90     print_matrix(v,1,m);
91     print_matrix(Q,m,m);
92     return r;
93 }

```

7.4 Automatic reformulation of QCQP problems in conic form

Despite that MOSEK can solve quadratic and quadratically constrained convex problems, as detailed in Section 5.5, it often performs better when the problems are reformulated in conic form. Moreover, the conic formulation can rely on a more sound duality theory. For this reason MOSEK provides a tool to reformulate automatically QCQP problem as Conic Quadratic problems.

We recall that QCQP problems that MOSEK can solve are of the form:

$$\begin{aligned}
 & \text{minimize} && \frac{1}{2}x^T Q^o x + c^T x + c^f \\
 & \text{subject to} && l_k^c \leq \frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j \leq u_k^c, \quad k = 0, \dots, m-1, \\
 & \text{subject to} && l_k^{cl} \leq \sum_{j=0}^{n-1} a_{k,j}^l x_j \leq u_k^{cl}, \quad k = 0, \dots, m_l-1, \\
 & && l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1.
 \end{aligned} \tag{7.13}$$

Without loss of generality it is assumed that Q^o and Q^k are all symmetric because

$$x^T Q x = 0.5x^T (Q + Q^T)x.$$

The reformulation is not in general unique. The approach followed in `MSK_toconic` is to introduce additional variables, linear constraints and second order cones to obtain a larger but equivalent problem

in which the original variables are preserved.

This allows the user to recover the original variable and constraint values, as well as their dual values, with no conversion or additional effort.

The reformulated model will contain:

- one second-order cone for each quadratic constraint,
- one second-order cone if the objective function is quadratic,
- each quadratic constraint will contain no coefficients and upper/lower bounds will be set to $\infty, -\infty$ respectively.

It is important to notice that `MSK_toconic` modified the input task in-place: this means that if the reformulation is not possible, i.e. the problem is not conic representable, the state of the task is in general undefined. The user should consider cloning the task.

7.4.1 Quadratic constraint reformulation

Let assume that the k -th constraint has some quadratic terms, i.e. it can be written in the form

$$l_k^c \leq \frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j \leq u_k^c.$$

First we note that either $l_k^c = -\infty$ or $u_k^c = -\infty$ must hold, otherwise either the constraint can be dropped, or the constraint is not convex. Thus

$$\frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{k,j} x_j \leq u_k^c.$$

can be considered without loss of generality. Introducing an additional variable y_k we obtain the equivalent form

$$\begin{aligned} x^T Q^k x &\leq 2y_k, \\ \sum_{j=0}^{n-1} a_{k,j} x_j - u_k^c &= y_k. \end{aligned}$$

If Q^k is positive semidefinite, we can compute its Cholesky factorization F^k and write

$$\begin{aligned} \|F^k x\|_2 &\leq 2y_k, \\ \sum_{j=0}^{n-1} a_{k,j} x_j - u_k^c &= y_k. \end{aligned}$$

The first constraint defines a second-order cone of dimension, i.e.

$$\|F^k x\|_2 \leq 2y_k \Leftrightarrow (y_k, Fx) \in \mathcal{Q}_r^{2+n}.$$

Thus, the constraint can be cast as

$$\begin{aligned} \sum_{j=0}^{n-1} a_{k,j} x_j - u_k^c &= y_k, \\ z &= Fx, \\ (1, y_k, z) &\in \mathcal{Q}_r^{2+n}. \end{aligned}$$

A similar approach is followed to deal with the case in which Q^k has exactly one negative eigenvalue. Moreover, some special cases, as such Q^k being diagonal, are taken into account.

7.4.2 Objective function reformulation

Let us assume that the objective function of problem (7.13) contains a quadratic terms, i.e. the matrix Q_o is not null.

From a logical point of view, we can introduce an additional free variable t and remove the quadratic term from the objective function, which reads

$$x_n + a^T x + c. \tag{7.14}$$

The next step is to introduce a quadratic constraint of the form

$$\frac{1}{2} x^T Q_o x \leq t. \tag{7.15}$$

where $Q_m = Q_o$. The problem has now a linear objective function, as required for any COP. The quadratic constraint can be converted as in Section 7.4.1.

In practice the transformation will not introduce any additional quadratic constraint, but a second order cone will be included along with the additional linear constraints.

7.4.3 A complete example

We report in this section an example of reformulation of a QCQP problem in conic form. The problem we work with is:

7.5 Customizing the warning and error reporting

You can customize the warning and error reporting in the C API. The `MSK_putresponsefunc` function can be used to register a user-defined function to be called every time a warning or an error is encountered by MOSEK. This user-defined function will then handle the error/warning as desired.

The following code shows how to define and register an error handling function:

```

1  /*
2      Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4      File: errorreporting.c
5
6      Purpose: To demonstrate how the error reporting can be customized.
7  */
8
9  #include <stdio.h>
10 #include <stdlib.h>
11 #include <string.h>
12
13
14 #include "mosek.h"
15
16 static MSKrescodee MSKAPI handleresponse(MSKuserhandle_t handle,
17                                         MSKrescodee r,
18                                         MSKCONST char msg[])
19 /* A custom response handler. */
20 {
21     if ( r==MSK_RES_OK )
22     {
23         /* Do nothing */
24     }
25     else if ( r<MSK_FIRST_ERR_CODE )
26     {
27         printf("MOSEK reports warning number %d: %s\n",r,msg);
28         r = MSK_RES_OK;
29     }
30     else
31     {
32         printf("MOSEK reports error number %d: %s\n",r,msg);
33     }
34
35     return ( r );
36 } /* handleresponse */
37
38
39 int main(int argc, char *argv[])
40 {
41     MSKenv_t    env;
42     MSKrescodee r;
43     MSKtask_t   task;
44
45     r = MSK_makeenv(&env,NULL);
46
47     if ( r==MSK_RES_OK )
48     {
49         r = MSK_makeemptytask(env,&task);
50         if ( r==MSK_RES_OK )
51         {
52             /*
53              * Input a custom warning and error handler function.
54              */
55
56             MSK_putresponsefunc(task,handleresponse,NULL);
57

```



```

58      /* User defined code goes here */
59      /* This will provoke an error */
60
61      if ( r==MSK_RES_OK )
62          r = MSK_putaij(task,10,10,1.0);
63
64      }
65      MSK_deletetask(&task);
66  }
67  MSK_deleteenv(&env);
68
69  printf("Return code - %d\n",r);
70
71  if ( r==MSK_RES_ERR_INDEX_IS_TOO_LARGE )
72      return ( MSK_RES_OK );
73  else
74      return (-1);
75  } /* main */

```

The output from the code above is:

```

MOSEK reports error number 1204: The index value 10 occurring in argument 'i' is too large.
Return code - 1204

```

7.6 Unicode strings

All strings i.e. `char *` in the C API are assumed to be UTF8 strings. Please note that

- an ASCII string is always a valid UTF8 string, and
- an UTF8 string is stored in an array of chars.

For more information about UTF8 encoded strings, please see <http://en.wikipedia.org/wiki/UTF-8>.

It is possible to convert a `wchar_t` string to a UTF8 string using the function `MSK_wchartoutf8`. The inverse function `MSK_utf8towchar` converts a UTF8 string to a `wchar_t` string.

7.6.1 A source code example

The example below documents how to convert a `wchar_t` string to a UTF8 string.

```

1  /*
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File: unicode.c
5
6  Purpose: To demonstrate how to use a unicoded strings.
7  */
8
9  #include <stdio.h>
10 #include <stdlib.h>

```

```

11  #include <string.h>
12
13
14  #include "mosek.h"
15
16  int main(int argc, char *argv[])
17  {
18      char          output[512];
19      wchar_t       *input=L"myfile.mps";
20      MSKenv_t       env;
21      MSKrescodee r;
22      MSKtask_t      task;
23      size_t         len,conv;
24
25
26      r = MSK_makeenv(&env,NULL);
27
28      if ( r==MSK_RES_OK )
29      {
30          r = MSK_makeemptytask(env,&task);
31
32          if ( r==MSK_RES_OK )
33          {
34              /*
35               The wchar_t string "input" specifying a file name
36               is converted to a UTF8 string that can be inputted
37               to MOSEK.
38              */
39
40              r = MSK_wchartoutf8(sizeof(output),&len,&conv,output,input);
41
42              if ( r==MSK_RES_OK )
43              {
44                  /* output is now an UTF8 encoded string. */
45                  r = MSK_readdata(task,output);
46              }
47
48              if ( r==MSK_RES_OK )
49              {
50                  r = MSK_optimize(task);
51                  MSK_solutionsummary(task,MSK_STREAM_MSG);
52              }
53          }
54          MSK_deletetask(&task);
55      }
56      MSK_deleteenv(&env);
57
58      printf("Return code - %d\n",r);
59
60      return ( r );
61  } /* main */

```

7.6.2 Limitations

Please note that the MPS and LP format are based ASCII formats whereas the OPF, task, and XML formats are UTF8 based formats. This implies that problems which contains non-ASCII variable or constraint names can only be written correctly to an MPS or LP formatted file using generic names.

Chapter 8

A case study

8.1 Portfolio optimization

8.1.1 Introduction

In this section the Markowitz portfolio optimization problem and variants are implemented using the MOSEK optimizer API.

An alternative to using the optimizer API is the Fusion API which is much simpler to use because it makes it possible to implement the model almost as stated on paper. It is not uncommon that an optimization problem can be implemented using the Fusion API in 1/10th of the time implementing it using the optimizer API. On the other hand, a well implemented model in the optimizer API will usually run faster than the same Fusion model.

Since it is so fast to implement a model in Fusion it can be attractive to implement a model in Fusion first because that way the results from the Fusion based code can be used to validate the results of the optimizer API implementation.

Subsequently the following MATLAB inspired notation will be employed. The $:$ operator is used as follows

$$i:j = \{i, i+1, \dots, j\}$$

and hence

$$x_{2:4} = \begin{bmatrix} x_2 \\ x_3 \\ x_4 \end{bmatrix}$$

If x and y are two column vectors, then

$$[x; y] = \begin{bmatrix} x \\ y \end{bmatrix}$$

Furthermore, if $f \in R^{m \times n}$ then

$$f(\cdot) = \begin{bmatrix} f_{1,1} \\ f_{2,1} \\ \vdots \\ f_{m-1,n} \\ f_{m,n} \end{bmatrix}$$

i.e. $f(\cdot)$ stacks the columns of the matrix f .

8.1.2 A basic portfolio optimization model

The classical Markowitz portfolio optimization problem considers investing in n stocks or assets held over a period of time. Let x_j denote the amount invested in asset j , and assume a stochastic model where the return of the assets is a random variable r with known mean

$$\mu = \mathbf{E}r$$

and covariance

$$\Sigma = \mathbf{E}(r - \mu)(r - \mu)^T.$$

The return of the investment is also a random variable $y = r^T x$ with mean (or expected return)

$$\mathbf{E}y = \mu^T x$$

and variance (or risk)

$$(y - \mathbf{E}y)^2 = x^T \Sigma x.$$

The problem facing the investor is to rebalance the portfolio to achieve a good compromise between risk and expected return, e.g., maximize the expected return subject to a budget constraint and an upper bound (denoted γ) on the tolerable risk. This leads to the optimization problem

$$\begin{aligned} & \text{maximize} && \mu^T x \\ & \text{subject to} && e^T x = w + e^T x^0, \\ & && x^T \Sigma x \leq \gamma^2, \\ & && x \geq 0. \end{aligned} \tag{8.1}$$

The variables x denote the investment i.e. x_j is the amount invested in asset j and x_j^0 is the initial holding of asset j . Finally, w is the initial amount of cash available.

A popular choice is $x^0 = 0$ and $w = 1$ because then x_j may be interpreted as the relative amount of the total portfolio that is invested in asset j .

Since e is the vector of all ones then

$$e^T x = \sum_{j=1}^n x_j$$

is the total investment. Clearly, the total amount invested must be equal to the initial wealth, which is

$$w + e^T x^0.$$

This leads to the first constraint

$$e^T x = w + e^T x^0.$$

The second constraint

$$x^T \Sigma x \leq \gamma^2$$

ensures that the variance, or the risk, is bounded by γ^2 . Therefore, γ specifies an upper bound of the standard deviation the investor is willing to undertake. Finally, the constraint

$$x_j \geq 0$$

excludes the possibility of short-selling. This constraint can of course be excluded if short-selling is allowed.

The covariance matrix Σ is positive semidefinite by definition and therefore there exist a matrix G such that

$$\Sigma = GG^T. \tag{8.2}$$

In general the choice of G is **not** unique and one possible choice of G is the Cholesky factorization of Σ . However, in many cases another choice is better for efficiency reasons as discussed in Section 8.1.4.

For a given G we have that

$$\begin{aligned} x^T \Sigma x &= x^T G G^T x \\ &= \|G^T x\|^2. \end{aligned}$$

Hence, we may write the risk constraint as

$$\gamma \geq \|G^T x\|$$

or equivalently

$$[\gamma; G^T x] \in Q^{n+1}.$$

where Q^{n+1} is the $n + 1$ dimensional quadratic cone. Therefore, problem (8.1) can be written as

$$\begin{aligned}
& \text{maximize} && \mu^T x \\
& \text{subject to} && e^T x = w + e^T x^0, \\
& && [\gamma; G^T x] \in Q^{n+1}, \\
& && x \geq 0,
\end{aligned} \tag{8.3}$$

which is a conic quadratic optimization problem that can easily be solved using MOSEK.

Subsequently we will use the example data

$$\mu = \begin{bmatrix} 0.1073 \\ 0.0737 \\ 0.0627 \end{bmatrix}$$

and

$$\Sigma = 0.1 \begin{bmatrix} 0.2778 & 0.0387 & 0.0021 \\ 0.0387 & 0.1112 & -0.0020 \\ 0.0021 & -0.0020 & 0.0115 \end{bmatrix}$$

This implies

$$G^T = \sqrt{0.1} \begin{bmatrix} 0.5271 & 0.0734 & 0.0040 \\ 0 & 0.3253 & -0.0070 \\ 0 & 0 & 0.1069 \end{bmatrix}$$

using 5 figures of accuracy. Moreover, let

$$x^0 = \begin{bmatrix} 0.0 \\ 0.0 \\ 0.0 \end{bmatrix}$$

and

$$w = 1.0.$$

The data has been taken from [5].

8.1.2.1 Why a conic formulation?

The problem (8.1) is a convex quadratically constrained optimization problems that can be solved directly using MOSEK, then why reformulate it as a conic quadratic optimization problem? The main reason for choosing a conic model is that it is more robust and usually leads to a shorter solution times. For instance it is not always easy to determine whether the Q matrix in (8.1) is positive semidefinite due to the presence of rounding errors. It is also very easy to make a mistake so Q becomes indefinite. These causes of problems are completely eliminated in the conic formulation.

Moreover, observe the constraint

$$\|G^T x\| \leq \gamma$$

is nicer than

$$x^T \Sigma x \leq \gamma^2$$

for small values of γ . For instance assume a γ of 10000 then γ^2 would be 1.0e8 which introduces a scaling issue in the model. Hence, using conic formulation it is possible to work with the standard deviation instead of the variance, which usually gives rise to a better scaled model.

8.1.2.2 Implementing the portfolio model

The model (8.3) can not be implemented as stated using the MOSEK optimizer API because the API requires the problem to be on the form

$$\begin{aligned} & \text{maximize} && c^T \hat{x} \\ & \text{subject to} && l^c \leq A\hat{x} \leq u^c, \\ & && l^x \leq \hat{x} \leq u^x, \\ & && \hat{x} \in K. \end{aligned} \tag{8.4}$$

where \hat{x} is referred to as the API variable.

The first step in bringing (8.3) to the form (8.4) is the reformulation

$$\begin{aligned} & \text{maximize} && \mu^T x \\ & \text{subject to} && e^T x = w + e^T x^0, \\ & && G^T x - t = 0 \\ & && [s; t] \in Q^{n+1}, \\ & && x \geq 0, \\ & && s \geq 0. \end{aligned} \tag{8.5}$$

where s is an additional scalar variable and t is a n dimensional vector variable. The next step is to define a mapping of the variables

$$\hat{x} = [x; s; t] = \begin{bmatrix} x \\ s \\ t \end{bmatrix}. \tag{8.6}$$

Hence, the API variable \hat{x} is concatenation of model variables x , s and t . In Table (8.1) the details of the concatenation are specified. For instance it can be seen that

$$\hat{x}_{n+2} = t_1.$$

because the offset of the t variable is $n + 2$.

Given the ordering of the variables specified by (8.6) the data should be defined as follows

Variable	Length	Offset
x	n	1
s	1	$n+1$
t	n	$n+2$

Figure 8.1: Storage layout of the \hat{x} variable.

$$\begin{aligned}
c &= \begin{bmatrix} \mu^T & 0 & 0_{n,1} \end{bmatrix}^T, \\
A &= \begin{bmatrix} e^T & 0 & 0_{n,1} \\ G^T & 0_{n,1} & -I_n \end{bmatrix}, \\
l^c &= \begin{bmatrix} w + e^T x^0 & 0_{1,n} \end{bmatrix}^T, \\
u^c &= \begin{bmatrix} w + e^T x^0 & 0_{1,n} \end{bmatrix}^T, \\
l^x &= \begin{bmatrix} 0_{1,n} & \gamma & -\infty_{n,1} \end{bmatrix}^T, \\
u^x &= \begin{bmatrix} \infty_{n,1} & \gamma & \infty_{n,1} \end{bmatrix}^T.
\end{aligned}$$

The next step is to consider how the columns of A is defined. The following pseudo code

```

for      j = 1 : n
     $\hat{x}_j = x_j$ 
     $A_{1,j} = 1.0$ 
     $A_{2:(n+1),j} = G_{j,1:n}^T$ 

 $\hat{x}_{n+1} = s$ 

for      j = 1 : n
     $\hat{x}_{n+1+j} = t_j$ 
     $A_{n+1+j,n+1+j} = -1.0$ 

```

show how to construct each column of A .

In the above discussion index origin 1 is employed, i.e., the first position in a vector is 1. The C programming language employs 0 as index origin and that should be kept in mind when reading the example code.

```

1  /*-----[ case_portfolio_1.c ]-----
2  File : case_portfolio_1.c
3
4  Copyright : Copyright (c) MOSEK ApS, Denmark. All rights reserved.
5
6  Description : Implements a basic portfolio optimization model.
7  */
8
9  #include <math.h>
10 #include <stdio.h>
11
12 #include "mosek.h"
13
14 #define MOSEKCALL(r,_call)  ( (_r)==MSK_RES_OK ? ( (_r) = (_call) ) : ( (_r) = (r) ) );

```

```

15
16 static void MSKAPI printstr(void *handle,
17                             MSKCONST char str[])
18 {
19     printf("%s",str);
20 } /* printstr */
21
22 int main(int argc, const char argv[])
23 {
24     char          buf[128];
25     const MSKint32t n=3;
26     const double   gamma=0.05,
27                   mu[]={0.1073, 0.0737, 0.0627},
28                   GT[][3]={0.1667, 0.0232, 0.0013},
29                           {0.0000, 0.1033, -0.0022},
30                           {0.0000, 0.0000, 0.0338}},
31                   x0[3]={0.0, 0.0, 0.0},
32                   w=1.0;
33     double         rtemp;
34     MSKenv_t       env;
35     MSKint32t      k,i,j,offsetx,offsets,offsett,*sub;
36     MSKrescodee    res=MSK_RES_OK;
37     MSKtask_t      task;
38
39     sub = (MSKint32t *) calloc(n,sizeof(MSKint32t));
40
41     res = sub==NULL ? MSK_RES_ERR_SPACE : MSK_RES_OK;
42
43     /* Initial setup. */
44     MOSEKCALL(res,MSK_makeenv(&env,NULL));
45     MOSEKCALL(res,MSK_maketask(env,0,0,&task));
46     MOSEKCALL(res,MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr));
47
48     rtemp = w;
49     for(j=0; j<n; ++j)
50         rtemp += x0[j];
51
52     /* Constraints. */
53     MOSEKCALL(res,MSK_appendcons(task,1+n));
54     MOSEKCALL(res,MSK_putconbound(task,0,MSK_BK_FX,rtemp,rtemp));
55     sprintf(buf,"%s","budget");
56     MOSEKCALL(res,MSK_putconname(task,0,buf));
57
58     for(i=0; i<n; ++i)
59     {
60         MOSEKCALL(res,MSK_putconbound(task,1+i,MSK_BK_FX,0.0,0.0));
61         sprintf(buf,"GT[%d]",1+i);
62         MOSEKCALL(res,MSK_putconname(task,1+i,buf));
63     }
64
65     /* Variables. */
66     MOSEKCALL(res,MSK_appendvars(task,1+2*n));
67
68     offsetx = 0; /* Offset of variable x into the API variable. */
69     offsets = n; /* Offset of variable x into the API variable. */
70     offsett = n+1; /* Offset of variable t into the API variable. */
71
72     /* x variables. */

```

```

73     for(j=0; j<n; ++j)
74     {
75         MOSEKCALL(res,MSK_putc_j(task,offsetx+j,mu[j]));
76         MOSEKCALL(res,MSK_putaij(task,0,offsetx+j,1.0));
77         for(k=0; k<n; ++k)
78             if( GT[k][j]!=0.0 )
79                 MOSEKCALL(res, MSK_putaij(task, 1 + k, offsetx + j, GT[k][j]));
80
81         MOSEKCALL(res,MSK_putvarbound(task,offsetx+j,MSK_BK_L0,0.0,MSK_INFINITY));
82         sprintf(buf,"%d",1+j);
83         MOSEKCALL(res,MSK_putvarname(task,offsetx+j,buf));
84     }
85
86     /* s variable. */
87     MOSEKCALL(res,MSK_putvarbound(task,offsets+0,MSK_BK_FX,gamma,gamma));
88     sprintf(buf,"s");
89     MOSEKCALL(res,MSK_putvarname(task,offsets+0,buf));
90
91     /* t variables. */
92     for(j=0; j<n; ++j)
93     {
94         MOSEKCALL(res,MSK_putaij(task,1+j,offsett+j,-1.0));
95         MOSEKCALL(res,MSK_putvarbound(task,offsett+j,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY));
96         sprintf(buf,"%d",1+j);
97         MOSEKCALL(res,MSK_putvarname(task,offsett+j,buf));
98     }
99
100     sub[0] = offsets+0;
101     for(j=0; j<n; ++j)
102         sub[j+1] = offsett+j;
103
104     MOSEKCALL(res,MSK_appendcone(task,MSK_CT_QUAD,0.0,n+1,sub));
105     MOSEKCALL(res,MSK_putconename(task,0,"stddev"));
106
107     MOSEKCALL(res,MSK_putobjsense(task,MSK_OBJECTIVE_SENSE_MAXIMIZE));
108
109     #if 0
110     /* Turn all logout put off. */
111     MOSEKCALL(res,MSK_putintparam(task,MSK_IPAR_LOG,0));
112     #endif
113
114     #if 0
115     /* Dump the problem to a human readable OPF file. */
116     MOSEKCALL(res,MSK_writedata(task,"dump.opf"));
117     #endif
118
119     MOSEKCALL(res,MSK_optimize(task));
120
121     #if 1
122     /* Display the solution summary for quick inspection of results. */
123     MSK_solutionsummary(task,MSK_STREAM_MSG);
124     #endif
125
126     if ( res==MSK_RES_OK )
127     {
128         double expret=0.0,stddev=0.0,xj;
129
130         for(j=0; j<n; ++j)

```

```

131     {
132         MOSEKCALL(res,MSK_getxxslice(task,MSK_SOL_ITR,offsetx+j,offsetx+j+1,&xj));
133         expret += mu[j]*xj;
134     }
135
136     MOSEKCALL(res,MSK_getxxslice(task,MSK_SOL_ITR,offsets+0,offsets+1,&stddev));
137
138     printf("\nExpected return %e for gamma %e\n",expret,stddev);
139 }
140
141 free(sub);
142
143 return ( 0 );
144 }

```

The above code produce the result

```

Interior-point solution summary
Problem status : PRIMAL_AND_DUAL_FEASIBLE
Solution status : OPTIMAL
Primal.  obj: 7.4766497707e-002   Viol.  con: 2e-008   var: 0e+000   cones: 3e-009
Dual.    obj: 7.4766522618e-002   Viol.  con: 0e+000   var: 4e-008   cones: 0e+000

```

Expected return 7.476650e-002 for gamma 5.000000e-002

The source code should be self-explanatory but a few comments are nevertheless in place. In the lines

```

68 offsetx = 0; /* Offset of variable x into the API variable. */
69 offsets = n; /* Offset of variable x into the API variable. */
70 offsett = n+1; /* Offset of variable t into the API variable. */

```

offsets into the MOSEK API variables are stored and those offsets are used later. The code

```

73 for(j=0; j<n; ++j)
74 {
75     MOSEKCALL(res,MSK_putcj(task,offsetx+j,mu[j]));
76     MOSEKCALL(res,MSK_putaij(task,0,offsetx+j,1.0));
77     for(k=0; k<n; ++k)
78         if( GT[k][j]!=0.0 )
79             MOSEKCALL(res, MSK_putaij(task, 1 + k, offsetx + j, GT[k][j]));
80
81     MOSEKCALL(res,MSK_putvarbound(task,offsetx+j,MSK_BK_LO,0.0,MSK_INFINITY));
82     sprintf(buf,"x[%d]",1+j);
83     MOSEKCALL(res,MSK_putvarname(task,offsetx+j,buf));
84 }

```

sets up the data for x variables. For instance

```

75 MOSEKCALL(res,MSK_putcj(task,offsetx+j,mu[j]));

```

inputs the objective coefficients for the x variables. Moreover, the code

```

82  sprintf(buf, "x[%d]", 1+j);
83  MOSEKCALL(res, MSK_putvarname(task, offsetx+j, buf));

```

assigns meaningful names to the API variables. This is not needed but it makes debugging easier.

8.1.2.3 Debugging tips

Implementing an optimization model in optimizer can be cumbersome and error-prone and it is very easy to make mistakes. In order to check the implemented code for mistakes it is very useful to dump the problem to a file in a human readable form for visual inspection. The line

```

116 MOSEKCALL(res, MSK_writedata(task, "dump.opf"));

```

does that and this will produce a file with the content

```

[comment]
  Written by MOSEK version 7.0.0.86
  Date 01-10-13
  Time 08:43:21
[/comment]

[hints]
[ hint NUMVAR] 7 [/hint]
[ hint NUMCON] 4 [/hint]
[ hint NUMANZ] 12 [/hint]
[ hint NUMQNZ] 0 [/hint]
[ hint NUMCONE] 1 [/hint]
[/hints]

[variables disallow_new_variables]
'x[1]' 'x[2]' 'x[3]' 's' 't[1]'
't[2]' 't[3]'
[/variables]

[objective maximize]
  1.073e-001 'x[1]' + 7.37e-002 'x[2]' + 6.2700000000000001e-002 'x[3]'
[/objective]

[constraints]
[con 'budget'] 'x[1]' + 'x[2]' + 'x[3]' = 1e+000 [/con]
[con 'GT[1]'] 1.667e-001 'x[1]' + 2.32e-002 'x[2]' + 1.3e-003 'x[3]' - 't[1]' = 0e+000 [/con]
[con 'GT[2]'] 1.033e-001 'x[2]' - 2.2e-003 'x[3]' - 't[2]' = 0e+000 [/con]
[con 'GT[3]'] 3.38e-002 'x[3]' - 't[3]' = 0e+000 [/con]
[/constraints]

[bounds]
[b] 0 <= * [/b]
[b] s = 5e-002 [/b]
[b] 't[1]', 't[2]', 't[3]' free [/b]
[cone quad 'stddev'] s, 't[1]', 't[2]', 't[3]' [/cone]
[/bounds]

```

Observe that since the API variables have been given meaningful names it is easy to see the model is correct.

8.1.3 The efficient frontier

The portfolio computed by the Markowitz model is efficient in the sense that there is no other portfolio giving a strictly higher return for the same amount of risk. An efficient portfolio is also sometimes called a Pareto optimal portfolio. Clearly, an investor should only invest in efficient portfolios and therefore it may be relevant to present the investor with all efficient portfolios so the investor can choose the portfolio that has the desired tradeoff between return and risk.

Given a nonnegative α then the problem

$$\begin{aligned} & \text{maximize} && \mu^T x - \alpha s \\ & \text{subject to} && e^T x = w + e^T x^0, \\ & && [s; G^T x] \in Q^{n+1}, \\ & && x \geq 0. \end{aligned} \tag{8.7}$$

computes efficient portfolios. Note that the objective maximizes the expected return while maximizing $-\alpha$ times the standard deviation. Hence, the standard deviation is minimized while α specifies the tradeoff between expected return and risk.

Ideally the problem 8.7 should be solved for all values $\alpha \geq 0$ but in practice that is computationally too costly.

Using the example data from Section 8.1.2, the optimal values of return and risk for several α s are listed below:

alpha	exp ret	std dev
0.000e+000	1.073e-001	7.261e-001
2.500e-001	1.033e-001	1.499e-001
5.000e-001	6.976e-002	3.735e-002
7.500e-001	6.766e-002	3.383e-002
1.000e+000	6.679e-002	3.281e-002
1.500e+000	6.599e-002	3.214e-002
2.000e+000	6.560e-002	3.192e-002
2.500e+000	6.537e-002	3.181e-002
3.000e+000	6.522e-002	3.176e-002
3.500e+000	6.512e-002	3.173e-002
4.000e+000	6.503e-002	3.170e-002
4.500e+000	6.497e-002	3.169e-002

8.1.3.1 Example code

The following example code demonstrates how to compute the efficient portfolios for several values of α .

```

1  /*
2  File : case_portfolio.2.c
3
4  Copyright : Copyright (c) MOSEK ApS, Denmark. All rights reserved.
```

```

5
6     Description : Implements a basic portfolio optimization model.
7     */
8
9     #include <math.h>
10    #include <stdio.h>
11
12    #include "mosek.h"
13
14    #define MOSEKCALL(_r,_call) ( (_r)==MSK_RES_OK ? ( (_r) = (_call) ) : ( (_r) = (_r) ) );
15
16    static void MSKAPI printstr(void *handle,
17                                MSKCONST char str[])
18    {
19        printf("%s",str);
20    } /* printstr */
21
22    int main(int argc, const char argv[])
23    {
24        char          buf[128];
25        const MSKint32t n=3,numalpha=12;
26        const double   mu[]={0.1073, 0.0737, 0.0627},
27                        G[][3]={0.1667, 0.0232, 0.0013},
28                               {0.0000, 0.1033, -0.0022},
29                               {0.0000, 0.0000, 0.0338}},
30                        x0[3]={0.0, 0.0, 0.0},
31                        w=1.0,
32                        alphas[12]={0.0, 0.25, 0.5, 0.75, 1.0, 1.5, 2.0, 2.5, 3.0, 3.5, 4.0, 4.5};
33        MSKenv_t      env;
34        MSKint32t      k,i,j,offsetx,offsets,offsett,*sub;
35        MSKrescodee    res=MSK_RES_OK;
36        MSKtask_t      task;
37
38        sub = (MSKint32t *) calloc(n,sizeof(MSKint32t));
39
40        res = sub==NULL ? MSK_RES_ERR_SPACE : MSK_RES_OK;
41
42        /* Initial setup. */
43        MOSEKCALL(res,MSK_makeenv(&env,NULL));
44        MOSEKCALL(res,MSK_maketask(env,0,0,&task));
45        MOSEKCALL(res,MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr));
46
47        /* Constraints. */
48        MOSEKCALL(res,MSK_appendcons(task,1+n));
49        MOSEKCALL(res,MSK_putconbound(task,0,MSK_BK_FX,1.0,1.0));
50        sprintf(buf,"%s","budget");
51        MOSEKCALL(res,MSK_putconname(task,0,buf));
52
53        for(i=0; i<n; ++i)
54        {
55            MOSEKCALL(res,MSK_putconbound(task,1+i,MSK_BK_FX,0.0,0.0));
56            sprintf(buf,"GT[%d]",1+i);
57            MOSEKCALL(res,MSK_putconname(task,1+i,buf));
58        }
59
60        /* Variables. */
61        MOSEKCALL(res,MSK_appendvars(task,1+2*n));
62

```



```

63     offsetx = 0; /* Offset of variable x into the API variable. */
64     offsets = n; /* Offset of variable x into the API variable. */
65     offsett = n+1; /* Offset of variable t into the API variable. */
66
67     /* x variables. */
68     for(j=0; j<n; ++j)
69     {
70         MOSEKCALL(res,MSK_putcj(task,offsetx+j,mu[j]));
71         MOSEKCALL(res,MSK_putaij(task,0,offsetx+j,1.0));
72         for(k=0; k<n; ++k)
73             if( G[k][j]!=0.0 )
74                 MOSEKCALL(res, MSK_putaij(task, 1 + k, offsetx + j, G[k][j]));
75
76         MOSEKCALL(res,MSK_putvarbound(task,offsetx+j,MSK_BK_L0,0.0,MSK_INFINITY));
77         sprintf(buf,"x[%d]",1+j);
78         MOSEKCALL(res,MSK_putvarname(task,offsetx+j,buf));
79     }
80
81     /* s variable. */
82     MOSEKCALL(res,MSK_putvarbound(task,offsets+0,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY));
83     sprintf(buf,"s");
84     MOSEKCALL(res,MSK_putvarname(task,offsets+0,buf));
85
86     /* t variables. */
87     for(j=0; j<n; ++j)
88     {
89         MOSEKCALL(res,MSK_putaij(task,1+j,offsett+j,-1.0));
90         MOSEKCALL(res,MSK_putvarbound(task,offsett+j,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY));
91         sprintf(buf,"t[%d]",1+j);
92         MOSEKCALL(res,MSK_putvarname(task,offsett+j,buf));
93     }
94
95     sub[0] = offsets+0;
96     for(j=0; j<n; ++j)
97         sub[j+1] = offsett+j;
98
99     MOSEKCALL(res,MSK_appendcone(task,MSK_CT_QUAD,0.0,n+1,sub));
100    MOSEKCALL(res,MSK_putconename(task,0,"stddev"));
101
102    MOSEKCALL(res,MSK_putobjsense(task,MSK_OBJECTIVE_SENSE_MAXIMIZE));
103
104    /* Turn all log output off. */
105    MOSEKCALL(res,MSK_putintparam(task,MSK_IPAR_LOG,0));
106
107    printf("%-12s  %-12s  %-12s\n","alpha","exp ret","std dev");
108
109    for(k=0; k<numalpha; ++k)
110    {
111        double    expret,stddev,alpha;
112        MSKsolstae solsta;
113
114        alpha = alphas[k];
115
116        /* Sets the objective function coefficient for s. */
117        MOSEKCALL(res,MSK_putcj(task,offsets+0,-alpha));
118
119        MOSEKCALL(res,MSK_optimize(task));
120

```

```

121     MOSEKCALL(res,MSK_getsolsta(task,MSK_SOL_ITR,&solsta));
122
123     if( solsta==MSK_SOL_STA_OPTIMAL || solsta==MSK_SOL_STA_NEAR_OPTIMAL )
124     {
125         double expret,stddev,xj;
126
127         expret = 0.0;
128         for(j=0; j<n; ++j)
129         {
130             MOSEKCALL(res,MSK_getxxslice(task,MSK_SOL_ITR,offsetx+j,offsetx+j+1,&xj));
131             expret += mu[j]*xj;
132         }
133
134         MOSEKCALL(res,MSK_getxxslice(task,MSK_SOL_ITR,offsets+0,offsets+1,&stddev));
135
136         printf("%-12.3e  %-12.3e  %-12.3e\n",alpha,expret,stddev);
137     }
138     else
139     {
140         printf("An error occurred when solving for alpha=%e\n",alpha);
141     }
142 }
143
144 free(sub);
145
146 return ( 0 );
147 }

```

8.1.4 Improving the computational efficiency

In practice it is often important to solve the portfolio problem in a short amount of time; this section it discusses what can be done at the modelling stage to improve the computational efficiency.

The computational cost is of course to some extent dependent on the number of constraints and variables in the optimization problem. However, in practice a more important factor is the number nonzeros used to represent the problem. Indeed it is often better to focus at the number of nonzeros in G (see (8.2)) and try to reduce that number by for instance changing the choice of G .

In other words, if the computational efficiency should be improved then it is always good idea to start with focusing at the covariance matrix. As an example assume that

$$\Sigma = D + VV^T$$

where D is positive definite diagonal matrix. Moreover, V is a matrix with n rows and p columns. Such a model for the covariance matrix is called a factor model and usually p is much smaller than n . In practice p tends to be a small number say less than 100 independent of n .

One possible choice for G is the Cholesky factorization of Σ which requires storage proportional to $n(n+1)/2$. However, another choice is

$$G^T = \begin{bmatrix} D^{1/2} \\ V^T \end{bmatrix}$$

because then

$$GG^T = D + VV^T.$$

This choice requires storage proportional to $n + pn$ which is much less than for the Cholesky choice of G . Indeed assuming p is a constant then the difference in storage requirements is a factor of n .

The example above exploits the so-called factor structure and demonstrates that an alternative choice of G may lead to a significant reduction in the amount of storage used to represent the problem. This will in most cases also lead to a significant reduction in the solution time.

The lesson to be learned is that it is important to investigate how the covariance is formed. Given this knowledge it might be possible to make a special choice for G that helps reducing the storage requirements and enhance the computational efficiency.

8.1.5 Slippage cost

The basic Markowitz portfolio model assumes that there are no costs associated with trading the assets and that the returns of the assets is independent of the amount traded. None of those assumptions are usually valid in practice. Therefore, a more realistic model is

$$\begin{aligned} & \text{maximize} && \mu^T x \\ & \text{subject to} && e^T x + \sum_{j=1}^n C_j(x_j - x_j^0) = w + e^T x^0, \\ & && x^T \Sigma x \leq \gamma^2, \\ & && x \geq 0, \end{aligned} \tag{8.8}$$

where the function

$$C_j(x_j - x_j^0)$$

specifies the transaction costs when the holding of asset j is changed from its initial value.

8.1.5.1 Market impact costs

If the initial wealth is fairly small and short selling is not allowed, then the holdings will be small. Therefore, the amount traded of each asset must also be small. Hence, it is reasonable to assume that the prices of the assets is independent of the amount traded. However, if a large volume of an asset is sold or purchased it can be expected that the price change and hence the expected return also change. This effect is called market impact costs. It is common to assume that market impact costs for asset j can be modelled by

$$m_j \sqrt{|x_j - x_j^0|}$$

where m_j is a constant that is estimated in some way. See [6][p. 452] for details. To summarize then

$$C_j(x_j - x_j^0) = m_j |x_j - x_j^0| \sqrt{|x_j - x_j^0|} = m_j |x_j - x_j^0|^{3/2}.$$

From [7] it is known

$$\{(c, z) : c \geq z^{3/2}, z \geq 0\} = \{(c, z) : [v; c; z], [z; 1/8; v] \in Q_r^3\}$$

where Q_r^3 is the 3 dimensional rotated quadratic cone implying

$$\begin{aligned} z_j &= |x_j - x_j^0|, \\ [v_j; c_j; z_j], [z_j; 1/8; v_j] &\in Q_r^3, \\ \sum_{j=1}^n C_j(x_j - x_j^0) &= \sum_{j=1}^n c_j. \end{aligned}$$

Unfortunately this set of constraints is nonconvex due to the constraint

$$z_j = |x_j - x_j^0| \tag{8.9}$$

but in many cases that constraint can safely be replaced by the relaxed constraint

$$z_j \geq |x_j - x_j^0| \tag{8.10}$$

which is convex. If for instance the universe of assets contains a risk free asset with a positive return then

$$z_j > |x_j - x_j^0| \tag{8.11}$$

cannot hold for an optimal solution because that would imply the solution is not optimal.

Now assume that the optimal solution has the property that (8.11) holds then the market impact cost within the model is larger than the true market impact cost and hence money are essentially considered garbage and removed by generating transaction costs. This may happen if a portfolio with very small risk is requested because then the only way to obtain a small risk is to get rid of some of the assets by generating transaction costs. Here it is assumed this is not the case and hence the models (8.9) and (8.10) are equivalent.

Formula (8.10) is replaced by constraints

$$\begin{aligned} z_j &\geq x_j - x_j^0, \\ z_j &\geq -(x_j - x_j^0). \end{aligned} \tag{8.12}$$

Now we have

$$\begin{aligned}
& \text{maximize} && \mu^T x \\
& \text{subject to} && e^T x + m^T c = w + e^T x^0, \\
& && z_j \geq x_j - x_j^0, & j = 1, \dots, n, \\
& && z_j \geq x_j^0 - x_j, & j = 1, \dots, n, \\
& && [\gamma; G^T x] \in Q^{n+1}, \\
& && [v_j; c_j; z_j] \in Q_r^3, & j = 1, \dots, n, \\
& && [z_j; 1/8; v_j] \in Q_r^3, & j = 1, \dots, n, \\
& && x \geq 0.
\end{aligned} \tag{8.13}$$

The revised budget constraint

$$e^T x = w + e^T x^0 - m^T c$$

specifies that the total investment must be equal to the initial wealth minus the transaction costs. Moreover, observe the variables v and z are some auxiliary variables that model the market impact cost. Indeed it holds

$$z_j \geq |x_j - x_j^0|$$

and

$$c_j \geq z_j^{3/2}.$$

Before proceeding it should be mentioned that transaction costs of the form

$$c_j \geq z_j^{p/q}$$

where p and q are both integers and $p \geq q$ can be modelled using quadratic cones. See [7] for details.

One more reformulation of (8.13) is needed,

$$\begin{aligned}
& \text{maximize} && \mu^T x \\
& \text{subject to} && e^T x + m^T c = w + e^T x^0, \\
& && G^T x - t = 0, \\
& && z_j - x_j \geq -x_j^0, & j = 1, \dots, n, \\
& && z_j + x_j \geq x_j^0, & j = 1, \dots, n, \\
& && [v_j; c_j; z_j] - f_{j,1:3} = 0, & j = 1, \dots, n, \\
& && [z_j; 0; v_j] - g_{j,1:3} = [0; -1/8; 0], & j = 1, \dots, n, \\
& && [s; t] \in Q^{n+1}, \\
& && f_{j,1:3}^T \in Q_r^3, & j = 1, \dots, n, \\
& && g_{j,1:3}^T \in Q_r^3, & j = 1, \dots, n, \\
& && x \geq 0, \\
& && s = \gamma,
\end{aligned} \tag{8.14}$$

where $f, g \in R^{n \times 3}$. These additional variables f and g are only introduced to bring the problem on the API standard form.

Variable	Length	Offset
x	n	1
s	1	$n+1$
t	n	$n+2$
c	n	$2n+2$
v	n	$3n+2$
z	n	$4n+2$
$f(\cdot)^T$	$3n$	$7n+2$
$g(\cdot)^T$	$3n$	$10n+2$

Figure 8.2: Storage layout for the \hat{x}

The formulation (8.14) is not the most compact possible. However, the MOSEK presolve will automatically make it more compact and since it is easier to implement (8.14) than a more compact form then the form (8.14) is preferred.

The first step in developing the optimizer API implementation is to chose an ordering of the variables. In this case the ordering

$$\hat{x} = \begin{bmatrix} x \\ s \\ t \\ c \\ v \\ z \\ f^T(\cdot) \\ g^T(\cdot) \end{bmatrix}$$

will be used. Note $f^T(\cdot)$ means the rows of f are transposed and stacked on top of each other to form a long column vector. The Table 8.2 shows the mapping between the \hat{x} and the model variables.

The next step is to consider how the columns of A is defined. Reusing the idea in Section 8.1.2 then the following pseudo code describes the setup of A .

```

for      j = 1 : n
           $\hat{x}_j = x_j$ 
           $A_{1,j} = 1.0$ 
           $A_{2:n+1,j} = G_{j,1:n}^T$ 
           $A_{n+1+j,j} = -1.0$ 
           $A_{2n+1+j,j} = 1.0$ 

 $\hat{x}_{n+1} = s$ 

for      j = 1 : n
           $\hat{x}_{n+1+j} = t_j$ 
           $A_{1+j,n+1+j} = -1.0$ 

for      j = 1 : n
           $\hat{x}_{2n+1+j} = c_j$ 
           $A_{1,2n+1+j} = m_j$ 
           $A_{3n+1+3(j-1)+2,2n+1+j} = 1.0$ 

for      j = 1 : n
           $\hat{x}_{3n+1+j} = v_j$ 
           $A_{3n+1+3(j-1)+1,3n+1+j} = 1.0$ 
           $A_{6n+1+3(j-1)+3,3n+1+j} = 1.0$ 

for      j = 1 : n
           $\hat{x}_{4n+1+j} = z_j$ 
           $A_{1+n+j,4n+1+j} = 1.0$ 
           $A_{1+2n+j,4n+1+j} = 1.0$ 
           $A_{3n+1+3(j-1)+3,4n+1+j} = 1.0$ 
           $A_{6n+1+3(j-1)+1,4n+1+j} = 1.0$ 

for      j = 1 : n
           $\hat{x}_{7n+1+3(j-1)+1} = f_{j,1}$ 
           $A_{3n+1+3(j-1)+1,7n+(3(j-1)+1)} = -1.0$ 
           $\hat{x}_{7n+1+3(j-1)+2} = f_{j,2}$ 
           $A_{3n+1+3(j-1)+2,7n+(3(j-1)+2)} = -1.0$ 
           $\hat{x}_{7n+1+3(j-1)+3} = f_{j,3}$ 
           $A_{3n+1+3(j-1)+3,7n+(3(j-1)+3)} = -1.0$ 

for      j = 1 : n
           $\hat{x}_{10n+1+3(j-1)+1} = g_{j,1}$ 
           $A_{6n+1+3(j-1)+1,7n+(3(j-1)+1)} = -1.0$ 
           $\hat{x}_{10n+1+3(j-1)+2} = g_{j,2}$ 
           $A_{6n+1+3(j-1)+2,7n+(3(j-1)+2)} = -1.0$ 
           $\hat{x}_{10n+1+3(j-1)+3} = g_{j,3}$ 
           $A_{6n+1+3(j-1)+3,7n+(3(j-1)+3)} = -1.0$ 

```

The following example code demonstrates how to implement the model (8.14).

```

1  /*
2   File : case_portfolio_3.c
3
4   Copyright : Copyright (c) MOSEK ApS, Denmark. All rights reserved.
5
6   Description : Implements a basic portfolio optimization model.
7   */
8
9  #include <math.h>
10 #include <stdio.h>
11
12 #include "mosek.h"
13
14 #define MOSEKCALL(r,_call) ( (_r)==MSK_RES_OK ? ( (_r) = (_call) ) : ( (_r) = (r) ) );
15
16 static void MSKAPI printstr(void *handle,
17                             MSKCONST char str[])
18 {
19     printf("%s",str);
20 } /* printstr */
21
22 int main(int argc, const char argv[])
23 {
24     char          buf[128];
25     const MSKint32t n=3;
26     const double   w=1.0,
27                   x0[3]={0.0, 0.0, 0.0},
28                   gamma=0.05,
29                   mu[]={0.1073, 0.0737, 0.0627},
30                   GT[][3]={0.1667, 0.0232, 0.0013},
31                           {0.0000, 0.1033, -0.0022},
32                           {0.0000, 0.0000, 0.0338}},
33                   m[3]={0.01, 0.01, 0.01};
34     double
35     MSKenv_t      env;
36     MSKint32t     k,i,j,
37                   offsetx,offsets,offsett,offsetc,
38                   offsetv,offsetz,offsetf,offsetg,
39                   *sub;
40     MSKrescode_e   res=MSK_RES_OK;
41     MSKtask_t      task;
42
43     sub = (MSKint32t *) calloc(max(3,n),sizeof(MSKint32t));
44
45     res = sub==NULL ? MSK_RES_ERR_SPACE : MSK_RES_OK;
46
47     /* Initial setup. */
48     MOSEKCALL(res,MSK_makeenv(&env,NULL));
49     MOSEKCALL(res,MSK_maketask(env,0,0,&task));
50     MOSEKCALL(res,MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr));
51
52     rtemp = w;
53     for(k=0; k<n; ++k)
54         rtemp += x0[k];
55

```



```

56  /* Constraints. */
57  MOSEKCALL(res,MSK_appendcons(task,1+9*n));
58  MOSEKCALL(res,MSK_putconbound(task,0,MSK_BK_FX,w,w));
59  sprintf(buf,"%s","budget");
60  MOSEKCALL(res,MSK_putconname(task,0,buf));
61
62  for(i=0; i<n; ++i)
63  {
64      MOSEKCALL(res,MSK_putconbound(task,1+i,MSK_BK_FX,0.0,0.0));
65      sprintf(buf,"GT[%d]",1+i);
66      MOSEKCALL(res,MSK_putconname(task,1+i,buf));
67  }
68
69  for(i=0; i<n; ++i)
70  {
71      MOSEKCALL(res,MSK_putconbound(task,1+n+i,MSK_BK_LO,-x0[i],MSK_INFINITY));
72      sprintf(buf,"zabs1[%d]",1+i);
73      MOSEKCALL(res,MSK_putconname(task,1+n+i,buf));
74  }
75
76  for(i=0; i<n; ++i)
77  {
78      MOSEKCALL(res,MSK_putconbound(task,1+2*n+i,MSK_BK_LO,x0[i],MSK_INFINITY));
79      sprintf(buf,"zabs2[%d]",1+i);
80      MOSEKCALL(res,MSK_putconname(task,1+2*n+i,buf));
81  }
82
83  for(i=0; i<n; ++i)
84  {
85      for(k=0; k<3; ++k)
86      {
87          MOSEKCALL(res,MSK_putconbound(task,1+3*n+3*i+k,MSK_BK_FX,0.0,0.0));
88          sprintf(buf,"f[%d,%d]",1+i,1+k);
89          MOSEKCALL(res,MSK_putconname(task,1+3*n+3*i+k,buf));
90      }
91  }
92
93
94  for(i=0; i<n; ++i)
95  {
96      double b[3]={0.0, -1.0/8.0, 0.0};
97
98      for(k=0; k<3; ++k)
99      {
100          MOSEKCALL(res,MSK_putconbound(task,1+6*n+3*i+k,MSK_BK_FX,b[k],b[k]));
101          sprintf(buf,"g[%d,%d]",1+i,1+k);
102          MOSEKCALL(res,MSK_putconname(task,1+6*n+3*i+k,buf));
103      }
104  }
105
106
107  /* Offsets of variables into the (serialized) API variable. */
108  offsetx = 0;
109  offsets = n;
110  offsett = n+1;
111  offsetc = 2*n+1;
112  offsetv = 3*n+1;
113  offsetz = 4*n+1;

```

```

114     offsetf = 5*n+1;
115     offsetg = 8*n+1;
116
117     /* Variables. */
118     MOSEKCALL(res,MSK_appendvars(task,11*n+1));
119
120     /* x variables. */
121     for(j=0; j<n; ++j)
122     {
123         MOSEKCALL(res,MSK_putcj(task,offsetx+j,mu[j]));
124         MOSEKCALL(res,MSK_putaij(task,0,offsetx+j,1.0));
125         for(k=0; k<n; ++k)
126             if( GT[k][j]!=0.0 )
127                 MOSEKCALL(res, MSK_putaij(task,1+k,offsetx+j,GT[k][j]));
128         MOSEKCALL(res,MSK_putaij(task,1+n+j,offsetx+j,-1.0));
129         MOSEKCALL(res,MSK_putaij(task,1+2*n+j,offsetx+j,1.0));
130
131         MOSEKCALL(res,MSK_putvarbound(task,offsetx+j,MSK_BK_LO,0.0,MSK_INFINITY));
132         sprintf(buf,"x[%d]",1+j);
133         MOSEKCALL(res,MSK_putvarname(task,offsetx+j,buf));
134     }
135
136     /* s variable. */
137     MOSEKCALL(res,MSK_putvarbound(task,offsets+0,MSK_BK_FX,gamma,gamma));
138     sprintf(buf,"s");
139     MOSEKCALL(res,MSK_putvarname(task,offsets+0,buf));
140
141     /* t variables. */
142     for(j=0; j<n; ++j)
143     {
144         MOSEKCALL(res,MSK_putaij(task,1+j,offsett+j,-1.0));
145         MOSEKCALL(res,MSK_putvarbound(task,offsett+j,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY));
146         sprintf(buf,"t[%d]",1+j);
147         MOSEKCALL(res,MSK_putvarname(task,offsett+j,buf));
148     }
149
150     /* c variables. */
151     for(j=0; j<n; ++j)
152     {
153         MOSEKCALL(res,MSK_putaij(task,0,offsetc+j,m[j]));
154         MOSEKCALL(res,MSK_putaij(task,1+3*n+3*j+1,offsetc+j,1.0));
155         MOSEKCALL(res,MSK_putvarbound(task,offsetc+j,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY));
156         sprintf(buf,"c[%d]",1+j);
157         MOSEKCALL(res,MSK_putvarname(task,offsetc+j,buf));
158     }
159
160     /* v variables. */
161     for(j=0; j<n; ++j)
162     {
163         MOSEKCALL(res,MSK_putaij(task,1+3*n+3*j+0,offsetv+j,1.0));
164         MOSEKCALL(res,MSK_putaij(task,1+6*n+3*j+2,offsetv+j,1.0));
165         MOSEKCALL(res,MSK_putvarbound(task,offsetv+j,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY));
166         sprintf(buf,"v[%d]",1+j);
167         MOSEKCALL(res,MSK_putvarname(task,offsetv+j,buf));
168     }
169
170     /* z variables. */
171     for(j=0; j<n; ++j)

```

```

172 {
173     MOSEKCALL(res,MSK_putaij(task,1+1*n+j,offsetz+j,1.0));
174     MOSEKCALL(res,MSK_putaij(task,1+2*n+j,offsetz+j,1.0));
175     MOSEKCALL(res,MSK_putaij(task,1+3*n+3*j+2,offsetz+j,1.0));
176     MOSEKCALL(res,MSK_putaij(task,1+6*n+3*j+0,offsetz+j,1.0));
177     MOSEKCALL(res,MSK_putvarbound(task,offsetz+j,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY));
178     sprintf(buf,"z[%d]",1+j);
179     MOSEKCALL(res,MSK_putvarname(task,offsetz+j,buf));
180 }
181
182 /* f variables. */
183 for(j=0; j<n; ++j)
184 {
185     for(k=0; k<3; ++k)
186     {
187         MOSEKCALL(res,MSK_putaij(task,1+3*n+3*j+k,offsetf+3*j+k,-1.0));
188         MOSEKCALL(res,MSK_putvarbound(task,offsetf+3*j+k,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY));
189         sprintf(buf,"f[%d,%d]",1+j,1+k);
190         MOSEKCALL(res,MSK_putvarname(task,offsetf+3*j+k,buf));
191     }
192 }
193
194 /* g variables. */
195 for(j=0; j<n; ++j)
196 {
197     for(k=0; k<3; ++k)
198     {
199         MOSEKCALL(res,MSK_putaij(task,1+6*n+3*j+k,offsetg+3*j+k,-1.0));
200         MOSEKCALL(res,MSK_putvarbound(task,offsetg+3*j+k,MSK_BK_FR,-MSK_INFINITY,MSK_INFINITY));
201         sprintf(buf,"g[%d,%d]",1+j,1+k);
202         MOSEKCALL(res,MSK_putvarname(task,offsetg+3*j+k,buf));
203     }
204 }
205
206 sub[0] = offsets+0;
207 for(j=0; j<n; ++j)
208     sub[j+1] = offsett+j;
209
210 MOSEKCALL(res,MSK_appendcone(task,MSK_CT_QUAD,0.0,n+1,sub));
211 MOSEKCALL(res,MSK_putconename(task,0,"stddev"));
212
213 for(k=0; k<n; ++k)
214 {
215     MOSEKCALL(res,MSK_appendconeseq(task,MSK_CT_RQUAD,0.0,3,offsetf+k*3));
216     sprintf(buf,"f[%d]",1+k);
217     MOSEKCALL(res,MSK_putconename(task,1+k,buf));
218 }
219
220 for(k=0; k<n; ++k)
221 {
222     MOSEKCALL(res,MSK_appendconeseq(task,MSK_CT_RQUAD,0.0,3,offsetg+k*3));
223     sprintf(buf,"g[%d]",1+k);
224     MOSEKCALL(res,MSK_putconename(task,1+n+k,buf));
225 }
226
227 MOSEKCALL(res,MSK_putobjsense(task,MSK_OBJECTIVE_SENSE_MAXIMIZE));
228
229 #if 0

```

```

230  /* Turn all logout put off. */
231  MOSEKCALL(res,MSK_putintparam(task,MSK_IPAR_LOG,0));
232  #endif
233
234  #if 1
235  /* Dump the problem to a human readable OPF file. */
236  MOSEKCALL(res,MSK_writedata(task,"dump.opf"));
237  #endif
238
239  MOSEKCALL(res,MSK_optimize(task));
240
241  #if 1
242  /* Display the solution summary for quick inspection of results. */
243  MSK_solutionsummary(task,MSK_STREAM_MSG);
244  #endif
245
246  if ( res==MSK_RES_OK )
247  {
248      double expret=0.0,stddev=0.0,xj;
249
250      for(j=0; j<n; ++j)
251      {
252          MOSEKCALL(res,MSK_getxxslice(task,MSK_SOL_ITR,offsetx+j,offsetx+j+1,&xj));
253          expret += mu[j]*xj;
254      }
255
256      MOSEKCALL(res,MSK_getxxslice(task,MSK_SOL_ITR,offsets+0,offsets+1,&stddev));
257
258      printf("\nExpected return %e for gamma %e\n",expret,stddev);
259  }
260
261  free(sub);
262
263  return ( 0 );
264  }

```

The example code above produces the result

```

Interior-point solution summary
Problem status : PRIMAL_AND_DUAL_FEASIBLE
Solution status : OPTIMAL
Primal.  obj: 7.4390660228e-002   Viol.  con: 2e-007   var: 0e+000   cones: 1e-009
Dual.    obj: 7.4390669047e-002   Viol.  con: 1e-008   var: 1e-008   cones: 0e+000

```

Expected return 7.439066e-002 for gamma 5.000000e-002

If the problem is dumped to an OPF formatted file, then it has the following content.

```

[comment]
  Written by MOSEK version 7.0.0.86
  Date 01-10-13
  Time 08:59:30
[/comment]

[hints]
[hint NUMVAR] 34 [/hint]
[hint NUMCON] 28 [/hint]
[hint NUMANZ] 60 [/hint]

```

```

[ hint NUMQNZ] 0 [/ hint]
[ hint NUMCONE] 7 [/ hint]
[/ hints]

[ variables disallow_new_variables]
'x[1]' 'x[2]' 'x[3]' 's' 't[1]'
't[2]' 't[3]' 'c[1]' 'c[2]' 'c[3]'
'v[1]' 'v[2]' 'v[3]' 'z[1]' 'z[2]'
'z[3]' 'f[1,1]' 'f[1,2]' 'f[1,3]' 'f[2,1]'
'f[2,2]' 'f[2,3]' 'f[3,1]' 'f[3,2]' 'f[3,3]'
'g[1,1]' 'g[1,2]' 'g[1,3]' 'g[2,1]' 'g[2,2]'
'g[2,3]' 'g[3,1]' 'g[3,2]' 'g[3,3]'
[/ variables]

[ objective maximize]
1.073e-001 'x[1]' + 7.37e-002 'x[2]' + 6.2700000000000001e-002 'x[3]'
[/ objective]

[ constraints]
[ con 'budget' ] 'x[1]' + 'x[2]' + 'x[3]' + 1e-002 'c[1]' + 1e-002 'c[2]'
+ 1e-002 'c[3]' = 1e+000 [/ con]
[ con 'GT[1]' ] 1.667e-001 'x[1]' + 2.32e-002 'x[2]' + 1.3e-003 'x[3]' - 't[1]' = 0e+000 [/ con]
[ con 'GT[2]' ] 1.033e-001 'x[2]' - 2.2e-003 'x[3]' - 't[2]' = 0e+000 [/ con]
[ con 'GT[3]' ] 3.38e-002 'x[3]' - 't[3]' = 0e+000 [/ con]
[ con 'zabs1[1]' ] 0e+000 <= - 'x[1]' + 'z[1]' [/ con]
[ con 'zabs1[2]' ] 0e+000 <= - 'x[2]' + 'z[2]' [/ con]
[ con 'zabs1[3]' ] 0e+000 <= - 'x[3]' + 'z[3]' [/ con]
[ con 'zabs2[1]' ] 0e+000 <= 'x[1]' + 'z[1]' [/ con]
[ con 'zabs2[2]' ] 0e+000 <= 'x[2]' + 'z[2]' [/ con]
[ con 'zabs2[3]' ] 0e+000 <= 'x[3]' + 'z[3]' [/ con]
[ con 'f[1,1]' ] 'v[1]' - 'f[1,1]' = 0e+000 [/ con]
[ con 'f[1,2]' ] 'c[1]' - 'f[1,2]' = 0e+000 [/ con]
[ con 'f[1,3]' ] 'z[1]' - 'f[1,3]' = 0e+000 [/ con]
[ con 'f[2,1]' ] 'v[2]' - 'f[2,1]' = 0e+000 [/ con]
[ con 'f[2,2]' ] 'c[2]' - 'f[2,2]' = 0e+000 [/ con]
[ con 'f[2,3]' ] 'z[2]' - 'f[2,3]' = 0e+000 [/ con]
[ con 'f[3,1]' ] 'v[3]' - 'f[3,1]' = 0e+000 [/ con]
[ con 'f[3,2]' ] 'c[3]' - 'f[3,2]' = 0e+000 [/ con]
[ con 'f[3,3]' ] 'z[3]' - 'f[3,3]' = 0e+000 [/ con]
[ con 'g[1,1]' ] 'z[1]' - 'g[1,1]' = 0e+000 [/ con]
[ con 'g[1,2]' ] - 'g[1,2]' = -1.25e-001 [/ con]
[ con 'g[1,3]' ] 'v[1]' - 'g[1,3]' = 0e+000 [/ con]
[ con 'g[2,1]' ] 'z[2]' - 'g[2,1]' = 0e+000 [/ con]
[ con 'g[2,2]' ] - 'g[2,2]' = -1.25e-001 [/ con]
[ con 'g[2,3]' ] 'v[2]' - 'g[2,3]' = 0e+000 [/ con]
[ con 'g[3,1]' ] 'z[3]' - 'g[3,1]' = 0e+000 [/ con]
[ con 'g[3,2]' ] - 'g[3,2]' = -1.25e-001 [/ con]
[ con 'g[3,3]' ] 'v[3]' - 'g[3,3]' = 0e+000 [/ con]
[/ constraints]

[ bounds]
[b] 0 <= * [/ b]
[b] s = 5e-002 [/ b]
[b] 't[1]', 't[2]', 't[3]', 'c[1]', 'c[2]', 'c[3]' free [/ b]
[b] 'v[1]', 'v[2]', 'v[3]', 'z[1]', 'z[2]', 'z[3]' free [/ b]
[b] 'f[1,1]', 'f[1,2]', 'f[1,3]', 'f[2,1]', 'f[2,2]', 'f[2,3]' free [/ b]
[b] 'f[3,1]', 'f[3,2]', 'f[3,3]', 'g[1,1]', 'g[1,2]', 'g[1,3]' free [/ b]
[b] 'g[2,1]', 'g[2,2]', 'g[2,3]', 'g[3,1]', 'g[3,2]', 'g[3,3]' free [/ b]

```

```

[cone quad 'stddev' s, 't[1]', 't[2]', 't[3]' [/cone]
[cone rquad 'f[1]'] 'f[1,1]', 'f[1,2]', 'f[1,3]' [/cone]
[cone rquad 'f[2]'] 'f[2,1]', 'f[2,2]', 'f[2,3]' [/cone]
[cone rquad 'f[3]'] 'f[3,1]', 'f[3,2]', 'f[3,3]' [/cone]
[cone rquad 'g[1]'] 'g[1,1]', 'g[1,2]', 'g[1,3]' [/cone]
[cone rquad 'g[2]'] 'g[2,1]', 'g[2,2]', 'g[2,3]' [/cone]
[cone rquad 'g[3]'] 'g[3,1]', 'g[3,2]', 'g[3,3]' [/cone]
[/bounds]

```

The file verifies that the correct problem has been setup.

Chapter 9

Usage guidelines

The purpose of this chapter is to present some general guidelines to follow when using MOSEK.

9.1 Verifying the results

The main purpose of MOSEK is to solve optimization problems and therefore the most fundamental question to be asked is whether the solution reported by MOSEK is a solution to the desired optimization problem.

There can be several reasons why it might be not case. The most prominent reasons are:

- A wrong problem. The problem inputted to MOSEK is simply not the right problem, i.e. some of the data may have been corrupted or the model has been incorrectly built.
- Numerical issues. The problem is badly scaled or otherwise badly posed.
- Other reasons. E.g. not enough memory or an explicit user request to stop.

The first step in verifying that MOSEK reports the expected solution is to inspect the solution summary generated by MOSEK. The solution summary provides information about

- the problem and solution statuses,
- objective value and infeasibility measures for the primal solution, and
- objective value and infeasibility measures for the dual solution, where applicable.

By inspecting the solution summary it can be verified that MOSEK produces a feasible solution, and, in the continuous case, the optimality can be checked using the dual solution. Furthermore, the problem itself can be inspected using the problem analyzer discussed in section [13.1](#).

If the summary reports conflicting information (e.g. a solution status that does not match the actual solution), or the cause for terminating the solver before a solution was found cannot be traced back to

the reasons stated above, it may be caused by a bug in the solver; in this case, please contact MOSEK support.

9.1.1 Verifying primal feasibility

If it has been verified that MOSEK solves the problem correctly but the solution is still not as expected, next step is to verify that the primal solution satisfies all the constraints. Hence, using the original problem it must be determined whether the solution satisfies all the required constraints in the model. For instance assume that the problem has the constraints

$$\begin{aligned} x_1 + 2x_2 + x_3 &\leq 1, \\ x_1, x_2, x_3 &\geq 0 \end{aligned}$$

and MOSEK reports the optimal solution

$$x_1 = x_2 = x_3 = 1.$$

Then clearly the solution violates the constraints. The most likely explanation is that the model does not match the problem entered into MOSEK, for instance

$$x_1 - 2x_2 + x_3 \leq 1$$

may have been inputted instead of

$$x_1 + 2x_2 + x_3 \leq 1.$$

A good way to debug such an issue is to dump the problem to OPF file and check whether the violated constraint has been specified correctly.

9.1.2 Verifying optimality

Verifying that a feasible solution is optimal can be harder. However, for continuous problems optimality can be verified using a dual solution. Normally, MOSEK will report a dual solution; if that is feasible and has the same objective value as the primal solution, then the primal solution must be optimal.

An alternative method is to find another primal solution that has better objective value than the one reported to MOSEK. If that is possible then either the problem is badly posed or there is a bug in MOSEK.

9.2 Turn on logging

While developing a new application it is recommended to turn on logging, so that error and diagnostics messages are displayed.

Using the `MSK_linkfiletotaskstream` function a file can be linked to a task stream. This means that all messages sent to a task stream are also written to a file. As an example consider the code fragment


```
MSK_linkfiletotaskstream(task,MSK_STREAM_LOG,"moseklog.txt");
```

which shows how to link the file `moseklog.txt` to the log stream.

It is also possible to link a custom function to a stream using the `MSK_linkfunctotaskstream` function.

More log information can be obtained by modifying one or more of the parameters:

- `MSK_IPAR_LOG`,
- `MSK_IPAR_LOG_INTPNT`,
- `MSK_IPAR_LOG_MIO`,
- `MSK_IPAR_LOG_CUT_SECOND_OPT`,
- `MSK_IPAR_LOG_SIM`, and
- `MSK_IPAR_LOG_SIM_MINOR`.

By default MOSEK will reduce the amount of log information after the first optimization on a given task. To get full log output on subsequent optimizations set:

```
MSK_IPAR_LOG_CUT_SECOND_OPT 0
```

9.3 Writing task data to a file

If something is wrong with a problem or a solution, one option is to output the problem to an OPF file and inspect it by hand. Use the `MSK_writedata` function to write a task to a file immediately before optimizing, for example as follows:

```
task.writedata(task,"taskdump.opf");
task.optimize(task);
```

This will write the problem in `task` to the file `taskdump.opf`. Inspecting the text file `taskdump.opf` may reveal what is wrong in the problem setup.

9.4 Error handling

Most functions in the C API return a *response code* which indicates whether an error occurred. It is recommended to check to the response code and in case it is indicating an error then an appropriate action should be taken.

9.5 Fatal error handling

If MOSEK encounter a fatal error caused by either an internal bug or a user error, an *exit function* is called. It is possible to tell MOSEK to use a custom exit function using the `MSK_putexitfunc` function. The user-defined exit function will then be called if a fatal error is detected.

The purpose of an exit function is to print out a suitable message that can help diagnose the cause of the error.

9.6 Checking for memory leaks and overwrites

If you suspect that MOSEK or your own application incorrectly overwrites memory or leaks memory, we suggest you use external tools such as **Purify** or **valgrind** to pinpoint the cause of the problem.

Alternatively, MOSEK has a memory check feature which can be enabled by letting the argument **dbugfile** be the name of a writable file when calling **MSK.makeenv**. If **dgbfile** is valid file name, then MOSEK will write memory debug information to this file. Assuming memory debugging is turned on, MOSEK will warn about MOSEK specific memory leaks when a MOSEK environment or task is deleted.

Moreover, the functions **MSK.checkmemenv** and **MSK.checkmemtask** can be used to check the memory allocated by a MOSEK environment or task at any time. If one these functions finds that the memory has been corrupted a fatal error is generated.

9.7 Important API limitations

9.7.1 Thread safety

The MOSEK API is thread-safe provided that a task is accessed from one thread only at any time.

9.7.2 Uncoded strings

The C API supports the usage of uncoded strings. Indeed all (**char ***) arguments are allowed to be UTF8 encoded strings.

9.7.2.1 Limitations

Please note that the MPS and LP file formats are ASCII formats. Therefore, it might be advantageous to limit all names of constraints, variables etc. to ASCII strings.

Chapter 10

Problem formulation and solutions

In this chapter we will discuss the following issues:

- The formal definitions of the problem types that MOSEK can solve.
- The solution information produced by MOSEK.
- The information produced by MOSEK if the problem is infeasible.

10.1 Linear optimization

A linear optimization problem can be written as

$$\begin{array}{llllll} \text{minimize} & & c^T x + c^f & & & \\ \text{subject to} & l^c & \leq & Ax & \leq & u^c, \\ & l^x & \leq & x & \leq & u^x, \end{array} \quad (10.1)$$

where

- m is the number of constraints.
- n is the number of decision variables.
- $x \in \mathbb{R}^n$ is a vector of decision variables.
- $c \in \mathbb{R}^n$ is the linear part of the objective function.
- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.

- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.

A primal solution (x) is *(primal) feasible* if it satisfies all constraints in (10.1). If (10.1) has at least one primal feasible solution, then (10.1) is said to be (primal) feasible.

In case (10.1) does not have a feasible solution, the problem is said to be *(primal) infeasible*.

10.1.1 Duality for linear optimization

Corresponding to the primal problem (10.1), there is a dual problem

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ & \text{subject to} && A^T y + s_l^x - s_u^x = c, \\ & && -y + s_l^c - s_u^c = 0, \\ & && s_l^c, s_u^c, s_l^x, s_u^x \geq 0. \end{aligned} \tag{10.2}$$

If a bound in the primal problem is plus or minus infinity, the corresponding dual variable is fixed at 0, and we use the convention that the product of the bound value and the corresponding dual variable is 0. E.g.

$$l_j^x = -\infty \Rightarrow (s_l^x)_j = 0 \text{ and } l_j^x \cdot (s_l^x)_j = 0.$$

This is equivalent to removing variable $(s_l^x)_j$ from the dual problem.

A solution

$$(y, s_l^c, s_u^c, s_l^x, s_u^x)$$

to the dual problem is feasible if it satisfies all the constraints in (10.2). If (10.2) has at least one feasible solution, then (10.2) is *(dual) feasible*, otherwise the problem is *(dual) infeasible*.

10.1.1.1 A primal-dual feasible solution

A solution

$$(x, y, s_l^c, s_u^c, s_l^x, s_u^x)$$

is denoted a *primal-dual feasible solution*, if (x) is a solution to the primal problem (10.1) and $(y, s_l^c, s_u^c, s_l^x, s_u^x)$ is a solution to the corresponding dual problem (10.2).

10.1.1.2 The duality gap

Let

$$(x^*, y^*, (s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*)$$

be a primal-dual feasible solution, and let

$$(x^c)^* := Ax^*.$$

For a primal-dual feasible solution we define the *duality gap* as the difference between the primal and the dual objective value,

$$\begin{aligned} & c^T x^* + c^f - ((l^c)^T (s_l^c)^* - (u^c)^T (s_u^c)^* + (l^x)^T (s_l^x)^* - (u^x)^T (s_u^x)^* + c^f) \\ &= \sum_{i=0}^{m-1} [(s_l^c)^*_i ((x_i^c)^* - l_i^c) + (s_u^c)^*_i (u_i^c - (x_i^c)^*)] + \sum_{j=0}^{n-1} [(s_l^x)^*_j (x_j - l_j^x) + (s_u^x)^*_j (u_j^x - x_j^*)] \quad (10.3) \\ &\geq 0 \end{aligned}$$

where the first relation can be obtained by transposing and multiplying the dual constraints (10.2) by x^* and $(x^c)^*$ respectively, and the second relation comes from the fact that each term in each sum is nonnegative. It follows that the primal objective will always be greater than or equal to the dual objective.

10.1.1.3 When the objective is to be maximized

When the objective sense of problem (10.1) is maximization, i.e.

$$\begin{array}{llll} \text{maximize} & & c^T x + c^f & \\ \text{subject to} & l^c & \leq & Ax \leq u^c, \\ & l^x & \leq & x \leq u^x, \end{array}$$

the objective sense of the dual problem changes to minimization, and the domain of all dual variables changes sign in comparison to (10.2). The dual problem thus takes the form

$$\begin{array}{ll} \text{minimize} & (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ \text{subject to} & A^T y + s_l^x - s_u^x = c, \\ & -y + s_l^c - s_u^c = 0, \\ & s_l^c, s_u^c, s_l^x, s_u^x \leq 0. \end{array}$$

This means that the duality gap, defined in (10.3) as the primal minus the dual objective value, becomes nonpositive. It follows that the dual objective will always be greater than or equal to the primal objective.

10.1.1.4 An optimal solution

It is well-known that a linear optimization problem has an optimal solution if and only if there exist feasible primal and dual solutions so that the duality gap is zero, or, equivalently, that the *complementarity conditions*

$$\begin{aligned}
(s_l^c)_i^* ((x_i^c)^* - l_i^c) &= 0, \quad i = 0, \dots, m-1, \\
(s_u^c)_i^* (u_i^c - (x_i^c)^*) &= 0, \quad i = 0, \dots, m-1, \\
(s_l^x)_j^* (x_j^* - l_j^x) &= 0, \quad j = 0, \dots, n-1, \\
(s_u^x)_j^* (u_j^x - x_j^*) &= 0, \quad j = 0, \dots, n-1,
\end{aligned}$$

are satisfied.

If (10.1) has an optimal solution and MOSEK solves the problem successfully, both the primal and dual solution are reported, including a status indicating the exact state of the solution.

10.1.2 Infeasibility for linear optimization

10.1.2.1 Primal infeasible problems

If the problem (10.1) is infeasible (has no feasible solution), MOSEK will report a certificate of primal infeasibility: The dual solution reported is the certificate of infeasibility, and the primal solution is undefined.

A certificate of primal infeasibility is a feasible solution to the modified dual problem

$$\begin{aligned}
&\text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x \\
&\text{subject to} && A^T y + s_l^x - s_u^x = 0, \\
& && -y + s_l^c - s_u^c = 0, \\
& && s_l^c, s_u^c, s_l^x, s_u^x \geq 0,
\end{aligned} \tag{10.4}$$

such that the objective value is strictly positive, i.e. a solution

$$(y^*, (s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*)$$

to (10.4) so that

$$(l^c)^T (s_l^c)^* - (u^c)^T (s_u^c)^* + (l^x)^T (s_l^x)^* - (u^x)^T (s_u^x)^* > 0.$$

Such a solution implies that (10.4) is unbounded, and that its dual is infeasible. As the constraints to the dual of (10.4) is identical to the constraints of problem (10.1), we thus have that problem (10.1) is also infeasible.

10.1.2.2 Dual infeasible problems

If the problem (10.2) is infeasible (has no feasible solution), MOSEK will report a certificate of dual infeasibility: The primal solution reported is the certificate of infeasibility, and the dual solution is undefined.

A certificate of dual infeasibility is a feasible solution to the modified primal problem

$$\begin{aligned}
&\text{minimize} && c^T x \\
&\text{subject to} && \hat{l}^c \leq Ax \leq \hat{u}^c, \\
& && \hat{l}^x \leq x \leq \hat{u}^x,
\end{aligned} \tag{10.5}$$

where

$$\hat{l}_i^c = \begin{cases} 0 & \text{if } l_i^c > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and } \hat{u}_i^c := \begin{cases} 0 & \text{if } u_i^c < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

and

$$\hat{l}_j^x = \begin{cases} 0 & \text{if } l_j^x > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and } \hat{u}_j^x := \begin{cases} 0 & \text{if } u_j^x < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

such that the objective value $c^T x$ is strictly negative.

Such a solution implies that (10.5) is unbounded, and that its dual is infeasible. As the constraints to the dual of (10.5) is identical to the constraints of problem (10.2), we thus have that problem (10.2) is also infeasible.

10.1.2.3 Primal and dual infeasible case

In case that both the primal problem (10.1) and the dual problem (10.2) are infeasible, MOSEK will report only one of the two possible certificates — which one is not defined (MOSEK returns the first certificate found).

10.2 Conic quadratic optimization

Conic quadratic optimization is an extensions of linear optimization (see Section 10.1) allowing conic domains to be specified for subsets of the problem variables. A conic quadratic optimization problem can be written as

$$\begin{aligned} & \text{minimize} && c^T x + c^f \\ & \text{subject to} && \begin{array}{lll} l^c & \leq & Ax & \leq & u^c, \\ l^x & \leq & x & \leq & u^x, \end{array} \\ & && x \in \mathcal{C}, \end{aligned} \tag{10.6}$$

where set \mathcal{C} is a Cartesian product of convex cones, namely $\mathcal{C} = \mathcal{C}_1 \times \cdots \times \mathcal{C}_p$. Having the domain restriction, $x \in \mathcal{C}$, is thus equivalent to

$$x^t \in \mathcal{C}_t \subseteq \mathbb{R}^{n_t},$$

where $x = (x^1, \dots, x^p)$ is a partition of the problem variables. Please note that the n -dimensional Euclidean space \mathbb{R}^n is a cone itself, so simple linear variables are still allowed.

MOSEK supports only a limited number of cones, specifically:

- The \mathbb{R}^n set.

- The quadratic cone:

$$\mathcal{Q}_n = \left\{ x \in \mathbb{R}^n : x_1 \geq \sqrt{\sum_{j=2}^n x_j^2} \right\}.$$

- The rotated quadratic cone:

$$\mathcal{Q}_n^r = \left\{ x \in \mathbb{R}^n : 2x_1x_2 \geq \sum_{j=3}^n x_j^2, x_1 \geq 0, x_2 \geq 0 \right\}.$$

Although these cones may seem to provide only limited expressive power they can be used to model a wide range of problems as demonstrated in [7].

10.2.1 Duality for conic quadratic optimization

The dual problem corresponding to the conic quadratic optimization problem (10.6) is given by

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ & \text{subject to} && A^T y + s_l^x - s_u^x + s_n^x = c, \\ & && -y + s_l^c - s_u^c = 0, \\ & && s_l^c, s_u^c, s_l^x, s_u^x \geq 0, \\ & && s_n^x \in \mathcal{C}^*, \end{aligned} \tag{10.7}$$

where the dual cone \mathcal{C}^* is a Cartesian product of the cones

$$\mathcal{C}^* = \mathcal{C}_1^* \times \cdots \times \mathcal{C}_p^*,$$

where each \mathcal{C}_t^* is the dual cone of \mathcal{C}_t . For the cone types MOSEK can handle, the relation between the primal and dual cone is given as follows:

- The \mathbb{R}^n set:

$$\mathcal{C}_t = \mathbb{R}^{n_t} \Leftrightarrow \mathcal{C}_t^* = \{s \in \mathbb{R}^{n_t} : s = 0\}.$$

- The quadratic cone:

$$\mathcal{C}_t = \mathcal{Q}_{n_t} \Leftrightarrow \mathcal{C}_t^* = \mathcal{Q}_{n_t} = \left\{ s \in \mathbb{R}^{n_t} : s_1 \geq \sqrt{\sum_{j=2}^{n_t} s_j^2} \right\}.$$

- The rotated quadratic cone:

$$\mathcal{C}_t = \mathcal{Q}_{n_t}^r \Leftrightarrow \mathcal{C}_t^* = \mathcal{Q}_{n_t}^r = \left\{ s \in \mathbb{R}^{n_t} : 2s_1s_2 \geq \sum_{j=3}^{n_t} s_j^2, s_1 \geq 0, s_2 \geq 0 \right\}.$$

Please note that the dual problem of the dual problem is identical to the original primal problem.

10.2.2 Infeasibility for conic quadratic optimization

In case MOSEK finds a problem to be infeasible it reports a certificate of the infeasibility. This works exactly as for linear problems (see Section 10.1.2).

10.2.2.1 Primal infeasible problems

If the problem (10.6) is infeasible, MOSEK will report a certificate of primal infeasibility: The dual solution reported is the certificate of infeasibility, and the primal solution is undefined.

A certificate of primal infeasibility is a feasible solution to the problem

$$\begin{aligned}
 & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x \\
 & \text{subject to} && A^T y + s_l^x - s_u^x + s_n^x = 0, \\
 & && -y + s_l^c - s_u^c = 0, \\
 & && s_l^c, s_u^c, s_l^x, s_u^x \geq 0, \\
 & && s_n^x \in \mathcal{C}^*,
 \end{aligned} \tag{10.8}$$

such that the objective value is strictly positive.

10.2.2.2 Dual infeasible problems

If the problem (10.7) is infeasible, MOSEK will report a certificate of dual infeasibility: The primal solution reported is the certificate of infeasibility, and the dual solution is undefined.

A certificate of dual infeasibility is a feasible solution to the problem

$$\begin{aligned}
 & \text{minimize} && c^T x \\
 & \text{subject to} && \hat{l}^c \leq Ax \leq \hat{u}^c, \\
 & && \hat{l}^x \leq x \leq \hat{u}^x, \\
 & && x \in \mathcal{C},
 \end{aligned} \tag{10.9}$$

where

$$\hat{l}_i^c = \begin{cases} 0 & \text{if } l_i^c > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and } \hat{u}_i^c := \begin{cases} 0 & \text{if } u_i^c < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

and

$$\hat{l}_j^x = \begin{cases} 0 & \text{if } l_j^x > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and } \hat{u}_j^x := \begin{cases} 0 & \text{if } u_j^x < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

such that the objective value is strictly negative.

10.3 Semidefinite optimization

Semidefinite optimization is an extension of conic quadratic optimization (see Section 10.2) allowing positive semidefinite matrix variables to be used in addition to the usual scalar variables. A semidefinite optimization problem can be written as

$$\begin{aligned}
& \text{minimize} && \sum_{j=0}^{n-1} c_j x_j + \sum_{j=0}^{p-1} \langle \overline{C}_j, \overline{X}_j \rangle + c^f \\
& \text{subject to} && l_i^c \leq \sum_{j=0}^{n-1} a_{ij} x_j + \sum_{j=0}^{p-1} \langle \overline{A}_{ij}, \overline{X}_j \rangle \leq u_i^c, \quad i = 0, \dots, m-1 \\
& && l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1 \\
& && x \in \mathcal{C}, \overline{X}_j \in \mathcal{S}_{r_j}^+, \quad j = 0, \dots, p-1
\end{aligned} \tag{10.10}$$

where the problem has p symmetric positive semidefinite variables $\overline{X}_j \in \mathcal{S}_{r_j}^+$ of dimension r_j with symmetric coefficient matrices $\overline{C}_j \in \mathcal{S}_{r_j}$ and $\overline{A}_{i,j} \in \mathcal{S}_{r_j}$. We use standard notation for the matrix inner product, i.e., for $U, V \in \mathbb{R}^{m \times n}$ we have

$$\langle U, V \rangle := \sum_{i=0}^{m-1} \sum_{j=0}^{n-1} U_{ij} V_{ij}.$$

With semidefinite optimization we can model a wide range of problems as demonstrated in [7].

10.3.1 Duality for semidefinite optimization

The dual problem corresponding to the semidefinite optimization problem (10.10) is given by

$$\begin{aligned}
& \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\
& \text{subject to} && c - A^T y + s_u^x - s_l^x = s_n^x, \\
& && \overline{C}_j - \sum_{i=0}^m y_i \overline{A}_{ij} = \overline{S}_j, \quad j = 0, \dots, p-1 \\
& && s_l^c - s_u^c = y, \\
& && s_l^c, s_u^c, s_l^x, s_u^x \geq 0, \\
& && s_n^x \in \mathcal{C}^*, \overline{S}_j \in \mathcal{S}_{r_j}^+, \quad j = 0, \dots, p-1
\end{aligned} \tag{10.11}$$

where $A \in \mathbb{R}^{m \times n}$, $A_{ij} = a_{ij}$, which is similar to the dual problem for conic quadratic optimization (see Section 10.7), except for the addition of dual constraints

$$(\overline{C}_j - \sum_{i=0}^m y_i \overline{A}_{ij}) \in \mathcal{S}_{r_j}^+.$$

Note that the dual of the dual problem is identical to the original primal problem.

10.3.2 Infeasibility for semidefinite optimization

In case MOSEK finds a problem to be infeasible it reports a certificate of the infeasibility. This works exactly as for linear problems (see Section 10.1.2).

10.3.2.1 Primal infeasible problems

If the problem (10.10) is infeasible, MOSEK will report a certificate of primal infeasibility: The dual solution reported is a certificate of infeasibility, and the primal solution is undefined.

A certificate of primal infeasibility is a feasible solution to the problem

$$\begin{aligned}
 & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x \\
 & \text{subject to} && A^T y + s_l^x - s_u^x + s_n^x = 0, \\
 & && \sum_{i=0}^{m-1} y_i \bar{A}_{ij} + \bar{S}_j = 0, && j = 0, \dots, p-1 \\
 & && -y + s_l^c - s_u^c = 0, \\
 & && s_l^c, s_u^c, s_l^x, s_u^x \geq 0, \\
 & && s_n^x \in \mathcal{C}^*, \bar{S}_j \in \mathcal{S}_{r_j}^+, && j = 0, \dots, p-1
 \end{aligned} \tag{10.12}$$

such that the objective value is strictly positive.

10.3.2.2 Dual infeasible problems

If the problem (10.11) is infeasible, MOSEK will report a certificate of dual infeasibility: The primal solution reported is the certificate of infeasibility, and the dual solution is undefined.

A certificate of dual infeasibility is a feasible solution to the problem

$$\begin{aligned}
 & \text{minimize} && \sum_{j=0}^{n-1} c_j x_j + \sum_{j=0}^{p-1} \langle \bar{C}_j, \bar{X}_j \rangle \\
 & \text{subject to} && \hat{l}_i^c \leq \sum_{j=1}^m a_{ij} x_j + \sum_{j=0}^{p-1} \langle \bar{A}_{ij}, \bar{X}_j \rangle \leq \hat{u}_i^c, \quad i = 0, \dots, m-1 \\
 & && \hat{l}_j^x \leq \frac{x}{\bar{X}_j} \leq \hat{u}_j^x, \\
 & && x \in \mathcal{C}, \bar{X}_j \in \mathcal{S}_{r_j}^+, && j = 0, \dots, p-1
 \end{aligned} \tag{10.13}$$

where

$$\hat{l}_i^c = \begin{cases} 0 & \text{if } l_i^c > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and } \hat{u}_i^c := \begin{cases} 0 & \text{if } u_i^c < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

and

$$\hat{l}_j^x = \begin{cases} 0 & \text{if } l_j^x > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and } \hat{u}_j^x := \begin{cases} 0 & \text{if } u_j^x < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

such that the objective value is strictly negative.

10.4 Quadratic and quadratically constrained optimization

A convex quadratic and quadratically constrained optimization problem is an optimization problem of the form

$$\begin{aligned} & \text{minimize} && \frac{1}{2}x^T Q^o x + c^T x + c^f \\ & \text{subject to} && l_k^c \leq \frac{1}{2}x^T Q^k x + \sum_{j=0}^{n-1} a_{kj} x_j \leq u_k^c, \quad k = 0, \dots, m-1, \\ & && l_j^x \leq x_j \leq u_j^x, \quad j = 0, \dots, n-1, \end{aligned} \quad (10.14)$$

where Q^o and all Q^k are symmetric matrices. Moreover for convexity, Q^o must be a positive semidefinite matrix and Q^k must satisfy

$$\begin{aligned} -\infty < l_k^c &\Rightarrow Q^k \text{ is negative semidefinite,} \\ u_k^c < \infty &\Rightarrow Q^k \text{ is positive semidefinite,} \\ -\infty < l_k^c \leq u_k^c &\Rightarrow Q^k = 0. \end{aligned}$$

The convexity requirement is very important and it is strongly recommended that MOSEK is applied to convex problems only.

Note that any convex quadratic and quadratically constrained optimization problem can be reformulated as a conic optimization problem. It is our experience that for the majority of practical applications it is better to cast them as conic problems because

- the resulting problem is convex by construction, and
- the conic optimizer is more efficient than the optimizer for general quadratic problems.

See [7] for further details.

10.4.1 Duality for quadratic and quadratically constrained optimization

The dual problem corresponding to the quadratic and quadratically constrained optimization problem (10.14) is given by

$$\begin{aligned} & \text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + \frac{1}{2}x^T \left(\sum_{k=0}^{m-1} y_k Q^k - Q^o \right) x + c^f \\ & \text{subject to} && A^T y + s_l^x - s_u^x + \left(\sum_{k=0}^{m-1} y_k Q^k - Q^o \right) x = c, \\ & && -y + s_l^c - s_u^c = 0, \\ & && s_l^c, s_u^c, s_l^x, s_u^x \geq 0. \end{aligned} \quad (10.15)$$

The dual problem is related to the dual problem for linear optimization (see Section 10.2), but depend on variable x which in general can not be eliminated. In the solutions reported by MOSEK, the value of x is the same for the primal problem (10.14) and the dual problem (10.15).

10.4.2 Infeasibility for quadratic and quadratically constrained optimization

In case MOSEK finds a problem to be infeasible it reports a certificate of the infeasibility. This works exactly as for linear problems (see Section 10.1.2).

10.4.2.1 Primal infeasible problems

If the problem (10.14) with all $Q^k = 0$ is infeasible, MOSEK will report a certificate of primal infeasibility. As the constraints is the same as for a linear problem, the certificate of infeasibility is the same as for linear optimization (see Section 10.1.2.1).

10.4.2.2 Dual infeasible problems

If the problem (10.15) with all $Q^k = 0$ is infeasible, MOSEK will report a certificate of dual infeasibility: The primal solution reported is the certificate of infeasibility, and the dual solution is undefined.

A certificate of dual infeasibility is a feasible solution to the problem

$$\begin{aligned} & \text{minimize} && c^T x \\ & \text{subject to} && \hat{l}^c \leq Ax \leq \hat{u}^c, \\ & && 0 \leq Q^o x \leq 0, \\ & && \hat{l}^x \leq x \leq \hat{u}^x, \end{aligned} \tag{10.16}$$

where

$$\hat{l}_i^c = \begin{cases} 0 & \text{if } l_i^c > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and } \hat{u}_i^c := \begin{cases} 0 & \text{if } u_i^c < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

and

$$\hat{l}_j^x = \begin{cases} 0 & \text{if } l_j^x > -\infty, \\ -\infty & \text{otherwise,} \end{cases} \quad \text{and } \hat{u}_j^x := \begin{cases} 0 & \text{if } u_j^x < \infty, \\ \infty & \text{otherwise,} \end{cases}$$

such that the objective value is strictly negative.

10.5 General convex optimization

MOSEK is capable of solving smooth (twice differentiable) convex nonlinear optimization problems of the form

$$\begin{array}{ll}
\text{minimize} & f(x) + c^T x + c^f \\
\text{subject to} & \begin{array}{ll} l^c & \leq \\ l^x & \leq \end{array} \begin{array}{ll} g(x) + Ax & \leq \\ x & \leq \end{array} \begin{array}{l} u^c, \\ u^x, \end{array}
\end{array} \tag{10.17}$$

where

- m is the number of constraints.
- n is the number of decision variables.
- $x \in \mathbb{R}^n$ is a vector of decision variables.
- $c \in \mathbb{R}^n$ is the linear part objective function.
- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.
- $f : \mathbb{R}^n \rightarrow \mathbb{R}$ is a nonlinear function.
- $g : \mathbb{R}^n \rightarrow \mathbb{R}^m$ is a nonlinear vector function.

This means that the i th constraint has the form

$$l_i^c \leq g_i(x) + \sum_{j=1}^n a_{ij}x_j \leq u_i^c.$$

The linear term Ax is not included in $g(x)$ since it can be handled much more efficiently as a separate entity when optimizing.

The nonlinear functions f and g must be smooth in all $x \in [l^x; u^x]$. Moreover, $f(x)$ must be a convex function and $g_i(x)$ must satisfy

$$\begin{array}{ll}
-\infty < l_i^c & \Rightarrow g_i(x) \text{ is concave,} \\
u_i^c < \infty & \Rightarrow g_i(x) \text{ is convex,} \\
-\infty < l_i^c \leq u_i^c < \infty & \Rightarrow g_i(x) = 0.
\end{array}$$

10.5.1 Duality for general convex optimization

Similar to the linear case, MOSEK reports dual information in the general nonlinear case. Indeed in this case the Lagrange function is defined by

$$\begin{aligned}
L(x, s_l^c, s_u^c, s_l^x, s_u^x) &:= f(x) + c^T x + c^f \\
&\quad - (s_l^c)^T (g(x) + Ax - l^c) - (s_u^c)^T (u^c - g(x) - Ax) \\
&\quad - (s_l^x)^T (x - l^x) - (s_u^x)^T (u^x - x),
\end{aligned}$$

and the dual problem is given by

$$\begin{aligned}
&\text{maximize} && L(x, s_l^c, s_u^c, s_l^x, s_u^x) \\
&\text{subject to} && \nabla_x L(x, s_l^c, s_u^c, s_l^x, s_u^x)^T = 0, \\
&&& s_l^c, s_u^c, s_l^x, s_u^x \geq 0,
\end{aligned}$$

which is equivalent to

$$\begin{aligned}
&\text{maximize} && (l^c)^T s_l^c - (u^c)^T s_u^c + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\
&&& + f(x) - g(x)^T y - (\nabla f(x)^T - \nabla g(x)^T y)^T x \\
&\text{subject to} && A^T y + s_l^x - s_u^x - (\nabla f(x)^T - \nabla g(x)^T y) = c, \\
&&& -y + s_l^c - s_u^c = 0, \\
&&& s_l^c, s_u^c, s_l^x, s_u^x \geq 0.
\end{aligned} \tag{10.18}$$

In this context we use the following definition for scalar functions

$$\nabla f(x) = \left[\frac{\partial f(x)}{\partial x_1}, \dots, \frac{\partial f(x)}{\partial x_n} \right],$$

and accordingly for vector functions

$$\nabla g(x) = \begin{bmatrix} \nabla g_1(x) \\ \vdots \\ \nabla g_m(x) \end{bmatrix}.$$

Chapter 11

The optimizers for continuous problems

The most essential part of MOSEK is the optimizers. Each optimizer is designed to solve a particular class of problems i.e. linear, conic, or general nonlinear problems. The purpose of the present chapter is to discuss which optimizers are available for the continuous problem classes and how the performance of an optimizer can be tuned, if needed.

This chapter deals with the optimizers for *continuous problems* with no integer variables.

11.1 How an optimizer works

When the optimizer is called, it roughly performs the following steps:

Presolve:

Preprocessing to reduce the size of the problem.

Dualizer:

Choosing whether to solve the primal or the dual form of the problem.

Scaling:

Scaling the problem for better numerical stability.

Optimize:

Solve the problem using selected method.

The first three preprocessing steps are transparent to the user, but useful to know about for tuning purposes. In general, the purpose of the preprocessing steps is to make the actual optimization more efficient and robust.

11.1.1 Presolve

Before an optimizer actually performs the optimization the problem is preprocessed using the so-called presolve. The purpose of the presolve is to

- remove redundant constraints,
- eliminate fixed variables,
- remove linear dependencies,
- substitute out (implied) free variables, and
- reduce the size of the optimization problem in general.

After the presolved problem has been optimized the solution is automatically postsolved so that the returned solution is valid for the original problem. Hence, the presolve is completely transparent. For further details about the presolve phase, please see [8], [9].

It is possible to fine-tune the behavior of the presolve or to turn it off entirely. If presolve consumes too much time or memory compared to the reduction in problem size gained it may be disabled. This is done by setting the parameter `MSK_IPAR_PRESOLVE_USE` to `MSK_PRESOLVE_MODE_OFF`.

The two most time-consuming steps of the presolve are

- the eliminator, and
- the linear dependency check.

Therefore, in some cases it is worthwhile to disable one or both of these.

11.1.1.1 Numerical issues in the presolve

During the presolve the problem is reformulated so that it hopefully solves faster. However, in rare cases the presolved problem may be harder to solve than the original problem. The presolve may also be infeasible although the original problem is not.

If it is suspected that presolved problem is much harder to solve than the original then it is suggested to first turn the eliminator off by setting the parameter `MSK_IPAR_PRESOLVE_ELIMINATOR_USE`. If that does not help, then trying to turn presolve off may help.

Since all computations are done in finite precision then the presolve employs some tolerances when concluding a variable is fixed or constraint is redundant. If it happens that MOSEK incorrectly concludes a problem is primal or dual infeasible, then it is worthwhile to try to reduce the parameters `MSK_DPAR_PRESOLVE_TOL_X` and `MSK_DPAR_PRESOLVE_TOL_S`. However, if actually help reducing the parameters then this should be taken as an indication of the problem is badly formulated.

11.1.1.2 Eliminator

The purpose of the eliminator is to eliminate free and implied free variables from the problem using substitution. For instance, given the constraints

$$\begin{aligned} y &= \sum x_j, \\ y, x &\geq 0, \end{aligned}$$

y is an implied free variable that can be substituted out of the problem, if deemed worthwhile.

If the eliminator consumes too much time or memory compared to the reduction in problem size gained it may be disabled. This can be done with the parameter `MSK_IPAR_PRESOLVE_ELIMINATOR_USE` to `MSK_OFF`.

In rare cases the eliminator may cause that the problem becomes much hard to solve.

11.1.1.3 Linear dependency checker

The purpose of the linear dependency check is to remove linear dependencies among the linear equalities. For instance, the three linear equalities

$$\begin{aligned} x_1 + x_2 + x_3 &= 1, \\ x_1 + 0.5x_2 &= 0.5, \\ 0.5x_2 + x_3 &= 0.5 \end{aligned}$$

contain exactly one linear dependency. This implies that one of the constraints can be dropped without changing the set of feasible solutions. Removing linear dependencies is in general a good idea since it reduces the size of the problem. Moreover, the linear dependencies are likely to introduce numerical problems in the optimization phase.

It is best practise to build models without linear dependencies. If the linear dependencies are removed at the modeling stage, the linear dependency check can safely be disabled by setting the parameter `MSK_IPAR_PRESOLVE_LINDEP_USE` to `MSK_OFF`.

11.1.2 Dualizer

All linear, conic, and convex optimization problems have an equivalent dual problem associated with them. MOSEK has built-in heuristics to determine if it is most efficient to solve the primal or dual problem. The form (primal or dual) solved is displayed in the MOSEK log. Should the internal heuristics not choose the most efficient form of the problem it may be worthwhile to set the dualizer manually by setting the parameters:

- `MSK_IPAR_INTPNT_SOLVE_FORM`: In case of the interior-point optimizer.
- `MSK_IPAR_SIM_SOLVE_FORM`: In case of the simplex optimizer.

Note that currently only linear problems may be dualized.

11.1.3 Scaling

Problems containing data with large and/or small coefficients, say $1.0e + 9$ or $1.0e - 7$, are often hard to solve. Significant digits may be truncated in calculations with finite precision, which can result in the optimizer relying on inaccurate calculations. Since computers work in finite precision, extreme coefficients should be avoided. In general, data around the same "order of magnitude" is preferred, and we will refer to a problem, satisfying this loose property, as being *well-scaled*. If the problem is not well scaled, MOSEK will try to scale (multiply) constraints and variables by suitable constants. MOSEK solves the scaled problem to improve the numerical properties.

The scaling process is transparent, i.e. the solution to the original problem is reported. It is important to be aware that the optimizer terminates when the termination criterion is met on the scaled problem, therefore significant primal or dual infeasibilities may occur after unscaling for badly scaled problems. The best solution to this problem is to reformulate it, making it better scaled.

By default MOSEK heuristically chooses a suitable scaling. The scaling for interior-point and simplex optimizers can be controlled with the parameters `MSK_IPAR_INTPNT_SCALING` and `MSK_IPAR_SIM_SCALING` respectively.

11.1.4 Using multiple threads

The interior-point optimizers in MOSEK have been parallelized. This means that if you solve linear, quadratic, conic, or general convex optimization problem using the interior-point optimizer, you can take advantage of multiple CPU's.

By default MOSEK will automatically select the number of threads to be employed when solving the problem. However, the number of threads employed can be changed by setting the parameter `MSK_IPAR_NUM_THREADS`. This should never exceed the number of cores on the computer.

The speed-up obtained when using multiple threads is highly problem and hardware dependent, and consequently, it is advisable to compare single threaded and multi threaded performance for the given problem type to determine the optimal settings.

For small problems, using multiple threads is not be worthwhile and may even be counter productive.

11.2 Linear optimization

11.2.1 Optimizer selection

Two different types of optimizers are available for linear problems: The default is an interior-point method, and the alternatives are simplex methods. The optimizer can be selected using the parameter `MSK_IPAR_OPTIMIZER`.

11.2.2 The interior-point optimizer

The purpose of this section is to provide information about the algorithm employed in MOSEK interior-point optimizer.

In order to keep the discussion simple it is assumed that MOSEK solves linear optimization problems on standard form

$$\begin{aligned} & \text{minimize} && c^T x \\ & \text{subject to} && Ax = b, \\ & && x \geq 0. \end{aligned} \tag{11.1}$$

This is in fact what happens inside MOSEK; for efficiency reasons MOSEK converts the problem to standard form before solving, then convert it back to the input form when reporting the solution.

Since it is not known beforehand whether problem (11.1) has an optimal solution, is primal infeasible or is dual infeasible, the optimization algorithm must deal with all three situations. This is the reason that MOSEK solves the so-called homogeneous model

$$\begin{aligned} Ax - b\tau &= 0, \\ A^T y + s - c\tau &= 0, \\ -c^T x + b^T y - \kappa &= 0, \\ x, s, \tau, \kappa &\geq 0, \end{aligned} \tag{11.2}$$

where y and s correspond to the dual variables in (11.1), and τ and κ are two additional scalar variables. Note that the homogeneous model (11.2) always has solution since

$$(x, y, s, \tau, \kappa) = (0, 0, 0, 0, 0)$$

is a solution, although not a very interesting one.

Any solution

$$(x^*, y^*, s^*, \tau^*, \kappa^*)$$

to the homogeneous model (11.2) satisfies

$$x_j^* s_j^* = 0 \text{ and } \tau^* \kappa^* = 0.$$

Moreover, there is always a solution that has the property

$$\tau^* + \kappa^* > 0.$$

First, assume that $\tau^* > 0$. It follows that

$$\begin{aligned}
A \frac{x^*}{\tau^*} &= b, \\
A^T \frac{y^*}{\tau^*} + \frac{s^*}{\tau^*} &= c, \\
-c^T \frac{x^*}{\tau^*} + b^T \frac{y^*}{\tau^*} &= 0, \\
x^*, s^*, \tau^*, \kappa^* &\geq 0.
\end{aligned}$$

This shows that $\frac{x^*}{\tau^*}$ is a primal optimal solution and $(\frac{y^*}{\tau^*}, \frac{s^*}{\tau^*})$ is a dual optimal solution; this is reported as the optimal interior-point solution since

$$(x, y, s) = \left(\frac{x^*}{\tau^*}, \frac{y^*}{\tau^*}, \frac{s^*}{\tau^*} \right)$$

is a primal-dual optimal solution.

On other hand, if $\kappa^* > 0$ then

$$\begin{aligned}
Ax^* &= 0, \\
A^T y^* + s^* &= 0, \\
-c^T x^* + b^T y^* &= \kappa^*, \\
x^*, s^*, \tau^*, \kappa^* &\geq 0.
\end{aligned}$$

This implies that at least one of

$$-c^T x^* > 0 \tag{11.3}$$

or

$$b^T y^* > 0 \tag{11.4}$$

is satisfied. If (11.3) is satisfied then x^* is a certificate of dual infeasibility, whereas if (11.4) is satisfied then y^* is a certificate of dual infeasibility.

In summary, by computing an appropriate solution to the homogeneous model, all information required for a solution to the original problem is obtained. A solution to the homogeneous model can be computed using a primal-dual interior-point algorithm [10].

11.2.2.1 Interior-point termination criterion

For efficiency reasons it is not practical to solve the homogeneous model exactly. Hence, an exact optimal solution or an exact infeasibility certificate cannot be computed and a reasonable termination criterion has to be employed.

In every iteration, k , of the interior-point algorithm a trial solution

$$(x^k, y^k, s^k, \tau^k, \kappa^k)$$

to homogeneous model is generated where

$$x^k, s^k, \tau^k, \kappa^k > 0.$$

Whenever the trial solution satisfies the criterion

$$\begin{aligned} \left\| A \frac{x^k}{\tau^k} - b \right\|_{\infty} &\leq \epsilon_p (1 + \|b\|_{\infty}), \\ \left\| A^T \frac{y^k}{\tau^k} + \frac{s^k}{\tau^k} - c \right\|_{\infty} &\leq \epsilon_d (1 + \|c\|_{\infty}), \text{ and} \\ \min \left(\frac{(x^k)^T s^k}{(\tau^k)^2}, \left| \frac{c^T x^k}{\tau^k} - \frac{b^T y^k}{\tau^k} \right| \right) &\leq \epsilon_g \max \left(1, \frac{\min(|c^T x^k|, |b^T y^k|)}{\tau^k} \right), \end{aligned} \quad (11.5)$$

the interior-point optimizer is terminated and

$$\frac{(x^k, y^k, s^k)}{\tau^k}$$

is reported as the primal-dual optimal solution. The interpretation of (11.5) is that the optimizer is terminated if

- $\frac{x^k}{\tau^k}$ is approximately primal feasible,
- $\left(\frac{y^k}{\tau^k}, \frac{s^k}{\tau^k} \right)$ is approximately dual feasible, and
- the duality gap is almost zero.

On the other hand, if the trial solution satisfies

$$-\epsilon_i c^T x^k > \frac{\|c\|_{\infty}}{\max(1, \|b\|_{\infty})} \|Ax^k\|_{\infty}$$

then the problem is declared dual infeasible and x^k is reported as a certificate of dual infeasibility. The motivation for this stopping criterion is as follows: First assume that $\|Ax^k\|_{\infty} = 0$; then x^k is an exact certificate of dual infeasibility. Next assume that this is not the case, i.e.

$$\|Ax^k\|_{\infty} > 0,$$

and define

$$\bar{x} := \epsilon_i \frac{\max(1, \|b\|_{\infty})}{\|Ax^k\|_{\infty} \|c\|_{\infty}} x^k.$$

It is easy to verify that

$$\|A\bar{x}\|_{\infty} = \epsilon_i \frac{\max(1, \|b\|_{\infty})}{\|c\|_{\infty}} \text{ and } -c^T \bar{x} > 1,$$

which shows \bar{x} is an approximate certificate of dual infeasibility where ϵ_i controls the quality of the approximation. A smaller value means a better approximation.

Tolerance	Parameter name
ϵ_p	<code>MSK_DPAR_INTPNT_TOL_PFEAS</code>
ϵ_d	<code>MSK_DPAR_INTPNT_TOL_DFEAS</code>
ϵ_g	<code>MSK_DPAR_INTPNT_TOL_REL_GAP</code>
ϵ_i	<code>MSK_DPAR_INTPNT_TOL_INFEAS</code>

Table 11.1: Parameters employed in termination criterion.

Finally, if

$$\epsilon_i b^T y^k > \frac{\|b\|_\infty}{\max(1, \|c\|_\infty)} \|A^T y^k + s^k\|_\infty$$

then y^k is reported as a certificate of primal infeasibility.

It is possible to adjust the tolerances ϵ_p , ϵ_d , ϵ_g and ϵ_i using parameters; see table 11.1 for details. The default values of the termination tolerances are chosen such that for a majority of problems appearing in practice it is not possible to achieve much better accuracy. Therefore, tightening the tolerances usually is not worthwhile. However, an inspection of (11.5) reveals that quality of the solution is dependent on $\|b\|_\infty$ and $\|c\|_\infty$; the smaller the norms are, the better the solution accuracy.

The interior-point method as implemented by MOSEK will converge toward optimality and primal and dual feasibility at the same rate [10]. This means that if the optimizer is stopped prematurely then it is very unlikely that either the primal or dual solution is feasible. Another consequence is that in most cases all the tolerances, ϵ_p , ϵ_d and ϵ_g , has to be relaxed together to achieve an effect.

The basis identification discussed in section 11.2.2.2 requires an optimal solution to work well; hence basis identification should be turned off if the termination criterion is relaxed.

To conclude the discussion in this section, relaxing the termination criterion is usually not worthwhile.

11.2.2.2 Basis identification

An interior-point optimizer does not return an optimal basic solution unless the problem has a unique primal and dual optimal solution. Therefore, the interior-point optimizer has an optional post-processing step that computes an optimal basic solution starting from the optimal interior-point solution. More information about the basis identification procedure may be found in [11].

Please note that a basic solution is often more accurate than an interior-point solution.

By default MOSEK performs a basis identification. However, if a basic solution is not needed, the basis identification procedure can be turned off. The parameters

- `MSK_IPAR_INTPNT_BASIS`,
- `MSK_IPAR_BI_IGNORE_MAX_ITER`, and
- `MSK_IPAR_BI_IGNORE_NUM_ERROR`

controls when basis identification is performed.

11.2.2.3 The interior-point log

Below is a typical log output from the interior-point optimizer presented:

```

Optimizer - threads          : 1
Optimizer - solved problem   : the dual
Optimizer - Constraints       : 2
Optimizer - Cones            : 0
Optimizer - Scalar variables : 6          conic          : 0
Optimizer - Semi-definite variables: 0      scalarized       : 0
Factor    - setup time       : 0.00        dense det. time  : 0.00
Factor    - ML order time    : 0.00        GP order time   : 0.00
Factor    - nonzeros before factor : 3      after factor     : 3
Factor    - dense dim.       : 0          flops           : 7.00e+001
ITE PFEAS   DFEAS   GFEAS   PRSTATUS   POBJ      DOBJ      MU      TIME
0  1.0e+000  8.6e+000  6.1e+000  1.00e+000  0.000000000e+000 -2.208000000e+003 1.0e+000 0.00
1  1.1e+000  2.5e+000  1.6e-001  0.00e+000 -7.901380925e+003 -7.394611417e+003 2.5e+000 0.00
2  1.4e-001  3.4e-001  2.1e-002  8.36e-001 -8.113031650e+003 -8.055866001e+003 3.3e-001 0.00
3  2.4e-002  5.8e-002  3.6e-003  1.27e+000 -7.777530698e+003 -7.766471080e+003 5.7e-002 0.01
4  1.3e-004  3.2e-004  2.0e-005  1.08e+000 -7.668323435e+003 -7.668207177e+003 3.2e-004 0.01
5  1.3e-008  3.2e-008  2.0e-009  1.00e+000 -7.668000027e+003 -7.668000015e+003 3.2e-008 0.01
6  1.3e-012  3.2e-012  2.0e-013  1.00e+000 -7.667999994e+003 -7.667999994e+003 3.2e-012 0.01

```

The first line displays the number of threads used by the optimizer and second line tells that the optimizer choose to solve the dual problem rather than the primal problem. The next line displays the problem dimensions as seen by the optimizer, and the "Factor..." lines show various statistics. This is followed by the iteration log.

Using the same notation as in section 11.2.2 the columns of the iteration log has the following meaning:

- ITE: Iteration index.
- PFEAS: $\|Ax^k - b\tau^k\|_\infty$. The numbers in this column should converge monotonically towards to zero but may stall at low level due to rounding errors.
- DFEAS: $\|A^T y^k + s^k - c\tau^k\|_\infty$. The numbers in this column should converge monotonically toward to zero but may stall at low level due to rounding errors.
- GFEAS: $\| -cx^k + b^T y^k - \kappa^k \|_\infty$. The numbers in this column should converge monotonically toward to zero but may stall at low level due to rounding errors.
- PRSTATUS: This number converge to 1 if the problem has an optimal solution whereas it converge to -1 if that is not the case.
- POBJ: $c^T x^k / \tau^k$. An estimate for the primal objective value.
- DOBJ: $b^T y^k / \tau^k$. An estimate for the dual objective value.
- MU: $\frac{(x^k)^T s^k + \tau^k \kappa^k}{n+1}$. The numbers in this column should always converge monotonically to zero.
- TIME: Time spend since the optimization started.

11.2.3 The simplex based optimizer

An alternative to the interior-point optimizer is the simplex optimizer.

The simplex optimizer uses a different method that allows exploiting an initial guess for the optimal solution to reduce the solution time. Depending on the problem it may be faster or slower to use an initial guess; see section 11.2.4 for a discussion.

MOSEK provides both a primal and a dual variant of the simplex optimizer — we will return to this later.

11.2.3.1 Simplex termination criterion

The simplex optimizer terminates when it finds an optimal basic solution or an infeasibility certificate. A basic solution is optimal when it is primal and dual feasible; see (10.1) and (10.2) for a definition of the primal and dual problem. Due the fact that to computations are performed in finite precision MOSEK allows violation of primal and dual feasibility within certain tolerances. The user can control the allowed primal and dual infeasibility with the parameters `MSK_DPAR_BASIS_TOL_X` and `MSK_DPAR_BASIS_TOL_S`.

11.2.3.2 Starting from an existing solution

When using the simplex optimizer it may be possible to reuse an existing solution and thereby reduce the solution time significantly. When a simplex optimizer starts from an existing solution it is said to perform a *hot-start*. If the user is solving a sequence of optimization problems by solving the problem, making modifications, and solving again, MOSEK will hot-start automatically.

Setting the parameter `MSK_IPAR_OPTIMIZER` to `MSK_OPTIMIZER_FREE_SIMPLEX` instructs MOSEK to select automatically between the primal and the dual simplex optimizers. Hence, MOSEK tries to choose the best optimizer for the given problem and the available solution.

By default MOSEK uses presolve when performing a hot-start. If the optimizer only needs very few iterations to find the optimal solution it may be better to turn off the presolve.

11.2.3.3 Numerical difficulties in the simplex optimizers

Though MOSEK is designed to minimize numerical instability, completely avoiding it is impossible when working in finite precision. MOSEK counts a "numerical unexpected behavior" event inside the optimizer as a *set-back*. The user can define how many set-backs the optimizer accepts; if that number is exceeded, the optimization will be aborted. Set-backs are implemented to avoid long sequences where the optimizer tries to recover from an unstable situation.

Set-backs are, for example, repeated singularities when factorizing the basis matrix, repeated loss of feasibility, degeneracy problems (no progress in objective) and other events indicating numerical difficulties. If the simplex optimizer encounters a lot of set-backs the problem is usually badly scaled; in such a situation try to reformulate into a better scaled problem. Then, if a lot of set-backs still occur, trying one or more of the following suggestions may be worthwhile:

- Raise tolerances for allowed primal or dual feasibility: Hence, increase the value of
 - `MSK_DPAR.BASIS.TOL.X`, and
 - `MSK_DPAR.BASIS.TOL.S`.
- Raise or lower pivot tolerance: Change the `MSK_DPAR.SIMPLEX.ABS.TOL.PIV` parameter.
- Switch optimizer: Try another optimizer.
- Switch off crash: Set both `MSK_IPAR.SIM.PRIMAL.CRASH` and `MSK_IPAR.SIM.DUAL.CRASH` to 0.
- Experiment with other pricing strategies: Try different values for the parameters
 - `MSK_IPAR.SIM.PRIMAL.SELECTION` and
 - `MSK_IPAR.SIM.DUAL.SELECTION`.
- If you are using hot-starts, in rare cases switching off this feature may improve stability. This is controlled by the `MSK_IPAR.SIM.HOTSTART` parameter.
- Increase maximum set-backs allowed controlled by `MSK_IPAR.SIM.MAX.NUM.SETBACKS`.
- If the problem repeatedly becomes infeasible try switching off the special degeneracy handling. See the parameter `MSK_IPAR.SIM.DEGEN` for details.

11.2.4 The interior-point or the simplex optimizer?

Given a linear optimization problem, which optimizer is the best: The primal simplex, the dual simplex or the interior-point optimizer?

It is impossible to provide a general answer to this question, however, the interior-point optimizer behaves more predictably — it tends to use between 20 and 100 iterations, almost independently of problem size — but cannot perform hot-start, while simplex can take advantage of an initial solution, but is less predictable for cold-start. The interior-point optimizer is used by default.

11.2.5 The primal or the dual simplex variant?

MOSEK provides both a primal and a dual simplex optimizer. Predicting which simplex optimizer is faster is impossible, however, in recent years the dual optimizer has seen several algorithmic and computational improvements, which, in our experience, makes it faster on average than the primal simplex optimizer. Still, it depends much on the problem structure and size.

Setting the `MSK_IPAR.OPTIMIZER` parameter to `MSK_OPTIMIZER.FREE.SIMPLEX` instructs MOSEK to choose which simplex optimizer to use automatically.

To summarize, if you want to know which optimizer is faster for a given problem type, you should try all the optimizers.

Alternatively, use the concurrent optimizer presented in Section 11.6.3.

Parameter name	Purpose
<code>MSK_DPAR_INTPNT_CO_TOL_PFEAS</code>	Controls primal feasibility
<code>MSK_DPAR_INTPNT_CO_TOL_DFEAS</code>	Controls dual feasibility
<code>MSK_DPAR_INTPNT_CO_TOL_REL_GAP</code>	Controls relative gap
<code>MSK_DPAR_INTPNT_TOL_INFEAS</code>	Controls when the problem is declared infeasible
<code>MSK_DPAR_INTPNT_CO_TOL_MU_RED</code>	Controls when the complementarity is reduced enough

Table 11.2: Parameters employed in termination criterion.

11.3 Linear network optimization

11.3.1 Network flow problems

Linear optimization problems with network flow structure can often be solved significantly faster with a specialized version of the simplex method [12] than with the general solvers.

MOSEK includes a network simplex solver which frequently solves network problems significantly faster than the standard simplex optimizers.

To use the network simplex optimizer, do the following:

- Input the network flow problem as an ordinary linear optimization problem.
- Set the parameters
 - `MSK_IPAR_OPTIMIZER` to `MSK_OPTIMIZER_NETWORK_PRIMAL_SIMPLEX`.
- Optimize the problem using `MSK.optimize`.

MOSEK will automatically detect the network structure and apply the specialized simplex optimizer.

11.4 Conic optimization

11.4.1 The interior-point optimizer

For conic optimization problems only an interior-point type optimizer is available. The interior-point optimizer is an implementation of the so-called homogeneous and self-dual algorithm. For a detailed description of the algorithm, please see [13].

11.4.1.1 Interior-point termination criteria

The parameters controlling when the conic interior-point optimizer terminates are shown in Table 11.2.

11.5 Nonlinear convex optimization

11.5.1 The interior-point optimizer

For quadratic, quadratically constrained, and general convex optimization problems an interior-point type optimizer is available. The interior-point optimizer is an implementation of the homogeneous and self-dual algorithm. For a detailed description of the algorithm, please see [14], [15].

11.5.1.1 The convexity requirement

Continuous nonlinear problems are required to be convex. For quadratic problems MOSEK test this requirement before optimizing. Specifying a non-convex problem results in an error message.

The following parameters are available to control the convexity check:

- **MSK_IPAR_CHECK_CONVEXITY**: Turn convexity check on/off.
- **MSK_DPAR_CHECK_CONVEXITY_REL_TOL**: Tolerance for convexity check.
- **MSK_IPAR_LOG_CHECK_CONVEXITY**: Turn on more log information for debugging.

11.5.1.2 The differentiability requirement

The nonlinear optimizer in MOSEK requires both first order and second order derivatives. This of course implies care should be taken when solving problems involving non-differentiable functions.

For instance, the function

$$f(x) = x^2$$

is differentiable everywhere whereas the function

$$f(x) = \sqrt{x}$$

is only differentiable for $x > 0$. In order to make sure that MOSEK evaluates the functions at points where they are differentiable, the function domains must be defined by setting appropriate variable bounds.

In general, if a variable is not ranged MOSEK will only evaluate that variable at points strictly within the bounds. Hence, imposing the bound

$$x \geq 0$$

in the case of \sqrt{x} is sufficient to guarantee that the function will only be evaluated in points where it is differentiable.

However, if a function is differentiable on closed a range, specifying the variable bounds is not sufficient. Consider the function

Parameter name	Purpose
<code>MSK_DPAR_INTPNT_NL_TOL_PFEAS</code>	Controls primal feasibility
<code>MSK_DPAR_INTPNT_NL_TOL_DFEAS</code>	Controls dual feasibility
<code>MSK_DPAR_INTPNT_NL_TOL_REL_GAP</code>	Controls relative gap
<code>MSK_DPAR_INTPNT_TOL_INFEAS</code>	Controls when the problem is declared infeasible
<code>MSK_DPAR_INTPNT_NL_TOL_MU_RED</code>	Controls when the complementarity is reduced enough

Table 11.3: Parameters employed in termination criteria.

$$f(x) = \frac{1}{x} + \frac{1}{1-x}. \quad (11.6)$$

In this case the bounds

$$0 \leq x \leq 1$$

will not guarantee that MOSEK only evaluates the function for x between 0 and 1. To force MOSEK to strictly satisfy both bounds on ranged variables set the parameter `MSK_IPAR_INTPNT_STARTING_POINT` to `MSK_STARTING_POINT_SATISFY_BOUNDS`.

For efficiency reasons it may be better to reformulate the problem than to force MOSEK to observe ranged bounds strictly. For instance, (11.6) can be reformulated as follows

$$\begin{aligned} f(x) &= \frac{1}{x} + \frac{1}{y} \\ 0 &= 1 - x - y \\ 0 &\leq x \\ 0 &\leq y. \end{aligned}$$

11.5.1.3 Interior-point termination criteria

The parameters controlling when the general convex interior-point optimizer terminates are shown in Table 11.3.

11.6 Solving problems in parallel

If a computer has multiple CPUs, or has a CPU with multiple cores, it is possible for MOSEK to take advantage of this to speed up solution times.

11.6.1 Thread safety

The MOSEK API is thread-safe provided that a task is only modified or accessed from one thread at any given time — accessing two separate tasks from two separate threads at the same time is safe. Sharing an environment between threads is safe.

11.6.2 The parallelized interior-point optimizer

The interior-point optimizer is capable of using multiple CPUs or cores. This implies that whenever the MOSEK interior-point optimizer solves an optimization problem, it will try to divide the work so that each core gets a share of the work. The user decides how many cores MOSEK should exploit.

It is not always possible to divide the work equally, and often parts of the computations and the coordination of the work is processed sequentially, even if several cores are present. Therefore, the speed-up obtained when using multiple cores is highly problem dependent. However, as a rule of thumb, if the problem solves very quickly, i.e. in less than 60 seconds, it is not advantageous to use the parallel option.

The `MSK_IPAR_NUM_THREADS` parameter sets the number of threads (and therefore the number of cores) that the interior point optimizer will use.

11.6.3 The concurrent optimizer

An alternative to the parallel interior-point optimizer is the *concurrent optimizer*. The idea of the concurrent optimizer is to run multiple optimizers on the same problem concurrently, for instance, it allows you to apply the interior-point and the dual simplex optimizers to a linear optimization problem concurrently. The concurrent optimizer terminates when the first of the applied optimizers has terminated successfully, and it reports the solution of the fastest optimizer. In that way a new optimizer has been created which essentially performs as the fastest of the interior-point and the dual simplex optimizers. Hence, the concurrent optimizer is the best one to use if there are multiple optimizers available in MOSEK for the problem and you cannot say beforehand which one will be faster.

Note in particular that any solution present in the task will also be used for hot-starting the simplex algorithms. One possible scenario would therefore be running a hot-start dual simplex in parallel with interior point, taking advantage of both the stability of the interior-point method and the ability of the simplex method to use an initial solution.

By setting the

`MSK_IPAR_OPTIMIZER`

parameter to

`MSK_OPTIMIZER_CONCURRENT`

the concurrent optimizer chosen.

The number of optimizers used in parallel is determined by the

`MSK_IPAR_CONCURRENT_NUM_OPTIMIZERS`.

parameter. Moreover, the optimizers are selected according to a preassigned priority with optimizers having the highest priority being selected first. The default priority for each optimizer is shown in Table 11.6.3. For example, setting the `MSK_IPAR_CONCURRENT_NUM_OPTIMIZERS` parameter to 2 tells the concurrent optimizer to apply the two optimizers with highest priorities: In the default case that means the interior-point optimizer and one of the simplex optimizers.

Optimizer	Associated parameter	Default priority
MSK_OPTIMIZER_INTPNT	MSK_IPAR_CONCURRENT_PRIORITY_INTPNT	4
MSK_OPTIMIZER_FREE_SIMPLEX	MSK_IPAR_CONCURRENT_PRIORITY_FREE_SIMPLEX	3
MSK_OPTIMIZER_PRIMAL_SIMPLEX	MSK_IPAR_CONCURRENT_PRIORITY_PRIMAL_SIMPLEX	2
MSK_OPTIMIZER_DUAL_SIMPLEX	MSK_IPAR_CONCURRENT_PRIORITY_DUAL_SIMPLEX	1

Table 11.4: Default priorities for optimizer selection in concurrent optimization.

11.6.3.1 Concurrent optimization through the API

The following example shows how to call the concurrent optimizer through the API.

```

/*
  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.

  File:      concurrent1.c

  Purpose:   To demonstrate how to solve a problem
             with the concurrent optimizer.
*/

#include <stdio.h>

#include "mosek.h"

static void MSKAPI printstr(void *handle,
                           MSKCONST char str[])
{
  printf("%s",str);
} /* printstr */

int main(int argc,char *argv[])
{
  MSKenv_t env = NULL;
  MSKtask_t task = NULL;
  MSKintt r = MSK_RES_OK;

  /* Create mosek environment. */
  r = MSK_makeenv(&env,NULL);

  if ( r==MSK_RES_OK )
    r = MSK_maketask(env,0,0,&task);

  if ( r==MSK_RES_OK )
    MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);

  if (r == MSK_RES_OK)
    r = MSK_readdata(task,argv[1]);

  MSK_putintparam(task,MSK_IPAR_OPTIMIZER,MSK_OPTIMIZER_CONCURRENT);
  MSK_putintparam(task,MSK_IPAR_CONCURRENT_NUM_OPTIMIZERS,2);

  if (r == MSK_RES_OK)

```



```

    r = MSK_optimize(task);

    MSK_solutionsummary(task,MSK_STREAM_LOG);

    MSK_deletetask(&task);
    MSK_deleteenv(&env);

    printf("Return code: %d (0 means no error occurred.)\n",r);

    return ( r );
} /* main */

```

11.6.4 A more flexible concurrent optimizer

MOSEK also provides a more flexible method of concurrent optimization by using the function `MSK_optimizeconcurrent`. The main advantages of this function are that it allows the calling application to assign arbitrary values to the parameters of each task, and that call-back functions can be attached to each task. This may be useful in the following situation: Assume that you know the primal simplex optimizer to be the best optimizer for your problem, but that you do not know which of the available selection strategies (as defined by the `MSK_IPAR_SIM_PRIMAL_SELECTION` parameter) is the best. In this case you can solve the problem with the primal simplex optimizer using several different selection strategies concurrently.

An example demonstrating the usage of the `MSK_optimizeconcurrent` function is included below. The example solves a single problem using the interior-point and primal simplex optimizers in parallel.

```

/*
   Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.

   File:      concurrent2.c

   Purpose:   To demonstrate a more flexible interface for concurrent optimization.
*/

#include "mosek.h"

static void MSKAPI printstr(void *handle,
                           MSKCONST char str[])
{
    printf("env: %s",str);
} /* printstr */

static void MSKAPI printstr1(void *handle,
                             MSKCONST char str[])
{
    printf("simplex: %s",str);
} /* printstr */

static void MSKAPI printstr2(void *handle,
                             MSKCONST char str[])
{
    printf("intpnt: %s",str);
} /* printstr */

```

```

#define NUMTASKS 1

int main(int argc, char **argv)
{
    MSKintt   r=MSK_RES_OK,i;
    MSKenv_t  env = NULL;
    MSKtask_t task = NULL;
    MSKtask_t task_list[NUMTASKS];

    /* Ensure that we can delete tasks even if they are not allocated */
    task_list[0] = NULL;

    /* Create mosek environment. */
    r = MSK_makeenv(&env,NULL);

    /* Create a task for each concurrent optimization.
       The 'task' is the master task that will hold the problem data.
    */

    if ( r==MSK_RES_OK )
        r = MSK_maketask(env,0,0,&task);

    if (r == MSK_RES_OK)
        r = MSK_maketask(env,0,0,&task_list[0]);

    /* Assign call-back functions to each task */

    if (r == MSK_RES_OK)
        MSK_linkfunctotaskstream(task,
                                MSK_STREAM_LOG,
                                NULL,
                                printstr1);

    if (r == MSK_RES_OK)
        MSK_linkfunctotaskstream(task_list[0],
                                MSK_STREAM_LOG,
                                NULL,
                                printstr2);

    if (r == MSK_RES_OK)
        r = MSK_linkfiletotaskstream(task,
                                MSK_STREAM_LOG,
                                "simplex.log",
                                0);

    if (r == MSK_RES_OK)
        r = MSK_linkfiletotaskstream(task_list[0],
                                MSK_STREAM_LOG,
                                "intpnt.log",
                                0);

    if (r == MSK_RES_OK)
        r = MSK_readdata(task,argv[1]);

    /* Assign different parameter values to each task.
       In this case different optimizers. */

```

```

if (r == MSK_RES_OK)
    r = MSK_putintparam(task,
                        MSK_IPAR_OPTIMIZER,
                        MSK_OPTIMIZER_PRIMAL_SIMPLEX);

if (r == MSK_RES_OK)
    r = MSK_putintparam(task_list[0],
                        MSK_IPAR_OPTIMIZER,
                        MSK_OPTIMIZER_INTPNT);

/* Optimize task and task_list[0] in parallel.
   The problem data i.e. C, A, etc.
   is copied from task to task_list[0].
*/

if (r == MSK_RES_OK)
    r = MSK_optimizeconcurrent (task,
                               task_list,
                               NUMTASKS);

printf ("Return Code = %d\n",r);

MSK_solutionsummary(task,
                    MSK_STREAM_LOG);

MSK_deletetask(&task);
MSK_deletetask(&task_list[0]);
MSK_deleteenv(&env);

return r;
}

```


Chapter 12

The optimizers for mixed-integer problems

A problem is a mixed-integer optimization problem when one or more of the variables are constrained to be integer valued. MOSEK contains two optimizers for mixed integer problems that is capable for solving mixed-integer

- linear,
- quadratic and quadratically constrained, and
- conic

problems.

Readers unfamiliar with integer optimization are recommended to consult some relevant literature, e.g. the book [16] by Wolsey.

12.1 Some concepts and facts related to mixed-integer optimization

It is important to understand that in a worst-case scenario, the time required to solve integer optimization problems grows exponentially with the size of the problem. For instance, assume that a problem contains n binary variables, then the time required to solve the problem in the worst case may be proportional to 2^n . The value of 2^n is huge even for moderate values of n .

In practice this implies that the focus should be on computing a near optimal solution quickly rather than at locating an optimal solution. Even if the problem is only solved approximately, it is important to know how far the approximate solution is from an optimal one. In order to say something about the goodness of an approximate solution then the concept of a relaxation is important.

Name	Run-to-run deterministic	Parallelized	Strength	Cost
Mixed-integer conic	Yes	Yes	Conic	Free add-on
Mixed-integer	No	Partial	Linear	Payed add-on

Table 12.1: Mixed-integer optimizers.

The mixed-integer optimization problem

$$\begin{aligned}
 z^* = \quad & \text{minimize} && c^T x \\
 & \text{subject to} && Ax = b, \\
 & && x \geq 0 \\
 & && x_j \in \mathbb{Z}, \quad \forall j \in \mathcal{J},
 \end{aligned} \tag{12.1}$$

has the continuous relaxation

$$\begin{aligned}
 \underline{z} = \quad & \text{minimize} && c^T x \\
 & \text{subject to} && Ax = b, \\
 & && x \geq 0
 \end{aligned} \tag{12.2}$$

The continuous relaxation is identical to the mixed-integer problem with the restriction that some variables must be integer removed.

There are two important observations about the continuous relaxation. Firstly, the continuous relaxation is usually much faster to optimize than the mixed-integer problem. Secondly if \hat{x} is any feasible solution to (12.1) and

$$\bar{z} := c^T \hat{x}$$

then

$$\underline{z} \leq z^* \leq \bar{z}.$$

This is an important observation since if it is only possible to find a near optimal solution within a reasonable time frame then the quality of the solution can nevertheless be evaluated. The value \underline{z} is a lower bound on the optimal objective value. This implies that the obtained solution is no further away from the optimum than $\bar{z} - \underline{z}$ in terms of the objective value.

Whenever a mixed-integer problem is solved MOSEK reports this lower bound so that the quality of the reported solution can be evaluated.

12.2 The mixed-integer optimizers

MOSEK includes two mixed-integer optimizer which is compared in Table 12.1. Both optimizers can handle problems with linear, quadratic objective and constraints and conic constraints. However, a problem must not contain both quadratic objective and constraints and conic constraints.

The mixed-integer conic optimizer is specialized for solving linear and conic optimization problems. It can also solve pure quadratic and quadratically constrained problems, these problems are automatically converted to conic problems before being solved. Whereas the mixed-integer optimizer deals with quadratic and quadratically constrained problems directly.

The mixed-integer conic optimizer is run-to-run deterministic. This means that if a problem is solved twice on the same computer with identical options then the obtained solution will be bit-for-bit identical for the two runs. However, if a time limit is set then this may not be case since the time taken to solve a problem is not deterministic. Moreover, the mixed-integer conic optimizer is parallelized i.e. it can exploit multiple cores during the optimization. Finally, the mixed-integer conic optimizer is a free add-on to the continuous optimizers. However, for some linear problems the mixed-integer optimizer may outperform the mixed-integer conic optimizer. On the other hand the mixed-integer conic optimizer is included with continuous optimizers free of charge and usually the fastest for conic problems.

None of the mixed-integer optimizers handles symmetric matrix variables i.e semi-definite optimization problems.

12.3 The mixed-integer conic optimizer

The mixed-integer conic optimizer is employed by setting the parameter `MSK_IPAR_OPTIMIZER` to `MSK_OPTIMIZER_MIXED_INT_CONIC`.

The mixed-integer conic employs three phases:

Presolve:

In this phase the optimizer tries to reduce the size of the problem using preprocessing techniques. Moreover, it strengthens the continuous relaxation, if possible.

Heuristic:

Using heuristics the optimizer tries to guess a good feasible solution.

Optimization:

The optimal solution is located using a variant of the branch-and-cut method.

12.3.1 Presolve

In the preprocessing stage redundant variables and constraints are removed. The presolve stage can be turned off using the `MSK_IPAR_MIO_PRESOLVE_USE` parameter.

12.3.2 Heuristic

Initially, the integer optimizer tries to guess a good feasible solution using a heuristic.

12.3.3 The optimization phase

This phase solves the problem using the branch and cut algorithm.

12.3.4 Caveats

The mixed-integer conic optimizer ignores the parameter

MSK_IPAR_MIO_CONT_SOL:

The user should fix all the integer variables at their optimal value and reoptimize instead of relying in this option.

12.4 The mixed-integer optimizer

The mixed-integer optimizer is employed by setting the parameter **MSK_IPAR_OPTIMIZER** to **MSK_OPTIMIZER_MIXED_INT**. In the following it is briefly described how the optimizer works.

The process of solving an integer optimization problem can be split in three phases:

Presolve:

In this phase the optimizer tries to reduce the size of the problem using preprocessing techniques. Moreover, it strengthens the continuous relaxation, if possible.

Heuristic:

Using heuristics the optimizer tries to guess a good feasible solution.

Optimization:

The optimal solution is located using a variant of the branch-and-cut method.

12.4.1 Presolve

In the preprocessing stage redundant variables and constraints are removed. The presolve stage can be turned off using the **MSK_IPAR_MIO_PRESOLVE_USE** parameter.

12.4.2 Heuristic

Initially, the integer optimizer tries to guess a good feasible solution using different heuristics:

- First a very simple rounding heuristic is employed.
- Next, if deemed worthwhile, the *feasibility pump* heuristic is used.
- Finally, if the two previous stages did not produce a good initial solution, more sophisticated heuristics are used.

The following parameters can be used to control the effort made by the integer optimizer to find an initial feasible solution.

- **MSK_IPAR_MIO_HEURISTIC_LEVEL**: Controls how sophisticated and computationally expensive a heuristic to employ.
- **MSK_DPAR_MIO_HEURISTIC_TIME**: The minimum amount of time to spend in the heuristic search.
- **MSK_IPAR_MIO_FEASPUMP_LEVEL**: Controls how aggressively the feasibility pump heuristic is used.

12.4.3 The optimization phase

This phase solves the problem using the branch and cut algorithm.

12.5 Termination criterion

In general, it is time consuming to find an exact feasible and optimal solution to an integer optimization problem, though in many practical cases it may be possible to find a sufficiently good solution. Therefore, the mixed-integer optimizer employs a relaxed feasibility and optimality criterion to determine when a satisfactory solution is located.

A candidate solution that is feasible to the continuous relaxation is said to be an integer feasible solution if the criterion

$$\min(|x_j| - \lfloor x_j \rfloor, \lceil x_j \rceil - |x_j|) \leq \max(\delta_1, \delta_2 |x_j|) \quad \forall j \in \mathcal{J}$$

is satisfied.

Whenever the integer optimizer locates an integer feasible solution it will check if the criterion

$$\bar{z} - \underline{z} \leq \max(\delta_3, \delta_4 \max(1, |\bar{z}|))$$

is satisfied. If this is the case, the integer optimizer terminates and reports the integer feasible solution as an optimal solution. Please note that \underline{z} is a valid lower bound determined by the integer optimizer during the solution process, i.e.

$$\underline{z} \leq z^*.$$

The lower bound \underline{z} normally increases during the solution process.

12.5.1 Relaxed termination

If an optimal solution cannot be located within a reasonable time, it may be advantageous to employ a relaxed termination criterion after some time. Whenever the integer optimizer locates an integer feasible solution and has spent at least the number of seconds defined by the **MSK_DPAR_MIO_DISABLE_TERM_TIME** parameter on solving the problem, it will check whether the criterion

Tolerance	Parameter name
δ_1	<code>MSK_DPAR_MIO_TOL_ABS_RELAX_INT</code>
δ_2	<code>MSK_DPAR_MIO_TOL_REL_RELAX_INT</code>
δ_3	<code>MSK_DPAR_MIO_TOL_ABS_GAP</code>
δ_4	<code>MSK_DPAR_MIO_TOL_REL_GAP</code>
δ_5	<code>MSK_DPAR_MIO_NEAR_TOL_ABS_GAP</code>
δ_6	<code>MSK_DPAR_MIO_NEAR_TOL_REL_GAP</code>

Table 12.2: Integer optimizer tolerances.

Parameter name	Delayed	Explanation
<code>MSK_IPAR_MIO_MAX_NUM_BRANCHES</code>	Yes	Maximum number of branches allowed.
<code>MSK_IPAR_MIO_MAX_NUM_RELAXS</code>	Yes	Maximum number of realizations allowed.
<code>MSK_IPAR_MIO_MAX_NUM_SOLUTIONS</code>	Yes	Maximum number of feasible integer solutions allowed.

Table 12.3: Parameters affecting the termination of the integer optimizer.

$$\bar{z} - \underline{z} \leq \max(\delta_5, \delta_6 \max(1, |\bar{z}|))$$

is satisfied. If it is satisfied, the optimizer will report that the candidate solution is **near optimal** and then terminate. Please note that since this criteria depends on timing, the optimizer will not be run to run deterministic.

12.5.2 Important parameters

All δ tolerances can be adjusted using suitable parameters — see Table 12.2. In Table 12.3 some other parameters affecting the integer optimizer termination criterion are shown. Please note that if the effect of a parameter is delayed, the associated termination criterion is applied only after some time, specified by the `MSK_DPAR_MIO_DISABLE_TERM_TIME` parameter.

12.6 How to speed up the solution process

As mentioned previously, in many cases it is not possible to find an optimal solution to an integer optimization problem in a reasonable amount of time. Some suggestions to reduce the solution time are:

- Relax the termination criterion: In case the run time is not acceptable, the first thing to do is to relax the termination criterion — see Section 12.5 for details.
- Specify a good initial solution: In many cases a good feasible solution is either known or easily computed using problem specific knowledge. If a good feasible solution is known, it is usually worthwhile to use this as a starting point for the integer optimizer.

- Improve the formulation: A mixed-integer optimization problem may be impossible to solve in one form and quite easy in another form. However, it is beyond the scope of this manual to discuss good formulations for mixed-integer problems. For discussions on this topic see for example [16].

12.7 Understanding solution quality

To determine the quality of the solution one should check the following:

- The solution status key returned by MOSEK.
- The *optimality gap*: A measure for how much the located solution can deviate from the optimal solution to the problem.
- Feasibility. How much the solution violates the constraints of the problem.

The *optimality gap* is a measure for how close the solution is to the optimal solution. The optimality gap is given by

$$\epsilon = |(\text{objective value of feasible solution}) - (\text{objective bound})|.$$

The objective value of the solution is guaranteed to be within ϵ of the optimal solution.

The optimality gap can be retrieved through the solution item `MSK_DINF_MIO_OBJ_ABS_GAP`. Often it is more meaningful to look at the optimality gap normalized with the magnitude of the solution. The relative optimality gap is available in `MSK_DINF_MIO_OBJ_REL_GAP`.

Chapter 13

The analyzers

13.1 The problem analyzer

The problem analyzer prints a detailed survey of the

- linear constraints and objective
- quadratic constraints
- conic constraints
- variables

of the model.

In the initial stages of model formulation the problem analyzer may be used as a quick way of verifying that the model has been built or imported correctly. In later stages it can help revealing special structures within the model that may be used to tune the optimizer's performance or to identify the causes of numerical difficulties.

The problem analyzer is run from the command line using the `-anapro` argument and produces something similar to the following (this is the problemanalyzer's survey of the `aflow30a` problem from the MIPLIB 2003 collection, see Appendix F for more examples):

Analyzing the problem

Constraints		Bounds		Variables	
upper bd:	421	ranged	: all	cont:	421
fixed :	58			bin :	421

Objective, min cx		
range: min c :	0.00000	min c >0: 11.0000
distrib:	c	vars
	0	421

```

      [11, 100)      150
      [100, 500]    271
-----

Constraint matrix A has
      479 rows (constraints)
      842 columns (variables)
      2091 (0.518449%) nonzero entries (coefficients)

Row nonzeros, A_i
      range: min A_i: 2 (0.23753%)    max A_i: 34 (4.038%)
distrib:
      A_i      rows      rows%      acc%
           2      421      87.89      87.89
      [8, 15]      20       4.18      92.07
      [16, 31]     30       6.26      98.33
      [32, 34]      8       1.67     100.00

Column nonzeros, A_j
      range: min A_j: 2 (0.417537%)    max A_j: 3 (0.626305%)
distrib:
      A_j      cols      cols%      acc%
           2      435      51.66      51.66
           3      407      48.34     100.00

A nonzeros, A(i,j)
      range: min |A(i,j)|: 1.00000    max |A(i,j)|: 100.000
distrib:
      A(i,j)      coeffs
      [1, 10)      1670
      [10, 100]    421
-----

Constraint bounds, lb <= Ax <= ub
distrib:
      |b|      lbs      ubs
           0      421
      [1, 10]     58      58

Variable bounds, lb <= x <= ub
distrib:
      |b|      lbs      ubs
           0      842
      [1, 10)      421
      [10, 100]    421
-----

```

The survey is divided into six different sections, each described below. To keep the presentation short with focus on key elements the analyzer generally attempts to display information on issues relevant for the current model only: E.g., if the model does not have any conic constraints (this is the case in the example above) or any integer variables, those parts of the analysis will not appear.

13.1.1 General characteristics

The first part of the survey consists of a brief summary of the model's linear and quadratic constraints (indexed by i) and variables (indexed by j). The summary is divided into three subsections:

Constraints

upper bd:

The number of upper bounded constraints, $\sum_{j=0}^{n-1} a_{ij}x_j \leq u_i^c$

lower bd:

The number of lower bounded constraints, $l_i^c \leq \sum_{j=0}^{n-1} a_{ij}x_j$

ranged :

The number of ranged constraints, $l_i^c \leq \sum_{j=0}^{n-1} a_{ij}x_j \leq u_i^c$

fixed :

The number of fixed constraints, $l_i^c = \sum_{j=0}^{n-1} a_{ij}x_j = u_i^c$

free :

The number of free constraints

Bounds

upper bd:

The number of upper bounded variables, $x_j \leq u_j^x$

lower bd:

The number of lower bounded variables, $l_k^x \leq x_j$

ranged :

The number of ranged variables, $l_k^x \leq x_j \leq u_j^x$

fixed :

The number of fixed variables, $l_k^x = x_j = u_j^x$

free :

The number of free variables

Variables

cont:

The number of continuous variables, $x_j \in \mathbb{R}$

bin :

The number of binary variables, $x_j \in \{0, 1\}$

int :

The number of general integer variables, $x_j \in \mathbb{Z}$

Only constraints, bounds and domains actually in the model will be reported on, cf. appendix F; if all entities in a section turn out to be of the same kind, the number will be replaced by **all** for brevity.

13.1.2 Objective

The second part of the survey focuses on (the linear part of) the objective, summarizing the optimization sense and the coefficients' absolute value range and distribution. The number of 0 (zero) coefficients is singled out (if any such variables are in the problem).

The range is displayed using three terms:

min |c|:

The minimum absolute value among all coefficients

min |c|>0:

The minimum absolute value among the nonzero coefficients

max |c|:

The maximum absolute value among the coefficients

If some of these extrema turn out to be equal, the display is shortened accordingly:

- If **min** |c| is greater than zero, the **min** |c|?0 term is obsolete and will not be displayed
- If only one or two different coefficients occur this will be displayed using **all** and an explicit listing of the coefficients

The absolute value distribution is displayed as a table summarizing the numbers by orders of magnitude (with a ratio of 10). Again, the number of variables with a coefficient of 0 (if any) is singled out. Each line of the table is headed by an interval (half-open intervals including their lower bounds), and is followed by the number of variables with their objective coefficient in this interval. Intervals with no elements are skipped.

13.1.3 Linear constraints

The third part of the survey displays information on the nonzero coefficients of the linear constraint matrix.

Following a brief summary of the matrix dimensions and the number of nonzero coefficients in total, three sections provide further details on how the nonzero coefficients are distributed by row-wise count (**A.i**), by column-wise count (**A.j**), and by absolute value (**|A(ij)|**). Each section is headed by a brief display of the distribution's range (**min** and **max**), and for the row/column-wise counts the corresponding densities are displayed too (in parentheses).

The distribution tables single out three particularly interesting counts: zero, one, and two nonzeros per row/column; the remaining row/column nonzeros are displayed by orders of magnitude (ratio 2). For each interval the relative and accumulated relative counts are also displayed.

Note that constraints may have both linear and quadratic terms, but the empty rows and columns reported in this part of the survey relate to the linear terms only. If empty rows and/or columns are found in the linear constraint matrix, the problem is analyzed further in order to determine if the

corresponding constraints have any quadratic terms or the corresponding variables are used in conic or quadratic constraints; cf. the last two examples of appendix F.

The distribution of the absolute values, $|A(ij)|$, is displayed just as for the objective coefficients described above.

13.1.4 Constraint and variable bounds

The fourth part of the survey displays distributions for the absolute values of the finite lower and upper bounds for both constraints and variables. The number of bounds at 0 is singled out and, otherwise, displayed by orders of magnitude (with a ratio of 10).

13.1.5 Quadratic constraints

The fifth part of the survey displays distributions for the nonzero elements in the gradient of the quadratic constraints, i.e. the nonzero row counts for the column vectors Qx . The table is similar to the tables for the linear constraints' nonzero row and column counts described in the survey's third part.

Note: Quadratic constraints may also have a linear part, but that will be included in the linear constraints survey; this means that if a problem has one or more pure quadratic constraints, part three of the survey will report an equal number of linear constraint rows with 0 (zero) nonzeros, cf. the last example in appendix F. Likewise, variables that appear in quadratic terms only will be reported as empty columns (0 nonzeros) in the linear constraint report.

13.1.6 Conic constraints

The last part of the survey summarizes the model's conic constraints. For each of the two types of cones, quadratic and rotated quadratic, the total number of cones are reported, and the distribution of the cones' dimensions are displayed using intervals. Cone dimensions of 2, 3, and 4 are singled out.

13.2 Analyzing infeasible problems

When developing and implementing a new optimization model, the first attempts will often be either infeasible, due to specification of inconsistent constraints, or unbounded, if important constraints have been left out.

In this chapter we will

- go over an example demonstrating how to locate infeasible constraints using the MOSEK infeasibility report tool,
- discuss in more general terms which properties that may cause infeasibilities, and
- present the more formal theory of infeasible and unbounded problems.




Figure 13.1: Supply, demand and cost of transportation.

Furthermore, chapter 14 contains a discussion on a specific method for repairing infeasibility problems where infeasibilities are caused by model parameters rather than errors in the model or the implementation.

13.2.1 Example: Primal infeasibility

A problem is said to be *primal infeasible* if no solution exists that satisfy all the constraints of the problem.

As an example of a primal infeasible problem consider the problem of minimizing the cost of transportation between a number of production plants and stores: Each plant produces a fixed number of goods, and each store has a fixed demand that must be met. Supply, demand and cost of transportation per unit are given in figure 13.1. The problem represented in figure 13.1 is infeasible, since the total demand

$$2300 = 1100 + 200 + 500 + 500$$

exceeds the total supply

$$2200 = 200 + 1000 + 1000$$

If we denote the number of transported goods from plant i to store j by x_{ij} , the problem can be formulated as the LP:

$$\begin{array}{llllllllllll}
 \text{minimize} & x_{11} & + & 2x_{12} & + & 5x_{23} & + & 2x_{24} & + & x_{31} & + & 2x_{33} & + & x_{34} \\
 \text{subject to} & x_{11} & + & x_{12} & & & & & & & & & & & \leq & 200, \\
 & & & & & x_{23} & + & x_{24} & & & & & & & \leq & 1000, \\
 & & & & & & & & & x_{31} & + & x_{33} & + & x_{34} & \leq & 1000, \\
 & x_{11} & & & & & & & & + & x_{31} & & & & = & 1100, \\
 & & x_{12} & & & & & & & & & & & & = & 200, \\
 & & & x_{23} & + & & & & & & & x_{33} & & & = & 500, \\
 & & & & & x_{24} & + & & & & & & x_{34} & = & 500, \\
 & x_{ij} & \geq & 0. & & & & & & & & & & & &
 \end{array} \tag{13.1}$$

Solving the problem (13.1) using MOSEK will result in a solution, a solution status and a problem status. Among the log output from the execution of MOSEK on the above problem are the lines:

```

Basic solution
Problem status : PRIMAL_INFEASIBLE
Solution status : PRIMAL_INFEASIBLE_CER

```

The first line indicates that the problem status is primal infeasible. The second line says that a *certificate of the infeasibility* was found. The certificate is returned in place of the solution to the problem.

13.2.2 Locating the cause of primal infeasibility

Usually a primal infeasible problem status is caused by a mistake in formulating the problem and therefore the question arises: "What is the cause of the infeasible status?" When trying to answer this question, it is often advantageous to follow these steps:

- Remove the objective function. This does not change the infeasible status but simplifies the problem, eliminating any possibility of problems related to the objective function.
- Consider whether your problem has some necessary conditions for feasibility and examine if these are satisfied, e.g. total supply should be greater than or equal to total demand.
- Verify that coefficients and bounds are reasonably sized in your problem.

If the problem is still primal infeasible, some of the constraints must be relaxed or removed completely. The MOSEK infeasibility report (Section 13.2.4) may assist you in finding the constraints causing the infeasibility.

Possible ways of relaxing your problem include:

- Increasing (decreasing) upper (lower) bounds on variables and constraints.

- Removing suspected constraints from the problem.

Returning to the transportation example, we discover that removing the fifth constraint

$$x_{12} = 200$$

makes the problem feasible.

13.2.3 Locating the cause of dual infeasibility

A problem may also be *dual infeasible*. In this case the primal problem is often unbounded, meaning that feasible solutions exist such that the objective tends towards infinity. An example of a dual infeasible and primal unbounded problem is:

$$\begin{array}{ll} \text{minimize} & x_1 \\ \text{subject to} & x_1 \leq 5. \end{array}$$

To resolve a dual infeasibility the primal problem must be made more restricted by

- Adding upper or lower bounds on variables or constraints.
- Removing variables.
- Changing the objective.

13.2.3.1 A cautious note

The problem

$$\begin{array}{ll} \text{minimize} & 0 \\ \text{subject to} & 0 \leq x_1, \\ & x_j \leq x_{j+1}, \quad j = 1, \dots, n-1, \\ & x_n \leq -1 \end{array}$$

is clearly infeasible. Moreover, if any one of the constraints are dropped, then the problem becomes feasible.

This illustrates the worst case scenario that all, or at least a significant portion, of the constraints are involved in the infeasibility. Hence, it may not always be easy or possible to pinpoint a few constraints which are causing the infeasibility.

13.2.4 The infeasibility report

MOSEK includes functionality for diagnosing the cause of a primal or a dual infeasibility. It can be turned on by setting the `MSK_IPAR_INFEAS_REPORT_AUTO` to `MSK_ON`. This causes MOSEK to print a report on variables and constraints involved in the infeasibility.

The `MSK_IPAR_INFEAS_REPORT_LEVEL` parameter controls the amount of information presented in the infeasibility report. The default value is 1 .

13.2.4.1 Example: Primal infeasibility

We will reuse the example (13.1) located in `infeas.lp`:

```
\
\ An example of an infeasible linear problem.
\
minimize
  obj: + 1 x11 + 2 x12 + 1 x13
        + 4 x21 + 2 x22 + 5 x23
        + 4 x31 + 1 x32 + 2 x33
st
  s0: + x11 + x12      <= 200
  s1: + x23 + x24      <= 1000
  s2: + x31 + x33 + x34 <= 1000
  d1: + x11 + x31      = 1100
  d2: + x12            = 200
  d3: + x23 + x33      = 500
  d4: + x24 + x34      = 500
bounds
end
```

Using the command line (please remember it accepts options following the C API format)

```
mosek -d MSK_IPAR_INFEAS_REPORT_AUTO MSK_ON infeas.lp
```

MOSEK produces the following infeasibility report

```
MOSEK PRIMAL INFEASIBILITY REPORT.
```

```
Problem status: The problem is primal infeasible
```

```
The following constraints are involved in the primal infeasibility.
```

Index	Name	Lower bound	Upper bound	Dual lower	Dual upper
0	s0	NONE	2.000000e+002	0.000000e+000	1.000000e+000
2	s2	NONE	1.000000e+003	0.000000e+000	1.000000e+000
3	d1	1.100000e+003	1.100000e+003	1.000000e+000	0.000000e+000
4	d2	2.000000e+002	2.000000e+002	1.000000e+000	0.000000e+000

```
The following bound constraints are involved in the infeasibility.
```

Index	Name	Lower bound	Upper bound	Dual lower	Dual upper
8	x33	0.000000e+000	NONE	1.000000e+000	0.000000e+000
10	x34	0.000000e+000	NONE	1.000000e+000	0.000000e+000

The infeasibility report is divided into two sections where the first section shows which constraints that are important for the infeasibility. In this case the important constraints are the ones named `s0`, `s2`, `d1`, and `d2`. The values in the columns "Dual lower" and "Dual upper" are also useful, since a non-zero *dual lower* value for a constraint implies that the lower bound on the constraint is important for the infeasibility. Similarly, a non-zero *dual upper* value implies that the upper bound on the constraint is important for the infeasibility.

It is also possible to obtain the infeasible subproblem. The command line

```
mosek -d MSK_IPAR_INFEAS_REPORT_AUTO MSK_ON infeas.lp -info rinfeas.lp
```

produces the files `rinfeas.bas.inf.lp`. In this case the content of the file `rinfeas.bas.inf.lp` is

```
minimize
  Obj: + CFIXVAR
st
  s0: + x11 + x12 <= 200
  s2: + x31 + x33 + x34 <= 1e+003
  d1: + x11 + x31 = 1.1e+003
  d2: + x12 = 200
bounds
  x11 free
  x12 free
  x13 free
  x21 free
  x22 free
  x23 free
  x31 free
  x32 free
  x24 free
  CFIXVAR = 0e+000
end
```

which is an optimization problem. This problem is identical to (13.1), except that the objective and some of the constraints and bounds have been removed. Executing the command

```
mosek -d MSK_IPAR_INFEAS_REPORT_AUTO MSK_ON rinfeas.bas.inf.lp
```

demonstrates that the reduced problem is **primal infeasible**. Since the reduced problem is usually smaller than original problem, it should be easier to locate the cause of the infeasibility in this rather than in the original (13.1).

13.2.4.2 Example: Dual infeasibility

The example problem

```
maximize - 200 y1 - 1000 y2 - 1000 y3
          - 1100 y4 - 200 y5 - 500 y6
          - 500 y7
subject to
  x11: y1+y4 < 1
  x12: y1+y5 < 2
  x23: y2+y6 < 5
  x24: y2+y7 < 2
  x31: y3+y4 < 1
  x33: y3+y6 < 2
  x44: y3+y7 < 1
bounds
  y1 < 0
  y2 < 0
  y3 < 0
  y4 free
  y5 free
  y6 free
  y7 free
end
```

is dual infeasible. This can be verified by proving that

$$y_1=-1, y_2=-1, y_3=0, y_4=1, y_5=1$$

is a certificate of dual infeasibility. In this example the following infeasibility report is produced (slightly edited):

The following constraints are involved in the infeasibility.

Index	Name	Activity	Objective	Lower bound	Upper bound
0	x11	-1.000000e+00		NONE	1.000000e+00
4	x31	-1.000000e+00		NONE	1.000000e+00

The following variables are involved in the infeasibility.

Index	Name	Activity	Objective	Lower bound	Upper bound
3	y4	-1.000000e+00	-1.100000e+03	NONE	NONE

Interior-point solution

Problem status : DUAL_INFEASIBLE

Solution status : DUAL_INFEASIBLE_CER

Primal - objective: 1.1000000000e+03 eq. infeas.: 0.00e+00 max bound infeas.: 0.00e+00 cone infeas.: 0.00e+00

Dual - objective: 0.0000000000e+00 eq. infeas.: 0.00e+00 max bound infeas.: 0.00e+00 cone infeas.: 0.00e+00

Let x^* denote the reported primal solution. MOSEK states

- that the problem is *dual infeasible*,
- that the reported solution is a certificate of dual infeasibility, and
- that the infeasibility measure for x^* is approximately zero.

Since it was an maximization problem, this implies that

$$c^t x^* > 0. \quad (13.2)$$

For a minimization problem this inequality would have been reversed — see (13.5).

From the infeasibility report we see that the variable **y4**, and the constraints **x11** and **x33** are involved in the infeasibility since these appear with non-zero values in the "Activity" column.

One possible strategy to "fix" the infeasibility is to modify the problem so that the certificate of infeasibility becomes invalid. In this case we may do one the following things:

- Put a lower bound in **y3**. This will directly invalidate the certificate of dual infeasibility.
- Increase the object coefficient of **y3**. Changing the coefficients sufficiently will invalidate the inequality (13.2) and thus the certificate.
- Put lower bounds on **x11** or **x31**. This will directly invalidate the certificate of infeasibility.

Please note that modifying the problem to invalidate the reported certificate does *not* imply that the problem becomes dual feasible — the infeasibility may simply "move", resulting in a new infeasibility.

More often, the reported certificate can be used to give a hint about errors or inconsistencies in the model that produced the problem.

13.2.5 Theory concerning infeasible problems

This section discusses the theory of infeasibility certificates and how MOSEK uses a certificate to produce an infeasibility report. In general, MOSEK solves the problem

$$\begin{array}{llllll} \text{minimize} & & c^T x + c^f & & & \\ \text{subject to} & l^c & \leq & Ax & \leq & u^c, \\ & l^x & \leq & x & \leq & u^x \end{array} \quad (13.3)$$

where the corresponding dual problem is

$$\begin{array}{llll} \text{maximize} & (l^c)^T s_l^c - (u^c)^T s_u^c \\ & + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ \text{subject to} & A^T y + s_l^x - s_u^x & = & c, \\ & -y + s_l^c - s_u^c & = & 0, \\ & s_l^c, s_u^c, s_l^x, s_u^x \geq 0. \end{array} \quad (13.4)$$

We use the convention that for any bound that is not finite, the corresponding dual variable is fixed at zero (and thus will have no influence on the dual problem). For example

$$l_j^x = -\infty \Rightarrow (s_l^x)_j = 0$$

13.2.6 The certificate of primal infeasibility

A certificate of primal infeasibility is *any* solution to the homogenized dual problem

$$\begin{array}{llll} \text{maximize} & (l^c)^T s_l^c - (u^c)^T s_u^c \\ & + (l^x)^T s_l^x - (u^x)^T s_u^x \\ \text{subject to} & A^T y + s_l^x - s_u^x & = & 0, \\ & -y + s_l^c - s_u^c & = & 0, \\ & s_l^c, s_u^c, s_l^x, s_u^x \geq 0. \end{array}$$

with a positive objective value. That is, $(s_l^{c*}, s_u^{c*}, s_l^{x*}, s_u^{x*})$ is a certificate of primal infeasibility if

$$(l^c)^T s_l^{c*} - (u^c)^T s_u^{c*} + (l^x)^T s_l^{x*} - (u^x)^T s_u^{x*} > 0$$

and

$$\begin{array}{ll} A^T y + s_l^{x*} - s_u^{x*} & = 0, \\ -y + s_l^{c*} - s_u^{c*} & = 0, \\ s_l^{c*}, s_u^{c*}, s_l^{x*}, s_u^{x*} & \geq 0. \end{array}$$

The well-known Farkas Lemma tells us that (13.3) is infeasible if and only if a certificate of primal infeasibility exists.

Let $(s_l^{c*}, s_u^{c*}, s_l^{x*}, s_u^{x*})$ be a certificate of primal infeasibility then

$$(s_l^{c*})_i > 0 ((s_u^{c*})_i > 0)$$

implies that the lower (upper) bound on the i th constraint is important for the infeasibility. Furthermore,

$$(s_l^{x*})_j > 0 ((s_u^{x*})_i > 0)$$

implies that the lower (upper) bound on the j th variable is important for the infeasibility.

13.2.7 The certificate of dual infeasibility

A certificate of dual infeasibility is *any* solution to the problem

$$\begin{array}{ll} \text{minimize} & c^T x \\ \text{subject to} & \bar{l}^c \leq Ax \leq \bar{u}^c, \\ & \bar{l}^x \leq x \leq \bar{u}^x \end{array}$$

with negative objective value, where we use the definitions

$$\bar{l}_i^c := \begin{cases} 0, & l_i^c > -\infty, \\ -\infty, & \text{otherwise,} \end{cases}, \quad \bar{u}_i^c := \begin{cases} 0, & u_i^c < \infty, \\ \infty, & \text{otherwise,} \end{cases}$$

and

$$\bar{l}_i^x := \begin{cases} 0, & l_i^x > -\infty, \\ -\infty, & \text{otherwise,} \end{cases} \quad \text{and} \quad \bar{u}_i^x := \begin{cases} 0, & u_i^x < \infty, \\ \infty, & \text{otherwise.} \end{cases}$$

Stated differently, a certificate of dual infeasibility is any x^* such that

$$\begin{array}{llll} c^T x^* & < & 0, \\ \bar{l}^c & \leq & Ax^* & \leq & \bar{u}^c, \\ \bar{l}^x & \leq & x^* & \leq & \bar{u}^x \end{array} \tag{13.5}$$

The well-known Farkas Lemma tells us that (13.4) is infeasible if and only if a certificate of dual infeasibility exists.

Note that if x^* is a certificate of dual infeasibility then for any j such that

$$x_j^* \neq 0,$$

variable j is involved in the dual infeasibility.

Chapter 14

Primal feasibility repair

Section 13.2.2 discusses how MOSEK treats infeasible problems. In particular, it is discussed which information MOSEK returns when a problem is infeasible and how this information can be used to pinpoint the cause of the infeasibility.

In this section we discuss how to repair a primal infeasible problem by relaxing the constraints in a controlled way. For the sake of simplicity we discuss the method in the context of linear optimization.

14.1 Manual repair

Subsequently we discuss an automatic method for repairing an infeasible optimization problem. However, it should be observed that the best way to repair an infeasible problem usually depends on what the optimization problem models. For instance in many optimization problem it does not make sense to relax the constraints $x \geq 0$ e.g. it is not possible to produce a negative quantity. Hence, whatever automatic method MOSEK provides it will never be as good as a method that exploits knowledge about what is being modelled. This implies that it is usually better to remove the underlying cause of infeasibility at the modelling stage.

Indeed consider the example

$$\begin{array}{llllllll} \text{minimize} & & & & & & & \\ \text{subject to} & x_1 & + & x_2 & & & & = & 1, \\ & & & & x_3 & + & x_4 & = & 1, \\ & - & x_1 & & - & x_3 & & = & -1 + \epsilon \\ & & - & x_2 & & - & x_4 & = & -1, \\ & x_1, & & x_2, & & x_3, & & x_4 & \geq & 0 \end{array} \quad (14.1)$$

then if we add the equalities together we obtain the implied equality

$$0 = \epsilon$$

which is infeasible for any $\epsilon \neq 0$. Here the infeasibility is caused by a linear dependency in the constraint matrix and that the right-hand side does not match if $\epsilon \neq 0$. Observe even if the problem is feasible then just a tiny perturbation to the right-hand side will make the problem infeasible. Therefore, even though the problem can be repaired then a much more robust solution is to avoid problems with linear dependent constraints. Indeed if a problem contains linear dependencies then the problem is either infeasible or contains redundant constraints. In the above case any of the equality constraints can be removed while not changing the set of feasible solutions.

To summarize linear dependencies in the constraints can give rise to infeasible problems and therefore it is better to avoid them. Note that most network flow models usually is formulated with one linear dependent constraint.

Next consider the problem

$$\begin{aligned}
 & \text{minimize} \\
 & \text{subject to} \quad x_1 - 0.01x_2 = 0 \\
 & \quad \quad \quad x_2 - 0.01x_3 = 0 \\
 & \quad \quad \quad x_3 - 0.01x_4 = 0 \\
 & \quad \quad \quad x_1 \geq -1.0e-9 \\
 & \quad \quad \quad x_1 \leq 1.0e-9 \\
 & \quad \quad \quad x_4 \leq -1.0e-4
 \end{aligned} \tag{14.2}$$

Now the MOSEK presolve for the sake of efficiency fix variables (and constraints) that has tight bounds where tightness is controlled by the parameter `MSK_DPAR_PRESOLVE_TOL_X`. Since, the bounds

$$-1.0e-9 \leq x_1 \leq 1.0e-9$$

are tight then the MOSEK presolve will fix variable x_1 at the mid point between the bounds i.e. at 0. It easy to see that this implies $x_4 = 0$ too which leads to the incorrect conclusion that the problem is infeasible. Observe tiny change of the size $1.0e-9$ make the problem switch from feasible to infeasible. Such a problem is inherently unstable and is hard to solve. We normally call such a problem ill-posed. In general it is recommended to avoid ill-posed problems, but if that is not possible then one solution to this issue is to reduce the parameter to say `MSK_DPAR_PRESOLVE_TOL_X` to say $1.0e-10$. This will at least make sure that the presolve does not make the wrong conclusion.

14.2 Automatic repair

In this section we will describe the idea behind a method that automatically can repair an infeasible problem. The main idea can be described as follows.

Consider the linear optimization problem with m constraints and n variables

$$\begin{aligned}
 & \text{minimize} \quad c^T x + c^f \\
 & \text{subject to} \quad \begin{array}{ll} l^c & \leq Ax \leq u^c, \\ l^x & \leq x \leq u^x, \end{array}
 \end{aligned} \tag{14.3}$$

which is assumed to be infeasible.

One way of making the problem feasible is to reduce the lower bounds and increase the upper bounds. If the change is sufficiently large the problem becomes feasible. Now an obvious idea is to compute the optimal relaxation by solving an optimization problem. The problem

$$\begin{aligned}
 & \text{minimize} && p(v_l^c, v_u^c, v_l^x, v_u^x) \\
 & \text{subject to} && l^c \leq Ax + v_l^c - v_u^c \leq u^c, \\
 & && l^x \leq x + v_l^x - v_u^x \leq u^x, \\
 & && v_l^c, v_u^c, v_l^x, v_u^x \geq 0
 \end{aligned} \tag{14.4}$$

does exactly that. The additional variables $(v_l^c)_i$, $(v_u^c)_i$, $(v_l^x)_j$ and $(v_u^x)_j$ are *elasticity* variables because they allow a constraint to be violated and hence add some elasticity to the problem. For instance, the elasticity variable $(v_l^c)_i$ controls how much the lower bound $(l^c)_i$ should be relaxed to make the problem feasible. Finally, the so-called penalty function

$$p(v_l^c, v_u^c, v_l^x, v_u^x)$$

is chosen so it penalize changes to bounds. Given the weights

- $w_l^c \in \mathbb{R}^m$ (associated with l^c),
- $w_u^c \in \mathbb{R}^m$ (associated with u^c),
- $w_l^x \in \mathbb{R}^n$ (associated with l^x),
- $w_u^x \in \mathbb{R}^n$ (associated with u^x),

then a natural choice is

$$p(v_l^c, v_u^c, v_l^x, v_u^x) = (w_l^c)^T v_l^c + (w_u^c)^T v_u^c + (w_l^x)^T v_l^x + (w_u^x)^T v_u^x. \tag{14.5}$$

Hence, the penalty function $p()$ is a weighted sum of the relaxation and therefore the problem (14.4) keeps the amount of relaxation at a minimum. Please observe that

- the problem (14.6) is always feasible.
- a negative weight implies problem (14.6) is unbounded. For this reason if the value of a weight is negative MOSEK fixes the associated elasticity variable to zero. Clearly, if one or more of the weights are negative may imply that it is not possible repair the problem.

A simple choice of weights is to let them all to be 1, but of course that does not take into account that constraints may have different importance.

14.2.1 Caveats

Observe if the infeasible problem

$$\begin{array}{llll}
\text{minimize} & x + z & & \\
\text{subject to} & x & = & -1, \\
& x & \geq & 0
\end{array} \tag{14.6}$$

is repaired then it will be unbounded. Hence, a repaired problem may not have an optimal solution.

Another and more important caveat is that only a minimal repair is performed i.e. the repair that just makes the problem feasible. Hence, the repaired problem is barely feasible and that sometimes makes the repaired problem hard to solve.

14.3 Feasibility repair in MOSEK

MOSEK includes a function that repairs an infeasible problem using the idea described in the previous section simply by passing a set of weights to MOSEK. This can be used for linear and conic optimization problems, possibly having integer constrained variables.

14.3.1 An example using the command line tool

Consider the example linear optimization

$$\begin{array}{llllll}
\text{minimize} & -10x_1 & & -9x_2, & & \\
\text{subject to} & 7/10x_1 & + & 1x_2 & \leq & 630, \\
& 1/2x_1 & + & 5/6x_2 & \leq & 600, \\
& 1x_1 & + & 2/3x_2 & \leq & 708, \\
& 1/10x_1 & + & 1/4x_2 & \leq & 135, \\
& x_1, & & x_2 & \geq & 0, \\
& & & & & x_2 \geq 650
\end{array} \tag{14.7}$$

which is infeasible. Now suppose we wish to use MOSEK to suggest a modification to the bounds that makes the problem feasible.

Given the assumption that all weights are 1 then the command

```
mosek -primalrepair -d MSK_IPAR_LOG_FEAS_REPAIR 3 feasrepair.lp
```

will form the repaired problem and solve it. The parameter

```
MSK_IPAR_LOG_FEAS_REPAIR
```

controls the amount of log output from the repair. A value of 2 causes the optimal repair to be printed out.

The output from running the above command is:

```
Copyright (c) 1998-2013 MOSEK ApS, Denmark. WWW: http://mosek.com
```

```
Open file 'feasrepair.lp'
```

```
Read summary
```

```

Type           : LO (linear optimization problem)
Objective sense : min

```

```

Constraints      : 4
Scalar variables : 2
Matrix variables : 0
Time             : 0.0

Computer
Platform          : Windows/64-X86
Cores             : 4

Problem
Name              :
Objective sense   : min
Type              : LO (linear optimization problem)
Constraints       : 4
Cones             : 0
Scalar variables  : 2
Matrix variables  : 0
Integer variables : 0

Primal feasibility repair started.
Optimizer started.
Interior-point optimizer started.
Presolve started.
Linear dependency checker started.
Linear dependency checker terminated.
Eliminator started.
Total number of eliminations : 2
Eliminator terminated.
Eliminator - tries          : 1           time           : 0.00
Eliminator - elim's         : 2
Lin. dep. - tries          : 1           time           : 0.00
Lin. dep. - number         : 0
Presolve terminated. Time: 0.00
Optimizer - threads         : 1
Optimizer - solved problem  : the primal
Optimizer - Constraints      : 2
Optimizer - Cones           : 0
Optimizer - Scalar variables : 6           conic           : 0
Optimizer - Semi-definite variables: 0       scalarized        : 0
Factor - setup time         : 0.00         dense det. time   : 0.00
Factor - ML order time      : 0.00         GP order time     : 0.00
Factor - nonzeros before factor : 3         after factor      : 3
Factor - dense dim.         : 0           flops             : 5.40e+001
ITE PFEAS   DFEAS   GFEAS   PRSTATUS   POBJ           DOBJ           MU           TIME
0   2.7e+001 1.0e+000 4.8e+000 1.00e+000 4.195228609e+000 0.000000000e+000 1.0e+000 0.00
1   2.4e+001 8.6e-001 1.5e+000 0.00e+000 1.227497414e+001 1.504971820e+001 2.6e+000 0.00
2   2.6e+000 9.7e-002 1.7e-001 -6.19e-001 4.363064729e+001 4.648523094e+001 3.0e-001 0.00
3   4.7e-001 1.7e-002 3.1e-002 1.24e+000 4.256803136e+001 4.298540657e+001 5.2e-002 0.00
4   8.7e-004 3.2e-005 5.7e-005 1.08e+000 4.249989892e+001 4.250078747e+001 9.7e-005 0.00
5   8.7e-008 3.2e-009 5.7e-009 1.00e+000 4.249999999e+001 4.250000008e+001 9.7e-009 0.00
6   8.7e-012 3.2e-013 5.7e-013 1.00e+000 4.250000000e+001 4.250000000e+001 9.7e-013 0.00
Basis identification started.
Primal basis identification phase started.
ITER      TIME
0          0.00
Primal basis identification phase terminated. Time: 0.00
Dual basis identification phase started.
ITER      TIME

```

```

0          0.00
Dual basis identification phase terminated. Time: 0.00
Basis identification terminated. Time: 0.00
Interior-point optimizer terminated. Time: 0.00.

Optimizer terminated. Time: 0.03
Basic solution summary
  Problem status : PRIMAL_AND_DUAL_FEASIBLE
  Solution status : OPTIMAL
  Primal.  obj: 4.2500000000e+001  Viol.  con: 1e-013  var: 0e+000
  Dual.    obj: 4.2500000000e+001  Viol.  con: 0e+000  var: 5e-013
Optimal objective value of the penalty problem: 4.2500000000e+001

Repairing bounds.
Increasing the upper bound -2.25e+001 on constraint 'c4' (3) with 1.35e+002.
Decreasing the lower bound 6.50e+002 on variable 'x2' (4) with 2.00e+001.
Primal feasibility repair terminated.
Optimizer started.
Interior-point optimizer started.
Presolve started.
Presolve terminated. Time: 0.00
Interior-point optimizer terminated. Time: 0.00.

Optimizer terminated. Time: 0.00

Interior-point solution summary
  Problem status : PRIMAL_AND_DUAL_FEASIBLE
  Solution status : OPTIMAL
  Primal.  obj: -5.6700000000e+003  Viol.  con: 0e+000  var: 0e+000
  Dual.    obj: -5.6700000000e+003  Viol.  con: 0e+000  var: 0e+000

Basic solution summary
  Problem status : PRIMAL_AND_DUAL_FEASIBLE
  Solution status : OPTIMAL
  Primal.  obj: -5.6700000000e+003  Viol.  con: 0e+000  var: 0e+000
  Dual.    obj: -5.6700000000e+003  Viol.  con: 0e+000  var: 0e+000

Optimizer summary
Optimizer          -          time: 0.00
  Interior-point    - iterations : 0      time: 0.00
    Basis identification -          time: 0.00
      Primal        - iterations : 0      time: 0.00
      Dual          - iterations : 0      time: 0.00
      Clean primal   - iterations : 0      time: 0.00
      Clean dual     - iterations : 0      time: 0.00
      Clean primal-dual - iterations : 0      time: 0.00
    Simplex         -          time: 0.00
      Primal simplex - iterations : 0      time: 0.00
      Dual simplex   - iterations : 0      time: 0.00
      Primal-dual simplex - iterations : 0      time: 0.00
    Mixed integer    - relaxations: 0      time: 0.00

```

reports the optimal repair. In this case it is to increase the upper bound on constraint `c4` by `1.35e2` and decrease the lower bound on variable `x2` by `20`.

14.3.2 Feasibility repair using the API

The function `MSK_primalrepair` can be used to repair an infeasible problem. Details about the function `MSK_primalrepair` can be seen in the reference.

14.3.2.1 An example

Consider once again the example (14.7) then

```

2  /*
3   Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
4
5   File:      feasrepairex1.c
6
7   Purpose:   To demonstrate how to use the MSK_primalrepair function to
8               repair an infeasible problem.
9
10  Syntax: On command line
11            feasrepairex1 feasrepair.lp
12            feasrepair.lp is located in mosek\<version>\tools\examples.
13  */
14
15
16  #include <math.h>
17  #include <stdio.h>
18
19  #include "mosek.h"
20
21
22  static void MSKAPI printstr(void *handle,
23                             MSKCONST char str[])
24  {
25      fputs(str,stdout);
26  } /* printstr */
27
28  int main(int argc,MSKCONST char** argv)
29  {
30      double      sum_viol;
31      MSKenv_t     env;
32      MSKrescodee r;
33      MSKtask_t    task;
34
35      r = MSK_makeenv(&env,NULL);
36
37      if ( r==MSK_RES_OK )
38          r = MSK_makeemptytask(env,&task);
39
40      if ( r==MSK_RES_OK )
41          MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
42
43      if ( r==MSK_RES_OK )
44          r = MSK_readdata(task,argv[1]); /* Read file from current dir */
45
46      if ( r==MSK_RES_OK )
47          r = MSK_putintparam(task,MSK_IPAR_LOG_FEAS_REPAIR,3);

```

```
48
49  if ( r==MSK_RES_OK )
50  {
51      /* Weights are NULL implying all weights are 1. */
52      r = MSK_primalrepair(task,NULL,NULL,NULL,NULL);
53  }
54
55  if ( r==MSK_RES_OK )
56      r = MSK_getdouinf(task,MSK_DINF_PRIMAL_REPAIR_PENALTY_OBJ,&sum_viol);
57
58  if ( r==MSK_RES_OK )
59  {
60      printf ("Minimized sum of violations = %e\n",sum_viol);
61
62      r = MSK_optimize(task); /* Optimize the repaired task. */
63
64      MSK_solutionsummary(task,MSK_STREAM_MSG);
65  }
66
67  printf("Return code: %d\n",r);
68
69  return ( r );
70 }
```

will produce the same output as the command line tool discussed in Section 14.3.1.

Chapter 15

Sensitivity analysis

15.1 Introduction

Given an optimization problem it is often useful to obtain information about how the optimal objective value changes when the problem parameters are perturbed. E.g, assume that a bound represents a capacity of a machine. Now, it may be possible to expand the capacity for a certain cost and hence it is worthwhile knowing what the value of additional capacity is. This is precisely the type of questions the sensitivity analysis deals with.

Analyzing how the optimal objective value changes when the problem data is changed is called sensitivity analysis.

15.2 Restrictions

Currently, sensitivity analysis is only available for continuous linear optimization problems. Moreover, MOSEK can only deal with perturbations in bounds and objective coefficients.

15.3 References

The book [1] discusses the classical sensitivity analysis in Chapter 10 whereas the book [17] presents a modern introduction to sensitivity analysis. Finally, it is recommended to read the short paper [18] to avoid some of the pitfalls associated with sensitivity analysis.




Figure 15.1: The optimal value function $f_{l_i^c}(\beta)$. Left: $\beta = 0$ is in the interior of linearity interval. Right: $\beta = 0$ is a breakpoint.

15.4 Sensitivity analysis for linear problems

15.4.1 The optimal objective value function

Assume that we are given the problem

$$\begin{aligned} z(l^c, u^c, l^x, u^x, c) = \text{minimize} \quad & c^T x \\ \text{subject to} \quad & l^c \leq Ax \leq u^c, \\ & l^x \leq x \leq u^x, \end{aligned} \quad (15.1)$$

and we want to know how the optimal objective value changes as l_i^c is perturbed. To answer this question we define the perturbed problem for l_i^c as follows

$$\begin{aligned} f_{l_i^c}(\beta) = \text{minimize} \quad & c^T x \\ \text{subject to} \quad & l^c + \beta e_i \leq Ax \leq u^c, \\ & l^x \leq x \leq u^x, \end{aligned}$$

where e_i is the i th column of the identity matrix. The function

$$f_{l_i^c}(\beta) \quad (15.2)$$

shows the optimal objective value as a function of β . Please note that a change in β corresponds to a perturbation in l_i^c and hence (15.2) shows the optimal objective value as a function of l_i^c .

It is possible to prove that the function (15.2) is a piecewise linear and convex function, i.e. the function may look like the illustration in Figure 15.1. Clearly, if the function $f_{l_i^c}(\beta)$ does not change much when β is changed, then we can conclude that the optimal objective value is insensitive to changes in l_i^c . Therefore, we are interested in the rate of change in $f_{l_i^c}(\beta)$ for small changes in β — specifically the gradient

$$f'_{l_i^c}(0),$$

which is called the *shadow price* related to l_i^c . The shadow price specifies how the objective value changes for small changes in β around zero. Moreover, we are interested in the *linearity interval*

$$\beta \in [\beta_1, \beta_2]$$

for which

$$f'_{l_i^c}(\beta) = f'_{l_i^c}(0).$$

Since $f_{l_i^c}$ is not a smooth function $f'_{l_i^c}$ may not be defined at 0, as illustrated by the right example in figure 15.1. In this case we can define a left and a right shadow price and a left and a right linearity interval.

The function $f_{l_i^c}$ considered only changes in l_i^c . We can define similar functions for the remaining parameters of the z defined in (15.1) as well:

$$\begin{aligned} f_{u_i^c}(\beta) &= z(l^c, u^c + \beta e_i, l^x, u^x, c), & i = 1, \dots, m, \\ f_{l_j^x}(\beta) &= z(l^c, u^c, l^x + \beta e_j, u^x, c), & j = 1, \dots, n, \\ f_{u_j^x}(\beta) &= z(l^c, u^c, l^x, u^x + \beta e_j, c), & j = 1, \dots, n, \\ f_{c_j}(\beta) &= z(l^c, u^c, l^x, u^x, c + \beta e_j), & j = 1, \dots, n. \end{aligned}$$

Given these definitions it should be clear how linearity intervals and shadow prices are defined for the parameters u_i^c etc.

15.4.1.1 Equality constraints

In MOSEK a constraint can be specified as either an equality constraint or a ranged constraint. If constraint i is an equality constraint, we define the optimal value function for this as

$$f_{e_i^c}(\beta) = z(l^c + \beta e_i, u^c + \beta e_i, l^x, u^x, c)$$

Thus for an equality constraint the upper and the lower bounds (which are equal) are perturbed simultaneously. Therefore, MOSEK will handle sensitivity analysis differently for a ranged constraint with $l_i^c = u_i^c$ and for an equality constraint.

15.4.2 The basis type sensitivity analysis

The classical sensitivity analysis discussed in most textbooks about linear optimization, e.g. [1], is based on an optimal basic solution or, equivalently, on an optimal basis. This method may produce misleading results [17] but is **computationally cheap**. Therefore, and for historical reasons this method is available in MOSEK. We will now briefly discuss the basis type sensitivity analysis. Given an optimal basic solution which provides a partition of variables into basic and non-basic variables, the basis type sensitivity analysis computes the linearity interval $[\beta_1, \beta_2]$ so that the basis remains optimal for the perturbed problem. A shadow price associated with the linearity interval is also computed. However, it is well-known that an optimal basic solution may not be unique and therefore the result depends on the optimal basic solution employed in the sensitivity analysis. This implies that the computed interval is only a subset of the largest interval for which the shadow price is constant. Furthermore, the optimal objective value function might have a breakpoint for $\beta = 0$. In this case the basis type sensitivity method will only provide a subset of either the left or the right linearity interval.

In summary, the basis type sensitivity analysis is computationally cheap but does not provide complete information. Hence, the results of the basis type sensitivity analysis should be used with care.

15.4.3 The optimal partition type sensitivity analysis

Another method for computing the complete linearity interval is called the *optimal partition type sensitivity analysis*. The main drawback of the optimal partition type sensitivity analysis is that it is computationally expensive compared to the basis type analysts. This type of sensitivity analysis is currently provided as an experimental feature in MOSEK.

Given the optimal primal and dual solutions to (15.1), i.e. x^* and $((s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*)$ the optimal objective value is given by

$$z^* := c^T x^*.$$

The left and right shadow prices σ_1 and σ_2 for l_i^c are given by this pair of optimization problems:

$$\begin{aligned} \sigma_1 &= \text{minimize} && e_i^T s_l^c \\ &\text{subject to} && A^T(s_l^c - s_u^c) + s_l^x - s_u^x = c, \\ &&& (l_c)^T(s_l^c) - (u_c)^T(s_u^c) + (l_x)^T(s_l^x) - (u_x)^T(s_u^x) = z^*, \\ &&& s_l^c, s_u^c, s_l^x, s_u^x \geq 0 \end{aligned}$$

and

$$\begin{aligned} \sigma_2 &= \text{maximize} && e_i^T s_l^c \\ &\text{subject to} && A^T(s_l^c - s_u^c) + s_l^x - s_u^x = c, \\ &&& (l_c)^T(s_l^c) - (u_c)^T(s_u^c) + (l_x)^T(s_l^x) - (u_x)^T(s_u^x) = z^*, \\ &&& s_l^c, s_u^c, s_l^x, s_u^x \geq 0. \end{aligned}$$

These two optimization problems make it easy to interpret the shadow price. Indeed, if $((s_l^c)^*, (s_u^c)^*, (s_l^x)^*, (s_u^x)^*)$ is an arbitrary optimal solution then

$$(s_l^c)_i^* \in [\sigma_1, \sigma_2].$$

Next, the linearity interval $[\beta_1, \beta_2]$ for l_i^c is computed by solving the two optimization problems

$$\begin{aligned} \beta_1 &= \text{minimize} && \beta \\ &\text{subject to} && l^c + \beta e_i \leq Ax \leq u^c, \\ &&& c^T x - \sigma_1 \beta = z^*, \\ &&& l^x \leq x \leq u^x, \end{aligned}$$

and

$$\begin{aligned} \beta_2 &= \text{maximize} && \beta \\ &\text{subject to} && l^c + \beta e_i \leq Ax \leq u^c, \\ &&& c^T x - \sigma_2 \beta = z^*, \\ &&& l^x \leq x \leq u^x. \end{aligned}$$

The linearity intervals and shadow prices for u_i^c , l_j^x , and u_j^x are computed similarly to l_i^c .

The left and right shadow prices for c_j denoted σ_1 and σ_2 respectively are computed as follows:

$$\begin{aligned} \sigma_1 = \text{minimize} \quad & e_j^T x \\ \text{subject to} \quad & l^c + \beta e_i \leq Ax \leq u^c, \\ & c^T x = z^*, \\ & l^x \leq x \leq u^x \end{aligned}$$

and

$$\begin{aligned} \sigma_2 = \text{maximize} \quad & e_j^T x \\ \text{subject to} \quad & l^c + \beta e_i \leq Ax \leq u^c, \\ & c^T x = z^*, \\ & l^x \leq x \leq u^x. \end{aligned}$$

Once again the above two optimization problems make it easy to interpret the shadow prices. Indeed, if x^* is an arbitrary primal optimal solution, then

$$x_j^* \in [\sigma_1, \sigma_2].$$

The linearity interval $[\beta_1, \beta_2]$ for a c_j is computed as follows:

$$\begin{aligned} \beta_1 = \text{minimize} \quad & \beta \\ \text{subject to} \quad & A^T(s_l^c - s_u^c) + s_l^x - s_u^x = c + \beta e_j, \\ & (l_c)^T(s_l^c) - (u_c)^T(s_u^c) + (l_x)^T(s_l^x) - (u_x)^T(s_u^x) - \sigma_1 \beta \leq z^*, \\ & s_l^c, s_u^c, s_l^x, s_u^x \geq 0 \end{aligned}$$

and

$$\begin{aligned} \beta_2 = \text{maximize} \quad & \beta \\ \text{subject to} \quad & A^T(s_l^c - s_u^c) + s_l^x - s_u^x = c + \beta e_j, \\ & (l_c)^T(s_l^c) - (u_c)^T(s_u^c) + (l_x)^T(s_l^x) - (u_x)^T(s_u^x) - \sigma_2 \beta \leq z^*, \\ & s_l^c, s_u^c, s_l^x, s_u^x \geq 0. \end{aligned}$$

15.4.4 Example: Sensitivity analysis

As an example we will use the following transportation problem. Consider the problem of minimizing the transportation cost between a number of production plants and stores. Each plant supplies a number of goods and each store has a given demand that must be met. Supply, demand and cost of transportation per unit are shown in Figure 15.2. If we denote the number of transported goods from location i to location j by x_{ij} , problem can be formulated as the linear optimization problem minimize

$$1x_{11} + 2x_{12} + 5x_{23} + 2x_{24} + 1x_{31} + 2x_{33} + 1x_{34}$$

subject to




Figure 15.2: Supply, demand and cost of transportation.

Basis type					Optimal partition type				
Con.	β_1	β_2	σ_1	σ_2	Con.	β_1	β_2	σ_1	σ_2
1	-300.00	0.00	3.00	3.00	1	-300.00	500.00	3.00	1.00
2	-700.00	$+\infty$	0.00	0.00	2	-700.00	$+\infty$	-0.00	-0.00
3	-500.00	0.00	3.00	3.00	3	-500.00	500.00	3.00	1.00
4	-0.00	500.00	4.00	4.00	4	-500.00	500.00	2.00	4.00
5	-0.00	300.00	5.00	5.00	5	-100.00	300.00	3.00	5.00
6	-0.00	700.00	5.00	5.00	6	-500.00	700.00	3.00	5.00
7	-500.00	700.00	2.00	2.00	7	-500.00	700.00	2.00	2.00
Var.	β_1	β_2	σ_1	σ_2	Var.	β_1	β_2	σ_1	σ_2
x_{11}	$-\infty$	300.00	0.00	0.00	x_{11}	$-\infty$	300.00	0.00	0.00
x_{12}	$-\infty$	100.00	0.00	0.00	x_{12}	$-\infty$	100.00	0.00	0.00
x_{23}	$-\infty$	0.00	0.00	0.00	x_{23}	$-\infty$	500.00	0.00	2.00
x_{24}	$-\infty$	500.00	0.00	0.00	x_{24}	$-\infty$	500.00	0.00	0.00
x_{31}	$-\infty$	500.00	0.00	0.00	x_{31}	$-\infty$	500.00	0.00	0.00
x_{33}	$-\infty$	500.00	0.00	0.00	x_{33}	$-\infty$	500.00	0.00	0.00
x_{34}	-0.000000	500.00	2.00	2.00	x_{34}	$-\infty$	500.00	0.00	2.00

Table 15.1: Ranges and shadow prices related to bounds on constraints and variables. Left: Results for the basis type sensitivity analysis. Right: Results for the optimal partition type sensitivity analysis.

$$\begin{array}{rcl}
x_{11} + x_{12} & & \leq 400, \\
& x_{23} + x_{24} & \leq 1200, \\
& & x_{31} + x_{33} + x_{34} \leq 1000, \\
x_{11} & & + x_{31} = 800, \\
& x_{12} & = 100, \\
& & x_{23} + x_{33} = 500, \\
& & x_{24} + x_{34} = 500, \\
x_{11}, & x_{12}, & x_{23}, & x_{24}, & x_{31}, & x_{33}, & x_{34} \geq 0.
\end{array} \tag{15.3}$$

The basis type and the optimal partition type sensitivity results for the transportation problem are shown in Table 15.1 and 15.2 respectively. Examining the results from the optimal partition type sensitivity analysis we see that for constraint number 1 we have $\sigma_1 \neq \sigma_2$ and $\beta_1 \neq \beta_2$. Therefore, we have a left linearity interval of $[-300, 0]$ and a right interval of $[0, 500]$. The corresponding left and right shadow prices are 3 and 1 respectively. This implies that if the upper bound on constraint 1 increases by

$$\beta \in [0, \beta_1] = [0, 500]$$

then the optimal objective value will decrease by the value

$$\sigma_2 \beta = 1\beta.$$

Correspondingly, if the upper bound on constraint 1 is decreased by

Basis type					Optimal partition type				
Var.	β_1	β_2	σ_1	σ_2	Var.	β_1	β_2	σ_1	σ_2
c_1	$-\infty$	3.00	300.00	300.00	c_1	$-\infty$	3.00	300.00	300.00
c_2	$-\infty$	∞	100.00	100.00	c_2	$-\infty$	∞	100.00	100.00
c_3	-2.00	∞	0.00	0.00	c_3	-2.00	∞	0.00	0.00
c_4	$-\infty$	2.00	500.00	500.00	c_4	$-\infty$	2.00	500.00	500.00
c_5	-3.00	∞	500.00	500.00	c_5	-3.00	∞	500.00	500.00
c_6	$-\infty$	2.00	500.00	500.00	c_6	$-\infty$	2.00	500.00	500.00
c_7	-2.00	∞	0.00	0.00	c_7	-2.00	∞	0.00	0.00

Table 15.2: Ranges and shadow prices related to the objective coefficients. Left: Results for the basis type sensitivity analysis. Right: Results for the optimal partition type sensitivity analysis.

$$\beta \in [0, 300]$$

then the optimal objective value will increase by the value

$$\sigma_1 \beta = 3\beta.$$

15.5 Sensitivity analysis from the MOSEK API

MOSEK provides the functions `MSK_primalsensitivity` and `MSK_dualsensitivity` for performing sensitivity analysis. The code below gives an example of its use.

```

1  /*
2  Copyright: Copyright (c) MOSEK ApS, Denmark. All rights reserved.
3
4  File:      sensitivity.c
5
6  Purpose:   To demonstrate how to perform sensitivity
7             analysis from the API on a small problem:
8
9  minimize
10
11  obj: +1 x11 + 2 x12 + 5 x23 + 2 x24 + 1 x31 + 2 x33 + 1 x34
12  st
13  c1:  + x11 + x12                                     <= 400
14  c2:              + x23 + x24                         <= 1200
15  c3:              + x31 + x33 + x34                   <= 1000
16  c4:  + x11                                     + x31   = 800
17  c5:              + x12                                     = 100
18  c6:              + x23                                     + x33   = 500
19  c7:              + x24                                     + x34   = 500
20
21  The example uses basis type sensitivity analysis.
22  */
23

```

```

24 #include <stdio.h>
25
26 #include "mosek.h" /* Include the MOSEK definition file. */
27
28 static void MSKAPI printstr(void *handle,
29                             MSKCONST char str[])
30 {
31     printf("%s",str);
32 } /* printstr */
33
34 int main(int argc,char *argv[])
35 {
36     const MSKint32t numcon=7,
37               numvar=7;
38     MSKint32t   i,j;
39     MSKboundkeye bkc[] = {MSK_BK_UP, MSK_BK_UP, MSK_BK_UP, MSK_BK_FX,
40                           MSK_BK_FX, MSK_BK_FX,MSK_BK_FX};
41     MSKboundkeye bkc[] = {MSK_BK_LO, MSK_BK_LO, MSK_BK_LO,
42                           MSK_BK_LO, MSK_BK_LO, MSK_BK_LO,MSK_BK_LO};
43     MSKint32t    ptrb[] = {0,2,4,6,8,10,12};
44     MSKint32t    ptre[] = {2,4,6,8,10,12,14};
45     MSKidx_t     sub[] = {0,3,0,4,1,5,1,6,2,3,2,5,2,6};
46     MSKrealt     blc[] = {-MSK_INFINITY,-MSK_INFINITY,-MSK_INFINITY,800,100,500,500};
47     MSKrealt     buc[] = {400,          1200,          1000,          800,100,500,500};
48     MSKrealt     c[]   = {1.0,2.0,5.0,2.0,1.0,2.0,1.0};
49     MSKrealt     blx[] = {0.0,0.0,0.0,0.0,0.0,0.0,0.0};
50     MSKrealt     bux[] = {MSK_INFINITY,MSK_INFINITY,MSK_INFINITY,MSK_INFINITY,
51                           MSK_INFINITY,MSK_INFINITY,MSK_INFINITY};
52     MSKrealt     val[] = {1.0,1.0,1.0,1.0,1.0,1.0,1.0,1.0,1.0,1.0,1.0,1.0,1.0};
53     MSKrescodee   r;
54
55     MSKenv_t       env;
56     MSKtask_t      task;
57
58     /* Create mosek environment. */
59     r = MSK_makeenv(&env,NULL);
60
61     if ( r==MSK_RES_OK )
62     {
63         /* Make the optimization task. */
64         r = MSK_makeemptytask(env,&task);
65
66         if ( r==MSK_RES_OK )
67         {
68             /* Directs the log task stream to the user
69              specified procedure 'printstr'. */
70
71             MSK_linkfunctotaskstream(task,MSK_STREAM_LOG,NULL,printstr);
72
73             MSK_echotask(task,
74                           MSK_STREAM_MSG,
75                           "Defining the problem data.\n");
76         }
77
78         /* Append the constraints. */
79         if ( r==MSK_RES_OK )
80             r = MSK_appendcons(task,numcon);
81

```

```

82      /* Append the variables. */
83      if ( r==MSK_RES_OK )
84          r = MSK_appendvars(task,numvar);
85
86      /* Put C. */
87      if ( r==MSK_RES_OK )
88          r = MSK_putcfix(task,0.0);
89
90      if ( r==MSK_RES_OK )
91          r = MSK_putcslice(task,0,numvar,c);
92
93      /* Put constraint bounds. */
94      if ( r==MSK_RES_OK )
95          r = MSK_putconboundslice(task,0,numcon,bkc,blc,buc);
96
97      /* Put variable bounds. */
98      if ( r==MSK_RES_OK )
99          r = MSK_putvarboundslice(task,0,numvar,bkx,blx,bux);
100
101      /* Put A. */
102      if ( r==MSK_RES_OK )
103          r = MSK_putacolslice(task,0,numvar,ptrb,ptre,sub,val);
104
105      if ( r==MSK_RES_OK )
106          r = MSK_putobjsense(task,MSK_OBJECTIVE_SENSE_MINIMIZE);
107
108      if ( r==MSK_RES_OK )
109          r = MSK_optimize(task);
110
111      if ( r==MSK_RES_OK )
112      {
113          /* Analyze upper bound on c1 and the equality constraint on c4 */
114          MSKidx subi[] = {0,3};
115          MSKmarke marki[] = {MSK_MARK_UP,MSK_MARK_UP};
116
117          /* Analyze lower bound on the variables x12 and x31 */
118          MSKidx subj[] = {1,4};
119          MSKmarke markj[] = {MSK_MARK_LO,MSK_MARK_LO};
120
121          MSKrealt leftpricei[2];
122          MSKrealt rightpricei[2];
123          MSKrealt leftrangei[2];
124          MSKrealt rightrangei[2];
125          MSKrealt leftpricej[2];
126          MSKrealt rightpricej[2];
127          MSKrealt leftrangej[2];
128          MSKrealt rightrangej[2];
129
130          r = MSK_primalsensitivity( task,
131                                   2,
132                                   subi,
133                                   marki,
134                                   2,
135                                   subj,
136                                   markj,
137                                   leftpricei,
138                                   rightpricei,
139                                   leftrangei,

```

```

140             rightrangei,
141             leftpricej,
142             rightpricej,
143             leftrangej,
144             rightrangej);
145
146     printf("Results from sensitivity analysis on bounds:\n");
147
148     printf("For constraints:\n");
149     for (i=0;i<2;++i)
150         printf("leftprice = %e, rightprice = %e,leftrange = %e, rightrange =%e\n",
151             leftpricei[i], rightpricei[i], leftrangei[i], rightrangei[i]);
152
153     printf("For variables:\n");
154     for (i=0;i<2;++i)
155         printf("leftprice = %e, rightprice = %e,leftrange = %e, rightrange =%e\n",
156             leftpricej[i], rightpricej[i], leftrangej[i], rightrangej[i]);
157 }
158
159 if ( r==MSK_RES_OK )
160 {
161     MSKint32t subj[] = {2,5};
162     MSKrealt leftprice[2];
163     MSKrealt rightprice[2];
164     MSKrealt leftrange[2];
165     MSKrealt rightrange[2];
166
167     r = MSK_dualsensitivity(task,
168         2,
169         subj,
170         leftprice,
171         rightprice,
172         leftrange,
173         rightrange
174     );
175
176     printf("Results from sensitivity analysis on objective coefficients:\n");
177
178     for (i=0;i<2;++i)
179         printf("leftprice = %e, rightprice = %e,leftrange = %e, rightrange =%e\n",
180             leftprice[i], rightprice[i], leftrange[i], rightrange[i]);
181 }
182
183 MSK_deletetask(&task);
184 }
185 MSK_deleteenv(&env);
186
187 printf("Return code: %d (0 means no error occured.)\n",r);
188
189 return ( r );
190 } /* main */

```

```

* A comment
BOUNDS CONSTRAINTS
U|L|LU [cname1]
U|L|LU [cname2]-[cname3]
BOUNDS VARIABLES
U|L|LU [vname1]
U|L|LU [vname2]-[vname3]
OBJECTIVE VARIABLES
[vname1]
[vname2]-[vname3]

```

Figure 15.3: The sensitivity analysis file format.

15.6 Sensitivity analysis with the command line tool

A sensitivity analysis can be performed with the MOSEK command line tool using the command

```
mosek myproblem.mps -sen sensitivity.ssp
```

where `sensitivity.ssp` is a file in the format described in the next section. The `ssp` file describes which parts of the problem the sensitivity analysis should be performed on.

By default results are written to a file named `myproblem.sen`. If necessary, this filename can be changed by setting the

```
MSK_SPAR_SENSITIVITY_RES_FILE_NAME
```

parameter. By default a basis type sensitivity analysis is performed. However, the type of sensitivity analysis (basis or optimal partition) can be changed by setting the parameter

```
MSK_IPAR_SENSITIVITY_TYPE
```

appropriately. Following values are accepted for this parameter:

- `MSK_SENSITIVITY_TYPE_BASIS`
- `MSK_SENSITIVITY_TYPE_OPTIMAL_PARTITION`

It is also possible to use the command line

```
mosek myproblem.mps -d MSK_IPAR_SENSITIVITY_ALL MSK_ON
```

in which case a sensitivity analysis on all the parameters is performed.

15.6.1 Sensitivity analysis specification file

MOSEK employs an MPS like file format to specify on which model parameters the sensitivity analysis should be performed. As the optimal partition type sensitivity analysis can be computationally expensive it is important to limit the sensitivity analysis. The format of the sensitivity specification file is shown in figure 15.3, where capitalized names are keywords, and names in brackets are names of the constraints and variables to be included in the analysis.

The sensitivity specification file has three sections, i.e.

- **BOUNDS CONSTRAINTS:** Specifies on which bounds on constraints the sensitivity analysis should be performed.
- **BOUNDS VARIABLES:** Specifies on which bounds on variables the sensitivity analysis should be performed.
- **OBJECTIVE VARIABLES:** Specifies on which objective coefficients the sensitivity analysis should be performed.

A line in the body of a section must begin with a whitespace. In the **BOUNDS** sections one of the keys L, U, and LU must appear next. These keys specify whether the sensitivity analysis is performed on the lower bound, on the upper bound, or on both the lower and the upper bound respectively. Next, a single constraint (variable) or range of constraints (variables) is specified.

Recall from Section 15.4.1.1 that equality constraints are handled in a special way. Sensitivity analysis of an equality constraint can be specified with either L, U, or LU, all indicating the same, namely that upper and lower bounds (which are equal) are perturbed simultaneously.

As an example consider

```
BOUNDS CONSTRAINTS
L  "cons1"
U  "cons2"
LU "cons3"-"cons6"
```

which requests that sensitivity analysis is performed on the lower bound of the constraint named **cons1**, on the upper bound of the constraint named **cons2**, and on both lower and upper bound on the constraints named **cons3** to **cons6**.

It is allowed to use indexes instead of names, for instance

```
BOUNDS CONSTRAINTS
L  "cons1"
U  2
LU 3 - 6
```

The character "*" indicates that the line contains a comment and is ignored.

15.6.2 Example: Sensitivity analysis from command line

As an example consider the **sensitivity.ssp** file shown in Figure 15.4. The command

```
mosek transport.lp -sen sensitivity.ssp -d MSK_IPAR_SENSITIVITY_TYPE MSK_SENSITIVITY_TYPE_BASIS
```

produces the **transport.sen** file shown below.

```
BOUNDS CONSTRAINTS
INDEX  NAME          BOUND  LEFTRANGE  RIGHTRANGE  LEFTPRICE  RIGHTPRICE
0      c1             UP      -6.574875e-18  5.000000e+02  1.000000e+00  1.000000e+00
2      c3             UP      -6.574875e-18  5.000000e+02  1.000000e+00  1.000000e+00
3      c4             FIX      -5.000000e+02  6.574875e-18  2.000000e+00  2.000000e+00
4      c5             FIX      -1.000000e+02  6.574875e-18  3.000000e+00  3.000000e+00
5      c6             FIX      -5.000000e+02  6.574875e-18  3.000000e+00  3.000000e+00

BOUNDS VARIABLES
INDEX  NAME          BOUND  LEFTRANGE  RIGHTRANGE  LEFTPRICE  RIGHTPRICE
```

```

* Comment 1

BOUNDS CONSTRAINTS
U "c1"      * Analyze upper bound for constraint named c1
U 2         * Analyze upper bound for the second constraint
U 3-5       * Analyze upper bound for constraint number 3 to number 5

BOUNDS VARIABLES
L 2-4       * This section specifies which bounds on variables should be analyzed
L "x11"

OBJECTIVE VARIABLES
"x11"       * This section specifies which objective coefficients should be analyzed
2

```

Figure 15.4: Example of the sensitivity file format.

2	x23	L0	-6.574875e-18	5.000000e+02	2.000000e+00	2.000000e+00
3	x24	L0	-inf	5.000000e+02	0.000000e+00	0.000000e+00
4	x31	L0	-inf	5.000000e+02	0.000000e+00	0.000000e+00
0	x11	L0	-inf	3.000000e+02	0.000000e+00	0.000000e+00

OBJECTIVE VARIABLES						
INDEX	NAME	LEFTRANGE	RIGHTRANGE	LEFTPRICE	RIGHTPRICE	
0	x11	-inf	1.000000e+00	3.000000e+02	3.000000e+02	
2	x23	-2.000000e+00	+inf	0.000000e+00	0.000000e+00	

15.6.3 Controlling log output

Setting the parameter

```
MSK_IPAR_LOG_SENSITIVITY
```

to 1 or 0 (default) controls whether or not the results from sensitivity calculations are printed to the message stream.

The parameter

```
MSK_IPAR_LOG_SENSITIVITY_OPT
```

controls the amount of debug information on internal calculations from the sensitivity analysis.

Appendix A

API reference

This chapter lists all functionality in the MOSEK C API.

Type definitions

Operate on data associated with scalar variables

- `MSK_appendvars`
- `MSK_getnumvar`
- `MSK_putacol`
- `MSK_putaij`
- `MSK_putarow`
- `MSK_putcj`
- `MSK_putqcon`
- `MSK_putqconk`
- `MSK_putqobj`
- `MSK_putqobjij`
- `MSK_putvarbound`
- `MSK_putvartype`
- `MSK_removevars`

Operate on data associated with symmetric matrix variables

- `MSK_appendbarvars`
- `MSK_appendsparsesymmat`
- `MSK_putbaraij`
- `MSK_putbarcj`

Operate on data associated with the constraints

- `MSK_appendcons`
- `MSK_getnumcon`
- `MSK_putconbound`
- `MSK_removecons`

Operate on data associated with the conic constraints

- `MSK_appendcone`
- `MSK_putcone`
- `MSK_removecones`

Operate on data associated with objective.

- `MSK_putcfix`
- `MSK_putobjsense`

Naming

- `MSK_putbarvarname`
- `MSK_putconename`
- `MSK_putconname`
- `MSK_putobjname`
- `MSK_puttaskname`
- `MSK_putvarname`

Setting task parameter values

- `MSK_putdouparam`
- `MSK_putintparam`
- `MSK_putstrparam`

Optimization

- `MSK_optimize`
- `MSK_optimizeconcurrent`
- `MSK_optimizetrm`

Obtain information about the solutions.

- `MSK_getdualobj`
- `MSK_getdviolbarvar`
- `MSK_getdviolcon`

- `MSK_getdviolcones`
- `MSK_getdviolvar`
- `MSK_getprimalobj`
- `MSK_getprosta`
- `MSK_getpviolbarvar`
- `MSK_getpviolcon`
- `MSK_getpviolcones`
- `MSK_getpviolvar`
- `MSK_getsolsta`
- `MSK_getsolutioninfo`
- `MSK_solutiondef`

Obtaining solution values

- `MSK_getbarsj`
- `MSK_getbarxj`
- `MSK_getskcslice`
- `MSK_getskxslice`
- `MSK_getslcslice`
- `MSK_getslxslice`
- `MSK_getsnxslice`
- `MSK_getsucslice`
- `MSK_getsuxslice`
- `MSK_getxcslice`
- `MSK_getxxslice`
- `MSK_getyslice`

Inputting solution values

- `MSK_putbarsj`
- `MSK_putbarxj`
- `MSK_putskcslice`
- `MSK_putskxslice`
- `MSK_putslcslice`
- `MSK_putslxslice`
- `MSK_putsnxslice`
- `MSK_putsolution`
- `MSK_putsolutioni`

- `MSK_putsucslice`
- `MSK_putsuxslice`
- `MSK_putxcslice`
- `MSK_putxxslice`
- `MSK_putyslice`

Task management.

- `MSK_deletetask`
- `MSK_maketask`

Task diagnostics

- `MSK_checkconvexity`
- `MSK_getproptype`
- `MSK_optimizersummary`
- `MSK_printdata`
- `MSK_printparam`
- `MSK_solutionsummary`
- `MSK_updatesolutioninfo`

Reading and writing data files

- `MSK_readdata`
- `MSK_readsolution`
- `MSK_writedata`
- `MSK_writesolution`

Call-backs (put/get)

- `MSK_linkfunctotaskstream`
- `MSK_putcallbackfunc`
- `MSK_putnlfunc`
- `MSK_unlinkfuncfromtaskstream`

Bounds

- `MSK_putconboundlist`
- `MSK_putvarboundlist`

Output stream functions

- `MSK_linkfiletotaskstream`

- `MSK_linkfunctotaskstream`
- `MSK_unlinkfuncfromtaskstream`

Optimizer statistics

- `MSK_getdouinf`
- `MSK_getintinf`
- `MSK_getlintinf`

Diagnosing infeasibility

- `MSK_getinfeasiblesubproblem`
- `MSK_primalrepair`
- `MSK_relaxprimal`

Sensitivity analysis

- `MSK_dualsensitivity`
- `MSK_primalsensitivity`
- `MSK_sensitivityreport`

Management of the environment

- `MSK_deleteenv`
- `MSK_licensecleanup`
- `MSK_makeenv`
- `MSK_putlicensedebug`
- `MSK_putlicensepath`
- `MSK_putlicensewait`

Linear algebra utility functions for performing linear algebra operations

- `MSK_axpy`
- `MSK_dot`
- `MSK_gemm`
- `MSK_gemv`
- `MSK_potrf`
- `MSK_syeig`
- `MSK_syevd`
- `MSK_syrk`

Alphabetic list of functions

A.1 API type definitions

MSKboolean_t

A signed integer interpreted as a boolean value.

MSKenv_t

The MOSEK Environment type.

MSKint32t

Signed 32bit integer.

MSKint64t

Signed 64bit integer.

MSKrealt

The floating point type used by MOSEK.

MSKstring_t

The string type used by MOSEK. This is an UTF-8 encoded zero-terminated char string.

MSKtask_t

The MOSEK Task type.

MSKuserhandle_t

A pointer to a generic user-defined structure.

MSKwchart

Wide char type. The actual type may differ depending on the platform; it is either a 16 or 32 bits signed or unsigned integer.

MSKcallbackfunc

```
MSKint32t MSKcallbackfunc (
    MSKtask_t          task,
    MSKuserhandle_t    usrptr,
    MSKcallbackcodee    caller,
    MSKCONST MSKrealt *  douinf,
    MSKCONST MSKint32t * intinf,
    MSKCONST MSKint64t * lintinf);
```

The progress call-back function is a user-defined function which will be called by MOSEK occasionally during the optimization process. In particular, the call-back function is called at the beginning of each iteration in the interior-point optimizer. For the simplex optimizers **MSK_IPAR_LOG_SIM_FREQ** controls how frequently the call-back is called.

The call-back provides an integer denoting the point in the solver from which the call happened, and a set of arrays containing information items related to the current state of the solver.

Typically the user-defined call-back function displays information about the solution process. The call-back function can also be used to terminate the optimization process since if the progress call-back function returns a non-zero value, the optimization process is aborted. The user *must not* call any MOSEK function directly or indirectly from the call-back function.

task (input)

An optimization task.

usrptr (input/output)

A pointer to a user-defined structure.

caller (input)

An integer which tells where the function was called from. See section [MSKcallbackcodee](#) for the possible values of this argument.

douinf (input)

An array of doubles. The elements correspond to the definitions in [MSKdinfiteme](#).

intinf (input)

An array of doubles. The elements correspond to the definitions in [MSKiinfiteme](#).

lintinf (input)

An array of doubles. The elements correspond to the definitions in [MSKliinfiteme](#).

MSKcallocfunc

```
void * MSKcallocfunc (
    MSKuserhandle_t  usrptr,
    MSKCONST size_t  num,
    MSKCONST size_t  size);
```

A user-defined memory allocation function. The function must be compatible with the C calloc function.

usrptr (input)

A pointer to a user-defined structure.

num (input)

The number of elements.

size (input)

The number of elements.

MSKexitfunc

```
void MSKexitfunc (
    MSKuserhandle_t  usrptr,
    MSKCONST char *  file,
    MSKint32t        line,
    MSKCONST char *  msg);
```

A user-defined exit function which is called in case of fatal errors to handle an error message and terminate the program. The function should never return.

usrptr (input/output)

A pointer to a user-defined structure.

file (input)

The name of the file where the fatal error occurred.

line (input)

The line number in the file where the fatal error occurred.

msg (input)

A message about the error.

MSKfreefunc

```
void MSKfreefunc (
    MSKuserhandle_t  usrptr,
    void *           buffer);
```

A user-defined memory freeing function.

usrptr (input)

A pointer to a user-defined structure.

buffer (input/output)

A pointer to the buffer which should be freed.

MSKmallocfunc

```
void * MSKmallocfunc (
    MSKuserhandle_t  usrptr,
    MSKCONST size_t  size);
```

A user-defined memory allocation function.

usrptr (input)

A pointer to a user-defined structure.

size (input)

The number of characters to allocate.

MSKnlgetspfunc

```
MSKint32t MSKnlgetspfunc (
    MSKuserhandle_t      nlhandle,
    MSKint32t *          numgrdobjnz,
    MSKint32t *          grdobjsub,
    MSKint32t            i,
    MSKboolean *         convali,
    MSKint32t *          grdconinz,
    MSKint32t *          grdconisub,
    MSKint32t            yo,
    MSKint32t            numycnz,
```



```

MSKCONST MSKint32t * ysub,
MSKint32t          maxnumhesnz,
MSKint32t *        numhesnz,
MSKint32t *        hessubi,
MSKint32t *        hessubj);

```

Type definition of the call-back function which is used to provide structural information about the nonlinear functions f and g in the optimization problem.

Hence, it is the user's responsibility to provide a function satisfying the definition. The function is inputted to MOSEK using the API function `MSK_putnlfunc`.

The user *must not* call any MOSEK function directly or indirectly from the call-back function.

nlhandle (input/output)

A pointer to a user-defined data structure specified when the function is attached to a task using the function `MSK_putnlfunc`.

numgrdobjnz (output)

If requested, `numgrdobjnz` should be assigned the number of non-zero elements in the gradient of f .

grdobjsub (output)

If requested, put here the positions of the non-zero elements in the gradient of f . The elements are stored in

$$\text{grdobjsub}[0, \dots, \text{numgrdobjnz} - 1].$$

i (input)

Index of a constraint. If $i < 0$ or $i \geq \text{numcon}$, no information about a constraint is requested.

convali (output)

If requested, assign a true/false value indicating if constraint `i` contains general non-linear terms.

grdconinz (output)

If requested, `grdconinz` shall be assigned the number of non-zero elements in $\nabla g_i(x)$.

grdconisub (output)

If requested, this array shall contain the indexes of the non-zeros in $\nabla g_i(x)$. The length of the array must be the same as given in `grdconinz`.

yo (input)

If non-zero, then the f shall be included when the gradient and the Hessian of the Lagrangian are computed.

numycnz (input)

Number of constraint functions which are included in the definition of the Lagrangian. See (A.1).

ysub (input)

Index of constraint functions which are included in the definition of the Lagrangian. See (A.1).

maxnumhesnz (input)

Length of the arguments `hessubi` and `hessubj`.

numhesnz (output)

If requested, **numhesnz** should be assigned the number of non-zero elements in the lower triangular part of the Hessian of the Lagrangian:

$$L := yof(x) - \sum_{k=0}^{numycnz-1} g_{ycsub[k]}(x). \quad (\text{A.1})$$

hessubi (output)

If requested, **hessubi** and **hessubj** are used to convey the position of the non-zeros in the Hessian of the Lagrangian L (see (A.1)) as follows

$$\nabla^2 L_{\text{hessubi}[k], \text{hessubj}[k]}(x) \neq 0.0$$

for $k = 0, \dots, \text{numhesnz} - 1$. All other positions in L are assumed to be zero. Please note that *only* the lower *or* the upper triangular part of the Hessian should be return.

hessubj (output)

See the argument **hessubi**.

MSKnlgetvafunc

```
MSKint32t MSKnlgetvafunc (
    MSKuserhandle_t    nlhandle,
    MSKCONST MSKrealt * xx,
    MSKrealt           yo,
    MSKCONST MSKrealt * yc,
    MSKrealt *         objval,
    MSKint32t *         numgrdobjnz,
    MSKint32t *         grdobjsub,
    MSKrealt *         grdobjval,
    MSKint32t          numi,
    MSKCONST MSKint32t * subi,
    MSKrealt *         conval,
    MSKCONST MSKint32t * grdconptrb,
    MSKCONST MSKint32t * grdconptre,
    MSKCONST MSKint32t * grdconsub,
    MSKrealt *         grdconval,
    MSKrealt *         grdlag,
    MSKint32t          maxnumhesnz,
    MSKint32t *         numhesnz,
    MSKint32t *         hessubi,
    MSKint32t *         hessubj,
    MSKrealt *         hesval);
```

Type definition of the call-back function which is used to provide structural and numerical information about the nonlinear functions f and g in an optimization problem.

For later use we need the definition of the Lagrangian L which is given by

$$L := yof(\mathbf{xx}) - \sum_{k=0}^{numi-1} y_{c_{\text{subi}[k]}} g_{\text{subi}[k]}(\mathbf{xx}). \quad (\text{A.2})$$

The user *must not* call any MOSEK function directly or indirectly from the call-back function.

nlhandle (input/output)

A pointer to a user-defined data structure. The pointer is passed to MOSEK when the function **MSK_putnlfunc** is called.

xx (input)

The point at which the nonlinear function must be evaluated. The length equals the number of variables in the task.

yo (input)

Multiplier on the objective function f .

yc (input)

Multipliers for the constraint functions g_i . The length is **numcon**.

objval (output)

If requested, **objval** shall be assigned the value of f evaluated at **xx**.

numgrdobjnz (output)

If requested, **numgrdobjnz** shall be assigned the number of non-zero elements in the gradient of f .

grdobjsub (output)

If requested, it shall contain the position of the non-zero elements in the gradient of f . The elements are stored in

$$\text{grdobjsub}[0, \dots, \text{numgrdobjnz} - 1].$$

%

grdobjval (output)

If requested, it shall contain the the gradient of f evaluated at **xx**. The following data structure

$$\text{grdobjval}[k] = \frac{\partial f}{\partial x_{\text{grdobjsub}[k]}}(\text{xx})$$

for $k = 0, \dots, \text{numgrdobjnz} - 1$ is used.

numi (input)

Number of elements in **subi**.

subi (input)

subi[0, ..., **numi** - 1] contain the indexes of the constraints that has to be evaluated. The length is **numi**.

conval (output)

$g(\text{xx})$ for the required constraint functions i.e.

$$\text{conval}[k] = g_{\text{subi}[k]}(\text{xx})$$

for $k = 0, \dots, \text{numi} - 1$.

grdconptrb (input)

If given, it specifies the structure of the gradients of the constraint functions. See the argument **grdconval** for details.

grdconptre (input)

If given, it specifies the structure of the gradients of the constraint functions. See the argument **grdconval** for details.

grdconsub (input)

It specifies the positions of the non-zeros in the gradients of the constraints. See the argument **grdconval** for details.

grdconval (output)

If requested, it shall specify the values of the gradient of the nonlinear constraints.

Together **grdconptrb**, **grdconptre**, **grdconsub** and **grdconval** are used to specify the gradients of the nonlinear constraint functions.

The gradient data is stored as follows

$$\text{grdconval}[k] = \frac{\partial g_{\text{subi}[i]}(xx)}{\partial xx_{\text{grdconsub}[k]}}, \quad \text{for} \\ k = \text{grdconptrb}[i], \dots, \text{grdconptre}[i] - 1, \\ i = 0, \dots, \text{numi} - 1.$$

grdlag (output)

If requested, **grdlag** shall contain the gradient of the Lagrangian function, i.e.

$$\text{grdlag} = \nabla L.$$

maxnumhesnz (input)

Maximum number of non-zeros in the Hessian of the Lagrangian, i.e. **maxnumhesnz** is the length of the arrays **hessubi**, **hessubj**, and **hesval**.

numhesnz (output)

If requested, **numhesnz** shall be assigned the number of non-zeros elements in the Hessian of the Lagrangian L . See (A.2).

hessubi (output)

See the argument **hesval**.

hessubj (output)

See the argument **hesval**.

hesval (output)

Together **hessubi**, **hessubj**, and **hesval** specify the Hessian of the Lagrangian function L defined in (A.2).

The Hessian is stored in the following format:

$$\text{hesval}[k] = \nabla^2 L_{\min(\text{hessubi}[k], \text{hessubj}[k]), \max(\text{hessubi}[k], \text{hessubj}[k])}$$

for $k = 0, \dots, \text{numhesnz}[0] - 1$. Please note that if an element is specified multiple times, then the elements are added together. Hence, *only* the lower or the upper triangular part of the Hessian should be returned.

MSKreallocfunc

```
void * MSKreallocfunc (
```

```

MSKuserhandle_t  usrptr,
void *          ptr,
MSKCONST size_t  size);

```

A user-defined memory allocation function. The function must be compatible with the C `realloc` function.

usrptr (input)
A pointer to a user-defined structure.

ptr (input/output)
The pointer to reallocated.

size (input)
Size of the new block.

MSKresponsefunc

```

MSKrescodee MSKresponsefunc (
    MSKuserhandle_t  handle,
    MSKrescodee      r,
    MSKCONST char *  msg);

```

Whenever MOSEK generate a warning or an error this function is called. The argument `r` contains the code of the error/warning and the argument `msg` contains the corresponding error/warning message. This function should always return `MSK_RES_OK`.

handle (input/output)
A pointer to a user-defined data structure or NULL.

r (input)
The response code corresponding to the exception.

msg (input)
A string containing the exception message.

MSKstreamfunc

```

void MSKstreamfunc (
    MSKuserhandle_t  handle,
    MSKCONST char *  str);

```

A function of this type can be linked to any of the MOSEK streams. This implies that if a message is send to the stream to which the function is linked, the function is called by MOSEK and the argument `str` will contain the message. Hence, the user can decide what should happen to message.

The user *must not* call any MOSEK function directly or indirectly from the call-back function.

handle (input/output)
A pointer to a user-defined data structure (or a null pointer).

str (input)
A string containing a message to a stream.

A.2 All functions by name

`MSK_analyzenames`

Analyze the names and issue an error for the first invalid name.

`MSK_analyzeproblem`

Analyze the data of a task.

`MSK_analyzesolution`

Print information related to the quality of the solution.

`MSK_appendbarvars`

Appends a semidefinite variable of dimension `dim` to the problem.

`MSK_appendcone`

Appends a new cone constraint to the problem.

`MSK_appendconeseq`

Appends a new conic constraint to the problem.

`MSK_appendconesseq`

Appends multiple conic constraints to the problem.

`MSK_appendcons`

Appends a number of constraints to the optimization task.

`MSK_appendsparsesymmat`

Appends a general sparse symmetric matrix to the vector `E` of symmetric matrixes.

`MSK_appendstat`

Appends a record the statistics file.

`MSK_appendvars`

Appends a number of variables to the optimization task.

`MSK_axpy`

Adds α times `x` to `y`.

`MSK_basiscond`

Computes conditioning information for the basis matrix.

`MSK_bktostr`

Obtains a bound key string identifier.

`MSK_callbackcodetostr`

Obtains a call-back code string identifier.

MSK_callocdbgenv

A replacement for the system calloc function.

MSK_callocdbgtask

A replacement for the system calloc function.

MSK_callocenv

A replacement for the system calloc function.

MSK_calloctask

A replacement for the system calloc function.

MSK_checkconvexity

Checks if a quadratic optimization problem is convex.

MSK_checkinlicense

Check in a license feature from the license server ahead of time.

MSK_checkmemenv

Checks the memory allocated by the environment.

MSK_checkmentask

Checks the memory allocated by the task.

MSK_checkoutlicense

Check out a license feature from the license server ahead of time.

MSK_checkversion

Compares a version of the MOSEK DLL with a specified version.

MSK_chgbound

Changes the bounds for one constraint or variable.

MSK_clonetask

Creates a clone of an existing task.

MSK_commitchanges

Commits all cached problem changes.

MSK_conetypetostr

Obtains a cone type string identifier.

MSK_deleteenv

Delete a MOSEK environment.

MSK_deletesolution

Undefines a solution and frees the memory it uses.

MSK_deletetask

Deletes an optimization task.

MSK_dot

Computes the inner product of two vectors.

MSK_dualsensitivity

Performs sensitivity analysis on objective coefficients.

MSK_echoenv

Sends a message to a given environment stream.

MSK_echointro

Prints an intro to message stream.

MSK_echotask

Prints a format string to a task stream.

MSK_freedbgenv

Frees space allocated by MOSEK.

MSK_freedbgtask

Frees space allocated by MOSEK.

MSK_freeenv

Frees space allocated by MOSEK.

MSK_freetask

Frees space allocated by MOSEK.

MSK_gemm

Performs a dense matrix multiplication.

MSK_gemv

Computes dense matrix times a dense vector product.

MSK_getacol

Obtains one column of the linear constraint matrix.

MSK_getacolnumnz

Obtains the number of non-zero elements in one column of the linear constraint matrix

MSK_getacolslicetrip

Obtains a sequence of columns from the coefficient matrix in triplet format.

MSK_getaij

Obtains a single coefficient in linear constraint matrix.

MSK_getapieceenumnz

Obtains the number non-zeros in a rectangular piece of the linear constraint matrix.

MSK_getarow

Obtains one row of the linear constraint matrix.

MSK_getarownumnz

Obtains the number of non-zero elements in one row of the linear constraint matrix

MSK_getarowslicetrip

Obtains a sequence of rows from the coefficient matrix in triplet format.

MSK_getaslice

Obtains a sequence of rows or columns from the coefficient matrix.

MSK_getaslice64

Obtains a sequence of rows or columns from the coefficient matrix.

MSK_getaslicenumnz

Obtains the number of non-zeros in a row or column slice of the coefficient matrix.

MSK_getaslicenumnz64

Obtains the number of non-zeros in a slice of rows or columns of the coefficient matrix.

MSK_getbarablocktriplet

Obtains barA in block triplet form.

MSK_getbaraidx

Obtains information about an element barA.

MSK_getbaraidxij

Obtains information about an element barA.

MSK_getbaraidxinfo

Obtains the number terms in the weighted sum that forms a particular element in barA.

MSK_getbarasparsity

Obtains the sparsity pattern of the barA matrix.

MSK_getbarcblocktriplet

Obtains barc in block triplet form.

MSK_getbarcidx

Obtains information about an element in barc.

MSK_getbarcidxinfo

Obtains information about an element in barc.

MSK_getbarcidxj

Obtains the row index of an element in barc.

MSK_getbarcsparsity

Get the positions of the nonzero elements in barc.

MSK_getbarsj

Obtains the dual solution for a semidefinite variable.

MSK_getbarvarname

Obtains a name of a semidefinite variable.

MSK_getbarvarnameindex

Obtains the index of name of semidefinite variable.

MSK_getbarvarnamelen

Obtains the length of a name of a semidefinite variable.

MSK_getbarxj

Obtains the primal solution for a semidefinite variable.

MSK_getbound

Obtains bound information for one constraint or variable.

MSK_getboundslice

Obtains bounds information for a sequence of variables or constraints.

MSK_getbuildinfo

Obtains build information.

MSK_getc

Obtains all objective coefficients.

MSK_getcallbackfunc

Obtains the call-back function and the associated user handle.

MSK_getcfix

Obtains the fixed term in the objective.

MSK_getcj

Obtains one coefficient of c.

MSK_getcodedesc

Obtains a short description of a response code.

MSK_getconbound

Obtains bound information for one constraint.

MSK_getconboundslice

Obtains bounds information for a slice of the constraints.

MSK_getcone

Obtains a conic constraint.

MSK_getconeinfo

Obtains information about a conic constraint.

MSK_getconename

Obtains a name of a cone.

MSK_getconenameindex

Checks whether the name somename has been assigned to any cone.

MSK_getconenamelen

Obtains the length of a name of a cone.

MSK_getconname

Obtains a name of a constraint.

MSK_getconnameindex

Checks whether the name somename has been assigned to any constraint.

MSK_getconnamelen

Obtains the length of a name of a constraint variable.

MSK_getcslice

Obtains a sequence of coefficients from the objective.

MSK_getdbi

Deprecated.

MSK_getdcni

Deprecated.

MSK_getdeqi

Deprecated.

MSK_getdimbarvarj

Obtains the dimension of a symmetric matrix variable.

MSK_getdouinf

Obtains a double information item.

MSK_getdoupam

Obtains a double parameter.

MSK_getdualobj

Computes the dual objective value associated with the solution.

MSK_getdviolbarvar

Computes the violation of dual solution for a set of barx variables.

MSK_getdviolcon

Computes the violation of a dual solution associated with a set of constraints.

MSK_getdviolcones

Computes the violation of a solution for set of dual conic constraints.

MSK_getdviolvar

Computes the violation of a dual solution associated with a set of x variables.

MSK_getenv

Obtains the environment used to create the task.

MSK_getglbdlname

Obtains the name of the global optimizer DLL.

MSK_getinfeasiblesubproblem

Obtains an infeasible sub problem.

MSK_getinfindex

Obtains the index of a named information item.

MSK_getinfmax

Obtains the maximum index of an information of a given type inftype plus 1.

MSK_getinfname

Obtains the name of an information item.

MSK_getinti

Deprecated.

MSK_getintinf

Obtains an integer information item.

MSK_getintparam

Obtains an integer parameter.

MSK_getlasterror

Obtains the last error code and error message reported in MOSEK.

MSK_getlasterror64

Obtains the last error code and error message reported in MOSEK.

MSK_getlenbarvarj

Obtains the length of the j 'th semidefinite variables.

MSK_getlintinf

Obtains an integer information item.

MSK_getmaxnamelen

Obtains the maximum length (not including terminating zero character) of any objective, constraint, variable or cone name.

MSK_getmaxnumanz

Obtains number of preallocated non-zeros in the linear constraint matrix.

MSK_getmaxnumanz64

Obtains number of preallocated non-zeros in the linear constraint matrix.

MSK_getmaxnumbarvar

Obtains the number of semidefinite variables.

MSK_getmaxnumcon

Obtains the number of preallocated constraints in the optimization task.

MSK_getmaxnumcone

Obtains the number of preallocated cones in the optimization task.

MSK_getmaxnumqnz

Obtains the number of preallocated non-zeros for all quadratic terms in objective and constraints.

MSK_getmaxnumqnz64

Obtains the number of preallocated non-zeros for all quadratic terms in objective and constraints.

MSK_getmaxnumvar

Obtains the maximum number variables allowed.

MSK_getmemusagetask

Obtains information about the amount of memory used by a task.

MSK_getnadouinf

Obtains a double information item.

MSK_getnadouparam

Obtains a double parameter.

MSK_getnaintinf

Obtains an integer information item.

MSK_getnaintparam

Obtains an integer parameter.

MSK_getnastrparam

Obtains a string parameter.

MSK_getnastrparamal

Obtains the value of a string parameter.

MSK_getnlfunc

Gets nonlinear call-back functions.

MSK_getnumanz

Obtains the number of non-zeros in the coefficient matrix.

MSK_getnumanz64

Obtains the number of non-zeros in the coefficient matrix.

MSK_getnumbarablocktriplets

Obtains an upper bound on the number of scalar elements in the block triplet form of bara.

MSK_getnumbaranz

Get the number of nonzero elements in barA.

MSK_getnumbarcblocktriplets

Obtains an upper bound on the number of elements in the block triplet form of barc.

MSK_getnumbarcnz

Obtains the number of nonzero elements in barc.

MSK_getnumbarvar

Obtains the number of semidefinite variables.

MSK_getnumcon

Obtains the number of constraints.

MSK_getnumcone

Obtains the number of cones.

MSK_getnumconemem

Obtains the number of members in a cone.

MSK_getnumintvar

Obtains the number of integer-constrained variables.

MSK_getnumparam

Obtains the number of parameters of a given type.

MSK_getnumqconknz

Obtains the number of non-zero quadratic terms in a constraint.

MSK_getnumqconknz64

Obtains the number of non-zero quadratic terms in a constraint.

MSK_getnumqobjnz

Obtains the number of non-zero quadratic terms in the objective.

MSK_getnumqobjnz64

Obtains the number of non-zero quadratic terms in the objective.

MSK_getnumsymmat

Get the number of symmetric matrixes stored.

MSK_getnumvar

Obtains the number of variables.

MSK_getobjname

Obtains the name assigned to the objective function.

MSK_getobjnamelen

Obtains the length of the name assigned to the objective function.

MSK_getobjsense

Gets the objective sense.

MSK_getparammax

Obtains the maximum index of a parameter of a given type plus 1.

MSK_getparamname

Obtains the name of a parameter.

MSK_getpbi

Deprecated.

MSK_getpcni

Deprecated.

MSK_getpeqi

Deprecated.

MSK_getprimalobj

Computes the primal objective value for the desired solution.

MSK_getprobtype

Obtains the problem type.

MSK_getprosta

Obtains the problem status.

MSK_getpviolbarvar

Computes the violation of a primal solution for a list of barx variables.

MSK_getpviolcon

Computes the violation of a primal solution for a list of xc variables.

MSK_getpviolcones

Computes the violation of a solution for set of conic constraints.

MSK_getpviolvar

Computes the violation of a primal solution for a list of x variables.

MSK_getqconk

Obtains all the quadratic terms in a constraint.

MSK_getqconk64

Obtains all the quadratic terms in a constraint.

MSK_getqobj

Obtains all the quadratic terms in the objective.

MSK_getqobj64

Obtains all the quadratic terms in the objective.

MSK_getqobjij

Obtains one coefficient from the quadratic term of the objective

MSK_getreducedcosts

Obtains the difference of (slx-sux) for a sequence of variables.

MSK_getresponseclass

Obtain the class of a response code.

MSK_getskc

Obtains the status keys for the constraints.

MSK_getskcslice

Obtains the status keys for the constraints.

MSK_getskx

Obtains the status keys for the scalar variables.

MSK_getskxslice

Obtains the status keys for the variables.

MSK_getslc

Obtains the slc vector for a solution.

MSK_getslcslice

Obtains a slice of the slc vector for a solution.

MSK_getslx

Obtains the slx vector for a solution.

MSK_getslxslice

Obtains a slice of the slx vector for a solution.

MSK_getsnx

Obtains the snx vector for a solution.

MSK_getsnxslice

Obtains a slice of the snx vector for a solution.

MSK_getsolsta

Obtains the solution status.

MSK_getsolution

Obtains the complete solution.

MSK_getsolutioni

Obtains the solution for a single constraint or variable.

MSK_getsolutionincallback

Obtains the whole or a part of the solution from the progress call-back function.

MSK_getsolutioninf

Deprecated

MSK_getsolutioninfo

Obtains information about of a solution.

MSK_getsolutionslice

Obtains a slice of the solution.

MSK_getsparsesymmat

Gets a single symmetric matrix from the matrix store.

MSK_getstrparam

Obtains the value of a string parameter.

MSK_getstrparamal

Obtains the value a string parameter.

MSK_getstrparamlen

Obtains the length of a string parameter.

MSK_getsuc

Obtains the suc vector for a solution.

MSK_getsucslice

Obtains a slice of the suc vector for a solution.

MSK_getsux

Obtains the sux vector for a solution.

MSK_getsuxslice

Obtains a slice of the sux vector for a solution.

MSK_getsymbcon

Obtains a cone type string identifier.

MSK_getsymbcondim

Obtains dimensional information for the defined symbolic constants.

MSK_getsymmatinfo

Obtains information of a matrix from the symmetric matrix storage E.

MSK_gettaskname

Obtains the task name.

MSK_gettasknamelen

Obtains the length the task name.

MSK_getvarbound

Obtains bound information for one variable.

MSK_getvarboundslice

Obtains bounds information for a slice of the variables.

MSK_getvarbranchdir

Obtains the branching direction for a variable.

MSK_getvarbranchorder

Obtains the branching priority for a variable.

MSK_getvarbranchpri

Obtains the branching priority for a variable.

MSK_getvarname

Obtains a name of a variable.

MSK_getvarnameindex

Checks whether the name *somename* has been assigned to any variable.

MSK_getvarnamelen

Obtains the length of a name of a variable *variable*.

MSK_getvartype

Gets the variable type of one variable.

MSK_getvartypelist

Obtains the variable type for one or more variables.

MSK_getversion

Obtains MOSEK version information.

MSK_getxc

Obtains the xc vector for a solution.

MSK_getxcslice

Obtains a slice of the xc vector for a solution.

MSK_getxx

Obtains the xx vector for a solution.

MSK_getxxslice

Obtains a slice of the xx vector for a solution.

MSK_gety

Obtains the y vector for a solution.

MSK_getyslice

Obtains a slice of the y vector for a solution.

MSK_initbasissolve

Prepare a task for basis solver.

MSK_initenv

Initialize a MOSEK environment.

MSK_inputdata

Input the linear part of an optimization task in one function call.

MSK_inputdata64

Input the linear part of an optimization task in one function call.

MSK_iparvaltosymnam

Obtains the symbolic name corresponding to a value that can be assigned to an integer parameter.

MSK_isdouponname

Checks a double parameter name.

MSK_isinfinity

Return true if value considered infinity by MOSEK.

MSK_isintparname

Checks an integer parameter name.

MSK_isstrparname

Checks a string parameter name.

MSK_licensecleanup

Stops all threads and delete all handles used by the license system.

MSK_linkfiletoenvstream

Directs all output from a stream to a file.

MSK_linkfiletotaskstream

Directs all output from a task stream to a file.

MSK_linkfunctoenvstream

Connects a user-defined function to a stream.

MSK_linkfunctotaskstream

Connects a user-defined function to a task stream.

MSK_makeemptytask

Creates a new and empty optimization task.

MSK_makeenv

Creates a new MOSEK environment.

MSK_makeenvalloc

Creates a new MOSEK environment.

MSK_maketask

Creates a new optimization task.

MSK_onesolutionsummary

Prints a short summary for the specified solution.

MSK_optimize

Optimizes the problem.

MSK_optimizeconcurrent

Optimize a given task with several optimizers concurrently.

MSK_optimizersummary

Prints a short summary with optimizer statistics for last optimization.

MSK_optimizetrm

Optimizes the problem.

MSK_potrf

Computes a Cholesky factorization a dense matrix.

MSK_primalrepair

The function repairs a primal infeasible optimization problem by adjusting the bounds on the constraints and variables.

MSK_primalsensitivity

Perform sensitivity analysis on bounds.

MSK_printdata

Prints a part of the problem data to a stream.

MSK_printparam

Prints the current parameter settings.

MSK_probtypetostr

Obtains a string containing the name of a problem type given.

MSK_prostatostr

Obtains a string containing the name of a problem status given.

MSK_putacol

Replaces all elements in one column of A.

MSK_putacollist

Replaces all elements in several columns the linear constraint matrix by new values.

MSK_putacollist64

Replaces all elements in several columns the linear constraint matrix by new values.

MSK_putacolslice

Replaces all elements in several columns the linear constraint matrix by new values.

MSK_putacolslice64

Replaces all elements in several columns the linear constraint matrix by new values.

MSK_putaij

Changes a single value in the linear coefficient matrix.

MSK_putaijlist

Changes one or more coefficients in the linear constraint matrix.

MSK_putaijlist64

Changes one or more coefficients in the linear constraint matrix.

MSK_putarow

Replaces all elements in one row of A.

MSK_putarowlist

Replaces all elements in several rows the linear constraint matrix by new values.

MSK_putarowlist64

Replaces all elements in several rows the linear constraint matrix by new values.

MSK_putarowslice

Replaces all elements in several rows the linear constraint matrix by new values.

MSK_putarowslice64

Replaces all elements in several rows the linear constraint matrix by new values.

MSK_putbarablocktriplet

Inputs barA in block triplet form.

MSK_putbaraij

Inputs an element of barA.

MSK_putbarcblocktriplet

Inputs barC in block triplet form.

MSK_putbarcj

Changes one element in barc.

MSK_putbarsj

Sets the dual solution for a semidefinite variable.

MSK_putbarvarname

Puts the name of a semidefinite variable.

MSK_putbarxj

Sets the primal solution for a semidefinite variable.

MSK_putbound

Changes the bound for either one constraint or one variable.

MSK_putboundlist

Changes the bounds of constraints or variables.

MSK.putboundslice

Modifies bounds.

MSK.putcallbackfunc

Input the progress call-back function.

MSK.putcfix

Replaces the fixed term in the objective.

MSK.putcj

Modifies one linear coefficient in the objective.

MSK.putclist

Modifies a part of the linear objective coefficients.

MSK.putconbound

Changes the bound for one constraint.

MSK.putconboundlist

Changes the bounds of a list of constraints.

MSK.putconboundslice

Changes the bounds for a slice of the constraints.

MSK.putcone

Replaces a conic constraint.

MSK.putconename

Puts the name of a cone.

MSK.putconname

Puts the name of a constraint.

MSK.putcslice

Modifies a slice of the linear objective coefficients.

MSK.putdllpath

Sets the path to the DLL/shared libraries that MOSEK is loading.

MSK.putdoupam

Sets a double parameter.

MSK.putexitfunc

Inputs a user-defined exit function which is called in case of fatal errors.

MSK.putintparam

Sets an integer parameter.

MSK_putkeepdlls

Controls whether explicitly loaded DLLs should be kept.

MSK_putlicensecode

The purpose of this function is to input a runtime license code.

MSK_putlicensedebug

Enables debug information for the license system.

MSK_putlicensepath

Set the path to the license file.

MSK_putlicensewait

Control whether mosek should wait for an available license if no license is available.

MSK_putmaxnumanz

The function changes the size of the preallocated storage for linear coefficients.

MSK_putmaxnumbarvar

Sets the number of preallocated symmetric matrix variables in the optimization task.

MSK_putmaxnumcon

Sets the number of preallocated constraints in the optimization task.

MSK_putmaxnumcone

Sets the number of preallocated conic constraints in the optimization task.

MSK_putmaxnumqnz

Changes the size of the preallocated storage for quadratic terms.

MSK_putmaxnumvar

Sets the number of preallocated variables in the optimization task.

MSK_putnadouparam

Sets a double parameter.

MSK_putnaintparam

Sets an integer parameter.

MSK_putnastrparam

Sets a string parameter.

MSK_putnlfunc

Inputs nonlinear function information.

MSK_putobjname

Assigns a new name to the objective.

MSK.putobjsense

Sets the objective sense.

MSK.putparam

Modifies the value of parameter.

MSK.putqcon

Replaces all quadratic terms in constraints.

MSK.putqconk

Replaces all quadratic terms in a single constraint.

MSK.putqobj

Replaces all quadratic terms in the objective.

MSK.putqobjij

Replaces one coefficient in the quadratic term in the objective.

MSK.putresponsefunc

Inputs a user-defined error call-back function.

MSK.putskc

Sets the status keys for the constraints.

MSK.putskcslice

Sets the status keys for the constraints.

MSK.putskx

Sets the status keys for the scalar variables.

MSK.putskxslice

Sets the status keys for the variables.

MSK.putslc

Sets the slc vector for a solution.

MSK.putslcslice

Sets a slice of the slc vector for a solution.

MSK.putslx

Sets the slx vector for a solution.

MSK.putslxslice

Sets a slice of the slx vector for a solution.

MSK.putsnx

Sets the snx vector for a solution.

MSK_putsnxslice

Sets a slice of the snx vector for a solution.

MSK_putsolution

Inserts a solution.

MSK_putsolutioni

Sets the primal and dual solution information for a single constraint or variable.

MSK_putsolutionyi

Inputs the dual variable of a solution.

MSK_putstrparam

Sets a string parameter.

MSK_putsuc

Sets the suc vector for a solution.

MSK_putsucslice

Sets a slice of the suc vector for a solution.

MSK_putsux

Sets the sux vector for a solution.

MSK_putsuxslice

Sets a slice of the sux vector for a solution.

MSK_puttaskname

Assigns a new name to the task.

MSK_putvarbound

Changes the bound for one variable.

MSK_putvarboundlist

Changes the bounds of a list of variables.

MSK_putvarboundslice

Changes the bounds for a slice of the variables.

MSK_putvarbranchorder

Assigns a branching priority and direction to a variable.

MSK_putvarname

Puts the name of a variable.

MSK_putvartype

Sets the variable type of one variable.

MSK.putvartypelist

Sets the variable type for one or more variables.

MSK.putxc

Sets the xc vector for a solution.

MSK.putxcslice

Sets a slice of the xc vector for a solution.

MSK.putxx

Sets the xx vector for a solution.

MSK.putxxslice

Obtains a slice of the xx vector for a solution.

MSK.puty

Sets the y vector for a solution.

MSK.putyslice

Sets a slice of the y vector for a solution.

MSK.readbranchpriorities

Reads branching priority data from a file.

MSK.readdata

Reads problem data from a file.

MSK.readdataautoformat

Reads problem data from a file.

MSK.readdataformat

Reads problem data from a file.

MSK.readparamfile

Reads a parameter file.

MSK.readsolution

Reads a solution from a file.

MSK.readsummary

Prints information about last file read.

MSK.readtask

Load task data from a file.

MSK.reformqcqotosocp

Reformulates a quadratic optimization problem to a conic quadratic problem.

MSK_relaxprimal

Deprecated.

MSK_removebarvars

The function removes a number of symmetric matrix.

MSK_removecones

Removes a conic constraint from the problem.

MSK_removecons

The function removes a number of constraints.

MSK_removevars

The function removes a number of variables.

MSK_resizetask

Resizes an optimization task.

MSK_sensitivityreport

Creates a sensitivity report.

MSK_setdefaults

Resets all parameters values.

MSK_sktostr

Obtains a status key string.

MSK_solstatostr

Obtains a solution status string.

MSK_solutiondef

Checks whether a solution is defined.

MSK_solutionsummary

Prints a short summary of the current solutions.

MSK_solvewithbasis

Solve a linear equation system involving a basis matrix.

MSK_startstat

Starts the statistics file.

MSK_stopstat

Stops the statistics file.

MSK_strdupbgenv

Make a copy of a string.

MSK_strdupdbgtask

Make a copy of a string.

MSK_strdupenv

Make a copy of a string.

MSK_strduptask

Make a copy of a string.

MSK_strtoconetype

Obtains a cone type code.

MSK_strtosk

Obtains a status key.

MSK_syeig

Computes all eigenvalues of a symmetric dense matrix.

MSK_syevd

Computes all the eigenvalue and eigenvectors of a symmetric dense matrix, and thus its eigenvalue decomposition.

MSK_symnamtovalue

Obtains the value corresponding to a symbolic name defined by MOSEK.

MSK_syrk

Performs a rank-k update of a symmetric matrix.

MSK_toconic

Inplace reformulation of a QCQP to a COP

MSK_unlinkfuncfromenvstream

Disconnects a user-defined function from a stream.

MSK_unlinkfuncfromtaskstream

Disconnects a user-defined function from a task stream.

MSK_updatesolutioninfo

Update the information items related to the solution.

MSK_utf8towchar

Converts an UTF8 string to a wchar string.

MSK_wchartoutf8

Converts a wchar string to an UTF8 string.

MSK.whichparam

Checks a parameter name.

MSK.writebranchpriorities

Writes branching priority data to a file.

MSK.writedata

Writes problem data to a file.

MSK.writeparamfile

Writes all the parameters to a parameter file.

MSK.writesolution

Write a solution to a file.

MSK.writetask

Write a complete binary dump of the task data.

A.2.1 MSK.analyzenames()

```
MSKrescode MSK.analyzenames (
    MSKtask_t      task,
    MSKstreamtypee whichstream,
    MSKnametypee   nametype);
```

Analyze the names and issue an error for the first invalid name.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

nametype

The type of names e.g. valid in MPS or LP files.

The function analyzes the names and issue an error if a name is invalid.

A.2.2 MSK_analyzeproblem()

```
MSKrescodee MSK_analyzeproblem (
    MSKtask_t      task,
    MSKstreamtypee whichstream);
```

Analyze the data of a task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

The function analyzes the data of task and writes out a report.

A.2.3 MSK_analyzesolution()

```
MSKrescodee MSK_analyzesolution (
    MSKtask_t      task,
    MSKstreamtypee whichstream,
    MSKsoltypee    whichsol);
```

Print information related to the quality of the solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

whichsol

Selects a solution.

Print information related to the quality of the solution and other solution statistics.

By default this function prints information about the largest infeasibilities in the solution, the primal (and possibly dual) objective value and the solution status.

Following parameters can be used to configure the printed statistics:

- **MSK_IPAR_ANA_SOL_BASIS**. Enables or disables printing of statistics specific to the basis solution (condition number, number of basic variables etc.). Default is on.

- **MSK_IPAR_ANA_SOL_PRINT_VIOLATED**. Enables or disables listing names of all constraints (both primal and dual) which are violated by the solution. Default is off.
- **MSK_DPAR_ANA_SOL_INFEAS_TOL**. The tolerance defining when a constraint is considered violated. If a constraint is violated more than this, it will be listed in the summary.

See also

- **MSK_getpviolcon** Computes the violation of a primal solution for a list of xc variables.
- **MSK_getpviolvar** Computes the violation of a primal solution for a list of x variables.
- **MSK_getpviolbarvar** Computes the violation of a primal solution for a list of barx variables.
- **MSK_getpviolcones** Computes the violation of a solution for set of conic constraints.
- **MSK_getdviolcon** Computes the violation of a dual solution associated with a set of constraints.
- **MSK_getdviolvar** Computes the violation of a dual solution associated with a set of x variables.
- **MSK_getdviolbarvar** Computes the violation of dual solution for a set of barx variables.
- **MSK_getdviolcones** Computes the violation of a solution for set of dual conic constraints.
- **MSK_IPAR_ANA_SOL_BASIS** Controls whether the basis matrix is analyzed in solution analyzer.

A.2.4 MSK_appendbarvars()

```
MSKrescode MSK_appendbarvars (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * dim);
```

Appends a semidefinite variable of dimension `dim` to the problem.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of symmetric matrix variables to be appended.

dim

Dimension of symmetric matrix variables to be added.

Appends a positive semidefinite matrix variable of dimension `dim` to the problem.

A.2.5 MSK_appendcone()

```

MSKrescodee MSK_appendcone (
    MSKtask_t      task,
    MSKconetypee   conetype,
    MSKrealt        coneapar,
    MSKint32t       nummem,
    MSKCONST MSKint32t * submem);

```

Appends a new cone constraint to the problem.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

conetype

Specifies the type of the cone.

coneapar

This argument is currently not used. Can be set to 0.0.

nummem

Number of member variables in the cone.

submem

Variable subscripts of the members in the cone.

Appends a new conic constraint to the problem. Hence, add a constraint

$$\hat{x} \in \mathcal{C}$$

to the problem where \mathcal{C} is a convex cone. \hat{x} is a subset of the variables which will be specified by the argument **submem**.

Depending on the value of **conetype** this function appends a normal (**MSK_CT_QUAD**) or rotated quadratic cone (**MSK_CT_RQUAD**). Define

$$\hat{x} = x_{\text{submem}[0]}, \dots, x_{\text{submem}[\text{nummem}-1]}$$

. Depending on the value of **conetype** this function appends one of the constraints:

- Quadratic cone (**MSK_CT_QUAD**) :

$$\hat{x}_0 \geq \sqrt{\sum_{i=1}^{\text{nummem}} \hat{x}_i^2}$$

- Rotated quadratic cone (**MSK_CT_RQUAD**) :

$$2\hat{x}_0\hat{x}_1 \geq \sum_{i=2}^{i < \text{nummem}} \hat{x}_i^2, \quad \hat{x}_0, \hat{x}_1 \geq 0$$

Please note that the sets of variables appearing in different conic constraints must be disjoint.
For an explained code example see Section 5.3.

See also

- **MSK_appendconeseq** Appends a new conic constraint to the problem.
- **MSK_appendconesseq** Appends multiple conic constraints to the problem.

A.2.6 MSK_appendconeseq()

```
MSKrescodee MSK_appendconeseq (
    MSKtask_t      task,
    MSKconetypee   conetype,
    MSKrealt        coneapar,
    MSKint32t       nummem,
    MSKint32t       j);
```

Appends a new conic constraint to the problem.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

conetype

Specifies the type of the cone.

coneapar

This argument is currently not used. Can be set to 0.0.

nummem

Dimension of the conic constraint to be appended.

j

Index of the first variable in the conic constraint.

Appends a new conic constraint to the problem. The function assumes the members of cone are sequential where the first member has index `j` and the last `j+nummem-1`.

See also

- **MSK_appendcone** Appends a new cone constraint to the problem.
- **MSK_appendconesseq** Appends multiple conic constraints to the problem.

A.2.7 MSK_appendconeseq()

```
MSKrescodee MSK_appendconeseq (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKconetypee * conetype,
    MSKCONST MSKrealt * coneapar,
    MSKCONST MSKint32t * nummem,
    MSKint32t      j);
```

Appends multiple conic constraints to the problem.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of cones to be added.

conetype

Specifies the type of the cone.

coneapar

This argument is currently not used. Can be set to 0.0.

nummem

Number of member variables in the cone.

j

Index of the first variable in the first cone to be appended.

Appends a number conic constraints to the problem. The k th cone is assumed to be of dimension `nummem[k]`. Moreover, it is assumed that the first variable of the first cone has index j and the index of the variable in each cone are sequential. Finally, it is assumed in the second cone is the last index of first cone plus one and so forth.

See also

- **MSK_appendcone** Appends a new cone constraint to the problem.
- **MSK_appendconeseq** Appends a new conic constraint to the problem.

A.2.8 MSK_appendcons()

```
MSKrescodee MSK_appendcons (
    MSKtask_t task,
    MSKint32t num);
```

Appends a number of constraints to the optimization task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of constraints which should be appended.

Appends a number of constraints to the model. Appended constraints will be declared free. Please note that MOSEK will automatically expand the problem dimension to accommodate the additional constraints.

See also

- **MSK_removecons** The function removes a number of constraints.

A.2.9 MSK_appendsparsesymmat()

```
MSKrescodee MSK_appendsparsesymmat (
    MSKtask_t      task,
    MSKint32t      dim,
    MSKint64t      nz,
    MSKCONST MSKint32t * subi,
    MSKCONST MSKint32t * subj,
    MSKCONST MSKrealt * valij,
    MSKint64t *     idx);
```

Appends a general sparse symmetric matrix to the vector E of symmetric matrixes.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

dim

Dimension of the symmetric matrix that is appended.

nz

Number of triplets.

subi

Row subscript in the triplets.

subj

Column subscripts in the triplets.

valij

Values of each triplet.

`idx`

Each matrix that is appended to E is assigned a unique index i.e. `idx` that can be used for later reference.

MOSEK maintains a storage of symmetric data matrixes that is used to build the \bar{c} and \bar{A} . The storage can be thought of as a vector of symmetric matrixes denoted E . Hence, E_i is a symmetric matrix of certain dimension.

This function appends a general sparse symmetric matrix on triplet form to the vector E of symmetric matrixes. The vectors `subi`, `subj`, and `valij` contains the row subscripts, column subscripts and values of each element in the symmetric matrix to be appended. Since the matrix that is appended is symmetric then only the lower triangular part should be specified. Moreover, duplicates are not allowed.

Observe the function reports the index (position) of the appended matrix in E . This index should be used for later references to the appended matrix.

A.2.10 MSK_appendstat()

```
MSKrescodee MSK_appendstat (MSKtask_t task)
```

Appends a record the statistics file.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

Appends a record to the statistics file.

A.2.11 MSK_appendvars()

```
MSKrescodee MSK_appendvars (
    MSKtask_t task,
    MSKint32t num);
```

Appends a number of variables to the optimization task.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

num

Number of variables which should be appended.

Appends a number of variables to the model. Appended variables will be fixed at zero. Please note that MOSEK will automatically expand the problem dimension to accommodate the additional variables.

See also

- **MSK_removevars** The function removes a number of variables.

A.2.12 MSK_axpy()

```
MSKrescodee MSK_axpy (
    MSKenv_t      env,
    MSKint32t     n,
    MSKrealt      alpha,
    MSKCONST MSKrealt * x,
    MSKrealt *     y);
```

Adds α times x to y .

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

n

Length of the vectors.

alpha

The scalar that multiplies x .

x

The vector.

y

The vector.

Adds αx to y .

A.2.13 MSK_basiscond()

```
MSKrescodee MSK_basiscond (
    MSKtask_t task,
    MSKrealt * nrmbasis,
    MSKrealt * nrminvbasis);
```

Computes conditioning information for the basis matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

nrmbasis

An estimate for the 1 norm of the basis.

nrminvbasis

An estimate for the 1 norm of the inverse of the basis.

If a basic solution is available and it defines a nonsingular basis, then this function computes the 1-norm estimate of the basis matrix and an 1-norm estimate for the inverse of the basis matrix. The 1-norm estimates are computed using the method outlined in [19].

By definition the 1-norm condition number of a matrix B is defined as

$$\kappa_1(B) := \|B\|_1 \|B^{-1}\|_1.$$

Moreover, the larger the condition number is the harder it is to solve linear equation systems involving B . Given estimates for $\|B\|_1$ and $\|B^{-1}\|_1$ it is also possible to estimate $\kappa_1(B)$.

A.2.14 MSK_bktostr()

```
MSKrescodee MSK_bktostr (
    MSKtask_t    task,
    MSKboundkeye bk,
    char *       str);
```

Obtains a bound key string identifier.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

bk

Bound key.

str

String corresponding to the bound key code **bk**.

Obtains an identifier string corresponding to a bound key.

A.2.15 `MSK_callbackcodetostr()`

```
MSKrescodee MSK_callbackcodetostr (
    MSKcallbackcodee code,
    char *           callbackcodestr);
```

Obtains a call-back code string identifier.

Returns:

A response code indicating the status of the function call.

`code`

A call-back code.

`callbackcodestr`

String corresponding to the call-back code.

Obtains a the string representation of a corresponding to a call-back code.

A.2.16 `MSK_callocdbgenv()`

```
void * MSK_callocdbgenv (
    MSKenv_t      env,
    MSKCONST size_t number,
    MSKCONST size_t size,
    MSKCONST char * file,
    MSKCONST unsigned line);
```

A replacement for the system `calloc` function.

Returns:

A response code indicating the status of the function call.

`env`

The MOSEK environment.

`number`

Number of elements.

`size`

Size of each individual element.

`file`

File from which the function is called.

`line`

Line in the file from which the function is called.

Debug version of `MSK_callocenv`.

A.2.17 MSK_callocdbgtask()

```
void * MSK_callocdbgtask (  
    MSKtask_t      task,  
    MSKCONST size_t number,  
    MSKCONST size_t size,  
    MSKCONST char * file,  
    MSKCONST unsigned line);
```

A replacement for the system calloc function.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

number

Number of elements.

size

Size of each individual element.

file

File from which the function is called.

line

Line in the file from which the function is called.

Debug version of **MSK.calloc**task.

A.2.18 MSK_callocenv()

```
void * MSK_callocenv (  
    MSKenv_t      env,  
    MSKCONST size_t number,  
    MSKCONST size_t size);
```

A replacement for the system calloc function.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

number

Number of elements.

size

Size of each individual element.

Equivalent to `calloc` i.e. allocate space for an array of length `number` where each element is of size `size`.

A.2.19 `MSK_calloctask()`

```
void * MSK_calloctask (
    MSKtask_t      task,
    MSKCONST size_t number,
    MSKCONST size_t size);
```

A replacement for the system `calloc` function.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

number

Number of elements.

size

Size of each individual element.

Equivalent to `calloc` i.e. allocate space for an array of length `number` where each element is of size `size`.

A.2.20 `MSK_checkconvexity()`

```
MSKrescodee MSK_checkconvexity (MSKtask_t task)
```

Checks if a quadratic optimization problem is convex.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

This function checks if a quadratic optimization problem is convex. The amount of checking is controlled by `MSK_IPAR_CHECK_CONVEXITY`.

The function returns an error code other than `MSK_RES_OK` if the problem is not convex.

See also

- **MSK_IPAR_CHECK_CONVEXITY** Specify the level of convexity check on quadratic problems

A.2.21 MSK_checkinlicense()

```
MSKrescodee MSK_checkinlicense (
    MSKenv_t      env,
    MSKfeaturee   feature);
```

Check in a license feature from the license server ahead of time.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

feature

Feature to check in to the license system.

Check in a license feature to the license server. By default all licenses consumed by functions using a single environment is kept checked out for the lifetime of the MOSEK environment. This function checks in a given license feature to the license server immediately.

If the given license feature is not checked out or is in use by a call to **MSK_optimizetrm** calling this function has no effect.

Please note that returning a license to the license server incurs a small overhead, so frequent calls to this function should be avoided.

A.2.22 MSK_checkmemenv()

```
MSKrescodee MSK_checkmemenv (
    MSKenv_t      env,
    MSKCONST char * file,
    MSKint32t     line);
```

Checks the memory allocated by the environment.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

file

File from which the function is called.

line

Line in the file from which the function is called.

Checks the memory allocated by the environment.

A.2.23 MSK_checkmemtask()

```
MSKrescodee MSK_checkmemtask (
    MSKtask_t      task,
    MSKCONST char * file,
    MSKint32t      line);
```

Checks the memory allocated by the task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

file

File from which the function is called.

line

Line in the file from which the function is called.

Checks the memory allocated by the task.

A.2.24 MSK_checkoutlicense()

```
MSKrescodee MSK_checkoutlicense (
    MSKenv_t      env,
    MSKfeaturee   feature);
```

Check out a license feature from the license server ahead of time.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

feature

Feature to check out from the license system.

Check out a license feature from the license server. Normally the required license features will be automatically checked out the first time it is needed by the function `MSK_optimizetrm`. This function can be used to check out one or more features ahead of time.

The license will remain checked out until the environment is deleted with `MSK_deleteenv` or the function `MSK_checkinlicense` is called.

If a given feature is already checked out when this function is called, only one feature will be checked out from the license server.

A.2.25 MSK_checkversion()

```
MSKrescodee MSK_checkversion (
    MSKenv_t    env,
    MSKint32t   major,
    MSKint32t   minor,
    MSKint32t   build,
    MSKint32t   revision);
```

Compares a version of the MOSEK DLL with a specified version.

Returns:

A response code indicating the status of the function call.

`env`

The MOSEK environment.

`major`

Major version number.

`minor`

Minor version number.

`build`

Build number.

`revision`

Revision number.

Compares the version of the MOSEK DLL with a specified version. Normally the specified version is the version at the build time.

A.2.26 MSK_chgbound()

```
MSKrescodee MSK_chgbound (
    MSKtask_t    task,
    MSKaccmodee  accmode,
    MSKint32t     i,
```

```

MSKint32t    lower,
MSKint32t    finite,
MSKrealt     value);

```

Changes the bounds for one constraint or variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

Defines if operations are performed row-wise (constraint-oriented) or column-wise (variable-oriented).

i

Index of the constraint or variable for which the bounds should be changed.

lower

If non-zero, then the lower bound is changed, otherwise the upper bound is changed.

finite

If non-zero, then **value** is assumed to be finite.

value

New value for the bound.

Changes a bound for one constraint or variable. If **accmode** equals **MSK_ACC_CON**, a constraint bound is changed, otherwise a variable bound is changed.

If **lower** is non-zero, then the lower bound is changed as follows:

$$\text{new lower bound} = \begin{cases} -\infty, & \text{finite} = 0, \\ \text{value} & \text{otherwise.} \end{cases}$$

Otherwise if **lower** is zero, then

$$\text{new upper bound} = \begin{cases} \infty, & \text{finite} = 0, \\ \text{value} & \text{otherwise.} \end{cases}$$

Please note that this function automatically updates the bound key for bound, in particular, if the lower and upper bounds are identical, the bound key is changed to **fixed**.

See also

- **MSK_putbound** Changes the bound for either one constraint or one variable.
- **MSK_DPAR_DATA_TOL_BOUND_INF** Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_BOUND_WRN** Data tolerance threshold.

A.2.27 MSK_clonetask()

```
MSKrescodee MSK_clonetask (
    MSKtask_t    task,
    MSKtask_t *  clonedtask);
```

Creates a clone of an existing task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

clonedtask

The cloned task.

Creates a clone of an existing task copying all problem data and parameter settings to a new task. Call-back functions are not copied, so a task containing nonlinear functions cannot be cloned.

A.2.28 MSK_commitchanges()

```
MSKrescodee MSK_commitchanges (MSKtask_t task)
```

Commits all cached problem changes.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

Commits all cached problem changes to the task. It is usually not necessary explicitly to call this function since changes will be committed automatically when required.

A.2.29 MSK_conetypetostr()

```
MSKrescodee MSK_conetypetostr (
    MSKtask_t    task,
    MSKconetypee conetype,
    char *       str);
```

Obtains a cone type string identifier.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

conetype

Specifies the type of the cone.

str

String corresponding to the cone type code **conetype**.

Obtains the cone string identifier corresponding to a cone type.

A.2.30 MSK_deleteenv()

```
MSKrescodee MSK_deleteenv (MSKenv_t * env)
```

Delete a MOSEK environment.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

Deletes a MOSEK environment and all the data associated with it.

Before calling this function it is a good idea to call the function **MSK_unlinkfuncfromenvstream** for each stream that has have had function linked to it.

A.2.31 MSK_deletesolution()

```
MSKrescodee MSK_deletesolution (
    MSKtask_t    task,
    MSKsoltypee  whichsol);
```

Undefines a solution and frees the memory it uses.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

Undefines a solution and frees the memory it uses.

A.2.32 MSK_deletetask()

```
MSKrescodee MSK_deletetask (MSKtask_t * task)
```

Deletes an optimization task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

Deletes a task.

A.2.33 MSK_dot()

```
MSKrescodee MSK_dot (
    MSKenv_t      env,
    MSKint32t     n,
    MSKCONST MSKrealt * x,
    MSKCONST MSKrealt * y,
    MSKrealt *    xty);
```

Computes the inner product of two vectors.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

n

Length of the vectors.

x

The x vector.

y

The y vector.

xty

The result of the inner product between x and y .

Computes the inner product of two vectors x, y of length $n \geq 0$, i.e

$$x \cdot y = \sum_{i=1} x_i y_i.$$

Note that if $n = 0$, then the results of the operation is 0.

A.2.34 MSK_dualsensitivity()

```
MSKrescodee MSK_dualsensitivity (
    MSKtask_t          task,
    MSKint32t          numj,
    MSKCONST MSKint32t * subj,
    MSKrealt *         leftpricej,
    MSKrealt *         rightpricej,
    MSKrealt *         leftrangej,
    MSKrealt *         rightrangej);
```

Performs sensitivity analysis on objective coefficients.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numj

Number of coefficients to be analyzed. Length of **subj**.

subj

Index of objective coefficients to analyze.

leftpricej

leftpricej[j] is the left shadow price for the coefficients with index **subj[j]**.

rightpricej

rightpricej[j] is the right shadow price for the coefficients with index **subj[j]**.

leftrangej

leftrangej[j] is the left range β_1 for the coefficient with index **subj[j]**.

rightrangej

rightrangej[j] is the right range β_2 for the coefficient with index **subj[j]**.

Calculates sensitivity information for objective coefficients. The indexes of the coefficients to analyze are

$$\{\text{subj}[i] | i \in 0, \dots, \text{numj} - 1\}$$

The results are returned so that e.g **leftprice[j]** is the left shadow price of the objective coefficient with index **subj[j]**.

The type of sensitivity analysis to perform (basis or optimal partition) is controlled by the parameter **MSK_IPAR_SENSITIVITY_TYPE**.

For an example, please see Section 15.5.

See also

- **MSK_primalsensitivity** Perform sensitivity analysis on bounds.

- **MSK_sensitivityreport** Creates a sensitivity report.
- **MSK_IPAR_SENSITIVITY_TYPE** Controls which type of sensitivity analysis is to be performed.
- **MSK_IPAR_LOG_SENSITIVITY** Control logging in sensitivity analyzer.
- **MSK_IPAR_LOG_SENSITIVITY_OPT** Control logging in sensitivity analyzer.

A.2.35 MSK_echoenv()

```
MSKrescodee MSK_echoenv (
    MSKenv_t      env,
    MSKstreamtypee whichstream,
    MSKCONST char * format,
    ...);
```

Sends a message to a given environment stream.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

whichstream

Index of the stream.

format

Is a valid C format string which matches the arguments in ‘...’.

varnumarg

A variable argument list.

Sends a message to a given environment stream.

A.2.36 MSK_echointro()

```
MSKrescodee MSK_echointro (
    MSKenv_t      env,
    MSKint32t     longver);
```

Prints an intro to message stream.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

longver

If non-zero, then the intro is slightly longer.

Prints an intro to message stream.

A.2.37 MSK_echotask()

```
MSKrescodee MSK_echotask (
    MSKtask_t      task,
    MSKstreamtypee whichstream,
    MSKCONST char * format,
    ...);
```

Prints a format string to a task stream.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

format

varnumarg

Prints a format string to a task stream.

A.2.38 MSK_freedbgenenv()

```
void MSK_freedbgenenv (
    MSKenv_t      env,
    MSKCONST void * buffer,
    MSKCONST char * file,
    MSKCONST unsigned line);
```

Frees space allocated by MOSEK.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

buffer

A pointer.

file

File from which the function is called.

line

Line in the file from which the function is called.

Frees space allocated by a MOSEK function. Must not be applied to the MOSEK environment and task.

A.2.39 MSK_freedbgtask()

```
void MSK_freedbgtask (
    MSKtask_t      task,
    MSKCONST void * buffer,
    MSKCONST char * file,
    MSKCONST unsigned line);
```

Frees space allocated by MOSEK.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

buffer

A pointer.

file

File from which the function is called.

line

Line in the file from which the function is called.

Frees space allocated by a MOSEK function. Must not be applied to the MOSEK environment and task.

A.2.40 MSK_freeenv()

```
void MSK_freeenv (
    MSKenv_t      env,
    MSKCONST void * buffer);
```

Frees space allocated by MOSEK.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

buffer

A pointer.

Frees space allocated by a MOSEK function. Must not be applied to the MOSEK environment and task.

A.2.41 MSK_freetask()

```
void MSK_freetask (
    MSKtask_t      task,
    MSKCONST void * buffer);
```

Frees space allocated by MOSEK.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

buffer

A pointer.

Frees space allocated by a MOSEK function. Must not be applied to the MOSEK environment and task.

A.2.42 MSK_gemm()

```
MSKrescodee MSK_gemm (
    MSKenv_t      env,
    MSKtranspose  transa,
    MSKtranspose  transb,
    MSKint32t     m,
    MSKint32t     n,
    MSKint32t     k,
    MSKrealt      alpha,
    MSKCONST MSKrealt * a,
    MSKCONST MSKrealt * b,
    MSKrealt      beta,
    MSKrealt *     c);
```

Performs a dense matrix multiplication.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

transa

Indicates whether the matrix A must be transposed.

transb

Indicates whether the matrix B must be transposed.

m

Indicates the number of rows of matrices A and C .

n

Indicates the number of columns of matrices B and C .

k

Specifies the number of columns of the matrix A and the number of rows of the matrix B .

alpha

A scalar value multiplying the result of the matrix multiplication.

a

The pointer to the array storing matrix A in a column-major format.

b

Indicates the number of rows of matrix B and columns of matrix A .

beta

A scalar value that multiplies C .

c

The pointer to the array storing matrix C in a column-major format.

Performs a matrix multiplication plus addition of dense matrices. Given A , B and C of compatible dimensions, this function computes

$$C := \alpha op(A)op(B) + \beta C$$

where α, β are two scalar values. The function $op(X)$ return X if transX is YES, or X^T if set to NO. Dimensions of A, b must therefore match those of C .

The result of this operation is stored in C .

A.2.43 MSK_gemv()

```
MSKrescodee MSK_gemv (
    MSKenv_t      env,
    MSKtransposee transa,
    MSKint32t     m,
```

```

MSKint32t      n,
MSKrealt       alpha,
MSKCONST MSKrealt * a,
MSKCONST MSKrealt * x,
MSKrealt       beta,
MSKrealt *      y);

```

Computes dense matrix times a dense vector product.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

transa

Indicates whether the matrix A must be transposed.

m

Specifies the number of rows of the matrix A .

n

Specifies the number of columns of the matrix A .

alpha

A scalar value multiplying the matrix A .

a

A pointer to the array storing matrix A in a column-major format.

x

A pointer to the array storing the vector x .

beta

A scalar value multiplying the vector y .

y

A pointer to the array storing the vector y .

Computes the multiplication of a scaled dense matrix times a dense vector product, plus a scaled dense vector. In formula

$$y = \alpha Ax + \beta y,$$

or if trans is set to transpose.yes

$$y = \alpha A^T x + \beta y,$$

where α, β are scalar values. A is an $n \times m$ matrix, $x \in \mathbb{R}^m$ and $y \in \mathbb{R}^n$.

Note that the result is stored overwriting y .

A.2.44 MSK_getacol()

```
MSKrescodee MSK_getacol (
    MSKtask_t    task,
    MSKint32t    j,
    MSKint32t *   nzj,
    MSKint32t *   subj,
    MSKrealt *    valj);
```

Obtains one column of the linear constraint matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the column.

nzj

Number of non-zeros in the column obtained.

subj

Index of the non-zeros in the row obtained.

valj

Numerical values of the column obtained.

Obtains one row of A in a sparse format.

A.2.45 MSK_getacolnumnz()

```
MSKrescodee MSK_getacolnumnz (
    MSKtask_t    task,
    MSKint32t    i,
    MSKint32t *   nzj);
```

Obtains the number of non-zero elements in one column of the linear constraint matrix

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index of the column.

nzj

Number of non-zeros in the j th row or column of A .

Obtains the number of non-zero elements in one column of A .

A.2.46 MSK_getacolslicetrip()

```
MSKrescodee MSK_getacolslicetrip (
    MSKtask_t    task,
    MSKint32t    first,
    MSKint32t    last,
    MSKint64t    maxnumnz,
    MSKint64t *  surp,
    MSKint32t *  subi,
    MSKint32t *  subj,
    MSKrealt *   val);
```

Obtains a sequence of columns from the coefficient matrix in triplet format.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

Index of the first column in the sequence.

last

Index of the last column in the sequence **plus one**.

maxnumnz

Denotes the length of the arrays **subi**, **subj**, and **aval**.

surp

The required columns are stored sequentially in **subi** and **val** starting from position **maxnumnz-surp[0]**.
On return **surp** has been decremented by the total number of non-zero elements in the columns obtained.

subi

Constraint subscripts.

subj

Column subscripts.

val

Values.

Obtains a sequence of columns from A in a sparse triplet format.

Define p^1 as

$$p^1 = \text{maxnumnz} - \text{surp}[0]$$

when the function is called and p^2 by

$$p^2 = \text{maxnumnz} - \text{surp}[0],$$

where $\text{surp}[0]$ is the value upon termination. Using this notation then

$$\text{val}[k] = a_{\text{subi}[k], \text{subj}[k]}, \quad k = p^1, \dots, p^2 - 1.$$

See also

- **MSK.getaslicenumnz** Obtains the number of non-zeros in a row or column slice of the coefficient matrix.

A.2.47 MSK.getaij()

```
MSKrescodee MSK_getaij (
    MSKtask_t    task,
    MSKint32t    i,
    MSKint32t    j,
    MSKrealt *   aij);
```

Obtains a single coefficient in linear constraint matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Row index of the coefficient to be returned.

j

Column index of the coefficient to be returned.

aij

The required coefficient $a_{i,j}$.

Obtains a single coefficient in A .

A.2.48 `MSK_getapiecenumnz()`

```

MSKrescodee MSK_getapiecenumnz (
    MSKtask_t    task,
    MSKint32t    firsti,
    MSKint32t    lasti,
    MSKint32t    firstj,
    MSKint32t    lastj,
    MSKint32t *   numnz);

```

Obtains the number non-zeros in a rectangular piece of the linear constraint matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

firsti

Index of the first row in the rectangular piece.

lasti

Index of the last row plus one in the rectangular piece.

firstj

Index of the first column in the rectangular piece.

lastj

Index of the last column plus one in the rectangular piece.

numnz

Number of non-zero A elements in the rectangular piece.

Obtains the number non-zeros in a rectangular piece of A , i.e. the number

$$|\{(i, j) : a_{i,j} \neq 0, \text{firsti} \leq i \leq \text{lasti} - 1, \text{firstj} \leq j \leq \text{lastj} - 1\}|$$

where $|Z|$ means the number of elements in the set Z .

This function is not an efficient way to obtain the number of non-zeros in one row or column. In that case use the function `MSK_getarownumnz` or `MSK_getacolnumnz`.

See also

- `MSK_getaslicenumnz` Obtains the number of non-zeros in a row or column slice of the coefficient matrix.

A.2.49 MSK_getarow()

```
MSKrescodee MSK_getarow (
    MSKtask_t    task,
    MSKint32t    i,
    MSKint32t *   nzi,
    MSKint32t *   subi,
    MSKrealt *    vali);
```

Obtains one row of the linear constraint matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index of the row or column.

nzi

Number of non-zeros in the row obtained.

subi

Index of the non-zeros in the row obtained.

vali

Numerical values of the row obtained.

Obtains one row of A in a sparse format.

A.2.50 MSK_getarownumnz()

```
MSKrescodee MSK_getarownumnz (
    MSKtask_t    task,
    MSKint32t    i,
    MSKint32t *   nzi);
```

Obtains the number of non-zero elements in one row of the linear constraint matrix

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index of the row or column.

nzi

Number of non-zeros in the i th row of A .

Obtains the number of non-zero elements in one row of A .

A.2.51 MSK_getarowslicetrip()

```
MSKrescodee MSK_getarowslicetrip (
    MSKtask_t    task,
    MSKint32t    first,
    MSKint32t    last,
    MSKint64t    maxnumnz,
    MSKint64t *  surp,
    MSKint32t *  subi,
    MSKint32t *  subj,
    MSKrealt *   val);
```

Obtains a sequence of rows from the coefficient matrix in triplet format.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

Index of the first row or column in the sequence.

last

Index of the last row or column in the sequence **plus one**.

maxnumnz

Denotes the length of the arrays **subi**, **subj**, and **aval**.

surp

The required rows are stored sequentially in **subi** and **val** starting from position **maxnumnz-surp[0]**.
On return **surp** has been decremented by the total number of non-zero elements in the rows obtained.

subi

Constraint subscripts.

subj

Column subscripts.

val

Values.

Obtains a sequence of rows from A in a sparse triplet format.

Define p^1 as

$$p^1 = \text{maxnumnz} - \text{surp}[0]$$

when the function is called and p^2 by

$$p^2 = \text{maxnumnz} - \text{surp}[0],$$

where $\text{surp}[0]$ is the value upon termination. Using this notation then

$$\text{val}[k] = a_{\text{subi}[k], \text{subj}[k]}, \quad k = p^1, \dots, p^2 - 1.$$

See also

- **MSK.getaslicenumnz** Obtains the number of non-zeros in a row or column slice of the coefficient matrix.

A.2.52 MSK.getaslice()

```
MSKrescodee MSK_getaslice (
    MSKtask_t    task,
    MSKaccmodee  accmode,
    MSKint32t    first,
    MSKint32t    last,
    MSKint32t    maxnumnz,
    MSKint32t *  surp,
    MSKint32t *  ptrb,
    MSKint32t *  ptre,
    MSKint32t *  sub,
    MSKrealt *   val);
```

Obtains a sequence of rows or columns from the coefficient matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

Defines whether a column-slice or a row-slice is requested.

first

Index of the first row or column in the sequence.

last

Index of the last row or column in the sequence **plus one**.

maxnumnz

Denotes the length of the arrays **sub** and **val**.

surp

The required rows and columns are stored sequentially in **sub** and **val** starting from position **maxnumnz-surp[0]**. Upon return **surp** has been decremented by the total number of non-zero elements in the rows and columns obtained.

ptrb

ptrb[t] is an index pointing to the first element in the *t*th row or column obtained.

ptre

ptre[t] is an index pointing to the last element plus one in the *t*th row or column obtained.

sub

Contains the row or column subscripts.

val

Contains the coefficient values.

Obtains a sequence of rows or columns from *A* in sparse format.

See also

- **MSK_getaslicenumnz** Obtains the number of non-zeros in a row or column slice of the coefficient matrix.

A.2.53 MSK_getaslice64()

```
MSKrescodee MSK_getaslice64 (
    MSKtask_t    task,
    MSKaccmodee  accmode,
    MSKint32t    first,
    MSKint32t    last,
    MSKint64t    maxnumnz,
    MSKint64t *  surp,
    MSKint64t *  ptrb,
    MSKint64t *  ptre,
    MSKint32t *  sub,
    MSKrealt *   val);
```

Obtains a sequence of rows or columns from the coefficient matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

Defines whether a column slice or a row slice is requested.

first

Index of the first row or column in the sequence.

last

Index of the last row or column in the sequence **plus one**.

maxnumnz

Denotes the length of the arrays **sub** and **val**.

surp

The required rows and columns are stored sequentially in **sub** and **val** starting from position **maxnumnz-surp[0]**. Upon return **surp** has been decremented by the total number of non-zero elements in the rows and columns obtained.

ptrb

ptrb[t] is an index pointing to the first element in the *t*th row or column obtained.

ptre

ptre[t] is an index pointing to the last element plus one in the *t*th row or column obtained.

sub

Contains the row or column subscripts.

val

Contains the coefficient values.

Obtains a sequence of rows or columns from *A* in sparse format.

See also

- **MSK_getaslicenumnz64** Obtains the number of non-zeros in a slice of rows or columns of the coefficient matrix.

A.2.54 MSK_getaslicenumnz()

```
MSKrescodee MSK_getaslicenumnz (
    MSKtask_t    task,
    MSKaccmodee  accmode,
    MSKint32t    first,
    MSKint32t    last,
    MSKint32t *   numnz);
```

Obtains the number of non-zeros in a row or column slice of the coefficient matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

Defines whether non-zeros are counted in a column-slice or a row-slice.

first

Index of the first row or column in the sequence.

last

Index of the last row or column **plus one** in the sequence.

numnz

Number of non-zeros in the slice.

Obtains the number of non-zeros in a row or column slice of A .

A.2.55 MSK_getaslicenumnz64()

```
MSKrescodee MSK_getaslicenumnz64 (
    MSKtask_t    task,
    MSKaccmodee  accmode,
    MSKint32t    first,
    MSKint32t    last,
    MSKint64t *  numnz);
```

Obtains the number of non-zeros in a slice of rows or columns of the coefficient matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

Defines whether non-zeros are counted in a column slice or a row slice.

first

Index of the first row or column in the sequence.

last

Index of the last row or column **plus one** in the sequence.

numnz

Number of non-zeros in the slice.

Obtains the number of non-zeros in a slice of rows or columns of A .

A.2.56 MSK_getbarablocktriplet()

```
MSKrescodee MSK_getbarablocktriplet (
    MSKtask_t    task,
    MSKint64t    maxnum,
    MSKint64t *  num,
```

```

MSKint32t * subi,
MSKint32t * subj,
MSKint32t * subk,
MSKint32t * subl,
MSKrealt * valijkl);

```

Obtains \bar{A} in block triplet form.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnum

`subi`, `subj`, `subk`, `subl` and `valijkl` must be `maxnum` long.

num

Number of elements in the block triplet form.

subi

Constraint index.

subj

Symmetric matrix variable index.

subk

Block row index.

subl

Block column index.

valijkl

A list indexes of the elements from symmetric matrix storage that appears in the weighted sum.

Obtains \bar{A} in block triplet form.

A.2.57 MSK_getbaraidx()

```

MSKrescode MSK_getbaraidx (
    MSKtask_t    task,
    MSKint64t    idx,
    MSKint64t    maxnum,
    MSKint32t * i,
    MSKint32t * j,
    MSKint64t * num,
    MSKint64t * sub,
    MSKrealt * weights);

```

Obtains information about an element \bar{A} .

Returns:

A response code indicating the status of the function call.

task

An optimization task.

idx

Position of the element in the vectorized form.

maxnum

sub and **weights** must be at least **maxnum** long.

i

Row index of the element at position **idx**.

j

Column index of the element at position **idx**.

num

Number of terms in weighted sum that forms the element.

sub

A list indexes of the elements from symmetric matrix storage that appers in the weighted sum.

weights

The weights associated with each term in the weighted sum.

Obtains information about an element in \bar{A} . Since \bar{A} is a sparse matrix of symmetric matrixes then only the nonzero elements in \bar{A} are stored in order to save space. Now \bar{A} is stored vectorized form i.e. as one long vector. This function makes it possible to obtain information such as the row index and the column index of a particular element of the vectorized form of \bar{A} .

Please observe if one element of \bar{A} is inputted multiple times then it may be stored several times in vectorized form. In that case the element with the highest index is the one that is used.

A.2.58 MSK_getbaraidxij()

```
MSKrescodee MSK_getbaraidxij (
    MSKtask_t    task,
    MSKint64t    idx,
    MSKint32t *  i,
    MSKint32t *  j);
```

Obtains information about an element barA.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

idx
Position of the element in the vectorized form.

i
Row index of the element at position **idx**.

j
Column index of the element at position **idx**.

Obtains information about an element in \bar{A} . Since \bar{A} is a sparse matrix of symmetric matrixes only the nonzero elements in \bar{A} are stored in order to save space. Now \bar{A} is stored vectorized form i.e. as one long vector. This function makes it possible to obtain information such as the row index and the column index of a particular element of the vectorized form of \bar{A} .

Please note that if one element of \bar{A} is inputted multiple times then it may be stored several times in vectorized form. In that case the element with the highest index is the one that is used.

A.2.59 MSK_getbaraidxinfo()

```
MSKrescodee MSK_getbaraidxinfo (
    MSKtask_t    task,
    MSKint64t    idx,
    MSKint64t *  num);
```

Obtains the number terms in the weighted sum that forms a particular element in \bar{A} .

Returns:

A response code indicating the status of the function call.

task
An optimization task.

idx
The internal position of the element that should be obtained information for.

num
Number of terms in the weighted sum that forms the specified element in \bar{A} .

Each nonzero element in \bar{A}_{ij} is formed as a weighted sum of symmetric matrixes. Using this function the number terms in the weighted sum can be obtained. See description of [MSK_appendsparsesymmat](#) for details about the weighted sum.

A.2.60 MSK_getbarasparsity()

```
MSKrescodee MSK_getbarasparsity (
    MSKtask_t    task,
    MSKint64t    maxnumnz,
```

```
MSKint64t * numnz,
MSKint64t * idxij);
```

Obtains the sparsity pattern of the barA matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumnz

The arrays **subi**, **subj**, and **idxij** must be at least **maxnumnz** long.

numnz

Number of nonzero elements in \bar{A} .

idxij

Position of each nonzero element in the vectorized form of \bar{A}_{ij} . Hence, **idxij**[**k**] is the vector position of the element in row **subi**[**k**] and column **subj**[**k**] of \bar{A}_{ij} .

The matrix \bar{A} is assumed to be a sparse matrix of symmetric matrixes. This implies that many of elements in \bar{A} is likely to be zero matrixes. Therefore, in order to save space only nonzero elements in \bar{A} are stored on vectorized form. This function is used to obtain the sparsity pattern of \bar{A} and the position of each nonzero element in the vectorized form of \bar{A} .

A.2.61 MSK_getbarcblocktriplet()

```
MSKrescodee MSK_getbarcblocktriplet (
    MSKtask_t    task,
    MSKint64t    maxnum,
    MSKint64t *  num,
    MSKint32t *  subj,
    MSKint32t *  subk,
    MSKint32t *  subl,
    MSKrealt *   valijkl);
```

Obtains barc in block triplet form.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnum

subj, **subk**, **subl** and **valijkl** must be **maxnum** long.

num

Number of elements in the block triplet form.

subj
Symmetric matrix variable index.

subk
Block row index.

subl
Block column index.

valijkl
A list indexes of the elements from symmetric matrix storage that appers in the weighted sum.

Obtains \bar{C} in block triplet form.

A.2.62 MSK_getbarcidx()

```
MSKrescodee MSK_getbarcidx (
    MSKtask_t    task,
    MSKint64t    idx,
    MSKint64t    maxnum,
    MSKint32t *   j,
    MSKint64t *   num,
    MSKint64t *   sub,
    MSKrealt *    weights);
```

Obtains information about an element in `barc`.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

idx

Index of the element that should be obtained information about.

maxnum

`sub` and `weights` must be at least `maxnum` long.

j

Row index in \bar{c} .

num

Number of terms in the weighted sum.

sub

Elements appearing the weighted sum.

weights

Weights of terms in the weighted sum.

Obtains information about an element in \bar{c} .

A.2.63 MSK_getbarcidxinfo()

```
MSKrescodee MSK_getbarcidxinfo (
    MSKtask_t    task,
    MSKint64t    idx,
    MSKint64t *  num);
```

Obtains information about an element in `barc`.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

idx

Index of element that should be obtained information about. The value is an index of a symmetric sparse variable.

num

Number of terms that appears in weighted that forms the requested element.

Obtains information about about the \bar{c}_{ij} .

A.2.64 MSK_getbarcidxj()

```
MSKrescodee MSK_getbarcidxj (
    MSKtask_t    task,
    MSKint64t    idx,
    MSKint32t *  j);
```

Obtains the row index of an element in `barc`.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

idx

Index of the element that should be obtained information about.

j

Row index in \bar{c} .

Obtains the row index of an element in \bar{c} .

A.2.65 MSK_getbarcsparsity()

```
MSKrescodee MSK_getbarcsparsity (
    MSKtask_t    task,
    MSKint64t    maxnumnz,
    MSKint64t *   numnz,
    MSKint64t *   idxj);
```

Get the positions of the nonzero elements in `barc`.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`maxnumnz`

`idxj` must be at least `maxnumnz` long.

`numnz`

Number of nonzero elements in \bar{C} .

`idxj`

Internal positions of the nonzero elements in \bar{c} .

Internally only the nonzero elements of \bar{c} is stored

in a vector. This function returns which elements \bar{c} that are nonzero (in `subj`) and their internal position (in `idx`). Using the position detailed information about each nonzero \bar{C}_j can be obtained using `MSK_getbarcidxinfo` and `MSK_getbarcidx`.

A.2.66 MSK_getbarsj()

```
MSKrescodee MSK_getbarsj (
    MSKtask_t    task,
    MSKsoltypee   whichsol,
    MSKint32t     j,
    MSKrealt *    barsj);
```

Obtains the dual solution for a semidefinite variable.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`whichsol`

Selects a solution.

j
Index of the semidefinite variable.

barsj
Value of \bar{s}_j .

Obtains the dual solution for a semidefinite variable.

A.2.67 MSK_getbarvarname()

```
MSKrescodee MSK_getbarvarname (
    MSKtask_t   task,
    MSKint32t   i,
    MSKint32t   maxlen,
    char *      name);
```

Obtains a name of a semidefinite variable.

Returns:

A response code indicating the status of the function call.

task
An optimization task.

i
Index.

maxlen
Length of the name buffer.

name
The requested name is copied to this buffer.

Obtains a name of a semidefinite variable.

See also

- **MSK_getbarvarnamelen** Obtains the length of a name of a semidefinite variable.

A.2.68 MSK_getbarvarnameindex()

```
MSKrescodee MSK_getbarvarnameindex (
    MSKtask_t   task,
    MSKCONST char * somename,
    MSKint32t *  asgn,
    MSKint32t *  index);
```

Obtains the index of name of semidefinite variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

somename

The requested name is copied to this buffer.

asgn

Is non-zero if the name **somename** is assigned to a semidefinite variable.

index

If the name **somename** is assigned to a semidefinite variable, then **index** is the name of the constraint.

Obtains the index of name of semidefinite variable.

See also

- **MSK_getbarvarname** Obtains a name of a semidefinite variable.

A.2.69 MSK_getbarvarnamelen()

```
MSKrescodee MSK_getbarvarnamelen (
    MSKtask_t    task,
    MSKint32t    i,
    MSKint32t *  len);
```

Obtains the length of a name of a semidefinite variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index.

len

Returns the length of the indicated name.

Obtains the length of a name of a semidefinite variable.

See also

- **MSK_getbarvarname** Obtains a name of a semidefinite variable.

A.2.70 MSK_getbarxj()

```
MSKrescodee MSK_getbarxj (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      j,
    MSKrealt *     barxj);
```

Obtains the primal solution for a semidefinite variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

j

Index of the semidefinite variable.

barxj

Value of \bar{X}_j .

Obtains the primal solution for a semidefinite variable.

A.2.71 MSK_getbound()

```
MSKrescodee MSK_getbound (
    MSKtask_t      task,
    MSKaccmodee    accmode,
    MSKint32t      i,
    MSKboundkeye * bk,
    MSKrealt *     bl,
    MSKrealt *     bu);
```

Obtains bound information for one constraint or variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

Defines if operations are performed row-wise (constraint-oriented) or column-wise (variable-oriented).

i
Index of the constraint or variable for which the bound information should be obtained.

bk
Bound keys.

bl
Values for lower bounds.

bu
Values for upper bounds.

Obtains bound information for one constraint or variable.

A.2.72 MSK_getboundslice()

```
MSKrescodee MSK_getboundslice (
    MSKtask_t      task,
    MSKaccmodee    accmode,
    MSKint32t      first,
    MSKint32t      last,
    MSKboundkeye * bk,
    MSKrealt *     bl,
    MSKrealt *     bu);
```

Obtains bounds information for a sequence of variables or constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

Defines if operations are performed row-wise (constraint-oriented) or column-wise (variable-oriented).

first

First index in the sequence.

last

Last index plus 1 in the sequence.

bk

Bound keys.

bl

Values for lower bounds.

bu

Values for upper bounds.

Obtains bounds information for a sequence of variables or constraints.

A.2.73 MSK_getbuildinfo()

```
MSKrescodee MSK_getbuildinfo (  
    char *   buildstate,  
    char *   builddate,  
    char *   buildtool);
```

Obtains build information.

Returns:

A response code indicating the status of the function call.

buildstate

State of binaries, i.e. a debug, release candidate or final release.

builddate

Date when the binaries were build.

buildtool

Tool(s) used to build the binaries.

Obtains build information.

A.2.74 MSK_getc()

```
MSKrescodee MSK_getc (  
    MSKtask_t task,  
    MSKrealt * c);
```

Obtains all objective coefficients.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

c

Linear terms of the objective as a dense vector. The lengths is the number of variables.

Obtains all objective coefficients *c*.

A.2.75 MSK_getcallbackfunc()

```
MSKrescodee MSK_getcallbackfunc (  
    MSKtask_t      task,  
    MSKcallbackfunc * func,  
    MSKuserhandle_t * handle);
```

Obtains the call-back function and the associated user handle.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

func

Get the user-defined progress call-back function **MSKcallbackfunc** associated with **task**. If **func** is identical to NULL, then no call-back function is associated with the **task**.

handle

The user-defined pointer associated with the user-defined call-back function.

Obtains the current user-defined call-back function and associated **userhandle**.

A.2.76 MSK_getcfix()

```
MSKrescodee MSK_getcfix (  
    MSKtask_t      task,  
    MSKrealt *      cfix);
```

Obtains the fixed term in the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

cfix

Fixed term in the objective.

Obtains the fixed term in the objective.

A.2.77 MSK_getcj()

```
MSKrescodee MSK_getcj (
    MSKtask_t    task,
    MSKint32t    j,
    MSKrealt *   cj);
```

Obtains one coefficient of c .

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable for which c coefficient should be obtained.

cj

The value of c_j .

Obtains one coefficient of c .

See also

- **MSK_getcslice** Obtains a sequence of coefficients from the objective.

A.2.78 MSK_getcodedesc()

```
MSKrescodee MSK_getcodedesc (
    MSKrescodee code,
    char *       symname,
    char *       str);
```

Obtains a short description of a response code.

Returns:

A response code indicating the status of the function call.

code

A valid MOSEK response code.

symname

Symbolic name corresponding to **code**.

str

Obtains a short description of a response code.

Obtains a short description of the meaning of the response code given by **code**.

A.2.79 MSK_getconbound()

```
MSKrescodee MSK_getconbound (
    MSKtask_t      task,
    MSKint32t      i,
    MSKboundkeye * bk,
    MSKrealt *     bl,
    MSKrealt *     bu);
```

Obtains bound information for one constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index of the constraint for which the bound information should be obtained.

bk

Bound keys.

bl

Values for lower bounds.

bu

Values for upper bounds.

Obtains bound information for one constraint.

A.2.80 MSK_getconboundslice()

```
MSKrescodee MSK_getconboundslice (
    MSKtask_t      task,
    MSKint32t      first,
    MSKint32t      last,
    MSKboundkeye * bk,
    MSKrealt *     bl,
    MSKrealt *     bu);
```

Obtains bounds information for a slice of the constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first
First index in the sequence.

last
Last index plus 1 in the sequence.

bk
Bound keys.

bl
Values for lower bounds.

bu
Values for upper bounds.

Obtains bounds information for a slice of the constraints.

A.2.81 MSK_getcone()

```
MSKrescodee MSK_getcone (
    MSKtask_t      task,
    MSKint32t      k,
    MSKconetypeee * conetype,
    MSKrealt *      coneapar,
    MSKint32t *     nummem,
    MSKint32t *     submem);
```

Obtains a conic constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

k

Index of the cone constraint.

conetype

Specifies the type of the cone.

coneapar

This argument is currently not used. Can be set to 0.0.

nummem

Number of member variables in the cone.

submem

Variable subscripts of the members in the cone.

Obtains a conic constraint.

A.2.82 MSK_getconeinfo()

```
MSKrescodee MSK_getconeinfo (
    MSKtask_t    task,
    MSKint32t    k,
    MSKconetypee * conetype,
    MSKrealt *    coneapar,
    MSKint32t *    nummem);
```

Obtains information about a conic constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

k

Index of the conic constraint.

conetype

Specifies the type of the cone.

coneapar

This argument is currently not used. Can be set to 0.0.

nummem

Number of member variables in the cone.

Obtains information about a conic constraint.

A.2.83 MSK_getconename()

```
MSKrescodee MSK_getconename (
    MSKtask_t    task,
    MSKint32t    i,
    MSKint32t    maxlen,
    char *        name);
```

Obtains a name of a cone.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index.

maxlen

Maximum length of name that can be stored in **name**.

name

Is assigned the required name.

Obtains a name of a cone.

See also

- **MSK_getconnamelen** Obtains the length of a name of a constraint variable.

A.2.84 MSK_getconenameindex()

```
MSKrescodee MSK_getconenameindex (
    MSKtask_t      task,
    MSKCONST char * somename,
    MSKint32t *     asgn,
    MSKint32t *     index);
```

Checks whether the name **somename** has been assigned to any cone.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

somename

The name which should be checked.

asgn

Is non-zero if the name **somename** is assigned to a cone.

index

If the name **somename** is assigned to a cone, then **index** is the name of the cone.

Checks whether the name **somename** has been assigned to any cone. If it has been assigned to cone, then index of the cone is reported.

A.2.85 MSK_getconenamelen()

```
MSKrescodee MSK_getconenamelen (
    MSKtask_t      task,
    MSKint32t      i,
    MSKint32t *     len);
```

Obtains the length of a name of a cone.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index.

len

Returns the length of the indicated name.

Obtains the length of a name of a cone.

See also

- **MSK_getbarvarname** Obtains a name of a semidefinite variable.

A.2.86 MSK_getconname()

```
MSKrescodee MSK_getconname (
    MSKtask_t   task,
    MSKint32t   i,
    MSKint32t   maxlen,
    char *      name);
```

Obtains a name of a constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index.

maxlen

Maximum length of name that can be stored in **name**.

name

Is assigned the required name.

Obtains a name of a constraint.

See also

- **MSK_getconnamelen** Obtains the length of a name of a constraint variable.

A.2.87 MSK_getconnameindex()

```
MSKrescodee MSK_getconnameindex (
    MSKtask_t      task,
    MSKCONST char * somename,
    MSKint32t *    asgn,
    MSKint32t *    index);
```

Checks whether the name `somename` has been assigned to any constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

somename

The name which should be checked.

asgn

Is non-zero if the name `somename` is assigned to a constraint.

index

If the name `somename` is assigned to a constraint, then `index` is the name of the constraint.

Checks whether the name `somename` has been assigned to any constraint. If it has been assigned to constraint, then index of the constraint is reported.

A.2.88 MSK_getconnamelen()

```
MSKrescodee MSK_getconnamelen (
    MSKtask_t      task,
    MSKint32t      i,
    MSKint32t *    len);
```

Obtains the length of a name of a constraint variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index.

len

Returns the length of the indicated name.

Obtains the length of a name of a constraint variable.

See also

- **MSK_getbarvarname** Obtains a name of a semidefinite variable.

A.2.89 MSK_getcslice()

```
MSKrescodee MSK_getcslice (
    MSKtask_t    task,
    MSKint32t    first,
    MSKint32t    last,
    MSKrealt *   c);
```

Obtains a sequence of coefficients from the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

c

Linear terms of the objective as a dense vector. The length is the number of variables.

Obtains a sequence of elements in *c*.

A.2.90 MSK_getdbi()

```
MSKrescodee MSK_getdbi (
    MSKtask_t    task,
    MSKsoltypee   whichsol,
    MSKaccmodee   accmode,
    MSKCONST MSKint32t * sub,
    MSKint32t     len,
    MSKrealt *    dbi);
```

Deprecated.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

accmode

If set to **MSK_ACC_CON** then **sub** contains constraint indexes, otherwise variable indexes.

sub

Indexes of constraints or variables.

len

Length of **sub**

dbi

Dual bound infeasibility. If **acmode** is **MSK_ACC_CON** then

$$\text{dbi}[i] = \max(-(s_l^c)_{\text{sub}[i]}, -(s_u^c)_{\text{sub}[i]}, 0) \quad \text{for } i = 0, \dots, \text{len} - 1$$

else

$$\text{dbi}[i] = \max(-(s_l^x)_{\text{sub}[i]}, -(s_u^x)_{\text{sub}[i]}, 0) \quad \text{for } i = 0, \dots, \text{len} - 1.$$

Deprecated.

Obtains the dual bound infeasibility.

A.2.91 MSK_getdcni()

```
MSKrescodee MSK_getdcni (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST MSKint32t * sub,
    MSKint32t      len,
    MSKrealt *      dcni);
```

Deprecated.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

sub

Constraint indexes to calculate equation infeasibility for.

`len`

Length of `sub` and `dcni`

`dcni`

`dcni[i]` contains dual cone infeasibility for the cone with index `sub[i]`.

Deprecated.

Obtains the dual cone infeasibility.

A.2.92 `MSK_getdeqi()`

```
MSKrescodee MSK_getdeqi (
    MSKtask_t      task,
    MSKsoltypee     whichsol,
    MSKaccmodee     accmode,
    MSKCONST MSKint32t * sub,
    MSKint32t       len,
    MSKrealt *       deqi,
    MSKint32t        normalize);
```

Deprecated.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`whichsol`

Selects a solution.

`accmode`

If set to `MSK_ACC_CON` the dual equation infeasibilities corresponding to constraints are retrieved. Otherwise for a variables.

`sub`

Indexes of constraints or variables.

`len`

Length of `sub` and `deqi`.

`deqi`

Dual equation infeasibilities corresponding to constraints or variables.

`normalize`

If non-zero, normalize with largest absolute value of the input data used to compute the individual infeasibility.

Deprecated.

Obtains the dual equation infeasibility. If `acmode` is `MSK_ACC_CON` then

$$\text{pbi}[i] = |(-y + s_l^c - s_u^c)_{\text{sub}[i]}| \quad \text{for } i = 0, \dots, \text{len} - 1$$

If `acmode` is `MSK_ACC_VAR` then

$$\text{pbi}[i] = |(A^T y + s_l^x - s_u^x - c)_{\text{sub}[i]}| \quad \text{for } i = 0, \dots, \text{len} - 1$$

A.2.93 `MSK_getdimbarvarj()`

```
MSKrescodee MSK_getdimbarvarj (
    MSKtask_t    task,
    MSKint32t    j,
    MSKint32t *   dimbarvarj);
```

Obtains the dimension of a symmetric matrix variable.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`j`

Index of the semidefinite variable whose dimension is requested.

`dimbarvarj`

The dimension of the `j`'th semidefinite variable.

Obtains the dimension of a symmetric matrix variable.

A.2.94 `MSK_getdouinf()`

```
MSKrescodee MSK_getdouinf (
    MSKtask_t    task,
    MSKdinfiteme whichdinf,
    MSKrealt *    dvalue);
```

Obtains a double information item.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichdinf

A double information item. See section **MSKdinfiteme** for the possible values.

dvalue

The value of the required double information item.

Obtains a double information item from the task information database.

A.2.95 MSK_getdouparam()

```
MSKrescodee MSK_getdouparam (
    MSKtask_t    task,
    MSKdparame   param,
    MSKrealt *   parvalue);
```

Obtains a double parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

param

Which parameter.

parvalue

Parameter value.

Obtains the value of a double parameter.

A.2.96 MSK_getdualobj()

```
MSKrescodee MSK_getdualobj (
    MSKtask_t    task,
    MSKsoltypee   whichsol,
    MSKrealt *   dualobj);
```

Computes the dual objective value associated with the solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

dualobj

Objective value corresponding to the dual solution.

Computes the dual objective value associated with the solution. Note if the solution is a primal infeasibility certificate, then the fixed term in the objective value is not included.

A.2.97 MSK_getdviolbarvar()

```
MSKrescodee MSK_getdviolbarvar (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKrealt *     viol);
```

Computes the violation of dual solution for a set of barx variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

num

Length of **sub** and **viol**.

sub

An array of indexes of \bar{X} variables.

viol

viol[k] is violation of the solution for the constraint $\bar{S}_{\text{sub}[k]} \in \mathcal{S}$.

Let $(\bar{S}_j)^*$ be the value of variable \bar{S}_j for the specified solution. Then the dual violation of the solution associated with variable \bar{S}_j is given by

$$\max(-\lambda_{\min}(\bar{S}_j), 0.0).$$

Both when the solution is a certificate of primal infeasibility or when it is dual feasible solution the violation should be small.

A.2.98 MSK_getdviolcon()

```

MSKrescodee MSK_getdviolcon (
    MSKtask_t          task,
    MSKsoltypee        whichsol,
    MSKint32t          num,
    MSKCONST MSKint32t * sub,
    MSKrealt *         viol);

```

Computes the violation of a dual solution associated with a set of constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

num

Length of **sub** and **viol**.

sub

An array of indexes of constraints.

viol

viol[k] is the violation of dual solution associated with the constraint **sub[k]**.

The violation of the dual solution associated with the i 'th constraint is computed as follows

$$\max(\rho((s_l^c)^*, (b_l^c)_i), \rho((s_u^c)^*, -(b_u^c)_i), |-y_i + (s_l^c)^* - (s_u^c)^*|)$$

where

$$\rho(x, l) = \begin{cases} -x, & l > -\infty, \\ |x|, & \text{otherwise} \end{cases}$$

Both when the solution is a certificate of primal infeasibility or it is a dual feasible solution the violation should be small.

A.2.99 MSK_getdviolcones()

```

MSKrescodee MSK_getdviolcones (
    MSKtask_t          task,
    MSKsoltypee        whichsol,
    MSKint32t          num,
    MSKCONST MSKint32t * sub,
    MSKrealt *         viol);

```

Computes the violation of a solution for set of dual conic constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

num

Length of **sub** and **viol**.

sub

An array of indexes of \bar{X} variables.

viol

viol[k] violation of the solution associated with **sub[k]**'th dual conic constraint.

Let $(s_n^x)^*$ be the value of variable (s_n^x) for the specified solution. For simplicity let us assume that s_n^x is a member of quadratic cone, then the violation is computed as follows

$$\begin{cases} \max(0, \|(s_n^x)_{2:n}\|^* - (s_n^x)_1)/\sqrt{2}, & (s_n^x)^* \geq -\|(s_n^x)_{2:n}\|, \\ \|(s_n^x)^*\|, & \text{otherwise.} \end{cases}$$

Both when the solution is a certificate of primal infeasibility or when it is a dual feasible solution the violation should be small.

A.2.100 MSK_getdviolvar()

```
MSKrescodee MSK_getdviolvar (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKrealt *     viol);
```

Computes the violation of a dual solution associated with a set of x variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

num

Length of **sub** and **viol**.

sub

An array of indexes of x variables.

viol

viol[**k**] is the maximal violation of the solution for the constraints $(s_l^x)_{\text{sub}[k]} \geq 0$ and $(s_u^x)_{\text{sub}[k]} \geq 0$.

The violation fo dual solution associated with the j 'th variable is computed as follows

$$\max(\rho((s_l^x)_i^*, (b_l^x)_i), \rho((s_u^x)_i^*, -(b_u^x)_i), |\sum_j j = 0^{numcon-1} a_{ij} y_i + (s_l^x)_i^* - (s_u^x)_i^* - \tau c_j|)$$

where

$$\rho(x, l) = \begin{cases} -x, & l > -\infty, \\ |x|, & \text{otherwise} \end{cases}$$

$\tau = 0$ if the the solution is certificate of dual infeasibility and $\tau = 1$ otherwise. The formula for computing the violation is only shown for linear case but is generalized appropriately for the more general problems.

A.2.101 MSK_getenv()

```
MSKrescodee MSK_getenv (
    MSKtask_t   task,
    MSKenv_t *  env);
```

Obtains the environment used to create the task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

env

The MOSEK environment.

Obtains the environment used to create the task.

A.2.102 MSK_getglbdlname()

```
MSKrescodee MSK_getglbdlname (
    MSKenv_t      env,
    MSKCONST size_t sizedllname,
    char *        dllname);
```

Obtains the name of the global optimizer DLL.

Returns:

A response code indicating the status of the function call.

`env`

The MOSEK environment.

`sizedllname`

`dllname`

The DLL name.

Obtains the name of the global optimizer DLL.

A.2.103 MSK_getinfeasiblesubproblem()

```
MSKrescodee MSK_getinfeasiblesubproblem (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKtask_t *    inftask);
```

Obtains an infeasible sub problem.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`whichsol`

Which solution to use when determining the infeasible subproblem.

`inftask`

A new task containing the infeasible subproblem.

Given the solution is a certificate of primal or dual infeasibility then a primal or dual infeasible subproblem is obtained respectively. The subproblem tend to be much smaller than the original problem and hence it easier to locate the infeasibility inspecting the subproblem than the original problem.

For the procedure to be useful then it is important to assigning meaningful names to constraints, variables etc. in the original task because those names will be duplicated in the subproblem.

The function is only applicable to linear and conic quadratic optimization problems.

For more information see Section 13.2.

See also

- **MSK_IPAR_INFEAS_PREFER_PRIMAL** Controls which certificate is used if both primal- and dual- certificate of infeasibility is available.
- **MSK_relaxprimal** Deprecated.

A.2.104 MSK_getinfindex()

```
MSKrescodee MSK_getinfindex (
    MSKtask_t      task,
    MSKinfypee     inftype,
    MSKCONST char * infname,
    MSKint32t *    infindex);
```

Obtains the index of a named information item.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

inftype

Type of the information item.

infname

Name of the information item.

infindex

The item index.

Obtains the index of a named information item.

A.2.105 MSK_getinfmax()

```
MSKrescodee MSK_getinfmax (
    MSKtask_t      task,
    MSKinfypee     inftype,
    MSKint32t *    infmax);
```

Obtains the maximum index of an information of a given type inftype plus 1.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`inftype`

Type of the information item.

`infmax`

Obtains the maximum index of an information of a given type `inftype` plus 1.

A.2.106 `MSK_getinfname()`

```
MSKrescodee MSK_getinfname (
    MSKtask_t    task,
    MSKinftype   inftype,
    MSKint32t    whichinf,
    char *       infname);
```

Obtains the name of an information item.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`inftype`

Type of the information item.

`whichinf`

An information item. See Section `MSKdinfiteme`, Section `MSKiinfiteme` and Section `MSKliinfiteme` for the possible values.

`infname`

Name of the information item.

Obtains the name of an information item.

A.2.107 `MSK_getinti()`

```
MSKrescodee MSK_getinti (
    MSKtask_t    task,
    MSKsoltype    whichsol,
    MSKCONST MSKint32t * sub,
    MSKint32t    len,
```

```
MSKrealt *      inti);
```

Deprecated.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

sub

Variable indexes for which to calculate the integer infeasibility.

len

Length of **sub** and **inti**

inti

inti[i] contains integer infeasibility of variable **sub[i]**.

Deprecated.

Obtains the primal equation infeasibility.

$$\text{peqi}[i] = |(Ax - x^c)_{\text{sub}[i]}| \quad \text{for } i = 0, \dots, \text{len} - 1.$$

A.2.108 MSK_getintinf()

```
MSKrescodee MSK_getintinf (
    MSKtask_t      task,
    MSKiinfiteme   whichiinf,
    MSKint32t *    ivalue);
```

Obtains an integer information item.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichiinf

Specifies an information item.

ivalue

The value of the required integer information item.

Obtains an integer information item from the task information database.

A.2.109 MSK_getintparam()

```
MSKrescodee MSK_getintparam (
    MSKtask_t    task,
    MSKiparam     param,
    MSKint32t *   parvalue);
```

Obtains an integer parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

param

Which parameter.

parvalue

Parameter value.

Obtains the value of an integer parameter.

A.2.110 MSK_getlasterror()

```
MSKrescodee MSK_getlasterror (
    MSKtask_t    task,
    MSKrescodee * lastrescode,
    MSKint32t     maxlen,
    MSKint32t *   lastmsglen,
    char *        lastmsg);
```

Obtains the last error code and error message reported in MOSEK.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

lastrescode

Returns the last error code reported in the task.

maxlen

The length of the lastmsg buffer.

lastmsglen

Returns the length of the last error message reported in the task.

`lastmsg`

Returns the the last error message reported in the task.

Obtains the last response code and corresponding message reported in MOSEK.

If there is no previous error, warning or termination code for this task, `lastrescode` returns `MSK_RES_OK` and `lastmsg` returns an empty string, otherwise the last response code different from `MSK_RES_OK` and the corresponding message are returned.

A.2.111 `MSK_getlasterror64()`

```
MSKrescodee MSK_getlasterror64 (
    MSKtask_t      task,
    MSKrescodee *  lastrescode,
    MSKint64t      maxlen,
    MSKint64t *    lastmsglen,
    char *         lastmsg);
```

Obtains the last error code and error message reported in MOSEK.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`lastrescode`

Returns the last error code reported in the task.

`maxlen`

The length if the `lastmsg` buffer.

`lastmsglen`

Returns the length of the last error message reported in the task.

`lastmsg`

Returns the the last error message reported in the task.

Obtains the last response code and corresponding message reported in MOSEK.

If there is no previous error, warning or termination code for this task, `lastrescode` returns `MSK_RES_OK` and `lastmsg` returns an empty string, otherwise the last response code different from `MSK_RES_OK` and the corresponding message are returned.

A.2.112 `MSK_getlenbarvarj()`

```
MSKrescodee MSK_getlenbarvarj (
    MSKtask_t      task,
```

```
MSKint32t    j,
MSKint64t *  lenbarvarj);
```

Obtains the length of the j 'th semidefinite variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the semidefinite variable whose length is requested.

lenbarvarj

Number of scalar elements in the lower triangular part of the semidefinite variable.

Obtains the length of the j th semidefinite variable i.e. the number of elements in the triangular part.

A.2.113 MSK_getlintinf()

```
MSKrescodee MSK_getlintinf (
    MSKtask_t      task,
    MSKliinfiteme  whichliinf,
    MSKint64t *    ivalue);
```

Obtains an integer information item.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichliinf

Specifies an information item.

ivalue

The value of the required integer information item.

Obtains an integer information item from the task information database.

A.2.114 MSK_getmaxnamelen()

```
MSKrescodee MSK_getmaxnamelen (
    MSKtask_t    task,
    MSKint32t *  maxlen);
```

Obtains the maximum length (not including terminating zero character) of any objective, constraint, variable or cone name.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxlen

The maximum length of any name.

Obtains the maximum length (not including terminating zero character) of any objective, constraint, variable or cone name.

A.2.115 MSK_getmaxnumanz()

```
MSKrescodee MSK_getmaxnumanz (
    MSKtask_t    task,
    MSKint32t *  maxnumanz);
```

Obtains number of preallocated non-zeros in the linear constraint matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumanz

Number of preallocated non-zero elements in A .

Obtains number of preallocated non-zeros in A . When this number of non-zeros is reached MOSEK will automatically allocate more space for A .

A.2.116 MSK_getmaxnumanz64()

```
MSKrescodee MSK_getmaxnumanz64 (
```

```
MSKtask_t    task,
MSKint64t *  maxnumanz);
```

Obtains number of preallocated non-zeros in the linear constraint matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumanz

Number of preallocated non-zero elements in A .

Obtains number of preallocated non-zeros in A . When this number of non-zeros is reached MOSEK will automatically allocate more space for A .

A.2.117 MSK_getmaxnumbarvar()

```
MSKrescodee MSK_getmaxnumbarvar (
    MSKtask_t    task,
    MSKint32t *  maxnumbarvar);
```

Obtains the number of semidefinite variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumbarvar

Obtains maximum number of semidefinite variable currently allowed.

Obtains the number of semidefinite variables.

A.2.118 MSK_getmaxnumcon()

```
MSKrescodee MSK_getmaxnumcon (
    MSKtask_t    task,
    MSKint32t *  maxnumcon);
```

Obtains the number of preallocated constraints in the optimization task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumcon

Number of preallocated constraints in the optimization task.

Obtains the number of preallocated constraints in the optimization task. When this number of constraints is reached MOSEK will automatically allocate more space for constraints.

A.2.119 MSK_getmaxnumcone()

```
MSKrescodee MSK_getmaxnumcone (
    MSKtask_t    task,
    MSKint32t *  maxnumcone);
```

Obtains the number of preallocated cones in the optimization task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumcone

Number of preallocated conic constraints in the optimization task.

Obtains the number of preallocated cones in the optimization task. When this number of cones is reached MOSEK will automatically allocate space for more cones.

A.2.120 MSK_getmaxnumqnz()

```
MSKrescodee MSK_getmaxnumqnz (
    MSKtask_t    task,
    MSKint32t *  maxnumqnz);
```

Obtains the number of preallocated non-zeros for all quadratic terms in objective and constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumqnz

Number of non-zero elements preallocated in quadratic coefficient matrixes.

Obtains the number of preallocated non-zeros for Q (both objective and constraints). When this number of non-zeros is reached MOSEK will automatically allocate more space for Q .

A.2.121 MSK_getmaxnumqnz64()

```
MSKrescodee MSK_getmaxnumqnz64 (
    MSKtask_t    task,
    MSKint64t *  maxnumqnz);
```

Obtains the number of preallocated non-zeros for all quadratic terms in objective and constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumqnz

Number of non-zero elements preallocated in quadratic coefficient matrixes.

Obtains the number of preallocated non-zeros for Q (both objective and constraints). When this number of non-zeros is reached MOSEK will automatically allocate more space for Q .

A.2.122 MSK_getmaxnumvar()

```
MSKrescodee MSK_getmaxnumvar (
    MSKtask_t    task,
    MSKint32t *  maxnumvar);
```

Obtains the maximum number variables allowed.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumvar

Number of preallocated variables in the optimization task.

Obtains the number of preallocated variables in the optimization task. When this number of variables is reached MOSEK will automatically allocate more space for constraints.

A.2.123 MSK_getmemusagetask()

```
MSKrescodee MSK_getmemusagetask (
    MSKtask_t    task,
    MSKint64t *  meminuse,
```

```
MSKint64t * maxmemuse);
```

Obtains information about the amount of memory used by a task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

meminuse

Amount of memory currently used by the **task**.

maxmemuse

Maximum amount of memory used by the **task** until now.

Obtains information about the amount of memory used by a task.

A.2.124 MSK_getnadouinf()

```
MSKrescodee MSK_getnadouinf (
    MSKtask_t      task,
    MSKCONST char * whichdinf,
    MSKrealt *     dvalue);
```

Obtains a double information item.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichdinf

A double information item. See section [MSKdinfiteme](#) for the possible values.

dvalue

The value of the required double information item.

Obtains a double information item from task information database.

A.2.125 MSK_getnadoupam()

```
MSKrescodee MSK_getnadoupam (
    MSKtask_t      task,
    MSKCONST char * paramname,
    MSKrealt *     parvalue);
```

Obtains a double parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

paramname

Name of a parameter.

parvalue

Parameter value.

Obtains the value of a named double parameter.

A.2.126 MSK_getnaintinf()

```
MSKrescodee MSK_getnaintinf (
    MSKtask_t      task,
    MSKCONST char * infitemname,
    MSKint32t *     ivalue);
```

Obtains an integer information item.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

infitemname

ivalue

The value of the required integer information item.

Obtains an integer information item from the task information database.

A.2.127 MSK_getnaintparam()

```
MSKrescodee MSK_getnaintparam (
    MSKtask_t      task,
    MSKCONST char * paramname,
    MSKint32t *     parvalue);
```

Obtains an integer parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

paramname

Name of a parameter.

parvalue

Parameter value.

Obtains the value of a named integer parameter.

A.2.128 MSK_getnastrparam()

```
MSKrescodee MSK_getnastrparam (
    MSKtask_t      task,
    MSKCONST char * paramname,
    MSKint32t      maxlen,
    MSKint32t *    len,
    char *         parvalue);
```

Obtains a string parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

paramname

Name of a parameter.

maxlen

Length of **parvalue**.

len

Identical to length of string hold by **parvalue**.

parvalue

Parameter value.

Obtains the value of a named string parameter.

A.2.129 MSK_getnastrparamal()

```
MSKrescodee MSK_getnastrparamal (
    MSKtask_t      task,
    MSKCONST char * paramname,
    MSKint32t      numaddchr,
    MSKstring_t *   value);
```

Obtains the value of a string parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

paramname

Name of a parameter.

numaddchr

Number of additional characters that is made room for in `value[0]`.

value

Is the value corresponding to string parameter `param`. `value[0]` is char buffer allocated MOSEK and it must be freed by `MSK_freetask`.

Obtains the value of a string parameter.

A.2.130 MSK_getnlfunc()

```
MSKrescodee MSK_getnlfunc (
    MSKtask_t      task,
    MSKuserhandle_t * nlhandle,
    MSKnlgetspfunc * nlgetsp,
    MSKnlgetvafunc * nlgetva);
```

Gets nonlinear call-back functions.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

nlhandle

Retrieve the pointer to the user-defined data structure. This structure is passed to the functions `nlgetsp` and `nlgetva` whenever those two functions called.

nlgetsp

Retrieve the function which provide information about the structure of the nonlinear functions in the optimization problem.

nlgetva

Retrieve the function which is used to evaluate the nonlinear function in the optimization problem at a given point.

This function is used to retrieve the nonlinear call-back functions. If NULL no nonlinear call-back function exists.

A.2.131 MSK_getnumanz()

```
MSKrescodee MSK_getnumanz (
    MSKtask_t    task,
    MSKint32t *  numanz);
```

Obtains the number of non-zeros in the coefficient matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numanz

Number of non-zero elements in A .

Obtains the number of non-zeros in A .

A.2.132 MSK_getnumanz64()

```
MSKrescodee MSK_getnumanz64 (
    MSKtask_t    task,
    MSKint64t *  numanz);
```

Obtains the number of non-zeros in the coefficient matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numanz

Number of non-zero elements in A .

Obtains the number of non-zeros in A .

A.2.133 MSK_getnumbarablocktriplets()

```
MSKrescodee MSK_getnumbarablocktriplets (
    MSKtask_t    task,
    MSKint64t *  num);
```

Obtains an upper bound on the number of scalar elements in the block triplet form of \bar{A} .

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number elements in the block triplet form of \bar{A} .

Obtains an upper bound on the number of elements in the block triplet form of \bar{A} .

A.2.134 MSK_getnumbaranz()

```
MSKrescodee MSK_getnumbaranz (
    MSKtask_t    task,
    MSKint64t *  nz);
```

Get the number of nonzero elements in \bar{A} .

Returns:

A response code indicating the status of the function call.

task

An optimization task.

nz

The number of nonzero elements in \bar{A} i.e. the number of \bar{a}_{ij} elements that is nonzero.

Get the number of nonzero elements in \bar{A} .

A.2.135 MSK_getnumbarcblocktriplets()

```
MSKrescodee MSK_getnumbarcblocktriplets (
    MSKtask_t    task,
    MSKint64t *  num);
```

Obtains an upper bound on the number of elements in the block triplet form of \bar{A} .

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

An upper bound on the number elements in the block trip let form of \bar{c} .

Obtains an upper bound on the number of elements in the block triplet form of \bar{C} .

A.2.136 MSK_getnumbarcnz()

```
MSKrescodee MSK_getnumbarcnz (
    MSKtask_t    task,
    MSKint64t *  nz);
```

Obtains the number of nonzero elements in barc .

Returns:

A response code indicating the status of the function call.

task

An optimization task.

nz

The number of nonzeros in \bar{c} i.e. the number of elements \bar{c}_j that is different from 0.

Obtains the number of nonzero elements in \bar{c} .

A.2.137 MSK_getnumbarvar()

```
MSKrescodee MSK_getnumbarvar (
    MSKtask_t    task,
    MSKint32t *  numbarvar);
```

Obtains the number of semidefinite variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numbarvar

Number of semidefinite variable in the problem.

Obtains the number of semidefinite variables.

A.2.138 MSK_getnumcon()

```
MSKrescodee MSK_getnumcon (
    MSKtask_t    task,
    MSKint32t *  numcon);
```

Obtains the number of constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numcon

Number of constraints.

Obtains the number of constraints.

A.2.139 MSK_getnumcone()

```
MSKrescodee MSK_getnumcone (
    MSKtask_t    task,
    MSKint32t *  numcone);
```

Obtains the number of cones.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numcone

Number conic constraints.

Obtains the number of cones.

A.2.140 MSK_getnumconemem()

```
MSKrescodee MSK_getnumconemem (
    MSKtask_t    task,
    MSKint32t    k,
    MSKint32t *  nummem);
```

Obtains the number of members in a cone.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

k

Index of the cone.

nummem

Number of member variables in the cone.

Obtains the number of members in a cone.

A.2.141 MSK_getnumintvar()

```
MSKrescodee MSK_getnumintvar (
    MSKtask_t    task,
    MSKint32t *  numintvar);
```

Obtains the number of integer-constrained variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numintvar

Number of integer variables.

Obtains the number of integer-constrained variables.

A.2.142 MSK_getnumparam()

```
MSKrescodee MSK_getnumparam (
    MSKtask_t    task,
    MSKparametertypee partype,
    MSKint32t *  numparam);
```

Obtains the number of parameters of a given type.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

partype

Parameter type.

numparam

Identical to the number of parameters of the type **partype**.

Obtains the number of parameters of a given type.

A.2.143 MSK_getnumqconknz()

```
MSKrescodee MSK_getnumqconknz (
    MSKtask_t    task,
    MSKint32t    k,
    MSKint32t *  numqcnz);
```

Obtains the number of non-zero quadratic terms in a constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

k

Index of the constraint for which the number of non-zero quadratic terms should be obtained.

numqcnz

Number of quadratic terms. See (5.15).

Obtains the number of non-zero quadratic terms in a constraint.

A.2.144 MSK_getnumqconknz64()

```
MSKrescodee MSK_getnumqconknz64 (
    MSKtask_t    task,
    MSKint32t    k,
    MSKint64t *  numqcnz);
```

Obtains the number of non-zero quadratic terms in a constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

k

Index of the constraint for which the number quadratic terms should be obtained.

numqcnz

Number of quadratic terms. See (5.15).

Obtains the number of non-zero quadratic terms in a constraint.

A.2.145 MSK_getnumqobjnz()

```
MSKrescodee MSK_getnumqobjnz (
    MSKtask_t    task,
    MSKint32t *  numqonz);
```

Obtains the number of non-zero quadratic terms in the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numqonz

Number of non-zero elements in Q^o .

Obtains the number of non-zero quadratic terms in the objective.

A.2.146 MSK_getnumqobjnz64()

```
MSKrescodee MSK_getnumqobjnz64 (
    MSKtask_t    task,
    MSKint64t *  numqonz);
```

Obtains the number of non-zero quadratic terms in the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numqonz

Number of non-zero elements in Q^o .

Obtains the number of non-zero quadratic terms in the objective.

A.2.147 MSK_getnumsymmat()

```
MSKrescodee MSK_getnumsymmat (
    MSKtask_t    task,
    MSKint64t *  num);
```

Get the number of symmetric matrixes stored.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Returns the number of symmetric sparse matrixes.

Get the number of symmetric matrixes stored in the vector E .

A.2.148 MSK_getnumvar()

```
MSKrescodee MSK_getnumvar (
    MSKtask_t    task,
    MSKint32t *  numvar);
```

Obtains the number of variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numvar

Number of variables.

Obtains the number of variables.

A.2.149 MSK_getobjname()

```
MSKrescodee MSK_getobjname (
    MSKtask_t    task,
    MSKint32t    maxlen,
    char *       objname);
```

Obtains the name assigned to the objective function.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`maxlen`

Length of `objname`.

`objname`

Assigned the objective name.

Obtains the name assigned to the objective function.

A.2.150 `MSK_getobjnamelen()`

```
MSKrescodee MSK_getobjnamelen (
    MSKtask_t    task,
    MSKint32t *  len);
```

Obtains the length of the name assigned to the objective function.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`len`

Assigned the length of the objective name.

Obtains the length of the name assigned to the objective function.

A.2.151 `MSK_getobjsense()`

```
MSKrescodee MSK_getobjsense (
    MSKtask_t    task,
    MSKobjsensee *  sense);
```

Gets the objective sense.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

sense

The returned objective sense.

Gets the objective sense of the task.

See also

- **MSK_putobjsense** Sets the objective sense.

A.2.152 MSK_getparammax()

```
MSKrescodee MSK_getparammax (
    MSKtask_t      task,
    MSKparametertypee partype,
    MSKint32t *      parammax);
```

Obtains the maximum index of a parameter of a given type plus 1.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

partype

Parameter type.

parammax

Obtains the maximum index of a parameter of a given type plus 1.

A.2.153 MSK_getparamname()

```
MSKrescodee MSK_getparamname (
    MSKtask_t      task,
    MSKparametertypee partype,
    MSKint32t      param,
    char *          parname);
```

Obtains the name of a parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

partype

Parameter type.

param

Which parameter.

parname

Parameter name.

Obtains the name for a parameter **param** of type **partype**.**A.2.154 MSK_getpbi()**

```

MSKrescodee MSK_getpbi (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKaccmodee    accmode,
    MSKCONST MSKint32t * sub,
    MSKint32t      len,
    MSKrealt *      pbi,
    MSKint32t      normalize);

```

Deprecated.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

accmodeIf set to **MSK_ACC_VAR** return bound infeasibility for x otherwise for x^c .**sub**

An array of constraint or variable indexes.

lenLength of **sub** and **pbi****pbi**Bound infeasibility for x or x^c .**normalize**

If non-zero, normalize with largest absolute value of the input data used to compute the individual infeasibility.

Deprecated.

Obtains the primal bound infeasibility. If `acmode` is `MSK_ACC_CON` then

$$\text{pbi}[i] = \max(x_{\text{sub}[i]}^c - u_{\text{sub}[i]}^c, l_{\text{sub}[i]}^c - x_{\text{sub}[i]}^c, 0) \quad \text{for } i = 0, \dots, \text{len} - 1$$

If `acmode` is `MSK_ACC_VAR` then

$$\text{pbi}[i] = \max(x_{\text{sub}[i]} - u_{\text{sub}[i]}^x, l_{\text{sub}[i]}^x - x_{\text{sub}[i]}, 0) \quad \text{for } i = 0, \dots, \text{len} - 1$$

A.2.155 MSK_getpcni()

```
MSKrescodee MSK_getpcni (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST MSKint32t * sub,
    MSKint32t      len,
    MSKrealt *     pcni);
```

Deprecated.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`whichsol`

Selects a solution.

`sub`

Constraint indexes for which to calculate the equation infeasibility.

`len`

Length of `sub` and `pcni`

`pcni`

`pcni[i]` contains primal cone infeasibility for the cone with index `sub[i]`.

Deprectaed.

A.2.156 MSK_getpeqi()

```
MSKrescodee MSK_getpeqi (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST MSKint32t * sub,
    MSKint32t      len,
```

```
MSKrealt *      peqi,
MSKint32t      normalize);
```

Deprecated.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

sub

Constraint indexes for which to calculate the equation infeasibility.

len

Length of **sub** and **peqi**

peqi

peqi[i] contains equation infeasibility of constraint **sub[i]**.

normalize

If non-zero, normalize with largest absolute value of the input data used to compute the individual infeasibility.

Deprecated.

Obtains the primal equation infeasibility.

$$\text{peqi}[i] = |(Ax - x^c)_{\text{sub}[i]}| \quad \text{for } i = 0, \dots, \text{len} - 1.$$

A.2.157 MSK_getprimalobj()

```
MSKrescodee MSK_getprimalobj (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKrealt *    primalobj);
```

Computes the primal objective value for the desired solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

`primalobj`

Objective value corresponding to the primal solution.

Computes the primal objective value for the desired solution. Note if the solution is an infeasibility certificate, then the fixed term in the objective is not included.

A.2.158 `MSK_getprobtype()`

```
MSKrescodee MSK_getprobtype (
    MSKtask_t      task,
    MSKproblemtypee * probtype);
```

Obtains the problem type.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`probtype`

The problem type.

Obtains the problem type.

A.2.159 `MSK_getprosta()`

```
MSKrescodee MSK_getprosta (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKprostae *   prosta);
```

Obtains the problem status.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`whichsol`

Selects a solution.

`prosta`

Problem status.

Obtains the problem status.

A.2.160 MSK_getpviolbarvar()

```
MSKrescodee MSK_getpviolbarvar (
    MSKtask_t      task,
    MSKsoltypee     whichsol,
    MSKint32t       num,
    MSKCONST MSKint32t * sub,
    MSKrealt *      viol);
```

Computes the violation of a primal solution for a list of barx variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

num

Length of **sub** and **viol**.

sub

An array of indexes of \bar{X} variables.

viol

viol[k] is how much the solution violate the constraint $\bar{X}_{\text{sub}[k]} \in \mathcal{S}^+$.

Let $(\bar{X}_j)^*$ be the value of variable \bar{X}_j for the specified solution. Then the primal violation of the solution associated with variable \bar{X}_j is given by

$$\max(-\lambda_{\min}(\bar{X}_j), 0.0).$$

A.2.161 MSK_getpviolcon()

```
MSKrescodee MSK_getpviolcon (
    MSKtask_t      task,
    MSKsoltypee     whichsol,
    MSKint32t       num,
    MSKCONST MSKint32t * sub,
    MSKrealt *      viol);
```

Computes the violation of a primal solution for a list of xc variables.

Returns:

A response code indicating the status of the function call.

task
An optimization task.

whichsol
Selects a solution.

num
Length of **sub** and **viol**.

sub
An array of indexes of constraints.

viol
viol[k] associated with the solution for the **sub[k]**'th constraint.

The primal violation of the solution associated of constraint is computed by

$$\max(l_i^c \tau - (x_i^c)^*, (x_i^c)^* \tau - u_i^c \tau, \left| \sum_{j=0}^{numvar-1} a_{ij} x_j^* - x_i^c \right|)$$

where τ is defined as follows. If the solution is a certificate of dual infeasibility, then $\tau = 0$ and otherwise $\tau = 1$. Both when the solution is a valid certificate of dual infeasibility or when it is primal feasible solution the violation should be small. The above is only shown for linear case but is appropriately generalized for the other cases.

A.2.162 MSK_getpviolcones()

```
MSKrescode MSK_getpviolcones (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKrealt *     viol);
```

Computes the violation of a solution for set of conic constraints.

Returns:

A response code indicating the status of the function call.

task
An optimization task.

whichsol
Selects a solution.

num
Length of **sub** and **viol**.

sub
An array of indexes of \bar{X} variables.

viol

viol[k] violation of the solution associated with **sub[k]**'th conic constraint.

Let x^* be the value of variable x for the specified solution. For simplicity let us assume that x is a member of quadratic cone, then the violation is computed as follows

$$\begin{cases} \max(0, \|x_{2:n}\| - x_1)/\sqrt{2}, & x_1 \geq -\|x_{2:n}\|, \\ \|x\|, & \text{otherwise.} \end{cases}$$

Both when the solution is a certificate of dual infeasibility or when it is a primal feasible solution the violation should be small.

A.2.163 MSK_getpviolvar()

```
MSKrescodee MSK_getpviolvar (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKrealt *     viol);
```

Computes the violation of a primal solution for a list of x variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

num

Length of **sub** and **viol**.

sub

An array of indexes of x variables.

viol

viol[k] is the violation associated the solution for variable x_j .

Let x_j^* be the value of variable x_j for the specified solution. Then the primal violation of the solution associated with variable x_j is given by

$$\max(l_j^x \tau - x_j^*, x_j^* - u_j^x \tau).$$

where τ is defined as follows. If the solution is a certificate of dual infeasibility, then $\tau = 0$ and otherwise $\tau = 1$. Both when the solution is a valid certificate of dual infeasibility or when it is primal feasible solution the violation should be small.

A.2.164 MSK_getqconk()

```

MSKrescodee MSK_getqconk (
    MSKtask_t    task,
    MSKint32t    k,
    MSKint32t    maxnumqcnz,
    MSKint32t *   qcsurp,
    MSKint32t *   numqcnz,
    MSKint32t *   qcsubi,
    MSKint32t *   qcsubj,
    MSKrealt *   qcval);

```

Obtains all the quadratic terms in a constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

k

Which constraint.

maxnumqcnz

Length of the arrays **qcsubi**, **qcsubj**, and **qcval**.

qcsurp

When entering the function it is assumed that the last **qcsurp**[0] positions in **qcsubi**, **qcsubj**, and **qcval** are free. Hence, the quadratic terms are stored in this area, and upon return **qcsurp** is number of free positions left in **qcsubi**, **qcsubj**, and **qcval**.

numqcnz

Number of quadratic terms. See (5.15).

qcsubi

i subscripts for q_{ij}^k . See (5.15).

qcsubj

j subscripts for q_{ij}^k . See (5.15).

qcval

Numerical value for q_{ij}^k .

Obtains all the quadratic terms in a constraint. The quadratic terms are stored sequentially **qcsubi**, **qcsubj**, and **qcval**.

A.2.165 MSK_getqconk64()

```

MSKrescodee MSK_getqconk64 (

```



```

MSKtask_t    task,
MSKint32t    k,
MSKint64t    maxnumqcnz,
MSKint64t *  qcsurp,
MSKint64t *  numqcnz,
MSKint32t *  qcsubi,
MSKint32t *  qcsubj,
MSKrealt *   qcval);

```

Obtains all the quadratic terms in a constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

k

Which constraint.

maxnumqcnz

Length of the arrays **qcsubi**, **qcsubj**, and **qcval**.

qcsurp

When entering the function it is assumed that the last **qcsurp[0]** positions in **qcsubi**, **qcsubj**, and **qcval** are free. Hence, the quadratic terms are stored in this area, and upon return **qcsurp** is number of free positions left in **qcsubi**, **qcsubj**, and **qcval**.

numqcnz

Number of quadratic terms. See (5.15).

qcsubi

i subscripts for q_{ij}^k . See (5.15).

qcsubj

j subscripts for q_{ij}^k . See (5.15).

qcval

Numerical value for q_{ij}^k .

Obtains all the quadratic terms in a constraint. The quadratic terms are stored sequentially **qcsubi**, **qcsubj**, and **qcval**.

A.2.166 MSK_getqobj()

```

MSKrescodee MSK_getqobj (
    MSKtask_t    task,
    MSKint32t    maxnumqonz,
    MSKint32t *  qosurp,
    MSKint32t *  numqonz,
    MSKint32t *  qosubi,

```

```
MSKint32t * qosubj,
MSKrealt * qoval);
```

Obtains all the quadratic terms in the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumqonz

The length of the arrays **qosubi**, **qosubj**, and **qoval**.

qosurp

When entering the function **qosurp**[0] is the number of free positions at the end of the arrays **qosubi**, **qosubj**, and **qoval**, and upon return **qosurp** is the updated number of free positions left in those arrays.

numqonz

Number of non-zero elements in Q^o .

qosubi

i subscript for q_{ij}^o .

qosubj

j subscript for q_{ij}^o .

qoval

Numerical value for q_{ij}^o .

Obtains the quadratic terms in the objective. The required quadratic terms are stored sequentially in **qosubi**, **qosubj**, and **qoval**.

A.2.167 MSK_getqobj64()

```
MSKrescodee MSK_getqobj64 (
    MSKtask_t    task,
    MSKint64t    maxnumqonz,
    MSKint64t *  qosurp,
    MSKint64t *  numqonz,
    MSKint32t *  qosubi,
    MSKint32t *  qosubj,
    MSKrealt *   qoval);
```

Obtains all the quadratic terms in the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumqonz

The length of the arrays **qosubi**, **qosubj**, and **qoval**.

qosurp

When entering the function **qosurp**[0] is the number of free positions at the end of the arrays **qosubi**, **qosubj**, and **qoval**, and upon return **qosurp** is the updated number of free positions left in those arrays.

numqonz

Number of non-zero elements in Q^o .

qosubi

i subscript for q_{ij}^o .

qosubj

j subscript for q_{ij}^o .

qoval

Numerical value for q_{ij}^o .

Obtains the quadratic terms in the objective. The required quadratic terms are stored sequentially in **qosubi**, **qosubj**, and **qoval**.

A.2.168 MSK_getqobjij()

```
MSKrescodee MSK_getqobjij (
    MSKtask_t    task,
    MSKint32t    i,
    MSKint32t    j,
    MSKrealt *   qoij);
```

Obtains one coefficient from the quadratic term of the objective

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Row index of the coefficient.

j

Column index of coefficient.

qoij

The required coefficient.

Obtains one coefficient q_{ij}^o in the quadratic term of the objective.

A.2.169 MSK_getreducedcosts()

```
MSKrescodee MSK_getreducedcosts (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKrealt *     redcosts);
```

Obtains the difference of (slx-sux) for a sequence of variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

See formula (A.3) for the definition.

last

See formula (A.3) for the definition.

redcosts

The reduced costs in the required sequence of variables are stored sequentially in **redcosts** starting at **redcosts[0]**.

Computes the reduced costs for a sequence of variables and return them in the variable **redcosts** i.e.

$$\text{redcosts}[j - \text{first}] = (s_l^x)_j - (s_u^x)_j, \quad j = \text{first}, \dots, \text{last} - 1. \quad (\text{A.3})$$

A.2.170 MSK_getresponseclass()

```
MSKrescodee MSK_getresponseclass (
    MSKrescodee    r,
    MSKrescodetype * rc);
```

Obtain the class of a response code.

Returns:

A response code indicating the status of the function call.

r

A response code indicating the result of function call.

rc

The return response class

Obtain the class of a response code.

A.2.171 MSK_getskc()

```
MSKrescodee MSK_getskc (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKstakeye *   skc);
```

Obtains the status keys for the constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

skc

Status keys for the constraints.

Obtains the status keys for the constraints.

See also

- **MSK_getskcslice** Obtains the status keys for the constraints.

A.2.172 MSK_getskcslice()

```
MSKrescodee MSK_getskcslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKstakeye *   skc);
```

Obtains the status keys for the constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

skc

Status keys for the constraints.

Obtains the status keys for the constraints.

See also

- **MSK_getskc** Obtains the status keys for the constraints.

A.2.173 MSK_getskx()

```
MSKrescodee MSK_getskx (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKstakeye * skx);
```

Obtains the status keys for the scalar variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

skx

Status keys for the variables.

Obtains the status keys for the scalar variables.

See also

- **MSK_getskxslice** Obtains the status keys for the variables.

A.2.174 MSK_getskxslice()

```
MSKrescodee MSK_getskxslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKstakeye *   skx);
```

Obtains the status keys for the variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

skx

Status keys for the variables.

Obtains the status keys for the variables.

A.2.175 MSK_getslc()

```
MSKrescodee MSK_getslc (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKrealt *     slc);
```

Obtains the slc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

slc

The s_l^c vector.

Obtains the s_l^c vector for a solution.

See also

- **MSK_getslcslice** Obtains a slice of the slc vector for a solution.

A.2.176 MSK_getslcslice()

```
MSKrescodee MSK_getslcslice (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKint32t    first,
    MSKint32t    last,
    MSKrealt *   slc);
```

Obtains a slice of the slc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

slc

Dual variables corresponding to the lower bounds on the constraints (s_l^c).

Obtains a slice of the s_l^c vector for a solution.

See also

- **MSK_getslc** Obtains the slc vector for a solution.

A.2.177 MSK_getslx()

```
MSKrescodee MSK_getslx (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKrealt *   slx);
```

Obtains the slx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

slx

The s_l^x vector.

Obtains the s_l^x vector for a solution.

See also

- **MSK_getslx** Obtains the slx vector for a solution.

A.2.178 MSK_getslxslice()

```
MSKrescodee MSK_getslxslice (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKint32t    first,
    MSKint32t    last,
    MSKrealt *   slx);
```

Obtains a slice of the slx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

slx

Dual variables corresponding to the lower bounds on the variables (s_l^x).

Obtains a slice of the s_l^x vector for a solution.

See also

- **MSK_getslx** Obtains the slx vector for a solution.

A.2.179 MSK_getsnx()

```
MSKrescodee MSK_getsnx (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKrealt *   snx);
```

Obtains the snx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

snx

The s_n^x vector.

Obtains the s_n^x vector for a solution.

See also

- **MSK_getsnxslice** Obtains a slice of the snx vector for a solution.

A.2.180 MSK_getsnxslice()

```
MSKrescodee MSK_getsnxslice (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKint32t    first,
    MSKint32t    last,
    MSKrealt *   snx);
```

Obtains a slice of the snx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

snx

Dual variables corresponding to the conic constraints on the variables (s_n^x).

Obtains a slice of the s_n^x vector for a solution.

See also

- **MSK_getsnx** Obtains the snx vector for a solution.

A.2.181 MSK_getsolsta()

```
MSKrescodee MSK_getsolsta (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKsolstae * solsta);
```

Obtains the solution status.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

solsta

Solution status.

Obtains the solution status.

A.2.182 MSK_getsolution()

```

MSKrescodee MSK_getsolution (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKprosta *    prosta,
    MSKsolsta *    solsta,
    MSKstakeye *   skc,
    MSKstakeye *   skx,
    MSKstakeye *   skn,
    MSKrealt *     xc,
    MSKrealt *     xx,
    MSKrealt *     y,
    MSKrealt *     slc,
    MSKrealt *     suc,
    MSKrealt *     slx,
    MSKrealt *     sux,
    MSKrealt *     snx);

```

Obtains the complete solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

prosta

Problem status.

solsta

Solution status.

skc

Status keys for the constraints.

skx

Status keys for the variables.

skn

Status keys for the conic constraints.

xc

Primal constraint solution.

xx

Primal variable solution (x).

y

Vector of dual variables corresponding to the constraints.

slcDual variables corresponding to the lower bounds on the constraints (s_l^c).**suc**Dual variables corresponding to the upper bounds on the constraints (s_u^c).**slx**Dual variables corresponding to the lower bounds on the variables (s_l^x).**sux**Dual variables corresponding to the upper bounds on the variables (appears as s_u^x).**snx**Dual variables corresponding to the conic constraints on the variables (s_n^x).

Obtains the complete solution.

Consider the case of linear programming. The primal problem is given by

$$\begin{array}{ll}
\text{minimize} & c^T x + c^f \\
\text{subject to} & l^c \leq Ax \leq u^c, \\
& l^x \leq x \leq u^x.
\end{array}$$

and the corresponding dual problem is

$$\begin{array}{ll}
\text{maximize} & (l^c)^T s_l^c - (u^c)^T s_u^c \\
& + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\
\text{subject to} & A^T y + s_l^x - s_u^x = c, \\
& -y + s_l^c - s_u^c = 0, \\
& s_l^c, s_u^c, s_l^x, s_u^x \geq 0.
\end{array}$$

In this case the mapping between variables and arguments to the function is as follows:

xx:Corresponds to variable x .**y:**Corresponds to variable y .**slc:**Corresponds to variable s_l^c .**suc:**Corresponds to variable s_u^c .**slx:**Corresponds to variable s_l^x .**sux:**Corresponds to variable s_u^x .**xc:**Corresponds to Ax .

The meaning of the values returned by this function depend on the *solution status* returned in the argument `solsta`. The most important possible values of `solsta` are:

MSK_SOL_STA_OPTIMAL

An optimal solution satisfying the optimality criteria for continuous problems is returned.

MSK_SOL_STA_INTEGER_OPTIMAL

An optimal solution satisfying the optimality criteria for integer problems is returned.

MSK_SOL_STA_PRIM_FEAS

A solution satisfying the feasibility criteria.

MSK_SOL_STA_PRIM_INFEAS_CER

A primal certificate of infeasibility is returned.

MSK_SOL_STA_DUAL_INFEAS_CER

A dual certificate of infeasibility is returned.

See also

- **MSK_getsolutioni** Obtains the solution for a single constraint or variable.
- **MSK_getsolutionslice** Obtains a slice of the solution.

A.2.183 MSK_getsolutioni()

```
MSKrescodee MSK_getsolutioni (
    MSKtask_t    task,
    MSKaccmodee  accmode,
    MSKint32t    i,
    MSKsolttypee whichsol,
    MSKstakeye * sk,
    MSKrealt *   x,
    MSKrealt *   sl,
    MSKrealt *   su,
    MSKrealt *   sn);
```

Obtains the solution for a single constraint or variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

If set to **MSK_ACC_CON** the solution information for a constraint is retrieved. Otherwise for a variable.

i

Index of the constraint or variable.

whichsol

Selects a solution.

sk

Status key of the constraint of variable.

x

Solution value of the primal variable.

sl

Solution value of the dual variable associated with the lower bound.

su

Solution value of the dual variable associated with the upper bound.

sn

Solution value of the dual variable associated with the cone constraint.

Obtains the primal and dual solution information for a single constraint or variable.

See also

- **MSK_getsolution** Obtains the complete solution.
- **MSK_getsolutionslice** Obtains a slice of the solution.

A.2.184 MSK_getsolutionincallback()

```

MSKrescodee MSK_getsolutionincallback (
    MSKtask_t      task,
    MSKcallbackcodee where,
    MSKsoltypee    whichsol,
    MSKprosta *    prosta,
    MSKsolstae *   solsta,
    MSKstakeye *   skc,
    MSKstakeye *   skx,
    MSKstakeye *   skn,
    MSKrealt *     xc,
    MSKrealt *     xx,
    MSKrealt *     y,
    MSKrealt *     slc,
    MSKrealt *     suc,
    MSKrealt *     slx,
    MSKrealt *     sux,
    MSKrealt *     snx);

```

Obtains the whole or a part of the solution from the progress call-back function.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

where

The call-back-key from the current call-back

whichsol

Selects a solution.

prosta

Problem status.

solsta

Solution status.

skc

Status keys for the constraints.

skx

Status keys for the variables.

skn

Status keys for the conic constraints.

xc

Primal constraint solution.

xx

Primal variable solution (x).

y

Vector of dual variables corresponding to the constraints.

slc

Dual variables corresponding to the lower bounds on the constraints (s_l^c).

suc

Dual variables corresponding to the upper bounds on the constraints (s_u^c).

slx

Dual variables corresponding to the lower bounds on the variables (s_l^x).

sux

Dual variables corresponding to the upper bounds on the variables (appears as s_u^x).

snx

Dual variables corresponding to the conic constraints on the variables (s_n^x).

Obtains the whole or a part of the solution from within a progress call-back. This function must only be called from a progress call-back function.

This is an experimental feature. Please contact MOSEK support before using this function.

A.2.185 MSK_getsolutioninf()

```

MSKrescodee MSK_getsolutioninf (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKprosta *    prosta,
    MSKsolsta *    solsta,
    MSKrealt *     primalobj,
    MSKrealt *     maxpbi,
    MSKrealt *     maxpcni,
    MSKrealt *     maxpeqi,
    MSKrealt *     maxinti,
    MSKrealt *     dualobj,
    MSKrealt *     maxdbi,
    MSKrealt *     maxdcni,
    MSKrealt *     maxdeqi);

```

Deprecated

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

prosta

Problem status.

solsta

Solution status.

primalobj

Value of the primal objective.

$$c^T x + c^f$$

maxpbi

Maximum infeasibility in primal bounds on variables.

$$\max \{0, \max_{i \in 1, \dots, n-1} (x_i - u_i^x), \max_{i \in 1, \dots, n-1} (l_i^x - x_i), \max_{i \in 1, \dots, n-1} (x_i^c - u_i^c), \max_{i \in 1, \dots, n-1} (l_i^c - x_i^c)\}$$

maxpcni

Maximum infeasibility in the primal conic constraints.

maxpeqi

Maximum infeasibility in primal equality constraints.

$$\|Ax - x^c\|_\infty$$

maxinti

Maximum infeasibility in integer constraints.

$$\max_{i \in \{0, \dots, n-1\}} (\min(x_i - \lfloor x_i \rfloor, \lceil x_i \rceil - x_i)).$$

dualobj

Value of the dual objective.

$$(l^c)^T s_l^c - (u^c)^T s_u^c + c^f$$

maxdbi

Maximum infeasibility in bounds on dual variables.

$$\max\{0, \max_{i \in \{0, \dots, n-1\}} -(s_l^x)_i, \max_{i \in \{0, \dots, n-1\}} -(s_u^x)_i, \max_{i \in \{0, \dots, m-1\}} -(s_l^c)_i, \max_{i \in \{0, \dots, m-1\}} -(s_u^c)_i\}$$

maxdcni

Maximum infeasibility in the dual conic constraints.

maxdeqi

Maximum infeasibility in the dual equality constraints.

$$\max\{\|A^T y + s_l^x - s_u^x - c\|_\infty, \|-y + s_l^c - s_u^c\|_\infty\}$$

Deprecated. Use **MSK_getsolutioninfo** instead.

A.2.186 MSK_getsolutioninfo()

```
MSKrescodee MSK_getsolutioninfo (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKrealt *     pobj,
    MSKrealt *     pviolcon,
    MSKrealt *     pviolvar,
    MSKrealt *     pviolbarvar,
    MSKrealt *     pviolcone,
    MSKrealt *     pviolitg,
    MSKrealt *     dobj,
    MSKrealt *     dviolcon,
    MSKrealt *     dviolvar,
    MSKrealt *     dviolbarvar,
    MSKrealt *     dviolcone);
```

Obtains information about of a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

pobj

The primal objective value as computed by **MSK_getprimalobj**.

pviolcon

Maximal primal violation of the solution associated with the x^c variables where the violations are computed by **MSK_getpviolcon**.

pviolvar

Maximal primal violation of the solution for the x^x variables where the violations are computed by **MSK_getpviolvar**.

pviolbarvar

Maximal primal violation of solution for the \bar{X} variables where the violations are computed by **MSK_getpviolbarvar**.

pviolcone

Maximal primal violation of solution for the conic constraints where the violations are computed by **MSK_getpviolcones**.

pviolitg

Maximal violation in the integer constraints. The violation for an integer constrained variable x_j is given by

$$\min(x_j - \lfloor x_j \rfloor, \lceil x_j \rceil - x_j).$$

This number is always zero for the interior-point and the basic solutions.

dobj

Dual objective value as computed as computed by **MSK_getdualobj**.

dviolcon

Maximal violation of the dual solution associated with the x^c variable as computed by as computed by **MSK_getdviolcon**.

dviolvar

Maximal violation of the dual solution associated with the x variable as computed by as computed by **MSK_getdviolvar**.

dviolbarvar

Maximal violation of the dual solution associated with the \bar{s} variable as computed by as computed by **MSK_getdviolbarvar**.

dviolcone

Maximal violation of the dual solution associated with the dual conic constraints as computed by **MSK_getdviolcones**.

Obtains information about a solution.

See also

- **MSK_getsolsta** Obtains the solution status.
- **MSK_getprimalobj** Computes the primal objective value for the desired solution.
- **MSK_getpviolcon** Computes the violation of a primal solution for a list of xc variables.
- **MSK_getpviolvar** Computes the violation of a primal solution for a list of x variables.
- **MSK_getpviolbarvar** Computes the violation of a primal solution for a list of barx variables.
- **MSK_getpviolcones** Computes the violation of a solution for set of conic constraints.
- **MSK_getdualobj** Computes the dual objective value associated with the solution.
- **MSK_getdviolcon** Computes the violation of a dual solution associated with a set of constraints.
- **MSK_getdviolvar** Computes the violation of a dual solution associated with a set of x variables.
- **MSK_getdviolbarvar** Computes the violation of dual solution for a set of barx variables.
- **MSK_getdviolcones** Computes the violation of a solution for set of dual conic constraints.

A.2.187 MSK_getsolutionslice()

```
MSKrescodee MSK_getsolutionslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKsoliteme    solitem,
    MSKint32t      first,
    MSKint32t      last,
    MSKrealt *     values);
```

Obtains a slice of the solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

solitem

Which part of the solution is required.

first

Index of the first value in the slice.

last

Value of the last index+1 in the slice, e.g. if $xx[5, \dots, 9]$ is required **last** should be 10.

values

The values in the required sequence are stored sequentially in **values** starting at **values[0]**.

Obtains a slice of the solution.

Consider the case of linear programming. The primal problem is given by

$$\begin{array}{llllll} \text{minimize} & & c^T x + c^f & & & \\ \text{subject to} & l^c & \leq & Ax & \leq & u^c, \\ & l^x & \leq & x & \leq & u^x. \end{array}$$

and the corresponding dual problem is

$$\begin{array}{llll} \text{maximize} & (l^c)^T s_l^c - (u^c)^T s_u^c \\ & + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ \text{subject to} & A^T y + s_l^x - s_u^x & = & c, \\ & -y + s_l^c - s_u^c & = & 0, \\ & s_l^c, s_u^c, s_l^x, s_u^x \geq 0. \end{array}$$

The **solitem** argument determines which part of the solution is returned:

MSK_SOL_ITEM_XX:

The variable **values** return x .

MSK_SOL_ITEM_Y:

The variable **values** return y .

MSK_SOL_ITEM_SLC:

The variable **values** return s_l^c .

MSK_SOL_ITEM_SUC:

The variable **values** return s_u^c .

MSK_SOL_ITEM_SLX:

The variable **values** return s_l^x .

MSK_SOL_ITEM_SUX:

The variable **values** return s_u^x .

A conic optimization problem has the same primal variables as in the linear case. Recall that the dual of a conic optimization problem is given by:

$$\begin{array}{llll} \text{maximize} & (l^c)^T s_l^c - (u^c)^T s_u^c \\ & + (l^x)^T s_l^x - (u^x)^T s_u^x + c^f \\ \text{subject to} & A^T y + s_l^x - s_u^x + s_n^x & = & c, \\ & -y + s_l^c - s_u^c & = & 0, \\ & s_l^c, s_u^c, s_l^x, s_u^x & \geq & 0, \\ & s_n^x \in \mathcal{C}^* \end{array}$$

This introduces one additional dual variable s_n^x . This variable can be accessed by selecting **solitem** as **MSK_SOL_ITEM_SNX**.

The meaning of the values returned by this function also depends on the *solution status* which can be obtained with **MSK.getsolsta**. Depending on the solution status **value** will be:

MSK_SOL_STA_OPTIMAL

A part of the optimal solution satisfying the optimality criteria for continuous problems.

MSK_SOL_STA_INTEGER_OPTIMAL

A part of the optimal solution satisfying the optimality criteria for integer problems.

MSK_SOL_STA_PRIM_FEAS

A part of the solution satisfying the feasibility criteria.

MSK_SOL_STA_PRIM_INFEAS_CER

A part of the primal certificate of infeasibility.

MSK_SOL_STA_DUAL_INFEAS_CER

A part of the dual certificate of infeasibility.

See also

- **MSK_getsolution** Obtains the complete solution.
- **MSK_getsolutioni** Obtains the solution for a single constraint or variable.

A.2.188 MSK_getsparsesymmat()

```
MSKrescodee MSK_getsparsesymmat (
    MSKtask_t    task,
    MSKint64t    idx,
    MSKint64t    maxlen,
    MSKint32t *   subi,
    MSKint32t *   subj,
    MSKrealt *    valij);
```

Gets a single symmetric matrix from the matrix store.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

idx

Index of the matrix to get.

maxlen

Length of the output arrays **subi**, **subj** and **valij**.

subi

Row subscripts of the matrix non-zero elements.

subj

Column subscripts of the matrix non-zero elements.

valij

Coefficients of the matrix non-zero elements.

Get a single symmetric matrix from the matrix store.

A.2.189 MSK_getstrparam()

```
MSKrescodee MSK_getstrparam (
    MSKtask_t    task,
    MSKsparame   param,
    MSKint32t    maxlen,
    MSKint32t *   len,
    char *        parvalue);
```

Obtains the value of a string parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

param

Which parameter.

maxlen

Length of the **parvalue** buffer.

len

The length of the parameter value.

parvalue

If this is not NULL, the parameter value is stored here.

Obtains the value of a string parameter.

A.2.190 MSK_getstrparamal()

```
MSKrescodee MSK_getstrparamal (
    MSKtask_t    task,
    MSKsparame   param,
    MSKint32t    numaddchr,
    MSKstring_t * value);
```

Obtains the value a string parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

param

Which parameter.

`numaddchr`

Number of additional characters that is made room for in `value[0]`.

`value`

Is the value corresponding to string parameter `param`. `value[0]` is char buffer allocated MOSEK and it must be freed by `MSK_freetask`.

Obtains the value of a string parameter.

A.2.191 `MSK_getstrparamlen()`

```
MSKrescodee MSK_getstrparamlen (
    MSKtask_t    task,
    MSKsparame   param,
    MSKint32t *  len);
```

Obtains the length of a string parameter.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`param`

Which parameter.

`len`

The length of the parameter value.

Obtains the length of a string parameter.

A.2.192 `MSK_getsuc()`

```
MSKrescodee MSK_getsuc (
    MSKtask_t    task,
    MSKsoltypee   whichsol,
    MSKrealt *    suc);
```

Obtains the suc vector for a solution.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

whichsol

Selects a solution.

suc

The s_u^c vector.

Obtains the s_u^c vector for a solution.

See also

- **MSK_getsucslice** Obtains a slice of the suc vector for a solution.

A.2.193 MSK_getsucslice()

```
MSKrescodee MSK_getsucslice (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKint32t    first,
    MSKint32t    last,
    MSKrealt *   suc);
```

Obtains a slice of the suc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

suc

Dual variables corresponding to the upper bounds on the constraints (s_u^c).

Obtains a slice of the s_u^c vector for a solution.

See also

- **MSK_getsuc** Obtains the suc vector for a solution.

A.2.194 MSK_getsux()

```
MSKrescodee MSK_getsux (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKrealt *   sux);
```

Obtains the sux vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

sux

The s_u^x vector.

Obtains the s_u^x vector for a solution.

See also

- **MSK_getsuxslice** Obtains a slice of the sux vector for a solution.

A.2.195 MSK_getsuxslice()

```
MSKrescodee MSK_getsuxslice (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKint32t    first,
    MSKint32t    last,
    MSKrealt *   sux);
```

Obtains a slice of the sux vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

sux

Dual variables corresponding to the upper bounds on the variables (appears as s_u^x).

Obtains a slice of the s_u^x vector for a solution.

See also

- **MSK_getsux** Obtains the sux vector for a solution.

A.2.196 MSK_getsymbcon()

```
MSKrescodee MSK_getsymbcon (
    MSKtask_t    task,
    MSKint32t    i,
    MSKint32t    maxlen,
    char *       name,
    MSKint32t *  value);
```

Obtains a cone type string identifier.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index.

maxlen

The length of the buffer pointed to by the **value** argument.

name

Name of the i th symbolic constant.

value

The corresponding value.

Obtains the name and corresponding value for the i th symbolic constant.

A.2.197 MSK_getsymbcondim()

```
MSKrescodee MSK_getsymbcondim (
    MSKenv_t     env,
    MSKint32t *  num,
```

```
size_t *    maxlen);
```

Obtains dimensional information for the defined symbolic constants.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

num

Number of symbolic constants defined by MOSEK.

maxlen

Maximum length of the name of any symbolic constants.

Obtains the number of symbolic constants defined by MOSEK and the maximum length of the name of any symbolic constant.

A.2.198 MSK_getsymmatinfo()

```
MSKrescodee MSK_getsymmatinfo (
    MSKtask_t      task,
    MSKint64t      idx,
    MSKint32t *    dim,
    MSKint64t *    nz,
    MSKsymmattypee * type);
```

Obtains information of a matrix from the symmetric matrix storage E .

Returns:

A response code indicating the status of the function call.

task

An optimization task.

idx

Index of the matrix that is requested information about.

dim

Returns the dimension of the requested matrix.

nz

Returns the number of non-zeros in the requested matrix.

type

Returns the type of the requested matrix.

MOSEK maintains a vector denoted E of symmetric data matrixes. This function makes it possible to obtain important information about an data matrix in E .

A.2.199 MSK_gettaskname()

```
MSKrescodee MSK_gettaskname (  
    MSKtask_t  task,  
    MSKint32t  maxlen,  
    char *     taskname);
```

Obtains the task name.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxlen

Length of the **taskname** array.

taskname

Is assigned the task name.

Obtains the name assigned to the task.

A.2.200 MSK_gettasknamelen()

```
MSKrescodee MSK_gettasknamelen (  
    MSKtask_t  task,  
    MSKint32t * len);
```

Obtains the length the task name.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

len

Returns the length of the task name.

Obtains the length the task name.

See also

- **MSK_getbarvarname** Obtains a name of a semidefinite variable.

A.2.201 MSK_getvarbound()

```
MSKrescodee MSK_getvarbound (
    MSKtask_t      task,
    MSKint32t      i,
    MSKboundkeye * bk,
    MSKrealt *     bl,
    MSKrealt *     bu);
```

Obtains bound information for one variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index of the variable for which the bound information should be obtained.

bk

Bound keys.

bl

Values for lower bounds.

bu

Values for upper bounds.

Obtains bound information for one variable.

A.2.202 MSK_getvarboundslice()

```
MSKrescodee MSK_getvarboundslice (
    MSKtask_t      task,
    MSKint32t      first,
    MSKint32t      last,
    MSKboundkeye * bk,
    MSKrealt *     bl,
    MSKrealt *     bu);
```

Obtains bounds information for a slice of the variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first
First index in the sequence.

last
Last index plus 1 in the sequence.

bk
Bound keys.

bl
Values for lower bounds.

bu
Values for upper bounds.

Obtains bounds information for a slice of the variables.

A.2.203 MSK_getvarbranchdir()

```
MSKrescodee MSK_getvarbranchdir (
    MSKtask_t      task,
    MSKint32t      j,
    MSKbranchdire * direction);
```

Obtains the branching direction for a variable.

Returns:

A response code indicating the status of the function call.

task
An optimization task.

j
Index of the variable.

direction
The branching direction assigned to variable j .

Obtains the branching direction for a given variable j .

A.2.204 MSK_getvarbranchorder()

```
MSKrescodee MSK_getvarbranchorder (
    MSKtask_t      task,
    MSKint32t      j,
    MSKint32t *    priority,
    MSKbranchdire * direction);
```

Obtains the branching priority for a variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable.

priority

The branching priority assigned to variable j .

direction

The preferred branching direction for the j 'th variable.

Obtains the branching priority and direction for a given variable j .

A.2.205 `MSK_getvarbranchpri()`

```
MSKrescodee MSK_getvarbranchpri (
    MSKtask_t    task,
    MSKint32t    j,
    MSKint32t *  priority);
```

Obtains the branching priority for a variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable.

priority

The branching priority assigned to variable j .

Obtains the branching priority for a given variable j .

A.2.206 `MSK_getvarname()`

```
MSKrescodee MSK_getvarname (
    MSKtask_t    task,
    MSKint32t    j,
    MSKint32t    maxlen,
    char *        name);
```

Obtains a name of a variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index.

maxlen

The length of the buffer pointed to by the **name** argument.

name

Is assigned the required name.

Obtains a name of a variable.

See also

- **MSK.getmaxnamelen** Obtains the maximum length (not including terminating zero character) of any objective, constraint, variable or cone name.

A.2.207 MSK_getvarnameindex()

```
MSKrescodee MSK_getvarnameindex (
    MSKtask_t      task,
    MSKCONST char * somename,
    MSKint32t *    asgn,
    MSKint32t *    index);
```

Checks whether the name **somename** has been assigned to any variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

somename

The name which should be checked.

asgn

Is non-zero if the name **somename** is assigned to a variable.

index

If the name **somename** is assigned to a variable, then **index** is the name of the variable.

Checks whether the name **somename** has been assigned to any variable. If it has been assigned to variable, then index of the variable is reported.

A.2.208 MSK_getvarnamelen()

```
MSKrescodee MSK_getvarnamelen (
    MSKtask_t    task,
    MSKint32t    i,
    MSKint32t *  len);
```

Obtains the length of a name of a variable variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index.

len

Returns the length of the indicated name.

Obtains the length of a name of a variable variable.

See also

- **MSK_getbarvarname** Obtains a name of a semidefinite variable.

A.2.209 MSK_getvartype()

```
MSKrescodee MSK_getvartype (
    MSKtask_t    task,
    MSKint32t    j,
    MSKvariabletypee *  vartype);
```

Gets the variable type of one variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable.

vartype

Variable type of variable j.

Gets the variable type of one variable.

A.2.210 MSK_getvartypelist()

```
MSKrescodee MSK_getvartypelist (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * subj,
    MSKvariabletypee * vartype);
```

Obtains the variable type for one or more variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of variables for which the variable type should be obtained.

subj

A list of variable indexes.

vartype

The variables types corresponding to the variables specified by **subj**.

Obtains the variable type of one or more variables.

Upon return **vartype[k]** is the variable type of variable **subj[k]**.

A.2.211 MSK_getversion()

```
MSKrescodee MSK_getversion (
    MSKint32t * major,
    MSKint32t * minor,
    MSKint32t * build,
    MSKint32t * revision);
```

Obtains MOSEK version information.

Returns:

A response code indicating the status of the function call.

major

Major version number.

minor

Minor version number.

build

Build number.

revision

Revision number.

Obtains MOSEK version information.

A.2.212 MSK_getxc()

```
MSKrescodee MSK_getxc (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKrealt *   xc);
```

Obtains the xc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

xc

The x^c vector.

Obtains the x^c vector for a solution.

See also

- **MSK_getxcslice** Obtains a slice of the xc vector for a solution.

A.2.213 MSK_getxcslice()

```
MSKrescodee MSK_getxcslice (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKint32t    first,
    MSKint32t    last,
    MSKrealt *   xc);
```

Obtains a slice of the xc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

xc

Primal constraint solution.

Obtains a slice of the x^c vector for a solution.

See also

- **MSK_getxc** Obtains the xc vector for a solution.

A.2.214 MSK_getxx()

```
MSKrescodee MSK_getxx (
    MSKtask_t   task,
    MSKsoltypee whichsol,
    MSKrealt *  xx);
```

Obtains the xx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

xx

The x^x vector.

Obtains the x^x vector for a solution.

See also

- **MSK_getxxslice** Obtains a slice of the xx vector for a solution.

A.2.215 MSK_getxxslice()

```
MSKrescodee MSK_getxxslice (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKint32t    first,
    MSKint32t    last,
    MSKrealt *   xx);
```

Obtains a slice of the xx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

xx

Primal variable solution (x).

Obtains a slice of the x^x vector for a solution.

See also

- **MSK_getxx** Obtains the xx vector for a solution.

A.2.216 MSK_gety()

```
MSKrescodee MSK_gety (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKrealt *   y);
```

Obtains the y vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

yThe y vector.Obtains the y vector for a solution.

See also

- **MSK_getyslice** Obtains a slice of the y vector for a solution.

A.2.217 MSK_getyslice()

```
MSKrescodee MSK_getyslice (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKint32t    first,
    MSKint32t    last,
    MSKrealt *   y);
```

Obtains a slice of the y vector for a solution.**Returns:**

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

y

Vector of dual variables corresponding to the constraints.

Obtains a slice of the y vector for a solution.

See also

- **MSK_gety** Obtains the y vector for a solution.

A.2.218 MSK_initbasissolve()

```
MSKrescodee MSK_initbasissolve (
    MSKtask_t    task,
    MSKint32t *  basis);
```

Prepare a task for basis solver.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

basis

The array of basis indexes to use.

The array is interpreted as follows: If $\text{basis}[i] \leq \text{numcon} - 1$, then $x_{\text{basis}[i]}^c$ is in the basis at position i , otherwise $x_{\text{basis}[i] - \text{numcon}}$ is in the basis at position i .

Prepare a task for use with the **MSK_solvewithbasis** function.

This function should be called

- immediately before the first call to **MSK_solvewithbasis**, and
- immediately before any subsequent call to **MSK_solvewithbasis** if the task has been modified.

If the basis is singular i.e. not invertible, then

the response code **MSK_RES_ERR_BASIS_SINGULAR**.

A.2.219 MSK_initenv()

```
MSKrescodee MSK_initenv (MSKenv_t  env)
```

Initialize a MOSEK environment.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

This function initializes the MOSEK environment. Among other things the license server will be contacted. Error messages from the license manager can be captured by linking to the environment message stream before calling this function.

A.2.220 MSK_inputdata()

```

MSKrescodee MSK_inputdata (
    MSKtask_t          task,
    MSKint32t          maxnumcon,
    MSKint32t          maxnumvar,
    MSKint32t          numcon,
    MSKint32t          numvar,
    MSKCONST MSKrealt * c,
    MSKrealt          cfix,
    MSKCONST MSKint32t * aptrb,
    MSKCONST MSKint32t * aptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt * aval,
    MSKCONST MSKboundkeye * bkc,
    MSKCONST MSKrealt * blc,
    MSKCONST MSKrealt * buc,
    MSKCONST MSKboundkeye * bkc,
    MSKCONST MSKrealt * blx,
    MSKCONST MSKrealt * bux);

```

Input the linear part of an optimization task in one function call.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumcon

Number of preallocated constraints in the optimization task.

maxnumvar

Number of preallocated variables in the optimization task.

numcon

Number of constraints.

numvar

Number of variables.

c

Linear terms of the objective as a dense vector. The length is the number of variables.

cfix

Fixed term in the objective.

aptrb

Pointer to the first element in the rows or the columns of A . See (5.16) and Section 5.13.3.

aptre

Pointers to the last element + 1 in the rows or the columns of A . See (5.16) and Section 5.13.3

asub

Coefficient subscripts. See (5.16) and Section 5.13.3.

aval

Coefficient values. See (5.16) and Section 5.13.3.

bkc

Bound keys for the constraints.

blc

Lower bounds for the constraints.

buc

Upper bounds for the constraints.

bkx

Bound keys for the variables.

blx

Lower bounds for the variables.

bux

Upper bounds for the variables.

Input the linear part of an optimization problem.

The non-zeros of A are inputted column-wise in the format described in Section 5.13.3.2.

For an explained code example see Section 5.2 and Section 5.13.3.

A.2.221 MSK_inputdata64()

```
MSKrescodee MSK_inputdata64 (
    MSKtask_t          task,
    MSKint32t           maxnumcon,
    MSKint32t           maxnumvar,
    MSKint32t           numcon,
    MSKint32t           numvar,
    MSKCONST MSKrealt * c,
    MSKrealt           cfix,
    MSKCONST MSKint64t * aptrb,
    MSKCONST MSKint64t * aptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt * aval,
    MSKCONST MSKboundkeye * bkc,
    MSKCONST MSKrealt * blc,
    MSKCONST MSKrealt * buc,
    MSKCONST MSKboundkeye * bkx,
    MSKCONST MSKrealt * blx,
    MSKCONST MSKrealt * bux);
```

Input the linear part of an optimization task in one function call.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumcon

Number of preallocated constraints in the optimization task.

maxnumvar

Number of preallocated variables in the optimization task.

numcon

Number of constraints.

numvar

Number of variables.

c

Linear terms of the objective as a dense vector. The length is the number of variables.

cfix

Fixed term in the objective.

aptrb

Pointer to the first element in the rows or the columns of A . See (5.16) and Section 5.13.3.

aptre

Pointers to the last element + 1 in the rows or the columns of A . See (5.16) and Section 5.13.3

asub

Coefficient subscripts. See (5.16) and Section 5.13.3.

aval

Coefficient values. See (5.16) and Section 5.13.3.

bkc

Bound keys for the constraints.

blc

Lower bounds for the constraints.

buc

Upper bounds for the constraints.

bkx

Bound keys for the variables.

blx

Lower bounds for the variables.

bux

Upper bounds for the variables.

Input the linear part of an optimization problem.

The non-zeros of A are inputted column-wise in the format described in Section 5.13.3.2.

For an explained code example see Section 5.2 and Section 5.13.3.

A.2.222 MSK_iparvaltosymnam()

```
MSKrescodee MSK_iparvaltosymnam (
    MSKenv_t      env,
    MSKiparam     whichparam,
    MSKint32t     whichvalue,
    char *        symbolicname);
```

Obtains the symbolic name corresponding to a value that can be assigned to an integer parameter.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

whichparam

Which parameter.

whichvalue

Which value.

symbolicname

The symbolic name corresponding to **whichvalue**.

Obtains the symbolic name corresponding to a value that can be assigned to an integer parameter.

A.2.223 MSK_isdoupurname()

```
MSKrescodee MSK_isdoupurname (
    MSKtask_t      task,
    MSKCONST char * parname,
    MSKdparam *    param);
```

Checks a double parameter name.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

parname

Parameter name.

param

Which parameter.

Checks whether **parname** is a valid double parameter name.

A.2.224 MSK_isinfinity()

```
MSKboolean MSK_isinfinity (MSKrealt value)
```

Return true if value considered infinity by MOSEK.

Returns:

A response code indicating the status of the function call.

value

Return true if **value** considered infinity by MOSEK

A.2.225 MSK_isintparname()

```
MSKrescode MSK_isintparname (
    MSKtask_t      task,
    MSKCONST char * parname,
    MSKiparam *    param);
```

Checks an integer parameter name.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

parname

Parameter name.

param

Which parameter.

Checks whether **parname** is a valid integer parameter name.

A.2.226 MSK_isstrparname()

```
MSKrescode MSK_isstrparname (
    MSKtask_t      task,
    MSKCONST char * parname,
    MSKsparam *    param);
```

Checks a string parameter name.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

parname

Parameter name.

param

Which parameter.

Checks whether **parname** is a valid string parameter name.

A.2.227 MSK_licensecleanup()

```
MSKrescodee MSK_licensecleanup ()
```

Stops all threads and delete all handles used by the license system.

Stops all threads and delete all handles used by the license system. If this function is called, it must be called as the last MOSEK API call. No other MOSEK API calls are valid after this.

A.2.228 MSK_linkfiletoenvstream()

```
MSKrescodee MSK_linkfiletoenvstream (
    MSKenv_t      env,
    MSKstreamtypee whichstream,
    MSKCONST char * filename,
    MSKint32t     append);
```

Directs all output from a stream to a file.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

whichstream

Index of the stream.

filename

Sends all output from the stream defined by **whichstream** to the file given by **filename**.

append

If this argument is non-zero, the output is appended to the file.

Directs all output from a stream to a file.

A.2.229 MSK_linkfiletotaskstream()

```
MSKrescodee MSK_linkfiletotaskstream (
    MSKtask_t      task,
    MSKstreamtypee whichstream,
    MSKCONST char * filename,
    MSKint32t      append);
```

Directs all output from a task stream to a file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

filename

The name of the file where text from the stream defined by **whichstream** is written.

append

If this argument is 0 the output file will be overwritten, otherwise text is append to the output file.

Directs all output from a task stream to a file.

A.2.230 MSK_linkfunctoenvstream()

```
MSKrescodee MSK_linkfunctoenvstream (
    MSKenv_t      env,
    MSKstreamtypee whichstream,
    MSKuserhandle_t handle,
    MSKstreamfunc func);
```

Connects a user-defined function to a stream.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

whichstream

Index of the stream.

handle

A user-defined handle which is passed to the user-defined function **func**.

func

All output to the stream **whichstream** is passed to **func**.

Connects a user-defined function to a stream.

A.2.231 MSK_linkfunctotaskstream()

```
MSKrescodee MSK_linkfunctotaskstream (
    MSKtask_t      task,
    MSKstreamtypee whichstream,
    MSKuserhandle_t handle,
    MSKstreamfunc  func);
```

Connects a user-defined function to a task stream.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

handle

A user-defined handle which is passed to the user-defined function **func**.

func

All output to the stream **whichstream** is passed to **func**.

Connects a user-defined function to a task stream.

A.2.232 MSK_makeemptytask()

```
MSKrescodee MSK_makeemptytask (
    MSKenv_t      env,
    MSKtask_t *   task);
```

Creates a new and empty optimization task.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

task

An optimization task.

Creates a new optimization task.

A.2.233 MSK_makeenv()

```
MSKrescodee MSK_makeenv (
    MSKenv_t *      env,
    MSKCONST char * dbgfile);
```

Creates a new MOSEK environment.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

dbgfile

A user-defined file debug file.

Creates a new MOSEK environment. The environment must be shared among all tasks in a program.

See also

- **MSK_initenv** Initialize a MOSEK environment.
- **MSK_putdllpath** Sets the path to the DLL/shared libraries that MOSEK is loading.
- **MSK_deleteenv** Delete a MOSEK environment.

A.2.234 MSK_makeenvalloc()

```
MSKrescodee MSK_makeenvalloc (
    MSKenv_t *      env,
    MSKUserhandle_t usrptr,
    MSKmallocfunc   usrmalloc,
    MSKcallocfunc   usrcalloc,
    MSKreallocfunc  usrrealloc,
    MSKfreefunc     usrfree,
    MSKCONST char * dbgfile);
```

Creates a new MOSEK environment.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

usrptr

A pointer to user-defined data structure. The pointer is feed into **usrmalloc** and **usrfree**.

usrmalloc

A user-defined **malloc** function or a NULL pointer.

usrcalloc

A user-defined **calloc** function or a NULL pointer.

usrrealloc

A user-defined **realloc** function or a NULL pointer.

usrfree

A user-defined **free** function which is used deallocate space allocated by **usrmalloc**. This function must be defined if **usrmalloc**!=NULL.

dbgfile

A user-defined file debug file.

Creates a new MOSEK environment. The environment must be shared among all tasks in a program.

See also

- **MSK_initenv** Initialize a MOSEK environment.
- **MSK_putdllpath** Sets the path to the DLL/shared libraries that MOSEK is loading.
- **MSK_deleteenv** Delete a MOSEK environment.

A.2.235 MSK_maketask()

```
MSKrescodee MSK_maketask (
    MSKenv_t      env,
    MSKint32t     maxnumcon,
    MSKint32t     maxnumvar,
    MSKtask_t *   task);
```

Creates a new optimization task.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

maxnumcon

An optional estimate on the maximum number of constraints in the task. Can e.g be 0 if no such estimate is known.

maxnumvar

An optional estimate on the maximum number of variables in the task. Can be 0 if no such estimate is known.

task

An optimization task.

Creates a new task.

A.2.236 MSK_onesolutionsummary()

```
MSKrescodee MSK_onesolutionsummary (
    MSKtask_t      task,
    MSKstreamtypee whichstream,
    MSKsoltypee    whichsol);
```

Prints a short summary for the specified solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

whichsol

Selects a solution.

Prints a short summary for a specified solution.

A.2.237 MSK_optimize()

```
MSKrescodee MSK_optimize (MSKtask_t task)
```

Optimizes the problem.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

Calls the optimizer. Depending on the problem type and the selected optimizer this will call one of the optimizers in MOSEK. By default the interior point optimizer will be selected for continuous problems. The optimizer may be selected manually by setting the parameter **MSK_IPAR_OPTIMIZER**.

See also

- **MSK_optimizeconcurrent** Optimize a given task with several optimizers concurrently.
- **MSK_getsolution** Obtains the complete solution.
- **MSK_getsolutioni** Obtains the solution for a single constraint or variable.
- **MSK_getsolutioninfo** Obtains information about of a solution.
- **MSK_IPAR_OPTIMIZER** Controls which optimizer is used to optimize the task.

A.2.238 `MSK_optimizeconcurrent()`

```
MSKrescodee MSK_optimizeconcurrent (
    MSKtask_t      task,
    MSKCONST MSKtask_t * taskarray,
    MSKint32t      num);
```

Optimize a given task with several optimizers concurrently.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

taskarray

An array of `num` tasks.

num

Length of `taskarray`.

Solves several instances of the same problem in parallel, with unique parameter settings for each task. The argument `task` contains the problem to be solved. `taskarray` is a pointer to an array of `num` empty tasks. The task `task` and the `num` tasks pointed to by `taskarray` are solved in parallel. That is `num + 1` threads are started with one optimizer in each. Each of the tasks can be initialized with different parameters, e.g different selection of solver.

All the concurrently running tasks are stopped when the optimizer successfully terminates for one of the tasks. After the function returns `task` contains the solution found by the task that finished first.

After `MSK_optimizeconcurrent` returns `task` holds the optimal solution of the task which finished first. If all the concurrent optimizations finished without providing an optimal solution the error code from the solution of the task `task` is returned.

In summary a call to `MSK_optimizeconcurrent` does the following:

- All data except task parameters (`MSKiparame`, `MSKdparame` and `MSKsparame`) in `task` is copied to each of the tasks in `taskarray`. In particular this means that any solution in `task` is copied to the other tasks. Call-back functions are not copied.
- The tasks `task` and the `num` tasks in `taskarray` are started in parallel.
- When a task finishes providing an optimal solution (or a certificate of infeasibility) its solution is copied to `task` and all other tasks are stopped.

Observe the concurrent optimizer is not deterministic.

For an explained code example see Section 11.6.4.

A.2.239 MSK_optimizersummary()

```
MSKrescodee MSK_optimizersummary (
    MSKtask_t      task,
    MSKstreamtypee whichstream);
```

Prints a short summary with optimizer statistics for last optimization.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

Prints a short summary with optimizer statistics for last optimization.

A.2.240 MSK_optimizetrm()

```
MSKrescodee MSK_optimizetrm (
    MSKtask_t      task,
    MSKrescodee *  trmcode);
```

Optimizes the problem.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

trmcode

Is either **MSK_RES_OK** or a termination response code.

Calls the optimizer. Depending on the problem type and the selected optimizer this will call one of the optimizers in MOSEK. By default the interior point optimizer will be selected for continuous problems. The optimizer may be selected manually by setting the parameter **MSK_IPAR_OPTIMIZER**.

This function is equivalent to **MSK_optimize** except in the case where **MSK_optimize** would have returned a termination response code such as

- **MSK_RES_TRM_MAX_ITERATIONS** or
- **MSK_RES_TRM_STALL**.

Response codes comes in three categories:

- Errors: Indicate that an error has occurred during the optimization. E.g that the optimizer has run out of memory (`MSK_RES_ERR_SPACE`).
- Warnings: Less fatal than errors. E.g `MSK_RES_WRN_LARGE_CJ` indicating possibly problematic problem data.
- Termination codes: Relaying information about the conditions under which the optimizer terminated. E.g `MSK_RES_TRM_MAX_ITERATIONS` indicates that the optimizer finished because it reached the maximum number of iterations specified by the user.

This function returns errors on the left hand side. Warnings are not returned and termination codes are returned in the separate argument `trmcode`.

See also

- `MSK_optimize` Optimizes the problem.
- `MSK_optimizeconcurrent` Optimize a given task with several optimizers concurrently.
- `MSK_getsolution` Obtains the complete solution.
- `MSK_getsolutioni` Obtains the solution for a single constraint or variable.
- `MSK_getsolutioninfo` Obtains information about of a solution.
- `MSK_IPAR_OPTIMIZER` Controls which optimizer is used to optimize the task.

A.2.241 `MSK_potrf()`

```
MSKrescodee MSK_potrf (
    MSKenv_t    env,
    MSKuploe    upto,
    MSKint32t   n,
    MSKrealt *  a);
```

Computes a Cholesky factorization a dense matrix.

Returns:

A response code indicating the status of the function call.

`env`

The MOSEK environment.

`upto`

Indicates whether the upper or lower triangular part of the matrix is stored.

`n`

Dimension of the symmetric matrix.

`a`

A symmetric matrix stored in column-major order. Only the lower or the upper triangular part is used, accordingly with the `upto` parameter. It will contain the result on exit.

Computes a Cholesky factorization of a real symmetric positive definite dense matrix.

A.2.242 MSK_primalrepair()

```

MSKrescodee MSK_primalrepair (
    MSKtask_t      task,
    MSKCONST MSKrealt * wlc,
    MSKCONST MSKrealt * wuc,
    MSKCONST MSKrealt * wlx,
    MSKCONST MSKrealt * wux);

```

The function repairs a primal infeasible optimization problem by adjusting the bounds on the constraints and variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

wlc

$(w_l^c)_i$ is the weight associated with relaxing the lower bound on constraint i . If the weight is negative, then the lower bound is not relaxed. Moreover, if the argument is NULL, then all the weights are assumed to be 1.

wuc

$(w_u^c)_i$ is the weight associated with relaxing the upper bound on constraint i . If the weight is negative, then the upper bound is not relaxed. Moreover, if the argument is NULL, then all the weights are assumed to be 1.

wlx

$(w_l^x)_j$ is the weight associated with relaxing the upper bound on constraint j . If the weight is negative, then the lower bound is not relaxed. Moreover, if the argument is NULL, then all the weights are assumed to be 1.

wux

$(w_l^x)_i$ is the weight associated with relaxing the upper bound on variable j . If the weight is negative, then the upper bound is not relaxed. Moreover, if the argument is NULL, then all the weights are assumed to be 1.

The function repairs a primal infeasible optimization problem by adjusting the bounds on the constraints and variables where the adjustment is computed as the minimal weighted sum relaxation to the bounds on the constraints and variables.

The function is applicable to linear and conic problems possibly having integer constrained variables.

Observe that when computing the minimal weighted relaxation then the termination tolerance specified by the parameters of the task is employed. For instance the parameter **MSK_IPAR_MIO_MODE** can be used make MOSEK ignore the integer constraints during the repair leading to a possibly a much faster repair. However, the drawback is of course that the repaired problem may not have integer feasible solution.

Note the function modifies the bounds on the constraints and variables. If this is not a desired feature, then apply the function to a cloned task.

See also

- **MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER** Controls which optimizer that is used to find the optimal repair.
- **MSK_IPAR_LOG_FEAS_REPAIR** Controls the amount of output printed when performing feasibility repair. A value higher than one means extensive logging.
- **MSK_DINF_PRIMAL_REPAIR_PENALTY_OBJ** The optimal objective value of the penalty function.

A.2.243 MSK_primalsensitivity()

```
MSKrescodee MSK_primalsensitivity (
    MSKtask_t      task,
    MSKint32t      numi,
    MSKCONST MSKint32t * subi,
    MSKCONST MSKmarke * marki,
    MSKint32t      numj,
    MSKCONST MSKint32t * subj,
    MSKCONST MSKmarke * markj,
    MSKrealt *      leftpricei,
    MSKrealt *      rightpricei,
    MSKrealt *      leftrangei,
    MSKrealt *      rightrangei,
    MSKrealt *      leftpricej,
    MSKrealt *      rightpricej,
    MSKrealt *      leftrangej,
    MSKrealt *      rightrangej);
```

Perform sensitivity analysis on bounds.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numi

Number of bounds on constraints to be analyzed. Length of **subi** and **marki**.

subi

Indexes of bounds on constraints to analyze.

marki

The value of **marki[i]** specifies for which bound (upper or lower) on constraint **subi[i]** sensitivity analysis should be performed.

numj

Number of bounds on variables to be analyzed. Length of **subj** and **markj**.

`subj`

Indexes of bounds on variables to analyze.

`markj`

The value of `markj[j]` specifies for which bound (upper or lower) on variable `subj[j]` sensitivity analysis should be performed.

`leftpricei`

`leftpricei[i]` is the left shadow price for the upper/lower bound (indicated by `marki[i]`) of the constraint with index `subi[i]`.

`rightpricei`

`rightpricei[i]` is the right shadow price for the upper/lower bound (indicated by `marki[i]`) of the constraint with index `subi[i]`.

`leftrangei`

`leftrangei[i]` is the left range for the upper/lower bound (indicated by `marki[i]`) of the constraint with index `subi[i]`.

`rightrangei`

`rightrangei[i]` is the right range for the upper/lower bound (indicated by `marki[i]`) of the constraint with index `subi[i]`.

`leftpricej`

`leftpricej[j]` is the left shadow price for the upper/lower bound (indicated by `marki[j]`) on variable `subj[j]`.

`rightpricej`

`rightpricej[j]` is the right shadow price for the upper/lower bound (indicated by `marki[j]`) on variable `subj[j]`.

`leftrangej`

`leftrangej[j]` is the left range for the upper/lower bound (indicated by `marki[j]`) on variable `subj[j]`.

`rightrangej`

`rightrangej[j]` is the right range for the upper/lower bound (indicated by `marki[j]`) on variable `subj[j]`.

Calculates sensitivity information for bounds on variables and constraints.

For details on sensitivity analysis and the definitions of *shadow price* and *linearity interval* see chapter 15.

The constraints for which sensitivity analysis is performed are given by the data structures:

- `subi` Index of constraint to analyze.
- `marki` Indicate for which bound of constraint `subi[i]` sensitivity analysis is performed. If `marki[i] = MSK_MARK_UP` the upper bound of constraint `subi[i]` is analyzed, and if `marki[i] = MSK_MARK_LO` the lower bound is analyzed. If `subi[i]` is an equality constraint, either `MSK_MARK_LO` or `MSK_MARK_UP` can be used to select the constraint for sensitivity analysis.

Consider the problem:

$$\begin{array}{llll} \text{minimize} & x_1 + x_2 & & \\ \text{subject to} & -1 \leq x_1 - x_2 \leq 1, & & \\ & x_1 = 0, & & \\ & x_1 \geq 0, x_2 \geq 0 & & \end{array}$$

Suppose that

- `numi = 1;`
- `subi = [0];`
- `marki = [MSK_MARK_UP]`

then

`leftpricei[0]`, `rightpricei[0]`, `leftrangei[0]` and `rightrangei[0]` will contain the sensitivity information for the upper bound on constraint 0 given by the expression:

$$x_1 - x_2 \leq 1$$

Similarly, the variables for which to perform sensitivity analysis are given by the structures:

- `subj` Index of variables to analyze.
- `markj` Indicate for which bound of variable `subi[j]` sensitivity analysis is performed. If `markj[j] = MSK_MARK_UP` the upper bound of constraint `subi[j]` is analyzed, and if `markj[j] = MSK_MARK_LO` the lower bound is analyzed. If `subi[j]` is an equality constraint, either `MSK_MARK_LO` or `MSK_MARK_UP` can be used to select the constraint for sensitivity analysis.

For an example, please see Section 15.5.

The type of sensitivity analysis to be performed (basis or optimal partition) is controlled by the parameter `MSK_IPAR_SENSITIVITY_TYPE`.

See also

- `MSK_dualsensitivity` Performs sensitivity analysis on objective coefficients.
- `MSK_sensitivityreport` Creates a sensitivity report.
- `MSK_IPAR_SENSITIVITY_TYPE` Controls which type of sensitivity analysis is to be performed.
- `MSK_IPAR_LOG_SENSITIVITY` Control logging in sensitivity analyzer.
- `MSK_IPAR_LOG_SENSITIVITY_OPT` Control logging in sensitivity analyzer.

A.2.244 MSK_printdata()

```

MSKrescodee MSK_printdata (
    MSKtask_t      task,
    MSKstreamtypee whichstream,
    MSKint32t      firsti,
    MSKint32t      lasti,
    MSKint32t      firstj,
    MSKint32t      lastj,
    MSKint32t      firstk,
    MSKint32t      lastk,
    MSKint32t      c,
    MSKint32t      qo,
    MSKint32t      a,
    MSKint32t      qc,
    MSKint32t      bc,
    MSKint32t      bx,
    MSKint32t      vartype,
    MSKint32t      cones);

```

Prints a part of the problem data to a stream.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

firsti

Index of first constraint for which data should be printed.

lasti

Index of last constraint plus 1 for which data should be printed.

firstj

Index of first variable for which data should be printed.

lastj

Index of last variable plus 1 for which data should be printed.

firstk

Index of first cone for which data should be printed.

lastk

Index of last cone plus 1 for which data should be printed.

c

If non-zero c is printed.

qo

If non-zero Q^o is printed.

a
If non-zero A is printed.

qc
If non-zero Q^k is printed for the relevant constraints.

bc
If non-zero the constraints bounds are printed.

bx
If non-zero the variable bounds are printed.

vartype
If non-zero the variable types are printed.

cones
If non-zero the conic data is printed.

Prints a part of the problem data to a stream. This function is normally used for debugging purposes only, e.g. to verify that the correct data has been inputted.

A.2.245 MSK_printparam()

```
MSKrescodee MSK_printparam (MSKtask_t task)
```

Prints the current parameter settings.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

Prints the current parameter settings to the message stream.

A.2.246 MSK_probtypetostr()

```
MSKrescodee MSK_probtypetostr (
    MSKtask_t      task,
    MSKproblemtypee probtype,
    char *         str);
```

Obtains a string containing the name of a problem type given.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

prodtype

Problem type.

str

String corresponding to the problem type key **prodtype**.

Obtains a string containing the name of a problem type given.

A.2.247 MSK_prostatostr()

```
MSKrescodee MSK_prostatostr (
    MSKtask_t    task,
    MSKprosta_e  prosta,
    char *       str);
```

Obtains a string containing the name of a problem status given.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

prosta

Problem status.

str

String corresponding to the status key **prosta**.

Obtains a string containing the name of a problem status given.

A.2.248 MSK_putacol()

```
MSKrescodee MSK_putacol (
    MSKtask_t      task,
    MSKint32t      j,
    MSKint32t      nzj,
    MSKCONST MSKint32t * subj,
    MSKCONST MSKrealt * valj);
```

Replaces all elements in one column of A.

Returns:

A response code indicating the status of the function call.

task
An optimization task.

j
Index of column in A .

nzj
Number of non-zeros in column j of A .

subj
Row indexes of non-zero values in column j of A .

valj
New non-zero values of column j in A .

Replaces all entries in column j of A . Assuming that there are no duplicate subscripts in **subj**, assignment is performed as follows:

$$A_{\text{subj}[k],j} = \text{valj}[k], \quad k = 0, \dots, \text{nzj} - 1$$

All other entries in column j are set to zero.

See also

- **MSK_putacolslice** Replaces all elements in several columns the linear constraint matrix by new values.
- **MSK_putacollist** Replaces all elements in several columns the linear constraint matrix by new values.
- **MSK.putarow** Replaces all elements in one row of A .
- **MSK.putaij** Changes a single value in the linear coefficient matrix.
- **MSK.putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.249 MSK_putacollist()

```
MSKrescode MSK_putacollist (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKCONST MSKint32t * ptrb,
    MSKCONST MSKint32t * ptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt * aval);
```

Replaces all elements in several columns the linear constraint matrix by new values.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of columns of A to replace.

sub

Indexes of columns that should be replaced. **sub** should not contain duplicate values.

ptrb

Array of pointers to the first element in the columns stored in **asub** and **aval**.

For an explanation of the meaning of **ptrb** see Section 5.13.3.2.

ptre

Array of pointers to the last element plus one in the columns stored in **asub** and **aval**.

For an explanation of the meaning of **ptre** see Section 5.13.3.2.

asub

asub contains the new variable indexes.

aval

Coefficient values. See (5.16) and Section 5.13.3.

Replaces all elements in a set of columns of A . The elements are replaced as follows

$$\begin{aligned} \text{for } i = 0, \dots, num - 1 \\ a_{\text{asub}[k], \text{sub}[i]} = \text{aval}[k], \quad k = \text{aptrb}[i], \dots, \text{aptre}[i] - 1. \end{aligned}$$

See also

- **MSK.putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.
- **MSK.putacollist64** Replaces all elements in several columns the linear constraint matrix by new values.

A.2.250 MSK_putacollist64()

```
MSKrescodee MSK_putacollist64 (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKCONST MSKint64t * ptrb,
    MSKCONST MSKint64t * ptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt * aval);
```

Replaces all elements in several columns the linear constraint matrix by new values.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of columns of A to replace.

sub

Indexes of columns that should be replaced. **sub** should not contain duplicate values.

ptrb

Array of pointers to the first element in the columns stored in **asub** and **aval**.

For an explanation of the meaning of **ptrb** see Section 5.13.3.2.

ptre

Array of pointers to the last element plus one in the columns stored in **asub** and **aval**.

For an explanation of the meaning of **ptre** see Section 5.13.3.2.

asub

asub contains the new variable indexes.

aval

Coefficient values. See (5.16) and Section 5.13.3.

Replaces all elements in a set of columns of A . The elements are replaced as follows

$$\text{for } i = 0, \dots, num - 1 \\ a_{\text{asub}[k], \text{sub}[i]} = \text{aval}[k], \quad k = \text{ptrb}[i], \dots, \text{ptre}[i] - 1.$$

See also

- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.251 MSK_putacolslice()

```
MSKrescodee MSK_putacolslice (
    MSKtask_t      task,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKint32t * ptrb,
    MSKCONST MSKint32t * ptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt *  aval);
```

Replaces all elements in several columns the linear constraint matrix by new values.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

First column in the slice.

last

Last column plus one in the slice.

ptrb

Array of pointers to the first element in the columns stored in **asub** and **aval**.

For an explanation of the meaning of **ptrb** see Section 5.13.3.2.

ptre

Array of pointers to the last element plus one in the columns stored in **asub** and **aval**.

For an explanation of the meaning of **ptre** see Section 5.13.3.2.

asub

asub contains the new variable indexes.

aval

Coefficient values. See (5.16) and Section 5.13.3.

Replaces all elements in a set of columns of A .

See also

- **MSK_putacolslice64** Replaces all elements in several columns the linear constraint matrix by new values.
- **MSK.putarowslice** Replaces all elements in several rows the linear constraint matrix by new values.
- **MSK.putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.252 MSK_putacolslice64()

```
MSKrescodee MSK_putacolslice64 (
    MSKtask_t      task,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKint64t * ptrb,
    MSKCONST MSKint64t * ptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt * aval);
```

Replaces all elements in several columns the linear constraint matrix by new values.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

First column in the slice.

last

Last column plus one in the slice.

ptrb

Array of pointers to the first element in the columns stored in **asub** and **aval**.

For an explanation of the meaning of **ptrb** see Section 5.13.3.2.

ptre

Array of pointers to the last element plus one in the columns stored in **asub** and **aval**.

For an explanation of the meaning of **ptre** see Section 5.13.3.2.

asub

asub contains the new variable indexes.

aval

Coefficient values. See (5.16) and Section 5.13.3.

Replaces all elements in a set of columns of A .

See also

- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.253 MSK_putaij()

```
MSKrescodee MSK_putaij (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t j,
    MSKrealt  aij);
```

Changes a single value in the linear coefficient matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index of the constraint in which the change should occur.

j

Index of the variable in which the change should occur.

aijNew coefficient for $a_{i,j}$.Changes a coefficient in A using the method

$$a_{ij} = \text{aij}.$$

See also

- **MSK.putarow** Replaces all elements in one row of A .
- **MSK.putacol** Replaces all elements in one column of A .
- **MSK.putaij** Changes a single value in the linear coefficient matrix.
- **MSK.putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.254 MSK.putaijlist()

```
MSKrescodee MSK.putaijlist (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * subi,
    MSKCONST MSKint32t * subj,
    MSKCONST MSKrealt * valij);
```

Changes one or more coefficients in the linear constraint matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of coefficients that should be changed.

subi

Constraint indexes in which the change should occur.

subj

Variable indexes in which the change should occur.

valijNew coefficient values for $a_{i,j}$.

Changes one or more coefficients in A using the method

$$a_{\text{subi}[k], \text{subj}[k]} = \text{valij}[k], \quad k = 0, \dots, \text{num} - 1.$$

Multiple elements are not allowed.

See also

- **MSK_putarow** Replaces all elements in one row of A .
- **MSK_putacol** Replaces all elements in one column of A .
- **MSK_putaij** Changes a single value in the linear coefficient matrix.
- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.255 MSK_putaijlist64()

```
MSKrescodee MSK_putaijlist64 (
    MSKtask_t      task,
    MSKint64t      num,
    MSKCONST MSKint32t * subi,
    MSKCONST MSKint32t * subj,
    MSKCONST MSKrealt * valij);
```

Changes one or more coefficients in the linear constraint matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of coefficients that should be changed.

subi

Constraint indexes in which the change should occur.

subj

Variable indexes in which the change should occur.

valij

New coefficient values for $a_{i,j}$.

Changes one or more coefficients in A using the method

$$a_{\text{subi}[k], \text{subj}[k]} = \text{valij}[k], \quad k = 0, \dots, \text{num} - 1.$$

See also

- **MSK_putarow** Replaces all elements in one row of A .
- **MSK_putacol** Replaces all elements in one column of A .
- **MSK_putaij** Changes a single value in the linear coefficient matrix.
- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.256 MSK_putarow()

```
MSKrescodee MSK_putarow (
    MSKtask_t      task,
    MSKint32t      i,
    MSKint32t      nzi,
    MSKCONST MSKint32t * subi,
    MSKCONST MSKrealt * vali);
```

Replaces all elements in one row of A .

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index of row in A .

nzi

Number of non-zeros in row i of A .

subi

Row indexes of non-zero values in row i of A .

vali

New non-zero values of row i in A .

Replaces all entries in row i of A . Assuming that there are no duplicate subscripts in **subi**, assignment is performed as follows:

$$A_{i, \text{subi}[k]} = \text{vali}[k], \quad k = 0, \dots, \text{nzi} - 1$$

All other entries in row i are set to zero.

See also

- **MSK_putarowslice** Replaces all elements in several rows the linear constraint matrix by new values.
- **MSK_putarowlist** Replaces all elements in several rows the linear constraint matrix by new values.

- **MSK_putacol** Replaces all elements in one column of A .
- **MSK_putaij** Changes a single value in the linear coefficient matrix.
- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.257 MSK_putarowlist()

```
MSKrescodee MSK_putarowlist (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKCONST MSKint32t * aptrb,
    MSKCONST MSKint32t * aptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt * aval);
```

Replaces all elements in several rows the linear constraint matrix by new values.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of rows of A to replace.

sub

Indexes of rows or columns that should be replaced. **sub** should not contain duplicate values.

aptrb

Array of pointers to the first element in the rows stored in **asub** and **aval**.

For an explanation of the meaning of **ptrb** see Section 5.13.3.2.

aptre

Array of pointers to the last element plus one in the rows stored in **asub** and **aval**.

For an explanation of the meaning of **ptre** see Section 5.13.3.2.

asub

asub contains the new variable indexes.

aval

Coefficient values. See (5.16) and Section 5.13.3.

Replaces all elements in a set of rows of A . The elements are replaced as follows

$$\begin{aligned} \text{for } i = 0, \dots, num - 1 \\ a_{\text{sub}[i], \text{asub}[k]} = \text{aval}[k], \quad k = \text{aptrb}[i], \dots, \text{aptre}[i] - 1. \end{aligned}$$

See also

- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.258 MSK_putarowlist64()

```
MSKrescodee MSK_putarowlist64 (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKCONST MSKint64t * ptrb,
    MSKCONST MSKint64t * ptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt * aval);
```

Replaces all elements in several rows the linear constraint matrix by new values.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of rows of A to replace.

sub

Indexes of rows or columns that should be replaced. **sub** should not contain duplicate values.

ptrb

Array of pointers to the first element in the rows stored in **asub** and **aval**.

For an explanation of the meaning of **ptrb** see Section 5.13.3.2.

ptre

Array of pointers to the last element plus one in the rows stored in **asub** and **aval**.

For an explanation of the meaning of **ptre** see Section 5.13.3.2.

asub

asub contains the new variable indexes.

aval

Coefficient values. See (5.16) and Section 5.13.3.

Replaces all elements in a set of rows of A . The elements are replaced as follows

$$\begin{aligned} &\text{for } i = \text{first}, \dots, \text{last} - 1 \\ &\quad a_{\text{sub}[i], \text{asub}[k]} = \text{aval}[k], \quad k = \text{aptrb}[i], \dots, \text{aptre}[i] - 1. \end{aligned}$$

See also

- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.259 MSK_putarowslice()

```

MSKrescodee MSK_putarowslice (
    MSKtask_t          task,
    MSKint32t          first,
    MSKint32t          last,
    MSKCONST MSKint32t * ptrb,
    MSKCONST MSKint32t * ptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt *  aval);

```

Replaces all elements in several rows the linear constraint matrix by new values.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

First row in the slice.

last

Last row plus one in the slice.

ptrb

Array of pointers to the first element in the rows stored in **asub** and **aval**.

For an explanation of the meaning of **ptrb** see Section 5.13.3.2.

ptre

Array of pointers to the last element plus one in the rows stored in **asub** and **aval**.

For an explanation of the meaning of **ptre** see Section 5.13.3.2.

asub

asub contains the new variable indexes.

aval

Coefficient values. See (5.16) and Section 5.13.3.

Replaces all elements in a set of rows of A . The elements are replaced as follows

$$\text{for } i = \text{first}, \dots, \text{last} - 1 \\ a_{\text{sub}[i], \text{asub}[k]} = \text{aval}[k], \quad k = \text{aptrb}[i], \dots, \text{aptre}[i] - 1.$$

See also

- **MSK_putarowslice64** Replaces all elements in several rows the linear constraint matrix by new values.
- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.260 MSK_putarowslice64()

```

MSKrescodee MSK_putarowslice64 (
    MSKtask_t      task,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKint64t * ptrb,
    MSKCONST MSKint64t * ptre,
    MSKCONST MSKint32t * asub,
    MSKCONST MSKrealt * aval);

```

Replaces all elements in several rows the linear constraint matrix by new values.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

First row in the slice.

last

Last row plus one in the slice.

ptrb

Array of pointers to the first element in the rows stored in **asub** and **aval**.

For an explanation of the meaning of **ptrb** see Section 5.13.3.2.

ptre

Array of pointers to the last element plus one in the rows stored in **asub** and **aval**.

For an explanation of the meaning of **ptre** see Section 5.13.3.2.

asub

asub contains the new variable indexes.

aval

Coefficient values. See (5.16) and Section 5.13.3.

Replaces all elements in a set of rows of A . The elements is replaced as follows

$$\text{for } i = \text{first}, \dots, \text{last} - 1 \\ a_{\text{sub}[i], \text{asub}[k]} = \text{aval}[k], \quad k = \text{aptrb}[i], \dots, \text{aptre}[i] - 1.$$

See also

- **MSK_putarowlist** Replaces all elements in several rows the linear constraint matrix by new values.
- **MSK_putarowlist64** Replaces all elements in several rows the linear constraint matrix by new values.
- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.

A.2.261 MSK_putbarablocktriplet()

```

MSKrescodee MSK_putbarablocktriplet (
    MSKtask_t      task,
    MSKint64t      num,
    MSKCONST MSKint32t * subi,
    MSKCONST MSKint32t * subj,
    MSKCONST MSKint32t * subk,
    MSKCONST MSKint32t * subl,
    MSKCONST MSKrealt * valijkl);

```

Inputs barA in block triplet form.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of elements in the block triplet form.

subi

Constraint index.

subj

Symmetric matrix variable index.

subk

Block row index.

subl

Block column index.

valijkl

The numerical value associated with the block triplet.

Inputs the \bar{A} in block triplet form.

A.2.262 MSK_putbaraij()

```

MSKrescodee MSK_putbaraij (
    MSKtask_t      task,
    MSKint32t      i,
    MSKint32t      j,
    MSKint64t      num,
    MSKCONST MSKint64t * sub,
    MSKCONST MSKrealt * weights);

```

Inputs an element of barA.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Row index of \bar{A} .

j

Column index of \bar{A} .

num

num is the number of terms in the wighted sum that forms \bar{A}_{ij} .

sub

See argument **weights** for an explanation.

weights

weights[k] times **sub[k]**'th term of E is added to \bar{A}_{ij} .

This function puts one element associated with \bar{X}_j in the \bar{A} matrix.

Each element in the \bar{A} matrix is a weighted sum of symmetric matrixes, i.e. \bar{A}_{ij} is a symmetric matrix with dimensions as \bar{X}_j . By default all elements in \bar{A} are 0, so only non-zero elements need be added.

Setting the same elements again will overwrite the earlier entry.

The symmetric matrixes themselves are defined separately using the funtion **MSK_appendsparsesymmat**.

A.2.263 MSK_putbarcblocktriplet()

```
MSKrescodee MSK_putbarcblocktriplet (
    MSKtask_t      task,
    MSKint64t      num,
    MSKCONST MSKint32t * subj,
    MSKCONST MSKint32t * subk,
    MSKCONST MSKint32t * subl,
    MSKCONST MSKrealt * valjkl);
```

Inputs barC in block triplet form.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of elements in the block triplet form.

subj
Symmetric matrix variable index.

subk
Block row index.

subl
Block column index.

valjkl
The numerical value associated with the block triplet.

Inputs the \bar{C} in block triplet form.

A.2.264 MSK_putbarcj()

```
MSKrescodee MSK_putbarcj (
    MSKtask_t      task,
    MSKint32t      j,
    MSKint64t      num,
    MSKCONST MSKint64t * sub,
    MSKCONST MSKrealt * weights);
```

Changes one element in `barc`.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the element in \bar{c} that should be changed.

num

The number elements appearing in the sum that forms \bar{c}_j .

sub

`sub` is list of indexes of those symmetric matrixes appearing in sum.

weights

The weights of the terms in the weighted sum that forms c_j .

This function puts one element associated with \bar{X}_j in the \bar{c} vector.

Each element in the \bar{c} vector is a weighted sum of symmetric matrixes, i.e. \bar{c}_j is a symmetric matrix with dimensions as \bar{X}_j . By default all elements in \bar{c} are 0, so only non-zero elements need be added.

Setting the same elements again will overwrite the earlier entry.

The symmetric matrixes themselves are defined separately using the funtion `MSK_appendsparsesymmat`.

A.2.265 MSK_putbarsj()

```
MSKrescodee MSK_putbarsj (
    MSKtask_t      task,
    MSKsoltypee     whichsol,
    MSKint32t       j,
    MSKCONST MSKrealt * barsj);
```

Sets the dual solution for a semidefinite variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

j

Index of the semidefinite variable.

barsj

Value of \bar{s}_j .

Sets the dual solution for a semidefinite variable.

A.2.266 MSK_putbarvarname()

```
MSKrescodee MSK_putbarvarname (
    MSKtask_t      task,
    MSKint32t       j,
    MSKCONST char * name);
```

Puts the name of a semidefinite variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable.

name

The variable name.

Puts the name of a semidefinite variable.

See also

- `MSK_getbarvarnamelen` Obtains the length of a name of a semidefinite variable.

A.2.267 `MSK_putbarxj()`

```
MSKrescodee MSK_putbarxj (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      j,
    MSKCONST MSKrealt * barxj);
```

Sets the primal solution for a semidefinite variable.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`whichsol`

Selects a solution.

`j`

Index of the semidefinite variable.

`barxj`

Value of \bar{X}_j .

Sets the primal solution for a semidefinite variable.

A.2.268 `MSK_putbound()`

```
MSKrescodee MSK_putbound (
    MSKtask_t      task,
    MSKaccmodee    accmode,
    MSKint32t      i,
    MSKboundkeye   bk,
    MSKrealt       bl,
    MSKrealt       bu);
```

Changes the bound for either one constraint or one variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

Defines whether the bound for a constraint or a variable is changed.

i

Index of the constraint or variable.

bk

New bound key.

bl

New lower bound.

bu

New upper bound.

Changes the bounds for either one constraint or one variable.

If the a bound value specified is numerically larger than **MSK_DPAR_DATA_TOL_BOUND_INF** it is considered infinite and the bound key is changed accordingly. If a bound value is numerically larger than **MSK_DPAR_DATA_TOL_BOUND_WRN**, a warning will be displayed, but the bound is inputted as specified.

See also

- **MSK_putboundlist** Changes the bounds of constraints or variables.

A.2.269 MSK_putboundlist()

```
MSKrescodee MSK_putboundlist (
    MSKtask_t      task,
    MSKaccmodee    accmode,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKCONST MSKboundkeye * bk,
    MSKCONST MSKrealt * bl,
    MSKCONST MSKrealt * bu);
```

Changes the bounds of constraints or variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

Defines whether bounds for constraints (**MSK_ACC_CON**) or variables (**MSK_ACC_VAR**) are changed.

num

Number of bounds that should be changed.

sub

Subscripts of the bounds that should be changed.

bk

Constraint or variable index **sub[t]** is assigned the bound key **bk[t]**.

bl

Constraint or variable index **sub[t]** is assigned the lower bound **bl[t]**.

bu

Constraint or variable index **sub[t]** is assigned the upper bound **bu[t]**.

Changes the bounds for either some constraints or variables. If multiple bound changes are specified for a constraint or a variable, only the last change takes effect.

See also

- **MSK_putbound** Changes the bound for either one constraint or one variable.
- **MSK_DPAR_DATA_TOL_BOUND_INF** Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_BOUND_WRN** Data tolerance threshold.

A.2.270 MSK_putboundslice()

```
MSKrescodee MSK_putboundslice (
    MSKtask_t      task,
    MSKaccmodee    con,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKboundkeye * bk,
    MSKCONST MSKrealt *   bl,
    MSKCONST MSKrealt *   bu);
```

Modifies bounds.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

con

Defines whether bounds for constraints (**MSK_ACC_CON**) or variables (**MSK_ACC_VAR**) are changed.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

bk

Bound keys.

bl

Values for lower bounds.

bu

Values for upper bounds.

Changes the bounds for a sequence of variables or constraints.

See also

- **MSK_putbound** Changes the bound for either one constraint or one variable.
- **MSK_DPAR_DATA_TOL_BOUND_INF** Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_BOUND_WRN** Data tolerance threshold.

A.2.271 MSK_putcallbackfunc()

```
MSKrescodee MSK_putcallbackfunc (
    MSKtask_t      task,
    MSKcallbackfunc func,
    MSKuserhandle_t handle);
```

Input the progress call-back function.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

func

A user-defined function which will be called occasionally from within the MOSEK optimizers. If the argument is a NULL pointer, then a previous inputted call-back function removed. The progress function has the type **MSKcallbackfunc**.

handle

A pointer to a user-defined data structure. Whenever the function **callbackfunc** is called, then **handle** is passed to the function.

The function is used to input a user-defined progress call-back function of type **MSKcallbackfunc**. The call-back function is called frequently during the optimization process.

See also

- **MSK_IPAR_LOG_SIM_FREQ** Controls simplex logging frequency.

A.2.272 MSK_putcfix()

```
MSKrescodee MSK_putcfix (
    MSKtask_t  task,
    MSKrealt   cfix);
```

Replaces the fixed term in the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

cfix

Fixed term in the objective.

Replaces the fixed term in the objective by a new one.

A.2.273 MSK_putcj()

```
MSKrescodee MSK_putcj (
    MSKtask_t  task,
    MSKint32t  j,
    MSKrealt   cj);
```

Modifies one linear coefficient in the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable for which c should be changed.

cj

New value of c_j .

Modifies one coefficient in the linear objective vector c , i.e.

$$c_j = cj.$$

See also

- **MSK_putclist** Modifies a part of the linear objective coefficients.
- **MSK_putcslice** Modifies a slice of the linear objective coefficients.

A.2.274 MSK_putclist()

```
MSKrescodee MSK_putclist (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * subj,
    MSKCONST MSKrealt * val);
```

Modifies a part of the linear objective coefficients.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of coefficients that should be changed.

subj

Index of variables for which c should be changed.

val

New numerical values for coefficients in c that should be modified.

Modifies elements in the linear term c in the objective using the principle

$$c_{\text{subj}[t]} = \text{val}[t], \quad t = 0, \dots, \text{num} - 1.$$

If a variable index is specified multiple times in **subj** only the last entry is used.

A.2.275 MSK_putconbound()

```
MSKrescodee MSK_putconbound (
    MSKtask_t      task,
    MSKint32t      i,
    MSKboundkeye   bk,
    MSKrealt       bl,
    MSKrealt       bu);
```

Changes the bound for one constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

<code>i</code>	Index of the constraint.
<code>bk</code>	New bound key.
<code>bl</code>	New lower bound.
<code>bu</code>	New upper bound.

Changes the bounds for one constraint.

If the a bound value specified is numerically larger than `MSK_DPAR_DATA_TOL_BOUND_INF` it is considered infinite and the bound key is changed accordingly. If a bound value is numerically larger than `MSK_DPAR_DATA_TOL_BOUND_WRN`, a warning will be displayed, but the bound is inputted as specified.

See also

- `MSK_putconboundslice` Changes the bounds for a slice of the constraints.

A.2.276 `MSK_putconboundlist()`

```
MSKrescodee MSK_putconboundlist (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKCONST MSKboundkeye * bkc,
    MSKCONST MSKrealt * blc,
    MSKCONST MSKrealt * buc);
```

Changes the bounds of a list of constraints.

Returns:

A response code indicating the status of the function call.

`task`
An optimization task.

`num`
Number of bounds that should be changed.

`sub`
List constraints indexes.

`bkc`
New bound keys.

blc

New lower bound values.

buc

New upper bound values.

Changes the bounds for a list of constraints. If multiple bound changes are specified for a constraint, then only the last change takes effect.

See also

- **MSK_putconbound** Changes the bound for one constraint.
- **MSK_putconboundslice** Changes the bounds for a slice of the constraints.
- **MSK_DPAR_DATA_TOL_BOUND_INF** Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_BOUND_WRN** Data tolerance threshold.

A.2.277 MSK_putconboundslice()

```
MSKrescodee MSK_putconboundslice (
    MSKtask_t          task,
    MSKint32t          first,
    MSKint32t          last,
    MSKCONST MSKboundkey * bk,
    MSKCONST MSKrealt *  bl,
    MSKCONST MSKrealt *  bu);
```

Changes the bounds for a slice of the constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

Index of the first constraint in the slice.

last

Index of the last constraint in the slice plus 1.

bk

New bound keys.

bl

New lower bounds.

bu

New upper bounds.

Changes the bounds for a slice of the constraints.

See also

- **MSK_putconbound** Changes the bound for one constraint.
- **MSK_putconboundlist** Changes the bounds of a list of constraints.

A.2.278 MSK_putcone()

```
MSKrescodee MSK_putcone (
    MSKtask_t      task,
    MSKint32t      k,
    MSKconetypee   conetype,
    MSKrealt       coneapar,
    MSKint32t      nummem,
    MSKCONST MSKint32t * submem);
```

Replaces a conic constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

k

Index of the cone.

conetype

Specifies the type of the cone.

coneapar

This argument is currently not used. Can be set to 0.0.

nummem

Number of member variables in the cone.

submem

Variable subscripts of the members in the cone.

Replaces a conic constraint.

A.2.279 MSK_putconename()

```
MSKrescodee MSK_putconename (
    MSKtask_t      task,
    MSKint32t      j,
    MSKCONST char * name);
```

Puts the name of a cone.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable.

name

The variable name.

Puts the name of a cone.

A.2.280 MSK_putconname()

```
MSKrescodee MSK_putconname (
    MSKtask_t      task,
    MSKint32t      i,
    MSKCONST char * name);
```

Puts the name of a constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index of the variable.

name

The variable name.

Puts the name of a constraint.

A.2.281 MSK_putcslice()

```
MSKrescodee MSK_putcslice (
    MSKtask_t      task,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKrealt * slice);
```

Modifies a slice of the linear objective coefficients.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

First element in the slice of c .

last

Last element plus 1 of the slice in c to be changed.

slice

New numerical values for coefficients in c that should be modified.

Modifies a slice in the linear term c in the objective using the principle

$$c_j = \text{slice}[j - \text{first}], \quad j = \text{first}, \dots, \text{last} - 1$$

A.2.282 MSK_putdllpath()

```
MSKrescodee MSK_putdllpath (
    MSKenv_t      env,
    MSKCONST char * dllpath);
```

Sets the path to the DLL/shared libraries that MOSEK is loading.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

dllpath

A path to where the MOSEK dynamic link/shared libraries are located. If **dllpath** is **NULL**, then MOSEK assumes that the operating system can locate the libraries.

Sets the path to the DLL/shared libraries that MOSEK are loading.

A.2.283 MSK_putdouparam()

```
MSKrescodee MSK_putdouparam (
    MSKtask_t  task,
    MSKdparame param,
    MSKrealt   parvalue);
```

Sets a double parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

param

Which parameter.

parvalue

Parameter value.

Sets the value of a double parameter.

A.2.284 MSK_putexitfunc()

```
MSKrescodee MSK_putexitfunc (
    MSKenv_t      env,
    MSKexitfunc   exitfunc,
    MSKuserhandle_t handle);
```

Inputs a user-defined exit function which is called in case of fatal errors.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

exitfunc

A user-defined exit function.

handle

A pointer to user-defined data structure which is passed to **exitfunc** when called.

In case MOSEK has a fatal error, then an exit function is called. The exit function should terminate MOSEK. In general it is not necessary to define an exit function.

A.2.285 MSK_putintparam()

```
MSKrescodee MSK_putintparam (
    MSKtask_t      task,
    MSKiparam     param,
    MSKint32t      parvalue);
```

Sets an integer parameter.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`param`

Which parameter.

`parvalue`

Parameter value.

Sets the value of an integer parameter.

A.2.286 `MSK_putkeepdlls()`

```
MSKrescodee MSK_putkeepdlls (
    MSKenv_t    env,
    MSKint32t   keepdlls);
```

Controls whether explicitly loaded DLLs should be kept.

Returns:

A response code indicating the status of the function call.

`env`

The MOSEK environment.

`keepdlls`

Controls whether explicitly loaded DLLs should be kept.

Controls whether explicitly loaded DLLs should be kept when they no longer are in use.

A.2.287 `MSK_putlicensecode()`

```
MSKrescodee MSK_putlicensecode (
    MSKenv_t    env,
    MSKCONST MSKint32t * code);
```

The purpose of this function is to input a runtime license code.

Returns:

A response code indicating the status of the function call.

`env`

The MOSEK environment.

code

A runtime license code.

The purpose of this function is to input a runtime license code.

A.2.288 MSK_putlicensedebug()

```
MSKrescodee MSK_putlicensedebug (  
    MSKenv_t    env,  
    MSKint32t   licdebug);
```

Enables debug information for the license system.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

licdebug

If this argument is non-zero, then MOSEK will print debug info regarding the license checkout.

If **licdebug** is non-zero, then MOSEK will print debug info regarding the license checkout.

A.2.289 MSK_putlicensepath()

```
MSKrescodee MSK_putlicensepath (  
    MSKenv_t    env,  
    MSKCONST char * licensepath);
```

Set the path to the license file.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

licensepath

A path specifying where to search for the license.

Set the path to the license file.

A.2.290 MSK_putlicensewait()

```
MSKrescodee MSK_putlicensewait (
    MSKenv_t   env,
    MSKint32t  licwait);
```

Control whether mosek should wait for an available license if no license is available.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

licwait

If this argument is non-zero, then MOSEK will wait for a license if no license is available. Moreover, `licwait-1` is the number of milliseconds to wait between each check for an available license.

If `licwait` is non-zero, then MOSEK will wait for a license if no license is available. Moreover, `licwait-1` is the number of milliseconds to wait between each check for an available license.

A.2.291 MSK_putmaxnumanz()

```
MSKrescodee MSK_putmaxnumanz (
    MSKtask_t  task,
    MSKint64t  maxnumanz);
```

The function changes the size of the preallocated storage for linear coefficients.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumanz

New size of the storage reserved for storing A .

MOSEK stores only the non-zero elements in A . Therefore, MOSEK cannot predict how much storage is required to store A . Using this function it is possible to specify the number of non-zeros to preallocate for storing A .

If the number of non-zeros in the problem is known, it is a good idea to set `maxnumanz` slightly larger than this number, otherwise a rough estimate can be used. In general, if A is inputted in many small chunks, setting this value may speed up the data input phase.

It is not mandatory to call this function, since MOSEK will reallocate internal structures whenever it is necessary.

See also

- **MSK_IINF_STO_NUM_A_REALLOC** Number of times the storage for storing the linear coefficient matrix has been changed.

A.2.292 MSK_putmaxnumbarvar()

```
MSKrescodee MSK_putmaxnumbarvar (
    MSKtask_t task,
    MSKint32t maxnumbarvar);
```

Sets the number of preallocated symmetric matrix variables in the optimization task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumbarvar

The maximum number of semidefinite variables.

Sets the number of preallocated symmetric matrix variables in the optimization task. When this number of variables is reached MOSEK will automatically allocate more space for variables.

It is not mandatory to call this function, since its only function is to give a hint of the amount of data to preallocate for efficiency reasons.

Please note that **maxnumbarvar** must be larger than the current number of variables in the task.

A.2.293 MSK_putmaxnumcon()

```
MSKrescodee MSK_putmaxnumcon (
    MSKtask_t task,
    MSKint32t maxnumcon);
```

Sets the number of preallocated constraints in the optimization task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumcon

Number of preallocated constraints in the optimization task.

Sets the number of preallocated constraints in the optimization task. When this number of constraints is reached MOSEK will automatically allocate more space for constraints.

It is never mandatory to call this function, since MOSEK will reallocate any internal structures whenever it is required.

Please note that `maxnumcon` must be larger than the current number of constraints in the task.

A.2.294 `MSK_putmaxnumcone()`

```
MSKrescodee MSK_putmaxnumcone (
    MSKtask_t  task,
    MSKint32t  maxnumcone);
```

Sets the number of preallocated conic constraints in the optimization task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumcone

Number of preallocated conic constraints in the optimization task.

Sets the number of preallocated conic constraints in the optimization task. When this number of conic constraints is reached MOSEK will automatically allocate more space for conic constraints.

It is never mandatory to call this function, since MOSEK will reallocate any internal structures whenever it is required.

Please note that `maxnumcon` must be larger than the current number of constraints in the task.

A.2.295 `MSK_putmaxnumqnz()`

```
MSKrescodee MSK_putmaxnumqnz (
    MSKtask_t  task,
    MSKint64t  maxnumqnz);
```

Changes the size of the preallocated storage for quadratic terms.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumqnz

Number of non-zero elements preallocated in quadratic coefficient matrixes.

MOSEK stores only the non-zero elements in Q . Therefore, MOSEK cannot predict how much storage is required to store Q . Using this function it is possible to specify the number non-zeros to preallocate for storing Q (both objective and constraints).

It may be advantageous to reserve more non-zeros for Q than actually needed since it may improve the internal efficiency of MOSEK, however, it is never worthwhile to specify more than the double of the anticipated number of non-zeros in Q .

It is never mandatory to call this function, since its only function is to give a hint of the amount of data to preallocate for efficiency reasons.

A.2.296 MSK_putmaxnumvar()

```
MSKrescodee MSK_putmaxnumvar (
    MSKtask_t   task,
    MSKint32t   maxnumvar);
```

Sets the number of preallocated variables in the optimization task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumvar

Number of preallocated variables in the optimization task.

Sets the number of preallocated variables in the optimization task. When this number of variables is reached MOSEK will automatically allocate more space for variables.

It is never mandatory to call this function, since its only function is to give a hint of the amount of data to preallocate for efficiency reasons.

Please note that **maxnumvar** must be larger than the current number of variables in the task.

A.2.297 MSK_putnadouparam()

```
MSKrescodee MSK_putnadouparam (
    MSKtask_t   task,
    MSKCONST char * paramname,
    MSKrealt     parvalue);
```

Sets a double parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

paramname

Name of a parameter.

parvalue

Parameter value.

Sets the value of a named double parameter.

A.2.298 MSK_putnaintparam()

```
MSKrescodee MSK_putnaintparam (
    MSKtask_t      task,
    MSKCONST char * paramname,
    MSKint32t      parvalue);
```

Sets an integer parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

paramname

Name of a parameter.

parvalue

Parameter value.

Sets the value of a named integer parameter.

A.2.299 MSK_putnastrparam()

```
MSKrescodee MSK_putnastrparam (
    MSKtask_t      task,
    MSKCONST char * paramname,
    MSKCONST char * parvalue);
```

Sets a string parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

paramname

Name of a parameter.

parvalue

Parameter value.

Sets the value of a named string parameter.

A.2.300 MSK_putnlfunc()

```
MSKrescodee MSK_putnlfunc (
    MSKtask_t      task,
    MSKuserhandle_t nlhandle,
    MSKnlgetspfunc nlgetsp,
    MSKnlgetvafunc nlgetva);
```

Inputs nonlinear function information.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

nlhandle

A pointer to a user-defined data structure. It is passed to the functions **nlgetsp** and **nlgetva** whenever those two functions called.

nlgetsp

A user-defined function which provide information about the structure of the nonlinear functions in the optimization problem.

nlgetva

A user-defined function which is used to evaluate the nonlinear function in the optimization problem at a given point.

This function is used to communicate the nonlinear function information to MOSEK.

A.2.301 MSK_putobjname()

```
MSKrescodee MSK_putobjname (
```

```
MSKtask_t      task,
MSKCONST char * objname);
```

Assigns a new name to the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

objname

Name of the objective.

Assigns the name given by **objname** to the objective function.

A.2.302 MSK_putobjsense()

```
MSKrescodee MSK_putobjsense (
    MSKtask_t      task,
    MSKobjsensee   sense);
```

Sets the objective sense.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

sense

The objective sense of the task. The values **MSK_OBJECTIVE_SENSE_MAXIMIZE** and **MSK_OBJECTIVE_SENSE_MINIMIZE** means that the the problem is maximized or minimized respectively.

Sets the objective sense of the task.

See also

- **MSK_getobjsense** Gets the objective sense.

A.2.303 MSK_putparam()

```
MSKrescodee MSK_putparam (
    MSKtask_t      task,
    MSKCONST char * parname,
    MSKCONST char * parvalue);
```

Modifies the value of parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

parname

Parameter name.

parvalue

Parameter value.

Checks if a **parname** is valid parameter name. If it is, the parameter is assigned the value specified by **parvalue**.

A.2.304 MSK_putqcon()

```
MSKrescode MSK_putqcon (
    MSKtask_t      task,
    MSKint32t      numqcnz,
    MSKCONST MSKint32t * qcsubk,
    MSKCONST MSKint32t * qcsubi,
    MSKCONST MSKint32t * qcsubj,
    MSKCONST MSKrealt * qcval);
```

Replaces all quadratic terms in constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numqcnz

Number of quadratic terms. See (5.15).

qcsubk

k subscripts for q_{ij}^k . See (5.15).

qcsubi

i subscripts for q_{ij}^k . See (5.15).

qcsubj

j subscripts for q_{ij}^k . See (5.15).

qcval

Numerical value for q_{ij}^k .

Replaces all quadratic entries in the constraints. Consider constraints on the form:

$$l_k^c \leq \frac{1}{2} \sum_{i=0}^{numvar-1} \sum_{j=0}^{numvar-1} q_{ij}^k x_i x_j + \sum_{j=0}^{numvar-1} a_{kj} x_j \leq u_k^c, \quad k = 0, \dots, m-1.$$

The function assigns values to q such that:

$$q_{qcsubi[t], qcsobj[t]}^{qcsubk[t]} = qcval[t], \quad t = 0, \dots, numqcnz - 1.$$

and

$$q_{qcsobj[t], qcsubi[t]}^{qcsubk[t]} = qcval[t], \quad t = 0, \dots, numqcnz - 1.$$

Values not assigned are set to zero.

Please note that duplicate entries are added together.

See also

- **MSK_putqconk** Replaces all quadratic terms in a single constraint.
- **MSK_putmaxnumqnz** Changes the size of the preallocated storage for quadratic terms.

A.2.305 MSK_putqconk()

```
MSKrescodee MSK_putqconk (
    MSKtask_t      task,
    MSKint32t      k,
    MSKint32t      numqcnz,
    MSKCONST MSKint32t * qcsubi,
    MSKCONST MSKint32t * qcsobj,
    MSKCONST MSKrealt * qcval);
```

Replaces all quadratic terms in a single constraint.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

k

The constraint in which the new Q elements are inserted.

numqcnz

Number of quadratic terms. See (5.15).

qcsubi

i subscripts for q_{ij}^k . See (5.15).

qcsubj j subscripts for q_{ij}^k . See (5.15).**qcval**Numerical value for q_{ij}^k .Replaces all the quadratic entries in one constraint k of the form:

$$l_k^c \leq \frac{1}{2} \sum_{i=0}^{numvar-1} \sum_{j=0}^{numvar-1} q_{ij}^k x_i x_j + \sum_{j=0}^{numvar-1} a_{kj} x_j \leq u_k^c.$$

It is assumed that Q^k is symmetric, i.e. $q_{ij}^k = q_{ji}^k$, and therefore, only the values of q_{ij}^k for which $i \geq j$ should be inputted to MOSEK. To be precise, MOSEK uses the following procedure

1. $Q^k = 0$
2. for $t = 0$ to $numqonz - 1$
3. $q_{qcsubi[t], qcsubj[t]}^k = q_{qcsubi[t], qcsubj[t]}^k + qcval[t]$
3. $q_{qcsubj[t], qcsubi[t]}^k = q_{qcsubj[t], qcsubi[t]}^k + qcval[t]$

Please note that:

- For large problems it is essential for the efficiency that the function **MSK.putmaxnumqnz** is employed to specify an appropriate **maxnumqnz**.
- Only the lower triangular part should be specified because Q^k is symmetric. Specifying values for q_{ij}^k where $i < j$ will result in an error.
- Only non-zero elements should be specified.
- The order in which the non-zero elements are specified is insignificant.
- Duplicate elements are added together. Hence, it is recommended not to specify the same element multiple times in **qosubi**, **qosubj**, and **qoval**.

For a code example see Section 5.5.2.

See also

- **MSK.putqcon** Replaces all quadratic terms in constraints.
- **MSK.putmaxnumqnz** Changes the size of the preallocated storage for quadratic terms.

A.2.306 MSK.putqobj()

```
MSKrescodee MSK_putqobj (
    MSKtask_t      task,
    MSKint32t      numqonz,
    MSKCONST MSKint32t * qosubi,
    MSKCONST MSKint32t * qosubj,
    MSKCONST MSKrealt * qoval);
```

Replaces all quadratic terms in the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

numqonz

Number of non-zero elements in Q^o .

qosubi

i subscript for q_{ij}^o .

qosubj

j subscript for q_{ij}^o .

qoval

Numerical value for q_{ij}^o .

Replaces all the quadratic terms in the objective

$$\frac{1}{2} \sum_{i=0}^{numvar-1} \sum_{j=0}^{numvar-1} q_{ij}^o x_i x_j + \sum_{j=0}^{numvar-1} c_j x_j + c^f.$$

It is assumed that Q^o is symmetric, i.e. $q_{ij}^o = q_{ji}^o$, and therefore, only the values of q_{ij}^o for which $i \geq j$ should be specified. To be precise, MOSEK uses the following procedure

1. $Q^o = 0$
2. for $t = 0$ to $numqonz - 1$
3. $q_{qosubi[t], qosubj[t]}^o = q_{qosubi[t], qosubj[t]}^o + qoval[t]$
3. $q_{qosubj[t], qosubi[t]}^o = q_{qosubj[t], qosubi[t]}^o + qoval[t]$

Please note that:

- Only the lower triangular part should be specified because Q^o is symmetric. Specifying values for q_{ij}^o where $i < j$ will result in an error.
- Only non-zero elements should be specified.
- The order in which the non-zero elements are specified is insignificant.
- Duplicate entries are added to together.

For a code example see Section 5.5.1.

A.2.307 MSK_putqobjij()

```
MSKrescodee MSK_putqobjij (
    MSKtask_t task,
    MSKint32t i,
    MSKint32t j,
    MSKrealt qoij);
```

Replaces one coefficient in the quadratic term in the objective.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Row index for the coefficient to be replaced.

j

Column index for the coefficient to be replaced.

qoij

The new value for q_{ij}^o .

Replaces one coefficient in the quadratic term in the objective. The function performs the assignment

$$q_{ij}^o = \text{qoij}.$$

Only the elements in the lower triangular part are accepted. Setting q_{ij} with $j > i$ will cause an error.

Please note that replacing all quadratic element, one at a time, is more computationally expensive than replacing all elements at once. Use **MSK.putqobj** instead whenever possible.

A.2.308 MSK_putresponsefunc()

```
MSKrescodee MSK_putresponsefunc (
    MSKtask_t      task,
    MSKresponsefunc responsefunc,
    MSKuserhandle_t handle);
```

Inputs a user-defined error call-back function.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

responsefunc

A user-defined response handling function.

handle

A user-defined data structure that is passed to the function **responsefunc** whenever it is called.

Inputs a user-defined error call-back which is called when an error or warning occurs.

A.2.309 MSK_putskc()

```
MSKrescodee MSK_putskc (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST MSKstakeye * skc);
```

Sets the status keys for the constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

skc

Status keys for the constraints.

Sets the status keys for the constraints.

See also

- **MSK_putskcslice** Sets the status keys for the constraints.

A.2.310 MSK_putskcslice()

```
MSKrescodee MSK_putskcslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKstakeye * skc);
```

Sets the status keys for the constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

skc

Status keys for the constraints.

Sets the status keys for the constraints.

See also

- **MSK_putskc** Sets the status keys for the constraints.

A.2.311 MSK_putskx()

```
MSKrescodee MSK_putskx (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST MSKstakeye * skx);
```

Sets the status keys for the scalar variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

skx

Status keys for the variables.

Sets the status keys for the scalar variables.

See also

- **MSK_putskxslice** Sets the status keys for the variables.

A.2.312 MSK_putskxslice()

```
MSKrescodee MSK_putskxslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKstakeye * skx);
```

Sets the status keys for the variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

skx

Status keys for the variables.

Sets the status keys for the variables.

A.2.313 MSK_putslc()

```
MSKrescodee MSK_putslc (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST MSKrealt * slc);
```

Sets the slc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

slc

The s_l^c vector.

Sets the s_l^c vector for a solution.

See also

- **MSK_putslcslice** Sets a slice of the slc vector for a solution.

A.2.314 MSK_putslicslice()

```
MSKrescodee MSK_putslicslice (
    MSKtask_t      task,
    MSKsoltypee     whichsol,
    MSKint32t       first,
    MSKint32t       last,
    MSKCONST MSKrealt * slc);
```

Sets a slice of the slc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

slc

Dual variables corresponding to the lower bounds on the constraints (s_l^c).

Sets a slice of the s_l^c vector for a solution.

See also

- **MSK_putslic** Sets the slc vector for a solution.

A.2.315 MSK_putslix()

```
MSKrescodee MSK_putslix (
    MSKtask_t      task,
    MSKsoltypee     whichsol,
    MSKCONST MSKrealt * slx);
```

Sets the slx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

slx

The s_l^x vector.

Sets the s_l^x vector for a solution.

See also

- **MSK_putslx** Sets the slx vector for a solution.

A.2.316 MSK_putslxslice()

```
MSKrescodee MSK_putslxslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKrealt * slx);
```

Sets a slice of the slx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

slx

Dual variables corresponding to the lower bounds on the variables (s_l^x).

Sets a slice of the s_l^x vector for a solution.

See also

- **MSK_putslx** Sets the slx vector for a solution.

A.2.317 MSK_putsnx()

```
MSKrescodee MSK_putsnx (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST MSKrealt *  sux);
```

Sets the snx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

sux

The s_n^x vector.

Sets the s_n^x vector for a solution.

See also

- **MSK_putsnxslice** Sets a slice of the snx vector for a solution.

A.2.318 MSK_putsnxslice()

```
MSKrescodee MSK_putsnxslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKrealt *  snx);
```

Sets a slice of the snx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

snx

Dual variables corresponding to the conic constraints on the variables (s_n^x).

Sets a slice of the s_n^x vector for a solution.

See also

- **MSK_putsnx** Sets the snx vector for a solution.

A.2.319 MSK_putsolution()

```
MSKrescodee MSK_putsolution (
    MSKtask_t          task,
    MSKsoltypee        whichsol,
    MSKCONST MSKstakeye * skc,
    MSKCONST MSKstakeye * skx,
    MSKCONST MSKstakeye * skn,
    MSKCONST MSKrealt * xc,
    MSKCONST MSKrealt * xx,
    MSKCONST MSKrealt * y,
    MSKCONST MSKrealt * slc,
    MSKCONST MSKrealt * suc,
    MSKCONST MSKrealt * slx,
    MSKCONST MSKrealt * sux,
    MSKCONST MSKrealt * snx);
```

Inserts a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

skc

Status keys for the constraints.

skx

Status keys for the variables.

skn

Status keys for the conic constraints.

xc

Primal constraint solution.

xx
Primal variable solution (x).

y
Vector of dual variables corresponding to the constraints.

slc
Dual variables corresponding to the lower bounds on the constraints (s_l^c).

suc
Dual variables corresponding to the upper bounds on the constraints (s_u^c).

slx
Dual variables corresponding to the lower bounds on the variables (s_l^x).

sux
Dual variables corresponding to the upper bounds on the variables (appears as s_u^x).

snx
Dual variables corresponding to the conic constraints on the variables (s_n^x).

Inserts a solution into the task.

A.2.320 MSK_putsolutioni()

```
MSKrescodee MSK_putsolutioni (
    MSKtask_t    task,
    MSKaccmodee  accmode,
    MSKint32t    i,
    MSKsoltypee  whichsol,
    MSKstakeye   sk,
    MSKrealt     x,
    MSKrealt     sl,
    MSKrealt     su,
    MSKrealt     sn);
```

Sets the primal and dual solution information for a single constraint or variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

accmode

If set to **MSK_ACC_CON** the solution information for a constraint is modified. Otherwise for a variable.

i

Index of the constraint or variable.

whichsol

Selects a solution.

sk

Status key of the constraint or variable.

x

Solution value of the primal constraint or variable.

sl

Solution value of the dual variable associated with the lower bound.

su

Solution value of the dual variable associated with the upper bound.

sn

Solution value of the dual variable associated with the cone constraint.

Sets the primal and dual solution information for a single constraint or variable.

A.2.321 MSK_putsolutionyi()

```
MSKrescodee MSK_putsolutionyi (
    MSKtask_t    task,
    MSKint32t    i,
    MSKsoltypee  whichsol,
    MSKrealt     y);
```

Inputs the dual variable of a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

i

Index of the dual variable.

whichsol

Selects a solution.

y

Solution value of the dual variable.

Inputs the dual variable of a solution.

See also

- **MSK_putsolutioni** Sets the primal and dual solution information for a single constraint or variable.

A.2.322 MSK_putstrparam()

```
MSKrescodee MSK_putstrparam (
    MSKtask_t      task,
    MSKsparame     param,
    MSKCONST char * parvalue);
```

Sets a string parameter.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

param

Which parameter.

parvalue

Parameter value.

Sets the value of a string parameter.

A.2.323 MSK_putsuc()

```
MSKrescodee MSK_putsuc (
    MSKtask_t      task,
    MSKsoltypee     whichsol,
    MSKCONST MSKrealt * suc);
```

Sets the suc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

suc

The s_u^c vector.

Sets the s_u^c vector for a solution.

See also

- **MSK_putsucslice** Sets a slice of the suc vector for a solution.

A.2.324 MSK_putsucslice()

```
MSKrescodee MSK_putsucslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKrealt * suc);
```

Sets a slice of the suc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

suc

Dual variables corresponding to the upper bounds on the constraints (s_u^c).

Sets a slice of the s_u^c vector for a solution.

See also

- **MSK_putsuc** Sets the suc vector for a solution.

A.2.325 MSK_putsux()

```
MSKrescodee MSK_putsux (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST MSKrealt * sux);
```

Sets the sux vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

suxThe s_u^x vector.Sets the s_u^x vector for a solution.

See also

- **MSK_putsuxslice** Sets a slice of the sux vector for a solution.

A.2.326 MSK_putsuxslice()

```
MSKrescodee MSK_putsuxslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKrealt * sux);
```

Sets a slice of the sux vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

suxDual variables corresponding to the upper bounds on the variables (appears as s_u^x).Sets a slice of the s_u^x vector for a solution.

See also

- **MSK_putsux** Sets the sux vector for a solution.

A.2.327 MSK_puttaskname()

```
MSKrescodee MSK_puttaskname (  
    MSKtask_t      task,  
    MSKCONST char * taskname);
```

Assigns a new name to the task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

taskname

Name assigned to the task.

Assigns the name **taskname** to the task.

A.2.328 MSK_putvarbound()

```
MSKrescodee MSK_putvarbound (  
    MSKtask_t      task,  
    MSKint32t      j,  
    MSKboundkeye   bk,  
    MSKrealt       bl,  
    MSKrealt       bu);
```

Changes the bound for one variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable.

bk

New bound key.

bl

New lower bound.

bu

New upper bound.

Changes the bounds for one variable.

If the a bound value specified is numerically larger than `MSK_DPAR_DATA_TOL_BOUND_INF` it is considered infinite and the bound key is changed accordingly. If a bound value is numerically larger than `MSK_DPAR_DATA_TOL_BOUND_WRN`, a warning will be displayed, but the bound is inputted as specified.

See also

- `MSK_putvarboundslice` Changes the bounds for a slice of the variables.

A.2.329 `MSK_putvarboundlist()`

```
MSKrescodee MSK_putvarboundlist (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * sub,
    MSKCONST MSKboundkeye * bxx,
    MSKCONST MSKrealt * blx,
    MSKCONST MSKrealt * bux);
```

Changes the bounds of a list of variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of bounds that should be changed.

sub

List of variable indexes.

bxx

New bound keys.

blx

New lower bound values.

bux

New upper bound values.

Changes the bounds for one or more variables. If multiple bound changes are specified for a variable, then only the last change takes effect.

See also

- `MSK_putvarbound` Changes the bound for one variable.
- `MSK_putvarboundslice` Changes the bounds for a slice of the variables.
- `MSK_DPAR_DATA_TOL_BOUND_INF` Data tolerance threshold.
- `MSK_DPAR_DATA_TOL_BOUND_WRN` Data tolerance threshold.

A.2.330 MSK_putvarboundslice()

```

MSKrescodee MSK_putvarboundslice (
    MSKtask_t      task,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKboundkeye * bk,
    MSKCONST MSKrealt *   bl,
    MSKCONST MSKrealt *   bu);

```

Changes the bounds for a slice of the variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

first

Index of the first variable in the slice.

last

Index of the last variable in the slice plus 1.

bk

New bound keys.

bl

New lower bounds.

bu

New upper bounds.

Changes the bounds for a slice of the variables.

See also

- **MSK_putconbound** Changes the bound for one constraint.

A.2.331 MSK_putvarbranchorder()

```

MSKrescodee MSK_putvarbranchorder (
    MSKtask_t task,
    MSKint32t j,
    MSKint32t priority,
    int       direction);

```

Assigns a branching priority and direction to a variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable.

priority

The branching priority that should be assigned to variable j .

direction

Specifies the preferred branching direction for variable j .

The purpose of the function is to assign a branching priority and direction. The higher priority that is assigned to an integer variable the earlier the mixed integer optimizer will branch on the variable. The branching direction controls if the optimizer branches up or down on the variable.

A.2.332 MSK_putvarname()

```
MSKrescodee MSK_putvarname (
    MSKtask_t      task,
    MSKint32t      j,
    MSKCONST char * name);
```

Puts the name of a variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable.

name

The variable name.

Puts the name of a variable.

A.2.333 MSK_putvartype()

```
MSKrescodee MSK_putvartype (
    MSKtask_t      task,
    MSKint32t      j,
    MSKvariabletype vartype);
```

Sets the variable type of one variable.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

j

Index of the variable.

vartype

The new variable type.

Sets the variable type of one variable.

See also

- **MSK_putvartypelist** Sets the variable type for one or more variables.

A.2.334 MSK_putvartypelist()

```
MSKrescodee MSK_putvartypelist (
    MSKtask_t          task,
    MSKint32t          num,
    MSKCONST MSKint32t * subj,
    MSKCONST MSKvariabletypee * vartype);
```

Sets the variable type for one or more variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of variables for which the variable type should be set.

subj

A list of variable indexes for which the variable type should be changed.

vartype

A list of variable types that should be assigned to the variables specified by **subj**. See section **MSKvariabletypee** for the possible values of **vartype**.

Sets the variable type for one or more variables, i.e. variable number **subj[k]** is assigned the variable type **vartype[k]**.

If the same index is specified multiple times in **subj** only the last entry takes effect.

See also

- **MSK_putvartype** Sets the variable type of one variable.

A.2.335 MSK_putxc()

```
MSKrescodee MSK_putxc (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKrealt *   xc);
```

Sets the xc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

xc

The x^c vector.

Sets the x^c vector for a solution.

See also

- **MSK_putxcslice** Sets a slice of the xc vector for a solution.

A.2.336 MSK_putxcslice()

```
MSKrescodee MSK_putxcslice (
    MSKtask_t    task,
    MSKsoltypee  whichsol,
    MSKint32t    first,
    MSKint32t    last,
    MSKCONST MSKrealt * xc);
```

Sets a slice of the xc vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

xc

Primal constraint solution.

Sets a slice of the x^c vector for a solution.

See also

- **MSK_putxc** Sets the xc vector for a solution.

A.2.337 MSK_putxx()

```
MSKrescodee MSK_putxx (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST MSKrealt * xx);
```

Sets the xx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

xx

The x^x vector.

Sets the x^x vector for a solution.

See also

- **MSK_putxxslice** Obtains a slice of the xx vector for a solution.

A.2.338 MSK_putxxslice()

```
MSKrescodee MSK_putxxslice (
    MSKtask_t      task,
    MSKsoltypee     whichsol,
    MSKint32t       first,
    MSKint32t       last,
    MSKCONST MSKrealt * xx);
```

Obtains a slice of the xx vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

xx

Primal variable solution (x).

Obtains a slice of the x^x vector for a solution.

See also

- **MSK_putxx** Sets the xx vector for a solution.

A.2.339 MSK_puty()

```
MSKrescodee MSK_puty (
    MSKtask_t      task,
    MSKsoltypee     whichsol,
    MSKCONST MSKrealt * y);
```

Sets the y vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

y

The y vector.

Sets the y vector for a solution.

See also

- **MSK_putyslice** Sets a slice of the y vector for a solution.

A.2.340 MSK_putyslice()

```
MSKrescodee MSK_putyslice (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKint32t      first,
    MSKint32t      last,
    MSKCONST MSKrealt * y);
```

Sets a slice of the y vector for a solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

first

First index in the sequence.

last

Last index plus 1 in the sequence.

y

Vector of dual variables corresponding to the constraints.

Sets a slice of the y vector for a solution.

See also

- **MSK_puty** Sets the y vector for a solution.

A.2.341 MSK_readbranchpriorities()

```
MSKrescodee MSK_readbranchpriorities (
    MSKtask_t      task,
    MSKCONST char * filename);
```

Reads branching priority data from a file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

filename

Data is read from the file **filename**.

Reads branching priority data from a file.

See also

- **MSK_writebranchpriorities** Writes branching priority data to a file.

A.2.342 MSK_readdata()

```
MSKrescodee MSK_readdata (
    MSKtask_t      task,
    MSKCONST char * filename);
```

Reads problem data from a file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

filename

Data is read from the file **filename** if it is a nonempty string. Otherwise data is read from the file specified by **MSK_SPAR_DATA_FILE_NAME**.

Reads an optimization problem and associated data from a file.

The data file format is determined by the **MSK_IPAR_READ_DATA_FORMAT** parameter. By default the parameter has the value **MSK_DATA_FORMAT_EXTENSION** indicating that the extension of the input file should determine the file type, where the extension is interpreted as follows:

- “.lp” and “.lp.gz” are interpreted as an LP file and a compressed LP file respectively.

- ".opf" and ".opf.gz" are interpreted as an OPF file and a compressed OPF file respectively.
- ".mps" and ".mps.gz" are interpreted as an MPS file and a compressed MPS file respectively.
- ".task" and ".task.gz" are interpreted as an task file and a compressed task file respectively.

See also

- **MSK_writedata** Writes problem data to a file.
- **MSK_IPAR_READ_DATA_FORMAT** Format of the data file to be read.

A.2.343 MSK_readdataautoformat()

```
MSKrescodee MSK_readdataautoformat (
    MSKtask_t      task,
    MSKCONST char * filename);
```

Reads problem data from a file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

filename

Data is read from the file **filename**.

Reads an optimization problem and associated data from a file.

See also

- **MSK_IPAR_READ_DATA_FORMAT** Format of the data file to be read.

A.2.344 MSK_readdataformat()

```
MSKrescodee MSK_readdataformat (
    MSKtask_t      task,
    MSKCONST char * filename,
    int            format,
    int            compress);
```

Reads problem data from a file.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`filename`

Data is read from the file `filename`.

`format`

File data format.

`compress`

File compression type.

Reads an optimization problem and associated data from a file.

See also

- `MSK_IPAR_READ_DATA_FORMAT` Format of the data file to be read.

A.2.345 `MSK_readparamfile()`

```
MSKrescodee MSK_readparamfile (MSKtask_t task)
```

Reads a parameter file.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

Reads a parameter file.

A.2.346 `MSK_readsolution()`

```
MSKrescodee MSK_readsolution (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST char * filename);
```

Reads a solution from a file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

filename

A valid file name.

Reads a solution file and inserts the solution into the solution **whichsol**.

A.2.347 MSK_readsummary()

```
MSKrescodee MSK_readsummary (
    MSKtask_t      task,
    MSKstreamtypee whichstream);
```

Prints information about last file read.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

Prints a short summary of last file that was read.

A.2.348 MSK_readtask()

```
MSKrescodee MSK_readtask (
    MSKtask_t      task,
    MSKCONST char * filename);
```

Load task data from a file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

filename

Input file name.

Load task data from a file, replacing any data that already is in the task object. All problem data are resorted, but if the file contains solutions, the solution status after loading a file is still unknown, even if it was optimal or otherwise well-defined when the file was dumped.

See section [E.4](#) for a description of the Task format.

A.2.349 MSK_reformqcqotosocp()

```
MSKrescodee MSK_reformqcqotosocp (
    MSKtask_t  task,
    MSKtask_t  relaxedtask);
```

Reformulates a quadratic optimization problem to a conic quadratic problem.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

relaxedtask

Task to contain the reformulated problem. The task must be initialized before calling this function.

Reformulates a quadratic optimization problem to a conic quadratic problem.

A.2.350 MSK_relaxprimal()

```
MSKrescodee MSK_relaxprimal (
    MSKtask_t  task,
    MSKtask_t * relaxedtask,
    MSKrealt * wlc,
    MSKrealt * wuc,
    MSKrealt * wlx,
    MSKrealt * wux);
```

Deprecated.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

relaxedtask

The returned task.

wlc

Weights associated with lower bounds on the activity of constraints. If negative, the bound is strictly enforced, i.e. if $(w_l^c)_i < 0$, then $(v_l^c)_i$ is fixed to zero. On return **wlc[i]** contains the relaxed bound.

wuc

Weights associated with upper bounds on the activity of constraints. If negative, the bound is strictly enforced, i.e. if $(w_u^c)_i < 0$, then $(v_u^c)_i$ is fixed to zero. On return **wuc[i]** contains the relaxed bound.

wlx

Weights associated with lower bounds on the activity of variables. If negative, the bound is strictly enforced, i.e. if $(w_l^x)_j < 0$ then $(v_l^x)_j$ is fixed to zero. On return **wlx[i]** contains the relaxed bound.

wux

Weights associated with upper bounds on the activity of variables. If negative, the bound is strictly enforced, i.e. if $(w_u^x)_j < 0$ then $(v_u^x)_j$ is fixed to zero. On return **wux[i]** contains the relaxed bound.

Deprecated. Please use **MSK_primalrepair** instead.

See also

- **MSK_DPAR_FEASREPAIR_TOL** Tolerance for constraint enforcing upper bound on sum of weighted violations in feasibility repair.
- **MSK_IPAR_FEASREPAIR_OPTIMIZE** Controls which type of feasibility analysis is to be performed.
- **MSK_SPAR_FEASREPAIR_NAME_SEPARATOR** Feasibility repair name separator.
- **MSK_SPAR_FEASREPAIR_NAME_PREFIX** Feasibility repair name prefix.

A.2.351 MSK_removebarvars()

```
MSKrescodee MSK_removebarvars (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * subset);
```

The function removes a number of symmetric matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of symmetric matrix which should be removed.

subset

Indexes of symmetric matrix which should be removed.

The function removes a subset of the symmetric matrix from the optimization task. This implies that the existing symmetric matrix are renumbered, for instance if constraint 5 is removed then constraint 6 becomes constraint 5 and so forth.

See also

- **MSK_appendbarvars** Appends a semidefinite variable of dimension dim to the problem.

A.2.352 MSK_removecones()

```
MSKrescodee MSK_removecones (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * subset);
```

Removes a conic constraint from the problem.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of cones which should be removed.

subset

Indexes of cones which should be removed.

Removes a number conic constraint from the problem. In general, it is much more efficient to remove a cone with a high index than a low index.

A.2.353 MSK_removecons()

```
MSKrescodee MSK_removecons (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * subset);
```

The function removes a number of constraints.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of constraints which should be removed.

subset

Indexes of constraints which should be removed.

The function removes a subset of the constraints from the optimization task. This implies that the existing constraints are renumbered, for instance if constraint 5 is removed then constraint 6 becomes constraint 5 and so forth.

See also

- **MSK.appendcons** Appends a number of constraints to the optimization task.

A.2.354 MSK_removevars()

```
MSKrescodee MSK_removevars (
    MSKtask_t      task,
    MSKint32t      num,
    MSKCONST MSKint32t * subset);
```

The function removes a number of variables.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

num

Number of variables which should be removed.

subset

Indexes of variables which should be removed.

The function removes a subset of the variables from the optimization task. This implies that the existing variables are renumbered, for instance if constraint 5 is removed then constraint 6 becomes constraint 5 and so forth.

See also

- **MSK.appendvars** Appends a number of variables to the optimization task.

A.2.355 MSK_resizetask()

```

MSKrescodee MSK_resizetask (
    MSKtask_t    task,
    MSKint32t    maxnumcon,
    MSKint32t    maxnumvar,
    MSKint32t    maxnumcone,
    MSKint64t    maxnumanz,
    MSKint64t    maxnumqnz);

```

Resizes an optimization task.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

maxnumcon

New maximum number of constraints.

maxnumvar

New maximum number of variables.

maxnumcone

New maximum number of cones.

maxnumanz

New maximum number of non-zeros in A .

maxnumqnz

New maximum number of non-zeros in all Q matrixes.

Sets the amount of preallocated space assigned for each type of data in an optimization task.

It is never mandatory to call this function, since its only function is to give a hint of the amount of data to preallocate for efficiency reasons.

Please note that the procedure is **destructive** in the sense that all existing data stored in the task is destroyed.

See also

- **MSK_putmaxnumvar** Sets the number of preallocated variables in the optimization task.
- **MSK_putmaxnumcon** Sets the number of preallocated constraints in the optimization task.
- **MSK_putmaxnumcone** Sets the number of preallocated conic constraints in the optimization task.
- **MSK_putmaxnumanz** The function changes the size of the preallocated storage for linear coefficients.
- **MSK_putmaxnumqnz** Changes the size of the preallocated storage for quadratic terms.

A.2.356 MSK_sensitivityreport()

```
MSKrescodee MSK_sensitivityreport (
    MSKtask_t      task,
    MSKstreamtypee whichstream);
```

Creates a sensitivity report.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

Reads a sensitivity format file from a location given by **MSK_SPAR_SENSITIVITY_FILE_NAME** and writes the result to the stream **whichstream**. If **MSK_SPAR_SENSITIVITY_RES_FILE_NAME** is set to a non-empty string, then the sensitivity report is also written to a file of this name.

See also

- **MSK_dualsensitivity** Performs sensitivity analysis on objective coefficients.
- **MSK_primalsensitivity** Perform sensitivity analysis on bounds.
- **MSK_IPAR_LOG_SENSITIVITY** Control logging in sensitivity analyzer.
- **MSK_IPAR_LOG_SENSITIVITY_OPT** Control logging in sensitivity analyzer.
- **MSK_IPAR_SENSITIVITY_TYPE** Controls which type of sensitivity analysis is to be performed.

A.2.357 MSK_setdefaults()

```
MSKrescodee MSK_setdefaults (MSKtask_t task)
```

Resets all parameters values.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

Resets all the parameters to their default values.

A.2.358 MSK_sktostr()

```
MSKrescodee MSK_sktostr (
    MSKtask_t    task,
    MSKstakeye   sk,
    char *       str);
```

Obtains a status key string.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

sk

A valid status key.

str

String corresponding to the status key **sk**.

Obtains an explanatory string corresponding to a status key.

A.2.359 MSK_solstatostr()

```
MSKrescodee MSK_solstatostr (
    MSKtask_t    task,
    MSKsolstae   solsta,
    char *       str);
```

Obtains a solution status string.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

solsta

Solution status.

str

String corresponding to the solution status **solsta**.

Obtains an explanatory string corresponding to a solution status.

A.2.360 MSK_solutiondef()

```
MSKrescodee MSK_solutiondef (  
    MSKtask_t      task,  
    MSKsoltypee    whichsol,  
    MSKboolean *   isdef);
```

Checks whether a solution is defined.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

isdef

Is non-zero if the requested solution is defined.

Checks whether a solution is defined.

A.2.361 MSK_solutionsummary()

```
MSKrescodee MSK_solutionsummary (  
    MSKtask_t      task,  
    MSKstreamtypee whichstream);
```

Prints a short summary of the current solutions.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

Prints a short summary of the current solutions.

A.2.362 MSK_solvewithbasis()

```

MSKrescodee MSK_solvewithbasis (
    MSKtask_t    task,
    MSKint32t    transp,
    MSKint32t *   numnz,
    MSKint32t *   sub,
    MSKrealt *    val);

```

Solve a linear equation system involving a basis matrix.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

transp

If this argument is non-zero, then (A.5) is solved. Otherwise the system (A.4) is solved.

numnz

As input it is the number of non-zeros in b . As output it is the number of non-zeros in \bar{X} .

sub

As input it contains the positions of the non-zeros in b , i.e.

$$b[\text{sub}[k]] \neq 0, \quad k = 0, \dots, \text{numnz}[0] - 1.$$

As output it contains the positions of the non-zeros in \bar{X} . It is important that **sub** has room for **numcon** elements.

val

As input it is the vector b . Although the positions of the non-zero elements are specified in **sub** it is required that $\text{val}[i] = 0$ if $b[i] = 0$. As output **val** is the vector \bar{X} .

Please note that **val** is a dense vector — not a packed sparse vector. This implies that **val** has room for **numcon** elements.

If a basic solution is available, then exactly **numcon** basis variables are defined. These **numcon** basis variables are denoted the basis. Associated with the basis is a basis matrix denoted B . This function solves either the linear equation system

$$B\bar{X} = b \tag{A.4}$$

or the system

$$B^T \bar{X} = b \tag{A.5}$$

for the unknowns \bar{X} , with b being a user-defined vector.

In order to make sense of the solution \bar{X} it is important to know the ordering of the variables in the basis because the ordering specifies how B is constructed. When calling `MSK_initbasissolve` an ordering of the basis variables is obtained, which can be used to deduce how MOSEK has constructed B . Indeed if the k th basis variable is variable x_j it implies that

$$B_{i,k} = A_{i,j}, \quad i = 0, \dots, \text{numcon} - 1.$$

Otherwise if the k th basis variable is variable x_j^c it implies that

$$B_{i,k} = \begin{cases} -1, & i = j, \\ 0, & i \neq j. \end{cases}$$

Given the knowledge of how B is constructed it is possible to interpret the solution \bar{X} correctly. Please note that this function exploits the sparsity in the vector b to speed up the computations.

See also

- `MSK_initbasissolve` Prepare a task for basis solver.
- `MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE` Controls the sign of the columns in the basis matrix corresponding to slack variables.

A.2.363 `MSK_startstat()`

```
MSKrescodee MSK_startstat (MSKtask_t task)
```

Starts the statistics file.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

Starts the statistics file.

A.2.364 `MSK_stopstat()`

```
MSKrescodee MSK_stopstat (MSKtask_t task)
```

Stops the statistics file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

Stops the statistics file.

A.2.365 MSK_strdupdbgenenv()

```
char * MSK_strdupdbgenenv (
    MSKenv_t      env,
    MSKCONST char * str,
    MSKCONST char * file,
    MSKCONST unsigned line);
```

Make a copy of a string.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

str

String that should be copied.

file

File from which the function is called.

line

Line in the file from which the function is called.

Make a copy of a string. The string created by this procedure must be freed by **MSK_freeenv**.

A.2.366 MSK_strdupdbgtask()

```
char * MSK_strdupdbgtask (
    MSKtask_t      task,
    MSKCONST char * str,
    MSKCONST char * file,
    MSKCONST unsigned line);
```

Make a copy of a string.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

str
String that should be copied.

file
File from which the function is called.

line
Line in the file from which the function is called.

Make a copy of a string. The string created by this procedure must be freed by **MSK_freetask**.

A.2.367 MSK_strdupenv()

```
char * MSK_strdupenv (
    MSKenv_t      env,
    MSKCONST char * str);
```

Make a copy of a string.

Returns:

A response code indicating the status of the function call.

env
The MOSEK environment.

str
String that should be copied.

Make a copy of a string. The string created by this procedure must be freed by **MSK_freeenv**.

A.2.368 MSK_strduptask()

```
char * MSK_strduptask (
    MSKtask_t      task,
    MSKCONST char * str);
```

Make a copy of a string.

Returns:

A response code indicating the status of the function call.

task
An optimization task.

str
String that should be copied.

Make a copy of a string. The string created by this procedure must be freed by **MSK_freetask**.

A.2.369 MSK_strtoconetype()

```
MSKrescodee MSK_strtoconetype (  
    MSKtask_t      task,  
    MSKCONST char * str,  
    MSKconetypee * conetype);
```

Obtains a cone type code.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

str

String corresponding to the cone type code **codetype**.

conetype

The cone type corresponding to the string **str**.

Obtains cone type code corresponding to a cone type string.

A.2.370 MSK_strtosk()

```
MSKrescodee MSK_strtosk (  
    MSKtask_t      task,  
    MSKCONST char * str,  
    MSKint32t *    sk);
```

Obtains a status key.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

str

Status key string.

sk

Status key corresponding to the string.

Obtains the status key corresponding to an explanatory string.

A.2.371 MSK_sy eig()

```
MSKrescodee MSK_sy eig (
    MSKenv_t      env,
    MSKuploe      uplo,
    MSKint32t     n,
    MSKCONST MSKrealt * a,
    MSKrealt *    w);
```

Computes all eigenvalues of a symmetric dense matrix.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

uplo

Indicates whether the upper or lower triangular part is used.

n

Dimension of the symmetric input matrix.

a

A symmetric matrix stored in column-major order. Only the lower-triangular part is used.

w

Array of minimum dimension n where eigenvalues will be stored.

Computes all eigenvalues of a real symmetric matrix A . Eigenvalues are stored in the w array.

A.2.372 MSK_sy evd()

```
MSKrescodee MSK_sy evd (
    MSKenv_t      env,
    MSKuploe      uplo,
    MSKint32t     n,
    MSKrealt *    a,
    MSKrealt *    w);
```

Computes all the eigenvalue and eigenvectors of a symmetric dense matrix, and thus its eigenvalue decomposition.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

uplo

Indicates whether the upper or lower triangular part is used.

n

Dimension of symmetric input matrix.

a

A symmetric matrix stored in column-major order. Only the lower-triangular part is used. It will be overwritten on exit.

w

An array where eigenvalues will be stored. Its length must be at least the dimension of the input matrix.

Computes all the eigenvalues and eigenvectors a real symmetric matrix.

Given the input matrix $A \in \mathbb{R}^{n \times n}$, this function returns a vector $w \in \mathbb{R}^n$ containing the eigenvalues of A and the corresponding eigenvectors, stored in A as well.Therefore, this function compute the eigenvalue decomposition of A as

$$A = UVU^T,$$

where $V = \text{diag}(w)$ and U contains the eigen-vectors of A .**A.2.373** MSK_symnamtovalue()

```
MSKboolean MSK_symnamtovalue (
    MSKCONST char * name,
    char * value);
```

Obtains the value corresponding to a symbolic name defined by MOSEK.

Returns:

A response code indicating the status of the function call.

name

Symbolic name.

value

The corresponding value.

Obtains the value corresponding to a symbolic name defined by MOSEK.

A.2.374 MSK_syrk()

```

MSKrescodee MSK_syrk (
    MSKenv_t          env,
    MSKuploe          uplo,
    MSKtransposee     trans,
    MSKint32t          n,
    MSKint32t          k,
    MSKrealt           alpha,
    MSKCONST MSKrealt * a,
    MSKrealt           beta,
    MSKrealt *         c);

```

Performs a rank- k update of a symmetric matrix.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

uplo

Indicates whether the upper or lower triangular part of C is stored.

trans

Indicates whether the matrix A must be transposed.

n

Specifies the order of C .

k

Indicates the number of rows or columns of A , and its rank.

alpha

A scalar value multiplying the result of the matrix multiplication.

a

The pointer to the array storing matrix A in a column-major format.

beta

A scalar value that multiplies C .

c

The pointer to the array storing matrix C in a column-major format.

Performs a symmetric rank- k update for a symmetric matrix.

Given a symmetric matrix $C \in \mathbb{R}^{n \times n}$, two scalars α, β and a matrix A of rank $k \leq n$, it computes either

$$C = \alpha AA^T + \beta C,$$

or

$$C = \alpha A^T A + \beta C.$$

In the first case $A \in \mathbb{R}^{k \times n}$, in the second $A \in \mathbb{R}^{n \times k}$.

Note that the results overwrite the matrix C .

A.2.375 MSK_toconic()

```
MSKrescodee MSK_toconic (MSKtask_t task)
```

Inplace reformulation of a QCQP to a COP

Returns:

A response code indicating the status of the function call.

task

An optimization task.

This function tries to reformulate a given Quadratically Constrained Quadratic Optimization problem (QCQP) as a Conic Quadratic Optimization problem (CQO). The first step of the reformulation is to convert the quadratic term of the objective function as a constraint, if any. Then the following steps are repeated for each quadratic constraint:

- a conic constraint is added along with a suitable number of auxiliary variables and constraints;
- the original quadratic constraint is not removed, but all its coefficients are zeroed out.

Note that the reformulation preserves all the original variables.

The conversion is performed in-place, i.e. the task passed as argument is modified on exit. That also means that if the reformulation fails, i.e. the given QCQP is not representable as a CQO, then the task has an undefined state. In some cases, users may want to clone the task to ensure a clean copy is preserved.

A.2.376 MSK_unlinkfuncfromenvstream()

```
MSKrescodee MSK_unlinkfuncfromenvstream (
    MSKenv_t      env,
    MSKstreamtypee whichstream);
```

Disconnects a user-defined function from a stream.

Returns:

A response code indicating the status of the function call.

env

The MOSEK environment.

whichstream

Index of the stream.

Disconnects a user-defined function from a stream.

A.2.377 MSK_unlinkfuncfromtaskstream()

```
MSKrescodee MSK_unlinkfuncfromtaskstream (
    MSKtask_t    task,
    MSKstreamtypee whichstream);
```

Disconnects a user-defined function from a task stream.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichstream

Index of the stream.

Disconnects a user-defined function from a task stream.

A.2.378 MSK_updatesolutioninfo()

```
MSKrescodee MSK_updatesolutioninfo (
    MSKtask_t    task,
    MSKsoltypee  whichsol);
```

Update the information items related to the solution.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

Update the information items related to the solution.

A.2.379 MSK_utf8towchar()

```
MSKrescodee MSK_utf8towchar (
    MSKCONST size_t  outputlen,
    size_t *         len,
    size_t *         conv,
    MSKwchart *      output,
    MSKCONST char *  input);
```

Converts an UTF8 string to a wchar string.

Returns:

A response code indicating the status of the function call.

outputlen

The length of the output buffer.

len

The length of the string contained in the output buffer.

conv

Returns the number of characters from converted, i.e. `input[conv]` is the first char which was not converted. If the whole string was converted, then `input[conv]=0`.

output

The input string converted to a wchar string.

input

The UTF8 input string.

Converts an UTF8 string to a wchar string.

A.2.380 MSK_wchartoutf8()

```
MSKrescodee MSK_wchartoutf8 (
    MSKCONST size_t  outputlen,
    size_t *         len,
    size_t *         conv,
    char *           output,
    MSKCONST MSKwchart * input);
```

Converts a wchar string to an UTF8 string.

Returns:

A response code indicating the status of the function call.

outputlen

The length of the output buffer.

len

The length of the string contained in the output buffer.

conv

Returns the number of characters from converted, i.e. `input[conv]` is the first char which was not converted. If the whole string was converted, then `input[conv]=0`.

output

The input string converted to a wchar string.

input

The UTF8 input string.

Converts an UTF8 string to a wchar string.

A.2.381 MSK_whichparam()

```
MSKrescodee MSK_whichparam (
    MSKtask_t      task,
    MSKCONST char * parname,
    MSKparametertype * partype,
    MSKint32t *     param);
```

Checks a parameter name.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

parname

Parameter name.

partype

Parameter type.

param

Which parameter.

Checks if **parname** is valid parameter name. If yes then, **partype** and **param** denotes the type and the index of parameter respectively.

A.2.382 MSK_writebranchpriorities()

```
MSKrescodee MSK_writebranchpriorities (
    MSKtask_t      task,
    MSKCONST char * filename);
```

Writes branching priority data to a file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

filename

Data is written to the file **filename**.

Writes branching priority data to a file.

See also

- **MSK_readbranchpriorities** Reads branching priority data from a file.

A.2.383 MSK_writedata()

```
MSKrescodee MSK_writedata (
    MSKtask_t      task,
    MSKCONST char * filename);
```

Writes problem data to a file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

filename

Data is written to the file **filename** if it is a nonempty string. Otherwise data is written to the file specified by **MSK_SPAR_DATA_FILE_NAME**.

Writes problem data associated with the optimization task to a file in one of four formats:

LP:

A text based row oriented format. File extension **.lp**. See Appendix **E.2**.

MPS:

A text based column oriented format. File extension **.mps**. See Appendix **E.1**.

OPF:

A text based row oriented format. File extension **.opf**. Supports more problem types than MPS and LP. See Appendix **E.3**.

TASK:

A MOSEK specific binary format for fast reading and writing. File extension **.task**.

By default the data file format is determined by the file name extension. This behaviour can be overridden by setting the `MSK_IPAR.WRITE.DATA.FORMAT` parameter.

MOSEK is able to read and write files in a compressed format (gzip). To write in the compressed format append the extension ".gz". E.g to write a gzip compressed MPS file use the extension `mps.gz`.

Please note that MPS, LP and OPF files require all variables to have unique names. If a task contains no names, it is possible to write the file with automatically generated anonymous names by setting the `MSK_IPAR.WRITE.GENERIC.NAMES` parameter to `MSK_ON`.

Please note that if a general nonlinear function appears in the problem then such function *cannot* be written to file and MOSEK will issue a warning.

See also

- `MSK_readdata` Reads problem data from a file.
- `MSK_IPAR.WRITE.DATA.FORMAT` Controls the output file format.

A.2.384 `MSK_writeparamfile()`

```
MSKrescodee MSK_writeparamfile (
    MSKtask_t      task,
    MSKCONST char * filename);
```

Writes all the parameters to a parameter file.

Returns:

A response code indicating the status of the function call.

`task`

An optimization task.

`filename`

The name of parameter file.

Writes all the parameters to a parameter file.

A.2.385 `MSK_writesolution()`

```
MSKrescodee MSK_writesolution (
    MSKtask_t      task,
    MSKsoltypee    whichsol,
    MSKCONST char * filename);
```

Write a solution to a file.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

whichsol

Selects a solution.

filename

A valid file name.

Saves the current basic, interior-point, or integer solution to a file.

See also

- **MSK_IPAR.WRITE_SOL_IGNORE_INVALID_NAMES** Controls whether the user specified names are employed even if they are invalid names.
- **MSK_IPAR.WRITE_SOL_HEAD** Controls solution file format.
- **MSK_IPAR.WRITE_SOL_CONSTRAINTS** Controls the solution file format.
- **MSK_IPAR.WRITE_SOL_VARIABLES** Controls the solution file format.
- **MSK_IPAR.WRITE_SOL_BARVARIABLES** Controls the solution file format.
- **MSK_IPAR.WRITE_BAS_HEAD** Controls the basic solution file format.
- **MSK_IPAR.WRITE_BAS_CONSTRAINTS** Controls the basic solution file format.
- **MSK_IPAR.WRITE_BAS_VARIABLES** Controls the basic solution file format.

A.2.386 MSK_writetask()

```
MSKrescodee MSK_writetask (
    MSKtask_t      task,
    MSKCONST char * filename);
```

Write a complete binary dump of the task data.

Returns:

A response code indicating the status of the function call.

task

An optimization task.

filename

Output file name.

Write a binary dump of the task data. This format saves all problem data, but not callback-funktions and general non-linear terms.

See section [E.4](#) for a description of the Task format.

A.2.387 Task()

The task object is created from an environment object and, optionally, the problem maximum dimensions. The the dimensions are not given they default to 0, put they can be changed afterwards.

If a **Task** object is given instead of an **Env** object, the new task is created using the data from the old task. Callback objects are not copied.

Appendix B

Parameters

Parameters grouped by functionality.

Analysis parameters.

Parameters controlling the behaviour of the problem and solution analyzers.

- **MSK_DPAR.ANA_SOL_INFEAS_TOL**. If a constraint violates its bound with an amount larger than this value, the constraint name, index and violation will be printed by the solution analyzer.

Basis identification parameters.

- **MSK_IPAR.BI_CLEAN_OPTIMIZER**. Controls which simplex optimizer is used in the clean-up phase.
- **MSK_IPAR.BI_IGNORE_MAX_ITER**. Turns on basis identification in case the interior-point optimizer is terminated due to maximum number of iterations.
- **MSK_IPAR.BI_IGNORE_NUM_ERROR**. Turns on basis identification in case the interior-point optimizer is terminated due to a numerical problem.
- **MSK_IPAR.BI_MAX_ITERATIONS**. Maximum number of iterations after basis identification.
- **MSK_IPAR.INTPNT_BASIS**. Controls whether basis identification is performed.
- **MSK_IPAR.LOG_BI**. Controls the amount of output printed by the basis identification procedure. A higher level implies that more information is logged.
- **MSK_IPAR.LOG_BI_FREQ**. Controls the logging frequency.
- **MSK_DPAR.SIM_LU_TOL_REL_PIV**. Relative pivot tolerance employed when computing the LU factorization of the basis matrix.

Behavior of the optimization task.

Parameters defining the behavior of an optimization task when loading data.

- **MSK_SPAR.FEASREPAIR_NAME_PREFIX**. Feasibility repair name prefix.

- **MSK_SPAR_FEASREPAIR_NAME_SEPARATOR**. Feasibility repair name separator.
- **MSK_SPAR_FEASREPAIR_NAME_WSUMVIOL**. Feasibility repair name violation name.

Conic interior-point method parameters.

Parameters defining the behavior of the interior-point method for conic problems.

- **MSK_DPAR_INTPNT_CO_TOL_DFEAS**. Dual feasibility tolerance used by the conic interior-point optimizer.
- **MSK_DPAR_INTPNT_CO_TOL_INFEAS**. Infeasibility tolerance for the conic solver.
- **MSK_DPAR_INTPNT_CO_TOL_MU_RED**. Optimality tolerance for the conic solver.
- **MSK_DPAR_INTPNT_CO_TOL_NEAR_REL**. Optimality tolerance for the conic solver.
- **MSK_DPAR_INTPNT_CO_TOL_PFEAS**. Primal feasibility tolerance used by the conic interior-point optimizer.
- **MSK_DPAR_INTPNT_CO_TOL_REL_GAP**. Relative gap termination tolerance used by the conic interior-point optimizer.

Data check parameters.

These parameters defines data checking settings and problem data tolerances, i.e. which values are rounded to 0 or infinity, and which values are large or small enough to produce a warning.

- **MSK_DPAR_DATA_TOL_AIJ**. Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_AIJ_HUGE**. Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_AIJ_LARGE**. Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_BOUND_INF**. Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_BOUND_WRN**. Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_C_HUGE**. Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_CJ_LARGE**. Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_QIJ**. Data tolerance threshold.
- **MSK_DPAR_DATA_TOL_X**. Data tolerance threshold.
- **MSK_IPAR_LOG_CHECK_CONVEXITY**. Controls logging in convexity check on quadratic problems. Set to a positive value to turn logging on.
If a quadratic coefficient matrix is found to violate the requirement of PSD (NSD) then a list of negative (positive) pivot elements is printed. The absolute value of the pivot elements is also shown.

Data input/output parameters.

Parameters defining the behavior of data readers and writers.

- **MSK_SPAR_BAS_SOL_FILE_NAME**. Name of the bas solution file.
- **MSK_SPAR_DATA_FILE_NAME**. Data are read and written to this file.
- **MSK_SPAR_DEBUG_FILE_NAME**. MOSEK debug file.
- **MSK_SPAR_INT_SOL_FILE_NAME**. Name of the int solution file.

- **MSK_SPAR.ITR_SOL_FILE_NAME**. Name of the itr solution file.
- **MSK_IPAR.LOG_FILE**. If turned on, then some log info is printed when a file is written or read.
- **MSK_SPAR.MIO_DEBUG_STRING**. For internal use only.
- **MSK_SPAR.PARAM.COMMENT_SIGN**. Solution file comment character.
- **MSK_SPAR.PARAM.READ_FILE_NAME**. Modifications to the parameter database is read from this file.
- **MSK_SPAR.PARAM.WRITE_FILE_NAME**. The parameter database is written to this file.
- **MSK_SPAR.READ_MPS_BOU_NAME**. Name of the BOUNDS vector used. An empty name means that the first BOUNDS vector is used.
- **MSK_SPAR.READ_MPS_OBJ_NAME**. Objective name in the MPS file.
- **MSK_SPAR.READ_MPS_RAN_NAME**. Name of the RANGE vector used. An empty name means that the first RANGE vector is used.
- **MSK_SPAR.READ_MPS_RHS_NAME**. Name of the RHS used. An empty name means that the first RHS vector is used.
- **MSK_SPAR.SOL.FILTER_XC_LOW**. Solution file filter.
- **MSK_SPAR.SOL.FILTER_XC_UPR**. Solution file filter.
- **MSK_SPAR.SOL.FILTER_XX_LOW**. Solution file filter.
- **MSK_SPAR.SOL.FILTER_XX_UPR**. Solution file filter.
- **MSK_SPAR.STAT_FILE_NAME**. Statistics file name.
- **MSK_SPAR.STAT_KEY**. Key used when writing the summary file.
- **MSK_SPAR.STAT_NAME**. Name used when writing the statistics file.
- **MSK_SPAR.WRITE_LP_GEN_VAR_NAME**. Added variable names in the LP files.

Debugging parameters.

These parameters defines that can be used when debugging a problem.

- **MSK_IPAR.AUTO_SORT_A_BEFORE_OPT**. Controls whether the elements in each column of A are sorted before an optimization is performed.

Dual simplex optimizer parameters.

Parameters defining the behavior of the dual simplex optimizer for linear problems.

- **MSK_IPAR.SIM_DUAL_CRASH**. Controls whether crashing is performed in the dual simplex optimizer.
- **MSK_IPAR.SIM_DUAL_RESTRICT_SELECTION**. Controls how aggressively restricted selection is used.
- **MSK_IPAR.SIM_DUAL_SELECTION**. Controls the dual simplex strategy.

Feasibility repair parameters.

- **MSK_DPAR_FEASREPAIR_TOL**. Tolerance for constraint enforcing upper bound on sum of weighted violations in feasibility repair.

Infeasibility report parameters.

- **MSK_IPAR_LOG_INFEAS_ANA**. Controls log level for the infeasibility analyzer.

Interior-point method parameters.

Parameters defining the behavior of the interior-point method for linear, conic and convex problems.

- **MSK_IPAR_BI_IGNORE_MAX_ITER**. Turns on basis identification in case the interior-point optimizer is terminated due to maximum number of iterations.
- **MSK_IPAR_BI_IGNORE_NUM_ERROR**. Turns on basis identification in case the interior-point optimizer is terminated due to a numerical problem.
- **MSK_DPAR_CHECK_CONVEXITY_REL_TOL**. Convexity check tolerance.
- **MSK_IPAR_INTPNT_BASIS**. Controls whether basis identification is performed.
- **MSK_DPAR_INTPNT_CO_TOL_DFEAS**. Dual feasibility tolerance used by the conic interior-point optimizer.
- **MSK_DPAR_INTPNT_CO_TOL_INFEAS**. Infeasibility tolerance for the conic solver.
- **MSK_DPAR_INTPNT_CO_TOL_MU_RED**. Optimality tolerance for the conic solver.
- **MSK_DPAR_INTPNT_CO_TOL_NEAR_REL**. Optimality tolerance for the conic solver.
- **MSK_DPAR_INTPNT_CO_TOL_PFEAS**. Primal feasibility tolerance used by the conic interior-point optimizer.
- **MSK_DPAR_INTPNT_CO_TOL_REL_GAP**. Relative gap termination tolerance used by the conic interior-point optimizer.
- **MSK_IPAR_INTPNT_DIFF_STEP**. Controls whether different step sizes are allowed in the primal and dual space.
- **MSK_IPAR_INTPNT_MAX_ITERATIONS**. Controls the maximum number of iterations allowed in the interior-point optimizer.
- **MSK_IPAR_INTPNT_MAX_NUM_COR**. Maximum number of correction steps.
- **MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS**. Maximum number of steps to be used by the iterative search direction refinement.
- **MSK_DPAR_INTPNT_NL_MERIT_BAL**. Controls if the complementarity and infeasibility is converging to zero at about equal rates.
- **MSK_DPAR_INTPNT_NL_TOL_DFEAS**. Dual feasibility tolerance used when a nonlinear model is solved.
- **MSK_DPAR_INTPNT_NL_TOL_MU_RED**. Relative complementarity gap tolerance.
- **MSK_DPAR_INTPNT_NL_TOL_NEAR_REL**. Nonlinear solver optimality tolerance parameter.
- **MSK_DPAR_INTPNT_NL_TOL_PFEAS**. Primal feasibility tolerance used when a nonlinear model is solved.

- **MSK_DPAR.INTPNT_NL_TOL_REL_GAP**. Relative gap termination tolerance for nonlinear problems.
- **MSK_DPAR.INTPNT_NL_TOL_REL_STEP**. Relative step size to the boundary for general nonlinear optimization problems.
- **MSK_IPAR.INTPNT_OFF_COL_TRH**. Controls the aggressiveness of the offending column detection.
- **MSK_IPAR.INTPNT_ORDER_METHOD**. Controls the ordering strategy.
- **MSK_IPAR.INTPNT_REGULARIZATION_USE**. Controls whether regularization is allowed.
- **MSK_IPAR.INTPNT_SCALING**. Controls how the problem is scaled before the interior-point optimizer is used.
- **MSK_IPAR.INTPNT_SOLVE_FORM**. Controls whether the primal or the dual problem is solved.
- **MSK_IPAR.INTPNT_STARTING_POINT**. Starting point used by the interior-point optimizer.
- **MSK_DPAR.INTPNT_TOL_DFEAS**. Dual feasibility tolerance used for linear and quadratic optimization problems.
- **MSK_DPAR.INTPNT_TOL_DSAFE**. Controls the interior-point dual starting point.
- **MSK_DPAR.INTPNT_TOL_INFEAS**. Nonlinear solver infeasibility tolerance parameter.
- **MSK_DPAR.INTPNT_TOL_MU_RED**. Relative complementarity gap tolerance.
- **MSK_DPAR.INTPNT_TOL_PATH**. interior-point centering aggressiveness.
- **MSK_DPAR.INTPNT_TOL_PFEAS**. Primal feasibility tolerance used for linear and quadratic optimization problems.
- **MSK_DPAR.INTPNT_TOL_PSAFE**. Controls the interior-point primal starting point.
- **MSK_DPAR.INTPNT_TOL_REL_GAP**. Relative gap termination tolerance.
- **MSK_DPAR.INTPNT_TOL_REL_STEP**. Relative step size to the boundary for linear and quadratic optimization problems.
- **MSK_DPAR.INTPNT_TOL_STEP_SIZE**. If the step size falls below the value of this parameter, then the interior-point optimizer assumes that it is stalled. In other words the interior-point optimizer does not make any progress and therefore it is better stop.
- **MSK_IPAR.LOG_INTPNT**. Controls the amount of log information from the interior-point optimizers.
- **MSK_IPAR.LOG_PRESOLVE**. Controls amount of output printed by the presolve procedure. A higher level implies that more information is logged.
- **MSK_DPAR.QCQO_REFORMULATE_REL_DROP_TOL**. This parameter determines when columns are dropped in incomplete cholesky factorization doing reformulation of quadratic problems.

License manager parameters.

- **MSK_IPAR.CACHE_LICENSE**. Control license caching.
- **MSK_IPAR.LICENSE_DEBUG**. Controls the license manager client debugging behavior.
- **MSK_IPAR.LICENSE_PAUSE_TIME**. Controls license manager client behavior.
- **MSK_IPAR.LICENSE_SUPPRESS_EXPIRE_WRNS**. Controls license manager client behavior.

- **MSK_IPAR_LICENSE_WAIT**. Controls if MOSEK should queue for a license if none is available.

Logging parameters.

- **MSK_IPAR_LOG**. Controls the amount of log information.
- **MSK_IPAR_LOG_BI**. Controls the amount of output printed by the basis identification procedure. A higher level implies that more information is logged.
- **MSK_IPAR_LOG_BI_FREQ**. Controls the logging frequency.
- **MSK_IPAR_LOG_CONCURRENT**. Controls amount of output printed by the concurrent optimizer.
- **MSK_IPAR_LOG_EXPAND**. Controls the amount of logging when a data item such as the maximum number constraints is expanded.
- **MSK_IPAR_LOG_FACTOR**. If turned on, then the factor log lines are added to the log.
- **MSK_IPAR_LOG_FEAS_REPAIR**. Controls the amount of output printed when performing feasibility repair. A value higher than one means extensive logging.
- **MSK_IPAR_LOG_FILE**. If turned on, then some log info is printed when a file is written or read.
- **MSK_IPAR_LOG_HEAD**. If turned on, then a header line is added to the log.
- **MSK_IPAR_LOG_INFEAS_ANA**. Controls log level for the infeasibility analyzer.
- **MSK_IPAR_LOG_INTPNT**. Controls the amount of log information from the interior-point optimizers.
- **MSK_IPAR_LOG_MIO**. Controls the amount of log information from the mixed-integer optimizers.
- **MSK_IPAR_LOG_MIO_FREQ**. The mixed-integer solver logging frequency.
- **MSK_IPAR_LOG_NONCONVEX**. Controls amount of output printed by the nonconvex optimizer.
- **MSK_IPAR_LOG_OPTIMIZER**. Controls the amount of general optimizer information that is logged.
- **MSK_IPAR_LOG_ORDER**. If turned on, then factor lines are added to the log.
- **MSK_IPAR_LOG_PARAM**. Controls the amount of information printed out about parameter changes.
- **MSK_IPAR_LOG_PRESOLVE**. Controls amount of output printed by the presolve procedure. A higher level implies that more information is logged.
- **MSK_IPAR_LOG_RESPONSE**. Controls amount of output printed when response codes are reported. A higher level implies that more information is logged.
- **MSK_IPAR_LOG_SIM**. Controls the amount of log information from the simplex optimizers.
- **MSK_IPAR_LOG_SIM_FREQ**. Controls simplex logging frequency.
- **MSK_IPAR_LOG_SIM_NETWORK_FREQ**. Controls the network simplex logging frequency.
- **MSK_IPAR_LOG_STORAGE**. Controls the memory related log information.

Mixed-integer optimization parameters.

- **MSK_IPAR.LOG_MIO**. Controls the amount of log information from the mixed-integer optimizers.
- **MSK_IPAR.LOG_MIO_FREQ**. The mixed-integer solver logging frequency.
- **MSK_IPAR.MIO_BRANCH_DIR**. Controls whether the mixed-integer optimizer is branching up or down by default.
- **MSK_IPAR.MIO_CONSTRUCT_SOL**. Controls if an initial mixed integer solution should be constructed from the values of the integer variables.
- **MSK_IPAR.MIO_CONT_SOL**. Controls the meaning of interior-point and basic solutions in mixed integer problems.
- **MSK_IPAR.MIO_CUT_CG**. Controls whether CG cuts should be generated.
- **MSK_IPAR.MIO_CUT_CMIR**. Controls whether mixed integer rounding cuts should be generated.
- **MSK_IPAR.MIO_CUT_LEVEL_ROOT**. Controls the cut level employed by the mixed-integer optimizer at the root node.
- **MSK_IPAR.MIO_CUT_LEVEL_TREE**. Controls the cut level employed by the mixed-integer optimizer in the tree.
- **MSK_DPAR.MIO_DISABLE_TERM_TIME**. Certain termination criteria is disabled within the mixed-integer optimizer for period time specified by the parameter.
- **MSK_IPAR.MIO_FEASPUMP_LEVEL**. Controls the feasibility pump heuristic which is used to construct a good initial feasible solution.
- **MSK_IPAR.MIO_HEURISTIC_LEVEL**. Controls the heuristic employed by the mixed-integer optimizer to locate an initial integer feasible solution.
- **MSK_DPAR.MIO_HEURISTIC_TIME**. Time limit for the mixed-integer heuristics.
- **MSK_IPAR.MIO_HOTSTART**. Controls whether the integer optimizer is hot-started.
- **MSK_IPAR.MIO_KEEP_BASIS**. Controls whether the integer presolve keeps bases in memory.
- **MSK_IPAR.MIO_MAX_NUM_BRANCHES**. Maximum number of branches allowed during the branch and bound search.
- **MSK_IPAR.MIO_MAX_NUM_RELAXS**. Maximum number of relaxations in branch and bound search.
- **MSK_IPAR.MIO_MAX_NUM_SOLUTIONS**. Controls how many feasible solutions the mixed-integer optimizer investigates.
- **MSK_DPAR.MIO_MAX_TIME**. Time limit for the mixed-integer optimizer.
- **MSK_DPAR.MIO_MAX_TIME_APRX_OPT**. Time limit for the mixed-integer optimizer.
- **MSK_DPAR.MIO_NEAR_TOL_ABS_GAP**. Relaxed absolute optimality tolerance employed by the mixed-integer optimizer.
- **MSK_DPAR.MIO_NEAR_TOL_REL_GAP**. The mixed-integer optimizer is terminated when this tolerance is satisfied.
- **MSK_IPAR.MIO_NODE_OPTIMIZER**. Controls which optimizer is employed at the non-root nodes in the mixed-integer optimizer.
- **MSK_IPAR.MIO_NODE_SELECTION**. Controls the node selection strategy employed by the mixed-integer optimizer.

- **MSK_IPAR.MIO.OPTIMIZER_MODE**. An experimental feature.
- **MSK_IPAR.MIO.PRESOLVE.AGGREGATE**. Controls whether problem aggregation is performed in the mixed-integer presolve.
- **MSK_IPAR.MIO.PRESOLVE.PROBING**. Controls whether probing is employed by the mixed-integer presolve.
- **MSK_IPAR.MIO.PRESOLVE.USE**. Controls whether presolve is performed by the mixed-integer optimizer.
- **MSK_IPAR.MIO.PROBING.LEVEL**. Controls the amount of probing employed by the mixed-integer optimizer in presolve.
- **MSK_DPAR.MIO.REL.ADD.CUT.LIMITED**. Controls cut generation for mixed-integer optimizer.
- **MSK_DPAR.MIO.REL.GAP.CONST**. This value is used to compute the relative gap for the solution to an integer optimization problem.
- **MSK_IPAR.MIO.RINS.MAX.NODES**. Maximum number of nodes in each call to the RINS heuristic.
- **MSK_IPAR.MIO.ROOT.OPTIMIZER**. Controls which optimizer is employed at the root node in the mixed-integer optimizer.
- **MSK_IPAR.MIO.STRONG.BRANCH**. The depth from the root in which strong branching is employed.
- **MSK_DPAR.MIO.TOL.ABS.GAP**. Absolute optimality tolerance employed by the mixed-integer optimizer.
- **MSK_DPAR.MIO.TOL.ABS.RELAX.INT**. Integer constraint tolerance.
- **MSK_DPAR.MIO.TOL.FEAS**. Feasibility tolerance for mixed integer solver. Any solution with maximum infeasibility below this value will be considered feasible.
- **MSK_DPAR.MIO.TOL.MAX.CUT.FRAC.RHS**. Controls cut generation for mixed-integer optimizer.
- **MSK_DPAR.MIO.TOL.MIN.CUT.FRAC.RHS**. Controls cut generation for mixed-integer optimizer.
- **MSK_DPAR.MIO.TOL.REL.DUAL.BOUND.IMPROVEMENT**. Controls cut generation for mixed-integer optimizer.
- **MSK_DPAR.MIO.TOL.REL.GAP**. Relative optimality tolerance employed by the mixed-integer optimizer.
- **MSK_DPAR.MIO.TOL.REL.RELAX.INT**. Integer constraint tolerance.
- **MSK_DPAR.MIO.TOL.X**. Absolute solution tolerance used in mixed-integer optimizer.
- **MSK_IPAR.MIO.USE.MULTITHREADED.OPTIMIZER**. Controls whether the new multithreaded optimizer should be used for Mixed integer problems.

Network simplex optimizer parameters.

Parameters defining the behavior of the network simplex optimizer for linear problems.

- **MSK_IPAR.LOG.SIM.NETWORK.FREQ**. Controls the network simplex logging frequency.
- **MSK_IPAR.SIM.REFACTOR.FREQ**. Controls the basis refactoring frequency.

Non-convex solver parameters.

- **MSK_IPAR.LOG_NONCONVEX**. Controls amount of output printed by the nonconvex optimizer.
- **MSK_IPAR.NONCONVEX_MAX_ITERATIONS**. Maximum number of iterations that can be used by the nonconvex optimizer.
- **MSK_DPAR.NONCONVEX_TOL_FEAS**. Feasibility tolerance used by the nonconvex optimizer.
- **MSK_DPAR.NONCONVEX_TOL_OPT**. Optimality tolerance used by the nonconvex optimizer.

Nonlinear convex method parameters.

Parameters defining the behavior of the interior-point method for nonlinear convex problems.

- **MSK_DPAR.INTPNT_NL_MERIT_BAL**. Controls if the complementarity and infeasibility is converging to zero at about equal rates.
- **MSK_DPAR.INTPNT_NL_TOL_DFEAS**. Dual feasibility tolerance used when a nonlinear model is solved.
- **MSK_DPAR.INTPNT_NL_TOL_MU_RED**. Relative complementarity gap tolerance.
- **MSK_DPAR.INTPNT_NL_TOL_NEAR_REL**. Nonlinear solver optimality tolerance parameter.
- **MSK_DPAR.INTPNT_NL_TOL_PFEAS**. Primal feasibility tolerance used when a nonlinear model is solved.
- **MSK_DPAR.INTPNT_NL_TOL_REL_GAP**. Relative gap termination tolerance for nonlinear problems.
- **MSK_DPAR.INTPNT_NL_TOL_REL_STEP**. Relative step size to the boundary for general nonlinear optimization problems.
- **MSK_DPAR.INTPNT_TOL_INFEAS**. Nonlinear solver infeasibility tolerance parameter.
- **MSK_IPAR.LOG_CHECK_CONVEXITY**. Controls logging in convexity check on quadratic problems. Set to a positive value to turn logging on.
If a quadratic coefficient matrix is found to violate the requirement of PSD (NSD) then a list of negative (positive) pivot elements is printed. The absolute value of the pivot elements is also shown.

Optimization system parameters.

Parameters defining the overall solver system environment. This includes system and platform related information and behavior.

- **MSK_IPAR.LICENSE_WAIT**. Controls if MOSEK should queue for a license if none is available.
- **MSK_IPAR.LOG_STORAGE**. Controls the memory related log information.
- **MSK_IPAR.NUM_THREADS**. Controls the number of threads employed by the optimizer. If set to 0 the number of threads used will be equal to the number of cores detected on the machine.

Output information parameters.

- **MSK_IPAR.LICENSE_SUPPRESS_EXPIRE_WRNS**. Controls license manager client behavior.
- **MSK_IPAR.LOG**. Controls the amount of log information.
- **MSK_IPAR.LOG_BI**. Controls the amount of output printed by the basis identification procedure. A higher level implies that more information is logged.

- **MSK_IPAR.LOG_BI_FREQ**. Controls the logging frequency.
- **MSK_IPAR.LOG_EXPAND**. Controls the amount of logging when a data item such as the maximum number constraints is expanded.
- **MSK_IPAR.LOG_FACTOR**. If turned on, then the factor log lines are added to the log.
- **MSK_IPAR.LOG_FEAS_REPAIR**. Controls the amount of output printed when performing feasibility repair. A value higher than one means extensive logging.
- **MSK_IPAR.LOG_FILE**. If turned on, then some log info is printed when a file is written or read.
- **MSK_IPAR.LOG_HEAD**. If turned on, then a header line is added to the log.
- **MSK_IPAR.LOG_INFEAS_ANA**. Controls log level for the infeasibility analyzer.
- **MSK_IPAR.LOG_INTPNT**. Controls the amount of log information from the interior-point optimizers.
- **MSK_IPAR.LOG_MIO**. Controls the amount of log information from the mixed-integer optimizers.
- **MSK_IPAR.LOG_MIO_FREQ**. The mixed-integer solver logging frequency.
- **MSK_IPAR.LOG_NONCONVEX**. Controls amount of output printed by the nonconvex optimizer.
- **MSK_IPAR.LOG_OPTIMIZER**. Controls the amount of general optimizer information that is logged.
- **MSK_IPAR.LOG_ORDER**. If turned on, then factor lines are added to the log.
- **MSK_IPAR.LOG_PARAM**. Controls the amount of information printed out about parameter changes.
- **MSK_IPAR.LOG_RESPONSE**. Controls amount of output printed when response codes are reported. A higher level implies that more information is logged.
- **MSK_IPAR.LOG_SIM**. Controls the amount of log information from the simplex optimizers.
- **MSK_IPAR.LOG_SIM_FREQ**. Controls simplex logging frequency.
- **MSK_IPAR.LOG_SIM_MINOR**. Currently not in use.
- **MSK_IPAR.LOG_SIM_NETWORK_FREQ**. Controls the network simplex logging frequency.
- **MSK_IPAR.LOG_STORAGE**. Controls the memory related log information.
- **MSK_IPAR.MAX_NUM_WARNINGS**. A negative number means all warnings are logged. Otherwise the parameter specifies the maximum number times each warning is logged.
- **MSK_IPAR.WARNING_LEVEL**. Deprecated and not in use

Overall solver parameters.

- **MSK_IPAR.BI_CLEAN_OPTIMIZER**. Controls which simplex optimizer is used in the clean-up phase.
- **MSK_IPAR.CONCURRENT_NUM_OPTIMIZERS**. The maximum number of simultaneous optimizations that will be started by the concurrent optimizer.
- **MSK_IPAR.CONCURRENT_PRIORITY_DUAL_SIMPLEX**. Priority of the dual simplex algorithm when selecting solvers for concurrent optimization.

- **MSK_IPAR_CONCURRENT_PRIORITY_FREE_SIMPLEX**. Priority of the free simplex optimizer when selecting solvers for concurrent optimization.
- **MSK_IPAR_CONCURRENT_PRIORITY_INTPNT**. Priority of the interior-point algorithm when selecting solvers for concurrent optimization.
- **MSK_IPAR_CONCURRENT_PRIORITY_PRIMAL_SIMPLEX**. Priority of the primal simplex algorithm when selecting solvers for concurrent optimization.
- **MSK_IPAR_INFEAS_PREFER_PRIMAL**. Controls which certificate is used if both primal- and dual- certificate of infeasibility is available.
- **MSK_IPAR_LICENSE_WAIT**. Controls if MOSEK should queue for a license if none is available.
- **MSK_IPAR_MIO_CONT_SOL**. Controls the meaning of interior-point and basic solutions in mixed integer problems.
- **MSK_IPAR_MIO_LOCAL_BRANCH_NUMBER**. Controls the size of the local search space when doing local branching.
- **MSK_IPAR_MIO_MODE**. Turns on/off the mixed-integer mode.
- **MSK_IPAR_OPTIMIZER**. Controls which optimizer is used to optimize the task.
- **MSK_IPAR_PRESOLVE_LEVEL**. Currently not used.
- **MSK_IPAR_PRESOLVE_USE**. Controls whether the presolve is applied to a problem before it is optimized.
- **MSK_IPAR_SOLUTION_CALLBACK**. Indicates whether solution call-backs will be performed during the optimization.

Presolve parameters.

- **MSK_IPAR_PRESOLVE_ELIM_FILL**. Maximum amount of fill-in in the elimination phase.
- **MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_NUM_TRIES**. Control the maximum number of times the eliminator is tried.
- **MSK_IPAR_PRESOLVE_ELIMINATOR_USE**. Controls whether free or implied free variables are eliminated from the problem.
- **MSK_IPAR_PRESOLVE_LEVEL**. Currently not used.
- **MSK_IPAR_PRESOLVE_LINDEP_ABS_WORK_TRH**. Controls linear dependency check in presolve.
- **MSK_IPAR_PRESOLVE_LINDEP_REL_WORK_TRH**. Controls linear dependency check in presolve.
- **MSK_IPAR_PRESOLVE_LINDEP_USE**. Controls whether the linear constraints are checked for linear dependencies.
- **MSK_DPAR_PRESOLVE_TOL_ABS_LINDEP**. Absolute tolerance employed by the linear dependency checker.
- **MSK_DPAR_PRESOLVE_TOL_AIJ**. Absolute zero tolerance employed for constraint coefficients in the presolve.
- **MSK_DPAR_PRESOLVE_TOL_REL_LINDEP**. Relative tolerance employed by the linear dependency checker.
- **MSK_DPAR_PRESOLVE_TOL_S**. Absolute zero tolerance employed for slack variables in the presolve.

- **MSK_DPAR.PRESOLVE_TOL_X**. Absolute zero tolerance employed for variables in the presolve.
- **MSK_IPAR.PRESOLVE_USE**. Controls whether the presolve is applied to a problem before it is optimized.

Primal simplex optimizer parameters.

Parameters defining the behavior of the primal simplex optimizer for linear problems.

- **MSK_IPAR.SIM_PRIMAL_CRASH**. Controls the simplex crash.
- **MSK_IPAR.SIM_PRIMAL_RESTRICT_SELECTION**. Controls how aggressively restricted selection is used.
- **MSK_IPAR.SIM_PRIMAL_SELECTION**. Controls the primal simplex strategy.

Progress call-back parameters.

- **MSK_IPAR.SOLUTION_CALLBACK**. Indicates whether solution call-backs will be performed during the optimization.

Simplex optimizer parameters.

Parameters defining the behavior of the simplex optimizer for linear problems.

- **MSK_DPAR.BASIS_REL_TOL_S**. Maximum relative dual bound violation allowed in an optimal basic solution.
- **MSK_DPAR.BASIS_TOL_S**. Maximum absolute dual bound violation in an optimal basic solution.
- **MSK_DPAR.BASIS_TOL_X**. Maximum absolute primal bound violation allowed in an optimal basic solution.
- **MSK_IPAR.LOG_SIM**. Controls the amount of log information from the simplex optimizers.
- **MSK_IPAR.LOG_SIM_FREQ**. Controls simplex logging frequency.
- **MSK_IPAR.LOG_SIM_MINOR**. Currently not in use.
- **MSK_IPAR.SIM_BASIS_FACTOR_USE**. Controls whether a (LU) factorization of the basis is used in a hot-start. Forcing a refactorization sometimes improves the stability of the simplex optimizers, but in most cases there is a performance penalty.
- **MSK_IPAR.SIM_DEGEN**. Controls how aggressively degeneration is handled.
- **MSK_IPAR.SIM_DUAL_PHASEONE_METHOD**. An experimental feature.
- **MSK_IPAR.SIM_EXPLOIT_DUPVEC**. Controls if the simplex optimizers are allowed to exploit duplicated columns.
- **MSK_IPAR.SIM_HOTSTART**. Controls the type of hot-start that the simplex optimizer perform.
- **MSK_IPAR.SIM_INTEGER**. An experimental feature.
- **MSK_DPAR.SIM_LU_TOL_REL_PIV**. Relative pivot tolerance employed when computing the LU factorization of the basis matrix.
- **MSK_IPAR.SIM_MAX_ITERATIONS**. Maximum number of iterations that can be used by a simplex optimizer.

- **MSK_IPAR.SIM_MAX_NUM_SETBACKS**. Controls how many set-backs that are allowed within a simplex optimizer.
- **MSK_IPAR.SIM_NON_SINGULAR**. Controls if the simplex optimizer ensures a non-singular basis, if possible.
- **MSK_IPAR.SIM_PRIMAL_PHASEONE_METHOD**. An experimental feature.
- **MSK_IPAR.SIM_REFORMULATION**. Controls if the simplex optimizers are allowed to reformulate the problem.
- **MSK_IPAR.SIM_SAVE_LU**. Controls if the LU factorization stored should be replaced with the LU factorization corresponding to the initial basis.
- **MSK_IPAR.SIM_SCALING**. Controls how much effort is used in scaling the problem before a simplex optimizer is used.
- **MSK_IPAR.SIM_SCALING_METHOD**. Controls how the problem is scaled before a simplex optimizer is used.
- **MSK_IPAR.SIM_SOLVE_FORM**. Controls whether the primal or the dual problem is solved by the primal-/dual- simplex optimizer.
- **MSK_IPAR.SIM_STABILITY_PRIORITY**. Controls how high priority the numerical stability should be given.
- **MSK_IPAR.SIM_SWITCH_OPTIMIZER**. Controls the simplex behavior.
- **MSK_DPAR.SIMPLEX_ABS.TOL_PIV**. Absolute pivot tolerance employed by the simplex optimizers.

Solution input/output parameters.

Parameters defining the behavior of solution reader and writer.

- **MSK_SPAR.BAS_SOL_FILE_NAME**. Name of the bas solution file.
- **MSK_SPAR.INT_SOL_FILE_NAME**. Name of the int solution file.
- **MSK_SPAR.ITR_SOL_FILE_NAME**. Name of the itr solution file.
- **MSK_IPAR.SOL_FILTER_KEEP_BASIC**. Controls the license manager client behavior.
- **MSK_SPAR.SOL_FILTER_XC_LOW**. Solution file filter.
- **MSK_SPAR.SOL_FILTER_XC_UPR**. Solution file filter.
- **MSK_SPAR.SOL_FILTER_XX_LOW**. Solution file filter.
- **MSK_SPAR.SOL_FILTER_XX_UPR**. Solution file filter.

Termination criterion parameters.

Parameters which define termination and optimality criteria and related information.

- **MSK_DPAR.BASIS_REL.TOL_S**. Maximum relative dual bound violation allowed in an optimal basic solution.
- **MSK_DPAR.BASIS.TOL_S**. Maximum absolute dual bound violation in an optimal basic solution.
- **MSK_DPAR.BASIS.TOL_X**. Maximum absolute primal bound violation allowed in an optimal basic solution.

- **MSK_IPAR.BI_MAX_ITERATIONS**. Maximum number of iterations after basis identification.
- **MSK_DPAR.INTPNT.CO_TOL_DFEAS**. Dual feasibility tolerance used by the conic interior-point optimizer.
- **MSK_DPAR.INTPNT.CO_TOL_INFEAS**. Infeasibility tolerance for the conic solver.
- **MSK_DPAR.INTPNT.CO_TOL_MU_RED**. Optimality tolerance for the conic solver.
- **MSK_DPAR.INTPNT.CO_TOL_NEAR_REL**. Optimality tolerance for the conic solver.
- **MSK_DPAR.INTPNT.CO_TOL_PFEAS**. Primal feasibility tolerance used by the conic interior-point optimizer.
- **MSK_DPAR.INTPNT.CO_TOL_REL_GAP**. Relative gap termination tolerance used by the conic interior-point optimizer.
- **MSK_IPAR.INTPNT_MAX_ITERATIONS**. Controls the maximum number of iterations allowed in the interior-point optimizer.
- **MSK_DPAR.INTPNT.NL_TOL_DFEAS**. Dual feasibility tolerance used when a nonlinear model is solved.
- **MSK_DPAR.INTPNT.NL_TOL_MU_RED**. Relative complementarity gap tolerance.
- **MSK_DPAR.INTPNT.NL_TOL_NEAR_REL**. Nonlinear solver optimality tolerance parameter.
- **MSK_DPAR.INTPNT.NL_TOL_PFEAS**. Primal feasibility tolerance used when a nonlinear model is solved.
- **MSK_DPAR.INTPNT.NL_TOL_REL_GAP**. Relative gap termination tolerance for nonlinear problems.
- **MSK_DPAR.INTPNT.TOL_DFEAS**. Dual feasibility tolerance used for linear and quadratic optimization problems.
- **MSK_DPAR.INTPNT.TOL_INFEAS**. Nonlinear solver infeasibility tolerance parameter.
- **MSK_DPAR.INTPNT.TOL_MU_RED**. Relative complementarity gap tolerance.
- **MSK_DPAR.INTPNT.TOL_PFEAS**. Primal feasibility tolerance used for linear and quadratic optimization problems.
- **MSK_DPAR.INTPNT.TOL_REL_GAP**. Relative gap termination tolerance.
- **MSK_DPAR.LOWER.OBJ_CUT**. Objective bound.
- **MSK_DPAR.LOWER.OBJ_CUT_FINITE_TRH**. Objective bound.
- **MSK_DPAR.MIO_DISABLE_TERM_TIME**. Certain termination criteria is disabled within the mixed-integer optimizer for period time specified by the parameter.
- **MSK_IPAR.MIO_MAX_NUM_BRANCHES**. Maximum number of branches allowed during the branch and bound search.
- **MSK_IPAR.MIO_MAX_NUM_SOLUTIONS**. Controls how many feasible solutions the mixed-integer optimizer investigates.
- **MSK_DPAR.MIO_MAX_TIME**. Time limit for the mixed-integer optimizer.
- **MSK_DPAR.MIO_NEAR_TOL_REL_GAP**. The mixed-integer optimizer is terminated when this tolerance is satisfied.

- **MSK_DPAR_MIO_REL_GAP_CONST**. This value is used to compute the relative gap for the solution to an integer optimization problem.
 - **MSK_DPAR_MIO_TOL_REL_GAP**. Relative optimality tolerance employed by the mixed-integer optimizer.
 - **MSK_DPAR_OPTIMIZER_MAX_TIME**. Solver time limit.
 - **MSK_IPAR_SIM_MAX_ITERATIONS**. Maximum number of iterations that can be used by a simplex optimizer.
 - **MSK_DPAR_UPPER_OBJ_CUT**. Objective bound.
 - **MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH**. Objective bound.
-
- Integer parameters
 - Double parameters
 - String parameters

B.1 MSKdparame: Double parameters

B.1.1 MSK_DPAR_ANA_SOL_INFEAS_TOL

Corresponding constant:

MSK_DPAR_ANA_SOL_INFEAS_TOL

Description:

If a constraint violates its bound with an amount larger than this value, the constraint name, index and violation will be printed by the solution analyzer.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1e-6

B.1.2 MSK_DPAR_BASIS_REL_TOL_S

Corresponding constant:

MSK_DPAR_BASIS_REL_TOL_S

Description:

Maximum relative dual bound violation allowed in an optimal basic solution.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-12

B.1.3 MSK_DPAR_BASIS_TOL_S**Corresponding constant:**

MSK_DPAR_BASIS_TOL_S

Description:

Maximum absolute dual bound violation in an optimal basic solution.

Possible Values:

Any number between 1.0e-9 and +inf.

Default value:

1.0e-6

B.1.4 MSK_DPAR_BASIS_TOL_X**Corresponding constant:**

MSK_DPAR_BASIS_TOL_X

Description:

Maximum absolute primal bound violation allowed in an optimal basic solution.

Possible Values:

Any number between 1.0e-9 and +inf.

Default value:

1.0e-6

B.1.5 MSK_DPAR_CHECK_CONVEXITY_REL_TOL**Corresponding constant:**

MSK_DPAR_CHECK_CONVEXITY_REL_TOL

Description:

This parameter controls when the full convexity check declares a problem to be non-convex. Increasing this tolerance relaxes the criteria for declaring the problem non-convex.

A problem is declared non-convex if negative (positive) pivot elements are detected in the cholesky factor of a matrix which is required to be PSD (NSD). This parameter controls how much this non-negativity requirement may be violated.

If d_i is the pivot element for column i , then the matrix Q is considered to not be PSD if:

$$d_i \leq -|Q_{ii}| * \text{check_convexity_rel_tol}$$

Possible Values:

Any number between 0 and +inf.

Default value:

1e-10

B.1.6 MSK_DPAR_DATA_TOL_AIJ

Corresponding constant:

MSK_DPAR_DATA_TOL_AIJ

Description:

Absolute zero tolerance for elements in A . If any value A_{ij} is smaller than this parameter in absolute terms MOSEK will treat the values as zero and generate a warning.

Possible Values:

Any number between 1.0e-16 and 1.0e-6.

Default value:

1.0e-12

B.1.7 MSK_DPAR_DATA_TOL_AIJ_HUGE

Corresponding constant:

MSK_DPAR_DATA_TOL_AIJ_HUGE

Description:

An element in A which is larger than this value in absolute size causes an error.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e20

B.1.8 MSK_DPAR_DATA_TOL_AIJ_LARGE

Corresponding constant:

MSK_DPAR_DATA_TOL_AIJ_LARGE

Description:

An element in A which is larger than this value in absolute size causes a warning message to be printed.

Possible Values:

Any number between 0.0 and $+\text{inf}$.

Default value:

1.0e10

B.1.9 MSK_DPAR_DATA_TOL_BOUND_INF

Corresponding constant:

MSK_DPAR_DATA_TOL_BOUND_INF

Description:

Any bound which in absolute value is greater than this parameter is considered infinite.

Possible Values:

Any number between 0.0 and $+\text{inf}$.

Default value:

1.0e16

B.1.10 MSK_DPAR_DATA_TOL_BOUND_WRN

Corresponding constant:

MSK_DPAR_DATA_TOL_BOUND_WRN

Description:

If a bound value is larger than this value in absolute size, then a warning message is issued.

Possible Values:

Any number between 0.0 and $+\text{inf}$.

Default value:

1.0e8

B.1.11 MSK_DPAR_DATA_TOL_C_HUGE**Corresponding constant:**

MSK_DPAR_DATA_TOL_C_HUGE

Description:

An element in c which is larger than the value of this parameter in absolute terms is considered to be huge and generates an error.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e16

B.1.12 MSK_DPAR_DATA_TOL_CJ_LARGE**Corresponding constant:**

MSK_DPAR_DATA_TOL_CJ_LARGE

Description:

An element in c which is larger than this value in absolute terms causes a warning message to be printed.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e8

B.1.13 MSK_DPAR_DATA_TOL_QIJ**Corresponding constant:**

MSK_DPAR_DATA_TOL_QIJ

Description:

Absolute zero tolerance for elements in Q matrixes.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-16

B.1.14 MSK_DPAR_DATA_TOL_X**Corresponding constant:**

MSK_DPAR_DATA_TOL_X

Description:

Zero tolerance for constraints and variables i.e. if the distance between the lower and upper bound is less than this value, then the lower and lower bound is considered identical.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-8

B.1.15 MSK_DPAR_FEASREPAIR_TOL**Corresponding constant:**

MSK_DPAR_FEASREPAIR_TOL

Description:

Tolerance for constraint enforcing upper bound on sum of weighted violations in feasibility repair.

Possible Values:

Any number between 1.0e-16 and 1.0e+16.

Default value:

1.0e-10

B.1.16 MSK_DPAR_INTPNT_CO_TOL_DFEAS**Corresponding constant:**

MSK_DPAR_INTPNT_CO_TOL_DFEAS

Description:

Dual feasibility tolerance used by the conic interior-point optimizer.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-8

See also:

- **MSK_DPAR_INTPNT_CO_TOL_NEAR_REL** Optimality tolerance for the conic solver.

B.1.17 MSK_DPAR_INTPNT_CO_TOL_INFEAS**Corresponding constant:**

MSK_DPAR_INTPNT_CO_TOL_INFEAS

Description:

Controls when the conic interior-point optimizer declares the model primal or dual infeasible. A small number means the optimizer gets more conservative about declaring the model infeasible.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-10

B.1.18 MSK_DPAR_INTPNT_CO_TOL_MU_RED**Corresponding constant:**

MSK_DPAR_INTPNT_CO_TOL_MU_RED

Description:

Relative complementarity gap tolerance feasibility tolerance used by the conic interior-point optimizer.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-8

B.1.19 MSK_DPAR_INTPNT_CO_TOL_NEAR_REL**Corresponding constant:**

MSK_DPAR_INTPNT_CO_TOL_NEAR_REL

Description:

If MOSEK cannot compute a solution that has the prescribed accuracy, then it will multiply the termination tolerances with value of this parameter. If the solution then satisfies the termination criteria, then the solution is denoted near optimal, near feasible and so forth.

Possible Values:

Any number between 1.0 and +inf.

Default value:

1000

B.1.20 MSK_DPAR_INTPNT_CO_TOL_PFEAS**Corresponding constant:**

MSK_DPAR_INTPNT_CO_TOL_PFEAS

Description:

Primal feasibility tolerance used by the conic interior-point optimizer.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-8

See also:

- **MSK_DPAR_INTPNT_CO_TOL_NEAR_REL** Optimality tolerance for the conic solver.

B.1.21 MSK_DPAR_INTPNT_CO_TOL_REL_GAP**Corresponding constant:**

MSK_DPAR_INTPNT_CO_TOL_REL_GAP

Description:

Relative gap termination tolerance used by the conic interior-point optimizer.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-7

See also:

- **MSK_DPAR_INTPNT_CO_TOL_NEAR_REL** Optimality tolerance for the conic solver.

B.1.22 MSK_DPAR_INTPNT_NL_MERIT_BAL**Corresponding constant:**

MSK_DPAR_INTPNT_NL_MERIT_BAL

Description:

Controls if the complementarity and infeasibility is converging to zero at about equal rates.

Possible Values:

Any number between 0.0 and 0.99.

Default value:

1.0e-4

B.1.23 MSK_DPAR_INTPNT_NL_TOL_DFEAS**Corresponding constant:**

MSK_DPAR_INTPNT_NL_TOL_DFEAS

Description:

Dual feasibility tolerance used when a nonlinear model is solved.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-8

B.1.24 MSK_DPAR_INTPNT_NL_TOL_MU_RED**Corresponding constant:**

MSK_DPAR_INTPNT_NL_TOL_MU_RED

Description:

Relative complementarity gap tolerance.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-12

B.1.25 MSK_DPAR_INTPNT_NL_TOL_NEAR_REL**Corresponding constant:**

MSK_DPAR_INTPNT_NL_TOL_NEAR_REL

Description:

If the MOSEK nonlinear interior-point optimizer cannot compute a solution that has the prescribed accuracy, then it will multiply the termination tolerances with value of this parameter. If the solution then satisfies the termination criteria, then the solution is denoted near optimal, near feasible and so forth.

Possible Values:

Any number between 1.0 and +inf.

Default value:

1000.0

B.1.26 MSK_DPAR_INTPNT_NL_TOL_PFEAS**Corresponding constant:**

MSK_DPAR_INTPNT_NL_TOL_PFEAS

Description:

Primal feasibility tolerance used when a nonlinear model is solved.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-8

B.1.27 MSK_DPAR_INTPNT_NL_TOL_REL_GAP**Corresponding constant:**

MSK_DPAR_INTPNT_NL_TOL_REL_GAP

Description:

Relative gap termination tolerance for nonlinear problems.

Possible Values:

Any number between 1.0e-14 and +inf.

Default value:

1.0e-6

B.1.28 MSK_DPAR_INTPNT_NL_TOL_REL_STEP**Corresponding constant:**

MSK_DPAR_INTPNT_NL_TOL_REL_STEP

Description:

Relative step size to the boundary for general nonlinear optimization problems.

Possible Values:

Any number between 1.0e-4 and 0.9999999.

Default value:

0.995

B.1.29 MSK_DPAR_INTPNT_TOL_DFEAS**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_DFEAS

Description:

Dual feasibility tolerance used for linear and quadratic optimization problems.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-8

B.1.30 MSK_DPAR_INTPNT_TOL_DSAFE**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_DSAFE

Description:

Controls the initial dual starting point used by the interior-point optimizer. If the interior-point optimizer converges slowly.

Possible Values:

Any number between 1.0e-4 and +inf.

Default value:

1.0

B.1.31 MSK_DPAR_INTPNT_TOL_INFEAS**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_INFEAS

Description:

Controls when the optimizer declares the model primal or dual infeasible. A small number means the optimizer gets more conservative about declaring the model infeasible.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-10

B.1.32 MSK_DPAR_INTPNT_TOL_MU_RED**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_MU_RED

Description:

Relative complementarity gap tolerance.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-16

B.1.33 MSK_DPAR_INTPNT_TOL_PATH**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_PATH

Description:

Controls how close the interior-point optimizer follows the central path. A large value of this parameter means the central is followed very closely. On numerical unstable problems it may be worthwhile to increase this parameter.

Possible Values:

Any number between 0.0 and 0.9999.

Default value:

1.0e-8

B.1.34 MSK_DPAR_INTPNT_TOL_PFEAS**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_PFEAS

Description:

Primal feasibility tolerance used for linear and quadratic optimization problems.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-8

B.1.35 MSK_DPAR_INTPNT_TOL_PSAFE**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_PSAFE

Description:

Controls the initial primal starting point used by the interior-point optimizer. If the interior-point optimizer converges slowly and/or the constraint or variable bounds are very large, then it may be worthwhile to increase this value.

Possible Values:

Any number between 1.0e-4 and +inf.

Default value:

1.0

B.1.36 MSK_DPAR_INTPNT_TOL_REL_GAP**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_REL_GAP

Description:

Relative gap termination tolerance.

Possible Values:

Any number between 1.0e-14 and +inf.

Default value:

1.0e-8

B.1.37 MSK_DPAR_INTPNT_TOL_REL_STEP**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_REL_STEP

Description:

Relative step size to the boundary for linear and quadratic optimization problems.

Possible Values:

Any number between 1.0e-4 and 0.999999.

Default value:

0.9999

B.1.38 MSK_DPAR_INTPNT_TOL_STEP_SIZE**Corresponding constant:**

MSK_DPAR_INTPNT_TOL_STEP_SIZE

Description:

If the step size falls below the value of this parameter, then the interior-point optimizer assumes that it is stalled. In other words the interior-point optimizer does not make any progress and therefore it is better stop.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

1.0e-6

B.1.39 MSK_DPAR_LOWER_OBJ_CUT**Corresponding constant:**

MSK_DPAR_LOWER_OBJ_CUT

Description:

If either a primal or dual feasible solution is found proving that the optimal objective value is outside, the interval `[MSK_DPAR_LOWER_OBJ_CUT, MSK_DPAR_UPPER_OBJ_CUT]`, then MOSEK is terminated.

Possible Values:

Any number between -inf and +inf.

Default value:

-1.0e30

See also:

- `MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH` Objective bound.

B.1.40 MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH**Corresponding constant:**

MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH

Description:

If the lower objective cut is less than the value of this parameter value, then the lower objective cut i.e. `MSK_DPAR_LOWER_OBJ_CUT` is treated as $-\infty$.

Possible Values:

Any number between -inf and +inf.

Default value:

-0.5e30

B.1.41 MSK_DPAR_MIO_DISABLE_TERM_TIME**Corresponding constant:**

MSK_DPAR_MIO_DISABLE_TERM_TIME

Description:

The termination criteria governed by

- **MSK_IPAR_MIO_MAX_NUM_RELAXS**
- **MSK_IPAR_MIO_MAX_NUM_BRANCHES**
- **MSK_DPAR_MIO_NEAR_TOL_ABS_GAP**
- **MSK_DPAR_MIO_NEAR_TOL_REL_GAP**

is disabled the first n seconds. This parameter specifies the number n . A negative value is identical to infinity i.e. the termination criteria are never checked.

Possible Values:

Any number between -inf and +inf.

Default value:

-1.0

See also:

- **MSK_IPAR_MIO_MAX_NUM_RELAXS** Maximum number of relaxations in branch and bound search.
- **MSK_IPAR_MIO_MAX_NUM_BRANCHES** Maximum number of branches allowed during the branch and bound search.
- **MSK_DPAR_MIO_NEAR_TOL_ABS_GAP** Relaxed absolute optimality tolerance employed by the mixed-integer optimizer.
- **MSK_DPAR_MIO_NEAR_TOL_REL_GAP** The mixed-integer optimizer is terminated when this tolerance is satisfied.

B.1.42 MSK_DPAR_MIO_HEURISTIC_TIME**Corresponding constant:**

MSK_DPAR_MIO_HEURISTIC_TIME

Description:

Minimum amount of time to be used in the heuristic search for a good feasible integer solution. A negative values implies that the optimizer decides the amount of time to be spent in the heuristic.

Possible Values:

Any number between -inf and +inf.

Default value:

-1.0

B.1.43 MSK_DPAR_MIO_MAX_TIME**Corresponding constant:**

MSK_DPAR_MIO_MAX_TIME

Description:

This parameter limits the maximum time spent by the mixed-integer optimizer. A negative number means infinity.

Possible Values:

Any number between -inf and +inf.

Default value:

-1.0

B.1.44 MSK_DPAR_MIO_MAX_TIME_APRX_OPT**Corresponding constant:**

MSK_DPAR_MIO_MAX_TIME_APRX_OPT

Description:

Number of seconds spent by the mixed-integer optimizer before the **MSK_DPAR_MIO_TOL_REL_RELAX_INT** is applied.

Possible Values:

Any number between 0.0 and +inf.

Default value:

60

B.1.45 MSK_DPAR_MIO_NEAR_TOL_ABS_GAP**Corresponding constant:**

MSK_DPAR_MIO_NEAR_TOL_ABS_GAP

Description:

Relaxed absolute optimality tolerance employed by the mixed-integer optimizer. This termination criteria is delayed. See [MSK_DPAR_MIO_DISABLE_TERM_TIME](#) for details.

Possible Values:

Any number between 0.0 and +inf.

Default value:

0.0

See also:

- [MSK_DPAR_MIO_DISABLE_TERM_TIME](#) Certain termination criteria is disabled within the mixed-integer optimizer for period time specified by the parameter.

B.1.46 MSK_DPAR_MIO_NEAR_TOL_REL_GAP**Corresponding constant:**

MSK_DPAR_MIO_NEAR_TOL_REL_GAP

Description:

The mixed-integer optimizer is terminated when this tolerance is satisfied. This termination criteria is delayed. See [MSK_DPAR_MIO_DISABLE_TERM_TIME](#) for details.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-3

See also:

- [MSK_DPAR_MIO_DISABLE_TERM_TIME](#) Certain termination criteria is disabled within the mixed-integer optimizer for period time specified by the parameter.

B.1.47 MSK_DPAR_MIO_REL_ADD_CUT_LIMITED**Corresponding constant:**

MSK_DPAR_MIO_REL_ADD_CUT_LIMITED

Description:

Controls how many cuts the mixed-integer optimizer is allowed to add to the problem. Let α be the value of this parameter and m the number constraints, then mixed-integer optimizer is allowed to αm cuts.

Possible Values:

Any number between 0.0 and 2.0.

Default value:

0.75

B.1.48 MSK_DPAR_MIO_REL_GAP_CONST**Corresponding constant:**

MSK_DPAR_MIO_REL_GAP_CONST

Description:

This value is used to compute the relative gap for the solution to an integer optimization problem.

Possible Values:

Any number between 1.0e-15 and +inf.

Default value:

1.0e-10

B.1.49 MSK_DPAR_MIO_TOL_ABS_GAP**Corresponding constant:**

MSK_DPAR_MIO_TOL_ABS_GAP

Description:

Absolute optimality tolerance employed by the mixed-integer optimizer.

Possible Values:

Any number between 0.0 and +inf.

Default value:

0.0

B.1.50 MSK_DPAR_MIO_TOL_ABS_RELAX_INT**Corresponding constant:**

MSK_DPAR_MIO_TOL_ABS_RELAX_INT

Description:

Absolute relaxation tolerance of the integer constraints. I.e. $\min(|x| - \lfloor x \rfloor, \lceil x \rceil - |x|)$ is less than the tolerance then the integer restrictions assumed to be satisfied.

Possible Values:

Any number between 1e-9 and +inf.

Default value:

1.0e-5

B.1.51 MSK_DPAR_MIO_TOL_FEAS**Corresponding constant:**

MSK_DPAR_MIO_TOL_FEAS

Description:

Feasibility tolerance for mixed integer solver. Any solution with maximum infeasibility below this value will be considered feasible.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-7

B.1.52 MSK_DPAR_MIO_TOL_MAX_CUT_FRAC_RHS**Corresponding constant:**

MSK_DPAR_MIO_TOL_MAX_CUT_FRAC_RHS

Description:

Maximum value of fractional part of right hand side to generate CMIR and CG cuts for. A value of 0.0 means that the value is selected automatically.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

0.0

B.1.53 MSK_DPAR_MIO_TOL_MIN_CUT_FRAC_RHS**Corresponding constant:**

MSK_DPAR_MIO_TOL_MIN_CUT_FRAC_RHS

Description:

Minimum value of fractional part of right hand side to generate CMIR and CG cuts for. A value of 0.0 means that the value is selected automatically.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

0.0

B.1.54 MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT**Corresponding constant:**

MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT

Description:

If the relative improvement of the dual bound is smaller than this value, the solver will terminate the root cut generation. A value of 0.0 means that the value is selected automatically.

Possible Values:

Any number between 0.0 and 1.0.

Default value:

0.0

B.1.55 MSK_DPAR_MIO_TOL_REL_GAP**Corresponding constant:**

MSK_DPAR_MIO_TOL_REL_GAP

Description:

Relative optimality tolerance employed by the mixed-integer optimizer.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-4

B.1.56 MSK_DPAR_MIO_TOL_REL_RELAX_INT**Corresponding constant:**

MSK_DPAR_MIO_TOL_REL_RELAX_INT

Description:

Relative relaxation tolerance of the integer constraints. I.e $(\min(|x| - \lfloor x \rfloor, \lceil x \rceil - |x|))$ is less than the tolerance times $|x|$ then the integer restrictions assumed to be satisfied.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-6

B.1.57 MSK_DPAR_MIO_TOL_X**Corresponding constant:**

MSK_DPAR_MIO_TOL_X

Description:

Absolute solution tolerance used in mixed-integer optimizer.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-6

B.1.58 MSK_DPAR_NONCONVEX_TOL_FEAS**Corresponding constant:**

MSK_DPAR_NONCONVEX_TOL_FEAS

Description:

Feasibility tolerance used by the nonconvex optimizer.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-6

B.1.59 MSK_DPAR_NONCONVEX_TOL_OPT**Corresponding constant:**

MSK_DPAR_NONCONVEX_TOL_OPT

Description:

Optimality tolerance used by the nonconvex optimizer.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-7

B.1.60 MSK_DPAR_OPTIMIZER_MAX_TIME**Corresponding constant:**

MSK_DPAR_OPTIMIZER_MAX_TIME

Description:

Maximum amount of time the optimizer is allowed to spent on the optimization. A negative number means infinity.

Possible Values:

Any number between -inf and +inf.

Default value:

-1.0

B.1.61 MSK_DPAR_PREOLVE_TOL_ABS_LINDEP**Corresponding constant:**

MSK_DPAR_PREOLVE_TOL_ABS_LINDEP

Description:

Absolute tolerance employed by the linear dependency checker.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-6

B.1.62 MSK_DPAR_PREOLVE_TOL_AIJ**Corresponding constant:**

MSK_DPAR_PREOLVE_TOL_AIJ

Description:Absolute zero tolerance employed for a_{ij} in the presolve.**Possible Values:**

Any number between 1.0e-15 and +inf.

Default value:

1.0e-12

B.1.63 MSK_DPAR_PREOLVE_TOL_REL_LINDEP**Corresponding constant:**

MSK_DPAR_PREOLVE_TOL_REL_LINDEP

Description:

Relative tolerance employed by the linear dependency checker.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-10

B.1.64 MSK_DPAR_PREOLVE_TOL_S**Corresponding constant:**

MSK_DPAR_PREOLVE_TOL_S

Description:Absolute zero tolerance employed for s_i in the presolve.**Possible Values:**

Any number between 0.0 and +inf.

Default value:

1.0e-8

B.1.65 MSK_DPAR_PRESOLVE_TOL_X**Corresponding constant:**

MSK_DPAR_PRESOLVE_TOL_X

Description:

Absolute zero tolerance employed for x_j in the presolve.

Possible Values:

Any number between 0.0 and +inf.

Default value:

1.0e-8

B.1.66 MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL**Corresponding constant:**

MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL

Description:

This parameter determines when columns are dropped in incomplete cholesky factorization doing reformulation of quadratic problems.

Possible Values:

Any number between 0 and +inf.

Default value:

1e-15

B.1.67 MSK_DPAR_SIM_LU_TOL_REL_PIV**Corresponding constant:**

MSK_DPAR_SIM_LU_TOL_REL_PIV

Description:

Relative pivot tolerance employed when computing the LU factorization of the basis in the simplex optimizers and in the basis identification procedure.

A value closer to 1.0 generally improves numerical stability but typically also implies an increase in the computational work.

Possible Values:

Any number between 1.0e-6 and 0.999999.

Default value:

0.01

B.1.68 MSK_DPAR_SIMPLEX_ABS_TOL_PIV**Corresponding constant:**

MSK_DPAR_SIMPLEX_ABS_TOL_PIV

Description:

Absolute pivot tolerance employed by the simplex optimizers.

Possible Values:

Any number between 1.0e-12 and +inf.

Default value:

1.0e-7

B.1.69 MSK_DPAR_UPPER_OBJ_CUT**Corresponding constant:**

MSK_DPAR_UPPER_OBJ_CUT

Description:

If either a primal or dual feasible solution is found proving that the optimal objective value is outside, `[MSK_DPAR_LOWER_OBJ_CUT, MSK_DPAR_UPPER_OBJ_CUT]`, then MOSEK is terminated.

Possible Values:

Any number between -inf and +inf.

Default value:

1.0e30

See also:

- `MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH` Objective bound.

B.1.70 MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH**Corresponding constant:**

MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH

Description:

If the upper objective cut is greater than the value of this value parameter, then the the upper objective cut `MSK_DPAR_UPPER_OBJ_CUT` is treated as ∞ .

Possible Values:

Any number between -inf and +inf.

Default value:

0.5e30

B.2 MSKiparame: Integer parameters

B.2.1 MSK_IPAR_ALLOC_ADD_QNZ

Corresponding constant:

MSK_IPAR_ALLOC_ADD_QNZ

Description:

Additional number of Q non-zeros that are allocated space for when `numanz` exceeds `maxnumqnz` during addition of new Q entries.

Possible Values:

Any number between 0 and `+inf`.

Default value:

5000

B.2.2 MSK_IPAR_ANA_SOL_BASIS

Corresponding constant:

MSK_IPAR_ANA_SOL_BASIS

Description:

Controls whether the basis matrix is analyzed in solution analyzer.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.3 MSK_IPAR_ANA_SOL_PRINT_VIOLATED

Corresponding constant:

MSK_IPAR_ANA_SOL_PRINT_VIOLATED

Description:

Controls whether a list of violated constraints is printed when calling **MSK_analyzesolution**. All constraints violated by more than the value set by the parameter **MSK_DPAR_ANA_SOL_INFEAS_TOL** will be printed.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.4 MSK_IPAR_AUTO_SORT_A_BEFORE_OPT

Corresponding constant:

MSK_IPAR_AUTO_SORT_A_BEFORE_OPT

Description:

Controls whether the elements in each column of A are sorted before an optimization is performed. This is not required but makes the optimization more deterministic.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.5 MSK_IPAR_AUTO_UPDATE_SOL_INFO

Corresponding constant:

MSK_IPAR_AUTO_UPDATE_SOL_INFO

Description:

Controls whether the solution information items are automatically updated after an optimization is performed.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.6 MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE

Corresponding constant:

MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE

Description:

If a slack variable is in the basis, then the corresponding column in the basis is a unit vector with -1 in the right position. However, if this parameter is set to **MSK_ON**, -1 is replaced by 1.

This has significance for the results returned by the **MSK_solvewithbasis** function.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.7 MSK_IPAR_BI_CLEAN_OPTIMIZER

Corresponding constant:

MSK_IPAR_BI_CLEAN_OPTIMIZER

Description:

Controls which simplex optimizer is used in the clean-up phase.

Possible values:

- **MSK_OPTIMIZER_CONCURRENT** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_CONIC** The optimizer for problems having conic constraints.
- **MSK_OPTIMIZER_DUAL_SIMPLEX** The dual simplex optimizer is used.
- **MSK_OPTIMIZER_FREE** The optimizer is chosen automatically.
- **MSK_OPTIMIZER_FREE_SIMPLEX** One of the simplex optimizers is used.
- **MSK_OPTIMIZER_INTPNT** The interior-point optimizer is used.
- **MSK_OPTIMIZER_MIXED_INT** The mixed-integer optimizer.
- **MSK_OPTIMIZER_MIXED_INT_CONIC** The mixed-integer optimizer for conic and linear problems.
- **MSK_OPTIMIZER_NETWORK_PRIMAL_SIMPLEX** The network primal simplex optimizer is used. It is only applicable to pure network problems.
- **MSK_OPTIMIZER_NONCONVEX** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_PRIMAL_DUAL_SIMPLEX** The primal dual simplex optimizer is used.
- **MSK_OPTIMIZER_PRIMAL_SIMPLEX** The primal simplex optimizer is used.

Default value:

MSK_OPTIMIZER_FREE

B.2.8 MSK_IPAR_BI_IGNORE_MAX_ITER

Corresponding constant:

MSK_IPAR_BI_IGNORE_MAX_ITER

Description:

If the parameter **MSK_IPAR_INTPNT_BASIS** has the value **MSK_BI_NO_ERROR** and the interior-point optimizer has terminated due to maximum number of iterations, then basis identification is performed if this parameter has the value **MSK_ON**.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.9 MSK_IPAR_BI_IGNORE_NUM_ERROR

Corresponding constant:

MSK_IPAR_BI_IGNORE_NUM_ERROR

Description:

If the parameter **MSK_IPAR_INTPNT_BASIS** has the value **MSK_BI_NO_ERROR** and the interior-point optimizer has terminated due to a numerical problem, then basis identification is performed if this parameter has the value **MSK_ON**.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.10 MSK_IPAR_BI_MAX_ITERATIONS

Corresponding constant:

MSK_IPAR_BI_MAX_ITERATIONS

Description:

Controls the maximum number of simplex iterations allowed to optimize a basis after the basis identification.

Possible Values:

Any number between 0 and +inf.

Default value:

1000000

B.2.11 MSK_IPAR_CACHE_LICENSE**Corresponding constant:**

MSK_IPAR_CACHE_LICENSE

Description:

Specifies if the license is kept checked out for the lifetime of the mosek environment (on) or returned to the server immediately after the optimization (off).

By default the license is checked out for the lifetime of the MOSEK environment by the first call to **MSK.optimizetrm**. The license is checked in when **MSK.deleteenv** is called.

A specific license feature may be checked in when not in use with the function **MSK.checkinlicense**.

Check-in and check-out of licenses have an overhead. Frequent communication with the license server should be avoided.

Possible values:

- **MSK.OFF** Switch the option off.
- **MSK.ON** Switch the option on.

Default value:

MSK.ON

B.2.12 MSK_IPAR_CHECK_CONVEXITY**Corresponding constant:**

MSK_IPAR_CHECK_CONVEXITY

Description:

Specify the level of convexity check on quadratic problems

Possible values:

- **MSK.CHECK_CONVEXITY_FULL** Perform a full convexity check.
- **MSK.CHECK_CONVEXITY_NONE** No convexity check.
- **MSK.CHECK_CONVEXITY_SIMPLE** Perform simple and fast convexity check.

Default value:

MSK.CHECK_CONVEXITY_FULL

B.2.13 MSK_IPAR_COMPRESS_STATFILE**Corresponding constant:**

MSK_IPAR_COMPRESS_STATFILE

Description:

Control compression of stat files.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.14 MSK_IPAR_CONCURRENT_NUM_OPTIMIZERS**Corresponding constant:**

MSK_IPAR_CONCURRENT_NUM_OPTIMIZERS

Description:

The maximum number of simultaneous optimizations that will be started by the concurrent optimizer.

Possible Values:

Any number between 0 and +inf.

Default value:

2

B.2.15 MSK_IPAR_CONCURRENT_PRIORITY_DUAL_SIMPLEX**Corresponding constant:**

MSK_IPAR_CONCURRENT_PRIORITY_DUAL_SIMPLEX

Description:

Priority of the dual simplex algorithm when selecting solvers for concurrent optimization.

Possible Values:

Any number between 0 and +inf.

Default value:

2

B.2.16 MSK_IPAR_CONCURRENT_PRIORITY_FREE_SIMPLEX**Corresponding constant:**

MSK_IPAR_CONCURRENT_PRIORITY_FREE_SIMPLEX

Description:

Priority of the free simplex optimizer when selecting solvers for concurrent optimization.

Possible Values:

Any number between 0 and +inf.

Default value:

3

B.2.17 MSK_IPAR_CONCURRENT_PRIORITY_INTPNT**Corresponding constant:**

MSK_IPAR_CONCURRENT_PRIORITY_INTPNT

Description:

Priority of the interior-point algorithm when selecting solvers for concurrent optimization.

Possible Values:

Any number between 0 and +inf.

Default value:

4

B.2.18 MSK_IPAR_CONCURRENT_PRIORITY_PRIMAL_SIMPLEX**Corresponding constant:**

MSK_IPAR_CONCURRENT_PRIORITY_PRIMAL_SIMPLEX

Description:

Priority of the primal simplex algorithm when selecting solvers for concurrent optimization.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.19 MSK_IPAR_FEASREPAIR_OPTIMIZE**Corresponding constant:**

MSK_IPAR_FEASREPAIR_OPTIMIZE

Description:

Controls which type of feasibility analysis is to be performed.

Possible values:

- **MSK_FEASREPAIR_OPTIMIZE_COMBINED** Minimize with original objective subject to minimal weighted violation of bounds.
- **MSK_FEASREPAIR_OPTIMIZE_NONE** Do not optimize the feasibility repair problem.
- **MSK_FEASREPAIR_OPTIMIZE_PENALTY** Minimize weighted sum of violations.

Default value:

MSK_FEASREPAIR_OPTIMIZE_NONE

B.2.20 MSK_IPAR_INFEAS_GENERIC_NAMES**Corresponding constant:**

MSK_IPAR_INFEAS_GENERIC_NAMES

Description:

Controls whether generic names are used when an infeasible subproblem is created.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.21 MSK_IPAR_INFEAS_PREFER_PRIMAL**Corresponding constant:**

MSK_IPAR_INFEAS_PREFER_PRIMAL

Description:

If both certificates of primal and dual infeasibility are supplied then only the primal is used when this option is turned on.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.22 MSK_IPAR_INFEAS_REPORT_AUTO

Corresponding constant:

MSK_IPAR_INFEAS_REPORT_AUTO

Description:

Controls whether an infeasibility report is automatically produced after the optimization if the problem is primal or dual infeasible.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.23 MSK_IPAR_INFEAS_REPORT_LEVEL

Corresponding constant:

MSK_IPAR_INFEAS_REPORT_LEVEL

Description:

Controls the amount of information presented in an infeasibility report. Higher values imply more information.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.24 MSK_IPAR_INTPNT_BASIS

Corresponding constant:

MSK_IPAR_INTPNT_BASIS

Description:

Controls whether the interior-point optimizer also computes an optimal basis.

Possible values:

- **MSK_BI_ALWAYS** Basis identification is always performed even if the interior-point optimizer terminates abnormally.
- **MSK_BI_IF_FEASIBLE** Basis identification is not performed if the interior-point optimizer terminates with a problem status saying that the problem is primal or dual infeasible.
- **MSK_BI_NEVER** Never do basis identification.
- **MSK_BI_NO_ERROR** Basis identification is performed if the interior-point optimizer terminates without an error.
- **MSK_BI_RESERVED** Not currently in use.

Default value:

MSK_BI_ALWAYS

See also:

- **MSK_IPAR_BI_IGNORE_MAX_ITER** Turns on basis identification in case the interior-point optimizer is terminated due to maximum number of iterations.
- **MSK_IPAR_BI_IGNORE_NUM_ERROR** Turns on basis identification in case the interior-point optimizer is terminated due to a numerical problem.

B.2.25 MSK_IPAR_INTPNT_DIFF_STEP

Corresponding constant:

MSK_IPAR_INTPNT_DIFF_STEP

Description:

Controls whether different step sizes are allowed in the primal and dual space.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.26 MSK_IPAR_INTPNT_FACTOR_DEBUG_LVL

Corresponding constant:

MSK_IPAR_INTPNT_FACTOR_DEBUG_LVL

Description:

Controls factorization debug level.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.27 MSK_IPAR_INTPNT_FACTOR_METHOD

Corresponding constant:

MSK_IPAR_INTPNT_FACTOR_METHOD

Description:

Controls the method used to factor the Newton equation system.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.28 MSK_IPAR_INTPNT_HOTSTART

Corresponding constant:

MSK_IPAR_INTPNT_HOTSTART

Description:

Currently not in use.

Possible values:

- **MSK_INTPNT_HOTSTART_DUAL** The interior-point optimizer exploits the dual solution only.
- **MSK_INTPNT_HOTSTART_NONE** The interior-point optimizer performs a coldstart.
- **MSK_INTPNT_HOTSTART_PRIMAL** The interior-point optimizer exploits the primal solution only.
- **MSK_INTPNT_HOTSTART_PRIMAL_DUAL** The interior-point optimizer exploits both the primal and dual solution.

Default value:

`MSK_INTPNT_HOTSTART_NONE`

B.2.29 MSK_IPAR_INTPNT_MAX_ITERATIONS

Corresponding constant:

`MSK_IPAR_INTPNT_MAX_ITERATIONS`

Description:

Controls the maximum number of iterations allowed in the interior-point optimizer.

Possible Values:

Any number between 0 and +inf.

Default value:

400

B.2.30 MSK_IPAR_INTPNT_MAX_NUM_COR

Corresponding constant:

`MSK_IPAR_INTPNT_MAX_NUM_COR`

Description:

Controls the maximum number of correctors allowed by the multiple corrector procedure. A negative value means that MOSEK is making the choice.

Possible Values:

Any number between -1 and +inf.

Default value:

-1

B.2.31 MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS

Corresponding constant:

`MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS`

Description:

Maximum number of steps to be used by the iterative refinement of the search direction. A negative value implies that the optimizer Chooses the maximum number of iterative refinement steps.

Possible Values:

Any number between -inf and +inf.

Default value:

-1

B.2.32 MSK_IPAR_INTPNT_OFF_COL_TRH

Corresponding constant:

MSK_IPAR_INTPNT_OFF_COL_TRH

Description:

Controls how many offending columns are detected in the Jacobian of the constraint matrix.

1 means aggressive detection, higher values mean less aggressive detection.

0 means no detection.

Possible Values:

Any number between 0 and +inf.

Default value:

40

B.2.33 MSK_IPAR_INTPNT_ORDER_METHOD

Corresponding constant:

MSK_IPAR_INTPNT_ORDER_METHOD

Description:

Controls the ordering strategy used by the interior-point optimizer when factorizing the Newton equation system.

Possible values:

- **MSK_ORDER_METHOD_APPMINLOC** Approximate minimum local fill-in ordering is employed.
- **MSK_ORDER_METHOD_EXPERIMENTAL** This option should not be used.
- **MSK_ORDER_METHOD_FORCE_GRAPHPAR** Always use the graph partitioning based ordering even if it is worse than the approximate minimum local fill ordering.
- **MSK_ORDER_METHOD_FREE** The ordering method is chosen automatically.
- **MSK_ORDER_METHOD_NONE** No ordering is used.
- **MSK_ORDER_METHOD_TRY_GRAPHPAR** Always try the the graph partitioning based ordering.

Default value:

MSK_ORDER_METHOD_FREE

B.2.34 MSK_IPAR_INTPNT_REGULARIZATION_USE**Corresponding constant:**

MSK_IPAR_INTPNT_REGULARIZATION_USE

Description:

Controls whether regularization is allowed.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.35 MSK_IPAR_INTPNT_SCALING**Corresponding constant:**

MSK_IPAR_INTPNT_SCALING

Description:

Controls how the problem is scaled before the interior-point optimizer is used.

Possible values:

- **MSK_SCALING_AGGRESSIVE** A very aggressive scaling is performed.
- **MSK_SCALING_FREE** The optimizer chooses the scaling heuristic.
- **MSK_SCALING_MODERATE** A conservative scaling is performed.
- **MSK_SCALING_NONE** No scaling is performed.

Default value:

MSK_SCALING_FREE

B.2.36 MSK_IPAR_INTPNT_SOLVE_FORM**Corresponding constant:**

MSK_IPAR_INTPNT_SOLVE_FORM

Description:

Controls whether the primal or the dual problem is solved.

Possible values:

- **MSK_SOLVE_DUAL** The optimizer should solve the dual problem.
- **MSK_SOLVE_FREE** The optimizer is free to solve either the primal or the dual problem.
- **MSK_SOLVE_PRIMAL** The optimizer should solve the primal problem.

Default value:

MSK_SOLVE_FREE

B.2.37 MSK_IPAR_INTPNT_STARTING_POINT

Corresponding constant:

MSK_IPAR_INTPNT_STARTING_POINT

Description:

Starting point used by the interior-point optimizer.

Possible values:

- **MSK_STARTING_POINT_CONSTANT** The optimizer constructs a starting point by assigning a constant value to all primal and dual variables. This starting point is normally robust.
- **MSK_STARTING_POINT_FREE** The starting point is chosen automatically.
- **MSK_STARTING_POINT_GUESS** The optimizer guesses a starting point.
- **MSK_STARTING_POINT_SATISFY_BOUNDS** The starting point is chosen to satisfy all the simple bounds on nonlinear variables. If this starting point is employed, then more care than usual should be employed when choosing the bounds on the nonlinear variables. In particular very tight bounds should be avoided.

Default value:

MSK_STARTING_POINT_FREE

B.2.38 MSK_IPAR_LIC_TRH_EXPIRY_WRN

Corresponding constant:

MSK_IPAR_LIC_TRH_EXPIRY_WRN

Description:

If a license feature expires in a number of days less than the value of this parameter then a warning will be issued.

Possible Values:

Any number between 0 and +inf.

Default value:

7

B.2.39 MSK_IPAR_LICENSE_DEBUG

Corresponding constant:

MSK_IPAR_LICENSE_DEBUG

Description:

This option is used to turn on debugging of the incense manager.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.40 MSK_IPAR_LICENSE_PAUSE_TIME

Corresponding constant:

MSK_IPAR_LICENSE_PAUSE_TIME

Description:

If **MSK_IPAR_LICENSE_WAIT=MSK_ON** and no license is available, then MOSEK sleeps a number of milliseconds between each check of whether a license has become free.

Possible Values:

Any number between 0 and 1000000.

Default value:

100

B.2.41 MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS

Corresponding constant:

MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS

Description:

Controls whether license features expire warnings are suppressed.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.42 MSK_IPAR_LICENSE_WAIT

Corresponding constant:

MSK_IPAR_LICENSE_WAIT

Description:

If all licenses are in use MOSEK returns with an error code. However, by turning on this parameter MOSEK will wait for an available license.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.43 MSK_IPAR_LOG

Corresponding constant:

MSK_IPAR_LOG

Description:

Controls the amount of log information. The value 0 implies that all log information is suppressed. A higher level implies that more information is logged.

Please note that if a task is employed to solve a sequence of optimization problems the value of this parameter is reduced by the value of **MSK_IPAR_LOG_CUT_SECOND_OPT** for the second and any subsequent optimizations.

Possible Values:

Any number between 0 and +inf.

Default value:

10

See also:

- **MSK_IPAR_LOG_CUT_SECOND_OPT** Controls the reduction in the log levels for the second and any subsequent optimizations.

B.2.44 MSK_IPAR_LOG_BI**Corresponding constant:**

MSK_IPAR_LOG_BI

Description:

Controls the amount of output printed by the basis identification procedure. A higher level implies that more information is logged.

Possible Values:

Any number between 0 and +inf.

Default value:

4

B.2.45 MSK_IPAR_LOG_BI_FREQ**Corresponding constant:**

MSK_IPAR_LOG_BI_FREQ

Description:

Controls how frequent the optimizer outputs information about the basis identification and how frequent the user-defined call-back function is called.

Possible Values:

Any number between 0 and +inf.

Default value:

2500

B.2.46 MSK_IPAR_LOG_CHECK_CONVEXITY**Corresponding constant:**

MSK_IPAR_LOG_CHECK_CONVEXITY

Description:

Controls logging in convexity check on quadratic problems. Set to a positive value to turn logging on.

If a quadratic coefficient matrix is found to violate the requirement of PSD (NSD) then a list of negative (positive) pivot elements is printed. The absolute value of the pivot elements is also shown.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.47 MSK_IPAR_LOG_CONCURRENT

Corresponding constant:

MSK_IPAR_LOG_CONCURRENT

Description:

Controls amount of output printed by the concurrent optimizer.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.48 MSK_IPAR_LOG_CUT_SECOND_OPT

Corresponding constant:

MSK_IPAR_LOG_CUT_SECOND_OPT

Description:

If a task is employed to solve a sequence of optimization problems, then the value of the log levels is reduced by the value of this parameter. E.g **MSK_IPAR_LOG** and **MSK_IPAR_LOG_SIM** are reduced by the value of this parameter for the second and any subsequent optimizations.

Possible Values:

Any number between 0 and +inf.

Default value:

1

See also:

- **MSK_IPAR_LOG** Controls the amount of log information.
- **MSK_IPAR_LOG_INTPNT** Controls the amount of log information from the interior-point optimizers.
- **MSK_IPAR_LOG_MIO** Controls the amount of log information from the mixed-integer optimizers.
- **MSK_IPAR_LOG_SIM** Controls the amount of log information from the simplex optimizers.

B.2.49 MSK_IPAR_LOG_EXPAND**Corresponding constant:**

MSK_IPAR_LOG_EXPAND

Description:

Controls the amount of logging when a data item such as the maximum number constrains is expanded.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.50 MSK_IPAR_LOG_FACTOR**Corresponding constant:**

MSK_IPAR_LOG_FACTOR

Description:

If turned on, then the factor log lines are added to the log.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.51 MSK_IPAR_LOG_FEAS_REPAIR**Corresponding constant:**

MSK_IPAR_LOG_FEAS_REPAIR

Description:

Controls the amount of output printed when performing feasibility repair. A value higher than one means extensive logging.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.52 MSK_IPAR_LOG_FILE

Corresponding constant:

MSK_IPAR_LOG_FILE

Description:

If turned on, then some log info is printed when a file is written or read.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.53 MSK_IPAR_LOG_HEAD

Corresponding constant:

MSK_IPAR_LOG_HEAD

Description:

If turned on, then a header line is added to the log.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.54 MSK_IPAR_LOG_INFEAS_ANA

Corresponding constant:

MSK_IPAR_LOG_INFEAS_ANA

Description:

Controls amount of output printed by the infeasibility analyzer procedures. A higher level implies that more information is logged.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.55 MSK_IPAR_LOG_INTPNT**Corresponding constant:**

MSK_IPAR_LOG_INTPNT

Description:

Controls amount of output printed by the interior-point optimizer. A higher level implies that more information is logged.

Possible Values:

Any number between 0 and +inf.

Default value:

4

B.2.56 MSK_IPAR_LOG_MIO**Corresponding constant:**

MSK_IPAR_LOG_MIO

Description:

Controls the log level for the mixed-integer optimizer. A higher level implies that more information is logged.

Possible Values:

Any number between 0 and +inf.

Default value:

4

B.2.57 MSK_IPAR_LOG_MIO_FREQ**Corresponding constant:**

MSK_IPAR_LOG_MIO_FREQ

Description:

Controls how frequent the mixed-integer optimizer prints the log line. It will print line every time **MSK_IPAR_LOG_MIO_FREQ** relaxations have been solved.

Possible Values:

A integer value.

Default value:

1000

B.2.58 MSK_IPAR_LOG_NONCONVEX**Corresponding constant:**

MSK_IPAR_LOG_NONCONVEX

Description:

Controls amount of output printed by the nonconvex optimizer.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.59 MSK_IPAR_LOG_OPTIMIZER**Corresponding constant:**

MSK_IPAR_LOG_OPTIMIZER

Description:

Controls the amount of general optimizer information that is logged.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.60 MSK_IPAR_LOG_ORDER**Corresponding constant:**

MSK_IPAR_LOG_ORDER

Description:

If turned on, then factor lines are added to the log.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.61 MSK_IPAR_LOG_PARAM**Corresponding constant:**

MSK_IPAR_LOG_PARAM

Description:

Controls the amount of information printed out about parameter changes.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.62 MSK_IPAR_LOG_PRESOLVE**Corresponding constant:**

MSK_IPAR_LOG_PRESOLVE

Description:

Controls amount of output printed by the presolve procedure. A higher level implies that more information is logged.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.63 MSK_IPAR_LOG_RESPONSE**Corresponding constant:**

MSK_IPAR_LOG_RESPONSE

Description:

Controls amount of output printed when response codes are reported. A higher level implies that more information is logged.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.64 MSK_IPAR_LOG_SENSITIVITY

Corresponding constant:

MSK_IPAR_LOG_SENSITIVITY

Description:

Controls the amount of logging during the sensitivity analysis. 0: Means no logging information is produced. 1: Timing information is printed. 2: Sensitivity results are printed.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.65 MSK_IPAR_LOG_SENSITIVITY_OPT

Corresponding constant:

MSK_IPAR_LOG_SENSITIVITY_OPT

Description:

Controls the amount of logging from the optimizers employed during the sensitivity analysis. 0 means no logging information is produced.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.66 MSK_IPAR_LOG_SIM

Corresponding constant:

MSK_IPAR_LOG_SIM

Description:

Controls amount of output printed by the simplex optimizer. A higher level implies that more information is logged.

Possible Values:

Any number between 0 and +inf.

Default value:

4

B.2.67 MSK_IPAR_LOG_SIM_FREQ**Corresponding constant:**

MSK_IPAR_LOG_SIM_FREQ

Description:

Controls how frequent the simplex optimizer outputs information about the optimization and how frequent the user-defined call-back function is called.

Possible Values:

Any number between 0 and +inf.

Default value:

1000

B.2.68 MSK_IPAR_LOG_SIM_MINOR**Corresponding constant:**

MSK_IPAR_LOG_SIM_MINOR

Description:

Currently not in use.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.69 MSK_IPAR_LOG_SIM_NETWORK_FREQ**Corresponding constant:**

MSK_IPAR_LOG_SIM_NETWORK_FREQ

Description:

Controls how frequent the network simplex optimizer outputs information about the optimization and how frequent the user-defined call-back function is called. The network optimizer will use a logging frequency equal to **MSK_IPAR_LOG_SIM_FREQ** times **MSK_IPAR_LOG_SIM_NETWORK_FREQ**.

Possible Values:

Any number between 0 and +inf.

Default value:

1000

B.2.70 MSK_IPAR_LOG_STORAGE

Corresponding constant:

MSK_IPAR_LOG_STORAGE

Description:

When turned on, MOSEK prints messages regarding the storage usage and allocation.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.71 MSK_IPAR_MAX_NUM_WARNINGS

Corresponding constant:

MSK_IPAR_MAX_NUM_WARNINGS

Description:

A negative number means all warnings are logged. Otherwise the parameter specifies the maximum number times each warning is logged.

Possible Values:

Any number between -inf and +inf.

Default value:

6

B.2.72 MSK_IPAR_MIO_BRANCH_DIR

Corresponding constant:

MSK_IPAR_MIO_BRANCH_DIR

Description:

Controls whether the mixed-integer optimizer is branching up or down by default.

Possible values:

- **MSK_BRANCH_DIR_DOWN** The mixed-integer optimizer always chooses the down branch first.
- **MSK_BRANCH_DIR_FREE** The mixed-integer optimizer decides which branch to choose.
- **MSK_BRANCH_DIR_UP** The mixed-integer optimizer always chooses the up branch first.

Default value:

MSK_BRANCH_DIR_FREE

B.2.73 MSK_IPAR_MIO_BRANCH_PRIORITIES_USE

Corresponding constant:

MSK_IPAR_MIO_BRANCH_PRIORITIES_USE

Description:

Controls whether branching priorities are used by the mixed-integer optimizer.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.74 MSK_IPAR_MIO_CONSTRUCT_SOL

Corresponding constant:

MSK_IPAR_MIO_CONSTRUCT_SOL

Description:

If set to **MSK_ON** and all integer variables have been given a value for which a feasible mixed integer solution exists, then MOSEK generates an initial solution to the mixed integer problem by fixing all integer values and solving the remaining problem.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.75 MSK_IPAR_MIO_CONT_SOL

Corresponding constant:

MSK_IPAR_MIO_CONT_SOL

Description:

Controls the meaning of the interior-point and basic solutions in mixed integer problems.

Possible values:

- **MSK_MIO_CONT_SOL_ITG** The reported interior-point and basic solutions are a solution to the problem with all integer variables fixed at the value they have in the integer solution. A solution is only reported in case the problem has a primal feasible solution.
- **MSK_MIO_CONT_SOL_ITG_REL** In case the problem is primal feasible then the reported interior-point and basic solutions are a solution to the problem with all integer variables fixed at the value they have in the integer solution. If the problem is primal infeasible, then the solution to the root node problem is reported.
- **MSK_MIO_CONT_SOL_NONE** No interior-point or basic solution are reported when the mixed-integer optimizer is used.
- **MSK_MIO_CONT_SOL_ROOT** The reported interior-point and basic solutions are a solution to the root node problem when mixed-integer optimizer is used.

Default value:

MSK_MIO_CONT_SOL_NONE

B.2.76 MSK_IPAR_MIO_CUT_CG

Corresponding constant:

MSK_IPAR_MIO_CUT_CG

Description:

Controls whether CG cuts should be generated.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.77 MSK_IPAR_MIO_CUT_CMIR

Corresponding constant:

MSK_IPAR_MIO_CUT_CMIR

Description:

Controls whether mixed integer rounding cuts should be generated.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.78 MSK_IPAR_MIO_CUT_LEVEL_ROOT**Corresponding constant:**

MSK_IPAR_MIO_CUT_LEVEL_ROOT

Description:

Controls the cut level employed by the mixed-integer optimizer at the root node. A negative value means a default value determined by the mixed-integer optimizer is used. By adding the appropriate values from the following table the employed cut types can be controlled.

GUB cover	+2
Flow cover	+4
Lifting	+8
Plant location	+16
Disaggregation	+32
Knapsack cover	+64
Lattice	+128
Gomory	+256
Coefficient reduction	+512
GCD	+1024
Obj. integrality	+2048

Possible Values:

Any value.

Default value:

-1

B.2.79 MSK_IPAR_MIO_CUT_LEVEL_TREE**Corresponding constant:**

MSK_IPAR_MIO_CUT_LEVEL_TREE

Description:

Controls the cut level employed by the mixed-integer optimizer at the tree. See [MSK_IPAR_MIO_CUT_LEVEL_ROOT](#) for an explanation of the parameter values.

Possible Values:

Any value.

Default value:

-1

B.2.80 MSK_IPAR_MIO_FEASPUMP_LEVEL**Corresponding constant:**

MSK_IPAR_MIO_FEASPUMP_LEVEL

Description:

Feasibility pump is a heuristic designed to compute an initial feasible solution. A value of 0 implies that the feasibility pump heuristic is not used. A value of -1 implies that the mixed-integer optimizer decides how the feasibility pump heuristic is used. A larger value than 1 implies that the feasibility pump is employed more aggressively. Normally a value beyond 3 is not worthwhile.

Possible Values:

Any number between -inf and 3.

Default value:

-1

B.2.81 MSK_IPAR_MIO_HEURISTIC_LEVEL**Corresponding constant:**

MSK_IPAR_MIO_HEURISTIC_LEVEL

Description:

Controls the heuristic employed by the mixed-integer optimizer to locate an initial good integer feasible solution. A value of zero means the heuristic is not used at all. A larger value than 0 means that a gradually more sophisticated heuristic is used which is computationally more expensive. A negative value implies that the optimizer chooses the heuristic. Normally a value around 3 to 5 should be optimal.

Possible Values:

Any value.

Default value:

-1

B.2.82 MSK_IPAR_MIO_HOTSTART**Corresponding constant:**

MSK_IPAR_MIO_HOTSTART

Description:

Controls whether the integer optimizer is hot-started.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.83 MSK_IPAR_MIO_KEEP_BASIS

Corresponding constant:

MSK_IPAR_MIO_KEEP_BASIS

Description:

Controls whether the integer presolve keeps bases in memory. This speeds on the solution process at cost of bigger memory consumption.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.84 MSK_IPAR_MIO_LOCAL_BRANCH_NUMBER

Corresponding constant:

MSK_IPAR_MIO_LOCAL_BRANCH_NUMBER

Description:

Controls the size of the local search space when doing local branching.

Possible Values:

Any number between -inf and +inf.

Default value:

-1

B.2.85 MSK_IPAR_MIO_MAX_NUM_BRANCHES

Corresponding constant:

MSK_IPAR_MIO_MAX_NUM_BRANCHES

Description:

Maximum number of branches allowed during the branch and bound search. A negative value means infinite.

Possible Values:

Any number between -inf and +inf.

Default value:

-1

See also:

- **MSK_DPAR_MIO_DISABLE_TERM_TIME** Certain termination criteria is disabled within the mixed-integer optimizer for period time specified by the parameter.

B.2.86 MSK_IPAR_MIO_MAX_NUM_RELAXS**Corresponding constant:**

MSK_IPAR_MIO_MAX_NUM_RELAXS

Description:

Maximum number of relaxations allowed during the branch and bound search. A negative value means infinite.

Possible Values:

Any number between -inf and +inf.

Default value:

-1

See also:

- **MSK_DPAR_MIO_DISABLE_TERM_TIME** Certain termination criteria is disabled within the mixed-integer optimizer for period time specified by the parameter.

B.2.87 MSK_IPAR_MIO_MAX_NUM_SOLUTIONS**Corresponding constant:**

MSK_IPAR_MIO_MAX_NUM_SOLUTIONS

Description:

The mixed-integer optimizer can be terminated after a certain number of different feasible solutions has been located. If this parameter has the value n and n is strictly positive, then the mixed-integer optimizer will be terminated when n feasible solutions have been located.

Possible Values:

Any number between -inf and +inf.

Default value:

-1

See also:

- **MSK_DPAR_MIO_DISABLE_TERM_TIME** Certain termination criteria is disabled within the mixed-integer optimizer for period time specified by the parameter.

B.2.88 MSK_IPAR_MIO_MODE**Corresponding constant:**

MSK_IPAR_MIO_MODE

Description:

Controls whether the optimizer includes the integer restrictions when solving a (mixed) integer optimization problem.

Possible values:

- **MSK_MIO_MODE_IGNORED** The integer constraints are ignored and the problem is solved as a continuous problem.
- **MSK_MIO_MODE_LAZY** Integer restrictions should be satisfied if an optimizer is available for the problem.
- **MSK_MIO_MODE_SATISFIED** Integer restrictions should be satisfied.

Default value:

MSK_MIO_MODE_SATISFIED

B.2.89 MSK_IPAR_MIO_MT_USER_CB**Corresponding constant:**

MSK_IPAR_MIO_MT_USER_CB

Description:

If true user callbacks are called from each thread used by this optimizer. If false the user callback is only called from a single thread.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.90 MSK_IPAR_MIO_NODE_OPTIMIZER

Corresponding constant:

MSK_IPAR_MIO_NODE_OPTIMIZER

Description:

Controls which optimizer is employed at the non-root nodes in the mixed-integer optimizer.

Possible values:

- **MSK_OPTIMIZER_CONCURRENT** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_CONIC** The optimizer for problems having conic constraints.
- **MSK_OPTIMIZER_DUAL_SIMPLEX** The dual simplex optimizer is used.
- **MSK_OPTIMIZER_FREE** The optimizer is chosen automatically.
- **MSK_OPTIMIZER_FREE_SIMPLEX** One of the simplex optimizers is used.
- **MSK_OPTIMIZER_INTPNT** The interior-point optimizer is used.
- **MSK_OPTIMIZER_MIXED_INT** The mixed-integer optimizer.
- **MSK_OPTIMIZER_MIXED_INT_CONIC** The mixed-integer optimizer for conic and linear problems.
- **MSK_OPTIMIZER_NETWORK_PRIMAL_SIMPLEX** The network primal simplex optimizer is used. It is only applicable to pure network problems.
- **MSK_OPTIMIZER_NONCONVEX** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_PRIMAL_DUAL_SIMPLEX** The primal dual simplex optimizer is used.
- **MSK_OPTIMIZER_PRIMAL_SIMPLEX** The primal simplex optimizer is used.

Default value:

MSK_OPTIMIZER_FREE

B.2.91 MSK_IPAR_MIO_NODE_SELECTION

Corresponding constant:

MSK_IPAR_MIO_NODE_SELECTION

Description:

Controls the node selection strategy employed by the mixed-integer optimizer.

Possible values:

- **MSK_MIO_NODE_SELECTION_BEST** The optimizer employs a best bound node selection strategy.
- **MSK_MIO_NODE_SELECTION_FIRST** The optimizer employs a depth first node selection strategy.
- **MSK_MIO_NODE_SELECTION_FREE** The optimizer decides the node selection strategy.

- **MSK_MIO_NODE_SELECTION_HYBRID** The optimizer employs a hybrid strategy.
- **MSK_MIO_NODE_SELECTION_PSEUDO** The optimizer employs selects the node based on a pseudo cost estimate.
- **MSK_MIO_NODE_SELECTION_WORST** The optimizer employs a worst bound node selection strategy.

Default value:

MSK_MIO_NODE_SELECTION_FREE

B.2.92 MSK_IPAR_MIO_OPTIMIZER_MODE

Corresponding constant:

MSK_IPAR_MIO_OPTIMIZER_MODE

Description:

An experimental feature.

Possible Values:

Any number between 0 and 1.

Default value:

0

B.2.93 MSK_IPAR_MIO_PRESOLVE_AGGREGATE

Corresponding constant:

MSK_IPAR_MIO_PRESOLVE_AGGREGATE

Description:

Controls whether the presolve used by the mixed-integer optimizer tries to aggregate the constraints.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.94 MSK_IPAR_MIO_PRESOLVE_PROBING

Corresponding constant:

MSK_IPAR_MIO_PRESOLVE_PROBING

Description:

Controls whether the mixed-integer presolve performs probing. Probing can be very time consuming.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.95 MSK_IPAR_MIO_PRESOLVE_USE

Corresponding constant:

MSK_IPAR_MIO_PRESOLVE_USE

Description:

Controls whether presolve is performed by the mixed-integer optimizer.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.96 MSK_IPAR_MIO_PROBING_LEVEL

Corresponding constant:

MSK_IPAR_MIO_PROBING_LEVEL

Description:

Controls the amount of probing employed by the mixed-integer optimizer in presolve.

- -1 The optimizer chooses the level of probing employed.
- 0 Probing is disabled.
- 1 A low amount of probing is employed.

- 2 A medium amount of probing is employed.
- 3 A high amount of probing is employed.

Possible Values:

An integer value in the range of -1 to 3.

Default value:

-1

B.2.97 MSK_IPAR_MIO_RINS_MAX_NODES**Corresponding constant:**

MSK_IPAR_MIO_RINS_MAX_NODES

Description:

Controls the maximum number of nodes allowed in each call to the RINS heuristic. The default value of -1 means that the value is determined automatically. A value of zero turns off the heuristic.

Possible Values:

Any number between -1 and +inf.

Default value:

-1

B.2.98 MSK_IPAR_MIO_ROOT_OPTIMIZER**Corresponding constant:**

MSK_IPAR_MIO_ROOT_OPTIMIZER

Description:

Controls which optimizer is employed at the root node in the mixed-integer optimizer.

Possible values:

- **MSK_OPTIMIZER_CONCURRENT** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_CONIC** The optimizer for problems having conic constraints.
- **MSK_OPTIMIZER_DUAL_SIMPLEX** The dual simplex optimizer is used.
- **MSK_OPTIMIZER_FREE** The optimizer is chosen automatically.
- **MSK_OPTIMIZER_FREE_SIMPLEX** One of the simplex optimizers is used.
- **MSK_OPTIMIZER_INTPNT** The interior-point optimizer is used.
- **MSK_OPTIMIZER_MIXED_INT** The mixed-integer optimizer.

- **MSK_OPTIMIZER_MIXED_INT_CONIC** The mixed-integer optimizer for conic and linear problems.
- **MSK_OPTIMIZER_NETWORK_PRIMAL_SIMPLEX** The network primal simplex optimizer is used. It is only applicable to pure network problems.
- **MSK_OPTIMIZER_NONCONVEX** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_PRIMAL_DUAL_SIMPLEX** The primal dual simplex optimizer is used.
- **MSK_OPTIMIZER_PRIMAL_SIMPLEX** The primal simplex optimizer is used.

Default value:

MSK_OPTIMIZER_FREE

B.2.99 MSK_IPAR_MIO_STRONG_BRANCH

Corresponding constant:

MSK_IPAR_MIO_STRONG_BRANCH

Description:

The value specifies the depth from the root in which strong branching is used. A negative value means that the optimizer chooses a default value automatically.

Possible Values:

Any number between -inf and +inf.

Default value:

-1

B.2.100 MSK_IPAR_MIO_USE_MULTITHREADED_OPTIMIZER

Corresponding constant:

MSK_IPAR_MIO_USE_MULTITHREADED_OPTIMIZER

Description:

Controls whether the new multithreaded optimizer should be used for Mixed integer problems.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.101 MSK_IPAR_MT_SPINCOUNT**Corresponding constant:**

MSK_IPAR_MT_SPINCOUNT

Description:

Set the number of iterations to spin before sleeping.

Possible Values:

Any integer greater or equal to 0.

Default value:

0

B.2.102 MSK_IPAR_NONCONVEX_MAX_ITERATIONS**Corresponding constant:**

MSK_IPAR_NONCONVEX_MAX_ITERATIONS

Description:

Maximum number of iterations that can be used by the nonconvex optimizer.

Possible Values:

Any number between 0 and +inf.

Default value:

100000

B.2.103 MSK_IPAR_NUM_THREADS**Corresponding constant:**

MSK_IPAR_NUM_THREADS

Description:

Controls the number of threads employed by the optimizer. If set to 0 the number of threads used will be equal to the number of cores detected on the machine.

Possible Values:

Any integer greater or equal to 0.

Default value:

0

B.2.104 MSK_IPAR_OPF_MAX_TERMS_PER_LINE

Corresponding constant:

MSK_IPAR_OPF_MAX_TERMS_PER_LINE

Description:

The maximum number of terms (linear and quadratic) per line when an OPF file is written.

Possible Values:

Any number between 0 and +inf.

Default value:

5

B.2.105 MSK_IPAR_OPF_WRITE_HEADER

Corresponding constant:

MSK_IPAR_OPF_WRITE_HEADER

Description:

Write a text header with date and MOSEK version in an OPF file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.106 MSK_IPAR_OPF_WRITE_HINTS

Corresponding constant:

MSK_IPAR_OPF_WRITE_HINTS

Description:

Write a hint section with problem dimensions in the beginning of an OPF file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.107 MSK_IPAR_OPF_WRITE_PARAMETERS**Corresponding constant:**

MSK_IPAR_OPF_WRITE_PARAMETERS

Description:

Write a parameter section in an OPF file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_OFF****B.2.108 MSK_IPAR_OPF_WRITE_PROBLEM****Corresponding constant:**

MSK_IPAR_OPF_WRITE_PROBLEM

Description:

Write objective, constraints, bounds etc. to an OPF file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_ON****B.2.109 MSK_IPAR_OPF_WRITE_SOL_BAS****Corresponding constant:**

MSK_IPAR_OPF_WRITE_SOL_BAS

Description:

If **MSK_IPAR_OPF_WRITE_SOLUTIONS** is **MSK_ON** and a basic solution is defined, include the basic solution in OPF files.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_ON**

B.2.110 MSK_IPAR_OPF_WRITE_SOL_ITG

Corresponding constant:

MSK_IPAR_OPF_WRITE_SOL_ITG

Description:

If **MSK_IPAR_OPF_WRITE_SOLUTIONS** is **MSK_ON** and an integer solution is defined, write the integer solution in OPF files.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.111 MSK_IPAR_OPF_WRITE_SOL_ITR

Corresponding constant:

MSK_IPAR_OPF_WRITE_SOL_ITR

Description:

If **MSK_IPAR_OPF_WRITE_SOLUTIONS** is **MSK_ON** and an interior solution is defined, write the interior solution in OPF files.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.112 MSK_IPAR_OPF_WRITE_SOLUTIONS

Corresponding constant:

MSK_IPAR_OPF_WRITE_SOLUTIONS

Description:

Enable inclusion of solutions in the OPF files.

Possible values:

- **MSK_OFF** Switch the option off.

- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.113 MSK_IPAR_OPTIMIZER

Corresponding constant:

MSK_IPAR_OPTIMIZER

Description:

The parameter controls which optimizer is used to optimize the task.

Possible values:

- **MSK_OPTIMIZER_CONCURRENT** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_CONIC** The optimizer for problems having conic constraints.
- **MSK_OPTIMIZER_DUAL_SIMPLEX** The dual simplex optimizer is used.
- **MSK_OPTIMIZER_FREE** The optimizer is chosen automatically.
- **MSK_OPTIMIZER_FREE_SIMPLEX** One of the simplex optimizers is used.
- **MSK_OPTIMIZER_INTPNT** The interior-point optimizer is used.
- **MSK_OPTIMIZER_MIXED_INT** The mixed-integer optimizer.
- **MSK_OPTIMIZER_MIXED_INT_CONIC** The mixed-integer optimizer for conic and linear problems.
- **MSK_OPTIMIZER_NETWORK_PRIMAL_SIMPLEX** The network primal simplex optimizer is used. It is only applicable to pure network problems.
- **MSK_OPTIMIZER_NONCONVEX** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_PRIMAL_DUAL_SIMPLEX** The primal dual simplex optimizer is used.
- **MSK_OPTIMIZER_PRIMAL_SIMPLEX** The primal simplex optimizer is used.

Default value:

MSK_OPTIMIZER_FREE

B.2.114 MSK_IPAR_PARAM_READ_CASE_NAME

Corresponding constant:

MSK_IPAR_PARAM_READ_CASE_NAME

Description:

If turned on, then names in the parameter file are case sensitive.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_ON****B.2.115 MSK_IPAR_PARAM_READ_IGN_ERROR****Corresponding constant:**

MSK_IPAR_PARAM_READ_IGN_ERROR

Description:

If turned on, then errors in parameter settings is ignored.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_OFF****B.2.116 MSK_IPAR_PREOLVE_ELIM_FILL****Corresponding constant:**

MSK_IPAR_PREOLVE_ELIM_FILL

Description:

Controls the maximum amount of fill-in that can be created during the elimination phase of the presolve. This parameter times (**numcon**+**numvar**) denotes the amount of fill-in.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.117 MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_NUM_TRIES**Corresponding constant:**

MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_NUM_TRIES

Description:

Control the maximum number of times the eliminator is tried.

Possible Values:

A negative value implies MOSEK decides maximum number of times.

Default value:

-1

B.2.118 MSK_IPAR_PRESOLVE_ELIMINATOR_USE**Corresponding constant:**

MSK_IPAR_PRESOLVE_ELIMINATOR_USE

Description:

Controls whether free or implied free variables are eliminated from the problem.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.119 MSK_IPAR_PRESOLVE_LEVEL**Corresponding constant:**

MSK_IPAR_PRESOLVE_LEVEL

Description:

Currently not used.

Possible Values:

Any number between -inf and +inf.

Default value:

-1

B.2.120 MSK_IPAR_PRESOLVE_LINDEP_ABS_WORK_TRH

Corresponding constant:

MSK_IPAR_PRESOLVE_LINDEP_ABS_WORK_TRH

Description:

The linear dependency check is potentially computationally expensive.

Possible Values:

Any number between 0 and +inf.

Default value:

100

B.2.121 MSK_IPAR_PRESOLVE_LINDEP_REL_WORK_TRH

Corresponding constant:

MSK_IPAR_PRESOLVE_LINDEP_REL_WORK_TRH

Description:

The linear dependency check is potentially computationally expensive.

Possible Values:

Any number between 0 and +inf.

Default value:

100

B.2.122 MSK_IPAR_PRESOLVE_LINDEP_USE

Corresponding constant:

MSK_IPAR_PRESOLVE_LINDEP_USE

Description:

Controls whether the linear constraints are checked for linear dependencies.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.123 MSK_IPAR_PRESOLVE_MAX_NUM_REDUCTIONS**Corresponding constant:**

MSK_IPAR_PRESOLVE_MAX_NUM_REDUCTIONS

Description:

Controls the maximum number reductions performed by the presolve. The value of the parameter is normally only changed in connection with debugging. A negative value implies that an infinite number of reductions are allowed.

Possible Values:

Any number between -inf and +inf.

Default value:

-1

B.2.124 MSK_IPAR_PRESOLVE_USE**Corresponding constant:**

MSK_IPAR_PRESOLVE_USE

Description:

Controls whether the presolve is applied to a problem before it is optimized.

Possible values:

- **MSK_PRESOLVE_MODE_FREE** It is decided automatically whether to presolve before the problem is optimized.
- **MSK_PRESOLVE_MODE_OFF** The problem is not presolved before it is optimized.
- **MSK_PRESOLVE_MODE_ON** The problem is presolved before it is optimized.

Default value:

MSK_PRESOLVE_MODE_FREE

B.2.125 MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER**Corresponding constant:**

MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER

Description:

Controls which optimizer that is used to find the optimal repair.

Possible values:

- **MSK_OPTIMIZER_CONCURRENT** The optimizer for nonconvex nonlinear problems.

- **MSK_OPTIMIZER_CONIC** The optimizer for problems having conic constraints.
- **MSK_OPTIMIZER_DUAL_SIMPLEX** The dual simplex optimizer is used.
- **MSK_OPTIMIZER_FREE** The optimizer is chosen automatically.
- **MSK_OPTIMIZER_FREE_SIMPLEX** One of the simplex optimizers is used.
- **MSK_OPTIMIZER_INTPNT** The interior-point optimizer is used.
- **MSK_OPTIMIZER_MIXED_INT** The mixed-integer optimizer.
- **MSK_OPTIMIZER_MIXED_INT_CONIC** The mixed-integer optimizer for conic and linear problems.
- **MSK_OPTIMIZER_NETWORK_PRIMAL_SIMPLEX** The network primal simplex optimizer is used. It is only applicable to pure network problems.
- **MSK_OPTIMIZER_NONCONVEX** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_PRIMAL_DUAL_SIMPLEX** The primal dual simplex optimizer is used.
- **MSK_OPTIMIZER_PRIMAL_SIMPLEX** The primal simplex optimizer is used.

Default value:

MSK_OPTIMIZER_FREE

B.2.126 MSK_IPAR_QO_SEPARABLE_REFORMULATION

Corresponding constant:

MSK_IPAR_QO_SEPARABLE_REFORMULATION

Description:

Determine if Quadratic programming problems should be reformulated to separable form.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.127 MSK_IPAR_READ_ANZ

Corresponding constant:

MSK_IPAR_READ_ANZ

Description:

Expected maximum number of A non-zeros to be read. The option is used only by fast MPS and LP file readers.

Possible Values:

Any number between 0 and +inf.

Default value:

100000

B.2.128 MSK_IPAR_READ_CON**Corresponding constant:**

MSK_IPAR_READ_CON

Description:

Expected maximum number of constraints to be read. The option is only used by fast MPS and LP file readers.

Possible Values:

Any number between 0 and +inf.

Default value:

10000

B.2.129 MSK_IPAR_READ_CONE**Corresponding constant:**

MSK_IPAR_READ_CONE

Description:

Expected maximum number of conic constraints to be read. The option is used only by fast MPS and LP file readers.

Possible Values:

Any number between 0 and +inf.

Default value:

2500

B.2.130 MSK_IPAR_READ_DATA_COMPRESSED**Corresponding constant:**

MSK_IPAR_READ_DATA_COMPRESSED

Description:

If this option is turned on, it is assumed that the data file is compressed.

Possible values:

- **MSK_COMPRESS_FREE** The type of compression used is chosen automatically.
- **MSK_COMPRESS_GZIP** The type of compression used is gzip compatible.
- **MSK_COMPRESS_NONE** No compression is used.

Default value:**MSK_COMPRESS_FREE****B.2.131 MSK_IPAR_READ_DATA_FORMAT****Corresponding constant:****MSK_IPAR_READ_DATA_FORMAT****Description:**

Format of the data file to be read.

Possible values:

- **MSK_DATA_FORMAT_CB** Conic benchmark format.
- **MSK_DATA_FORMAT_EXTENSION** The file extension is used to determine the data file format.
- **MSK_DATA_FORMAT_FREE_MPS** The data data a free MPS formatted file.
- **MSK_DATA_FORMAT_LP** The data file is LP formatted.
- **MSK_DATA_FORMAT_MPS** The data file is MPS formatted.
- **MSK_DATA_FORMAT_OP** The data file is an optimization problem formatted file.
- **MSK_DATA_FORMAT_TASK** Generic task dump file.
- **MSK_DATA_FORMAT_XML** The data file is an XML formatted file.

Default value:**MSK_DATA_FORMAT_EXTENSION****B.2.132 MSK_IPAR_READ_DEBUG****Corresponding constant:****MSK_IPAR_READ_DEBUG****Description:**

Turns on additional debugging information when reading files.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_OFF**

B.2.133 MSK_IPAR_READ_KEEP_FREE_CON**Corresponding constant:**

MSK_IPAR_READ_KEEP_FREE_CON

Description:

Controls whether the free constraints are included in the problem.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.134 MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOU**Corresponding constant:**

MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOU

Description:

If this option is turned on, MOSEK will drop variables that are defined for the first time in the bounds section.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.135 MSK_IPAR_READ_LP_QUOTED_NAMES**Corresponding constant:**

MSK_IPAR_READ_LP_QUOTED_NAMES

Description:

If a name is in quotes when reading an LP file, the quotes will be removed.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.136 MSK_IPAR_READ_MPS_FORMAT

Corresponding constant:

MSK_IPAR_READ_MPS_FORMAT

Description:

Controls how strictly the MPS file reader interprets the MPS format.

Possible values:

- **MSK_MPS_FORMAT_FREE** It is assumed that the input file satisfies the free MPS format. This implies that spaces are not allowed in names. Otherwise the format is free.
- **MSK_MPS_FORMAT_RELAXED** It is assumed that the input file satisfies a slightly relaxed version of the MPS format.
- **MSK_MPS_FORMAT_STRICT** It is assumed that the input file satisfies the MPS format strictly.

Default value:

MSK_MPS_FORMAT_RELAXED

B.2.137 MSK_IPAR_READ_MPS_KEEP_INT

Corresponding constant:

MSK_IPAR_READ_MPS_KEEP_INT

Description:

Controls whether MOSEK should keep the integer restrictions on the variables while reading the MPS file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.138 MSK_IPAR_READ_MPS_OBJ_SENSE

Corresponding constant:

MSK_IPAR_READ_MPS_OBJ_SENSE

Description:

If turned on, the MPS reader uses the objective sense section. Otherwise the MPS reader ignores it.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_ON****B.2.139 MSK_IPAR_READ_MPS_RELAX****Corresponding constant:**

MSK_IPAR_READ_MPS_RELAX

Description:

If this option is turned on, then mixed integer constraints are ignored when a problem is read.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_ON****B.2.140 MSK_IPAR_READ_MPS_WIDTH****Corresponding constant:**

MSK_IPAR_READ_MPS_WIDTH

Description:

Controls the maximal number of characters allowed in one line of the MPS file.

Possible Values:

Any positive number greater than 80.

Default value:

1024

B.2.141 MSK_IPAR_READ_QNZ**Corresponding constant:**

MSK_IPAR_READ_QNZ

Description:

Expected maximum number of Q non-zeros to be read. The option is used only by MPS and LP file readers.

Possible Values:

Any number between 0 and $+\infty$.

Default value:

20000

B.2.142 MSK_IPAR_READ_TASK_IGNORE_PARAM**Corresponding constant:**

MSK_IPAR_READ_TASK_IGNORE_PARAM

Description:

Controls whether MOSEK should ignore the parameter setting defined in the task file and use the default parameter setting instead.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.143 MSK_IPAR_READ_VAR**Corresponding constant:**

MSK_IPAR_READ_VAR

Description:

Expected maximum number of variable to be read. The option is used only by MPS and LP file readers.

Possible Values:

Any number between 0 and $+\infty$.

Default value:

10000

B.2.144 MSK_IPAR_SENSITIVITY_ALL**Corresponding constant:**

MSK_IPAR_SENSITIVITY_ALL

Description:

If set to **MSK_ON**, then **MSK_sensitivityreport** analyzes all bounds and variables instead of reading a specification from the file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.145 MSK_IPAR_SENSITIVITY_OPTIMIZER**Corresponding constant:**

MSK_IPAR_SENSITIVITY_OPTIMIZER

Description:

Controls which optimizer is used for optimal partition sensitivity analysis.

Possible values:

- **MSK_OPTIMIZER_CONCURRENT** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_CONIC** The optimizer for problems having conic constraints.
- **MSK_OPTIMIZER_DUAL_SIMPLEX** The dual simplex optimizer is used.
- **MSK_OPTIMIZER_FREE** The optimizer is chosen automatically.
- **MSK_OPTIMIZER_FREE_SIMPLEX** One of the simplex optimizers is used.
- **MSK_OPTIMIZER_INTPNT** The interior-point optimizer is used.
- **MSK_OPTIMIZER_MIXED_INT** The mixed-integer optimizer.
- **MSK_OPTIMIZER_MIXED_INT_CONIC** The mixed-integer optimizer for conic and linear problems.
- **MSK_OPTIMIZER_NETWORK_PRIMAL_SIMPLEX** The network primal simplex optimizer is used. It is only applicable to pure network problems.
- **MSK_OPTIMIZER_NONCONVEX** The optimizer for nonconvex nonlinear problems.
- **MSK_OPTIMIZER_PRIMAL_DUAL_SIMPLEX** The primal dual simplex optimizer is used.
- **MSK_OPTIMIZER_PRIMAL_SIMPLEX** The primal simplex optimizer is used.

Default value:

MSK_OPTIMIZER_FREE_SIMPLEX

B.2.146 MSK_IPAR_SENSITIVITY_TYPE**Corresponding constant:**

MSK_IPAR_SENSITIVITY_TYPE

Description:

Controls which type of sensitivity analysis is to be performed.

Possible values:

- **MSK_SENSITIVITY_TYPE_BASIS** Basis sensitivity analysis is performed.
- **MSK_SENSITIVITY_TYPE_OPTIMAL_PARTITION** Optimal partition sensitivity analysis is performed.

Default value:

MSK_SENSITIVITY_TYPE_BASIS

B.2.147 MSK_IPAR_SIM_BASIS_FACTOR_USE**Corresponding constant:**

MSK_IPAR_SIM_BASIS_FACTOR_USE

Description:

Controls whether a (LU) factorization of the basis is used in a hot-start. Forcing a refactorization sometimes improves the stability of the simplex optimizers, but in most cases there is a performance penalty.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.148 MSK_IPAR_SIM_DEGEN**Corresponding constant:**

MSK_IPAR_SIM_DEGEN

Description:

Controls how aggressively degeneration is handled.

Possible values:

- **MSK_SIM_DEGEN_AGGRESSIVE** The simplex optimizer should use an aggressive degeneration strategy.
- **MSK_SIM_DEGEN_FREE** The simplex optimizer chooses the degeneration strategy.
- **MSK_SIM_DEGEN_MINIMUM** The simplex optimizer should use a minimum degeneration strategy.
- **MSK_SIM_DEGEN_MODERATE** The simplex optimizer should use a moderate degeneration strategy.
- **MSK_SIM_DEGEN_NONE** The simplex optimizer should use no degeneration strategy.

Default value:

MSK_SIM_DEGEN_FREE

B.2.149 MSK_IPAR_SIM_DUAL_CRASH

Corresponding constant:

MSK_IPAR_SIM_DUAL_CRASH

Description:

Controls whether crashing is performed in the dual simplex optimizer.

In general if a basis consists of more than (100-this parameter value)% fixed variables, then a crash will be performed.

Possible Values:

Any number between 0 and +inf.

Default value:

90

B.2.150 MSK_IPAR_SIM_DUAL_PHASEONE_METHOD

Corresponding constant:

MSK_IPAR_SIM_DUAL_PHASEONE_METHOD

Description:

An experimental feature.

Possible Values:

Any number between 0 and 10.

Default value:

0

B.2.151 MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION**Corresponding constant:**

MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION

Description:

The dual simplex optimizer can use a so-called restricted selection/pricing strategy to choose the outgoing variable. Hence, if restricted selection is applied, then the dual simplex optimizer first chooses a subset of all the potential outgoing variables. Next, for some time it will choose the outgoing variable only among the subset. From time to time the subset is redefined.

A larger value of this parameter implies that the optimizer will be more aggressive in its restriction strategy, i.e. a value of 0 implies that the restriction strategy is not applied at all.

Possible Values:

Any number between 0 and 100.

Default value:

50

B.2.152 MSK_IPAR_SIM_DUAL_SELECTION**Corresponding constant:**

MSK_IPAR_SIM_DUAL_SELECTION

Description:

Controls the choice of the incoming variable, known as the selection strategy, in the dual simplex optimizer.

Possible values:

- **MSK_SIM_SELECTION_ASE** The optimizer uses approximate steepest-edge pricing.
- **MSK_SIM_SELECTION_DEVEX** The optimizer uses devex steepest-edge pricing (or if it is not available an approximate steep-edge selection).
- **MSK_SIM_SELECTION_FREE** The optimizer chooses the pricing strategy.
- **MSK_SIM_SELECTION_FULL** The optimizer uses full pricing.
- **MSK_SIM_SELECTION_PARTIAL** The optimizer uses a partial selection approach. The approach is usually beneficial if the number of variables is much larger than the number of constraints.
- **MSK_SIM_SELECTION_SE** The optimizer uses steepest-edge selection (or if it is not available an approximate steep-edge selection).

Default value:**MSK_SIM_SELECTION_FREE**

B.2.153 MSK_IPAR_SIM_EXPLOIT_DUPVEC

Corresponding constant:

MSK_IPAR_SIM_EXPLOIT_DUPVEC

Description:

Controls if the simplex optimizers are allowed to exploit duplicated columns.

Possible values:

- **MSK_SIM_EXPLOIT_DUPVEC_FREE** The simplex optimizer can choose freely.
- **MSK_SIM_EXPLOIT_DUPVEC_OFF** Disallow the simplex optimizer to exploit duplicated columns.
- **MSK_SIM_EXPLOIT_DUPVEC_ON** Allow the simplex optimizer to exploit duplicated columns.

Default value:

MSK_SIM_EXPLOIT_DUPVEC_OFF

B.2.154 MSK_IPAR_SIM_HOTSTART

Corresponding constant:

MSK_IPAR_SIM_HOTSTART

Description:

Controls the type of hot-start that the simplex optimizer perform.

Possible values:

- **MSK_SIM_HOTSTART_FREE** The simplex optimize chooses the hot-start type.
- **MSK_SIM_HOTSTART_NONE** The simplex optimizer performs a coldstart.
- **MSK_SIM_HOTSTART_STATUS_KEYS** Only the status keys of the constraints and variables are used to choose the type of hot-start.

Default value:

MSK_SIM_HOTSTART_FREE

B.2.155 MSK_IPAR_SIM_HOTSTART_LU

Corresponding constant:

MSK_IPAR_SIM_HOTSTART_LU

Description:

Determines if the simplex optimizer should exploit the initial factorization.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.156 MSK_IPAR_SIM_INTEGER

Corresponding constant:

MSK_IPAR_SIM_INTEGER

Description:

An experimental feature.

Possible Values:

Any number between 0 and 10.

Default value:

0

B.2.157 MSK_IPAR_SIM_MAX_ITERATIONS

Corresponding constant:

MSK_IPAR_SIM_MAX_ITERATIONS

Description:

Maximum number of iterations that can be used by a simplex optimizer.

Possible Values:

Any number between 0 and +inf.

Default value:

10000000

B.2.158 MSK_IPAR_SIM_MAX_NUM_SETBACKS

Corresponding constant:

MSK_IPAR_SIM_MAX_NUM_SETBACKS

Description:

Controls how many set-backs are allowed within a simplex optimizer. A set-back is an event where the optimizer moves in the wrong direction. This is impossible in theory but may happen due to numerical problems.

Possible Values:

Any number between 0 and +inf.

Default value:

250

B.2.159 MSK_IPAR_SIM_NON_SINGULAR**Corresponding constant:**

MSK_IPAR_SIM_NON_SINGULAR

Description:

Controls if the simplex optimizer ensures a non-singular basis, if possible.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.160 MSK_IPAR_SIM_PRIMAL_CRASH**Corresponding constant:**

MSK_IPAR_SIM_PRIMAL_CRASH

Description:

Controls whether crashing is performed in the primal simplex optimizer.

In general, if a basis consists of more than (100-this parameter value)% fixed variables, then a crash will be performed.

Possible Values:

Any nonnegative integer value.

Default value:

90

B.2.161 MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD**Corresponding constant:**

MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD

Description:

An experimental feature.

Possible Values:

Any number between 0 and 10.

Default value:

0

B.2.162 MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION**Corresponding constant:**

MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION

Description:

The primal simplex optimizer can use a so-called restricted selection/pricing strategy to choose the outgoing variable. Hence, if restricted selection is applied, then the primal simplex optimizer first chooses a subset of all the potential incoming variables. Next, for some time it will choose the incoming variable only among the subset. From time to time the subset is redefined.

A larger value of this parameter implies that the optimizer will be more aggressive in its restriction strategy, i.e. a value of 0 implies that the restriction strategy is not applied at all.

Possible Values:

Any number between 0 and 100.

Default value:

50

B.2.163 MSK_IPAR_SIM_PRIMAL_SELECTION**Corresponding constant:**

MSK_IPAR_SIM_PRIMAL_SELECTION

Description:

Controls the choice of the incoming variable, known as the selection strategy, in the primal simplex optimizer.

Possible values:

- **MSK_SIM_SELECTION_ASE** The optimizer uses approximate steepest-edge pricing.

- **MSK_SIM_SELECTION_DEVEX** The optimizer uses devex steepest-edge pricing (or if it is not available an approximate steep-edge selection).
- **MSK_SIM_SELECTION_FREE** The optimizer chooses the pricing strategy.
- **MSK_SIM_SELECTION_FULL** The optimizer uses full pricing.
- **MSK_SIM_SELECTION_PARTIAL** The optimizer uses a partial selection approach. The approach is usually beneficial if the number of variables is much larger than the number of constraints.
- **MSK_SIM_SELECTION_SE** The optimizer uses steepest-edge selection (or if it is not available an approximate steep-edge selection).

Default value:

MSK_SIM_SELECTION_FREE

B.2.164 MSK_IPAR_SIM_REFACTOR_FREQ

Corresponding constant:

MSK_IPAR_SIM_REFACTOR_FREQ

Description:

Controls how frequent the basis is refactorized. The value 0 means that the optimizer determines the best point of refactorization.

It is strongly recommended NOT to change this parameter.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.165 MSK_IPAR_SIM_REFORMULATION

Corresponding constant:

MSK_IPAR_SIM_REFORMULATION

Description:

Controls if the simplex optimizers are allowed to reformulate the problem.

Possible values:

- **MSK_SIM_REFORMULATION_AGGRESSIVE** The simplex optimizer should use an aggressive reformulation strategy.
- **MSK_SIM_REFORMULATION_FREE** The simplex optimizer can choose freely.
- **MSK_SIM_REFORMULATION_OFF** Disallow the simplex optimizer to reformulate the problem.

- **MSK_SIM_REFORMULATION_ON** Allow the simplex optimizer to reformulate the problem.

Default value:

MSK_SIM_REFORMULATION_OFF

B.2.166 MSK_IPAR_SIM_SAVE_LU

Corresponding constant:

MSK_IPAR_SIM_SAVE_LU

Description:

Controls if the LU factorization stored should be replaced with the LU factorization corresponding to the initial basis.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.167 MSK_IPAR_SIM_SCALING

Corresponding constant:

MSK_IPAR_SIM_SCALING

Description:

Controls how much effort is used in scaling the problem before a simplex optimizer is used.

Possible values:

- **MSK_SCALING_AGGRESSIVE** A very aggressive scaling is performed.
- **MSK_SCALING_FREE** The optimizer chooses the scaling heuristic.
- **MSK_SCALING_MODERATE** A conservative scaling is performed.
- **MSK_SCALING_NONE** No scaling is performed.

Default value:

MSK_SCALING_FREE

B.2.168 MSK_IPAR_SIM_SCALING_METHOD**Corresponding constant:**

MSK_IPAR_SIM_SCALING_METHOD

Description:

Controls how the problem is scaled before a simplex optimizer is used.

Possible values:

- **MSK_SCALING_METHOD_FREE** The optimizer chooses the scaling heuristic.
- **MSK_SCALING_METHOD_POW2** Scales only with power of 2 leaving the mantissa untouched.

Default value:

MSK_SCALING_METHOD_POW2

B.2.169 MSK_IPAR_SIM_SOLVE_FORM**Corresponding constant:**

MSK_IPAR_SIM_SOLVE_FORM

Description:

Controls whether the primal or the dual problem is solved by the primal-/dual- simplex optimizer.

Possible values:

- **MSK_SOLVE_DUAL** The optimizer should solve the dual problem.
- **MSK_SOLVE_FREE** The optimizer is free to solve either the primal or the dual problem.
- **MSK_SOLVE_PRIMAL** The optimizer should solve the primal problem.

Default value:

MSK_SOLVE_FREE

B.2.170 MSK_IPAR_SIM_STABILITY_PRIORITY**Corresponding constant:**

MSK_IPAR_SIM_STABILITY_PRIORITY

Description:

Controls how high priority the numerical stability should be given.

Possible Values:

Any number between 0 and 100.

Default value:

50

B.2.171 MSK_IPAR_SIM_SWITCH_OPTIMIZER**Corresponding constant:**

MSK_IPAR_SIM_SWITCH_OPTIMIZER

Description:

The simplex optimizer sometimes chooses to solve the dual problem instead of the primal problem. This implies that if you have chosen to use the dual simplex optimizer and the problem is dualized, then it actually makes sense to use the primal simplex optimizer instead. If this parameter is on and the problem is dualized and furthermore the simplex optimizer is chosen to be the primal (dual) one, then it is switched to the dual (primal).

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.172 MSK_IPAR_SOL_FILTER_KEEP_BASIC**Corresponding constant:**

MSK_IPAR_SOL_FILTER_KEEP_BASIC

Description:

If turned on, then basic and super basic constraints and variables are written to the solution file independent of the filter setting.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.173 MSK_IPAR_SOL_FILTER_KEEP_RANGED**Corresponding constant:**

MSK_IPAR_SOL_FILTER_KEEP_RANGED

Description:

If turned on, then ranged constraints and variables are written to the solution file independent of the filter setting.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_OFF****B.2.174 MSK_IPAR_SOL_READ_NAME_WIDTH****Corresponding constant:**

MSK_IPAR_SOL_READ_NAME_WIDTH

Description:

When a solution is read by MOSEK and some constraint, variable or cone names contain blanks, then a maximum name width must be specified. A negative value implies that no name contain blanks.

Possible Values:

Any number between -inf and +inf.

Default value:

-1

B.2.175 MSK_IPAR_SOL_READ_WIDTH**Corresponding constant:**

MSK_IPAR_SOL_READ_WIDTH

Description:

Controls the maximal acceptable width of line in the solutions when read by MOSEK.

Possible Values:

Any positive number greater than 80.

Default value:

1024

B.2.176 MSK_IPAR_SOLUTION_CALLBACK**Corresponding constant:**

MSK_IPAR_SOLUTION_CALLBACK

Description:

Indicates whether solution call-backs will be performed during the optimization.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.177 MSK_IPAR_TIMING_LEVEL**Corresponding constant:**

MSK_IPAR_TIMING_LEVEL

Description:

Controls the a amount of timing performed inside MOSEK.

Possible Values:

Any integer greater or equal to 0.

Default value:

1

B.2.178 MSK_IPAR_WARNING_LEVEL**Corresponding constant:**

MSK_IPAR_WARNING_LEVEL

Description:

Deprecated and not in use

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.179 MSK_IPAR_WRITE_BAS_CONSTRAINTS**Corresponding constant:**

MSK_IPAR_WRITE_BAS_CONSTRAINTS

Description:

Controls whether the constraint section is written to the basic solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_ON****B.2.180 MSK_IPAR_WRITE_BAS_HEAD****Corresponding constant:**

MSK_IPAR_WRITE_BAS_HEAD

Description:

Controls whether the header section is written to the basic solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_ON****B.2.181 MSK_IPAR_WRITE_BAS_VARIABLES****Corresponding constant:**

MSK_IPAR_WRITE_BAS_VARIABLES

Description:

Controls whether the variables section is written to the basic solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:**MSK_ON**

B.2.182 MSK_IPAR_WRITE_DATA_COMPRESSED

Corresponding constant:

MSK_IPAR_WRITE_DATA_COMPRESSED

Description:

Controls whether the data file is compressed while it is written. 0 means no compression while higher values mean more compression.

Possible Values:

Any number between 0 and +inf.

Default value:

0

B.2.183 MSK_IPAR_WRITE_DATA_FORMAT

Corresponding constant:

MSK_IPAR_WRITE_DATA_FORMAT

Description:

Controls the data format when a task is written using **MSK.writedata**.

Possible values:

- **MSK_DATA_FORMAT_CB** Conic benchmark format.
- **MSK_DATA_FORMAT_EXTENSION** The file extension is used to determine the data file format.
- **MSK_DATA_FORMAT_FREE_MPS** The data data a free MPS formatted file.
- **MSK_DATA_FORMAT_LP** The data file is LP formatted.
- **MSK_DATA_FORMAT_MPS** The data file is MPS formatted.
- **MSK_DATA_FORMAT_OP** The data file is an optimization problem formatted file.
- **MSK_DATA_FORMAT_TASK** Generic task dump file.
- **MSK_DATA_FORMAT_XML** The data file is an XML formatted file.

Default value:

MSK_DATA_FORMAT_EXTENSION

B.2.184 MSK_IPAR_WRITE_DATA_PARAM**Corresponding constant:**

MSK_IPAR_WRITE_DATA_PARAM

Description:

If this option is turned on the parameter settings are written to the data file as parameters.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.185 MSK_IPAR_WRITE_FREE_CON**Corresponding constant:**

MSK_IPAR_WRITE_FREE_CON

Description:

Controls whether the free constraints are written to the data file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.186 MSK_IPAR_WRITE_GENERIC_NAMES**Corresponding constant:**

MSK_IPAR_WRITE_GENERIC_NAMES

Description:

Controls whether the generic names or user-defined names are used in the data file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.187 MSK_IPAR_WRITE_GENERIC_NAMES_IO**Corresponding constant:**

MSK_IPAR_WRITE_GENERIC_NAMES_IO

Description:

Index origin used in generic names.

Possible Values:

Any number between 0 and +inf.

Default value:

1

B.2.188 MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_CONIC_ITEMS**Corresponding constant:**

MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_CONIC_ITEMS

Description:

If the output format is not compatible with conic quadratic problems this parameter controls if the writer ignores the conic parts or produces an error.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.189 MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS**Corresponding constant:**

MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS

Description:

Controls if the writer ignores incompatible problem items when writing files.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.190 MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_NL_ITEMS**Corresponding constant:**

MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_NL_ITEMS

Description:

Controls if the writer ignores general non-linear terms or produces an error.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.191 MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_PSD_ITEMS**Corresponding constant:**

MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_PSD_ITEMS

Description:

If the output format is not compatible with semidefinite problems this parameter controls if the writer ignores the conic parts or produces an error.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.192 MSK_IPAR_WRITE_INT_CONSTRAINTS**Corresponding constant:**

MSK_IPAR_WRITE_INT_CONSTRAINTS

Description:

Controls whether the constraint section is written to the integer solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.193 MSK_IPAR_WRITE_INT_HEAD**Corresponding constant:**

MSK_IPAR_WRITE_INT_HEAD

Description:

Controls whether the header section is written to the integer solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.194 MSK_IPAR_WRITE_INT_VARIABLES**Corresponding constant:**

MSK_IPAR_WRITE_INT_VARIABLES

Description:

Controls whether the variables section is written to the integer solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.195 MSK_IPAR_WRITE_LP_LINE_WIDTH**Corresponding constant:**

MSK_IPAR_WRITE_LP_LINE_WIDTH

Description:

Maximum width of line in an LP file written by MOSEK.

Possible Values:

Any positive number.

Default value:

80

B.2.196 MSK_IPAR_WRITE_LP_QUOTED_NAMES**Corresponding constant:**

MSK_IPAR_WRITE_LP_QUOTED_NAMES

Description:

If this option is turned on, then MOSEK will quote invalid LP names when writing an LP file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.197 MSK_IPAR_WRITE_LP_STRICT_FORMAT**Corresponding constant:**

MSK_IPAR_WRITE_LP_STRICT_FORMAT

Description:

Controls whether LP output files satisfy the LP format strictly.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.198 MSK_IPAR_WRITE_LP_TERMS_PER_LINE**Corresponding constant:**

MSK_IPAR_WRITE_LP_TERMS_PER_LINE

Description:

Maximum number of terms on a single line in an LP file written by MOSEK. 0 means unlimited.

Possible Values:

Any number between 0 and +inf.

Default value:

10

B.2.199 MSK_IPAR_WRITE_MPS_INT

Corresponding constant:

MSK_IPAR_WRITE_MPS_INT

Description:

Controls if marker records are written to the MPS file to indicate whether variables are integer restricted.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.200 MSK_IPAR_WRITE_PRECISION

Corresponding constant:

MSK_IPAR_WRITE_PRECISION

Description:

Controls the precision with which **double** numbers are printed in the MPS data file. In general it is not worthwhile to use a value higher than 15.

Possible Values:

Any number between 0 and +inf.

Default value:

8

B.2.201 MSK_IPAR_WRITE_SOL_BARVARIABLES

Corresponding constant:

MSK_IPAR_WRITE_SOL_BARVARIABLES

Description:

Controls whether the symmetric matrix variables section is written to the solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.202 MSK_IPAR_WRITE_SOL_CONSTRAINTS**Corresponding constant:**

MSK_IPAR_WRITE_SOL_CONSTRAINTS

Description:

Controls whether the constraint section is written to the solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.203 MSK_IPAR_WRITE_SOL_HEAD**Corresponding constant:**

MSK_IPAR_WRITE_SOL_HEAD

Description:

Controls whether the header section is written to the solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.204 MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES**Corresponding constant:**

MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES

Description:

Even if the names are invalid MPS names, then they are employed when writing the solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_OFF

B.2.205 MSK_IPAR_WRITE_SOL_VARIABLES

Corresponding constant:

MSK_IPAR_WRITE_SOL_VARIABLES

Description:

Controls whether the variables section is written to the solution file.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.206 MSK_IPAR_WRITE_TASK_INC_SOL

Corresponding constant:

MSK_IPAR_WRITE_TASK_INC_SOL

Description:

Controls whether the solutions are stored in the task file too.

Possible values:

- **MSK_OFF** Switch the option off.
- **MSK_ON** Switch the option on.

Default value:

MSK_ON

B.2.207 MSK_IPAR_WRITE_XML_MODE

Corresponding constant:

MSK_IPAR_WRITE_XML_MODE

Description:

Controls if linear coefficients should be written by row or column when writing in the XML file format.

Possible values:

- **MSK_WRITE_XML_MODE_COL** Write in column order.
- **MSK_WRITE_XML_MODE_ROW** Write in row order.

Default value:

MSK_WRITE_XML_MODE_ROW

B.3 MSKsparame: String parameter types

B.3.1 MSK_SPAR_BAS_SOL_FILE_NAME

Corresponding constant:

MSK_SPAR_BAS_SOL_FILE_NAME

Description:

Name of the `bas` solution file.

Possible Values:

Any valid file name.

Default value:

""

B.3.2 MSK_SPAR_DATA_FILE_NAME

Corresponding constant:

MSK_SPAR_DATA_FILE_NAME

Description:

Data are read and written to this file.

Possible Values:

Any valid file name.

Default value:

""

B.3.3 MSK_SPAR_DEBUG_FILE_NAME

Corresponding constant:

MSK_SPAR_DEBUG_FILE_NAME

Description:

MOSEK debug file.

Possible Values:

Any valid file name.

Default value:

""

B.3.4 MSK_SPAR_FEASREPAIR_NAME_PREFIX

Corresponding constant:

MSK_SPAR_FEASREPAIR_NAME_PREFIX

Description:

If the function `MSK_relaxprimal` adds new constraints to the problem, then they are prefixed by the value of this parameter.

Possible Values:

Any valid string.

Default value:

"MSK-"

B.3.5 MSK_SPAR_FEASREPAIR_NAME_SEPARATOR

Corresponding constant:

MSK_SPAR_FEASREPAIR_NAME_SEPARATOR

Description:

Separator string for names of constraints and variables generated by `MSK_relaxprimal`.

Possible Values:

Any valid string.

Default value:

"_"

B.3.6 MSK_SPAR_FEASREPAIR_NAME_WSUMVIOL

Corresponding constant:

MSK_SPAR_FEASREPAIR_NAME_WSUMVIOL

Description:

The constraint and variable associated with the total weighted sum of violations are each given the name of this parameter postfixed with `CON` and `VAR` respectively.

Possible Values:

Any valid string.

Default value:

"WSUMVIOL"

B.3.7 MSK_SPAR_INT_SOL_FILE_NAME

Corresponding constant:

MSK_SPAR_INT_SOL_FILE_NAME

Description:

Name of the `int` solution file.

Possible Values:

Any valid file name.

Default value:

""

B.3.8 MSK_SPAR_ITR_SOL_FILE_NAME

Corresponding constant:

MSK_SPAR_ITR_SOL_FILE_NAME

Description:

Name of the `itr` solution file.

Possible Values:

Any valid file name.

Default value:

""

B.3.9 MSK_SPAR_MIO_DEBUG_STRING

Corresponding constant:

MSK_SPAR_MIO_DEBUG_STRING

Description:

For internal use only.

Possible Values:

Any valid string.

Default value:

""

B.3.10 MSK_SPAR_PARAM_COMMENT_SIGN**Corresponding constant:**

MSK_SPAR_PARAM_COMMENT_SIGN

Description:

Only the first character in this string is used. It is considered as a start of comment sign in the MOSEK parameter file. Spaces are ignored in the string.

Possible Values:

Any valid string.

Default value:

"%"

B.3.11 MSK_SPAR_PARAM_READ_FILE_NAME**Corresponding constant:**

MSK_SPAR_PARAM_READ_FILE_NAME

Description:

Modifications to the parameter database is read from this file.

Possible Values:

Any valid file name.

Default value:

""

B.3.12 MSK_SPAR_PARAM_WRITE_FILE_NAME**Corresponding constant:**

MSK_SPAR_PARAM_WRITE_FILE_NAME

Description:

The parameter database is written to this file.

Possible Values:

Any valid file name.

Default value:

""

B.3.13 MSK_SPAR_READ_MPS_BOU_NAME**Corresponding constant:**

MSK_SPAR_READ_MPS_BOU_NAME

Description:

Name of the BOUNDS vector used. An empty name means that the first BOUNDS vector is used.

Possible Values:

Any valid MPS name.

Default value:

""

B.3.14 MSK_SPAR_READ_MPS_OBJ_NAME**Corresponding constant:**

MSK_SPAR_READ_MPS_OBJ_NAME

Description:

Name of the free constraint used as objective function. An empty name means that the first constraint is used as objective function.

Possible Values:

Any valid MPS name.

Default value:

""

B.3.15 MSK_SPAR_READ_MPS_RAN_NAME**Corresponding constant:**

MSK_SPAR_READ_MPS_RAN_NAME

Description:

Name of the RANGE vector used. An empty name means that the first RANGE vector is used.

Possible Values:

Any valid MPS name.

Default value:

""

B.3.16 MSK_SPAR_READ_MPS_RHS_NAME

Corresponding constant:

MSK_SPAR_READ_MPS_RHS_NAME

Description:

Name of the RHS used. An empty name means that the first RHS vector is used.

Possible Values:

Any valid MPS name.

Default value:

""

B.3.17 MSK_SPAR_SENSITIVITY_FILE_NAME

Corresponding constant:

MSK_SPAR_SENSITIVITY_FILE_NAME

Description:

If defined **MSK_sensitivityreport** reads this file as a sensitivity analysis data file specifying the type of analysis to be done.

Possible Values:

Any valid string.

Default value:

""

B.3.18 MSK_SPAR_SENSITIVITY_RES_FILE_NAME

Corresponding constant:

MSK_SPAR_SENSITIVITY_RES_FILE_NAME

Description:

If this is a nonempty string, then **MSK_sensitivityreport** writes results to this file.

Possible Values:

Any valid string.

Default value:

""

B.3.19 MSK_SPAR_SOL_FILTER_XC_LOW**Corresponding constant:**

MSK_SPAR_SOL_FILTER_XC_LOW

Description:

A filter used to determine which constraints should be listed in the solution file. A value of "0.5" means that all constraints having $xc[i] > 0.5$ should be listed, whereas "+0.5" means that all constraints having $xc[i] \geq blc[i] + 0.5$ should be listed. An empty filter means that no filter is applied.

Possible Values:

Any valid filter.

Default value:

" "

B.3.20 MSK_SPAR_SOL_FILTER_XC_UPR**Corresponding constant:**

MSK_SPAR_SOL_FILTER_XC_UPR

Description:

A filter used to determine which constraints should be listed in the solution file. A value of "0.5" means that all constraints having $xc[i] < 0.5$ should be listed, whereas "-0.5" means all constraints having $xc[i] \leq buc[i] - 0.5$ should be listed. An empty filter means that no filter is applied.

Possible Values:

Any valid filter.

Default value:

" "

B.3.21 MSK_SPAR_SOL_FILTER_XX_LOW**Corresponding constant:**

MSK_SPAR_SOL_FILTER_XX_LOW

Description:

A filter used to determine which variables should be listed in the solution file. A value of "0.5" means that all constraints having $xx[j] \geq 0.5$ should be listed, whereas "+0.5" means that all constraints having $xx[j] \geq blx[j] + 0.5$ should be listed. An empty filter means no filter is applied.

Possible Values:

Any valid filter.

Default value:

""

B.3.22 MSK_SPAR_SOL_FILTER_XX_UPR**Corresponding constant:**

MSK_SPAR_SOL_FILTER_XX_UPR

Description:

A filter used to determine which variables should be listed in the solution file. A value of "0.5" means that all constraints having $xx[j] < 0.5$ should be printed, whereas "-0.5" means all constraints having $xx[j] \leq bux[j] - 0.5$ should be listed. An empty filter means no filter is applied.

Possible Values:

Any valid file name.

Default value:

""

B.3.23 MSK_SPAR_STAT_FILE_NAME**Corresponding constant:**

MSK_SPAR_STAT_FILE_NAME

Description:

Statistics file name.

Possible Values:

Any valid file name.

Default value:

""

B.3.24 MSK_SPAR_STAT_KEY**Corresponding constant:**

MSK_SPAR_STAT_KEY

Description:

Key used when writing the summary file.

Possible Values:

Any valid XML string.

Default value:

""

B.3.25 MSK_SPAR_STAT_NAME**Corresponding constant:**

MSK_SPAR_STAT_NAME

Description:

Name used when writing the statistics file.

Possible Values:

Any valid XML string.

Default value:

""

B.3.26 MSK_SPAR_WRITE_LP_GEN_VAR_NAME**Corresponding constant:**

MSK_SPAR_WRITE_LP_GEN_VAR_NAME

Description:

Sometimes when an LP file is written additional variables must be inserted. They will have the prefix denoted by this parameter.

Possible Values:

Any valid string.

Default value:

"xmskgen"

Appendix C

Response codes

Response codes ordered by name.

`MSK_RES_ERR_AD_INVALID_CODELIST` (3102)

The code list data was invalid.

`MSK_RES_ERR_AD_INVALID_OPERAND` (3104)

The code list data was invalid. An unknown operand was used.

`MSK_RES_ERR_AD_INVALID_OPERATOR` (3103)

The code list data was invalid. An unknown operator was used.

`MSK_RES_ERR_AD_MISSING_OPERAND` (3105)

The code list data was invalid. Missing operand for operator.

`MSK_RES_ERR_AD_MISSING_RETURN` (3106)

The code list data was invalid. Missing return operation in function.

`MSK_RES_ERR_API_ARRAY_TOO_SMALL` (3001)

An input array was too short.

`MSK_RES_ERR_API_CB_CONNECT` (3002)

Failed to connect a callback object.

`MSK_RES_ERR_API_FATAL_ERROR` (3005)

An internal error occurred in the API. Please report this problem.

`MSK_RES_ERR_API_INTERNAL` (3999)

An internal fatal error occurred in an interface function.

`MSK_RES_ERR_ARG_IS_TOO_LARGE` (1227)

The value of a argument is too small.

MSK_RES_ERR_ARG_IS_TOO_SMALL (1226)

The value of a argument is too small.

MSK_RES_ERR_ARGUMENT_DIMENSION (1201)

A function argument is of incorrect dimension.

MSK_RES_ERR_ARGUMENT_IS_TOO_LARGE (5005)

The value of a function argument is too large.

MSK_RES_ERR_ARGUMENT_LENNEQ (1197)

Incorrect length of arguments.

MSK_RES_ERR_ARGUMENT_PERM_ARRAY (1299)

An invalid permutation array is specified.

MSK_RES_ERR_ARGUMENT_TYPE (1198)

Incorrect argument type.

MSK_RES_ERR_BAR_VAR_DIM (3920)

The dimension of a symmetric matrix variable has to greater than 0.

MSK_RES_ERR_BASIS (1266)

An invalid basis is specified. Either too many or too few basis variables are specified.

MSK_RES_ERR_BASIS_FACTOR (1610)

The factorization of the basis is invalid.

MSK_RES_ERR_BASIS_SINGULAR (1615)

The basis is singular and hence cannot be factored.

MSK_RES_ERR_BLANK_NAME (1070)

An all blank name has been specified.

MSK_RES_ERR_CANNOT_CLONE_NL (2505)

A task with a nonlinear function call-back cannot be cloned.

MSK_RES_ERR_CANNOT_HANDLE_NL (2506)

A function cannot handle a task with nonlinear function call-backs.

MSK_RES_ERR_CBF_DUPLICATE_ACOORD (7116)

Duplicate index in ACOORD.

MSK_RES_ERR_CBF_DUPLICATE_BCOORD (7115)

Duplicate index in BCOORD.

MSK_RES_ERR_CBF_DUPLICATE_CON (7108)

Duplicate CON keyword.

MSK_RES_ERR_CBF_DUPLICATE_INT (7110)

Duplicate INT keyword.

MSK_RES_ERR_CBF_DUPLICATE_OBJ (7107)

Duplicate OBJ keyword.

MSK_RES_ERR_CBF_DUPLICATE_OBJCOORD (7114)

Duplicate index in OBJCOORD.

MSK_RES_ERR_CBF_DUPLICATE_VAR (7109)

Duplicate VAR keyword.

MSK_RES_ERR_CBF_INVALID_CON_TYPE (7112)

Invalid constraint type.

MSK_RES_ERR_CBF_INVALID_DOMAIN_DIMENSION (7113)

Invalid domain dimension.

MSK_RES_ERR_CBF_INVALID_INT_INDEX (7121)

Invalid INT index.

MSK_RES_ERR_CBF_INVALID_VAR_TYPE (7111)

Invalid variable type.

MSK_RES_ERR_CBF_NO_VARIABLES (7102)

No variables are specified.

MSK_RES_ERR_CBF_NO_VERSION_SPECIFIED (7105)

No version specified.

MSK_RES_ERR_CBF_OBJ_SENSE (7101)

An invalid objective sense is specified.

MSK_RES_ERR_CBF_PARSE (7100)

An error occurred while parsing an CBF file.

MSK_RES_ERR_CBF_SYNTAX (7106)

Invalid syntax.

MSK_RES_ERR_CBF_TOO_FEW_CONSTRAINTS (7118)

Too few constraints defined.

MSK_RES_ERR_CBF_TOO_FEW_INTS (7119)

Too few ints are specified.

MSK_RES_ERR_CBF_TOO_FEW_VARIABLES (7117)

Too few variables defined.

MSK_RES_ERR_CBF_TOO_MANY_CONSTRAINTS (7103)

Too many constraints specified.

MSK_RES_ERR_CBF_TOO_MANY_INTS (7120)

Too many ints are specified.

MSK_RES_ERR_CBF_TOO_MANY_VARIABLES (7104)

Too many variables specified.

MSK_RES_ERR_CBF_UNSUPPORTED (7122)

Unsupported feature is present.

MSK_RES_ERR_CON_Q_NOT_NSD (1294)

The quadratic constraint matrix is not negative semidefinite as expected for a constraint with finite lower bound. This results in a nonconvex problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.

MSK_RES_ERR_CON_Q_NOT_PSD (1293)

The quadratic constraint matrix is not positive semidefinite as expected for a constraint with finite upper bound. This results in a nonconvex problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.

MSK_RES_ERR_CONCURRENT_OPTIMIZER (3059)

An unsupported optimizer was chosen for use with the concurrent optimizer.

MSK_RES_ERR_CONE_INDEX (1300)

An index of a non-existing cone has been specified.

MSK_RES_ERR_CONE_OVERLAP (1302)

A new cone which variables overlap with an existing cone has been specified.

MSK_RES_ERR_CONE_OVERLAP_APPEND (1307)

The cone to be appended has one variable which is already member of another cone.

MSK_RES_ERR_CONE_REP_VAR (1303)

A variable is included multiple times in the cone.

MSK_RES_ERR_CONE_SIZE (1301)

A cone with too few members is specified.

MSK_RES_ERR_CONE_TYPE (1305)

Invalid cone type specified.

MSK_RES_ERR_CONE_TYPE_STR (1306)

Invalid cone type specified.

MSK_RES_ERR_DATA_FILE_EXT (1055)

The data file format cannot be determined from the file name.

MSK_RES_ERR_DUP_NAME (1071)

The same name was used multiple times for the same problem item type.

MSK_RES_ERR_DUPLICATE_BARVARIABLE_NAMES (4502)

Two barvariable names are identical.

MSK_RES_ERR_DUPLICATE_CONE_NAMES (4503)

Two cone names are identical.

MSK_RES_ERR_DUPLICATE_CONSTRAINT_NAMES (4500)

Two constraint names are identical.

MSK_RES_ERR_DUPLICATE_VARIABLE_NAMES (4501)

Two variable names are identical.

MSK_RES_ERR_END_OF_FILE (1059)

End of file reached.

MSK_RES_ERR_FACTOR (1650)

An error occurred while factorizing a matrix.

MSK_RES_ERR_FEASREPAIR_CANNOT_RELAX (1700)

An optimization problem cannot be relaxed. This is the case e.g. for general nonlinear optimization problems.

MSK_RES_ERR_FEASREPAIR_INCONSISTENT_BOUND (1702)

The upper bound is less than the lower bound for a variable or a constraint. Please correct this before running the feasibility repair.

MSK_RES_ERR_FEASREPAIR_SOLVING_RELAXED (1701)

The relaxed problem could not be solved to optimality. Please consult the log file for further details.

MSK_RES_ERR_FILE_LICENSE (1007)

Invalid license file.

MSK_RES_ERR_FILE_OPEN (1052)

Error while opening a file.

MSK_RES_ERR_FILE_READ (1053)

File read error.

MSK_RES_ERR_FILE_WRITE (1054)

File write error.

MSK_RES_ERR_FIRST (1261)

Invalid `first`.

MSK_RES_ERR_FIRSTI (1285)

Invalid `firsti`.

MSK_RES_ERR_FIRSTJ (1287)

Invalid `firstj`.

MSK_RES_ERR_FIXED_BOUND_VALUES (1425)

A fixed constraint/variable has been specified using the bound keys but the numerical value of the lower and upper bound is different.

MSK_RES_ERR_FLEXLM (1014)

The FLEXlm license manager reported an error.

MSK_RES_ERR_GLOBAL_INV_CONIC_PROBLEM (1503)

The global optimizer can only be applied to problems without semidefinite variables.

MSK_RES_ERR_HUGE_AIJ (1380)

A numerically huge value is specified for an $a_{i,j}$ element in A . The parameter `MSK_DPAR_DATA_TOL_AIJ_HUGE` controls when an $a_{i,j}$ is considered huge.

MSK_RES_ERR_HUGE_C (1375)

A huge value in absolute size is specified for one c_j .

MSK_RES_ERR_IDENTICAL_TASKS (3101)

Some tasks related to this function call were identical. Unique tasks were expected.

MSK_RES_ERR_IN_ARGUMENT (1200)

A function argument is incorrect.

MSK_RES_ERR_INDEX (1235)

An index is out of range.

MSK_RES_ERR_INDEX_ARR_IS_TOO_LARGE (1222)

An index in an array argument is too large.

MSK_RES_ERR_INDEX_ARR_IS_TOO_SMALL (1221)

An index in an array argument is too small.

MSK_RES_ERR_INDEX_IS_TOO_LARGE (1204)

An index in an argument is too large.

MSK_RES_ERR_INDEX_IS_TOO_SMALL (1203)

An index in an argument is too small.

MSK_RES_ERR_INF_DOU_INDEX (1219)

A double information index is out of range for the specified type.

MSK_RES_ERR_INF_DOU_NAME (1230)

A double information name is invalid.

MSK_RES_ERR_INF_INT_INDEX (1220)

An integer information index is out of range for the specified type.

MSK_RES_ERR_INF_INT_NAME (1231)

An integer information name is invalid.

MSK_RES_ERR_INF_LINT_INDEX (1225)

A long integer information index is out of range for the specified type.

MSK_RES_ERR_INF_LINT_NAME (1234)

A long integer information name is invalid.

MSK_RES_ERR_INF_TYPE (1232)

The information type is invalid.

MSK_RES_ERR_INFEAS_UNDEFINED (3910)

The requested value is not defined for this solution type.

MSK_RES_ERR_INFINITE_BOUND (1400)

A numerically huge bound value is specified.

MSK_RES_ERR_INT64_TO_INT32_CAST (3800)

An 32 bit integer could not cast to a 64 bit integer.

MSK_RES_ERR_INTERNAL (3000)

An internal error occurred. Please report this problem.

MSK_RES_ERR_INTERNAL_TEST_FAILED (3500)

An internal unit test function failed.

MSK_RES_ERR_INV_APTRE (1253)

`aptre[j]` is strictly smaller than `aptrb[j]` for some `j`.

MSK_RES_ERR_INV_BK (1255)

Invalid bound key.

MSK_RES_ERR_INV_BKC (1256)

Invalid bound key is specified for a constraint.

MSK_RES_ERR_INV_BKX (1257)

An invalid bound key is specified for a variable.

MSK_RES_ERR_INV_CONE_TYPE (1272)

Invalid cone type code is encountered.

MSK_RES_ERR_INV_CONE_TYPE_STR (1271)

Invalid cone type string encountered.

MSK_RES_ERR_INV_CONIC_PROBLEM (1502)

The conic optimizer can only be applied to problems with linear objective and constraints. Many problems such convex quadratically constrained problems can easily be reformulated to conic problems. See the appropriate MOSEK manual for details.

MSK_RES_ERR_INV_MARKI (2501)

Invalid value in marki.

MSK_RES_ERR_INV_MARKJ (2502)

Invalid value in markj.

MSK_RES_ERR_INV_NAME_ITEM (1280)

An invalid name item code is used.

MSK_RES_ERR_INV_NUMI (2503)

Invalid numi.

MSK_RES_ERR_INV_NUMJ (2504)

Invalid numj.

MSK_RES_ERR_INV_OPTIMIZER (1550)

An invalid optimizer has been chosen for the problem. This means that the simplex or the conic optimizer is chosen to optimize a nonlinear problem.

MSK_RES_ERR_INV_PROBLEM (1500)

Invalid problem type. Probably a nonconvex problem has been specified.

MSK_RES_ERR_INV_QCON_SUBI (1405)

Invalid value in qcsubi.

MSK_RES_ERR_INV_QCON_SUBJ (1406)

Invalid value in qcsubj.

MSK_RES_ERR_INV_QCON_SUBK (1404)

Invalid value in qcsubk.

MSK_RES_ERR_INV_QCON_VAL (1407)

Invalid value in qcval.

MSK_RES_ERR_INV_QOBJ_SUBI (1401)

Invalid value in qosubi.

MSK_RES_ERR_INV_QOBJ_SUBJ (1402)

Invalid value in `qosubj`.

MSK_RES_ERR_INV_QOBJ_VAL (1403)

Invalid value in `qoval`.

MSK_RES_ERR_INV_SK (1270)

Invalid status key code.

MSK_RES_ERR_INV_SK_STR (1269)

Invalid status key string encountered.

MSK_RES_ERR_INV_SKC (1267)

Invalid value in `skc`.

MSK_RES_ERR_INV_SKN (1274)

Invalid value in `skn`.

MSK_RES_ERR_INV_SKX (1268)

Invalid value in `skx`.

MSK_RES_ERR_INV_VAR_TYPE (1258)

An invalid variable type is specified for a variable.

MSK_RES_ERR_INVALID_ACCMODE (2520)

An invalid access mode is specified.

MSK_RES_ERR_INVALID_AIJ (1473)

$a_{i,j}$ contains an invalid floating point value, i.e. a NaN or an infinite value.

MSK_RES_ERR_INVALID_AMPL_STUB (3700)

Invalid AMPL stub.

MSK_RES_ERR_INVALID_BARVAR_NAME (1079)

An invalid symmetric matrix variable name is used.

MSK_RES_ERR_INVALID_BRANCH_DIRECTION (3200)

An invalid branching direction is specified.

MSK_RES_ERR_INVALID_BRANCH_PRIORITY (3201)

An invalid branching priority is specified. It should be nonnegative.

MSK_RES_ERR_INVALID_COMPRESSION (1800)

Invalid compression type.

MSK_RES_ERR_INVALID_CON_NAME (1076)

An invalid constraint name is used.

MSK_RES_ERR_INVALID_CONE_NAME (1078)

An invalid cone name is used.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_CONES (4005)

The file format does not support a problem with conic constraints.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_GENERAL_NL (4010)

The file format does not support a problem with general nonlinear terms.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_SYM_MAT (4000)

The file format does not support a problem with symmetric matrix variables.

MSK_RES_ERR_INVALID_FILE_NAME (1056)

An invalid file name has been specified.

MSK_RES_ERR_INVALID_FORMAT_TYPE (1283)

Invalid format type.

MSK_RES_ERR_INVALID_IDX (1246)

A specified index is invalid.

MSK_RES_ERR_INVALID_IOMODE (1801)

Invalid io mode.

MSK_RES_ERR_INVALID_MAX_NUM (1247)

A specified index is invalid.

MSK_RES_ERR_INVALID_NAME_IN_SOL_FILE (1170)

An invalid name occurred in a solution file.

MSK_RES_ERR_INVALID_NETWORK_PROBLEM (1504)

The problem is not a network problem as expected. The error occurs if a network optimizer is applied to a problem that cannot (easily) be converted to a network problem.

MSK_RES_ERR_INVALID_OBJ_NAME (1075)

An invalid objective name is specified.

MSK_RES_ERR_INVALID_OBJECTIVE_SENSE (1445)

An invalid objective sense is specified.

MSK_RES_ERR_INVALID_PROBLEM_TYPE (6000)

An invalid problem type.

MSK_RES_ERR_INVALID_SOL_FILE_NAME (1057)

An invalid file name has been specified.

MSK_RES_ERR_INVALID_STREAM (1062)

An invalid stream is referenced.

MSK_RES_ERR_INVALID_SURPLUS (1275)

Invalid surplus.

MSK_RES_ERR_INVALID_SYM_MAT_DIM (3950)

A sparse symmetric matrix of invalid dimension is specified.

MSK_RES_ERR_INVALID_TASK (1064)

The `task` is invalid.

MSK_RES_ERR_INVALID_UTF8 (2900)

An invalid UTF8 string is encountered.

MSK_RES_ERR_INVALID_VAR_NAME (1077)

An invalid variable name is used.

MSK_RES_ERR_INVALID_WCHAR (2901)

An invalid `wchar` string is encountered.

MSK_RES_ERR_INVALID_WHICH_SOL (1228)

`whichsol` is invalid.

MSK_RES_ERR_LAST (1262)

Invalid index `last`. A given index was out of expected range.

MSK_RES_ERR_LAST_I (1286)

Invalid `lasti`.

MSK_RES_ERR_LAST_J (1288)

Invalid `lastj`.

MSK_RES_ERR_LAU_ARG_K (7004)

Invalid argument `k`.

MSK_RES_ERR_LAU_ARG_M (7002)

Invalid argument `m`.

MSK_RES_ERR_LAU_ARG_N (7003)

Invalid argument `n`.

MSK_RES_ERR_LAU_ARG_TRANS (7008)

Invalid argument `trans`.

MSK_RES_ERR_LAU_ARG_TRANSA (7005)

Invalid argument `transa`.

MSK_RES_ERR_LAU_ARG_TRANSB (7006)

Invalid argument transb.

MSK_RES_ERR_LAU_ARG_UPLO (7007)

Invalid argument uplo.

MSK_RES_ERR_LAU_SINGULAR_MATRIX (7000)

A matrix is singular.

MSK_RES_ERR_LAU_UNKNOWN (7001)

An unknown error.

MSK_RES_ERR_LICENSE (1000)

Invalid license.

MSK_RES_ERR_LICENSE_CANNOT_ALLOCATE (1020)

The license system cannot allocate the memory required.

MSK_RES_ERR_LICENSE_CANNOT_CONNECT (1021)

MOSEK cannot connect to the license server. Most likely the license server is not up and running.

MSK_RES_ERR_LICENSE_EXPIRED (1001)

The license has expired.

MSK_RES_ERR_LICENSE_FEATURE (1018)

A requested feature is not available in the license file(s). Most likely due to an incorrect license system setup.

MSK_RES_ERR_LICENSE_INVALID_HOSTID (1025)

The host ID specified in the license file does not match the host ID of the computer.

MSK_RES_ERR_LICENSE_MAX (1016)

Maximum number of licenses is reached.

MSK_RES_ERR_LICENSE_MOSEKLM_DAEMON (1017)

The MOSEKLM license manager daemon is not up and running.

MSK_RES_ERR_LICENSE_NO_SERVER_LINE (1028)

There is no **SERVER** line in the license file. All non-zero license count features need at least one **SERVER** line.

MSK_RES_ERR_LICENSE_NO_SERVER_SUPPORT (1027)

The license server does not support the requested feature. Possible reasons for this error include:

- The feature has expired.
- The feature's start date is later than today's date.

- The version requested is higher than feature's the highest supported version.
- A corrupted license file.

Try restarting the license and inspect the license server debug file, usually called `lmgrd.log`.

`MSK_RES_ERR_LICENSE_SERVER` (1015)

The license server is not responding.

`MSK_RES_ERR_LICENSE_SERVER_VERSION` (1026)

The version specified in the checkout request is greater than the highest version number the daemon supports.

`MSK_RES_ERR_LICENSE_VERSION` (1002)

The license is valid for another version of MOSEK.

`MSK_RES_ERR_LINK_FILE_DLL` (1040)

A file cannot be linked to a stream in the DLL version.

`MSK_RES_ERR_LIVING_TASKS` (1066)

All tasks associated with an environment must be deleted before the environment is deleted. There are still some undeleted tasks.

`MSK_RES_ERR_LOWER_BOUND_IS_A_NAN` (1390)

The lower bound specified is not a number (nan).

`MSK_RES_ERR_LP_DUP_SLACK_NAME` (1152)

The name of the slack variable added to a ranged constraint already exists.

`MSK_RES_ERR_LP_EMPTY` (1151)

The problem cannot be written to an LP formatted file.

`MSK_RES_ERR_LP_FILE_FORMAT` (1157)

Syntax error in an LP file.

`MSK_RES_ERR_LP_FORMAT` (1160)

Syntax error in an LP file.

`MSK_RES_ERR_LP_FREE_CONSTRAINT` (1155)

Free constraints cannot be written in LP file format.

`MSK_RES_ERR_LP_INCOMPATIBLE` (1150)

The problem cannot be written to an LP formatted file.

`MSK_RES_ERR_LP_INVALID_CON_NAME` (1171)

A constraint name is invalid when used in an LP formatted file.

MSK_RES_ERR_LP_INVALID_VAR_NAME (1154)

A variable name is invalid when used in an LP formatted file.

MSK_RES_ERR_LP_WRITE_CONIC_PROBLEM (1163)

The problem contains cones that cannot be written to an LP formatted file.

MSK_RES_ERR_LP_WRITE_GECO_PROBLEM (1164)

The problem contains general convex terms that cannot be written to an LP formatted file.

MSK_RES_ERR_LU_MAX_NUM_TRIES (2800)

Could not compute the LU factors of the matrix within the maximum number of allowed tries.

MSK_RES_ERR_MAX_LEN_IS_TOO_SMALL (1289)

An maximum length that is too small has been specified.

MSK_RES_ERR_MAXNUMBARVAR (1242)

The maximum number of semidefinite variables specified is smaller than the number of semidefinite variables in the task.

MSK_RES_ERR_MAXNUMCON (1240)

The maximum number of constraints specified is smaller than the number of constraints in the task.

MSK_RES_ERR_MAXNUMCONE (1304)

The value specified for `maxnumcone` is too small.

MSK_RES_ERR_MAXNUMQNZ (1243)

The maximum number of non-zeros specified for the Q matrixes is smaller than the number of non-zeros in the current Q matrixes.

MSK_RES_ERR_MAXNUMVAR (1241)

The maximum number of variables specified is smaller than the number of variables in the task.

MSK_RES_ERR_MBT_INCOMPATIBLE (2550)

The MBT file is incompatible with this platform. This results from reading a file on a 32 bit platform generated on a 64 bit platform.

MSK_RES_ERR_MBT_INVALID (2551)

The MBT file is invalid.

MSK_RES_ERR_MIO_INTERNAL (5010)

A fatal error occurred in the mixed integer optimizer. Please contact MOSEK support.

MSK_RES_ERR_MIO_INVALID_NODE_OPTIMIZER (7131)

An invalid node optimizer was selected for the problem type.

MSK_RES_ERR_MIO_INVALID_ROOT_OPTIMIZER (7130)

An invalid root optimizer was selected for the problem type.

MSK_RES_ERR_MIO_NO_OPTIMIZER (1551)

No optimizer is available for the current class of integer optimization problems.

MSK_RES_ERR_MIO_NOT_LOADED (1553)

The mixed-integer optimizer is not loaded.

MSK_RES_ERR_MISSING_LICENSE_FILE (1008)

MOSEK cannot license file or a token server. See the MOSEK installation manual for details.

MSK_RES_ERR_MIXED_PROBLEM (1501)

The problem contains both conic and nonlinear constraints.

MSK_RES_ERR_MPS_CONE_OVERLAP (1118)

A variable is specified to be a member of several cones.

MSK_RES_ERR_MPS_CONE_REPEAT (1119)

A variable is repeated within the CSECTION.

MSK_RES_ERR_MPS_CONE_TYPE (1117)

Invalid cone type specified in a CSECTION.

MSK_RES_ERR_MPS_DUPLICATE_Q_ELEMENT (1121)

Duplicate elements is specified in a Q matrix.

MSK_RES_ERR_MPS_FILE (1100)

An error occurred while reading an MPS file.

MSK_RES_ERR_MPS_INV_BOUND_KEY (1108)

An invalid bound key occurred in an MPS file.

MSK_RES_ERR_MPS_INV_CON_KEY (1107)

An invalid constraint key occurred in an MPS file.

MSK_RES_ERR_MPS_INV_FIELD (1101)

A field in the MPS file is invalid. Probably it is too wide.

MSK_RES_ERR_MPS_INV_MARKER (1102)

An invalid marker has been specified in the MPS file.

MSK_RES_ERR_MPS_INV_SEC_NAME (1109)

An invalid section name occurred in an MPS file.

MSK_RES_ERR_MPS_INV_SEC_ORDER (1115)

The sections in the MPS data file are not in the correct order.

MSK_RES_ERR_MPS_INVALID_OBJ_NAME (1128)

An invalid objective name is specified.

MSK_RES_ERR_MPS_INVALID_OBJSENSE (1122)

An invalid objective sense is specified.

MSK_RES_ERR_MPS_MUL_CON_NAME (1112)

A constraint name was specified multiple times in the ROWS section.

MSK_RES_ERR_MPS_MUL_CSEC (1116)

Multiple CSECTIONs are given the same name.

MSK_RES_ERR_MPS_MUL_QOBJ (1114)

The Q term in the objective is specified multiple times in the MPS data file.

MSK_RES_ERR_MPS_MUL_QSEC (1113)

Multiple QSECTIONs are specified for a constraint in the MPS data file.

MSK_RES_ERR_MPS_NO_OBJECTIVE (1110)

No objective is defined in an MPS file.

MSK_RES_ERR_MPS_NON_SYMMETRIC_Q (1120)

A non symmetric matrice has been speciefied.

MSK_RES_ERR_MPS_NULL_CON_NAME (1103)

An empty constraint name is used in an MPS file.

MSK_RES_ERR_MPS_NULL_VAR_NAME (1104)

An empty variable name is used in an MPS file.

MSK_RES_ERR_MPS_SPLITTED_VAR (1111)

All elements in a column of the A matrix must be specified consecutively. Hence, it is illegal to specify non-zero elements in A for variable 1, then for variable 2 and then variable 1 again.

MSK_RES_ERR_MPS_TAB_IN_FIELD2 (1125)

A tab char occurred in field 2.

MSK_RES_ERR_MPS_TAB_IN_FIELD3 (1126)

A tab char occurred in field 3.

MSK_RES_ERR_MPS_TAB_IN_FIELD5 (1127)

A tab char occurred in field 5.

MSK_RES_ERR_MPS_UNDEF_CON_NAME (1105)

An undefined constraint name occurred in an MPS file.

MSK_RES_ERR_MPS_UNDEF_VAR_NAME (1106)

An undefined variable name occurred in an MPS file.

MSK_RES_ERR_MUL_A_ELEMENT (1254)

An element in A is defined multiple times.

MSK_RES_ERR_NAME_IS_NULL (1760)

The name buffer is a NULL pointer.

MSK_RES_ERR_NAME_MAX_LEN (1750)

A name is longer than the buffer that is supposed to hold it.

MSK_RES_ERR_NAN_IN_BLC (1461)

l^c contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_BLX (1471)

l^x contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_BUC (1462)

u^c contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_BUX (1472)

u^x contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_C (1470)

c contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_DOUBLE_DATA (1450)

An invalid floating point value was used in some double data.

MSK_RES_ERR_NEGATIVE_APPEND (1264)

Cannot append a negative number.

MSK_RES_ERR_NEGATIVE_SURPLUS (1263)

Negative surplus.

MSK_RES_ERR_NEWER_DLL (1036)

The dynamic link library is newer than the specified version.

MSK_RES_ERR_NO_BARS_FOR_SOLUTION (3916)

There is no \bar{s} available for the solution specified. In particular note there are no \bar{s} defined for the basic and integer solutions.

MSK_RES_ERR_NO_BARX_FOR_SOLUTION (3915)

There is no \bar{X} available for the solution specified. In particular note there are no \bar{X} defined for the basic and integer solutions.

MSK_RES_ERR_NO_BASIS_SOL (1600)

No basic solution is defined.

MSK_RES_ERR_NO_DUAL_FOR_ITG_SOL (2950)

No dual information is available for the integer solution.

MSK_RES_ERR_NO_DUAL_INFEAS_CER (2001)

A certificate of infeasibility is not available.

MSK_RES_ERR_NO_DUAL_INFO_FOR_ITG_SOL (3300)

Dual information is not available for the integer solution.

MSK_RES_ERR_NO_INIT_ENV (1063)

`env` is not initialized.

MSK_RES_ERR_NO_OPTIMIZER_VAR_TYPE (1552)

No optimizer is available for this class of optimization problems.

MSK_RES_ERR_NO_PRIMAL_INFEAS_CER (2000)

A certificate of primal infeasibility is not available.

MSK_RES_ERR_NO_SNX_FOR_BAS_SOL (2953)

s_n^x is not available for the basis solution.

MSK_RES_ERR_NO_SOLUTION_IN_CALLBACK (2500)

The required solution is not available.

MSK_RES_ERR_NON_UNIQUE_ARRAY (5000)

An array does not contain unique elements.

MSK_RES_ERR_NONCONVEX (1291)

The optimization problem is nonconvex.

MSK_RES_ERR_NONLINEAR_EQUALITY (1290)

The model contains a nonlinear equality which defines a nonconvex set.

MSK_RES_ERR_NONLINEAR_FUNCTIONS_NOT_ALLOWED (1428)

An operation that is invalid for problems with nonlinear functions defined has been attempted.

MSK_RES_ERR_NONLINEAR_RANGED (1292)

The model contains a nonlinear ranged constraint which by definition defines a nonconvex set.

MSK_RES_ERR_NR_ARGUMENTS (1199)

Incorrect number of function arguments.

MSK_RES_ERR_NULL_ENV (1060)

`env` is a NULL pointer.

MSK_RES_ERR_NULL_POINTER (1065)

An argument to a function is unexpectedly a NULL pointer.

MSK_RES_ERR_NULL_TASK (1061)

`task` is a NULL pointer.

MSK_RES_ERR_NUMCONLIM (1250)

Maximum number of constraints limit is exceeded.

MSK_RES_ERR_NUMVARLIM (1251)

Maximum number of variables limit is exceeded.

MSK_RES_ERR_OBJ_Q_NOT_NSD (1296)

The quadratic coefficient matrix in the objective is not negative semidefinite as expected for a maximization problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.

MSK_RES_ERR_OBJ_Q_NOT_PSD (1295)

The quadratic coefficient matrix in the objective is not positive semidefinite as expected for a minimization problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.

MSK_RES_ERR_OBJECTIVE_RANGE (1260)

Empty objective range.

MSK_RES_ERR_OLDER_DLL (1035)

The dynamic link library is older than the specified version.

MSK_RES_ERR_OPEN_DL (1030)

A dynamic link library could not be opened.

MSK_RES_ERR_OPF_FORMAT (1168)

Syntax error in an OPF file

MSK_RES_ERR_OPF_NEW_VARIABLE (1169)

Introducing new variables is now allowed. When a `[variables]` section is present, it is not allowed to introduce new variables later in the problem.

MSK_RES_ERR_OPF_PREMATURE_EOF (1172)

Premature end of file in an OPF file.

MSK_RES_ERR_OPTIMIZER_LICENSE (1013)

The optimizer required is not licensed.

MSK_RES_ERR_ORD_INVALID (1131)

Invalid content in branch ordering file.

MSK_RES_ERR_ORD_INVALID_BRANCH_DIR (1130)

An invalid branch direction key is specified.

MSK_RES_ERR_OVERFLOW (1590)

A computation produced an overflow i.e. a very large number.

MSK_RES_ERR_PARAM_INDEX (1210)

Parameter index is out of range.

MSK_RES_ERR_PARAM_IS_TOO_LARGE (1215)

The parameter value is too large.

MSK_RES_ERR_PARAM_IS_TOO_SMALL (1216)

The parameter value is too small.

MSK_RES_ERR_PARAM_NAME (1205)

The parameter name is not correct.

MSK_RES_ERR_PARAM_NAME_DOUB (1206)

The parameter name is not correct for a double parameter.

MSK_RES_ERR_PARAM_NAME_INT (1207)

The parameter name is not correct for an integer parameter.

MSK_RES_ERR_PARAM_NAME_STR (1208)

The parameter name is not correct for a string parameter.

MSK_RES_ERR_PARAM_TYPE (1218)

The parameter type is invalid.

MSK_RES_ERR_PARAM_VALUE_STR (1217)

The parameter value string is incorrect.

MSK_RES_ERR_PLATFORM_NOT_LICENSED (1019)

A requested license feature is not available for the required platform.

MSK_RES_ERR_POSTSOLVE (1580)

An error occurred during the postsolve. Please contact MOSEK support.

MSK_RES_ERR_PROBLEM_ITEM (1281)

An invalid problem is used.

MSK_RES_ERR_PROB_LICENSE (1006)

The software is not licensed to solve the problem.

MSK_RES_ERR_QCON_SUBI_TOO_LARGE (1409)

Invalid value in `qconsubi`.

MSK_RES_ERR_QCON_SUBI_TOO_SMALL (1408)

Invalid value in `qcsubi`.

MSK_RES_ERR_QCON_UPPER_TRIANGLE (1417)

An element in the upper triangle of a Q^k is specified. Only elements in the lower triangle should be specified.

MSK_RES_ERR_QOBJ_UPPER_TRIANGLE (1415)

An element in the upper triangle of Q^o is specified. Only elements in the lower triangle should be specified.

MSK_RES_ERR_READ_FORMAT (1090)

The specified format cannot be read.

MSK_RES_ERR_READ_LP_MISSING_END_TAG (1159)

Syntax error in LP file. Possibly missing End tag.

MSK_RES_ERR_READ_LP_NONEXISTING_NAME (1162)

A variable never occurred in objective or constraints.

MSK_RES_ERR_REMOVE_CONE_VARIABLE (1310)

A variable cannot be removed because it will make a cone invalid.

MSK_RES_ERR_REPAIR_INVALID_PROBLEM (1710)

The feasibility repair does not support the specified problem type.

MSK_RES_ERR_REPAIR_OPTIMIZATION_FAILED (1711)

Computation the optimal relaxation failed. The cause may have been numerical problems.

MSK_RES_ERR_SEN_BOUND_INVALID_LO (3054)

Analysis of lower bound requested for an index, where no lower bound exists.

MSK_RES_ERR_SEN_BOUND_INVALID_UP (3053)

Analysis of upper bound requested for an index, where no upper bound exists.

MSK_RES_ERR_SEN_FORMAT (3050)

Syntax error in sensitivity analysis file.

MSK_RES_ERR_SEN_INDEX_INVALID (3055)

Invalid range given in the sensitivity file.

MSK_RES_ERR_SEN_INDEX_RANGE (3052)

Index out of range in the sensitivity analysis file.

MSK_RES_ERR_SEN_INVALID_REGEX (3056)

Syntax error in regexp or regexp longer than 1024.

MSK_RES_ERR_SEN_NUMERICAL (3058)

Numerical difficulties encountered performing the sensitivity analysis.

MSK_RES_ERR_SEN_SOLUTION_STATUS (3057)

No optimal solution found to the original problem given for sensitivity analysis.

MSK_RES_ERR_SEN_UNDEF_NAME (3051)

An undefined name was encountered in the sensitivity analysis file.

MSK_RES_ERR_SEN_UNHANDLED_PROBLEM_TYPE (3080)

Sensitivity analysis cannot be performed for the specified problem. Sensitivity analysis is only possible for linear problems.

MSK_RES_ERR_SIZE_LICENSE (1005)

The problem is bigger than the license.

MSK_RES_ERR_SIZE_LICENSE_CON (1010)

The problem has too many constraints to be solved with the available license.

MSK_RES_ERR_SIZE_LICENSE_INTVAR (1012)

The problem contains too many integer variables to be solved with the available license.

MSK_RES_ERR_SIZE_LICENSE_NUMCORES (3900)

The computer contains more cpu cores than the license allows for.

MSK_RES_ERR_SIZE_LICENSE_VAR (1011)

The problem has too many variables to be solved with the available license.

MSK_RES_ERR_SOL_FILE_INVALID_NUMBER (1350)

An invalid number is specified in a solution file.

MSK_RES_ERR_SOLITEM (1237)

The solution item number `solitem` is invalid. Please note that `MSK_SOL_ITEM_SNX` is invalid for the basic solution.

MSK_RES_ERR_SOLVER_PROBTYPE (1259)

Problem type does not match the chosen optimizer.

MSK_RES_ERR_SPACE (1051)

Out of space.

MSK_RES_ERR_SPACE_LEAKING (1080)

MOSEK is leaking memory. This can be due to either an incorrect use of MOSEK or a bug.

MSK_RES_ERR_SPACE_NO_INFO (1081)

No available information about the space usage.

MSK_RES_ERR_SYM_MAT_DUPLICATE (3944)

A value in a symmetric matrix as been specified more than once.

MSK_RES_ERR_SYM_MAT_INVALID_COL_INDEX (3941)

A column index specified for sparse symmetric maxtrix is invalid.

MSK_RES_ERR_SYM_MAT_INVALID_ROW_INDEX (3940)

A row index specified for sparse symmetric maxtrix is invalid.

MSK_RES_ERR_SYM_MAT_INVALID_VALUE (3943)

The numerical value specified in a sparse symmetric matrix is not a value floating value.

MSK_RES_ERR_SYM_MAT_NOT_LOWER_TRINGULAR (3942)

Only the lower triangular part of sparse symmetric matrix should be specified.

MSK_RES_ERR_TASK_INCOMPATIBLE (2560)

The Task file is incompatible with this platform. This results from reading a file on a 32 bit platform generated on a 64 bit platform.

MSK_RES_ERR_TASK_INVALID (2561)

The Task file is invalid.

MSK_RES_ERR_THREAD_COND_INIT (1049)

Could not initialize a condition.

MSK_RES_ERR_THREAD_CREATE (1048)

Could not create a thread. This error may occur if a large number of environments are created and not deleted again. In any case it is a good practice to minimize the number of environments created.

MSK_RES_ERR_THREAD_MUTEX_INIT (1045)

Could not initialize a mutex.

MSK_RES_ERR_THREAD_MUTEX_LOCK (1046)

Could not lock a mutex.

MSK_RES_ERR_THREAD_MUTEX_UNLOCK (1047)

Could not unlock a mutex.

MSK_RES_ERR_TOO_MANY_CONCURRENT_TASKS (3090)

Too many concurrent tasks specified.

MSK_RES_ERR_TOO_SMALL_MAX_NUM_NZ (1245)

The maximum number of non-zeros specified is too small.

MSK_RES_ERR_TOO_SMALL_MAXNUMANZ (1252)

The maximum number of non-zeros specified for A is smaller than the number of non-zeros in the current A .

MSK_RES_ERR_UNB_STEP_SIZE (3100)

A step size in an optimizer was unexpectedly unbounded. For instance, if the step-size becomes unbounded in phase 1 of the simplex algorithm then an error occurs. Normally this will happen only if the problem is badly formulated. Please contact MOSEK support if this error occurs.

MSK_RES_ERR_UNDEF_SOLUTION (1265)

MOSEK has the following solution types:

- an interior-point solution,
- an basic solution,
- and an integer solution.

Each optimizer may set one or more of these solutions; e.g by default a successful optimization with the interior-point optimizer defines the interior-point solution, and, for linear problems, also the basic solution. This error occurs when asking for a solution or for information about a solution that is not defined.

MSK_RES_ERR_UNDEFINED_OBJECTIVE_SENSE (1446)

The objective sense has not been specified before the optimization.

MSK_RES_ERR_UNHANDLED_SOLUTION_STATUS (6010)

Unhandled solution status.

MSK_RES_ERR_UNKNOWN (1050)

Unknown error.

MSK_RES_ERR_UPPER_BOUND_IS_A_NAN (1391)

The upper bound specified is not a number (nan).

MSK_RES_ERR_UPPER_TRIANGLE (6020)

An element in the upper triangle of a lower triangular matrix is specified.

MSK_RES_ERR_USER_FUNC_RET (1430)

An user function reported an error.

MSK_RES_ERR_USER_FUNC_RET_DATA (1431)

An user function returned invalid data.

MSK_RES_ERR_USER_NLO_EVAL (1433)

The user-defined nonlinear function reported an error.

MSK_RES_ERR_USER_NLO_EVAL_HESSUBI (1440)

The user-defined nonlinear function reported an invalid subscript in the Hessian.

MSK_RES_ERR_USER_NLO_EVAL_HESSUBJ (1441)

The user-defined nonlinear function reported an invalid subscript in the Hessian.

MSK_RES_ERR_USER_NLO_FUNC (1432)

The user-defined nonlinear function reported an error.

MSK_RES_ERR_WHICHITEM_NOT_ALLOWED (1238)

`whichitem` is unacceptable.

MSK_RES_ERR_WHICHSOL (1236)

The solution defined by `compwhichsol` does not exist.

MSK_RES_ERR_WRITE_LP_FORMAT (1158)

Problem cannot be written as an LP file.

MSK_RES_ERR_WRITE_LP_NON_UNIQUE_NAME (1161)

An auto-generated name is not unique.

MSK_RES_ERR_WRITE_MPS_INVALID_NAME (1153)

An invalid name is created while writing an MPS file. Usually this will make the MPS file unreadable.

MSK_RES_ERR_WRITE_OPF_INVALID_VAR_NAME (1156)

Empty variable names cannot be written to OPF files.

MSK_RES_ERR_WRITING_FILE (1166)

An error occurred while writing file

MSK_RES_ERR_XML_INVALID_PROBLEM_TYPE (3600)

The problem type is not supported by the XML format.

MSK_RES_ERR_Y_IS_UNDEFINED (1449)

The solution item y is undefined.

MSK_RES_OK (0)

No error occurred.

MSK_RES_TRM_INTERNAL (10030)

The optimizer terminated due to some internal reason. Please contact MOSEK support.

MSK_RES_TRM_INTERNAL_STOP (10031)

The optimizer terminated for internal reasons. Please contact MOSEK support.

MSK_RES_TRM_MAX_ITERATIONS (10000)

The optimizer terminated at the maximum number of iterations.

MSK_RES_TRM_MAX_NUM_SETBACKS (10020)

The optimizer terminated as the maximum number of set-backs was reached. This indicates numerical problems and a possibly badly formulated problem.

MSK_RES_TRM_MAX_TIME (10001)

The optimizer terminated at the maximum amount of time.

MSK_RES_TRM_MIO_NEAR_ABS_GAP (10004)

The mixed-integer optimizer terminated because the near optimal absolute gap tolerance was satisfied.

MSK_RES_TRM_MIO_NEAR_REL_GAP (10003)

The mixed-integer optimizer terminated because the near optimal relative gap tolerance was satisfied.

MSK_RES_TRM_MIO_NUM_BRANCHES (10009)

The mixed-integer optimizer terminated as to the maximum number of branches was reached.

MSK_RES_TRM_MIO_NUM_RELAXS (10008)

The mixed-integer optimizer terminated as the maximum number of relaxations was reached.

MSK_RES_TRM_NUM_MAX_NUM_INT_SOLUTIONS (10015)

The mixed-integer optimizer terminated as the maximum number of feasible solutions was reached.

MSK_RES_TRM_NUMERICAL_PROBLEM (10025)

The optimizer terminated due to numerical problems.

MSK_RES_TRM_OBJECTIVE_RANGE (10002)

The optimizer terminated on the bound of the objective range.

MSK_RES_TRM_STALL (10006)

The optimizer is terminated due to slow progress.

Stalling means that numerical problems prevent the optimizer from making reasonable progress and that it make no sense to continue. In many cases this happens if the problem is badly scaled or otherwise ill-conditioned. There is no guarantee that the solution will be (near) feasible or near optimal. However, often stalling happens near the optimum, and the returned solution may be of good quality. Therefore, it is recommended to check the status of then solution. If the solution near optimal the solution is most likely good enough for most practical purposes.

Please note that if a linear optimization problem is solved using the interior-point optimizer with basis identification turned on, the returned basic solution likely to have high accuracy, even though the optimizer stalled.

Some common causes of stalling are a) badly scaled models, b) near feasible or near infeasible problems and c) a non-convex problems. Case c) is only relevant for general non-linear problems. It is not possible in general for MOSEK to check if a specific problems is convex since such a check would be NP hard in itself. This implies that care should be taken when solving problems involving general user defined functions.

MSK_RES_TRM_USER_CALLBACK (10007)

The optimizer terminated due to the return of the user-defined call-back function.

MSK_RES_WRN_ANA_ALMOST_INT_BOUNDS (904)

This warning is issued by the problem analyzer if a constraint is bound nearly integral.

MSK_RES_WRN_ANA_C_ZERO (901)

This warning is issued by the problem analyzer, if the coefficients in the linear part of the objective are all zero.

MSK_RES_WRN_ANA_CLOSE_BOUNDS (903)

This warning is issued by problem analyzer, if ranged constraints or variables with very close upper and lower bounds are detected. One should consider treating such constraints as equalities and such variables as constants.

MSK_RES_WRN_ANA_EMPTY_COLS (902)

This warning is issued by the problem analyzer, if columns, in which all coefficients are zero, are found.

MSK_RES_WRN_ANA_LARGE_BOUNDS (900)

This warning is issued by the problem analyzer, if one or more constraint or variable bounds are very large. One should consider omitting these bounds entirely by setting them to $+\infty$ or $-\infty$.

MSK_RES_WRN_CONSTRUCT_INVALID_SOL_ITG (807)

The initial value for one or more of the integer variables is not feasible.

MSK_RES_WRN_CONSTRUCT_NO_SOL_ITG (810)

The construct solution requires an integer solution.

MSK_RES_WRN_CONSTRUCT_SOLUTION_INFEAS (805)

After fixing the integer variables at the suggested values then the problem is infeasible.

MSK_RES_WRN_DROPPED_NZ_QOBJ (201)

One or more non-zero elements were dropped in the Q matrix in the objective.

MSK_RES_WRN_DUPLICATE_BARVARIABLE_NAMES (852)

Two barvariable names are identical.

MSK_RES_WRN_DUPLICATE_CONE_NAMES (853)

Two cone names are identical.

MSK_RES_WRN_DUPLICATE_CONSTRAINT_NAMES (850)

Two constraint names are identical.

MSK_RES_WRN_DUPLICATE_VARIABLE_NAMES (851)

Two variable names are identical.

MSK_RES_WRN_ELIMINATOR_SPACE (801)

The eliminator is skipped at least once due to lack of space.

MSK_RES_WRN_EMPTY_NAME (502)

A variable or constraint name is empty. The output file may be invalid.

MSK_RES_WRN_IGNORE_INTEGER (250)

Ignored integer constraints.

MSK_RES_WRN_INCOMPLETE_LINEAR_DEPENDENCY_CHECK (800)

The linear dependency check(s) is not completed. Normally this is not an important warning unless the optimization problem has been formulated with linear dependencies which is bad practice.

MSK_RES_WRN_LARGE_AIJ (62)

A numerically large value is specified for an $a_{i,j}$ element in A . The parameter **MSK_DPAR_DATA_TOL_AIJ_LARGE** controls when an $a_{i,j}$ is considered large.

MSK_RES_WRN_LARGE_BOUND (51)

A numerically large bound value is specified.

MSK_RES_WRN_LARGE_CJ (57)

A numerically large value is specified for one c_j .

MSK_RES_WRN_LARGE_CON_FX (54)

An equality constraint is fixed to a numerically large value. This can cause numerical problems.

MSK_RES_WRN_LARGE_LO_BOUND (52)

A numerically large lower bound value is specified.

MSK_RES_WRN_LARGE_UP_BOUND (53)

A numerically large upper bound value is specified.

MSK_RES_WRN_LICENSE_EXPIRE (500)

The license expires.

MSK_RES_WRN_LICENSE_FEATURE_EXPIRE (505)

The license expires.

MSK_RES_WRN_LICENSE_SERVER (501)

The license server is not responding.

MSK_RES_WRN_LP_DROP_VARIABLE (85)

Ignored a variable because the variable was not previously defined. Usually this implies that a variable appears in the bound section but not in the objective or the constraints.

MSK_RES_WRN_LP_OLD_QUAD_FORMAT (80)

Missing $\prime/2\prime$ after quadratic expressions in bound or objective.

MSK_RES_WRN_MIO_INFEASIBLE_FINAL (270)

The final mixed-integer problem with all the integer variables fixed at their optimal values is infeasible.

MSK_RES_WRN_MPS_SPLIT_BOU_VECTOR (72)

A BOUNDS vector is split into several nonadjacent parts in an MPS file.

MSK_RES_WRN_MPS_SPLIT_RAN_VECTOR (71)

A RANGE vector is split into several nonadjacent parts in an MPS file.

MSK_RES_WRN_MPS_SPLIT_RHS_VECTOR (70)

An RHS vector is split into several nonadjacent parts in an MPS file.

MSK_RES_WRN_NAME_MAX_LEN (65)

A name is longer than the buffer that is supposed to hold it.

MSK_RES_WRN_NO_DUALIZER (950)

No automatic dualizer is available for the specified problem. The primal problem is solved.

MSK_RES_WRN_NO_GLOBAL_OPTIMIZER (251)

No global optimizer is available.

MSK_RES_WRN_NO_NONLINEAR_FUNCTION_WRITE (450)

The problem contains a general nonlinear function in either the objective or the constraints. Such a nonlinear function cannot be written to a disk file. Note that quadratic terms when inputted explicitly can be written to disk.

MSK_RES_WRN_NZ_IN_UPR_TRI (200)

Non-zero elements specified in the upper triangle of a matrix were ignored.

MSK_RES_WRN_OPEN_PARAM_FILE (50)

The parameter file could not be opened.

MSK_RES_WRN_PARAM_IGNORED_CMIO (516)

A parameter was ignored by the conic mixed integer optimizer.

MSK_RES_WRN_PARAM_NAME_DOU (510)

The parameter name is not recognized as a double parameter.

MSK_RES_WRN_PARAM_NAME_INT (511)

The parameter name is not recognized as an integer parameter.

MSK_RES_WRN_PARAM_NAME_STR (512)

The parameter name is not recognized as a string parameter.

MSK_RES_WRN_PARAM_STR_VALUE (515)

The string is not recognized as a symbolic value for the parameter.

MSK_RES_WRN_PRESOLVE_OUTOFSPACE (802)

The presolve is incomplete due to lack of space.

MSK_RES_WRN_QUAD_CONES_WITH_ROOT_FIXED_AT_ZERO (930)

For at least one quadratic cone the root is fixed at (nearly) zero. This may cause problems such as a very large dual solution. Therefore, it is recommended to remove such cones before optimizing the problems, or to fix all the variables in the cone to 0.

MSK_RES_WRN_RQUAD_CONES_WITH_ROOT_FIXED_AT_ZERO (931)

For at least one rotated quadratic cone at least one of the root variables are fixed at (nearly) zero. This may cause problems such as a very large dual solution. Therefore, it is recommended to remove such cones before optimizing the problems, or to fix all the variables in the cone to 0.

MSK_RES_WRN_SOL_FILE_IGNORED_CON (351)

One or more lines in the constraint section were ignored when reading a solution file.

MSK_RES_WRN_SOL_FILE_IGNORED_VAR (352)

One or more lines in the variable section were ignored when reading a solution file.

MSK_RES_WRN_SOL_FILTER (300)

Invalid solution filter is specified.

MSK_RES_WRN_SPAR_MAX_LEN (66)

A value for a string parameter is longer than the buffer that is supposed to hold it.

MSK_RES_WRN_TOO_FEW_BASIS_VARS (400)

An incomplete basis has been specified. Too few basis variables are specified.

MSK_RES_WRN_TOO_MANY_BASIS_VARS (405)

A basis with too many variables has been specified.

MSK_RES_WRN_TOO_MANY_THREADS_CONCURRENT (750)

The concurrent optimizer employs more threads than available. This will lead to poor performance.

MSK_RES_WRN_UNDEF_SOL_FILE_NAME (350)

Undefined name occurred in a solution.

MSK_RES_WRN_USING_GENERIC_NAMES (503)

Generic names are used because a name is not valid. For instance when writing an LP file the names must not contain blanks or start with a digit.

MSK_RES_WRN_WRITE_CHANGED_NAMES (803)

Some names were changed because they were invalid for the output file format.

MSK_RES_WRN_WRITE_DISCARDED_CFIX (804)

The fixed objective term could not be converted to a variable and was discarded in the output file.

MSK_RES_WRN_ZERO_AIJ (63)

One or more zero elements are specified in A.

MSK_RES_WRN_ZEROS_IN_SPARSE_COL (710)

One or more (near) zero elements are specified in a sparse column of a matrix. It is redundant to specify zero elements. Hence, it may indicate an error.

MSK_RES_WRN_ZEROS_IN_SPARSE_ROW (705)

One or more (near) zero elements are specified in a sparse row of a matrix. It is redundant to specify zero elements. Hence it may indicate an error.

Appendix D

API constants

D.1 Constraint or variable access modes

MSK_ACC_VAR

Access data by columns (variable oriented)

MSK_ACC_CON

Access data by rows (constraint oriented)

D.2 Basis identification

MSK_BI_NEVER

Never do basis identification.

MSK_BI_ALWAYS

Basis identification is always performed even if the interior-point optimizer terminates abnormally.

MSK_BI_NO_ERROR

Basis identification is performed if the interior-point optimizer terminates without an error.

MSK_BI_IF_FEASIBLE

Basis identification is not performed if the interior-point optimizer terminates with a problem status saying that the problem is primal or dual infeasible.

MSK_BI_RESERVED

Not currently in use.

D.3 Bound keys

MSK_BK_LO

The constraint or variable has a finite lower bound and an infinite upper bound.

MSK_BK_UP

The constraint or variable has an infinite lower bound and a finite upper bound.

MSK_BK_FX

The constraint or variable is fixed.

MSK_BK_FR

The constraint or variable is free.

MSK_BK_RA

The constraint or variable is ranged.

D.4 Specifies the branching direction.

MSK_BRANCH_DIR_FREE

The mixed-integer optimizer decides which branch to choose.

MSK_BRANCH_DIR_UP

The mixed-integer optimizer always chooses the up branch first.

MSK_BRANCH_DIR_DOWN

The mixed-integer optimizer always chooses the down branch first.

D.5 Progress call-back codes

MSK_CALLBACK_BEGIN_BI

The basis identification procedure has been started.

MSK_CALLBACK_BEGIN_CONCURRENT

Concurrent optimizer is started.

MSK_CALLBACK_BEGIN_CONIC

The call-back function is called when the conic optimizer is started.

MSK_CALLBACK_BEGIN_DUAL_BI

The call-back function is called from within the basis identification procedure when the dual phase is started.

MSK_CALLBACK_BEGIN_DUAL_SENSITIVITY

Dual sensitivity analysis is started.

MSK_CALLBACK_BEGIN_DUAL_SETUP_BI

The call-back function is called when the dual BI phase is started.

MSK_CALLBACK_BEGIN_DUAL_SIMPLEX

The call-back function is called when the dual simplex optimizer started.

MSK_CALLBACK_BEGIN_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the dual simplex clean-up phase is started.

MSK_CALLBACK_BEGIN_FULL_CONVEXITY_CHECK

Begin full convexity check.

MSK_CALLBACK_BEGIN_INFEAS_ANA

The call-back function is called when the infeasibility analyzer is started.

MSK_CALLBACK_BEGIN_INTPNT

The call-back function is called when the interior-point optimizer is started.

MSK_CALLBACK_BEGIN_LICENSE_WAIT

Begin waiting for license.

MSK_CALLBACK_BEGIN_MIO

The call-back function is called when the mixed-integer optimizer is started.

MSK_CALLBACK_BEGIN_NETWORK_DUAL_SIMPLEX

The call-back function is called when the dual network simplex optimizer is started.

MSK_CALLBACK_BEGIN_NETWORK_PRIMAL_SIMPLEX

The call-back function is called when the primal network simplex optimizer is started.

MSK_CALLBACK_BEGIN_NETWORK_SIMPLEX

The call-back function is called when the simplex network optimizer is started.

MSK_CALLBACK_BEGIN_NONCONVEX

The call-back function is called when the nonconvex optimizer is started.

MSK_CALLBACK_BEGIN_OPTIMIZER

The call-back function is called when the optimizer is started.

MSK_CALLBACK_BEGIN_PRESOLVE

The call-back function is called when the presolve is started.

MSK_CALLBACK_BEGIN_PRIMAL_BI

The call-back function is called from within the basis identification procedure when the primal phase is started.

MSK_CALLBACK_BEGIN_PRIMAL_DUAL_SIMPLEX

The call-back function is called when the primal-dual simplex optimizer is started.

MSK_CALLBACK_BEGIN_PRIMAL_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the primal-dual simplex clean-up phase is started.

MSK_CALLBACK_BEGIN_PRIMAL_REPAIR

Begin primal feasibility repair.

MSK_CALLBACK_BEGIN_PRIMAL_SENSITIVITY

Primal sensitivity analysis is started.

MSK_CALLBACK_BEGIN_PRIMAL_SETUP_BI

The call-back function is called when the primal BI setup is started.

MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX

The call-back function is called when the primal simplex optimizer is started.

MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the primal simplex clean-up phase is started.

MSK_CALLBACK_BEGIN_QCQO_REFORMULATE

Begin QCQO reformulation.

MSK_CALLBACK_BEGIN_READ

MOSEK has started reading a problem file.

MSK_CALLBACK_BEGIN_SIMPLEX

The call-back function is called when the simplex optimizer is started.

MSK_CALLBACK_BEGIN_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the simplex clean-up phase is started.

MSK_CALLBACK_BEGIN_SIMPLEX_NETWORK_DETECT

The call-back function is called when the network detection procedure is started.

MSK_CALLBACK_BEGIN_WRITE

MOSEK has started writing a problem file.

MSK_CALLBACK_CONIC

The call-back function is called from within the conic optimizer after the information database has been updated.

MSK_CALLBACK_DUAL_SIMPLEX

The call-back function is called from within the dual simplex optimizer.

MSK_CALLBACK_END_BI

The call-back function is called when the basis identification procedure is terminated.

MSK_CALLBACK_END_CONCURRENT

Concurrent optimizer is terminated.

MSK_CALLBACK_END_CONIC

The call-back function is called when the conic optimizer is terminated.

MSK_CALLBACK_END_DUAL_BI

The call-back function is called from within the basis identification procedure when the dual phase is terminated.

MSK_CALLBACK_END_DUAL_SENSITIVITY

Dual sensitivity analysis is terminated.

MSK_CALLBACK_END_DUAL_SETUP_BI

The call-back function is called when the dual BI phase is terminated.

MSK_CALLBACK_END_DUAL_SIMPLEX

The call-back function is called when the dual simplex optimizer is terminated.

MSK_CALLBACK_END_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the dual clean-up phase is terminated.

MSK_CALLBACK_END_FULL_CONVEXITY_CHECK

End full convexity check.

MSK_CALLBACK_END_INFEAS_ANA

The call-back function is called when the infeasibility analyzer is terminated.

MSK_CALLBACK_END_INTPNT

The call-back function is called when the interior-point optimizer is terminated.

MSK_CALLBACK_END_LICENSE_WAIT

End waiting for license.

MSK_CALLBACK_END_MIO

The call-back function is called when the mixed-integer optimizer is terminated.

MSK_CALLBACK_END_NETWORK_DUAL_SIMPLEX

The call-back function is called when the dual network simplex optimizer is terminated.

MSK_CALLBACK_END_NETWORK_PRIMAL_SIMPLEX

The call-back function is called when the primal network simplex optimizer is terminated.

MSK_CALLBACK_END_NETWORK_SIMPLEX

The call-back function is called when the simplex network optimizer is terminated.

MSK_CALLBACK_END_NONCONVEX

The call-back function is called when the nonconvex optimizer is terminated.

MSK_CALLBACK_END_OPTIMIZER

The call-back function is called when the optimizer is terminated.

MSK_CALLBACK_END_PRESOLVE

The call-back function is called when the presolve is completed.

MSK_CALLBACK_END_PRIMAL_BI

The call-back function is called from within the basis identification procedure when the primal phase is terminated.

MSK_CALLBACK_END_PRIMAL_DUAL_SIMPLEX

The call-back function is called when the primal-dual simplex optimizer is terminated.

MSK_CALLBACK_END_PRIMAL_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the primal-dual clean-up phase is terminated.

MSK_CALLBACK_END_PRIMAL_REPAIR

End primal feasibility repair.

MSK_CALLBACK_END_PRIMAL_SENSITIVITY

Primal sensitivity analysis is terminated.

MSK_CALLBACK_END_PRIMAL_SETUP_BI

The call-back function is called when the primal BI setup is terminated.

MSK_CALLBACK_END_PRIMAL_SIMPLEX

The call-back function is called when the primal simplex optimizer is terminated.

MSK_CALLBACK_END_PRIMAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the primal clean-up phase is terminated.

MSK_CALLBACK_END_QCQO_REFORMULATE

End QCQO reformulation.

MSK_CALLBACK_END_READ

MOSEK has finished reading a problem file.

MSK_CALLBACK_END_SIMPLEX

The call-back function is called when the simplex optimizer is terminated.

MSK_CALLBACK_END_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the simplex clean-up phase is terminated.

MSK_CALLBACK_END_SIMPLEX_NETWORK_DETECT

The call-back function is called when the network detection procedure is terminated.

MSK_CALLBACK_END_WRITE

MOSEK has finished writing a problem file.

MSK_CALLBACK_IM_BI

The call-back function is called from within the basis identification procedure at an intermediate point.

MSK_CALLBACK_IM_CONIC

The call-back function is called at an intermediate stage within the conic optimizer where the information database has not been updated.

MSK_CALLBACK_IM_DUAL_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the dual phase.

MSK_CALLBACK_IM_DUAL_SENSIVITY

The call-back function is called at an intermediate stage of the dual sensitivity analysis.

MSK_CALLBACK_IM_DUAL_SIMPLEX

The call-back function is called at an intermediate point in the dual simplex optimizer.

MSK_CALLBACK_IM_FULL_CONVEXITY_CHECK

The call-back function is called at an intermediate stage of the full convexity check.

MSK_CALLBACK_IM_INTPNT

The call-back function is called at an intermediate stage within the interior-point optimizer where the information database has not been updated.

MSK_CALLBACK_IM_LICENSE_WAIT

MOSEK is waiting for a license.

MSK_CALLBACK_IM_LU

The call-back function is called from within the LU factorization procedure at an intermediate point.

MSK_CALLBACK_IM_MIO

The call-back function is called at an intermediate point in the mixed-integer optimizer.

MSK_CALLBACK_IM_MIO_DUAL_SIMPLEX

The call-back function is called at an intermediate point in the mixed-integer optimizer while running the dual simplex optimizer.

MSK_CALLBACK_IM_MIO_INTPNT

The call-back function is called at an intermediate point in the mixed-integer optimizer while running the interior-point optimizer.

MSK_CALLBACK_IM_MIO_PRESOLVE

The call-back function is called at an intermediate point in the mixed-integer optimizer while running the presolve.

MSK_CALLBACK_IM_MIO_PRIMAL_SIMPLEX

The call-back function is called at an intermediate point in the mixed-integer optimizer while running the primal simplex optimizer.

MSK_CALLBACK_IM_NETWORK_DUAL_SIMPLEX

The call-back function is called at an intermediate point in the dual network simplex optimizer.

MSK_CALLBACK_IM_NETWORK_PRIMAL_SIMPLEX

The call-back function is called at an intermediate point in the primal network simplex optimizer.

MSK_CALLBACK_IM_NONCONVEX

The call-back function is called at an intermediate stage within the nonconvex optimizer where the information database has not been updated.

MSK_CALLBACK_IM_ORDER

The call-back function is called from within the matrix ordering procedure at an intermediate point.

MSK_CALLBACK_IM_PRESOLVE

The call-back function is called from within the presolve procedure at an intermediate stage.

MSK_CALLBACK_IM_PRIMAL_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the primal phase.

MSK_CALLBACK_IM_PRIMAL_DUAL_SIMPLEX

The call-back function is called at an intermediate point in the primal-dual simplex optimizer.

MSK_CALLBACK_IM_PRIMAL_SENSIVITY

The call-back function is called at an intermediate stage of the primal sensitivity analysis.

MSK_CALLBACK_IM_PRIMAL_SIMPLEX

The call-back function is called at an intermediate point in the primal simplex optimizer.

MSK_CALLBACK_IM_QO_REFORMULATE

The call-back function is called at an intermediate stage of the conic quadratic reformulation.

MSK_CALLBACK_IM_READ

Intermediate stage in reading.

MSK_CALLBACK_IM_SIMPLEX

The call-back function is called from within the simplex optimizer at an intermediate point.

MSK_CALLBACK_IM_SIMPLEX_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the simplex clean-up phase. The frequency of the call-backs is controlled by the **MSK_IPAR_LOG_SIM_FREQ** parameter.

MSK_CALLBACK_INTPNT

The call-back function is called from within the interior-point optimizer after the information database has been updated.

MSK_CALLBACK_NEW_INT_MIO

The call-back function is called after a new integer solution has been located by the mixed-integer optimizer.

MSK_CALLBACK_NONCOVEX

The call-back function is called from within the nonconvex optimizer after the information database has been updated.

MSK_CALLBACK_PRIMAL_SIMPLEX

The call-back function is called from within the primal simplex optimizer.

MSK_CALLBACK_READ_OPF

The call-back function is called from the OPF reader.

MSK_CALLBACK_READ_OPF_SECTION

A chunk of Q non-zeros has been read from a problem file.

MSK_CALLBACK_UPDATE_DUAL_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the dual phase.

MSK_CALLBACK_UPDATE_DUAL_SIMPLEX

The call-back function is called in the dual simplex optimizer.

MSK_CALLBACK_UPDATE_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the dual simplex clean-up phase. The frequency of the call-backs is controlled by the **MSK_IPAR_LOG_SIM_FREQ** parameter.

MSK_CALLBACK_UPDATE_NETWORK_DUAL_SIMPLEX

The call-back function is called in the dual network simplex optimizer.

MSK_CALLBACK_UPDATE_NETWORK_PRIMAL_SIMPLEX

The call-back function is called in the primal network simplex optimizer.

MSK_CALLBACK_UPDATE_NONCONVEX

The call-back function is called at an intermediate stage within the nonconvex optimizer where the information database has been updated.

MSK_CALLBACK_UPDATE_PRESOLVE

The call-back function is called from within the presolve procedure.

MSK_CALLBACK_UPDATE_PRIMAL_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the primal phase.

MSK_CALLBACK_UPDATE_PRIMAL_DUAL_SIMPLEX

The call-back function is called in the primal-dual simplex optimizer.

MSK_CALLBACK_UPDATE_PRIMAL_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the primal-dual simplex clean-up phase. The frequency of the call-backs is controlled by the **MSK_IPAR_LOG_SIM_FREQ** parameter.

MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX

The call-back function is called in the primal simplex optimizer.

MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the primal simplex clean-up phase. The frequency of the call-backs is controlled by the **MSK_IPAR_LOG_SIM_FREQ** parameter.

MSK_CALLBACK_WRITE_OPF

The call-back function is called from the OPF writer.

D.6 Types of convexity checks.

MSK_CHECK_CONVEXITY_NONE

No convexity check.

MSK_CHECK_CONVEXITY_SIMPLE

Perform simple and fast convexity check.

MSK_CHECK_CONVEXITY_FULL

Perform a full convexity check.

D.7 Compression types

MSK_COMPRESS_NONE

No compression is used.

MSK_COMPRESS_FREE

The type of compression used is chosen automatically.

MSK_COMPRESS_GZIP

The type of compression used is gzip compatible.

D.8 Cone types

MSK_CT_QUAD

The cone is a quadratic cone.

MSK_CT_RQUAD

The cone is a rotated quadratic cone.

D.9 Data format types

MSK_DATA_FORMAT_EXTENSION

The file extension is used to determine the data file format.

MSK_DATA_FORMAT_MPS

The data file is MPS formatted.

MSK_DATA_FORMAT_LP

The data file is LP formatted.

MSK_DATA_FORMAT_OP

The data file is an optimization problem formatted file.

MSK_DATA_FORMAT_XML

The data file is an XML formatted file.

MSK_DATA_FORMAT_FREE_MPS

The data data a free MPS formatted file.

MSK_DATA_FORMAT_TASK

Generic task dump file.

MSK_DATA_FORMAT_CB

Conic benchmark format.

D.10 Double information items

MSK_DINF_BI_CLEAN_DUAL_TIME

Time spent within the dual clean-up optimizer of the basis identification procedure since its invocation.

MSK_DINF_BI_CLEAN_PRIMAL_DUAL_TIME

Time spent within the primal-dual clean-up optimizer of the basis identification procedure since its invocation.

MSK_DINF_BI_CLEAN_PRIMAL_TIME

Time spent within the primal clean-up optimizer of the basis identification procedure since its invocation.

MSK_DINF_BI_CLEAN_TIME

Time spent within the clean-up phase of the basis identification procedure since its invocation.

MSK_DINF_BI_DUAL_TIME

Time spent within the dual phase basis identification procedure since its invocation.

MSK_DINF_BI_PRIMAL_TIME

Time spent within the primal phase of the basis identification procedure since its invocation.

MSK_DINF_BI_TIME

Time spent within the basis identification procedure since its invocation.

MSK_DINF_CONCURRENT_TIME

Time spent within the concurrent optimizer since its invocation.

MSK_DINF_INTPNT_DUAL_FEAS

Dual feasibility measure reported by the interior-point optimizer. (For the interior-point optimizer this measure does not directly related to the original problem because a homogeneous model is employed.)

MSK_DINF_INTPNT_DUAL_OBJ

Dual objective value reported by the interior-point optimizer.

MSK_DINF_INTPNT_FACTOR_NUM_FLOPS

An estimate of the number of flops used in the factorization.

MSK_DINF_INTPNT_OPT_STATUS

This measure should converge to +1 if the problem has a primal-dual optimal solution, and converge to -1 if problem is (strictly) primal or dual infeasible. Furthermore, if the measure converges to 0 the problem is usually ill-posed.

MSK_DINF_INTPNT_ORDER_TIME

Order time (in seconds).

MSK_DINF_INTPNT_PRIMAL_FEAS

Primal feasibility measure reported by the interior-point optimizers. (For the interior-point optimizer this measure does not directly related to the original problem because a homogeneous model is employed).

MSK_DINF_INTPNT_PRIMAL_OBJ

Primal objective value reported by the interior-point optimizer.

MSK_DINF_INTPNT_TIME

Time spent within the interior-point optimizer since its invocation.

MSK_DINF_MIO_CG_SEPERATION_TIME

Seperation time for CG cuts.

MSK_DINF_MIO_CMIR_SEPERATION_TIME

Seperation time for CMIR cuts.

MSK_DINF_MIO_CONSTRUCT_SOLUTION_OBJ

If MOSEK has successfully constructed an integer feasible solution, then this item contains the optimal objective value corresponding to the feasible solution.

MSK_DINF_MIO_DUAL_BOUND_AFTER_PRESOLVE

Value of the dual bound after presolve but before cut generation.

MSK_DINF_MIO_HEURISTIC_TIME

Time spent in the optimizer while solving the relaxtions.

MSK_DINF_MIO_OBJ_ABS_GAP

Given the mixed-integer optimizer has computed a feasible solution and a bound on the optimal objective value, then this item contains the absolute gap defined by

$$|(\text{objective value of feasible solution}) - (\text{objective bound})|.$$

Otherwise it has the value -1.0.

MSK_DINF_MIO_OBJ_BOUND

The best known bound on the objective function. This value is undefined until at least one relaxation has been solved: To see if this is the case check that **MSK_IINF_MIO_NUM_RELAX** is strictly positive.

MSK_DINF_MIO_OBJ_INT

The primal objective value corresponding to the best integer feasible solution. Please note that at least one integer feasible solution must have located i.e. check **MSK_IINF_MIO_NUM_INT_SOLUTIONS**.

MSK_DINF_MIO_OBJ_REL_GAP

Given that the mixed-integer optimizer has computed a feasible solution and a bound on the optimal objective value, then this item contains the relative gap defined by

$$\frac{|(\text{objective value of feasible solution}) - (\text{objective bound})|}{\max(\delta, |(\text{objective value of feasible solution})|)}.$$

where δ is given by the parameter **MSK_DPAR_MIO_REL_GAP_CONST**. Otherwise it has the value -1.0.

MSK_DINF_MIO_OPTIMIZER_TIME

Time spent in the optimizer while solving the relaxations.

MSK_DINF_MIO_PROBING_TIME

Total time for probing.

MSK_DINF_MIO_ROOT_CUTGEN_TIME

Total time for cut generation.

MSK_DINF_MIO_ROOT_OPTIMIZER_TIME

Time spent in the optimizer while solving the root relaxation.

MSK_DINF_MIO_ROOT_PRESOLVE_TIME

Time spent in while presolveing the root relaxation.

MSK_DINF_MIO_TIME

Time spent in the mixed-integer optimizer.

MSK_DINF_MIO_USER_OBJ_CUT

If the objective cut is used, then this information item has the value of the cut.

MSK_DINF_OPTIMIZER_TIME

Total time spent in the optimizer since it was invoked.

MSK_DINF_PRESOLVE_ELI_TIME

Total time spent in the eliminator since the presolve was invoked.

MSK_DINF_PRESOLVE_LINDEP_TIME

Total time spent in the linear dependency checker since the presolve was invoked.

MSK_DINF_PRESOLVE_TIME

Total time (in seconds) spent in the presolve since it was invoked.

MSK_DINF_PRIMAL_REPAIR_PENALTY_OBJ

The optimal objective value of the penalty function.

MSK_DINF_QCQO_REFORMULATE_TIME

Time spent with conic quadratic reformulation.

MSK_DINF_RD_TIME

Time spent reading the data file.

MSK_DINF_SIM_DUAL_TIME

Time spent in the dual simplex optimizer since invoking it.

MSK_DINF_SIM_FEAS

Feasibility measure reported by the simplex optimizer.

MSK_DINF_SIM_NETWORK_DUAL_TIME

Time spent in the dual network simplex optimizer since invoking it.

MSK_DINF_SIM_NETWORK_PRIMAL_TIME

Time spent in the primal network simplex optimizer since invoking it.

MSK_DINF_SIM_NETWORK_TIME

Time spent in the network simplex optimizer since invoking it.

MSK_DINF_SIM_OBJ

Objective value reported by the simplex optimizer.

MSK_DINF_SIM_PRIMAL_DUAL_TIME

Time spent in the primal-dual simplex optimizer optimizer since invoking it.

MSK_DINF_SIM_PRIMAL_TIME

Time spent in the primal simplex optimizer since invoking it.

MSK_DINF_SIM_TIME

Time spent in the simplex optimizer since invoking it.

MSK_DINF_SOL_BAS_DUAL_OBJ

Dual objective value of the basic solution.

MSK_DINF_SOL_BAS_DVIOLCON

Maximal dual bound violation for x^c in the basic solution.

MSK_DINF_SOL_BAS_DVIOLVAR

Maximal dual bound violation for x^x in the basic solution.

MSK_DINF_SOL_BAS_PRIMAL_OBJ

Primal objective value of the basic solution.

MSK_DINF_SOL_BAS_PVIOLCON

Maximal primal bound violation for x^c in the basic solution.

MSK_DINF_SOL_BAS_PVIOLVAR

Maximal primal bound violation for x^x in the basic solution.

MSK_DINF_SOL_ITG_PRIMAL_OBJ

Primal objective value of the integer solution.

MSK_DINF_SOL_ITG_PVIOLBARVAR

Maximal primal bound violation for \bar{X} in the integer solution.

MSK_DINF_SOL_ITG_PVIOLCON

Maximal primal bound violation for x^c in the integer solution.

MSK_DINF_SOL_ITG_PVIOLCONES

Maximal primal violation for primal conic constraints in the integer solution.

MSK_DINF_SOL_ITG_PVIOLITG

Maximal violation for the integer constraints in the integer solution.

MSK_DINF_SOL_ITG_PVIOLVAR

Maximal primal bound violation for x^x in the integer solution.

MSK_DINF_SOL_ITR_DUAL_OBJ

Dual objective value of the interior-point solution.

MSK_DINF_SOL_ITR_DVIOLBARVAR

Maximal dual bound violation for \bar{X} in the interior-point solution.

MSK_DINF_SOL_ITR_DVIOLCON

Maximal dual bound violation for x^c in the interior-point solution.

MSK_DINF_SOL_ITR_DVIOLCONES

Maximal dual violation for dual conic constraints in the interior-point solution.

MSK_DINF_SOL_ITR_DVIOLVAR

Maximal dual bound violation for x^x in the interior-point solution.

MSK_DINF_SOL_ITR_PRIMAL_OBJ

Primal objective value of the interior-point solution.

MSK_DINF_SOL_ITR_PVIOLBARVAR

Maximal primal bound violation for \bar{X} in the interior-point solution.

MSK_DINF_SOL_ITR_PVIOLCON

Maximal primal bound violation for x^c in the interior-point solution.

MSK_DINF_SOL_ITR_PVIOLCONES

Maximal primal violation for primal conic constraints in the interior-point solution.

MSK_DINF_SOL_ITR_PVIOLVAR

Maximal primal bound violation for x^x in the interior-point solution.

D.11 Feasibility repair types

MSK_FEASREPAIR_OPTIMIZE_NONE

Do not optimize the feasibility repair problem.

MSK_FEASREPAIR_OPTIMIZE_PENALTY

Minimize weighted sum of violations.

MSK_FEASREPAIR_OPTIMIZE_COMBINED

Minimize with original objective subject to minimal weighted violation of bounds.

D.12 License feature

MSK_FEATURE_PTS

Base system.

MSK_FEATURE_PTON

Nonlinear extension.

MSK_FEATURE_PTOM

Mixed-integer extension.

MSK_FEATURE_PTOX

Non-convex extension.

D.13 Integer information items.

MSK_IINF_ANA_PRO_NUM_CON

Number of constraints in the problem.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_CON_EQ

Number of equality constraints.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_CON_FR

Number of unbounded constraints.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_CON_LO

Number of constraints with a lower bound and an infinite upper bound.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_CON_RA

Number of constraints with finite lower and upper bounds.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_CON_UP

Number of constraints with an upper bound and an infinite lower bound.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_VAR

Number of variables in the problem.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_VAR_BIN

Number of binary (0-1) variables.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_VAR_CONT

Number of continuous variables.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_VAR_EQ

Number of fixed variables.

This value is set by `MSK_analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_VAR_FR

Number of free variables.

This value is set by `MSK.analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_VAR_INT

Number of general integer variables.

This value is set by `MSK.analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_VAR_LO

Number of variables with a lower bound and an infinite upper bound.

This value is set by `MSK.analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_VAR_RA

Number of variables with finite lower and upper bounds.

This value is set by `MSK.analyzeproblem`.

MSK_IINF_ANA_PRO_NUM_VAR_UP

Number of variables with an upper bound and an infinite lower bound. This value is set by

This value is set by `MSK.analyzeproblem`.

MSK_IINF_CONCURRENT_FASTEST_OPTIMIZER

The type of the optimizer that finished first in a concurrent optimization.

MSK_IINF_INTPNT_FACTOR_DIM_DENSE

Dimension of the dense sub system in factorization.

MSK_IINF_INTPNT_ITER

Number of interior-point iterations since invoking the interior-point optimizer.

MSK_IINF_INTPNT_NUM_THREADS

Number of threads that the interior-point optimizer is using.

MSK_IINF_INTPNT_SOLVE_DUAL

Non-zero if the interior-point optimizer is solving the dual problem.

MSK_IINF_MIO_CONSTRUCT_NUM_ROUNDINGS

Number of values in the integer solution that is rounded to an integer value.

MSK_IINF_MIO_CONSTRUCT_SOLUTION

If this item has the value 0, then MOSEK did not try to construct an initial integer feasible solution. If the item has a positive value, then MOSEK successfully constructed an initial integer feasible solution.

MSK_IINF_MIO_INITIAL_SOLUTION

Is non-zero if an initial integer solution is specified.

MSK_IINF_MIO_NUM_ACTIVE_NODES

Number of active branch bound nodes.

MSK_IINF_MIO_NUM_BASIS_CUTS

Number of basis cuts.

MSK_IINF_MIO_NUM_BRANCH

Number of branches performed during the optimization.

MSK_IINF_MIO_NUM_CARDGUB_CUTS

Number of cardgub cuts.

MSK_IINF_MIO_NUM_CLIQUÉ_CUTS

Number of clique cuts.

MSK_IINF_MIO_NUM_COEF_REDC_CUTS

Number of coef. redc. cuts.

MSK_IINF_MIO_NUM_CONTRA_CUTS

Number of contra cuts.

MSK_IINF_MIO_NUM_DISAGG_CUTS

Number of diasagg cuts.

MSK_IINF_MIO_NUM_FLOW_COVER_CUTS

Number of flow cover cuts.

MSK_IINF_MIO_NUM_GCD_CUTS

Number of gcd cuts.

MSK_IINF_MIO_NUM_GOMORY_CUTS

Number of Gomory cuts.

MSK_IINF_MIO_NUM_GUB_COVER_CUTS

Number of GUB cover cuts.

MSK_IINF_MIO_NUM_INT_SOLUTIONS

Number of integer feasible solutions that has been found.

MSK_IINF_MIO_NUM_KNAPSUR_COVER_CUTS

Number of knapsack cover cuts.

MSK_IINF_MIO_NUM_LATTICE_CUTS

Number of lattice cuts.

MSK_IINF_MIO_NUM_LIFT_CUTS

Number of lift cuts.

MSK_IINF_MIO_NUM_OBJ_CUTS

Number of obj cuts.

MSK_IINF_MIO_NUM_PLAN_LOC_CUTS

Number of loc cuts.

MSK_IINF_MIO_NUM_RELAX

Number of relaxations solved during the optimization.

MSK_IINF_MIO_NUMCON

Number of constraints in the problem solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMINT

Number of integer variables in the problem solved by the mixed-integer optimizer.

MSK_IINF_MIO_NUMVAR

Number of variables in the problem solved by the mixed-integer optimizer.

MSK_IINF_MIO_OBJ_BOUND_DEFINED

Non-zero if a valid objective bound has been found, otherwise zero.

MSK_IINF_MIO_TOTAL_NUM_CUTS

Total number of cuts generated by the mixed-integer optimizer.

MSK_IINF_MIO_USER_OBJ_CUT

If it is non-zero, then the objective cut is used.

MSK_IINF_OPT_NUMCON

Number of constraints in the problem solved when the optimizer is called.

MSK_IINF_OPT_NUMVAR

Number of variables in the problem solved when the optimizer is called

MSK_IINF_OPTIMIZE_RESPONSE

The response code returned by optimize.

MSK_IINF_RD_NUMBARVAR

Number of variables read.

MSK_IINF_RD_NUMCON

Number of constraints read.

MSK_IINF_RD_NUMCONE

Number of conic constraints read.

MSK_IINF_RD_NUMINTVAR

Number of integer-constrained variables read.

MSK_IINF_RD_NUMQ

Number of nonempty Q matrixes read.

MSK_IINF_RD_NUMVAR

Number of variables read.

MSK_IINF_RD_PROTOTYPE

Problem type.

MSK_IINF_SIM_DUAL_DEG_ITER

The number of dual degenerate iterations.

MSK_IINF_SIM_DUAL_HOTSTART

If 1 then the dual simplex algorithm is solving from an advanced basis.

MSK_IINF_SIM_DUAL_HOTSTART_LU

If 1 then a valid basis factorization of full rank was located and used by the dual simplex algorithm.

MSK_IINF_SIM_DUAL_INF_ITER

The number of iterations taken with dual infeasibility.

MSK_IINF_SIM_DUAL_ITER

Number of dual simplex iterations during the last optimization.

MSK_IINF_SIM_NETWORK_DUAL_DEG_ITER

The number of dual network degenerate iterations.

MSK_IINF_SIM_NETWORK_DUAL_HOTSTART

If 1 then the dual network simplex algorithm is solving from an advanced basis.

MSK_IINF_SIM_NETWORK_DUAL_HOTSTART_LU

If 1 then a valid basis factorization of full rank was located and used by the dual network simplex algorithm.

MSK_IINF_SIM_NETWORK_DUAL_INF_ITER

The number of iterations taken with dual infeasibility in the network optimizer.

MSK_IINF_SIM_NETWORK_DUAL_ITER

Number of dual network simplex iterations during the last optimization.

MSK_IINF_SIM_NETWORK_PRIMAL_DEG_ITER

The number of primal network degenerate iterations.

MSK_IINF_SIM_NETWORK_PRIMAL_HOTSTART

If 1 then the primal network simplex algorithm is solving from an advanced basis.

MSK_IINF_SIM_NETWORK_PRIMAL_HOTSTART_LU

If 1 then a valid basis factorization of full rank was located and used by the primal network simplex algorithm.

MSK_IINF_SIM_NETWORK_PRIMAL_INF_ITER

The number of iterations taken with primal infeasibility in the network optimizer.

MSK_IINF_SIM_NETWORK_PRIMAL_ITER

Number of primal network simplex iterations during the last optimization.

MSK_IINF_SIM_NUMCON

Number of constraints in the problem solved by the simplex optimizer.

MSK_IINF_SIM_NUMVAR

Number of variables in the problem solved by the simplex optimizer.

MSK_IINF_SIM_PRIMAL_DEG_ITER

The number of primal degenerate iterations.

MSK_IINF_SIM_PRIMAL_DUAL_DEG_ITER

The number of degenerate major iterations taken by the primal dual simplex algorithm.

MSK_IINF_SIM_PRIMAL_DUAL_HOTSTART

If 1 then the primal dual simplex algorithm is solving from an advanced basis.

MSK_IINF_SIM_PRIMAL_DUAL_HOTSTART_LU

If 1 then a valid basis factorization of full rank was located and used by the primal dual simplex algorithm.

MSK_IINF_SIM_PRIMAL_DUAL_INF_ITER

The number of master iterations with dual infeasibility taken by the primal dual simplex algorithm.

MSK_IINF_SIM_PRIMAL_DUAL_ITER

Number of primal dual simplex iterations during the last optimization.

MSK_IINF_SIM_PRIMAL_HOTSTART

If 1 then the primal simplex algorithm is solving from an advanced basis.

MSK_IINF_SIM_PRIMAL_HOTSTART_LU

If 1 then a valid basis factorization of full rank was located and used by the primal simplex algorithm.

MSK_IINF_SIM_PRIMAL_INF_ITER

The number of iterations taken with primal infeasibility.

MSK_IINF_SIM_PRIMAL_ITER

Number of primal simplex iterations during the last optimization.

MSK_IINF_SIM_SOLVE_DUAL

Is non-zero if dual problem is solved.

MSK_IINF_SOL_BAS_PROSTA

Problem status of the basic solution. Updated after each optimization.

MSK_IINF_SOL_BAS_SOLSTA

Solution status of the basic solution. Updated after each optimization.

MSK_IINF_SOL_INT_PROSTA

Deprecated.

MSK_IINF_SOL_INT_SOLSTA

Deprecated.

MSK_IINF_SOL_ITG_PROSTA

Problem status of the integer solution. Updated after each optimization.

MSK_IINF_SOL_ITG_SOLSTA

Solution status of the integer solution. Updated after each optimization.

MSK_IINF_SOL_ITR_PROSTA

Problem status of the interior-point solution. Updated after each optimization.

MSK_IINF_SOL_ITR_SOLSTA

Solution status of the interior-point solution. Updated after each optimization.

MSK_IINF_STO_NUM_A_CACHE_FLUSHES

Number of times the cache of A elements is flushed. A large number implies that `maxnumanz` is too small as well as an inefficient usage of MOSEK.

MSK_IINF_STO_NUM_A_REALLOC

Number of times the storage for storing A has been changed. A large value may indicate that memory fragmentation may occur.

MSK_IINF_STO_NUM_A_TRANSPOSES

Number of times the A matrix is transposed. A large number implies that `maxnumanz` is too small or an inefficient usage of MOSEK. This will occur in particular if the code alternate between accessing rows and columns of A .

D.14 Information item types

MSK_INF_DOU_TYPE

Is a double information type.

MSK_INF_INT_TYPE

Is an integer.

MSK_INF_LINT_TYPE

Is a long integer.

D.15 Hot-start type employed by the interior-point optimizers.

MSK_INTPNT_HOTSTART_NONE

The interior-point optimizer performs a coldstart.

MSK_INTPNT_HOTSTART_PRIMAL

The interior-point optimizer exploits the primal solution only.

MSK_INTPNT_HOTSTART_DUAL

The interior-point optimizer exploits the dual solution only.

MSK_INTPNT_HOTSTART_PRIMAL_DUAL

The interior-point optimizer exploits both the primal and dual solution.

D.16 Input/output modes

MSK_IOMODE_READ

The file is read-only.

MSK_IOMODE_WRITE

The file is write-only. If the file exists then it is truncated when it is opened. Otherwise it is created when it is opened.

MSK_IOMODE_READWRITE

The file is to read and written.

D.17 Language selection constants

MSK_LANG_ENG

English language selection

MSK_LANG_DAN

Danish language selection

D.18 Long integer information items.

MSK_LIINF_BI_CLEAN_DUAL_DEG_ITER

Number of dual degenerate clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_DUAL_ITER

Number of dual clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_DEG_ITER

Number of primal degenerate clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_DUAL_DEG_ITER

Number of primal-dual degenerate clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_DUAL_ITER

Number of primal-dual clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_DUAL_SUB_ITER

Number of primal-dual subproblem clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_ITER

Number of primal clean iterations performed in the basis identification.

MSK_LIINF_BI_DUAL_ITER

Number of dual pivots performed in the basis identification.

MSK_LIINF_BI_PRIMAL_ITER

Number of primal pivots performed in the basis identification.

MSK_LIINF_INTPNT_FACTOR_NUM_NZ

Number of non-zeros in factorization.

MSK_LIINF_MIO_INTPNT_ITER

Number of interior-point iterations performed by the mixed-integer optimizer.

MSK_LIINF_MIO_SIMPLEX_ITER

Number of simplex iterations performed by the mixed-integer optimizer.

MSK_LIINF_RD_NUMANZ

Number of non-zeros in A that is read.

MSK_LIINF_RD_NUMQNZ

Number of Q non-zeros.

D.19 Mark

MSK_MARK_LO

The lower bound is selected for sensitivity analysis.

MSK_MARK_UP

The upper bound is selected for sensitivity analysis.

D.20 Continuous mixed-integer solution type

MSK_MIO_CONT_SOL_NONE

No interior-point or basic solution are reported when the mixed-integer optimizer is used.

MSK_MIO_CONT_SOL_ROOT

The reported interior-point and basic solutions are a solution to the root node problem when mixed-integer optimizer is used.

MSK_MIO_CONT_SOL_ITG

The reported interior-point and basic solutions are a solution to the problem with all integer variables fixed at the value they have in the integer solution. A solution is only reported in case the problem has a primal feasible solution.

MSK_MIO_CONT_SOL_ITG_REL

In case the problem is primal feasible then the reported interior-point and basic solutions are a solution to the problem with all integer variables fixed at the value they have in the integer solution. If the problem is primal infeasible, then the solution to the root node problem is reported.

D.21 Integer restrictions

MSK_MIO_MODE_IGNORED

The integer constraints are ignored and the problem is solved as a continuous problem.

MSK_MIO_MODE_SATISFIED

Integer restrictions should be satisfied.

MSK_MIO_MODE_LAZY

Integer restrictions should be satisfied if an optimizer is available for the problem.

D.22 Mixed-integer node selection types

MSK_MIO_NODE_SELECTION_FREE

The optimizer decides the node selection strategy.

MSK_MIO_NODE_SELECTION_FIRST

The optimizer employs a depth first node selection strategy.

MSK_MIO_NODE_SELECTION_BEST

The optimizer employs a best bound node selection strategy.

MSK_MIO_NODE_SELECTION_WORST

The optimizer employs a worst bound node selection strategy.

MSK_MIO_NODE_SELECTION_HYBRID

The optimizer employs a hybrid strategy.

MSK_MIO_NODE_SELECTION_PSEUDO

The optimizer employs selects the node based on a pseudo cost estimate.

D.23 MPS file format type

MSK_MPS_FORMAT_STRICT

It is assumed that the input file satisfies the MPS format strictly.

MSK_MPS_FORMAT_RELAXED

It is assumed that the input file satisfies a slightly relaxed version of the MPS format.

MSK_MPS_FORMAT_FREE

It is assumed that the input file satisfies the free MPS format. This implies that spaces are not allowed in names. Otherwise the format is free.

D.24 Message keys

MSK_MSG_READING_FILE

MSK_MSG_WRITING_FILE

MSK_MSG_MPS_SELECTED

D.25 Cone types

MSK_NAME_TYPE_GEN

General names. However, no duplicate and blank names are allowed.

MSK_NAME_TYPE_MPS

MPS type names.

MSK_NAME_TYPE_LP

LP type names.

D.26 Objective sense types

MSK_OBJECTIVE_SENSE_MINIMIZE

The problem should be minimized.

MSK_OBJECTIVE_SENSE_MAXIMIZE

The problem should be maximized.

D.27 On/off

MSK_OFF

Switch the option off.

MSK_ON

Switch the option on.

D.28 Optimizer types

MSK_OPTIMIZER_FREE

The optimizer is chosen automatically.

MSK_OPTIMIZER_INTPNT

The interior-point optimizer is used.

MSK_OPTIMIZER_CONIC

The optimizer for problems having conic constraints.

MSK_OPTIMIZER_PRIMAL_SIMPLEX

The primal simplex optimizer is used.

MSK_OPTIMIZER_DUAL_SIMPLEX

The dual simplex optimizer is used.

MSK_OPTIMIZER_PRIMAL_DUAL_SIMPLEX

The primal dual simplex optimizer is used.

MSK_OPTIMIZER_FREE_SIMPLEX

One of the simplex optimizers is used.

MSK_OPTIMIZER_NETWORK_PRIMAL_SIMPLEX

The network primal simplex optimizer is used. It is only applicable to pure network problems.

MSK_OPTIMIZER_MIXED_INT_CONIC

The mixed-integer optimizer for conic and linear problems.

MSK_OPTIMIZER_MIXED_INT

The mixed-integer optimizer.

MSK_OPTIMIZER_CONCURRENT

The optimizer for nonconvex nonlinear problems.

MSK_OPTIMIZER_NONCONVEX

The optimizer for nonconvex nonlinear problems.

D.29 Ordering strategies

MSK_ORDER_METHOD_FREE

The ordering method is chosen automatically.

MSK_ORDER_METHOD_APPMINLOC

Approximate minimum local fill-in ordering is employed.

MSK_ORDER_METHOD_EXPERIMENTAL

This option should not be used.

MSK_ORDER_METHOD_TRY_GRAPHPAR

Always try the the graph partitioning based ordering.

MSK_ORDER_METHOD_FORCE_GRAPHPAR

Always use the graph partitioning based ordering even if it is worse than the approximate minimum local fill ordering.

MSK_ORDER_METHOD_NONE

No ordering is used.

D.30 Parameter type

MSK_PAR_INVALID_TYPE

Not a valid parameter.

MSK_PAR_DOU_TYPE

Is a double parameter.

MSK_PAR_INT_TYPE

Is an integer parameter.

MSK_PAR_STR_TYPE

Is a string parameter.

D.31 Presolve method.

MSK_PRESOLVE_MODE_OFF

The problem is not presolved before it is optimized.

MSK_PRESOLVE_MODE_ON

The problem is presolved before it is optimized.

MSK_PRESOLVE_MODE_FREE

It is decided automatically whether to presolve before the problem is optimized.

D.32 Problem data items

MSK_PI_VAR

Item is a variable.

MSK_PI_CON

Item is a constraint.

MSK_PI_CONE

Item is a cone.

D.33 Problem types

MSK_PROBTYPE_LO

The problem is a linear optimization problem.

MSK_PROBTYPE_QO

The problem is a quadratic optimization problem.

MSK_PROBTYPE_QCQO

The problem is a quadratically constrained optimization problem.

MSK_PROBTYPE_GECO

General convex optimization.

MSK_PROBTYPE_CONIC

A conic optimization.

MSK_PROBTYPE_MIXED

General nonlinear constraints and conic constraints. This combination can not be solved by MOSEK.

D.34 Problem status keys

MSK_PRO_STA_UNKNOWN

Unknown problem status.

MSK_PRO_STA_PRIM_AND_DUAL_FEAS

The problem is primal and dual feasible.

MSK_PRO_STA_PRIM_FEAS

The problem is primal feasible.

MSK_PRO_STA_DUAL_FEAS

The problem is dual feasible.

MSK_PRO_STA_PRIM_INFEAS

The problem is primal infeasible.

MSK_PRO_STA_DUAL_INFEAS

The problem is dual infeasible.

MSK_PRO_STA_PRIM_AND_DUAL_INFEAS

The problem is primal and dual infeasible.

MSK_PRO_STA_ILL_POSED

The problem is ill-posed. For example, it may be primal and dual feasible but have a positive duality gap.

MSK_PRO_STA_NEAR_PRIM_AND_DUAL_FEAS

The problem is at least nearly primal and dual feasible.

MSK_PRO_STA_NEAR_PRIM_FEAS

The problem is at least nearly primal feasible.

MSK_PRO_STA_NEAR_DUAL_FEAS

The problem is at least nearly dual feasible.

MSK_PRO_STA_PRIM_INFEAS_OR_UNBOUNDED

The problem is either primal infeasible or unbounded. This may occur for mixed-integer problems.

D.35 Response code type

MSK_RESPONSE_OK

The response code is OK.

MSK_RESPONSE_WRN

The response code is a warning.

MSK_RESPONSE_TRM

The response code is an optimizer termination status.

MSK_RESPONSE_ERR

The response code is an error.

MSK_RESPONSE_UNK

The response code does not belong to any class.

D.36 Scaling type

MSK_SCALING_METHOD_POW2

Scales only with power of 2 leaving the mantissa untouched.

MSK_SCALING_METHOD_FREE

The optimizer chooses the scaling heuristic.

D.37 Scaling type

MSK_SCALING_FREE

The optimizer chooses the scaling heuristic.

MSK_SCALING_NONE

No scaling is performed.

MSK_SCALING_MODERATE

A conservative scaling is performed.

MSK_SCALING_AGGRESSIVE

A very aggressive scaling is performed.

D.38 Sensitivity types

MSK_SENSITIVITY_TYPE_BASIS

Basis sensitivity analysis is performed.

MSK_SENSITIVITY_TYPE_OPTIMAL_PARTITION

Optimal partition sensitivity analysis is performed.

D.39 Degeneracy strategies

MSK_SIM_DEGEN_NONE

The simplex optimizer should use no degeneration strategy.

MSK_SIM_DEGEN_FREE

The simplex optimizer chooses the degeneration strategy.

MSK_SIM_DEGEN_AGGRESSIVE

The simplex optimizer should use an aggressive degeneration strategy.

MSK_SIM_DEGEN_MODERATE

The simplex optimizer should use a moderate degeneration strategy.

MSK_SIM_DEGEN_MINIMUM

The simplex optimizer should use a minimum degeneration strategy.

D.40 Exploit duplicate columns.

MSK_SIM_EXPLOIT_DUPVEC_OFF

Disallow the simplex optimizer to exploit duplicated columns.

MSK_SIM_EXPLOIT_DUPVEC_ON

Allow the simplex optimizer to exploit duplicated columns.

MSK_SIM_EXPLOIT_DUPVEC_FREE

The simplex optimizer can choose freely.

D.41 Hot-start type employed by the simplex optimizer

MSK_SIM_HOTSTART_NONE

The simplex optimizer performs a coldstart.

MSK_SIM_HOTSTART_FREE

The simplex optimizer chooses the hot-start type.

MSK_SIM_HOTSTART_STATUS_KEYS

Only the status keys of the constraints and variables are used to choose the type of hot-start.

D.42 Problem reformulation.

MSK_SIM_REFORMULATION_OFF

Disallow the simplex optimizer to reformulate the problem.

MSK_SIM_REFORMULATION_ON

Allow the simplex optimizer to reformulate the problem.

MSK_SIM_REFORMULATION_FREE

The simplex optimizer can choose freely.

MSK_SIM_REFORMULATION_AGGRESSIVE

The simplex optimizer should use an aggressive reformulation strategy.

D.43 Simplex selection strategy

MSK_SIM_SELECTION_FREE

The optimizer chooses the pricing strategy.

MSK_SIM_SELECTION_FULL

The optimizer uses full pricing.

MSK_SIM_SELECTION_ASE

The optimizer uses approximate steepest-edge pricing.

MSK_SIM_SELECTION_DEVEX

The optimizer uses devex steepest-edge pricing (or if it is not available an approximate steep-edge selection).

MSK_SIM_SELECTION_SE

The optimizer uses steepest-edge selection (or if it is not available an approximate steep-edge selection).

MSK_SIM_SELECTION_PARTIAL

The optimizer uses a partial selection approach. The approach is usually beneficial if the number of variables is much larger than the number of constraints.

D.44 Solution items

MSK_SOL_ITEM_XC

Solution for the constraints.

MSK_SOL_ITEM_XX

Variable solution.

MSK_SOL_ITEM_Y

Lagrange multipliers for equations.

MSK_SOL_ITEM_SLC

Lagrange multipliers for lower bounds on the constraints.

MSK_SOL_ITEM_SUC

Lagrange multipliers for upper bounds on the constraints.

MSK_SOL_ITEM_SLX

Lagrange multipliers for lower bounds on the variables.

MSK_SOL_ITEM_SUX

Lagrange multipliers for upper bounds on the variables.

MSK_SOL_ITEM_SNX

Lagrange multipliers corresponding to the conic constraints on the variables.

D.45 Solution status keys

MSK_SOL_STA_UNKNOWN

Status of the solution is unknown.

MSK_SOL_STA_OPTIMAL

The solution is optimal.

MSK_SOL_STA_PRIM_FEAS

The solution is primal feasible.

MSK_SOL_STA_DUAL_FEAS

The solution is dual feasible.

MSK_SOL_STA_PRIM_AND_DUAL_FEAS

The solution is both primal and dual feasible.

MSK_SOL_STA_PRIM_INFEAS_CER

The solution is a certificate of primal infeasibility.

MSK_SOL_STA_DUAL_INFEAS_CER

The solution is a certificate of dual infeasibility.

MSK_SOL_STA_NEAR_OPTIMAL

The solution is nearly optimal.

MSK_SOL_STA_NEAR_PRIM_FEAS

The solution is nearly primal feasible.

MSK_SOL_STA_NEAR_DUAL_FEAS

The solution is nearly dual feasible.

MSK_SOL_STA_NEAR_PRIM_AND_DUAL_FEAS

The solution is nearly both primal and dual feasible.

MSK_SOL_STA_NEAR_PRIM_INFEAS_CER

The solution is almost a certificate of primal infeasibility.

MSK_SOL_STA_NEAR_DUAL_INFEAS_CER

The solution is almost a certificate of dual infeasibility.

MSK_SOL_STA_INTEGER_OPTIMAL

The primal solution is integer optimal.

MSK_SOL_STA_NEAR_INTEGER_OPTIMAL

The primal solution is near integer optimal.

D.46 Solution types

MSK_SOL_ITR

The interior solution.

MSK_SOL_BAS

The basic solution.

MSK_SOL_ITG

The integer solution.

D.47 Solve primal or dual form

MSK_SOLVE_FREE

The optimizer is free to solve either the primal or the dual problem.

MSK_SOLVE_PRIMAL

The optimizer should solve the primal problem.

MSK_SOLVE_DUAL

The optimizer should solve the dual problem.

D.48 Status keys

MSK_SK_UNK

The status for the constraint or variable is unknown.

MSK_SK_BAS

The constraint or variable is in the basis.

MSK_SK_SUPBAS

The constraint or variable is super basic.

MSK_SK_LOW

The constraint or variable is at its lower bound.

MSK_SK_UPR

The constraint or variable is at its upper bound.

MSK_SK_FIX

The constraint or variable is fixed.

MSK_SK_INF

The constraint or variable is infeasible in the bounds.

D.49 Starting point types

MSK_STARTING_POINT_FREE

The starting point is chosen automatically.

MSK_STARTING_POINT_GUESS

The optimizer guesses a starting point.

MSK_STARTING_POINT_CONSTANT

The optimizer constructs a starting point by assigning a constant value to all primal and dual variables. This starting point is normally robust.

MSK_STARTING_POINT_SATISFY_BOUNDS

The starting point is chosen to satisfy all the simple bounds on nonlinear variables. If this starting point is employed, then more care than usual should be employed when choosing the bounds on the nonlinear variables. In particular very tight bounds should be avoided.

D.50 Stream types

MSK_STREAM_LOG

Log stream. Contains the aggregated contents of all other streams. This means that a message written to any other stream will also be written to this stream.

MSK_STREAM_MSG

Message stream. Log information relating to performance and progress of the optimization is written to this stream.

MSK_STREAM_ERR

Error stream. Error messages are written to this stream.

MSK_STREAM_WRN

Warning stream. Warning messages are written to this stream.

D.51 Cone types

MSK_SYMMAT_TYPE_SPARSE

Sparse symmetric matrix.

D.52 Transposed matrix.

MSK_TRANSPOSE_NO

No transpose is applied.

MSK_TRANSPOSE_YES

A transpose is applied.

D.53 Triangular part of a symmetric matrix.

MSK_UPLO_LO

Lower part.

MSK_UPLO_UP

Upper part

D.54 Integer values

MSK_LICENSE_BUFFER_LENGTH

The length of a license key buffer.

MSK_MAX_STR_LEN

Maximum string length allowed in MOSEK.

D.55 Variable types

MSK_VAR_TYPE_CONT

Is a continuous variable.

MSK_VAR_TYPE_INT

Is an integer variable.

D.56 XML writer output mode

MSK_WRITE_XML_MODE_ROW

Write in row order.

MSK_WRITE_XML_MODE_COL

Write in column order.

Appendix E

Mosek file formats

MOSEK supports a range of problem and solution formats. The Task format is MOSEK's native binary format and it supports all features that MOSEK supports. OPF is the corresponding ASCII format and this supports nearly all features (everything except semidefinite problems). In general, the text formats are significantly slower to read, but they can be examined and edited directly in any text editor.

MOSEK supports GZIP compression of files. Problem files with an additional ".gz" extension are assumed to be compressed when read, and is automatically compressed when written. For example, a file called

`problem.mps.gz`

will be read as a GZIP compressed MPS file.

E.1 The MPS file format

MOSEK supports the standard MPS format with some extensions. For a detailed description of the MPS format see the book by Nazareth [2].

E.1.1 MPS file structure

The version of the MPS format supported by MOSEK allows specification of an optimization problem on the form

$$\begin{array}{llll} l^c & \leq & Ax + q(x) & \leq & u^c, \\ l^x & \leq & x & \leq & u^x, \\ & & x \in \mathcal{C}, & & \\ & & x_{\mathcal{J}} \text{ integer}, & & \end{array} \tag{E.1}$$

where

- $x \in \mathbb{R}^n$ is the vector of decision variables.
- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.
- $q : \mathbb{R}^n \rightarrow \mathbb{R}$ is a vector of quadratic functions. Hence,

$$q_i(x) = 1/2 x^T Q^i x$$

where it is assumed that

$$Q^i = (Q^i)^T.$$

Please note the explicit 1/2 in the quadratic term and that Q^i is required to be symmetric.

- \mathcal{C} is a convex cone.
- $\mathcal{J} \subseteq \{1, 2, \dots, n\}$ is an index set of the integer-constrained variables.

An MPS file with one row and one column can be illustrated like this:

```
*          1          2          3          4          5          6
*23456789012345678901234567890123456789012345678901234567890
NAME          [name]
OBJSENSE
    [objsense]
OBJNAME
    [objname]
ROWS
    ? [cname1]
COLUMNNS
    [vname1] [cname1] [value1] [vname3] [value2]
RHS
    [name] [cname1] [value1] [cname2] [value2]
RANGES
    [name] [cname1] [value1] [cname2] [value2]
QSECTION
    [vname1] [vname2] [value1] [vname3] [value2]
BOUNDS
    ?? [name] [vname1] [value1]
CSECTION
    [vname1] [kname1] [value1] [ktype]
ENDATA
```

Here the names in capitals are keywords of the MPS format and names in brackets are custom defined names or values. A couple of notes on the structure:

Fields:

All items surrounded by brackets appear in *fields*. The fields named "valueN" are numerical values. Hence, they must have the format

```
[+|-]XXXXXXXX.XXXXXX[[e|E][+|-]XXX]
```

where

```
x = [0|1|2|3|4|5|6|7|8|9].
```

Sections:

The MPS file consists of several sections where the names in capitals indicate the beginning of a new section. For example, COLUMNS denotes the beginning of the columns section.

Comments:

Lines starting with an "*" are comment lines and are ignored by MOSEK.

Keys:

The question marks represent keys to be specified later.

Extensions:

The sections QSECTION and CSECTION are MOSEK specific extensions of the MPS format.

The standard MPS format is a fixed format, i.e. everything in the MPS file must be within certain fixed positions. MOSEK also supports a *free format*. See Section [E.1.5](#) for details.

E.1.1.1 Linear example lo1.mps

A concrete example of a MPS file is presented below:

```
* File: lo1.mps
NAME          lo1
OBJSENSE
    MAX
ROWS
N  obj
E  c1
G  c2
L  c3
COLUMNS
    x1      obj      3
    x1      c1       3
    x1      c2       2
    x2      obj      1
    x2      c1       1
    x2      c2       1
    x2      c3       2
    x3      obj      5
    x3      c1       2
    x3      c2       3
    x4      obj      1
    x4      c2       1
    x4      c3       3
```

```

RHS
  rhs      c1      30
  rhs      c2      15
  rhs      c3      25
RANGES
BOUNDS
  UP bound  x2      10
ENDATA

```

Subsequently each individual section in the MPS format is discussed.

E.1.1.2 NAME

In this section a name (`[name]`) is assigned to the problem.

E.1.1.3 OBJSENSE (optional)

This is an optional section that can be used to specify the sense of the objective function. The **OBJSENSE** section contains one line at most which can be one of the following

```

MIN
MINIMIZE
MAX
MAXIMIZE

```

It should be obvious what the implication is of each of these four lines.

E.1.1.4 OBJNAME (optional)

This is an optional section that can be used to specify the name of the row that is used as objective function. The **OBJNAME** section contains one line at most which has the form

```
objname
```

`objname` should be a valid row name.

E.1.1.5 ROWS

A record in the **ROWS** section has the form

```
? [cname1]
```

where the requirements for the fields are as follows:

Field	Starting position	Maximum width	Required	Description
?	2	1	Yes	Constraint key
[cname1]	5	8	Yes	Constraint name

Hence, in this section each constraint is assigned an unique name denoted by `[cname1]`. Please note that `[cname1]` starts in position 5 and the field can be at most 8 characters wide. An initial key (?)

must be present to specify the type of the constraint. The key can have the values E, G, L, or N with the following interpretation:

Constraint type	l_i^c	u_i^c
E	finite	l_i^c
G	finite	∞
L	$-\infty$	finite
N	$-\infty$	∞

In the MPS format an objective vector is not specified explicitly, but one of the constraints having the key N will be used as the objective vector c . In general, if multiple N type constraints are specified, then the first will be used as the objective vector c .

E.1.1.6 COLUMNS

In this section the elements of A are specified using one or more records having the form

[vname1] [cname1] [value1] [cname2] [value2]

where the requirements for each field are as follows:

Field	Starting position	Maximum width	Re- quired	Description
[vname1]	5	8	Yes	Variable name
[cname1]	15	8	Yes	Constraint name
[value1]	25	12	Yes	Numerical value
[cname2]	40	8	No	Constraint name
[value2]	50	12	No	Numerical value

Hence, a record specifies one or two elements a_{ij} of A using the principle that [vname1] and [cname1] determines j and i respectively. Please note that [cname1] must be a constraint name specified in the ROWS section. Finally, [value1] denotes the numerical value of a_{ij} . Another optional element is specified by [cname2], and [value2] for the variable specified by [vname1]. Some important comments are:

- All elements belonging to one variable must be grouped together.
- Zero elements of A should not be specified.
- At least one element for each variable should be specified.

E.1.1.7 RHS (optional)

A record in this section has the format

[name] [cname1] [value1] [cname2] [value2]

where the requirements for each field are as follows:

Field	Starting position	Maximum width	Re- quired	Description
[name]	5	8	Yes	Name of the RHS vector
[cname1]	15	8	Yes	Constraint name
[value1]	25	12	Yes	Numerical value
[cname2]	40	8	No	Constraint name
[value2]	50	12	No	Numerical value

The interpretation of a record is that [name] is the name of the RHS vector to be specified. In general, several vectors can be specified. [cname1] denotes a constraint name previously specified in the ROWS section. Now, assume that this name has been assigned to the i th constraint and v_1 denotes the value specified by [value1], then the interpretation of v_1 is:

Constraint type	l_i^c	u_i^c
E	v_1	v_1
G	v_1	
L		v_1
N		

An optional second element is specified by [cname2] and [value2] and is interpreted in the same way. Please note that it is not necessary to specify zero elements, because elements are assumed to be zero.

E.1.1.8 RANGES (optional)

A record in this section has the form

[name] [cname1] [value1] [cname2] [value2]

where the requirements for each fields are as follows:

Field	Starting position	Maximum width	Re- quired	Description
[name]	5	8	Yes	Name of the RANGE vector
[cname1]	15	8	Yes	Constraint name
[value1]	25	12	Yes	Numerical value
[cname2]	40	8	No	Constraint name
[value2]	50	12	No	Numerical value

The records in this section are used to modify the bound vectors for the constraints, i.e. the values in l^c and u^c . A record has the following interpretation: [name] is the name of the RANGE vector and [cname1] is a valid constraint name. Assume that [cname1] is assigned to the i th constraint and let v_1 be the value specified by [value1], then a record has the interpretation:

Constraint type	Sign of v_1	l_i^c	u_i^c
E	-	$u_i^c + v_1$	
E	+		$l_i^c + v_1$
G	- or +		$l_i^c + v_1 $
L	- or +	$u_i^c - v_1 $	
N			

E.1.1.9 QSECTION (optional)

Within the QSECTION the label [cname1] must be a constraint name previously specified in the ROWS section. The label [cname1] denotes the constraint to which the quadratic term belongs. A record in the QSECTION has the form

[vname1] [vname2] [value1] [vname3] [value2]

where the requirements for each field are:

Field	Starting position	Maximum width	Re- quired	Description
[vname1]	5	8	Yes	Variable name
[vname2]	15	8	Yes	Variable name
[value1]	25	12	Yes	Numerical value
[vname3]	40	8	No	Variable name
[value2]	50	12	No	Numerical value

A record specifies one or two elements in the lower triangular part of the Q^i matrix where [cname1] specifies the i . Hence, if the names [vname1] and [vname2] have been assigned to the k th and j th variable, then Q_{kj}^i is assigned the value given by [value1]. An optional second element is specified in the same way by the fields [vname1], [vname3], and [value2].

The example

$$\begin{array}{ll}
 \text{minimize} & -x_2 + 0.5(2x_1^2 - 2x_1x_3 + 0.2x_2^2 + 2x_3^2) \\
 \text{subject to} & x_1 + x_2 + x_3 \geq 1, \\
 & x \geq 0
 \end{array}$$

has the following MPS file representation

```

* File: qo1.mps
NAME          qo1
ROWS
  N  obj
  G  c1
COLUMNS
  x1      c1      1.0
  x2      obj     -1.0
  x2      c1      1.0
  x3      c1      1.0
RHS
  rhs     c1      1.0

```

```

QSECTION      obj
  x1          x1          2.0
  x1          x3         -1.0
  x2          x2          0.2
  x3          x3          2.0
ENDATA

```

Regarding the QSECTIONs please note that:

- Only one QSECTION is allowed for each constraint.
- The QSECTIONs can appear in an arbitrary order after the COLUMNS section.
- All variable names occurring in the QSECTION must already be specified in the COLUMNS section.
- All entries specified in a QSECTION are assumed to belong to the lower triangular part of the quadratic term of Q .

E.1.1.10 BOUNDS (optional)

In the BOUNDS section changes to the default bounds vectors l^x and u^x are specified. The default bounds vectors are $l^x = 0$ and $u^x = \infty$. Moreover, it is possible to specify several sets of bound vectors. A record in this section has the form

```
?? [name]    [vname1]    [value1]
```

where the requirements for each field are:

Field	Starting position	Maximum width	Required	Description
??	2	2	Yes	Bound key
[name]	5	8	Yes	Name of the BOUNDS vector
[vname1]	15	8	Yes	Variable name
[value1]	25	12	No	Numerical value

Hence, a record in the BOUNDS section has the following interpretation: [name] is the name of the bound vector and [vname1] is the name of the variable which bounds are modified by the record. ?? and [value1] are used to modify the bound vectors according to the following table:

??	l_j^x	u_j^x	Made integer (added to \mathcal{J})
FR	$-\infty$	∞	No
FX	v_1	v_1	No
LO	v_1	unchanged	No
MI	$-\infty$	unchanged	No
PL	unchanged	∞	No
UP	unchanged	v_1	No
BV	0	1	Yes
LI	$[v_1]$	unchanged	Yes
UI	unchanged	$[v_1]$	Yes

v_1 is the value specified by [value1].

E.1.1.11 CSECTION (optional)

The purpose of the CSECTION is to specify the constraint

$$x \in \mathcal{C}.$$

in (E.1).

It is assumed that \mathcal{C} satisfies the following requirements. Let

$$x^t \in \mathbb{R}^{n^t}, \quad t = 1, \dots, k$$

be vectors comprised of parts of the decision variables x so that each decision variable is a member of exactly **one** vector x^t , for example

$$x^1 = \begin{bmatrix} x_1 \\ x_4 \\ x_7 \end{bmatrix} \quad \text{and} \quad x^2 = \begin{bmatrix} x_6 \\ x_5 \\ x_3 \\ x_2 \end{bmatrix}.$$

Next define

$$\mathcal{C} := \{x \in \mathbb{R}^n : x^t \in \mathcal{C}_t, \quad t = 1, \dots, k\}$$

where \mathcal{C}_t must have one of the following forms

- \mathbb{R} set:

$$\mathcal{C}_t = \{x \in \mathbb{R}^{n^t}\}.$$

- Quadratic cone:

$$\mathcal{C}_t = \left\{ x \in \mathbb{R}^{n^t} : x_1 \geq \sqrt{\sum_{j=2}^{n^t} x_j^2} \right\}. \quad (\text{E.2})$$

- Rotated quadratic cone:

$$\mathcal{C}_t = \left\{ x \in \mathbb{R}^{n^t} : 2x_1x_2 \geq \sum_{j=3}^{n^t} x_j^2, \quad x_1, x_2 \geq 0 \right\}. \quad (\text{E.3})$$

In general, only quadratic and rotated quadratic cones are specified in the MPS file whereas membership of the \mathbb{R} set is not. If a variable is not a member of any other cone then it is assumed to be a member of an \mathbb{R} cone.

Next, let us study an example. Assume that the quadratic cone

$$x_4 \geq \sqrt{x_5^2 + x_8^2} \quad (\text{E.4})$$

and the rotated quadratic cone

$$2x_3x_7 \geq x_1^2 + x_0^2, \quad x_3, x_7 \geq 0, \quad (\text{E.5})$$

should be specified in the MPS file. One CSECTION is required for each cone and they are specified as follows:

```

*          1          2          3          4          5          6
*23456789012345678901234567890123456789012345678901234567890
CSECTION      konea      0.0      QUAD
  x4
  x5
  x8
CSECTION      koneb      0.0      RQUAD
  x7
  x3
  x1
  x0

```

This first CSECTION specifies the cone (E.4) which is given the name `konea`. This is a quadratic cone which is specified by the keyword `QUAD` in the CSECTION header. The 0.0 value in the CSECTION header is not used by the `QUAD` cone.

The second CSECTION specifies the rotated quadratic cone (E.5). Please note the keyword `RQUAD` in the CSECTION which is used to specify that the cone is a rotated quadratic cone instead of a quadratic cone. The 0.0 value in the CSECTION header is not used by the `RQUAD` cone.

In general, a CSECTION header has the format

```
CSECTION      [kname1]      [value1]      [ktype]
```

where the requirement for each field are as follows:

Field	Starting position	Maximum width	Required	Description
[kname1]	5	8	Yes	Name of the cone
[value1]	15	12	No	Cone parameter
[ktype]	25		Yes	Type of the cone.

The possible cone type keys are:

Cone type key	Members	Interpretation.
QUAD	≥ 1	Quadratic cone i.e. (E.2).
RQUAD	≥ 2	Rotated quadratic cone i.e. (E.3).

Please note that a quadratic cone must have at least one member whereas a rotated quadratic cone must have at least two members. A record in the CSECTION has the format

[vname1]

where the requirements for each field are

Field	Starting position	Maximum width	Required	Description
[vname1]	2	8	Yes	A valid variable name

The most important restriction with respect to the CSECTION is that a variable must occur in only one CSECTION.

E.1.1.12 ENDATA

This keyword denotes the end of the MPS file.

E.1.2 Integer variables

Using special bound keys in the BOUNDS section it is possible to specify that some or all of the variables should be integer-constrained i.e. be members of \mathcal{J} . However, an alternative method is available.

This method is available only for backward compatibility and we recommend that it is not used. This method requires that markers are placed in the COLUMNS section as in the example:

```
COLUMNS
  x1      obj      -10.0      c1      0.7
  x1      c2        0.5      c3      1.0
  x1      c4        0.1
* Start of integer-constrained variables.
  MARK000  'MARKER'      'INTORG'
  x2      obj      -9.0      c1      1.0
  x2      c2      0.8333333333333333 c3      0.666666667
  x2      c4        0.25
  x3      obj      1.0      c6      2.0
  MARK001  'MARKER'      'INTEND'
* End of integer-constrained variables.
```

Please note that special marker lines are used to indicate the start and the end of the integer variables. Furthermore be aware of the following

- **IMPORTANT:** All variables between the markers are assigned a default lower bound of 0 and a default upper bound of 1. **This may not be what is intended.** If it is not intended, the correct bounds should be defined in the BOUNDS section of the MPS formatted file.
- MOSEK ignores field 1, i.e. MARK0001 and MARK001, however, other optimization systems require them.
- Field 2, i.e. 'MARKER', must be specified including the single quotes. This implies that no row can be assigned the name 'MARKER'.

- Field 3 is ignored and should be left blank.
- Field 4, i.e. 'INTORG' and 'INTEND', must be specified.
- It is possible to specify several such integer marker sections within the COLUMNS section.

E.1.3 General limitations

- An MPS file should be an ASCII file.

E.1.4 Interpretation of the MPS format

Several issues related to the MPS format are not well-defined by the industry standard. However, MOSEK uses the following interpretation:

- If a matrix element in the COLUMNS section is specified multiple times, then the multiple entries are added together.
- If a matrix element in a QSECTION section is specified multiple times, then the multiple entries are added together.

E.1.5 The free MPS format

MOSEK supports a free format variation of the MPS format. The free format is similar to the MPS file format but less restrictive, e.g. it allows longer names. However, it also presents two main limitations:

- By default a line in the MPS file must not contain more than 1024 characters. However, by modifying the parameter `MSK_IPAR_READ_MPS_WIDTH` an arbitrary large line width will be accepted.
- A name must not contain any blanks.

To use the free MPS format instead of the default MPS format the MOSEK parameter `MSK_IPAR_READ_MPS_FORMAT` should be changed.

E.2 The LP file format

MOSEK supports the LP file format with some extensions i.e. MOSEK can read and write LP formatted files.

Please note that the LP format is not a completely well-defined standard and hence different optimization packages may interpret the same LP file in slightly different ways. MOSEK tries to emulate as closely as possible CPLEX's behavior, but tries to stay backward compatible.

The LP file format can specify problems on the form

$$\begin{array}{llll}
\text{minimize/maximize} & & c^T x + \frac{1}{2} q^o(x) & \\
\text{subject to} & l^c \leq & Ax + \frac{1}{2} q(x) \leq & u^c, \\
& l^x \leq & x \leq & u^x, \\
& & x_{\mathcal{J}} \text{ integer,} &
\end{array}$$

where

- $x \in \mathbb{R}^n$ is the vector of decision variables.
- $c \in \mathbb{R}^n$ is the linear term in the objective.
- $q^o : \mathbb{R}^n \rightarrow \mathbb{R}$ is the quadratic term in the objective where

$$q^o(x) = x^T Q^o x$$

and it is assumed that

$$Q^o = (Q^o)^T.$$

- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.
- $q : \mathbb{R}^n \rightarrow \mathbb{R}$ is a vector of quadratic functions. Hence,

$$q_i(x) = x^T Q^i x$$

where it is assumed that

$$Q^i = (Q^i)^T.$$

- $\mathcal{J} \subseteq \{1, 2, \dots, n\}$ is an index set of the integer constrained variables.

E.2.1 The sections

An LP formatted file contains a number of sections specifying the objective, constraints, variable bounds, and variable types. The section keywords may be any mix of upper and lower case letters.

E.2.1.1 The objective

The first section beginning with one of the keywords

```
max
maximum
maximize
min
minimum
minimize
```

defines the objective sense and the objective function, i.e.

$$c^T x + \frac{1}{2} x^T Q^o x.$$

The objective may be given a name by writing

```
myname:
```

before the expressions. If no name is given, then the objective is named `obj`.

The objective function contains linear and quadratic terms. The linear terms are written as

```
4 x1 + x2 - 0.1 x3
```

and so forth. The quadratic terms are written in square brackets (`[]`) and are either squared or multiplied as in the examples

```
x1^2
```

and

```
x1 * x2
```

There may be zero or more pairs of brackets containing quadratic expressions.

An example of an objective section is:

```
minimize
myobj: 4 x1 + x2 - 0.1 x3 + [ x1^2 + 2.1 x1 * x2 ]/2
```

Please note that the quadratic expressions are multiplied with $\frac{1}{2}$, so that the above expression means

$$\text{minimize } 4x_1 + x_2 - 0.1 \cdot x_3 + \frac{1}{2}(x_1^2 + 2.1 \cdot x_1 \cdot x_2)$$

If the same variable occurs more than once in the linear part, the coefficients are added, so that `4 x1 + 2 x1` is equivalent to `6 x1`. In the quadratic expressions `x1 * x2` is equivalent to `x2 * x1` and as in the linear part, if the same variables multiplied or squared occur several times their coefficients are added.

E.2.1.2 The constraints

The second section beginning with one of the keywords

```
subj to
subject to
s.t.
```

```
st
```

defines the linear constraint matrix (A) and the quadratic matrices (Q^i).

A constraint contains a name (optional), expressions adhering to the same rules as in the objective and a bound:

```
subject to
con1: x1 + x2 + [ x3^2 ]/2 <= 5.1
```

The bound type (here \leq) may be any of $<$, \leq , $=$, $>$, \geq ($<$ and \leq mean the same), and the bound may be any number.

In the standard LP format it is not possible to define more than one bound, but MOSEK supports defining ranged constraints by using double-colon (':') instead of a single-colon (':') after the constraint name, i.e.

$$-5 \leq x_1 + x_2 \leq 5 \tag{E.6}$$

may be written as

```
con:: -5 < x_1 + x_2 < 5
```

By default MOSEK writes ranged constraints this way.

If the files must adhere to the LP standard, ranged constraints must either be split into upper bounded and lower bounded constraints or be written as an equality with a slack variable. For example the expression (E.6) may be written as

$$x_1 + x_2 - sl_1 = 0, -5 \leq sl_1 \leq 5.$$

E.2.1.3 Bounds

Bounds on the variables can be specified in the bound section beginning with one of the keywords

```
bound
bounds
```

The bounds section is optional but should, if present, follow the **subject to** section. All variables listed in the bounds section must occur in either the objective or a constraint.

The default lower and upper bounds are 0 and $+\infty$. A variable may be declared free with the keyword **free**, which means that the lower bound is $-\infty$ and the upper bound is $+\infty$. Furthermore it may be assigned a finite lower and upper bound. The bound definitions for a given variable may be written in one or two lines, and bounds can be any number or $\pm\infty$ (written as **+inf/-inf/+infinity/-infinity**) as in the example

```
bounds
x1 free
x2 <= 5
0.1 <= x2
x3 = 42
2 <= x4 < +inf
```

E.2.1.4 Variable types

The final two sections are optional and must begin with one of the keywords

```
bin
binaries
binary
```

and

```
gen
general
```

Under **general** all integer variables are listed, and under **binary** all binary (integer variables with bounds 0 and 1) are listed:

```
general
x1 x2
binary
x3 x4
```

Again, all variables listed in the binary or general sections must occur in either the objective or a constraint.

E.2.1.5 Terminating section

Finally, an LP formatted file must be terminated with the keyword

```
end
```

E.2.1.6 Linear example lo1.lp

A simple example of an LP file is:

```
\ File: lo1.lp
maximize
obj: 3 x1 + x2 + 5 x3 + x4
subject to
c1: 3 x1 + x2 + 2 x3 = 30
c2: 2 x1 + x2 + 3 x3 + x4 >= 15
c3: 2 x2 + 3 x4 <= 25
bounds
0 <= x1 <= +infinity
0 <= x2 <= 10
0 <= x3 <= +infinity
0 <= x4 <= +infinity
end
```

E.2.1.7 Mixed integer example milo1.lp

```
maximize
obj: x1 + 6.4e-01 x2
subject to
c1: 5e+01 x1 + 3.1e+01 x2 <= 2.5e+02
c2: 3e+00 x1 - 2e+00 x2 >= -4e+00
```



```

bounds
  0 <= x1 <= +infinity
  0 <= x2 <= +infinity
general
  x1 x2
end

```

E.2.2 LP format peculiarities

E.2.2.1 Comments

Anything on a line after a `"\"` is ignored and is treated as a comment.

E.2.2.2 Names

A name for an objective, a constraint or a variable may contain the letters a-z, A-Z, the digits 0-9 and the characters

```
! " # $ % & ( ) / , . ; : ? @ _ ' ` | ~
```

The first character in a name must not be a number, a period or the letter 'e' or 'E'. Keywords must not be used as names.

MOSEK accepts any character as valid for names, except `'\0'`. When writing a name that is not allowed in LP files, it is changed and a warning is issued.

The algorithm for making names LP valid works as follows: The name is interpreted as an `utf-8` string. For a unicode character `c`:

- If `c == '_'` (underscore), the output is `'__'` (two underscores).
- If `c` is a valid LP name character, the output is just `c`.
- If `c` is another character in the ASCII range, the output is `_XX`, where `XX` is the hexadecimal code for the character.
- If `c` is a character in the range 127—65535, the output is `_uXXXX`, where `XXXX` is the hexadecimal code for the character.
- If `c` is a character above 65535, the output is `_UXXXXXXXX`, where `XXXXXXXX` is the hexadecimal code for the character.

Invalid `utf-8` substrings are escaped as `'_XX'`, and if a name starts with a period, 'e' or 'E', that character is escaped as `'_XX'`.

E.2.2.3 Variable bounds

Specifying several upper or lower bounds on one variable is possible but MOSEK uses only the tightest bounds. If a variable is fixed (with `=`), then it is considered the tightest bound.

E.2.2.4 MOSEK specific extensions to the LP format

Some optimization software packages employ a more strict definition of the LP format than the one used by MOSEK. The limitations imposed by the strict LP format are the following:

- Quadratic terms in the constraints are not allowed.
- Names can be only 16 characters long.
- Lines must not exceed 255 characters in length.

If an LP formatted file created by MOSEK should satisfy the strict definition, then the parameter

MSK_IPAR.WRITE_LP_STRICT_FORMAT

should be set; note, however, that some problems cannot be written correctly as a strict LP formatted file. For instance, all names are truncated to 16 characters and hence they may lose their uniqueness and change the problem.

To get around some of the inconveniences converting from other problem formats, MOSEK allows lines to contain 1024 characters and names may have any length (shorter than the 1024 characters).

Internally in MOSEK names may contain any (printable) character, many of which cannot be used in LP names. Setting the parameters

MSK_IPAR.READ_LP_QUOTED_NAMES

and

MSK_IPAR.WRITE_LP_QUOTED_NAMES

allows MOSEK to use quoted names. The first parameter tells MOSEK to remove quotes from quoted names e.g., "x1", when reading LP formatted files. The second parameter tells MOSEK to put quotes around any semi-illegal name (names beginning with a number or a period) and fully illegal name (containing illegal characters). As double quote is a legal character in the LP format, quoting semi-illegal names makes them legal in the pure LP format as long as they are still shorter than 16 characters. Fully illegal names are still illegal in a pure LP file.

E.2.3 The strict LP format

The LP format is not a formal standard and different vendors have slightly different interpretations of the LP format. To make MOSEK's definition of the LP format more compatible with the definitions of other vendors, use the parameter setting

MSK_IPAR.WRITE_LP_STRICT_FORMAT = MSK_ON

This setting may lead to truncation of some names and hence to an invalid LP file. The simple solution to this problem is to use the parameter setting

```
MSK_IPAR.WRITE_GENERIC_NAMES = MSK_ON
```

which will cause all names to be renamed systematically in the output file.

E.2.4 Formatting of an LP file

A few parameters control the visual formatting of LP files written by MOSEK in order to make it easier to read the files. These parameters are

```
MSK_IPAR.WRITE_LP_LINE_WIDTH
```

```
MSK_IPAR.WRITE_LP_TERMS_PER_LINE
```

The first parameter sets the maximum number of characters on a single line. The default value is 80 corresponding roughly to the width of a standard text document.

The second parameter sets the maximum number of terms per line; a term means a sign, a coefficient, and a name (for example "+ 42 elephants"). The default value is 0, meaning that there is no maximum.

E.2.4.1 Speeding up file reading

If the input file should be read as fast as possible using the least amount of memory, then it is important to tell MOSEK how many non-zeros, variables and constraints the problem contains. These values can be set using the parameters

```
MSK_IPAR.READ_CON
```

```
MSK_IPAR.READ_VAR
```

```
MSK_IPAR.READ_ANZ
```

```
MSK_IPAR.READ_QNZ
```

E.2.4.2 Unnamed constraints

Reading and writing an LP file with MOSEK may change it superficially. If an LP file contains unnamed constraints or objective these are given their generic names when the file is read (however unnamed constraints in MOSEK are written without names).

E.3 The OPF format

The Optimization Problem Format (OPF) is an alternative to LP and MPS files for specifying optimization problems. It is row-oriented, inspired by the CPLEX LP format.

Apart from containing objective, constraints, bounds etc. it may contain complete or partial solutions, comments and extra information relevant for solving the problem. It is designed to be easily read and modified by hand and to be forward compatible with possible future extensions.

E.3.1 Intended use

The OPF file format is meant to replace several other files:

- The LP file format. Any problem that can be written as an LP file can be written as an OPF file to; furthermore it naturally accommodates ranged constraints and variables as well as arbitrary characters in names, fixed expressions in the objective, empty constraints, and conic constraints.
- Parameter files. It is possible to specify integer, double and string parameters along with the problem (or in a separate OPF file).
- Solution files. It is possible to store a full or a partial solution in an OPF file and later reload it.

E.3.2 The file format

The format uses tags to structure data. A simple example with the basic sections may look like this:

```
[comment]
  This is a comment. You may write almost anything here...
[/comment]

# This is a single-line comment.

[objective min 'myobj']
  x + 3 y + x^2 + 3 y^2 + z + 1
[/objective]

[constraints]
  [con 'con01'] 4 <= x + y  [/con]
[/constraints]

[bounds]
  [b] -10 <= x,y <= 10  [/b]

  [cone quad] x,y,z [/cone]
[/bounds]
```

A scope is opened by a tag of the form `[tag]` and closed by a tag of the form `[/tag]`. An opening tag may accept a list of unnamed and named arguments, for examples

```
[tag value] tag with one unnamed argument [/tag]
[tag arg=value] tag with one named argument in quotes [/tag]
```

Unnamed arguments are identified by their order, while named arguments may appear in any order, but never before an unnamed argument. The `value` can be a quoted, single-quoted or double-quoted text string, i.e.

```
[tag 'value']      single-quoted value [/tag]
[tag arg='value']  single-quoted value [/tag]
```

```
[tag "value"]      double-quoted value [/tag]
[tag arg="value"] double-quoted value [/tag]
```

E.3.2.1 Sections

The recognized tags are

- **[comment]** A comment section. This can contain *almost* any text: Between single quotes (') or double quotes (") any text may appear. Outside quotes the markup characters ([and]) must be prefixed by backslashes. Both single and double quotes may appear alone or inside a pair of quotes if it is prefixed by a backslash.
- **[objective]** The objective function: This accepts one or two parameters, where the first one (in the above example 'min') is either **min** or **max** (regardless of case) and defines the objective sense, and the second one (above 'myobj'), if present, is the objective name. The section may contain linear and quadratic expressions.

If several objectives are specified, all but the last are ignored.

- **[constraints]** This does not directly contain any data, but may contain the subsection 'con' defining a linear constraint.

[con] defines a single constraint; if an argument is present ([con NAME]) this is used as the name of the constraint, otherwise it is given a null-name. The section contains a constraint definition written as linear and quadratic expressions with a lower bound, an upper bound, with both or with an equality. Examples:

```
[constraints]
[con 'con1'] 0 <= x + y      [/con]
[con 'con2'] 0 >= x + y      [/con]
[con 'con3'] 0 <= x + y <= 10 [/con]
[con 'con4']      x + y = 10 [/con]
[/constraints]
```

Constraint names are unique. If a constraint is specified which has the same name as a previously defined constraint, the new constraint replaces the existing one.

- **[bounds]** This does not directly contain any data, but may contain the subsections 'b' (linear bounds on variables) and **cone** (quadratic cone).

- **[b]**. Bound definition on one or several variables separated by comma (','). An upper or lower bound on a variable replaces any earlier defined bound on that variable. If only one bound (upper or lower) is given only this bound is replaced. This means that upper and lower bounds can be specified separately. So the OPF bound definition:

```
[b] x,y >= -10 [/b]
[b] x,y <= 10  [/b]
```

results in the bound

$$-10 \leq x, y \leq 10.$$

- **[cone]**. Currently, the supported cones are the *quadratic cone* and the *rotated quadratic cone* (see section 5.3). A conic constraint is defined as a set of variables which belongs to a single unique cone.

A quadratic cone of n variables x_1, \dots, x_n defines a constraint of the form

$$x_1^2 > \sum_{i=2}^n x_i^2.$$

A rotated quadratic cone of n variables x_1, \dots, x_n defines a constraint of the form

$$x_1 x_2 > \sum_{i=3}^n x_i^2.$$

A **[bounds]**-section example:

```
[bounds]
[b]  0 <= x,y <= 10  [/b] # ranged bound
[b]  10 >= x,y >=  0  [/b] # ranged bound
[b]  0 <= x,y <= inf  [/b] # using inf
[b]          x,y free  [/b] # free variables
# Let (x,y,z,w) belong to the cone K
[cone quad]  x,y,z,w  [/cone] # quadratic cone
[cone rquad] x,y,z,w  [/cone] # rotated quadratic cone
[/bounds]
```

By default all variables are free.

- **[variables]** This defines an ordering of variables as they should appear in the problem. This is simply a space-separated list of variable names.
- **[integer]** This contains a space-separated list of variables and defines the constraint that the listed variables must be integer values.
- **[hints]** This may contain only non-essential data; for example estimates of the number of variables, constraints and non-zeros. Placed before all other sections containing data this may reduce the time spent reading the file.

In the **hints** section, any subsection which is not recognized by MOSEK is simply ignored. In this section a hint in a subsection is defined as follows:

```
[hint ITEM] value [/hint]
```

where **ITEM** may be replaced by **numvar** (number of variables), **numcon** (number of linear/quadratic constraints), **numanz** (number of linear non-zeros in constraints) and **numqnz** (number of quadratic non-zeros in constraints).

- **[solutions]** This section can contain a set of full or partial solutions to a problem. Each solution must be specified using a **[solution]**-section, i.e.

```
[solutions]
[solution]...[/solution] #solution 1
[solution]...[/solution] #solution 2
                        #other solutions....
[solution]...[/solution] #solution n
[/solutions]
```

Note that a `[solution]`-section must be always specified inside a `[solutions]`-section. The syntax of a `[solution]`-section is the following:

```
[solution SOLTYPE status=STATUS]...[/solution]
```

where `SOLTYPE` is one of the strings

- ‘interior’, a non-basic solution,
- ‘basic’, a basic solution,
- ‘integer’, an integer solution,

and `STATUS` is one of the strings

- ‘UNKNOWN’,
- ‘OPTIMAL’,
- ‘INTEGER_OPTIMAL’,
- ‘PRIM_FEAS’,
- ‘DUAL_FEAS’,
- ‘PRIM_AND_DUAL_FEAS’,
- ‘NEAR_OPTIMAL’,
- ‘NEAR_PRIM_FEAS’,
- ‘NEAR_DUAL_FEAS’,
- ‘NEAR_PRIM_AND_DUAL_FEAS’,
- ‘PRIM_INFEAS_CER’,
- ‘DUAL_INFEAS_CER’,
- ‘NEAR_PRIM_INFEAS_CER’,
- ‘NEAR_DUAL_INFEAS_CER’,
- ‘NEAR_INTEGER_OPTIMAL’.

Most of these values are irrelevant for input solutions; when constructing a solution for simplex hot-start or an initial solution for a mixed integer problem the safe setting is `UNKNOWN`.

A `[solution]`-section contains `[con]` and `[var]` sections. Each `[con]` and `[var]` section defines solution information for a single variable or constraint, specified as list of `KEYWORD/value` pairs, in any order, written as

```
KEYWORD=value
```

Allowed keywords are as follows:

- **sk**. The status of the item, where the **value** is one of the following strings:
 - * **LOW**, the item is on its lower bound.
 - * **UPR**, the item is on its upper bound.
 - * **FIX**, it is a fixed item.
 - * **BAS**, the item is in the basis.
 - * **SUPBAS**, the item is super basic.

- * UNK, the status is unknown.
- * INF, the item is outside its bounds (infeasible).
- **lvl** Defines the level of the item.
- **s1** Defines the level of the dual variable associated with its lower bound.
- **su** Defines the level of the dual variable associated with its upper bound.
- **sn** Defines the level of the variable associated with its cone.
- **y** Defines the level of the corresponding dual variable (for constraints only).

A **[var]** section should always contain the items **sk**, **lvl**, **s1** and **su**. Items **s1** and **su** are not required for **integer** solutions.

A **[con]** section should always contain **sk**, **lvl**, **s1**, **su** and **y**.

An example of a solution section

```
[solution basic status=UNKNOWN]
  [var x0] sk=LOW    lvl=5.0      [/var]
  [var x1] sk=UPR    lvl=10.0     [/var]
  [var x2] sk=SUPBAS lvl=2.0    s1=1.5 su=0.0 [/var]

  [con c0] sk=LOW    lvl=3.0 y=0.0 [/con]
  [con c0] sk=UPR    lvl=0.0 y=5.0 [/con]
[/solution]
```

- **[vendor]** This contains solver/vendor specific data. It accepts one argument, which is a vendor ID – for MOSEK the ID is simply **mosek** – and the section contains the subsection **parameters** defining solver parameters. When reading a vendor section, any unknown vendor can be safely ignored. This is described later.

Comments using the ‘#’ may appear anywhere in the file. Between the ‘#’ and the following line-break any text may be written, including markup characters.

E.3.2.2 Numbers

Numbers, when used for parameter values or coefficients, are written in the usual way by the **printf** function. That is, they may be prefixed by a sign (+ or -) and may contain an integer part, decimal part and an exponent. The decimal point is always ‘.’ (a dot). Some examples are

```
1
1.0
.0
1.
1e10
1e+10
1e-10
```

Some *invalid* examples are

```
e10    # invalid, must contain either integer or decimal part
.       # invalid
.e10   # invalid
```

More formally, the following standard regular expression describes numbers as used:

```
[+|-]?([0-9]+[.][0-9]*|.[0-9]+)([eE][+|-]?[0-9]+)?
```


E.3.2.3 Names

Variable names, constraint names and objective name may contain arbitrary characters, which in some cases must be enclosed by quotes (single or double) that in turn must be preceded by a backslash. Unquoted names must begin with a letter (**a-z** or **A-Z**) and contain only the following characters: the letters **a-z** and **A-Z**, the digits **0-9**, braces (**{** and **}**) and underscore (**_**).

Some examples of legal names:

```
an_unquoted_name
another_name{123}
'single quoted name'
"double quoted name"
"name with \"quote\" in it"
"name with []s in it"
```

E.3.3 Parameters section

In the **vendor** section solver parameters are defined inside the **parameters** subsection. Each parameter is written as

```
[p PARAMETER_NAME] value [/p]
```

where **PARAMETER_NAME** is replaced by a MOSEK parameter name, usually of the form **MSK_IPAR_...**, **MSK_DPAR_...** or **MSK_SPAR_...**, and the **value** is replaced by the value of that parameter; both integer values and named values may be used. Some simple examples are:

```
[vendor mosek]
[parameters]
  [p MSK_IPAR_OPF_MAX_TERMS_PER_LINE] 10      [/p]
  [p MSK_IPAR_OPF_WRITE_PARAMETERS]    MSK_ON [/p]
  [p MSK_DPAR_DATA_TOL_BOUND_INF]      1.0e18 [/p]
[/parameters]
[/vendor]
```

E.3.4 Writing OPF files from MOSEK

The function **MSK.writedata** can be used to produce an OPF file from a task.

To write an OPF file set the parameter **MSK_IPAR_WRITE_DATA_FORMAT** to **MSK_DATA_FORMAT_OP** as this ensures that OPF format is used. Then modify the following parameters to define what the file should contain:

- **MSK_IPAR_OPF_WRITE_HEADER**, include a small header with comments.
- **MSK_IPAR_OPF_WRITE_HINTS**, include hints about the size of the problem.
- **MSK_IPAR_OPF_WRITE_PROBLEM**, include the problem itself — objective, constraints and bounds.
- **MSK_IPAR_OPF_WRITE_SOLUTIONS**, include solutions if they are defined. If this is off, no solutions are included.
- **MSK_IPAR_OPF_WRITE_SOL_BAS**, include basic solution, if defined.

- `MSK_IPAR_OPF_WRITE_SOL_ITG`, include integer solution, if defined.
- `MSK_IPAR_OPF_WRITE_SOL_ITR`, include interior solution, if defined.
- `MSK_IPAR_OPF_WRITE_PARAMETERS`, include all parameter settings.

E.3.5 Examples

This section contains a set of small examples written in OPF and describing how to formulate linear, quadratic and conic problems.

E.3.5.1 Linear example `lo1.opf`

Consider the example:

$$\begin{array}{llllll}
 \text{maximize} & 3x_0 & + & 1x_1 & + & 5x_2 & + & 1x_3 \\
 \text{subject to} & 3x_0 & + & 1x_1 & + & 2x_2 & & = & 30, \\
 & 2x_0 & + & 1x_1 & + & 3x_2 & + & 1x_3 & \geq & 15, \\
 & & & 2x_1 & & & + & 3x_3 & \leq & 25,
 \end{array}$$

having the bounds

$$\begin{array}{llll}
 0 & \leq & x_0 & \leq & \infty, \\
 0 & \leq & x_1 & \leq & 10, \\
 0 & \leq & x_2 & \leq & \infty, \\
 0 & \leq & x_3 & \leq & \infty.
 \end{array}$$

In the OPF format the example is displayed as shown below:

```

[comment]
  The lo1 example in OPF format
[/comment]

[hints]
  [hint NUMVAR] 4 [/hint]
  [hint NUMCON] 3 [/hint]
  [hint NUMANZ] 9 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2 x3 x4
[/variables]

[objective maximize 'obj']
  3 x1 + x2 + 5 x3 + x4
[/objective]

[constraints]
  [con 'c1'] 3 x1 +   x2 + 2 x3           = 30 [/con]
  [con 'c2'] 2 x1 +   x2 + 3 x3 +   x4 >= 15 [/con]
  [con 'c3']      2 x2           + 3 x4 <= 25 [/con]
[/constraints]

```

```
[bounds]
  [b] 0 <= * [/b]
  [b] 0 <= x2 <= 10 [/b]
[/bounds]
```

E.3.5.2 Quadratic example qo1.opf

An example of a quadratic optimization problem is

$$\begin{array}{ll} \text{minimize} & x_1^2 + 0.1x_2^2 + x_3^2 - x_1x_3 - x_2 \\ \text{subject to} & 1 \leq x_1 + x_2 + x_3, \\ & x \geq 0. \end{array}$$

This can be formulated in `opf` as shown below.

```
[comment]
  The qo1 example in OPF format
[/comment]

[hints]
  [hint NUMVAR] 3 [/hint]
  [hint NUMCON] 1 [/hint]
  [hint NUMANZ] 3 [/hint]
  [hint NUMQNZ] 4 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2 x3
[/variables]

[objective minimize 'obj']
  # The quadratic terms are often written with a factor of 1/2 as here,
  # but this is not required.

  - x2 + 0.5 ( 2.0 x1 ^ 2 - 2.0 x3 * x1 + 0.2 x2 ^ 2 + 2.0 x3 ^ 2 )
[/objective]

[constraints]
  [con 'c1'] 1.0 <= x1 + x2 + x3 [/con]
[/constraints]

[bounds]
  [b] 0 <= * [/b]
[/bounds]
```

E.3.5.3 Conic quadratic example cqo1.opf

Consider the example:

$$\begin{array}{llll}
\text{minimize} & x_3 + x_4 + x_5 & & \\
\text{subject to} & x_0 + x_1 + 2x_2 & = & 1, \\
& x_0, x_1, x_2 & \geq & 0, \\
& x_3 \geq \sqrt{x_0^2 + x_1^2}, & & \\
& 2x_4x_5 \geq x_2^2. & &
\end{array}$$

Please note that the type of the cones is defined by the parameter to `[cone ...]`; the content of the `cone`-section is the names of variables that belong to the cone.

```

[comment]
  The cq01 example in OPF format.
[/comment]

[hints]
  [hint NUMVAR] 6 [/hint]
  [hint NUMCON] 1 [/hint]
  [hint NUMANZ] 3 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2 x3 x4 x5 x6
[/variables]

[objective minimize 'obj']
  x4 + x5 + x6
[/objective]

[constraints]
  [con 'c1'] x1 + x2 + 2e+00 x3 = 1e+00 [/con]
[/constraints]

[bounds]
  # We let all variables default to the positive orthant
  [b] 0 <= * [/b]

  # ...and change those that differ from the default
  [b] x4,x5,x6 free [/b]

  # Define quadratic cone: x4 >= sqrt( x1^2 + x2^2 )
  [cone quad 'k1'] x4, x1, x2 [/cone]

  # Define rotated quadratic cone: 2 x5 x6 >= x3^2
  [cone rquad 'k2'] x5, x6, x3 [/cone]
[/bounds]

```

E.3.5.4 Mixed integer example milo1.opf

Consider the mixed integer problem:

$$\begin{array}{llll}
\text{maximize} & x_0 + 0.64x_1 & & \\
\text{subject to} & 50x_0 + 31x_1 & \leq & 250, \\
& 3x_0 - 2x_1 & \geq & -4, \\
& x_0, x_1 \geq 0 & & \text{and integer}
\end{array}$$

This can be implemented in OPF with:

```
[comment]
  The milo1 example in OPF format
[/comment]

[hints]
  [hint NUMVAR] 2 [/hint]
  [hint NUMCON] 2 [/hint]
  [hint NUMANZ] 4 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2
[/variables]

[objective maximize 'obj']
  x1 + 6.4e-1 x2
[/objective]

[constraints]
  [con 'c1'] 5e+1 x1 + 3.1e+1 x2 <= 2.5e+2 [/con]
  [con 'c2'] -4 <= 3 x1 - 2 x2 [/con]
[/constraints]

[bounds]
  [b] 0 <= * [/b]
[/bounds]

[integer]
  x1 x2
[/integer]
```

E.4 The Task format

The Task format is MOSEK's native binary format. It contains a complete image of a MOSEK task, i.e.

- Problem data: Linear, conic quadratic, semidefinite and quadratic data
- Problem item names: Variable names, constraints names, cone names etc.
- Parameter settings
- Solutions

There are a few things to be aware of:

- The task format *does not* support General Convex problems since these are defined by arbitrary user-defined functions.
- Status of a solution read from a file will *always* be unknown.

```

*          1          2          3          4          5          6
*23456789012345678901234567890123456789012345678901234567890
NAME          [name]
?? [vname1]          [value1]
ENDATA

```

Figure E.1: The standard ORD format.

The format is based on the TAR (USTar) file format. This means that the individual pieces of data in a `.task` file can be examined by unpacking it as a TAR file. Please note that the inverse may not work: Creating a file using TAR will most probably not create a valid MOSEK Task file since the order of the entries is important.

E.5 The XML (OSiL) format

MOSEK can write data in the standard OSiL xml format. For a definition of the OSiL format please see <http://www.optimizationservices.org/>. Only linear constraints (possibly with integer variables) are supported. By default output files with the extension `.xml` are written in the OSiL format.

The parameter `MSK_IPAR_WRITE_XML_MODE` controls if the linear coefficients in the A matrix are written in row or column order.

E.6 The ORD file format

An ORD formatted file specifies in which order the mixed integer optimizer branches on variables. The format of an ORD file is shown in Figure E.1. In the figure names in capitals are keywords of the ORD format, whereas names in brackets are custom names or values. The `??` is an optional key specifying the preferred branching direction. The possible keys are `DN` and `UP` which indicate that down or up is the preferred branching direction respectively. The branching direction key is optional and is left blank the mixed integer optimizer will decide whether to branch up or down.

E.6.1 An example

A concrete example of a ORD file is presented below:

```

NAME          EXAMPLE
DN x1          2
UP x2          1
  x3          10
ENDATA

```

This implies that the priorities 2, 1, and 10 are assigned to variable `x1`, `x2`, and `x3` respectively. The higher the priority value assigned to a variable the earlier the mixed integer optimizer will branch on that variable. The key `DN` implies that the mixed integer optimizer first will branch down on variable whereas the key `UP` implies that the mixed integer optimizer will first branch up on a variable.

If no branch direction is specified for a variable then the mixed integer optimizer will automatically

choose the branching direction for that variable. Similarly, if no priority is assigned to a variable then it is automatically assigned the priority of 0.

E.7 The solution file format

MOSEK provides one or two solution files depending on the problem type and the optimizer used. If a problem is optimized using the interior-point optimizer and no basis identification is required, then a file named **probrname.sol** is provided. **probrname** is the name of the problem and **.sol** is the file extension. If the problem is optimized using the simplex optimizer or basis identification is performed, then a file named **probrname.bas** is created presenting the optimal basis solution. Finally, if the problem contains integer constrained variables then a file named **probrname.int** is created. It contains the integer solution.

E.7.1 The basic and interior solution files

In general both the interior-point and the basis solution files have the format:

NAME	:	<problem name>					
PROBLEM STATUS	:	<status of the problem>					
SOLUTION STATUS	:	<status of the solution>					
OBJECTIVE NAME	:	<name of the objective function>					
PRIMAL OBJECTIVE	:	<primal objective value corresponding to the solution>					
DUAL OBJECTIVE	:	<dual objective value corresponding to the solution>					
CONSTRAINTS							
INDEX	NAME	AT ACTIVITY	LOWER LIMIT	UPPER LIMIT	DUAL LOWER	DUAL UPPER	
?	<name>	?? <a value>	<a value>	<a value>	<a value>	<a value>	
VARIABLES							
INDEX	NAME	AT ACTIVITY	LOWER LIMIT	UPPER LIMIT	DUAL LOWER	DUAL UPPER	CONIC DUAL
?	<name>	?? <a value>	<a value>	<a value>	<a value>	<a value>	<a value>

In the example the fields ? and <> will be filled with problem and solution specific information. As can be observed a solution report consists of three sections, i.e.

HEADER

In this section, first the name of the problem is listed and afterwards the problem and solution statuses are shown. In this case the information shows that the problem is primal and dual feasible and the solution is optimal. Next the primal and dual objective values are displayed.

CONSTRAINTS

Subsequently in the constraint section the following information is listed for each constraint:

INDEX

A sequential index assigned to the constraint by MOSEK

NAME

The name of the constraint assigned by the user.

Status key	Interpretation
UN	Unknown status
BS	Is basic
SB	Is superbasic
LL	Is at the lower limit (bound)
UL	Is at the upper limit (bound)
EQ	Lower limit is identical to upper limit
**	Is infeasible i.e. the lower limit is greater than the upper limit.

Table E.1: Status keys.

AT

The status of the constraint. In Table E.1 the possible values of the status keys and their interpretation are shown.

ACTIVITY

Given the i th constraint on the form

$$l_i^c \leq \sum_{j=1}^n a_{ij}x_j \leq u_i^c, \quad (\text{E.7})$$

then activity denote the quantity $\sum_{j=1}^n a_{ij}x_j^*$, where x^* is the value for the x solution.

LOWER LIMIT

Is the quantity l_i^c (see (E.7)).

UPPER LIMIT

Is the quantity u_i^c (see (E.7)).

DUAL LOWER

Is the dual multiplier corresponding to the lower limit on the constraint.

DUAL UPPER

Is the dual multiplier corresponding to the upper limit on the constraint.

VARIABLES

The last section of the solution report lists information for the variables. This information has a similar interpretation as for the constraints. However, the column with the header [CONIC DUAL] is only included for problems having one or more conic constraints. This column shows the dual variables corresponding to the conic constraints.

E.7.2 The integer solution file

The integer solution is equivalent to the basic and interior solution files except that no dual information is included.

Appendix F

Problem analyzer examples

This appendix presents a few examples of the output produced by the problem analyzer described in Section 13.1. The first two problems are taken from the MIPLIB 2003 collection, <http://miplib.zib.de/>.

F.1 air04

Analyzing the problem

Constraints	Bounds	Variables
fixed : all	ranged : all	bin : all

```
-----
Objective, min cx
  range: min |c|: 31.0000      max |c|: 2258.00
distrib:      |c|      vars
           [31, 100)      176
           [100, 1e+03)    8084
           [1e+03, 2.26e+03] 644
-----
```

```
Constraint matrix A has
  823 rows (constraints)
 8904 columns (variables)
72965 (0.995703%) nonzero entries (coefficients)
```

```
Row nonzeros, A_i
  range: min A_i: 2 (0.0224618%)      max A_i: 368 (4.13297%)
distrib:      A_i      rows      rows%      acc%
           2          2          0.24        0.24
           [3, 7]      4          0.49        0.73
           [8, 15]     19          2.31        3.04
           [16, 31]    80          9.72       12.76
           [32, 63]   236         28.68       41.43
           [64, 127]  289         35.12       76.55
```

[128, 255]	186	22.60	99.15
[256, 368]	7	0.85	100.00

Column nonzeros, A|j
 range: min A|j: 2 (0.243013%) max A|j: 15 (1.8226%)
 distrib: A|j cols cols% acc%
 2 118 1.33 1.33
 [3, 7] 2853 32.04 33.37
 [8, 15] 5933 66.63 100.00

A nonzeros, A(ij)
 range: all |A(ij)| = 1.00000

Constraint bounds, lb <= Ax <= ub
 distrib: |b| lbs ubs
 [1, 10] 823 823

Variable bounds, lb <= x <= ub
 distrib: |b| lbs ubs
 0 8904 8904
 [1, 10]

F.2 arki001

Analyzing the problem

Constraints		Bounds		Variables	
lower bd:	82	lower bd:	38	cont:	850
upper bd:	946	fixed :	353	bin :	415
fixed :	20	free :	1	int :	123
		ranged :	996		

Objective, min cx
 range: all |c| in {0.00000, 1.00000}
 distrib: |c| vars
 0 1387
 1 1

Constraint matrix A has
 1048 rows (constraints)
 1388 columns (variables)
 20439 (1.40511%) nonzero entries (coefficients)

Row nonzeros, A_i
 range: min A_i: 1 (0.0720461%) max A_i: 1046 (75.3602%)
 distrib: A_i rows rows% acc%
 1 29 2.77 2.77

2	476	45.42	48.19
[3, 7]	49	4.68	52.86
[8, 15]	56	5.34	58.21
[16, 31]	64	6.11	64.31
[32, 63]	373	35.59	99.90
[1024, 1046]	1	0.10	100.00

Column nonzeros, A|j
 range: min A|j: 1 (0.0954198%) max A|j: 29 (2.76718%)
 distrib: A|j cols cols% acc%

1	381	27.45	27.45
2	19	1.37	28.82
[3, 7]	38	2.74	31.56
[8, 15]	233	16.79	48.34
[16, 29]	717	51.66	100.00

A nonzeros, A(ij)
 range: min |A(ij)|: 0.000200000 max |A(ij)|: 2.33067e+07
 distrib: A(ij) coeffs

[0.0002, 0.001)	167
[0.001, 0.01)	1049
[0.01, 0.1)	4553
[0.1, 1)	8840
[1, 10)	3822
[10, 100)	630
[100, 1e+03)	267
[1e+03, 1e+04)	699
[1e+04, 1e+05)	291
[1e+05, 1e+06)	83
[1e+06, 1e+07)	19
[1e+07, 2.33e+07]	19

Constraint bounds, lb <= Ax <= ub
 distrib: |b| lbs ub

[0.1, 1)		386
[1, 10)		74
[10, 100)	101	456
[100, 1000)		34
[1000, 10000)		15
[100000, 1e+06]	1	1

Variable bounds, lb <= x <= ub
 distrib: |b| lbs ub

0	974	323
[0.001, 0.01)		19
[0.1, 1)	370	57
[1, 10)	41	704
[10, 100]	2	246

F.3 Problem with both linear and quadratic constraints

Analyzing the problem

Constraints		Bounds		Variables
lower bd:	40	upper bd:	1	cont: all
upper bd:	121	fixed :	204	
fixed :	5480	free :	5600	
ranged :	161	ranged :	40	

Objective, maximize cx
 range: all |c| in {0.00000, 15.4737}
 distrib: |c| vars
 0 5844
 15.4737 1

Constraint matrix A has
 5802 rows (constraints)
 5845 columns (variables)
 6480 (0.0191079%) nonzero entries (coefficients)

Row nonzeros, A_i
 range: min A_i: 0 (0%) max A_i: 3 (0.0513259%)
 distrib: A_i rows rows% acc%
 0 80 1.38 1.38
 1 5003 86.23 87.61
 2 680 11.72 99.33
 3 39 0.67 100.00

0/80 empty rows have quadratic terms

Column nonzeros, A_j
 range: min A_j: 0 (0%) max A_j: 15 (0.258532%)
 distrib: A_j cols cols% acc%
 0 204 3.49 3.49
 1 5521 94.46 97.95
 2 40 0.68 98.63
 [3, 7] 40 0.68 99.32
 [8, 15] 40 0.68 100.00

0/204 empty columns correspond to variables used in conic
 and/or quadratic expressions only

A nonzeros, A_(ij)
 range: min |A_(ij)|: 2.02410e-05 max |A_(ij)|: 35.8400
 distrib: A_(ij) coeffs
 [2.02e-05, 0.0001) 40
 [0.0001, 0.001) 118
 [0.001, 0.01) 305
 [0.01, 0.1) 176
 [0.1, 1) 40
 [1, 10) 5721
 [10, 35.8] 80

```

Constraint bounds, lb <= Ax <= ub
distrib:      |b|      lbs      ub
              0      5481      5600
              [1000, 10000)
              [10000, 100000)
              [1e+06, 1e+07)
              [1e+08, 1e+09]
              120      120

Variable bounds, lb <= x <= ub
distrib:      |b|      lbs      ub
              0      243      203
              [0.1, 1)
              [1e+06, 1e+07)
              [1e+11, 1e+12]
              1
              40
              1

```

Quadratic constraints: 121

```

Gradient nonzeros, Qx
range: min Qx: 1 (0.0171086%)    max Qx: 2720 (46.5355%)
distrib:      Qx      cons      cons%      acc%
              1      40      33.06      33.06
              [64, 127]      80      66.12      99.17
              [2048, 2720]      1      0.83      100.00

```

F.4 Problem with both linear and conic constraints

Analyzing the problem

```

Constraints      Bounds      Variables
upper bd:      3600      fixed :      3601      cont: all
fixed :      21760      free  :      28802

```

```

Objective, minimize cx
range: all |c| in {0.00000, 1.00000}
distrib:      |c|      vars
              0      32402
              1      1

```

```

Constraint matrix A has
25360 rows (constraints)
32403 columns (variables)
93339 (0.0113587%) nonzero entries (coefficients)

```

```

Row nonzeros, A_i
range: min A_i: 1 (0.00308613%)    max A_i: 8 (0.0246891%)

```

distrib:	A _i	rows	rows%	acc%
	1	3600	14.20	14.20
	2	10803	42.60	56.79
	[3, 7]	3995	15.75	72.55
	8	6962	27.45	100.00

Column nonzeros, A_j

range: min A_j: 0 (0%) max A_j: 61 (0.240536%)

distrib:	A _j	cols	cols%	acc%
	0	3602	11.12	11.12
	1	10800	33.33	44.45
	2	7200	22.22	66.67
	[3, 7]	7279	22.46	89.13
	[8, 15]	3521	10.87	100.00
	[32, 61]	1	0.00	100.00

3600/3602 empty columns correspond to variables used in conic
and/or quadratic constraints only

A nonzeros, A(ij)

range: min |A(ij)|: 0.00833333 max |A(ij)|: 1.00000

distrib:	A(ij)	coeffs
	[0.00833, 0.01)	57280
	[0.01, 0.1)	59
	[0.1, 1]	36000

Constraint bounds, lb ≤ Ax ≤ ub

distrib:	b	lbs	ubs
	0	21760	21760
	[0.1, 1]		3600

Variable bounds, lb ≤ x ≤ ub

distrib:	b	lbs	ubs
	[1, 10]	3601	3601

Rotated quadratic cones: 3600

dim	RQCs
4	3600

Bibliography

- [1] Chvátal, V.. Linear programming, 1983. W.H. Freeman and Company
- [2] Nazareth, J. L.. Computer Solution of Linear Programs, 1987. Oxford University Press, New York
- [3] Bazaraa, M. S., Sherali, H. D. and Shetty, C. M.. Nonlinear programming: Theory and algorithms, 2 edition, 1993. John Wiley and Sons, New York
- [4] Williams, H. P.. Model building in mathematical programming, 3 edition, 1993. John Wiley and Sons
- [5] Cornuejols, Gerard and Tütüncü, Reha. Optimization methods in finance, 2007. Cambridge University Press, New York
- [6] Ronald N. Kahn and Richard C. Grinold. Active portfolio management, 2 edition, 2000. McGraw-Hill, New York
- [7] MOSEK ApS. MOSEK Modeling manual, 2012. Last revised January 31 2013. <http://docs.mosek.com/generic/modeling-a4.pdf>
- [8] Andersen, E. D. and Andersen, K. D.. Presolving in linear programming. Math. Programming 2:221-245
- [9] Andersen, E. D., Gondzio, J., Mészáros, Cs. and Xu, X.. Implementation of interior point methods for large scale linear programming, Interior-point methods of mathematical programming p. 189-252, 1996. Kluwer Academic Publishers
- [10] Erling D. Andersen. The homogeneous and self-dual model and algorithm for linear optimization. Technical report TR-1-2009, 2009. MOSEK ApS. <http://www.mosek.com/fileadmin/reports/tech/homolo.pdf>
- [11] Andersen, E. D. and Ye, Y.. Combining interior-point and pivoting algorithms. Management Sci. December 12:1719-1731
- [12] Ahuja, R. K., Magnanti, T. L. and Orlin, J. B.. Network flows, Optimization, vol. 1 p. 211-369, 1989. North Holland, Amsterdam
- [13] Andersen, E. D., Roos, C. and Terlaky, T.. On implementing a primal-dual interior-point method for conic quadratic optimization. Math. Programming February 2

- [14] Andersen, E. D. and Ye, Y.. A computational study of the homogeneous algorithm for large-scale convex optimization. *Computational Optimization and Applications* 10:243-269
- [15] Andersen, E. D. and Ye, Y.. On a homogeneous algorithm for the monotone complementarity problem. *Math. Programming* February 2:375-399
- [16] Wolsey, L. A.. *Integer programming*, 1998. John Wiley and Sons
- [17] Roos, C., Terlaky, T. and Vial, J. -Ph.. *Theory and algorithms for linear optimization: an interior point approach*, 1997. John Wiley and Sons, New York
- [18] Wallace, S. W.. Decision making under uncertainty: Is sensitivity of any use. *Oper. Res.* January 1:20-25
- [19] G. W. Stewart. *Matrix Algorithms. Volume 1: Basic decompositions*, 1998. P. SIAM

Index

- analyzenames, 316
- analyzeproblem, 317
- analyzesolution, 317
- API reference, 279
- appendbarvars, 318
- appendcone, 319
- appendconeseq, 320
- appendconeseq, 321
- appendcons, 321
- appendsparsesymmat, 322
- appendstat, 323
- appendvars, 323
- attaching streams, 37
- axpy, 324

- basis identification, 222
- basiscond, 324
- bktostr, 325
- BLAS, 158
 - AXPY, 159
 - DOT, 159
 - GEMM, 160
 - GEMV, 159
 - SYEIG, 161
 - SYRK, 160
- bounds, infinite, 202

- callbackcodetostr, 326
- callocdbgen, 326
- callocdbgtask, 327
- callocenv, 327
- calloctask, 328
- certificate
 - dual, 204, 207, 209, 211
 - primal, 204, 207, 209
- checkconvexity, 328
- checkinlicense, 329
- checkmemenv, 329
- checkmemtask, 330
- checkoutlicense, 330
- checkversion, 331
- chgbound, 331
- clonetask, 333
- commitchanges, 333
- compiling examples, 22
 - compiling examples (Linux), 26
 - compiling examples (Solaris), 27
 - compiling examples (Windows), 22
- complementarity conditions, 203
- concurrent optimization, 229
- concurrent solution, 228
- conetypetostr, 333
- conic, 45, 51
 - optimization, 205
 - problem, 205
- conic optimization, 45, 51
- conic problem example, 46
- conic quadratic optimization, 45
- Conic quadratic reformulation, 163
- constraint
 - matrix, 201, 212, 768
 - quadratic, 210
- constraints
 - lower limit, 201, 212, 768
 - number of, 33
 - upper limit, 201, 212, 768
- continuous relaxation, 235
- convex quadratic problem, 58
- copyright, ii

- deleteenv, 334
- deletesolution, 334
- deletetask, 335
- dot, 335
- dual certificate, 204, 207, 209, 211

- dual feasible, 202
- dual geometric optimization, 139
- dual infeasible, 202, 204, 207, 209, 211
- duality gap, 202
- dualizer, 217
- dualsensitivity, 336
- echoenv, 337
- echointro, 337
- echotask, 338
- eliminator, 217
- env, creating, 30
- env, initializing, 30
- example
 - conic problem, 46
 - cqo1, 46
 - ill-posed, 258
 - linear dependency, 257
 - complo1, 34
 - complo2, 41
 - compmilo1, 71
 - miointsol, 75
 - compqo1, 59
 - quadratic constraints, 64
 - quadratic objective, 59
 - sdo1, 52
 - semidefinite problem, 52
 - simple, 30
 - compsolutionquality.c, 87
- examples
 - compiling (Linux), 26
 - compiling (Solaris), 27
 - compiling (Windows), 22
 - compile and run, 22
 - makefiles (Linux), 25
 - makefiles (Windows), 22
- exponential optimization, 130
- factor model, 184
- fatal error, 199
- feasibility repair, 257
- feasible, dual, 202
- feasible, primal, 202
- freedbgenv, 338
- freedbgtask, 339
- freeenv, 339
- freetask, 340
- gemm, 340
- gemv, 341
- geometric optimization, 139
- getacol, 343
- getacolnumnz, 343
- getacolslicetrip, 344
- getaij, 345
- getapiecenumnz, 346
- getarow, 347
- getarownumnz, 347
- getarowslicetrip, 348
- getaslice, 349
- getaslice64, 350
- getaslicenumnz, 351
- getaslicenumnz64, 352
- getbarablocktriplet, 352
- getbaraidx, 353
- getbaraidxij, 354
- getbaraidxinfo, 355
- getbarasparsity, 355
- getbarcblocktriplet, 356
- getbarcidx, 357
- getbarcidxinfo, 358
- getbarcidxj, 358
- getbarcsparsity, 359
- getbarsj, 359
- getbarvarname, 360
- getbarvarnameindex, 360
- getbarvarnamelen, 361
- getbarxj, 362
- getbound, 362
- getboundslice, 363
- getbuildinfo, 364
- getc, 364
- getcallbackfunc, 365
- getcfix, 365
- getcj, 366
- getcodedesc, 366
- getconbound, 367
- getconboundslice, 367
- getcone, 368
- getconeinfo, 369
- getconename, 369
- getconenameindex, 370
- getconenamel, 370
- getconname, 371

- getconnameindex, 372
- getconnamelen, 372
- getcslice, 373
- getdbi, 373
- getdcni, 374
- getdeqi, 375
- getdimbarvarj, 376
- getdouinf, 376
- getdoupam, 377
- getdualobj, 377
- getdviolbarvar, 378
- getdviolcon, 379
- getdviolcones, 379
- getdviolvar, 380
- getenv, 381
- getglbdlname, 382
- getinfeasiblesubproblem, 382
- getinfindex, 383
- getinfmax, 383
- getinfname, 384
- getinti, 384
- getintinf, 385
- getintparam, 386
- getlasterror, 386
- getlasterror64, 387
- getlenbarvarj, 387
- getlintinf, 388
- getmaxnamelen, 389
- getmaxnumanz, 389
- getmaxnumanz64, 389
- getmaxnumbarvar, 390
- getmaxnumcon, 390
- getmaxnumcone, 391
- getmaxnumqnz, 391
- getmaxnumqnz64, 392
- getmaxnumvar, 392
- getmemusagetask, 392
- getnadouinf, 393
- getnadoupam, 393
- getnaintinf, 394
- getnaintparam, 394
- getnastrparam, 395
- getnastrparamal, 396
- getnlfunc, 396
- getnumanz, 397
- getnumanz64, 397
- getnumbarablocktriplets, 398
- getnumbaranz, 398
- getnumbarcblocktriplets, 398
- getnumbarcnz, 399
- getnumbarvar, 399
- getnumcon, 400
- getnumcone, 400
- getnumconemem, 400
- getnumintvar, 401
- getnumparam, 401
- getnumqconknz, 402
- getnumqconknz64, 402
- getnumqobjjnz, 403
- getnumqobjjnz64, 403
- getnumsymmat, 404
- getnumvar, 404
- getobjname, 404
- getobjnamelen, 405
- getobjsense, 405
- getparammax, 406
- getparamname, 406
- getpbi, 407
- getpcni, 408
- getpeqi, 408
- getprimalobj, 409
- getprobtype, 410
- getprosta, 410
- getpviolbarvar, 411
- getpviolcon, 411
- getpviolcones, 412
- getpviolvar, 413
- getqconk, 414
- getqconk64, 414
- getqobj, 415
- getqobj64, 416
- getqobjjij, 417
- getreducedcosts, 418
- getresponseclass, 418
- getskc, 419
- getskcslice, 419
- getskx, 420
- getskxslice, 421
- getslc, 421
- getslcslice, 422
- getslx, 423
- getslxslice, 423

- getsnx, 424
- getsnxslice, 424
- getsolsta, 425
- getsolution, 426
- getsolutioni, 428
- getsolutionincallback, 429
- getsolutioninf, 431
- getsolutioninfo, 432
- getsolutionslice, 434
- getsparsesymmat, 436
- getstrparam, 437
- getstrparamal, 437
- getstrparamlen, 438
- getsuc, 438
- getsucslice, 439
- getsux, 440
- getsuxslice, 440
- getsymbcon, 441
- getsymbcondim, 441
- getsymmatinfo, 442
- gettaskname, 443
- gettasknamelen, 443
- getvarbound, 444
- getvarboundslice, 444
- getvarbranchdir, 445
- getvarbranchorder, 445
- getvarbranchpri, 446
- getvarname, 446
- getvarnameindex, 447
- getvarnamelen, 448
- getvartype, 448
- getvartypelist, 449
- getversion, 449
- getxc, 450
- getxcslice, 450
- getxx, 451
- getxxslice, 452
- gety, 452
- getslice, 453
- primal, 204, 207, 209
- infeasible problem, 257
- infeasible problems, 247
- infeasible, dual, 202
- infeasible, primal, 202
- infinite bounds, 202
- initbasissolve, 454
- initenv, 454
- inputdata, 455
- inputdata64, 456
- integer optimization, 70, 235
 - relaxation, 235
- interior-point optimizer, 219, 226, 227
- interior-point or simplex optimizer, 225
- iparvaltosymnam, 458
- isdouparname, 458
- isinfinity, 459
- isintparname, 459
- isstrparname, 459
- LAPACK, 158
 - POTRF, 161
 - SYEVD, 161
- leak, 200
- licensecleanup, 460
- linear dependency, 217
 - example, 257
- linear dependency check, 217
- linear optimization, 33
- linear problem, 201
- linearity interval, 266
- linkfiletoenvstream, 460
- linkfiletotaskstream, 461
- linkfunctoenvstream, 461
- linkfunctotaskstream, 462
- LP format, 778
- makeemptytask, 462
- makeenv, 463
- makeenvalloc, 463
- makefile examples (Linux), 25
- makefile examples (Windows), 22
- maketask, 464
- Markowitz model, 171
- matrix format
 - column ordered, 95
 - row ordered, 95
- ill-posed
 - example, 258
- infeasible, 247
 - dual, 204, 207, 209, 211

- triplets, 95
- maximization problem, 203
- memory leak, 200
- mixed integer optimization, 70
- mixed-integer optimization, 235
- model
 - Markowitz, 171
 - portfolio optimization, 171
- MPS format, 767
 - compBOUNDS, 774
 - compCOLUMNS, 771
 - free, 778
 - compNAME, 770
 - compOBJNAME, 770
 - compOBJSENSE, 770
 - compQSECTION, 773
 - compRANGES, 772
 - compRHS, 771
 - compROWS, 770
- mskexpopt, 131
- Network flow problems
 - optimizing, 226
- objective
 - defining, 37
 - linear, 37
 - vector, 201
- objective sense
 - maximize, 203
- objective vector, 212
- onesolutionsummary, 465
- OPF format, 785
- OPF, writing, 30
- optimal solution, 203
- optimality gap, 202, 241
- optimization
 - conic, 205
 - integer, 70, 235
 - mixed integer, 70
 - mixed-integer, 235
- optimize, 465
- optimizeconcurrent, 466
- optimizers
 - concurrent, 229
 - conic interior-point, 226
 - convex interior-point, 227

- linear interior-point, 219
- parallel, 229
- simplex, 224
- optimizersummary, 467
- optimizetrm, 467
- Optimizing
 - network flow problems, 226
- ORD format, 796
- parallel extensions, 228
- parallel interior-point, 218
- parallel optimizers
 - interior point, 218
- parallel solution, 228
- portfolio optimization, 171
- potrf, 468
- presolve, 216
 - eliminator, 217
 - linear dependency check, 217
 - numerical issues, 216
- primal certificate, 204, 207, 209
- primal feasible, 202
- primal infeasible, 202, 204, 207, 209, 257
- primal-dual solution, 202
- primalrepair, 469
- primalsensitivity, 470
- printdata, 473
- printparam, 474
- problem element
 - bounds
 - constraint, 33
 - variable, 34
 - constraint
 - bounds, 33
 - constraint matrix, 33
 - objective, linear, 33
 - variable
 - bounds, 34
 - variable vector, 33
- probttypetostr, 474
- progress call-back, 145
- prostatostr, 475
- Purify, 200
- putacol, 475
- putacollist, 476
- putacollist64, 477

- putacolslice, 478
- putacolslice64, 479
- putaij, 480
- putaijlist, 481
- putaijlist64, 482
- putarow, 483
- putarowlist, 484
- putarowlist64, 485
- putarowslice, 486
- putarowslice64, 487
- putbarablocktriplet, 488
- putbaraij, 488
- putbarcblocktriplet, 489
- putbarcj, 490
- putbarsj, 491
- putbarvarname, 491
- putbarxj, 492
- putbound, 492
- putboundlist, 493
- putboundslice, 494
- putcallbackfunc, 495
- putcfix, 496
- putcj, 496
- putclist, 497
- putconbound, 497
- putconboundlist, 498
- putconboundslice, 499
- putcone, 500
- putconename, 500
- putconname, 501
- putcslice, 501
- putdllpath, 502
- putdoupam, 502
- putexitfunc, 503
- putintparam, 503
- putkeepdlls, 504
- putlicensecode, 504
- putlicensedebug, 505
- putlicensepath, 505
- putlicensewait, 506
- putmaxnumanz, 506
- putmaxnumbarvar, 507
- putmaxnumcon, 507
- putmaxnumcone, 508
- putmaxnumqnz, 508
- putmaxnumvar, 509
- putnadoupam, 509
- putnaintparam, 510
- putnastrparam, 510
- putnlfunc, 511
- putobjname, 511
- putobjsense, 512
- putparam, 512
- putqcon, 513
- putqconk, 514
- putqobj, 515
- putqobjij, 516
- putresponsefunc, 517
- putskc, 518
- putskcslice, 518
- putskx, 519
- putskxslice, 519
- putslc, 520
- putslcslice, 521
- putslx, 521
- putslxslice, 522
- putsnx, 523
- putsnxslice, 523
- putsolution, 524
- putsolutioni, 525
- putsolutionyi, 526
- putstrparam, 527
- putsuc, 527
- putsucslice, 528
- putsux, 528
- putsuxslice, 529
- puttaskname, 530
- putvarbound, 530
- putvarboundlist, 531
- putvarboundslice, 532
- putvarbranchorder, 532
- putvarname, 533
- putvartype, 533
- putvartypelist, 534
- putxc, 535
- putxcslice, 535
- putxx, 536
- putxxslice, 537
- puty, 537
- putsyslice, 538
- quadratic constraint, 210

- quadratic constraints, example, 64
- quadratic objective, example, 59
- quadratic optimization, 58, 210
- quadratic problem, 58

- readbranchpriorities, 539
- readdata, 539
- readdataautoformat, 540
- readdataformat, 540
- readparamfile, 541
- readsolution, 541
- readsummary, 542
- readtask, 542
- reformqcqotosocp, 543
- relaxation, continuous, 235
- relaxprimal, 543
- removebarvars, 544
- removecones, 545
- removecons, 545
- removevars, 546
- resizetask, 547
- Response codes
 - MSK_RES_ERR_AD_INVALID_CODELIST, 695
 - MSK_RES_ERR_AD_INVALID_OPERAND, 695
 - MSK_RES_ERR_AD_INVALID_OPERATOR, 695
 - MSK_RES_ERR_AD_MISSING_OPERAND, 695
 - MSK_RES_ERR_AD_MISSING_RETURN, 695
 - MSK_RES_ERR_API_ARRAY_TOO_SMALL, 695
 - MSK_RES_ERR_API_CB_CONNECT, 695
 - MSK_RES_ERR_API_FATAL_ERROR, 695
 - MSK_RES_ERR_API_INTERNAL, 695
 - MSK_RES_ERR_ARG_IS_TOO_LARGE, 695
 - MSK_RES_ERR_ARG_IS_TOO_SMALL, 696
 - MSK_RES_ERR_ARGUMENT_DIMENSION, 696
 - MSK_RES_ERR_ARGUMENT_IS_TOO_LARGE, 696
 - MSK_RES_ERR_ARGUMENT_LENNEQ, 696
 - MSK_RES_ERR_ARGUMENT_PERM_ARRAY, 696
 - MSK_RES_ERR_ARGUMENT_TYPE, 696
 - MSK_RES_ERR_BAR_VAR_DIM, 696
 - MSK_RES_ERR_BASIS, 696
 - MSK_RES_ERR_BASIS_FACTOR, 696
 - MSK_RES_ERR_BASIS_SINGULAR, 696
 - MSK_RES_ERR_BLANK_NAME, 696
 - MSK_RES_ERR_CANNOT_CLONE_NL, 696
 - MSK_RES_ERR_CANNOT_HANDLE_NL, 696
 - MSK_RES_ERR_CBF_DUPLICATE_ACOORD, 696
 - MSK_RES_ERR_CBF_DUPLICATE_BCOORD, 696
 - MSK_RES_ERR_CBF_DUPLICATE_CON, 696
 - MSK_RES_ERR_CBF_DUPLICATE_INT, 697
 - MSK_RES_ERR_CBF_DUPLICATE_OBJ, 697
 - MSK_RES_ERR_CBF_DUPLICATE_OBJACORD, 697
 - MSK_RES_ERR_CBF_DUPLICATE_VAR, 697
 - MSK_RES_ERR_CBF_INVALID_CON_TYPE, 697
 - MSK_RES_ERR_CBF_INVALID_DOMAIN_DIMENSION, 697
 - MSK_RES_ERR_CBF_INVALID_INT_INDEX, 697
 - MSK_RES_ERR_CBF_INVALID_VAR_TYPE, 697
 - MSK_RES_ERR_CBF_NO_VARIABLES, 697
 - MSK_RES_ERR_CBF_NO_VERSION_SPECIFIED, 697
 - MSK_RES_ERR_CBF_OBJ_SENSE, 697
 - MSK_RES_ERR_CBF_PARSE, 697
 - MSK_RES_ERR_CBF_SYNTAX, 697
 - MSK_RES_ERR_CBF_TOO_FEW_CONSTRAINTS, 697
 - MSK_RES_ERR_CBF_TOO_FEW_INTS, 697
 - MSK_RES_ERR_CBF_TOO_FEW_VARIABLES, 697
 - MSK_RES_ERR_CBF_TOO_MANY_CONSTRAINTS, 698
 - MSK_RES_ERR_CBF_TOO_MANY_INTS, 698
 - MSK_RES_ERR_CBF_TOO_MANY_VARIABLES, 698
 - MSK_RES_ERR_CBF_UNSUPPORTED, 698
 - MSK_RES_ERR_CON_Q_NOT_NSD, 698
 - MSK_RES_ERR_CON_Q_NOT_PSD, 698
 - MSK_RES_ERR_CONCURRENT_OPTIMIZER, 698
 - MSK_RES_ERR_CONE_INDEX, 698
 - MSK_RES_ERR_CONE_OVERLAP, 698
 - MSK_RES_ERR_CONE_OVERLAP_APPEND,

- 698
 MSK_RES_ERR_CONE_REP_VAR, 698
 MSK_RES_ERR_CONE_SIZE, 698
 MSK_RES_ERR_CONE_TYPE, 698
 MSK_RES_ERR_CONE_TYPE_STR, 698
 MSK_RES_ERR_DATA_FILE_EXT, 699
 MSK_RES_ERR_DUP_NAME, 699
 MSK_RES_ERR_DUPLICATE_BARVARIABLE_NAMES, 699
 MSK_RES_ERR_DUPLICATE_CONE_NAMES, 699
 MSK_RES_ERR_DUPLICATE_CONSTRAINT_NAMES, 699
 MSK_RES_ERR_DUPLICATE_VARIABLE_NAMES, 699
 MSK_RES_ERR_END_OF_FILE, 699
 MSK_RES_ERR_FACTOR, 699
 MSK_RES_ERR_FEASREPAIR_CANNOT_RELAX_BOUNDS, 699
 MSK_RES_ERR_FEASREPAIR_INCONSISTENT_BOUNDS, 699
 MSK_RES_ERR_FEASREPAIR_SOLVING_RELAXED_BOUNDS, 699
 MSK_RES_ERR_FILE_LICENSE, 699
 MSK_RES_ERR_FILE_OPEN, 699
 MSK_RES_ERR_FILE_READ, 699
 MSK_RES_ERR_FILE_WRITE, 699
 MSK_RES_ERR_FIRST, 700
 MSK_RES_ERR_FIRSTI, 700
 MSK_RES_ERR_FIRSTJ, 700
 MSK_RES_ERR_FIXED_BOUND_VALUES, 700
 MSK_RES_ERR_FLEXLM, 700
 MSK_RES_ERR_GLOBAL_INV_CONIC_PROBLEM, 700
 MSK_RES_ERR_HUGE_AIJ, 700
 MSK_RES_ERR_HUGE_C, 700
 MSK_RES_ERR_IDENTICAL_TASKS, 700
 MSK_RES_ERR_IN_ARGUMENT, 700
 MSK_RES_ERR_INDEX, 700
 MSK_RES_ERR_INDEX_ARR_IS_TOO_LARGE, 700
 MSK_RES_ERR_INDEX_ARR_IS_TOO_SMALL, 700
 MSK_RES_ERR_INDEX_IS_TOO_LARGE, 700
 MSK_RES_ERR_INDEX_IS_TOO_SMALL, 700
 MSK_RES_ERR_INF_DOU_INDEX, 701
 MSK_RES_ERR_INF_DOU_NAME, 701
 MSK_RES_ERR_INF_INT_INDEX, 701
 MSK_RES_ERR_INF_INT_NAME, 701
 MSK_RES_ERR_INF_LINT_INDEX, 701
 MSK_RES_ERR_INF_LINT_NAME, 701
 MSK_RES_ERR_INF_TYPE, 701
 MSK_RES_ERR_INFEAS_UNDEFINED, 701
 MSK_RES_ERR_INFINITE_BOUND, 701
 MSK_RES_ERR_INT64_TO_INT32_CAST, 701
 MSK_RES_ERR_INTERNAL, 701
 MSK_RES_ERR_INTERNAL_TEST_FAILED, 701
 MSK_RES_ERR_INV_APTRE, 701
 MSK_RES_ERR_INV_BK, 701
 MSK_RES_ERR_INV_BKC, 701
 MSK_RES_ERR_INV_BKX, 701
 MSK_RES_ERR_INV_CONE_TYPE, 702
 MSK_RES_ERR_INV_CONE_TYPE_STR, 702
 MSK_RES_ERR_INV_CONIC_PROBLEM, 702
 MSK_RES_ERR_INV_MARKI, 702
 MSK_RES_ERR_INV_MARKJ, 702
 MSK_RES_ERR_INV_NAME_ITEM, 702
 MSK_RES_ERR_INV_NUMI, 702
 MSK_RES_ERR_INV_NUMJ, 702
 MSK_RES_ERR_INV_OPTIMIZER, 702
 MSK_RES_ERR_INV_PROBLEM, 702
 MSK_RES_ERR_INV_QCON_SUBI, 702
 MSK_RES_ERR_INV_QCON_SUBJ, 702
 MSK_RES_ERR_INV_QCON_SUBK, 702
 MSK_RES_ERR_INV_QCON_VAL, 702
 MSK_RES_ERR_INV_QOBJ_SUBI, 702
 MSK_RES_ERR_INV_QOBJ_SUBJ, 703
 MSK_RES_ERR_INV_QOBJ_VAL, 703
 MSK_RES_ERR_INV_SK, 703
 MSK_RES_ERR_INV_SK_STR, 703
 MSK_RES_ERR_INV_SKC, 703
 MSK_RES_ERR_INV_SKN, 703
 MSK_RES_ERR_INV_SKX, 703
 MSK_RES_ERR_INV_VAR_TYPE, 703
 MSK_RES_ERR_INVALID_ACCMODE, 703
 MSK_RES_ERR_INVALID_AIJ, 703
 MSK_RES_ERR_INVALID_AMPL_STUB, 703
 MSK_RES_ERR_INVALID_BARVAR_NAME, 703
 MSK_RES_ERR_INVALID_BRANCH_DIRECTION, 703

- MSK_RES_ERR_INVALID_BRANCH_PRIORITY, 703
 MSK_RES_ERR_INVALID_COMPRESSION, 703
 MSK_RES_ERR_INVALID_CON_NAME, 703
 MSK_RES_ERR_INVALID_CONE_NAME, 704
 MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_CONES, 704
 MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_GENERAL, 704
 MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_SYMMAT, 704
 MSK_RES_ERR_INVALID_FILE_NAME, 704
 MSK_RES_ERR_INVALID_FORMAT_TYPE, 704
 MSK_RES_ERR_INVALID_IDX, 704
 MSK_RES_ERR_INVALID_IOMODE, 704
 MSK_RES_ERR_INVALID_MAX_NUM, 704
 MSK_RES_ERR_INVALID_NAME_IN_SOL_FILE, 704
 MSK_RES_ERR_INVALID_NETWORK_PROBLEM, 704
 MSK_RES_ERR_INVALID_OBJ_NAME, 704
 MSK_RES_ERR_INVALID_OBJECTIVE_SENSE, 704
 MSK_RES_ERR_INVALID_PROBLEM_TYPE, 704
 MSK_RES_ERR_INVALID_SOL_FILE_NAME, 704
 MSK_RES_ERR_INVALID_STREAM, 705
 MSK_RES_ERR_INVALID_SURPLUS, 705
 MSK_RES_ERR_INVALID_SYMMAT_DIM, 705
 MSK_RES_ERR_INVALID_TASK, 705
 MSK_RES_ERR_INVALID_UTF8, 705
 MSK_RES_ERR_INVALID_VAR_NAME, 705
 MSK_RES_ERR_INVALID_WCHAR, 705
 MSK_RES_ERR_INVALID_WHICH_SOL, 705
 MSK_RES_ERR_LAST, 705
 MSK_RES_ERR_LASTI, 705
 MSK_RES_ERR_LASTJ, 705
 MSK_RES_ERR_LAU_ARG_K, 705
 MSK_RES_ERR_LAU_ARG_M, 705
 MSK_RES_ERR_LAU_ARG_N, 705
 MSK_RES_ERR_LAU_ARG_TRANS, 705
 MSK_RES_ERR_LAU_ARG_TRANSA, 705
 MSK_RES_ERR_LAU_ARG_TRANSB, 706
 MSK_RES_ERR_LAU_ARG_UPLO, 706
 MSK_RES_ERR_LAU_SINGULAR_MATRIX, 706
 MSK_RES_ERR_LAU_UNKNOWN, 706
 MSK_RES_ERR_LICENSE, 706
 MSK_RES_ERR_LICENSE_CANNOT_ALLOCATE, 706
 MSK_RES_ERR_LICENSE_CANNOT_CONNECT, 706
 MSK_RES_ERR_LICENSE_EXPIRED, 706
 MSK_RES_ERR_LICENSE_FEATURE, 706
 MSK_RES_ERR_LICENSE_INVALID_HOSTID, 706
 MSK_RES_ERR_LICENSE_MAX, 706
 MSK_RES_ERR_LICENSE_MOSEKLM_DAEMON, 706
 MSK_RES_ERR_LICENSE_NO_SERVER_LINE, 706
 MSK_RES_ERR_LICENSE_NO_SERVER_SUPPORT, 706
 MSK_RES_ERR_LICENSE_SERVER, 707
 MSK_RES_ERR_LICENSE_SERVER_VERSION, 707
 MSK_RES_ERR_LICENSE_VERSION, 707
 MSK_RES_ERR_LINK_FILE_DLL, 707
 MSK_RES_ERR_LIVING_TASKS, 707
 MSK_RES_ERR_LOWER_BOUND_IS_A_NAN, 707
 MSK_RES_ERR_LP_DUP_SLACK_NAME, 707
 MSK_RES_ERR_LP_EMPTY, 707
 MSK_RES_ERR_LP_FILE_FORMAT, 707
 MSK_RES_ERR_LP_FORMAT, 707
 MSK_RES_ERR_LP_FREE_CONSTRAINT, 707
 MSK_RES_ERR_LP_INCOMPATIBLE, 707
 MSK_RES_ERR_LP_INVALID_CON_NAME, 707
 MSK_RES_ERR_LP_INVALID_VAR_NAME, 708
 MSK_RES_ERR_LP_WRITE_CONIC_PROBLEM, 708
 MSK_RES_ERR_LP_WRITE_GECO_PROBLEM, 708
 MSK_RES_ERR_LU_MAX_NUM_TRIES, 708
 MSK_RES_ERR_MAX_LEN_IS_TOO_SMALL, 708
 MSK_RES_ERR_MAXNUMBARVAR, 708
 MSK_RES_ERR_MAXNUMCON, 708

- MSK_RES_ERR_MAXNUMCONE, 708
- MSK_RES_ERR_MAXNUMQNZ, 708
- MSK_RES_ERR_MAXNUMVAR, 708
- MSK_RES_ERR_MBT_INCOMPATIBLE, 708
- MSK_RES_ERR_MBT_INVALID, 708
- MSK_RES_ERR_MIO_INTERNAL, 708
- MSK_RES_ERR_MIO_INVALID_NODE_OPTIMIZER, 708
- MSK_RES_ERR_MIO_INVALID_ROOT_OPTIMIZER, 709
- MSK_RES_ERR_MIO_NO_OPTIMIZER, 709
- MSK_RES_ERR_MIO_NOT_LOADED, 709
- MSK_RES_ERR_MISSING_LICENSE_FILE, 709
- MSK_RES_ERR_MIXED_PROBLEM, 709
- MSK_RES_ERR_MPS_CONE_OVERLAP, 709
- MSK_RES_ERR_MPS_CONE_REPEAT, 709
- MSK_RES_ERR_MPS_CONE_TYPE, 709
- MSK_RES_ERR_MPS_DUPLICATE_Q_ELEMENT, 709
- MSK_RES_ERR_MPS_FILE, 709
- MSK_RES_ERR_MPS_INV_BOUND_KEY, 709
- MSK_RES_ERR_MPS_INV_CON_KEY, 709
- MSK_RES_ERR_MPS_INV_FIELD, 709
- MSK_RES_ERR_MPS_INV_MARKER, 709
- MSK_RES_ERR_MPS_INV_SEC_NAME, 709
- MSK_RES_ERR_MPS_INV_SEC_ORDER, 709
- MSK_RES_ERR_MPS_INVALID_OBJ_NAME, 710
- MSK_RES_ERR_MPS_INVALID_OBJSENSE, 710
- MSK_RES_ERR_MPS_MUL_CON_NAME, 710
- MSK_RES_ERR_MPS_MUL_CSEC, 710
- MSK_RES_ERR_MPS_MUL_QOBJ, 710
- MSK_RES_ERR_MPS_MUL_QSEC, 710
- MSK_RES_ERR_MPS_NO_OBJECTIVE, 710
- MSK_RES_ERR_MPS_NON_SYMMETRIC_Q, 710
- MSK_RES_ERR_MPS_NULL_CON_NAME, 710
- MSK_RES_ERR_MPS_NULL_VAR_NAME, 710
- MSK_RES_ERR_MPS_SPLITTED_VAR, 710
- MSK_RES_ERR_MPS_TAB_IN_FIELD2, 710
- MSK_RES_ERR_MPS_TAB_IN_FIELD3, 710
- MSK_RES_ERR_MPS_TAB_IN_FIELD5, 710
- MSK_RES_ERR_MPS_UNDEF_CON_NAME, 710
- MSK_RES_ERR_MPS_UNDEF_VAR_NAME, 711
- MSK_RES_ERR_MUL_A_ELEMENT, 711
- MSK_RES_ERR_NAME_IS_NULL, 711
- MSK_RES_ERR_NAME_MAX_LEN, 711
- MSK_RES_ERR_NAN_IN_BLC, 711
- MSK_RES_ERR_NAN_IN_BLX, 711
- MSK_RES_ERR_NAN_IN_BUC, 711
- MSK_RES_ERR_NAN_IN_BUX, 711
- MSK_RES_ERR_NAN_IN_C, 711
- MSK_RES_ERR_NAN_IN_DOUBLE_DATA, 711
- MSK_RES_ERR_NEGATIVE_APPEND, 711
- MSK_RES_ERR_NEGATIVE_SURPLUS, 711
- MSK_RES_ERR_NEWER_DLL, 711
- MSK_RES_ERR_NO_BARS_FOR_SOLUTION, 711
- MSK_RES_ERR_NO_BARX_FOR_SOLUTION, 711
- MSK_RES_ERR_NO_BASIS_SOL, 712
- MSK_RES_ERR_NO_DUAL_FOR_ITG_SOL, 712
- MSK_RES_ERR_NO_DUAL_INFEAS_CER, 712
- MSK_RES_ERR_NO_DUAL_INFO_FOR_ITG_SOL, 712
- MSK_RES_ERR_NO_INIT_ENV, 712
- MSK_RES_ERR_NO_OPTIMIZER_VAR_TYPE, 712
- MSK_RES_ERR_NO_PRIMAL_INFEAS_CER, 712
- MSK_RES_ERR_NO_SNX_FOR_BAS_SOL, 712
- MSK_RES_ERR_NO_SOLUTION_IN_CALLBACK, 712
- MSK_RES_ERR_NON_UNIQUE_ARRAY, 712
- MSK_RES_ERR_NONCONVEX, 712
- MSK_RES_ERR_NONLINEAR_EQUALITY, 712
- MSK_RES_ERR_NONLINEAR_FUNCTIONS_NOT_ALLOWED, 712
- MSK_RES_ERR_NONLINEAR_RANGED, 712
- MSK_RES_ERR_NR_ARGUMENTS, 712
- MSK_RES_ERR_NULL_ENV, 712
- MSK_RES_ERR_NULL_POINTER, 713
- MSK_RES_ERR_NULL_TASK, 713
- MSK_RES_ERR_NUMCONLIM, 713
- MSK_RES_ERR_NUMVARLIM, 713
- MSK_RES_ERR_OBJ_Q_NOT_NSD, 713
- MSK_RES_ERR_OBJ_Q_NOT_PSD, 713
- MSK_RES_ERR_OBJECTIVE_RANGE, 713

- MSK_RES_ERR_OLDER_DLL, 713
- MSK_RES_ERR_OPEN_DL, 713
- MSK_RES_ERR_OPF_FORMAT, 713
- MSK_RES_ERR_OPF_NEW_VARIABLE, 713
- MSK_RES_ERR_OPF_PREMATURE_EOF, 713
- MSK_RES_ERR_OPTIMIZER_LICENSE, 713
- MSK_RES_ERR_ORD_INVALID, 713
- MSK_RES_ERR_ORD_INVALID_BRANCH_DIR, 714
- MSK_RES_ERR_OVERFLOW, 714
- MSK_RES_ERR_PARAM_INDEX, 714
- MSK_RES_ERR_PARAM_IS_TOO_LARGE, 714
- MSK_RES_ERR_PARAM_IS_TOO_SMALL, 714
- MSK_RES_ERR_PARAM_NAME, 714
- MSK_RES_ERR_PARAM_NAME_DOU, 714
- MSK_RES_ERR_PARAM_NAME_INT, 714
- MSK_RES_ERR_PARAM_NAME_STR, 714
- MSK_RES_ERR_PARAM_TYPE, 714
- MSK_RES_ERR_PARAM_VALUE_STR, 714
- MSK_RES_ERR_PLATFORM_NOT_LICENSED, 714
- MSK_RES_ERR_POSTSOLVE, 714
- MSK_RES_ERR_PRO_ITEM, 714
- MSK_RES_ERR_PROB_LICENSE, 714
- MSK_RES_ERR_QCON_SUBI_TOO_LARGE, 714
- MSK_RES_ERR_QCON_SUBI_TOO_SMALL, 715
- MSK_RES_ERR_QCON_UPPER_TRIANGLE, 715
- MSK_RES_ERR_QOBJ_UPPER_TRIANGLE, 715
- MSK_RES_ERR_READ_FORMAT, 715
- MSK_RES_ERR_READ_LP_MISSING_END_TAG, 715
- MSK_RES_ERR_READ_LP_NONEXISTING_NAME, 715
- MSK_RES_ERR_REMOVE_CONE_VARIABLE, 715
- MSK_RES_ERR_REPAIR_INVALID_PROBLEM, 715
- MSK_RES_ERR_REPAIR_OPTIMIZATION_FAILED, 715
- MSK_RES_ERR_SEN_BOUND_INVALID_LO, 715
- MSK_RES_ERR_SEN_BOUND_INVALID_UP, 715
- MSK_RES_ERR_SEN_FORMAT, 715
- MSK_RES_ERR_SEN_INDEX_INVALID, 715
- MSK_RES_ERR_SEN_INDEX_RANGE, 715
- MSK_RES_ERR_SEN_INVALID_REGEX, 715
- MSK_RES_ERR_SEN_NUMERICAL, 716
- MSK_RES_ERR_SEN_SOLUTION_STATUS, 716
- MSK_RES_ERR_SEN_UNDEF_NAME, 716
- MSK_RES_ERR_SEN_UNHANDLED_PROBLEM_TYPE, 716
- MSK_RES_ERR_SIZE_LICENSE, 716
- MSK_RES_ERR_SIZE_LICENSE_CON, 716
- MSK_RES_ERR_SIZE_LICENSE_INTVAR, 716
- MSK_RES_ERR_SIZE_LICENSE_NUMCORES, 716
- MSK_RES_ERR_SIZE_LICENSE_VAR, 716
- MSK_RES_ERR_SOL_FILE_INVALID_NUMBER, 716
- MSK_RES_ERR_SOLITEM, 716
- MSK_RES_ERR_SOLVER_PROBTYPE, 716
- MSK_RES_ERR_SPACE, 716
- MSK_RES_ERR_SPACE_LEAKING, 716
- MSK_RES_ERR_SPACE_NO_INFO, 716
- MSK_RES_ERR_SYM_MAT_DUPLICATE, 717
- MSK_RES_ERR_SYM_MAT_INVALID_COL_INDEX, 717
- MSK_RES_ERR_SYM_MAT_INVALID_ROW_INDEX, 717
- MSK_RES_ERR_SYM_MAT_INVALID_VALUE, 717
- MSK_RES_ERR_SYM_MAT_NOT_LOWER_TRINGULAR, 717
- MSK_RES_ERR_TASK_INCOMPATIBLE, 717
- MSK_RES_ERR_TASK_INVALID, 717
- MSK_RES_ERR_THREAD_COND_INIT, 717
- MSK_RES_ERR_THREAD_CREATE, 717
- MSK_RES_ERR_THREAD_MUTEX_INIT, 717
- MSK_RES_ERR_THREAD_MUTEX_LOCK, 717
- MSK_RES_ERR_THREAD_MUTEX_UNLOCK, 717
- MSK_RES_ERR_TOO_MANY_CONCURRENT_TASKS, 717
- MSK_RES_ERR_TOO_SMALL_MAX_NUM_NZ, 717
- MSK_RES_ERR_TOO_SMALL_MAXNUMANZ, 718

- MSK_RES_ERR_UNB_STEP_SIZE, 718
 MSK_RES_ERR_UNDEF_SOLUTION, 718
 MSK_RES_ERR_UNDEFINED_OBJECTIVE_SENSE, 718
 MSK_RES_ERR_UNHANDLED_SOLUTION_STATUS, 718
 MSK_RES_ERR_UNKNOWN, 718
 MSK_RES_ERR_UPPER_BOUND_IS_A_NAN, 718
 MSK_RES_ERR_UPPER_TRIANGLE, 718
 MSK_RES_ERR_USER_FUNC_RET, 718
 MSK_RES_ERR_USER_FUNC_RET_DATA, 718
 MSK_RES_ERR_USER_NLO_EVAL, 718
 MSK_RES_ERR_USER_NLO_EVAL_HESSUBI, 718
 MSK_RES_ERR_USER_NLO_EVAL_HESSUBJ, 719
 MSK_RES_ERR_USER_NLO_FUNC, 719
 MSK_RES_ERR_WHICHITEM_NOT_ALLOWED, 719
 MSK_RES_ERR_WHICHSOL, 719
 MSK_RES_ERR_WRITE_LP_FORMAT, 719
 MSK_RES_ERR_WRITE_LP_NON_UNIQUE_NAME, 719
 MSK_RES_ERR_WRITE_MPS_INVALID_NAME, 719
 MSK_RES_ERR_WRITE_OPF_INVALID_VAR_NAME, 719
 MSK_RES_ERR_WRITING_FILE, 719
 MSK_RES_ERR_XML_INVALID_PROBLEM_TYPE, 719
 MSK_RES_ERR_Y_IS_UNDEFINED, 719
 MSK_RES_OK, 719
 MSK_RES_TRM_INTERNAL, 719
 MSK_RES_TRM_INTERNAL_STOP, 719
 MSK_RES_TRM_MAX_ITERATIONS, 719
 MSK_RES_TRM_MAX_NUM_SETBACKS, 720
 MSK_RES_TRM_MAX_TIME, 720
 MSK_RES_TRM_MIO_NEAR_ABS_GAP, 720
 MSK_RES_TRM_MIO_NEAR_REL_GAP, 720
 MSK_RES_TRM_MIO_NUM_BRANCHES, 720
 MSK_RES_TRM_MIO_NUM_RELAXS, 720
 MSK_RES_TRM_NUM_MAX_NUM_INT_SOLUTIONS, 720
 MSK_RES_TRM_NUMERICAL_PROBLEM, 720
 MSK_RES_TRM_OBJECTIVE_RANGE, 720
 MSK_RES_TRM_STALL, 720
 MSK_RES_TRM_USER_CALLBACK, 721
 MSK_RES_WRN_ANA_ALMOST_INT_BOUNDS, 721
 MSK_RES_WRN_ANA_C_ZERO, 721
 MSK_RES_WRN_ANA_CLOSE_BOUNDS, 721
 MSK_RES_WRN_ANA_EMPTY_COLS, 721
 MSK_RES_WRN_ANA_LARGE_BOUNDS, 721
 MSK_RES_WRN_CONSTRUCT_INVALID_SOL_ITG, 721
 MSK_RES_WRN_CONSTRUCT_NO_SOL_ITG, 721
 MSK_RES_WRN_CONSTRUCT_SOLUTION_INFEAS, 721
 MSK_RES_WRN_DROPPED_NZ_QOBJ, 721
 MSK_RES_WRN_DUPLICATE_BAR_VARIABLE_NAMES, 721
 MSK_RES_WRN_DUPLICATE_CONE_NAMES, 721
 MSK_RES_WRN_DUPLICATE_CONSTRAINT_NAMES, 721
 MSK_RES_WRN_DUPLICATE_VARIABLE_NAMES, 721
 MSK_RES_WRN_ELIMINATOR_SPACE, 722
 MSK_RES_WRN_EMPTY_NAME, 722
 MSK_RES_WRN_IGNORE_INTEGER, 722
 MSK_RES_WRN_INCOMPLETE_LINEAR_DEPENDENCY_CHECK, 722
 MSK_RES_WRN_LARGE_AIJ, 722
 MSK_RES_WRN_LARGE_BOUND, 722
 MSK_RES_WRN_LARGE_CJ, 722
 MSK_RES_WRN_LARGE_CON_FX, 722
 MSK_RES_WRN_LARGE_LO_BOUND, 722
 MSK_RES_WRN_LARGE_UP_BOUND, 722
 MSK_RES_WRN_LICENSE_EXPIRE, 722
 MSK_RES_WRN_LICENSE_FEATURE_EXPIRE, 722
 MSK_RES_WRN_LICENSE_SERVER, 722
 MSK_RES_WRN_LP_DROP_VARIABLE, 722
 MSK_RES_WRN_LP_OLD_QUAD_FORMAT, 723
 MSK_RES_WRN_MIO_INFEASIBLE_FINAL, 723
 MSK_RES_WRN_MPS_SPLIT_BOUNDS_VECTOR, 723

- MSK_RES_WRN_MPS_SPLIT_RAN_VECTOR, 725
- 723
- MSK_RES_WRN_MPS_SPLIT_RHS_VECTOR, scaling, 218
- 723 scopt
- MSK_RES_WRN_NAME_MAX_LEN, 723 compscopt, 102
- MSK_RES_WRN_NO_DUALIZER, 723 semidefinite optimization, 51
- MSK_RES_WRN_NO_GLOBAL_OPTIMIZER, semidefinite problem example, 52
- 723 sensitivity analysis, 265
- MSK_RES_WRN_NO_NONLINEAR_FUNCTION_WRITE, basis type, 267
- 723 optimal partition type, 268
- MSK_RES_WRN_NZ_IN_UPR_TRI, 723 sensitivityreport, 548
- MSK_RES_WRN_OPEN_PARAM_FILE, 723 separable convex optimization, 100
- MSK_RES_WRN_PARAM_IGNORED_CMIO, setdefaults, 548
- 723 shadow price, 266
- MSK_RES_WRN_PARAM_NAME_DOU, 723 simplex optimizer, 224
- MSK_RES_WRN_PARAM_NAME_INT, 723 sktostr, 549
- MSK_RES_WRN_PARAM_NAME_STR, 723 solstatostr, 549
- MSK_RES_WRN_PARAM_STR_VALUE, 724 solution
- MSK_RES_WRN_PRESOLVE_OUTOFSPACE, optimal, 203
- 724 primal-dual, 202
- MSK_RES_WRN_QUAD_CONES_WITH_ROOT_FIXED_AT_ZERO, solution summary, 69, 78
- 724 solutiondef, 550
- MSK_RES_WRN_RQUAD_CONES_WITH_ROOT_FIXED_AT_ZERO, solutionsummary, 550
- 724 solvewithbasis, 551
- MSK_RES_WRN_SOL_FILE_IGNORED_CON, sparse vector, 94
- 724 startstat, 552
- MSK_RES_WRN_SOL_FILE_IGNORED_VAR, stopstat, 552
- 724 strdupdbgen, 553
- MSK_RES_WRN_SOL_FILTER, 724 strdupdbgtask, 553
- MSK_RES_WRN_SPAR_MAX_LEN, 724 strdupenv, 554
- MSK_RES_WRN_TOO_FEW_BASIS_VARS, 724 strduptask, 554
- MSK_RES_WRN_TOO_MANY_BASIS_VARS, stream
- 724 attaching, 37
- MSK_RES_WRN_TOO_MANY_THREADS_CONCURRENT, string
- 724 UTF8, 167
- MSK_RES_WRN_UNDEF_SOL_FILE_NAME, unicode, 167
- 724 strtocointype, 555
- MSK_RES_WRN_USING_GENERIC_NAMES, strtosk, 555
- 724 syeig, 556
- MSK_RES_WRN_WRITE_CHANGED_NAMES, syevd, 556
- 724 symnamtovalue, 557
- MSK_RES_WRN_WRITE_DISCARDED_CFIX, syrk, 558
- 725 task, creating, 30
- MSK_RES_WRN_ZERO_AIJ, 725 thread safety, 200
- MSK_RES_WRN_ZEROS_IN_SPARSE_COL, 725 toconic, 559
- MSK_RES_WRN_ZEROS_IN_SPARSE_ROW, typedef

- MSKboolean_t, 284
- MSKcallbackfunc, 284
- MSKcallocfunc, 285
- MSKenv_t, 284
- MSKexitfunc, 285
- MSKfreefunc, 286
- MSKint32t, 284
- MSKint64t, 284
- MSKmallocfunc, 286
- MSKnlgetspfunc, 286
- MSKnlgetvafunc, 288
- MSKreallocfunc, 290
- MSKrealt, 284
- MSKresponsefunc, 291
- MSKstreamfunc, 291
- MSKstring_t, 284
- MSKtask_t, 284
- MSKuserhandle_t, 284
- MSKwchart, 284
- unicode string, 167
- unlinkfuncfromenvstream, 559
- unlinkfuncfromtaskstream, 560
- updatesolutioninfo, 560
- UTF8, 167
- utf8towchar, 561
- valgrind, 200
- variables
 - decision, 201, 212, 768
 - lower limit, 202, 212, 768
 - number of, 33
 - upper limit, 202, 212, 768
- vector format
 - full, 94
 - sparse, 94
- wchartoutf8, 561
- whichparam, 562
- writebranchpriorities, 562
- writedata, 563
- writeparamfile, 564
- writesolution, 564
- writetask, 565
- xml format, 796