

# The SFrame Format

---

Version 1

Indu Bhagat

---

Copyright © 2021-2022 Free Software Foundation, Inc.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU General Public License, Version 3 or any later version published by the Free Software Foundation. A copy of the license is included in the section entitled “GNU General Public License”.

# Table of Contents

<b>Overview</b> .....	<b>1</b>
<b>1 SFrame section</b> .....	<b>2</b>
1.1 SFrame Preamble .....	2
1.1.1 SFrame endianness .....	2
1.1.2 SFrame version .....	2
1.1.3 SFrame flags .....	3
1.2 SFrame Header .....	3
1.2.1 SFrame ABI/arch identifier .....	5
1.3 SFrame FDE .....	5
1.3.1 The SFrame FDE info word .....	6
1.3.2 The SFrame FDE types .....	6
1.3.3 The SFrame FRE types .....	7
1.4 SFrame FRE .....	7
1.4.1 The SFrame FRE info word .....	8
<b>Index</b> .....	<b>10</b>

## Overview

The SFrame unwind information is provided in a loaded section, known as the `.sframe` section. When available, the `.sframe` section appears in a new segment of its own, `PT_GNU_SFRAME`.

The SFrame format is currently supported only for select ABIs, namely, AMD64 and AAPCS64.

The contents of the SFrame section are stored in the target endianness, i.e., in the endianness of the system on which the section is targetted to be used. An SFrame section reader may use the magic number in the SFrame header to identify the endianness of the SFrame section.

Addresses in this specification are expressed in bytes.

The associated API to decode, probe and encode the SFrame section, provided via `libsframe`, is not accompanied here at this time. This will be added later.

This document is intended to be in sync with the C code in `sframe.h`. Please report discrepancies between the two, if any.

# 1 SFrame section

The SFrame section consists of an SFrame header, starting with a preamble, and two other sub-sections, namely the SFrame Function Descriptor Entry (SFrame FDE) sub-section, and the SFrame Frame Row Entry (SFrame FRE) sub-section.

## 1.1 SFrame Preamble

The preamble is a 32-bit packed structure; the only part of the SFrame whose format cannot vary between versions.

```
typedef struct sframe_preamble
{
    uint16_t sfp_magic;
    uint8_t sfp_version;
    uint8_t sfp_flags;
} ATTRIBUTE_PACKED sframe_preamble;
```

All values are stored in the endianness of the target system for which the SFrame section is intended. Further details:

Offset	Name	Description
0x00	uint16_t sfp_magic	The magic number for SFrame section: 0xdee2. Defined as a macro <code>SFRAME_MAGIC</code> .
0x02	uint8_t sfp_version	The version number of this SFrame section. See Section 1.1.2 [SFrame version], page 2, for the set of valid values. Current version is <code>SFRAME_VERSION_1</code> .
0x03	uint8_t sfp_flags	Flags (section-wide) for this SFrame section. See Section 1.1.3 [SFrame flags], page 3, for the set of valid values.

### 1.1.1 SFrame endianness

SFrame sections are stored in the target endianness of the system that consumes them. The SFrame library (`libsframe`) can, however, detect whether to endian-flip an SFrame section at decode time, by inspecting the `sfp_magic` field in the SFrame header (If it appears as 0xe2de, endian-flipping is needed).

### 1.1.2 SFrame version

The version of the SFrame format can be determined by inspecting `sfp_version`. The following versions are currently valid:

Version	Number	Description
<code>SFRAME_VERSION_1</code>	1	First version, under development.

This section documents `SFRAME_VERSION_1`.

### 1.1.3 SFrame flags

The preamble contains bitflags in its `sfp_flags` field that describe various section-wide properties.

The following flags are currently defined.

Flag	Versions	Value	Meaning
SFRAME_F_FDE_SORTED	All	0x1	Function Descriptor Entries are sorted on PC.
SFRAME_F_FRAME_POINTER	All	0x2	Functions preserve frame-pointer.

Further flags may be added in future.

## 1.2 SFrame Header

The SFrame header is the first part of an SFrame section. It begins with the SFrame preamble. All parts of it other than the preamble (see Section 1.1 [SFrame Preamble], page 2) can vary between SFrame file versions. It contains things that apply to the section as a whole, and offsets to the various other sub-sections defined in the format. As with the rest of the SFrame section, all values are stored in the endianness of the target system.

The two sub-sections tile the SFrame section: each section runs from the offset given until the start of the next section. An explicit length is given for the last sub-section, the SFrame Frame Row Entry (SFrame FRE) sub-section.

```
typedef struct sframe_header
{
    sframe_preamble sfh_preamble;
    uint8_t sfh_abi_arch;
    int8_t sfh_cfa_fixed_fp_offset;
    int8_t sfh_cfa_fixed_ra_offset;
    uint8_t sfh_auxhdr_len;
    uint32_t sfh_num_fdes;
    uint32_t sfh_num_fres;
    uint32_t sfh_fre_len;
    uint32_t sfh_fdeoff;
    uint32_t sfh_freoff;
} ATTRIBUTE_PACKED sframe_header;
```

The sub-section offsets, namely `sfh_fdeoff` and `sfh_freoff`, in the SFrame header are relative to the *end* of the SFrame header; they are each an offset in bytes into the SFrame section where the SFrame FDE sub-section and the SFrame FRE sub-section respectively start.

SFrame header allows specifying explicitly the fixed offsets from CFA, if any, from which FP or RA may be recovered. For example, in AMD64, the stack offset of the return address is `CFA - 8`. Since this offset is in close vicinity with the CFA in most ABIs, `sfh_cfa_fixed_fp_offset` and `sfh_cfa_fixed_ra_offset` are limited to signed 8-bit integers.

SFrame format has provisioned for future ABIs/architectures that it may support. The `sframe_header` structure provides an unsigned 8-bit integral field to denote the size of an

auxilliary SFrame header. The auxilliary SFrame header follows right after the `sframe_header` structure. As for the offset calculations, the *end* of SFrame header must be the end of the auxilliary SFrame header, if the latter is present.

Tieing it all together:

Offset	Name	Description
0x00	<code>sframe_preamble sfh_preamble</code>	The SFrame preamble. See Section 1.1 [SFrame Preamble], page 2.
0x04	<code>uint8_t sfh_abi_arch</code>	The ABI/arch identifier. See Section 1.2.1 [SFrame ABI/arch identifier], page 5.
0x05	<code>int8_t sfh_cfa_fixed_fp_offset</code>	The CFA fixed FP offset, if any.
0x06	<code>int8_t sfh_cfa_fixed_ra_offset</code>	The CFA fixed RA offset, if any.
0x07	<code>uint8_t sfh_auxhdr_len</code>	Size in bytes of the auxilliary header that follows the <code>sframe_header</code> structure.
0x08	<code>uint32_t sfh_num_fdes</code>	The number of SFrame FDEs in the section.
0xc	<code>uint32_t sfh_num_fres</code>	The number of SFrame FREs in the section.
0x10	<code>uint32_t sfh_fre_len</code>	The length in bytes of the SFrame FRE sub-section.
0x14	<code>uint32_t sfh_fdeoff</code>	The offset in bytes of the SFrame FDE sub-section. This sub-section contains <code>sfh_num_fdes</code> number of fixed-length array elements. The array element is of type SFrame function descriptor entry, each providing a high-level function description for backtracing. See Section 1.3 [SFrame Function Descriptor Entries], page 5.

0x18	<code>uint32_t sfh_freoff</code>	The offset in bytes of the SFrame FRE sub-section, the core of the SFrame section, which describes the unwind information using variable-length array elements. See Section 1.4 [SFrame Frame Row Entries], page 7.
------	----------------------------------	---

### 1.2.1 SFrame ABI/arch identifier

SFrame header identifies the ABI/arch of the target system for which the executable and it's unwind information is intended. There are currently three identifiable ABI/arch values in the format.

ABI/arch Identifier	Value	Description
<code>SFRAME_ABI_AARCH64_ENDIAN_BIG</code>	1	AARCH64 big-endian
<code>SFRAME_ABI_AARCH64_ENDIAN_LITTLE</code>	2	AARCH64 little-endian
<code>SFRAME_ABI_AMD64_ENDIAN_LITTLE</code>	3	AMD64 little-endian

The presence of an explicit identification of ABI/arch in SFrame may allow unwinders to make certain ABI-specific decisions.

## 1.3 SFrame FDE

The SFrame Function Descriptor Entry sub-section is a sorted array of fixed-length SFrame function descriptor entries (SFrame FDEs). Each SFrame FDE is a packed structure which contains information to describe a function's unwind information at a high-level.

```
typedef struct sfame_func_desc_entry
{
    int32_t sfde_func_start_address;
    uint32_t sfde_func_size;
    uint32_t sfde_func_start_fre_off;
    uint32_t sfde_func_num_fres;
    uint8_t sfde_func_info;
} ATTRIBUTE_PACKED sfame_func_desc_entry;
```

`sfde_func_start_fre_off` is the offset to the first SFrame FRE for the function. This offset is relative to the *end of the SFrame FDE* sub-section (unlike the offsets in the SFrame header, which are relative to the *end* of the SFrame header).

`sfde_func_info` is the "info word", containing information on the FRE type and the FDE type for the function See Section 1.3.1 [The SFrame FDE info word], page 6.

Following table describes each component of the SFrame FDE structure:



Offset	Name	Description
0x00	<code>int32_t sfde_func_start_address</code>	Signed 32-bit integral field denoting the virtual memory address of the described function.
0x04	<code>uint32_t sfde_func_size</code>	Unsigned 32-bit integral field specifying the size of the function in bytes.
0x08	<code>uint32_t sfde_func_start_fre_off</code>	Unsigned 32-bit integral field specifying the offset in bytes of the function's first SFrame FRE in the SFrame section.
0x0c	<code>uint32_t sfde_func_num_fres</code>	Unsigned 32-bit integral field specifying the total number of SFrame FREs used for the function.
0x10	<code>uint8_t sfde_func_info</code>	The SFrame FDE info word. See Section 1.3.1 [The SFrame FDE info word], page 6.

### 1.3.1 The SFrame FDE info word

The info word is a bitfield split into three parts. From MSB to LSB:

Bit offset	Name	Description
7–5	<code>unused</code>	Unused bits.
4	<code>fdetype</code>	<code>SFRAME_FDE_TYPE_PCMASK</code> (1) or <code>SFRAME_FDE_TYPE_PCINC</code> (0). See Section 1.3.2 [The SFrame FDE types], page 6.
0–3	<code>fretype</code>	Choice of three SFrame FRE types. See Section 1.3.3 [The SFrame FRE types], page 7.

### 1.3.2 The SFrame FDE types

SFrame format defines two types of FDE entries. The choice of which SFrame FDE type to use is made based on the instruction patterns in the relevant program stub.

An SFrame FDE of type `SFRAME_FDE_TYPE_PCINC` is an indication that the PCs in the FREs should be treated as increments in bytes. This is used for the bulk of the executable code of a program, which contains instructions with no specific pattern.

In contrast, an SFrame FDE of type `SFRAME_FDE_TYPE_PCMASK` is an indication that the PCs in the FREs should be treated as masks. This type is useful for the cases where a small pattern of instructions in a program stub is used repeatedly for a specific functionality. Typical usecases are `pltN` entries and trampolines.

Name of SFrame FDE type	Value	Description
SFRAME_FDE_TYPE_PCIN0		Unwinders perform a (PC >= FRE_START_ADDR) to look up a matching FRE.
SFRAME_FDE_TYPE_PC_MASK		Unwinders perform a (PC & FRE_START_ADDR_AS_MASK >= FRE_START_ADDR_AS_MASK) to look up a matching FRE.

### 1.3.3 The SFrame FRE types

A real world application can have functions of size big and small. SFrame format defines three types of SFrame FRE entries to represent the unwind information for such a variety of function sizes. These representations vary in the number of bits needed to encode the start address offset in the SFrame FRE.

The following constants are defined and used to identify the SFrame FRE types:

Name	Value	Description
SFRAME_FRE_TYPE_ADDR1	0	The start address offset (in bytes) of the SFrame FRE is an unsigned 8-bit value.
SFRAME_FRE_TYPE_ADDR2	1	The start address offset (in bytes) of the SFrame FRE is an unsigned 16-bit value.
SFRAME_FRE_TYPE_ADDR4	2	The start address offset (in bytes) of the SFrame FRE is an unsigned 32-bit value.

A single function must use the same type of FRE throughout. The choice of which SFrame FRE is used to encode the unwind information of a function, is stored in the See Section 1.3.1 [The SFrame FDE info word], page 6.

## 1.4 SFrame FRE

The SFrame Frame Row Entry sub-section contains the core of the unwind information.

An SFrame Frame Row Entry is a self-sufficient record containing SFrame unwind info for a range of contiguous addresses, starting at the specified offset from the start of the function. Each SFrame Frame Row Entry is followed by S\*N bytes, where:

- S is the size of the stack frame offset for the FRE, and
- N is the number of stack frame offsets in the FRE

The stack offsets, following the FRE, are interpreted in order as follows:

- The first offset is always used to locate the CFA, by interpreting it as:  $CFA = BASE\_REG + offset1$ .
- If RA is being tracked, the second offset is always used to locate the RA, by interpreting it as:  $RA = CFA + offset2$ . If RA is *not* being tracked *and* FP is being tracked, the second offset will be used to locate the FP, by interpreting it as:  $FP = CFA + offset2$ .
- If both RA and FP are being tracked, the third offset will be used to locate the FP, by interpreting it as  $FP = CFA + offset3$ .

The entities S, N and BASE\_REG are identified using the SFrame FRE info word, a.k.a. the `sframe_fre_info`. See Section 1.4.1 [The SFrame FRE info word], page 8.

Following are the definitions of the allowed SFrame FRE:

```
typedef struct sframe_frame_row_entry_addr1
{
    uint8_t sfre_start_address;
    sframe_fre_info sfre_info;
} ATTRIBUTE_PACKED sframe_frame_row_entry_addr1;

typedef struct sframe_frame_row_entry_addr2
{
    uint16_t sfre_start_address;
    sframe_fre_info sfre_info;
} ATTRIBUTE_PACKED sframe_frame_row_entry_addr2;

typedef struct sframe_frame_row_entry_addr4
{
    uint32_t sfre_start_address;
    sframe_fre_info sfre_info;
} ATTRIBUTE_PACKED sframe_frame_row_entry_addr4;
```

`sfre_start_address` is an unsigned 8-bit/16-bit/32-bit integral field identifies the start address of the range of program counters, for which the SFrame FRE applies. The value encoded in the `sfre_start_address` field is the offset in bytes of the start address of the SFrame FRE, from the start address of the function.

Further FRE types may be added in future.

### 1.4.1 The SFrame FRE info word

The SFrame FRE info word is a bitfield split into four parts. From MSB to LSB:

Bit offset	Name	Description
7	<code>fre_mangled_ra_p</code>	Indicate whether the return address is mangled with any authorization bits (signed RA).
5-6	<code>fre_offset_size</code>	Size of stack offsets in bytes. Valid values are <code>SFRAME_FRE_OFFSET_1B</code> , <code>SFRAME_FRE_OFFSET_2B</code> , and <code>SFRAME_FRE_OFFSET_4B</code> .

1-4	<code>fre_offset_count</code>	A value of upto 3 is allowed to track all three of CFA, FP and RA.
0	<code>fre_cfa_base_reg_id</code>	Distinguish between SP or FP based CFA recovery.

Name	Value	Description
<code>SFRAME_FRE_OFFSET_1B</code>	0	All stack offsets following the fixed-length FRE structure are 1 byte long.
<code>SFRAME_FRE_OFFSET_2B</code>	1	All stack offsets following the fixed-length FRE structure are 2 bytes long.
<code>SFRAME_FRE_OFFSET_4B</code>	2	All stack offsets following the fixed-length FRE structure are 4 bytes long.

# Index

## E

endianness ..... 2

## O

Overview ..... 1

## S

SFrame ABI/arch identifier ..... 5  
 SFrame FDE ..... 5  
 SFrame flags ..... 3  
 SFrame FRE ..... 7  
 SFrame header ..... 3  
 SFrame preamble ..... 2  
 SFrame section ..... 2  
 SFrame versions ..... 2

## T

The SFrame FDE info word ..... 6  
 The SFrame FRE info word ..... 8