

Anonymous Call Mobile SDK User Guide for Android

Version Number: **4.5.9**

Revision Date: **May 02, 2019**

Table of Contents

1. [Anonymous Call Mobile SDK overview](#)
 1. [What's in this document?](#)
 2. [Before you start developing your application](#)
2. [Get Started](#)
 1. [Create your Android project](#)
 2. [Use the Anonymous Call Mobile SDK in your Android project](#)
 3. [Enable background processing](#)
 4. [Set application configuration](#)
 5. [Set up logging functionality](#)
3. [Basic Usage](#)
 1. [Listen Call Service notifications](#)
 2. [Add STUN/TURN servers](#)
 1. [Add SPiDR's \(Kandy Link\) TURN server](#)
 2. [Add an external TURN/STUN server](#)
 3. [Make an anonymous call](#)
 4. [Make a time-limited token based anonymous call](#)
 5. [End an anonymous call](#)
 6. [End calls with reason](#)
 7. [Supported call end reasons](#)
 1. [CallState class fields](#)
 8. [Get active call list](#)
 9. [Mid-Call operations](#)
 1. [Mute/Unmute Call](#)
 2. [Video Start/Stop on a Call](#)
 3. [Hold/Unhold Call and Double Hold](#)
 10. [Change default camera device \(front or back\)](#)
 11. [Change camera orientation](#)
 12. [Change local video resolution or camera position](#)
 13. [Send DTMF \(Dual-Tone Multi-Frequency\) signals](#)
 14. [Get media attributes](#)
4. [Advanced Usage](#)

1. [Send Custom Parameters for an anonymous call](#)
 2. [Set ICE options](#)
 3. [Early media](#)
 4. [Set codec priority](#)
 5. [Replace codec payload number](#)
 6. [Control audio bandwidth](#)
 7. [Get additional information about a call](#)
 8. [Retrieve audio and video RTP/RTCP statistics](#)
5. [Appendices](#)
1. [Appendix A: High-level Anonymous Call Mobile SDK structure](#)
 2. [Appendix B: Call state transitions](#)
 1. [Anonymous call state transitions](#)
 3. [Appendix C: Performance management](#)
 4. [Appendix D: Detailed Configurations](#)
 5. [Appendix E: Examples of call statistic data](#)
 6. [Appendix F: ProGuard support on Android](#)
 1. [ProGuard configuration without obfuscation](#)
 2. [ProGuard configuration with obfuscation](#)
 3. [ProGuard configuration for production](#)

Anonymous Call Mobile SDK overview

The SPiDR/Kandy Link Anonymous Call Mobile Software Development Kit (SDK) defines a library implementation supporting SPiDR/Kandy Link platform features like anonymous call management (allowing unregistered users to place voice or video calls) and WebRTC on Android. You can use this library implementation to integrate SPiDR/Kandy Link services and WebRTC into your native mobile applications to create new, innovative user experiences.

The Anonymous Call Mobile SDK has the following characteristics:

- supports REST over HTTP/HTTPS for integration with the presentation layer of SPiDR/Kandy Link
- supports WebSocket for notification
- access to REST APIs provided by Ribbon's Kandy platform

See [Appendix A: High-level Anonymous Call Mobile SDK structure](#) for a high-level view of the Anonymous Call Mobile SDK and its sub-modules.

The Anonymous Call Mobile SDK for Android is compatible with Android 4.1.x-9.x and has been tested on the Nexus 7, Nexus 5, Samsung Note 3, Samsung Note 5, Samsung S7, HTC Desire 626, HTC One A9, HTC 10, LG G2, LG G3, LG G5, LG G6, SONY XPERIA Z5, SONY XPERIA XZ, General Mobile GM 5+, Huawei P10.

What's in this document?

This document provides help getting started developing your mobile application using the Anonymous Call Mobile SDK for Android. This guide contains:

- Steps to create your Android project using the Anonymous Call Mobile SDK
- Sample code to illustrate common tasks

Before you start developing your application

The following items need to be complete prior to beginning work on your application:

- You have downloaded the MobileSDKAnonymous package from <http://developer.genband.com/MobileSDK> .
- You have extracted the contents of the MobileSDKAnonymous package and located:
 - The MobileSDKAnonymous jar file
 - The libjingle_peerconnection_so.so file
- Your Android Studio development environment is set up and ready for new projects.
- You are familiar with Android development fundamentals.
- You know the IP address and port of the SPiDR/Kandy Link server.


Get Started

This section provides an example of creating your Android project and using the Anonymous Call Mobile SDK in your project. Android Studio 3.3 is used for this example, but you may use your development environment of choice to create your project.


Create your Android project

The following procedure uses Android Studio IDE to illustrate adding the Anonymous Call Mobile SDK library file to the Android application's build path.

1. Open the development environment (in this example, Android Studio).
2. Click **Start a new Android Studio project**.



3. Select an activity or leave as default (Empty Activity) and click **Next**.




4. Fill in the configurations for your project.

- Type your project's **Name**, **Package name** and **Save location**. Select the **Language** you prefer your project.
- Select minimum Android SDK version for phone and tablet (API Level 16 is recommended).

Note that, this is the minimum Android SDK API version that the demo application supports.

For the target SDK version, Google suggests to set API Level 26 or higher. Target SDK can be changed on **build.gradle** file after the project creation.



Create New Project

Configure your project

Name
AnonymousCallMobileSDKDemo

Package name
com.rbbn.anonymouscallmobilesdksdemo

Save location
/Users/user1/AndroidProjects/AnonymousCallMobileSDKDemo

Language
Java

Minimum API level
API 16: Android 4.1 (Jelly Bean)

Empty Activity
Creates a new empty activity


Information
Your app will run on approximately **99.6%** of devices.
[Help me choose](#)

☐ This project will support instant apps

☐ Use AndroidX artifacts


Buttons: Cancel, Previous, Next, Finish

5. Copy the Anonymous Call Mobile SDK jar file under your application's **libs** folder.




6. In MobileSDKAnonymous-x.x.x.zip”, along with the MobileSDKAnonymous_x.x.x.jar, you will also find native WebRTC library called "libjingle_peerconnection_so.so", compiled for different architectures.

In Android projects the ones in “armeabi” and “arm64-v8a” folders will be used. If you wish to use simulator for testing, then you should use the “x86” library as well. Move those folders named under the **libs** folder in the project along with the “libjingle_peerconnection_so.so” files, described above, inside them.




7. Open **build.gradle** file, located under **app** module of **AnonymousCallMobileSDKDemo** project. Add the configuration script below to the file, in order the application to locate libjingle library (and other JNI libraries if used in the application).

```
android {  
    .  
    .  
    .  
    sourceSets {  
        main {  
            jniLibs.srcDirs = ['libs']  
        }  
    }  
}
```



8. An Android application project must be compatible with Java 8 when it is using Anonymous Call Mobile SDK library. This necessity comes from the WebRTC library, its code is dependent on some Java 8 features. In order to set this compliance, open **build.gradle** file, located under **app** module of **AnonymousCallMobileSDKDemo** project. Add the configuration script below to the file.

```
android {
    .
    .
    .
    compileOptions {
        targetCompatibility 1.8
        sourceCompatibility 1.8
    }
}
```




Use the Anonymous Call Mobile SDK in your Android project

Once the library is attached to the Android project, the Anonymous Call Mobile SDK can be used by defining the necessary import items.

The following is an example using the Anonymous Call Mobile SDK in Android:

1. Locate and open **AndroidManifest.xml**.



2. Add the following permissions to the manifest file:


```

<uses-feature android:glEsVersion="0x00020000" android:required="true" />
<uses-feature android:name="android.hardware.camera" />
<uses-feature android:name="android.hardware.camera.autofocus" />

<uses-permission android:name="android.permission.INTERNET" />
<uses-permission android:name="android.permission.ACCESS_NETWORK_STATE" />
<uses-permission android:name="android.permission.MODIFY_AUDIO_SETTINGS" />
<uses-permission android:name="android.permission.RECORD_AUDIO" />
<uses-permission android:name="android.permission.CAMERA" />

```

3. In your project folder, navigate to **res > layout** and open **activity_main.xml** to create your UI.



4. You can create your UI in a graphical mode (if available) or in xml editor mode. In this example, editing will be done in the xml view.
5. Choose a layout for your UI. In Android, developers can use a variety of layouts for UI. In this example, we will use `LinearLayout (Vertical)` for the UI and set the orientation vertical. The example layout below also contains two buttons and two video views in the `LinearLayout`.


```
<?xml version="1.0" encoding="utf-8"?>
<LinearLayout xmlns:android="http://schemas.android.com/apk/res/android"
    android:layout_width="match_parent"
    android:layout_height="match_parent"
    android:orientation="vertical">

    <com.genband.mobile.core.WebRTC.view.VideoView
        android:id="@+id/remoteVideoView"
        android:layout_width="120dp"
        android:layout_height="90dp"
    />

    <com.genband.mobile.core.WebRTC.view.VideoView
        android:id="@+id/localVideoView"
        android:layout_width="120dp"
        android:layout_height="90dp"
    />

    <Button
        android:id="@+id/startVideoButton"
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        android:text="Start Call"
    />

    <Button
        android:id="@+id/stopVideoButton"
        android:layout_width="wrap_content"
        android:layout_height="wrap_content"
        android:text="End Call"
    />
</LinearLayout>
```



6. Open the `MainActivity` . If project has no activity, create one.

```
public class MainActivity extends Activity {  
  
    @Override  
    protected void onCreate(Bundle savedInstanceState) {  
        super.onCreate(savedInstanceState);  
        setContentView(R.layout.activity_main);  
    }  
}
```

7. Define the configuration attributes.

```
public void configExample() {
    Configuration configuration = Configuration.getInstance();

    configuration.setRestServerIp("rbbn.com/anonymouscallmobilesdkdemo");
    configuration.setRestServerPort(443);
    configuration.setRequestHttpProtocol(false);

    ICEServers iceServers = new ICEServers();
    iceServers.addICEServer("stun:rbbn.com/anonymouscallmobilesdkdemo:3478");
    configuration.setICEServers(iceServers);

    configuration.setWebSocketServerIp("rbbn.com/anonymouscallmobilesdkdemo");
    configuration.setWebSocketServerPort(443);
    configuration.setSecuredWSProtocol(true);
}
```

8. Define a global variable `call`.

```
CallInterface call;
```

9. The Call service uses callbacks to publish response events. To receive callbacks, a class must implement the necessary interface.

Modify the activity class to implement the interface.

```
public class MainActivity extends Activity
    implements CallApplicationListener {

    .
    .
    .

}
```

10. Define `startCall()` method which will create an outgoing call instance and establish an anonymous call with it.


```

public void startCall() {
    AnonymousServiceProvider serviceProvider =
AnonymousServiceProvider.getInstance(getApplicationContext());
    CallServiceInterface callService = serviceProvider.getCallService();
    try {
        callService.setCallApplication(MainActivity.this);
    } catch (MobileException exception) {
    }
    callService.createOutgoingCall("AnonymousCaller", " alice@rbbn.com ",
        MainActivity.this, new OutgoingCallCreateInterface() {
            @Override
            public void callCreated(OutgoingCallInterface callInterface) {
                call = callInterface;
                callInterface.setLocalVideoView((VideoView)
                    findViewById(R.id.localVideoView));
                callInterface.setRemoteVideoView((VideoView)
                    findViewById(R.id.remoteVideoView));
                callInterface.establishCall(true);
            }

            @Override
            public void callCreationFailed(MobileError error) {
            }
        });
}

```

11. Bind the `startCall()` method with the start video button.

```

Button startCall = (Button) findViewById(R.id.startVideoButton);
startCall.setOnClickListener(new View.OnClickListener() {
    @Override
    public void onClick(View v) {
        register();
    }
});

```

12. Define `stopCall()` method.

```


public void stopCall() throws MobileException {
    if(call != null) {
        call.endCall();
    }
}

```

13. Bind the `stopCall()` method with the stop video button.

```
Button stopCall = (Button) findViewById(R.id.stopVideoButton);
stopCall.setOnClickListener(new View.OnClickListener() {
    @Override
    public void onClick(View v) {
        try {
            stopCall();
        }
        catch (MobileException exception) {
        }
    }
});
```

14. Run the demo application.



Enable background processing

The application must support background processing while on an active call, allowing SDK to process WebSocket operations even after the user presses the Home button, the Sleep/Wake button, or if another application is launched. Implement triggers for related activities (e.g. video call) to respond to Android's activity life-cycle events (e.g. pause/resume).

Example: Implement triggers for background processing

```
@Override
protected void onPause()
{
    super.onPause();
    SDKEventManager.handleEvent(SDKEvents.EVENT_BACKGROUND);
}

@Override
protected void onResume()
{
    super.onResume();
    SDKEventManager.handleEvent(SDKEvents.EVENT_FOREGROUND);
}
```

WARNING

Android may kill an activity under certain conditions (e.g while the application or activity is in the background). This behavior causes VideoView objects to be disposed; Therefore, both local and remote VideoView objects must be set again when activity resumes from the background.

If there is more than one call object, video views must be set again for each of the call objects.

Use the onResume function to set all video views.

Example: Set all views

```
@Override
protected void onResume()
{
    super.onResume();
    SDKEventManager.handleEvent(SDKEvents.EVENT_FOREGROUND);
    call.setLocalVideoView((VideoView)findViewById(R.id.localVideoView));
    call.setRemoteVideoView((VideoView)findViewById(R.id.remoteVideoView));
    call2.setLocalVideoView((VideoView)findViewById(R.id.localVideoView2));
    call2.setRemoteVideoView((VideoView)findViewById(R.id.remoteVideoView2));
}
```

Set application configuration

First, you must access and modify the Configuration utility to update attributes such as REST server IP or Port. The Anonymous Call Mobile SDK receives data from the Configuration utility, and the third-party mobile application (third-party app) must provide necessary data to the Configuration utility.

To see all available configurations, see [Appendix D: Detailed Configurations](#).

Example: Accessing and updating Configuration

```
public class Demo {
    public void configurationExample() {
        //Configuration.getInstance is used to access the static Configuration
        instance
        //Access Configuration values through Java Beans getter/setter approach
        Configuration configuration = Configuration.getInstance();

        //set minimum Configuration values

        //server IP value for SPiDR/Kandy Link
        configuration.setRestServerIp("127.0.0.1");
        //server port value for SPiDR/Kandy Link
        configuration.setRestServerPort(443);

        //IP used in websocket connection creation
        configuration.setWebSocketServerIp("127.0.0.1");
        //port used in websocket connection creation
        configuration.setWebSocketServerPort(443);

        // SPiDR/Kandy Link TURN server using udp transport in WebRTC's peer
        connection
        ICEServers iceServers = new ICEServers();
        iceServers.addICEServer("turns:turn.spidr.com:443?transport=tcp");
        iceServers.addICEServer("stun:stun1.spidr.com:3478?transport=udp");
        configuration.setICEServers(iceServers);
    }
}
```

Set up logging functionality

Logging provides a way to trace process execution. The Log Manager is defined to handle logging requests made by the Mobile SDK. The Log Manager does not process the logging messages, rather it receives logging message requests and delivers them to the logger defined in the Configuration utility (logger is initially "null"; you must set an object which conforms to LoggingInterface methods in the Configuration utility).

The Mobile SDK supports the following log levels:

- ERROR (all exceptions are logged at this level)
- WARNING
- INFO (used for tracing issues)
- TRACE
- VERBOSE
- TRACE_WEBRTC

Example: Define logger

```
public class LogUtilityExample implements LoggingInterface {  
  
    @Override  
    public void log(LogLevel loglevel, String tag, String message) {  
        if(loglevel == LogLevel.ERROR) {  
            Log.e(tag, message);  
        } else if(loglevel == LogLevel.WARNING) {  
            Log.w(tag, message);  
        } else if(loglevel == LogLevel.INFO) {  
            Log.i(tag, message);  
        } else {  
            Log.d(tag, message);  
        }  
    }  
}
```

Example: Initialize logger

```
public void initializeAndUseLogger() {  
    Configuration.getInstance().setLogger(new LogUtilityExample());  
    LogManager.log(LogLevel.INFO, "Test", "logger is initialized");  
}
```

Basic Usage

Listen Call Service notifications

To receive event notifications of call service, `CallApplicationListener` should be implemented by calling `setCallApplication`.

Anonymous calls can be manipulated with methods such as mute/unmute and start/stop video.

Example: Setting Call Application Listener

```
public class CallActivity extends Activity implements CallApplicationListener {

    @Override
    protected void onResume() {
        super.onResume();

        AnonymousServiceProvider serviceProvider =
        AnonymousServiceProvider.getInstance(getApplicationContext());
        CallServiceInterface callService = serviceProvider.getCallService();
        callService.setCallApplication(CallActivity.this);
    }

}
```

Add STUN/TURN servers

SPiDR/Kandy Link provides TURN server support for media relay between two WebRTC endpoints in core version 3.0 and later. The `ICEServers` property in the `Configuration` class is used to store the ICE servers list; more than one `ICEServer` can exist in this property.

Add SPiDR's (Kandy Link) TURN server

After registration, the Mobile SDK gets default credentials from SPiDR/Kandy Link for the TURN servers and updates the `defaultICEUsername` and `defaultICEPassword` configuration properties. The list of `ICEServers` and their credentials are added to the `PeerConnection` when creating a call.

The following code sample will request TURN server credentials from SPiDR/Kandy Link and update the configuration instance.

Note: If your SPiDR/Kandy Link core version does not have TURN Server support, adding a TURN server without a username and password will cause the registration request to fail.

Example: Adding STUN/TURN server

```
ICEServers servers = new ICEServers();
servers.addICEServer("turns:turn1.spidr.com:443?transport=tcp");
servers.addICEServer("stun:turn1.spidr.com:3478?transport=udp");
servers.addICEServer("turns:turn2.spidr.com:443?transport=tcp");
servers.addICEServer("stun:turn2.spidr.com:3478?transport=udp");

Configuration.getInstance().setICEServers(servers);
```

Add an external TURN/STUN server

You also have the option of using external TURN/STUN servers while establishing calls rather than SPiDR's (Kandy Link) TURN server(s). The ICEServers property will store the address and username/password for the server(s).

Use the addICEServer:username:password: method of the ICEServers object to define credentials.

Example: Add a STUN server

```
ICEServers servers = new ICEServers();
servers.addICEServer("stun:stun1.spidr.com:8322");
Configuration.getInstance().setICEServers(servers);
// or
ICEServers servers = Configuration.getInstance().getICEServers();
servers.addICEServer("stun:stun1.spidr.com:8322");
```

Example: Add a TURN server

```
ICEServers servers = Configuration.getInstance().getICEServers();
servers.addICEServer("turns:turn1.spidr.com:443?transport=tcp", "username",
"password");
servers.addICEServer("turns:turn2.spidr.com:443?transport=tcp", "username",
"password");
servers.addICEServer("turns:turn3.spidr.com:443?transport=tcp", "username",
"password");
```

Example: Get the server(s)

```
ICEServers iceServers = Configuration.getInstance().getICEServers();

//credentials may also be updated directly
ArrayList<ICEServer> serversArray = iceServers.servers();
String urlOfFirst = serversArray.getFirst().getUrl();
String userOfFirst = serversArray.getFirst().getUsername();
String passOfFirst = serversArray.getFirst().getPassword();
```

If a server URL is entered multiple times, the last username and password will be used for the specified server. To remove a server, you must dispose the existing one and create a new instance, defining necessary servers again.

Make an anonymous call

Use the Anonymous Call functionality to place audio only or audio/video calls anonymously (without logging in with a username and password). The Anonymous Call Mobile SDK supports establishing calls with only one m line (audio only) or with two m lines (audio and video or one sendrecv/sendonly audio and one recvonly video m line). The number of m lines in the response should match the number of m lines in the initial offer.

Example: Establishing an anonymous call


```

public void anonymousCallExample() {

    //prepare outgoing call parameters
    String terminatorAddress = "user@domain";

    //initialize related video UI views for local and remote video display
    VideoView localVideoView = (VideoView)findViewById(R.id.localVideoView);
    VideoView remoteVideoView = (VideoView)findViewById(R.id.remoteVideoView);

    AnonymousServiceProvider serviceProvider =
    AnonymousServiceProvider.getInstance(getApplicationContext());
    CallServiceInterface callService = serviceProvider.getCallService();

    callService.createOutgoingCall(terminatorAddress, this, new
    OutgoingCallCreateInterface()
    {
        @Override
        public void callCreated(OutgoingCallInterface callInterface) {
            callInterface.setLocalVideoView(LocalVideoView);
            callInterface.setRemoteVideoView(remoteVideoView);
            //To set the caller's display name
            callInterface.setCallerName("aDisplayName");
            //To create an audio and video call:
            callInterface.establishCall(true);
            //OR To create audio only call with two m lines which can be answered
with video
            //directly, use:
            callInterface.establishCall(false);
            //OR To create an audio only call with only one m line, use:
            callInterface.establishAudioCall();
        }
        @Override
        public void callCreationFailed(MobileError error) {

        }
    });
}

@Override
public void establishCallSucceeded(OutgoingCallInterface outgoingCall)
{
    //called when establish call succeeds
    Log.i("Call", "establish call is OK");
}

@Override
public void establishCallFailed(OutgoingCallInterface outgoingCall, MobileError
error)
{
    //called when establish call fails
}

```

```
Log.e("Call", "establish call failed : " + error.getMessage());  
}
```

Make a time-limited token based anonymous call

Use the Time-Limited Token Based Anonymous Call functionality to place audio only or audio/video calls anonymously (without logging in with a username and password). A pre-shared (provisioned) key is used to obfuscate the time in the token - once handed out, SPiDR/KL will only allow the token to be used to access/subscribe to the services for a limited time (i.e. within 10 minutes of UTC time in token). This helps anonymous call functionality to be more secure.

Application developer will be responsible for token generation. Token can be generated using the "Security Key" defined in SPiDR/KL and must be supplied to the SDK to start a call.

Example: Establishing a time-limited token based anonymous call

```

public void anonymousCallExample() {

    // Following tokens should be generated by the app developer
    // by using the security key defined in the SPiDR/KL Admin GUI
    String accountToken;
    String originatorToken;
    String terminatorToken;

    String tokenRealm; // use the token realm defined in the SPiDR/KL Admin GUI

    //initialize related video UI views for local and remote video display
    VideoView localVideoView = (VideoView)findViewById(R.id.localVideoView);
    VideoView remoteVideoView = (VideoView)findViewById(R.id.remoteVideoView);

    AnonymousServiceProvider serviceProvider =
    AnonymousServiceProvider.getInstance(getApplicationContext());
    CallServiceInterface callService = serviceProvider.getCallService();

    callService.createOutgoingCall(accountToken, originatorToken, terminatorToken,
    tokenRealm, this, new OutgoingCallCreateInterface()
    {
        @Override
        public void callCreated(OutgoingCallInterface callInterface) {
            callInterface.setLocalVideoView(LocalVideoView);
            callInterface.setRemoteVideoView(remoteVideoView);
            //To create an audio and video call:
            callInterface.establishCall(true);
            //OR To create audio only call with two m lines which can be answered
with video
            //directly, use:
            callInterface.establishCall(false);
            //OR To create an audio only call with only one m line, use:
            callInterface.establishAudioCall();
        }
        @Override
        public void callCreationFailed(MobileError error) {

        }
    });
}

@Override
public void establishCallSucceeded(OutgoingCallInterface outgoingCall)
{
    //called when establish call succeeds
    Log.i("Call", "establish call is OK");
}

@Override
public void establishCallFailed(OutgoingCallInterface outgoingCall, MobileError

```

```
error)
{
    //called when establish call fails
    Log.e("Call", "establish call failed : " + error.getErrorMessage());
}
```

End an anonymous call

Use the End Call functionality to stop a current, anonymous call.

Example: Ending an anonymous call

```
public void endCallExample() {
    // To end the call
    call.endCall();
}

@Override
public void endCallSucceed(CallInterface call) {
    //called when end call succeeds
    Log.i("Call", "end call is OK");
}

@Override
public void endCallFailed(CallInterface call, MobileError error) {
    //called when end call fails
    Log.e("Call", "end call failed : " + error.getErrorMessage());
}
```

End calls with reason

Applications can use the `endCallWithReason` API to send the end call reason to SPiDR/Kandy Link, then SPiDR/Kandy Link will send the SIP BYE message with the reason to the remote user. The remote user gets the reason using the `callStatusChanged` API. If the call end reason string length exceeds the character limitation defined in SPiDR/Kandy Link Core, then SPiDR/Kandy Link Core will not send the excess characters.

Example: End call with reason

```
call.endCall("Reason"); // ends the call with reason
```

Example: Receiving end call notification with reason

```
@Override
public void callStatusChanged(CallInterface callInterface, CallState callState) {
    if (callState.getType() == CallState.Type.ENDED){
        Log.i(TAG, "Call Ended with reason:" + callState.getReason());
    }
}
```

Supported call end reasons

When an endCall notification is received from SPiDR/Kandy Link, the Anonymous Call SDK forwards the status code (statusCode) and status reason (reasonText) to the application layer, informing the user why the call has ended.

Anonymous Call SDK-specific status codes and reasons sent to the application layer include:

```
("reason":"Reason not provided","statusCode":"9900")
("reason":"Ended by local user","statusCode":"9901")
```

"Reason not provided" (9900) returns in two situations:

- When endCall notification does not provide reasonText and/or statusCode information in sessionParams.
- When an unhandled notification like Ringing or Dialing is received.

The following Anonymous Call Mobile SDK-call specific status codes are mapped to ENDED in CallState.Type:

statusCode	Definition	Description
9900	STATUS_CODE_NOT_PROVIDED	Remote party ended the call normally
9901	ENDED_BY_LOCAL	Local user ended the call normally
9906	ENDED_BY_ERROR	Call ended due to error

Other SIP-specific sessionParam statusCode values mapped to ENDED (e.g. statusCode 480, equivalent to previous NOT_AVAILABLE) are forwarded directly to the application layer.

CallState class fields

```
private Type type;
private int statusCode;
private String reason;
```

Example: Getting call end reason

```
@Override
public void callStatusChanged(CallInterface callInterface, CallState callState); {
    switch (callState.getType()) {
        case ENDED:
            switch(callState.getStatusCode()) {
                case 404:
                    Log.i("Call", "Callee does not exist");
                    break;
                case 480:
                    Log.i("Call", "Callee is offline");
                    break;
                case 487:
                    Log.i("Call", "Callee did not answer");
                case CallState.STATUS_CODE_NOT_PROVIDED:
                    Log.i("Call", "Call end reason is not provided");
                    break;
                case CallState.ENDED_BY_LOCAL:
                    Log.i("Call", "Caller ended the call normally");
                    break;
                default:
                    break;
            }
            break;
        case IN_CALL:
            Log.i("Call", "Call establishment is successful");
            break;
        case RINGING:
            Log.i("Call", "Callee is ringing now");
            break;
        default:
            break;
    }
}
```

Get active call list

Use the following API to get a pointer to the list of active call objects (i.e. `CallInterface`). Any changes in the call objects affect objects of the returned list.

Example: Getting active calls

```
ImmutableList callList = callService.getActiveCalls();
```

Mid-Call operations

While in the established call, mid-call operations can be called such as Mute-Unmute/Hold-Unhold/Video Start-Stop.

See [Appendix B: Call state transitions](#), for which operations are allowed respect to state of the call.

Mute/Unmute Call

To stop sending audio from the microphone, mute method can be called. Until unmuting the call, participants cannot hear the voice from the device.

Example: Mute/unmute the call

```
public void muteUnmuteExample() {
    // To mute the call
    call.mute();

    // To unmute the call
    call.unMute();
}

@Override
public void muteCallSucceed(CallInterface call) {
    //called when mute call succeeds
    Log.i("Call", "mute call is OK");
}

@Override
public void muteCallFailed(CallInterface call, MobileError error) {
    //called when mute call fails
    Log.e("Call", "mute call failed : " + error.getErrorMessage());
}

@Override
public void unMuteCallSucceed(CallInterface call) {
    //called when unmute call succeeds
    Log.i("Call", "unmute call is OK");
}

@Override
public void unMuteCallFailed(CallInterface call, MobileError error) {
    //called when unmute call fails
    Log.e("Call", "unmute call failed : " + error.getErrorMessage());
}
```

Video Start/Stop on a Call

To start/stop sending video from the camera, video start/stop method can be called. Note that, these operations take some time, thus listening operation results from `CallApplicationListener`, and acting accordingly is recommended.

Example: Video Start/Stop


```
public void videoStartStopExample() {
    // To start video in the call
    call.videoStart();

    // To stop video in the call
    call.videoStop();
}

@Override
public void videoStartSucceed(CallInterface call) {
    //called when video start succeeds
    Log.i("Call", "video start is OK");
}

@Override
public void videoStartFailed(CallInterface call, MobileError error) {
    //called when video start fails
    Log.e("Call", "video start failed : " + error.getErrorMessage());
}

@Override
public void videoStopSucceed(CallInterface call) {
    //called when video stop succeeds
    Log.i("Call", "video stop is OK");
}

@Override
public void videoStopFailed(CallInterface call, MobileError error) {
    //called when video stop fails
    Log.e("Call", "video stop failed : " + error.getErrorMessage());
}
```

Hold/Unhold Call and Double Hold

While in a call, a participant may be placed on hold by calling `holdCall` method. When operation succeeds, media transfer between participants stops, and call state will change to `ON_HOLD` state. Remote participant will see this call session in `REMOTELY_HELD` state.

To resume to the call, `unholdCall` method should be called. Note that, these operations take some time, thus listening operation results from `CallApplicationListener`, and acting accordingly is recommended.

Users may also place one another on hold at the same time (Double Hold). The following scenario illustrates a double hold with call states in parenthesis:

1. User A and User B are in an active call (`IN_CALL`).

2. A places B on hold (A is `ON_HOLD` , B is `REMOTEY_HELD`).
3. B places A on hold (`ON_DOUBLE_HOLD`).
4. A retrieves the call (A is `REMOTEY_HELD` , B is `ON_HOLD`).
5. B retrieves the call, and A and B are in an active call again (`IN_CALL`). For more information about call states, see [Appendix B: Call state transitions](#).

Example: Hold/unhold the call

```
public void holdUnholdExample() {
    // To hold the call
    call.holdCall();
    // If call in REMOTEY_HELD state, will be ON_DOUBLE_HOLD

    // To unhold the call
    call.unHoldCall();
}

@Override
public void holdCallSucceed(CallInterface call) {
    //called when hold call succeeds
    Log.i("Call", "hold call is OK");
}

@Override
public void holdCallFailed(CallInterface call, MobileError error) {
    //called when hold call fails
    Log.e("Call", "hold call failed : " + error.getErrorMessage());
}

@Override
public void unHoldCallSucceed(CallInterface call) {
    //called when unhold call succeeds
    Log.i("Call", "unhold call is OK");
}

@Override
public void unHoldCallFailed(CallInterface call, MobileError error) {
    //called when unhold call fails
    Log.e("Call", "unhold call failed : " + error.getErrorMessage());
}
```

Example: Hold/unhold callback information

When remote peer holds the call, call status will be changed accordingly.

```
@Override
public void callStatusChanged(CallInterface callInterface, CallState callState);
{
    if(callState == CallState.ON_HOLD) {
        Log.i("Call", "Call is on hold");
    } else if(callState == CallState.REMOTELY_HELD) {
        Log.i("Call", "Remote party holds the call");
    } else if(callState == CallState.ON_DOUBLE_HOLD) {
        Log.i("Call", "Both parties are in hold state");
    }
}
```

Change default camera device (front or back)

New calls are started using the default camera device (front or back). The default is set to the front camera (CAMERA_FACING_FRONT), however, you can also change the default for new calls.

Call the Configuration class with property "setDefaultCameraMode" to change the default camera device. The parameter "cameraMode" uses the static integer values provided in the Android Camera class. The available cameraMode parameter values include :

- CAMERA_FACING_BACK = 0
- CAMERA_FACING_FRONT = 1

Example: Change camera device default

```
// To set front camera
Configuration.getInstance().setDefaultCameraMode(CameraInfo.CAMERA_FACING_FRONT);

// To set back camera
Configuration.getInstance().setDefaultCameraMode(CameraInfo.CAMERA_FACING_BACK);
```

Change camera orientation

Smartphones can change the screen view to portrait or landscape based on how the user is holding their device. There are two different video camera orientation settings—device orientation and application orientation—with three different handling options. The three handling options are:

- `CAMERA_ORIENTATION_USES_NONE` : Video orientation does not change when the user rotates their device.
- `CAMERA_ORIENTATION_USES_DEVICE` : Video orientation changes when the user rotates their device, even if the application interface orientation is not changed.
- `CAMERA_ORIENTATION_USES_STATUS_BAR` : Video orientation changes according to the application interface orientation.

To change video orientation manually, call `rotateCameraOrientationToPosition`. The following values are supported:

- `LANDSCAPE`
- `PORTRAIT`
- `REVERSE_LANDSCAPE`
- `REVERSE_PORTRAIT`

Example: Configure camera orientation for incoming and outgoing video

```
public class CallActivity extends Activity {
    @Override
    public void onCreate(Bundle savedInstanceState) {
        super.onCreate(savedInstanceState);

        Configuration.getInstance().setOrientationMode(OrientationMode.CAMERA_ORIENTATION_USES_NONE);
    }
    private void changeOrientationToLandscape() {

        CallService.getInstance().rotateCameraOrientationToPosition(ScreenOrientation.LANDSCAPE);
    }
}
```

Change local video resolution or camera position

Users can set local video resolution and switch between front and back cameras at any time during the call; there are no call state constraints. Android will return the available video resolutions as a list of the `Camera.Size` object, which the application can use to set the video resolution. Setting camera position uses the static integer values provided in the Android `Camera` class (see [Changing default camera device \(front or back\)](#)).

Example: Changing video resolution and camera position

```

public void changeVideoResolutionAndPosition (){
    Camera camera = Camera.open();
    List<Camera.Size> supportedVideoSizes =
camera.getParameters().getSupportedVideoSizes();
    camera.release();

    currentCall.setCaptureDevice(CameraInfo.CAMERA_FACING_FRONT ,
supportedVideoSizes.get(0) , new ProcessListener() {
        @Override
        public void onSuccess() {
            Log.i("Device Capture" , "setting capture device succeeded");
        }

        @Override
        public void onFailed(MobileError error) {
            if (error.getErrorCode() == Constants.ErrorCodes.WEBRTC_FAILURE){
                Log.e("Device Capture" , "setting capture device position failed,
error explanation : "
                    + error.getErrorMessage());
            }
            else {
                Log.e("Video Resolution" , "video resolution cannot be set, error
explanation : "
                    + error.getErrorMessage());
            }
        }
    });
}

```

Send DTMF (Dual-Tone Multi-Frequency) signals

The Anonymous Call Mobile SDK supports sending Dual-Tone Multi-Frequency (DTMF) signals to an Interactive Voice Response (IVR) system via the SPiDR/Kandy Link Media Broker. This allows callers to enter passcodes on active or ringing calls. Available keys for tones include 0-9, *, #, A, B, C, and D, as outlined in RFC 4733. When remote party doesn't support out-of-band DTMF, the API method will return false.

Note: This feature only provides the functionality for sending DTMF signals. It does not include the functionality for getting keypad input or for playing key press volume.

API definition for sending DTMF

```
public interface CallInterface {  
  
    // other method definitions for CallInterface  
  
    // Send Dual Tone Multi Frequency Signal.  
    // tone: character value of DTMF  
    public void sendDTMF(char tone);  
  
    // other method definitions for CallInterface  
  
}
```

Example: Sending DTMF

```
public void sendDTMFExample(CallInterface call, char tone) {  
    call.sendDTMF(tone);  
}
```

Get media attributes

The application is notified of audio/video state, capture device position, and aspect ratio changes by the `mediaAttributesChanged` method. The `getMediaAttributes` method is used to retrieve the current media attributes. The following shows an example using the `getMediaAttributes` method and an example notification following an aspect ratio change.

Note: As of release 4.0.1, the `MediaState` class is renamed as `MediaAttributes`, and the `mediaStateChanged` method is renamed as `mediaAttributesChanged`.

Example: Using the `getMediaAttributes` method

```
MediaAttributes currentMediaAttributes = currentCall.getMediaAttributes();  
boolean localVideo = currentMediaAttributes.getLocalVideo();  
boolean localAudio = currentMediaAttributes.getLocalAudio();  
boolean remoteVideo = currentMediaAttributes.getRemoteVideo();  
float remoteVideoAspectRatio = currentMediaAttributes.getRemoteVideoAspectRatio();  
float localVideoAspectRatio = currentMediaAttributes.getLocalVideoAspectRatio();
```

Example: Getting remote and local aspect ratios

```
@Override
public void mediaAttributesChanged(CallInterface callInterface, MediaAttributes
mediaAttributes) {
    float remoteVideoAspectRatio = mediaAttributes.getRemoteVideoAspectRatio();
    float localVideoAspectRatio = mediaAttributes.getLocalVideoAspectRatio();
}
```

The aspect ratio value is provided as the width/height of the video. For example, if the video resolution is:

- 360x640 (9:16), the aspect ratio will be 0.56
- 480x640 (3:4), the aspect ratio will be 0.75

Note: If the application does not provide any view to the MobileSDK, the MobileSDK will not provide any aspect ratio notification to the application.

Advanced Usage

Send Custom Parameters for an anonymous call

If desired, custom SIP Headers can be send while initiating call and/or during the mid-call events. Parameters should contain key-value pairs that are provisioned by the backend.

Example: Sending Custom Parameters while establishing call

```
public void callWithCustomHeadersExample(String terminatorAddress, boolean
videoEnabled, Map<String, String> customParameters) {
    callService.createOutgoingCall(terminatorAddress, this, new
OutgoingCallCreateInterface()
    {
        @Override
        public void callCreated(OutgoingCallInterface callInterface) {
            callInterface.establishCall(videoEnabled, customParameters);
        }
        @Override
        public void callCreationFailed(MobileError error) {
        }
    });
}
```

Example: Setting Custom Parameters during the call

Custom Parameters can be set during the call, and they will send when next mid-call event occurs.

```
public void setParametersToCall(CallInterface call, Map<String, String>
customParameters) {
    call.setCustomParameters(customParameters);
}
```

Example: Sending Custom Parameters during the call

After setting custom parameters, instead of waiting next mid-call event, custom parameters can sent by `sendCustomParameters` method.

```
public void sendParametersToCall(CallInterface call, Map<String, String>
customParameters) {
    call.sendCustomParameters(customParameters);
}
```


Set ICE options

The Configuration class has an “iceOption” attribute used to determine the ICE behavior. The following are the available ICE options:

- **ICE_TRICKLE:** Trickle ICE completes signaling without waiting for candidate collection. Clients send candidates to one another as they’re discovered (after the call signaling is complete and the call is established). This provides faster call setup times but may cause media delays.
- **ICE_VANILLA:** The default value. The clients must collect and send all candidates before initializing signaling. This process, in addition to the particular network configuration and the number of interfaces in the clients’ devices, can cause call setup delays.

If the “ICE_TRICKLE” option is selected, the “ICECollectionTimeout” value is not used. If the call ends before all ICE candidates are collected, the MobileSDK does not listen to the TURN/STUN server since the peer connection is closed.

WARNING

Both parties must support Trickle ICE; Half Trickle is not supported in this implementation. If one party does not support Trickle ICE, signaling may be completed, but the Vanilla ICE client cannot receive ICE candidates sent by the other party. This state should be handled by the developer either by checking the RTCP statistics or waiting for the user to end the call. The MobileSDK will not end the call.

Example: Setting ICE options

```
Configuration.getInstance().setICEOption(ICEOptions.ICE_TRICKLE);
```

Early media

The Anonymous Call Mobile SDK supports early media (for example, hearing a ringing tone or an announcement from the network instead of a local ringing tone before a call is established) and transitions to call state `SESSION_PROGRESS` after receiving the 183 Session Progress notification. See [Appendix B: Call state transitions](#) for call state diagrams.

To support early media, feature should be added to `supportedCallFeatures` before starting call.

Example: Enabling early media

```
String supportedCallFeatures[] = {  
    Constants.SupportedCallFeatures.EARLY_MEDIA.toString() };  
  
Configuration.getInstance().setSupportedCallFeatures(supportedCallFeatures);
```

Example: Call in early media

```
private CallState.Type callState = CallState.Type.UNKNOWN;  
...  
@Override  
public void callStatusChanged(CallInterface callInterface, CallState callState) {  
    switch (callState.getType()) {  
        case SESSION_PROGRESS:  
            Log.i("Call", "Call is in early media state");  
            break;  
        case RINGING:  
            if (callState == CallState.Type.SESSION_PROGRESS) {  
                Log.i("Call", "Ignoring ringing state");  
                return;  
            }  
            Log.i("Call", "Call is in ringing state");  
            break;  
        ...  
        default:  
            break;  
    }  
    callState = callState.getType();  
}
```

Set codec priority

The Configuration class has a variable "preferredCodecSet", which is an instance of the CodecSet class. To use only a subset of the available codecs or to change the default priority, the "audioCodecs" and "videoCodecs" arrays of preferredCodecSet must be set. Codecs should be listed in order of priority (i.e. first codec listed is first priority).

If you do not add any codecs to the preferredCodecSet variable or if you create the preferredCodecSet variable with a default constructor, the SDK uses the default codecs in the following priority order:

- Audio Codecs: AC_OPUS, AC_G722, AC_PCMA, AC_PCMU, AC_ISAC, AC_ILBC
- Video Codecs: VC_VP8, VC_VP9, VC_H264

Example: Setting codec priority

```
CodecSet preferredCodecSet = new CodecSet();
AudioCodecType audioCodecs[] = {AudioCodecType.AC_G722, AudioCodecType.AC_PCMA,
AudioCodecType.AC_PCMU}
preferredCodecSet.setAudioCodecs(audioCodecs);

VideoCodecType videoCodecs[] = {VideoCodecType.VC_VP8};
preferredCodecSet.setVideoCodecs(videoCodecs);

Configuration.getInstance().setPreferredCodecSet(preferredCodecSet);
```

Or

```
AudioCodecType audioCodecs[] = {AudioCodecType.AC_G722, AudioCodecType.AC_PCMA,
AudioCodecType.AC_PCMU}
VideoCodecType videoCodecs[] = {VideoCodecType.VC_VP8};
CodecSet preferredCodecSet = new CodecSet(audioCodecs, videoCodecs);
Configuration.getInstance().setPreferredCodecSet(preferredCodecSet);
```

Replace codec payload number

Using "CodecToReplace" feature of Mobile SDK, applications can manipulate the codec payload numbers in SDP. For this feature to work, these codecs and their payload numbers should be set before the call operation started (before the call creation).

Note that, it is strongly recommended **not** to use this API during an ongoing call operation (e.g. mid-call events). A configuration change will affect the ongoing call and this may cause unstable WebRTC behavior.

For the replacing codec payload number feature, the MobileSDK user have to create an instance of the CodecToReplace model class and set the codecDefinition (the definition of the codec that can be seen on the rtpmap in SDP, e.g. "telephone-event/8000" or "opus/48000/2") and payloadNumber (e.g. "101" or "96" etc.) parameters. After creation of CodecToReplace object(s), they should be set to Mobile SDK through `setReplaceCodecSet` API on `Configuration` class.

After the Mobile SDK user set the ReplaceCodecSet configuration, all of the local offer call SDPs will be generated with the specified codec payload numbers and there will be no modification done on remote SDPs and local answer SDPs.

NOTE

- If this configuration is not set, the SDK will keep the default WebRTC behavior and there will be no modification on the codec payload numbers on the SDP.
- The SDK user should not set the same payload number to different codecs in the same media line (e.g. telephone-event and opus codecs must not have the same payload number), it causes WebRTC layer to behave unpredictable and calls may fail. But it is okay to set the same payload number to codecs that are in the different media lines (e.g. opus and VP8 codecs can have the same payload number).

If one of the codec numbers which is set through this configuration conflicts with number of another codec that WebRTC created, SDK will swap payload numbers of these two codecs to recover from the unpredictable behavior described above.

- As described in RFC5761, dynamic RTP payload types should be chosen from the range 96-127. Otherwise, this could cause an unstable WebRTC behavior.

Example: Replace codec payload number

```
try {
    List<CodecToReplace> codecsToReplace = new ArrayList<>();

    codecsToReplace.add(CodecToReplace.create("telephone-event/8000", "101"));
    codecsToReplace.add(CodecToReplace.create("opus/48000/2", "114"));
    codecsToReplace.add(CodecToReplace.create("VP8/90000", "100"));

    Map<String, String> customProperties = new HashMap<>();
    customProperties.put("profile-level-id", "42e01f");
    customProperties.put("packetization-mode", "1");
    codecsToReplace.add(CodecToReplace.create("H264/90000", "120", customProperties));

    Configuration.getInstance().setReplaceCodecSet(codecsToReplace);
} catch (MobileException ex) {
    //handle exception
}
```

Example: Effect of the Codec Payload Number Change on Sample SDPs

Let's assume the audio and video media lines of original SDP are given as follows:

```
...
m=audio 9 RTP/SAVPF 111 103 9 102 0 8 105 13 110 113 126
c=IN IP4 127.0.0.1
a=rtcp:9 IN IP4 0.0.0.0
a=ice-ufrag:cCs7
a=ice-pwd:GeKDhmK0uPScU9b+nXmpV7by
a=ice-options:trickle renomination
a=mid:audio
a=extmap:1 urn:ietf:params:rtp-hdrext:ssrc-audio-level
a=sendrecv
a=rtcp-mux
a=crypto:1 AES_CM_128_HMAC_SHA1_80 inline:FmJG3viNo+YcpGzfAEAPxtXP3vsFYPyBpy4UMuF5
a=rtpmap:111 opus/48000/2
a=rtcp-fb:111 transport-cc
a=fmtp:111 minptime=10;useinbandfec=1
a=rtpmap:103 ISAC/16000
a=rtpmap:9 G722/8000
a=rtpmap:102 ILBC/8000
a=rtpmap:0 PCMU/8000
a=rtpmap:8 PCMA/8000
a=rtpmap:105 CN/16000
a=rtpmap:13 CN/8000
a=rtpmap:110 telephone-event/48000
a=rtpmap:113 telephone-event/16000
a=rtpmap:126 telephone-event/8000
...
m=video 9 RTP/SAVPF 96 97 98 99 100 101 127 125 104 124 106
c=IN IP4 127.0.0.1
a=rtcp:9 IN IP4 0.0.0.0
a=ice-ufrag:cCs7
a=ice-pwd:GeKDhmK0uPScU9b+nXmpV7by
a=ice-options:trickle renomination
a=mid:video
a=extmap:2 urn:ietf:params:rtp-hdrext:toffset
a=extmap:3 http://www.webrtc.org/experiments/rtp-hdrext/abs-send-time
a=extmap:4 urn:3gpp:video-orientation
a=extmap:5 http://www.ietf.org/id/draft-holmer-rmcat-transport-wide-cc-extensions-01
a=extmap:6 http://www.webrtc.org/experiments/rtp-hdrext/playout-delay
a=extmap:7 http://www.webrtc.org/experiments/rtp-hdrext/video-content-type
a=extmap:8 http://www.webrtc.org/experiments/rtp-hdrext/video-timing
a=extmap:10 http://tools.ietf.org/html/draft-ietf-avtext-framemarking-07
a=sendrecv
a=rtcp-mux
a=rtcp-rsize
a=crypto:1 AES_CM_128_HMAC_SHA1_80 inline:FmJG3viNo+YcpGzfAEAPxtXP3vsFYPyBpy4UMuF5
a=rtpmap:96 H264/90000
a=rtcp-fb:96 goog-remb
a=rtcp-fb:96 transport-cc
a=rtcp-fb:96 ccm fir
```

```
a=rtcp-fb:96 nack
a=rtcp-fb:96 nack pli
a=fmtp:96 level-asymmetry-allowed=1;packetization-mode=1;profile-level-id=640c29
a=rtpmap:97 rtx/90000
a=fmtp:97 apt=96
a=rtpmap:98 H264/90000
a=rtcp-fb:98 goog-remb
a=rtcp-fb:98 transport-cc
a=rtcp-fb:98 ccm fir
a=rtcp-fb:98 nack
a=rtcp-fb:98 nack pli
a=fmtp:98 level-asymmetry-allowed=1;packetization-mode=1;profile-level-id=42e029
a=rtpmap:99 rtx/90000
a=fmtp:99 apt=98
a=rtpmap:100 VP8/90000
a=rtcp-fb:100 goog-remb
a=rtcp-fb:100 transport-cc
a=rtcp-fb:100 ccm fir
a=rtcp-fb:100 nack
a=rtcp-fb:100 nack pli
a=rtpmap:101 rtx/90000
a=fmtp:101 apt=100
a=rtpmap:127 VP9/90000
a=rtcp-fb:127 goog-remb
a=rtcp-fb:127 transport-cc
a=rtcp-fb:127 ccm fir
a=rtcp-fb:127 nack
a=rtcp-fb:127 nack pli
a=rtpmap:125 rtx/90000
a=fmtp:125 apt=127
a=rtpmap:104 red/90000
a=rtpmap:124 rtx/90000
a=fmtp:124 apt=104
a=rtpmap:106 ulpfec/90000
...
```

- A simple replacement as <"opus/48000/2", "114"> and <"telephone-event/48000", "101"> :

```
...
m=audio 9 RTP/SAVPF 114 103 9 102 0 8 105 13 101 113 126
c=IN IP4 127.0.0.1
a=rtcp:9 IN IP4 0.0.0.0
a=ice-ufrag:cCs7
a=ice-pwd:GeKDhmK0uPScU9b+nXmpV7by
a=ice-options:trickle renomination
a=mid:audio
a=extmap:1 urn:ietf:params:rtp-hdext:ssrc-audio-level
a=sendrecv
a=rtcp-mux
a=crypto:1 AES_CM_128_HMAC_SHA1_80 inline:FmJG3viNo+YcpGzfAEAPxtXP3vsFYPyBpy4UMuF5
a=rtpmap:114 opus/48000/2
a=rtcp-fb:114 transport-cc
a=fmtp:114 minptime=10;useinbandfec=1
a=rtpmap:103 ISAC/16000
a=rtpmap:9 G722/8000
a=rtpmap:102 ILBC/8000
a=rtpmap:0 PCMU/8000
a=rtpmap:8 PCMA/8000
a=rtpmap:105 CN/16000
a=rtpmap:13 CN/8000
a=rtpmap:101 telephone-event/48000
a=rtpmap:113 telephone-event/16000
a=rtpmap:126 telephone-event/8000
...
m=video 9 RTP/SAVPF 96 97 98 99 100 101 127 125 104 124 106
c=IN IP4 127.0.0.1
a=rtcp:9 IN IP4 0.0.0.0
a=ice-ufrag:cCs7
a=ice-pwd:GeKDhmK0uPScU9b+nXmpV7by
a=ice-options:trickle renomination
a=mid:video
a=extmap:2 urn:ietf:params:rtp-hdext:toffset
a=extmap:3 http://www.webrtc.org/experiments/rtp-hdext/abs-send-time
a=extmap:4 urn:3gpp:video-orientation
a=extmap:5 http://www.ietf.org/id/draft-holmer-rmcat-transport-wide-cc-extensions-01
a=extmap:6 http://www.webrtc.org/experiments/rtp-hdext/playout-delay
a=extmap:7 http://www.webrtc.org/experiments/rtp-hdext/video-content-type
a=extmap:8 http://www.webrtc.org/experiments/rtp-hdext/video-timing
a=extmap:10 http://tools.ietf.org/html/draft-ietf-avtext-framemarking-07
a=sendrecv
a=rtcp-mux
a=rtcp-rsize
a=crypto:1 AES_CM_128_HMAC_SHA1_80 inline:FmJG3viNo+YcpGzfAEAPxtXP3vsFYPyBpy4UMuF5
a=rtpmap:96 H264/90000
a=rtcp-fb:96 goog-remb
a=rtcp-fb:96 transport-cc
a=rtcp-fb:96 ccm fir
```

```
a=rtcp-fb:96 nack
a=rtcp-fb:96 nack pli
a=fmtp:96 level-asymmetry-allowed=1;packetization-mode=1;profile-level-id=640c29
a=rtpmap:97 rtx/90000
a=fmtp:97 apt=96
a=rtpmap:98 H264/90000
a=rtcp-fb:98 goog-remb
a=rtcp-fb:98 transport-cc
a=rtcp-fb:98 ccm fir
a=rtcp-fb:98 nack
a=rtcp-fb:98 nack pli
a=fmtp:98 level-asymmetry-allowed=1;packetization-mode=1;profile-level-id=42e029
a=rtpmap:99 rtx/90000
a=fmtp:99 apt=98
a=rtpmap:100 VP8/90000
a=rtcp-fb:100 goog-remb
a=rtcp-fb:100 transport-cc
a=rtcp-fb:100 ccm fir
a=rtcp-fb:100 nack
a=rtcp-fb:100 nack pli
a=rtpmap:101 rtx/90000
a=fmtp:101 apt=100
a=rtpmap:127 VP9/90000
a=rtcp-fb:127 goog-remb
a=rtcp-fb:127 transport-cc
a=rtcp-fb:127 ccm fir
a=rtcp-fb:127 nack
a=rtcp-fb:127 nack pli
a=rtpmap:125 rtx/90000
a=fmtp:125 apt=127
a=rtpmap:104 red/90000
a=rtpmap:124 rtx/90000
a=fmtp:124 apt=104
a=rtpmap:106 ulpfec/90000
...
```

- For H264, there are 2 codecs with the same description, so another property should be introduced for comparison in order to define which one to replace. So replacement should be defined as <"H264/90000", "126", "profile-level-id=42e029">:


```
...
m=audio 9 RTP/SAVPF 111 103 9 102 0 8 105 13 110 113 126
c=IN IP4 127.0.0.1
a=rtcp:9 IN IP4 0.0.0.0
a=ice-ufrag:cCs7
a=ice-pwd:GeKDhmK0uPScU9b+nXmpV7by
a=ice-options:trickle renomination
a=mid:audio
a=extmap:1 urn:ietf:params:rtp-hdrext:ssrc-audio-level
a=sendrecv
a=rtcp-mux
a=crypto:1 AES_CM_128_HMAC_SHA1_80 inline:FmJG3viNo+YcpGzfAEAPxtXP3vsFYPyBpy4UMuF5
a=rtpmap:111 opus/48000/2
a=rtcp-fb:111 transport-cc
a=fmtp:111 minptime=10;useinbandfec=1
a=rtpmap:103 ISAC/16000
a=rtpmap:9 G722/8000
a=rtpmap:102 ILBC/8000
a=rtpmap:0 PCMU/8000
a=rtpmap:8 PCMA/8000
a=rtpmap:105 CN/16000
a=rtpmap:13 CN/8000
a=rtpmap:110 telephone-event/48000
a=rtpmap:113 telephone-event/16000
a=rtpmap:126 telephone-event/8000
...
m=video 9 RTP/SAVPF 96 97 126 99 100 101 127 125 104 124 106
c=IN IP4 127.0.0.1
a=rtcp:9 IN IP4 0.0.0.0
a=ice-ufrag:cCs7
a=ice-pwd:GeKDhmK0uPScU9b+nXmpV7by
a=ice-options:trickle renomination
a=mid:video
a=extmap:2 urn:ietf:params:rtp-hdrext:toffset
a=extmap:3 http://www.webrtc.org/experiments/rtp-hdrext/abs-send-time
a=extmap:4 urn:3gpp:video-orientation
a=extmap:5 http://www.ietf.org/id/draft-holmer-rmcat-transport-wide-cc-extensions-01
a=extmap:6 http://www.webrtc.org/experiments/rtp-hdrext/playout-delay
a=extmap:7 http://www.webrtc.org/experiments/rtp-hdrext/video-content-type
a=extmap:8 http://www.webrtc.org/experiments/rtp-hdrext/video-timing
a=extmap:10 http://tools.ietf.org/html/draft-ietf-avtext-framemarking-07
a=sendrecv
a=rtcp-mux
a=rtcp-rsize
a=crypto:1 AES_CM_128_HMAC_SHA1_80 inline:FmJG3viNo+YcpGzfAEAPxtXP3vsFYPyBpy4UMuF5
a=rtpmap:96 H264/90000
a=rtcp-fb:96 goog-remb
a=rtcp-fb:96 transport-cc
a=rtcp-fb:96 ccm fir
```

```
a=rtcp-fb:96 nack
a=rtcp-fb:96 nack pli
a=fmtp:96 level-asymmetry-allowed=1;packetization-mode=1;profile-level-id=640c29
a=rtpmap:97 rtx/90000
a=fmtp:97 apt=96
a=rtpmap:126 H264/90000
a=rtcp-fb:126 goog-remb
a=rtcp-fb:126 transport-cc
a=rtcp-fb:126 ccm fir
a=rtcp-fb:126 nack
a=rtcp-fb:126 nack pli
a=fmtp:126 level-asymmetry-allowed=1;packetization-mode=1;profile-level-id=42e029
a=rtpmap:99 rtx/90000
a=fmtp:99 apt=126
a=rtpmap:100 VP8/90000
a=rtcp-fb:100 goog-remb
a=rtcp-fb:100 transport-cc
a=rtcp-fb:100 ccm fir
a=rtcp-fb:100 nack
a=rtcp-fb:100 nack pli
a=rtpmap:101 rtx/90000
a=fmtp:101 apt=100
a=rtpmap:127 VP9/90000
a=rtcp-fb:127 goog-remb
a=rtcp-fb:127 transport-cc
a=rtcp-fb:127 ccm fir
a=rtcp-fb:127 nack
a=rtcp-fb:127 nack pli
a=rtpmap:125 rtx/90000
a=fmtp:125 apt=127
a=rtpmap:104 red/90000
a=rtpmap:124 rtx/90000
a=fmtp:124 apt=104
a=rtpmap:106 ulpfec/90000
```

- If <"opus/48000/2", "105"> provided through this configuration, there will be a conflict with "CN/16000" in the original SDP. In this case Mobile SDK will swap the payload numbers of these codecs as follows:

```
...
m=audio 9 RTP/SAVPF 105 103 9 102 0 8 111 13 110 113 126
c=IN IP4 127.0.0.1
a=rtcp:9 IN IP4 0.0.0.0
a=ice-ufrag:cCs7
a=ice-pwd:GeKDhmK0uPScU9b+nXmpV7by
a=ice-options:trickle renomination
a=mid:audio
a=extmap:1 urn:ietf:params:rtp-hdrext:ssrc-audio-level
a=sendrecv
a=rtcp-mux
a=crypto:1 AES_CM_128_HMAC_SHA1_80 inline:FmJG3viNo+YcpGzfAEAPxtXP3vsFYPyBpy4UMuF5
a=rtpmap:105 opus/48000/2
a=rtcp-fb:105 transport-cc
a=fmtp:105 minptime=10;useinbandfec=1
a=rtpmap:103 ISAC/16000
a=rtpmap:9 G722/8000
a=rtpmap:102 ILBC/8000
a=rtpmap:0 PCMU/8000
a=rtpmap:8 PCMA/8000
a=rtpmap:111 CN/16000
a=rtpmap:13 CN/8000
a=rtpmap:110 telephone-event/48000
a=rtpmap:113 telephone-event/16000
a=rtpmap:126 telephone-event/8000
...
m=video 9 RTP/SAVPF 96 97 98 99 100 101 127 125 104 124 106
c=IN IP4 127.0.0.1
a=rtcp:9 IN IP4 0.0.0.0
a=ice-ufrag:cCs7
a=ice-pwd:GeKDhmK0uPScU9b+nXmpV7by
a=ice-options:trickle renomination
a=mid:video
a=extmap:2 urn:ietf:params:rtp-hdrext:toffset
a=extmap:3 http://www.webrtc.org/experiments/rtp-hdrext/abs-send-time
a=extmap:4 urn:3gpp:video-orientation
a=extmap:5 http://www.ietf.org/id/draft-holmer-rmcat-transport-wide-cc-extensions-01
a=extmap:6 http://www.webrtc.org/experiments/rtp-hdrext/playout-delay
a=extmap:7 http://www.webrtc.org/experiments/rtp-hdrext/video-content-type
a=extmap:8 http://www.webrtc.org/experiments/rtp-hdrext/video-timing
a=extmap:10 http://tools.ietf.org/html/draft-ietf-avtext-framemarking-07
a=sendrecv
a=rtcp-mux
a=rtcp-rsize
a=crypto:1 AES_CM_128_HMAC_SHA1_80 inline:FmJG3viNo+YcpGzfAEAPxtXP3vsFYPyBpy4UMuF5
a=rtpmap:96 H264/90000
a=rtcp-fb:96 goog-remb
a=rtcp-fb:96 transport-cc
a=rtcp-fb:96 ccm fir
```

```
a=rtcp-fb:96 nack
a=rtcp-fb:96 nack pli
a=fmtp:96 level-asymmetry-allowed=1;packetization-mode=1;profile-level-id=640c29
a=rtpmap:97 rtx/90000
a=fmtp:97 apt=96
a=rtpmap:98 H264/90000
a=rtcp-fb:98 goog-remb
a=rtcp-fb:98 transport-cc
a=rtcp-fb:98 ccm fir
a=rtcp-fb:98 nack
a=rtcp-fb:98 nack pli
a=fmtp:98 level-asymmetry-allowed=1;packetization-mode=1;profile-level-id=42e029
a=rtpmap:99 rtx/90000
a=fmtp:99 apt=98
a=rtpmap:100 VP8/90000
a=rtcp-fb:100 goog-remb
a=rtcp-fb:100 transport-cc
a=rtcp-fb:100 ccm fir
a=rtcp-fb:100 nack
a=rtcp-fb:100 nack pli
a=rtpmap:101 rtx/90000
a=fmtp:101 apt=100
a=rtpmap:127 VP9/90000
a=rtcp-fb:127 goog-remb
a=rtcp-fb:127 transport-cc
a=rtcp-fb:127 ccm fir
a=rtcp-fb:127 nack
a=rtcp-fb:127 nack pli
a=rtpmap:125 rtx/90000
a=fmtp:125 apt=127
a=rtpmap:104 red/90000
a=rtpmap:124 rtx/90000
a=fmtp:124 apt=104
a=rtpmap:106 ulpfec/90000
...
```

Control audio bandwidth

Applications can modify five audio codec properties to control audio bandwidth. The `MaxPlaybackRate`, `MaxAverageBitrate`, `Discontinuous Transmission (DTX)`, and `Forward Error Correction (FEC)` properties apply to the Opus audio codec. The fifth property, `packetization time (ptime)`, affects all audio codecs. Refer to RFC 7587 for descriptions, acceptable values, and recommended values for the audio codec properties.

Set your application to use the WebRTC default set or the Mobile SDK preferred set; the application can change properties within either set. If the values of any property exceed the acceptable values identified in RFC 7587, the Mobile SDK ignores the value and uses the default configuration for that

property. The following table shows the property values for the WebRTC default set and the Mobile SDK preferred set as well as the RFC 7587–defined acceptable values.

WebRTC default settings, MobileSDK preferred default settings, and acceptable values

	WebRTC default	Mobile SDK preferred	Acceptable values
MaxPlaybackRate	24000	16000	8000-48000
MaxAverageBitRate	40000	20000	6000-510000
DTX	Disabled	Enabled	true or false
FEC	Enabled	Enabled	true or false
Ptime	20	60	3, 5, 10, 20, 40, 60...120 (2.5*n round up to next full integer)

The following adjustments decrease bandwidth usage:

- Decreasing MaxPlaybackRate
- Decreasing MaxAverageBitRate
- Enabling DTX
- Disabling FEC (**Note:** Disabling FEC does not greatly reduce bandwidth usage. Therefore, the Mobile SDK preferred set enables FEC by default.)
- Increasing Ptime

The application can modify audio bandwidth usage in all call states (before and during calls). When the application modifies audio bandwidth during a call, the properties change after the Mobile SDK sends a call update to the remote side (e.g. a user holds the call).

The following shows different audio bandwidth usage configuration examples. If a codec property value is not specified, the application uses the default value for the configured set. If the application does not perform any audio bandwidth usage configuration or sets the configuration as null, the Mobile SDK uses the WebRTC default set.

Example: Use the Mobile SDK preferred set

```
AudioCodecConfiguration config = new  
AudioCodecConfiguration(AudioCodecConfiguration.DefaultConfigurationType.MOBILESDK_P  
REFERRED_SET);  
Configuration.getInstance().setAudioCodecConfigurations(config);
```

Example: Use the Mobile SDK preferred set with changes

```
AudioCodecConfiguration config = new  
AudioCodecConfiguration(AudioCodecConfiguration.DefaultConfigurationType.MOBILESDK_P  
REFERRED_SET);  
config.setOpusMaxAverageBitRate(25000);  
config.setOpusMaxPlaybackRate(24000);  
Configuration.getInstance().setAudioCodecConfigurations(config);
```

Example: Use the WebRTC default set with changes

```
AudioCodecConfiguration config = new  
AudioCodecConfiguration(AudioCodecConfiguration.DefaultConfigurationType.WEBRTC_DEFA  
ULT_SET);  
config.setOpusMaxAverageBitRate(25000);  
config.setOpusMaxPlaybackRate(24000);  
config.setOpusDtx(true);  
config.setOpusFec(true);  
config.setPtime(40);  
Configuration.getInstance().setAudioCodecConfigurations(config);
```

Get additional information about a call

Use the `callAdditionalInfoChanged` callback method in `callApplicationListener` to determine when particular actions occurred on a specific call. Use this data to learn information such as the time from when a call was created until the time a REST request was sent. The additional info map includes the fields:

Field	Description
action	The primary category of information
type	The “action” sub-category
callId	<p>The identifier for the related call, which is different than the call session id. This id is either randomly generated by the Mobile SDK or set by the user.</p> <p>Note: The call identifier is obtained using the “getId” method rather than the “getCallId” method (which would return the call session identifier)</p>
time	Occurrence time (epoch in milliseconds)

Example: Additional Info

```
{  
  "action": "callMetric",  
  "type": "callRestSent",  
  "callId": "7E60066C-C7F3-438A-95B1-DDE8634E1072",  
  "time": "1455701052999"  
}
```

The following list shows each available “action” category and its “type” sub-category:

- **iceTimeout:** Includes types for ICE collection timeout (assuming “2x” is the timeout configuration and “t” is when the ICE process ended)
 - **iceNormal:** Time when the ICE collection process ended normally (period of $t < x$)
 - **iceOneRelay:** Time when the ICE collection process was interrupted by a timeout with at least one (audio and video) relay candidate (period of $x < t < 2x$)
 - **iceNoRelay:** Time when the ICE collection process was interrupted by a timeout without a relay candidate (period of $t = 2x$)
- **callMetric:** Includes types for call setup time measurements
 - **callCreate:** Time of the establishCall start
 - **callRestSent:** Time when the REST request was sent following creating a call
 - **callRinging:** Time when the ringing notification was received for an outgoing call
 - **callAnswerReceived:** Time when the answer notification was received for an outgoing call
- **iceState:** Includes types for ICE state change
 - **iceConnected:** Time when the ICE media channel was established on WebRTC
 - **iceDisconnected:** Time when the ICE media channel failed on WebRTC
- **ipChange:** Includes types of IP change while in an active call
 - **ipChangeStarted:** Time when the IP change event started
 - **ipChangeEnded:** Time when the IP change event finished

Example: Listening call additional info changes


```

@Override
private void callAdditionalInfoChanged (CallInterface call, Map<String, String>
events)
{
    long time = Long.parseLong(events.get("time"));
    String action = events.get("action");
    String type = events.get("type");
    String callId = call.getCallId();

    if(type.equals(AdditionalInfoConstants.CALL_CREATE)) {
        callCreateTime = time;
    }
    long delay = time - callCreateTime;
    Log.i("Call", "Time from creating call until " + type + " is " + delay + "for
callId" + callId );
    StringBuilder sb = new StringBuilder("{}");
    for (Map.Entry<String,String > entry : events.entrySet()) {

sb.append(entry.getKey()).append(":").append(entry.getValue()).append(",\n");
    }
    sb.append("{}");
    Log.i("Call", "Detailed info is " + sb.toString());
}

```

Retrieve audio and video RTP/RTCP statistics

The Mobile SDK can retrieve audio and video RTP/RTCP statistics providing information including:

- Number of packets lost
- Number of packets sent/received
- Number of bytes sent/received
- Call Jitter received
- RTT (round trip delay)
- Local/Remote network addresses and ports
- Audio/Video codec names

Note: The Mobile SDK does not keep the statistics after the call ends.

Use the "getRTPStatistics" method in an SMCall object to retrieve an array containing RTP/RTCP statistics. The array includes objects of the SMCallStatistic class—a class which stores statistic details. This class has the following public variables:

- id (string)
- type (string)
- timestamp (double)
- values (value[]) - a class containing "name" and "value" variables

The following are RTP/RTCP statistics related to camera and video resolution:

- googFrameWidthInput: Video width value fed by the camera
- googFrameWidthSent: Video width value sent to the remote side
- googFrameHeightInput: Video height value fed by the camera
- googFrameHeightSent: Video height value sent to the remote side
- googFrameRateInput: Frames per second (FPS) value fed by the camera
- googFrameRateSent: FPS value sent to the remote side
- googBandwidthLimitedResolution: If true, video resolution is decreased due to bandwidth limitations
- googCpuLimitedResolution: If true, video resolution is decreased due to CPU limitations

See [Appendix E: Examples of call statistic data](#) for additional information.

WARNING

If there is a bandwidth or CPU limitation, WebRTC will decrease video resolution and FPS values automatically. The Mobile SDK does not inform the application of the automatic change; the application must check the values using the `getRTPStatistics` method.

Example: CallStatistic object

```
id: Conn-audio-1-0,  
type: googCandidatePair,  
timestamp: 1.444311978571412E12,  
values: [googActiveConnection: true], [bytesReceived: 92193], [bytesSent: 87940],  
[packetsSent: 796]
```

Example: Retrieving statistics


```
currentCall.getRTPStatistics(new RTPStatisticHandler() {  
  
    @Override  
    public void onReportReceived(CallStatistics[] statistics) {  
        CallStatistic statistic = callStatistics[0];  
  
        Log.i("Call", "Report id : " +statistic.id);  
        Log.i("Call", "Report type : " +statistic.type);  
        Log.i("Call", "Report timestamp : " +statistic.timestamp);  
        Log.i("Call", "Report values : " +statistic.values);  
    }  
});
```

For a full example of the data received, see [Appendix E: Examples of call statistic data](#).

Appendices

Appendix A: High-level Anonymous Call Mobile SDK structure

The following image illustrates the high-level Anonymous Call Mobile SDK structure and its sub-modules.



Appendix B: Call state transitions


The following diagram and table describe call state transitions and the methods available for each call state.

The Anonymous Call Mobile SDK allows only one active request per call. Additional requests will be rejected if a request is already being processed. End Call requests are the exception and may be triggered at any time.

Unacceptable invocations from the application will also be rejected to prevent the application from crashing. Incorrect notification sequences will be disabled.

The call state becomes INITIAL after the call object is created. The call state becomes ENDED after the call is disposed.

Anonymous call state transitions



Method availability

Call State	Available methods
INITIAL	establish
DIALING	endCall
SESSION_PROGRESS	endCall
RINGING	endCall
IN_CALL	videoStart / videoStop / mute / unmute / hold / switchCamera / endCall
ON_HOLD	unhold / endCall
ON_DOUBLE_HOLD	unhold / endCall
REMOTELY_HELD	videoStart / videoStop / mute / unmute / hold / switchCamera / endCall
ENDED	No operation is allowed

Appendix C: Performance management

The following impacts should be considered when managing your mobile application's performance:

- The default video codec defined by the WebRTC code base is VP8. VP8 may have performance issues, resulting in high CPU usage, increased battery usage, and a heat increase on devices with less surface area for cooling. Alternative solutions to eliminate or lessen the impact of this behavior include:
 - Using another codec (for example, H264 provides better CPU performance)
 - Using lower video resolution and fps (frame per second) in video calls
- Cellular network connectivity is directly related to the transmission level of data and therefore can impact the quality and the performance of audio/video calls. The WebRTC code base attempts to adjust network transmission capacity, but it is still possible to observe low video resolution and freezing videos while using cellular network connectivity.

Appendix D: Detailed Configurations

This section contains usage of all configurations that Anonymous Call Mobile SDK provides.

```
public class Demo {
    public void configurationExample() {
        //Configuration.getInstance is used to access the static Configuration
instance
        //Access Configuration values through Java Beans getter/setter approach

        Configuration configuration = Configuration.getInstance();

        //server IP value for SPiDR
        configuration.setRestServerIp("127.0.0.1");
        //server port value for SPiDR
        configuration.setRestServerPort(443);
        //logger implementation defined by the application
        configuration.setLogger(new DefaultLogUtility());
        //HTTP or HTTPS while accessing REST server
        configuration.setRequestHttpProtocol(false);

        //connection type for notification
        configuration.setNotificationType(NotificationType.WebSocket);
        //IP used in websocket connection creation
        configuration.setWebSocketServerIp("127.0.0.1");
        //port used in websocket connection creation
        configuration.setWebSocketServerPort(443);
        //set to WS or WSS protocol
        configuration.setSecuredWSProtocol(true);

        // SPiDR/Kandy Link TURN server in WebRTC's peer connection
        ICEServers iceServers = new ICEServers();
        iceServers.addICEServer("turns:turn.spidr.com:443?transport=tcp");
        iceServers.addICEServer("turns:turn2.spidr.com:443?transport=tcp");

        // Adding SPiDR/Kandy Link STUN server
        iceServers.addICEServer("stun:stun1.spidr.com:3478?transport=udp");
        iceServers.addICEServer("stun:turn2.spidr.com:3478?transport=udp");

        configuration.setICEServers(iceServers);

        //Integer value in seconds to limit the ICE collection duration. Default is
0 (no timeout)
        configuration.setICECollectionTimeout(4);

        //Set supported call features (early media and/or ringing feedback)
        //SPiDR server must support these features
        configuration.setSupportedCallFeatures(new String[] {
Constants.SupportedCallFeatures.EARLY_MEDIA.toString() });

        //Set one of the ice candidate negotiation types (ICE_VANILLA or
ICE_TRICKLE)
        //The default is ICE_VANILLA
    }
}
```



```
configuration.setIceOption(ICEOptions.ICE_TRICKLE);

// Audit Configuration. Default is enabled and 30 secs.
configuration.setAuditEnabled(true);
configuration.setAuditFrequency(30);
    }
}
```

Appendix E: Examples of call statistic data

This section provides an example of statistic data retrieved for audio calls and video calls. See [Retrieving audio and video RTP/RTCP statistics](#) for the method used to retrieve call statistic data.

Example (Sample) statistic data for an audio call

```
id: googTrack_ARDAMSa0, type: googTrack, timestamp: 1445079424793.019043, values: (
  "googTrackId: ARDAMSa0"
),
id: googLibjingleSession_3498004751352045309, type: googLibjingleSession, timestamp:
1445079424793.019043, values: (
  "googInitiator: true"
),
id: Channel-audio-1, type: googComponent, timestamp: 1445079424793.019043, values: (
  "selectedCandidatePairId: Conn-audio-1-0",
  "googComponent: 1"
),
id: Conn-audio-1-0, type: googCandidatePair, timestamp: 1445079424793.019043,
values: (
  "googActiveConnection: true",
  "bytesReceived: 67136",
  "bytesSent: 65617",
  "packetsSent: 587",
  "googReadable: true",
  "googChannelId: Channel-audio-1",
  "googLocalAddress: 10.254.20.195:61074",
  "localCandidateId: Cand-Ab3LbCOD",
  "googLocalCandidateType: local",
  "googRemoteAddress: 10.254.16.20:57624",
  "remoteCandidateId: Cand-TQH102WG",
  "googRemoteCandidateType: local",
  "googRtt: 12",
  "packetsDiscardedOnSend: 0",
  "googTransportType: udp",
  "googWritable: true"
),
id: Cand-Ab3LbCOD, type: localcandidate, timestamp: 1445079412616.024902, values: (
  "ipAddress: 10.254.20.195",
  "networkType: unknown",
  "portNumber: 61074",
  "priority: 2122260223",
  "transport: udp",
  "candidateType: host"
),
```

```
id: Cand-jyPmgIgv, type: remotecandidate, timestamp: 1445079412616.024902, values: (
  "ipAddress: 10.254.16.20",
  "portNumber: 57624",
  "priority: 1853824767",
  "transport: udp",
  "candidateType: peerreflexive"
),
id: Channel-audio-2, type: googComponent, timestamp: 1445079413203.319092, values: (
  "googComponent: 2"
),
id: Channel-video-1, type: googComponent, timestamp: 1445079413203.319092, values: (
  "selectedCandidatePairId: Conn-video-1-0",
  "googComponent: 1"
),
id: Channel-video-2, type: googComponent, timestamp: 1445079413203.319092, values: (
  "googComponent: 2"
),
id: ssrc_586305605_send, type: ssrc, timestamp: 1445079424793.019043, values: (
  "audioInputLevel: 8966",
  "bytesSent: 59363",
  "packetsLost: 0",
  "packetsSent: 573",
  "ssrc: 586305605",
  "transportId: Channel-audio-1",
  "googCodecName: opus",
  "googEchoCancellationQualityMin: 0",
  "googEchoCancellationEchoDelayMedian: 0",
  "googEchoCancellationEchoDelayStdDev: 0",
  "googEchoCancellationReturnLoss: 0",
  "googEchoCancellationReturnLossEnhancement: 0",
  "googJitterReceived: 6",
  "googRtt: 38",
  "googTrackId: ARDAMSa0",
  "googTypingNoiseState: false"
),
id: bweforvideo, type: VideoBwe, timestamp: 1445079424793.019043, values: (
  "googActualEncBitrate: 0",
  "googAvailableReceiveBandwidth: 0",
  "googAvailableSendBandwidth: 300000",
  "googBucketDelay: 0",
  "googRetransmitBitrate: 0",
  "googTargetEncBitrate: 0",
  "googTransmitBitrate: 0"
),
id: Cand-TQH102WG, type: remotecandidate, timestamp: 1445079413203.319092, values: (
  "ipAddress: 10.254.16.20",
  "portNumber: 57624",
  "priority: 2122260223",
  "transport: udp",
```

```

        "candidateType: host"
    ),
    id: Conn-video-1-0, type: googCandidatePair, timestamp: 1445079413203.319092,
    values: (
        "googActiveConnection: true",
        "bytesReceived: 0",
        "bytesSent: 0",
        "packetsSent: 0",
        "googReadable: false",
        "googChannelId: Channel-video-1",
        "googLocalAddress: 10.254.20.195:53869",
        "localCandidateId: Cand-+0vP4WY",
        "googLocalCandidateType: local",
        "googRemoteAddress: 10.254.16.20:57624",
        "remoteCandidateId: Cand-EoPuaL+p",
        "googRemoteCandidateType: local",
        "googRtt: 2251",
        "packetsDiscardedOnSend: 0",
        "googTransportType: udp",
        "googWritable: true"
    ),
    id: Cand-+0vP4WY, type: localcandidate, timestamp: 1445079413203.319092, values: (
        "ipAddress: 10.254.20.195",
        "networkType: unknown",
        "portNumber: 53869",
        "priority: 2122260223",
        "transport: udp",
        "candidateType: host"
    ),
    id: Cand-EoPuaL+p, type: remotecandidate, timestamp: 1445079413203.319092, values: (
        "ipAddress: 10.254.16.20",
        "portNumber: 57624",
        "priority: 2122260223",
        "transport: udp",
        "candidateType: host"
    ),
    id: googTrack_eb9de414-8e72-4c91-959e-311e87535120, type: googTrack, timestamp:
    1445079424793.019043, values: (
        "googTrackId: eb9de414-8e72-4c91-959e-311e87535120"
    ),
    id: googTrack_579706d2-916c-4743-8675-5a0cd1b9d077, type: googTrack, timestamp:
    1445079424793.019043, values: (
        "googTrackId: 579706d2-916c-4743-8675-5a0cd1b9d077"
    ),
    id: ssrc_3857903642_recv, type: ssrc, timestamp: 1445079424793.019043, values: (
        "audioOutputLevel: 3587",
        "bytesReceived: 60735",
        "packetsLost: 0",
        "packetsReceived: 580",
        "ssrc: 3857903642",

```

```

    "transportId: Channel-audio-1",
    "googAccelerateRate: 0.0177612",
    "googCaptureStartNtpTimeMs: 3654068213162",
    "googCodecName: opus",
    "googCurrentDelayMs: 91",
    "googDecodingCNG: 0",
    "googDecodingCTN: 1156",
    "googDecodingCTSG: 0",
    "googDecodingNormal: 1139",
    "googDecodingPLC: 16",
    "googDecodingPLCCNG: 1",
    "googExpandRate: 0.0105591",
    "googJitterBufferMs: 70",
    "googJitterReceived: 1",
    "googPreemptiveExpandRate: 0.0045166",
    "googPreferredJitterBufferMs: 20",
    "googSecondaryDecodedRate: 0",
    "googSpeechExpandRate: 0.0105591",
    "googTrackId: eb9de414-8e72-4c91-959e-311e87535120"
  ),
  id: ssrc_2201928905_recv, type: ssrc, timestamp: 1445079424793.019043, values: (
    "bytesReceived: 0",
    "packetsLost: 0",
    "packetsReceived: 0",
    "ssrc: 2201928905",
    "transportId: Channel-audio-1",
    "googCaptureStartNtpTimeMs: 0",
    "googCurrentDelayMs: 0",
    "googDecodeMs: 0",
    "googFirsSent: 0",
    "googFrameHeightReceived: -1",
    "googFrameRateDecoded: 0",
    "googFrameRateOutput: 0",
    "googFrameRateReceived: 0",
    "googFrameWidthReceived: -1",
    "googJitterBufferMs: 0",
    "googMaxDecodeMs: 0",
    "googMinPlayoutDelayMs: 0",
    "googNacksSent: 0",
    "googPlisSent: 0",
    "googRenderDelayMs: 10",
    "googTargetDelayMs: 10",
    "googTrackId: 579706d2-916c-4743-8675-5a0cd1b9d077"
  )
)

```

Example (Sample) statistic data for a video call

```

id: googTrack_ARDAMSa0, type: googTrack, timestamp: 1445079500335.081055, values: (
  "googTrackId: ARDAMSa0"
),
id: googLibjingleSession_8093042484470420018, type: googLibjingleSession, timestamp:
1445079500335.081055, values: (
  "googInitiator: true"
),
id: Channel-audio-1, type: googComponent, timestamp: 1445079500335.081055, values: (
  "selectedCandidatePairId: Conn-audio-1-0",
  "googComponent: 1"
),
id: Conn-audio-1-0, type: googCandidatePair, timestamp: 1445079500335.081055,
values: (
  "googActiveConnection: true",
  "bytesReceived: 132837",
  "bytesSent: 262260",
  "packetsSent: 540",
  "googReadable: true",
  "googChannelId: Channel-audio-1",
  "googLocalAddress: 10.254.20.195:54073",
  "localCandidateId: Cand-zBqBr3MR",
  "googLocalCandidateType: local",
  "googRemoteAddress: 10.254.16.20:52444",
  "remoteCandidateId: Cand-JpDFew8o",
  "googRemoteCandidateType: local",
  "googRtt: 721",
  "packetsDiscardedOnSend: 0",
  "googTransportType: udp",
  "googWritable: true"
),
id: Cand-zBqBr3MR, type: localcandidate, timestamp: 1445079494022.980957, values: (
  "ipAddress: 10.254.20.195",
  "networkType: unknown",
  "portNumber: 54073",
  "priority: 2122260223",
  "transport: udp",
  "candidateType: host"
),
id: Cand-6MH4gGBl, type: remotecandidate, timestamp: 1445079494022.980957, values: (
  "ipAddress: 10.254.16.20",
  "portNumber: 52444",
  "priority: 1853824767",
  "transport: udp",
  "candidateType: peerreflexive"
),
id: Channel-audio-2, type: googComponent, timestamp: 1445079494560.142090, values: (
  "googComponent: 2"
),
id: Channel-video-1, type: googComponent, timestamp: 1445079494560.142090, values: (

```

```

    "selectedCandidatePairId: Conn-video-1-0",
    "googComponent: 1"
  ),
  id: Channel-video-2, type: googComponent, timestamp: 1445079494560.142090, values: (
    "googComponent: 2"
  ),
  id: ssrc_2166116287_send, type: ssrc, timestamp: 1445079500335.081055, values: (
    "audioInputLevel: 3993",
    "bytesSent: 27518",
    "packetsLost: 0",
    "packetsSent: 286",
    "ssrc: 2166116287",
    "transportId: Channel-audio-1",
    "googCodecName: opus",
    "googEchoCancellationQualityMin: 0",
    "googEchoCancellationEchoDelayMedian: 0",
    "googEchoCancellationEchoDelayStdDev: 0",
    "googEchoCancellationReturnLoss: 0",
    "googEchoCancellationReturnLossEnhancement: 0",
    "googJitterReceived: 19",
    "googRtt: 762",
    "googTrackId: ARDAMSa0",
    "googTypingNoiseState: false"
  ),
  id: ssrc_515953527_send, type: ssrc, timestamp: 1445079500335.081055, values: (
    "bytesSent: 253747",
    "packetsLost: 0",
    "packetsSent: 269",
    "ssrc: 515953527",
    "transportId: Channel-audio-1",
    "googAdaptationChanges: 0",
    "googAvgEncodeMs: 43",
    //If true, video resolution is decreased due to bandwidth limitations
    "googBandwidthLimitedResolution: false",
    "googCodecName: VP8",
    //If true, video resolution is decreased due to CPU limitations
    "googCpuLimitedResolution: false",
    "googEncodeUsagePercent: 70",
    "googFirsReceived: 0",
    //video height value fed by camera
    "googFrameHeightInput: 640",
    //video height value sent to remote side
    "googFrameHeightSent: 640",
    //FPS value fed by camera
    "googFrameRateInput: 23",
    //FPS value sent to remote side
    "googFrameRateSent: 20",
    //video width value fed by camera
    "googFrameWidthInput: 480",
    //video width value sent to remote side

```

```

    "googFrameWidthSent: 480",
    "googNacksReceived: 0",
    "googPlisReceived: 0",
    "googRtt: 702",
    "googTrackId: ARDAMSv0",
    "googViewLimitedResolution: false"
  ),
  id: bweforvideo, type: VideoBwe, timestamp: 1445079500335.081055, values: (
    "googActualEncBitrate: 381882",
    "googAvailableReceiveBandwidth: 116883",
    "googAvailableSendBandwidth: 338258",
    "googBucketDelay: 0",
    "googRetransmitBitrate: 0",
    "googTargetEncBitrate: 338258",
    "googTransmitBitrate: 380040"
  ),
  id: Cand-JpDFew8o, type: remotecandidate, timestamp: 1445079494560.142090, values: (
    "ipAddress: 10.254.16.20",
    "portNumber: 52444",
    "priority: 2122260223",
    "transport: udp",
    "candidateType: host"
  ),
  id: Conn-video-1-0, type: googCandidatePair, timestamp: 1445079494560.142090,
  values: (
    "googActiveConnection: true",
    "bytesReceived: 0",
    "bytesSent: 0",
    "packetsSent: 0",
    "googReadable: false",
    "googChannelId: Channel-video-1",
    "googLocalAddress: 10.254.20.195:52759",
    "localCandidateId: Cand-xMjVXfM2",
    "googLocalCandidateType: local",
    "googRemoteAddress: 10.254.16.20:52444",
    "remoteCandidateId: Cand-VMyvLE3v",
    "googRemoteCandidateType: local",
    "googRtt: 2251",
    "packetsDiscardedOnSend: 0",
    "googTransportType: udp",
    "googWritable: true"
  ),
  id: Cand-xMjVXfM2, type: localcandidate, timestamp: 1445079494560.142090, values: (
    "ipAddress: 10.254.20.195",
    "networkType: unknown",
    "portNumber: 52759",
    "priority: 2122260223",
    "transport: udp",
    "candidateType: host"
  ),

```



```
id: Cand-VMyvLE3v, type: remotecandidate, timestamp: 1445079494560.142090, values: (
  "ipAddress: 10.254.16.20",
  "portNumber: 52444",
  "priority: 2122260223",
  "transport: udp",
  "candidateType: host"
),
id: googTrack_6adfc0a7-8ad6-47a0-b523-f62a59edf961, type: googTrack, timestamp:
1445079500335.081055, values: (
  "googTrackId: 6adfc0a7-8ad6-47a0-b523-f62a59edf961"
),
id: googTrack_00dc3a53-4f92-44b4-a71e-3291716e2ae0, type: googTrack, timestamp:
1445079500335.081055, values: (
  "googTrackId: 00dc3a53-4f92-44b4-a71e-3291716e2ae0"
),
id: ssrc_2707401590_recv, type: ssrc, timestamp: 1445079500335.081055, values: (
  "audioOutputLevel: 0",
  "bytesReceived: 18924",
  "packetsLost: 0",
  "packetsReceived: 181",
  "ssrc: 2707401590",
  "transportId: Channel-audio-1",
  "googAccelerateRate: 0.0055542",
  "googCaptureStartNtpTimeMs: -1",
  "googCodecName: opus",
  "googCurrentDelayMs: 563",
  "googDecodingCNG: 0",
  "googDecodingCTN: 599",
  "googDecodingCTSG: 0",
  "googDecodingNormal: 378",
  "googDecodingPLC: 76",
  "googDecodingPLCCNG: 145",
  "googExpandRate: 0.354492",
  "googJitterBufferMs: 3",
  "googJitterReceived: 31",
  "googPreemptiveExpandRate: 0.0315552",
  "googPreferredJitterBufferMs: 520",
  "googSecondaryDecodedRate: 0",
  "googSpeechExpandRate: 0.11969",
  "googTrackId: 6adfc0a7-8ad6-47a0-b523-f62a59edf961"
),
id: ssrc_279863464_recv, type: ssrc, timestamp: 1445079500335.081055, values: (
  "bytesReceived: 105125",
  "packetsLost: 0",
  "packetsReceived: 142",
  "ssrc: 279863464",
  "transportId: Channel-audio-1",
  "googCaptureStartNtpTimeMs: 0",
  "googCurrentDelayMs: 235",
  "googDecodeMs: 4",
```

```
"googFirsSent: 0",  
"googFrameHeightReceived: 240",  
"googFrameRateDecoded: 30",  
"googFrameRateOutput: 28",  
"googFrameRateReceived: 0",  
"googFrameWidthReceived: 320",  
"googJitterBufferMs: 215",  
"googMaxDecodeMs: 10",  
"googMinPlayoutDelayMs: 38",  
"googNacksSent: 0",  
"googPlisSent: 3",  
"googRenderDelayMs: 10",  
"googTargetDelayMs: 235",  
"googTrackId: 00dc3a53-4f92-44b4-a71e-3291716e2ae0"  
)
```

Appendix F: ProGuard support on Android

The ProGuard optimization tool for Android (<https://www.guardsquare.com/en/products/proguard>) can cause runtime and debugging issues on applications using the MobileSDK. ProGuard may obfuscate Java Interfaces, enum classes, and shrink implicit, compiler-generated static methods, causing crashes. RIBBON suggests not to obfuscate the MobileSDK public codebase since public classes related to the MobileSDK are available to any developer with documentation. Therefore, ProGuard would not provide effective protection for the MobileSDK API against reverse engineering.

If ProGuard is enabled, RIBBON recommends adding one of the following configurations to ProGuard to avoid crashes and make debugging easier.

ProGuard configuration without obfuscation

```
-dontusemixedcaseclassnames
-dontskipnonpubliclibraryclasses
-dontpreverify
-verbose

# Enable optimization
-optimizations
!code/simplification/arithmetic,!code/simplification/cast,!field/*,!class/merging/*
-optimizationpasses 5
-allowaccessmodification

#===== MobileSDK =====#
# Keep everything in com.genband.mobile
-keep class com.genband.mobile.** { *; }
-keep class org.webrtc.** { *; }
#===== MobileSDK =====#
```

ProGuard configuration with obfuscation

The following configuration makes debugging more difficult.

```

-dontusemixedcaseclassnames
-dontskipnonpubliclibraryclasses
-dontpreverify
-verbose

# Enable optimization
-optimizations
!code/simplification/arithmetic,!code/simplification/cast,!field/*,!class/merging/*
-optimizationpasses 5
-allowaccessmodification

#===== MobileSDK =====#
# Keep only publics with SDPObserver
-keep public class com.genband.mobile.** { *; }
-keep class com.genband.mobile.core.WebRTC.SDPObserver { *; }
# Keep all in webrtc
-keep class org.webrtc.** { *; }

# For native methods, see
http://proguard.sourceforge.net/manual/examples.html#native
-keepclasseswithmembernames class * {
    native <methods>;
}

# For enumeration classes, see
http://proguard.sourceforge.net/manual/examples.html#enumerations
-keepclassmembers enum * {
    public static **[] values();
    public static ** valueOf(java.lang.String);
}
#===== MobileSDK =====#

```

ProGuard configuration for production

This configuration obfuscates the MobileSDK API as much as possible while avoiding runtime crashes.

```

-dontusemixedcaseclassnames
-dontskipnonpubliclibraryclasses
-dontpreverify
-verbose

# Enable optimization
-optimizations
!code/simplification/arithmetic,!code/simplification/cast,!field/*,!class/merging/*
-optimizationpasses 5
-allowaccessmodification

#===== MobileSDK =====#
-keep class org.webrtc.AudioTrack { *; }
-keep class org.webrtc.Camera2Enumerator { *; }
-keep class org.webrtc.CameraEnumerationAndroid { *; }
-keep class org.webrtc.CameraEnumerationAndroid$CaptureFormat { *; }
-keep class org.webrtc.CameraEnumerator { *; }
-keep class org.webrtc.DTMFSender { *; }
-keep class org.webrtc.DataChannel { *; }
-keep class org.webrtc.DataChannel$Buffer { *; }
-keep class org.webrtc.DataChannel$Init { *; }
-keep class org.webrtc.DataChannel$Observer { *; }
-keep class org.webrtc.DataChannel$State { *; }
-keep class org.webrtc.EglBase { *; }
-keep class org.webrtc.EglBase$Context { *; }
-keep class org.webrtc.EglBase14 { *; }
-keep class org.webrtc.EglBase14$Context { *; }
-keep class org.webrtc.IceCandidate { *; }
-keep class org.webrtc.MediaConstraints { *; }
-keep class org.webrtc.MediaConstraints$KeyValuePair { *; }
-keep class org.webrtc.MediaCodecVideoDecoder { *; }
-keep class org.webrtc.MediaCodecVideoDecoder$DecodedOutputBuffer { *; }
-keep class org.webrtc.MediaCodecVideoDecoder$DecodedTextureBuffer { *; }
-keep class org.webrtc.MediaCodecVideoDecoder$VideoCodecType { *; }
-keep class org.webrtc.MediaCodecVideoEncoder { *; }
-keep class org.webrtc.MediaCodecVideoEncoder$OutputBufferInfo { *; }
-keep class org.webrtc.MediaCodecVideoEncoder$VideoCodecType { *; }
-keep class org.webrtc.MediaSource$State { *; }
-keep class org.webrtc.MediaStream { *; }
-keep class org.webrtc.MediaStreamDelegate { *; }
-keep class org.webrtc.MediaStreamTrack$State { *; }
-keep class org.webrtc.NetworkMonitor { *; }
-keep class org.webrtc.NetworkMonitorAutoDetect$* { *; }
-keep class org.webrtc.PeerConnection { *; }
-keep class org.webrtc.PeerConnection$BundlePolicy { *; }
-keep class org.webrtc.PeerConnection$ContinualGatheringPolicy { *; }
-keep class org.webrtc.PeerConnection$IceConnectionState { *; }
-keep class org.webrtc.PeerConnection$IceGatheringState { *; }
-keep class org.webrtc.PeerConnection$IceServer { *; }

```

```

-keep class org.webrtc.PeerConnection$IceTransportsType { *; }
-keep class org.webrtc.PeerConnection$KeyType { *; }
-keep class org.webrtc.PeerConnection$Observer { *; }
-keep class org.webrtc.PeerConnection$RTCConfiguration { *; }
-keep class org.webrtc.PeerConnection$RtcpMuxPolicy { *; }
-keep class org.webrtc.PeerConnection$SignalingState { *; }
-keep class org.webrtc.PeerConnection$TcpCandidatePolicy { *; }
-keep class org.webrtc.PeerConnectionFactory { *; }
-keep class org.webrtc.RtpReceiver { *; }
-keep class org.webrtc.RtpSender { *; }
-keep class org.webrtc.SessionDescription { *; }
-keep class org.webrtc.SessionDescription$Type { *; }
-keep class org.webrtc.StatsReport { *; }
-keep class org.webrtc.StatsReport$Value { *; }
-keep class org.webrtc.SurfaceTextureHelper { *; }
-keep class org.webrtc.voiceengine.BuildInfo { *; }
-keep class org.webrtc.VideoCapturer { *; }
-keep class org.webrtc.VideoCapturer$CapturerObserver { *; }
-keep class org.webrtc.VideoCapturer$NativeObserver { *; }
-keep class org.webrtc.VideoCapturerAndroid { *; }
-keep class org.webrtc.VideoCapturerAndroid$CapturerObserver { *; }
-keep class org.webrtc.VideoCapturerAndroid$NativeObserver { *; }
-keep class org.webrtc.voiceengine.WebRtcAudioManager { *; }
-keep class org.webrtc.voiceengine.WebRtcAudioRecord { *; }
-keep class org.webrtc.voiceengine.WebRtcAudioTrack { *; }
-keep class org.webrtc.VideoRenderer$I420Frame { *; }
-keep class org.webrtc.VideoTrack { *; }

-keep class com.genband.mobile.api.utilities.LogManager { *; }
-keep class com.genband.mobile.core.WebRTC.view.SurfaceViewRenderer { *; }
-keep class com.genband.mobile.core.WebRTC.SDPObserver { *; }
-keep class com.genband.mobile.core.WebRTC.WebRTCCall$* { *; }

# For native methods, see
http://proguard.sourceforge.net/manual/examples.html#native
-keepclasseswithmembernames class * {
    native <methods>;
}

# For enumeration classes, see
http://proguard.sourceforge.net/manual/examples.html#enumerations
-keepclassmembers enum * {
    public static **[] values();
    public static ** valueOf(java.lang.String);
}
#===== MobileSDK =====#

```