

/enable-remote-control POST

Parameter:

user	email	required
------	-------	----------

Info: returns session unique 'remote_key'

/disable-remote-control POST

Parameter:

user	email	required
remote_key	gets returned by enable-remote-control	required

/add-order POST

Parameter:

location	ex. Morty	required
user	email	required
priority	True / False	not required

Info: Add Order to que

/cancel-order POST

Parameter:

user	email	required
------	-------	----------

Info: Cancel open order

/confirm-delivery POST

Parameter:

user	email	required
------	-------	----------

Info: Mark your order as delivered

Example AJAX Call:

```
function addOrder(location) {
    $.ajax({
        "type": "POST",
        "dataType": "json",
        "url": "/add-order/",
        "data": {'user': 'lion.reinacher@gmail.com', 'location':
'Morty', 'csrfmiddlewaretoken': '{{ csrf_token }}'},
        "success": function(result) {
            console.log(result);
        },
    });
};
```

/api/update-orders POST

Parameter:

data	order list	required
verify_key	generated verification hash	required
timestamp	timestamp	required

/api/update-last-barcode POST

Parameter:

data	last barcode identifier (str)	required
verify_key	generated verification hash	required
timestamp	timestamp	required

/api/update-remote-control POST

Parameter:

data	{remote_control_status, remote_control_user}	required
verify_key	generated verification hash	required
timestamp	timestamp	required

Status Codes:

CODE	TYPE	DEFINITION
100	OK	Call Successful
101	ERROR	no open order
102	ERROR	no open remote session
103	ERROR	already remote controlled returns current remote-user as data['user']
104	ERROR	not your remote session returns current remote-user as data['user']
105	ERROR	speed for left motor not defined
106	ERROR	speed for right motor not defined
107	ERROR	Unknown left speed Identifier
108	ERROR	Unknown right speed Identifier
109	ERROR	Invalid left speed Identifier - speed Identifier has to be float
110	ERROR	Invalid right speed Identifier - speed Identifier has to be float
111	ERROR	remote control not enabled
115	ERROR	user not defined
116	ERROR	authorisation failed - key invalid
117	ERROR	parameter missing
199	ERROR	General Error, see returned response data

Verification Hash:

```
def generate_verification_hash(identifier, secret_key):  
    import hashlib  
    from datetime import datetime  
    timestamp = str(datetime.utcnow().timestamp())  
    hash = hashlib.sha224((identifier + secret_key +  
timestamp).encode('UTF-8')).hexdigest()  
    return hash, timestamp
```

For Interface-to-Robot-Calls the identifier is the user, so in most cases the email address.

```
def verify_call(hash, timestamp, identifier, secret_key):  
    import hashlib  
    from datetime import datetime  
    try:  
        timestamp = float(timestamp)  
    except:  
        return False  
    if datetime.utcnow().timestamp() - timestamp < 30:  
        compare_hash = hashlib.sha224((identifier + secret_key +  
str(timestamp)).encode('UTF-8')).hexdigest()  
        if hash == compare_hash:  
            return True  
    return False
```

For Robot-to-Interface-Calls the identifier is an empty string.

Keys:

```
secret_keys = {'add_order': '45Aa*+=H5Nc NdLm',  
               'cancel_order': '^SF%NqDZB8av_KbB',  
               'confirm_order': 'EdHD&k5X$y4UTv%z',  
               'enable_remote': '@Qzc?UwqkVbh5z@W',  
               'update_remote_control_status': 'A5_8umdWZd84RLar',  
               'update_order_list': 'yYRJ6=P*H9e7x^nA',  
               'update_last_barcode': '9qm*YAG#rQJK+fY^'}
```