

# L'extension geometry

Hideo Umeki  
latexgeometry@gmail.com

2010/09/12 v5.6

## Résumé

Cette extension met à disposition une interface flexible et simple pour traiter les dimensions des pages. Vous pouvez ainsi changer la mise en page avec des paramètres intuitifs. Par exemple, si vous voulez fixer une marge de 2 cm pour chaque bord de la feuille, vous pouvez juste taper `\usepackage[margin=2cm]{geometry}`. L'aspect de la page peut être changé en cours de document avec la commande `\newgeometry`.

## 1 Préface à la version 5

- **Changement de la mise en page en cours de document.**  
Les nouvelles commandes `\newgeometry{...}` et `\restoregeometry` permettent à l'utilisateur de changer les dimensions de la page en cours de document. `\newgeometry` est assez similaire à `\geometry`, à ceci près que `\newgeometry` désactive toutes les options indiquées dans le préambule mais conserve les options liées à la taille du papier : `landscape`, `portrait` et les options de format (telles que `papersize`, `paper=a4paper` et ainsi de suite).
- **Un nouvel ensemble d'options pour spécifier la zone de mise en page.**  
Les options spécifiant la zone dans laquelle sont calculées les dimensions de la page sont ajoutées : `layout`, `layoutsizex`, `layoutwidth`, `layoutheight` et ainsi de suite. Ces options aident à imprimer la mise en forme pour une autre taille de papier. Par exemple, avec `a4paper` et `layout=a5paper`, l'extension `geometry` utilise la mise en forme A5 pour calculer les marges avec un format de papier A4.
- **Une nouvelle option de pilote xetex.**  
Une nouvelle option de pilote, `xetex`, est ajoutée. La routine d'auto-détection des pilotes a été revue pour éviter une erreur avec les commandes non définies. Notez que « `geometry.cfg` » (dans `TEX Live`), qui désactive la routine d'auto-détection et sélectionne `pdftex`, n'est plus nécessaire et ne crée plus de problème quand bien même il existe toujours. Sélectionner `xetex` est fortement recommandé avec `XYLATEX`.
- **Nouveaux formats de papier prédéfinis pour les formats JIS B et les formats ISO C**  
Les formats de papier prédéfinis `b0j` à `b6j` pour les formats JIS (Japanese Industrial Standards) B et `c0paper` à `c6paper` pour les formats ISO C (v5.4~) sont ajoutés.
- **Changement des valeurs par défaut pour les marges sous-définies.**  
Dans les versions précédentes, si une marge seulement était spécifiée, `bottom=1cm` par exemple, alors `geometry` fixait l'autre marge avec le ratio de marge (1:1 par défaut pour les dimensions verticales) et obtenait `top=1cm` dans ce cas. La version 5 fixe la taille du corps du texte avec la valeur par défaut `scale` (= 0.7) et détermine la marge non spécifiée. (Voir Section 6.5)
- **Les options `showframe` et `showcrop` fonctionnent sur chaque page.**  
Avec l'option `showframe`, le cadre de la page est affiché sur chaque page. En complément, une nouvelle option `showcrop` affiche les traits de coupe à chaque coin de la zone de mise en page sur chaque page. Notez que les marques seront invisibles sans spécification d'une taille de mise en page plus petite que la taille du papier. La version 5.4 introduit un nouveau processus de débordement `\shipout` utilisant l'extension `atbegshi` impliquant le chargement de cette extension quand les options `showframe` ou `showcrop` sont sélectionnées.
- **Le chargement de `geometry.cfg` précède le traitement des options de classe.**  
La version antérieure chargeait `geometry.cfg` après avoir traité les options de classe du document. Maintenant que le fichier de configuration est chargé avant, vous pouvez changer le comportement indiqué dans `geometry.cfg` en ajoutant des options dans `\documentclass` aussi bien que dans `\usepackage` et `\geometry`.
- **Options supprimées : `compat2` et `twosideshift`.** La version 5 n'est plus compatible avec ces options `compat2` et `twosideshift` pour des raisons de simplification.

## 2 Introduction

Fixer des dimensions pour une mise en page sous L<sup>A</sup>T<sub>E</sub>X n'est pas immédiat. Vous devez ajuster plusieurs dimensions inhérentes à L<sup>A</sup>T<sub>E</sub>X pour placer une zone de texte où vous le souhaitez. Si vous voulez centrer la zone de texte dans un papier que vous utilisez, par exemple, vous devez spécifier les dimensions fondamentales suivantes :

```
\usepackage{calc}
\setlength\textwidth{7in}
\setlength\textheight{10in}
\setlength\oddsidemargin{(\paperwidth-\textwidth)/2 - 1in}
\setlength\topmargin{(\paperheight-\textheight
-\headheight-\headsep-\footskip)/2 - 1in}.
```

Sans l'extension *calc*, l'exemple ci-dessus demanderait des réglages plus fastidieux. L'extension *geometry* présente une façon simple de fixer des paramètres de mise en page. Dans ce cas, ce que vous avez à faire est juste

```
\usepackage[text={7in,10in},centering]{geometry}.
```

En plus du centrage, le réglage des marges par rapport à chaque bord de la feuille est également problématique. Mais *geometry* simplifie aussi ce point. Si vous souhaitez fixer chaque marge à 1,8 cm, vous pouvez saisir

```
\usepackage[margin=3.8cm]{geometry}
```

De fait, l'extension *geometry* dispose d'un mécanisme d'auto-complétion dans lequel les dimensions manquantes sont automatiquement déterminées. L'extension *geometry* sera également utile lorsque vous avez à traiter la mise en page en suivant des instructions strictes. Par exemple,

*La largeur maximale de la zone de texte est de 16,5cm de large par 22,25 cm de haut. La marge de tête sur chaque page doit être de 3 cm depuis le bord haut de la feuille. La marge gauche doit être de 2.3 cm depuis le bord gauche. Le pied de page avec le numéro de la page doit être en bas de la zone de texte.*

Dans ce cas, avec *geometry* vous saisissez

```
\usepackage[total={16.5cm,22.25cm},
top=3cm, left=2.3cm, includefoot]{geometry}.
```

Définir une zone de texte sur papier dans un système de préparation de document présente certaines analogies avec le placement d'une fenêtre dans un système d'environnement de bureau. Le nom « *geometry* » provient de l'option *-geometry* utilisée pour spécifier la taille et la localisation d'une fenêtre dans l'environnement de bureau X Window.

## 3 Anatomie d'une page

✖Figure 1 shows the page layout dimensions defined in the *geometry* package. The page layout contains a *total body* (printable area) and *margins*. The *total body* consists of a *body* (text area) with an optional *header*, *footer* and marginal notes (*marginpar*). There are four margins : *left*, *right*, *top* and *bottom*. For twosided documents, horizontal margins should be called *inner* and *outer*.

<i>paper</i>	:	<i>total body</i> and <i>margins</i>
<i>total body</i>	:	<i>body</i> (text area) (optional <i>head</i> , <i>foot</i> and <i>marginpar</i> )
<i>margins</i>	:	<i>left</i> ( <i>inner</i> ), <i>right</i> ( <i>outer</i> ), <i>top</i> and <i>bottom</i>

Each margin is measured from the corresponding edge of a paper. For example, left margin (inner margin) means a horizontal distance between the left (inner) edge of the paper and that of the total body. Therefore the left and top margins defined in *geometry* are different from the native dimensions *\leftmargin* and *\topmargin*. The size of a body (text area) can be modified by *\textwidth* and *\textheight*. The dimensions for paper, total body and margins have the following relations.

$$\text{paperwidth} = \text{left} + \text{width} + \text{right} \quad (1)$$

$$\text{paperheight} = \text{top} + \text{height} + \text{bottom} \quad (2)$$

The total body width and height would be defined :

$$\text{width} := \text{textwidth} \quad (+ \text{marginparsep} + \text{marginparwidth}) \quad (3)$$

$$\text{height} := \text{textheight} \quad (+ \text{headheight} + \text{headsep} + \text{footskip}) \quad (4)$$




FIGURE 1 – Dimension names used in the `geometry` package. `width = textwidth` and `height = textheight` by default. `left`, `right`, `top` and `bottom` are margins. If margins on verso pages are swapped by `twoside` option, margins specified by `left` and `right` options are used for the inside and outside margins respectively. `inner` and `outer` are aliases of `left` and `right` respectively.




FIGURE 2 – `includehead` and `includefoot` include the head and foot respectively into `total body`. (a) `height = textheight` (default). (b) `height = textheight + headheight + headsep + footskip` if `includehead` and `includefoot`. If the top and bottom margins are specified, `includehead` and `includefoot` result in shorter `textheight`.

In Equation (3) `width:=textwidth` by default, while `marginparsep` and `marginparwidth` are included in `width` if `includemp` option is set true. In Equation (4), `height:=textheight` by default. If `includehead` is set to true, `headheight` and `headsep` are considered as a part of `height`. In the same way, `includefoot` takes `footskip` into `height`. Figure 2 shows how these options work in the vertical direction.

Thus, the page layout consists of three parts (lengths) in each direction : one body and two margins. If the two of them are explicitly specified, the other length is obvious and no need to be specified. Figure 3 shows a simple model of page dimensions. When a length  $L$  is given and is partitioned into the body  $b$ , the margins  $a$  and  $c$ , it's obvious that

$$L = a + b + c \quad (5)$$

The specification with two of the three ( $a, b$  and  $c$ ) fixed explicitly is solvable. If two or more are left unspecified or ‘underspecified’, Equation (5) cannot be solved without any other relation between them. If all of them are specified, then it needs to check whether or not they satisfy Equation (5), that is too much specification or ‘overspecified’.

The `geometry` package has auto-completion mechanism that saves the trouble of specifying the page layout dimensions. For example, you can set

```
\usepackage[width=14cm, left=3cm]{geometry}
```




FIGURE 3 – A simple model of page dimensions.

on A4 paper. In this case you don't have to set the right margin. The details of auto-completion will be described in Section 6.5.

## 4 User interface

### 4.1 Commands

The geometry package provides the following commands :

- `\geometry{<options>}`
- `\newgeometry{<options>}` and `\restoregeometry`
- `\savegeometry{<name>}` and `\loadgeometry{<name>}`

`\geometry{<options>}` changes the page layout according to the options specified in the argument. This command, if any, should be placed only in the preamble (before `\begin{document}`).

The geometry package may be used as part of a class or another package you use in your document. The command `\geometry` can overwrite some of the settings in the preamble. Multiple use of `\geometry` is allowed and then processed with the options concatenated. If geometry is not yet loaded, you can use only `\usepackage[<options>]{geometry}` instead of `\geometry`.

`\newgeometry{<options>}` changes the page layout mid-document. `\newgeometry` is almost similar to `\geometry` except that `\newgeometry` disables all the options specified by `\usepackage` and `\geometry` in the preamble and skips papersize-related options. `\restoregeometry` restores the page layout specified in the preamble. This command has no arguments. See Section 7 for details.

`\savegeometry{<name>}` saves the page dimensions as `<name>` where you put this command. `\loadgeometry{<name>}` loads the page dimensions saved as `<name>`. See Section 7 for details.

### 4.2 Optional argument

The geometry package adopts keyval interface '`<key>=<value>`' for the optional argument to `\usepackage`, `\geometry` and `\newgeometry`.

The argument includes a list of comma-separated keyval options and has basic rules as follows :

- Multiple lines are allowed, while blank lines are not.
- Any spaces between words are ignored.
- Options are basically order-independent. (There are some exceptions. See Section 6.2 for details.)

For example,

```
\usepackage[ a5paper , hmargin = { 3cm,
                                .8in } , height
              = 10in ]{geometry}
```

is equivalent to

```
\usepackage[height=10in,a5paper,hmargin={3cm,0.8in}]{geometry}
```

Some options are allowed to have sub-list, e.g. `{3cm,0.8in}`. Note that the order of values in the sub-list is significant. The above setting is also equivalent to the followings :

```
\usepackage{geometry}
\geometry{height=10in,a5paper,hmargin={3cm,0.8in}}
```

or

```
\usepackage[a5paper]{geometry}
\geometry{hmargin={3cm,0.8in},height=8in}
\geometry{height=10in}.
```

Thus, multiple use of `\geometry` just appends options.

geometry supports package *calc*<sup>1</sup>. For example,

---

1. CTAN : `macros/latex/required/tools`

```
\usepackage{calc}
\usepackage[height=20\baselineskip+10pt]{geometry}
```

### 4.3 Option types

geometry options are categorized into four types :

#### 1. Boolean type

takes a boolean value (**true** or **false**). If no value, **true** is set by default.

$\langle key \rangle = \text{true} \mid \text{false}$ .

$\langle key \rangle$  with no value is equivalent to  $\langle key \rangle = \text{true}$ .

*Examples :* `verbose=true`, `includehead`, `twoside=false`.

Paper name is the exception. The preferred paper name should be set with no values. Whatever value is given, it is ignored. For instance, `a4paper=XXX` is equivalent to `a4paper`.

#### 2. Single-valued type

takes a mandatory value.

$\langle key \rangle = \langle value \rangle$ .

*Examples :* `width=7in`, `left=1.25in`, `footskip=1cm`, `height=.86\paperheight`.

#### 3. Double-valued type

takes a pair of comma-separated values in braces. The two values can be shortened to one value if they are identical.

$\langle key \rangle = \{ \langle value1 \rangle, \langle value2 \rangle \}$ .

$\langle key \rangle = \langle value \rangle$  is equivalent to  $\langle key \rangle = \{ \langle value \rangle, \langle value \rangle \}$ .

*Examples :* `hmargin={1.5in,1in}`, `scale=0.8`, `body={7in,10in}`.

#### 4. Triple-valued type

takes three mandatory, comma-separated values in braces.

$\langle key \rangle = \{ \langle value1 \rangle, \langle value2 \rangle, \langle value3 \rangle \}$

Each value must be a dimension or null. When you give an empty value or ‘\*’, it means null and leaves the appropriate value to the auto-completion mechanism. You need to specify at least one dimension, typically two dimensions. You can set nulls for all the values, but it makes no sense.

*Examples :*

`hdivide={2cm,*,1cm}`, `vdivide={3cm,19cm, }`, `divide={1in,*,1in}`.

## 5 Option details

This section describes all options available in `geometry`. Options with a dagger <sup>†</sup> are not available as arguments of `\newgeometry` (See Section 7).

### 5.1 Paper size

The options below set paper/media size and orientation.

<sup>†</sup> `paper` | `papername`

specifies the paper size by name. `paper=\langle paper-name \rangle`. For convenience, you can specify the paper name without `paper=`. For example, `a4paper` is equivalent to `paper=a4paper`.

<sup>†</sup> `a0paper`, `a1paper`, `a2paper`, `a3paper`, `a4paper`, `a5paper`, `a6paper`,  
`b0paper`, `b1paper`, `b2paper`, `b3paper`, `b4paper`, `b5paper`, `b6paper`,  
`c0paper`, `c1paper`, `c2paper`, `c3paper`, `c4paper`, `c5paper`, `c6paper`,  
`b0j`, `b1j`, `b2j`, `b3j`, `b4j`, `b5j`, `b6j`,  
`ansiapaper`, `ansibpaper`, `ansicpaper`, `ansidpaper`, `ansiepaper`,  
`letterpaper`, `executivepaper`, `legalpaper`

specifies paper name. The value part is ignored even if any. For example, the followings have the same effect : `a5paper`, `a5paper=true`, `a5paper=false` and so forth.

`a[0-6]paper`, `b[0-6]paper` and `c[0-6]paper` are ISO A, B and C series of paper sizes respectively. The JIS (Japanese Industrial Standards) A-series is identical to the ISO A-series, but the JIS B-series is different from the ISO B-series. `b[0-6]j` should be used for the JIS B-series.




FIGURE 4 – The dimensions related to the layout size. Note that the layout size defaults to the same size as the paper, so you don’t have to specify layout-related options explicitly in most cases.

- † **screen** a special paper size with (W,H) = (225mm,180mm). For presentation with PC and video projector, “**screen,centering**” with ‘slide’ documentclass would be useful.
- † **paperwidth** width of the paper. **paperwidth**=*<length>*.
- † **paperheight** height of the paper. **paperheight**=*<length>*.
- † **papersize** width and height of the paper. **papersize**=*{<width>,<height>}* or **papersize**=*<length>*.
- † **landscape** switches the paper orientation to landscape mode.
- † **portrait** switches the paper orientation to portrait mode. This is equivalent to **landscape**=false.

The options for paper names (e.g., **a4paper**) and orientation (**portrait** and **landscape**) can be set as document class options. For example, you can set `\documentclass[a4paper,landscape]{article}`, then **a4paper** and **landscape** are processed in geometry as well. This is also the case for **twoside** and **twocolumn** (see also Section 5.5).

## 5.2 Layout size

You can specify the layout area with options described in this section regardless of the paper size. The options would help to print the specified layout to a different sized paper. For example, with **a4paper** and **layout=a5paper**, the package uses ‘A5’ layout to calculate margins on ‘A4’ paper. The layout size defaults to the same as the paper. The options for the layout size are available in **\newgeometry**, so that you can change the layout size in the middle of the document. The paper size itself can’t be changed though. Figure 4 shows what the difference between **layout** and **paper** is.

- layout** specifies the layout size by paper name. **layout**=*<paper-name>*. All the paper names defined in **geometry** are available. See Section 5.1 for details.
- layoutwidth** width of the layout. **layoutwidth**=*<length>*.
- layoutheight** height of the layout. **layoutheight**=*<length>*.
- layoutsiz** width and height of the layout. **layoutsiz**=*{<width>,<height>}* or **layoutsiz**=*<length>*.
- layoutoffset** specifies the horizontal offset from the left edge of the paper. **layoutoffset**=*<length>*.
- layoutvoffset** specifies the vertical offset from the top edge of the paper. **layoutvoffset**=*<length>*.
- layoutoffset** specifies both horizontal and vertical offsets. **layoutoffset**=*{<hoffset>,<voffset>}* or **layoutsiz**=*<length>*.

## 5.3 Body size

The options specifying the size of **total body** are described in this section.

- hscale** ratio of width of **total body** to **\paperwidth**. **hscale**=*<h-scale>*, e.g., **hscale**=0.8 is equivalent to **width**=0.8**\paperwidth**. (0.7 by default)
- vscale** ratio of height of **total body** to **\paperheight**, e.g., **vscale**=*<v-scale>*. (0.7 by default) **vscale**=0.9 is equivalent to **height**=0.9**\paperheight**.
- scale** ratio of **total body** to the paper. **scale**=*{<h-scale>,<v-scale>}* or **scale**=*<scale>*. (0.7 by default)

width   totalwidth	width of <i>total body</i> . <code>width=&lt;length&gt;</code> or <code>totalwidth=&lt;length&gt;</code> . This dimension defaults to <code>textwidth</code> , but if <code>includemp</code> is set to <code>true</code> , <code>width ≥ textwidth</code> because <code>width</code> includes the width of the marginal notes. If <code>textwidth</code> and <code>width</code> are specified at the same time, <code>textwidth</code> takes priority over <code>width</code> .
height   totalheight	height of <i>total body</i> , excluding header and footer by default. If <code>includehead</code> or <code>includefoot</code> is set, <code>height</code> includes the head or foot of the page as well as <code>textheight</code> . <code>height=&lt;length&gt;</code> or <code>totalheight=&lt;length&gt;</code> . If both <code>textheight</code> and <code>height</code> are specified, <code>height</code> will be ignored.
total	width and height of <i>total body</i> . <code>total={&lt;width&gt;,&lt;height&gt;}</code> or <code>total=&lt;length&gt;</code> .
textwidth	specifies <code>\textwidth</code> , the width of <i>body</i> (the text area). <code>textwidth=&lt;length&gt;</code> .
textheight	specifies <code>\textheight</code> , the height of <i>body</i> (the text area). <code>textheight=&lt;length&gt;</code> .
text   body	specifies both <code>\textwidth</code> and <code>\textheight</code> of the body of page. <code>body={&lt;width&gt;,&lt;height&gt;}</code> or <code>text=&lt;length&gt;</code> .
lines	enables users to specify <code>\textheight</code> by the number of lines. <code>lines=&lt;integer&gt;</code> .
includehead	includes the head of the page, <code>\headheight</code> and <code>\headsep</code> , into <i>total body</i> . It is set to <code>false</code> by default. It is opposite to <code>ignorehead</code> . See Figure 2 and Figure 5.
includefoot	includes the foot of the page, <code>\footskip</code> , into <i>total body</i> . It is opposite to <code>ignorefoot</code> . It is <code>false</code> by default. See Figure 2 and Figure 5.
includeheadfoot	sets both <code>includehead</code> and <code>includefoot</code> to <code>true</code> , which is opposite to <code>ignoreheadfoot</code> . See Figure 2 and Figure 5.
includemp	includes the margin notes, <code>\marginparwidth</code> and <code>\marginparsep</code> , into <i>body</i> when calculating horizontal calculation.
includeall	sets both <code>includeheadfoot</code> and <code>includemp</code> to <code>true</code> . See Figure 5.
ignorehead	disregards the head of the page, <code>headheight</code> and <code>headsep</code> , in determining vertical layout, but does not change those lengths. It is equivalent to <code>includehead=false</code> . It is set to <code>true</code> by default. See also <code>includehead</code> .
ignorefoot	disregards the foot of page, <code>footskip</code> , in determining vertical layout, but does not change that length. This option defaults to <code>true</code> . See also <code>includefoot</code> .
ignoreheadfoot	sets both <code>ignorehead</code> and <code>ignorefoot</code> to <code>true</code> . See also <code>includeheadfoot</code> .
ignoremp	disregards the marginal notes in determining the horizontal margins (defaults to <code>true</code> ). If marginal notes overrun the page, the warning message will be displayed when <code>verbose=true</code> . See also <code>includemp</code> and Figure 5.
ignoreall	sets both <code>ignoreheadfoot</code> and <code>ignoremp</code> to <code>true</code> . See also <code>includeall</code> .
heightrounded	This option rounds <code>\textheight</code> to $n$ -times ( $n$ : an integer) of <code>\baselineskip</code> plus <code>\topskip</code> to avoid “underfull vbox” in some cases. For example, if <code>\textheight</code> is 486pt with <code>\baselineskip 12pt</code> and <code>\topskip 10pt</code> , then $(39 \times 12\text{pt} + 10\text{pt}) = 478\text{pt} < 486\text{pt} < 490\text{pt} (= 40 \times 12\text{pt} + 10\text{pt}),$ as a result <code>\textheight</code> is rounded to 490pt. <code>heightrounded=false</code> by default.

Figure 5 illustrates various layouts with different layout modes. The dimensions for a header and a footer can be controlled by `nohead` or `nofoot` mode, which sets each length to 0pt directly. On the other hand, options with the prefix `ignore` do *not* change the corresponding native dimensions.

The following options can specify body and margins simultaneously with three comma-separated values in braces.

hdivide	horizontal partitions (left,width,right). <code>hdivide={&lt;left margin&gt;,&lt;width&gt;,&lt;right margin&gt;}</code> . Note that you should not specify all of the three parameters. The best way of using this option is to specify two of three and leave the rest with null(nothing) or <code>*</code> . For example, when you set <code>hdivide={2cm,15cm, }</code> , the margin from the right-side edge of page will be determined calculating <code>paperwidth-2cm-15cm</code> .
vdivide	vertical partitions (top,height,bottom). <code>vdivide={&lt;top margin&gt;,&lt;height&gt;,&lt;bottom margin&gt;}</code> .
divide	<code>divide={A,B,C}</code> is interpreted as <code>hdivide={A,B,C}</code> and <code>vdivide={A,B,C}</code> .




FIGURE 5 – Sample layouts for *total body* with different switches. (a) `includeheadfoot`, (b) `includeall`, (c) `includefoot` and (d) `includefoot, includemp`. If `reversemp` is set to `true`, the location of the marginal notes are swapped on every page. Option `twoside` swaps both margins and marginal notes on verso pages. Note that the marginal note, if any, is printed despite `ignoremp` or `includemp=false` and overrun the page in some cases.



## 5.4 Margin size

The options specifying the size of the margins are listed below.

left   lmargin   inner	left margin (for oneside) or inner margin (for twoside) of <i>total body</i> . In other words, the distance between the left (inner) edge of the paper and that of <i>total body</i> . left= <i>&lt;length&gt;</i> . inner has no special meaning, just an alias of left and lmargin.
right   rmargin   outer	right or outer margin of <i>total body</i> . right= <i>&lt;length&gt;</i> .
top   tmargin	top margin of the page. top= <i>&lt;length&gt;</i> . Note this option has nothing to do with the native dimension \topmargin.
bottom   bmargin	bottom margin of the page. bottom= <i>&lt;length&gt;</i> .
hmargin	left and right margin. hmargin={ <i>&lt;left margin&gt;</i> , <i>&lt;right margin&gt;</i> } or hmargin= <i>&lt;length&gt;</i> .
vmargin	top and bottom margin. vmargin={ <i>&lt;top margin&gt;</i> , <i>&lt;bottom margin&gt;</i> } or vmargin= <i>&lt;length&gt;</i> .
margin	margin={ <i>A,B</i> } is equivalent to hmargin={ <i>A,B</i> } and vmargin={ <i>A,B</i> }. margin= <i>A</i> is automatically expanded to hmargin= <i>A</i> and vmargin= <i>A</i> .
hmarginratio	horizontal margin ratio of left (inner) to right (outer). The value of <i>&lt;ratio&gt;</i> should be specified with colon-separated two values. Each value should be a positive integer less than 100 to prevent arithmetic overflow, e.g., 2:3 instead of 1:1.5. The default ratio is 1:1 for oneside, 2:3 for twoside.
vmarginratio	vertical margin ratio of top to bottom. The default ratio is 2:3.
marginratio   ratio	horizontal and vertical margin ratios. marginratio={( <i>horizontal ratio</i> ),( <i>vertical ratio</i> )} or marginratio= <i>&lt;ratio&gt;</i> .
hcentering	sets auto-centering horizontally and is equivalent to hmarginratio=1:1. It is set to true by default for oneside. See also hmarginratio.
vcentering	sets auto-centering vertically and is equivalent to vmarginratio=1:1. The default is false. See also vmarginratio.
centering	sets auto-centering and is equivalent to marginratio=1:1. See also marginratio. The default is false. See also marginratio.
twoside	switches on twoside mode with left and right margins swapped on verso pages. The option sets \@twoside and \@mparswitch switches. See also asymmetric.
asymmetric	implements a twosided layout in which margins are not swapped on alternate pages (by setting \oddsidemargin to \evensidemargin + bindingoffset) and in which the marginal notes stay always on the same side. This option can be used as an alternative to the twoside option. See also twoside.
bindingoffset	removes a specified space from the lefthand-side of the page for oneside or the inner-side for twoside. bindingoffset= <i>&lt;length&gt;</i> . This is useful if pages are bound by a press binding (glued, stitched, stapled ...). See Figure 6.
hdivide	See description in Section 5.3.
vdivide	See description in Section 5.3.
divide	See description in Section 5.3.

## 5.5 Native dimensions

The options below overwrite L<sup>A</sup>T<sub>E</sub>X native dimensions and switches for page layout (See the right-hand side in Figure 1).

<code>headheight</code>		<code>head</code>	modifies <code>\headheight</code> , height of header. <code>headheight=&lt;length&gt;</code> or <code>head=&lt;length&gt;</code> .
<code>headsep</code>	modifies <code>\headsep</code> , separation between header and text (body). <code>headsep=&lt;length&gt;</code> .		
<code>footskip</code>		<code>foot</code>	modifies <code>\footskip</code> , distance separation between baseline of last line of text and baseline of footer. <code>footskip=&lt;length&gt;</code> or <code>foot=&lt;length&gt;</code> .
<code>nohead</code>	eliminates spaces for the head of the page, which is equivalent to both <code>\headheight=0pt</code> and <code>\headsep=0pt</code> .		
<code>nofoot</code>	eliminates spaces for the foot of the page, which is equivalent to <code>\footskip=0pt</code> .		




FIGURE 6 – The option `bindingoffset` adds the specified length to the inner margin. Note that `twoside` option swaps the horizontal margins and the marginal notes together with `bindingoffset` on even pages (see **b**)), but `asymmetric` option suppresses the swap of the margins and marginal notes (but `bindingoffset` is still swapped).

<code>noheadfoot</code>	equivalent to <code>nohead</code> and <code>nofoot</code> , which means that <code>\headheight</code> , <code>\headsep</code> and <code>\footskip</code> are all set to <code>0pt</code> .
<code>footnotesep</code>	changes the dimension <code>\skip\footins</code> , separation between the bottom of text body and the top of footnote text.
<code>marginparwidth</code>   <code>marginpar</code>	modifies <code>\marginparwidth</code> , width of the marginal notes. <code>marginparwidth=&lt;length&gt;</code> .
<code>marginparsep</code>	modifies <code>\marginparsep</code> , separation between body and marginal notes. <code>marginparsep=&lt;length&gt;</code> .
<code>nomarginpar</code>	shrinks spaces for marginal notes to <code>0pt</code> , which is equivalent to <code>\marginparwidth=0pt</code> and <code>\marginparsep=0pt</code> .
<code>columnsep</code>	modifies <code>\columnsep</code> , the separation between two columns in <code>twocolumn</code> mode.
<code>hoffset</code>	modifies <code>\hoffset</code> . <code>hoffset=&lt;length&gt;</code> .
<code>voffset</code>	modifies <code>\voffset</code> . <code>voffset=&lt;length&gt;</code> .
<code>offset</code>	horizontal and vertical offset. <code>offset={&lt;hoffset&gt;,&lt;voffset&gt;}</code> or <code>offset=&lt;length&gt;</code> .
<code>twocolumn</code>	sets <code>twocolumn</code> mode with <code>\@twocolumntrue</code> . <code>twocolumn=false</code> denotes <code>onecolumn</code> mode with <code>\@twocolumnfalse</code> . Instead of <code>twocolumn=false</code> , you can specify <code>onecolumn</code> (which defaults to <code>true</code> )
<code>onecolumn</code>	works as <code>twocolumn=false</code> . On the other hand, <code>onecolumn=false</code> is equivalent to <code>twocolumn</code> .
<code>twoside</code>	sets both <code>\@twosidetrue</code> and <code>\@mparswitchtrue</code> . See Section 5.4.
<code>textwidth</code>	sets <code>\textwidth</code> directly. See Section 5.3.
<code>textheight</code>	sets <code>\textheight</code> directly. See Section 5.3.
<code>reversemp</code>   <code>reversemarginpar</code>	makes the marginal notes appear in the left (inner) margin with <code>\@reversemargintrue</code> . The option doesn't change <code>includemp</code> mode. It's set <code>false</code> by default.

## 5.6 Drivers

The package supports drivers `dvips`, `dvipdfm`, `pdftex`, `xetex` and `vtex`. You can also set `dvipdfm` for `dvipdfmx` and `xdvipdfmx`. `pdftex` for `pdflatex`, and `vtex` for `VTEX` environment. The driver options are exclusive. The driver can be set by either `driver=<driver name>` or any of the drivers directly like `pdftex`. By default, `geometry` guesses the driver appropriate to the system in use. Therefore, you don't have to set a driver in most cases. However, if you want to use `dvipdfm`, you should specify it explicitly.

<sup>†</sup> <code>driver</code>	specifies the driver with <code>driver=&lt;driver name&gt;</code> . <code>dvips</code> , <code>dvipdfm</code> , <code>pdftex</code> , <code>vtex</code> , <code>xetex</code> , <code>auto</code> and <code>none</code> are available as a driver name. The names except for <code>auto</code> and <code>none</code> can be specified directly with the name without <code>driver=</code> . <code>driver=auto</code> makes the auto-detection work whatever the previous setting is. <code>driver=none</code> disables the
----------------------------------	---

auto-detection and sets no driver, which may be useful when you want to let other package work out the driver setting. For example, if you want to use `crop` package with `geometry`, you should call `\usepackage[driver=none]{geometry}` before the `crop` package.

- <sup>†</sup> `dvips` writes the paper size in dvi output with the `\special` macro. If you use `dvips` as a DVI-to-PS driver, for example, to print a document with `\geometry{a3paper,landscape}` on A3 paper in landscape orientation, you don't need options “`-t a3 -t landscape`” to `dvips`.
- <sup>†</sup> `dvipdfm` works like `dvips` except for landscape correction. You can set this option when using `dvipdfmx` and `xdvipdfmx` to process the dvi output.
- <sup>†</sup> `pdftex` sets `\pdfpagewidth` and `\pdfpageheight` internally.
- <sup>†</sup> `xetex` is the same as `pdftex` except for ignoring `\pdf{h,v}origin` undefined in  $\text{\LaTeX}$ . This option is introduced in the version 5. Note that ‘`geometry.cfg`’ in  $\text{\TeX}$  Live, which disables the auto-detection routine and sets `pdftex`, is no longer necessary, but has no problem even though it's left undeleted. Instead of `xetex`, you can specify `dvipdfm` with  $\text{\LaTeX}$  if you want to use specials of `dvipdfm`  $\text{\LaTeX}$  supports.
- <sup>†</sup> `vtex` sets dimensions `\mediawidth` and `\mediaheight` for  $\text{\VTeX}$ . When this driver is selected (explicitly or automatically), `geometry` will auto-detect which output mode (DVI, PDF or PS) is selected in  $\text{\VTeX}$ , and do proper settings for it.

If explicit driver setting is mismatched with the typesetting program in use, the default driver `dvips` would be selected.

## 5.7 Other options

The other useful options are described here.

- <sup>†</sup> `verbose` displays the parameter results on the terminal. `verbose=false` (default) still puts them into the log file.
- <sup>†</sup> `reset` sets back the layout dimensions and switches to the settings before `geometry` is loaded. Options given in `geometry.cfg` are also cleared. Note that this cannot reset `pass` and `mag` with `true`dimen. `reset=false` has no effect and cannot cancel the previous `reset=true` if any. For example, when you go
 

```
\documentclass[landscape]{article}
\usepackage[twoside,reset,left=2cm]{geometry}
```

 with `\ExecuteOptions{scale=0.9}` in `geometry.cfg`, then as a result, `landscape` and `left=2cm` remain effective, and `scale=0.9` and `twoside` are ineffective.
- <sup>†</sup> `mag` sets magnification value (`\mag`) and automatically modifies `\hoffset` and `\voffset` according to the magnification. `mag=<value>`. Note that `<value>` should be an integer value with 1000 as a normal size. For example, `mag=1414` with `a4paper` provides an enlarged print fitting in `a3paper`, which is 1.414 ( $=\sqrt{2}$ ) times larger than `a4paper`. Font enlargement needs extra disk space. **Note that setting `mag` should precede any other settings with ‘true’ dimensions, such as `1.5truein`, `2truecm` and so on.** See also `true`dimen option.
- <sup>†</sup> `true`dimen changes all internal explicit dimension values into *true* dimensions, e.g., `1in` is changed to `1truein`. Typically this option will be used together with `mag` option. Note that this is ineffective against externally specified dimensions. For example, when you set “`mag=1440, margin=10pt, true`dimen”, margins are not ‘true’ but magnified. If you want to set exact margins, you should set like “`mag=1440, margin=10truept, true`dimen” instead.
- <sup>†</sup> `pass` disables all of the `geometry` options and calculations except `verbose` and `showframe`. It is order-independent and can be used for checking out the page layout of the documentclass, other packages and manual settings without `geometry`.
- <sup>†</sup> `showframe` shows visible frames for the text area and page, and the lines for the head and foot on the first page.
- <sup>†</sup> `showcrop` prints crop marks at each corner of user-specified layout area.

## 6 Processing options

### 6.1 Order of loading

If there's `geometry.cfg` somewhere  $\TeX$  can find it, `geometry` loads it first. For example, in `geometry.cfg` you may write `\ExecuteOptions{a4paper}`, which specifies A4 paper as the default paper. Basically you can use all the options defined in `geometry` with `\ExecuteOptions{}`.

The order of loading in the preamble of your document is as follows :

1. `geometry.cfg` if it exists.
2. Options specified with `\documentclass[options]{...}`.
3. Options specified with `\usepackage[options]{geometry}`
4. Options specified with `\geometry{options}`, which can be called multiple times. (`reset` option will cancel the specified options ever given in `\usepackage{geometry}` or `\geometry`.)

### 6.2 Order of options

The specification of `geometry` options is order-independent, and overwrites the previous one for the same setting. For example,

`[left=2cm, right=3cm]` is equivalent to `[right=3cm, left=2cm]`.

The options called multiple times overwrite the previous settings. For example,

`[verbose=true, verbose=false]` results in `verbose=false`.

`[hmargin={3cm,2cm}, left=1cm]` is the same as `hmargin={1cm,2cm}`, where the left (or inner) margin is overwritten by `left=1cm`.

`reset` and `mag` are exceptions. The `reset` option removes all the `geometry` options (except `pass`) before it. If you set

```
\documentclass[landscape]{article}
\usepackage[margin=1cm,twoside]{geometry}
\geometry{a5paper, reset, left=2cm}
```

then `margin=1cm`, `twoside` and `a5paper` are removed, and is eventually equivalent to

```
\documentclass[landscape]{article}
\usepackage[left=2cm]{geometry}
```

The `mag` option should be set in advance of any other settings with 'true' length, such as `left=1.5truecm`, `width=5truein` and so on. The `\mag` primitive can be set before this package is called.

### 6.3 Priority

There are several ways to set dimensions of the *body* : `scale`, `total`, `text` and `lines`. The `geometry` package gives higher priority to the more concrete specification. Here is the priority rule for *body*.

priority :    low     $\longrightarrow$     high

$$\left\{ \begin{array}{c} \text{hscale} \\ \text{vscale} \\ \text{scale} \end{array} \right\} < \left\{ \begin{array}{c} \text{width} \\ \text{height} \\ \text{total} \end{array} \right\} < \left\{ \begin{array}{c} \text{textwidth} \\ \text{textheight} \\ \text{text} \end{array} \right\} < \text{lines}.$$

For example,

```
\usepackage[hscale=0.8, textwidth=7in, width=18cm]{geometry}
```

is the same as `\usepackage[textwidth=7in]{geometry}`. Another example :

```
\usepackage[lines=30, scale=0.8, text=7in]{geometry}
```

results in `[lines=30, textwidth=7in]`.




FIGURE 7 – Specifications  $S(0,0)$  to  $S(2,1)$  and the completion rules (arrows). Column and row numbers denote the number of explicitly specified lengths for margin and body respectively.  $S(m,b)$  denote a specification with a set of the numbers  $(margin, body) = (m, b)$ .

## 6.4 Defaults

This section sums up the default settings for the auto-completion described later.

The default vertical margin ratio is  $2/3$ , namely,

$$top : bottom = 2 : 3 \quad \text{default.} \quad (6)$$

As for the horizontal margin ratio, the default value depends on whether the document is onesided or twosided,

$$left(inner) : right(outer) = \begin{cases} 1 : 1 & \text{default for oneside,} \\ 2 : 3 & \text{default for twoside.} \end{cases} \quad (7)$$

Obviously the default horizontal margin ratio for oneside is ‘centering’.

The `geometry` package has the following default setting for *onesided* documents :

- `scale=0.7` (*body* is  $0.7 \times paper$ )
- `marginratio={1:1, 2:3}` (1:1 for horizontal and 2:3 for vertical margins)
- `ignoreall` (the header, footer, marginal notes are excluded when calculating the size of *body*.)

For *twosided* document with `twoside` option, the default setting is the same as *onesided* except that the horizontal margin ratio is set to 2:3 as well.

Additional options overwrite the previous specified dimensions.

## 6.5 Auto-completion

Figure 7 shows schematically how many specification patterns exist and how to solve the ambiguity of the specifications. Each axis shows the numbers of lengths explicitly specified for body and margins.  $S(m,b)$  presents the specification with a set of numbers  $(margin, body) = (m, b)$ .

For example, the specification `width=14cm, left=3cm` is categorized into  $S(1,1)$ , which is an adequate specification. If you add `right=4cm`, it would be in  $S(2,1)$  and overspecified. If only `width=14cm` is given, it’s in  $S(0,1)$ , underspecified.

The `geometry` package has the auto-completion mechanism, in which if the layout parameters are underspecified or overspecified, `geometry` works out the ambiguity using the defaults and other relations. Here are the specifications and the completion rules.

**S(0,0)** Nothing is specified. The `geometry` package sets *body* with the default `scale` ( $= 0.7$ ). For example, `width` is set to be  $0.7 \times layoutwidth$ . Note that by default `layoutwidth` and `loutheight` will be equal to `\paperwidth` and `\paperheight` respectively. Thus  $S(0,0)$  goes to  $S(0,1)$ . See  $S(0,1)$ .

**S(0,1)** Only *body* is specified, such as `width=7in, lines=20, body={20cm,24cm}, scale=0.9` and so forth. Then `geometry` sets margins with the margin ratio. If the margin ratio is not specified, the default is used. The default vertical margin ratio is defined as

$$top : bottom = 2 : 3 \quad \text{default.} \quad (8)$$

As for the horizontal margin ratio, the default value depends on whether the document is onesided or twosided,

$$\text{left (inner) : right (outer)} = \begin{cases} 1 : 1 & \text{default for oneside,} \\ 2 : 3 & \text{default for twoside.} \end{cases} \quad (9)$$

For example, if `height=22cm` is specified on A4 paper, geometry calculates `top` margin as follows :

$$\begin{aligned} \text{top} &= (\text{layoutheight} - \text{height}) \times 2/5 \\ &= (29.7 - 22) \times 2/5 = 3.08(\text{cm}) \end{aligned} \quad (10)$$

Thus `top` margin and body `height` have been determined, the specification for the vertical goes to `S(1,1)` and all the parameters can be solved.

- S(1,0)** Only one margin is specified, such as `bottom=2cm`, `left=1in`, `top=3cm`, and so forth.
- **If the margin ratio is *not* specified**, geometry sets *body* with the default `scale` (`= 0.7`). For example, if `top=2.4cm` is specified, geometry sets `height = 0.7 × layoutheight` (`= 0.7\paperheight` by default), then `S(1,0)` goes to `S(1,1)`, in which `bottom` is calculated with `layoutheight - (height + top)` and results in 6.51cm on A4 paper if the layout size is equal to the paper size.
  - **If the margin ratio is specified**, such as `hmarginratio={1:2}`, `vratio={3:4}` and so forth, geometry sets the other margin with the specified margin ratio. For example, if a set of options “`top=2.4cm, vratio={3:4}`” is specified, geometry sets `bottom` to be 3.2cm calculating 
$$\text{bottom} = \text{top}/3 \times 4 = 3.2\text{cm}$$
 Thus `S(1,0)` goes to `S(2,0)`.

Note that the version 4 or earlier used to set the other margin with the margin ratio. In the version 5, therefore, with the same specification, the result will be different from the one in the version 4. For example, if only `top=2.4cm` is specified, you got `bottom=2.4cm` in the version 4 or earlier, but you will get `bottom=6.51cm` in the version 5.

- S(2,1)** The *body* and two *margins* are all specified, such as `vdivide={1in,8in,1.5in}`, “`left=3cm,width=13cm,right=4cm`” and so forth. Since geometry basically gives priority to *margins* if dimensions are overspecified, geometry forgets and resets *body*. For example, if you specify

```
\usepackage[a4paper,left=3cm,width=13cm,right=4cm]{geometry},
```

`width` is reset to be 14cm because the width of a A4 paper is 21cm long.

## 7 Changing layout mid-document

The version 5 provides the new commands `\newgeometry{...}` and `\restoregeometry`, which allow you to change page dimensions in the middle of the document. Unlike `\geometry` in the preamble, `\newgeometry` is available only after `\begin{document}`, resets all the options ever specified except for the papersize-related options : `landscape`, `portrait`, and paper size options (such as `papersize`, `paper=a4paper` and so forth), which can't be changed with `\newgeometry`.

The command `\restoregeometry` restores the page layout specified in the preamble (before `\begin{document}`) with the options to `\usepackage{geometry}` and `\geometry`.

Note that both `\newgeometry` and `\restoregeometry` insert `\clearpage` where they are called.

Below is an example of changing layout mid-document. The layout L1 specified with `hmargin=3cm` (`left` and `right` margins are 3cm long) is changed to L2 with `left=3cm`, `right=1cm` and `bottom=0.1cm`. The layout L1 is restored with `\restoregeometry`.

```

\usepackage[hmargin=3cm]{geometry}
\begin{document}
  Layout L1

\newgeometry{left=3cm,right=1cm,bottom=0.1cm}

  Layout L2 (new)

\restoregeometry


  Layout L1 (restored)

\newgeometry{margin=1cm,includefoot}

  Layout L3 (new)

\end{document}

```



A set of commands `\savegeometry{<name>}` and `\loadgeometry{<name>}` is handy if you want to reuse more different layouts in your document. For example,

```

\usepackage[hmargin=3cm]{geometry}
\begin{document}
  L1
\newgeometry{left=3cm,right=1cm,bottom=0.1cm}
\savegeometry{L2}
  L2 (new, saved)
\restoregeometry
  L1 (restored)
\newgeometry{margin=1cm,includefoot}
  L3 (new)
\loadgeometry{L2}
  L2 (loaded)
\end{document}

```

## 8 Examples

1. A onesided page layout with the text area centered in the paper. The examples below have the same result because the horizontal margin ratio is set 1:1 for oneside by default.
  - `centering`
  - `marginratio=1:1`
  - `vcentering`
2. A twosided page layout with the inside offset for binding set to 1cm.
  - `twoside, bindingoffset=1cm`

In this case, `textwidth` is shorter than that of the default twosided document by  $0.7 \times 1\text{cm}$  ( $= 0.7\text{cm}$ ) because the default width of *body* is set with `scale=0.7`, which means `width = 0.7 \times layoutwidth` ( $= 0.7\text{\textbackslash paperwidth}$  by default).
3. A layout with the left, right, and top margin 3cm, 2cm and 2.5in respectively, with `textheight` of 40 lines, and with the head and foot of the page included in *total body*. The two examples below have the same result.

- `left=3cm, right=2cm, lines=40, top=2.5in, includeheadfoot`
  - `hmargin={3cm,2cm}, tmargin=2.5in, lines=40, includeheadfoot`
4. A layout with the height of *total body* 10in, the bottom margin 2cm, and the default width. The top margin will be calculated automatically. Each solution below results in the same page layout.
- `vdivide={*, 10in, 2cm}`
  - `bmarg=2cm, height=10in`
  - `bottom=2cm, textheight=10in`
- Note that dimensions for *head* and *foot* are excluded from height of *total body*. An additional `includefoot` makes `\footskip` included in `totalheight`. Therefore, in the two cases below, `textheight` in the former layout is shorter than the latter (with 10in exactly) by `\footskip`. In other words, `height = textheight + footskip` when `includefoot=true` in this case.
- `bmarg=2cm, height=10in, includefoot`
  - `bottom=2cm, textheight=10in, includefoot`
5. A layout with `textwidth` and `textheight` 90% of the paper and with *body* centered. Each solution below results in the same page layout as long as `layoutwidth` and `layoutheight` are not modified from the default.
- `scale=0.9, centering`
  - `text={.9\paperwidth,.9\paperheight}, ratio=1:1`
  - `width=.9\paperwidth, vmargin=.05\paperheight, marginratio=1:1`
  - `hdivide={*,0.9\paperwidth,*}, vdivide={*,0.9\paperheight,*}` (as for onesided documents)
  - `margin={0.05\paperwidth,0.05\paperheight}`
- You can add `heightrounded` to avoid an “underfull vbox warning” like
- ```
Underfull \vbox (badness 10000) has occurred while \output is active.
```
- See Section 5.3 for the detailed description about `heightrounded`.
6. A layout with the width of marginal notes set to 3cm and included in the width of *total body*. The following examples are the same.
- `marginparwidth=3cm, includemp`
  - `marginpar=3cm, ignoremp=false`
7. A layout where *body* occupies the whole paper with A5 paper in landscape. The following examples are the same.
- `a5paper, landscape, scale=1.0`
  - `landscape=TRUE, paper=a5paper, margin=0pt`
8. A screen size layout appropriate for presentation with PC and video projector.
- ```
\documentclass{slide}
\usepackage[screen,margin=0.8in]{geometry}
...
\begin{slide}
...
\end{slide}
```
9. A layout with fonts and spaces both enlarged from A4 to A3. In the case below, the resulting paper size is A3.
- `a4paper, mag=1414`.
- If you want to have a layout with two times bigger fonts, but without changing paper size, you can type
- `letterpaper, mag=2000, truedimen`.
- You can add `dvips` option, that is useful to preview it with proper paper size by `dviout` or `xdvi`.
10. Changing the layout of the first page and leaving the others as default before loading `geometry`. Use `pass` option, `\newgeometry` and `\restoregeometry`.
- ```
\documentclass{book}
\usepackage[pass]{geometry}
% 'pass' disregards the package layout,
% so the original 'book' layout is memorized here.
\begin{document}
\newgeometry{margin=1cm}% changes the first page dimensions.
Page 1
\restoregeometry % restores the original 'book' layout.
Page 2 and more
\end{document}
```



## 11. A complex page layout.

```
\usepackage[a5paper, landscape, twocolumn, twoside,  
left=2cm, hmarginratio=2:1, includemp, marginparwidth=43pt,  
bottom=1cm, foot=.7cm, includefoot, textheight=11cm, heightrounded,  
columnsep=1cm, dvips, verbose]{geometry}
```

Try typesetting it and checking out the result yourself. :-)

## 9 Known problems

- With `mag`  $\neq 1000$  and `truedimen`, `paperwidth` and `paperheight` shown in verbose mode are different from the real size of the resulted PDF. The PDF itself is correct anyway.
- With `mag`  $\neq 1000$ , *no* `truedimen` and `hyperref`, `hyperref` should be loaded before `geometry`. Otherwise the resulted PDF size will become wrong.
- With `crop` package and `mag`  $\neq 1000$ , `center` option of `crop` doesn't work well.

## 10 Acknowledgments

The author appreciates helpful suggestions and comments from many people including (in alphabetical order of family name) : Jean-Bernard Addor, Frank Bennett, Alexis Dimitriadis, Friedrich Flender, Adrian Heathcote, Stephan Hennig, Morten Høgholm, Jonathan Kew, James Kilfiger, Yusuke Kuroki, Jean-Marc Lasgouttes, Włodzimierz Macewicz, Frank Mittelbach, Eckhard Neber, Rolf Niepraschk, Hans Fr. Nordhaug, Heiko Oberdiek, Keith Reckdahl, Peter Riocreux, Will Robertson, Pablo Rodriguez, Nico Schlöemer, Perry C. Stearns, Frank Stengel, Plamen Tanovski, Petr Uher, Piet van Oostrum, Vladimir Volovich, Michael Vulis.

## 11 Implementation

```

1 (*package)

This package requires the following packages : keyval, ifpdf, ifvtex and ifxetex.
2 \RequirePackage{keyval}%
3 \RequirePackage{ifpdf}%
4 \RequirePackage{ifvtex}%
5 \RequirePackage{ifxetex}%

    Internal switches are declared here.
6 \newif\ifGm@verbose
7 \newif\ifGm@landscape
8 \newif\ifGm@swap@papersize
9 \newif\ifGm@includehead
10 \newif\ifGm@includefoot
11 \newif\ifGm@includemp
12 \newif\ifGm@hbody
13 \newif\ifGm@vbody
14 \newif\ifGm@heightrounded
15 \newif\ifGm@showframe
16 \newif\ifGm@showcrop
17 \newif\ifGm@pass
18 \newif\ifGm@resetpaper
19 \newif\ifGm@layout
20 \newif\ifGm@newgm

\Gm@cnth The counters for horizontal and vertical partitioning patterns.
\Gm@cntv 21 \newcount\Gm@cnth
22 \newcount\Gm@cntv

\c@Gm@tempcnt The counter is used to set number with calc.
23 \newcount\c@Gm@tempcnt

\Gm@bindingoffset The binding offset for the inner margin.
24 \newdimen\Gm@bindingoffset

    \Gm@wd@mp Correction lengths for \textwidth, \oddsidemargin and \evensidemargin in includemp mode.
    \Gm@odd@mp 25 \newdimen\Gm@wd@mp
    \Gm@even@mp 26 \newdimen\Gm@odd@mp
27 \newdimen\Gm@even@mp

\Gm@layoutwidth The dimensions for the layout area.
\Gm@layoutheight 28 \newdimen\Gm@layoutwidth
\Gm@layouthoffset 29 \newdimen\Gm@layoutheight
\Gm@layoutvoffset 30 \newdimen\Gm@layouthoffset
31 \newdimen\Gm@layoutvoffset

\Gm@dimlist The token in which LATEX native dimensions can be stored.
32 \newtoks\Gm@dimlist

\Gm@warning The macro to print warning messages.
33 \def\Gm@warning#1{\PackageWarningNoLine{geometry}{#1}}%

\ifGm@preamble The macro executes the option given as an argument only if it's specified in the preamble, as the
options of \usepackage and/or the argument of \geometry. Otherwise, the macro would print the
warning message and ignores the option setting.
34 \def\ifGm@preamble#1{%
35   \ifGm@newgm
36     \Gm@warning{‘#1’: not available in ‘\string\newgeometry’; skipped}%
37   \else
38     \expandafter\@firstofone
39   \fi}%

```

`\Gm@Dhratio` The default values for the horizontal and vertical *marginalratio* are defined. `\Gm@Dhratio` denotes the default value of horizontal *marginratio* for twoside page layout with left and right margins

`\Gm@Dhratio` swapped on verso pages, which is set by `twoside`.

```

40 \def\Gm@Dhratio{1:1}% = left:right default for oneside
41 \def\Gm@Dhratio{2:3}% = inner:outer default for twoside.
42 \def\Gm@Dvratio{2:3}% = top:bottom default

```

`\Gm@Dhscale` The default values for the horizontal and vertical *scale* are defined with 0.7.

`\Gm@Dvscale`

```

43 \def\Gm@Dhscale{0.7}%
44 \def\Gm@Dvscale{0.7}%

```

`\Gm@dvi` The driver names.

`\Gm@dvi`

```

45 \def\Gm@dvi{dvips}%
46 \def\Gm@dvi{dvipdfm}%
47 \def\Gm@dvi{pdftex}%
48 \def\Gm@dvi{xetex}%
49 \def\Gm@dvi{vtex}%

```

`\Gm@true` The macros for true and false.

`\Gm@false`

```

50 \def\Gm@true{true}%
51 \def\Gm@false{false}%

```

`\Gm@orgpw` These macros keep original paper (media) size intact.

`\Gm@orgph`

```

52 \edef\Gm@orgpw{\the\paperwidth}%
53 \edef\Gm@orgph{\the\paperheight}%

```

`\Gm@savelength` The macro saves the specified length to `\Gm@restore`.

```

54 \def\Gm@savelength#1{%
55   \g@addto@macro\Gm@restore{\expandafter\noexpand\expandafter\csname
56     #1\endcsname\expandafter=\expandafter\the\csname #1\endcsname\relax}}%

```

`\Gm@saveboolean` The macro saves the specified boolean to `\Gm@restore`.

```

57 \def\Gm@saveboolean#1{%
58   \csname if#1\endcsname
59     \g@addto@macro\Gm@restore{\expandafter\noexpand\csname #1true\endcsname}%
60   \else
61     \g@addto@macro\Gm@restore{\expandafter\noexpand\csname #1false\endcsname}%
62   \fi}%

```

`\Gm@restore` The initialization for `\Gm@restore`.

```

63 \def\Gm@restore{}%

```

`\Gm@save` The definition of the macro saving the real lengths L<sup>A</sup>T<sub>E</sub>X options.

```

64 \def\Gm@save{%
65   \Gm@savelength{\paperwidth}%
66   \Gm@savelength{\paperheight}%
67   \Gm@savelength{\textwidth}%
68   \Gm@savelength{\textheight}%
69   \Gm@savelength{\evensidemargin}%
70   \Gm@savelength{\oddsidemargin}%
71   \Gm@savelength{\topmargin}%
72   \Gm@savelength{\headheight}%
73   \Gm@savelength{\headsep}%
74   \Gm@savelength{\topskip}%
75   \Gm@savelength{\footskip}%
76   \Gm@savelength{\baselineskip}%
77   \Gm@savelength{\marginparwidth}%
78   \Gm@savelength{\marginparsep}%
79   \Gm@savelength{\columnsep}%
80   \Gm@savelength{\hoffset}%
81   \Gm@savelength{\voffset}%
82   \Gm@savelength{\Gm@layoutwidth}%
83   \Gm@savelength{\Gm@layoutheight}%
84   \Gm@savelength{\Gm@layouthoffset}%

```

```

85 \Gm@savelength{Gm@layoutvoffset}%
86 \Gm@saveboolean{@twocolumn}%
87 \Gm@saveboolean{@twoside}%
88 \Gm@saveboolean{@mparswitch}%
89 \Gm@saveboolean{@reversemargin}}%

\Gm@initnewgm The macro initializes the parameters for layout in \newgeometry.
90 \def\Gm@initnewgm{%
91 \Gm@passfalse
92 \Gm@swap@papersizefalse
93 \Gm@dimlist={}
94 \Gm@hbodyfalse
95 \Gm@vbodyfalse
96 \Gm@heightroundedfalse
97 \Gm@includeheadfalse
98 \Gm@includefootfalse
99 \Gm@includempfalse
100 \let\Gm@width\@undefined
101 \let\Gm@height\@undefined
102 \let\Gm@textwidth\@undefined
103 \let\Gm@textheight\@undefined
104 \let\Gm@lines\@undefined
105 \let\Gm@hscale\@undefined
106 \let\Gm@vscale\@undefined
107 \let\Gm@hmarginratio\@undefined
108 \let\Gm@vmarginratio\@undefined
109 \let\Gm@lmargin\@undefined
110 \let\Gm@rmargin\@undefined
111 \let\Gm@tmargin\@undefined
112 \let\Gm@bmargin\@undefined
113 \Gm@layoutfalse
114 \Gm@layouthoffset\z@
115 \Gm@layoutvoffset\z@
116 \Gm@bindingoffset\z@}%

\Gm@initall This initialization is called as soon as the package is load It's also called as soon as reset option is
specified.
117 \def\Gm@initall{%
118 \let\Gm@driver\@empty
119 \let\Gm@truedimen\@empty
120 \let\Gm@paper\@undefined
121 \Gm@resetpaperfalse
122 \Gm@landscapefalse
123 \Gm@verbosefalse
124 \Gm@showframefalse
125 \Gm@showcropfalse
126 \Gm@newgmfalse
127 \Gm@initnewgm}%

\Gm@setdriver The macro sets the specified driver.
128 \def\Gm@setdriver#1{%
129 \expandafter\let\expandafter\Gm@driver\csname Gm@#1\endcsname}%

\Gm@unsetdriver The macro unsets the specified driver if it has been set.
130 \def\Gm@unsetdriver#1{%
131 \expandafter\ifx\csname Gm@#1\endcsname\Gm@driver\let\Gm@driver\@empty\fi}%

\Gm@setbool The macros for boolean option processing.
\Gm@setboolrev 132 \def\Gm@setbool{ \@dblarg\Gm@@setbool}%
133 \def\Gm@setboolrev{ \@dblarg\Gm@@setboolrev}%
134 \def\Gm@@setbool[#1]#2#3{\Gm@doif{#1}{#3}{\csname Gm@#2\Gm@bool\endcsname}}%
135 \def\Gm@@setboolrev[#1]#2#3{\Gm@doifelse{#1}{#3}%
136 {\csname Gm@#2\Gm@false\endcsname}{\csname Gm@#2\Gm@true\endcsname}}%

```

`\Gm@doif` `\Gm@doif` executes the third argument #3 using a boolean value #2 of a option #1. `\Gm@doifelse` executes the third argument #3 if a boolean option #1 with its value #2 true, and executes the fourth argument #4 if false.

```

137 \def\Gm@doif#1#2#3{%
138   \lowercase{\def\Gm@bool{#2}}%
139   \ifx\Gm@bool\@empty
140     \let\Gm@bool\Gm@true
141   \fi
142   \ifx\Gm@bool\Gm@true
143   \else
144     \ifx\Gm@bool\Gm@false
145     \else
146       \let\Gm@bool\relax
147     \fi
148   \fi
149   \ifx\Gm@bool\relax
150     \Gm@warning{‘#1’ should be set to ‘true’ or ‘false’}%
151   \else
152     #3
153   \fi}%
154 \def\Gm@doifelse#1#2#3#4{%
155   \Gm@doif{#1}{#2}{\ifx\Gm@bool\Gm@true #3\else #4\fi}}%

```

`\Gm@reverse` The macro reverses a bool value.

```

156 \def\Gm@reverse#1{%
157   \csname ifGm@#1\endcsname
158   \csname Gm@#1false\endcsname\else\csname Gm@#1true\endcsname\fi}%

```

`\Gm@defbylen` Macros `\Gm@defbylen` and `\Gm@defbycnt` can be used to define `\Gm@xxxx` variables by length and counter respectively with calc package.

```

159 \def\Gm@defbylen#1#2{%
160   \begingroup\setlength\@tempdima{#2}%
161   \expandafter\xdef\csname Gm@#1\endcsname{\the\@tempdima}\endgroup}%
162 \def\Gm@defbycnt#1#2{%
163   \begingroup\setcounter{Gm@tempcnt}{#2}%
164   \expandafter\xdef\csname Gm@#1\endcsname{\the\value{Gm@tempcnt}}\endgroup}%

```

`\Gm@set@ratio` The macro parses the value of options specifying marginal ratios, which is used in `\Gm@setbyratio` macro.

```

165 \def\Gm@sep@ratio#1:#2{\@tempcnta=#1\@tempcntb=#2}%

```

`\Gm@setbyratio` The macro determines the dimension specified by #4 calculating  $\#3 \times a/b$ , where  $a$  and  $b$  are given by `\Gm@mratio` with  $a : b$  value. If #1 in brackets is `b`,  $a$  and  $b$  are swapped. The second argument with `h` or `v` denoting horizontal or vertical is not used in this macro.

```

166 \def\Gm@setbyratio[#1]#2#3#4{% determine #4 by ratio
167   \expandafter\Gm@sep@ratio\Gm@mratio\relax
168   \if#1b
169     \edef\@tempa{\the\@tempcnta}%
170     \@tempcnta=\@tempcntb
171     \@tempcntb=\@tempa\relax
172   \fi
173   \expandafter\setlength\expandafter\@tempdimb\expandafter
174     {\csname Gm@#3\endcsname}%
175   \ifnum\@tempcntb>\z@
176     \multiply\@tempdimb\@tempcnta
177     \divide\@tempdimb\@tempcntb
178   \fi
179   \expandafter\edef\csname Gm@#4\endcsname{\the\@tempdimb}}%

```

`\Gm@detiv` This macro determines the fourth length(#4) from #1(layoutwidth or layoutheight), #2 and #3. It is used in `\Gm@detall` macro.

```

180 \def\Gm@detiv#1#2#3#4{% determine #4.
181   \expandafter\setlength\expandafter\@tempdima\expandafter
182     {\csname Gm@layout#1\endcsname}%

```

```

183 \expandafter\setlength\expandafter\@tempdimb\expandafter
184   {\csname Gm@#2\endcsname}%
185 \addtolength\@tempdima{-\@tempdimb}%
186 \expandafter\setlength\expandafter\@tempdimb\expandafter
187   {\csname Gm@#3\endcsname}%
188 \addtolength\@tempdima{-\@tempdimb}%
189 \ifdim\@tempdima<\z@
190   \Gm@warning{‘#4’ results in NEGATIVE (\the\@tempdima).%
191     ^^J\@spaces ‘#2’ or ‘#3’ should be shortened in length}%
192 \fi
193 \expandafter\edef\csname Gm@#4\endcsname{\the\@tempdima}}%

```

**\Gm@detiandiii** This macro determines #2 and #3 from #1 with the first argument (#1) can be width or height, which is expanded into dimensions of paper and total body. It is used in \Gm@detall macro.

```

194 \def\Gm@detiandiii#1#2#3{% determine #2 and #3.
195   \expandafter\setlength\expandafter\@tempdima\expandafter
196     {\csname Gm@layout#1\endcsname}%
197   \expandafter\setlength\expandafter\@tempdimb\expandafter
198     {\csname Gm@#1\endcsname}%
199   \addtolength\@tempdima{-\@tempdimb}%
200   \ifdim\@tempdima<\z@
201     \Gm@warning{‘#2’ and ‘#3’ result in NEGATIVE (\the\@tempdima).%
202       ^^J\@spaces ‘#1’ should be shortened in length}%
203   \fi
204   \ifx\Gm@mratio\undefined
205     \expandafter\Gm@sep@ratio\Gm@Dmratio\relax
206   \else
207     \expandafter\Gm@sep@ratio\Gm@mratio\relax
208     \ifnum\@tempcntb>\z@\else
209       \Gm@warning{margin ratio a:b should be non-zero; default used}%
210       \expandafter\Gm@sep@ratio\Gm@Dmratio\relax
211     \fi
212   \fi
213   \@tempdimb=\@tempdima
214   \advance\@tempcntb\@tempcnta
215   \divide\@tempdima\@tempcntb
216   \multiply\@tempdima\@tempcnta
217   \advance\@tempdimb-\@tempdima
218   \expandafter\edef\csname Gm@#2\endcsname{\the\@tempdima}%
219   \expandafter\edef\csname Gm@#3\endcsname{\the\@tempdimb}}%

```

**\Gm@detall** This macro determines partition of each direction. The first argument (#1) should be h or v, the second (#2) width or height, the third (#3) lmargin or top, and the last (#4) rmargin or bottom.

```

220 \def\Gm@detall#1#2#3#4{%
221   \@tempcnta\z@
222   \if#1h
223     \let\Gm@mratio\Gm@hmarginratio
224     \edef\Gm@Dmratio{\if@twoside\Gm@Dhratiotwo\else\Gm@Dhratio\fi}%
225   \else
226     \let\Gm@mratio\Gm@vmarginratio
227     \edef\Gm@Dmratio{\Gm@Dvratio}%
228   \fi

```

\@tempcnta is treated as a three-digit binary value with top, middle and bottom denoted left(top), width(height) and right(bottom) margins user specified respectively.

```

229   \if#1h
230     \ifx\Gm@lmargin\undefined\else\advance\@tempcnta4\relax\fi
231     \ifGm@hbody\advance\@tempcnta2\relax\fi
232     \ifx\Gm@rmargin\undefined\else\advance\@tempcnta1\relax\fi
233     \Gm@cntb\@tempcnta
234   \else
235     \ifx\Gm@tmargin\undefined\else\advance\@tempcnta4\relax\fi
236     \ifGm@vbody\advance\@tempcnta2\relax\fi
237     \ifx\Gm@bmargin\undefined\else\advance\@tempcnta1\relax\fi
238     \Gm@cntv\@tempcnta
239   \fi

```

Case the value is 000 (=0) with nothing fixed (default) :

```

240 \ifcase\@tempcnta
241 \if#1h
242 \Gm@defbylen{width}{\Gm@Dhscale\Gm@layoutwidth}%
243 \else
244 \Gm@defbylen{height}{\Gm@Dvscale\Gm@layoutheight}%
245 \fi
246 \Gm@detiandiii{#2}{#3}{#4}%

```

Case 001 (=1) with right(bottom) fixed :

```

247 \or
248 \ifx\Gm@ratio\@undefined
249 \if#1h
250 \Gm@defbylen{width}{\Gm@Dhscale\Gm@layoutwidth}%
251 \else
252 \Gm@defbylen{height}{\Gm@Dvscale\Gm@layoutheight}%
253 \fi
254 \setlength\@tempdimc{\@nameuse{Gm@#4}}%
255 \Gm@detiandiii{#2}{#3}{#4}%
256 \expandafter\let\csname Gm@#2\endcsname\@undefined
257 \Gm@defbylen{#4}{\@tempdimc}%
258 \else
259 \Gm@setbyratio[f]{#1}{#4}{#3}%
260 \fi
261 \Gm@detiv{#2}{#3}{#4}{#2}%

```

Case 010 (=2) with width(height) fixed :

```

262 \or\Gm@detiandiii{#2}{#3}{#4}%

```

Case 011 (=3) with both width(height) and right(bottom) fixed :

```

263 \or\Gm@detiv{#2}{#2}{#4}{#3}%

```

Case 100 (=4) with left(top) fixed :

```

264 \or
265 \ifx\Gm@ratio\@undefined
266 \if#1h
267 \Gm@defbylen{width}{\Gm@Dhscale\Gm@layoutwidth}%
268 \else
269 \Gm@defbylen{height}{\Gm@Dvscale\Gm@layoutheight}%
270 \fi
271 \setlength\@tempdimc{\@nameuse{Gm@#3}}%
272 \Gm@detiandiii{#2}{#4}{#3}%
273 \expandafter\let\csname Gm@#2\endcsname\@undefined
274 \Gm@defbylen{#3}{\@tempdimc}%
275 \else
276 \Gm@setbyratio[b]{#1}{#3}{#4}%
277 \fi
278 \Gm@detiv{#2}{#3}{#4}{#2}%

```

Case 101 (=5) with both left(top) and right(bottom) fixed :

```

279 \or\Gm@detiv{#2}{#3}{#4}{#2}%

```

Case 110 (=6) with both left(top) and width(height) fixed :

```

280 \or\Gm@detiv{#2}{#2}{#3}{#4}%

```

Case 111 (=7) with all fixed though it is over-specified :

```

281 \or\Gm@warning{Over-specification in ‘#1’-direction.%
282 ~~~~J\spaces ‘#2’ (\@nameuse{Gm@#2}) is ignored}%
283 \Gm@detiv{#2}{#3}{#4}{#2}%
284 \else\fi}%

```

**\Gm@clean** The macro for setting unspecified dimensions to be \@undefined. This is used by \geometry macro.

```

285 \def\Gm@clean{%
286 \ifnum\Gm@cnth<4\let\Gm@lmargin\@undefined\fi
287 \ifodd\Gm@cnth\else\let\Gm@rmargin\@undefined\fi
288 \ifnum\Gm@cntv<4\let\Gm@tmargin\@undefined\fi
289 \ifodd\Gm@cntv\else\let\Gm@bmargin\@undefined\fi
290 \ifGm@hbody\else

```

```

291 \let\Gm@hscale\@undefined
292 \let\Gm@width\@undefined
293 \let\Gm@textwidth\@undefined
294 \fi
295 \ifGm@vbody\else
296 \let\Gm@vscale\@undefined
297 \let\Gm@height\@undefined
298 \let\Gm@textheight\@undefined
299 \fi
300 }%

```

**\Gm@parse@divide** The macro parses (h,v)divide options.

```

301 \def\Gm@parse@divide#1#2#3#4{%
302 \def\Gm@star{*}%
303 \@tempcnta\z@
304 \@for\Gm@tmp:=#1\do{%
305 \expandafter\KV@@sp@def\expandafter\Gm@frag\expandafter{\Gm@tmp}%
306 \edef\Gm@value{\Gm@frag}%
307 \ifcase\@tempcnta\relax\edef\Gm@key{#2}%
308 \or\edef\Gm@key{#3}%
309 \else\edef\Gm@key{#4}%
310 \fi
311 \@nameuse{Gm@set\Gm@key false}%
312 \ifx\empty\Gm@value\else
313 \ifx\Gm@star\Gm@value\else
314 \setkeys{Gm}{\Gm@key=\Gm@value}%
315 \fi\fi
316 \advance\@tempcnta\@ne}%
317 \let\Gm@star\relax}%

```

**\Gm@branch** The macro splits a value into the same two values.

```

318 \def\Gm@branch#1#2#3{%
319 \@tempcnta\z@
320 \@for\Gm@tmp:=#1\do{%
321 \KV@@sp@def\Gm@frag{\Gm@tmp}%
322 \edef\Gm@value{\Gm@frag}%
323 \ifcase\@tempcnta\relax% cnta == 0
324 \setkeys{Gm}{#2=\Gm@value}%
325 \or% cnta == 1
326 \setkeys{Gm}{#3=\Gm@value}%
327 \else\fi
328 \advance\@tempcnta\@ne}%
329 \ifnum\@tempcnta=\@ne
330 \setkeys{Gm}{#3=\Gm@value}%
331 \fi}%

```

**\Gm@magtooffset** This macro is used to adjust offsets by \mag.

```

332 \def\Gm@magtooffset{%
333 \@tempdima=\mag\Gm@truedimen sp%
334 \@tempdimb=1\Gm@truedimen in%
335 \divide\@tempdimb\@tempdima
336 \multiply\@tempdimb\@m
337 \addtolength{\hoffset}{1\Gm@truedimen in}%
338 \addtolength{\voffset}{1\Gm@truedimen in}%
339 \addtolength{\hoffset}{-\the\@tempdimb}%
340 \addtolength{\voffset}{-\the\@tempdimb}}%

```

**\Gm@setlength** This macro stores L<sup>A</sup>T<sub>E</sub>X native dimensions, which are stored and set afterwards.

```

341 \def\Gm@setlength#1#2{%
342 \let\Gm@len=\relax\let\Gm@td=\relax
343 \edef\addtolist{\noexpand\Gm@dimlist=%
344 {\the\Gm@dimlist \Gm@len{#1}{#2}}}\addtolist}%

```

**\Gm@expandlengths** This macro processes \Gm@dimlist.

```

345 \def\Gm@expandlengths{%

```



```

346 \def\Gm@td{\Gm@truedimen}%
347 \def\Gm@len#1#2{\setlength{#1}{#2}}%
348 \the\Gm@dimlist}%

```

`\Gm@setsize` The macro sets paperwidth and paperheight dimensions using `\Gm@setlength` macro.

```

349 \def\Gm@setsize#1(#2,#3)#4{%
350 \let\Gm@td\relax
351 \expandafter\Gm@setlength\csname #1width\endcsname{#2\Gm@td #4}%
352 \expandafter\Gm@setlength\csname #1height\endcsname{#3\Gm@td #4}%
353 \ifGm@landscape\Gm@swap@papersizetrue\else\Gm@swap@papersizefalse\fi}%

```

`\Gm@setpaper@ifpre` The macro changes the paper size.

```

354 \def\Gm@setpaper@ifpre#1{%
355 \ifGm@preamble{#1}\def\Gm@paper{#1}\@nameuse{Gm@#1}{paper}}}%

```

Various paper size are defined here.

```

356 \namedef{Gm@a0paper}#1{\Gm@setsize{#1}(841,1189){mm}}% ISO A0
357 \namedef{Gm@a1paper}#1{\Gm@setsize{#1}(594,841){mm}}% ISO A1
358 \namedef{Gm@a2paper}#1{\Gm@setsize{#1}(420,594){mm}}% ISO A2
359 \namedef{Gm@a3paper}#1{\Gm@setsize{#1}(297,420){mm}}% ISO A3
360 \namedef{Gm@a4paper}#1{\Gm@setsize{#1}(210,297){mm}}% ISO A4
361 \namedef{Gm@a5paper}#1{\Gm@setsize{#1}(148,210){mm}}% ISO A5
362 \namedef{Gm@a6paper}#1{\Gm@setsize{#1}(105,148){mm}}% ISO A6
363 \namedef{Gm@b0paper}#1{\Gm@setsize{#1}(1000,1414){mm}}% ISO B0
364 \namedef{Gm@b1paper}#1{\Gm@setsize{#1}(707,1000){mm}}% ISO B1
365 \namedef{Gm@b2paper}#1{\Gm@setsize{#1}(500,707){mm}}% ISO B2
366 \namedef{Gm@b3paper}#1{\Gm@setsize{#1}(353,500){mm}}% ISO B3
367 \namedef{Gm@b4paper}#1{\Gm@setsize{#1}(250,353){mm}}% ISO B4
368 \namedef{Gm@b5paper}#1{\Gm@setsize{#1}(176,250){mm}}% ISO B5
369 \namedef{Gm@b6paper}#1{\Gm@setsize{#1}(125,176){mm}}% ISO B6
370 \namedef{Gm@c0paper}#1{\Gm@setsize{#1}(917,1297){mm}}% ISO C0
371 \namedef{Gm@c1paper}#1{\Gm@setsize{#1}(648,917){mm}}% ISO C1
372 \namedef{Gm@c2paper}#1{\Gm@setsize{#1}(458,648){mm}}% ISO C2
373 \namedef{Gm@c3paper}#1{\Gm@setsize{#1}(324,458){mm}}% ISO C3
374 \namedef{Gm@c4paper}#1{\Gm@setsize{#1}(229,324){mm}}% ISO C4
375 \namedef{Gm@c5paper}#1{\Gm@setsize{#1}(162,229){mm}}% ISO C5
376 \namedef{Gm@c6paper}#1{\Gm@setsize{#1}(114,162){mm}}% ISO C6
377 \namedef{Gm@b0j}#1{\Gm@setsize{#1}(1030,1456){mm}}% JIS B0
378 \namedef{Gm@b1j}#1{\Gm@setsize{#1}(728,1030){mm}}% JIS B1
379 \namedef{Gm@b2j}#1{\Gm@setsize{#1}(515,728){mm}}% JIS B2
380 \namedef{Gm@b3j}#1{\Gm@setsize{#1}(364,515){mm}}% JIS B3
381 \namedef{Gm@b4j}#1{\Gm@setsize{#1}(257,364){mm}}% JIS B4
382 \namedef{Gm@b5j}#1{\Gm@setsize{#1}(182,257){mm}}% JIS B5
383 \namedef{Gm@b6j}#1{\Gm@setsize{#1}(128,182){mm}}% JIS B6
384 \namedef{Gm@ansipaper}#1{\Gm@setsize{#1}(8.5,11){in}}%
385 \namedef{Gm@ansibpaper}#1{\Gm@setsize{#1}(11,17){in}}%
386 \namedef{Gm@ansicpaper}#1{\Gm@setsize{#1}(17,22){in}}%
387 \namedef{Gm@ansidpaper}#1{\Gm@setsize{#1}(22,34){in}}%
388 \namedef{Gm@ansiepaper}#1{\Gm@setsize{#1}(34,44){in}}%
389 \namedef{Gm@letterpaper}#1{\Gm@setsize{#1}(8.5,11){in}}%
390 \namedef{Gm@legalpaper}#1{\Gm@setsize{#1}(8.5,14){in}}%
391 \namedef{Gm@executivepaper}#1{\Gm@setsize{#1}(7.25,10.5){in}}%
392 \namedef{Gm@screen}#1{\Gm@setsize{#1}(225,180){mm}}%

```

`'paper'` paper takes a paper name as its value.

```

393 \define@key{Gm}{paper}{\setkeys{Gm}{#1}}%
394 \let\KV@Gm@papername\KV@Gm@paper

```

`'a[0-6]paper'` The following paper names are available.

```

' b[0-6]paper' 395 \define@key{Gm}{a0paper}[true]{\Gm@setpaper@ifpre{a0paper}}%
' b[0-6]j' 396 \define@key{Gm}{a1paper}[true]{\Gm@setpaper@ifpre{a1paper}}%
'ansi[a-e]paper' 397 \define@key{Gm}{a2paper}[true]{\Gm@setpaper@ifpre{a2paper}}%
'letterpaper' 398 \define@key{Gm}{a3paper}[true]{\Gm@setpaper@ifpre{a3paper}}%
'legalpaper' 399 \define@key{Gm}{a4paper}[true]{\Gm@setpaper@ifpre{a4paper}}%
'executivepaper' 400 \define@key{Gm}{a5paper}[true]{\Gm@setpaper@ifpre{a5paper}}%
'screen'

```

```

401 \define@key{Gm}{a6paper}[true]{\Gm@setpaper@ifpre{a6paper}}%
402 \define@key{Gm}{b0paper}[true]{\Gm@setpaper@ifpre{b0paper}}%
403 \define@key{Gm}{b1paper}[true]{\Gm@setpaper@ifpre{b1paper}}%
404 \define@key{Gm}{b2paper}[true]{\Gm@setpaper@ifpre{b2paper}}%
405 \define@key{Gm}{b3paper}[true]{\Gm@setpaper@ifpre{b3paper}}%
406 \define@key{Gm}{b4paper}[true]{\Gm@setpaper@ifpre{b4paper}}%
407 \define@key{Gm}{b5paper}[true]{\Gm@setpaper@ifpre{b5paper}}%
408 \define@key{Gm}{b6paper}[true]{\Gm@setpaper@ifpre{b6paper}}%
409 \define@key{Gm}{c0paper}[true]{\Gm@setpaper@ifpre{c0paper}}%
410 \define@key{Gm}{c1paper}[true]{\Gm@setpaper@ifpre{c1paper}}%
411 \define@key{Gm}{c2paper}[true]{\Gm@setpaper@ifpre{c2paper}}%
412 \define@key{Gm}{c3paper}[true]{\Gm@setpaper@ifpre{c3paper}}%
413 \define@key{Gm}{c4paper}[true]{\Gm@setpaper@ifpre{c4paper}}%
414 \define@key{Gm}{c5paper}[true]{\Gm@setpaper@ifpre{c5paper}}%
415 \define@key{Gm}{c6paper}[true]{\Gm@setpaper@ifpre{c6paper}}%
416 \define@key{Gm}{b0j}[true]{\Gm@setpaper@ifpre{b0j}}%
417 \define@key{Gm}{b1j}[true]{\Gm@setpaper@ifpre{b1j}}%
418 \define@key{Gm}{b2j}[true]{\Gm@setpaper@ifpre{b2j}}%
419 \define@key{Gm}{b3j}[true]{\Gm@setpaper@ifpre{b3j}}%
420 \define@key{Gm}{b4j}[true]{\Gm@setpaper@ifpre{b4j}}%
421 \define@key{Gm}{b5j}[true]{\Gm@setpaper@ifpre{b5j}}%
422 \define@key{Gm}{b6j}[true]{\Gm@setpaper@ifpre{b6j}}%
423 \define@key{Gm}{ansiapaper}[true]{\Gm@setpaper@ifpre{ansiapaper}}%
424 \define@key{Gm}{ansibpaper}[true]{\Gm@setpaper@ifpre{ansibpaper}}%
425 \define@key{Gm}{ansicpaper}[true]{\Gm@setpaper@ifpre{ansicpaper}}%
426 \define@key{Gm}{ansidpaper}[true]{\Gm@setpaper@ifpre{ansidpaper}}%
427 \define@key{Gm}{ansiepaper}[true]{\Gm@setpaper@ifpre{ansiepaper}}%
428 \define@key{Gm}{letterpaper}[true]{\Gm@setpaper@ifpre{letterpaper}}%
429 \define@key{Gm}{legalpaper}[true]{\Gm@setpaper@ifpre{legalpaper}}%
430 \define@key{Gm}{executivepaper}[true]{\Gm@setpaper@ifpre{executivepaper}}%
431 \define@key{Gm}{screen}[true]{\Gm@setpaper@ifpre{screen}}%

```

‘paperwidth’ Direct specification for paper size is also possible.

```

‘paperheight’ 432 \define@key{Gm}{paperwidth}{\ifGm@preamble{paperwidth}{%
‘papersize’ 433 \def\Gm@paper{custom}\Gm@setlength\paperwidth{#1}}}%
434 \define@key{Gm}{paperheight}{\ifGm@preamble{paperheight}{%
435 \def\Gm@paper{custom}\Gm@setlength\paperheight{#1}}}%
436 \define@key{Gm}{papersize}{\ifGm@preamble{papersize}{%
437 \def\Gm@paper{custom}\Gm@branch{#1}{paperwidth}{paperheight}}}%

```

‘layout’ Direct specification for layout size is also possible.

```

‘layoutwidth’ 438 \define@key{Gm}{layout}{\Gm@layouttrue\@nameuse{Gm#1}{Gm@layout}}%
‘layoutheight’ 439 \let\KV@Gm@layoutname\KV@Gm@layout
‘layoutsizes’ 440 \define@key{Gm}{layoutwidth}{\Gm@layouttrue\Gm@setlength\Gm@layoutwidth{#1}}%
441 \define@key{Gm}{layoutheight}{\Gm@layouttrue\Gm@setlength\Gm@layoutheight{#1}}%
442 \define@key{Gm}{layoutsizes}{\Gm@branch{#1}{layoutwidth}{layoutheight}}%

```

‘landscape’ Paper orientation setting.

```

‘portrait’ 443 \define@key{Gm}{landscape}[true]{\ifGm@preamble{landscape}{%
444 \Gm@doifelse{landscape}{#1}%
445 {\ifGm@landscape\else\Gm@landscapetrue\Gm@reverse{swap@papersize}\fi}%
446 {\ifGm@landscape\Gm@landscapefalse\Gm@reverse{swap@papersize}\fi}}%
447 \define@key{Gm}{portrait}[true]{\ifGm@preamble{portrait}{%
448 \Gm@doifelse{portrait}{#1}%
449 {\ifGm@landscape\Gm@landscapefalse\Gm@reverse{swap@papersize}\fi}%
450 {\ifGm@landscape\else\Gm@landscapetrue\Gm@reverse{swap@papersize}\fi}}%

```

‘hscale’ These options can determine the length(s) of *total body* giving *scale(s)* against the paper size.

```

‘vscale’ 451 \define@key{Gm}{hscale}{\Gm@hbodytrue\edef\Gm@hscale{#1}}%
‘scale’ 452 \define@key{Gm}{vscale}{\Gm@vbodytrue\edef\Gm@vscale{#1}}%
453 \define@key{Gm}{scale}{\Gm@branch{#1}{hscale}{vscale}}%

```

‘width’ These options give concrete dimension(s) of *total body*. totalwidth and totalheight are aliases of

‘height’ width and height respectively.

‘total’

‘totalwidth’

‘totalheight’

```

454 \define@key{Gm}{width}{\Gm@hbodytrue\Gm@defbylen{width}{#1}}%
455 \define@key{Gm}{height}{\Gm@vbodytrue\Gm@defbylen{height}{#1}}%
456 \define@key{Gm}{total}{\Gm@branch{#1}{width}{height}}%
457 \let\KV@Gm@totalwidth\KV@Gm@width
458 \let\KV@Gm@totalheight\KV@Gm@height

‘textwidth’ These options directly sets the dimensions \textwidth and \textheight. body is an alias of text.
‘textheight’ 459 \define@key{Gm}{textwidth}{\Gm@hbodytrue\Gm@defbylen{textwidth}{#1}}%
‘text’ 460 \define@key{Gm}{textheight}{\Gm@vbodytrue\Gm@defbylen{textheight}{#1}}%
‘body’ 461 \define@key{Gm}{text}{\Gm@branch{#1}{textwidth}{textheight}}%
462 \let\KV@Gm@body\KV@Gm@text

‘lines’ The option sets \textheight with the number of lines.
463 \define@key{Gm}{lines}{\Gm@vbodytrue\Gm@defbycnt{lines}{#1}}%

‘includehead’ The options take the corresponding dimensions as part of body.
‘includefoot’ 464 \define@key{Gm}{includehead}[true]{\Gm@setbool{includehead}{#1}}%
‘includeheadfoot’ 465 \define@key{Gm}{includefoot}[true]{\Gm@setbool{includefoot}{#1}}%
‘includemp’ 466 \define@key{Gm}{includeheadfoot}[true]{\Gm@doifelse{includeheadfoot}{#1}}%
‘includeall’ 467 {\Gm@includeheadtrue\Gm@includefoottrue}%
468 {\Gm@includeheadfalse\Gm@includefootfalse}%
469 \define@key{Gm}{includemp}[true]{\Gm@setbool{includemp}{#1}}%
470 \define@key{Gm}{includeall}[true]{\Gm@doifelse{includeall}{#1}}%
471 {\Gm@includeheadtrue\Gm@includefoottrue\Gm@includemptrue}%
472 {\Gm@includeheadfalse\Gm@includefootfalse\Gm@includempfalse}%

‘ignorehead’ These options exclude head, foot and marginpars when determining body.
‘ignorefoot’ 473 \define@key{Gm}{ignorehead}[true]{%
‘ignoreheadfoot’ 474 \Gm@setboolrev[ignorehead]{includehead}{#1}}%
‘ignoremp’ 475 \define@key{Gm}{ignorefoot}[true]{%
‘ignoreall’ 476 \Gm@setboolrev[ignorefoot]{includefoot}{#1}}%
477 \define@key{Gm}{ignoreheadfoot}[true]{\Gm@doifelse{ignoreheadfoot}{#1}}%
478 {\Gm@includeheadfalse\Gm@includefootfalse}%
479 {\Gm@includeheadtrue\Gm@includefoottrue}%
480 \define@key{Gm}{ignoremp}[true]{%
481 \Gm@setboolrev[ignoremp]{includemp}{#1}}%
482 \define@key{Gm}{ignoreall}[true]{\Gm@doifelse{ignoreall}{#1}}%
483 {\Gm@includeheadfalse\Gm@includefootfalse\Gm@includempfalse}%
484 {\Gm@includeheadtrue\Gm@includefoottrue\Gm@includemptrue}%

‘heightrounded’ The option rounds \textheight to n-times of \baselineskip plus \topskip.
485 \define@key{Gm}{heightrounded}[true]{\Gm@setbool{heightrounded}{#1}}%

‘hdivide’ The options are useful to specify partitioning in each direction of the paper.
‘vdivide’ 486 \define@key{Gm}{hdivide}{\Gm@parse@divide{#1}{lmargin}{width}{rmargin}}%
‘divide’ 487 \define@key{Gm}{vdivide}{\Gm@parse@divide{#1}{tmargin}{height}{bmargin}}%
488 \define@key{Gm}{divide}{\Gm@parse@divide{#1}{lmargin}{width}{rmargin}}%
489 \Gm@parse@divide{#1}{tmargin}{height}{bmargin}}%

‘lmargin’ These options set margins. left, inner, innermargin are aliases of lmargin. right, outer,
‘rmargin’ outermargin are aliases of rmargin. top and bottom are aliases of tmargin and bmargin respectively.
‘tmargin’ 490 \define@key{Gm}{lmargin}{\Gm@defbylen{lmargin}{#1}}%
‘bmargin’ 491 \define@key{Gm}{rmargin}{\Gm@defbylen{rmargin}{#1}}%
‘left’ 492 \let\KV@Gm@left\KV@Gm@lmargin
‘inner’ 493 \let\KV@Gm@inner\KV@Gm@lmargin
‘innermargin’ 494 \let\KV@Gm@innermargin\KV@Gm@lmargin
‘right’ 495 \let\KV@Gm@right\KV@Gm@rmargin
‘outer’ 496 \let\KV@Gm@outer\KV@Gm@rmargin
‘outermargin’ 497 \let\KV@Gm@outermargin\KV@Gm@rmargin
‘top’ 498 \define@key{Gm}{tmargin}{\Gm@defbylen{tmargin}{#1}}%
‘bottom’ 499 \define@key{Gm}{bmargin}{\Gm@defbylen{bmargin}{#1}}%
500 \let\KV@Gm@top\KV@Gm@tmargin
501 \let\KV@Gm@bottom\KV@Gm@bmargin

```

```

‘hmargin’   These options are shorthands for setting margins.
‘vmargin’   502 \define@key{Gm}{hmargin}{\Gm@branch{#1}{lmargin}{rmargin}}%
‘margin’    503 \define@key{Gm}{vmargin}{\Gm@branch{#1}{tmargin}{bmargin}}%
            504 \define@key{Gm}{margin}{\Gm@branch{#1}{lmargin}{tmargin}}%
            505 \Gm@branch{#1}{rmargin}{bmargin}}%

‘hmarginratio’ Options specifying the margin ratios.
‘vmarginratio’ 506 \define@key{Gm}{hmarginratio}{\edef\Gm@hmarginratio{#1}}%
‘marginratio’ 507 \define@key{Gm}{vmarginratio}{\edef\Gm@vmarginratio{#1}}%
‘hratio’      508 \define@key{Gm}{marginratio}{\Gm@branch{#1}{hmarginratio}{vmarginratio}}%
‘vratio’      509 \let\KV@Gm@hratio\KV@Gm@hmarginratio
‘ratio’       510 \let\KV@Gm@vratio\KV@Gm@vmarginratio
            511 \let\KV@Gm@ratio\KV@Gm@marginratio

‘hcentering’ Useful shorthands to place body centered.
‘vcentering’ 512 \define@key{Gm}{hcentering}[true]{\Gm@doifelse{hcentering}{#1}}%
‘centering’   513 {\def\Gm@hmarginratio{1:1}}{}%
            514 \define@key{Gm}{vcentering}[true]{\Gm@doifelse{vcentering}{#1}}%
            515 {\def\Gm@vmarginratio{1:1}}{}%
            516 \define@key{Gm}{centering}[true]{\Gm@doifelse{centering}{#1}}%
            517 {\def\Gm@hmarginratio{1:1}\def\Gm@vmarginratio{1:1}}{}%

‘twoside’     If twoside=true, \@twoside and \@mparswitch is set to true.
            518 \define@key{Gm}{twoside}[true]{\Gm@doifelse{twoside}{#1}}%
            519 {\@twosidetrue\@mparswitchtrue}{\@twosidefalse\@mparswitchfalse}}%

‘asymmetric’ asymmetric sets \@mparswitchfalse and \@twosidetrue A asymmetric=false has no effect.
            520 \define@key{Gm}{asymmetric}[true]{\Gm@doifelse{asymmetric}{#1}}%
            521 {\@twosidetrue\@mparswitchfalse}}{}%

‘bindingoffset’ The macro adds the specified space to the inner margin.
            522 \define@key{Gm}{bindingoffset}{\Gm@setlength\Gm@bindingoffset{#1}}%

‘headheight’ The direct settings of head and/or foot dimensions.
‘headsep’    523 \define@key{Gm}{headheight}{\Gm@setlength\headheight{#1}}%
‘footskip’   524 \define@key{Gm}{headsep}{\Gm@setlength\headsep{#1}}%
‘head’       525 \define@key{Gm}{footskip}{\Gm@setlength\footskip{#1}}%
‘foot’       526 \let\KV@Gm@head\KV@Gm@headheight
            527 \let\KV@Gm@foot\KV@Gm@footskip

‘nohead’     They are only shorthands to set head and/or foot to be 0pt.
‘nofoot’     528 \define@key{Gm}{nohead}[true]{\Gm@doifelse{nohead}{#1}}%
‘noheadfoot’ 529 {\Gm@setlength\headheight\z@\Gm@setlength\headsep\z@}{}%
            530 \define@key{Gm}{nofoot}[true]{\Gm@doifelse{nofoot}{#1}}%
            531 {\Gm@setlength\footskip\z@}{}%
            532 \define@key{Gm}{noheadfoot}[true]{\Gm@doifelse{noheadfoot}{#1}}%
            533 {\Gm@setlength\headheight\z@\Gm@setlength\headsep
            534 \z@\Gm@setlength\footskip\z@}{}%

‘footnotesep’ The option directly sets a native dimension \footnotesep.
            535 \define@key{Gm}{footnotesep}{\Gm@setlength{\skip\footins}{#1}}%

‘marginparwidth’ They directly set native dimensions \marginparwidth and \marginparsep.
‘marginpar’   536 \define@key{Gm}{marginparwidth}{\Gm@setlength\marginparwidth{#1}}%
‘marginparsep’ 537 \let\KV@Gm@marginpar\KV@Gm@marginparwidth
            538 \define@key{Gm}{marginparsep}{\Gm@setlength\marginparsep{#1}}%

‘nomarginpar’ The macro is a shorthand for \marginparwidth=0pt and \marginparsep=0pt.
            539 \define@key{Gm}{nomarginpar}[true]{\Gm@doifelse{nomarginpar}{#1}}%
            540 {\Gm@setlength\marginparwidth\z@\Gm@setlength\marginparsep\z@}{}%

‘columnsep’ The option sets a native dimension \columnsep.
            541 \define@key{Gm}{columnsep}{\Gm@setlength\columnsep{#1}}%

```

```

‘hoffset’ The former two options set native dimensions \hoffset and \voffset. offset can set both of them
‘voffset’ with the same value.
‘offset’ 542 \define@key{Gm}{hoffset}{\Gm@setlength\hoffset{#1}}%
543 \define@key{Gm}{voffset}{\Gm@setlength\voffset{#1}}%
544 \define@key{Gm}{offset}{\Gm@branch{#1}{hoffset}{voffset}}%

‘layouthoffset’
‘layoutvoffset’ 545 \define@key{Gm}{layouthoffset}{\Gm@setlength\Gm@layouthoffset{#1}}%
‘layoutvoffset’ 546 \define@key{Gm}{layoutvoffset}{\Gm@setlength\Gm@layoutvoffset{#1}}%
547 \define@key{Gm}{layoutoffset}{\Gm@branch{#1}{layouthoffset}{layoutvoffset}}%

‘twocolumn’ The option sets \twocolumn switch.
548 \define@key{Gm}{twocolumn}[true]{%
549 \Gm@doif{twocolumn}{#1}{\csname @twocolumn\Gm@bool\endcsname}}%

‘onecolumn’ This option has the reverse effect of twocolumn option.
550 \define@key{Gm}{onecolumn}[true]{%
551 \Gm@doifelse{onecolumn}{#1}{\@twocolumnfalse}{\@twocolumntrue}}%

‘reversemp’ The both options set \reversemargin.
‘reversemarginpar’ 552 \define@key{Gm}{reversemp}[true]{%
553 \Gm@doif{reversemp}{#1}{\csname @reversemargin\Gm@bool\endcsname}}%
554 \define@key{Gm}{reversemarginpar}[true]{%
555 \Gm@doif{reversemarginpar}{#1}{\csname @reversemargin\Gm@bool\endcsname}}%

‘driver’
556 \define@key{Gm}{driver}{\ifGm@preamble{driver}{%
557 \edef\@tempa{#1}\edef\@auto{auto}\edef\@none{none}%
558 \ifx\@tempa\empty\let\Gm@driver\relax\else
559 \ifx\@tempa\@none\let\Gm@driver\relax\else
560 \ifx\@tempa\@auto\let\Gm@driver\empty\else
561 \setkeys{Gm}{#1}\fi\fi\fi\let\@auto\relax\let\@none\relax}}%

‘dvips’ The geometry package supports dvips, dvipdfm, pdflatex and vtex. dvipdfm works like dvips.
‘dvipdfm’ 562 \define@key{Gm}{dvips}[true]{\ifGm@preamble{dvips}{%
‘pdftex’ 563 \Gm@doifelse{dvips}{#1}{\Gm@setdriver{dvips}}{\Gm@unsetdriver{dvips}}}%
‘xetex’ 564 \define@key{Gm}{dvipdfm}[true]{\ifGm@preamble{dvipdfm}{%
‘vtex’ 565 \Gm@doifelse{dvipdfm}{#1}{\Gm@setdriver{dvipdfm}}{\Gm@unsetdriver{dvipdfm}}}%
566 \define@key{Gm}{pdftex}[true]{\ifGm@preamble{pdftex}{%
567 \Gm@doifelse{pdftex}{#1}{\Gm@setdriver{pdftex}}{\Gm@unsetdriver{pdftex}}}%
568 \define@key{Gm}{xetex}[true]{\ifGm@preamble{xetex}{%
569 \Gm@doifelse{xetex}{#1}{\Gm@setdriver{xetex}}{\Gm@unsetdriver{xetex}}}%
570 \define@key{Gm}{vtex}[true]{\ifGm@preamble{vtex}{%
571 \Gm@doifelse{vtex}{#1}{\Gm@setdriver{vtex}}{\Gm@unsetdriver{vtex}}}%

‘verbose’ The verbose mode.
572 \define@key{Gm}{verbose}[true]{\ifGm@preamble{verbose}{\Gm@setbool{verbose}{#1}}}%

‘reset’ The option cancels all the options specified before reset, except pass. mag ( $\neq$  1000) with truedimen
cannot be also reset.
573 \define@key{Gm}{reset}[true]{\ifGm@preamble{reset}{%
574 \Gm@doifelse{reset}{#1}{\Gm@restore@org\Gm@initall
575 \ProcessOptionsKV[c]{Gm}\Gm@setdefaultpaper}{}}}%

‘resetpaper’ If resetpaper is set to true, the paper size redefined in the package is discarded and the original one
is restored. This option may be useful to print nonstandard sized documents with normal printers
and papers.
576 \define@key{Gm}{resetpaper}[true]{\ifGm@preamble{resetpaper}{%
577 \Gm@setbool{resetpaper}{#1}}}%

‘mag’ mag is expanded immediately when it is specified. So reset can’t reset mag when it is set with
truedimen.
578 \define@key{Gm}{mag}{\ifGm@preamble{mag}{\mag=#1}}%

```

‘truedimen’ If truedimen is set to true, all of the internal explicit dimensions is changed to *true* dimensions, e.g., 1in is changed to 1truein.

```
579 \define@key{Gm}{truedimen}[true]{\ifGm@preamble{truedimen}{%
580   \Gm@doifelse{truedimen}{#1}{\let\Gm@truedimen\Gm@true}%
581   {\let\Gm@truedimen\@empty}}}%
```

‘pass’ The option makes all the options specified ineffective except verbose switch.

```
582 \define@key{Gm}{pass}[true]{\ifGm@preamble{pass}{\Gm@setbool{pass}{#1}}}%
```

‘showframe’ The showframe option prints page frames to help you understand what the resulting layout is like.

```
583 \define@key{Gm}{showframe}[true]{\Gm@setbool{showframe}{#1}}%
```

‘showcrop’ The showcrop option prints crop marks at each corner of the layout area.

```
584 \define@key{Gm}{showcrop}[true]{\Gm@setbool{showcrop}{#1}}%
```

**\Gm@setdefaultpaper** The macro stores paper dimensions. This macro should be called after \ProcessOptionsKV[c]{Gm}. If the landscape option in \documentclass is specified, the class immediately swaps the paper dimensions.

```
585 \def\Gm@setdefaultpaper{%
586   \ifx\Gm@paper\@undefined
587     \Gm@setsize{paper}{\strip@pt\paperwidth,\strip@pt\paperheight}{pt}%
588     \Gm@setsize{Gm@layout}{\strip@pt\paperwidth,\strip@pt\paperheight}{pt}%
589     \Gm@swap@papersizefalse
590   \fi}%
```

**\Gm@adjustpaper** The macro checks if paperwidth/height is larger than 0pt, which is used in \Gm@process. The paper dimensions can be swapped when paper orientation is changed over by landscape and portrait options.

```
591 \def\Gm@adjustpaper{%
592   \ifdim\paperwidth>p@else
593     \PackageError{geometry}{%
594       \string\paperwidth\space(\the\paperwidth) too short}{%
595       Set a paper type (e.g., ‘a4paper’).}%
596   \fi
597   \ifdim\paperheight>p@else
598     \PackageError{geometry}{%
599       \string\paperheight\space(\the\paperheight) too short}{%
600       Set a paper type (e.g., ‘a4paper’).}%
601   \fi
602   \ifGm@swap@papersize
603     \setlength\@tempdima{\paperwidth}%
604     \setlength\paperwidth{\paperheight}%
605     \setlength\paperheight{\@tempdima}%
606   \fi
607   \ifGm@layoutelse
608     \setlength\Gm@layoutwidth{\paperwidth}%
609     \setlength\Gm@layoutheight{\paperheight}%
610   \fi}%
```

**\Gm@checkmp** The macro checks whether or not the marginpars overrun the page.

```
611 \def\Gm@checkmp{%
612   \ifGm@includempelse
613     \@tempcnta\z@\@tempcntb\@ne
614     \if@twocolumn
615       \@tempcnta\@ne
616     else
617       \if@reversemargin
618         \@tempcnta\@ne\@tempcntb\z@
619       \fi
620     \fi
621     \@tempdima\marginparwidth
622     \advance\@tempdima\marginparsep
623     \ifnum\@tempcnta=\@ne
624       \@tempdimc\@tempdima
```

```

625     \setlength\@tempdimb{\Gm@lmargin}%
626     \advance\@tempdimc-\@tempdimb
627     \ifdim\@tempdimc>\z@
628         \Gm@warning{The marginal notes overrun the paper edge.^^J
629         \spaces Add \the\@tempdimc\space and more to the left margin}%
630     \fi
631 \fi
632 \ifnum\@tempcntb=\@ne
633     \@tempdimc\@tempdima
634     \setlength\@tempdimb{\Gm@rmargin}%
635     \advance\@tempdimc-\@tempdimb
636     \ifdim\@tempdimc>\z@
637         \Gm@warning{The marginal notes overrun the paper.^^J
638         \spaces Add \the\@tempdimc\space and more to the right margin}%
639     \fi
640 \fi
641 \fi}%

```

`\Gm@adjustmp` The macro sets marginpar correction when `includemp` is set, which is used in `\Gm@process`. The variables `\Gm@wd@mp`, `\Gm@odd@mp` and `\Gm@even@mp` are set here. Note that `\Gm@even@mp` should be used only for twoside layout.

```

642 \def\Gm@adjustmp{%
643     \ifGm@includemp
644         \@tempdimb\marginparwidth
645         \advance\@tempdimb\marginparsep
646         \Gm@wd@mp\@tempdimb
647         \Gm@odd@mp\z@
648         \Gm@even@mp\z@
649         \if@twocolumn
650             \Gm@wd@mp2\@tempdimb
651             \Gm@odd@mp\@tempdimb
652             \Gm@even@mp\@tempdimb
653         \else
654             \if@reversemargin
655                 \Gm@odd@mp\@tempdimb
656             \if@mparswitch\else
657                 \Gm@even@mp\@tempdimb
658             \fi
659         \else
660             \if@mparswitch
661                 \Gm@even@mp\@tempdimb
662             \fi
663         \fi
664     \fi
665 \fi}%

```

`\Gm@adjustbody` If the horizontal dimension of *body* is specified by user, `\Gm@width` is set properly here.

```

666 \def\Gm@adjustbody{
667     \ifGm@hbody
668         \ifx\Gm@width\@undefined
669             \ifx\Gm@hscale\@undefined
670                 \Gm@defbylen{width}{\Gm@Dhscale\Gm@layoutwidth}%
671             \else
672                 \Gm@defbylen{width}{\Gm@hscale\Gm@layoutwidth}%
673             \fi
674         \fi
675         \ifx\Gm@textwidth\@undefined\else
676             \setlength\@tempdima{\Gm@textwidth}%
677             \ifGm@includemp
678                 \advance\@tempdima\Gm@wd@mp
679             \fi
680             \edef\Gm@width{\the\@tempdima}%
681         \fi
682     \fi

```



If the vertical dimension of *body* is specified by user, `\Gm@height` is set properly here.

```

683 \ifGm@vbody
684   \ifx\Gm@height\@undefined
685     \ifx\Gm@vscale\@undefined
686       \Gm@defbylen{height}{\Gm@Dvscale\Gm@layoutheight}%
687     \else
688       \Gm@defbylen{height}{\Gm@vscale\Gm@layoutheight}%
689     \fi
690   \fi
691   \ifx\Gm@lines\@undefined\else
\topskip has to be adjusted so that the formula “ $\text{textheight} = (\text{lines} - 1) \times \text{baselineskip} + \text{topskip}$ ”
to be correct even if large font sizes are specified by users. If \topskip is smaller than
\ht\strutbox, then \topskip is set to \ht\strutbox.
692     \ifdim\topskip<\ht\strutbox
693       \setlength\@tempdima{\topskip}%
694       \setlength\topskip{\ht\strutbox}%
695       \Gm@warning{noexpand\topskip was changed from \the\@tempdima\space
696         to \the\topskip}%
697     \fi
698     \setlength\@tempdima{\baselineskip}%
699     \multiply\@tempdima\Gm@lines
700     \addtolength\@tempdima{\topskip}%
701     \addtolength\@tempdima{-\baselineskip}%
702     \edef\Gm@textheight{\the\@tempdima}%
703   \fi
704   \ifx\Gm@textheight\@undefined\else
705     \setlength\@tempdima{\Gm@textheight}%
706     \ifGm@includehead
707       \addtolength\@tempdima{\headheight}%
708       \addtolength\@tempdima{\headsep}%
709     \fi
710     \ifGm@includefoot
711       \addtolength\@tempdima{\footskip}%
712     \fi
713     \edef\Gm@height{\the\@tempdima}%
714   \fi
715 \fi}%

```

`\Gm@process` The main macro processing the specified dimensions is defined.

```

716 \def\Gm@process{%
  If pass is set, the original dimensions and switches are restored and process is ended here.
717   \ifGm@pass
718     \Gm@restore@org
719   \else
720     \Gm@@process
721   \fi}%

```

The main processing macro.

```

722 \def\Gm@@process{%
723   \Gm@expandlengths
724   \Gm@adjustpaper
725   \addtolength\Gm@layoutwidth{-\Gm@bindingoffset}%
726   \Gm@adjustmp
727   \Gm@adjustbody
728   \Gm@detall{h}{width}{lmargin}{rmargin}%
729   \Gm@detall{v}{height}{tmargin}{bmargin}%

```

The real dimensions are set properly according to the result of the auto-completion calculation.

```

730   \setlength\textwidth{\Gm@width}%
731   \setlength\textheight{\Gm@height}%
732   \setlength\topmargin{\Gm@tmargin}%
733   \setlength\oddsidemargin{\Gm@lmargin}%
734   \addtolength\oddsidemargin{-1\Gm@truedimen in}%

```



If `\includemp` is set to true, `\textwidth` and `\oddsidemargin` are adjusted.

```
735 \ifGm@includemp
736   \advance\textwidth-\Gm@wd@mp
737   \advance\oddsidemargin\Gm@odd@mp
738 \fi
```

Determining `\evensidemargin`. In the twoside page layout, the right margin value `\Gm@rmargin` is used. If the marginal note width is included, `\evensidemargin` should be corrected by `\Gm@even@mp`.

```
739 \if@mparswitch
740   \setlength\evensidemargin{\Gm@rmargin}%
741   \addtolength\evensidemargin{-1\Gm@truedimen in}%
742   \ifGm@includemp
743     \advance\evensidemargin\Gm@even@mp
744   \fi
745 \else
746   \evensidemargin\oddsidemargin
747 \fi
```

The `\bindingoffset` correction for `\oddsidemargin`.

```
748 \advance\oddsidemargin\Gm@bindingoffset
749 \addtolength\topmargin{-1\Gm@truedimen in}%
```

If the head of the page is included in *total body*, `\headheight` and `\headsep` are removed from `\textheight`, otherwise from `\topmargin`.

```
750 \ifGm@includehead
751   \addtolength\textheight{-\headheight}%
752   \addtolength\textheight{-\headsep}%
753 \else
754   \addtolength\topmargin{-\headheight}%
755   \addtolength\topmargin{-\headsep}%
756 \fi
```

If the foot of the page is included in *total body*, `\footskip` is removed from `\textheight`.

```
757 \ifGm@includefoot
758   \addtolength\textheight{-\footskip}%
759 \fi
```

If `\heightrounded` is set, `\textheight` is rounded.

```
760 \ifGm@heightrounded
761   \setlength\@tempdima{\textheight}%
762   \addtolength\@tempdima{-\topskip}%
763   \@tempcnta\@tempdima
764   \@tempcntb\baselineskip
765   \divide\@tempcnta\@tempcntb
766   \setlength\@tempdimb{\baselineskip}%
767   \multiply\@tempdimb\@tempcnta
768   \advance\@tempdima-\@tempdimb
769   \multiply\@tempdima\tw@
770   \ifdim\@tempdima>\baselineskip
771     \addtolength\@tempdimb{\baselineskip}%
772   \fi
773   \addtolength\@tempdimb{\topskip}%
774   \textheight\@tempdimb
775 \fi
```

The paper width is set back by adding `\Gm@bindingoffset`.

```
776 \advance\oddsidemargin\Gm@layouthoffset%
777 \advance\evensidemargin\Gm@layouthoffset%
778 \advance\topmargin\Gm@layoutvoffset%
779 \addtolength\Gm@layoutwidth{\Gm@bindingoffset}%
780 }% end of \Gm@@process
```

`\Gm@detectdriver` The macro checks the typeset environment and changes the driver option if necessary. To make the engine detection more robust, the macro is rewritten with packages `ifpdf`, `ifvtex` and `ifxetex`.

```
781 \def\Gm@detectdriver{%
```

If the driver option is not specified explicitly, then driver auto-detection works.

```

782 \ifx\Gm@driver\@empty
783   \typeout{*geometry* driver: auto-detecting}%
   \ifpdf is defined in ifpdf package in ‘oberdiek’ bundle.
784   \ifpdf
785     \Gm@setdriver{pdftex}%
786   \else
787     \Gm@setdriver{dvips}%
788   \fi

```

\ifvtex is defined in ifvtex package in ‘oberdiek’ bundle.

```

789 \ifvtex
790   \Gm@setdriver{vtex}%
791 \fi

```

\ifxetex is defined in ifxetex package written by Will Robertson.

```

792 \ifxetex
793   \Gm@setdriver{xetex}
794 \fi

```

When the driver option is set by the user, check if it is valid or not.

```

795 \else
796   \ifx\Gm@driver\Gm@xetex %%
797     \ifxetex\else
798       \Gm@warning{Wrong driver setting: ‘xetex’; trying ‘pdftex’ driver}%
799       \Gm@setdriver{pdftex}
800     \fi
801   \fi
802   \ifx\Gm@driver\Gm@vtex
803     \ifvtex\else
804       \Gm@warning{Wrong driver setting: ‘vtex’; trying ‘dvips’ driver}%
805       \Gm@setdriver{dvips}%
806     \fi
807   \fi
808 \fi
809 \ifx\Gm@driver\relax
810   \typeout{*geometry* detected driver: <none>}%
811 \else
812   \typeout{*geometry* detected driver: \Gm@driver}%
813 \fi}%

```

**\Gm@showparams** Prints the resulted parameters and dimensions to STDOUT if verbose is true. \Gm@width and \Gm@height are expanded to get the real size.

```

814 \def\Gm@showparams#1{%
815   \ifGm@verbose\expandafter\typeout\else\expandafter\wlog\fi
816   {\Gm@logcontent{#1}}}%
817 \def\Gm@showdim#1{* \string#1=\the#1^^J}%
818 \def\Gm@showbool#1{\@nameuse{ifGm#1}#1\space\fi}%

```

**\Gm@logcontent** The content of geometry parameters and native dimensions for the page layout.

```

819 \def\Gm@logcontent#1{%
820   *geometry* verbose mode - [ #1 ] result:^^J%
821   \ifGm@pass * pass: disregarded the geometry package!^^J%
822   \else
823     * driver: \if\Gm@driver<none>\else\Gm@driver\fi^^J%
824     * paper: \ifx\Gm@paper\@undefined<default>\else\Gm@paper\fi^^J%
825     * layout: \ifGm@layout<custom>\else<same size as paper>\fi^^J%
826     \ifGm@layout
827       * layout(width,height): (\the\Gm@layoutwidth,\the\Gm@layoutheight)^^J%
828     \fi
829     * layoutoffset:(h,v)=(\the\Gm@layoutoffset,\the\Gm@layoutvoffset)^^J%
830     \@ifundefined{Gm@lines}{* lines: \Gm@lines^^J}%
831     \@ifundefined{Gm@hmarginratio}{* hratio: \Gm@hmarginratio^^J}%
832     \@ifundefined{Gm@vmarginratio}{* vratio: \Gm@vmarginratio^^J}%
833     \ifdim\Gm@bindingoffset=\z@\else

```

```

834 * bindingoffset: \the\Gm@bindingoffset^^J\fi
835 * modes: %
836 \Gm@showbool{landscape}%
837 \Gm@showbool{includehead}%
838 \Gm@showbool{includefoot}%
839 \Gm@showbool{includemp}%
840 \if@twoside twoside\space\fi%
841 \if@mparswitch\else\if@twoside asymmetric\space\fi\fi%
842 \Gm@showbool{heightrounded}%
843 \ifx\Gm@truedimen\@empty\else truedimen\space\fi%
844 \Gm@showbool{showframe}%
845 \Gm@showbool{showcrop}%
846 ^^J%
847 * h-part:(L,W,R)=(\Gm@lmargin, \Gm@width, \Gm@rmargin)^^J%
848 * v-part:(T,H,B)=(\Gm@tmargin, \Gm@height, \Gm@bmargin)^^J%
849 \fi
850 \Gm@showdim{\paperwidth}%
851 \Gm@showdim{\paperheight}%
852 \Gm@showdim{\textwidth}%
853 \Gm@showdim{\textheight}%
854 \Gm@showdim{\oddsidemargin}%
855 \Gm@showdim{\evensidemargin}%
856 \Gm@showdim{\topmargin}%
857 \Gm@showdim{\headheight}%
858 \Gm@showdim{\headsep}%
859 \Gm@showdim{\topskip}%
860 \Gm@showdim{\footskip}%
861 \Gm@showdim{\marginparwidth}%
862 \Gm@showdim{\marginparsep}%
863 \Gm@showdim{\columnsep}%
864 * \string\skip\string\footins=\the\skip\footins^^J%
865 \Gm@showdim{\hoffset}%
866 \Gm@showdim{\voffset}%
867 \Gm@showdim{\mag}%
868 * \string\@twocolumn\if@twocolumn true\else false\fi^^J%
869 * \string\@twoside\if@twoside true\else false\fi^^J%
870 * \string\@mparswitch\if@mparswitch true\else false\fi^^J%
871 * \string\@reversemargin\if@reversemargin true\else false\fi^^J%
872 * (1in=72.27pt=25.4mm, 1cm=28.453pt)^^J}%

```

Macros for the page frames and cropmarks.

```

873 \def\Gm@cropmark(#1,#2,#3,#4){%
874 \begin{picture}(0,0)
875 \setlength\unitlength{1truemm}%
876 \linethickness{0.25pt}%
877 \put(#3,0){\line(#1,0){17}}%
878 \put(0,#4){\line(0,#2){17}}%
879 \end{picture}}%
880 \providecommand*{\vb@xt@{\vbox to}}%
881 \def\Gm@vrule{\vrule width 0.2pt height\textheight depth\z@}%
882 \def\Gm@hrule{\hrule height 0.2pt depth\z@ width\textwidth}%
883 \def\Gm@hruled{\hrule height\z@ depth0.2pt width\textwidth}%
884 \newcommand*{\Gm@vrules@mpi}{%
885 \hb@xt@{\@tempdima}{\llap{\Gm@vrule}\ignorespaces
886 \hskip \textwidth\Gm@vrule\hskip \marginparsep
887 \llap{\Gm@vrule}\hfil\Gm@vrule}}%
888 \newcommand*{\Gm@vrules@mpii}{%
889 \hb@xt@{\@tempdima}{\hskip-\marginparwidth\hskip-\marginparsep
890 \llap{\Gm@vrule}\ignorespaces
891 \hskip \marginparwidth\rlap{\Gm@vrule}\hskip \marginparsep
892 \llap{\Gm@vrule}\hskip\textwidth\rlap{\Gm@vrule}\hss}}%
893 \newcommand*{\Gm@pageframes}{%
894 \vb@xt@\z@{%
895 \ifGm@showcrop
896 \vb@xt@\z@{\vskip-1\Gm@truedimen in\vskip\Gm@layoutvoffset%

```

```

897 \hb@xt@\z@\hskip-1\Gm@truedimen in\hskip\Gm@layouthoffset%
898 \vb@xt@\Gm@layoutheight{%
899 \let\protect\relax
900 \hb@xt@\Gm@layoutwidth{\Gm@cropmark(-1,1,-3,3)\hfil\Gm@cropmark(1,1,3,3)}%
901 \vfil
902 \hb@xt@\Gm@layoutwidth{\Gm@cropmark(-1,-1,-3,-3)\hfil\Gm@cropmark(1,-1,3,-3)}%
903 \hss}%
904 \vss}%
905 \fi%
906 \ifGm@showframe
907 \iftwoside
908 \ifodd\count\z@
909 \let\@themargin\oddsidemargin
910 \else
911 \let\@themargin\evensidemargin
912 \fi
913 \fi
914 \moveright\@themargin%
915 \vb@xt@\z@{%
916 \vskip\topmargin\vb@xt@\z@\vss\Gm@hrule}%
917 \vskip\headheight\vb@xt@\z@\vss\Gm@hruled}%
918 \vskip\headsep\vb@xt@\z@\vss\Gm@hrule}%
919 \@tempdima\textwidth
920 \advance\@tempdima by \marginparsep
921 \advance\@tempdima by \marginparwidth
922 \if@mparswitch
923 \ifodd\count\z@
924 \Gm@vrules@mpi
925 \else
926 \Gm@vrules@mpii
927 \fi
928 \else
929 \Gm@vrules@mpi
930 \fi
931 \vb@xt@\z@\vss\Gm@hrule}%
932 \vskip\footskip\vb@xt@\z@\vss\Gm@hruled}%
933 \vss}%
934 \fi%
935 }%

```

**\ProcessOptionsKV** This macro can process class and package options using ‘key=value’ scheme. Only class options are processed with an optional argument ‘c’, package options with ‘p’, and both of them by default.

```

936 \def\ProcessOptionsKV{\ifnextchar[%]
937 {\@ProcessOptionsKV}{\@ProcessOptionsKV[]}}%
938 \def\@ProcessOptionsKV[#1]#2{%
939 \let\@tempa\@empty
940 \@tempcnta\z@
941 \if#1p\@tempcnta\@one\else\if#1c\@tempcnta\tw\fi\fi
942 \ifodd\@tempcnta
943 \edef\@tempa{\@optionlist{\@currname.\@current}}%
944 \else
945 \@for\CurrentOption:=\@classoptionslist\do{%
946 \@ifundefined{KV@#2\CurrentOption}%
947 {\edef\@tempa{\@tempa,\CurrentOption,}}}%
948 \ifnum\@tempcnta=\z@
949 \edef\@tempa{\@tempa,\@optionlist{\@currname.\@current}}%
950 \fi
951 \fi
952 \edef\@tempa{\noexpand\setkeys{#2}{\@tempa}}%
953 \@tempa
954 \AtEndOfPackage{\let\@unprocessedoptions\relax}}%
955 \def\Gm@setkeys{\setkeys{Gm}}%

```

**\Gm@processconf** \ExecuteOptions is replaced with \Gm@setkey to make it possible to deal with ‘key=value’ as its argument.

```

956 \def\Gm@processconfig{%
957   \let\Gm@origExecuteOptions\ExecuteOptions
958   \let\ExecuteOptions\Gm@setkeys
959   \InputIfFileExists{geometry.cfg}{-}{-}
960   \let\ExecuteOptions\Gm@origExecuteOptions}%

```

The original page layout before loading geometry is saved here. \Gm@restore@org is defined here for reset option.

```

961 \Gm@save
962 \edef\Gm@restore@org{\Gm@restore}%
963 \Gm@initall

```

Processing config file.

```
964 \Gm@processconfig
```

The optional arguments to \documentclass are processed here.

```
965 \ProcessOptionsKV[c]{Gm}%
```

Paper dimensions given by class default are stored.

```
966 \Gm@setdefaultpaper
```

The optional arguments to \usepackage are processed here.

```
967 \ProcessOptionsKV[p]{Gm}%
```

Actual settings and calculation for layout dimensions are processed.

```
968 \Gm@process
```

\AtBeginDocument The processes for verbose, showframe and drivers are added to \AtBeginDocument. \Gm@restore@org is redefined here with the paper size specified in the preamble for \newgeometry to use it. This should be done before magnifying the paper size with \mag because the layout calculation would be affected by changing the paper size.

```

969 \AtBeginDocument{%
970   \Gm@savelength{paperwidth}%
971   \Gm@savelength{paperheight}%
972   \edef\Gm@restore@org{\Gm@restore}%

```

The original paper size is used if resetpaper.

```

973   \ifGm@resetpaper
974     \edef\Gm@pw{\Gm@orgpw}%
975     \edef\Gm@ph{\Gm@orgph}%
976   \else
977     \edef\Gm@pw{\the\paperwidth}%
978     \edef\Gm@ph{\the\paperheight}%
979   \fi

```

If pass is not set, the paper size is multiplied according to the specified mag.

```

980   \ifGm@pass\else
981     \ifnum\mag=\@m\else
982       \Gm@magtooffset
983       \divide\paperwidth\@m
984       \multiply\paperwidth\the\mag
985       \divide\paperheight\@m
986       \multiply\paperheight\the\mag
987     \fi
988   \fi

```

Checking the driver options.

```
989 \Gm@detectdriver
```

If xetex and \pdfpagewidth is defined, \pdfpagewidth and \pdfpageheight would be set.

```

990 \ifx\Gm@driver\Gm@xetex
991   \ifundefined{pdfpagewidth}{-}{-}%
992   \setlength\pdfpagewidth{\Gm@pw}%
993   \setlength\pdfpageheight{\Gm@ph}%
994   \ifnum\mag=\@m\else
995     \ifx\Gm@truedimen\Gm@true
996       \setlength\paperwidth{\Gm@pw}%
997       \setlength\paperheight{\Gm@ph}%

```

```

998     \fi
999     \fi
1000  \fi

```

If pdf<sub>tex</sub> is set to true, pdf-commands are set properly. To avoid pdf<sub>tex</sub> magnification problem, \pdfhorigin and \pdfvorigin are adjusted for \mag.

```

1001  \ifx\Gm@driver\Gm@pdftex
1002    \ifundefined{pdfpagewidth}{\%
1003      \setlength{pdfpagewidth}{\Gm@pw}%
1004      \setlength{pdfpageheight}{\Gm@ph}}%
1005    \ifnum\mag=\@m\else
1006      \@tempdima=\mag sp%
1007      \ifundefined{pdfhorigin}{\%
1008        \divide\pdfhorigin\@tempdima
1009        \multiply\pdfhorigin\@m
1010        \divide\pdfvorigin\@tempdima
1011        \multiply\pdfvorigin\@m}%
1012      \ifx\Gm@truedimen\Gm@true
1013        \setlength{paperwidth}{\Gm@pw}%
1014        \setlength{paperheight}{\Gm@ph}%
1015      \fi
1016    \fi
1017  \fi

```

With V<sub>T</sub><sub>E</sub>X environment, V<sub>T</sub><sub>E</sub>X variables are set here.

```

1018  \ifx\Gm@driver\Gm@vTEX
1019    \ifundefined{mediawidth}{\%
1020      \mediawidth=\paperwidth
1021      \mediaheight=\paperheight}%
1022    \ifvTEXdvi
1023      \AtBeginDvi{\special{papersize=\the\paperwidth,\the\paperheight}}%
1024    \fi
1025  \fi

```

If dvips or dvipdfm is specified, paper size is embedded in dvi file with \special. For dvips, a landscape correction is added because a landscape document converted by dvips is upside-down in PostScript viewers.

```

1026  \ifx\Gm@driver\Gm@dvips
1027    \AtBeginDvi{\special{papersize=\the\paperwidth,\the\paperheight}}%
1028    \ifx\Gm@driver\Gm@dvips\ifGm@landscape
1029      \AtBeginDvi{\special{! /landplus90 true store}}%
1030    \fi\fi

```

If dvipdfm is specified and atbegshi package in ‘oberdiek’ bundle is loaded, \AtBeginShipoutFirst is used instead of \AtBeginDvi for compatibility with hyperref and dvipdfm program.

```

1031  \else\ifx\Gm@driver\Gm@dvipdfm
1032    \ifcase\ifx\AtBeginShipoutFirst\relax\@ne\else
1033      \ifx\AtBeginShipoutFirst\@undefined\@ne\else\z@\fi\fi
1034      \AtBeginShipoutFirst{\special{papersize=\the\paperwidth,\the\paperheight}}%
1035    \or
1036      \AtBeginDvi{\special{papersize=\the\paperwidth,\the\paperheight}}%
1037    \fi
1038  \fi\fi

```

Page frames are shipped out when showframe=true, cropmarks for showcrop=true on each page. The atbegshi package is used for overloading \shipout.

```

1039  \@tempswafalse
1040  \ifGm@showframe
1041    \@tempswatruetrue
1042  \else\ifGm@showcrop
1043    \@tempswatruetrue
1044  \fi\fi
1045  \if@tempswa
1046    \RequirePackage{atbegshi}%
1047    \AtBeginShipout{\setbox\AtBeginShipoutBox=\vbox{
1048      \baselineskip\z@skip\lineskip\z@skip\lineskiplimit\z@
1049      \Gm@pageframes\box\AtBeginShipoutBox}}%

```

```

1050 \fi
    The layout dimensions for \restoregeometry are saved at the end of the \AtBeginDocument.
1051 \Gm@save
1052 \edef\Gm@restore@pkg{\Gm@restore}%
    The package checks whether or not the marginpars overrun the page, if verbose and unless pass.
1053 \ifGm@verbose\ifGm@pass\else\Gm@checkmp\fi\fi
    \Gm@showparams puts the resulting parameters and dimensions into the log file. With verbose, they
    are shown on the terminal as well.
1054 \Gm@showparams{preamble}%
    The following lines free the memories no longer needed.
1055 \let\Gm@pw\relax
1056 \let\Gm@ph\relax
1057 }% end of \AtBeginDocument

```

**\geometry** The macro \geometry can be called multiple times in the preamble (before \begin{document}).

```

1058 \newcommand{\geometry}[1]{%
1059 \Gm@clean
1060 \setkeys{Gm}{#1}%
1061 \Gm@process}%
1062 \@onlypreamble\geometry

```

**\Gm@changelayout** The macro, which can be called from \newgeometry, \restoregeometry and \loadgeometry, changes the layout in the middle of the document.

```

1063 \DeclareRobustCommand\Gm@changelayout{%
1064 \setlength{\@colht}{\textheight}
1065 \setlength{\@colroom}{\textheight}%
1066 \setlength{\vsize}{\textheight}
1067 \setlength{\columnwidth}{\textwidth}%
1068 \if@twocolumn%
1069 \advance\columnwidth-\columnsep
1070 \divide\columnwidth\tw@%
1071 \@firstcolumntrue%
1072 \fi%
1073 \setlength{\hsize}{\columnwidth}%
1074 \setlength{\linewidth}{\hsize}}%

```

**\newgeometry** The macro \newgeometry, which changes the layout, can be used only in the document. It would reset the options specified in the preamble except for paper size options and \mag.

```

1075 \newcommand{\newgeometry}[1]{%
1076 \clearpage
1077 \Gm@restore@org
1078 \Gm@initnewgm
1079 \Gm@newgmtrue
1080 \setkeys{Gm}{#1}%
1081 \Gm@newgmfalse
1082 \Gm@process
1083 \ifnum\mag=\@m\else\Gm@magtooffset\fi
1084 \Gm@changelayout
1085 \Gm@showparams{newgeometry}}%

```

**\restoregeometry** The macro restores the resulting layout specified in the preamble, namely the first-page layout right after \begin{document}.

```

1086 \newcommand{\restoregeometry}{%
1087 \clearpage
1088 \Gm@restore@pkg
1089 \Gm@changelayout}%

```

**\savegeometry** The macro saves the layout with the name specified with the argument. The saved layout can be loaded with \loadgeometry{<name>}.

```

1090 \newcommand*{\savegeometry}[1]{%
1091 \Gm@save
1092 \expandafter\edef\csname Gm@restore@@#1\endcsname{\Gm@restore}}%

```

`\loadgeometry` The macro loads the layout saved with `\savegeometry{<name>}`. If the name is not found, the macro would warn it and do nothing for the layout.

```

1093 \newcommand*{\loadgeometry}[1]{%
1094   \clearpage
1095   \@ifundefined{Gm@restore@@#1}{%
1096     \PackageError{geometry}{%
1097       \string\loadgeometry : name ‘#1’ undefined}{%
1098       The name ‘#1’ should be predefined with \string\savegeometry}%
1099   }{\@nameuse{Gm@restore@@#1}%
1100   \Gm@changelayout}}%
1101 \end{package}

```

## 12 Config file

In the configuration file `geometry.cfg`, one can use `\ExecuteOptions` to set the site or user default settings.

```

1102 <*config>
1103 %<<SAVE_INTACT
1104
1105 % Uncomment and edit the line below to set default options.
1106 %\ExecuteOptions{a4paper}
1107
1108 %SAVE_INTACT
1109 </config>

```

## 13 Sample file

Here is a sample document for the geometry package.

```

1110 <*samples>
1111 %<<SAVE_INTACT
1112 \documentclass[12pt]{article}% uses letterpaper by default
1113 \documentclass[12pt,a4paper]{article}% for A4 paper
1114 %-----
1115 % Edit and uncomment one of the settings below
1116 %-----
1117 % \usepackage{geometry}
1118 % \usepackage[centering]{geometry}
1119 % \usepackage[width=10cm,vscale=.7]{geometry}
1120 % \usepackage[margin=1cm, papersize={12cm,19cm}, resetpaper]{geometry}
1121 % \usepackage[margin=1cm,includeheadfoot]{geometry}
1122 % \usepackage[margin=1cm,includeheadfoot,includemp]{geometry}
1123 % \usepackage[margin=1cm,bindingoffset=1cm,twoside]{geometry}
1124 % \usepackage[hmarginratio=2:1, vmargin=2cm]{geometry}
1125 % \usepackage[hscale=0.5,twoside]{geometry}
1126 % \usepackage[hscale=0.5,asymmetric]{geometry}
1127 % \usepackage[hscale=0.5,heightrounded]{geometry}
1128 % \usepackage[left=1cm,right=4cm,top=2cm,includefoot]{geometry}
1129 % \usepackage[lines=20,left=2cm,right=6cm,top=2cm,twoside]{geometry}
1130 % \usepackage[width=15cm, marginparwidth=3cm, includemp]{geometry}
1131 % \usepackage[hdivide={1cm,,2cm}, vdivide={3cm,8in,,}, nohead]{geometry}
1132 % \usepackage[headsep=20pt, head=40pt,foot=20pt,includeheadfoot]{geometry}
1133 % \usepackage[text={6in,8in}, top=2cm, left=2cm]{geometry}
1134 % \usepackage[centering,includemp,twoside,landscape]{geometry}
1135 % \usepackage[mag=1414,margin=2cm]{geometry}
1136 % \usepackage[mag=1414,margin=2truecm,truedimen]{geometry}
1137 % \usepackage[a5paper, landscape, twocolumn, twoside,
1138 %   left=2cm, hmarginratio=2:1, includemp, marginparwidth=43pt,
1139 %   bottom=1cm, foot=.7cm, includefoot, textheight=11cm, heightrounded,
1140 %   columnsep=1cm,verbose]{geometry}
1141 %-----
1142 % No need to change below
1143 %-----

```



```

1144 \geometry{verbose,showframe}% the options appended.
1145 \usepackage{lipsum}% for dummy text of 150 paragraphs
1146 \newcommand\mynote{\marginpar[\raggedright
1147 A sample margin note in the left side.]}%
1148 {\raggedright A sample margin note.}}%
1149 \newcommand\myfootnote{\footnote{This is a sample footnote text.}}
1150 \begin{document}
1151 \lipsum[1-2]\mynote\lipsum[3-4]\mynote
1152 \lipsum[5-11]\mynote\lipsum[12]\myfootnote
1153 \lipsum[13-22]\mynote\lipsum[23-32]
1154 \end{document}
1155 %SAVE_INTACT
1156 </samples>
1157 %\tradfin

```