


# CS 305 Lab Tutorial

## Lab 14 Layer3 Switch

Dept. Computer Science and Engineering  
Southern University of Science and Technology


# Ethernet switch

- **link-layer device: takes an *active* role**
  - store, forward Ethernet frames
  - examine incoming frame's MAC address, **selectively** forward frame to one-or-more outgoing links when frame is to be forwarded on segment, uses CSMA/CD to access segment
- ***transparent***
  - hosts are unaware of presence of switches
- ***plug-and-play, self-learning***
  - switches do not need to be configured



switch with six interfaces  
(1,2,3,4,5,6)

# S5110 (Gigabit Ethernet switch)





1. 10/100/1000M Base-T electric interface
2. 100/1000 Base-X SFP optical interface
3. Console interface
4. Port status indicator
5. Power status indicator

# Connect with switch by console (1)

To configure the switch by PC

1. Connect the **console** port of switch with **com** port of PC
2. Invoke the SecureCRT Portable on PC to communicate with CLI of switch



Type : Serial

Port : COMx

Baud rate : 9600

Data-width: 8

Parity check: None

Stop bit: 1


Flow control : NO flow control

# Connect with switch by console (2)



# CLI (Command Line Interface)

- TEXT style instruction interaction interface between user and device.
  - Users input text commands, submit devices by inputting return key to execute corresponding commands for configure and manage the devices.
  - confirm the configuration results by viewing the output information.




```
*****
* Copyright (c) 2004-2014 Hangzhou H3C Tech. Co., Ltd. All rights reserved. *
* Without the owner's prior written consent,                               *
* no decompiling or reverse-engineering shall be allowed.                 *
*****

Line aux0 is available.

Press ENTER to get started.
<H3C>%Jun 23 09:52:58:243 2014 H3C SHELL/5/SHELL_LOGIN: TTY logged in from aux0.

<H3C>
<H3C>
<H3C>
<H3C>_
```

# Views and Command



Tips: 1. /ctrl+c could be used to return to exit current view.

2.tab key and '?' following the command will help you a lot.

# Views in CLI

- **USER** : After the user logs on to the device, he enters **the user view** directly. The prompt displayed on the screen is <Device Name>.
- **SYSTEM** : The **system view** can be shift from the user view, where the prompt displayed on the screen is: [device name].
  - The system view can **configure** the operation parameters and some functions of the equipment, such as configuration welcome information, shortcut keys, etc.
- **FUNCTION**: Input specific commands in the system view, you can enter the **corresponding function view**
  - complete the configuration of the corresponding functions, such as: enter the interface view to configure interface parameters, enter the VLAN view to add ports to the VLAN, and so on
- **Tips**: using “undo” to cancel the finished setting command.



# Commands and Keys

- Setting
  - Restore factory default, reboot
  - In different views (system, interface, sub-functions)
  - To set device, interface, ip address, service, AAA etc.
- Display
  - Device, interface, dhcp, ip routing-table etc.
  - The keys useful for displaying the output in pages.

keys	function
space key	continue to display the message of next screen
enter key	continue to display the message of next line
<Ctrl + C>	stop display,return to the command line state
<PageUp>	display last page
<PageDown>	display next page

# Reminds on error inputs

表1-11 命令行常见错误信息表

英文错误信息	错误原因
% Unrecognized command found at '^' position.	命令无法解析，符号“^”指示位置出错
% Incomplete command found at '^' position.	符号“^”指示位置的参数输入不完整
% Ambiguous command found at '^' position.	符号“^”指示位置的关键字不明确，存在二义性
% Too many parameters.	输入参数太多
% Wrong parameter found at '^' position.	在符号“^”指示位置的参数错误

Tips: “ display history-command “ to display 10 history commands by default.

# Interface - work mode

```
[H3C]display interface brief
The brief information of interface(s) under route mode:
Link: ADM - administratively down; Stby - standby
Protocol: (s) - spoofing
Interface      Link Protocol Main IP      Description
NULL0         UP      UP(s)    --

The brief information of interface(s) under bridge mode:
Link: ADM - administratively down; Stby - standby
Speed or Duplex: (a)/A - auto; H - half; F - full
Type: A - access; T - trunk; H - hybrid
Interface      Link Speed Duplex Type PVID Description
GE1/0/1        DOWN auto  A     A     1
GE1/0/2        DOWN auto  A     A     1
GE1/0/3        DOWN auto  A     A     1
GE1/0/4        DOWN auto  A     A     1
GE1/0/5        DOWN auto  A     A     1
GE1/0/6        DOWN auto  A     A     1
GE1/0/7        DOWN auto  A     A     1
GE1/0/8        DOWN auto  A     A     1
GE1/0/9        DOWN auto  A     A     1
GE1/0/10       DOWN auto  A     A     1
GE1/0/11       DOWN auto  A     A     1
GE1/0/12       DOWN auto  A     A     1
GE1/0/13       DOWN auto  A     A     1
GE1/0/14       DOWN auto  A     A     1
GE1/0/15       DOWN auto  A     A     1
GE1/0/16       DOWN auto  A     A     1
GE1/0/17       DOWN auto  A     A     1
GE1/0/18       DOWN auto  A     A     1
GE1/0/19       DOWN auto  A     A     1
GE1/0/20       DOWN auto  A     A     1
GE1/0/21       DOWN auto  A     A     1
GE1/0/22       DOWN auto  A     A     1
GE1/0/23       DOWN auto  A     A     1
GE1/0/24       DOWN auto  A     A     1
GE1/0/25       DOWN auto  A     A     1
GE1/0/26       DOWN auto  A     A     1
GE1/0/27       DOWN auto  A     A     1
GE1/0/28       DOWN auto  A     A     1

[H3C]
```

- Use “**display interface brief**” to show the brief info of all the interfaces.
- For S5110, all the gigabit-ethernet interface works on the **bridge** mode.
- All the gigabit gigabit-ethernet interface **access** into the **VLAN 1** by default.
- ‘**port link-type**’ is configurable :
  - access
  - trunk
- Tips: all the interfaces of **switch** work on **bridge** mode, while the interface of **router** could work on **bridge** or **route** mode.

# MAC-address-table(1)

- For S5110, the mac-address could be learned as dynamic, or configured as static or dynamic.
  - A **static mac-address item** gets higher priority than a dynamic item
  - A **dynamic mac-address item** has a default aging time which is configurable, while a static item is no-aged.

```
[H3C]display mac-address
MAC ADDR      VLAN ID  STATE      PORT INDEX      AGING TIME(s)
309c-236e-8f3b 102      Learned    GigabitEthernet1/0/2  AGING
309c-236e-8f81 102      Learned    GigabitEthernet1/0/23 AGING

--- 2 mac address(es) found ---
```

```
[H3C]display mac-address aging-time
Mac address aging time: 300s
```

```
[H3C]display mac-address
MAC ADDR      VLAN ID  STATE      PORT INDEX      AGING TIME(s)
309c-236e-8f3b 102      Learned    GigabitEthernet1/0/2  AGING
309c-236e-8f81 102      Learned    GigabitEthernet1/0/23 AGING

--- 2 mac address(es) found ---

[H3C]mac-address static 309c-236e-8f3b interface gigabitethernet1/0/2 vlan 102
[H3C]display mac-address
MAC ADDR      VLAN ID  STATE      PORT INDEX      AGING TIME(s)
309c-236e-8f3b 102      Config static GigabitEthernet1/0/2  NOAGED
309c-236e-8f81 102      Learned    GigabitEthernet1/0/23 AGING

--- 2 mac address(es) found ---
```

# MAC-address-table(2)

- The '**blackhole**' mac address means while the packets related to the blackhole, they will be dropped, switch will not forward the packets.
- The 'blackhole' mac address is marked on the mac-address table.
- using command "mac-address blackhole mac-address-x vlan vlan\_id" to configure the mac-address-x as a blackhole mac address.

```
[H3C]display mac-address
MAC ADDR          VLAN ID  STATE      PORT INDEX      AGING TIME(s)
309c-236e-8f3b    102      Learned    GigabitEthernet1/0/2  AGING
309c-236e-8f81    102      Learned    GigabitEthernet1/0/23  AGING

--- 2 mac address(es) found ---

[H3C]mac-address blackhole 309c-236e-8f3b vlan 102
[H3C]display mac-address
MAC ADDR          VLAN ID  STATE      PORT INDEX      AGING TIME(s)
309c-236e-8f3b    102      Blackhole   N/A              NOAGED
309c-236e-8f81    102      Learned    GigabitEthernet1/0/23  AGING

--- 2 mac address(es) found ---
```

'ping' a PC whose MAC address is marked as 'blackhole' on a connected switch to test whether it is reachable or not.

# Isolate Port Group

- The interfaces which belong to an **isolate group** can't reach each other, but can communicate with the interfaces which does not belong to the isolate group.

```
[H3C]display port-isolate group
Port-isolate group information:
Uplink port support: NO
Group ID: 1
Group members:
  No ports.

[H3C]inter
[H3C]interface giga
[H3C]interface GigabitEthernet 1/0/2
[H3C-GigabitEthernet1/0/2]port-isolate enable
[H3C-GigabitEthernet1/0/2]quit
[H3C]interface giga
[H3C]interface GigabitEthernet 1/0/23
[H3C-GigabitEthernet1/0/23]port-isolate enable
[H3C-GigabitEthernet1/0/23]quit
[H3C]display port-isolate group
Port-isolate group information:
Uplink port support: NO
Group ID: 1
Group members:
  GigabitEthernet1/0/2      GigabitEthernet1/0/23

[H3C]
```

- Two steps to add an interface into isolate port group:
  - step1: using “interface xxx” to enter interface function configuration mode.
  - step2: using command “port-isolate enable” to add this interface into isolate port group

# Practice 14.1

1. Build a network: connect PCa and PCb with a Layer 3 Switch / Router, set PCa to be in the same network with PCb.
2. On PCa , use “ping” to test whether PCb is reachable.
3. Use at least two ways to make PCa un-reachable from PCb without changing the connections on them.
4. After finishing step1~3, using “display mac-address” to find the mac-address table of Layer 3 Switch/Router:
  - 1) How many items are there on the switch mac-address table?  
Are they static or dynamic?
  - 2) For every item, does the mac-address belong to the connected PC or the connected interface of Layer 3 Switch / Router?

# VLAN

- A **Virtual LAN (VLAN)** is any broadcast domain that is partitioned and isolated in a computer network at the data link layer (OSI layer 2).
- Use command “vlan vlan\_id” to create or configure a VLAN.

```
[H3C]display vlan
Total 1 VLAN exist(s).
The following VLANs exist:
  1(default),
[H3C]display vlan 1
VLAN ID: 1
VLAN Type: static
Route Interface: not configured
Description: VLAN 0001
Name: VLAN 0001
Tagged   Ports: none
Untagged Ports:
  GigabitEthernet1/0/1    GigabitEthernet1/0/2    GigabitEthernet1/0/3
  GigabitEthernet1/0/4    GigabitEthernet1/0/5    GigabitEthernet1/0/6
  GigabitEthernet1/0/7    GigabitEthernet1/0/8    GigabitEthernet1/0/9
  GigabitEthernet1/0/10   GigabitEthernet1/0/11   GigabitEthernet1/0/12
  GigabitEthernet1/0/13   GigabitEthernet1/0/14   GigabitEthernet1/0/15
  GigabitEthernet1/0/16   GigabitEthernet1/0/17   GigabitEthernet1/0/18
  GigabitEthernet1/0/19   GigabitEthernet1/0/20   GigabitEthernet1/0/21
  GigabitEthernet1/0/22   GigabitEthernet1/0/23   GigabitEthernet1/0/24
  GigabitEthernet1/0/25   GigabitEthernet1/0/26   GigabitEthernet1/0/27
  GigabitEthernet1/0/28
```



# Link-type (access to VLAN)

```
[H3C-GigabitEthernet1/0/1]display this
#
interface GigabitEthernet1/0/1
#
return
[H3C-GigabitEthernet1/0/1]port link-type access
[H3C-GigabitEthernet1/0/1]port access vlan 101
[H3C-GigabitEthernet1/0/1]display this
#
interface GigabitEthernet1/0/1
port access vlan 101
#
return
[H3C-GigabitEthernet1/0/1]
```

- If the 'port link-type' is access, it means the interface can only belong to one VLAN.

## NOTES:

1. VLAN 101 is not the default VLAN on Layer Switch / Router.
2. VLAN should be created before being accessed by interfaces.

```
[H3C]display vlan
Total 2 VLAN exist(s).
The following VLANs exist:
1(default), 101,
[H3C]display vlan 1
VLAN ID: 1
VLAN Type: static
Route Interface: not configured
Description: VLAN 0001
Name: VLAN 0001
Tagged Ports: none
Untagged Ports:
GigabitEthernet1/0/2    GigabitEthernet1/0/3    GigabitEthernet1/0/4
GigabitEthernet1/0/5    GigabitEthernet1/0/6    GigabitEthernet1/0/7
GigabitEthernet1/0/8    GigabitEthernet1/0/9    GigabitEthernet1/0/10
GigabitEthernet1/0/11   GigabitEthernet1/0/12   GigabitEthernet1/0/13
GigabitEthernet1/0/14   GigabitEthernet1/0/15   GigabitEthernet1/0/16
GigabitEthernet1/0/17   GigabitEthernet1/0/18   GigabitEthernet1/0/19
GigabitEthernet1/0/20   GigabitEthernet1/0/21   GigabitEthernet1/0/22
GigabitEthernet1/0/23   GigabitEthernet1/0/24   GigabitEthernet1/0/25
GigabitEthernet1/0/26   GigabitEthernet1/0/27   GigabitEthernet1/0/28
```

```
[H3C]display
[H3C]display vlan 101
VLAN ID: 101
VLAN Type: static
Route Interface: not configured
Description: VLAN 0101
Name: VLAN 0101
Tagged Ports: none
Untagged Ports:
GigabitEthernet1/0/1
```

[H3C]

# Link-type (trunk to VLAN)

```
[H3C-GigabitEthernet1/0/1]undo port link-type
[H3C-GigabitEthernet1/0/1]undo port access vlan
[H3C-GigabitEthernet1/0/1]port link-type trunk
[H3C-GigabitEthernet1/0/1]port trunk permit vlan 101
Please wait... Done.
[H3C-GigabitEthernet1/0/1]display this
#
interface GigabitEthernet1/0/1
port link-type trunk
port trunk permit vlan 1 101
#
return
[H3C-GigabitEthernet1/0/1]
```

- If the 'port link-type' is trunk, it means the interface could belongs to more than one VLAN.

```
[H3C]display vlan
Total 2 VLAN exist(s).
The following VLANs exist:
1(default), 101,
[H3C]display vlan 1
VLAN ID: 1
VLAN Type: static
Route Interface: not configured
Description: VLAN 0001
Name: VLAN 0001
Tagged Ports: none
Untagged Ports:
  GigabitEthernet1/0/1
  GigabitEthernet1/0/4
  GigabitEthernet1/0/7
  GigabitEthernet1/0/10
  GigabitEthernet1/0/13
  GigabitEthernet1/0/16
  GigabitEthernet1/0/19
  GigabitEthernet1/0/22
  GigabitEthernet1/0/25
  GigabitEthernet1/0/28
  GigabitEthernet1/0/2
  GigabitEthernet1/0/5
  GigabitEthernet1/0/8
  GigabitEthernet1/0/11
  GigabitEthernet1/0/14
  GigabitEthernet1/0/17
  GigabitEthernet1/0/20
  GigabitEthernet1/0/23
  GigabitEthernet1/0/26
  GigabitEthernet1/0/3
  GigabitEthernet1/0/6
  GigabitEthernet1/0/9
  GigabitEthernet1/0/12
  GigabitEthernet1/0/15
  GigabitEthernet1/0/18
  GigabitEthernet1/0/21
  GigabitEthernet1/0/24
  GigabitEthernet1/0/27
[H3C]display vlan 101
VLAN ID: 101
VLAN Type: static
Route Interface: not configured
Description: VLAN 0101
Name: VLAN 0101
Tagged Ports:
  GigabitEthernet1/0/1
Untagged Ports: none
[H3C]
```

# Practice 14.2

1. Use "display vlan brief" to find the information about VLAN and interface.
2. Is there any default VLAN on Layer 3 Switch / Router? Which interfaces belong to this default VLAN?
3. Create two VLANs: VLAN 'x' and VLAN 'y' on Layer3 Switch / Router.
4. Configure the VLANs and interfaces:
  - 1) Giga-ethernet interface 'a1' accesses to VLAN 'x'
  - 2) Giga-ethernet interface 'b1' accesses to VLAN 'y'
5. Setup the connections:
  - 1) Connect the Giga-ethernet interface 'a1' with PCa
  - 2) Connect the Giga-ethernet interface 'b1' with PCb
6. Configure PCa and PCb with static IP addresses which belong to the same network.  
Use "ping" on PCa to test if PCb is reachable.
7. Is there anyway to make the PCa reachable from PCb without changing the connection? Try and test.

NOTES: 'x', 'y' should be two different numbers, while 'a1' and 'b1' should be the index of interface on Layer3 Switch / Router.

# IPv6 configuration on Layer 3

- Different types of IPv6 address
  - State address : got from DHCP server , global address.
  - Stateless address: got by Route Advise, same as private address in IPv4.
  - Local link address: with prefix(FE80::/64) as its prefix, this address could be used to communicate with other PCs on the local network.

## Tips:

S5110 Ethernet interface works on bridge mode, PCs can't get an IPv6 address while the vlan-interface working on route mode.

# Got a stateless IPv6 address(1)

Enable the neighbor discover on an IPv6 interface.

```
[H3C]vlan 101
[H3C-vlan101]quit
[H3C]interface vlan-interface 101
[H3C-Vlan-interface101]ipv6 address 1001::1/64
[H3C-Vlan-interface101]undo ipv6 nd ra halt
[H3C-Vlan-interface101]quit
[H3C]
```

```
[H3C]interface vlan-interface 101
[H3C-Vlan-interface101]display
[H3C-Vlan-interface101]display this
#
interface Vlan-interface101
undo ipv6 nd ra halt
ipv6 address 1001::1/64
#
return
```

```
IPv6 地址 . . . . . : 1001::9cc7:4dc7:b538:91f(首选)
临时 IPv6 地址 . . . . . : 1001::3901:a40d:760:d81e(首选)
本地链接 IPv6 地址 . . . . . : fe80::9cc7:4dc7:b538:91f%67(首选)
```

```
[H3C]display ipv6 neighbors all
Type: S-Static      D-Dynamic
IPv6 Address      Link-layer      VID  Interface      State T Age
FE80::3C56:9767:E588:42FC  309c-236e-8f3b 101  GE1/0/1      REACH D 12
FE80::9CC7:4DC7:B538:91F  00e0-4c68-0577 101  GE1/0/5      STALE D 34
```

```
C:\Users\vivi>ping -6 1001::3c56:9767:e588:42fc
```

```
正在 Ping 1001::3c56:9767:e588:42fc 具有 32 字节的数据:
来自 1001::3c56:9767:e588:42fc 的回复: 时间=3ms
来自 1001::3c56:9767:e588:42fc 的回复: 时间=1ms
来自 1001::3c56:9767:e588:42fc 的回复: 时间=1ms
来自 1001::3c56:9767:e588:42fc 的回复: 时间=1ms
```

```
1001::3c56:9767:e588:42fc 的 Ping 统计信息:
    数据包: 已发送 = 4, 已接收 = 4, 丢失 = 0 (0% 丢失),
    往返行程的估计时间(以毫秒为单位):
        最短 = 1ms, 最长 = 3ms, 平均 = 1ms
```

# Got a stateless IPv6 address (2)

```
[H3C]display ipv6 interface Vlan-interface 101
Vlan-interface101 current state :UP
Line protocol current state :UP
IPv6 is enabled, link-local address is FE80::723D:15FF:FEA6:D540
Global unicast address(es):
  1001::1, subnet is 1001::/64
Joined group address(es):
  FF02::1:FF00:0
  FF02::1:FF00:1
  FF02::1:FFA6:D540
  FF02::2
  FF02::1
MTU is 1500 bytes
ND DAD is enabled, number of DAD attempts: 1
ND reachable time is 30000 milliseconds
ND retransmit interval is 1000 milliseconds
ND advertised reachable time is 0 milliseconds
ND advertised retransmit interval is 0 milliseconds
ND router advertisements are sent every 600 seconds
ND router advertisements live for 1800 seconds
Hosts use stateless autoconfig for addresses
IPv6 Packet statistics:
InReceives:                243
InTooShorts:                0
InTruncatedPkts:           0
InHopLimitExceeds:         0
InBadHeaders:              0
InBadOptions:              0
ReasmRegds:                0
ReasmOKs:                  0
InFragDrops:               0
InFragTimeouts:            0
OutFragFails:              0
InUnknownProtos:           0
InDelivers:                237
OutRequests:               252
OutForwDatagrams:          0
InNoRoutes:                0
InTooBigErrors:            0
OutFragOKs:                0
OutFragCreates:            0
InMcastPkts:               36
InMcastNotMembers:         6
OutMcastPkts:              23
InAddrErrors:              0
InDiscards:                0
OutDiscards:               0
```

[H3C]

```
[H3C]display ipv6 fib
FIB Table:
Total number of Routes : 4
```

Flag:

U:Useable G:Gateway H:Host B:Blackhole D:Dynamic S:Static

Destination:	1001::	PrefixLength :	64
NextHop :	::	Flag :	U
Label :	Null	Token :	Invalid
Interface :	Vlan-interface101		
Destination:	1001::1	PrefixLength :	128
NextHop :	::1	Flag :	UH
Label :	Null	Token :	Invalid
Interface :	InLoopBack0		

Find the subnet ID of this IPv6 LAN.

# Practice 14.3(optional)

- Build a LAN with PCa, PCb and a Layer3 switch/route
- Create a vlan-interface, configure its IPv6 address
- Enable the neighbor discovery on the vlan-interface to make the PCs which belong to the VLAN to get a stateless address
  - Can the PC get an IPv6 state-less address? What is the length of the prefix in the address?
  - What 's the difference between this address and IPv6 link address?
  - Invoke 'ping -6 ' test on PCa to check if PCb is reachable or not, explain the reason.

(Optional) create and enable a DHCPv6 server on the Layer3 switch / Router and test.

# Tips (1)

- If two PCs connecting to the same switch can not receive ICMP reply messages from each other, you can make some change about Fire Wall of the PC.

```
C:\users\Administrator>ping 172.18.5.114  
正在 Ping 172.18.5.114 具有 32 字节的数据:  
请求超时。  
请求超时。  
请求超时。  
请求超时。
```




# Tips (2)

- Go to [Control Panel] -> [System and Secure] -> [Windows Defender Fire Wall] -> [Advanced Setting]



# Tips (3)



文件和打印机共享(后台打印程序服务 - RPC-EPMAP) 文件和打印机共享

文件和打印机共享(回显请求 - ICMPv4-In)

文件和打印机共享(回显请求 - ICMPv4-In)

文件和打印机共享(回显请求 - ICMPv6-In)

文件和打印机共享(回显请求 - ICMPv6-In)

无线便携式设备(SSDP-In)

无线便携式设备(UPnP-In)

启用规则(E)

剪切(T)

复制(C)

删除(D)

属性(R)

帮助(H)

## 入站规则

名称

文件和打印机共享(SMB-In)

文件和打印机共享(后台打印程序服务 - RPC)

文件和打印机共享(后台打印程序服务 - RPC)

文件和打印机共享(后台打印程序服务 - RPC-EPMAP)

文件和打印机共享(后台打印程序服务 - RPC-EPMAP)

✓ 文件和打印机共享(回显请求 - ICMPv4-In)

✓ 文件和打印机共享(回显请求 - ICMPv4-In)

✓ 文件和打印机共享(回显请求 - ICMPv6-In)

✓ 文件和打印机共享(回显请求 - ICMPv6-In)

无线便携式设备(SSDP-In)

无线便携式设备(UPnP-In)

✓ 无线显示基础结构反向通道(TCP-In)

✓ 无线显示器(TCP-In)

性能日志和警报(DCOM-In)

性能日志和警报(DCOM-In)

性能日志和警报(TCP-In)

性能日志和警报(TCP-In)

虚拟机监控(DCOM-In)

虚拟机监控(NB-Session-In)

虚拟机监控(RPC)

✓ 虚拟机监控(回显请求 - ICMPv6-In)

✓ 虚拟机监控(回显请求 - ICMPv4-In)

✓ 移动套餐

# Tips (4)

```
C:\users\Administrator>ping 172.18.5.114

正在 Ping 172.18.5.114 具有 32 字节的数据:
请求超时。
请求超时。
请求超时。
请求超时。

172.18.5.114 的 Ping 统计信息:
    数据包: 已发送 = 4, 已接收 = 0, 丢失 = 4 (100% 丢失),

C:\users\Administrator>ping 172.18.5.114

正在 Ping 172.18.5.114 具有 32 字节的数据:
来自 172.18.5.114 的回复: 字节=32 时间=1ms TTL=128
来自 172.18.5.114 的回复: 字节=32 时间<1ms TTL=128
来自 172.18.5.114 的回复: 字节=32 时间=1ms TTL=128
来自 172.18.5.114 的回复: 字节=32 时间=1ms TTL=128

172.18.5.114 的 Ping 统计信息:
    数据包: 已发送 = 4, 已接收 = 4, 丢失 = 0 (0% 丢失),
往返行程的估计时间(以毫秒为单位):
    最短 = 0ms, 最长 = 1ms, 平均 = 0ms
```