

NAME

dwm – dynamic window manager

SYNOPSIS

dwm [-v]

DESCRIPTION

dwm is a dynamic window manager for X. It manages windows in tiled, monocle and floating layouts. Either layout can be applied dynamically, optimising the environment for the application in use and the task performed.

In tiled layouts windows are managed in a master and stacking area. The master area on the left contains one window by default, and the stacking area on the right contains all other windows. The number of master area windows can be adjusted from zero to an arbitrary number. In monocle layout all windows are maximised to the screen size. In floating layout windows can be resized and moved freely. Dialog windows are always managed floating, regardless of the layout applied.

Windows are grouped by tags. Each window can be tagged with one or multiple tags. Selecting certain tags displays all windows with these tags.

Each screen contains a small status bar which displays all available tags, the layout, the title of the focused window, and the text read from the root window name property, if the screen is focused. A floating window is indicated with an empty square and a maximised floating window is indicated with a filled square before the windows title. The selected tags are indicated with a different color. The tags of the focused window are indicated with a filled square in the top left corner. The tags which are applied to one or more windows are indicated with an empty square in the top left corner.

dwm draws a small border around windows to indicate the focus state.

OPTIONS

-v prints version information to standard output, then exits.

USAGE**Status bar****X root window name**

is read and displayed in the status text area. It can be set with the **xsetroot(1)** command.

Button1

click on a tag label to display all windows with that tag, click on the layout label toggles between tiled and floating layout.

Button3

click on a tag label adds/removes all windows with that tag to/from the view.

Mod4–Button1

click on a tag label applies that tag to the focused window.

Mod4–Button3

click on a tag label adds/removes that tag to/from the focused window.

Keyboard commands**Mod4–,**

Focus previous screen, if any.

Mod4–.

Focus next screen, if any.

Mod4–Control–,

Send focused window to previous screen, if any.

Mod4–Control–.

Send focused window to next screen, if any.

Mod4-b

Toggles bar on and off.

Mod4-space

Toggles between current and previous layout.

Mod4-Shift-,

Cycles backwards in layout list.

Mod4-Shift-.

Cycles forwards in layout list.

Mod4-j

Focus next window.

Mod4-k

Focus previous window.

Mod4-Shift-j

Swap current window with the next window in the stack.

Mod4-Shift-k

Swap current window with previous window in the stack.

Mod4-i

Increase number of windows in master area.

Mod4-o

Decrease number of windows in master area.

Mod4-l

Increase master area size.

Mod4-h

Decrease master area size.

Mod4-Return

Zooms/cycles focused window to/from master area (tiled layouts only).

Mod4-Shift-f

Toggle focused window between tiled and floating state.

Mod4-Tab

Toggles to the previously selected tags.

Mod4-Shift-[1..n]

Apply nth tag to focused window.

Mod4-Shift-0

Apply all tags to focused window.

Mod4-Control-Shift-[1..n]

Add/remove nth tag to/from focused window.

Mod4-[1..n]

View all windows with nth tag.

Mod4-0

View all windows with any tag.

Mod4-Control-[1..n]

Add/remove all windows with nth tag to/from the view.

Mod4-Shift-e

Quit(restart) dwm.

Mouse commands**Mod4–Button1**

Move focused window while dragging. Tiled windows will be toggled to the floating state.

Mod4–Button2

Toggles focused window between floating and tiled state.

Mod4–Button3

Resize focused window while dragging. Tiled windows will be toggled to the floating state.

CUSTOMIZATION

dwm is customized by creating a custom config.h and (re)compiling the source code. This keeps it fast, secure and simple.

SEE ALSO

dmenu(1), **st(1)**

ISSUES

Java applications which use the XToolkit/XAWT backend may draw grey windows only. The XToolkit/XAWT backend breaks ICCCM-compliance in recent JDK 1.5 and early JDK 1.6 versions, because it assumes a reparenting window manager. Possible workarounds are using JDK 1.4 (which doesn't contain the XToolkit/XAWT backend) or setting the environment variable **AWT_TOOLKIT=MToolkit** (to use the older Motif backend instead) or running **xprop -root -f _NET_WM_NAME 32a -set _NET_WM_NAME LG3D** or **wmname LG3D** (to pretend that a non-reparenting window manager is running that the XToolkit/XAWT backend can recognize) or when using OpenJDK setting the environment variable **_JAVA_AWT_WM_NONREParenting=1**.

BUGS

Send all bug reports with a patch to hackers@suckless.org.